HP Operations Smart Plug-in for SAP

for HP Operations Manager for Windows®

Software Version: 12.03

Printed Online Help



Document Release Date: January 2011 Software Release Date: January 2011

Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notices

© Copyright 1998-2011 Hewlett-Packard Development Company, L.P.

Trademark Notices

Acrobat®, Adobe®, and PostScript® are trademarks of Adobe Systems Incorporated.

HP-UX Release 10.20 and later and HP-UX Release 11.00 and later (in both 32- and 64-bit configurations) on all HP 9000 computers are Open Group UNIX 95 branded products.

Intel®, Itanium®, and Pentium® are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

JavaTM is a registered trademark of Oracle Corporation and/or its affiliates.

Microsoft®, Windows®, and Windows NT® are U.S. registered trademarks of Microsoft Corporation.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

X/Open® is a registered trademark, and the X device is a trademark of X/Open Company Ltd. in the UK and other countries.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

http://h20230.www2.hp.com/selfsolve/manuals

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to:

http://h20229.www2.hp.com/passport-registration.html

Or click the New users - please register link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

Visit the HP Software Support Online web site at:

www.hp.com/go/hpsoftwaresupport

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport user ID, go to:

http://h20229.www2.hp.com/passport-registration.html

To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

Contents

1	Introducing the Smart Plug-in tor SAP	17
2	Customizing the SPI for SAP Monitors	19
	Before Using the SPI for SAP Monitors	19
	r3itosap: Monitoring SAP NetWeaver	20
	The SPI for SAP Monitors	21
	Important Monitor-Configuration Concepts	22
	Monitor-Configuration Files	22
	Monitor-Configuration File: Global vs. Local	23
	Monitor-Configuration Modes	23
	Alert Monitor Order of Precedence	23
	Remote Monitoring with Alert Monitors	24
	The SPI for SAP Monitor-Configuration File	25
	AlertMonFun	26
	AlertDevMon	27
	AlertMonPro	27
	AlertInstMonPro	27
	AlerMonSyslog	27
	Alert Classes	28
	CCMS Acknowledge Message	31
	CCMS Monitor Set	32
	Disable Monitoring With Severity	32
	DP Queue Check	33
	Enable DP Queue Check	35
	History Path	36
	Instance Profile Path	36
	Remote Monitoring	37
	RFCTimeOut	38
	Severity Values	38
	Trace File	39
	Trace Level	40
	XMISyslogMode	40
	To Configure the SPI for SAP Alert Monitors	40
	Distributing Alert-Monitor Configuration Files	42
	Local and Global Configurations	43
	To Apply a Global Configuration	
	To Apply a Local Configuration	44
	To Delete Selected Local Configurations on a Node	45

3	SPI for SAP Alert Monitors	. 49
	Polling Rates for the Alert Monitors	. 49
	The Alert-Monitor Configuration Files	. 49
	r3monal: the CCMS 4.x Alert Monitor	. 51
	r3monal: Monitoring Conditions	. 52
	r3monal: CCMS Monitor Sets	. 52
	r3monal: CCMS Alert Monitors	. 55
	r3monal: CCMS Acknowledge Message	. 57
	r3monal: Environment Variables	. 57
	r3monal: File Locations	. 58
	r3monal: Remote Monitoring	. 58
	r3monal: RFC Time Out	. 58
	r3monal: Severity Levels	. 59
	r3monal: Trace Levels	
	r3monal: XMI Compatibility Mode	. 60
	r3monal: Alert Classes	
	r3monal: Migrating from r3monxmi	
	r3monal: Monitoring the J2EE Engine (Web AS Java)	
	r3monal: Monitoring Stand-alone Enqueue Servers	
	r3monal: Monitoring SAP Security-Audit Logs	
	r3monal: Monitoring the Enterprise Portal	
	r3monal: Monitoring the CEN	
	r3monal: Testing the Configuration	
	r3mondev: The SAP Trace-file Monitor	
	r3mondev: File Locations	
	r3mondev: Environment Variables	
	r3mondev: Monitoring Conditions	
	r3mondev: Editing the Configuration File	
	r3monpro: The SAP Process Monitor	
	r3monpro: File Locations	
	r3monpro: Environment Variables	
	r3monpro: Monitoring Conditions	
	r3monpro: Example Configuration	
	r3status: The SAP Status Monitor	
	r3status: File Locations	
	r3status: Environment Variables	
	r3status: History File	
	The r3status Configuration File	
	r3status: Establishing the SAP Status	
	r3status: Monitoring SAP Remotely	
	r3monsec: The SAP Security Monitor	
	r3monsec: File Locations	
	r3monsec: Alert Types	
	r3monsec: SAP_PARAMETERS	
	r3monsec: DEFAULT_USERS	
	r3monsec: PRIVILEGED_USERS	
	r3monsec: Monitoring Security Remotely	. 79

	r3mondisp: the ABAP Dispatcher Monitor	. 80
	r3mondisp: Pre-requisites	. 80
	r3mondisp: File Locations	. 81
	Integrating r3mondisp with the SPI for SAP Monitors	. 81
	The r3mondisp Configuration File	. 82
	The J2EE (Web AS Java) Monitor	. 84
	J2EE Monitor: Enabling CCMS Alerts	. 84
	J2EE Monitor: Configuration Pre-requisites	. 85
	Configuring the SPI for SAP J2EE Monitor	. 86
	The Enqueue-Server Monitor	. 87
	Enqueue Server: Enabling CCMS Alerts	. 87
	Enqueue Server: Configuration Pre-requisites	. 88
	Enqueue Server: Configuring the Enqueue-Server Monitor	. 88
	The SAP Enterprise-Portal Monitor	. 89
	Enterprise Portal: Enabling CCMS Alerts	. 90
	Enterprise Portal: Configuration Pre-requisites	. 90
	Enterprise Portal: Configuring the Portal Monitor	. 91
	The SAP Security-Audit Monitor	. 93
	SAP Security-Alerts	. 94
	Configuring the Security-Audit Monitor	. 94
	Installing the SPI for SAP's Security-Monitoring Feature	. 95
	Configuring the SAP Security Audit	. 96
	Enabling CCMS Security Monitoring	. 96
4	The SPI for SAP Alert-Collector Monitors	. 99
	Configuring the SPI for SAP Alert-Collector Monitors	
	Report Types for the Alert-Collector Monitors	
	Polling Rates for the Alert-Collector Monitors	
	Alert-Collector Monitor History	
	Alert-Collector Monitor Query Conditions	
	Parameter Data Types.	
	Specifying Query Conditions	
	Parameter Values	
	Query Conditions	
	Alert-Collector Monitor Environment Variables	105
	Alert-Collector Monitor Command-Line Parameters	106
	Remote Monitoring with the Alert-Collector Monitors	106
	The Alert-Collector Monitor Configuration Files	108
		100
	Alert-Collector Keywords and Parameters	
	Alert-Collector Keywords and Parameters	108
	Severity Levels	108 111 112
	Severity Levels. Validating the Alert-Collector Configuration Files. Understanding Configuration-File Error Messages.	108 111 112 112
	Severity Levels	108 111 112 112
	Severity Levels. Validating the Alert-Collector Configuration Files. Understanding Configuration-File Error Messages r3monale: The iDOC-Status Monitor Monitor Type.	108 111 112 112 115 115
	Severity Levels. Validating the Alert-Collector Configuration Files. Understanding Configuration-File Error Messages r3monale: The iDOC-Status Monitor Monitor Type Alert Types.	108 111 112 112 115 115
	Severity Levels. Validating the Alert-Collector Configuration Files. Understanding Configuration-File Error Messages r3monale: The iDOC-Status Monitor Monitor Type.	108 111 112 112 115 115 116

Command-Line Parameters	 . 116
Remote Monitoring	 . 116
Configuring iDOC-Monitor Alert Types	 . 116
IDOC_CURRENT_STATUS	 . 117
Checking the iDOC Status	 . 120
r3monchg: The System-Change-Option Monitor	 . 123
Monitor Type	 . 123
Alert Types	
File Locations	 . 124
Environment Variables	 . 124
Command-Line Parameters	
Remote Monitoring	 . 124
Configuring SYSTEM CHANGE OPTION Monitor Alert Types	
Parameter Values	
CHANGE_OPT	
r3moncts: The Correction and Transport System Monitor	
Monitor Type	
Alert Types.	
File Locations	
Environment Variables	
Command-Line Parameters	
Remote Monitoring	
Configuring CTS Monitor Alert Types.	
REQUEST_CREATED	
REQUEST_RELEASED	
TASK CREATED	
TASK_RELEASED	
OBJECT_USED	
OBJECT_USED	
-	
r3mondmp: The ABAP-Dump Monitor	
Monitor Type	
Alert Types	
File Locations	
Environment Variables	
Command-Line Parameters	
Remote Monitoring	
ABAP4_ERROR_EXIST	
r3monjob: The Job-Report Monitor	
Monitor Type	
Alert Types	
First Time Monitoring	
Performance Aspects	
File Locations	
Environment Variables	
Command-Line Parameters	
Remote Monitoring	
Configuring Job-Report Monitor Alert Types	 . 142

Parameter Values	. 	. 142
JOB_MAX_RUN_TIME		142
JOB_MIN_RUN_TIME		144
START_PASSED		145
JOB_ABORTED		146
r3monlck: The Lock-Check Monitor	. 	147
Monitor Type	. 	148
Alert Types		
File Locations		148
Environment Variables	. 	148
Command-Line Parameters		. 149
Remote Monitoring		149
OLD_LOCKS	. 	149
r3monoms: The Operation-Mode Monitor	. 	149
Monitor Type		
Alert Types		
File Locations		
Environment Variables		
Command-Line Parameters		
Remote Monitoring		
OM_SWITCH_OVERDUE		
r3monrfc: The RFC-Destination Monitor		
Monitor Type		
Alert Types		
File Locations		
Environment Variables		
Command-Line Parameters		
Remote Monitoring		
Limitations.		
Configuring RFC-destination Alert Types.		
Parameter Values		
CHECK		
r3monspl: The Spooler Monitor		
Monitor Type		
Alert Types		
File Locations		
Environment Variables		
Command-Line Parameters		
Remote Monitoring		
Configuring Spooler-Monitor Alert Types		
SPOOL_ENTRIES_RANGE		
SPOOL_ERROR_RANGE		
PRINT_ERROR_EXISTS		
r3montra: The Transport Monitor		
Monitor Type		
Alert Types		
File Locations		
1 110 LIOCAUDUD	, .	LUJ

Environment Variables	. 159	
Command-Line Parameters	. 159	
Remote Monitoring	. 160	
Configuring Transport-Monitor Alert Types	. 160	
Parameter Values	. 160	
TRANS	. 160	
REPAIR	. 162	
RFCONNECT	. 163	
TPTEST	. 164	
r3monupd: The Update Monitor	. 165	
Monitor Type		
Alert Types		
File Locations		
Environment Variables		
Command-Line Parameters		
Remote Monitoring		
Configuring Update-Monitor Alert Types		
UPDATE_ACTIVE		
UPDATE_ERRORS_EXIST		
r3monusr: The SAP-User Monitor		
Monitor Type		
Alert Types		
File Locations		
Environment Variables		
Command-Line Parameters		
Remote Monitoring		
USER_LOGGEDIN_MAX		
r3monwpa: The Work-Process Monitor.		
Monitor Type		
• •		
Alert Types		
File Locations		
Command-Line Parameters		
Remote Monitoring		
Configuring Work-Process Monitor Alert Types		
Parameter Values		
WP_AVAILABLE		
WP_IDLE		
WP_CHECK_CONFIGURED		
WP_STATUS		
Monitoring the TemSe file		
Monitor Type		
Report Description		
Running the TemSe Monitor	. 179	
Understanding Message Flow	181	
HPOM Message Customization		

	Setting Up the Message Filters	. 182
	Changing the Message Severity	. 183
	Customizing CCMS Message Flow in SAP	. 183
	Disabling Messages	. 184
	Setting Thresholds for SAP CCMS Alert Monitor Messages	. 185
	Obtaining a Message ID from the SAP NetWeaver Syslog File	. 186
	SAP Solution-Manager Integration	. 187
	Pre-requisites	. 187
	Integration Overview	
	Sending Messages from SAP to HPOM	. 189
	Sending Messages from HPOM to SAP	. 190
	The r3ovo2ccms Command	. 192
	Command Parameters	. 192
	Optional Parameters	. 193
	Examples	. 193
	Monitoring CCMS Alerts in the CEN	. 194
	CEN-Integration Overview	. 194
	Configuring the SAP CEN	. 194
	SAP Central Monitoring System	. 194
	SAP ABAP Instances	. 196
	J2EE Instances	. 197
	Configuring the SPI for SAP	. 198
6	The SPI for SAP Performance Monitors	201
	Performance Monitors Overview.	
	Upgrading the SPI for SAP R/3 Performance Agent	
	Upgrading the SPI for SAP R/3 Performance Agent with CODA	
	Installing the SPI for SAP R/3 Performance Agent	
	Locating the SPI for SAP R/3 Performance Agent Files	
	SPI for SAP R/3 Performance Agent: AIX	
	SPI for SAP R/3 Performance Agent: HP-UX, Solaris, and Linux	
	SPI for SAP R/3 Performance Agent: Windows	
	Configuring the SPI for SAP R/3 Performance Agent	
	Selecting the Performance-data Source	
	Configure the SPI for SAP R/3 Performance Agent	
	Remote Performance Monitoring	
	The Performance-Monitor Scheduler	
	The r3perfagent.cfg Configuration File	
	Managing the SPI for SAP R/3 Performance Agent	
	SPI for SAP R/3 Performance Agent Command Line Syntax	
	SAP Logins for the SPI for SAP R/3 Performance Agent	
	SAP/Performance agent Tools	
	The SPI for SAP Performance Monitors	
	DBINFO_PERF	
	Type	
	Frequency	. 223

Datasource	223
Metrics	223
DOCSTAT_PERF	224
Type	224
Frequency	224
Data Source	224
Metrics	224
EP_PERF	225
Type	225
Frequency	225
Datasource	225
Metrics	225
ICMSTAT_PERF	227
Type	227
Frequency	227
Datasource	
Metrics	
JOBREP_PERF	
Frequency	
Datasource	
Metrics	
SAPBUFFER_PERF	
Frequency	
Data Source	
Metrics	
SAPMEMORY_PERF	231
Type	
Frequency	231
Data source	
Metrics	231
SPOOL_PERF	231
Type	
Frequency	
Data Source	
Metrics	
STATRECS_PERF	
Type	
Frequency	
Data Source	
Metrics	
Configuring and Uploading STATRECS_PERF	
SYSUP_PERF	
Type	
Frequency	
Data Source	

	Metrics	236
	UPDATE_PERF	236
	Type	236
	Frequency	236
	Data Source	236
	Metrics	237
	USER_PERF	237
	Type	237
	Frequency	237
	Data source	237
	Metrics	238
	WLSUM_PERF	238
	Type	
	Frequency	
	Data source	
	Metrics	
	WP_PERF	
	Type	
	Frequency	
	Data Source	
	Metrics	
	Removing the SPI for SAP R/3 Performance Agent	241
7	Monitoring SAP NetWeaver Web Application Server (J2EE)	243
	Before You Begin	
	The SiteConfig File	
	Scenarios for Viewing the Service Map for the Java Systems	
	Monitoring the J2EE Engine	
	Deploy the Scheduled Task Policies	
	Deploy the Measurement Threshold Policies	
	Reference Information on SAP NetWeaver Java Monitoring 7.0 Policies	
	Policies: the J2EE Engine - Kernel Group	
	Policies to Monitor the Configuration Manager Data	252
	Policies to Monitor the Cluster Manager Data	
	Policies: the J2EE Engine - Services Group	273
	Policies to Monitor the JMX Adapter Service	274
	Policies to Monitor the HTTP Provider Service	276
	Policies to Monitor the SAPSR3DB Connector Container Service	278
	Policies to Monitor the SAP/EP_PRT Connector Container Service	280
	Policies to Monitor the SAP/BC_MIGSERVICE Connector Container Service	281
	Policies to Monitor the SAP/CAF_EUP_GP Connector Container Service	282
	Policies to Monitor the SAP/BC_WDRR Connector Container Service	284
	Policies to Monitor the SAP/CAF_RT Connector Container Service	285
	Policies to Monitor the SAP/BW_MMR Connector Container Service	286
	Policies to Monitor the SAP/EP_DQE Connector Container Service	
	Policies to Monitor the SAP/CAF/EUP_GP/MAIL_CF Connector Container Service	
	Policies to Monitor the SAP/BC_UME Connector Container Service	290

	Policies to Monitor the SAP/BC_JMS Connector Container Service	292
	Policies to Monitor the SAP/BC_FO Connector Container Service	293
	Policies to Monitor the SAP/BC_XMLA Container Service	294
	Policies to Monitor the SAP/BC_MON Connector Container Service	296
	Policies to Monitor the SAP/CAF_EUP_ER Connector Container Service	297
	Policies to Monitor the SAP/EP_PCD Connector Container Service	298
	Policies to Monitor the SAP/BC_ADM Connector Container Service	299
	Policies to Monitor the SAP/CAF_BW_RT Connector Container Service	301
	Policies to Monitor the SAP/BC_SLM Connector Container Service	302
	Policies to Monitor the SAP/LOCAL_MAINFRAME_POOL Connector Container Service	303
	Policies to Monitor the SAP/BC_SLD Connector Container Service	
	Policies to Monitor the SAP/BC_JDO Connector Container Service	305
	Policies to Monitor the SAP/BC_UDDI Connector Container Service	
	Policies to Monitor the utdb Connector Container Service	
	Policies to Monitor the ADS Connector Container Service	309
	Policies to Monitor the SDK_JDBC Connector Container Service	
	Policies to Monitor the SDK_CAF Connector Container Service	
	Policies to Monitor the SDK_SAPQ Connector Container Service	
	Policies to Monitor the SDK_XMLA Connector Container Service	
	Policies to Monitor the SDK_ODBO Connector Container Service	
	Policies to Monitor the EJB Container Services	
	Policies to Monitor the Web Container Service	
	Policies: the J2EE Engine - Performance Group	
	Reference Information on SAP Netweaver Java Monitoring 7.1 Policies	
	Policies : the J2EE Engine : Kernel Group	
	Policy to Monitor the Session Manager Data	
	Policies to Monitor the System Threads Pool	
	Policies to Monitor the Application Threads Pool	
	Policies to Monitor the Cluster Manager Data	
	Policy to Monitor the Class Loader Manager Data	
	Policies to Monitor the Configuration Manager Data	
	Policies : the J2EE Engine - Services Group	
	Policy to Monitor Timeout Service	
	Policy to Monitor WebContainer Service	
	Policies to Monitor the JMS Service	
	Policy to Monitor the Log Configurator Service	333
	Policies to Monitor the HTTP Provider Service	333
	Policy to Monitor the Transaction Service	334
	Policy to Monitor the IIOP Service	
	Policies to Monitor the JMX Adapter Service	
	Policies to Monitor the JNDI Registry Service	
	Policy to Monitor the Security Service	
	Policies : the J2EE Engine - Performance Group	
0		
8	Service Views	
	What are Service Views?	
	Service Views in the SPI for SAP	
	Line of Business Views	342

	Configuring Service Views for SAP	343
	Troubleshooting Service Discovery	344
	SPI for SAP Service View for Java Server	346
	Configuring Service Views for J2EE Server	346
	Deploy the SiteConfig File	346
	Configuring Service Views for Java System	347
9	Service Reports	349
	What Are Service Reports?	349
	Upgrading the SPI for SAP Reports	349
	Installing the SPI for SAP Reports	
	Before You Begin	
	Installing SAP Service Reports	351
	Service Reports in the SPI for SAP	
	SAP Reports	354
	Defining the Scope of SAP Service Reports	359
	Generating SPI for SAP Reports	360
	Viewing SPI for SAP Reports	361
	SPI for SAP Report Metrics	361
	SAP Report Metrics	361
	SAP Netweaver Report Metrics	362
	Removing the SPI for SAP Reports	363
	To Remove HP Reporter Snap-in Packages	363
	To Remove the SPI for SAP from the Reporter System	363
Α	SPI for SAP Golden Metrics	365
В	Data Store Details for SPI for SAP Reports	369
Inc	lex	383

1 Introducing the Smart Plug-in for SAP

This section describes what information is in the *HP Operations Smart Plug-in for SAP On-line Help* and where you can find it. The *HP Operations Smart Plug-in for SAP On-line Help* provides information that is designed to help the administrators of both HP Operations Manager for Windows (HPOM for Windows) and SAP NetWeaver to configure the SPI for SAP to suit the needs and requirements of the SAP NetWeaver landscape, which they plan to manage with HPOM for Windows. The on-line Help system also explains how to install and configure the various additional sub-agents that come with the SPI for SAP. Finally, the *HP Operations Smart Plug-in for SAP On-line Help* describes how to integrate the SPI for SAP with performance-related products that are available as a part of HP Software.

2 Customizing the SPI for SAP Monitors

This section describes how to set up the SPI for SAP monitors and deploy them to the SAP servers in your SAP landscape. The SPI for SAP includes a set of monitors, which you configure to run at regular intervals to collect information regarding various aspects of your SAP environment's health.

The HPOM for Windows administrators, working from the HPOM for Windows console, deploy the appropriate SPI for SAP policies to the SAP servers which they want to manage and monitor with HPOM for Windows. Monitor deployment is usually completed as part of the SPI for SAP installation and configuration process.

If you have never configured the SPI for SAP monitors, you will want to read the detailed description of each alert monitor and alert-monitor configuration file. The alert-monitor configuration files include information about default configurations as well as a list of changes you need to make sure that the monitor works correctly in your SAP environment.

Before Using the SPI for SAP Monitors

Before using any of these monitors, be sure to complete the following tasks:

- Set up the required SAP users and their associated logons as described in the HP
 Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows.
- Specify details of all SAP systems to monitor in the r3itosap.cfg file. You can define entries in r3itosap.cfg:
 - as a part of the installation procedure (refer to the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*) or,
 - At any time, use the configuration-file policy editor. For more information, see r3itosap: Monitoring SAP NetWeaver on page 20.



If the SAP instance you want to monitor is part of a high-availability cluster, such as MC/ServiceGuard, you need to add an extra entry to the "cluster host mapping" section of the r3itosap.cfg file to tell the SPI for SAP about the nodes configured in the cluster. If the host-mapping entry is not present in the r3itosap.cfg file, the SPI for SAP might encounter problems monitoring the nodes in the cluster, for example, resolving the hostname of the cluster nodes, starting the monitors at the correct time, and associating messages with the appropriate managed nodes.

For more information about configuring the SPI for SAP to monitor SAP in a high-availability environment, see the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

r3itosap: Monitoring SAP NetWeaver

This section describes how to use the configuration-file policy editor to modify the r3itosap.cfg configuration file. The r3itosap.cfg configuration file defines the SAP NetWeaver Systems, which the SPI for SAP should monitor. To complete this task successfully, you need to ensure that you have already installed the ConfigFile Editor and in addition, the appropriate SPI for SAP policies. For more information about installing packages and policies, refer to the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows.

You have to set up SAP NetWeaver users for each SAP NetWeaver client. The list of SAP NetWeaver clients you made in "Before You Begin" in the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows* includes the information you need for each configuration line. For more information about how to set up SAP NetWeaver users for HPOM for Windows, see "Setting Up an SAP User for HPOM" in the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

Using the format of the examples in the r3itosap.cfg configuration file, add an entry for each SAP NetWeaver instance, which you want to monitor with the SPI for SAP. In the central, SPI for SAP, monitor-configuration file r3itosap.cfg, the string =default is associated with the default ITOUSER password "HPSAP_30". If you intend to make use of your own SAP user logins, you need to replace =default with the appropriate user password. If you use the HPOM for Windows configuration-file policy editor to edit the r3itosap.cfg file, the policy editor encrypts the password automatically when you save the file.



r3status, the tool the SPI for SAP uses to monitor the status of SAP Systems, does not attempt to verify the existence of the SAP Systems specified in r3itosap.cfg. If r3status cannot find a named SAP instance, for example, because of a spelling mistake, it reports the instance as unavailable.

If the SAP instance you want to monitor is a part of a high-availability cluster, such as MC/ServiceGuard, you need to add an entry to the "cluster host mapping" section of the r3itosap.cfg file to tell the SPI for SAP about the nodes configured in the cluster. If the host-mapping entry is not present in the r3itosap.cfg file, the SPI for SAP could encounter problems monitoring the nodes in the cluster, for example, resolving the hostname of the cluster nodes and associating messages with the correct managed node in the cluster.

For more information about the SPI for SAP in high-availability clusters and configuring the r3itosap.cfg file, refer to the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

The SPI for SAP Monitors

Table 1 provides an overview of SPI for SAP alert-monitors.

Table 1 The Alert Monitors

Alert Monitor	Monitor Function
r3monal ^a	Monitors SAP NetWeaver system log events and alerts from the internal SAP CCMS 4.x alert monitor
r3mondev	Monitors errors in SAP trace and log files
r3mondisp	Monitors the status of the ABAP dispatcher for all SAP instances configured in the SPI for SAP's central configuration file r3itosap.cfg
r3monpro	Monitors SAP work processes and database processes
r3monsec	Monitors the security settings in SAP for instances configured in the r3itosap.cfg file
r3status	Monitors the status of the SAP instances configured in the r3itosap.cfg file
CAD 1	

a. SAP syslog monitor r3monxmi is now obsolete.

Table 2 provides an overview of the alert-collector monitors used by $\verb"r3moncol"$, the SPI for SAP alert collector.

Table 2 The r3moncol Alert-Collector Monitors

Alert-Collector Monitor	Monitor Function
r3monaco	Although this is not an alert-collector monitor, you must assign r3monaco to the managed nodes to monitor SAP's Temporary Sequential (TemSe) file. For more information, see Monitoring the TemSe file on page 179
r3monale	Monitors the status of iDOCs in the SAP NetWeaver System
r3monchg	Monitors the SAP NetWeaver system change options
r3moncts	Monitors the correction-and-transport system
r3mondmp	Monitors ABAP/4 Dumps
r3monjob	Monitors SAP NetWeaver batch jobs
r3monlck	Monitors the Enqueue process, which manages logical locks for SAP NetWeaver transactions and reports on obsolete locks

Table 2 The r3moncol Alert-Collector Monitors (cont'd)

Alert-Collector Monitor	Monitor Function
r3monoms	Monitors the operation mode switch to determine whether a scheduled operation mode started after the specified time. Note that changes in SAP mean there are no operation-mode switch errors to monitor in WebAS 7
r3monrfc	Checks the status of RFC destinations in an SAP environment
r3monspl	Monitors spooler entries, spooler errors, and print errors
r3montra	Monitors the transport system.
r3monupd	Monitors the update process for active status and errors
r3monusr	Monitors the number of users logged-in to SAP NetWeaver
r3monwpa	Monitors the status of the work processes. It reports any processes that are running in debug, private, or no restart modes, compares the number of configured work processes with the actual number running, and checks the number of expected work processes waiting and the number running

Important Monitor-Configuration Concepts

This section describes the concepts supporting the CCMS alert-monitors and in addition, explains how to configure the monitors.

Monitor-Configuration Files

Each alert or alert-collector monitor has an associated configuration file, which you can edit to define your own rules for how you want to monitor alerts for all the monitors. However, the monitors have default configurations, which you can use without modification. For more information about the contents of the SPI for SAP's monitor-configuration files, see:

- The SPI for SAP Monitor-Configuration File on page 25
 General information which applies to the configuration of *all* the SPI for SAP monitors.
- The Alert-Monitor Configuration Files on page 49
 Information about the keywords and parameters, which you use to configure the alert monitors r3monal, r3mondev, r3monpro, and r3monsec.
- The r3mondisp Configuration File on page 82

Information about the keywords and parameters, which you use to configure the ABAP dispatch-queue monitor, r3mondisp.

- The r3status Configuration File on page 72
- The Alert-Collector Monitor Configuration Files on page 108

Information which applies to the configuration of the alert-collector monitor r3moncol and the alert collectors it uses, for example, r3monale, r3mondmp, r3monjob, and so on.

Monitor-Configuration File: Global vs. Local

For more information about when to use each of these deployment methods and for instructions on editing the configuration files, see The SPI for SAP Monitor-Configuration File on page 25.

Monitor-Configuration Modes

The SPI for SAP supports the following configuration modes:

Global

You define the monitoring conditions for all managed nodes in a single configuration file. If you specify a *global* configuration, the monitoring conditions you define must cover the monitoring needs of all managed nodes.

Local

You define the monitoring conditions for a particular node in a configuration file associated only with that single, managed node. If a *local* configuration is used, each node can have its own configuration file, which defines only the monitoring conditions for that particular node.

You can deploy a mixture of global and local configurations. For an explanation of the relationship between local and global configuration as well as instructions on the use of each configuration mode, see Distributing Alert-Monitor Configuration Files on page 42.

Alert Monitor Order of Precedence

Each time an alert monitor runs, its behavior is determined by information defined in an alert-monitor-specific configuration file. An alert monitor chooses which configuration file to use according to a defined "order of precedence", as follows:

- The monitor first checks for the presence of the SAPOPC_<R3monitor_name>_CONFIGFILE variable and determines the location of the configuration files from this. For more information about the SAPOPC_<R3monitor_name>_CONFIGFILE variable, see the section about the specific monitor you want to configure, for example, r3monpro: Environment Variables on page 67.
- 2 On UNIX managed nodes:
 - a Local configuration file

The monitor checks for (and if found uses) the HPOM for UNIX local configuration file in:

< OvData Dir > / conf/sapspi/local

b Global configuration file

If the monitor does not find an HPOM for UNIX local configuration file, the monitor checks for (and if found uses) the HPOM for UNIX global configuration file in:

< OvData Dir > / conf/sapspi/global

- 3 On Windows managed nodes:
 - a Local configuration file

The monitor checks for (and if found uses) the HPOM for Windows local configuration file in:

%OvAgentDir%\conf\sapspi\local

b Global configuration file

If the monitor does not find an HPOM for Windows local configuration file, the monitor checks for (and if found uses) the HPOM for Windows *global* configuration file in:

 $%OvAgentDir\% \conf\sapspi\global$

Remote Monitoring with Alert Monitors

The SPI for SAP includes a feature which allows you to extend the scope of all the alert, alert-collector, and performance monitors (except r3mondev, r3monpro, r3mondisp) to monitor the status of SAP on remote SAP servers, which are *not* HPOM for Windows managed nodes and where the SPI for SAP is *not* installed. You set up and perform the remote monitoring from an HPOM for Windows managed node, where the SPI for SAP software is running.



Although the SAP Server defined in the RemoteHost parameter is not an HPOM for Windows managed node, it must still be present in the HPOM for Windows Node list. If you do not add the SAP Server defined in RemoteHost to the HPOM for Windows Node list, HPOM for Windows cannot resolve the host name associated with the remote host and, as a consequence, cannot display any messages from the remote host in the HPOM for Windows console.

In addition, the SAP Server defined in RemoteHost must appear in the r3itosap.cfg file to ensure that the SPI for SAP can log into (and extract information from) the SAP instances it is monitoring on the RemoteHost. For more information about the r3itosap.cfg file, refer to the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows.

Note that the SPI for SAP tools cannot start a SAP GUI on an SAP System, which the SPI for SAP is monitoring remotely from an HPOM for Windows Managed Node.

To make use of the remote-monitoring feature provided by the SPI for SAP, for example, to monitor an SAP System running in an environment that is not supported by the SPI for SAP, you need to perform the following actions. Specifying Individual Remote Servers to Monitor on page 25 shows how a new line is required for each *additional* SAP server, which you want to monitor remotely.

- Enable the **RemoteMonitoring** keyword by removing the leading hash symbol "#" in each monitor's configuration file.
- Define the name of the *local* host, on which you want to perform the monitoring. Note that you need a new line for each *local* host that you want to associate with a remote host.
- Define the name of the *remote* SAP server (*RemoteHost*), which you want to monitor.

Make sure that the remote host is added to the HPOM for Windows node list.

The RemoteMonitoring keyword accepts the following parameters:

LocalHost

This is the name of the local HPOM for Windows managed node where the SPI for SAP software is running and whose HPOM for Windows agent you want the SPI for SAP to use to remotely monitor the SAP server defined in the parameter "RemoteHost".

RemoteHost

This is the name of the *remote* SAP server you want to monitor from the host defined in the parameter "LocalHost". Although the remote host does not have the SPI for SAP software installed and is *not usually* an HPOM for Windows managed node, it must be present in the HPOM for Windows Node list to ensure that messages are handled correctly.

• **SAP System and SAP Number** (r3monal *only*)

The CCMS alert and syslog monitor r3monal needs to know both the ID and the Number of the SAP System running on the SAP server defined in the parameter "RemoteHost".

For more information about any additional requirements when defining remote monitoring with the alert monitors, and in particular r3monal (the CCMS alert monitor), see The SPI for SAP Monitor-Configuration File on page 25 and The Alert-Monitor Configuration Files on page 49.

Specifying Individual Remote Servers to Monitor

#		
# Remote	LocalHost	RemoteHost
# Monitoring		
RemoteMonitoring	=sap1	=sdsap1
RemoteMonitoring	=sap1	=sdsap2
RemoteMonitoring	=sap2	=sdsap3
#		

Note that you can use the Alert-classes section at the end of the monitor-configuration file to associate an instance of a monitor with a specific host, SAP instance, or processes on the remote server in the same way as you can with a normal (local) managed node. For more information about configuration-file keywords, see The SPI for SAP Monitor-Configuration File on page 25.

The SPI for SAP Monitor-Configuration File

During the SPI for SAP installation and configuration, the SAP specialist must set up initial configuration values for the SPI for SAP monitors and deploy the modified configuration files to the managed nodes.

Each configuration file provided with the SPI for SAP defines default settings by using the keyword. Some keywords can only be used with specific monitors, all which are specific to a particular sub-section of the monitor configuration file. The information below lists the keywords that appear in the various sub-sections of the configuration file and explains the contents of the alert-classes section at the end of the configuration file, where you define

conditions that when met, generate messages about the SAP alerts you are monitoring. You can also see which keywords you can use with which monitors and find out the permitted values for keyword parameters:

AlertMonFun on page 26

Configure the r3moncol alert collectors in the SAP System

• AlertDevMon on page 27

Configure trace- and log-file monitoring in the SAP System

AlertMonPro on page 27

Configure process monitoring per SAP System

• AlertInstMonPro on page 27

Configure process monitoring per SAP instance

AlerMonSyslog on page 27

Configure filtering of CCMS alerts or system logs

• Alert Classes on page 28

In the alert-classes section at the end of the configuration file, valid keywords are monitor-specific.

- CCMS Acknowledge Message on page 31
- CCMS Monitor Set on page 32
- Disable Monitoring With Severity on page 32
- DP Queue Check on page 33

Monitor the size of the ABAP-dispatcher queue

• Enable DP Queue Check on page 35

Check the status of the ABAP-dispatcher

- History Path on page 36
- Instance Profile Path on page 36
- Remote Monitoring on page 37
- RFCTimeOut on page 38
- Severity Values on page 38

The Severity Values section contains the Severity<Level> keyword

- Trace File on page 39
- Trace Level on page 40
- XMISyslogMode on page 40

AlertMonFun

Only with r3moncol

Use the AlertMonFun keyword in the r3moncol configuration files to configure the SPI for SAP alert collectors, which monitor internal SAP alerts generated by, for example, the iDOC monitor, the ABAP-dump monitor, the spooler monitor, and so on. The AlertMonFun keyword requires a value for the following parameters:

```
AlertMonFun =<SAP Hostname> =<SAP System> =<SAP Number> \
=<SAP Client> =<AlertMonitor> =<Enable/Disable> \
=<OpC Severity> =<OpC Object> =<OpC MsgGroup> \
=<Alerttype> =<RFC Parameter>
```

For more information about the parameters that you need to define for the AlertMonFun keyword, see Alert-Collector Keywords and Parameters on page 108.

AlertDevMon

Only with r3mondev

Use the AlertDevMon keyword in the r3mondev.cfg file to configure the SPI for SAP to monitor trace- and log-files in the SAP System. The AlertDevMon keyword requires a value for the following parameters:

```
AlertDevMon =<SAP System> =<SAP Number> =<Enable/Disable> \
=<Filemask> =<Opc Severity> =<Opc Object> =<Opc MsgGroup>
```

For more information about the parameters that you need to define for the AlertDevMon keyword, see Alert Classes on page 28.

AlertMonPro

Only with r3monpro

Use the AlertMonPro keyword in the r3monpro.cfg file to configure the SPI for SAP to monitor SAP-related processes per SAP System. On SAP servers running the UNIX operating systems, r3monpro can identify processes at the instance level with Alert*Inst*MonPro. For more information about r3monpro, see r3monpro: The SAP Process Monitor on page 66.

The AlertMonPro keyword requires a value for the following parameters:

```
AlertMonPro =<Hostname> =<Process name> =<Enable/Disable> \
=<Mode> =<Process number> =<Opc Severity> =<Opc Object> \ =<Opc MsgGroup>
```

For more information about the parameters that you need to define for the AlertMonPro keyword, see Alert Classes on page 28.

AlertInstMonPro

Only with r3monpro in UNIX

Use the AlertInstMonPro keyword in the r3monpro.cfg file to configure the SPI for SAP to monitor SAP-related processes per SAP *instance*. The AlertInstMonPro keyword requires a value for the following parameters:

```
AlertInstMonPro =<Hostname> =<Process name> \
=<Enable/
Disable> =<Mode> =<Process number> =<Opc Severity>\=<Opc Object> =<Opc MsgGro
up>
```

For more information about the parameters that you need to define for the AlertInstMonPro keyword, see Alert Classes on page 28.

AlerMonSyslog

Only with r3monal

Use the AlerMonSyslog keyword in the r3monal.cfg file to configure the SPI for SAP to monitor Syslog filtering. This can be used *only* with the r3monal alert monitor CCMS alerts or system logs in combination with the XMI/XAL interface. If you want the format of the syslog alerts to resemble the style used by the now-obsolete r3monxmi monitor, see also XMISyslogMode on page 40. The AlerMonSyslog keyword requires a value for the following parameters:

```
AlerMonSyslog =<SAP System> =<SAP Number> =<SyslogId>
=<Enabled/Disabled>
```

For more information about the parameters that you need to define for the AlerMonSyslog keyword, see Alert Classes on page 28.

Alert Classes

The alert-classes section at the end of the monitor-configuration file allows you to use keywords and parameters to define conditions that, when met, generate messages about the SAP alerts you are monitoring. The contents of the alert-classes section change according to the monitor you are configuring. Some monitors require a specific keyword, and each keyword requires a specific combination of parameters to configure a given SPI for SAP monitor.

For example, the keywords AlertMonPro and AlertInstMonPro appear exclusively in the configuration file for the SAP-process monitor, r3monpro. However, all r3moncol monitors use the keyword AlertMonFun to configure alert monitoring. The parameters SAP Hostname, SAP System, and SAP Number are present in all the monitor-configuration files, but the =CHANGE_OPT alert-type parameter can only be used with r3monchg, the SAP System-change Monitor.

For more information about which alert types and parameters are allowed with which monitor-specific alerts, see the information in this section and, in addition, the section which corresponds to the individual monitor you want to configure, for example: r3monale, or r3mondmp.



The SPI for SAP monitors are configured by default to manage *all* SAP Systems, which you define in the SPI for SAP's central configuration file r3itosap.cfg. The monitor-configuration files should not be edited by anyone who does not have a detailed knowledge of SAP NetWeaver and, in addition, the local SAP NetWeaver landscape, which you want to manage with the SPI for SAP.

The following list shows all the parameters in the alert-classes section of all the SPI for SAP monitor configuration files. Where appropriate, restrictions are indicated in brackets (), for example, (r3mondev only).

• **AlertMonitor** (r3moncol and r3monsec only):

=<Monitor_Name> The short form of the alert monitor you are configuring, for example, =ALE for r3monale, =CTS for r3moncts, and so on.

Note: =SECURITY for r3monsec.

• **Alerttype** (r3moncol and r3monsec only):

=<Alerttype>

The alert type is monitor specific. For example, r3monale uses the IDOC CURRENT STATUS alert type to monitor alerts related to the status of iDOCs; r3mondmp uses the alert type ABAP4_ERROR_EXIST to monitor alerts relating to each ABAP dump that occurs in a monitored SAP System. For more information about which alert types belong to which alert-collector monitor, see the "Alert-Types" section for a given monitor, for example, r3monale: The iDOC-Status Monitor on page 115 includes the alert type IDOC_CURRENT_STATUS on page 117.

Enable/Disable:

=0Disable the monitor

Enable the monitor. This is the default setting. =1

Filemask (r3mondev only):

=<File_Name>

The name of the trace file you want r3mondev to monitor. You can use the wildcard "*" (asterisk) to monitor multiple file names, for example, =dev *

Mode (r3monpro only):

=<mode value>

The mode or way in which you want to evaluate ProcessNumber, for example, Max, Min, Exact, and Delta. For more detailed information about the possible values, see r3monpro: The SAP Process Monitor on page 66.

OPCMsgGroup:

=<HPOM Msq Group> The name of the HPOM for Windows message group to which the generated message belongs, for example: R3_CTS, or R3_DMP. The default names all start with "R3_" and reflect the names of the alert monitors to which they correspond, for example, r3moncts or r3mondmp. Note that if you change the names of the HPOM for Windows message groups in the monitor-configuration files, remember to ensure that the changes are reflected in the message conditions to avoid the generation of unmatched messages.

OPC Object:

=<HPOM Object>

The HPOM for Windows object associated with the generated message. The object names tend to reflect the names of the alert types associated with the alert-collector monitor, for example, REQUEST or TASK for r3moncts.

If you change the names of the HPOM for Windows objects in the monitor-configuration files (or add new ones), you must ensure that these changes are reflected in the message conditions to avoid the generation of unmatched messages.

The =SyslogId string in the OPC Object field has nothing to do with the SyslogId alert parameter described below, which only appears in the syslog-filtering section of the r3monal.cfg file.

OPC Severity:

=<HPOM Msg Severity>

The severity level of the HPOM for Windows message you want to map the CCMS alert to, for example: Normal, Warning, Major, Critical.

Process Name (r3monpro only):

=<NameSID>

The name of the SAP process you want r3monpro to monitor.

Process Number (r3monpro only):

=<nn>

The number (nn) of instances of the SAP process defined in ProcessName. You can qualify the number with Max, Min, Exact, and Delta. For more information see r3monpro: The SAP Process Monitor on page 66.

RFC Parameter (r3moncol only):

=<RFC Param>

The name of the parameter followed by any required query conditions, each with the prefix "=", for example, =CP (for "Contains Pattern") or EQ for ("Equals"). For more information about query conditions, see Alert-Collector Monitor Query Conditions on page 102. For more information about monitorspecific, alert-type parameters, see the appropriate monitor description, for example: Table 24 on page 117 for the r3monale monitor.

SAP Client:

=ALL Monitor all SAP instance numbers with the SPI for SAP. This is the default setting.

=<ClientID> The number of the specific SAP client you want to monitor, for example, 099. Use a new line for each individual host.

SAP Hostname:

=ALL Monitor all SAP hosts with the SPI for SAP. This is the default setting.

=<SAP_host> The host name of a specific SAP server you want to monitor. Use a new line for each individual host.

• SAP Number:

=ALL Monitor all SAP instance numbers with the SPI for SAP. This is the

default setting.

=<Instance> The number of the specific SAP instance you want to monitor, for

example, 00, 99. Use a new line for each host.

• SAP System:

=ALL Monitor all SAP Systems with the SPI for SAP. This is the default

setting.

=<SAP_SID> The ID of a specific SAP System want to monitor, for example, DEV. Use

a new line for each individual host.

• **SyslogId** (r3monal only):

=A00 The *lower* end of the range of SAP syslog IDs, whose CCMS Alerts or

syslogs you want to monitor.

=ZZZ The *upper* end of the range of SAP syslog IDs, whose CCMS Alerts or

syslogs you want to monitor.

CCMS Acknowledge Message

The r3monal monitor uses the CCMSAcknowledgeMessage keyword to switch the CCMS auto-acknowledge feature on or off in SAP. CCMS alerts which are complete do not generate messages in HPOM for Windows. This keyword requires a value for the following parameters:

CCMSAcknowledgeMessage =<SAP System> =<Ack. Filtered
Messages> =<Enabled/Disabled>

• SAP System:

The SAP System ID whose CCMS Alerts you want to acknowledge (or complete) in SAP.

Ack. Filtered Messages:

This feature determines whether SAP acknowledges (or completes) CCMS Alerts which match the defined conditions in CCMS or not. Acknowledged CCMS alerts do not generate messages in HPOM.

- =0 *Do not* acknowledge (complete) the CCMS Alerts in SAP. This is the default setting and leads to matched alerts generating an HPOM for Windows message.
- =1 Acknowledge the CCMS Alerts in SAP. This is same as clicking the [Complete Alert] button in SAP CCMS. No messages are sent to HPOM for Windows.

Enable/Disable:

- =0 *Disable* the auto-completion of CCMS alerts. Note that this also disables the setting for **Ack. Filtered Messages**. This is the default setting.
- =1 *Enable* the auto-completion of CCMS alerts.

CCMS Monitor Set

Define a CCMS monitor set to use with the new and enhanced XMI/XAL interface (BAPI). The CCMSMonitorSet keyword requires a value for the following parameters:

```
CCMSMonitorSet =<SAP System> =<SAP Number> =<Monitor Set>
=<Monitor>
```

• SAP System:

The SAP System ID whose CCMS Alerts are defined in the parameter Monitor Set.

SAP Number:

This SAP *instance* number of the SAP System whose CCMS Alerts are defined in the parameter Monitor Set.

• Monitor Set:

=SAP CCMS Technical Expert Monitors

The name of the monitor set as it appears in the CCMS Alert- Monitor tree.

• Monitor:

=System / All Monitoring Segments / All Monitoring Context

The names of the monitors belonging to the monitor set defined in the parameter "Monitor Set" separated by a forward slash (/).

Disable Monitoring With Severity

Only with r3mondisp, the ABAP dispatcher monitor

Specify which r3mondisp message severity should trigger the disabling of integrated SPI for SAP monitors to prevent the monitors increasing loads unnecessarily by requesting work processes from the SAP Systems, whose ABAP dispatcher you are monitoring with the SPI for SAP. The DisableMonitoringWithSeverity keyword accepts the following parameters:

```
DisableMonitoringWithSeverity =<hostname> =<SID>
=<InstanceNr> =<Severity>
```

• Hostname:

The name of the SAP Server where the instance is running whose ABAP dispatcher you want to monitor:

=ALL All hosts monitored by the SPI for SAP. This is the default setting.

=<SAP_host> The name of the SAP server, where you want to disable

dispatcher-queue monitoring. Use a new line (and keyword) for each,

individual SAP server.

• SID:

The SAP System ID of the instance whose ABAP dispatcher you are monitoring:

=ALL All System IDs which the SPI for SAP monitors. This is the default

setting.

=<SAP SID> The SAP System ID of the instance whose ABAP dispatcher you want to

monitor, for example: "SP1"

• InstanceNr:

The number of the SAP instance whose ABAP dispatcher you are monitoring:

=ALL All System IDs which the SPI for SAP monitors. This is the default

setting.

=< $SAP_InstNr>$ The number of the SAP instance whose ABAP dispatcher you want to

monitor, for example: "45"

• Severity:

The severity level of the message r3mondisp sends which would trigger the disabling of SPI for SAP monitors that require a work process to logon to SAP, for example: "warning"

The DisableMonitoringWithSeverity keyword must be used in conjunction with keywords DPQueueCheck, which you configure in the r3mondisp.cfg file, and EnableDPQueueCheck, which you define in the configuration file of the SPI for SAP monitor you want to integrate with r3mondisp.

DP Queue Check

Only with r3mondisp, the ABAP dispatcher monitor

Manages the pro-active monitoring of the ABAP dispatcher and its queues. If more than one threshold matches for the same managed node and the same work-process, r3mondisp only sends the message with the highest severity level. The DPQueueCheck keyword accepts the following parameters:

```
DPQueueCheck =<hostname> =<SID> =<InstanceNr> =<disable/enable>
=<OVO Msg Group> =<OVO Msg Object> =<OVO Severity>
=<WP-Type> =<Idle/Queue> =<percentage idle/full>
```

• Hostname:

The name of the SAP Server where the instance is running whose ABAP dispatcher you want to monitor:

=ALL All the hosts which the SPI for SAP monitors. This is the default setting.

=<SAP_host> The name of a SAP server, where you want to enable monitoring of the dispatcher-queue. Use a new line for each individual host.

• SID:

The System ID of the SAP instance whose ABAP dispatcher you want to monitor:

=ALL All System IDs which the SPI for SAP monitors. This is the default setting.

=<SAP_SID> The SAP System ID of the instance whose ABAP dispatcher you want to

monitor, for example: "SP1"

Instance Nr:

The number of the SAP instance whose ABAP dispatcher you want to monitor:

=ALL All instances which the SPI for SAP monitors. This is the default

setting.

=< $SAP_InstNr>$ The number the SAP instance whose ABAP dispatcher you want to

monitor, for example: "45"

• Enable/Disable:

Enable (1) or disable (0) the DPQueueCheck for the defined SAP instance, for example: 1

HPOM Msg Group:

The name of the HPOM for Windows message group to which the message generated by r3mondisp should be assigned

• HPOM Msg Object:

The name of the HPOM for Windows message object to which the message generated by r3mondisp should be assigned, for example: "Dialog"

HPOM Msg Severity:

The severity level assigned to the HPOM for Windows message generated by r3mondisp, for example: "critical"

• WP-Type:

The type of work process whose queues you want to check, for example: DIA (for dialog), or BTC (Batch)

Idle/Queue:

The status of the work process in the queues you are monitoring. Use "IDLE" if you want to monitor what percentage of the allocated work processes in the monitored queue are idle (or available) at a given point in time; use "QUEUE" if you want to monitor what percentage of the maximum allowed work processes in the monitored queue are currently allocated.

Percentage Full:

How full (or empty) the monitored queue must be as a percentage of the maximum before r3mondisp generates an alert. Note that =IDLE =10 generates an alert if *less* than 10% of the allocated work processes are idle; =QUEUE =70 generates an alert if *more* than 70% of the maximum allowed work processes in the queue are in use.

Enable DP Queue Check

Only with SPI for SAP monitors that require a dialog work process to log on to SAP.

Configure the SPI for SAP monitors that log on to SAP to check the status of the ABAP dispatcher and the size of its queues before starting. If there are no or too few dialog work processes available, the monitor does not start and displays a message in the console indicating the reason. Use this keyword if you think that allocating to the SPI for SAP monitor the work process it requires to logon to SAP might cause further performance problems for the ABAP dispatcher. For more information about monitoring the ABAP dispatcher and its queues, see r3mondisp: the ABAP Dispatcher Monitor on page 80.

The EnableDPQueueCheck keyword requires the following parameters:

```
EnableDPQueueCheck =<Hostname> =<SAP SID> =<SAP Number>
=<Enable/Disable>
```

• Hostname:

The name of the SAP Server where the instance is running whose ABAP dispatcher you want the SPI for SAP monitors to check before starting:

=ALL	All the hosts which the SPI for SAP monitors. This is the default setting.
= <sap_host></sap_host>	The name of a SAP server, where you want to enable checking of the dispatcher-queue. Use a new line for each individual host.

• SAP SID:

The SAP System ID of the instance whose ABAP dispatcher you want the SPI for SAP monitors to check before starting:

=ALL	All System IDs which the SPI for SAP monitors. This is the default setting.
=< <i>SAP_SID</i> >	The SAP System ID of the instance whose ABAP dispatcher you want to check, for example: "SP1"

• SAP Number:

The number of the SAP instance whose ABAP dispatcher you want the SPI for SAP monitors to check before starting:

=ALL	All instances which the SPI for SAP monitors. This is the default setting.
= <sap_instnr></sap_instnr>	The number the SAP instance whose ABAP dispatcher you want the SPI for SAP monitors to check, for example: "45"

• Enable/Disable:

Enable (=1) or disable (=0) this particular monitor to monitor the ABAP dispatcher for the defined SAP instance, for example: 1. The default is Disable (=0). You have to enable the SPI for SAP monitors individually.

Note that if you enable this feature, you do not need to schedule the ABAP dispatcher monitor r3mondisp. However, to ensure that a valid configuration file for r3mondisp is available. The r3mondisp.cfg configuration file defines the path to the profile of the SAP instance the SPI for SAP is monitoring and, in addition, the severity level of the message sent to HPOM for Windows when a threshold is violated for the ABAP dispatcher.

History Path

The HistoryPath[Unix | AIX | WinNT] keyword in the monitor-configuration file accepts the following parameters:

HistoryPath<Unix|Aix|WinNT> <HostName> =<Path>

Hostname:

=ALLMonitor all hosts with the SPI for SAP. This is the default setting. =<SAP host> The name of a SAP server, where you want to specify the path to the

monitor history file. Use a new line for each individual host.

Path:

UNIX: =default AIX: =default Windows: =default

The =default value here is associated with the default path to the history files which the SPI for SAP monitors write. AIX uses /var/[lpp | opt]/OV/conf/sapspi/ for [DCE | HTTPS] nodes respectively, all other UNIX managed nodes use /var/opt/OV/conf/sapspi/, and Windows managed nodes use %OvAgentDir%\conf\sapspi\.

Instance Profile Path

Only with r3mondisp, the ABAP dispatcher monitor

The path to the profile-configuration file for an SAP instance whose ABAP dispatcher you want to monitor; the InstanceProfilePath keyword accepts the following parameters:

InstanceProfilePath =<hostname> =<SID> =<InstanceNr> =<path>

Hostname:

The name of the SAP Server where you want to specify a path to an SAP profile configuration file:

=ALLAll hosts monitored by the SPI for SAP. This is the default setting.

The name of a SAP server, where you want to specify the path to the =<SAP host>

SAP profile configuration file. Use a new line for each individual SAP

server.

• SID:

The ID of the SAP System whose profile path you want to specify:

=ALL All System IDs which the SPI for SAP monitors. This is the default

setting.

=<SAP SID> The System ID of the SAP instance whose configuration-file path you

want to specify, for example: "SP1"

Instance Nr:

The number of the SAP instance whose profile path you want to specify:

=ALL All instance numbers which the SPI for SAP monitors. This is the

default setting.

=<SAP InstNr> The number of the SAP instance whose configuration-file path you

want to specify, for example: "45"

• Path:

The path to the profile file for the specified SAP instance. The default location for SAP profile files is /usr/sap/<SID>/SYS/profile. If the SAP profile file resides in the default location, use =default; if the profile is *not* in the default location, specify the full path to the profile file, for example: /usr/sap/<path>/profile

Remote Monitoring

The RemoteMonitoring keyword allows you to configure the SPI for SAP on a local host to monitor an SAP instance on a remote host. You can use the RemoteMonitoring keyword with all the SPI for SAP monitors *except* r3mondey, r3monpro, and r3mondisp. RemoteMonitoring accepts the following parameters:

RemoteMonitoring =<LocalHost> =<RemoteHost> =<SAPSystem> =<SAPNumber>

• LocalHost:

The name of the HPOM for Windows managed node where the SPI for SAP is running and whose HPOM for Windows agent the SPI for SAP will use to do the monitoring on the host defined in "RemoteHost".

• RemoteHost:

The name of the *remote* SAP system monitored by the host defined in "LocalHost". The RemoteHost does not have the SPI for SAP installed and is not usually (but could theoretically be) an HPOM for Windows managed node.

• **SAP System** (r3monal *only*):

This is the ID of the SAP System running on the SAP server defined in the parameter "RemoteHost" which you want to remotely monitor with the SPI for SAP running on "LocalHost".

• **SAP Number** (r3monal *only*):

This is the specific instance number of the SAP System running on the SAP server defined in the parameter "RemoteHost" which you want to remotely monitor with the SPI for SAP running on "LocalHost".

Note that the remote-monitoring feature does not work with all the alert monitors, for example, you cannot configure r3mondev, r3monpro, and r3mondisp to monitor SAP instances running on a remote server. For more information, see the appropriate section on the individual alert monitor.

Setting up Remote Monitoring for r3monal

#				
# Remote	LocalHost	RemoteHost	SAP	SAP
# Monitoring			System	Number
RemoteMonitoring	=sap1	=sdsap1	=SP6	=00
RemoteMonitoring	=sap1	=sdsap2	=SP6	=00
RemoteMonitoring	=sap2	=sdsap3	=WA1	=33
#				



The name of the host where the remote SAP instance is running must appear in the SPI for SAP's central-configuration file (r3itosap.cfg) along with the appropriate login information.

For more information about using the RemoteMonitoring keyword, see the individual alert monitors and, in addition:

- Remote Monitoring with Alert Monitors on page 24
- r3status: Monitoring SAP Remotely on page 73
- Remote Monitoring with the Alert-Collector Monitors on page 106
- Remote Performance Monitoring on page 214

RFCTimeOut

For all monitors except r3mondey, r3monpro, r3mondisp, and r3status

RFCTimeOut defines the maximum amount of time, in seconds, before an RFC XMI/XAL function call is cancelled, for example: =120. If the RFC call takes longer than expected to complete, to receive a reply to the initial request, the System is probably down or has a serious performance problem.



The time limit no longer applies after the call completes and SAP allocates a free Dialog process.

Severity Values

Only with r3monal, the CCMS-alert monitor

In the Severity Values section of the r3monal.cfg configuration file, the Severity<*Level>* keyword configures the r3monal monitor to map the severity of CCMS alerts (for example, SeverityCritical) in the SAP subsystem to a specific message-severity level in HPOM for Windows (for example, CRITICAL). The Severity<*Level>* keyword accepts the following values:

```
Severity<Level> =<SAPSystem> =<SAPNumber> =<Enabled>
/<Disabled> =<OpcSeverity>
```

Note that the Enabled/Disabled parameter determines whether r3monal considers or ignores CCMS alerts with the specified SAP severity level for mapping to the defined message severity in HPOM for Windows:

=1 (Enabled) Cons	ider CCMS alerts with	h the severity	Severity< <i>Level</i> > (for
-------------------	-----------------------	----------------	-------------------------------

example: Severity Critical) and send a message to HPOM for Windows $\,$

with the severity < OpcSeverity>.

=0 (Disabled) Ignore CCMS alerts with the severity Severity < Level> (for example:

SeverityWarning) and do not send a message to HPOM for Windows.

Table 3 Mapping Severity Levels

CCMS Alert Severity	HPOM for Windows Message Severity		
SeverityCritical (red)	= CRITICAL		
SeverityWarning (yellow)	= WARNING		
SeverityNormal (green)	= NORMAL		
SeverityNull	= UNKNOWN		

The alert-collector monitors (r3moncol) have two additional HPOM for Windows severity levels to map to; Minor and Major. The severity hierarchy in ascending order is: Normal, Warning, Minor, Major, Critical.

Trace File

The TraceFile keyword in the monitor-configuration file accepts the following parameters:

Tracefile =<HostName> =<FileName> =<TraceMode> =<TracePeriod>

• Hostname:

=ALL Monitor all SAP servers with the SPI for SAP. This is the default setting.

=<*SAP_host>* The name of a specific host where tracing is enabled and you want to specify a trace level. Use a new line for each individual host.

• Filename:

=r3mon<alert_monitor_name>.log, for example, r3mondev.log, or r3mondmp.log. This is the default setting. Alternatively, you can specify the name of the file to which you want to write the trace log. By default, monitor trace files are located in the following directories:

— UNIX: /var/opt/OV/log

— AIX [DCE | HTTPS]:/var/[lpp | opt]/OV/conf/sapspi/

— Windows: %OvAgentDir%\log

For more information about changing the path, see the environment variable SAPOPC_TRACEPATH in Alert-Collector Monitor Environment Variables on page 105.

• TraceMode:

=w default value

=a append

TracePeriod

Monitor verifies whether the existing file has expired the time period mentioned in the config file. If the time period is expired, a new file will be created. Otherwise new trace log entries will be appended into the already existing file.

Trace Level

The TraceLevel keyword in the monitor-configuration file accepts the following parameters:

Tracelevel =<HostName> =<Trace Level>

• Hostname:

=ALL	Monitor all SAP hosts with the SPI for SAP. This is the default setting.
= <sap_host></sap_host>	The name of a SAP server, where you want to specify a trace level. Use a
	new line for each individual host.

• Trace level:

=0	Disable logging; this is the default setting for all configuration files.
=1	r3monal, r3mondev, r3monpro: Enable all logging
	r3moncol, r3mondisp, r3status, r3perfagent: Log only error messages
=2	r3moncol, r3mondisp, r3status, r3perfagent only: Log all messages
=3	r3moncol, r3mondisp, r3status, r3perfagent only: Log everything including debug messages

XMISyslogMode

Alert monitor r3monal only.

The XmiSyslogMode keyword allows you to specify that the r3monal monitor sends SAP system log messages in the style and format previously used by the monitor r3monxmi, which is now obsolete. The XmiSyslogMode keyword accepts the following parameters:

```
XmiSyslogMode =<Enable | Disable>
```

- Enable/Disable:
 - =0 Disable the XMI compatibility mode; this is the default setting.
 - =1 Enable XMI compatibility mode.

For more information about the XMISyslogMode keyword and when you can use it, see r3monal: XMI Compatibility Mode on page 60.

To Configure the SPI for SAP Alert Monitors

1 In the HPOM for Windows console, expand the following policy group:

Policy Management > Policy Groups > SPI for SAP

- 2 In the details pane, double-click the appropriate configuration-file policy, for example; global_r3moncts.cfg. The selected alert monitor's configuration file opens in the configuration-file policy editor. Note that there are two types of configuration-file policy for the SPI for SAP:
 - global

for global configurations, for example; global_r3moncts.cfg

local

for local configurations, for example; local_r3moncts.cfg

Edit or enter lines to define *trace levels*. For example, you can set a default for ALL hosts (hostname = ALL), then add lines for any hostname exceptions. For example:

```
TraceLevel =ALL =0
TraceLevel =hpbbx10 =1
```

In this example, tracing is turned off for all the hosts except for host hpbbx10. For more information about trace levels, see Trace Level on page 40.

4 Specify the name of the *trace file* in which you want to record trace information. For example:

```
TraceFile =ALL =r3monpro.log
```

Default trace file names for each monitor are given in Table 4

Table 4 Default Trace File Names

Tracefile Name	Monitor Alert Type
r3monaco.log	Alert Calls
r3monal.log	Alerts
r3monale.log	iDOC alerts
r3monchg.log	System Change
r3moncts.log	Correction and Transport System
r3mondev.log	Trace and Log Files
r3mondisp.log	ABAP dispatcher
r3mondmp.log	ABAP/4 Dumps
r3monjob.log	Job
r3monlck.log	Lock_Check
r3monoms.log	OM Switch
r3monpro.log	Work and Database Processes
r3monsec.log	Security
r3monspl.log	Spooling
r3montra.log	Transport

Table 4 Default Trace File Names (cont'd)

Tracefile Name	Monitor Alert Type
r3monupd.log	Update
r3monusr.log	User
r3monwpa.log	WorkProcess Availability

5 Specify the *history path*, which is the directory path by which you can locate an alert monitor's history file. Alert monitors include the following default paths for UNIX, AIX and Windows servers:

```
HistoryPathUnix =ALL =default
HistoryPathAIX =ALL =default
HistoryPathWinNT =ALL =default
```



You can tell the alert monitors to use a specific history path on Windows managed nodes rather than the default: =default, for example: %OvAgentDir%\Tmp. For more information, see the SAPOPC_HISTORYPATH environment variable and the alert-monitor configuration-file keyword, History Path on page 36.

Each alert monitor writes its own history file. Each time an alert monitor completes a run, it adds a new section to its history file. This feature enables the alert monitor to check for changes since the previous run.



Do *not* edit any of the monitor history (* .his) files. Editing the monitor history file could compromise the accuracy and consistency of your records. The monitor uses its history file to determine which, if any, events have occurred since the last run and whether to send any messages.

- 6 Define the monitoring conditions. Monitoring conditions are rules that control the checks which the alert monitor makes each time it runs. The monitoring conditions you enter are different for each alert monitor. See Alert Classes on page 28 for general information about the keywords and parameters that are allowed with each monitor.
 - For specific information on the monitoring conditions for each alert monitor, see the appropriate section on the particular alert monitor.

Distributing Alert-Monitor Configuration Files

You deploy configuration files to the HPOM for Windows managed nodes in the same way as HPOM for Windows policies, that is; using the standard policy-deployment mechanism.

Local and global configuration files

Local and global configuration files are installed in the following directories on the managed node:

• UNIX: /var/opt/OV/conf/sapspi/[global | local]

- AIX [DCE | HTTPS]:
 /var/[lpp | opt]/OV/conf/sapspi/[global | local]
- Windows: %OvAgentDir%\conf\sapspi\[global|local]

Local and Global Configurations

This section explains briefly how to apply either a local or a global alert-monitor configuration and, in addition, how to delete configurations, which have already been deployed. This section provides instructions for the following tasks:

- To Apply a Global Configuration on page 43
- To Apply a Local Configuration on page 44
- To Delete Selected Local Configurations on a Node on page 45

It is possible to configure both global and local directories on the same machine. When a monitor executable runs, it uses an order of precedence to determine which configuration file should be used. For more information, see Alert Monitor Order of Precedence on page 23.

The procedures described in this section assume that you have already deployed the SPI for SAP policies to the nodes you want to manage.

To Apply a Global Configuration

1 In the HPOM for Windows console, browse to the following directory:

Policy Management > Policy Groups > SPI for SAP

- 2 In the details pane, locate and double-click the configuration file associated with the alert monitor you want to configure, for example; the global_r3mondmp file for the ABAP-dump monitor. The configuration-file policy editor displays the selected file.
- 3 Make any modifications as required.
 - You do not *have* to modify the configuration files: the default configuration-file policies work without modification.
- 4 Save your changes using the **Save as...** option and close the configuration-file policy editor. When saving the modified policy, we recommend that you use the naming conventions for configuration-file policy types, for example; global_r3mondmp. The modified configuration-file policy for the SPI for SAP r3mondmp monitor appears in the list of policies in the details pane.
 - If you use the configuration-file policy editor to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.
- In the details pane, select and right-click the policies you want to deploy and use the following menu option:

All Tasks > Deploy on...

- 6 Use the Deploy Policies on... window to select the managed nodes to which you want to deploy the selected policies. Click **OK** to start the deployment.
- 7 Verify that the deployment operation completed successfully by right-clicking a managed node in the console and selecting the following option from the menu that pops up:

View > Policy Inventory

The configuration files are copied to one of the directories mentioned in Local and global configuration files on page 42 on each of the selected managed nodes.

To Apply a Local Configuration

1 In the HPOM for Windows console, browse to the following directory:

Policy Management > Policy Groups > SPI for SAP

- 2 In the details pane, locate and double-click the configuration file associated with the alert monitor you want to configure, for example; the local_r3mondmp file for the ABAP-dump monitor. The configuration-file policy editor displays the selected file allowing you to make any modifications as required.
- 3 Save your changes using the Save as... option and close the configuration-file policy editor. When saving the modified policy, replace "local" with the name of the SAP NetWeaver server for which the local configuration is intended, for example; <SAP_Server_Name>_r3mondmp. The modified configuration-file policy for the SPI for SAP r3mondmp monitor appears in the list of policies in the details pane.



If you use the configuration-file policy editor to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

- 4 Repeat steps 1 through 3 for each of the alert monitors for which you want to create a local configuration.
- In the details pane, select and right-click the policies you want to deploy and use the following menu option:

All Tasks > Deploy on...

- Use the Deploy Policies on... window to select the managed nodes to which you want to deploy the selected policies. Click **ok** to start the deployment.
- 7 Verify that the deployment operation completed successfully by right-clicking a managed node in the console and selecting the following option from the menu that pops up:

View > Policy Inventory

The configuration files are copied to one of the directories mentioned in Local and global configuration files on page 42 on each of the selected managed nodes.

To Delete Selected Local Configurations on a Node

In the HPOM for Windows console, right-click the managed node whose local alert-monitor configuration you want to delete and select the following option from the menu that pops up:

View > Policy Inventory

Press and hold down the **Ctrl** key to select the local configuration-file policies you want to remove. Right-click the policies and select the following option from the menu that pops up:

All Tasks > Uninstall from...

3 SPI for SAP Alert Monitors

This section describes the alert monitors r3monal, r3monpro, r3mondev, r3status, and r3monsec and explains how to use the configuration files to control them. The SPI for SAP includes a set of monitors, which you configure to run at regular intervals to collect information regarding various aspects of your SAP environment.

You deploy SPI for SAP monitors to the SAP NetWeaver servers, which you want to manage and monitor with HPOM for Windows. Monitor deployment is part of the SPI for SAP installation and configuration process. Before deploying a monitor, the HPOM for Windows administrator, working from the HPOM for Windows console, first deploys the appropriate SPI for SAP policies.

If you are new to configuring the monitors, you will want to read the detailed description of each alert monitor and alert-monitor configuration file. Each alert-monitor configuration file includes information about default configurations as well as a list of changes you must make to the configuration file.

Polling Rates for the Alert Monitors

The alert monitors have different polling rates, that is, the frequency at which the monitor runs. You can change the polling rate at the scheduled-task policy for the monitor. For more information about the default polling rates for each alert monitor, see Table 5, which shows the rates in days, hours, and minutes.

Polling Rate Alert-Monitor Name Mins Days Hours r3monal 5 5 r3mondev 3 r3mondisp 2 r3monpro 1 r3monsec 2

Table 5 **Default Polling Rates for Alert Monitors**

The Alert-Monitor Configuration Files

r3status

Each SPI for SAP alert monitor is defined and configured in an HPOM for Windows policy and in several files, including an executable file and a configuration file.

The policy defines the rules for generating messages that appear in the HPOM for Windows console. The policy also controls the frequency with which the associated executable file runs. If you want to customize a policy, follow the instructions given in the online help for HPOM for Windows administrators.

The monitor executable file runs at the regular interval specified in the monitor policy. The monitor executable checks for and, if present, reports conditions defined in the individual monitor's associated configuration file. You can define these monitoring conditions to suit the needs of your environment. For information about copying and renaming the monitor policies, refer to the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

The SPI for SAP monitor's configuration file allows you to use keywords to set up the monitor to meet the requirements of your particular environment. Note that although most of the keywords appear in *all* the configuration files, some of the keywords can only be used in conjunction with specific monitors.

For more information about the keywords which you can use in the SPI for SAP alert-monitor configuration files, see Monitor-Configuration Files on page 22. Note that the contents of r3status.cfg and the r3status monitor configuration file, are explained in greater detail in The r3status Configuration File on page 72. Excerpt from the r3mondev.cfg File on page 50 shows what a configuration file looks like for the r3mondev monitor, which scans the trace and log files of the SAP system for the string "ERROR".

Excerpt from the r3mondev.cfg File

```
_____
# TraceLevel hostname only error messages=1 info messages=2 debug
messages=3
                   Disable=0
TraceLevel =ALL
                     =0
 TraceFile hostname filename
                              TraceMode
                                                 TracePeriod
                        (a=append/w=create(default)) (in mins)
TraceFile =ALL
                  =r3moncts.log =w
                                                =60
# History
         hostname
                   path
# Path
HistoryPathUnix =ALL =default
HistoryPathAIX
             =ALL =default
HistoryPathWinNT =ALL =default
#-----
# AlertDevMon SAP SAP
                      Enable =1 Filemask Severity Opc
                                                        OpC
           Sys Number Disable=0
                                               Object
                                                        MsgGro
up
                              =dev *
                                       =WARNING =r3mondev =R3 Tr
#AlertDevMon =ALL =ALL
                      =1
ace
                               =std*
#AlertDevMon
           =ALL =ALL
                      =1
                                       =CRITICAL =r3mondev =R3 Tr
ace
#Dispatcher trace file
                      =1
AlertDevMon =ALL =ALL
                              =dev disp =WARNING =r3mondev =R3 Tr
#Workprocess trace file for workprocess with number 0
```

AlertDevMon	=ALL =ALL	=1	=dev_w0	=WARNING	=r3mondev	=R3_Tr
ace						
#message serve	er trace file					
AlertDevMon	=ALL =ALL	=1	=dev_ms	=WARNING	=r3mondev	=R3_Tr
ace						
#screen proces	ssor trace file	Э				
AlertDevMon	=ALL =ALL	=1	=dev_dy0	=WARNING	=r3mondev	$=R3_Tr$
ace						
#tp process to	race file					
AlertDevMon	=ALL =ALL	=1	=dev_tp	=WARNING	=r3mondev	$=R3_Tr$
ace						

r3monal: the CCMS 4.x Alert Monitor

The r3monal monitor uses the SAP NetWeaver CCMS monitoring architecture introduced at CCMS version 4.0 and enables you to monitor the output of SAP's own internal monitor, the CCMS alert monitor. The r3monal monitor maps the alerts identified by the CCMS monitor to HPOM for Windows messages, which you can view in the HPOM for Windows console.



Since SAP has indicated that it intends to phase out support for the shared-memory interface, the SPI for SAP only supports the XMI/XAL interface.

This section includes information about the following topics, which describe the contents of the r3monal configuration file:

- r3monal: Monitoring Conditions on page 52
- r3monal: CCMS Monitor Sets on page 52
- r3monal: CCMS Alert Monitors on page 55
- r3monal: CCMS Acknowledge Message on page 57
- r3monal: Environment Variables on page 57
- r3monal: File Locations on page 58
- r3monal: Remote Monitoring on page 58
- r3monal: RFC Time Out on page 58
- r3monal: Severity Levels on page 59
- r3monal: Trace Levels on page 60
- r3monal: XMI Compatibility Mode on page 60
- r3monal: Alert Classes on page 61
- r3monal: Migrating from r3monxmi on page 61
- r3monal: Monitoring the J2EE Engine (Web AS Java) on page 63
- r3monal: Monitoring Stand-alone Enqueue Servers on page 63
- r3monal: Monitoring SAP Security-Audit Logs on page 63
- r3monal: Monitoring the Enterprise Portal on page 63

- r3monal: Monitoring the CEN on page 64
- r3monal: Testing the Configuration on page 64

r3monal: Monitoring Conditions

You must define and enable the keywords: Severity < Level>, RFCTimeOut, CCMSMonitorSet, and CCMSAcknowledgeMessage. All other keywords in the r3monal.cfg configuration file are optional. For more information, see Severity Values on page 38, RFCTimeOut on page 38, CCMS Monitor Set on page 32, and CCMS Acknowledge Message on page 31 respectively.

r3monal: CCMS Monitor Sets

The XMI/XAL interface allows the SPI for SAP to read, write, and reset CCMS alerts directly in the CCMS alert-monitor tree. The most obvious advantage of this feature is that you can use existing CCMS monitor sets as templates to define your own monitor sets, which contain only those CCMS alerts you want to monitor with the SPI for SAP.

Remember to login to SAP and define the new CCMS monitor sets which you want the SPI for SAP to use to generate messages *before* you start the configuration of the r3monal monitor in HPOM for Windows. Figure 1 on page 53 shows how the application servers bounty and hpspi003 appear in the Monitor-tree when you select and expand the central-instance item WA1.




To create or modify items in the CCMS monitor tree, you need to make sure that the Maintenance Function for the CCMS monitor sets is switched on. You can find the Maintenance function option in the Extras menu, as follows:

Extras > Activate Maintenance Function

If you are not interested in receiving messages concerning *all* the alerts present in the default monitor set, for example, OperatingSystem, DatabaseClient, and so on, you can expand the individual application-server item and select only the alerts which you want to use to generate messages that will be sent to HPOM for Windows. In the example configuration shown in Figure 1, we have also selected the Oracle ® item so that we hear about problems with the database too.

Figure 1 Defining a Monitor Set



Make sure that the new monitor sets you define for the SPI for SAP are visible to and usable by the HPOM for Windows user, which you have defined for the SPI for SAP. If you are logged into SAP as the defined HPOM for Windows user, then you can see only the CCMS monitor sets defined for the defined HPOM for Windows user and those marked "Public". If you are logged into SAP as the administrator, you can see *all* available monitor sets, in which case you have to ensure that you make the *new* monitor sets you define for the SPI for SAP visible either to the defined HPOM for Windows user for the SPI for SAP or everyone by using the option "Public". Remember to use only ASCII characters when defining the name of a CCMS monitor set as the SPI for SAP cannot currently interpret non-ASCII characters in monitor-set names.

One SAP System/SID can have multiple monitor sets. If you need to define multiple monitor sets for a SAP System/SID, remember to include each new monitor set on a new line in the monitor-set section of the r3monal.cfg monitor configuration file, as illustrated in Configuring Multiple Monitor Sets. The name you define in the monitor parameter must match the name of the monitor set as it appears in the CCMS alert-monitor tree. The names of monitors must appear in the configuration file exactly as they are shown in SAP including, for example, forward slashes (/), as shown in Configuring Multiple Monitor Sets.

Note that the combination of traditional long SAP names and the line break in the example configuration file shown in Configuring Multiple Monitor Sets disguises the name of the monitor. The complete name of the last monitor is: =System / All Monitoring Segments / All Monitoring Contexts. Note that the names you use do not have to be this long. In addition, if you want to associate multiple monitors with one, single monitor set, you have to specify each individual monitor on a new line as shown by the first two entries in Configuring Multiple Monitor Sets, where the SPISAP monitor set has two Monitors; System and DB_ALERT.

Configuring Multiple Monitor Sets

#				
# Monitor Set	SAP	SAP	Monitor Set	Monitor
#	System	Number		
CCMSMonitorSet	=WA1	=33	=SPISAP	=System
CCMSMonitorSet	=WA1	=33	=SPISAP	=DB ALE
RT				_
CCMSMonitorSet	=SP6	=00	=SAP CCMS Technical Expert Monitors	=System
/\				
		А	ll Monitoring Segments / All Monitori	ng
Contexts				
#				

The default configuration of individual CCMS alert monitors does not always meet the demands of your environment and, in some instances, you will need to change it. You can check and, if necessary, modify a monitor's properties in the Performance Attribute tab of the Monitor: Properties and Methods window, as illustrated in Figure 2 on page 55. If you decide to change the monitor properties, you need to consider the following points:

- Ensure that the severity level of the CCMS Alerts matches the severity level of the HPOM for Windows messages, which are generated by the CCMS Alerts. For more information about configuring severity levels, see Severity Values on page 38.
- Ensure that severity-level thresholds configured for a given CCMS alert monitor are appropriate for your needs.

BOX SAP Properties Edit Goto System Help **②** Monitoring: Properties and Methods Properties of G11\sodom_G11_00\R3Services\Dialog\ResponseTime MTE class R3DialogResponseTime General PerformanceAttribute Methods Addnl info Performance properties assigned from group R3DialogResponseTime Comparison Value / O Smoothing over last 1 min. Last reported value Average in the last hour O Smoothing over last 5 min. O Average in the last quarter of an hour Smoothing over last 15 mins Threshold values Change from GREEN to YELLOW 2.000 Change from YELLOW to RED 3.000 msec Reset from RED to YELLOW 2.000 msec Reset from YELLOW to GREEN 1 000 msec Alert is triggered if the comparative value falls below threshold value exceeds the threshold value Alert text / RT Message class 127 Message number &1 &3 > &2 &3 Dialog response time exceeds threshold (&4 dialog steps) ₹

Figure 2 Checking and Modifying CCMS Alert-Monitor Thresholds


To open the Monitor: Properties and Methods window for a specific CCMS monitor, browse to the desired monitor in the monitor-set tree and either click the **Properties** button or double-click the monitor you want to view.

r3monal: CCMS Alert Monitors

Alerts are the most basic element of the strategy that SAP uses to monitor the health of the SAP Landscape. Alerts are associated with objects such as disks and CPUs, and objects have attributes such as response times and usage statistics. The status of the object as well as its performance and availability over time are important to the SAP System administrator. The SAP NetWeaver CCMS alert monitor displays the configured alerts (along with any associated objects and attributes) as CCMS **monitors** in a **monitor tree**, which you can browse, as illustrated in Figure 3. Note that *public* monitor sets are visible to (and usable by) all SAP users.


For ease of navigation, the CCMS monitors are grouped into pre-defined **monitor sets**, for example, SAP CCMS Technical Expert Monitors or SAP CCMS Admin Workplace. The pre-defined monitor sets contain a large number of sub sets and monitors, which can generate thousands of alerts, some of which you really do not need.

Figure 3 CCMS Monitor Sets



If you switch *on* the maintenance function for the CCMS monitor sets, you can create your own CCMS monitor sets, which contain only the monitors for the alerts you want to know about on a regular basis. When you have created your own monitor sets, you can add them to the monitor-set tree and configure the SPI for SAP to monitor them. In this way, you can reduce the alerts you hear about and the information you receive so that it is easier to manage.

Figure 4 CCMS Alert Properties



When a condition is reported in the SAP NetWeaver CCMS monitor, the monitoring object and its attributes are included in the resulting alert as shown in Figure 4.

r3monal: CCMS Acknowledge Message

The CCMSAcknowledgeMessage feature determines whether r3monal tells SAP to automatically acknowledge (complete) CCMS Alerts, which match the defined conditions. Enabling the CCMSAutoAcknowledge feature in the r3monal.cfg configuration file is same as selecting the alert and clicking the Complete Alert button in SAP CCMS.

Automatically Acknowledging CCMS Alerts

```
# Triggers auto-acknowledge of CCMS alerts
#------
# CCMSAcknowledgeMessage SAP Ack. filtered Enable=1
# System Messages Disable=0
CCMSAcknowledgeMessage =ALL =0 =0
CCMSAcknowledgeMessage =SP6 =0 =0
```

You can enable or disable the auto-acknowledgement feature for specific SAP Systems defined on individual lines in the r3monal.cfg configuration file. However, note that if you *disable* the auto-acknowledgement feature (=0) for a specific SAP System, r3monal ignores the setting for **Ack. Filtered Messages** defined on the same line.

If you enable the Ack. Filtered Messages keyword, messages that are filtered out (and not sent to the HP Operations agent) by the AlerMonSyslog specifications (which means, setting Disabled=0 in the appropriate line) will be acknowledged in CCMS. Therefore, these alerts will not be visible in the HPOM message browser or in SAP CCMS anymore. For more information on AlerMonSyslog, see r3monal: Alert Classes on page 61.

Note that, if you enable the CCMSAcknowledgeMessages keyword, you also need to make sure that you enable the Severity<*Level>* keyword. The Severity<*Level>* keyword allows you to filter CCMS alerts according to severity. For more information, see r3monal: Severity Levels on page 59.

r3monal: Environment Variables

Table 6 lists the environment variables, which you can use to configure the r3monal monitor.

Table 6 r3monal Environment Variables

Environment Variable	Description
SAPOPC_DRIVE	The Windows drive where the HPOM for Windows agent is running, for example, E:\usr\
SAPOPC_HISTORYPATH	Path to the r3monal history file
SAPOPC_R3MONAL_CONFIGFILE	Name of the r3monal configuration file
SAPOPC_SAPDIR	The Windows drive where SAP NetWeaver is running, for example, E:\usr\sap
SAPOPC_TRACEPATH	Path to the r3monal trace file

r3monal: File Locations

The r3monal monitor uses the default files listed in Table 7. For more detailed information about the contents of the in SPI for SAP monitor-configuration files in general and the file r3monal.cfg in particular, see The SPI for SAP Monitor-Configuration File on page 25.

Table 7 r3monal File

File Name	Description
r3monal(.exe)	Executable for the SAP NetWeaver CCMS alert monitor
r3monal.cfg	Configuration file for the CCMS alert monitor
r3monal.his	History file for storing data after each monitor run

r3monal: Remote Monitoring

The RemoteMonitoring keyword allows you to configure the SPI for SAP on local host to monitor an SAP instance on a remote host. For more information about the parameters you can use with the RemoteMonitoring keyword, see the list of keywords in Remote Monitoring with Alert Monitors on page 24. Note that SAP System and SAP Number are only required by r3monal.

Enabling Remote Monitoring in the r3monal.cfg File

#				
# Remote Host	Localhost	Remotehost	SAP	SAP
#			System	Number
RemoteMonitoring	=hpspi003	=ovsdsap6	=SP6	=00
#				

r3monal: RFC Time Out

You use the RFCTimeout keyword to define the maximum amount of time in seconds before an RFC XMI/XAL function call is canceled, for example: =120. You need to set a time-out which takes into account the environment in which SAP is running. For example, if the RFC call takes longer than expected to complete, that is, to receive a reply to the initial request, the SAP System is probably down or has a serious performance problem. Note that after the RFC call completes and SAP allocates a free Dialog process, the time limit no longer applies.

Setting the Time-out period for XMI/XAL Function Calls

```
# Max. time in sec. before a RFC XMI/XAL function call is # canceled. If the RFC call takes longer than expected, the # system is probably down or has a major performance problem. RFCTimeOut = 120 #------
```

r3monal: Severity Levels

The "Severity Values" section of the r3monal.cfg file defines how you filter CCMS alerts in the CCMS monitor trees you are managing with r3monal and map the severity level of the filtered CCMS Alerts to the desired severity level for the corresponding HPOM for Windows messages. You use the keywords SeverityWarning and SeverityCritical in combination with the CCMSAcknowledgeMessage keyword, which is described in more detail in r3monal: CCMS Acknowledge Message on page 57. For more information about the SPI for SAP configuration files in general, see The SPI for SAP Monitor-Configuration File on page 25.

By adding a new line for individual combinations of SAP system ID and SAP number, you can restrict the severity mapping between CCMS Alerts and HPOM for Windows messages to a specific SAP System ID and SAP Number. Default Settings for Severity Levels in r3monal.cfg shows the default settings for severity levels in the r3monal.cfg file.

Default Settings for Severity Levels in r3monal.cfg

#				
#Severity	SAP	SAP	Enabled=1	OpCSeverity
#Values	System	Number	Disabled=0	
SeverityWarning	=ALL	=ALL	=0	=WARNING
SeverityCritical	=ALL	=ALL	=1	=CRITICAL
#				

You can edit the severity levels in r3monal.cfg in any one of the following ways:

Enable or disable severity levels

If you want to disable (=0) the generation of messages for CCMS alerts with the severity "warning", add a new (or change the existing) SeverityWarning line as follows:

```
SeverityWarning =ALL =ALL =0 =WARNING
```

2 Change how the SPI for SAP maps CCMS severity levels to message severity levels in HPOM

If you want the SPI for SAP to report all SeverityWarning events as critical, add a new (or change the existing) SeverityWarning definition, as follows:

```
SeverityWarning =ALL =ALL =1 =CRITICAL
```

3 Define SID-Specific exceptions

If you want the SPI for SAP to report as critical all SeverityWarning events that occur on SAP system LP2, leave the default settings for ALL systems and add the following line:

```
SeverityWarning =LP2 =ALL =1 =CRITICAL
```

Excerpt from the r3monal Configuration File

```
# A Monitor Set defines the messages you want to forward to HPOM.
# Monitor Set
                SAP
                       SAP
                              Monitor Set Monitor
                System Number
                       =33
#CCMSMonitorSet
                =WA1
                               =SPISAP
                                           =System
#CCMSMonitorSet
                =WA1 = 33
                              =SPISAP
                                          =DB ALERT
                 =SP6 =00
#CCMSMonitorSet
                                 =SAP CCMS Technical Expert Monitors
=System / All Monitoring Segments / All Monitoring Contexts
                Localhost Remotehost SAP
# Remote Host
                                                SAP
                                        System Number
#RemoteMonitoring =hpspi003 =ovsdsap6 =SP6
                                                =00
```

```
# CCMSAcknowledgeMessage SAP Ack.filtered Enable=1
# System Messages Disable=0
CCMSAcknowledgeMessage =ALL =0
                                                     =0
CCMSAcknowledgeMessage =SP6
                                  =0
                                                    =0
# XMI compatibility mode
\# makes the r3monal send syslog messages r3monxmi style
# XmiSyslogMode Enabled =1
                  Disabled =0
                 =0
XmiSyslogMode
# Syslog filtering
# Alert Classes SAP SAP SyslogId Enabled=1
# System Number From To Disabled=0
AlerMonSyslog =ALL =ALL =A00 =MZZ =1
AlerMonSyslog =ALL =ALL =N00 =ZZZ =0
                                         =MZZ =1
AlerMonSyslog =LPO =01 =A00 =ZZZ =1
```

r3monal: Trace Levels

For more information about the trace levels the alert monitors use and, in particular, the trace levels available to the r3monal monitor, see Trace Level on page 40 in the section Monitor-Configuration Files on page 22.

r3monal: XMI Compatibility Mode

The XmiSyslogMode keyword allows you to specify that the r3monal monitor sends SAP system log alerts in the style and format previously used by the r3monxmi monitor. Note that at SPI for SAP version 11.x, the r3monxmi monitor is now obsolete; to continue monitoring CCMS syslog alerts, you will have to use the r3monal monitor, which uses the BAPI External Alert Management Interface (XAL).

Sending Syslog Messages in XMI Format

If you enable XmiSysLogMode you need to define in detail how the old r3monxmi monitor would filter SAP system-log messages. In most cases, you would do this by copying an existing configuration for the now-obsolete r3monxmi monitor and paste it into the r3monal configuration file, r3monal.cfg. If you do not provide the r3monxmi configuration, the SAP syslog messages will not appear in the XMI format you want. For more information about migrating from r3monxmi to r3monal, see r3monal: Migrating from r3monxmi on page 61.

r3monal: Alert Classes

In the alert-classes section of the r3monal.cfg file, you define how the SPI for SAP's CCMS alert monitor r3monal filters syslog events in the SAP System; the filtering mechanism ensures that you extract and display only those syslog events that you are interested in seeing. You filter the syslog events that you want to monitor by specifying ranges of message numbers (syslog IDs). Each line of the alert-classes section of the r3monal.cfg file is set up in a particular way. Each entry defines monitoring for a specified range of syslog events. You can specify which syslog events to monitor by enabling or disabling ranges of syslog IDs either globally or for specified SAP systems and instances.

In Syslog events in the r3monal.cfg file, r3monal monitors the syslog events with IDs A00 through MZZ on all SAP Systems and SAP numbers but does not monitor the syslog events with IDs N00 through ZZZ on all SAP Systems and numbers. Syslog event monitoring is enabled on SAP System LPO for IDs A00 through ZZZ.

Syslog events in the r3monal.cfg file

# Syslog filtering #						
# Alert Classes	SAP	SAP	Syslo	ogId	Enabled=1	
#	System	Number	From	To	Disabled=0	
AlerMonSyslog	=ALL	=ALL	=A00	=MZZ	=1	
AlerMonSyslog	=ALL	=ALL	=N00	=ZZZ	=0	
AlerMonSyslog	=LPO	=01	=A00	=ZZZ	=1	
#						

r3monal: Migrating from r3monxmi

The old r3monxmi monitor used XMI, the eXternal Management Interface, which was first introduced with SAP 3.0F. Since the SPI for SAP no longer supports SAP version 3.x, you can no longer use r3monxmi to monitor SAP System-log messages. If you want to continue to monitor syslog messages and CCMS alerts, you will have to migrate your XMI configuration to r3monal, the CCMS 4.x alert monitor. However, you can use the contents of the message-filtering section of the old r3monxmi.cfg file in the new configuration file for r3monal.



The r3monxmi monitor was application-server *dependent*; you had to install r3monxmi on each application server of the SAP System whose syslog messages you wanted to monitor.

The r3monal monitor is application server *independent*; r3monal can read the syslog messages from all application servers from a single location. Typically, you install r3monal on the central instance of the SAP system, whose syslog messages you want to monitor.

To migrate syslog-message monitoring from r3monxmi to r3monal:

- Define a CCMS monitor and monitor set for the syslog alerts r3monal uses the internal SAP NetWeaver CCMS monitor to check for syslog alerts; use transaction RZ20 to configure CCMS monitors.
- 2 In the CCMS monitor tree, check the r3syslog branches of *all* the application servers, whose syslog messages you want to monitor with the SPI for SAP.

You can automate the process by creating monitor-tree elements (MTEs) based on rules. When adding the new MTE node to the CCMS monitor, check the option Rule Node in the Create Nodes dialog; when setting up the CCMS rule, use the following values:

Rule Type:

 $CCMS_GET_MTE_BY_CLASS$

MTE Class:

R3Syslog

3 Enable the XmiSyslogMode keyword in the r3monal.cfg file

If you want the r3monal monitor to use the old r3monxmi configuration based on XMI message conditions, use the XmiSyslogMode keyword in the r3monal.cfg file. In this mode, r3monal sends SAP system-log alerts in the style and format previously used by the r3monxmi monitor.


4 Set up the system-log filters

Since r3monal supports the same system-log message filtering as r3monxmi, you can copy an existing system-log filtering configuration from the old r3monxmi.cfg configuration file and paste it into the new r3monal.cfg file. System-log message filtering is defined with the AlerMonSysLog keyword in the AlertClasses section of the configuration file.

#					
# Alert Classes	SAP	SAP	Syslog	gId	Enabled=1
#	System	Number	From	To	Disabled=0
AlerMonSyslog	=ALL	=ALL	=A00	=MZZ	=1
AlerMonSyslog	=ALL	=ALL	=N00	=ZZZ	=0
AlerMonSyslog	=LP	=01	=A00	=ZZZ	=1
#					

Figure 5 on page 62 shows you how the CCMS rule node for SAP syslog elements should look when you complete the configuration successfully.

Figure 5 Rules-based CCMS MTE for Syslog Elements



r3monal: Monitoring the J2EE Engine (Web AS Java)

The SPI for SAP can help you monitor the complete SAP NetWeaver environment, including the SAP J2EE Engine. Monitoring the SAP J2EE Engine is important since the combination of Java technology and the J2EE infrastructure is the foundation on which new SAP components such as the SAP Enterprise Portal or Process Infrastructure (PI) are built.

To monitor the SAP J2EE engine, you configure r3monal, the SPI for SAP's CCMS Alert monitor, to check for alerts generated by the J2EE monitor sets, which concern the status and availability of SAP's J2EE Engine, for example: the J2EE kernel, J2EE services, or the registered SAP CCMS agents within the SAP NetWeaver environments that you are monitoring with the SPI for SAP. For more information about configuring r3monal to monitor SAP's J2EE engine, see The J2EE (Web AS Java) Monitor on page 84.

r3monal: Monitoring Stand-alone Enqueue Servers

The enqueue server stores information about the locks currently in use by the users logged into the SAP System; the lock-related information is stored in the lock table of the main memory. If the host on which the enqueue server is running fails, the lock data is lost and cannot be restored even when the enqueue server restarts and all locks have to be reset. In a high-availability environment, you can avoid problems of this kind by configuring a stand-alone enqueue server. The combination of a stand-alone enqueue server and an enqueue replication server running on a separate host forms the basis of a high-availability solution.

To use the SPI for SAP to monitor alerts generated by a stand-alone enqueue server configured in a high-availability WebAS environment, you have to enable the appropriate CCMS monitors and MTEs (monitor-tree elements) in SAP and then configure r3monal, the SPI for SAP's CCMS alert monitor, to check for alerts concerning the status and performance of the stand-alone enqueue server in the SAP System. For more information about configuring r3monal to monitor a stand-alone enqueue server in WebAS, see The Enqueue-Server Monitor on page 87.

r3monal: Monitoring SAP Security-Audit Logs

The SAP security-audit log keeps a record of security-related activities in the SAP System and stores the information it collects in an audit log on each application server. The SPI for SAP allows you to monitor the CCMS alerts logged by the security-audit use them to generate messages, which you can arrange to send to the HPOM for Windows console.

To use the SPI for SAP to monitor the SAP security-audit logs, you have to enable the appropriate CCMS monitors and MTEs (monitor-tree elements) in SAP and then configure r3monal, the SPI for SAP's CCMS alert monitor, to check for alerts generated by the security-audit-log monitor, which concern the status of security events in the SAP System. For more information about configuring r3monal to monitor SAP's security-audit logs, see The SAP Security-Audit Monitor on page 93.

r3monal: Monitoring the Enterprise Portal

The SAP Enterprise Portal provides a secure and stable web interface that gives users global access to the information, applications, and services that they need to work effectively in the SAP landscape. The SPI for SAP allows you to make use of standard SAP elements to monitor the components of the SAP Enterprise Portal and provide reports on availability, response time, configuration, and performance.

To use the SPI for SAP to monitor alerts generated by a fully configured SAP Enterprise Portal, you have to enable the appropriate CCMS monitors and MTEs (monitor-tree elements) in SAP and then configure r3monal, the SPI for SAP's CCMS alert monitor, to check for alerts concerning the status and performance of the Enterprise Portal. For more information about configuring r3monal to monitor an Enterprise Portal, see The SAP Enterprise-Portal Monitor on page 89.

r3monal: Monitoring the CEN

The central monitoring system (CEN) is a single SAP system that you designate as the central point of control for CCMS alerts originating from all over the monitored SAP landscape. The CEN concept allows you to reduce the overhead of monitoring and managing multiple SAP systems by making essential information concerning problem alerts available in one, central location.

After you configure SAP to use the CEN for the central management of CCMS alerts, you can use the SPI for SAP's r3monal monitor to intercept the CCMS alerts destined for the CEN and use the alerts to generate messages, which it forwards to the HPOM for Windows console. For more information about configuring r3monal to monitor an SAP CEN, see Monitoring CCMS Alerts in the CEN on page 194.

r3monal: Testing the Configuration

The SPI for SAP's optional test transport includes a program that generates an ABAP dump which you can use to verify that the r3monal monitor checks the syslog and sends a message to HPOM for Windows if a dump occurs in the SAP System. If the test completes successfully, a message about the test dump appears in the HPOM for Windows console. Note that this test works only if you configure r3monal to monitor the appropriate SAP CCMS monitor sets, for example: <SAPSID>/R3Abap/Shortdumps.

For more information about SPI for SAP transports, see the transports read-me file \usr\sap\trans\readme on the HPOM for Windows managed node; for more information about importing and applying SPI for SAP transports, see the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*. After importing the transport, you can view the test programs installed by using the SAP transaction **SE80** to open the ABAP object navigator and browsing to the report (or program) /HPOV/YSPI0004.

r3mondev: The SAP Trace-file Monitor

The r3mondev monitor scans the trace files and log files of the SAP system for the string "ERROR". Because it monitors only what has occurred since its previous run, any error within a trace file generates only a single alert. The file monitor scans the following directories, where <SID> stands for the SAP system ID and <InstanceNumber> stands for the SAP instance number of the monitored SAP System:

- **UNIX/Linux**: /usr/sap/<*SID*>/<*InstanceNumber*>/work/
- Windows: <drive:>\usr\sap\<SID>\<InstanceNumber>\work

This section contains information about the following topics:

- r3mondev: File Locations on page 65
- r3mondev: Environment Variables on page 65

- r3mondev: Monitoring Conditions on page 65
- r3mondev: Editing the Configuration File on page 66

r3mondev: File Locations

The file monitor, r3mondev, includes the files listed in Table 8. For more detailed information about the contents of the in SPI for SAP monitor-configuration files in general and the file r3mondev.cfg in particular, see The SPI for SAP Monitor-Configuration File on page 25.

Table 8 r3mondev Files

File	Description
r3mondev(.exe)	Executable for the file monitor
r3mondev.cfg	Configuration file for monitored files
r3mondev.his	History file that stores data for each monitor run

r3mondev: Environment Variables

The file monitor uses environment variables listed in Table 9.

Table 9 r3mondev Environment Variables

Environment Variable	Description
SAPOPC_DRIVE	The Windows drive where the HPOM agent is running, for example, E:\usr\
SAPOPC_HISTORYPATH	Path to the r3mondev history file
SAPOPC_R3MONDEV_CONFIGFILE	Name of the r3mondev configuration file
SAPOPC_SAPDIR	The Windows drive where SAP NetWeaver is running, for example: E:\usr\sap
SAPOPC_TRACEPATH	Path to the r3mondev trace file

r3mondev: Monitoring Conditions

This section of the r3mondev.cfg file enables you to specify the device monitoring details for the SPI for SAP.

For more information about the entries in the r3mondev.cfg file including keywords and their possible values along with a description of each editable parameter, see The Alert-Monitor Configuration Files on page 49.

The monitoring conditions section of the r3mondev.cfg file includes the following default settings:

# AlertDevMon	SAP	SAP	Enable=1	File	Severity	Opc	OpC
#	System	Number	Disable=0	Mask		Object	MsgGrou
p			-				- 0 -
AlertDevMon	=ALL	=ALL	=1	=dev_*	=WARNING	=r3mondev	=R3_Tra
ce							

```
AlertDevMon =ALL =ALL =1 =std* =CRITICAL =r3mondev =R3_Tra
```

r3mondev: Editing the Configuration File

You can edit the r3mondev monitor's configuration file, r3mondev.cfg, in the following ways:

• Disable messages

If you do not want to receive any messages relating to dev_* files for any of the SAP systems you are monitoring with the SPI for SAP, change the first line of the r3mondev.cfg configuration file as follows:

```
AlertDevMon =ALL =ALL =0 =dev_* =WARNING =r3mondev =R3_Tr ace
```

• Change a message's severity level

If you want to reduce the severity of all messages relating to std* files from critical to warning, change the second line of the r3mondev.cfg configuration file as follows:

```
AlertDevMon =ALL =ALL =1 =std* =WARNING =r3mondev =R3 Trace
```

Define exceptions to general rules

If you want to increase the severity of messages relating to dev_* files on SAP system LP2 from warning to critical, leave the default settings as they are and add the following line:

```
AlertDevMon =LP2 =ALL =1 =dev_* =CRITICAL =r3mondev\
=R3 Trace
```



Wildcards are only allowed at the end of the string. Only SAP trace files located in the work directory are relevant and the names of these files must begin with either dev or std.

r3monpro: The SAP Process Monitor

The r3monpro monitor scans all processes associated with a given instance, such as dialog, enqueue, update, batch, dispatch, message, gateway, and spool work processes. It is also used for monitoring database processes.

This section contains information about the following topics:

- r3monpro: File Locations on page 67
- r3monpro: Environment Variables on page 67
- r3monpro: Monitoring Conditions on page 67
- r3monpro: Example Configuration on page 68

r3monpro: File Locations

The process monitor r3monpro contains the files listed in Table 10. For more detailed information about the contents of the in SPI for SAP monitor-configuration files in general and the file r3monpro.cfg in particular, see The SPI for SAP Monitor-Configuration File on page 25

Table 10 r3monpro Files

File	Description
r3monpro(.exe)	Executable for the process monitor
r3monpro.cfg	Configuration file for the process monitor
r3monpro.his	History file for storing data after each monitor run

r3monpro: Environment Variables

The process monitor r3monpro uses the environment variables listed in Table 11.

Table 11 r3monpro Environment Variables

Environment Variable	Description
SAPOPC_DRIVE	The Windows drive where the HPOM agent is running, for example, E:\usr\
SAPOPC_HISTORYPATH	Path to the r3monpro history file
SAPOPC_R3MONPRO_CONFIGFILE	Name of the r3monpro configuration file
SAPOPC_SAPDIR	The Windows drive where SAP NetWeaver is running, for example: E:\usr\sap
SAPOPC_TRACEPATH	Path to the r3monpro trace file

r3monpro: Monitoring Conditions

Monitoring conditions for r3monpro are specified in the r3monpro.cfg file. Individual rows define monitoring conditions for specific processes. You use the r3monpro.cfg file to set the rules which define how the number of processes running should be measured and what severity level should be assigned to the alert that is generated if the number of processes exceeds the limits you define.

You can set monitoring conditions for a specific process to any of the following modes:

Exact

The number of process running on a managed node must be equal to the specified number.

Mir

The number of processes running on a managed node must not be less than the specified number.

Max

The number of processes running on a managed node must not be more than the specified number

Delta

r3monpro triggers an alert if there is any change in the number of processes running on a managed node or if the specific amount of allowed change in the number of instances of the same process exceeds the defined limit. This mode enables you to recognize changes without having to define an absolute number of processes for a managed node.

For example, if Delta =2, then a difference of 2 or more between the number of processes (n) found in the previous and current monitor run on a managed node triggers an alert. Note that if r3monpro triggers an alarm, it resets n to the number of processes discovered in the most recent monitor run, and calculates the new Delta on the basis of the new number of processes found running.

Messages generated by matched conditions include an operated-initiated action; the action calls an SPI for SAP module which lists all the current processes for the affected SAP instance.

For more information about the entries in the r3monpro.cfg file including keywords and their possible values along with a description of each editable parameter, see The Alert-Monitor Configuration Files on page 49.

r3monpro: Example Configuration

The first row of the following example shows how to monitor the saposcol process on all hosts. Note that exactly one such process should run at any given time. Any violation of this number is critical. It affects the HPOM for Windows object saposcol. The associated HPOM for Windows message group is R3 State.

The last row of the same example specifies that eight or fewer instances of the dw.sapSID process should run on all hosts. If the number is larger than eight, the monitor generates a warning message associated with HPOM for Windows object dw.sap and HPOM for Windows message group R3_State.

The string SID has special meaning in this context. SID will be replaced by the SAP System name on the managed node. This enables global definitions for different SAP Systems.

```
AlertInstMonPro =ALL =00 =saposcol =1 =Exact=1 =CRITICAL =saposcol =R3_State

AlertInstMonPro =C01 =00 =explorer =1 =Max =1 =CRITICAL =explorer =R3_State

AlertInstMonPro =T11 =00 =dw.sapSID =1 =Min =8 =WARNING =dw.sap =R3_State
```

It is also possible to ensure that a process is not running. To do so, use the mode Exact and enter 0 as the number.



On servers running the UNIX operating system, r3monpro can identify processes at the instance level. On servers running the Windows operating system, you need to define on a single line the total number of work processes on the node. For example, if there are two SAP instances, each with four (4) work processes, the total number of processes is eight (8).

For SAP servers running on UNIX operating systems, you can configure the SPI for SAP process monitor r3monpro to monitor the specific SAP-gateway read process gwrd associated with individual SAP SIDs, which is especially useful in a multi-SID environment. If you have multiple instances of SAP running in the same SID, you can configure r3monpro to monitor

the specific SAP-gateway read process gwrd assigned to each, individual *instance*, too. For more information about how to configure r3monpro to monitor individual gwrd processes in an environment where multiple SAP instances or multiple SAP SIDs are running on the same SAP server, have a look at the following examples:

- Monitoring SAP-Gateway Read Processes per SID on page 69
 Monitoring SAP-Gateway Read Processes per SAP SID
- Monitoring SAP-Gateway Read Processes per SAP Instance on page 69
 Monitoring SAP-Gateway Read Processes per SAP Instance

Monitoring SAP-Gateway Read Processes per SID on page 69 shows how to configure r3monpro to monitor the individual gwrd processes associated with specific SIDs on a SAP server hosting multiple SAP SIDs.

Monitoring SAP-Gateway Read Processes per SID

```
AlertInstMonPro =Q12 =ALL =gwrd -dp pf=/usr/sap/

SID* =1 =Exact =1 =CRITICAL \

=gwrd =R3_State

AlertInstMonPro =Q22 =ALL =gwrd -dp pf=/usr/sap/

SID* =1 =Exact =1 =CRITICAL \

=gwrd =R3_State

AlertInstMonPro =Q32 =ALL =gwrd -dp pf=/sapmnt/

SID* =1 =Exact =1 =CRITICAL \

=gwrd =R3_State

AlertInstMonPro =Q52 =ALL =gwrd -dp pf=/usr/sap/

SID* =1 =Exact =1 =CRITICAL \

=gwrd =R3_State
```

Monitoring SAP-Gateway Read Processes per SAP Instance on page 69 shows how to configure r3monpro to monitor the individual gateway processes associated with specific SAP instances on a SAP server hosting multiple SAP instances per SAP SID.

Monitoring SAP-Gateway Read Processes per SAP Instance

```
AlertInstMonPro =Q12 =12 =gwrd -dp pf=/usr/sap/
SID* =1 =Exact =1 =CRITICAL \ =gwrd =R3_State
AlertInstMonPro =Q22 =21 =gwrd -dp pf=/usr/sap/Q22/SYS/profile/
Q22_D21_sap2ap1 \ =1 =Exact =1 =CRITICAL =gwrd =R3_State
AlertInstMonPro =Q22 =22 =gwrd -dp pf=/usr/sap/Q22/SYS/profile/
Q22_D22_sap2ap1 \ =1 =Exact =1 =CRITICAL =gwrd =R3_State
AlertInstMonPro =Q32 =32 =gwrd -dp pf=/sapmnt/
SID* =1 =Exact =1 =CRITICAL \ =gwrd =R3_State
AlertInstMonPro =Q52 =52 =gwrd -dp pf=/usr/sap/
SID* =1 =Exact =1 =CRITICAL \ =gwrd =R3_State
```

In the configuration file r3monpro.cfg, the path to the SAP-instance profile defined in the pf parameter is case-sensitive. To avoid problems, make sure that the path to the SAP-instance profile defined in the r3monpro.cfg configuration file matches the path displayed in the output of the ps command, for example:

r3status: The SAP Status Monitor

The r3status monitor checks the current status of SAP NetWeaver and compares it with the last recorded status to determine whether any change in status occurred since the last time the monitor ran. Using the SAP NetWeaver function module RFC_SYSTEM_INFO, the r3status monitor provides the following features:

- Reports about local SAP NetWeaver system-availability
- Recognition and monitoring of each individual SAP NetWeaver instance
- SAP NetWeaver availability status reported may be: up, down, hanging (RFC time out).

The r3status monitor is of type *time frame*. It runs every two minutes and compares the current value with the previous value stored in the history file and generates a message if it finds a difference, which it needs to report. For more information about reporting types, see Report Types for the Alert-Collector Monitors on page 101.



The lack of response from SAP could be due to a problem which does not mean that the System is down. For example, SAP would not respond if all available dialog work processes were allocated. For more information about how r3status interprets the responses it receives from SAP, see r3status: Establishing the SAP Status on page 73.

This section contains information about the following topics:

- r3status: File Locations on page 70
- r3status: Environment Variables on page 71
- r3status: History File on page 71
- The r3status Configuration File on page 72
- r3status: Establishing the SAP Status on page 73
- r3status: Monitoring SAP Remotely on page 73

r3status: File Locations

This table lists the files used by the r3status monitor.

Table 12 r3status Files

File	Description
r3status(.exe)	Executable for the r3status monitor
r3status.log	The r3status monitor creates a log/trace file after each run of the monitor. The trace file is stored in the standard HPOM Agent log directory.

Table 12 r3status Files (cont'd)

File	Description
r3itosap.cfg	The r3status monitor uses information in the r3itosap.cfg file to determine which SAP instances it is supposed to monitor.
r3status.cfg	The r3status monitor uses information in the r3status.cfg file to determine history paths, trace levels, and which SAP instances it is supposed to monitor on remote SAP servers.
r3status.his	History file for storing data after each run of the r3status monitor. The r3status monitor uses information in this file to determine whether a change of status has occurred. For more information, see r3status: History File on page 71.

r3status: Environment Variables

Table 13 lists the environment variables used by the r3status monitor.

Table 13 r3status Environment Variables

Environment Variable	Description
SAPOPC_RFC_TIMEOUT	set time out value for RFC connections - default is 20 seconds
SAPOPC_HISTORYPATH	Path to the r3status.his history file a
SAPOPC_R3STATUS_CONFIGFILE	Name of the configuration file, which the r3status monitor uses
SAPOPC_R3ITOSAP_CONFIGFILE	Name of the general configuration file, which contains SAP login information used by the SPI for SAP monitors
SAPOPC_TRACEPATH	Path to the r3status trace file
G 0 1 1 TT 1 TT 1	

a. See: r3status: History File on page 71

r3status: History File

The first time the r3status monitor runs, it writes its findings to the history file, r3status.his. The next time the r3status monitor runs, it uses the information in the r3status.his file to determine whether a change of status has occurred since the last time the monitor ran and, as a consequence, which if any message it needs to send to the HPOM for Windows management server. For more information about the default location of the monitor history files on the managed nodes, see The SPI for SAP Monitor-Configuration File on page 25.

The r3status monitor updates the entries in the r3status.his file at the end of each time it runs, with the current timestamp and the current status of each monitored SAP instance.

Excerpt from the r3status.his file on page 72 shows the format and contents of the r3status.his file.

Excerpt from the r3status.his file

021028-11:18:29					
#					
021028-11:18:29	#Keyword	SAP	SAP	SAP	State
021028-11:18:29	#	System	Number	Instance	
021028-11:18:29	#				
021028-11:18:29	ConfiguredInstance	=DEV	=00	=DVEBMGS00	=UP
021028-11:18:29	ConfiguredInstance	=PKR	=99	=DVEBMGS99	=DOWN

The r3status Configuration File

The r3status monitor's configuration file allows you to use the keywords listed below to change the configuration from the default settings to meet the requirements of your particular environment. Where appropriate, possible values for a given keyword are also specified. Default r3status Configuration File on page 74 shows what a complete configuration file looks like for the r3status monitor, which monitors the status of both local and remote SAP Systems.

The following standard keywords work as expected in the context of the r3status.cfg configuration file. For more information about the parameters the keywords require, see The SPI for SAP Monitor-Configuration File on page 25:

- TraceLevel
- TraceFile
- HistoryPath[Unix | AIX | WinNT]

The following keywords require special attention when used in the context of the SPI for SAP r3status.cfg configuration file:

EnableDPQueueCheck

r3status requires a dialog work process to log on to SAP and determine the System's status. Enable the EnableDPQueueCheck keyword (=1) if the SAP System whose status you are monitoring is experiencing performance problems and you want r3status to check the size and status of the ABAP dispatcher before starting its monitor run. If there are no, or too few, dialog work processes available, r3status sends a message to the console indicating that it did not start due to the violation of a threshold defined for dialog processes. The command disables the monitor run only for the SIDs where the threshold violation for the dialog work processes occurred.

If you use the EnableDPQueueCheck keyword in the r3status configuration file, remember to configure the keywords DPQueueCheck and DisableMonitoringWithSeverity in the r3mondisp.cfg configuration file, too. For more information about monitoring the ABAP dispatcher and its queues, see r3mondisp: the ABAP Dispatcher Monitor on page 80.

The default run interval for r3status is two minutes. If your SAP landscape consists of large numbers of SAP instances running on multiple hosts, network congestion or a slow response from SAP might prevent EnableDPQueue from checking the status of the ABAP dispatchers on all the configured SAP instances before r3status starts its next run. In

the unlikely event that this happens, the old instance of r3status aborts without reporting the status of any dispatchers that it has not yet checked. To avoid this problem re-occurring, increase the run interval for r3status.

RemoteMonitoring

r3status cannot check the status of the ABAP dispatcher on a SAP System, which the SPI for SAP is monitoring remotely.

For more information about monitoring the status of remote SAP Systems, see r3status: Monitoring SAP Remotely on page 73.

r3status: Establishing the SAP Status

When the status monitor r3status checks the availability of an SAP System, it reports the status as: up, down, or connection time-out. Although the meaning of "up" and "down" is clear, the status of the connection time-out status requires some explanation. The time-out status could occur if an SAP System is hanging, in which case the problem could be due to an RFC time out, which itself needs investigating and is a good example to show how difficult it can be sometimes be to establish the exact state of the SAP System the SPI for SAP is monitoring.

The status monitor, r3status, considers an SAP instance as "not available" if the SAP instance does not respond within 60 seconds. However, the lack of response from SAP could be due to a problem which does not mean that the System is down, for example: all available dialog work processes are allocated, or all available SAP gateway connections are busy. The SPI for SAP status monitor, r3status, reports the status of the SAP System it is monitoring according to the following rules:

• Available:

r3status reports an SAP System as available if it can log on to the SAP instance and, in addition, start and receive a response from the SAP function module RFC_SYSTEM_INFO within 60 seconds.

Not Available:

r3status reports an SAP System as *not* available if the SAP instance does not respond within 60 seconds or the function module RFC_SYSTEM_INFO could not start, for example: due to the fact that the instance is down.

r3status: Monitoring SAP Remotely

The SPI for SAP includes a feature which allows you to extend the scope of the monitors to remotely monitor the status of SAP on SAP servers (which are *not* HPOM for Windows managed nodes) from a host, which *is* already configured as an HPOM for Windows managed node and where the SPI for SAP is running.

To make use of the remote-monitoring feature provided by the SPI for SAP, for example, to monitor a SAP server running on an operating system that is not supported by the SPI for SAP, you need to enable the **RemoteMonitoring** keyword (by removing the leading hash symbol "#") in the r3status.cfg file. Next, on the same line, you define the name of the local host, which you want to perform the monitoring. Finally, you have to define the name of the

remote SAP server, which you want to monitor. Default r3status Configuration File on page 74 shows how a new line is required for each *additional* SAP server, which you want to monitor remotely.



You can associate multiple remote SAP servers with one, single local host or you can associate single remote hosts with individual, different local hosts. Default r3status Configuration File on page 74 shows a mixed approach where one *local* host "sap1" is used to monitor two *remote* hosts; "sdsap" and "sapwolf". A third local host "sap2" remotely monitors the remote host "triosap".

For more information about the contents of the r3status monitor's configuration file including the keywords and parameters you use to define local and remote server names, see the entry concerning "Remote Monitoring" in The r3status Configuration File on page 72.

Default r3status Configuration File

```
#-----
# TraceLevel hostname Disable=0 only error messages=1
            info messages=2 debug messages=3
TraceLevel =ALL =0
#-----
# TraceFile hostname filename TraceMode
                         (a=append/w=create(default)) (in mins)
TraceFile =ALL =r3status.log =w
#-----
              hostname path
# Path
HistoryPathUniX =ALL =default
HistoryPathAIX =ALL =default
HistoryPathWinN =ALL =default
#-----
# Check the ABAP dispatcher before a connection to SAP is
# opened. If the dialog queue is too full or not enough
# free work processes are available, monitoring is disabled.
# This feature should only be enabled in special cases. For
# regular dispatcher monitoring, use the r3mondisp.
# EnableDPQueueCheck hostname SAP SAP Enable=1/
                  System Number Disable=0
EnableDPQueueCheck =ALL =ALL =0
#-----
# Remote Local Remote 
# Monitoring Host Host
# Monitoring Host Host
RemoteMonitoring = sap1 = sdsap
RemoteMonitoring = sap1 = sapwolf
RemoteMonitoring = sap2 = triosap
```

r3monsec: The SAP Security Monitor

The SPI for SAP security monitor checks the following areas in your SAP Systems:

- The privileges and authorizations assigned to (and used by) important SAP users
- Insecure (default) passwords in use by SAP and Oracle users
- SAP System parameters which affect overall system security
- Miscellaneous security events such as failed logins or attempts to change SAP System settings

In addition to the other SAP user roles and authorizations required by the SPI for SAP (such as SAPSPI_MONITORING_*), you also have to assign the authorizations defined in the SAP user role /HPOV/SAPSPI_SECURITY_MON to the HPOM for Windows user under which r3monsec runs before r3monsec starts; the user role /HPOV/SAPSPI_SECURITY_MON includes authorizations (such as S_TCODE or S_USER_AUT) that are needed to execute the SAP reports, which r3monsec calls by means of the SAP RFC interface.

This section contains information about the following topics:

- r3monsec: File Locations on page 75
- r3monsec: Alert Types on page 75
- r3monsec: Monitoring Security Remotely on page 79



If you use the SPI for SAP tools located in the console to configure r3monsec, the SPI for SAP checks the validity of the new configuration when you try to save the modified configuration file. For more information about the validation tool and the messages it generates, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

r3monsec: File Locations

The SAP System-security monitor r3monsec uses the files listed in this table.

Table 14 r3monsec Files

File	Description
r3monsec(.exe)	Executable for the SAP System-security monitor
r3monsec.cfg	Configuration file for the SAP System-security monitor.
r3monsecpw.msg	Contains encrypted passwords for standard Oracle users in an SAP environment.
r3monsec.log	File used to store trace data collected by the SAP System-security monitor.

r3monsec: Alert Types

The security monitor r3monsec uses the following alert types:

• r3monsec: SAP_PARAMETERS on page 76

Monitors security-related parameters such as those defined in the SAP report RSPFPAR.

r3monsec: DEFAULT_USERS on page 78

Monitors settings for passwords defined for SAP and Oracle users to ensure that insecure default passwords are not in use.

r3monsec: PRIVILEGED_USERS on page 78

Monitors any special privileges granted to SAP users or being requested by users who are not normally entitled.

The SPI for SAP interprets *include* and *exclude* parameter values for an alert-type entry according to whether the values appear in the same parameters or in different parameters. The SPI for SAP compares values in *different* parameters using 'and'. The SPI for SAP compares values in the *same* parameter as follows.

- **Include**: use 'or' to compare the parameters
- **Exclude**: use 'and' to compare the parameters

The SPI for SAP evaluates *include* values before it evaluates *exclude* values.

Note that the SPI for SAP ignores include and exclude parameters for the r3monsec alert types SAP_PARAMETERS and DEFAULT_USERS; however, you *must* use include and exclude parameters for the alert type PRIVILEGED_USERS.

r3monsec: SAP PARAMETERS

Use the SAP_PARAMETERS alert type to configure the SPI for SAP's security monitor, r3monsec, to monitor the settings of (and any changes to) security-related SAP parameters. The SAP_PARAMETERS alert type compares the values you define in the r3monsec.cfg file with the contents of the SAP report RSPFPAR, which contains security-related parameters for the SAP instances you are monitoring.

The default settings for the alert type SAP_PARAMETERS reflect a small selection of the parameters defined in the SAP report RSPFPAR; you can change the contents of the SAP_PARAMETERS section of the r3monsec.cfg file to suit the needs of your SAP environment by adding, modifying, or removing values accordingly.



The alert type SAP_PARAMETERS ignores include (=I) and exclude (=E) parameter.

Example SAP_PARAMETERS settings on page 76 shows how to configure r3monsec to monitor the SAP parameter, which defines whether SAP should automatically unlock locked SAP users at midnight. The example configuration tells r3monsec to check that the automatic unlocking of locked SAP users is *disabled* in SAP (=EQ =0). In this example, r3monsec would generate a message with the severity level "critical" if it found that the parameter was enabled in SAP and assign the generated message to the HPOM for Windows message group R3_Security.

Example SAP_PARAMETERS settings

```
AlertMonFun =ALL =ALL =ALL =SECURITY =1\
=CRITICAL =SAP_PARAMETERS =R3_Security\
=SAP_PARAMETERS =login/failed user auto unlock =I =EQ =0 =
```

Table 15 on page 77 shows the default settings for the SAP_PARAMETERS alert type; if your SAP Systems are configured differently, r3monsec will generate alerts. For example, in the default configuration, SAP user passwords must have 6 characters or more and contain at least 4 letters and 2 integers. If you configure your SAP instance to allow passwords which do

not conform to the rules defined in r3monsec's configuration file, for example: passwords which contain only five characters or do not contain any integers, r3monsec sends a message to the console.

Note that r3monsec does not read or check the SAP passwords themselves; r3monsec compares the *rules* you define in r3monsec.cfg for the length and form of SAP passwords with the *rules* defined in SAP itself for password creation. If the rules for password creation, form, or length in the r3monsec.cfg file differ in any way from the rules for passwords defined in SAP, the SPI for SAP sends a message to the console..

Table 15 Default Settings for SAP_PARAMETERS

Parameter	Default Value
login/failed_user_auto_unlock	0 (0=disabled; 1=enabled)
login/fails_to_session_end	3
login/fails_to_user_lock	5
login/min_password_diff	3
login/min_password_lng	6
login/min_password_letters	4
login/min_password_digits	2
login/min_password_specials	0
login/no_automatic_user_sapstar	1
login/password_max_new_valid	10
login/password_max_reset_valid	2
login/password_expiration_time	30
login/disable_password_logon	0 (0=disabled; 1=enabled)
login/disable_multi_gui_login	0 (0=disabled; 1=enabled)
login/disable_cpic	0 (0=disabled; 1=enabled)
login/system_client	100
login/disable_multi_rfc_login	0 (0=disabled; 1=enabled)
rdisp/gui_auto_logout	1800

r3monsec: DEFAULT USERS

Use the DEFAULT_USERS alert type to configure the SPI for SAP's security monitor, r3monsec, to check the passwords for standard SAP or Oracle database users and determine whether any well-known, default passwords are still in use. Standard SAP users include SAP*, DDIC, SAPCPIC, and EARLYWATCH. The DEFAULT_USERS alert type makes use of the SAP report RSUSR003.

The r3monsec.cfg configuration file provides default settings for the alert type DEFAULT_USERS. Note that include (=I) and exclude (=E) parameter is ignored for the alert type DEFAULT USERS.

Default Settings for DEFAULT_USERS

```
AlertMonFun =ALL =ALL =ALL =ALL =SECURITY =1\
=CRITICAL =DEFAULT_USERS =R3_Security\
=DEFAULT USERS
```

The default configuration for the DEFAULT_USERS alert type enables the SAP and Oracle user check, which means the monitor generates an alert if it finds a default password in use.

r3monsec: PRIVILEGED USERS

Use the PRIVILEGED_USERS alert type to configure the SPI for SAP's security monitor, r3monsec, to check the authorizations granted to SAP users in the Systems you are monitoring with the SPI for SAP. The PRIVILEGED_USERS alert type compares the values defined in the r3monsec.cfg file with the contents of the SAP report RSUSR005, which lists information concerning the critical authorizations granted to SAP users. The SAP System-security monitor, r3monsec, generates an alert for any SAP user who has critical authorizations but is not defined in the r3monsec.cfg file.



The SAP report RSUSR005 is SAP-client dependent; r3monsec monitors only the users for the SAP clients defined in the central SPI for SAP configuration file r3itosap.cfg.

The r3monsec.cfg configuration file does not provide any default settings for the alert type PRIVILEGED_USERS; you have to decide which user authorizations you want to monitor in SAP and insert the strings that define them into the monitor-configuration file manually. You can use the report RSUSR005 to find the strings defining the authorizations you want to monitor, for example: "All rights for background jobs", as illustrated in Example Settings for PRIVILEGED_USERS on page 78. Note that you need to use a new line for each user authorization that you want to monitor.

After you have determined which user authorizations you want to monitor, set include (=I) or exclude (=E) parameter to specify which SAP users you want to check for the use (or misuse) of the defined authorization. Example Settings for PRIVILEGED_USERS on page 78 shows how to exclude SAP user KWAME from the check to determine which users have permission to execute external operating-system commands.

Example Settings for PRIVILEGED_USERS

```
AlertMonFun =ALL =ALL =ALL =SECURITY =1\
=CRITICAL =PRIVILEGED_USERS =R3_Security\
=PRIVILEGED_USERS =All rights for background jobs =I =EQ =ALL =
AlertMonFun =ALL =ALL =ALL =SECURITY =1\
=CRITICAL =PRIVILEGED_USERS =R3_Security\
=PRIVILEGED_USERS =Execute external operating system commands\
=E =EQ =KWAME =
```

Note that the string you paste into the r3monsec.cfg file must match an existing string in SAP. If the string you paste into the r3monsec.cfg configuration file does not exist in SAP, for example because it contains a typo or is only a sub-set of a known SAP user-authorization string, no match occurs and the r3monsec monitor does not send any message to the console. For example: "Execute external operating" would not match, since it is only a part of the complete user-authorization string "Execute external operating system commands" defined in the r3monsec.cfg file.

r3monsec: Monitoring Security Remotely

To make use of the remote-monitoring feature provided by the SPI for SAP, for example, to monitor security on an SAP server running on an operating system that is not supported by the SPI for SAP, you need to enable the RemoteMonitoring keyword (by removing the leading hash symbol "#") in the r3monsec.cfg file.

You also need to specify the name of the local host, which you want to perform the monitoring and the name of the remote SAP server, whose security settings you want to monitor. Note that you must add a new line for each *additional* SAP server, which you want to monitor remotely.

Default r3monsec Configuration File

```
#-----
# TraceLevel hostname Disable=0 only error messages=1
                 info messages=2 debug messages=3
TraceLevel =ALL =0
# TraceFile hostname filename TraceMode TracePeriod
                   (a=append/w=create(default)) (in mins)
TraceFile =ALL =r3monsec.log =w
#-----
# History hostname path
# Path
HistoryPathUnix =ALL =default
HistoryPathAIX =ALL =default
HistoryPathWinNT =ALL
                     =default
# Remote Local
# Monitoring Host
                      Remote
                      Host
RemoteMonitoring =sap1 =sdsap
#-----
# AlertMonFun SAP SAP SAP SAP Alertmonitor Enable =1/
         Hostname System Number Client
                                               Disable=0
           OpC
                     OpC
  OpC
  Severity Object MsgGroup \
# Alerttype RFC Parameter
           =Parameter =Sign =Opt =Low =High 
 [=Param =Sign =Opt =Low =High] \dots
#
AlertMonFun =ALL =ALL =ALL =SECURITY =1
```

```
=CRITICAL =SAP_PARAMETERS =R3_Security\
=SAP_PARAMETERS =login/failed_user_auto_unlock =I =EQ =0 =

AlertMonFun =ALL =ALL =ALL =SECURITY =1\
=CRITICAL =DEFAULT_USERS =R3_Security\
=DEFAULT_USERS = = = = =

AlertMonFun =ALL =ALL =ALL =SECURITY =1\
=CRITICAL =PRIVILEGED_USERS =R3_Security\
=PRIVILEGED_USERS =All rights for background jobs =I =EQ =ALL =
```

r3mondisp: the ABAP Dispatcher Monitor

The SPI for SAP's ABAP dispatcher monitor, ramondisp, checks the size, content, and status of the queues for the different types of SAP work-processes and generates an alert if a queue becomes so full that it could have an adverse effect on SAP-System performance, or if a low percentage of work processes are idle.

r3mondisp monitors the queues which belong to the SAP instances defined in the SPI for SAP's central configuration file, r3itosap.cfg and allows you to manage SAP performance issues more pro-actively by avoiding bottlenecks and helping to ensure that the monitored SAP Systems have enough work processes available to fulfill all user requests, even when loads are typically very high.

This section contains information about the following topics:

- r3mondisp: Pre-requisites on page 80
- r3mondisp: File Locations on page 81
- Integrating r3mondisp with the SPI for SAP Monitors on page 81
- The r3mondisp Configuration File on page 82

r3mondisp: Pre-requisites

If r3mondisp is not able to find either the correct version of the SAP executable dpmon or the profile of the SAP instance whose queues you want to monitor, it aborts its run, writes an entry in its log file, and sends a message to the console. r3mondisp requires a version of the dpmon executable, which recognizes the -s[snapshot] option.

To check if the correct version of the dpmon executable is available on the SAP server which you want to monitor with r3mondisp, log on to the SAP server as user <SID>adm and run the dpmon command with the -help option. If the command output displays the -s[snapshot] option as shown in Checking the snapshot option on page 80, you can configure and use the r3mondisp monitor.

Checking the snapshot option

\$>dpmon -help

```
-t <trace_level> tracelevel (default:1)
-f <trace_file>] name of the tracefile (default: dev_dpmon)
-T <timeout> network time-out value in ms (default:500)
```

On both UNIX and Windows operating systems, r3mondisp uses the environment variables SAPOPC_DPMON_PATH_ <SID> and SAPOPC_PROFILE_<SID>_<InstNr> to determine the location of dpmon and the SAP instance profile respectively. If the variables are not set, r3mondisp uses the registry on Windows operating systems to determine the path to dpmon and the profile-file for the monitored SAP instances.

On UNIX operating systems, r3mondisp does not require any special interface to determine the location of dpmon or the profile-file for the monitored SAP instances: it assumes they are in the default SAP location. If you know the profiles files are not in the default location, or the name of the profile does not follow standard SAP naming conventions, you must indicate this in the r3mondisp.cfg configuration file. The standard naming convention for an SAP profile is:

```
<SID>_[D|DVEBMGS]<SysNr>_<hostname>
```

For more information about the contents of the r3mondisp configuration file, see The r3mondisp Configuration File on page 82.

r3mondisp: File Locations

The SAP System-security monitor r3mondisp uses the files listed in this table.

File Description

r3mondisp(.exe) Executable for the ABAP Dispatcher-queue monitor

r3mondisp.cfg Configuration file for the ABAP dispatcher-queue monitor.

r3mondisp.log File used to store trace data collected by the ABAP dispatcher-queue monitor.

Table 16 r3mondisp Files

Integrating r3mondisp with the SPI for SAP Monitors

To prevent the SPI for SAP itself causing excessive and unnecessary load on the SAP System at critical times, you can configure the SPI for SAP's ABAP-dispatcher monitor r3mondisp to work together with the other SPI for SAP monitors so that the monitors check the status of the ABAP dispatcher and establish how full the dispatcher queues are *before* requesting a work process. SPI for SAP monitors require a dialog work process to logon to SAP. To enable this integration feature, use the EnableDPQueueCheck keyword in the configuration file for the SPI for SAP monitor, which you want to configure to check the dispatcher status before starting.

For example, if you want the CCMS monitor, r3monal, to check the status of the ABAP dispatcher before r3monal starts its monitor run, configure the EnableDPQueueCheck keyword in the file r3monal.cfg, as illustrated in Checking the ABAP Dispatcher Before Startup on page 82. If r3monal's request for a work process violated a threshold for dialog work processes defined in the r3mondisp.cfg configuration file, the r3monal monitor would not start its monitor run; it would send a message to the console indicating the reason why it

did not start. You should consider using this feature where SAP System performance could be further compromised as a result of a request for an additional dialog work process by a SPI for SAP monitor.



r3mondisp is not affected by the thresholds defined for the EnableDPQueueCheck keyword; r3mondisp continues to work normally even if other monitors do not start as a result of a lack of available dialog work processes.

Checking the ABAP Dispatcher Before Startup

<pre># EnableDPQueueCheck</pre>	hostname	SAP	SAP	Enable =1
#		System	Number	Disable=0
#				
EnableDPQueueCheck	=ALL	=ALL	=ALL	=1

For more information about the EnableDPQueueCheck keyword, see Enable DP Queue Check on page 35.

The r3mondisp Configuration File

The r3mondisp monitor's configuration file allows you to use the keywords listed in this section to configure r3mondisp to meet the requirements of your particular SAP environment. Excerpt from a r3mondisp Configuration File on page 83 shows an excerpt from the r3mondisp monitor's default configuration file.



If you configure the SPI for SAP monitors to check the status of the ABAP dispatcher before starting their monitor run, make sure they can see and read a valid r3mondisp.cfg configuration file. The monitors require the information stored in this file and will not start if they cannot find it.

You can use the following keywords in the SPI for SAP r3mondisp configuration file. For more information about allowed values for the parameters in the following list, see The SPI for SAP Monitor-Configuration File on page 25.

TraceLevel

Set the trace level for r3mondisp when it runs on the specified SAP server. The TraceLevel keyword accepts the following parameters:

```
TraceLevel =<hostname> =<TraceLevel>
```

TraceFile

Set the name of the trace file, which r3mondisp uses to log entries. The TraceFile keyword accepts the following parameters:

```
TraceFile =<hostname> =<filename> =<TraceMode> =<TracePeriod>
```

DPQueueCheck

Manages the pro-active monitoring of the ABAP dispatcher. If more than one threshold matches for the same managed node and the same work-process, r3mondisp only sends the message with the highest severity. The DPQueueCheck keyword accepts the following parameters:

```
DPQueueCheck =<hostname> =<SID> =<InstanceNr> \ =<disable/enable>\
=<OVO Msg Group> =<OVO Msg Object> =<OVO Severity> \
=<WP-Type> =<Idle/Queue> =<Percentage idle/full>
```

Since the status of queued work-process is, generally speaking, more important than the status of idle work processes of the same work-process type, we recommend that the severity level assigned to messages concerning queued work processes is higher than the severity level you associate with messages about idle work processes. For example, you can assign the severity level Warning to messages about idle work processes and Critical to messages about queued work processes.

For more information about required parameters, see The SPI for SAP Monitor-Configuration File on page 25.

• DisableMonitoringWithSeverity

Specify which r3mondisp message severity should trigger the disabling of integrated SPI for SAP monitors to prevent the monitors increasing loads unnecessarily by requesting additional dialog work processes from the SAP Systems, whose dispatcher you are monitoring with the SPI for SAP. The DisableMonitoringWithSeverity keyword accepts the following parameters:

```
DisableMonitoringWithSeverity =<hostname> =<SID> \
=<InstanceNr> =<Severity>
```

For more information about the required parameters, see The SPI for SAP Monitor-Configuration File on page 25.

The DisableMonitoringWithSeverity keyword must be used in conjunction with keywords DPQueueCheck, which you configure in the r3mondisp.cfg file, and EnableDPQueueCheck, which you define in the configuration file of the SPI for SAP monitor you want to integrate with r3mondisp. For more information about the keyword EnableDPQueueCheck, see Enable DP Queue Check on page 35.

InstanceProfilePath

The path to the profile-configuration file for an SAP instance whose dispatcher you want to monitor; the InstanceProfilePath keyword accepts the following parameters:

```
InstanceProfilePath =<hostname> =<SID> =<InstanceNr> \ =<path>
```

For more information about the required parameters, see The SPI for SAP Monitor-Configuration File on page 25.

#-----

Excerpt from a r3mondisp Configuration File on page 83 shows how to configure r3mondisp to send a warning message to the console if less than 15 percent of the total allocated dialog work processes for all SAP clients in all the SAP instances monitored by the SPI for SAP are idle.

Excerpt from a r3mondisp Configuration File

Excerpt from a r3mondisp Configuration File on page 83 also shows how to use the keyword DisableMonitoringWithSeverity to configure r3mondisp to prevent SPI for SAP monitors from starting if the start up requires a dialog work process (for example, to logon to SAP) and the allocation of that work process would violate a threshold for idle dialog work processes defined in the configuration file and, as a result, generate a message with the severity "warning" or higher.

Note that you have to use the EnableDPQueueCheck keyword to configure each individual SPI for SAP monitor that logs on to SAP to check the dialog work-process queue before starting its run. For more information about the keyword EnableDPQueueCheck, see Enable DP Queue Check on page 35.

The J2EE (Web AS Java) Monitor

Monitoring the SAP J2EE Engine is essential if you want to manage your SAP environment effectively, since the combination of Java technology and the J2EE infrastructure is the base on which new SAP components such as the SAP Enterprise Portal or Exchange Infrastructure (XI) are built.

This section contains information about the following topics:

- J2EE Monitor: Enabling CCMS Alerts on page 84
- J2EE Monitor: Configuration Pre-requisites on page 85
- Configuring the SPI for SAP J2EE Monitor on page 86

J2EE Monitor: Enabling CCMS Alerts

To enable the SPI for SAP to monitor the J2EE engine, you configure r3monal, the CCMS alert monitor, to monitor alerts in SAP generated by the J2EE and XI monitors. Monitoring Alerts from CCMS Monitor Sets on page 84 shows how to use the CCMSMonitorSet keyword in the r3monal.cfg configuration file to define which CCMS alerts to monitor and use to send messages to HPOM for Windows.

Monitoring Alerts from CCMS Monitor Sets

```
# Monitor Set SAP SAP Monitor Set Monitor

# System Number

CCMSMonitorSet =ALL =ALL =HP OV SAP-SPI =J2EE Monitoring

CCMSMonitorSet =ALL =ALL =HP OV SAP-SPI =XI Monitoring
```

Note that both the CCMS monitors (J2EE Monitoring/XI Monitoring) and the CCMS monitor set (HP OV SAP-SPI) shown in Monitoring Alerts from CCMS Monitor Sets on page 84 are automatically created when you apply the SPI for SAP transports to SAP. For more information about the contents of the SPI for SAP transports, see the transport README file, which you can find in the following location on the HPOM for Windows management server after the installation of the SPI for SAP bits:

%OvShareDir%\Packages\SAPTransports\readme

By default, the SPI for SAP monitor for Web AS Java allows you to monitor alerts from the following areas:

J2EE Kernel

Information about the registered managers such as the Connections Manipulator, the Locking Manager, or the Application Threads Pool. These managers provide the core functionality of the SAP J2EE Engine; it is essential to know if one of these managers is not working correctly since any malfunction could prevent the J2EE Services from working properly.

• J2EE Services

Information about J2EE services such as the Connector Service, Transaction Service, or Web Service, which form the second level of the SAP System after the SAP Java Runtime Environment. The SPI for SAP's CCMS alert-monitor tree gives you an overview of the health of important services in the J2EE Engine.

SAPCCMSR Availability

Information about the availability of all registered and installed SAP CCMS agents within the SAP NetWeaver environments you are monitoring with the SPI for SAP.

GRMG Monitoring

Information about the availability of the different Web AS Java instances configured in an SAP NetWeaver environment. Using heartbeat monitoring, you can monitor the status and accessibility of the SAP J2EE Engines within your SAP NetWeaver environment including the Web components such as: the EJB container (for Enterprise JavaBeans), the Java Connector (JCo), P4 services for managing communication between remote Java objects, the Java Servlet engine, and HTTP services.

Note that SAP's internal GRMG monitor does not enable monitoring of the SAP J2EE Engine by default. If you want to use the GRMG monitor, you will need to enable the CCMS monitors (such as heartbeat polling or Web Dynpro) so that CCMS alerts are generated, which the SPI for SAP CCMS alert monitor can use to send messages to the console.

J2EE System

Information about the J2EE system is now included as a separate CCMS-monitor node which collects information for both the dispatcher and the server. The SPI for SAP's CCMS alert-monitor tree gives you an overview of the health of important services in the J2EE Engine.

J2EE Monitor: Configuration Pre-requisites

If you want to use the SPI for SAP's J2EE monitor to manage the SAP J2EE environment, make sure that your environment meets the following pre-requisites:

• J2EE

Install, register with the -j2ee option, and start the CCMS agent for J2EE on *each* J2EE 6.40 (or later) engine, which you want to monitor with the SPI for SAP. The SAP CCMS agent must report to an SAP Web AS ABAP version 6.40 (or higher).

For more information about installing and configuring the CCMS agent, refer to the SAP product documentation, for example: *CCMS Agents: Features, Installation, and Operation*.

SPI for SAP Transports

The new SPI for SAP transports include the J2EE and security CCMS monitors, which you must apply to each of the SAP 6.40 (or later) Systems, to which the SAP CCMS agent monitoring the J2EE Engine reports.

For more information about applying the SPI for SAP transports, refer to the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

CCMS Agents

The CCMS agents ensure that CCMS alerts are reported in ABAP, where the SPI for SAP can intercept them. Make sure that the CCMS agent for J2EE is running on *each* J2EE Engine which you want to monitor with the SPI for SAP. This is especially important if multiple instances of the J2EE Engine are running in a stack.

SPI for SAP Monitors

The SPI for SAP monitors and their configuration files must be available for deployment to the SAP Systems, whose J2EE Engines you want to monitor.

Configuring the SPI for SAP J2EE Monitor

This section explains how to configure the SPI for SAP to monitor the J2EE engine. To configure the SPI for SAP to monitor the SAP J2EE engine:

- 1 Make sure that the CCMS agent for J2EE is running on *each* J2EE Engine which you want to monitor with the SPI for SAP. This is especially important if multiple instances of the J2EE Engine are running in a stack.
- 2 Apply the new SPI for SAP transports to the SAP System hosting the J2EE Engines you want to monitor; the new SPI for SAP transports include the J2EE and security monitors.
- 3 Edit the monitor-set section of the r3monal.cfg configuration file and enable the monitoring of the J2EE monitor sets, by removing the leading hash (#) from the appropriate lines, as illustrated in Monitoring Alerts from CCMS Monitor Sets on page 84.
- Enable the CCMS alerts for J2EE, which you want to monitor with r3monal. You enable CCMS alerts by checking the CCMS monitors in the CCMS monitor sets for J2EE, as illustrated in Monitoring Alerts from the J2EE Engine on page 87. For more information about which CCMS alerts you need to enable for J2EE, see J2EE Monitor: Enabling CCMS Alerts on page 84.

Monitoring Edit Goto Views Extras System Help

HP OV SAP-SPI (J2EE Monitoring) - Maintenance functions ON

View: Current system status (15.05.2007, 09:32:32)

View: Current System Status (15.05.2007, 09:32:32)

J2EE Monitoring
SAP

Wiew: Current System Status (15.05.2007, 09:32:32)

J2EE Services
SAP

J2EE Monitoring
SAP

J2EE System SAP

J2EE System SAP

A

A

Figure 6 Monitoring Alerts from the J2EE Engine

The Enqueue-Server Monitor

The combination of a stand-alone enqueue server and replication server running on separate hosts forms the basis of a high-availability enqueue solution for SAP WebAS; separating essential services avoids the necessity of replicating the entire central instance in a high-availability environment and makes the SAP System faster and more efficient. In a high-availability environment, the failover of a stand-alone enqueue server does not lose any lock data or require you to reset locks when the enqueue server restarts.

If your System runs a stand-alone enqueue server, you can use the SPI for SAP's CCMS-alert monitor, r3monal, to monitor CCMS alerts relating to the status of the stand-alone enqueue server and configure r3monal to send messages to the HPOM for Windows console when problems occur that require urgent attention. This section contains information about the following topics:

- Enqueue Server: Enabling CCMS Alerts on page 87
- Enqueue Server: Configuration Pre-requisites on page 88
- Enqueue Server: Configuring the Enqueue-Server Monitor on page 88

Enqueue Server: Enabling CCMS Alerts

To enable the SPI for SAP to monitor a stand-alone enqueue server, you configure r3monal, the SPI for SAP's CCMS alert monitor, to monitor alerts in SAP generated by the CCMS monitor Standalone Enqueue Server Monitoring. Monitoring Enqueue Alerts in CCMS on page 87 shows how to use the CCMSMonitorSet keyword in the r3monal.cfg configuration file to define which CCMS alerts to monitor and use to send messages to HPOM for Windows.

Monitoring Enqueue Alerts in CCMS

By default, the SPI for SAP monitor for stand-alone enqueue servers allows you to monitor alerts from the following areas:

Enqueue-Server Status

Information about the status and availability of the current enqueue server, for example, whether the enqueue server is available or running, whether a connection to a replication server exists, and whether replication is active, on hold, or disabled, and so on.

• Enqueue Replication-Server (ERS) Status

Information about the status and availability of the current enqueue-replication server, for example: whether the server is enabled, has acquired the replication table, is connected to the enqueue server, and so on.

Enqueue Server: Configuration Pre-requisites

If you want to use the SPI for SAP to monitor a stand-alone enqueue server running in a high-availability cluster, make sure that your environment meets the following pre-requisites:

SPI for SAP Transports

The new SPI for SAP transports include the enqueue-server CCMS monitor, which you must apply to each of the SAP Systems, to which the SAP CCMS agents report.

For more information about applying the SPI for SAP transports, refer to the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

CCMS Agents

The CCMS agents ensure that CCMS alerts are reported in ABAP, where the SPI for SAP can intercept them. Make sure that the CCMS agents are available on *all* the physical hosts in the high-availability cluster, where the stand-alone enqueue server that you want to monitor runs, that is: on both primary and backup nodes.

SPI for SAP Monitors

The SPI for SAP monitors and their configuration files must be available for deployment to the SAP Systems, whose stand-alone enqueue server you want to monitor.


Enqueue Server: Configuring the Enqueue-Server Monitor

This section explains how to configure the SPI for SAP to monitor CCMS alerts generated by a stand-alone enqueue server, which is running in a WebAS high-availability environment. To configure the SPI for SAP to monitor the stand-alone enqueue server, perform the following steps:

1 Make sure that the CCMS agents are running on *each* physical host system in the high-availability environment on which the stand-alone enqueue server runs and which you want to monitor with the SPI for SAP.

- 2 Edit the monitor-set section of the r3monal.cfg configuration file and enable the monitoring of the stand-alone enqueue-server monitor sets, for example: Standalone Enqueue Server Monitoring as illustrated in Monitoring Enqueue Alerts in CCMS on page 87.
- Enable the CCMS alerts for the stand-alone enqueue server, which you want to monitor with r3monal. You enable CCMS alerts by checking the CCMS monitors in the CCMS monitor sets for the Enqueue service, as illustrated in Figure 7 on page 89.

Figure 7 Enabling CCMS alerts for the Enqueue Server Instance



The SAP Enterprise-Portal Monitor

The SAP Enterprise Portal provides a secure and stable web interface that gives users global access to the information, applications, and services that they need to work effectively in the SAP landscape. The SPI for SAP allows you to monitor critical aspects of the Enterprise Portal such as availability, response times, configuration, and performance.

If your SAP System provides users with an Enterprise Portal, you can configure the SPI for SAP's CCMS-alert monitor, r3monal, to monitor CCMS alerts relating to the portal's status and send messages to the HPOM for Windows console when problems occur that require urgent attention. You can also use the SPI for SAP to collect and correlate performance and availability data and display the correlated data in service reports for more convenient viewing. This section contains information about the following topics:

- Enterprise Portal: Enabling CCMS Alerts on page 90
- Enterprise Portal: Configuration Pre-requisites on page 90
- Enterprise Portal: Configuring the Portal Monitor on page 91

Enterprise Portal: Enabling CCMS Alerts

To enable the SPI for SAP to monitor an instance of the Enterprise Portal, you configure r3monal, the SPI for SAP's CCMS alert monitor, to monitor alerts in SAP generated by the CCMS monitors J2EE Monitoring. Monitoring Enterprise-Portal Alerts in CCMS on page 90 shows how to use the CCMSMonitorSet keyword in the r3monal.cfg configuration file to define which CCMS alerts to monitor and use to send messages to HPOM for Windows.

Monitoring Enterprise-Portal Alerts in CCMS

By default, the SPI for SAP monitor for the Enterprise Portal allows you to monitor alerts from the following areas:

Enterprise-Portal Status

You can monitor information concerning the status and availability of the Java- or HTTP-based components of the Enterprise Portal. Java-based components include: the EJB container (for Enterprise JavaBeans), the Java Connector (JCo), P4 services for managing communication between remote Java objects, the Java Servlet engine, and Java Web services; HTTP-based components include all HTTP services.

Enterprise-Portal Performance

You can monitor information concerning the performance of the Enterprise Portal, for example: request response times, request demand over time, the number of component calls per request, the average amount of outbound data per request, and so on.

• Enterprise-Portal Configuration

You can monitor the information that is available concerning configuration parameters for Enterprise Portal components such as the portal runtime (PRT) and the portal content directory (PCD), for example: thread and connection pool size, security settings, cache length and validity times.

Enterprise Portal: Configuration Pre-requisites

If you want to use the SPI for SAP to monitor an instance of the Enterprise Portal, make sure that your environment meets the following pre-requisites:

• SPI for SAP Transports

The new SPI for SAP transports include the Enterprise-Portal monitor; you must apply the new transports included in the transport file SAPSPI_CCMS_Monitors.car to each of the SAP Systems, to which the SAP CCMS agents report.

For more information about applying the SPI for SAP transports, refer to the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

CCMS Agents

The CCMS agents ensure that CCMS alerts are reported in ABAP, where the SPI for SAP can intercept them. Make sure that the CCMS agents are available on the machine hosting the instance of the J2EE engine on which the Enterprise Portal that you want to

monitor is running. Note that, if the TREX component (for search and classification functionality) is running on a different system, you will have to make sure the CCMS agents are running there, too.

Java-Application Response-Time Measurement

To collect performance-related data from J2EE applications and components, you must enable Java-application response-time measurement (JARM) functionality. Note that JARM is enabled by default and maps all collected data to CCMS automatically; the J2EE engine's Network Administrator (NWA) displays the JARM status.

• Generic Request and Message Generator (GRMG)

To monitor the availability of the Enterprise Portal in SAP, you need to customize the GRMG configuration files and upload the modified configuration files to the CCMS agent; the J2EE engine's Network Administrator (NWA) displays example XML files that are available for modification and upload to CCMS, as illustrated in Figure 19 on page 198. You can also use the transaction GRMG to display a list of active GRMG configuration scenarios that are available in the SAP central monitoring system.



If you want to monitor system availability with the GRMG, you must assign and configure one SAP system as the central monitoring system (CEN) in your SAP landscape. For more information about setting up a CEN in SAP, see the SAP documentation; for more information about using the SPI for SAP to monitor the CEN, see Monitoring CCMS Alerts in the CEN on page 194.

• Performance Agents

Either the HP Software Embedded Performance Component(CODA) or the HP Performance Agent and, in addition, the SPI for SAP R/3 Performance Agent must be running on the system hosting the Enterprise Portal you want to monitor. For more information about the SPI for SAP's performance monitor for the SAP Enterprise-Portal, see EP_PERF on page 225. Note that the SPI for SAP uses the performance data collected by EP_PERF to generate service reports.

SPI for SAP Monitors

The SPI for SAP monitors and their configuration files must be available for deployment to the SAP Systems, whose Enterprise Portal you want to monitor.

Enterprise Portal: Configuring the Portal Monitor

The information in this section explains how to configure the SPI for SAP to monitor CCMS alerts generated by the Enterprise Portal. To configure the SPI for SAP to monitor an instance of the Enterprise Portal:

1 Make sure that the CCMS agents are running on the system hosting the Enterprise Portal services that you want to monitor with the SPI for SAP.



If you configure the TREX server to run on a separate host, you will need to make sure that CCMS agents are also running on the system hosting the remote TREX server and that CCMS alerts relating to search-and-classification functionality appear in ABAP.

2 If you have not already done so as part of the installation of the SPI for SAP, import the transport from SAPSPI_CCMS_Monitors.car file on each of the SAP Systems hosting the J2EE engine underlying the Enterprise Portal you want to monitor with the SPI for SAP; the SAPSPI CCMS Monitors.car transport file contains the CCMS monitors and

- objects that the SPI for SAP requires for EP performance monitoring. For more information about importing SPI for SAP transports, see the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.
- 3 Enable the Java Application Response-Time Measurement (JARM) functionality for the Java stack on which the Enterprise Portal is running; JARM allows you to monitor the availability and performance of the Java components underlying the Enterprise Portal. Use the J2EE Engine Network Administrator to check the JARM status. JARM is enabled by default.
 - The jarm/switch property key enables or disables performance monitoring; the jarm/comp/level property key allows you to modify the java-component monitor level, for example: 0 (default), 1, 2, or 3.
- 4 To monitor the availability of the web components in the J2EE engine underlying the Enterprise Portal, you need to customize an instance of the GRMG configuration files and upload the modified XML files to the CCMS agent. In particular, you need to define the names of the hosts where the instances of the J2EE engines are running. For more information about using the SAP Network Administrator to modify GRMG-configuration files and upload them to SAP's central monitoring system (CEN), see the SAP documentation.

Use the transaction GRMG to display a list of active GRMG configuration scenarios that are already uploaded to (and active in) CCMS.



It can take up to an hour for the GRMG scenarios that you upload in the Network Administrator to be transferred to the central monitoring system and started.

- 5 Edit the monitor-set section of the r3monal.cfg configuration file and enable the monitoring of both the J2EE monitor set, for example: J2EE Monitoring, as illustrated in Monitoring Enterprise-Portal Alerts in CCMS on page 90.
- 6 Enable the CCMS alerts for the Enterprise Portal that you want to monitor with r3monal. You enable CCMS alerts by checking the CCMS monitors in the CCMS monitor sets for the Enterprise Portal, as illustrated in Figure 8 on page 93.
 - Note that the Java-related CCMS alerts are available in the J2EE Services and J2EE System monitors, which you can find in the J2EE Monitoring CCMS monitor set. For more information about the SPI for SAP's J2EE monitor, see The J2EE (Web AS Java) Monitor on page 84.

Monitoring Edit Goto Views Extras System Help HP OV SAP-SPI (J2EE Monitoring) - Maintenance functions ON Open alerts D Properties O A G O D D C A S View: Current system status (24.05.2007 , 14:17:05) ☐ J2EE Monitoring ◎ □ J2EE Services 🕲 SP1 : Segment SAP_CCMS_sapspiw5_SP1_25 (Status = SHUTDOWN)

SP1 : Segment SAP_CCMS_sapspiwb (Status = SHUTDOWN)

SP1\SP1 00 Disp 3842700 sapspiw3\...\Services\... SP1\SP1 00 Serv 3842750 sapspiw3\...\Services\ -⊞ Connector Service Log Configurator - 🖭 ⊕ WebDynpro Security UME Œ Http Provider -Œ 🗸 Portal Web Container 器 - Œ □ EJB - Œ JNDI Registry Œ Security 뫎 - (FI) Timeout ☐ JMX Adapter · 🖭 -Œ ₽4 Provider -⊞ Transaction
-⊞ Deploy ☐ Web Services RFC Engine Service 4 b

Figure 8 Enabling CCMS alerts for the Enterprise-Portal Instance

The SAP Security-Audit Monitor

Monitoring security audits is essential if you want to manage your SAP environment effectively; you can use the security-audit monitor to check what security-related changes occur in the SAP Systems you are monitoring with the SPI for SAP, who or what is responsible for the change, and where and when the change occurred. The security-audit monitor checks for alerts concerning the following events in the SAP System:

- Logons
- RFC Logons
- Transaction Starts
- Report Starts
- RFC Calls
- User Master Records
- System
- Miscellaneous

This section explains how to set up SAP's self-monitoring feature and configure the SPI for SAP to monitor the alerts the self-monitoring feature generates. The information in this section helps you understand the following topics:

- SAP Security-Alerts on page 94
- Configuring the Security-Audit Monitor on page 94

SAP Security-Alerts

The SAP security-audit log keeps a record of security-related activities in the SAP System and stores the information it collects in an audit file on each application server. The audit log uses filters to determine what information is important enough to record and updates the log at regular intervals. When an event occurs that matches a configured filter (for example, for an RFC logon or a transaction start), the audit log generates a message and writes it to the audit file. At the same time, a corresponding alert appears in the CCMS alert monitor.

You can configure the SPI for SAP to monitor the CCMS alerts logged by the security audit in any areas of particular interest to you and use the alerts to generate messages, which you can send to the HPOM for Windows console. Table 17 on page 94 shows the security areas audited by the SAP self-monitoring feature; you can monitor all or any of these areas with the SPI for SAP.

Table 17 SAP Security-Audit Classes


Audit Class	Description
Logons	An SAP logon or password check failed; an operator illegally locked or unlocked an SAP user.
RFC Logons	An RFC or CPIC logon failed due to user error or an unauthorized attempt to log on with an illegal user/password combination.
Transaction Starts	Possible unauthorized execution of code in the SAP System
Report Starts	
RFC Calls	
User Master Records	A security or licensing issue occurred concerning user records or the inappropriate activation of an authorization or profile.
System	An application server stopped or started; the security-audit configuration changed.
Miscellaneous	A transport request contains source objects, which are critical for security.

Configuring the Security-Audit Monitor

Enabling the monitoring of security events audited by SAP's security-audit feature involves a number of steps both in SAP and in HPOM for Windows; the number and complexity of the steps you have to perform depends on the version of SAP installed on the SAP System, whose

security events you want to monitor with the SPI for SAP. Figure 9 on page 95 shows what the CCMS monitor tree looks like when you complete the configuration on the SAP side successfully.

Figure 9 CCMS Monitor Set: Monitoring Security Events



To configure the SPI for SAP to monitor the security events logged in the SAP security audit, perform the tasks described in more detail in the following topics:

- 1 Installing the SPI for SAP's Security-Monitoring Feature on page 95
- 2 Configuring the SAP Security Audit on page 96
- 3 Enabling CCMS Security Monitoring on page 96

Installing the SPI for SAP's Security-Monitoring Feature

The number and complexity of the steps you have to perform to enable the security-monitoring feature in SAP depends on the version of SAP installed on the SAP System you want to monitor with the SPI for SAP.


- For SAP Web AS ABAP version 6.40 and higher, apply the SPI for SAP transport, SAPSPI_CCMS_Monitors.car, which imports the new, CCMS monitor set automatically into SAP.
- For all supported SAP ABAP versions before 6.40:
 - Use transaction RZ20 to activate the SAP maintenance function.
 - Create a new CCMS monitor set called 'HP OV SAP-SPI'.
 - Create a new CCMS monitor called 'Security Monitoring' and add it to the monitor set HP OV SAP-SPI.

 Enable the alert classes you want to monitor with the new CCMS monitor 'Security-Monitoring'. You can enable the complete tree or individual classes, for example: Logon, or Transaction Start.

For more information about the individual security-audit alert classes you can choose to monitor, see SAP Security-Alerts on page 94.

Configuring the SAP Security Audit

The information in this section explains how to specify which events the new security-audit profile monitors, in which SAP client, and relating to which SAP user.



- 1 Use transaction **SM19** to create, customize, and activate a new profile for a security-audit.
 - To reduce administrative overhead, you can set up a system-wide profile which will monitor only the most important and critical security events, for example: critical SAP-logon events or important RFC-function calls.
 - Remember to check the Filter active option when configuring filter options.
- 2 Test the new profile for a security-audit.
 - You can test the activated profile by logging on to SAP with a false user/password combination. If you want to review the audit log, too, use transaction **SM20**.
- 3 Set up the SAP job REORG to maintain the security-audit logs:

The security audit writes logs to the file system which very quickly fills up if you do not implement a REORG job using the SAP report RSAUPURG. Transaction **SM38** allows you to create a variant of the RSAUPURG report, which meets the needs of your environment. For example, you can arrange to delete logs which are more than ten days old.

Enabling CCMS Security Monitoring

The information in this section explains how to enable r3monal to monitor the generation of CCMS alerts in SAP and in particular the alerts, which concern security-related events. After configuring r3monal to monitor security-related CCMS alerts, you also have to enable the SAP Security Monitoring monitor in CCMS and, in addition, the corresponding MTE's (monitor tree elements) of interest, for example: Logon, ReportStart, and so on.

The SPI for SAP creates the CCMS monitor "Security Monitoring" when you apply the SPI for SAP transport SAPSPI_CCMS_Monitors.car to SAP 6.40 Systems and higher, whose security events you want to monitor with the SPI for SAP. For older SAP versions, you have to create the CCMS monitors and monitor sets manually.

Monitoring Audit Alerts from CCMS Monitor Sets on page 96 shows an excerpt from the r3monal monitor's configuration file. The CCMSMonitorSets keyword allows you to define the CCMS alert monitor set and CCMS alert monitors created by the SPI for SAP. In the example shown, you configure r3monal to monitor security-audit alerts for all SAP Systems known to the SPI for SAP using the CCMS alert monitor set "HP OV SAP-SPI" and the CCMS alert monitor "Security Monitoring".

Monitoring Audit Alerts from CCMS Monitor Sets

For more information about enabling CCMS alerts, see r3monal: CCMS Monitor Sets on page 52.

4 The SPI for SAP Alert-Collector Monitors

The SPI for SAP uses the one, single alert collector r3moncol to collect alerts from a number of additional SAP NetWeaver alert monitors. Each of the alert monitors listed in this section takes its name from the nature of alerts it monitors. For example, the r3mondmp alert-collector monitors ABAP dumps. The SPI for SAP groups the tasks that each monitor performs according to *alert types*. For example, the alert type IDOC_CURRENT_STATUS helps the r3monale monitor determines the current status of iDOCs in an SAP System.

You specify monitoring parameters at the alert-type (rather than alert-monitor) level. For example, you could use the parameter =CHECK_INBOUND to limit the range of the alert type IDOC_CURRENT_STATUS so that it checks the status of inbound iDOCs only.

This section contains information about the following topics:

- Configuring the SPI for SAP Alert-Collector Monitors on page 101
- The Alert-Collector Monitor Configuration Files on page 108

The following list shows which alert-collectors are available to r3moncol and gives a short description of each monitor's scope. For more detailed information about the alert types associated with each alert monitor as well as the parameters you can use to configure them, see the appropriate sections and tables later in this chapter:

• r3monaco - Monitoring the TemSe file on page 179

To save runtime costs, a report now replaces the Temporary Sequential File (TEMSE) monitor. See Monitoring the TemSe file on page 179 for more details.

• r3monale: The iDOC-Status Monitor on page 115

The iDOC Status monitor checks the status of the iDOCs present in the SAP NetWeaver Systems configured in your SAP Landscape. r3monale generates an alert when a defined threshold for the number of iDOCs with a given status is exceeded.

r3monchg: The System-Change-Option Monitor on page 123

The SYSTEM CHANGE OPTION monitor checks for the occurrence of SAP System change options.

r3moncts: The Correction and Transport System Monitor on page 128

The CORRECTION and TRANSPORT SYSTEM monitor checks the correction and transport system for important transport requests, tasks and objects. It generates an alert according to the specifications you define.

• r3mondmp: The ABAP-Dump Monitor on page 137

The ABAP Dump monitor detects ABAP dumps which occur in the SAP System. The cause of the dump can be identified from the details which the message gives and used to determine any corrective action, which you need to take.

r3monjob: The Job-Report Monitor on page 139

The JOBREPORT monitor checks for jobs that:

exceed a specified run time

- do not run as long as they are expected to run
- do not start within a specified time frame
- are aborted
- r3monlck: The Lock-Check Monitor on page 147

The LOCK_CHECK monitor references the SAP NetWeaver Enqueue process which manages logical locks for SAP NetWeaver transactions and reports on obsolete locks. An obsolete lock is a lock which is older than the time period you specify.

• r3monoms: The Operation-Mode Monitor on page 149

The OPERATION MODE monitor detects when:

- a scheduled operation mode switch has occurred later than the time specified
- a scheduled operation mode switch has not occurred at all
- Changes in SAP mean there are no operation-mode-switch errors to monitor in WebAS 7.0/ Netweaver04s (kernel 7) environments.
 - r3monrfc: The RFC-Destination Monitor on page 152

The SAP-RFC monitor checks RFC destinations in an SAP environment:

- the status of connections
- the availability of connections
- r3monspl: The Spooler Monitor on page 155

The SPOOLER monitor checks:

- the number of spool entries
- the number of erroneous spool requests in a specified range
- spool entries with state ERROR for specified printers
- r3montra: The Transport Monitor on page 158

The TRANSPORT monitor checks the following parts of the transport system:

- the status of exports and imports
- confirmed and unconfirmed repairs
- performs a ping of the specified system
- checks the TP interface
- r3monupd: The Update Monitor on page 165

The UPDATE-alert monitor checks:

- if an SAP user or the SAP System stops an update
- if update errors have occurred
- r3monusr: The SAP-User Monitor on page 167

The USER monitor specifies the number of users which would trigger an alert, using SAP transaction SM04 as reference

• r3monwpa: The Work-Process Monitor on page 169

The WORKPROCESS monitor performs the following checks on work processes:

- monitors their status and reports any processes that are running in *debug*, *private* or *no-restart* modes
- compares the number of configured work processes with the number of work process actually running
- checks the number of expected work processes waiting and the number of expected work processes running for each work process type

Configuring the SPI for SAP Alert-Collector Monitors

You can use the alert-collector monitors to define a series of monitoring tasks within SAP NetWeaver, for example, checks on SAP NetWeaver processing modes, SAP NetWeaver dumps, or the availability of SAP NetWeaver work processes. The alert-collector monitors ensure that each defined alert-collector configuration is executed on a regular basis and reports any messages that come back from the called function. For more information about the contents of the individual alert-collector monitor configuration files, see The Alert-Collector Monitor Configuration Files on page 108.

Report Types for the Alert-Collector Monitors

Each of the alert monitors use one of two reporting types.

Time Frame

Time-frame monitors use a defined time range as their measurement base. For example, the r3monjob alert monitor uses a time frame which compares the time from the last monitor run with the configured start date and time of a batch job.

Snapshot

Snapshot monitors use one moment of time as their measurement base. For example, the r3monlck (LOCK_CHECK) monitor uses the moment the monitor runs to generate an alert indicating that a lock is "old", whenever the age of the lock exceeds a defined time span. The snapshot type is dynamic and can run continuously because the alerts can be generated without being confined to a specific time frame.

Polling Rates for the Alert-Collector Monitors

The alert-collector monitors have different default polling rates, that is: the frequency at which the monitor runs. You can change the polling rate at the scheduled-task policy for the monitor. For more information about the default polling rates for alert-collector monitors, see Table 18, which shows the rates in days, hours, and minutes.

Table 18 Default Polling Rates for Alert-Collector Monitors

	Polling Rate		
Alert-Monitor Name	Days	Hours	Mins
r3monale			10
r3monchg		4	
r3moncts		1	

Table 18 Default Polling Rates for Alert-Collector Monitors (cont'd)

	Polling Rate		
Alert-Monitor Name	Days	Hours	Mins
r3mondmp			5
r3monjob			5
r3monlck		1	
r3monoms			10
r3monrfc			5
r3monspl			30
r3montra	1		
r3monupd		1	
r3monusr			5
r3monwpa			5
r3monaco ^a			15

a. Strictly speaking,r3monaco is not an alert-collector monitor. See Monitoring the TemSe file on page 179.

Alert-Collector Monitor History

Unlike the SPI for SAP monitors r3monal or r3mondev, the alert-collector monitors controlled by r3moncol (such as r3monale or r3mondmp) do not write history information to a monitor-specific history file. Instead, any information relating to SAP alerts which come to the notice of the SPI for SAP alert-collector monitors is written directly to the SAP database, where it can be found by the alert collector r3moncol. At the start of each monitor run, r3moncol reads the relevant tables and uses the information to determine which if any events the HPOM for Windows management server has already been notified about and whether to generate further messages or not.

Alert-Collector Monitor Query Conditions

The data for each alert monitor is split into a number of alert types. For example, the JOBREPORT Monitor has four alert types: JOB_MAX_RUN-TIME, JOB_MIN_RUN_TIME, START_PASSED and JOB_ABORTED. For each of a given alert monitor's defined alert types you have to:

- specify which SAP NetWeaver Systems should be checked
- enter selection criteria which defines under what circumstances an alert will be raised. This is described in more detail below.

Parameter Data Types

Parameters in the monitoring-conditions section of the configuration files associated with each alert type define the conditions, which generate an alert. There are two general types of parameter data:

name

The parameter *name* describes the attributes of the SAP NetWeaver System for which you define the monitoring conditions. For example: MAX_RUNTIME and JOBNAME are the names of parameters for the alert type JOB_MAX_RUN_TIME, which is associated with the JOBREPORT Monitor, r3monjob.

delimiters

Parameter *delimiters* are used to specify the "select" options for each parameter. The parameter delimiters define the circumstances under which an alert should be generated. An HPOM for Windows message will be sent for each event that matches your specified conditions. There are four types of Parameter Delimiters, which must appear in the following order: SIGN, OPT(ION), LOW, and HIGH. (See Table 19 on page 104)

Specifying Query Conditions

The following points apply generally when using parameter delimiters to specify query conditions:

- All possible and reasonable conditions can be used to configure the query condition, within the limitations given below.
- Messages which are excluded by your defined conditions will not appear in the HPOM for Windows console.
- Detailed descriptions of the alert-type configurations for each monitor follow this introductory section.

The SPI for SAP installs the alert monitors by default with an example configuration of the allowed parameters for each alert type. However, this example configuration should not be treated as necessarily ready to use for your particular environment. As a general rule, you first need to customize the alert type by editing the parameters. You can find information about when it is possible to use these unedited default values (and when editing is mandatory) in the detailed descriptions of each alert monitor's alert types, which follows this introduction. Note that the order of the parameter delimiters for the query conditions must

match the order shown in Table 19, namely; SIGN, OPTION, LOW, HIGH. For examples of the use of query conditions, see the sections for the appropriate alert collectors, for example: r3moncts.

Table 19 Description of Parameter Delimiters

Parameter Delimiters	Description	
SIGN	I: Include	
	E: Exclude	
OPT	The standard SAP operators NE (Not Equal to), NB (Not Between and), and NP (does Not contain Pattern) cannot be used to configure the alert types described in this section. You should only use the following operators: • EQ: equal to • BT: between and • CP: contains pattern • LE: less than or equal to • GE: greater than or equal to • GT: greater than	
LOW	 A comparison value such as a string when used with the operator CP The lower value of a range when used in conjunction with the operator BT. For some ALERT_TYPES, the value X is also used simply as a flag or switch which enables monitoring, for example: r3montra's TRANS and REPAIR. 	
HIGH	A numeric comparison value to specify the higher value of a range. This parameter delimiter should only be used in conjunction with the operator BT	

Parameter Values

This section describes how the SPI for SAP interprets *include* and *exclude* parameter values for an alert type entry. The SPI for SAP compares values in *different* parameters using 'and'; the SPI for SAP compares values in the *same* parameter as follows.

• **Include**: use 'or' to compare the parameters

Exclude: use 'and' to compare the parameters

Note that the SPI for SAP evaluates *include* values before *exclude* values, as shown in the Table 20.

Table 20 Comparing Include and Exclude Conditions for the Same Parameter

Select Options	Example Configuration of Select Options for JOB_MAX_RUN_TIME	Comparison
1	=JOBNAME =I =CP =ZREP* = =MAX_RUNTIME =I =GT =10 =	OR
2	=JOBNAME =I =CP =SAP* = =MAX_RUNTIME =I =GT =20 =	OR
3	=JOBNAME =E =CP =SAP_ZREP* =	AND

Query Conditions

The following rules apply to the use of blocks and line breaks when configuring the alert types for the alert collector monitors:

- Configure each parameter as a separate block. For example for JOB_MAX_RUN_TIME:
 =JOBNAME =I =CP =SAP* = is the block for the parameter JOBNAME
 =MAX_RUNTIME =I =GT =20 = is the block for the parameter MAX_RUNTIME.
- The symbol '\' indicates a line continuation.
- Use line breaks in the following locations:
 - Within each specified configuration between:
 - the general alert class configuration (SAP hostname, system, number and client)
 - the HPOM for Windows configurations (severity level, object)
 - the monitoring query conditions (parameter name and the SIGN, OPT, LOW and HIGH parameter delimiters).
 - Between each separate specified condition for AND comparisons.

Alert-Collector Monitor Environment Variables

This section describes the environment variables for all the alert-collector monitors managed by r3moncol. The configuration is identical for all alert collectors except that the name of the alert-collector configuration file is monitor specific, for example: r3monjob, r3mondmp, r3monlok, r3monoms.

Table 21 Environment Variables for r3moncol.exe

Environment Variable	Description
SAPOPC_ <r3monname>_CONFIGFILE</r3monname>	Configuration-file name ^a
SAPOPC_R3ITOSAP_CONFIGFILE	General SAP NetWeaver login configuration file
SAPOPC_TRACEPATH	Trace path config. file

a. Where <R3MONNAME> is the name of the monitor whose configuration file location you want to change. For example, SAPOPC_R3MONDMP_CONFIGFILE

Alert-Collector Monitor Command-Line Parameters

The command line parameters for all the alert-collector monitors controlled by the r3moncol are described in this section. In the same way as for the environment variables, the configuration is identical for all alert-collector monitors except that the name of the alert-collector configuration file is monitor specific, for example: r3monjob.cfg, r3monlck.cfg, and r3monoms.cfg.

Table 22 r3moncol Command-Line Parameters

Parameter	Description ^a
-cfgfile	Name of the monitor's configuration file. For example, -cfgfile < <i>R3MONNAME</i> >.cfg
-trace	The monitor writes an initial trace file writetrace.log, which contains information about the configuration file r3itosap and the monitor-specific config file <r3monname>.cfg.</r3monname>

a. Where <*R3MONNAME*> is the name of the monitor whose configuration-file location you want to read. For example, r3mondmp

In the following example, the alert-collector monitor writes an initial trace file writetrace.log, which contains information about the general configuration file r3itosap and the monitor-specific configuration file r3monjob.cfg.

r3moncol -cfgfile r3monjob.cfg -trace

Remote Monitoring with the Alert-Collector Monitors

The current version of the SPI for SAP includes a feature which allows you to extend the scope of the alert-collector monitor to remotely monitor the health of SAP processes on additional SAP servers (which are *not* HPOM for Windows managed nodes) from an SAP server, which *is* already configured as an HPOM for Windows managed node.



Although the SAP Server defined in the RemoteHost parameter is not an HPOM for Windows managed node, it must still be present in the HPOM for Windows node list. If you do not add the SAP Server defined in RemoteHost to the HPOM for Windows Node list, HPOM for Windows cannot resolve the host name associated with the remote host and, as a consequence, cannot display any messages from the remote host in the HPOM for Windows console.

In addition, the SAP Server defined in RemoteHost must appear in the r3itosap.cfg file to ensure that the SPI for SAP can login to the SAP instances it is monitoring on the RemoteHost. For more information about the r3itosap.cfg file, refer to the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows.

To make use of the remote-monitoring feature provided by the SPI for SAP, for example, to monitor an SAP System running an operating system that is not supported by the SPI for SAP, you need to enable the new **RemoteMonitoring** keyword (by removing the leading hash symbol "#") in the r3mon<alert monitor name>.cfg file (for example,

r3mondmp.cfg) and then, on the same line, tell the SPI for SAP alert-collector monitor the name of the local server which you want to perform the monitoring and, finally, the name of the remote server, which you want to monitor. Default Configuration for the CTS Monitor (r3moncts) on page 111 shows how a new line is required for each additional SAP server, which you want to monitor remotely. You use the following keyword parameters to define local and remote server names:

LocalHost

the name of the HPOM for Windows managed node where the SPI for SAP is running and whose alert-collector monitor you want the SPI for SAP to use to do the monitoring on the remote host defined in "RemoteHost".

RemoteHost

the name of the *remote* system to monitor with the system defined in "LocalHost". The RemoteHost does not have the SPI for SAP installed and is not usually (but could theoretically be) an HPOM for Windows managed node.

For more information about the contents of the alert-collector monitor configuration file, see The Alert-Collector Monitor Configuration Files on page 108.

Specifying Monitoring Rules for Individual Remote Servers shows a hypothetical example of how to configure the SPI for SAP on two different HPOM for Windows managed nodes (sap1 and sap2) to remotely manage three different SAP servers (ovsdsap1, ovsdsap2, and ovsdsap3) and, in addition, specify different monitoring rules to suit the different roles of the individual SAP servers, for example, production, development, or even test/unused:

Production System

The remote server <code>ovsdsap1</code> in Specifying Monitoring Rules for Individual Remote Servers is the *production* system, it has the monitor enabled (=1) and associates the HPOM for Windows message severity CRITICAL with alerts generated by the <code>=REQUEST_CREATED</code> alert type.

Development System

The remote server ovsdsap2 in Specifying Monitoring Rules for Individual Remote Servers is the *development* system, it has the monitor enabled (=1) and associates the HPOM for Windows message severity MAJOR with alerts generated by the =REQUEST_CREATED alert type.

Test System

The remote server ovsdsap3 in Specifying Monitoring Rules for Individual Remote Servers is the test system whose configuration is unchanged from the default which has the monitor disabled (=0) and associates the HPOM for Windows message severity WARNING with alerts generated by the =REQUEST_CREATED alert type.

Specifying Monitoring Rules for Individual Remote Servers

```
# Remote
             LocalHost
                      RemoteHost
# Monitoring
RemoteMonitoring =sap1
                      =ovsdsap1
RemoteMonitoring =sap1
                      =ovsdsap2
RemoteMonitoring =sap2
                      =ovsdsap3
#-----
                         SAP
                                SAP
                                                 Enable =1/
# AlertMonFun SAP
                  SAP
                                      Alertmonitor
           Hostname System Number Client
                                                 Disable=0
```

```
# OpC
             OpC
                     OpC \
# Severity
             Object MsgGroup \
AlertMonFun =ovsdsap1 =ALL =ALL
                                    =ALL
                                         =CTS = 1
=CRITICAL =Request
                       =R3 CTS\
=REQUEST CREATED
                   =USERNAME
                               =I
                                     =CP
AlertMonFun =ovsdsap2 =ALL
                              =ALL
                                    =ALL
                    =R3 CTS\
=MAJOR =Request
                   =USERNAME
=REQUEST CREATED
                                     =CP
                               =I
AlertMonFun =ovsdsap3 =ALL =ALL
                                    =ALL
                                          =CTS
=WARNING =Request
                      =R3 CTS\
=REQUEST CREATED
                   =USERNAME
                               =I
                                     =CP
```

The Alert-Collector Monitor Configuration Files

The keywords listed in this section appear in the alert-collector monitors configuration files and can be used to set up the individual monitor to meet the requirements of your environment. Where appropriate, possible values for a given keyword are also specified. Default Configuration for the CTS Monitor (r3moncts) on page 111 shows what a complete configuration file looks like for the r3moncts monitor, which monitors the correction and transport system for important transport requests, tasks and objects. This section contains information about the following topics:

- Alert-Collector Keywords and Parameters on page 108
- Validating the Alert-Collector Configuration Files on page 112
- Understanding Configuration-File Error Messages on page 112

Alert-Collector Keywords and Parameters

The following list describes the keywords you can use in the configuration files for the SPI for SAP alert-collectors controlled by r3moncol; for more information about errors caused by incorrect configuration, see Validating the Alert-Collector Configuration Files on page 112:

TraceLevel

For more information, see The SPI for SAP Monitor-Configuration File on page 25.

TraceFile

For more information, see The SPI for SAP Monitor-Configuration File on page 25.

HistoryPath[Unix | AIX | Windows]

For more information, see The SPI for SAP Monitor-Configuration File on page 25.

AgentHostname

Make sure that the AgentHostname keyword set to ALL.

RemoteMonitoring

Enables the SPI for SAP to monitor an SAP instance installed on remote SAP server. For more information, see Remote Monitoring with the Alert-Collector Monitors on page 106.

AlertMonFun

The AlertMonFun keyword defines a function for the alert-collector monitor and *requires* a value for the following parameters:

AlertMonFun =<SAP Hostname> =<SAP System> =<SAP Number> =<SAP Client> =<AlertMonitor> =<Enable/Disable> =<OpC Severity> =<OpC Object> =<OpC MsqGroup> =<Alerttype> =<RFC Parameter>

— Alerttype:

=<Alerttype>

The alert type is monitor specific. For example, r3monale uses the IDOC_CURRENT_STATUS alert type to monitor alerts relating to the status of iDOCs; r3mondmp uses the alert type ABAP4_ERROR_EXIST to monitor alerts relating to each ABAP dump that occurs in a monitored SAP System. For more information about which alert types belong to which alert-collector monitor, see the "Alert-Types" section for a given monitor, for example, r3monale: The iDOC-Status Monitor on page 115 refers to the alert type IDOC_CURRENT_STATUS.

— AlertMonitor:

=<Monitor Name>

The short form of the alert monitor you are configuring, for example, ALE for r3monale, CTS for the r3moncts, and so on.

— Enable/Disable:

=0 Disable the monitor.

=1 Enable the monitor. This is the default setting.

— OPC Severity:

=<HPOM_Msg_Severity>

The severity level of the HPOM for Windows message you want to map the CCMS alert to, for example: Normal, Warning, Major, Critical.

— OPC Object:

=<OpC Object>

The HPOM for Windows object associated with the generated message. These tend to reflect the names of the alert types associated with the alert-collector monitor, for example, Request, task or object for r3moncts. Note that if you change the names of the HPOM for Windows objects in the monitor-configuration files (or add new ones), you must ensure that these changes are reflected in the message conditions to avoid the generation of unmatched messages.

— OPC MsgGroup:

=<OpC_Msg_Group>

The name of the HPOM for Windows message group to which the generated message belongs, for example: R3_CTS, or R3_ABAP-4. The default names all start with "R3_" and reflect the names of the alert monitors to which they correspond, for example, r3moncts or r3mondmp. Note that if you change the names of the HPOM for Windows message groups in the monitor-configuration files, remember to ensure that the changes are reflected in the message conditions to avoid the generation of unmatched messages.

— RFC Parameter:

=<RFC_Param> =I =CP =* =

=<RFC Param>

The name of a parameter for a given alert type, for example: USERNAME, followed by any required parameter-specific query conditions, each with the prefix "=", for example: = I (for include), =CP (for "Contains Pattern").

For more information about query conditions, see Alert-Collector Monitor Query Conditions on page 102. For more information about monitor- specific alert-type parameters, see the monitor descriptions. For example, for the r3moncts alert type REQUEST_CREATED, see: REQUEST_CREATED Configuration Parameters on page 131.

— SAP Client:

=ALL Monitor all SAP clients with the SPI for SAP. This is the

default setting.

=<ClientID> The ID of a specific SAP client ID whose performance you want to monitor, for example, 099. Use a new configuration

line for each entry.

— SAP Hostname:

=ALL Monitor all SAP hosts with the SPI for SAP. This is the

default setting.

=<SAP_host> The host name of a specific SAP server which you want to

monitor. Use a new configuration line for each individual

entry.

— SAP Number:

=ALL Monitor all SAP instances with the SPI for SAP. This is the

default setting.

=<Instance> The number of a specific SAP *instance* which you want to

monitor, for example, 00, 99. Use a new configuration line for

each entry.

— SAP System:

=ALL Monitor all SAP Systems with the SPI for SAP. This is the

default setting.

=<SAP SID> The ID of a SAP System ID which you want to monitor, for

example, DEV. Use a new configuration line for each

individual entry.

Severity Levels

The alert-collector monitors map the severity of alerts in the SAP subsystem to messages in HPOM. For example, SAP alerts with the severity level *SeverityCritical* are mapped by default to the HPOM for Windows message severity *Critical*. The HPOM for Windows message- status hierarchy is, in ascending order; Normal, Warning, Minor, Major, Critical.

You can customize these severity levels to suit the severity conditions you want to define. For example, for the alert type OLD_LOCKS for the alert monitor LOCK_CHECK you could specify that if the lock is older than 12 hours, you receive a WARNING message, and if it is older than 24 hours, you receive a CRITICAL message.

Default Configuration for the CTS Monitor (r3moncts)

```
#-----
# TraceLevel hostname Disable=0 only error messages=1 info messages=2 \
             debug messages=3
               =0
TraceLevel
        =\Delta T.T.
#-----
# TraceFile hostname filename
                    TraceMode
                                   TracePeriod
                  (a=append/w=create(default)) (in mins)
#
TraceFile =ALL =r3moncts.log =w
#-----
# History
      hostname
             path
# Path
HistoryPathUnix =ALL
                 =default
HistoryPathAIX
          =ALL
                 =default
HistoryPathWinNT =ALL
#-----
                 RemoteHost
# Remote
         LocalHost
# Monitoring
RemoteMonitoring =rum
                =ovsdsap1
RemoteMonitoring =whisky =ovsdsap2
#-----
# AlertMonFun SAP SAP SAP SAP Alertmonitor Enable =1/
 \
```

```
Client
                                                                       Disable=0
                Hostname
                          System
                                    Number
#
#
                               OpC
    OpC
                  OpC
    Severity
                  Object
                               MsgGroup
#
                 RFC Parameter
  Alerttype
                 =Parameter
                                 =Sign
                                          =Opt
                                                           =High
                                                  =Low
                [=Parameter
                                 =Sign
                                                           =High] ...
                                          =Opt
                                                  =Low
  Example:
AlertMonFun
             =ALL =ALL
                          =ALL
                                 =ALL
=WARNING
            =Request
                          =R3 CTS
=REQUEST CREATED
                    =USERNAME
                                 =I
                                       =CP
```

Validating the Alert-Collector Configuration Files

The configuration files used by r3moncol's alert-collector monitors have a known structure and content; commands and parameters appear in a particular order and location as illustrated in Default Configuration for the CTS Monitor (r3moncts) on page 111. To ensure an alert-collector monitor remains available and runs correctly, it is essential that the monitor can read and understand the contents of its configuration file each time the monitor starts. If the file is not available or contains errors, the monitor cannot perform its monitor function and in some cases will not start. To help prevent the situation where an alert-collector monitor cannot start or perform correctly due to a configuration error, the SPI for SAP automatically validates the contents of r3moncol configuration files when the SPI for SAP user tries to save it and when a SPI for SAP monitor reads it on startup.



The SPI for SAP checks the contents of an alert-collector's configuration file only if you use the HPOM for Windows configuration-file policy editor to edit and save it; the SPI for SAP does *not* check the contents of the configuration file for errors if you use a text editor to modify and save it.

If the SPI for SAP's validation tool finds an error when saving a configuration file, it displays a message describing the error, opens the file containing the error in the configuration-file policy editor, and places the cursor at the point in the configuration file where the error is located. To fix the problem, you will need to have a good understanding of the contents and structure of the configuration files, in particular, which parameters are associated with which commands and what values are allowed for the required parameters. For more information about the contents and the structure of the configuration files for the alert-collector-monitors, see Configuring the SPI for SAP Alert-Collector Monitors on page 101.

Understanding Configuration-File Error Messages

If you use the HPOM for Windows configuration-file policy editor to edit an alert-collector configuration file, you cannot save the file if it contains an error. If the SPI for SAP discovers an error when validating the contents of an alert-collector configuration file, it displays a message describing the error. For more information about the contents of the r3moncol configuration file, including what values are allowed and where, see The SPI for SAP Monitor-Configuration File on page 25.

The following list shows the messages that are displayed when an error is found in an alert-collector configuration file and explains what you need to do to fix the problem, which caused the error:

 Arguments/Parameters are expected but missing in command AlertMonFun; check for arguments after the equals sign '='

The number of arguments present in the configuration file does not match the number of arguments required for the AlertMonFun keyword; check that you have not added or removed all or part of a parameter by accident when editing the file.

• Value for the parameter Enable/Disable in command AlertMonFun must be '0' or '1'

The value assigned to the enable/disable parameter in the command AlertMonFun is an invalid number. It must be either 0 (disabled) or 1 (enabled).

The second argument in command TraceLevel must be a positive number between
 '0' and '3'

The TraceLevel setting is either missing or not allowed; the value must be one of the following: =0 (disabled), =1 (error messages), =2 (all messages), or =3 (debug).

• Argument for <command_name> must be a valid number

The indicated argument for the command command name> must be a valid number.

 Severity status <Status> defined in command DisableMonitoringWithSeverity is not allowed

The severity status of the messages you want to use to trigger the disable a monitor is unknown or not allowed. The following severity levels are allowed: Unknown, Normal, Warning, Minor, Major, Critical.

Invalid number of arguments in command DisableMonitoringWithSeverity

There are either too many or too few arguments defined in the command DisableMonitoringWithSeverity, which means the command is assuming the wrong values for the expected parameters. Check the number of parameters present in the command and their values.

• Value for Disable/Enable in command DPQueueCheck is not a valid number

The value for the enable/disable parameter in the command DPQueueCheck is incorrect; it must be either =0 (disabled) or =1 (enabled).

<SeverityLevel> is an invalid Severity

The defined severity level is not allowed; check that you have spelled the severity level correctly and that the specified severity level is allowed in this context. The following severity levels are allowed: Unknown, Normal, Warning, Minor, Major, Critical.

<WorkProcess> is an invalid work process

The name of the work process defined in <WorkProcess> is either not known or not allowed; the names you can use in this context are the three-letter acronyms used in SAP, for example: DIA (dialog), UPD (update), BTC (batch).

Value of Workprocess must be either Idle or Queue in command DPQueueCheck.

The value defined for the status of the work-processes monitored by the DPQueueCheck command is either missing or invalid; the value must be set to either "Idle" or "Queue".

• Threshold value in command DPOueueCheck is not a valid number.

The value defined (in percentage terms) for the status of the work-processes queue monitored by the DPQueueCheck command is either missing or invalid; the value must be between 0 (zero) and 100 (one hundred) per cent.

Threshold value is out of range in command DPQueueCheck

The value defined (in percentage terms) for the status of the work-processes queue monitored by the DPQueueCheck command must be between 0 (zero) and 100 (one hundred) per cent. This value defines how full (or empty) the monitored queue must be as a percentage of the maximum before the dispatch monitor r3mondisp generates an alert.

• Too many or too few arguments in command DPQueueCheck

The number of arguments present in the configuration file does not match the number of arguments required for the DPQueueCheck keyword. Check that you have not added or removed a parameter (or part thereof) by accident when editing the file.

<Keyword> is an unknown keyword.

The keyword specified is invalid; check that you have spelled the keyword correctly and that the specified keyword is allowed in this context.

 Invalid or missing value <Value> for RFC parameter in configuration item AlertMonFun.

The value for the defined RFC parameter indicated in <Value> is not allowed or is absent. Check and, if necessary, change or add the value for the specified parameter.

The name of the alert monitor or the type of parameter specified for a given alert type is not allowed in this context. Check the spelling and make sure that the alert type is allowed with the specified alert-collector monitor.

Parameter <ParameterName> for Alertmonitor <AlertMonitorName> is not valid.

The specified parameter is not allowed in combination with the specified alert-collector monitor.

 Alertmonitor <AlertMonitorName> and Alerttype <AlertTypeName> requires the parameter USERNAME.

You must define the parameter USERNAME if you want to use the alert monitor and alert type indicated.

Values specified for HIGH or LOW parameter must be positive numbers.

The value(s) defined in the HIGH/LOW parameters for a given alert type are incorrect or not allowed; use a positive number.

Values for HIGH or LOW parameter must be between <Number> and <Number>.

The HIGH/LOW parameters for a given alert type must be between the numbers indicated.

 Invalid values specified for parameters LOW or HIGH, see the administrator reference guide for valid values.

The *HP Operations Smart Plug-in for SAP On-line Help* describes the contents of each monitor's configuration file in great detail.

 The value <Value> specified for the SIGN parameter is not allowed; enter the appropriate value as described in the administrators reference.

The *HP Operations Smart Plug-in for SAP On-line Help* describes the contents of each monitor's configuration file in great detail.

• Invalid value <Value> specified for the OPTION parameter.

The value used to define the OPTION parameter in the monitor-configuration file is not allowed. Check that the value is valid and that this kind of option is allowed in the specified context.

Low AND High parameter is required if OPTION is <OptionName>.

You must specify values for both the HIGH and LOW parameters when using the option indicated in <OptionName>; either one or both of the values is missing or incorrectly defined.

No HIGH parameter is required if OPTION is <OptionName>.

Remove that value specified for the HIGH parameter; you do not need it when using the option indicated in <OptionName>.

• The number of arguments for keyword <KeyWord> is wrong.

Different keywords might require a different number or type of parameters. In this case, there are either too many or too few parameters specified for the keyword indicated in <keyword>. This could lead to a situation where the monitor assumes an incorrect value for a parameter.

r3monale: The iDOC-Status Monitor

The iDOC-status alert monitor, r3monale, is *time-frame* based and checks the status of existing iDOCs for errors using the transaction **WEO2** as the data source. The monitor is application-server independent and available for global (SAP NetWeaver System-wide) use.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The iDOC-status alert monitor is of type *time frame*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The iDOC-Status Monitor has the following alert types:

IDOC CURRENT STATUS

Defines when to generate an alert concerning the current state of the iDOCs

File Locations

The r3monale alert monitor uses the files listed in this table.

Table 23 r3monale Files

File	Description
r3moncol(.exe)	Collector executable for the iDOC-status monitor
r3monale.cfg	Configuration file for iDOC-status monitor
r3monale.log	Trace file for storing trace data

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monale monitor uses the environment variables described in Table 21 on page 105. The environment variables for all the alert-collector monitors share the same format, the only difference being that the name of the configuration file varies to match each specific monitor as indicated in Table 21 on page 105.

Command-Line Parameters

The r3monale monitor uses the command-line parameters described in Table 22 on page 106. The command-line parameters for all the alert-collector monitors share the same format, the only difference being that the name of the configuration file must vary to match each specific monitor for both the -cfqfile and -trace parameters as indicated in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.



The remainder of this section describes the specific configuration requirements for the r3monale alert monitor. Alert-Collector Monitor Query Conditions on page 102 describes general configuration query rules which apply to all alert collector monitors. If you use the HPOM for Windows configuration-file policy editor to configure r3moncol alert collectors, the SPI for SAP checks the validity of the changes you make when you try to save the modified configuration file.

Configuring iDOC-Monitor Alert Types

When configuring the IDOC_CURRENT_STATUS alert type for r3monale, the iDOC status monitor, remember that you must define at least one of the parameters listed in Table 24. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

IDOC CURRENT STATUS

Table 24 on page 117 lists the parameters that you can use to configure the IDOC_CURRENT_STATUS alert type and shows the well use assigned to the parameters by default. Note that "in the Default Value column signifies an empty string."

Table 24 IDOC_CURRENT_STATUS Configuration Parameters

MESCOD Parameter	Logical message	= Sign I	Default
Name	code Description	Quety Colditions	Value
DOCNUM	iDOC number, for	≣ Sogn: I, E	٤٤
	example: "05" (error during	≡ HighGE, GT, LE, LT,	£ £
MESFCT	trogichtionssage	BT Sign: I	"
	function	≣ bow: CP, EQ	"
		= High:	66
		= High	٠.
MESTYP	Logical message	= Sign: I	٠.
	type	= Opt: CP, EQ	"
		= Low	"
		= High	٠.
RCVPFC	Partner function	= Sign: I	"
	of receiver	= Opt: CP, EQ	"
		= Low	٠.
		= High	"

DOCTYP	the basic iDOC	= Sign: I	٠.
	type, for example: DOCMAS01	= Opt: CP, EQ	٠.
		= Low	٠.
		= High	"
MESCOD	Logical message	= Sign I	**
	code	= Opt: CP, EQ	"
		= Low	٠,٠
		= High	٠,٠
MESFCT	Logical message	= Sign: I	٠.
	function	= Opt: CP, EQ	٠.
		= Low	٠.
		= High	٠.
MESTYP	Logical message	= Sign: I	٠.
	type	= Opt: CP, EQ	٠.
		= Low	٠.
		= High	٠.
RCVPFC	Partner function	= Sign: I	٠.
	of receiver	= Opt: CP, EQ	٠.
		= Low	"
		= High	"

Table 24 IDOC_CURRENT_STATUS Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
SNDPFC	Partner function	= Sign: I	"
	of sender	= Opt: CP, EQ	"
		= Low	
		= High	
SNDPRN	Partner number	= Sign: I	"
	of sender	= Opt: CP, EQ	
		= Low	
		= High	
SNDPRT	Partner type of sender	= Sign: I	
		= Opt: CP, EQ	
		= Low	
		= High	
STATUS a	Status of iDOC	= Sign: I, E	
		= Opt: GE, GT, LE, LT, BT	
		= Low	
		= High	"

a. Possible values: CHECK_INBOUND, CHECK_OUTBOUND, MAX_ENTRIES, TIME_LIMIT



The iDOC changes listed here are applicable only to SAP versions 6.20 and above.

In Remote Monitoring, the r3monale alert checks the status of inbound iDOCs. An event generating an alert occurs if the number of in-bound iDOCS specified in IDOC_CURRENT_STATUS is greater than (GT) the value 4 (four) defined in MAX_ENTRIES. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

IDOC CURRENT STATUS Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL =1 \
=WARNING =ALE =R3_IDOC_STATUS \
=IDOC_CURRENT_STATUS =STATUS =I =EQ =CHECK_INBOUND \
=MAX_ENTRIES =I =GT =4
```

Checking the iDOC Status

Using the IDOC_CURRENT_STATUS alert type in conjunction with the STATUS parameter allows you to check any one of the different iDOC statuses that are registered in SAP NetWeaver or a range of statuses defined in a group. Table 25 lists all the statuses that the SPI for SAP recognizes.

In addition, the SPI for SAP provides two pre-defined groups that you can use to check for a range of errors relating to incoming or outgoing iDOCs. For example, you can use the values <code>CHECK_INBOUND</code> and <code>CHECK_OUTBOUND</code> to monitor a range of values:

CHECK_OUTBOUND

monitors iDOCs with status: 02, 04, 05, 25, 26, 29, 30, 32

CHECK INBOUND

monitors iDOCs with status: 51, 56, 60, 61, 62, 63, 64, 65, 66, 69

If you want to use the r3monale alert monitor to check for a specific iDOC status, replace the value <code>=CHECK_INBOUND</code> shown in <code>IDOC_CURRENT_STATUS</code> Configuration on page 119 with the iDOC status number listed in Table 25 that corresponds to the iDOC status you want to monitor. For example, to monitor the number of existing iDOCS, use <code>=01</code>. Note that it is not currently possible to define your own ranges similar to the pre-defined ranges <code>CHECK_INDOUND</code> and <code>CHECK_OUTBOUND</code>. Instead, you have to define a separate <code>AlertMonFun</code> entry for <code>each</code> additional value, which you want to monitor.

Table 25 Possible iDOC Status

iDOC Status	Description	Check Inbound	Check Outbound
00	Not used, only for R/2		
01	IDoc created		
02	Error passing data to port		✓
03	Data passed to port OK		
04	Error within control information of EDI subsystem		✓
05	Error during translation		✓
06	Translation OK		
07	Error during syntax check		
08	Syntax check OK		
09	Error during interchange handling		
10	Interchange handling OK		
11	Error during dispatch		
12	Dispatch OK		
13	Retransmission OK		
14	Interchange Acknowledgement positive		

Table 25 Possible iDOC Status (cont'd)

iDOC Status	Description	Check Inbound	Check Outbound
15	Interchange Acknowledgement negative		
16	Functional Acknowledgement positive		
17	Functional Acknowledgement negative		
18	Triggering EDI subsystem OK		
19	Data transfer for test OK		
20	Error triggering EDI subsystem		
21	Error passing data for test		
22	Dispatch OK, acknowledgement still due		
23	Error during retransmission		
24	Control information of EDI subsystem OK		
25	Processing despite syntax error (outbound)		1
26	Error during syntax check of IDoc (outbound)		1
27	Error in dispatch level (ALE service)		
28	Not used		
29	Error in ALE service		1
30	IDoc ready for dispatch (ALE service)		1
31	Error - no further processing		
32	IDoc was edited		1
33	Original of an IDoc which was edited		
34	Error in control record of IDoc		
35	IDoc reloaded from archive		
36	Electronic signature not performed (time-out)		
37	IDoc added incorrectly		
38	IDoc archived		

Table 25 Possible iDOC Status (cont'd)

iDOC Status	Description	Check Inbound	Check Outbound
39	IDoc is in the receiving system (ALE service)		
40	Application document not created in receiving system		
41	Application document created in receiving system		
42	IDoc was created by test transaction		
50	IDoc added		
51	Error: Application document not posted	1	
52	Application document not fully posted		
53	Application document posted		
54	Error during formal application check		
55	Formal application check OK		
56	IDoc with errors added	1	
57	Test IDoc: Error during application check		
58	IDoc-Copy from an R/2 connection		
59	Not used		
60	Error during syntax check of IDoc (Inbound)	1	
61	Processing despite syntax error (Inbound)	1	
62	IDoc passed to application	1	
63	Error passing IDoc to application	1	
64	IDoc ready for transfer to the application	1	
65	Error in ALE service		
66	IDoc is waiting for predecessor IDoc (serialization)		
67	Not used		
68	Error - no further processing		

Table 25 Possible iDOC Status (cont'd)

iDOC Status	Description	Check Inbound	Check Outbound
69	IDoc was edited	1	
70	Original of an IDoc which was edited		
71	IDoc reloaded from archive		
72	Not used, only for R/2		
73	IDoc archived		
74	IDoc was created by test transaction		

r3monchg: The System-Change-Option Monitor

The SAP System-change-option alert monitor r3monchg double-checks the SAP system change options using the SAP NetWeaver transaction **SE06** as a reference.

This section contains information about the following topics:

- Monitor Type on page 123
- Alert Types on page 123
- File Locations on page 124
- Environment Variables on page 124
- Command-Line Parameters on page 124
- Remote Monitoring on page 124

Note that if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3monchg monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The SPI for SAP monitor for SAP System-change-option alerts has only one alert type: CHANGE_OPT

Monitors and double-checks the SAP System change options and generates an alert if the option matches the configuration.

File Locations

The r3monchg alert monitor uses the files listed in this table.

Table 26 r3monchg Files

File	Description
r3moncol(.exe)	Collector executable for the system change option monitor
r3monchg.cfg	Configuration file for system change option monitor.
r3monchg.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monchg monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monchg monitor uses the command line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Configuring SYSTEM CHANGE OPTION Monitor Alert Types

The general rules repeated below concern the use of exclude and include parameter values: the rules are particularly important for these alert types.

Parameter Values

This section describes how the SPI for SAP interprets *include* and *exclude* parameter values for an alert type entry. The SPI for SAP compares values in *different* parameters using 'and'; the SPI for SAP compares values in the *same* parameter as follows.

- **Include**: use 'or' to compare the parameters
- **Exclude**: use 'and' to compare the parameters

Note that the SPI for SAP evaluates *include* values before *exclude* values, as shown in Table 27.

Table 27 Comparing Include and Exclude Conditions for the Same Parameter

Select Options	Alert Type: CHANGE_OPT (SAP 4.6x) Example Configuration of Select Options	Comparison
1	=SYSTEM_CHANGE_OPTION =1 =WARNING =SystemChange =R3_Security =NSP_EDTFLAG =I = CP= /0* =	OR
2	=SYSTEM_CHANGE_OPTION =1 =WARNING =SystemChange = =R3_Security = NSP_EDTFLAG =I =EQ =/SAPQUERY/ =	OR
3	=SYSTEM_CHANGE_OPTION =1 =WARNING =SystemChange =R3_Security = NSP_EDTFLAG =E =EQ =LOCAL =	AND

CHANGE_OPT

The CHANGE_OPT alert type monitors and double-checks the SAP- System change options and generates an alert if the settings for the flag parameters allow the editing you are trying to perform. Table 28 on page 125 lists the parameters that you can use to configure the CHANGE_OPT alert type and shows the value assigned to the parameters by default.

The configuration of all parameters is mandatory. Multiple parameter entries on a single line are *not* allowed; use a new line to specify each one of any multiple configurations. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 28 CHANGE_OPT Configuration Parameters (SAP 4.6/6.x)

Parameter Name	Description	Query Conditions	Default Value
EDTFLAG	Flag indicating if	= Sign: I	I
	an object can be edited.	= Opt: EQ	EQ
		= Low: ON, OFF, PATCH (PATCH=set to patch system)	PATCH
		= High:	
NSP_EDTFLAG Flag indicating	= Sign: I	I	
	which specified name space(s) to	= Opt: EQ, CP	СР
	set to ON.	= Low	*
		(See list of name space change options for SAP 4.6. X in Table 30.)	
		= High:	

Table 28 CHANGE_OPT Configuration Parameters (SAP 4.6/6.x)

Parameter Name	Description	Query Conditions	Default Value
SWC_EDTFLAG	Flag indicating	= Sign: I	I
	which specified software	= Opt: EQ, CP	СР
components to set to ON.	= Low: <specified software<br="">component> (See list of name space change options for SAP 4.6. X in Table 30.)</specified>	*	
		= High:	

In The Default CHANGE_OPT Configuration, an event generating an alert occurs when the global system change is OFF or the specified name space is Local Objects (/0LOCAL/), or the specified software component is Local Developments (no automatic transport).

The Default CHANGE OPT Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL
                                =SYSTEM CHANGE OPTION =1\
=WARNING
           =SystemChange =R3 Security \
=CHANGE OPT
             =NSP EDTFLAG =I =EQ =/OLOCAL/
AlertMonFun =ALL =ALL =ALL =SYSTEM CHANGE OPTION =1\
=WARNING
           =SystemChange =R3 Security \
                   =SWC EDTFLAG =I
=CHANGE OPT
                                      =EQ = LOCAL
AlertMonFun =ALL =ALL =ALL =SYSTEM CHANGE OPTION =1\
=WARNING
           =SystemChange =R3 Security \
=CHANGE OPT
                     =EDTFLAG
                                        =EQ = OFF =
```

The Customized CHANGE_OPT Configuration

```
AlertMonFun =ALL =ALL =SYSTEM CHANGE OPTION =1\
=WARNING
           =SystemChange =R3 Security \
=CHANGE OPT =NSP EDTFLAG =I
                              =EQ =/SAPQUERY/
AlertMonFun =ALL =ALL =ALL =SYSTEM CHANGE OPTION =1\
=WARNING
         =SystemChange =R3 Security \
=CHANGE OPT
                  =SWC EDTFLAG =I
                                    =EQ = SAP HR =
AlertMonFun =ALL =ALL =ALL =SYSTEM CHANGE OPTION =1 \
         =SystemChange =R3 Security \
=WARNING
=CHANGE OPT =EDTFLAG =I
                          =EQ =OFF =
```

In The Customized CHANGE_OPT Configuration, an event generating an alert occurs when the global change option is OFF or the system space change option ABAP query /SAP is ON, or the software component change option for Human Resources is ON. For more information about the change options for name system and software components, see Table 29 and Table 30.

Table 29 Software Components Change Options

Technical ID	Description
HOME	Customer developments
LOCAL	Local developments (no automatic transport)
SAP_ABA	Cross-Application Component
SAP_APPL	Logistics and Accounting
SAP_BASIS	SAP Basis Component
SAP_HR	Human Resources

Table 30 Name System Change Options for SAP 6.x

Technical ID	Description	
/0CUST/	Customer name range	
/0SAP/	General SAP name range	
/1BCABA/	ABAP & GUI tools	
/1BCDWB/	Development Workbench	
/1BCDWBEN/	Enqueue function groups	
/1COPA/	Generated objects in CO-PA	
/1ISRWP/	IS-R merchandise and assortment controlling	
/1ISU/	Generation namespace for CIC (Customer Interaction Center)	
/1PAPA/	Personnel administration	
/1PAPAXX/	Personnel administration - general	
/1PSIS/	Project Information System - Logical database PSJ	
/1PYXXFO/	PY-XX Form tool: Generated objects	
/1SAP1/	General SAP generation namespace	
/1SDBF12L/	Generation of pricing report	
/BI0/	Business Information Warehouse: SAP namespace	
/BIC/	Business Information Warehouse: Customer namespace	
/SAPQUERY/	ABAP query /SAP	

Table 30 Name System Change Options for SAP 6.x (cont'd)

Technical ID	Description
/SAPRRR/	Ready-to-Run SAP
/SAPSMOSS/	Interface: SAP messages to the SAP Online Service System
/SAPTRAIN/	SAP training

r3moncts: The Correction and Transport System Monitor

The correction-and-transport (CTS) alert monitor r3moncts identifies and monitors the Correction and Transport System for important transport requests, tasks and objects. Data collection is application-server independent.

The alert monitor r3moncts uses the following SAP elements as a reference:

- Transport requests and object lists created using SAP NetWeaver transaction SE01
- Tasks created using SAP NetWeaver transaction SE09

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3moncts monitor is of type *time frame*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The CTS monitor has the following alert types:

• REQUEST_CREATED

Defines when new requests generate an alert

REQUEST RELEASED

Defines whether to generate an alert for a released request

• TASK CREATED

Defines if new tasks should generated an alert

TASK RELEASED

Defines whether to generate an alert for released tasks

• OBJECT USED

Defines whether objects used by a task or a request generate an alert

OBJECT_RELEASED

Defines whether to generate an alert when a request or task releases an object

File Locations

The r3moncts monitor uses the files listed in this table.

Table 31 r3moncts Files

File	Description	
r3moncol(.exe)	Collector executable for the CTS monitor	
r3moncts.cfg	Configuration file for the CTS monitor.	
r3moncts.log	Trace file for storing trace data.	

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3moncts monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3moncts monitor uses the command line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Configuring CTS Monitor Alert Types

You should keep in mind the following rules when configuring the alert-type parameters for the CTS monitor, r3moncts:

- By default, the SPI for SAP selects *all* data for each parameter.
- You can restrict data by specifying some or all of the parameters for the alert type.
- The SPI for SAP only considers the named parameters if you change default values and overrides the default value ALL for the unspecified parameters.

Use the parameter TRFUNCTION to configure the REQUEST_CREATED, REQUEST_RELEASED, TASK CREATED and TASK RELEASED alert types. TRFUNCTION has request functions which you can specify using the letter codes indicated in Table 32.

Table 32 TRFUNCTION Request Functions

Letter Code	Function Description
A	Request: Unclassified request becomes K, L or W with first object
C	Transport with change authorization
D	Patch
K	Request: Change request with destination consolidation layer
L	Request: Local request without transport
R	Task: Repair
S	Task: Development/correction
T	Request: Transport without originals
U	Dummy
W	Request: Customizing request with cons. layer destination
X	Task: Unclassified task becomes S or R with first object
Z	(task without request) SE09 memory usage

In the descriptions of the use of this parameter for each of the CTS alert types, only the letter code is shown. If you do not know what these letter codes represent, consult Table 32.

REQUEST_CREATED

Use the REQUEST_CREATED alert type to configure the correction-and-transport (CTS) alert monitor r3moncts to generate a message for any new request created within the last specified time frame. For example, adding a new (or modifying an existing) function module requires a change request. Table 33 on page 131 lists the parameters that you can use to configure the REQUEST_CREATED alert type and shows the value assigned to the

parameters by default. The configuration of any of these parameters is optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 33 REQUEST_CREATED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
TRFUNCTION	The request function.	= Sign: I, E	I
		= Opt: CP, EQ	CP
		= Low: A,K,L,W,C,T, U, D ^a	*
		= High:	
TARGET	GET The target system for which this request was created. Note: this must be a SID	= Sign I, E	
		= Opt: EQ, CP	
		= Low: <name of="" system=""></name>	
		= High	
USERNAME	USERNAME The login name of the SAP NetWeaver user who created the request.	= Sign I	
1		= Opt: EQ, CP	
		= Low: <username created="" request="" this="" who=""></username>	
		= High	

a. You can only specify the listed functions (* means all).

In The Default REQUEST_CREATED Configuration, the monitor generates a message if a new request occurs within the last time frame.

The Default REQUEST_CREATED Configuration

```
AlertMonFun =ALL =ALL =ALL =CTS =1\
=WARNING =Request =R3_CTS\
=REQUEST CREATED =USERNAME =I =CP =* =
```

REQUEST_RELEASED

Use the REQUEST_RELEASED alert type to configure the correction-and-transport (CTS) alert monitor r3moncts to generate a message for any new request released within the last specified time frame. Table 34 on page 132 lists the parameters that you can use to configure the REQUEST_RELEASED alert type and shows the value assigned to the parameters by

default. The configuration of the parameters below is optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 34 REQUEST_RELEASED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
TRKORR	Request ID	= Sign: I, E	
		= Opt: EQ	
		= Low: <request id=""></request>	
		= High:	
TRFUNCTION	The request	= Sign: I, E	
	function.	= Opt: EQ	
		= Low: K,L, W,C,T, U, D. (You can only specify the listed functions (* means all).)	
		= High:	
TARGET	The target	= Sign I, E	I
	system for which this request was	= Opt: EQ, CP	СР
	created. This	= Low: <name of="" system=""></name>	*
	must be a SID	= High	
USERNAME	The login name of the SAP NetWeaver user who created the request.	= Sign I	
		= Opt: EQ,CP	
		= Low: <username created="" request="" this="" who=""></username>	
		= High	
CUSTOMIZING	Customizing Requests	= Sign I,E	
		= Opt: EQ	
		= Low (Any entry other than 'X' will be treated as space.)	
		= High	
WORKBENCH	Workbench	= Sign I, E	
	Requests	= Opt: EQ	
		= Low (Any entry other than 'X' will be treated as space.)	
		= High	

In The Default REQUEST_RELEASED Configuration, an event generating an alert occurs if any *customizing* request was released in the last time frame.

The Default REQUEST_RELEASED Configuration

```
AlertMonFun =ALL =ALL =ALL =CTS =1\
=WARNING =Request =R3_CTS\
=REQUEST RELEASED =CUSTOMIZING =I =EQ =X
```

TASK_CREATED

Use the TASK_CREATED alert type to configure the correction-and-transport (CTS) alert monitor r3moncts to generate a message for any new task *created* within the last specified time frame. Table 35 on page 133 lists the parameters that you can use to configure the TASK_CREATED alert type and shows the value assigned to the parameters by default. The configuration of any of these parameters is optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 35 TASK_CREATED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
TRFUNCTION	The request function.	= Sign: I, E	I
		= Opt: CP, EQ	СР
		= Low: X, S, R, Z ^a	*
		= High:	
USERNAME The login name of the SAP NetWeaver user who created the request.	_	= Sign: I	
	NetWeaver user who created the	= Opt: EQ, CP	
		= Low: <username created="" request="" this="" who=""></username>	
	= High:		

a. You can only specify the listed functions (* means all).

In The Default TASK_CREATED Configuration, r3moncts generates a message for any new task *created* within the last specified time frame.

The Default TASK_CREATED Configuration

```
AlertMonFun =ALL =ALL =ALL =CTS =1 \
=WARNING =Task =R3_CTS \
=TASK CREATED =TRFUNCTION =I =CP =*
```

TASK_RELEASED

Use the TASK_RELEASED alert type to configure the correction-and-transport (CTS) alert monitor r3moncts to generate a message for any new task released within the last time frame. Table 36 on page 134 lists the parameters that you can use to configure the TASK_RELEASED alert type and shows the value assigned to the parameters by default. The

configuration of the parameters below is optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 36 TASK_RELEASED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
TRKORR	Request ID	= Sign: I, E	
		= Opt: EQ	
		= Low: <request id=""></request>	
		= High:	
TRFUNCTION	The request function.	= Sign: I, E	I
		= Opt: CP, EQ	СР
		= Low: R, S, Z ^a	*
		= High:	
USERNAME	The login name	= Sign: I	
	of the SAP NetWeaver user who created the request.	= Opt: EQ, CP	
		= Low: <username created="" request="" this="" who=""></username>	
request.		= High	

a. You can only specify the listed functions (* means all).

In The Default TASK_RELEASED Configuration, r3moncts generates a message for any new task *released* in the last time frame.

The Default TASK_RELEASED Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL =CTS =1\
=WARNING =Task =R3_CTS\
=TASK_RELEASED =TRFUNCTION =I =CP =* =
```

OBJECT_USED

Use the OBJECT_USED alert type to configure the correction-and-transport (CTS) alert monitor r3moncts to generate a message if a task or a request uses an object matching the defined configuration within the last time frame. Table 37 on page 135 lists the parameters that you can use to configure the OBJECT_USED alert type and shows the value assigned to the parameters by default.

The configuration of the parameters below is optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 37 OBJECT_USED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
PGMID	Program ID	= Sign: I, E	
		= Opt: EQ, CP	
		= Low: <program id=""></program>	
		= High:	
OBJECT	Object type of	= Sign I, E	
	element	= Opt: EQ, CP	
		= Low: <object type=""></object>	
		= High	
OBJ_NAME	Object Name in object directory	= Sign I, E	I
		= Opt: EQ, CP	CP
		= Low: <object name=""></object>	*
		= High	
OBJ_FUNC	Special function for an object entry: D = Delete, or M = Delete and recreate.	= Sign I, E	
		= Opt: EQ, CP	
		= Low	
		= High	
IN_REQUEST	Alert generated if object container is a request	= Sign I,E	
		= Opt: EQ	
		= Low	
		= High	
IN_TASK	Alert generated if object	= Sign I, E	
		= Opt: EQ	
	container is a task.	= Low	
	task.	= High	

In The Default OBJECT_USED Configuration, an event generating an alert occurs if any object with Object Type "LIMU" is used by a task or a request.

The Default OBJECT_USED Configuration

```
AlertMonFun =ALL =SD1 =ALL =ALL =CTS =1\
=WARNING =Object =R3_CTS\
=OBJECT_USED =PGMID =I =EQ =LIMU =
```

OBJECT_RELEASED

Use the OBJECT_RELEASED alert type to configure the correction-and-transport (CTS) alert monitor r3moncts to generate a message if a request or a task released the specified object. Table 38 on page 136 lists the parameters that you can use to configure the OBJECT_USED alert type and shows the value assigned to the parameters by default.

The configuration of the parameters below is optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

 Table 38
 OBJECT_RELEASED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
TRKORR	Request ID	= Sign: I, E	
		= Opt: EQ, CP	
		= Low: <request id=""></request>	
		= High:	
PGMID	Program ID	= Sign: I, E	
		= Opt: EQ, CP	
		= Low: <program id=""></program>	
		= High:	
OBJECT	Object type of element	= Sign I, E	
		= Opt: EQ, CP	
		= Low: <object type=""></object>	
		= High	
	Object Name in	= Sign I	I
	object directory	= Opt: EQ, CP	СР
		= Low: <object name=""></object>	*
		= High	
IN_REQUEST	Alert	= Sign I,E	
	generated if object container is a request	= Opt: EQ	
		= Low (Any entry other than 'X' will be treated as space.)	
		= High	

Table 38 OBJECT_RELEASED Configuration Parameters (cont'd)

Parameter Name	Description	Query Conditions	Default Value
IN_TASK	Alert	= Sign I, E	
	generated if object container is a task.	= Opt: EQ	
		= Low (Any entry other than 'X' will be treated as space.)	
		= High	

In The Default OBJECT_RELEASED Configuration, an event generating an alert occurs if any object is released by a task.

The Default OBJECT_RELEASED Configuration

```
AlertMonFun =ALL =ALL =AL =CTS =1\
=WARNING =Object =R3_CTS\
=IN TASK =I =EQ =X =
```

r3mondmp: The ABAP-Dump Monitor

The ABAP-dump alert monitor, r3mondmp, reports ABAP dumps in the SAP NetWeaver system which have occurred within the last, defined, time frame. The check is performed once per monitor run for all application servers.

Dumps are usually runtime errors and hence they cannot always be detected by a static syntax check. They can occur for many reasons and may indicate serious problems. No dumps should occur on a production system.

Here are two examples of actions which cause dumps to occur:

- division by zero
- a called function model is not enabled

Since the system administrator generally has to do something to resolve problems associated with an ABAP dump, the messages generated by the r3mondmp alert monitor include an operator-initiated action that calls an ABAP program to display details of the dump.

The alert monitor r3mondmp references the SAP NetWeaver transaction ST22.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The ABAP-dump alert monitor is of type *time frame*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The ABAP-dump monitor has the following alert types:

ABAP4_ERROR_EXIST

Each ABAP dump generates one alert.

File Locations

The r3mondmp monitor uses the files listed in this table.

Table 39 r3mondmp Files

File	Description
r3moncol(.exe)	Collector executable for ABAP-dump monitor
r3mondmp.cfg	Configuration file for monitored application servers.
r3mondmp.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3mondmp monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3mondmp monitor uses the command line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

ABAP4 ERROR EXIST

Use the ABAP4_ERROR_EXIST alert type to configure the ABAP-dump alert monitor, r3mondmp, to generate an alert for each dump that occurred in the last time frame. The Default ABAP4_ERROR_EXIST Configuration shows how you can use =MAX_ENTRIES to count the number of dumps that have to occur before the SPI for SAP generates a message. In addition, you can specify a period of time in hours (=TIME_LIMIT) within which the defined number of dumps must occur. In this example, the SPI for SAP generates a message if ten dumps occur within twenty four hours.

The Default ABAP4_ERROR_EXIST Configuration

```
=ALL =ABAP4 =1\
AlertMonFun
                =ALL =ALL =ALL
=WARNING
            =ABAP Dump
                         =R3 ABAP-4\
=ABAP4 ERROR EXIST
# New feature in SPI for SAP version 8.0
#AlertMonFun
                =ALL
                       =ALL
                             =ALL
                                   =ALL
                                         =ABAP4 = 1
      =WARNING
                =ABAP Dump =R3 ABAP-4
                                        =ABAP4 ERROR EXIST\
                                          =10
                =MAX ENTRIES =I
                                    =GT
                =TIME LIMIT
                              =I
                                    =LT
                                          =24
```

The SPI for SAP's optional test transport includes a program that generates an ABAP dump which you can use to verify that the r3mondmp monitor correctly reports dumps to HPOM for Windows in the form of a message. If the test completes successfully, a message about the test dump appears in the HPOM for Windows console. For more information about SPI for SAP transports, see the transports read-me file \usr\sap\trans\readme on the HPOM for Windows managed node; for more information about importing and applying SPI for SAP transports, see the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows. After importing the transport, you can view the test programs installed by using the SAP transaction SE80 to open the ABAP object navigator and browsing to the report (or program) /HPOV/YSPI0004.

r3monjob: The Job-Report Monitor

The job-report alert monitor r3monjob identifies and reports on batch jobs for the following conditions:

- A batch job's run time is either less than or has exceeded a specified limit.
- A specified period of time passes between a batch job's scheduled and actual start time (and date).
- A batch job has aborted.



You cannot configure r3monjob to send multiple messages, for example, first send a WARNING message if the run time for a batch job exceeds 5 minutes and then send a CRITICAL message if the run time for the same batch job exceeds 10 minutes.

The alert monitor r3monjob references:

- Reports created using SAP NetWeaver transaction SM36 or SM38
- Job details including ID number using SAP NetWeaver transaction SM37

Messages generated by this alert monitor include an operator-initiated action that displays the list of current SAP batch jobs.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The job-report monitor is of type *time frame*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The Job-report monitor has the following alert types. Note that if you want to use the r3monjob monitor, you *must* configure the alert types listed below:

JOB MAX RUN TIME

defines the *maximum* allowed run time for a job. r3monjob sends an alert if the defined job runs for longer than the maximum defined time, specified in minutes.

JOB_MIN_RUN_TIME

defines the *minimum* allowed run time for a job. r3monjob sends an alert if the defined job does not run for at least as long as the defined time, specified in minutes.

START PASSED

is the maximum allowed delay between scheduled and actual start time for a defined job. r3monjob triggers an alert if the job does not start within the defined time, specified in minutes.

• JOB ABORTED

r3monjob sends an alert whenever the jobs specified in its configuration fail to complete successfully.

First Time Monitoring

When monitoring batch job alerts for a particular alert type for the first time, the Job-report monitor r3monjob checks for the following conditions in SAP:

- Jobs which are not yet scheduled to run
- Jobs which ended within the previous two days
- Jobs which are still running

Performance Aspects

On a production system the table tbtco is usually very big. To speed up the database selection you should specify the job names in as much detail as possible. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

The runtime cost of a job selection grows in the order shown in Table 40.

Table 40 Order of Runtime Cost of Job Selection Criteria

Specified Jobname	Sign	Option	Selection
JOBNAME	I	EQ	Z5_CRITICAL_JOB_1> select via index
JOBNAME	Ι	СР	Z5_CRITICAL_JOB*> select via index
JOBNAME	Е	СР	Z5_CRITICAL_JOB*> sequential scan

Note that exclude options tend to be more expensive than include options in performance terms. Using wild cards such as "*" in general database queries is more expensive than in explicit queries.

File Locations

The r3monjob monitor uses the files listed in this table

Table 41 r3monjob Files

File	Description
r3moncol(.exe)	Collector executable for the batch job monitor
r3monjob.cfg	Configuration file for monitored jobs and job conditions.
r3monjob.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monjob monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monjob monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Configuring Job-Report Monitor Alert Types

You can configure r3monjob, the job-report monitor, for each of the listed alert types for a specific job, a combination of jobs, or for *all* jobs. You can also define exceptions for jobs that need different monitoring conditions. For more detailed information, see the alert-type tables which list the parameters and configuration options for each alert type. Note that the general rules for using exclude and include parameter values, which are of particular importance for these alert types.

Try to avoid using select option CP with the JOBNAME parameter because CP slows down the selection process. If you do use CP, try to limit its scope, for example, instead of specifying CP *, specify CP SAP*.

Parameter Values

This section describes how the SPI for SAP interprets *include* and *exclude* parameter values for an alert type entry. The SPI for SAP compares values in *different* parameters using 'and'; the SPI for SAP compares values in the *same* parameter as follows.

- **Include**: use 'or' to compare the parameters
- Exclude: use 'and' to compare the parameters

The SPI for SAP evaluates include values before exclude values, as shown in Table 42.

Table 42 Comparing Include and Exclude Conditions for the Same Parameter

Select Options	AlertType:JOB_MAX_RUN_TIME Example Configuration of Select Options	Comparison
1	=JOBNAME =I =CP =ZREP* = =MAX_RUNTIME =I =GT =10 =	OR
2	=JOBNAME =I =CP =SAP* = =MAX_RUNTIME =I =GT =20 =	OR
3	=JOBNAME =E =CP =SAP_ZREP* =	AND

JOB_MAX_RUN_TIME

The JOB_MAX_RUN_TIME alert type defines the maximum allowed run time for a job. Use the JOB_MAX_RUN_TIME alert type to configure the job-report alert monitor r3monjob to generate an alert when a job exceeds the value configured in the parameter MAX_RUNTIME. Table 43 on page 143 lists the parameters that you can use to configure the JOB_MAX_RUN_TIME alert type and shows the value assigned to the parameters by default.

The configuration of any of the parameters listed in Table 43 is optional. If both parameters are omitted, r3monjob reports all jobs running in the specified time. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 43 JOB_MAX_RUN_TIME Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
JOBNAME	Name of the jobs to monitor	= Sign: I, E	I
		= Opt: EQ, CP, BT	CP
		= Low <name job="" of=""></name>	*
		= High (Only for use with a range)	
MAX_RUNTIME	Job run time in minutes which, if exceeded, generates an alert.	= Sign I, E	I
		= Opt: EQ, GE, GT, BT	GT
		= Low (Specify this parameter as a number. Otherwise the monitor ends with a dump.)	5
		= High (Only for use with a range)	

The following examples illustrates both the default and a customized configuration for the JOB_MAX_RUN_TIME alert type.

In The Default JOB_MAX_RUN_TIME Configuration, an event generating an alert occurs if any report named <jobname>* has a runtime exceeding five minutes.

The Default JOB_MAX_RUN_TIME Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL =JOBREPORT =1 \
=WARNING =MaxRunTime =R3_Jobs\
=JOB_MAX_RUN_TIME =JOBNAME =I =CP =<jobname>* =\
=MAX_RUNTIME =I =GT =5 =
```

In A Customized JOB_MAX_RUN_TIME Configuration, an event generating an alert occurs if all reports named SAP*, except reports SAPZ*, have a runtime exceeding ten minutes

A Customized JOB_MAX_RUN_TIME Configuration

```
AlertMonFun =ALL =ALL =ALL =JOBREPORT =1\
=WARNING =MaxRunTime =R3_Jobs \
=JOB_MAX_RUN_TIME =JOBNAME =I =CP =SAP* = \
=MAX_RUNTIME =I =GT =10 =
```

```
AlertMonFun =ALL =ALL =ALL =JOBREPORT =1\
=WARNING =MaxRunTime =R3_Jobs \
=JOB_MAX_RUN_TIME =JOBNAME =E =CP =SAPZ* = \
=MAX_RUNTIME =I =GT =10 =
```

The SPI for SAP's optional test transport includes a program that you can run to start a long-running job. You can use the job to verify that the r3monjob monitor is correctly configured to send a message to HPOM for Windows if a job runs for more than a defined amount of time. If the test completes successfully, a message about the test job appears in the HPOM for Windows console. For more information about SPI for SAP transports, see the transports read-me file \usr\sap\trans\readme on the HPOM for Windows managed node; for more information about importing and applying SPI for SAP transports, see the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows. After importing the transport, you can view the test programs installed by using the SAP transaction SE80 to open the ABAP object navigator and browsing to the report (or program) / HPOV/YSPI0002.

JOB MIN RUN TIME

The JOB_MIN_RUN_TIME alert type defines the minimum allowed run time for a job. Use the JOB_MIN_RUN_TIME alert type to configure the job-report alert monitor r3monjob to generate an alert when a job does not run for at least as long as the time specified in the parameter MIN_RUNTIME. Table 44 on page 144 lists the parameters that you can use to configure the JOB_MAX_RUN_TIME alert type and shows the value assigned to the parameters by default.

The configuration of any of the parameters below is optional. If both parameters are omitted, all jobs running in the specified time frame are reported. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 44 JOB_MIN_RUN_TIME Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
JOBNAME	Name of the jobs to monitor	= Sign: I, E	I
		= Opt: EQ, CP, BT	CP
		= Low <name job="" of=""></name>	*
		= High: ^a	
MIN_RUNTIME	This defines the minimum allowed run time Alerts are triggered for jobs which did not run for at least as long as the time specified (in minutes).	= Sign I, E	I
		= Opt: EQ,LE, LT, BT	LT
		=Low <min. in="" minutes="" value=""> b</min.>	1
		= High	

a. Only for use with a range

b. Specify this parameter as a number, otherwise the monitor ends with a dump.

The following examples illustrate both the default and a customized configuration for the JOB_MIN_RUN_TIME alert type.

In The Default JOB_MIN_RUN_TIME Configuration, an event generating an alert occurs if any report named <jobname>* has a runtime of less than one minute.

The Default JOB_MIN_RUN_TIME Configuration

```
AlertMonFun =ALL =ALL =ALL =JOBREPORT =1 \
=WARNING =MinRunTime =R3_Jobs\
=JOB_MIN_RUN_TIME =JOBNAME =I =CP =<jobname>* = \
=MIN_RUNTIME =I =LT =1 =
```

In Customized JOB_MIN_RUN_TIME Configuration, an event generating an alert occurs if all reports named SAP*, except reports SAPZ*, have a runtime of less than two minutes

${\bf Customized\ JOB_MIN_RUN_TIME\ Configuration}$

```
AlertMonFun =ALL =ALL
                        =ALL
                              =ALL
                         =R3 Jobs
=WARNING
           =MinRunTime
=JOB MIN RUN TIME =JOBNAME
                                =I
                                               =SAP*
=MIN RUNTIME =I =LT =2 =
AlertMonFun =ALL =ALL =ALL =JOBREPORT =1
=WARNING
                         =R3 Jobs \
           =MinRunTime
=JOB MIN RUN TIME =JOBNAME
                                =E
                                       =CP
                                               =SAPZ*
=MIN RUNTIME
              =I =LT
```

The SPI for SAP's optional test transport includes a program that you can run to start a short job. You can use the job to verify that the r3monjob monitor is correctly configured to send a message to HPOM for Windows if a job runs for less than a defined amount of time. If the test completes successfully, a message about the test job appears in the HPOM for Windows console. For more information about SPI for SAP transports, see the transports read-me file \usr\sap\trans\readme on the HPOM for Windows managed node; for more information about importing and applying SPI for SAP transports, see the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows. After importing the transport, you can view the test programs installed by using the SAP transaction SE80 to open the ABAP object navigator and browsing to the report (or program) /HPOV/YSPI0005.

START_PASSED

The START_PASSED alert type defines the maximum allowed delay between a job's scheduled and actual start times. Use the START_PASSED alert type to configure the job-report alert monitor r3monjob to generate an alert if the specified jobs do not start within the configured TIME_SPAN after the scheduled start time. Table 45 on page 146 lists the parameters that you can use to configure the START_PASSED alert type and shows the value assigned to the parameters by default.

If a job is scheduled but does not have a start time, r3monjob cannot monitor it until and unless an assigned start time is visible in the SAP database. SAP associates a start time with a job only when the job assumes a particular status. The following SAP job statuses have a start time which means you can monitor them with r3monjob: Released, Ready, Active, Finished, and Canceled.

The configuration of any of the parameters below is optional. If both parameters are omitted all jobs running in the specified time frame are reported. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 45 START_PASSED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
JOBNAME	Name of the jobs to monitor	= Sign: I, E	I
		= Opt: EQ, CP, BT	СР
		= Low <name job="" of=""></name>	*
	= High ^a		
TIME_SPAN	TIME_SPAN The job run time in minutes that specifies when an alert should be raised. Note that it is not necessary to use a time range. You can specify a particular time instead.	= Sign I, E	I
		= Opt: EQ, GT, GE, BT	GT
		=Low b < low_value_of_range _in_minutes_past_ scheduled_start_time>	1
can s parti		=High <high_value_of_ range_in_minutes_past_ scheduled_start_time></high_value_of_ 	

a. Only for use with a range

In The Default START_PASSED Configuration, an event generating an alert occurs if any report named < jobname>* does not start more than one minute after the scheduled start time.

The Default START_PASSED Configuration

```
AlertMonFun =ALL =ALL =ALL =JOBREPORT =1\
=WARNING =StartPassed =R3_Jobs \
=START_PASSED =JOBNAME =I =CP =<jobname>* =\
=TIME SPAN =I =GT =1 =
```

JOB_ABORTED

The JOB_ABORTED alert type defines the names of the jobs, which fail to complete successfully. Use the JOB_ABORTED alert type to configure the job-report alert monitor r3monjob to generate an alert whenever the jobs specified in its configuration file fail to complete successfully. Table 46 on page 147 lists the parameters that you can use to configure the JOB_ABORTED alert type and shows the value assigned to the parameters by default.

b. Specify this parameter as a number. Otherwise the monitor ends with a dump

The configuration of the parameter below is optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 46 JOB_ABORTED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
JOBNAME Name of the jobs to monitor		= Sign: I, E	I
		= Opt: EQ, CP, BT	СР
	= Low <name job="" of=""></name>	*	
		= High ^a	

a. Only for use when specifying a range

In The Default JOB_ABORTED Configuration, an event generating an alert occurs if any report named < jobname>* aborts.

The Default JOB_ABORTED Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL =JOBREPORT =1\
=WARNING =Aborted =R3_Jobs \
=JOB ABORTED =JOBNAME =I =CP = <jobname>*
```

In A Customized JOB_ABORTED Configuration, an event generating an alert occurs if jobs named SAP REORG ABAPDUMPS or ITOTEST are aborted.

A Customized JOB_ABORTED Configuration

```
AlertMonFun =ALL =ALL =ALL =JOBREPORT =1\
=WARNING =Aborted =R3_Jobs \
=JOB_ABORTED =JOBNAME =I =EQ =SAP_REORG_ABAPDUMPS =

AlertMonFun =ALL =ALL =ALL =JOBREPORT =1 \
=WARNING =Aborted =R3_Jobs\
=JOB_ABORTED =JOBNAME =I =EQ =ITOTEST =
```

The SPI for SAP's optional test transport includes a program that you can run to generate an ABAP dump. You can use the generated dump to verify that the r3monjob monitor is correctly configured to send a message to HPOM for Windows if a job aborts. For more information about SPI for SAP transports, see the transports read-me file \usr\sap\trans\readme on the HPOM for Windows managed node; for more information about importing and applying SPI for SAP transports, see the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows. After importing the transport, you can view the test programs installed by using the SAP transaction SE80 to open the ABAP object navigator and browsing to the report (or program) /HPOV/YSPI0004.

r3monlck: The Lock-Check Monitor

The lock-check alert-collector monitor r3monlck references the enqueue process which manages logical locks for SAP NetWeaver transactions and reports on obsolete locks. Obsolete locks are defined as locks which are older than the time period you specify. The check is performed once per monitor run for all application servers.

An object which is locked cannot be changed by anyone other than the user associated with it and can cause severe problems. The operator can check the locks set for a specific instance in **SM12**. Here are two examples of actions which cause locks to occur:

- Users switch off their computers without first logging off the SAP NetWeaver system this is the most common cause of locked objects.
- An entire SAP instance fails.

The alert monitor r3monlck references the SAP NetWeaver transaction SM12.

Messages generated by this alert monitor include an operator-initiated action that calls the **SM12** Locks Overview module. The operator can then check the locks set for a specific instance in **SM12**.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3monlck monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The lock-check monitor has only one alert type:

OLD_LOCKS

Specifies when to define a lock as "old", using the time period you specify in the parameter LOCK TIME.

File Locations

The r3monlck monitor uses the files listed in this table.

Table 47 r3monlck Files

File	Description
r3moncol(.exe)	Collector executable for the lock_check monitor
r3monlck.cfg	Configuration file for the lock_check monitor.
r3monlck.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monlck monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monlck monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

OLD LOCKS

The OLD_LOCKS alert type specifies when to define a lock as "old", using the time period you specify in the parameter LOCK_TIME. Use the OLD_LOCKS alert type to configure r3monlck to generate an alert when a job exceeds the time span defined in the parameter LOCK_TIME. Table 48 on page 149 lists the parameters that you can use to configure the OLD LOCKS alert type and shows the value assigned to the parameters by default.

The configuration of the parameter below is mandatory. Note that you can have more than one configuration in the .cfg file. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 48	LOCK	TIME Co	onfiguration	Parameters

Parameter Name	Description	Query Conditions	Default Value
		= Sign: I,E	I
		= Opt: EQ, GT, GE, LE, LT, BT	GT
	The time span (in hours) after	= Low: <time hours="" in=""> a</time>	
LOCK_TIME	which a lock is considered old	= High: ^b	

a. Specify this parameter as a number. Otherwise the monitor ends with a dump.

In The Default OLD_LOCKS Configuration, an event generating an alert occurs if any lock exceeds a time span of 24 hours.

The Default OLD_LOCKS Configuration

```
AlertMonFun =ALL =ALL =ALL =LOCK_CHECK =1\
=WARNING =Enqueue =R3_Enqueue\
=OLD LOCKS =LOCK TIME =I =GT =24 =
```

r3monoms: The Operation-Mode Monitor

The operation-mode alert monitor r3monoms checks each application server for the following conditions:

- A scheduled operation-mode switch occurs later than the time specified
- A scheduled operation-mode switch has not occurred at all

b. Only for use when specifying a range

The alert monitor r3monoms references the following SAP objects:

- Scheduled operation modes in SAP NetWeaver transaction SM63
- Configuration modes in SAP NetWeaver transaction RZ04



The operation-mode monitor r3monoms does not support the monitoring of WebAS 7.0/ Netweaver04s (kernel 7) environments; changes in SAP mean there are no operation-mode switch errors to monitor.

Operation-mode switch failures influence the performance of the SAP NetWeaver system and can cause problems. Operation-mode switches might occur for a number of reasons, for example, work processes that must be switched are still occupied in a process while the operation-mode switch is running. The system administrator usually needs to intervene to fix the problem, for example, by forcing and testing the operation mode's state.

If an operations-mode switch generates an alarm because the switch is not enabled in time, but then successfully occurs later without any intervention, the SPI for SAP sends a message indicating that the switch, although late, has now gone ahead as planned.

If you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3monoms monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The operation-mode, r3monoms, alert monitor has only one alert type:

• OM SWITCH OVERDUE

This defines when an operation mode switch is overdue.

File Locations

The r3monoms monitor uses the files listed in this table

Table 49 r3monoms Files

File	Description
r3moncol(.exe)	Collector executable for the operation mode monitor
r3monoms.cfg	Configuration file for the operation mode monitor.
r3monoms.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monoms monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monoms monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

OM_SWITCH_OVERDUE

The OM_SWITCH_OVERDUE alert type defines the period of time in which an operation-mode switch must occur. Use the OM_SWITCH_OVERDUE alert type to configure r3monoms to generate an alert if an operation-mode switch does not occur within the defined period of time. Table 50 lists the parameters that you can use to configure the OM_SWITCH_OVERDUE alert type and shows the value assigned to the parameters by default.

The configuration of the parameters in Table 50 is optional. By default, an alert is triggered if an operation-mode switch is more than three minutes late.

The APSERVER parameter allows you to set the application-server-dependent monitors, r3monwpa, r3monwsr, and r3monoms to monitor a specific application server. You need to configure APSERVER in the following manner, where <hostname> is the name of the application server to monitor as it appears in the list of application servers displayed in transaction **SM51**:

```
=APSERVER =I =CP =<hostname> <SID> <Instance Number> =
```

It is also recommended that you explicitly define the host name of the SAP NetWeaver central instance whose application server(s) you want to specify with APSERVER, as illustrated in the Specifying an Application Server.

Specifying an Application Server

```
AlertMonFun =<hostname> =ALL =ALL =ALL =OM =1 \
=WARNING =OperationMode =R3_WP \
=OM_SWITCH_OVERDUE =OVERDUE_TIME =I =GT =15 = \
=APSERVER =I =CP =hpdev01 MP3 00 =
```

The <hostname> in Specifying an Application Server is the name of the host where the r3monoms monitor is running. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 50 OM_SWITCH_OVERDUE Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
APSERVER	APSERVER specifies an application server to monitor	= Sign: I, E	
		= Opt: CP	
		= Low: <appserver_id></appserver_id>	
		= High:	
OVERDUE_TIME	The time in	= Sign: I, E	I
	minutes, after which a scheduled mode switch is considered	= Opt: GT, GE, LE, LT, BT	GT
		= Low: <time in="" minutes=""> a</time>	3
overdue.	= High: ^b		

Mandatory; if the query condition is not present, the monitor does not perform any check.

In The Default OM_SWITCH_OVERDUE Configuration, an event generating an alert occurs if a scheduled operation mode switch is more than three minutes late.

The Default OM_SWITCH_OVERDUE Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL=OM =1\
=WARNING =OperationMode =R3_WP\
=OM SWITCH OVERDUE =OVERDUE TIME =I =GT =3 =
```

r3monrfc: The RFC-Destination Monitor

The RFC-destination monitor r3monrfc is application-server independent and checks RFC destinations in an SAP environment. SAP uses RFC destinations to remotely execute function modules, which reside on other SAP Systems. The alert-collector monitor, r3monrfc, references the RFC destinations, which you can display, create, and maintain by means of the SAP NetWeaver transaction **SM59**.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

b. Only for use when specifying a range

Monitor Type

The r3monrfc monitor is of type *snapshot*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The RFC-destination alert monitor has the following alert type, which uses a snapshot report type:

CHECK

Defines alert conditions for failed SAP-RFC connections

File Locations

The r3monrfc monitor uses the files listed in this table.

Table 51 r3monrfc Files

File Description	
r3moncol(.exe)	Collector executable for the SAP-RFC monitor
r3monrfc.cfg	Configuration file for the SAP-RFC monitor.
r3monrfc.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monrfc monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monrfc monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Limitations

You can use r3monrfc to monitor the following RFC destinations as long as they are listed in SAP transaction SM59 (SAP 6.40 and later):

- HTTP Connection to External Server
- HTTP Connection to SAP NetWeaver System

Configuring RFC-destination Alert Types

You must configure the parameters CONNECTION_TYPE and NAME for all alert types for r3monrfc, the RFC-destination monitor. Note the general rules below on exclude and include parameters for r3monrfc.

Parameter Values

This section describes how the SPI for SAP interprets *include* and *exclude* parameter values for an alert type entry. The SPI for SAP compares values in *different* parameters using 'and'; the SPI for SAP compares values in the *same* parameter as follows.

- Include: use 'or' to compare the parameters
- **Exclude**: use 'and' to compare the parameters

The SPI for SAP evaluates *include* values before *exclude* values.

CHECK

CHECK is a snapshot alert type for r3monrfc, the SPI for SAP's RFC-destination monitor. Snapshot alert types take a picture of the SAP System at the moment the monitor runs.

The CHECK alert type defines alert conditions for failed SAP-RFC connections. Use the CHECK alert type to configure r3monrfc to generate an alert if the RFC connection test for the target system fails. Table 52 on page 154 lists the parameters that you can use to configure the CHECK alert type and shows the value assigned to the parameters by default.

The parameter CHECK is required. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 52.

Table 52 CHECK Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
CONNECTION_TYPE	Type of SAP RFC connection to monitor, for example: 1, 3, M, T Type 1= App. Server, 3= SAP NetWeaver System,	= Sign I, E	I
		= Opt: EQ	EQ
		= Low	3
	M= CMC, T =TCP/IP, G= HTTP connection to external server, H= HTTP connections to SAP NetWeaver system.	= High	
NAME Name you assigned to		= Sign: I, E	I
	the SAP-RFC connection as shown in the transaction /NSM59.	= Opt: EQ, CP	EQ
		= Low: <sid></sid>	,,
		= High:	

In The Default Check-RFC_DESTINATION Configuration, an event generating an alert occurs whenever the RFC_DESTINATION test fails for any *one* of the type 3 SAP-RFC destinations.

The Default Check-RFC_DESTINATION Configuration

```
AlertMonFun =ALL =ALL =ALL =RFC_DESTINATION =1 \
=WARNING =RFC_Destinations =R3_RFC \
=CHECK =CONNECTION TYPE =I =EQ =3 =
```

In An Example Check-RFC_DESTINATION Configuration, an event generating an alert occurs whenever RFC_DESTINATION test fails for the single SAP-RFC destination named OV_C01_099.

An Example Check-RFC_DESTINATION Configuration

```
AlertMonFun =ALL =ALL =ALL =RFC_DESTINATION =1 \
=WARNING =RFC_Destinations =R3_RFC \
=CHECK =NAME =I =CP =OV C01 099 =
```

r3monspl: The Spooler Monitor

The spooler alert monitor r3monspl is application-server independent and monitors spooler entries for the following conditions:

- The number of spool requests which would generate an alert
- The number of error-generating spool requests that would generate an alert
- A specified printer has received erroneous spool requests.

The alert monitor r3monspl references output tasks in SAP NetWeaver transaction **SP01** and report sources in SAP NetWeaver transaction **SE38**.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3monsp1 alert monitor is of type *snapshot*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The spooler alert monitor has the following alert types:

SPOOL ENTRIES RANGE

This defines the number of spool requests which, if exceeded, would cause an alert.

SPOOL ERROR RANGE

This defines the number of error-generating spool requests which, if exceeded, would cause an alert.

PRINT_ERROR_EXISTS

This specifies the name(s) of printers for which an alert would be generated if a spool error exists.

File Locations

The r3monspl monitor uses the files listed in this table.

Table 53 r3monspl Files

File	Description	
r3moncol(.exe)	Collector executable for the spooler monitor	
r3monspl.cfg	Configuration file for the spooler monitor.	
r3monspl.log	Trace file for storing trace data.	

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monspl monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monspl monitor uses the command line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Configuring Spooler-Monitor Alert Types

You can configure r3monspl, the spooler monitor, for each of the alert types and then define exceptions for different monitoring conditions. For more detailed information, see the alert-type tables which give the parameters and configuration for each alert type.

SPOOL_ENTRIES_RANGE

The SPOOL_ENTRIES_RANGE alert type defines the number of spool requests which, if exceeded, would generate an alert. Use the SPOOL_ENTRIES_RANGE alert type to configure r3monspl to generate an alert if the number of spool entries exceeds the range specified. Table 54 lists the parameters that you can use to configure the SPOOL_ENTRIES_RANGE alert type and shows the value assigned to the parameters by default.

The configuration of the RANGE parameter is mandatory. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 54 SPOOL_ENTRIES_RANGE Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
RANGE	The number of spool	= Sign: I, E	I
entries outside of which an alert will be generated. Note that, despite its name, you do not need to specify this parameter as a select- option range.	= Opt: EQ, GT, GE, LE, LT, BT	GT	
	= Low: ^a	50	
	= High:		

a. Specify this parameter as a number. Otherwise the monitor ends with a dump.

In The Default SPOOL_ENTRIES_RANGE Configuration, an event generating an alert occurs if there are more than 50 spooler entries.

The Default SPOOL_ENTRIES_RANGE Configuration

```
AlertMonFun =ALL =ALL =ALL =SPOOLER =1\
=CRITICAL =Spool =R3_Spooler \
=SPOOL ENTRIES RANGE =RANGE =I =GT =50 =
```

SPOOL ERROR RANGE

The SPOOL_ERROR_RANGE alert type defines the number of *erroneous* spool requests which, if exceeded, would generate an alert. Use the SPOOL_ERROR_RANGE alert type to configure r3monspl to generate an alert if the number of *erroneous* spool entries exceeds the range specified. Table 55 lists the parameters that you can use to configure the SPOOL_ERROR_RANGE alert type and shows the value assigned to the parameters by default.

The configuration of the RANGE parameter is mandatory. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 55 SPOOL_ERROR_RANGE Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
RANGE	The number of erroneous	= Sign: I, E	I
generated Note that	= Opt: EQ, GT, GE,LE, LT, BT	GT	
	= Low: ^a	50	
	= High:		

a. Specify this parameter as a number; otherwise the monitor ends with a dump.

In The Default SPOOL_ERROR_RANGE Configuration, an event generating an alert occurs if there are more than 50 erroneous spool requests.

The Default SPOOL_ERROR_RANGE Configuration

```
AlertMonFun =ALL =ALL =ALL =SPOOLER =1\
=CRITICAL =Spool =R3_Spooler \
=SPOOL ERROR RANGE =RANGE =I =GT =50 =
```

PRINT ERROR EXISTS

The PRINT_ERROR_EXISTS alert type defines the printers to monitor for spool errors. Use the PRINT_ERROR_EXISTS alert type to configure r3monspl to generate an alert if a spool error exists for the specified printer. Table 56 lists the parameters that you can use to configure the PRINT_ERROR_EXISTS alert type and shows the value assigned to the parameters by default.

r3monspl generates an alert if a spool error exists for a specified printer. The configuration of the PRINTER parameters is mandatory. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

		8	
Parameter Name	Description	Query Conditions	Default Value
PRINTER	The printer(s)	= Sign: I, E	I
	which should be checked for	= Opt:	СР
	spool entries of state error.	= Low:	*
		= High:	

Table 56 PRINT_ERROR_EXISTS Configuration Parameters

In The Default PRINT_ERROR_EXISTS Configuration, r3monspl generates an alert if any printer has a spool entry-state error.

The Default PRINT_ERROR_EXISTS Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL =SPOOLER =1\
=WARNING =Spool =R3_Spooler \
=PRINT_ERROR_EXISTS =PRINTER =I =CP =* =
```

r3montra: The Transport Monitor

The transport monitor r3montra is application-server independent and is used to check the following parts of the transport system:

- Successful or failed imports and exports for the monitored system
- The presence of confirmed and unconfirmed repairs in the monitored system
- Connections that use a connection test (PING) to the configured systems
- TP-Tests of the configured systems

The alert monitor r3montra references transport routes in SAP NetWeaver transactions **STMS** and **SE01**.

If you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3montra monitor is of type *snapshot*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The transport alert monitor has the following alert types, which use a mixture of snapshot and time-frame report types:

TRANS

Defines alert conditions for successful and failed transport exports and imports

REPAIR

Defines alert conditions for confirmed and unconfirmed repairs

RFCONNECT

Defines alert conditions for the RFC connections between the systems

TPTEST

Defines alert conditions concerning the TP interface with the database. It includes a connection test (PING), a TP call to the connected database, a check of the TP interface (version, transport directory, TPPARAM path, a file check and a TPLOG check).

File Locations

The r3montra monitor uses the files listed in this table.

Table 57 r3montra Files

File	Description	
r3moncol(.exe)	Collector executable for the transport monitor	
r3montra.cfg	Configuration file for the transport monitor.	
r3montra.log	Trace file for storing trace data.	

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3montra monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3montra monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Configuring Transport-Monitor Alert Types

You must configure the parameter ALERT_THRESHOLD for all alert types for r3montra, the transport monitor. All other parameters are optional. Note the general rules below on exclude and include parameters for r3montra.

Parameter Values

This section describes how the SPI for SAP interprets include and exclude parameter values for an alert type entry. the SPI for SAP compares values in different parameters using 'and;' the SPI for SAP compares values in the same parameter as follows.

- **Include:** Use 'or' to compare the parameters
- **Exclude:** Use 'and' to compare the parameters

The SPI for SAP evaluates *include* values before *exclude* values.

TRANS

TRANS is a time-frame based alert type for r3montra, the SPI for SAP's transport monitor. r3montra generates an alert if the number of failed or successful transport imports and exports exceeds a defined threshold. Note that the parameter USERNAME is mandatory for the TRANS alert type.

Table 58 on page 160 lists the parameters that you can use to configure the TRANS alert type and shows the value assigned to the parameters by default. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 58 TRANS Configuration Parameters

Parameter Name	Description	query conditions	Default Value
ALERT_THRESHOLD	The return code of the transport state above which	= Sign: I, E	I
		= Opt: GT, GE, LT, LE	GT
	an alert occurs for example, 4	= Low: ^a	4
	(warning).	= High:	
E_SUCCESS	Filtering option to include all successfully exported transports	= Sign: I, E	I
		= Opt: EQ	EQ
		= Low: ^b	X
		= High:	

Table 58 TRANS Configuration Parameters (cont'd)

Parameter Name	Description	query conditions	Default Value
E_FAILURE	Filtering option to	= Sign: I, E	I
	include all failed exported	= Opt: EQ	EQ
	transports	= Low: b	X
		= High:	
I_SUCCESS	Filtering option to	= Sign: I, E	I
	include all successfully	= Opt: EQ	EQ
	imported transports	= Low: b	X
		= High:	
I_FAILURE	Filtering option to	= Sign: I, E	I
	include all <i>failed</i> imported	= Opt: EQ	EQ
	transports	= Low ^b	X
		= High:	
USERNAME	The login name of	= Sign I, E	I
	the SAP NetWeaver user ^c .	= Opt: EQ,CP	EQ
	This parameter is mandatory.	= Low: <username></username>	ddic ^d
	manauoi y.	= High:	

- a. Specify as a number, otherwise the monitor ends with a dump
- b. Any entry other than the default is treated as space
- c. Since requests/tasks are user dependent, you can use it to restrict data.
- d. SAP user name for database-administration tasks

In The Default TRANS Configuration, an event generating an alert occurs if the threshold for imported or exported transports is greater than four (4). Note that the number "4" defined in the threshold for the parameter ALERT_THRESHOLD does not refer to the total number of imports it refers to the SAP return code associated with the import. In this example, transport imports with return codes of 4 (warning) and above (GT =4) would generate an alert. For more information about import return codes, refer to the SAP product documentation.

The Default TRANS Configuration

```
AlertMonFun =ALL =ALL =ALL =TRANSPORT =1\
=WARNING =Trans =R3_Transport\
=TRANS =I_FAILURE =I =EQ =X =\
=USERNAME =I =EQ =ITOUSER =\
=ALERT_THRESHOLD =I =GT =4 =
```

```
AlertMonFun =ALL =ALL =ALL =TRANSPORT =1\
=WARNING =Trans =R3_Transport\
=TRANS =I_SUCCESS =I =EQ =X =\
=USERNAME =I =EQ =ITOUSER =\
=ALERT_THRESHOLD =I =GE =4 =

AlertMonFun =ALL =ALL =ALL =ALL =TRANSPORT =1\
=WARNING =Trans =R3_Transport\
=TRANS =E_FAILURE =I =EQ =X =\
=USERNAME =I =EQ =ITOUSER =\
=ALERT_THRESHOLD =I =GT =4

AlertMonFun =ALL =ALL =ALL =TRANSPORT =1\
=WARNING =Trans =R3_Transport\
=TRANS =E_SUCCESS =I =EQ =X =\
=USERNAME =I =EQ =ITOUSER =\
=ALERT_THRESHOLD =I =GT = 4 =
```

REPAIR

REPAIR is a time-frame based alert type for r3montra, the SPI for SAP's Transport Monitor. r3montra generates an alert if the number of confirmed or unconfirmed repairs exceeds a specified threshold.

Table 59 on page 162 lists the parameters that you can use to configure the REPAIR alert type and shows the value assigned to the parameters by default. Note that the parameter ALERT_THRESHOLD is mandatory. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 59 REPAIR Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
R_CONFIRM	Filtering option to include all confirmed repairs.	= Sign: I, E	I
		= Opt: EQ	EQ
		= Low: ^a	X
		= High:	
to inc	Filtering option to include all unconfirmed	= Sign: I, E	I
		= Opt:	EQ
	repairs.	= Low: ^a	X
		= High:	
USERNAME	The login name of	= Sign I, E	I
the SAP NetWeaver u	NetWeaver user ^b .	= Opt: EQ,CP	EQ
	This parameter is	= Low: <username></username>	ddic ^c
mandatory.	= High:		

Table 59 REPAIR Configuration Parameters (cont'd)

Parameter Name	Description	Query Conditions	Default Value
ALERT_THRESHOLD	The number of	= Sign I, E	I
	the allowed repair state above which an alert occurs	= Opt: GT, GE, LT, LE	GT
		= Low: d	4
		= High:	

- a. Any entry other than the default is treated as space
- b. Since requests/tasks are user dependent, you can use it to restrict the data.
- c. SAP user name for database-administration tasks
- d. Specify the parameter as a number or the monitor ends with a dump

In The Default REPAIR Configuration, an event generating an alert occurs if the alert threshold of four (=GT =4) R_{ONFIRM} or $R_{UNCONFIR}$ errors is exceeded for the specified target System.

The Default REPAIR Configuration

```
AlertMonFun =ALL =ALL =ALL =TRANSPORT =1 \
=WARNING
          =Repair =R3 Transport \
=REPAIR =R CONFIRM =I =EQ =X = \
=ALERT THRESHOLD =I
                       =GT
AlertMonFun =ALL =ALL =ALL =TRANSPORT =1
=WARNING =Repair =R3 Transport \
=REPAIR =R UNCONFIR =I =EQ =X = \
=ALERT THRESHOLD =I
                       =GT
AlertMonFun =ALL =ALL =ALL =TRANSPORT =1 \
=WARNING
         =Repair =R3 Transport
=REPAIR =USERNAME =I =CP =* =\
=ALERT THRESHOLD =I
                    =GT = 4
```

RFCONNECT

RFCONNECT is a snapshot alert type for r3montra, the SPI for SAP's Transport Monitor. Snapshot alert types take a picture of the System at the moment the monitor runs. r3montra generates an alert if the number of RFC-connect errors to the target system exceeds the specified alert threshold.

Table 60 on page 164 lists the parameters that you can use to configure the RFCONNECT alert type and shows the value assigned to the parameters by default. Note that the parameter ALERT_THRESHOLD is mandatory. All other parameters are optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

 Table 60
 RFCONNECT Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
ALERT_THRESHOLD	Number of reconnect errors above which an alert occurs	= Sign I, E	I
		= Opt: GT, GE, LT, LE	GT
		= Low: ^a	4
		= High:	
system	System ID of the	G ,	I
	systems you are monitoring.	= Opt: EQ, CP	EQ
		= Low: <sid></sid>	, *,
		= High:	

a. Specify this parameter as a number; otherwise the monitor ends with a dump.

In The Default RFCONNECT Configuration, an event generating an alert occurs if the alert threshold of four RFC-connect errors is exceeded for the specified target system.

The Default RFCONNECT Configuration

```
AlertMonFun =ALL =ALL =ALL =TRANSPORT =1\
=WARNING =RfcConnect =R3_Transport\
=RFCCONNECT =CHECKSYSTEM =I =CP =* =\
=ALERT_THRESHOLD =I =GT =4 =
```

TPTEST

TPTEST is a snapshot alert type for r3montra, the SPI for SAP's Transport Monitor. Snapshot alert types take a picture of the System at the moment the monitor runs. r3montra generates an alert if the number of TPTEST errors to the target system exceeds a defined threshold.

Table 61 on page 165 lists the parameters that you can use to configure the TPTEST alert type and shows the value assigned to the parameters by default. Note that the parameter ALERT_THRESHOLD is mandatory. All other parameters are optional. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 61 TPTEST Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
ALERT_THRESHOLD	Number of TPTEST errors above which an alert occurs	= Sign I, E	I
		= Opt: GT, GE, LT, LE	GT
		= Low: a	4
		= High:	
CHECKSYSTEM	ID of the System which you are testing or monitoring.	= Sign: I, E	I
tes		= Opt: EQ, CP	EQ
		= Low: <sid></sid>	,,
		= High:	

a. Specify this parameter as a number; otherwise the monitor ends with a dump.

In The Default TPTEST Configuration, an event generating an alert occurs if the alert threshold of four TPTEST errors is exceeded for the specified target system.

The Default TPTEST Configuration

```
AlertMonFun =ALL =ALL =ALL =TRANSPORT =1\
=WARNING =TpTest =R3_Transport\
=TPTEST =CHECKSYSTEM =I =EQ =<SID> =\
=ALERT_THRESHOLD =I =GT =4 =
```

r3monupd: The Update Monitor

The update alert monitor identifies and reports the following update conditions:

- The update process is *in*active
- Update-process errors

r3monupd monitors the status of both active updates and updates that have been stopped by a SAP user or by the System. The alert monitor r3monupd references update errors and update status in SAP NetWeaver transaction **SM13**.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3monupd monitor is of type *snapshot*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The update monitor has the following alert types.

UPDATE_ACTIVE

Get information about the status of update processes and sends an alert if a process is not active

• UPDATE_ERRORS_EXIST

Get information about update processes that have errors.

File Locations

The r3monupd monitor uses the files listed in this table.

Table 62 r3monupd Files

File	Description
r3moncol(.exe)	Collector executable for the update monitor
r3monupd.cfg	Configuration file for the update monitor.
r3monupd.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monupd monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monupd monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Configuring Update-Monitor Alert Types

No parameters are used to configure alert types for r3monupd, the SPI for SAP's update monitor. You do not need to edit or customize the configuration file.

UPDATE ACTIVE

UPDATE_ACTIVE is an alert type for r3monupd, the SPI for SAP's Update Monitor. r3monupd generates an alert if the UPDATE task is inactive. The following example illustrates the default configuration for the UPDATE_ACTIVE alert type.

In The Default UPDATE_ACTIVE Configuration, an event generating an alert occurs if any update is stopped.

The Default UPDATE_ACTIVE Configuration

```
AlertMonFun =ALL =ALL =ALL =UPDATE =1\
=CRITICAL =UpdActive =R3 Update =UPDATE ACTIVE
```

UPDATE_ERRORS_EXIST

UPDATE_ERRORS_EXIST is an alert type for r3monupd, the SPI for SAP's Update Monitor. r3monupd generates an alert if any update errors exist. The following example illustrates the default configuration for the UPDATE_ERRORS_EXIST alert type.

In The Default UPDATE_ERRORS_EXIST Configuration on page 167, an event generating an alert occurs if any update error occurs.

The Default UPDATE ERRORS EXIST Configuration

```
AlertMonFun =ALL =ALL =ALL =UPDATE =1\
=CRITICAL =UpdError =R3 Update =UPDATE ERRORS EXIST
```

r3monusr: The SAP-User Monitor

The SAP-user alert monitor r3monusr identifies and reports the number of logged-in users. The check is performed for each application server. A very high number of users could indicate that performance problems might occur. The alert can then be used to decide whether it is necessary to ask or even force users to log out.

The alert monitor r3monusr references the SAP NetWeaver transaction SM04.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3monusr monitor is of type *snapshot*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The SAP-user monitor has only one alert type:

USER_LOGGEDIN_MAX

Define the maximum number of logged in users.

File Locations

The r3monusr monitor uses the files listed in this table.

Table 63 r3monusr Files

File	Description
r3moncol(.exe)	Collector executable for the user monitor
r3monusr.cfg	Configuration file for the user monitor.
r3monusr.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monusr monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monusr monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

USER LOGGEDIN MAX

USER_LOGGEDIN_MAX is an alert type for r3monusr, the SPI for SAP's SAP-user monitor. r3monusr generates an alert if the maximum number of SAP users exceeds a defined threshold. Table 64 on page 169 lists the parameters that you can use to configure the USER_LOGGEDIN_MAX alert type and shows the value assigned to the parameters by default. The configuration of the parameter MAX is mandatory.

The APSERVER parameter allows you to set the application-server-dependent monitors, r3monwpa, r3monwsr, and r3monoms to monitor a specific application server. You need to configure APSERVER in the following manner, where <hostname> is the name of the application server you are monitoring as it appears in the list of application servers displayed in transaction **sm51**:

```
=APSERVER =I =CP =<hostname> <SID> <Instance Number> =
```

We also recommend that you explicitly define the host name of the SAP NetWeaver central instance whose application server(s) you want to specify with APSERVER, as illustrated in Specifying an Application Server on page 151.

Specifying an Application Server

```
AlertMonFun =<Central_Inst_Hostname> =ALL =ALL =USER =1 \
=WARNING =Login =R3 WP \
```

```
=USER_LOGGEDIN_MAX =MAX =I =GT =30 = \
=APSERVER =I =CP =hpdev01 MP3 00 =
```

The remainder of this section describes the specific configuration requirements for this alert monitor. If you are unsure about the general configuration query rules which apply to all alert collector monitors, see Alert-Collector Monitor Query Conditions on page 102. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 64 USER_LOGGEDIN_MAX Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
APSERVER	Specifies the	= Sign: I, E	
	application server to	= Opt: CP	
monitor	= Low: <appserver_id></appserver_id>		
		= High:	
MAX The number of logged in users before an alert occurs. a	= Sign: I, E	I	
	= Opt: GT, GE	GT	
	occurs. ^a	= Low:	5
		= High:	

a. You must specify the parameter value as a number, otherwise the monitor ends with a dump.

In The Default USER_LOGGEDIN_MAX Configuration, an event generating an alert occurs if the number of users logged in exceeds thirty.

The Default USER_LOGGEDIN_MAX Configuration

```
AlertMonFun =ALL =ALL =ALL =USER =1\
=WARNING =Login =R3_User\
=USER LOGGEDIN MAX =MAX =I =GT =30 =
```

r3monwpa: The Work-Process Monitor

The work-process alert monitor r3monwpa references the SAP NetWeaver transaction **SM50** and reports the following conditions for work processes running on each of the application servers, which the SPI for SAP is monitoring:

- Reports the number of running work processes for each work-process type configured in the profile of the current operation mode
- Reports the number of *waiting* work processes for each work-process type configured in the profile of the current operation mode
- Compares the number of *active* work processes with the number of *configured* work processes (of the same work process type) in the profile of the current operation mode.
- Checks the status of the work processes, as follows:

— D (Debug)

No processes run on live systems

— P (Private)

Processes run using maximum available system resources.

— R (No Restart)

Failed processes do not restart, which means that dependent jobs also fail.

The work-process monitor r3monwpa can only monitor alerts from an enqueue work process that is part of a central instance; it cannot monitor the alerts from an enqueue work process belonging to a stand-alone enqueue server. To monitor stand-alone enqueue work processes, use the r3monal monitor to check for SAP CCMS alerts generated by the enqueue server. For more information about using r3monal to monitor a stand-alone enqueue server, see r3monal: Monitoring Stand-alone Enqueue Servers on page 63.

Note that, if you use standard SPI for SAP tools to configure r3moncol alert collectors, the SPI for SAP checks the validity of the new configuration and will not allow you to save a file, which contains configuration errors. For more information about the validation tool and the messages it generates when it encounters a problem, see Validating the Alert-Collector Configuration Files on page 112 and Understanding Configuration-File Error Messages on page 112.

Monitor Type

The r3monwpa monitor is of type *snapshot*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Alert Types

The work-process alert monitor has the following alert types.

WP AVAILABLE

The WP_AVAILABLE alert type defines alert conditions for the number of expected work processes running.

• WP_IDLE

The WP_IDLE alert type defines alert conditions for the number of idle work processes waiting.

• WP CHECK CONFIGURED

The WP_CHECK_CONFIGURED alert type defines alert conditions for comparing the actual number of running work processes with the number of configured work processes in the profile of the current operation mode. The monitor check only compares work processes of the same type.

WP STATUS

The WP_STATUS alert type defines alert conditions for work processes which the monitor finds in a problematic state, for example: D (Debug), P (Private) or R (No Restart).

File Locations

The r3monwpa monitor has the files listed in this table.

Table 65 r3monwpa Files

File	Description
r3moncol(.exe)	Collector executable for the WorkProcess monitor
r3monwpa.cfg	Configuration file for the WorkProcess monitor.
r3monwpa.log	Trace file for storing trace data.

The alert-collector monitors do not write history information to a specific history file. For more information, see Alert-Collector Monitor History on page 102.

Environment Variables

The r3monwpa monitor uses the environment variables described in Table 21 on page 105.

Command-Line Parameters

The r3monwpa monitor uses the command-line parameters described in Table 22 on page 106.

Remote Monitoring

For more information about configuring the alert-collector monitors to monitor another SAP System remotely, see Remote Monitoring with the Alert-Collector Monitors on page 106.

Configuring Work-Process Monitor Alert Types

This section helps you to configure alert types for r3monwpa, the SPI for SAP's work-process monitor. Note the general rules below concerning the use of the *exclude* and *include* parameter values; the rules are of particular importance for these alert types.

Parameter Values

This section describes how the SPI for SAP interprets *include* and *exclude* parameter values for an alert type entry. The SPI for SAP compares values in *different* parameters using 'and'; the SPI for SAP compares values in the *same* parameter as follows.

- **Include:** use 'or' to compare the parameters
- **Exclude:** use 'and' to compare the parameters

The SPI for SAP evaluates include values before exclude values, as shown in the Table 66.

Table 66 Comparing Include and Exclude Conditions for the Same Parameter

Select Options	Alert Type: WP_AVAILABLE Example Configuration of Select Options	Comparison
1	=DIA =I =BT =50 =100 =OPMODE =I =CP =DAY	OR
2	=DIA =I =GT =5 =OPMODE =I =CP =NIGHT	OR
3	=DIA = E =LT =60	AND

WP AVAILABLE

WP_AVAILABLE is an alert type for r3monwpa, the SPI for SAP's work-process monitor. r3monwpa generates an alert if the number of running work processes for each, selected work-process type is outside the specified maximum (or minimum) threshold.

Table 67 on page 173 lists the parameters that you can use to configure the WP_AVAILABLE alert type and shows the value assigned to the parameters by default. The configuration of the parameters listed for the WP_AVAILABLE alert type is mandatory. You must specify all threshold parameters as a number otherwise the monitor ends with a dump.

The APSERVER parameter allows you to set the application-server- dependent monitors, r3monwpa, r3monwsr, and r3monoms to monitor a specific application server. You need to configure APSERVER in the following manner, where <hostname> is the name of the application server to monitor as it appears in the list of application servers displayed in transaction SM51:

```
=APSERVER =I =CP =<hostname> <SID> <Instance Number> =
```

We also recommend that you explicitly define the host name of the SAP NetWeaver central instance whose application server(s) you want to specify with APSERVER, as illustrated in the Specifying an Application Server.

Specifying an Application Server

```
AlertMonFun =<Centr_Instance_Hostname> =ALL =ALL =WP =1 \
=WARNING =Availability =R3_WP \
=WP_AVAILABLE =DIA =I =GT =50 = \
=APSERVER =I =CP =hpdev01 MP3 00 =
```

The remainder of this section describes the specific configuration requirements for this alert monitor. If you are unsure about the general configuration query rules which apply to all alert collector monitors, see Alert-Collector Monitor Query Conditions on page 102. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 67 WP_AVAILABLE Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
APSERVER	to monitor	= Sign: I, E	
		= Opt: CP	
		= Low : <appserver_id></appserver_id>	
		= High:	
BTC	Threshold for batch work	= Sign: I, E	
	processes	= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
DIA	Threshold for dialog work	= Sign: I, E	
	processes	= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
ENQ	Threshold for enqueue work processes	= Sign: I, E	
		= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
OPMODE	Defines the operation mode for this parameter ^a	= Sign I, E	I
		= Opt: CP, EQ	EQ
		= Low: <operation_ mode=""></operation_>	current
		= High:	
SPO	Threshold for spool work	= Sign: I, E	GE, LT, LE mber> GE, LT, LE mber> I EQ eration_ mode> current GE, LT, LE
	processes	= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	

Table 67 WP_AVAILABLE Configuration Parameters (cont'd)

Parameter Name	Description	Query Conditions	Default Value
UPD	Threshold for update work processes	= Sign: I, E	, <u> </u>
		= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
UP2	Threshold for update2 work	= Sign: I, E	
	processes	= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	

a. A critical alert occurs if you specify a non-existent mode.

In The Default WP_AVAILABLE Configuration, an event generating an alert occurs if the number of available Dialog work processes is less than fifty.

The Default WP_AVAILABLE Configuration

```
AlertMonFun =ALL =ALL =ALL =WP =1\
=WARNING =Availability =R3_WP\
=WP AVAILABLE =DIA =I =LT =50 =
```



Check that the work-process types you want to monitor with r3monwpa are correctly configured in the SAP instance profile.

The r3monwpa monitor can only monitor work-process types that are configured in the SAP instance profile. If the DIA work-process type is not configured in the SAP instance profile (or "rdisp/wp_no_dia = 0"), then no DIA work processes are started. Since zero (0) DIA work processes is clearly less than the minimum allowed (50) specified in the default configuration for the WP_AVAILABLE alert type shown in The Default WP_AVAILABLE Configuration, this would, under normal circumstances, generate an alert.

However, if the DIA work-process type is not configured in the SAP instance profile, r3monwpa cannot monitor the number of DIA work processes that are running at any given point in time and, as a consequence, does not generate an alert. You can check discrepancies between the SAP instance profile and the r3monwpa configuration file with the alert type WP_CHECK_CONFIGURED on page 177.

WP_IDLE

WP_IDLE is an alert type for r3monwpa, the SPI for SAP's work-process monitor. r3monwpa generates an alert if the number of waiting work processes for each, selected work-process type is outside the specified max (or min) threshold.

Table 68 on page 175 lists the parameters that you can use to configure the WP_IDLE alert type and shows the value assigned to the parameters by default. The configuration of the parameters for the WP_IDLE alert type is mandatory. You must specify all threshold parameters as a number otherwise the monitor ends with a dump.

The APSERVER parameter allows you to set the application-server- dependent monitors, r3monwpa, r3monwsr, and r3monoms to monitor a specific application server. You need to configure APSERVER in the following manner, where <hostname> is the name of the application server to monitor as it appears in the list of application servers displayed in transaction SM51:

```
=APSERVER =I =CP =<hostname> <SID> <Instance Number> =
```

It is also recommended to define explicitly the host name of the SAP NetWeaver central instance whose application servers you want to specify with APSERVER, as illustrated in the Specifying an Application Server.

Specifying an Application Server

```
AlertMonFun =<Centr_Instance_Hostname> =ALL =ALL =ALL =WP =1 \
=WARNING =Idle =R3_WP \
=WP_IDLE =BTC =I =GT =20 = \
=APSERVER =I =CP =hpdev01 MP3 00 =
```

If you are unsure about the general configuration query rules which apply to all alert collector monitors, see Alert-Collector Monitor Query Conditions on page 102. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 68 WP_IDLE Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
APSERVER	specifies an application server to monitor	= Sign: I, E	
		= Opt: CP	
		= Low : <appserver_id></appserver_id>	
		= High:	
BTC	Threshold for batch work	= Sign: I, E	
	processes	= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
DIA	Threshold for dialog work	= Sign: I, E	
	processes	= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
ENQ	Threshold for enqueue work	= Sign: I, E	
	processes	= Opt: GT, GE, LT, LE	
		= Low:	
		= High:	

Table 68 WP_IDLE Configuration Parameters (cont'd)

Parameter Name	Description	Query Conditions	Default Value
OPMODE	Defines the operation mode for this parameter. ^a	= Sign I, E	I
		= Opt: CP, EQ	EQ
		= Low: <operation_mode></operation_mode>	current
		= High:	
SPO	Threshold for spool work processes	= Sign: I, E	
		= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
UPD	Threshold for update work processes	= Sign: I, E	
		= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	
UP2	Threshold for update 2 work processes	= Sign: I, E	
		= Opt: GT, GE, LT, LE	
		= Low: <number></number>	
		= High:	

a. If a non-existent mode is specified, a critical alert occurs.

In The Default WP_IDLE Configuration, an event generating an alert occurs if the number of idle Dialog work processes is less than ten.

The Default WP_IDLE Configuration

```
AlertMonFun =ALL =ALL =ALL =ALL =WP =1\
=WARNING =Idle =R3_WP\
=WP IDLE =DIA =I =LT =10 =
```



Check that the work-process types you want to monitor with r3monwpa are correctly configured in the SAP instance profile.

The r3monwpa monitor can only monitor work-process types that are configured in the SAP instance profile. If the DIA work-process type is not configured in the SAP instance profile (or "rdisp/wp_no_dia = 0"), then no DIA work processes are started. Since zero (0) DIA work processes is clearly less than the minimum allowed (10) specified in the default configuration for the WP_IDLE alert type shown in The Default WP_IDLE Configuration, this would, under normal circumstances, generate an alert.

However, if the DIA work-process type is not configured in the SAP instance profile, r3monwpa cannot monitor the number of DIA work processes that are running at any given point in time and, as a consequence, does not generate an alert. You can check discrepancies between the SAP instance profile and the r3monwpa configuration file with the alert type WP_CHECK_CONFIGURED on page 177.

WP_CHECK_CONFIGURED

WP_CHECK_CONFIGURED is an alert type for r3monwpa, the SPI for SAP's work-process monitor. The WP_CHECK_CONFIGURED alert type makes a comparison between the actual number of running work processes and the number of configured work processes in the profile of the current operation mode. Note that the monitor only compares work processes of the same type, for example: DIA, BTC. Table 69 on page 177 lists the parameters that you can use to configure the WP_CHECK_CONFIGURED alert type and shows the value assigned to the parameters by default.

The APSERVER parameter allows you to set the monitors, r3monwpa, r3monusr, and r3monoms to monitor a specific application server. You need to configure APSERVER in the following manner, where <hostname> is the name of the application server to monitor as it appears in the list of application servers displayed in transaction SM51:

```
=APSERVER =I =CP =<hostname>_<SID>_<Instance_Number> =
```

We also recommend that you explicitly define the host name of the SAP NetWeaver central instance whose application server(s) you want to specify with APSERVER, as illustrated in the Specifying an Application Server.

Specifying an Application Server

```
AlertMonFun =<Centr_Instance_Hostname> =ALL =ALL =WP =1 \
=WARNING =Check =R3_WP \
=WP_CHECK_CONFIGURED \
=APSERVER =I =CP =hpdev01 MP3 00 =
```

If you are unsure about the general configuration query rules which apply to all alert collector monitors, see Alert-Collector Monitor Query Conditions on page 102. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 69 WP CHECK CONFIGURED Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
APSERVER	specifies an application server to monitor = Sign: I, E = Opt: CP = Low: <appserver_id></appserver_id>	= Sign: I, E	
		= Low: <appserver_id></appserver_id>	
		= High:	

In Default WP_CHECK_CONFIGURED Configuration, r3monwpa generates an alert if the number of running work processes does not match the number of configured work processes for a given work-process type.

Default WP_CHECK_CONFIGURED Configuration

```
AlertMonFun =ALL =ALL =ALL =WP =1\
=WARNING =Check =R3_WP\
=WP_CHECK_CONFIGURED \
=APSERVER =I =CP =ALL =
```

WP_STATUS

WP_STATUS is an alert type for r3monwpa, the SPI for SAP's work-process monitor. WP_STATUS defines alert conditions for work processes which the monitor finds in a problematic state, for example: D (Debug), P (Private), or R (No Restart). r3monwpa generates an alert if the work processes running in the SAP Systems you are monitoring with the SPI for SAP match the conditions defined in the parameters below. The configuration of the parameter below is optional.

The APSERVER parameter allows you to set the application-server- dependent monitors, r3monwpa, r3monwsr, and r3monoms to monitor a specific application server. You need to configure APSERVER in the following manner, where <hostname> is the name of the application server to monitor as it appears in the list of application servers displayed in transaction SM51:

```
=APSERVER =I =CP =<hostname> <SID> <Instance Number> =
```

We also recommend that you explicitly define the host name of the SAP NetWeaver central instance whose application server(s) you want to specify with APSERVER, as illustrated in the Specifying an Application Server.

Specifying an Application Server

```
AlertMonFun =<Centr_Instance_Hostname> =ALL =ALL =WP =1 \
=WARNING =WP_Status =R3_WP \
=WP_STATUS =STATUS =I =GT =30 = \
=APSERVER =I =CP =hpdev01 MP3 00 =
```

If you are unsure about the general configuration query rules which apply to all alert collector monitors, see Alert-Collector Monitor Query Conditions on page 102. For more information about the meaning of the query conditions in the alert-collector monitor configuration files, see Table 19 on page 104.

Table 70 Configuration Parameters

Parameter Name	Description	Query Conditions	Default Value
APSERVER	monitor = O = Lo	= Sign: I, E	
		= Opt: CP	
		= Low: <appserver_id></appserver_id>	
		= High:	
STATUS ^a	The status which is monitored	= Sign: I, E	
		= Opt:	
		= Low: b	
		= High:	

a. Possible additional values: MAX_ENTRIES

b. Possible values: D=Debug, P=Private, R=Restart (no alert).

In The Default WP_STATUS Configuration, an event generating an alert occurs if the status of a running workprocess is *critical*. The Default WP_STATUS Configuration also shows how you can use =MAX_ENTRIES to define the number of work processes with a defined status that have to exist before the SPI for SAP generates a message.

The Default WP_STATUS Configuration

```
AlertMonFun =ALL =ALL =ALL =WP =1\
=CRITICAL =WP_Status =R3_WP\
=WP_STATUS =STATUS =I =CP =* =
```

Monitoring the TemSe file

To save runtime costs, the SPI for SAP monitors the consistency of SAP's Temporary Sequential file (TemSe) not by means of one of the SPI for SAP alert monitors, but by means of a report you set up in SAP. However, you still need to assign the SPI for SAP r3monaco monitor to the managed nodes.

Monitor Type

The TemSe monitor is of type *snapshot*. One monitor run gathers only one value set. For more information, see Report Types for the Alert-Collector Monitors on page 101.

Report Description

The TemSe report references the SAP NetWeaver transaction **SP12**. Any inconsistency found in the TEMSE database is serious; you must use the log in **SP12** to correct the cause of the inconsistency, for example a disk failure.

Running the TemSe Monitor

To run the TemSe monitor, you need to set up a job in SAP NetWeaver which references a report named /HPOV/ZHPSPIT1. Note that you can only use the report with SAP version 4.6 and later.

To set up the report:

- Login to SAP NetWeaver.
- 2 Set up a job using transaction SM36.
- 3 In the job, specify the following details:
 - the date on which the report should start
 - the frequency with which the report should run

5 Understanding Message Flow

This section describes how to use HPOM for Windows functionality and CCMS to control the flow of messages between SAP NetWeaver and HPOM for Windows. The information in this section describes how to control message flow between SAP NetWeaver and HPOM for Windows and includes the following topics:

- HPOM Message Customization on page 181
 Customize HPOM for Windows message policy conditions.
- Customizing CCMS Message Flow in SAP on page 183
 Use SAP NetWeaver features to control how CCMS alert monitors generate specific messages.
- SAP Solution-Manager Integration on page 187

Use the r3ovo2ccms command to write HPOM for Windows messages directly into the CCMS tree, where they can be viewed and used by the SAP Solution Manager in the same way as any other SAP message alert. You can also use r3monal to forward messages directly from CCMS to HPOM for Windows.

Monitoring CCMS Alerts in the CEN on page 194
 Monitor alerts and analyze data collected by the SAP central monitoring system (CEN).

The methods for setting thresholds in the CCMS monitor do not apply if you are using the new CCMS monitoring architecture, where thresholds can be set globally within SAP NetWeaver.

For details about the procedures outlined in these sections, refer to your SAP NetWeaver documentation and to the manuals supplied with HPOM for Windows.

HPOM Message Customization

With the aid of standard HPOM for Windows functionality, you can modify important aspects of the messages generated by the SPI for SAP monitors and in addition, specify which of the generated messages you want to be displayed. This section provides information about the following tasks:

Setting up message views

Use message filters to set up views that show you only those messages which fit specified criteria, for example, messages with the severity level "critical". For more information, see Setting Up the Message Filters on page 182.

Changing severity levels

Change the severity level of messages. For more information, see Changing the Message Severity on page 183.

Suppressing messages

Suppress specific messages by setting a suppress condition in the opens template. For more information, see the HP Operations Manager Smart Plug-in for SAP Configuration Guide for Windows.

Setting Up the Message Filters

By default, the HPOM for Windows console displays *active* messages generated on your managed nodes. However, you can modify the number and type of messages that are displayed so that only the most important messages appear. For example, you can filter messages by using any one or combination of the following criteria:

Application:

Filter messages according to the *application* message attribute, that is: the application responsible for sending the message

Message text:

Filter messages containing specific text

• Object:

Filter messages according to the *object* message attribute that is: the HPOM for Windows object responsible for sending the message

Ownership:

Filter messages according to message ownership

• Severity:

Filter messages according to the selected severity

• Time:


Filter messages created at/before/since particular dates and times

Unmatched:

Filter messages that either do or do not match any of the message conditions or suppressed conditions defined in the policies deployed on the managed nodes.

Using message filters, you can set up simple or complex views which display specific messages. For example, if you want to display messages with a severity level of critical, you can define a filter that prevents HPOM for Windows displaying messages with all other severity levels.

Figure 10 Applying Message Filters



To define your customized message filter:

1 Select the managed node.

In the HPOM for Windows console, locate and right-click the managed node whose messages you want to filter, and select the following option from the menu that pops up:

Configure > Message Filter

2 Create a new message filter.

In the Apply Message Filter window which appears, click **New...**. The Filter Properties window appears.

3 Define the new message filter.

Use the Filter Properties window to define the filtering patterns to use. For example, if you want to filter the messages to display on the basis of message severity, use the Severity field in the General property sheet.

Click **OK** to save your filtering pattern(s).

4 Save and apply the filter.

In the Apply Message Filter window, click Apply Filter, and then click Close.

Changing the Message Severity

To change the severity of specific SAP NetWeaver-generated messages in the HPOM for Windows console:

- 1 Log on to HPOM for Windows as administrator.
- 2 In the details pane, locate and right-click the message whose severity attribute you want to change, and select the following option from the menu which pops up:

Change Severity >

3 Select the severity level you want from the pop-up menu, for example, Major. The message severity is immediately updated in the active-messages browser.



The user who changes a message's severity automatically becomes the message's owner: message ownership is indicated by a flag in the **S** column in the HPOM for Windows console.

Customizing CCMS Message Flow in SAP

SAP CCMS provides a range of features enabling you to allow or prevent the inclusion of specific messages in its alert monitor. This section includes information about the following topics:

- Disabling Messages on page 184
- Setting Thresholds for SAP CCMS Alert Monitor Messages on page 185
- Obtaining a Message ID from the SAP NetWeaver Syslog File on page 186

Disabling Messages

To disable messages in SAP NetWeaver:

1 Browse to the following location using the SAP Easy-Access menu:

Tools > CCMS > Control/Monitoring > Control Panel


Alternatively, enter the following transaction code in the command field: RZ03

- 2 Select Edit > Choose.
- 3 Select your SAP instance.
- 4 Click the Alert Monitor button in the menu bar to display the CCMS alert-monitor dialog. Alternatively, enter the following transaction code in the command field: RZ20
- 5 Select the following menu items from the SAP NetWeaver menu bar:

Extras > activate maintenance function

6 In the list of monitors displayed, select the node or monitor-tree element whose messages you want to disable, for example: short- dump messages.

Figure 11 Deactivate Monitor Messages



- 7 To disable, for example, short-dump messages from the R3Abap monitor:
 - Click: SAP CCMS Technical Expert Monitors -> System / All monitoring segments / all monitoring contexts -> SAP_CCMS_<host>_<SID>_<Instance number> ->
 Host>_<SID>_<Instance number> -> R3Abap
 - b In the SAP NetWeaver menu bar, select the following menu items:

Edit > Nodes(MTE) > Deactivate

The selected item and the suppressed message type are now marked as "deactivated" in the SAP GUI.

- 8 Save your settings and return to the CCMS Monitor Sets screen.
- 9 Check the HPOM for Windows console. You should not receive any more short-dump messages.
- Since disabling messages will result in inconsistencies with the settings previously defined in the SPI for SAP configuration file, you must only perform this operation if you do *not* want to have a central configuration.

Setting Thresholds for SAP CCMS Alert Monitor Messages

To set thresholds for SAP NetWeaver CCMS alert monitor messages:

Browse to the following location using the SAP Easy-Access menu:

Tools > CCMS > Control/Monitoring > Control Panel

- Alternatively, enter the following transaction code in the command field: RZ03
- 2 Select the SAP NetWeaver instance (under Server name) for which you want to define a performance limit value.
 - Click the Alert Monitor button in the menu bar to display the CCMS alert-monitor dialog. Alternatively, enter the following transaction code in the command field: RZ20
- Browse to the CCMS monitor set which contains the monitor whose alert thresholds you want to modify:

SAP CCMS Technical Expert Monitors > System / All monitoring segments / all monitoring contexts

- 4 To display alert details for a selected monitor:
 - a Click Open alerts in the tool bar.
 - b Click Display alerts in the tool bar.
 - Note that you can display alerts for a desired SAP instance or for all monitored instances.
 - Select the alert whose details you want to display and click **Properties** in the tool bar.
- 5 Click the **Performance Attribute** tab to display the threshold values for the selected CCMS alert.
- 6 Click the **Display/Change** button (or the keyboard combination Shift+F6) and enter edit mode and change the threshold values as appropriate.
- 7 Save the changes to the threshold values; click the **Save** button in the menu bar, or use the following menu option:

Properties > Save

When the new threshold is reached, the SPI for SAP sends a warning or a critical Dialog Performance message (similar to Figure 12).

Monitoring: Properties and Methods G11\sodom_G11_00\R3Services\Dialog\FrontendResponseTime Properties of MTE class R3DialogFrontendResponseTime PerformanceAttribute Methods Addnl info Performance properties assigned from group R3DialogFrontendResponseTime Comparison Value Last reported value O Smoothing over last 1 min. O Smoothing over last 5 min. Average in the last hour O Average in the last quarter of an hour Smoothing over last 15 mins Threshold values Change from GREEN to YELLOW msec Change from YELLOW to RED 3.000 msec 2.000 Reset from RED to YELLOW msec Reset from YELLOW to GREEN 1.000 msec Alert is triggered if the comparative value falls below threshold value exceeds the threshold value Alert text Message class 257 Message number &1 &3 > &2 &3 Frontend response time exceeds threshold (&4 dialog steps)

Figure 12 Performance Alert Thresholds

Obtaining a Message ID from the SAP NetWeaver Syslog File

Any messages recorded in the SAP NetWeaver system log file can be defined to trigger an alert in CCMS. This alert can be picked up and used to display an associated message in the HPOM for Windows console with instructions for any appropriate actions, which are required.

To obtain the message ID of a critical message:

1 Browse to the following location using the SAP Easy-Access menu to read the system log file:

Tools > Administration > Monitor > System Log



Alternatively, you can enter the following transaction code into the SAP NetWeaver command field: **SM21**

2 Double-click System Log to display system-log details in the System Log:Local Analysis screen.

You can apply time restrictions to limit the contents of the syslog file to the currently relevant entries.

3 Click Reread System Log to display the system log file of your SAP NetWeaver system.

- 4 Double-click the message that you want to use to trigger an alert. The system displays details of the selected message.
- Make note of the message ID including group (for example: AB) and number (for example: 0); AB0 indicates a run-time error (RFC_NO_AUTHORITY).
- To display the ID numbers of all SAP NetWeaver syslog messages, enter the transaction code **SE92** into the SAP NetWeaver command field and click **All numbers**.
- 7 Use the ID number to set up a filter in the SPI for SAP r3monal.cfg configuration file, for example:

```
# Syslog filtering
#------
# Alert Classes SAP SAP SyslogId Enabled=1
# System Number From To Disabled=0
AlerMonSyslog =ALL =ALL =ABO =AB1 =1
```

SAP Solution-Manager Integration

The information in this section explains how you can set up the SPI for SAP to enable bi-directional communication between the SAP Solution Manager and HPOM for Windows. With the SPI for SAP's Solution-Manager integration, you can configure the SPI for SAP to inform HPOM for Windows when a Solution Manager business process fails: you can also set up the SPI for SAP in such a way as to enable it to populate the CCMS tree with managed objects from HPOM for Windows, for example, by means of an automatic or operator-initiated action attached to a message condition in a policy. The information in this section is split into the following topics:

- Pre-requisites on page 187
- Integration Overview on page 188
- Sending Messages from SAP to HPOM on page 189
- Sending Messages from HPOM to SAP on page 190
- The r3ovo2ccms Command on page 192

Pre-requisites

If you want to take advantage of the SPI for SAP's Solution-manager integration, note that the target system, that is; the SAP server to which the SPI for SAP writes the CCMS alerts, must meet the following pre-requisites:

- Satellite Systems that are monitored by the Solution Manager must have SAP Version 4.6 or higher
- The SPI for SAP supports the BC-XMW interface for 6.40 of the SAP BASIS package.
 - Release 6.40:


The BC-XMW interface is available and fully supported with the initial support package; no additional support packages are required.

Have a look at SAP notes 645353 and 608384, too.

Integration Overview

The SPI for SAP's Solution-manager integration uses the CCMS XMW and XAL interfaces to improve communication between SAP and HPOM for Windows. Using the CCMS interfaces, the SPI for SAP ensures that the power of both SAP and HPOM for Windows can be used to enhance and improve the information available to system administrators in both areas.

Figure 13 Choosing CCMS Alerts to Monitor



For example, you can now configure the SPI for SAP to write directly to CCMS and populate the CCMS tree with messages and alerts, which are discovered by HPOM for Windows and relate to problems not normally of particular interest to SAP, such as hardware and network performance. Conversely, Figure 13 on page 188 shows how you can use the Solution-manager integration to monitor specific CCMS alerts and, by linking the generated HPOM for Windows messages to a defined service ID, monitor the status of specific services. In this way, it is possible to ensure not only that HPOM for Windows knows as soon as a Solution-manager business process fails but also that the status of the service associated with the business process you are monitoring is immediately reflected in the service map in the HP Service Navigator.

To summarize how the SPI for SAP's Solution-manager integration enhances communication in both directions between SAP and HPOM for Windows:

SAP -> HPOM for Windows

By defining message conditions for r3monal, the SPI for SAP's CCMS alert monitor, you can keep an eye on specific CCMS alerts, for example, the alerts you have assigned to Business Processes. For more information about setting up r3monal, the CCMS alert monitor, see Sending Messages from SAP to HPOM on page 189.

HPOM for Windows -> SAP

You can attach an action to an HPOM for Windows message condition, which calls the r3ovo2ccms command and uses it to populate the CCMS tree with messages and objects monitored by HPOM for Windows. For more information about using the r3ovo2ccms command, see The r3ovo2ccms Command on page 192.

Sending Messages from SAP to HPOM

By defining message conditions for r3monal, the SPI for SAP's CCMS alert monitor, you can keep an eye on specific alerts in the CCMS tree. When the message condition for the specified CCMS alert matches, you can associate the HPOM for Windows message the condition generates with a known Service ID and, in this way, link the message directly to a service in the HPOM for Windows service tree. For more information about setting up r3monal, the CCMS alert monitor, see r3monal: the CCMS 4.x Alert Monitor on page 51.

To set up communication between the SAP Solution Manager and HPOM for Windows, you need to carry out the following high-level steps:

- In SAP, open up the CCMS alert tree for the Solution-manager business process which you want to monitor.
- 2 Expand the CCMS alert tree and browse to the alerts associated with individual steps in the selected business process.




If CCMS alerts are not already assigned to individual steps in the business process you want to monitor, you will have to use SAP to locate the CCMS monitor which generates the alerts you require (transaction RZ20) and then assign the alert(s) to the business-process step.

- 3 Assign the desired CCMS alert(s) to the step in the business process, which you want to link to service objects in HPOM for Windows.
- 4 If you want to link the HPOM for Windows messages to services in HPOM for Windows, you will need to assign a service ID at this point, too. The service ID must match the service name defined in the service-configuration file and take the following form:

SAP SPI:<SID>:<service instance name>

5 Remember to (re)deploy the SPI for SAP opcmsg policy with the new (or modified) conditions.

Figure 14 Linking Messages to Service IDs



Sending Messages from HPOM to SAP

The first and most important thing you need to do is to inform HPOM for Windows which of the incoming HPOM for Windows messages it should forward to SAP and write into the CCMS tree. The message-forwarding task is triggered by means of an action attached to the policy rule, which generates the original message. The action you configure can be either automatic or operator-initiated. For more information about the command you use and the parameters and options that are allowed, see The r3ovo2ccms Command on page 192.

To set up an automatic action in an HPOM for Windows policy, follow the instructions below. Note that the names and titles of the windows, tabs, and property sheets can sometimes vary according to the type of policy you select. The example described here uses a performance-threshold policy.

- In the console tree, locate and double-click the policy which generates the HPOM for Windows message you want to forward to SAP and write into the CCMS tree. In this example, we have chosen a performance monitor monitoring CPU load on the SAP server.
- 2 In the Measurement-threshold window which appears, click the **Threshold Levels** tab.
- 3 In the Threshold-levels tab, locate and double-click the rule which generates the message you want to forward to SAP. Note that you do not need to forward all messages. For example; the rule which generates a critical message is probably of more interest than the rules which generate messages with severity "warning" or "normal".
- 4 In the Threshold-level window which appears, click the **Start Actions** tab.
- 5 In the Start Actions window, click the **Automatic Action** button.
- 6 In the Automatic Action window which appears, enter the r3ovo2ccms command in the command box along with the parameters and options you need to perform the desired action, including the location in the CCMS tree, where you want the message to appear. If the location you specify in the CCMS tree does not already exist, r3ovo2ccms creates it for you when it forwards the message to SAP. The default name for the root HPOM for Windows monitor tree is ZSAPSPI. Note that provided you do not alter the default settings, you do not need to supply an absolute path with the command. For more information about the r3ovo2ccms command, see The r3ovo2ccms Command on page 192.

The Node text box defines the name of the node where the policy you are modifying is deployed and the r3ovo2ccms command runs. If you use the \$MSG_NODE_NAME variable in conjunction with the -host option in the Command text box, the SPI for SAP assumes the name of the node associated with the original message. Assuming the RemoteMonitoring feature is enabled, this is true even for nodes, which the SPI for SAP is monitoring remotely.

Figure 15 Configuring an Automatic Action



- 7 The CCMS alert (Monitor-tree element or MTE) that r3ovo2ccms writes to the CCMS monitor tree must be assigned to a specific step in the business process, for example; "Create Invoice", which you have defined in SAP Solution Manager.
 - a In SAP, enter the following transaction: /dswp
 The /dswp transaction displays the following page:

Change Mode: Setup Business Process Monitoring

- b Select the process step to which you want to assign the HPOM for Windows alert
- c Manually enter the name of the CCMS monitor, which you want to assign to the business-process step.
- The name of the monitor element that you enter must match the entry created by the r3ovo2ccms command, as it appears in the CCMS monitor tree. You do *not* need to include either the monitor context (ZSAPSPI) or the name of the CCMS Monitor *Set*, to which the monitor belongs.
- 8 Next, you need to create a CCMS monitor set, for example; HPOM, and generate a CCMS monitor, for example; SAPSPI, to host the alerts sent by the r3ovo2ccms command and make them visible to SAP users.
 - Then you can select the new monitor and, using the Change button, display a list of the CCMS alerts and alert groups, which you want to associate with the new monitor (SAPSPI) to make them visible to the Solution Manager. Scroll down the list of contexts displayed and select "ZSAPSPI".
 - The context ZSAPSPI is only visible for selection in the list of contexts displayed after the first HPOM for Windows message sent by the r3ovo2ccms command appears in the CCMS tree.

SAP Session components Edit Goto System Help **@** Change Mode: Setup Business Process Monitoring - jose BPM example HTML document Word document Attachments @ Business Process Monitoring • Other CCMS Monitor Solution Support Organiz • Business Processes Standard Sales Order F C Notifications √ (1) Create standard
 ←
 →
 Image: Ima Q (2) Create cash sal (17) Mail notification ✓ Other CCMS M. Analysis & Mon ✓ Monitoring Activ MTE (Monitoring Tree Element MTE GREEN t YELLOW RED to Y YELLOW Alert name C Notifications OVOMessages G11\0V0\...\mail\exchange Generate Monitorin Local RFC Destination for C Data Collection Frequenci Change Mode: Setup Business Process Monitoring - jose BPM example 🗵 G11\0\0\...\mail\exchange Li 1. Co 1 Ln 1 - Ln 1 of 1 lines 4 b 4 b **√** × 4 b 4 F ☑ G11 (1) 100 🖪 sodom OVR

Figure 16 Assigning CCMS MTEs to Business Process Steps

The r3ovo2ccms Command

The mechanism which the SPI for SAP uses to forward HPOM for Windows messages to SAP and write them directly into the CCMS tree is the r3ovo2ccms command, which the SPI for SAP installs in the default HPOM for Windows actions directory on the HPOM for Windows managed node.

You can use the r3ovo2ccms command directly on the command line or start it either automatically (as an automatic action) or manually (as an operator-initiated action). If you want to use the r3ovo2ccms command in a configured action, you need to modify each policy that generates an HPOM for Windows message, which you want to forward to CCMS. The SPI for SAP uses the configured action to forward the HPOM for Windows message to SAP, where it will appear in the CCMS tree in the location defined by the parameters and options you specify.

The r30v02ccms command accepts the following parameters and parameter options, which are displayed in the command shell if no parameters are specified:

 $r3ovo2ccms \ -level1_element < level1_element > -level2_element < level2_element > -text < text > -host < SAP_hostname > [-root_element < root element >] \ [-sid < SID >] \ [-number < SAP_instance_number >] \ [-severity < NORMAL | WARNING | CRITICAL >]$

Command Parameters

The r3ovo2ccms command accepts the following command parameters:

-level1 element <level1 element>

This parameter identifies first-level branch in the CCMS tree structure

-level2 element <level2 element>

This parameter identifies the second-level branch in the CCMS tree structure

-text <text>

Descriptive text explaining the event/problem in more details.

-host <SAP hostname>

The name of the SAP System on which the event/problem was originally detected by HPOM for Windows.

Optional Parameters

The following optional parameters can be used with the r3ovo2ccms command:

• -root element <root element>

The name of the root element of the branch of the CCMS tree into which you want to insert the message. The default value is "ZSAPSPI".

-sid <SID>

The System ID (SID) of the SAP System, where the original event/problem was detected when found by HPOM for Windows.

-number <SAP instance number>

The instance number of the SAP System, where the original event/problem was detected by HPOM for Windows.

-severity <NORMAL|WARNING|CRITICAL>

The severity of the CCMS alert message. The default value is "CRITICAL"

Examples

The following example shows how you can use the r3ovo2ccms command to forward to SAP an HPOM for Windows message relating to a problem with CPU load on the SAP server "example" and write it directly into a defined location in the CCMS tree. You can configure the HPOM for Windows policy which generates the message to execute the command either automatically by means of an automatic action or manually by means of an operator-initiated action.

Writing HPOM for Windows Messages into the CCMS Tree

```
r3ovo2ccms -root_element -level1_element Performance -level2_element CPU -text "CPU load: bottleneck situation 90%" -host example
```

In the example above, the HPOM for Windows message will appear in the **HPOM** > **Performance** > **CPU** branch of the SAP CCMS tree when a critical problem with the CPU load occurs and is reported by the SPI for SAP. The problem to which the message relates was originally reported on the SAP server, "example".

Monitoring CCMS Alerts in the CEN

If your SAP landscape includes multiple systems and numerous instances, you can reduce management overheads by using the SAP Computing Center Management System (CCMS) to monitor the entire landscape from one system, which SAP calls the central monitoring system (CEN), and then configuring the SPI for SAP to monitor the CEN. The SPI for SAP can then map alerts identified in the CCMS subsystem to messages that it sends to the HPOM for Windows console.

This section provides a brief overview of the things you need to look out for when considering the idea of using the SPI for SAP to monitor CCMS alerts in a SAP central monitoring system.

CEN-Integration Overview

The central monitoring system (CEN) is a single SAP system that you designate as the central point of control for CCMS alerts originating from all over the monitored SAP landscape. The CEN concept allows you to reduce the overhead of monitoring and managing multiple SAP systems by making essential information concerning problem alerts available in one, central location.

After you configure SAP to use the CEN for the central management of CCMS alerts, you can use the SPI for SAP's r3monal monitor to intercept the CCMS alerts destined for the CEN and use the alerts to generate messages, which it forwards to the HPOM for Windows console.

For more information about configuring SAP to use a central monitoring system (CEN) to manage CCMS alerts for a complete SAP landscape, see the SAP documentation; for more information about setting up the SPI for SAP to monitor CCMS alerts, see r3monal: the CCMS 4.x Alert Monitor on page 51.

Configuring the SAP CEN

The SPI for SAP supports the monitoring of CCMS alerts in a CEN provided you configure SAP to use the CEN as a central alert-monitoring location. Setting up the CEN as the central location for the collection and monitoring of alerts is straight forward but involves a number of steps. For example, you need to ensure (among other things) that you configure the required users, register and start the appropriate agents, and define the type of information you want to collect, such as: performance, statistical, or availability. The information in this section provides some pointers to what you need to consider when setting up the CEN for monitoring with the SPI for SAP.

For more information about configuring SAP to use a central monitoring system (CEN) to manage CCMS alerts for a complete SAP landscape, see the SAP documentation; you will need to find out in particular about the following high-level topics:

- SAP Central Monitoring System on page 194
- SAP ABAP Instances on page 196
- J2EE Instances on page 197

SAP Central Monitoring System

When you are setting up the SAP central monitoring system to collect, monitor, and analyze alert data, you need to consider the following important points:

Background Dispatching in the CEN

To ensure the correct and timely startup of all data collection methods by the background process, you have to enable the monitoring architecture. Enable background dispatching both in the CEN and in all monitored ABAP systems, as illustrated in Figure 17 on page 196.

The CSMREG User

You need to create the CSMREG user both in the CEN and in all the ABAP systems you want the CEN to monitor remotely. CSMREG is a user with specific authorizations, which SAP uses to collect data from the remote systems and send it to the CEN. For more information about the configuring the CSMREG user, see the SAP documentation.

The CSMCONF file

The CSMCONF file is mandatory for the registration and startup of the CCMS agents; it contains all the connection data that you would otherwise have to supply during the normal registration process, for example: the system ID of the CEN, the client number, user name, and so on.

Data Collection and Analysis

If you want to use the CEN to collect, monitor, and analyze data from remote ABAP systems, you need to create two RFC destinations for each monitored ABAP system. CEN requires an entry in the CCMS alert monitor for each SAP system it monitors remotely.

Statistical Workload Data

If you want to monitor the work-load statistics from the ABAP system in the CEN, use transaction **st03G** (Global System Workload Analysis) to enter the RFC destination of each ABAP system in the workload monitor, as illustrated in Figure 18 on page 197.

The CCMSPING Availability Agent

Make sure the CCMS availability agent, CCMSPING, is available so that CCMS can monitor the status and availability of remote SAP systems. See the SAP documentation for more information about the pre-requisites for (and configuration of) the CCMSPING agent.

Properties Edit Goto Methods Technical infrastructure System Help 1 Display Topology Configure Central System **Monitoring: Properties** Local Method Executio Central Performance History Deactivate Background Dispatching System Repository Properties Availability Monitoring Properties assigned to MTE classes Configure QRFC Monitoring O Properties assigned to Customizing Reorganize segment table O MTE-specific properties O Properties variants Variants currently active Display overview Methods Method definitions O Method release O Methods assigned to MTE classes O Methods assigned to specific MTEs Display overview Topology System Overview O Agents for Local System O Agents for Remote Systems O Segment Overview O Context Overview O Agents for 3.x Systems Display Overview SP1 (1) 000 sapspiw3 OVR SP1 (1) 000 sapspiw3 OVR

Figure 17 Enabling Background Dispatching

SAP ABAP Instances

When you are setting up the SAP central monitoring system to collect, monitor, and analyze alert ABAP data, you need to consider the following important points for each monitored ABAP instance:

The SAPCCM4X Agent

To avoid communication problems when using the CEN to monitor an ABAP instance, you need to register the CCMS agent SAPCCM4X; registering the SAPCCM4X agent establishes a communication channel between the CEN and the monitored ABAP instances. Since the SAPCCM4X agent does not requires a free work process, it is not affected by any error states in any of the monitored ABAP instances.

Note that you need to register the SAPCCM4X agent on each of the ABAP instances monitored with the CEN.

SAP Load display Goto System Help **@ Global System Workload Analysis** Fullscreen On/Off Component sapspiwb.ind.hp_TST_132249150 ServiceType SAP R/3 SP1
SAPJ2ENode TST Component Type SAPJ2ENode First Record 13.06.2007 13.06.2007 13.06.2007 sapspiwb.ind.hp_TST_13224 Last Minute's Load □ Day Average Values per Step / Average Values per Transaction Today 🔷 14.06.2007 Thu 13.06.2007 Wed
12.06.2007 Tues System Workload Overview: Average Times per Transaction in ms Service Type # Steps # Transact ØResp.Tim Ø CPU Tim ØWait Tim Ø CallTim Ø LoadTim Ø Gen.Tim This Week 574 574 0.1 ▽ 📵 Month 1.104 0,0 EJB Request 1,104 60.0 36.8 15.9 0.0 0.0 This Month 574 574 TOTAL> Web Service 1,1 0,1 0,0 0,0 561 0.0 0.0 0.0 0.0 0.0 Detailed Analysis Business Transaction Analysis Functional Trace Ø Co **4** F 4 B ▶ ■ Analyses 4 1 4 1

Figure 18 Monitoring ABAP Statistics in the CEN

J2EE Instances

When you are setting up the SAP central monitoring system to collect, monitor, and analyze alert data from SAP Java instances, you need to consider the following important points for each monitored J2EE instance:

The SAPCCMSR Agent

If you want to use CCMS to monitor J2EE instances with the CEN, you need to register the CCMS agent SAPCCMSR in the CEN since monitored data from the Java instances are transferred through the CCMS agent. Note that the installation of the J2EE engine configures the SAPCCMSR by default; you just need to register the SAPCCMSR agent with CEN for each J2EE instance and start the agent.

Java DSRs in the CEN

You can configure the global workload monitor to display distributed statistical records (DSR) for Java instances in the CEN. Figure 18 on page 197 shows the output for the Global System Workload Analysis transaction.

Availability monitoring with GRMG

To monitor the availability of a J2EE instance in SAP, you need to customize the configuration files for the General Request and Message Generator (GRMG) and upload the modified configuration files to the CCMS agent; the J2EE engine's Network Administrator (NWA) displays example XML files that are available for modification and upload to CCMS, as illustrated in Figure 19 on page 198. You can also use the transaction GRMG to display a list of active GRMG configuration scenarios that are available in the SAP central monitoring system.




Figure 19 Uploading the GRMG Configuration File to CCMS

Configuring the SPI for SAP

After you configure SAP to use the CEN for the central management of CCMS alerts, you can use the SPI for SAP's r3monal monitor to intercept the CCMS alerts destined for the CEN and generate a message that it forwards to the HPOM for Windows console.

For more information about configuring SAP to use a central monitoring system (CEN) to manage CCMS alerts for a complete SAP landscape, see the SAP documentation; for more information about setting up the SPI for SAP to monitor CCMS alerts, see r3monal: the CCMS 4.x Alert Monitor on page 51.

The following list provides a high-level overview of the steps you need to perform to configure the SPI for SAP to monitor CCMS alerts in the CEN:

- Install the SPI for SAP on the SAP system you assign as the central monitoring system (CEN).
 - Note that if you are already using the SPI for SAP to monitor the SAP System nominated as the CEN, you do not have to perform this step.
- 2 Import the SPI for SAP transports for CCMS into the SAP system nominated as the central monitoring system (CEN):
 - The SPI for SAP's CCMS transport (SAPSPI_CCMS_Monitors.car) provides a CCMS monitor set (HP OV SAP-SPI) that includes monitors for the following SAP components: the J2EE engine, SAP security, stand-alone enqueue servers, enterprise-portal performance and availability, and XI monitoring.




You can define new (or expand existing) monitor sets to include new CCMS monitors, whose alerts you want to display. For more information about defining CCMS monitor sets in the context of the SPI for SAP, see r3monal: CCMS Monitor Sets on page 52 and r3monal: CCMS Alert Monitors on page 55.

- 3 Import the SPI for SAP monitor transports:
 The SPI for SAP monitor transport (R3Trans.car) contains all the SPI for SAP's ABAP monitors and their default configuration settings. You must import the monitor transport into the central monitoring system which monitors all the ABAP and ABAP/JAVA (dual stack) systems connected to it.
- 4 Register and start the appropriate CCMS agent on each instance of the J2EE engine and ABAP that you want to monitor with the SPI for SAP through the CEN.
 - For a brief description of the SAPCCMSR agent (for J2EE) and the SAPCCM4X agent (for ABAP) in the context of the SPI for SAP, see J2EE Instances on page 197 and SAP ABAP Instances on page 196 respectively. For more detailed information about installing, registering, and starting the agents, see the SAP product documentation.
- If not already present, deploy the SPI for SAP's CCMS-alert monitor r3monal to the system hosting the CEN and modify the r3monal.cfg configuration file to enable the monitoring of CCMS monitor sets. For more information about enabling CCMS monitor sets in the r3monal.cfg configuration file, see CCMS Monitor Set on page 32.
- 6 Make sure the SPI for SAP is aware of the CEN.
 - If not already present, add an entry for the CEN to the SPI for SAP's central configuration file, r3itosap.cfg, on the system hosting the CEN instance.
 - For more information about the contents of the r3itosap.cfg file and an explanation of the syntax required with the HostSapAssign keyword used to define a new SAP instance to monitor, see the *HP Operations Manager Smart Plug-in for SAP Configuration Guide for Windows*.
- 7 If you previously used the SPI for SAP to monitor individual SAP Systems locally (and independently) and now want to change the configuration so that you can monitor all the individual SAP Systems remotely in the CEN, you will have to take note of the following points:
 - The r3monal monitor must not run on both the local SAP System and on the CEN System, too; this will lead to the duplication of messages.
 - To avoid message duplication, disable both the r3monal monitor and the r3itosap.cfg file on each of the individual SAP Systems whose CCMS alerts you were previously monitoring independently with the SPI for SAP.
 - b Configure the CEN to monitor CCMS alerts remotely from all the individual SAP Systems that you were monitoring locally.
 - c Configure r3monal on the CEN to intercept CCMS alerts arriving on the CEN from all the individual SAP Systems that you were monitoring locally.
 - To ensure that the CCMS alerts from the individual, remote SAP Systems now appear in the Solution Manager on the CEN, use transaction RZ20 to set up a CCMS monitor tree (on the CEN) for each SAP System ID that you previously monitored locally. The new monitor trees should specify which CCMS alerts you want to monitor and intercept with the SPI for SAP.
 - In this way, one instance of r3monal on the CEN can monitor CCMS alerts from all the SAP Systems monitored remotely by the CEN.
- 8 By default, the MTE rule nodes for J2EE monitoring installed with the SPI for SAP CCMS transport are set to monitor the "Current" System on which the transport is imported. This setting should be changed to "all" when imported into a CEN, so that alerts from remote Systems reporting to the CEN are monitored, as illustrated in Figure 20 on page 200.

9 If you were *not* already monitoring the CEN with the SPI for SAP, add the system hosting the CEN to the HPOM for Windows console so that messages generated by the SPI for SAP are visible in the HPOM for Windows console.

Figure 20 MTE Rule-Node Settings for CEN Monitoring



6 The SPI for SAP Performance Monitors

This section describes in detail how to install, set up, and use the SPI for SAP R/3 Performance Agent. It also provides information about how to put the performance monitors included in the SPI for SAP R/3 Performance Agent to best use and supplement the information collected by the SPI for SAP performance monitors with information supplied by the HP Performance Agent.

Performance Monitors Overview

The SPI for SAP R/3 Performance Agent uses a selection of performance monitors to collect SAP performance data and store them either in the HP Software Embedded Performance Component (CODA) or the Performance Agent (Unix/Windows). You can use the Performance Manager to monitor, manage, and correlate these data, together with data collected by any other application, database, system and network Performance Agent. The data can then be used to compare trends between SAP business transactions and other system metrics. This section provides information about the following topics:

- Performance monitoring with the SPI for SAP
- Using HPOM for Windows to install the SPI for SAP R/3 Performance Agent
- Configuring the performance monitors

Implemented ABAP-function modules inside SAP NetWeaver are accessed by means of an RFC-call. The performance monitors gather a snapshot of SAP-runtime performance data.

The SPI for SAP R/3 Performance Agent can collect more than 130 metrics in *addition* to those collected by the SAP NetWeaver Performance alert monitor (ST03), which is part of the SAP NetWeaver CCMS subsystem.

You can configure the SPI for SAP R/3 Performance Agent to specify which monitors should be run on specified SAP NetWeaver instances and how frequently. For more information, see Configuring the SPI for SAP R/3 Performance Agent on page 209.

The Performance Agent runs in Windows operating systems as a service and in UNIX operating systems as a daemon (background) process that runs independently of the HPOM for Windows agent processes. To start or stop the SPI for SAP R/3 Performance Agent processes, use the appropriate HPOM for Windows tool in the SPI for SAP tools group in the HPOM for Windows console. For more information, see Managing the SPI for SAP R/3 Performance Agent on page 219.

Upgrading the SPI for SAP R/3 Performance Agent

You cannot always use the data sources you defined in previous versions of the SPI for SAP R/3 Performance Agent with the latest version of the SPI for SAP. The upgrade strategy you adopt depends on the version of the SPI for SAP R/3 Performance Agent you want to upgrade.

If you are upgrading a recent version of the SPI for SAP R/3 Performance Agent such as 11.10, you can continue to use all existing data and data sources. If you are using an older version such as 10.x or 9.x you can re-use the data and data sources, but you have to migrate the data to the new format required by the latest SPI for SAP R/3 Performance Agent. If you are using a version of the SPI for SAP R/3 Performance Agent such as 08.11 or earlier, you will not be able to reuse any of the existing data and data sources.

To upgrade the SPI for SAP R/3 Performance Agent, perform the following high-level steps:

Remove the existing SPI for SAP R/3 Performance Agent

For more information about removing the SPI for SAP R/3 Performance Agent, see Removing the SPI for SAP R/3 Performance Agent on page 241.

Remove existing SPI for SAP R/3 Performance Agent data and data sources

SPI for SAP 10.70, 10.50, or 09.01 - If you are upgrading from versions 10.70, 10.50, or 09.01 to the current version of the SPI for SAP, you do not need to perform this step; you can continue to use existing data and data sources.

3 Upgrade the SPI for SAP

For more information, refer to the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

4 Install the new SPI for SAP R/3 Performance Agent

For more information about installing the SPI for SAP R/3 Performance Agent, see Installing the SPI for SAP R/3 Performance Agent on page 206.

5 Configure the new SPI for SAP R/3 Performance Agent

For more information about installing the SPI for SAP R/3 Performance Agent, see Configuring the SPI for SAP R/3 Performance Agent on page 209.

6 Upgrade the SPI for SAP/Reporter Integration

For more information about upgrading the SPI for SAP Reporter integration, see Upgrading the SPI for SAP Reports on page 349.

Migrating the SPI for SAP R/3 Performance Agent with the HP Performance Agent

If you are using the HP Performance Agent as your performance data source and want to upgrade the SPI for SAP R/3 Performance Agent from a previous to the most recent version, it is extremely important that you migrate (or in some cases remove) cleanly and completely the data and data sources associated with the old version of the SPI for SAP R/3 Performance Agent before you start the installation of the new version.

To migrate the SPI for SAP R/3 Performance Agent, you need to perform the following steps:

1 Stop the Performance Agent

On the node where you perform the upgrade, stop the Performance Agent:

• AIX operating systems:

/usr/lpp/perf/bin/mwa stop

• HP-UX/Solaris operating systems:

/opt/perf/bin/mwa stop

Windows operating systems:

mwacmd stop

2 Remove the old SPI for SAP R/3 Performance Agent

Remove the old version of the SPI for SAP R/3 Performance Agent from the managed node as described in Removing the SPI for SAP R/3 Performance Agent on page 241.

3 Clean up data sources

If you are upgrading from versions 08.70 or later to the current version of the SPI for SAP, you do not need to perform this step: you can continue to use existing data and data sources with the new SPI for SAP Performance Agent.

The configuration of the new SPI for SAP Performance Agent walks you through the migration process and locates and updates the old data to the new format for you. For more information, see Configure the SPI for SAP R/3 Performance Agent on page 210.

If you are upgrading from version 08.11 or earlier of the SPI for SAP, you need to remove all existing SPI for SAP R/3 Performance Agent performance data sources from the managed nodes as follows:

- a On the HPOM for Windows managed node, locate and, using text editor, open the following file, whose location differs according to operating system:
 - AIX operating systems:

/usr/lpp/perf/data/perflbd.rc

HP-UX/Solaris operating systems:


/var/opt/perf/data/perflbd.rc

Windows operating systems:

<OvPerfAgtInstallDir>\data\perflbd.mwc

b Remove any entries relating to the SPI for SAP R/3 Performance Agent present in the perflbd file, as illustrated in Figure 21 on page 203. Entries in the perflbd file relating to the SPI for SAP R/3 Performance Agent start with: DATASOURCE=R3_*.

Figure 21 Cleaning up the perflbd file



- c Remove the data-source files from the following directories:
 - AIX operating systems:

/var/lpp/OV/bin/R3PerfAgent/data

HP-UX/Solaris operating systems:

/var/opt/OV/bin/R3PerfAgent/data

Windows operating systems:

%OvDataDir%\bin\R3PerfAgent\data

4 Remove the old version of the SPI for SAP

If you have not already done so, remove the old version of the SPI for SAP from the management server. For more information see *Removing the SPI for SAP* in the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

5 Install the new version of the SPI for SAP

Install the new version of the SPI for SAP on the HPOM for Windows management server. For more information, see *Installing the SPI for SAP* in the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

6 Install the new SPI for SAP R/3 Performance Agent

Install the new version of the SPI for SAP R/3 Performance Agent as described in Installing the SPI for SAP R/3 Performance Agent on page 206.

7 Configure the new SPI for SAP R/3 Performance Agent

Configure the SPI for SAP R/3 Performance Agent. For more information, see Configuring the SPI for SAP R/3 Performance Agent on page 209.

Note that after finishing the migration described here, you do not need to execute steps 1 and 2 specified in Configure the SPI for SAP R/3 Performance Agent on page 210. You can proceed directly to step 3 and adapt the configuration file before starting the SPI for SAP R/3 Performance Agent in steps 4 and 5.

Upgrading the SPI for SAP R/3 Performance Agent with CODA

If you are using the HP Software Embedded Performance Component (CODA) as your performance data source and want to upgrade the SPI for SAP R/3 Performance Agent from a previous to the most recent version, it is extremely important that you migrate (or in some cases remove) cleanly and completely the data and data sources associated with the old version of the SPI for SAP R/3 Performance Agent before you start the installation of the new version.

To migrate the SPI for SAP R/3 Performance Agent, you need to perform the following steps:

Remove the old SPI for SAP R/3 Performance Agent

Remove the old version of the SPI for SAP R/3 Performance Agent from the managed node as described in Removing the SPI for SAP R/3 Performance Agent on page 241.

2 Clean up SPI for SAP R/3 Performance Agent data sources

If you are upgrading from version 08.70 or later to the current version of the SPI for SAP, you do not need to perform this step: you can continue to use existing data and data sources with the new SPI for SAP performance agent. The configuration of the new SPI for SAP performance agent walks you through the migration process and locates and updates the old data to the new format for you. For more information, see Configure the SPI for SAP R/3 Performance Agent on page 210.

If you are upgrading from version 08.11 or earlier of the SPI for SAP, you need to check for (and delete) entries relating to the old SPI for SAP R/3 Performance Agent present in the ddflbd file. Note that the location of the ddflbd file and the file extension differ according to platform, namely:

AIX operating systems:

/var/lpp/OV/conf/dsi2ddf/ddflbd.rc

HP-UX/Solaris operating systems:

/var/opt/OV/conf/dsi2ddf/ddflbd.rc

Windows operating systems:

%OvAgentDir%\conf\dsi2ddf\ddflbd.mwc

Entries in the ddflbd file relating to the SPI for SAP R/3 Performance Agent typically start with the following string: DATASOURCE=R3_* as illustrated in Figure 22 on page 205. The value of LOGFILE= defined for the SPI for SAP R/3 Performance Agent entries is important: you use it (including the complete path) as an argument with the command-line utility ddfutil -rm all to remove the entries one by one, as follows:

After you remove from the ddflbd file all the entries you can find relating to the SPI for SAP R/3 Performance Agent, check that the entries are no longer present by closing the ddflbd file and opening it again.

3 Remove the old version of the SPI for SAP

If you have not already done so, remove the old version of the SPI for SAP from the management server. For more information see "Removing the SPI for SAP" in the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

4 Install the new version of the SPI for SAP

Install the new version of the SPI for SAP on the HPOM for Windows management server. From more information, see *Installing the SPI for SAP* in the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

5 Install the new SPI for SAP R/3 Performance Agent


Install the new version of the SPI for SAP R/3 Performance Agent as described in Installing the SPI for SAP R/3 Performance Agent on page 206.

6 Configure the new SPI for SAP R/3 Performance Agent

Configure the SPI for SAP R/3 Performance Agent. For more information, see Configuring the SPI for SAP R/3 Performance Agent on page 209.

Note that after finishing the migration described here, you do not need to execute steps 1 and 2 specified in Configure the SPI for SAP R/3 Performance Agent on page 210. You can proceed directly to step 3 and adapt the configuration file before starting the SPI for SAP R/3 Performance Agent in steps 4 and 5.

Figure 22 The ddflbd.mwc File



Installing the SPI for SAP R/3 Performance Agent

This section describes how to use the HPOM for Windows console to install the SPI for SAP functionality for the performance-agent on the SAP servers you want to manage with HPOM for Windows and the SPI for SAP. Note that the instructions in this section assume the following is true:

- The HP Operations agent is already installed and running on the selected SAP servers.
- Either the HP Performance Agent or the HP Software Embedded Performance Component (CODA) is running on the selected SAP servers.

To install the SAP/Performance package, follow these steps:

Deploy the Performance-Monitor Instrumentation:

- a From the HPOM for Windows console, select and right-click the node(s) where you want to deploy the instrumentation.
- b Browse to the following menu option:

All tasks > Deploy instrumentation

- c In the Deploy Instrumentation window, select the following items:
 - SPIDataCollector
 - SPI for SAP Performance Package
- d Select OK.

2 Install the Performance-Monitor Package:

a In the HPOM for Windows console, browse to the following tools folder:

Tools > SPI for SAP > SAP R/3 Admin

- b Select and right-click the Performance Package tool which corresponds to the operating system for the SAP System environment you want to monitor. The choices are:
 - Install Performance Package (UNIX)
 - Install Performance Package (Windows)
- c Start the Install Performance Package tool for the appropriate operation system using the following option in the menu, which pops up:

All tasks > Launch Tool...

- In the window which pops up, select the SAP managed node(s) where you want to start the Performance Package installation. Remember to ensure that the nodes you select correspond to the operating system of the chosen tool, for example; UNIX or Microsoft Windows.
- e Click Launch... to start the installation.
- After installation, neither the SPIDataCollector nor the SPI for SAP Performance Package appears in the list of packages installed on the managed node.

Locating the SPI for SAP R/3 Performance Agent Files

The information in this section describes the location of the files which the SPI for SAP installs as part of the SPI for SAP R/3 Performance Agent package for the following platforms:

- SPI for SAP R/3 Performance Agent: AIX
- SPI for SAP R/3 Performance Agent: HP-UX, Solaris, and Linux
- SPI for SAP R/3 Performance Agent: Windows

The performance-related files listed in this section belong to the following categories: binaries and executable, configuration files, the dsilog files required by the HP Performance Agent, and templates.



The dsilog files are only required by the HP Performance Agent; the HP Software Embedded Performance Component does not require or make use of the dsilog files.

SPI for SAP R/3 Performance Agent: AIX

This section lists the files which the SPI for SAP installs as part of the SPI for SAP R/3 Performance Agent package for AIX.

- Binaries: /var/[lpp | opt]/OV/bin/R3PerfAgent/bin
 - r3perfconfig

SPI for SAP performance-monitor configuration tool

- r3perfagent

SPI for SAP performance-monitor agent

- Configuration files: /var/[lpp | opt]/OV/conf/sapspi/[global | local]
 - r3perfagent.cfg

Configuration file for the various global and local performance monitors. Note that the SPI for SAP creates this directory *after* you deploy the SPI for SAP performance-agent policies for the first time.

- Dsilog files: /var/[lpp |opt]/OV/bin/R3PerfAgent/data
 - R3 <HOSTNAME> <SID> ...

Immediately after installation, this directory is empty; the SPI for SAP uses the directory to store the dsilog files, which r3perfconfig and compdsifile.sh compile for the HP Performance Agent.

- Templates: /var/[lpp | opt]/OV/bin/R3PerfAgent/template
 - R3statistics.<PERF-MONITOR>

Files the SPI for SAP uses to compile the dsilog files

— Parm.UX

Template for the performance agent parameter file.

SPI for SAP R/3 Performance Agent: HP-UX, Solaris, and Linux

This section lists the files which the SPI for SAP installs as part of the SPI for SAP R/3 Performance Agent package for HP-UX, Solaris, and Linux:

- Binaries: /var/opt/OV/bin/R3PerfAgent/bin
 - r3perfconfig

SPI for SAP performance-monitor configuration tool

- r3perfagent

SPI for SAP performance-monitor agent

- Configuration files: /var/opt/OV/conf/sapspi/[global | local]
 - r3perfagent.cfg

Configuration file for the various performance monitors. Note that the SPI for SAP creates this directory *after* you deploy the SPI for SAP performance-agent policies for the first time.

- Dsilog files: /var/opt/OV/bin/R3PerfAgent/data
 - R3 <HOSTNAME> <SID> ...

Immediately after installation, this directory is empty; the SPI for SAP uses the directory to store the dsilog files, which r3perfconfig and compdsifile.sh compile for the HP Performance Agent.

• Templates: /var/opt/OV/bin/R3PerfAgent/template

```
R3statistics.<PERF-MONITOR>
```

Files the SPI for SAP uses to compile the dsilog files

— parm.UX

Template for the performance agent parameter file.

SPI for SAP R/3 Performance Agent: Windows

This section lists the files which the SPI for SAP installs as part of the SPI for SAP R/3 Performance Agent package for Windows:

- Binaries: %OvDataDir%\bin\R3PerfAgent\bin
 - r3perfconfig

SPI for SAP performance-monitor configuration tool

- r3perfagent

SPI for SAP performance-monitor agent

— r3perfagent_service

Starts the performance-monitor agent as a service under Windows

- Configuration files: %OvAgentDir%\conf\sapspi\[global| local]
 - r3perfagent.cfg

Configuration file for the various performance monitors. Note that the SPI for SAP creates this directory *after* you deploy the SPI for SAP performance-agent policies for the first time.

- Dsilog files: %OvDataDir%\bin\R3PerfAgent\data
 - R3 <HOSTNAME> <SID> ...

Immediately after installation, this directory is empty; the SPI for SAP uses the directory to store the dsilog files, which r3perfconfig.bat and compdsifile.bat compile for the HP Performance Agent.

- Templates: %OvDataDir%\bin\R3PerfAgent\template
 - R3statistics.<PERF-MONITOR>

Files the SPI for SAP uses to compile the dsilog files

— parm.UX

Template for the performance-agent parameter file.

Configuring the SPI for SAP R/3 Performance Agent

The information in this section takes you through the process of setting up and configuring the SPI for SAP R/3 Performance Agent.

Selecting the Performance-data Source

The HP Software Embedded Performance Component is, as the name suggests, embedded in the HPOM for Windows software and available, by default, in any HPOM for Windows installation. However, you can use the HPOM for Windows console to deploy the HP Performance Agent to the managed nodes, too.

If you prefer to use the HP Performance Agent as the source for performance data for newly installed HP Software products rather than the HP Software Embedded Performance Component, for example; to feed the data into the Performance Manager, you can set up a small text file, <code>nocoda.opt</code>, which instructs the SPI for SAP to ignore the default data source, the HP Software Embedded Performance Component, and switch to the HP Performance Agent. After you configure the <code>nocoda.opt</code> file, you must store it in the following location on each managed node, whose performance-data source you want to change:

• AIX [DCE | HTTPS]:

/var/[lpp | opt]/OV/conf/dsi2ddf/nocoda.opt

HP-UX/Solaris:

/var/opt/OV/conf/dsi2ddf/nocoda.opt

- Microsoft Windows:
- %OvAgentDir%\conf\dsi2ddf\nocoda.opt

To change the performance-data source, follow these steps:

1 Open the nocoda.opt file

Open the (or create a new) nocoda.opt file in a text editor and manually enter the appropriate information using the format and syntax illustrated in An Example of the nocoda.opt File on page 210.

2 Specify a generic data source

To designate the HP Performance Agent as the agent for all data sources on the managed node, enter (or enable) the key word ALL at the top of the nocoda.opt file.



Using the ALL keyword in the nocoda.opt file to enable all SAP NetWeaver instance on the managed node as data sources for the Performance Agent overrides any references to explicit data sources, which are still present in the nocoda.opt file.

3 Specify individual data sources

To designate the HP Performance Agent as the data source tied to a specific SAP NetWeaver instance, remove (or disable) the key word ALL at the top of the nocoda.opt file and include a reference to each SAP instance on a separate line of the nocoda.opt file, as illustrated in An Example of the nocoda.opt File, using the following format:

```
R3ITS <Virtual SAPITS Instance Name> <SAPITS Hostname> DATA
```



Any SAP NetWeaver and SAP ITS instances on the managed node which are not explicitly listed in the nocoda.opt file, will continue to use the default data source, namely; the HP Software Embedded Performance Component (CODA).

4 Save the changes to the nocoda.opt file

Save the changes to the nocoda.opt file.

5 Restart the HP Operations agent

Restart the HP Operation agent on the managed node where the nocoda.opt file has been modified.

An Example of the nocoda.opt File

Configure the SPI for SAP R/3 Performance Agent

You need to complete the following steps to configure the SPI for SAP R/3 Performance Agent:



Make sure that the OVDATADIR environment variable is set for all UNIX nodes.

1 Start the SPI for SAP R/3 Performance Agent configuration

On the node where you installed the SPI for SAP R/3 Performance Agent, switch to the appropriate directory and enter the following command to run the SPI for SAP R/3 Performance Agent configuration scripts:

- Windows operating systems: r3perfconfig
- UNIX operating systems: ./r3perfconfig

Follow the instructions which appear on screen. The script lists the SIDs that it finds and prompts you to choose one of the associated numbers to indicate which SAP NetWeaver instance you want to configure. For example:

Installed SAP Instances:

		SID	SapNr	HostName			
(0)		AST	45	sapper			
(1)		DEV	50	sapper			
(2)		SP1	80	sapper			
(3)		to co	nfigure	Netweaver	Datasource		
Choose:							
(x)	to	configure shown system					
888	to	manually configure a SAP system					
999	to	quit					

ABAP datasource is created by default. If you need to create a Netweaver datasource, select the appropriate options and click confirm for the datasource creation.

Enter the appropriate SAP-SID identification number, for example, **0** for AST, **1** for DEV, **2** for SP1, 3 for Netweaver Datasource, or **888** to configure a new SAP System:

a If no data source exists for the given SAP System ID, r3perfconfig creates one and configures it, as follows:

```
Choose:
(x) to configure shown system
888 to manually configure a SAP system
999 to quit
0
Creating new datasource: R3_sapper_AST_45_DATA
...Datasource successfully created
```

b If a valid data source already exists for the given SAP System ID, r3perfconfig lists the data source and prompts you to continue, as follows:

```
Choose:
(x) to configure shown system
888 to manually configure a SAP system
999 to quit
0
Valid datasource already exists: R3_sapper_AST_45_DATA
```

c If r3perfconfig finds an existing data source, which it can migrate to the required *new* format, it lists the old data source and asks you what to do:

```
Choose:
(x) to configure shown system
888 to manually configure a SAP system
999 to quit
1
Found an old datasource: R3_sapper_DEV_50_DATA
Should the existing datasource be migrated <yes/no>?
```

Bear in mind the following before you respond:

– yes

automatically migrates the old data source to the format required by the new version of the SPI for SAP R/3 Performance Agent


— nc

leaves the existing data source unchanged: the old data source *cannot* be used with the new version of the SPI for SAP R/3 Performance Agent

d If r3perfconfig finds an existing data source, which *cannot* be migrated to the new format, for example, because it belongs to a version of the SPI for SAP that is older than 08.70, it lists the old, *invalid* data source and prompts you to continue, as follows:

```
Choose:
(x) to configure shown system
888 to manually configure a SAP system
999 to quit
2
Found an invalid datasource: R3_sapper_SP1_80_DATA
Existing datasource cannot be migrated
```

e If you choose 888 to configure a SAP SID from scratch, you are required to answer a series of questions concerning the SAP SID you want to configure.



When you are finished, the data sources are created and added to the following file, which differs according to whether you are using HP Performance Agent or the HP Software Embedded Performance Component:

— Windows operating systems:

```
perflbd.mwc / ddflbd.mwc
```

— UNIX operating systems:

```
perflbd.rc / ddflbd.rc
```

It is a good idea to update the parm.mwc file as described in the next step before you restart the performance agent.

2 Update the performance-agent parameter file



This step does not apply to the HP Software Embedded Performance Component.

If you are using the performance agent, append the template file parm.NT (or Parm.UX, depending on the installed operating system on the managed node) to the parm file of the performance agent, as follows:

— UNIX operating systems:

```
cat parm.UX >> parm
```

In UNIX operating systems, the parm file is located in: /var/opt/perf/parm

— Windows operating systems:

```
type parm.NT >> parm.mwc
```

The parm.mwc file is located in the following directory: <drive letter>\rpmtools\data\parm.mwc

You can represent several SAP NetWeaver instances in the parm file by using the asterisk (*) wild card.

3 Configure the performance monitors

Configure the monitors in the r3perfagent.cfg file. If you do not do this, all monitors will run with the default settings as illustrated in the following example. There are two possible configurations:

— Global: global_r3perfagent.cfg

Global SPI for SAP R/3 Performance Agent settings for all SAP managed nodes

— Local: local r3perfagent.cfg

Local SPI for SAP R/3 Performance Agent settings for individual SAP managed nodes.

To open the r3perfagent.cfg file with the configuration-file policy editor, double-click the global_r3perfagent policy, which resides in the policy group:

Policy Management > Policy Groups > SPI for SAP



The settings in the *global* configuration files are used for all nodes which do not have *local* configuration settings. Where both files are present, local settings override global ones.

The default configuration is:

- All performance monitors are enabled for all SAP host names, systems, numbers and clients.
- The default polling intervals are set for each performance monitor in minutes.
- Hold Connections is disabled.

Change any values as required and save the file. You will have to restart the HP Performance Agent to upload the latest configurations.

4 Deploy the policies

To deploy the new or modified policies to the managed nodes, right-click the new or modified policies and use the following option from the menu which appears:

All Tasks > Deploy on...

5 Start the HP Performance Agent

Start the HP Performance Agent on the managed node by entering the following command in a shell:

- UNIX operating systems: mwa start
- Windows operating systems: mwacmd start

6 Start the SPI for SAP R/3 Performance Agent

On the managed node, switch to the directory in which the r3perfagent command resides and start the SPI for SAP R/3 Performance Agent by entering the following command in a shell:

— UNIX operating systems:

```
./r3perfagent [stop | start]
```

— Windows operating systems:

r3perfagent service [-e | -s]

Or, alternatively, in the HPOM for Windows console, use the following SPI for SAP tool:

— UNIX operating systems:


Tools > SPI for SAP > SAP R/3 UN*X > PerfAgt START

— Windows operating systems:


Tools > SPI for SAP > SAP R/3 NT > PerfAgt START

Remote Performance Monitoring

The current version of the SPI for SAP includes a feature, which allows you to extend the scope of the performance monitor to remotely monitor the health of an additional SAP server (which is *not* a managed node) from an SAP server, which *is* already configured as an HPOM for Windows managed node.



In addition, the SAP Server defined in RemoteHost must appear in the r3itosap.cfg file to ensure that the SPI for SAP can login to and extract information from the SAP instances it is monitoring on the remote host. For more information about the r3itosap.cfg file, refer to the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows.



To make use of the remote-monitoring feature provided by the SPI for SAP, for example, to collect SAP performance metrics from a SAP System running an operating system that is not supported by the SPI for SAP, you need to use the r3perfconfig command to manually add an additional data source for each system you plan to monitor remotely and then enable the new RemoteMonitoring keyword (by removing the leading hash symbol "#") in the *global* r3perfagent.cfg file.

On the same line in the <code>global</code> r3perfagent.cfg file, tell the SPI for SAP performance agent the name of the local SAP server which you want to perform the monitoring and, in addition, the name of the remote SAP server, which you want to monitor. Note that you must add a new line for each <code>additional</code> server that you want to monitor remotely. Specifying Remotely <code>Monitored Hosts</code> in the r3perfagent.cfg File on page 214, shows an excerpt from the <code>global</code> r3perfagent.cfg file with the remote-monitoring feature enabled; the <code>local</code> r3perfagent.cfg file, if present, would only contain references to the managed node on which the local configuration file is located.

The performance-monitoring conditions defined in the *Perfmon* section at the end of the r3perfagent.cfg file apply by default to all SAP instances running on all the servers listed in the configuration file, that is: all SAP instances running on both the local and remote servers defined in the RemoteMonitoring section. For more information about the keywords and parameters used to define remote monitoring in the r3perfagent.cfg file, see The r3perfagent.cfg Configuration File on page 216.

Specifying Remotely Monitored Hosts in the r3perfagent.cfg File

#		
# Remote # Monitoring	LocalHost	RemoteHost
RemoteMonitoring RemoteMonitoring RemoteMonitoring #	=sapwolf2 =sapwolf3 =sapper	=sapprod1 =sapprod2 =sapprod3

The Performance-Monitor Scheduler

An internal scheduler ensures that the performance monitors run according to the desired schedule. The scheduler keeps track of time and the number of runs that have been completed and uses this information to ensure that the performance monitors run at the correct time and collect the appropriate performance-related data.

If the performance monitor encounters any problems during its run and cannot complete its task before the start of the next scheduled run, it does not stop and leave tasks incomplete; the performance monitor continues to run until it has completed its task. However, the scheduler tracks the progress of the performance monitor and tries to synchronize the run schedules so that the time lost can be regained without affecting the collection of the performance data.

If the performance-monitor scheduler falls ten minutes behind schedule, it sends a message to the HPOM for Windows management server with the warning that the scheduler is out of synchronization. If the performance-monitor scheduler falls thirteen minutes behind schedule, it resets—ignoring all outstanding jobs. For more information about the keywords you can use to control the performance-monitor scheduler and the messages it generates, see The r3perfagent.cfg Configuration File on page 216.

The performance monitor has problems with synchronization if it is not able to complete all its scheduled tasks in the allowed time between each monitor run. To troubleshoot scheduler-synchronization problems:

1 Check the Polling Interval

Check that the polling interval for the individual r3perfagent monitors has not been changed in the r3perfagent.cfg file to a value that is too small. You can define the polling interval for individual monitors in the "Polling Interval" column of the r3perfagent.cfg file, as shown in Specifying Remotely Monitored Hosts in the r3perfagent.cfg File on page 214. The default polling intervals for the performance monitors are, with one or two exceptions, between 15 and 60 minutes.

For example, if you reduce the polling interval of all the performance monitors to one (1) minute, the performance-monitor scheduler tries to start all the performance monitors each time it runs. If there are ten monitors and each monitor takes ten seconds to respond, then the scheduler will already be out of synchronization by the time the scheduler starts its second run. You will have to increase the polling interval for the various performance monitors accordingly.

2 Disable Remote Monitoring

If you have enabled remote monitoring for the r3perfagent performance monitor, network problems could mean that requests for information from the remote server are not being answered in a timely fashion. Try disabling remote monitoring for a short while to test if this is the reason the r3perfagent performance monitor is having problems. You

can do this for one individual remote host, or all remote hosts (if there are more than one). For more information about remote monitoring with the SPI for SAP performance monitor, see Remote Performance Monitoring on page 214.

The r3perfagent.cfg Configuration File

The SPI for SAP provides a default configuration for the r3perfagent monitor; the default file works without modification immediately after installation. However, if you want to set up the r3perfagent monitor for your particular SAP environment, you can modify the r3perfagent.cfg file by enabling or disabling the keywords in the following list and, where necessary, setting or modifying the appropriate parameters:

TraceLevel

The TraceLevel keyword accepts the following parameters:

TraceLevel =<Hostname> =<TraceLevel>

— Hostname:

=ALL Monitor all hosts with the SPI for SAP. This is the default

setting.

=<SAP_host> The name of an SAP server, where you want to specify a trace

level. Use a new line for each individual host.

— TraceLevel:

=0 Disable. This is the default setting.

- =1 Log only error messages
- =2 Log all messages
- =3 Log only debug messages. Note that this trace level logs a lot of information and could very quickly lead to a very large trace file.

TraceFile:

The TraceFile keyword accepts the following parameters:

Tracefile =<Hostname> =<Filename>

— Hostname:

=ALL Monitor all SAP servers with the SPI for SAP. This is the default setting

=<*SAP_host*> The name of a specific host where tracing is enabled and you want to specify a trace level.

— Filename:

=r3perfmon.log - This is the default setting, which writes the log file to the default log file directory. Alternatively, you can specify the name of the file to which you want to write the trace log and, if necessary, the path. The path can be either absolute or relative to the working directory.

If you use standard SPI for SAP tools to start the r3perfagent, the working directory is the directory where the r3perfagent binary resides, for example in UNIX operating systems: /var/opt/OV/bin/R3PerfAgent/bin. For more information about the location of the r3perfagent binaries, see Locating the SPI for SAP R/3 Performance Agent Files.

• AgentHostname

Make sure that the AgentHostname keyword set to ALL.

SyncBack

The SyncBack keyword accepts the following parameters:

SyncBack = <Enable | Disable > = <SyncBack Threshold >

— Enable/Disable:

=0 Disable the scheduler synchronization

=1 Enable the scheduler synchronization. This is the default setting.

— SyncBack Threshold:

=< n > mins

The difference in minutes between defined and actual schedules. If the SyncBack threshold is reached, for example, when the scheduler is "n" minutes behind schedule, the scheduler restarts to return to the defined schedule. The SyncBack threshold should be *higher* than the Message Threshold value set in association with the BehindSyncMessage keyword so that you receive a message warning about schedule problems *before* the scheduler restarts.

BehindSyncMessage

The BehindSyncMessage keyword accepts the following parameters:

```
BehindSyncMessage =<Enable|Disable> =<OpC Severity>
=<OpC Object> =<OpC MsqGroup> =<Message Threshold>
```

— Enable/Disable:

=0 Disable the sending of a behind-schedule message.

=1 Enable the sending of a behind-schedule message. This is the default setting.

— OpC Severity:

=WARNING The severity of the behind-schedule message sent. This is the default value.

— OpC Object:

=r3perfagent The HPOM for Windows object to associate with the behind-schedule message. This is the default value.

— OpC MsgGroup:

=R3_General The HPOM for Windows message group to which the behind-schedule message belongs. This is the default value.

— Message Threshold:

=< n> mins

The elapsed time in minutes before a behind-schedule message is sent to the HPOM for Windows management server. The message-threshold value should be *less* than the SyncBack Threshold value set in association with the SyncBack keyword so that you receive a message warning about schedule problems *before* the scheduler restarts.

RemoteMonitoring

The RemoteMonitoring keyword accepts the following parameters:

RemoteMonitoring =<LocalHost> =<RemoteHost>

LocalHost

This is the name of the host where the SPI for SAP software is running and whose performance agent will be used to remotely monitor the SAP server defined in "Remotehost".

RemoteHost

This is the name of the *remote* SAP server that you want to monitor using the SPI for SAP on the SAP server defined in "Localhost". Although the remote host does not have the SPI for SAP software installed and is *not usually* an HPOM for Windows managed node, it must appear in the HPOM for Windows node list.

For more information, see Remote Performance Monitoring on page 214.

PerfMon

The Perfmon keyword *requires* a value for the following parameters:

```
PerfMon =<SAP Hostname> =<SAP System> =<SAP Number> \
=<SAP Client> =<RFC FUNCTION> =<Enable|Disable> \
=<Polling Interval> =<Hold Connection>
```

— SAP Hostname:

=ALL Monitor all SAP hosts with the SPI for SAP. This is the default setting.

=<*SAP_host*> The host name of a specific SAP server whose performance you want to monitor. Use a new line for each individual host

— SAP System:

=ALL Monitor all SAP Systems with the SPI for SAP. This is the default setting.

=<*SAP_SID*> The ID of a SAP System whose performance you want to monitor, for example, DEV. Use a new line for each individual SID.

— SAP Number:

=ALL Monitor all SAP numbers with the SPI for SAP. This is the default

setting.

=<Instance> The number of a specific SAP instance whose performance you want

to monitor, for example, 00, 99. Use a new line for each new SAP

number.

— SAP Client:

=ALL Monitor all SAP clients with the SPI for SAP. This is the default

setting.

=<*ClientID*> The number of a specific SAP client whose performance you want to

monitor, for example, 099. Use a new line for each SAP client.

— RFC FUNCTION:

=<metricname>_PERF, where metricname refers to the specific metric list you want the performance monitor to use, for example, DBINFO_PERF or SAPMEMORY_PERF. For more information about the possible values you can use, see The SPI for SAP Performance Monitors on page 221.

— Enable/Disable:

=0 Disable the performance monitor

=1 Enable the performance monitor. This is the default setting.

— Polling Interval:

=nn nn is the time in minutes between each run of the performance monitor

— Hold Connection:

=0 Disable: close the RFC connection after the call has completed. This is the default setting.

=1 Enable: keep the RFC connection open after the call has completed

Managing the SPI for SAP R/3 Performance Agent

You can control the SPI for SAP R/3 Performance Agent using command-line options, which differ according to the platform and operating system. You can manage the SPI for SAP R/3 Performance Agent either by using command-line options or the tools that are installed by the SPI for SAP.

SPI for SAP R/3 Performance Agent Command Line Syntax

You an use the following options with the r3perfagent command on UNIX managed nodes to control the SPI for SAP R/3 Performance Agent from the command line:

- r3perfagent start
- r3perfagent stop
- r3perfagent status

You can use the following syntax with the r3perfagent command on Windows managed nodes to control the SPI for SAP R/3 Performance Agent from the command line:

• r3perfagent_service -i
registers the r3perfagent service

• r3perfagent_service -u

deregisters the r3perfagent service

 r3perfagent_service -s starts the r3perfagent service

• r3perfagent_service -e stops the r3perfagent service

You can also use the Services option in the Windows Control Panel to control Windows services.

SAP Logins for the SPI for SAP R/3 Performance Agent

The SPI for SAP R/3 Performance Agent requires access to SAP to collect SAP-related metrics, which it then uses to generate reports and graphs. You define the SAP login for the SPI for SAP R/3 Performance Agent during the installation and configuration of the SPI for SAP. You also need to copy the combination of SAP user-name and password to the central SPI for SAP configuration file, r3itosap.cfg, which the SPI for SAP monitors and agents use to login to SAP.

This is particularly important for the SPI for SAP R/3 Performance Agent, which reads the SAP log-in information in the r3itosap.cfg *once only*, on startup, and will not start if it cannot log in to SAP. The SPI for SAP R/3 Performance Agent attempts to log in to SAP and, if it fails, sends a message to HPOM for Windows indicating that it was unable to start as a result of authorization problems.



Note that SAP has a security mechanism which blocks further logins from a user who tries (and fails) to login to SAP a given number of times. This number of failed logins could quickly be reached by the SPI for SAP R/3 Performance Agent if the SAP username/password for the SPI for SAP is changed in SAP but the changes to the SAP log-in details are not updated in the r3itosap.cfg file.

If you change the SAP user name-password combination that the SPI for SAP uses to log in to SAP, you need to make sure that the changes are reflected in the r3itosap.cfg file and, in addition, that the SPI for SAP components which use the information in the r3itosap.cfg are restarted to make them aware of the changes.

Best of all, stop the SAP/Performance Agent *before* you change the SAP user/password which the SPI for SAP needs for access to SAP, as follows:

1 Stop the SAP/Performance Agent

Stop the SAP/Performance Agent on all HPOM for Windows managed nodes where it is running. On each managed node, enter:

r3perfagent stop

2 Login to SAP

Login to SAP as the administrator and change the user-password combination that SPI for SAP uses to log in to SAP, as required.

Note that SAP requires you to change the password for dialog users more frequently than other types of SAP users.

3 Update the configuration file

Update the SPI for SAP configuration file, r3itosap.cfg, with the changes you have made to the SAP user and password and re-deploy to the managed nodes.

4 Restart the SAP/Performance Agent

Restart the SAP/Performance Agent on each of the HPOM for Windows managed nodes where the SAP/Performance Agent is running. On each managed node, enter:

r3perfagent start



The SPI for SAP cannot collect performance metrics during the period when the SAP/Performance Agent is not running.

SAP/Performance agent Tools

Table 71 shows which HPOM for Windows tools are available for the SPI for SAP R/3 Performance Agent in the appropriate SPI for SAP tool group—SAP R/3 NT or SAP R/3 UN*X.

Table 71 Performance Agent Tools

Tool Name	SAP R/3 NT	SAP R/3 UN*X
PerfAgt START	✓	✓
PerfAgt STOP	✓	✓
PerfAgt STATUS		√

The SPI for SAP Performance Monitors

The SPI for SAP performance monitors can be one of two types: **snapshot** or **time-frame**. A snapshot monitor runs once and gathers only one set of values. Snapshot monitors need to run on a regular basis to create a comprehensive picture of the performance of the SAP NetWeaver environment. Time-frame monitors run, as the name suggests, over a period of time. Most SPI for SAP performance monitors do not make use of alert types or parameters.

The following SPI for SAP performance monitors are available with the SPI for SAP and are explained in greater detail in the individual sections that follow:

DBINFO_PERF

Monitors database-performance analysis values

DOCSTAT_PERF

Collects the document volume statistics for the last full hour

• EP PERF

Monitors the status and performance of the SAP Enterprise Portal

ICMSTAT_PERF

Monitors the status and performance of the SAP Internet Communication Manager

JOBREP_PERF

Counts the number of jobs per state (scheduled, running)

SAPBUFFER_PERF

Returns values for the use of SAP buffers for an SAP instance

SAPMEMORY_PERF

Monitors SAP memory use by SAP users for an SAP instance

• SPOOL PERF

Counts the number of spool requests in different states

• STATRECS_PERF

Returns the response/net times of defined transactions

SYSUP_PERF

Monitors the status of the SAP NetWeaver instances

UPDATE PERF

Monitors the number of update processes

USER_PERF


Monitors the number of users and user sessions per SAP client

WLSUM PERF

Collects the performance-workload statistics hourly

WP_PERF

Monitors the number of users/sessions per SAP client for an SAP application server



DBINFO_PERF

The DBINFO_PERF performance monitor returns a set of values as they are displayed in the SAP database-performance analysis page. This information can be used to detect database performance problems and assess whether database tuning could improve database performance.

The DBINFO_PERF performance monitor works *only* with Oracle database data structures. It does *not* work with data structures from other database products.

Type

The DBINFO_PERF performance monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. The DBINFO_PERF performance monitor collects SID-related metrics and should run only once per monitored SID, that is: either on the SAP central instance or on *one* application server.

Frequency

It is recommended to run the DBINFO_PERF performance monitor once every 15 minutes.

Datasource

The DBINFO_PERF performance monitor uses the SAP transaction **ST04** (DB performance overview) as its data source.

Metrics

Table 72 shows the values in the performance table returned by the DBINFO_PERF performance monitor.

Table 72 DBINFO_PERF Performance Monitor Metrics

Order	Metric Name	Description	% Value	Cumul- ation
1	CPUUSAGE	Database CPU usage		No
2	BUFPREADS	Physical reads		Yes
3	BUFPWRITES	Physical writes		Yes
4	BUFQUAL	Quality of data base buffer pool	%	No
5	BUFSIZE	Database buffer pool size		Static
6	BUFWAITS	Buffer busy waits		Yes
7	BUFWTIME	Buffer busy wait time		Yes
8	DICTSIZE	Dictionary cache size		Static
9	DDQUAL	Quality of Data Dictionary cache	%	No
10	LOGBLOCKS	Redo log blocks written		Yes
11	LOGENTRIES	Redo log buffer entries		Yes
12	LOGSIZE	Redo log buffer size		Static
13	LOGFAULT	Allocation error rate of redo log buffer	%	No
14	LOGALLOC	Redo log buffer allocation retries		Yes
15	ROLLBACKS	Rollbacks		Yes

Table 72 DBINFO_PERF Performance Monitor Metrics (cont'd)

Order	Metric Name	Description	% Value	Cumul- ation
16	SCANLONG	Long table scans		Yes
17	SORTDISK	Sort disk		Yes
18	SORTMEM	Sort memory		Yes
19	SORTROWS	Sort rows		Yes

DOCSTAT_PERF

The performance monitor, DOCSTAT_PERF, collects statistics relating to the volume of documents generated and processed for the last full hour. You can only configure this monitor once for every SAP NetWeaver System that you want to monitor.

Type

The DOCSTAT_PERF performance monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. The DOCSTAT_PERF performance monitor collects SID-related metrics and should run only once per monitored SID, that is: either on the SAP central instance or on *one* application server.

Frequency

It is recommended to run the DOCSTAT_PERF performance monitor hourly.

Data Source

The DOCSTAT_PERF performance monitor uses the SAP transaction **ST07** (quantity structure) as its data source.

Metrics

Table 73 shows the values in the performance table returned by the DOCSTAT_PERF performance monitor.

Table 73 DOCSTAT_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	SID	The SAP System ID
2	DESCRIPTION	Description of an application-monitor object
3	CNTHEADER	Document headers
4	CNTITEM	Document items
5	CNTDIV	Document Division
6	CNTTOTAL	Total number of records

Table 73 DOCSTAT_PERF Performance Monitor Metrics (cont'd)

Order	Metric Name	Description
7	CNTLINE	Number of line items
8	CNTCHGDOC	The number of changed documents
9	CNTTEXT	Text

EP_PERF

The performance monitor, EP_PERF, monitors the status and performance of the SAP Enterprise Portal (EP) including (but not limited to) all the J2EE components on which it relies. For more information about the SPI for SAP's dedicated monitor for the SAP Enterprise Portal, see The SAP Enterprise-Portal Monitor on page 89.



EP_PERF is applicable wherever Enterprise Portal is available.

Type

The EP_PERF performance monitor is of type *time-frame* and does not make use of alert types or parameters. One monitor run gathers only one value set. The EP_PERF performance monitor collects SID-related metrics and should run only once per monitored SID, that is: either on the SAP central instance or on *one* application server.

Frequency

It is recommended to run the EP_PERF performance monitor approximately once every fifteen minutes.

Datasource

The EP_PERF monitor uses the SAP function /HPOV/OV_EP_PERF_MONITOR_2 as its data source.

Metrics

Table 74 shows the values in the performance table returned by the EP_PERF performance monitor.

Table 74 EP_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	SID_EP	ID of the SAP System hosting the Enterprise Portal
2	HOSTNAME_EP	Name of the system hosting the Enterprise Portal
3	START_TIME_EP	The time at which the EP-monitor run starts

Table 74 EP_PERF Performance Monitor Metrics (cont'd)

Order	Metric Name	Description
4	NO_REQ_EP	Number of requests to the Enterprise Portal
5	AVG_RESP_TIME_EP	Average time to respond to requests to the Enterprise Portal
6	AVG_CPU_TIME_EP ^a	Average CPU time required to respond to requests to the Enterprise Portal
7	REQ_PER_SEC_EP	Number of requests per second to the Enterprise Portal
8	AVG_OUTBND_DATA_EP	Average amount of out-bound data per request to the Enterprise Portal
9	ACC_RESP_TIME_EP	Accumulated response time of requests to the Enterprise Portal
10	ACC_CPU_TIME_EP (a)	Accumulated CPU time required to respond to EP requests
11	OUTBND_DATA_REQ_EP	Requests providing outbound data
12	ACC_OUTBND_DATA_EP	Amount of accumulated outbound data (in bytes)
13	NO_COMPCALLS_REQ_EP	Number of component calls by all requests to the Enterprise Portal
14	AVG_CMPCALLPERREQ_EP	Average number of component calls per EP request
15	VALID_MONDATA_REQ_EP	EP requests providing correct monitor data
16	REQ_NOT_CORR_CLSD_EP	EP requests with components that were not correctly closed
17	REQCLSD_TOOMNYCMP_EP	Number of EP requests that were closed because of too many components
18	REQS_RUNLEVEL_0_EP	EP requests running with level 0
19	REQS_RUNLEVEL_1_EP	EP requests running with level 1
20	REQS_RUNLEVEL_2_EP	EP requests running with level 2
21	USRS_SINCE_1_REQ_EP	Number of users making EP requests since the first request
22	USRS_SINCE_LSTRST_EP	Number of users making EP requests since the last user reset

Table 74 EP_PERF Performance Monitor Metrics (cont'd)

Order	Metric Name	Description
23	LST_REQ_RST_TSTMP_EP	Time of the last EP-request reset
24	LST_CMPREQ_TSTMP_EP	Time of the last component reset
25	LST_USRREQ_TSTMP_EP	Time of the last EP-user reset

a. Only for SAP NetWeaver portal version 7.0



If the performance monitor EP_PERF cannot find any data or it encounters a null string in SAP CCMS, it logs some performance metrics as '0' (zero); this behavior is expected.

ICMSTAT PERF

The performance monitor, ICMSTAT_PERF, monitors the status and performance of the SAP Internet Communication Manager (ICM).

Type

The ICMSTAT_PERF performance monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. The ICMSTAT_PERF performance monitor collects application-server-specific metrics; it should run on each application server whose performance you want to monitor.



ICMSTAT_PERF monitor is applicable till 6.40.

Frequency

It is recommended to run the ICMSTAT_PERF performance monitor approximately once every fifteen minutes.

Datasource

The ICMSTAT_PERF monitor uses the SAP transaction ${\tt SMICM}$ (ICM monitor) as its data source.

Table 75 shows the values in the performance table returned by the ICMSTAT_PERF performance monitor.

Table 75 ICMSTAT PERF Performance Monitor Metrics

Order	Metric Name	Description
1	ICM_Status	The status of the Internet Communication Manager
2	Max_Threads	The defined max. number of open threads allowed by the ICM
3	Peak_Threads	Peak number of open threads in the ICM in a given period
4	Cur_Threads	Number of currently open threads in the ICM
5	Max_Connections	The defined max. number of open connections allowed by the ICM
6	Peak_Connections	Peak number of connections in the ICM in a given period
7	Cur_Connections	Number of current connections in the ICM
8	Max_QueueEntries	The max. number of queued requests allowed by the ICM defined in: icm/req_queue_len
9	Peak_QueueEntries	Peak number of queued requests in the ICM in a given period
10	Cur_QueueEntries	Number of currently queued requests in the ICM
11	Running_Threads	Number of work threads waiting for a request (idle)
12	Dead_Threads	Number of work threads in a problematic state, for example, dead or hanging
13	Processed_Threads	Number of work threads currently processing a request

JOBREP_PERF

The JOBREF_PERF performance monitor counts the jobs per state in the time period between the end date and time of the last monitor run and the start date and time of the actual monitor run.

Type

The JOBREF_PERF monitor is of type *time-frame* and does not make use of alert types or parameters. One monitor run gathers only one value set. The JOBREF_PERF performance monitor collects SID-related metrics and should run only once per monitored SID, that is: either on the SAP central instance or on *one* application server.

Frequency

It is recommended to run the JOBREF_PERF performance monitor between once an hour and once a day.

Datasource

The JOBREF_PERF monitor uses the SAP transaction ${\bf SM37}$ (background job overview) as its data source.

Metrics

Table 76 shows the values in the performance table returned by the JOBREF_PERF performance monitor.

Table 76 JOBREF_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	RUNNING	The number of jobs with status <i>running</i> since the last monitor run
2	READY	The number of jobs with status <i>ready</i> since the last monitor run
3	SCHEDULED	The number of jobs with status $scheduled$ since the last monitor run
4	RELEASED	The number of jobs with status <i>released</i> since the last monitor run
5	ABORTED	The number of jobs with status <i>aborted</i> since the last monitor run
6	FINISHED	The number of jobs with status <i>finished</i> since the last monitor run
7	PUT_ACTIVE	The number of jobs with status put_active since the last monitor run
8	UNKNOWN_STATE	The number of jobs with status $unknown$ since the last monitor run

SAPBUFFER_PERF

The SAPBUFFER_PERF performance monitor returns values for the use of SAP memory *buffers* by SAP users for a given instance, for example, hit ratios, buffer quality, free space available and so on in the NetWeaver repository, programs, and database tables.

Type

The SAPBUFFER_PERF monitor is of type *time frame*. The SAPBUFFER_PERF performance monitor collects application-server-specific metrics; it should run on each application server whose performance you want to monitor.

Frequency

It is recommended to run the SAPBUFFER_PERF performance monitor once every fifteen minutes.

Data Source

The SAPBUFFER_PERF monitor reads information from the SAP- buffers transaction **ST02**.

Metrics

Table 77 shows the values in the performance table returned by the SAPBUFFER_PERF performance monitor.

Table 77 SAPBUFFER_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	BUFFER_NAME	The name of the buffer
2	HITRATIO	Buffer object reads / logical requests. The buffer hit ratio appears as a percentage
3	ALLOCATED_SIZE	The amount of space allocated to the buffers a
4	FREE_SPACE	The amount of free space (KB) available in the buffer
5	FREE_SPACE_PERCENT	Available free buffer space as a percentage of total
6	MAXDIR_ENTR	The number of directories available for the buffer $^{\rm b}$
7	FREEDIR_ENTR	Number of free directories available for the buffer
8	FDIR_ENTR_PERCENT	Free directories available for the buffer as a percentage
9	BUFFER_SWAPS	Swap activity both inwards and outwards since System start ^c
10	BUFFER_SWAPS_DELTA	Difference between the number of buffer swaps measured in the current and previous monitor runs
11	DB_ACCESSES	The number of database accesses since System start ^d
12	DB_ACCESSES_DELTA	Difference between the number of database accesses measured in the current and previous monitor runs

a. Buffer size and "available buffer size" differ, because part of the buffer space is used for buffer management.

b. The buffer directories point to the location of the objects stored in the buffer.

c. Buffers swap objects out of the buffer to load a new object in, if insufficient free space or free directories exist.

d. Database access occurs when an object cannot be read from the buffer.

SAPMEMORY PERF

The SAPMEMORY_PERF performance monitor returns values for SAP memory use by SAP users for a given instance, for example, roll and paging areas, and extended memory.

Type

The SAPMEMORY_PERF monitor is of type *snapshot*: one monitor run gathers one value set. The SAPMEMORY_PERF performance monitor collects application-server-specific metrics; it should run on each application server whose performance you want to monitor.

Frequency

It is recommended to run the SAPMEMORY_PERF performance monitor once every fifteen minutes.

Data source

The SAPMEMORY_PERF monitor reads information from the SAP- buffers transaction **ST02**.

Metrics

Table 78 shows the values in the performance table returned by the SAPMEMORY_PERF performance monitor.

Table 78 SAPMEMORY_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	MEMORY_AREA	The type of memory buffer
2	CURRENT_USE_PERCENT	The amount of space currently used expressed as a percentage of the total available
3	CURRENT_USE	The amount of space currently used in KB
4	MAX_USE	The maximum value (max. use) since system startup
5	IN_MEMORY	The amount of space used in shared memory
6	ON_DISK	The amount of space used on the disk

SPOOL_PERF

The SPOOL_PERF performance monitor counts the number of spool requests present in different states.

Type

The SPOOL_PERF performance monitor is of type *time frame* and does not make use of alert types or parameters. One monitor run gathers only one value set. The SPOOL_PERF performance monitor collects SID-related metrics and should run only once per monitored SID, that is: either on the SAP central instance or on *one* application server.

Frequency

It is recommended to run the SPOOL_PERF performance monitor once every 10 to 30 minutes.

Data Source

The $SPOOL_PERF$ performance monitor uses the SAP transaction SPO1 (output controller) as its data source.

Metrics

Table 79 shows the values in the performance table returned by the SPOOL_PERF performance monitor.

Table 79 SPOOL_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	ALL_SJ	Total number of spool jobs
2	SJ_ARCHIVE	Number of spool jobs in status archive
3	PRINT_REQ	Total number of print requests
4	OPEN_PR	Number of open print requests
5	SUCCESS_PR	Number of successfully processed print requests
6	ERROR_PR	Number of Print requests with errors
7	FAILED_PR	Number of failed print requests

STATRECS_PERF

The STATRECS_PERF performance monitor reads the statistical records and returns the average response time per transaction.

The STATRECS_PERF performance monitor uses the alert types RESPONSE_TIME and the parameter TRANSACTION to restrict the data selected. The transactions monitored are specified in the parameter TRANSACTION. If this parameter is not specified, the average response time is reported for each transaction in the local statistics file for the specified time frame.

Type

The STATRECS_PERF performance monitor is *time-frame* based. Each run gathers only one value set. To collect a set of values, the monitor must be scheduled on a regular basis. Since various monitors have different requirements, you have to specify the interval for each monitor individually. This monitor uses the time frame between the last start and the current start times and considers only those transactions which complete within the specified time-frame.

The STATRECS_PERF performance monitor collects application-server-specific metrics; it should run on each application server whose performance you want to monitor.

Frequency

It is recommended that you configure the STATRECS_PERF performance monitor to run once a minute

Data Source

The STATRECS_PERF performance monitor uses the following SAP transaction as its data source:

• For SAP 7.0 and higher: STAD

For SAP 6.40 version:STAT

Metrics

Table 80 shows the values in the performance table returned by the STATRECS_PERF performance monitor.

Table 80 STATRECS PERF Performance Monitor Metrics

Order	Metric Name	Description
1	SAP_TCODE	Transaction code associated with the measured transaction. This metric is only visible with the HP Performance Manager.
2	SAP_RESPONSE_TI ME	Time SAP takes to respond
3	SAP_NET_TIME	Net Time
4	SAP_REC_COUNT	The number of times the measured transaction occurs

Configuring and Uploading STATRECS_PERF

To enable the STATRECS_PERF monitor, you must configure the r3perfstat.cfg file and upload the results into SAP. There are two possible configurations:

• Global: global_r3perfstat.cfg

Local: local_r3perfstat.cfg

To set and upload the STATRECS_PERF configurations:

Open and edit the r3perfstat.cfg configuration file

Use the configuration-file policy editor to modify the global_r3perfstat policy to suit the needs of your environment:

a In the details pane of the HPOM for Windows console, select and right-click the configuration-file policy global_r3perfstat. The global_r3perfstat policy is located in the folder:

Policy Management > Policy Groups > SPI for SAP > en

b Click the following option in the menu which pops up:

All Tasks > Edit...

HPOM for Windows displays the global_r3perfstat policy shown in Figure 23 on page 235.

2 Modify and save the r3perfstat.cfg configuration file

Change any values as required and save the file. The global_r3perfstat configuration-file policy resides on the HPOM for Windows management server; you must deploy it to the managed nodes whose statistical records you want to monitor and, in addition, upload it to SAP NetWeaver.



For local configuration files, we suggest you include the name of the machine for which the local configuration is intended in the local-configuration file name, for example; <machine_name>_r3perfstat.cfg. Note that local configuration settings override global ones.

3 Deploy the r3perfstat.cfg file to the managed node

You need to deploy the modified r3perfstat.cfg file to the SAP NetWeaver servers, whose statistical records you want to monitor with the SPI for SAP, as follows:

a Locate and right-click the configuration file r3perfstat.cfg and browse to the following option in the menu which pops up:

All Tasks > Deploy on...

- b In the Deploy Policies on... dialog which appears, select the managed nodes to which you want to deploy the new r3perfstat.cfg file, and then click **OK**.
- c Verify that the deployment completes successfully by monitoring progress in the Deployment Jobs pane at the bottom of the HPOM for Windows console.

4 Upload the new configuration to SAP NetWeaver

Upload the global_r3perfstat configuration to SAP NetWeaver using the Write Statistical Records tool, which you can find in the SAP R/3 Admin tools group.

Locate and right-click the Write Statistical Records tool and browse to the following option in the menu which pops up:

All Tasks > Launch Tool...

b In the Edit Parameters... dialog which appears, select the managed nodes where you want to launch the tool, and then click **OK**.

🕵 global_r3perfstat [1.0] (ConfigFile) <u>File View Help</u> Save and Save P General Data Configuration File Content: • HistoryPathUnix =ALL =/var/opt/OV/tmp HistoryPathAIX HistoryPathWinNT =ALL =/var/1pp/OV/tmp -C:\temp =ALL # AgentHostname hostname aliasname AgentHostname =ALL =default SAP # AlertMonFun SAP SAP SAP Alertmonitor Hostname System Number Client

=ALL

=ALL

=ALL

Load Template

=ALL

=ALL

=ALL

Save as Template

=STATRECS_PERF

=STATRECS_PERF =STATRECS_PERF

=STATRECS_PERF

About Template

Figure 23 Editing the r3perfstat.cfg File

Example:

#PerfMonFun

#PerfMonFun

#PerfMonFun

#PerfMonFun

Ready

SYSUP_PERF

The SYSUP_PERF performance monitor is used to determine whether the SAP NetWeaver system is available or not.

Example for statistical records

=ALL

=ALL

=ALL

=ALL

=ALL

=ALL

Type

The SYSUP_PERF performance monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set.

Frequency

The SYSUP_PERF performance monitor runs once a minute; the run frequency cannot be modified.

Data Source

The SYSUP_PERF performance monitor uses internal SAP RFC calls as its data source.

Table 81 shows the values in the performance table returned by the SYSUP_PERF performance monitor.

Table 81 SYSUP_PERF Performance Monitor Metrics

Metric Name	Description	
SYSTEM_STATUS	Status of the System (UP/DOWN) on the basis of the following values: SAP System available SAP System logon failure SAP System communication problems SAP System unknown Indicates that the performance agent was not running and could not collect any data.	

UPDATE PERF

The UPDATE_PERF performance monitor is used to determine whether update errors are occurring.

When the SAP NetWeaver system is behaving well, no update errors should occur. However, an update error can occur, if an update is performed on a database table record that has previously been deleted. A normal update process should not have to wait in status INIT for more than 5 minutes for an update task. If a greater number of work processes exist with the status INIT the reason could be that a table space is full.

Type

The UPDATE_PERF monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. The UPDATE_PERF performance monitor collects SID-related metrics and should run only once per monitored SID, that is: either on the SAP central instance or on *one* application server.

Frequency

It is recommended you configure the UPDATE_PERF performance monitor to run once a minute.

Data Source

The UPDATE_PERF monitor uses the SAP transaction **SM13** (update records) as its data source.

Table 82 shows the values in the performance table returned by the UPDATE_PERF performance monitor.

Table 82 UPDATE_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	ALL	Number of all VB-update tasks
2	INITIAL	Number of initial VB-update tasks
3	ERRONEOUS	Number of erroneous VB-update tasks
4	VB1	Number of update tasks having V1 executed
5	VB2	Number of update tasks having V2 executed

USER PERF

The USER_PERF performance monitor provides important information about the number of users and user sessions per SAP client for a given SAP application server.

Type

The USER_PERF monitor is of type *snapshot*: one monitor run gathers one value set. The USER_PERF performance monitor collects application-server-specific metrics; it should run on each application server whose performance you want to monitor.

Frequency

It is recommended to run the USER_PERF performance monitor once every five minutes.

Data source

The USER_PERF performance monitor the SAP transaction ${\bf SM04}$ (overview of users) as its data source.

Table 83 shows the values in the performance table returned by the USER_PERF performance monitor.

Table 83 USER PERF Performance-Monitor Metrics

Order	Metric Name	Description
1	USER_CLIENT	The SAP client number associated with the users
2	USER_CNT	The number of users logged in per client
3	SESSION_CNT	The total number of user sessions per client

WLSUM_PERF

The performance monitor, WLSUM_PERF, collects the performance workload statistics for the last full hour. You can display the workload statistics for all task types, for example, dialog, background, RFC, ALE, or update. The WLSUM_PERF performance monitor is mandatory; you must configure it for every application server that you want to monitor.



The data collection for the WLSUM monitor is based on the internal SAP job COLLECTOR_FOR_PERFORMANCEMONITOR. This job must run with the same frequency as specified for WLSUM_PERF in r3perfagent.cfg. WLSUM_PERF will then pick up the data collected by the last run of COLLECTOR FOR PERFORMANCEMONITOR.

Type

The WLSUM_PERF performance monitor is of type *time-frame* and does not make use of alert types or parameters. One monitor run gathers only one value set. The WLSUM_PERF performance monitor collects application-server-specific metrics; it should run on each application server whose performance you want to monitor.

Frequency

Due to the way in which the performance monitor, WLSUM_PERF, measures and records time, it is *mandatory* to configure the WLSUM_PERF performance monitor to run once an hour.

Data source

The WLSUM_PERF performance monitor uses the SAP transaction **ST03** (workload analysis) as its data source.

Table 84 shows the values in the performance table returned by the WLSUM_PERF performance monitor.

Table 84 WLSUM_PERF Performance Monitor Metrics

Order	Metric Name	Description
1	Hostname	The SAP System hostname
2	SID	The SAP System ID
3	INSTANCE	The SAP instance number, if SAP version < 4.6x
4	TASKTYPE	Type of SAP NetWeaver task (RFC, dialog)
5	CNT	The number of dialog steps
6	DBACTIVCNT	Counter for database-active dialog steps
7	RESPTI	Time that elapses between a dialog sending a request to the dispatcher and receiving a response
8	CPUTI	CPU time used in the work process
9	QUEUETI	The time an unprocessed dialog step waits in the dispatcher queue for a free work process
10	LOADGENTI	Time taken loading and generating objects such as ABAP source code and screen information from the database
11	COMMITTI	Time required for commit to complete
12	DDICTI	Time required for Data Dictionary
13	QUETI	Time required for batch-input queue
14	CPICTI	Time required for RFC and CPI-C
15	ROLLINCNT	Number of roll-ins (rolled-in user contexts)
16	ROLLINTI	Processing time for roll-ins
17	ROLLOUTCNT	Number of roll-outs (rolled-out user contexts)
18	ROLLOUTTI	Processing time for roll-outs
19	READDIRCNT	Number of direct read accesses
20	READDIRTI	Time for direct read access
21	READSEQCNT	Number of sequential read attempts
22	READSEQTI	Time for sequential read accesses
23	CHNGCNT	Number of modified database accesses
24	CHNGTI	Time for modified database accesses
25	BYTES	Number of bytes

Table 84 WLSUM_PERF Performance Monitor Metrics (cont'd)

Order	Metric Name	Description
26	GUITIME	Total time taken for the dispatcher to execute a GUI request
27	GUICNT	Count of GUI steps
28	GUINETTIME	Time taken for the application server to respond to a request from the SAP GUI

WP PERF

The SPI for SAP performance agent uses the WP_PERF monitor to detect performance problems concerning SAP work processes. For example, WP_PERF can detect and report on the following situations:

- Work processes need to wait for semaphores
- Work processes are in private mode
- A dialog work-process does not return to idle after use/release

Type

The WP_PERF monitor is of type *snapshot* and does not make use of alert types or parameters. One monitor run gathers only one value set. The WP_PERF performance monitor collects application-server-specific metrics; it should run on each application server whose performance you want to monitor.

Frequency

It is recommended that you configure the WP_PERF performance monitor to run once every 15 minutes.

Data Source

The WP_PERF performance monitor uses SAP transaction **SM50** (work- process overview) as its data source.

Metrics

Table 85 shows the values in the performance table returned by the performance monitor.

Table 85 WP PERF Performance Monitor Metrics

Order	Metric Name	Description
1	ALL_WP	Number of all work processes
2	SEMAPHORE_WP	Number of work processes waiting on a semaphore
3	DEBUG_WP	Number of work processes in debug mode

Table 85 WP_PERF Performance Monitor Metrics (cont'd)

Order	Metric Name	Description	
4	LONG_RUNNING	Number of long running dialog wp	
5	PRIVAT_WP	Number of dialog wp in private mode	
6	NOSTART_WP	Number of dialog wp with no restart capability	
7	DIA_IDLE	Number of idle dialog work processes	
8	DIA_ALL	Number of dialog work processes	
9	DIA_RUNNING	Number of running dialog wp	
10	BTC_IDLE	Number of idle batch work processes	
11	BT_ALL	Number of batch work processes	
12	BTC_RUNNING	Number of running batch wp	
13	SPO_IDLE	Number of idle spool work processes	
14	SPO_ALL	Number of spool work processes	
15	SPO_RUNNING	Number of running spool wp	
16	ENQ_IDLE	Number of idle enqueue work processes	
17	ENQ_ALL	Number of enqueue work processes	
18	ENQ_RUNNING	Number of running enqueue wp	
19	UPD_IDLE	Number of idle update work processes	
20	UPD_ALL	Number of update work processes	
21	UPD_RUNNING	Number of running update wp	
22	UPD2_IDLE	Number of idle update2 work processes	
23	UPD2_ALL	Number of update2 work processes	
24	UPD2_RUNNING	Number of running update2 work processes	

Removing the SPI for SAP R/3 Performance Agent

To remove the SPI for SAP R/3 Performance Agent from the managed node, you need to perform the following steps in the order indicated:

- Before starting the process of removing the SPI for SAP R/3 Performance Agent from the managed node, make sure that you *stop* the SPI for SAP R/3 Performance Agent, for example;
 - Use the SPI for SAP application, PerfAgt Stop, which resides in the SAP R/3 UN*X or SAP R/3 NT Tools Group.

- Login to the SAP managed node and use the following command on the command line:
 - r3perfagent stop
- 2 In the HPOM for Windows console, browse to the following tools folder:

Tools > SPI for SAP > SAP R/3 Admin

- 3 Select and right-click the appropriate Performance Package tool (according to the operating system) for the SAP System environment as illustrated below:
 - Remove Performance Package (UNIX)
 - Remove Performance Package (Windows)
- 4 Start the Remove Performance Package tool you have selected using the following menu option:

All tasks > Launch Tool...

- 5 Select the SAP managed node(s) from which you want to remove the Performance Package. Remember to ensure that the nodes you select correspond to the operating system for the chosen tool (UNIX or Microsoft Windows).
- 6 Click **Launch...** to start the removal process.

7 Monitoring SAP NetWeaver Web Application Server (J2EE)

The SPI for SAP helps you monitor the health of the J2EE engine of the SAP NetWeaver Web Application Server. With the help of a series of policies, you can collect metrics indicating the health, availability, and performance of the J2EE engine of an SAP NetWeaver Web Application Server. All the policies, necessary for monitoring the J2EE engine of SAP NetWeaver, are grouped under the SAP NetWeaver Java Monitoring policy group.

The policies under the SAP NetWeaver Java Monitoring policy group cannot be used to monitor the Web AS (Java) environment of an SAP R/3 environment. For an SAP R/3 deployment, you can use the SAPSPI_CCMS_Monitors.car transport, which is distributed with the SPI for SAP, to monitor the Web AS (Java) environment.


This version of the SPI for SAP helps you monitor the SAP NetWeaver Web Application Server (J2EE) for SAP NetWeaver 6.40, 7.00, and 7.10 only.

Before You Begin

Before you start monitoring the SAP NetWeaver Web Application Server (J2EE) environment, follow these steps:


1 Deploy instrumentation.

Deploy the SPI for JMX Application Server instrumentation group (along with the SPI for SAP instrumentation group) on all the nodes where you want to monitor the SAP NetWeaver Web Application Server (J2EE) metrics.



2 Verify the location of necessary JAR files.

Make sure that the following JAR files are included in the specified locations on the SAP NetWeaver system:



The following are the jar file locations for Netweaver 7.0.

- logging.jar (in the <SAP_home>\j2ee\admin\lib directory)
- exception.jar (in the <SAP_home>\j2ee\admin\lib directory)
- com sap pj jmx.jar (in the <SAP_home>\j2ee\admin\lib directory)
- sapj2eeclient.jar (in the <SAP_home>\j2ee\j2eeclient directory)
- jmx.jar (in the <SAP_home>\j2ee\admin\logviewer_standalone\lib
 directory)

The following are the jar file locations for Netweaver 7.1.

- sap.com~tc~exception~impl.jar (in the
 <SAP-home>\j2ee\j2eeclient\sap.com directory)

3 Provide access-related details.

You must provide the SPI for SAP with the details to access SAP NetWeaver Web Application Servers. With the help of the <code>global_SiteConfig</code> policy (which uses the <code>SiteConfig</code> configuration file), you can provide the SPI for SAP with the access details of an SAP NetWeaver Web Application Server and enable the SPI for SAP to collect necessary metrics. To provide the SPI with all the access-related information, follow these steps:

- In the HPOM console, open the policy dialog of the global_SiteConfig policy from Policy groups > SPI for SAP > en.
- b Specify the value for every attribute of the SAP NetWeaver server that you want to monitor. See The SiteConfig File on page 245 for information on all the attributes.
- c Repeat step b for all the nodes that you want to monitor.
- The global_SiteConfig policy enables you to add the access details of all the SAP NetWeaver nodes that you want to monitor into the same file (see The SiteConfig File on page 245).
- d Click Save and Close.
- e Deploy the global SiteConfig policy on the node.

The SiteConfig file stores the password in an encrypted format. The password encryption happens in the managed node as part of Netweaver configuration and not on the management server.

Example of SiteConfig File in encrypted format

```
NUM_SERVERS=1
SERVER1_NAME=sapspil2.example.com
SERVER1_LOGIN=j2ee_admin
SERVER1_PASSWORD=ENCRYPTED 9pFfwhMzeSIx+BilJKRPlA==

SERVER1_PORT=50004
SERVER1_VERSION=71
SERVER1_HOME=/usr/sap/<SID>/DVEBMGS00
SERVER1_JAVA_HOME=/usr/sap/<SID>/DVEBMGS00\exe\sapjvm_5
SERVER1_SID=<SID>
SERVER1_SID=<SID>
SERVER1_NR=00
SERVER1_CLUSTERNODEID=<Cluster_ID>, where Cluster_ID is the cluster ID of the central instance
SERVER1_AS_DETAILS=null
SERVER1_AS_NUM=0
SERVER1_AS_NUM=0
SERVER1_AS_NUM=0
SERVER1_AS_NAME=null
```

SERVER1_AS1_LOGIN=null SERVER1_AS1_PASSWORD=null SERVER1_AS1_PORT=null



If you have upgraded the SPI for SAP from a previous version, the Siteconfig file for SAP Netweaver 7.0 will not work in the new environment. You need to configure the SiteConfig file in accordance with the new requirements.

4 Create necessary configurations on nodes.

Run the Create SPI for SAP NetWeaver Configtool to create necessary configurations on nodes. Run this tool on all the SAP NetWeaver Web Application Servers. This tool is available in the SPI for SAP > SAP R/3 Admin group in the HPOM console.

5 Test the monitoring setup.

The setup that you have prepared, by performing step 1 through step 3, can be tested with the help of the Check the SAP NetWeaver Connectiontool. From the HPOM console, run the Check the SAP NetWeaver Connectiontool (SPI for SAP > SAP R/3 Admin) on all the nodes that you want to monitor.

6 Deploy the collection definition.

The SPISAP-UpdateNWMetricConfig -1d policy (included in the SPI for SAP > en > SAP NW Java Monitoring 7.0 > Configure policy group and SPI for SAP > en > SAP NW Java Monitoring 7.1 > Configure) contains the mechanism to collect data from the SAP NetWeaver Web Application Servers. The policy provides the SPI with the following details:

- Types of information to be collected
- Types of information to be stored into the data store
- Types of information to be compared with preset thresholds

You must deploy the SPISAP-UpdateNWMetricConfig -1d policy on all the SAP NetWeaver Web Application Server nodes.

7 Create data sources.

Before the SPI for SAP starts logging the collected data into the data store on the node, necessary data tables must be created. The SPI for SAP and HP Operations environment use these data tables as the source of data to perform analysis, report building, and graph generation. When you install and configure the SPI for SAP R/3 Performance Agent on nodes, these data sources (data tables) are automatically created into the data store. Install and configure the SPI for SAP R/3 Performance Agent on the SAP NetWeaver Web Application Server nodes as described in Installing the SPI for SAP R/3 Performance Agent on page 206 and Configuring the SPI for SAP R/3 Performance Agent on page 209.



Data logging should always be enabled in the SPIConfig file which is available under < OVDataDir > / conf/sapspi/global

For example, DATA_LOGGING_ENABLED=TRUE

The SiteConfig File

The SiteConfig.cfg file contains the access-related details of an SAP NetWeaver Web Application Server. You can modify the contents of this file from the global_SiteConfig policy. You must specify values of the following attributes in this file:

The following SiteConfig.cfg file is an example of SAP Netweaver Web Application Server 7.0.

- NODE: The fully-qualified domain name of the SAP NetWeaver server that you want to monitor.
- NUM_SERVERS: The number of Web Application Server instances that you want to monitor on the node.

You can monitor only one instance of Web Application Server for every SAP NetWeaver node. Always set this property to 1.

- SERVER1_NAME: The fully-qualified domain name of the SAP NetWeaver 7.0 Web Application Server.
- SERVER1 LOGIN: The user name to log on to the server.
- SERVER1 PASSWORD: The password for the above-mentioned user.
- SERVER1 PORT: The port number for the Web Application Server.
- SERVER1_VERSION: The version of SAP NetWeaver on the node.
- SERVER1 HOME: The SAP home directory on the node.
- SERVER1 JAVA HOME: The JAVA HOME location on the node.
 - Always use the forward slash character (/) while specifying location-related details in the SiteConfig file.

After you specify the values for the aforementioned attributes for all the SAP NetWeaver nodes that you want to monitor, you must place the SiteConfig file on the node by deploying the global SiteConfig policy on the node.

Example SiteConfig File

```
NODE = sapspiw1.example.com

{

NUM_SERVERS=1

SERVER1_NAME=sapspiw2

SERVER1_LOGIN=j2ee_admin

SERVER1_PASSWORD=password

SERVER1_PORT=50104

SERVER1_VERSION=7.0

SERVER1_HOME=/usr/sap/GBR/DVEBMGS00

SERVER1_JAVA_HOME=/opt/java1.4

}

NODE = sapspiw2.example.com

{

NUM_SERVERS=1

SERVER1_NAME=sapspiw2

SERVER1_LOGIN=j2ee_admin

SERVER1_PASSWORD=password
```

```
SERVER1_PORT=50104
SERVER1_VERSION=7.0
SERVER1_HOME=/usr/sap/GBR/DVEBMGS00
SERVER1_JAVA_HOME=/opt/java1.4
SERVER1_CLUSTERNODEID=<Cluster_ID>, where Cluster_ID is the cluster ID of the central instance
SERVER1_AS_DETAILS=null
SERVER1_AS_NUM=0
}
```



To generate metric definition XML file on SAP Netweaver 7.1 node, use SERVER1_JAVA_HOME=/usr/sap/<SID>/DVEBMGS00\exe\sapjvm_5 for the Siteconfig file.

The SAP Netweaver Web Application Server 7.1 supports multiple instance for both Central Instance and Application Server. You can choose to monitor the Central Instance and the Application Server. You can specify the attributes of all the nodes in the SiteConfig file.

The SiteConfig file has access-related details of the Central Instance and the Application Server. You can also monitor the service map for the Java systems. For more information, refer SPI for SAP Service View for Java Server on page 346.

You can modify the contents of this file from the global_SiteConfig policy. You must specify values of the following attributes in this file:

- NODE: The fully-qualified domain name of the SAP NetWeaver 7.1 Central Instance server that you want to monitor.
- NUM_SERVERS: The number of Web Application Server instances that you want to monitor on the node for the Central Instance.
- SERVER1_NAME: The fully-qualified domain name of the SAP NetWeaver Web Application Server for the Central Instance.
- SERVER1_LOGIN: The user name to log on to the server where Central Instance is installed.
- SERVER1 PASSWORD: The password for the above-mentioned user.
- SERVER1 PORT: The port number for the Web Application Server for the Central Instance.
- SERVER1 VERSION: The version of SAP NetWeaver on the node for the Central Instance.
- SERVER1 HOME: The SAP home directory on the node for the Central Instance.
- SERVER1 JAVA HOME: The JAVA HOME location on the node for the Central Instance.
- SERVER1 SID: The SAP System ID for the Central Instance.
- SERVER1 NR: The NR number of the Central Instance.
- SERVER1 CLUSTERNODEID: The cluster node ID for the Central Instance.
- SERVER1 AS DETAILS: The details of the application server.
- SERVER1 AS NUM: The number of the application servers used.
- SERVER1 AS NAME: The domain name of the application server.

- SERVER1 AS LOGIN: The user name to log on to the application server.
- SERVER1 AS1 PASSWORD: The password for the user to log on to the application server.
- SERVER1 AS PORT: The port number for the application server.

Example SiteConfig File

```
NODE = sapspil2.example.com
{
NUM SERVERS=1
SERVER1 NAME=sapspil2
SERVER1_LOGIN=j2ee_admin
SERVER1 PASSWORD=ENCRYPTED 9pffwhMzESIx+BilJKRPlA==
SERVER1 PORT=50004
SERVER1 VERSION=71
SERVER1 HOME=/usr/sap/<SID>/DVEBMGS00
SERVER1 JAVA HOME=/usr/sap/<SID>/DVEBMGS00\exe\sapjvm 5
SERVER1 SID=<SID>
SERVER1 NR=00
SERVER1_CLUSTERNODEID=<Cluster ID>, where Cluster ID is the cluster ID of the central
instance
SERVER1_AS_DETAILS=sapspii4.example.com_<SID>_<NR>:<Cluster_ID>;
SERVER1 AS NUM=1
SERVER1 AS1 NAME=sapspii4.example.com
SERVER1 AS1 LOGIN=j2ee admin
SERVER1 AS1 PASSWORD=ENCRYPTED 9pFfwhMzESIx+BilJKRPlA==
SERVER1 AS1 PORT=50704
}
where,
sapspii4.example.com - the node name for the application server
SID - the system ID for the application server
NR - the NR number of the application server
Cluster ID - the cluster ID of the application server
You can find the Cluster ID values for both Central Instance and the Application Server by
```

the following way:

For dual stack and Java system enter, /usr/sap/CCMS/SID NR/j2ee<cluster ID>

Windows:

UNIX/LINUX:

For dual stack and Java system enter, <drive>\usr\sap\CCMS\SID_NR\j2ee<cluster_ID>

If you want to monitor only the Central Instance, you can choose to have the attribute as <code>SERVER1_AS_DETAILS=NULL</code>. To monitor only the Application Server, have the attribute as <code>SERVER1_CLUSTERNODEID=NULL</code>.

Scenarios for Viewing the Service Map for the Java Systems

You can use the <code>global_SiteConfig</code> and specify the attributes to modify and view the service map for the Java systems. The following are few possible scenarios to view the service map:

- Monitoring only the Central Instance
- Monitoring the Central Instance with one application server
- Monitoring the Central Instance with multiple application servers
- Monitoring two Central Instance servers with no application server
- Monitoring two Central Instance servers with application servers

Example of SiteConfig File with only Central Instance

```
NODE = sapspil2.example.com
NUM SERVERS=1
SERVER1 NAME=sapspil2
SERVER1 LOGIN=j2ee admin
SERVER1 PASSWORD=ENCRYPTED 9pffwhMzESIx+BilJKRPlA==
SERVER1 PORT=50004
SERVER1 VERSION=71
SERVER1 HOME=/usr/sap/<SID>/DVEBMGS00
SERVER1 JAVA HOME=/usr/sap/<SID>/DVEBMGS00\exe\sapjvm 5
SERVER1 SID=<SID>
SERVER1 NR=00
SERVER1 CLUSTERNODEID=<Cluster ID>, where Cluster ID is the cluster ID of the central
instance
SERVER1 AS DETAILS=null
SERVER1 AS NUM=0
SERVER1 AS1 NAME=null
SERVER1 AS1 LOGIN=null
SERVER1 AS1 PASSWORD=null
SERVER1 AS1 PORT=null
```

Example of SiteConfig File with Central Instance and Application Server

```
NODE = sapspil2.example.com
```

```
{
NUM SERVERS=1
SERVER1 NAME=sapspil2
SERVER1 LOGIN=j2ee admin
SERVER1 PASSWORD=ENCRYPTED 9pFfwhMzESIx+BilJKRPlA==
SERVER1 PORT=50004
SERVER1 VERSION=71
SERVER1 HOME=/usr/sap/<SID>/DVEBMGS00
SERVER1 JAVA HOME=/usr/sap/<SID>/DVEBMGS00\exe\sapjvm 5
SERVER1 SID=<SID>
SERVER1 NR=00
SERVER1 CLUSTERNODEID=<Cluster ID>, where Cluster ID is the cluster ID of the central
SERVER1 AS DETAILS=sapspii4.example.com < SID> <NR>:<Cluster ID>
SERVER1 AS NUM=1
SERVER1 AS1 NAME=sapspii4.example.com
SERVER1 AS1 LOGIN=j2ee admin
SERVER1 AS1 PASSWORD=ENCRYPTED 9pFfwhMzESIx+BilJKRPlA==
SERVER1 AS1 PORT=50704
Example of SiteConfig File with Central Instance and Multiple Application Servers
NODE = sapspil2.example.com
{
NUM SERVERS=1
SERVER1 NAME=sapspil2
SERVER1 LOGIN=j2ee admin
SERVER1 PASSWORD=ENCRYPTED 9pFfwhMzESIx+BilJKRPlA==
SERVER1 PORT=50004
SERVER1 VERSION=71
SERVER1 HOME=/usr/sap/<SID>/DVEBMGS00
SERVER1 JAVA HOME=/usr/sap/<SID>/DVEBMGS00\exe\sapjvm 5
SERVER1 SID=<SID>
SERVER1 NR=00
SERVER1 CLUSTERNODEID=<Cluster ID>, where Cluster ID is the cluster ID of the central
instance
SERVER1 AS DETAILS=sapspii4.example.com <SID> <NR>:<Cluster ID>;
sapspii5.example.com_<SID>_<NR>:<Cluster_ID>
```

```
SERVER1_AS1_NAME=sapspii4.example.com

SERVER1_AS1_LOGIN=j2ee_admin

SERVER1_AS1_PASSWORD=ENCRYPTED 9pFfwhMzeSix+BilJKRPlA==

SERVER1_AS1_PORT=50704

SERVER1_AS_NUM=2

SERVER1_AS1_NAME=sapspii5.example.com

SERVER1_AS1_LOGIN=j2ee_admin

SERVER1_AS1_LOGIN=j2ee_admin

SERVER1_AS1_PASSWORD=ENCRYPTED 9pFfwhMzeSix+BilJKRPlA==

SERVER1_AS1_PASSWORD=ENCRYPTED 9pFfwhMzeSix+BilJKRPlA==
```

Monitoring the J2EE Engine

After performing all the prerequisite tasks on the SAP NetWeaver Web AS node, you can start deploying the necessary policies to initiate monitoring. The SPI for SAP introduces three new policies to start the collector and analyzer programs on the SAP NetWeaver Web Application Server nodes.

Deploy the Scheduled Task Policies

Scheduled task policies help the collectors run on the node at a regular interval to collect metric data that can be stored or compared by the SPI for SAP against preset thresholds to generate alarms. The following are the policies for SAP Netweaver 7.0:

- **SPISAP-70-High-10m:** Runs every 10 minutes.
- **SPISAP-70-High-30m:** Runs every 30 minutes.
- **SPISAP-70-High-1h:** Runs every hour.
- **SPISAP-70-perf-30m:** Runs every 30 minutes.
- **SPISAP-NWSTATUS-02m:** Runs every 2 minutes. This policy sends an alert to the message browser if the SAP NetWeaver Web Application Server is found to be down.

These policies are grouped under the SPI for SAP > en >SAP NW Java Monitoring 7.0 > Monitors group.

The following are the templates for SAP Netweaver 7.10:

- **SPISAP-71-High-10m:** Runs every 10 minutes.
- **SPISAP-71-High-30m:** Runs every 30 minutes.
- SPISAP-71-High-1h: Runs every hour.
- **SPISAP-71-perf-30m:** Runs every 30 minutes.
- **SPISAP-NWSTATUS-02m:** Runs every 2 minutes. This policy sends an alert to the message browser if the SAP NetWeaver Web Application Server is found to be down.

These policies are grouped under the SPI for SAP > en >SAP NW Java Monitoring 7.1 > Monitors group.

Deploy the Measurement Threshold Policies

The measurement threshold policies help the SPI generate alarms in the event of threshold violation. The collectors and analyzers collect a variety of metrics on the node that indicates the availability, health, and performance of the J2EE engine of the Web AS. You must deploy the policies under the following groups to receive alerts and messages on your HPOM console.

- **J2EE Engine Kernel:** Includes the policies to monitor the Kernel of the J2EE engine.
- **J2EE Engine Performance:** Includes the policies to monitor the performance of the J2EE engine.
- **J2EE Engine Services:** Includes the policies to monitor the various services on the SAP NetWeaver Web Application Server.

For information on these policies, see Reference Information on SAP NetWeaver Java Monitoring 7.0 Policies.

Reference Information on SAP NetWeaver Java Monitoring 7.0 Policies

This section includes the reference information on all the policies required to monitor the SAP NetWeaver Web Application Server's J2EE engine. The SPI for SAP primarily collects metric data from the **managers** and **services** that run on the J2EE engine.

Policies: the J2EE Engine - Kernel Group

The policies under the J2EE Engine - Kernel group collect data from the managers available on the J2EE engine. The SPI for SAP monitors metrics indicating the health and performance of the J2EE engine kernel from the data collected from several monitored units on SAP nodes.

Policies to Monitor the Configuration Manager Data

The SPI for SAP collects and monitors values of monitored units of Configuration Manager from SAP nodes.

Policy name SPISAP 0001

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the Cache hit rate monitored unit of

the Configuration Manager.

Default threshold

110: The SPI for SAP sends an alert with the severity Warning when the cache hit rate exceeds 110.

• 120: The SPI for SAP sends an alert with the severity Major when the cache hit rate exceeds 120.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description Commit duration of the J2EE engine.

Default threshold • 30: The SPI for SAP sends an alert with the severity

Warning when the commit duration is above or equal to

30.

• 120: The SPI for SAP sends an alert with the severity Major when the commit duration is above or equal to

120.

Policy name SPISAP_0012

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description ClassLoader count of the J2EE engine.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the ClassLoader count is equal to 0.

Policy name SPISAP_0013

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description Total connection count of the J2EE engine.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the total connection count is equal to 0.

Policies to Monitor the Cluster Manager Data

The SPI for SAP collects and monitors values of monitored units of Cluster Manager from SAP nodes.

Policy name SPISAP_0038

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the value of the message context pool

size of cluster management.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value falls below the threshold.

Policy name SPISAP 0039

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the average message context pool size

of cluster management.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value falls below the threshold.

Policy name SPISAP 0040

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

configuration manager.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0041

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for cache

manager.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

service manager deploy distributor.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0043

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

service manager internal connection.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0044

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for P4.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 0045

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for iiop.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for sld.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0047

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for shell.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0048

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for web

services.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 0049

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for log

configurator.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for jmx

notification.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0051

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for telnet.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0052

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for jmx.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0053

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for jms

provider.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for http.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0055

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

deploy.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0056

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

naming.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 0057

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

connector.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for BI

MMR deployer.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0059

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

com.sap.security.core.ume.service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0060

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

security.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0061

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for web

dynpro.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

servlet jsp.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0063

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

rfcengine.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0064

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

apptracing.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0065

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte sent for

prtbridge.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

configuration manager.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0067

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

cache manager.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0068

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

service manager deploy distributor.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0069

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

service manager (internal connection).

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

P4.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0071

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

iiop.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 0072

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

sld.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0073

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

Shell.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

Web Services.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0075

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

Log Configurator.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0076

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

jmx notification.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0077

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

jmx notification.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

jmx.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0079

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

jms_provider.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0080

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

http.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0081

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

deploy.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

naming.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0083

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

connector.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 0084

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

bi~mmr~deployer.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0085

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

com.sap.security.core.ume.service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

security.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0087

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

web dynpro.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0088

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

servlet_jsp.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0089

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

rfcengine.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

apptracing.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0091

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the total message byte received for

prtbridge.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_0092

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the maximum session queue size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP 0093

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the P4 current session queue size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the internal current session queue

size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0095

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the telnet current session queue size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0096

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the http current session queue size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0097

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the jms_provider current session

queue size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the web services current session

queue size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0099

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors the iiop current session queue size.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0100

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session bytes sent for the P4

processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP 0101

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session bytes sent for the

internal processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session bytes sent for the telnet

processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0103

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session bytes sent for the http

processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0104

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session bytes sent for the

jms_provider processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0105

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session bytes sent for the web

services processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session bytes sent for the iiop

processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0107

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session byte received for the P4

processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0108

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session byte received for the

internal processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0109

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session byte received for the

telnet processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session byte received for the

http processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0111

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session byte received for the

jms_provider processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0112

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session byte received for the

web services processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policy name SPISAP_0113

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Kernel

Description This policy monitors total session byte received for the iiop

processor.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the value reaches the threshold.

Policies: the J2EE Engine - Services Group

The policies under the J2EE Engine - Services group collect data from the services available on the J2EE engine.

This group monitors states and conditions of the services that are necessary for the J2EE engine. Policies under this group monitor the following services and send alert messages to the message appropriate in the events of threshold violation:

- JMX Adapter Service
- HTTP Provider Service
- Connector Container Service: SAPSR3DB
- Connector Container Service: SAP/EP_PRT
- Connector Container Service: SAP/BC MIGSERVICE
- Connector Container Service: SAP/CAF EUF GP
- Connector Container Service: SAP/BC_WDRR
- Connector Container Service: SAP/CAF RT
- Connector Container Service: SAP/BW_MMR
- Connector Container Service: SAP/EP DQE
- Connector Container Service: SAP/CAF/EUP_GP/MAIL_CF
- Connector Container Service: SAP/BC UME
- Connector Container Service: SAP/BC JMS
- Connector Container Service: SAP/BC FO
- Connector Container Service: SAP/BC_XMLA
- Connector Container Service: SAP/BC MON
- Connector Container Service: SAP/CAF EUP ER
- Connector Container Service: SAP/EP PCD
- Connector Container Service: SAP/CAF BW RD
- Connector Container Service: SAP/BC_SLM
- Connector Container Service: SAP/LOCAL_MAINFRAME_POOL
- Connector Container Service: SAP/BC SLD
- Connector Container Service: SAP/BC JDO
- Connector Container Service: SAP/BC UDDI
- Connector Container Service: utdb
- Connector Container Service: ADS
- Connector Container Service: SDK JDBC
- Connector Container Service: SDK CAF
- Connector Container Service: SDK SAPQ
- Connector Container Service: SDK XMLA
- Connector Container Service: SDK_ODBO

EJB Container Service: Session stateful beans

EJB Container Service: Session stateless beans

EJB Container Service: Message driven beans.

EJB Container Service: Entity beans

Web Services Container Service

Web Container Service

Policies to Monitor the JMX Adapter Service

These policies monitor the JMX Adapter Service.

Policy name SPISAP_2001

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine

- Services

Description This policy monitors the maximum entries of the JMX

adapter service.

Default threshold 10000: The SPI for SAP sends an alert with the severity

Warning when the maximum entries of the JMX adapter

service exceeds 10000.

50000: The SPI for SAP sends an alert with the severity Major when the maximum entries of the JMX adapter

service exceeds 50000.

Policy name SPISAP_2002

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine

- Services

Description This policy monitors the current entries of the JMX

adapter service.

Default threshold 10000: The SPI for SAP sends an alert with the severity

Warning when the current entries of the JMX adapter

service exceeds 10000.

50000: The SPI for SAP sends an alert with the severity

Major when the current entries of the JMX adapter

service exceeds 50000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the replaced entries of the JMX

adapter service.

Default threshold 10000: The SPI for SAP sends an alert with the severity

Warning when the replaced entries of the JMX adapter

service exceeds 10000.

50000: The SPI for SAP sends an alert with the severity Major when the replaced entries of the JMX adapter

service exceeds 50000.

Policy name SPISAP 2004

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine

- Services

Description This policy monitors the hit rate of the JMX adapter v.

Default threshold 500: The SPI for SAP sends an alert with the severity

Warning when the hit rate of the JMX adapter service

exceeds 500.

1000: The SPI for SAP sends an alert with the severity Major when the hit rate of the JMX adapter service

exceeds 1000.

Policy name SPISAP_2005

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine

- Services

Description This policy monitors the notification queue size of the

JMX adapter service.

Default threshold 10: The SPI for SAP sends an alert with the severity

Warning when the queue size of the JMX adapter service

exceeds 10.

100: The SPI for SAP sends an alert with the severity Major when the queue size of the JMX adapter service

exceeds 100.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine

- Services

Description This policy monitors the number of active threads of the

JMX adapter service.

Default threshold 3: The SPI for SAP sends an alert with the severity Major

when the number of active threads of the JMX adapter

service exceeds 3.

Policy name SPISAP_2007

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine

- Services

Description This policy monitors the log size on the SAP node.

Default threshold 524288 (KB): The SPI for SAP sends an alert with the

severity Major when the log size of the monitored node

exceeds 524288 kb.

Policies to Monitor the HTTP Provider Service

These policies monitor the HTTP Provider Service.

Policy name SPISAP_2011

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine

- Services

Description This policy monitors the Current open connections: Total

count monitored unit of the HTTP Provider Service.

Default threshold 100: The SPI for SAP sends an alert with the severity

Major when the value of the *Current open connections*:

Total count monitored unit exceeds 100.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Current open connections*:

Reading request monitored unit of the HTTP Provider

Service.

Default threshold 100: The SPI for SAP sends an alert with the severity

Major when the value of the *Current open connections*:

Reading request monitored unit exceeds 100.

Policy name SPISAP 2013

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Current open connections*:

Reading response monitored unit of the HTTP Provider

Service.

Default threshold 100: The SPI for SAP sends an alert with the severity

Major when the value of the Current open connections:

Reading response monitored unit exceeds 100.

Policy name SPISAP_2014

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Current open connections*:

Skipping requests monitored unit of the HTTP Provider

Service.

Default threshold 100: The SPI for SAP sends an alert with the severity

Major when the value of the *Current open connections*:

Skipping requests monitored unit exceeds 100.

Policy name SPISAP_2015

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Current open connections*:

Keep-Alive waiting monitored unit of the HTTP Provider

Service.

Default threshold 100: The SPI for SAP sends an alert with the severity

Major when the value of the ${\it Current open connections}:$

Keep-Alive waiting monitored unit exceeds 100.

Policy name SPISAP_2016

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Total requests: Avg requests per*

connection rate monitored unit of the HTTP Provider Service.

Default threshold 100000: The SPI for SAP sends an alert with the severity Major

when the value of the *Total requests: Avg requests per connection*

rate monitored unit exceeds 100000.

Policy name SPISAP 2018

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Total requests: Avg request-response time*

monitored unit of the HTTP Provider Service.

Default threshold

• 120: The SPI for SAP sends an alert with the severity Major when the value of the *Total requests: Avg request-response time*

monitored unit exceeds 120.

• **60**: The SPI for SAP sends an alert with the severity Warning when the value of the *Total requests: Avg request-response time*

monitored unit exceeds 60.

Policies to Monitor the SAPSR3DB Connector Container Service

These policies monitor the SAPSR3DB Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAPSR3DB Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy name SPISAP_2020

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAPSR3DB Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2021

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAPSR3DB Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP_2022

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAPSR3DB Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/EP_PRT Connector Container Service

These policies monitor the SAP/EP_PRT Connector Container Service.

Policy name SPISAP_2023

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/EP_PRT Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the severity

Major when the value of the *Maximum connections number*

monitored unit exceeds 10000000.

Policy name SPISAP_2024

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Free managed connections number

monitored unit of the SAP/EP_PRT Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the severity

Major when the value of the Free managed connections number

monitored unit exceeds 10000000.

Policy name SPISAP_2025

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/EP_PRT Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP_2026

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/EP_PRT Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Waiting\ for\ connections\ number$ monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC MIGSERVICE Connector Container Service

These policies monitor the SAP/BC_MIGSERVICE Connector Container Service.

Policy name SPISAP 2027

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC MIGSERVICE Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Maximum

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC MIGSERVICE

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2029

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC_MIGSERVICE

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP_2030

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC MIGSERVICE Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/CAF EUP GP Connector Container Service

These policies monitor the SAP/CAF EUP GP Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/CAF EUP GP Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2032

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/CAF_EUP_GP

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP_2033

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/CAF_EUP_GP

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP_2034

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/CAF EUP GP Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_WDRR Connector Container Service

These policies monitor the SAP/BC_WDRR Connector Container Service.

Policy name SPISAP_2035

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_WDRR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy name SPISAP 2036

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_WDRR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Free\ managed$ connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC WDRR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Used\ managed\ connections\ number$ monitored unit exceeds 10000000.

Policy name SPISAP 2038

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC_WDRR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/CAF_RT Connector Container Service

These policies monitor the SAP/CAF_RT Connector Container Service.

Policy name SPISAP_2039

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/CAF_RT.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/CAF RT.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP_2041

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/CAF_RT.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP_2042

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/CAF_RT Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/BW MMR Connector Container Service

These policies monitor the SAP/BW_MMR Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BW_MMR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy name SPISAP_2044

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BW_MMR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP 2045

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BW MMR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP_2046

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BW MMR Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/EP_DQE Connector Container Service

These policies monitor the SAP/EP_DQE Connector Container Service.

Policy name SPISAP_2047

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/EP_DQE Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Maximum

connections number monitored unit exceeds 10000000.

Policy name SPISAP 2048

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/EP_DQE Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/EP DQE Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Used\ managed\ connections\ number$ monitored unit exceeds 10000000.

Policy name SPISAP_2050

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/EP_DQE Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/CAF/EUP_GP/MAIL_CF Connector Container Service

These policies monitor the SAP/CAF/EUP_GP/MAIL_CF Connector Container Service.

Policy name SPISAP 2051

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/CAF/EUP GP/MAIL CF

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Maximum

 $connections\ number\ monitored\ unit\ exceeds\ 10000000.$

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/CAF/EUP_GP/

MAIL CF Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP 2053

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/CAF/EUP_GP/

MAIL_CF Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP_2054

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/CAF/EUP_GP/MAIL_CF

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_UME Connector Container Service

These policies monitor the SAP/BC_UME Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_UME Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy name SPISAP_2056

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_UME Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2057

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC UME Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP_2058

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC_UME Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_JMS Connector Container Service

These policies monitor the SAP/BC JMS Connector Container Service.

Policy name SPISAP_2059

Policy type Measurement Threshold

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_JMS Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2060

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_JMS Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC JMS Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2062

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC_JMS Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_FO Connector Container Service

These policies monitor the SAP/BC_FO Connector Container Service.

Policy name SPISAP 2063

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_FO Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Maximum

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC FO Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2065

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC_FO Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP_2066

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC_FO Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_XMLA Container Service

These policies monitor the SAP/BC_XMLA Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC XMLA Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy name SPISAP_2068

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_XMLA Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy name SPISAP 2069

Policy type Measurement Threshold

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC XMLA Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP_2070

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC XMLA Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_MON Connector Container Service

These policies monitor the SAP/BC_MON Connector Container Service.

Policy name SPISAP_2071

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_MON Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy name SPISAP 2072

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_MON Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC MON Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy name SPISAP 2074

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Waiting for connections number*

monitored unit of the SAP/BC_MON Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/CAF_EUP_ER Connector Container Service

These policies monitor the SAP/CAF EUP ER Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/CAF_EUP_ER Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Maximum

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/CAF_EUP_ER

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Free\ managed$ connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/CAF_EUP_ER

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/CAF EUP ER Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/EP_PCD Connector Container Service

These policies monitor the SAP/EP_PCD Connector Container Service.

Policy type Measurement Threshold

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/EP PCD Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/EP PCD Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/EP_PCD Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/EP PCD Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC ADM Connector Container Service

These policies monitor the SAP/BC_ADM Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_ADM Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_ADM Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC ADM Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC_ADM Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/CAF BW RT Connector Container Service

These policies monitor the SAP/CAF_BW_RT Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/CAF_BW_RT Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/CAF_BW_RT

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/CAF_BW_RT

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/CAF BW RT Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC SLM Connector Container Service

These policies monitor the SAP/BC_SLM Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_SLM Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC SLM Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC_SLM Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC_SLM Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/LOCAL_MAINFRAME_POOL Connector Container Service

These policies monitor the SAP/LOCAL_MAINFRAME_POOL Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/LOCAL_MAINFRAME_POOL

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/

LOCAL_MAINFRAME_POOL Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/

LOCAL_MAINFRAME_POOL Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/LOCAL_MAINFRAME_POOL

Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_SLD Connector Container Service

These policies monitor the SAP/BC_SLD Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC SLD Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Maximum

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC SLD Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC_SLD Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC_SLD Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_JDO Connector Container Service

These policies monitor the SAP/BC JDO Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_JDO Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_JDO Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC JDO Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC JDO Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SAP/BC_UDDI Connector Container Service

These policies monitor the SAP/BC_UDDI Connector Container Service.

Policy type Measurement Threshold

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SAP/BC_UDDI Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SAP/BC_UDDI Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SAP/BC_UDDI Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SAP/BC UDDI Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the utdb Connector Container Service

These policies monitor the SAP/utdb Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the utdb Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the utdb Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the utdb Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the utdb Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the ADS Connector Container Service

These policies monitor the ADS Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the ADS Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the ADS Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the ADS Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Services

Description This policy monitors the Waiting for connections number

monitored unit of the ADS Connector Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for* connections number monitored unit exceeds 10000000.

Policies to Monitor the SDK JDBC Connector Container Service

These policies monitor the *SDK_JDBC Connector Container Service*.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SDK_JDBC Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SDK_JDBC Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SDK_JDBC Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SDK JDBC Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Waiting for connections number monitored unit exceeds 10000000.

Policies to Monitor the SDK CAF Connector Container Service

These policies monitor the *SDK_CAF Connector Container Service*.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SDK_CAF Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SDK_CAF Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SDK CAF Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Used\ managed\ connections\ number\ monitored\ unit\ exceeds\ 10000000.$

Policy type Measurement Threshold

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SDK CAF Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Waiting\ for\ connections\ number$ monitored unit exceeds 10000000.

Policies to Monitor the SDK SAPQ Connector Container Service

These policies monitor the SDK_SAPQ Connector Container Service.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SDK_SAPQ Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SDK SAPQ Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SDK_SAPQ Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SDK_SAPQ Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Waiting for connections number* monitored unit exceeds 10000000.

Policies to Monitor the SDK XMLA Connector Container Service

These policies monitor the *SDK_XMLA Connector Container Service*.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SDK_XMLA Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Maximum*

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SDK_XMLA Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SDK_XMLA Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SDK XMLA Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the $Waiting\ for\ connections\ number$ monitored unit exceeds 10000000.

Policies to Monitor the SDK ODBO Connector Container Service

These policies monitor the *SDK_ODBO Connector Container Service*.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Maximum connections number*

monitored unit of the SDK ODBO Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Maximum

connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Free managed connections*

number monitored unit of the SDK_ODBO Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Free managed* connections number monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Used managed connections*

number monitored unit of the SDK_ODBO Connector

Container Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the *Used managed connections number* monitored unit exceeds 10000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Waiting for connections number

monitored unit of the SDK_ODBO Connector Container

Service.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value of the Waiting for connections number monitored unit exceeds 10000000.

Policies to Monitor the EJB Container Services

These policies monitor the EJB container services.

Policy name SPISAP 2139

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the ActiveSessionTimeout

monitoring unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2140

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PassiveSessionTimeout

monitoring unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2141

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the ActiveSessionCount monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 2142

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PassiveSessionCount monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2143

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the CompletedSessions monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Creations Number monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2145

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the RemovalsNumber monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2146

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PassivationsNumber monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2147

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Activations Number monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Creations Number monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2149

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the RemovalsNumber monitoring

unit of the Stateful Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 2150

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the CurrentPoolSize monitoring unit

of the Stateless Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2151

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the MaxPoolSize monitoring unit of

the Stateless Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Initial Pool Size monitoring unit of

the Stateless Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2153

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PoolIncrementSize monitoring

unit of the Stateless Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2154

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PoolCurrentlyUsedObject

monitoring unit of the Stateless Session beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2155

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Creations Number monitoring

unit of the Message-Driven beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the RemovalsNumber monitoring

unit of the Message-Driven beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2157

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the CurrentPoolSize monitoring unit

of the Message-Driven beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2158

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the MaxPoolSize monitoring unit of

the Message-Driven beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2159

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Initial Pool Size monitoring unit of

the Message-Driven beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PoolIncrementSize monitoring

unit of the Message-Driven beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2161

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PoolCurrentlyUsedObject

monitoring unit of the Message-Driven beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2162

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the CreationsNumber monitoring

unit of the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2163

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Removals Number monitoring

unit of the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the CurrentPoolSize monitoring unit

of the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2165

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the MaxPoolSize monitoring unit of

the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP 2166

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the InitialPoolSize monitoring unit of

the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2167

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PoolIncrementSize monitoring

unit of the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PoolCurrentlyUsedObject

monitoring unit of the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2169

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the PassivationsNumber monitoring

unit of the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policy name SPISAP_2170

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the Activations Number monitoring

unit of the Entity beans.

Default threshold 10000000: The SPI for SAP sends an alert with the

severity Major when the value exceeds the threshold.

Policies to Monitor the Web Container Service

These policies monitor the Web Container Service.

Policy type Measurement Threshold

Services

Description This policy monitors the *Current Http sessions* monitored

unit of the Web Container Service.

Default threshold 500: The SPI for SAP sends an alert with the severity

Major when the value of the Current Http sessions

monitored unit exceeds 500.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Current security sessions*

monitored unit of the Web Container Service.

Default threshold 500: The SPI for SAP sends an alert with the severity

Major when the value of the *Current security sessions*

monitored unit exceeds 500.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Number of timed out http sessions*

monitored unit of the Web Container Service.

Default threshold 100000: The SPI for SAP sends an alert with the severity

Major when the value of the Number of timed out http

sessions monitored unit exceeds 100000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Services

Description This policy monitors the *Number of timed out security*

sessions monitored unit of the Web Container Service.

Default threshold 100000: The SPI for SAP sends an alert with the severity

Major when the value of the *Number of timed out security*

sessions monitored unit exceeds 100000.

Policies: the J2EE Engine - Performance Group

The J2EE Engine - Performance group of policies collects the performance monitor data of the J2EE engine. This group collects the data from the *Request performance* monitor group.

Policy name SPISAP 4001

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Performance

Description The SPISAP_4001 policy collects data from the *Number of*

requests monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with the severity

Major when the total number of JARM requests equals or

exceeds 1000000.

Policy name SPISAP 4002

Policy type Measurement Threshold

Performance

Description The SPISAP_4002 policy collects data from the *Requests*

per second monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with the severity

Major when the number of JARM requests per second

equals or exceeds 1000000.

Policy name SPISAP_4003

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Performance

Description The SPISAP_4003 policy collects data from the

Component calls monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with the severity

Major when the total number of component calls made by

all JARM requests equals or exceeds 1000000.

Policy name SPISAP_4004

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Performance

Description The SPISAP 4004 policy collects data from the Average

response time monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with the severity

Major when the total number of component calls made by

all JARM requests equals or exceeds 1000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Performance

Description The SPISAP_4005 policy collects data from the *Average*

CPU Time monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with the severity

Major when the average CPU time equals or exceeds

1000000.

Policy name SPISAP_4006

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.0 > J2EE Engine -

Performance

Description The SPISAP_4006 policy collects data from the *Average*

outbound data monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with the severity

Major when the average outbound data equals or exceeds

1000000.

Reference Information on SAP Netweaver Java Monitoring 7.1 Policies

This section includes the reference information on all policies required to monitor the SAP Netweaver Web Application Server's J2EE engine. The SPI for SAP primarily collects metric data from the managers and services that run on the J2EE engine.

Policies: the J2EE Engine: Kernel Group

The policies under the J2EE Engine - Kernel group collect data from the managers available on the J2EE engine. The SPI for SAP monitors metrics that indicate the health and performance of the J2EE engine kernel.

Policy to Monitor the Session Manager Data

This policy monitors the Session Manager Data from SAP nodes.

Policy name SPISAP_0204

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the number of active web sessions.

Default threshold 100: The SPI for SAP sends an alert with the severity

Major when the total connection count for the active web

sessions exceeds 100.

Policies to Monitor the System Threads Pool

These policies monitor the System Threads Pool data from SAP nodes.

Policy name SPISAP 0206

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the usage rate for different system

thread pools.

Default threshold 80: The SPI for SAP sends an alert with the severity

Major when the *usage rate* exceeds 80.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the system thread pool usage rate.

Default threshold 80: The SPI for SAP sends an alert with the severity

Major when the thread pool usage rate exceeds 80.

Policy name SPISAP_0208

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the system waiting pool usage rate.

Default threshold 80: The SPI for SAP sends an alert with the severity

Major when the waiting tasks usage rate exceeds 80.

Policy name SPISAP_0215

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the thread pool capacity rate. **Default threshold** 80: The SPI for SAP sends an alert with the severity

Major when the thread pool capacity rate exceeds 80.

Policies to Monitor the Application Threads Pool

These policies monitor the Application Threads Pool data from SAP nodes.

Policy name SPISAP_0218

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the usage rate for different

application threads pool.

Default threshold 80: The SPI for SAP sends an alert with the severity

Major when the usage rate exceeds 80.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the application thread pool usage

rate.

Default threshold 80: The SPI for SAP sends an alert with the severity

Major when the thread pool usage rate exceeds 80.

Policy name SPISAP_0220

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the application waiting pool usage

rate.

Default threshold 80: The SPI for SAP sends an alert with the severity

Major when the waiting tasks usage rate exceeds 80.

Policy name SPISAP_0227

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the thread pool capacity rate for

applications.

Default threshold 80: The SPI for SAP sends an alert with the severity

Major when the thread pool capacity rate exceeds 80.

Policies to Monitor the Cluster Manager Data

These policies monitor the Cluster Manager Data from SAP nodes.

Policy name SPISAP_0230

Policy type Measurement Threshold

Kernel

Description This policy monitors the average time in microseconds

that a message spends in the message queue of the

message server communication layer.

Default threshold 500: The SPI for SAP sends an alert with the severity

Major when the value exceeds 500.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the average time in microseconds

that a message spends in the message queue of the session

communication layer.

Default threshold 500: The SPI for SAP sends an alert with the severity

Major when the value exceeds 500.

Policy to Monitor the Class Loader Manager Data

This policy monitors the Class Loader Manager Data from SAP nodes.

Policy name SPISAP_0232

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the count of the registered

classloaders of the J2EE engine.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the *class loaders count* is below 0.

Policies to Monitor the Configuration Manager Data

These policies monitor the Configuration Manager Data from SAP nodes.

Policy name SPISAP_0233

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the *cache hit rate* monitored unit of

the Configuration Manager.

Default threshold 120: The SPI for SAP sends an alert with the severity

Major when the cache hit rate exceeds 120.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Kernel

Description This policy monitors the commit duration of the J2EE

engine.

Default threshold 120000: The SPI for SAP sends an alert with the severity

Major when the commit duration exceeds 120000.

Policies: the J2EE Engine - Services Group

The policies under the J2EE Engine - Services group collect data from the services available in the J2EE engine. The SPI for SAP monitors states and conditions of the services that are necessary for the J2EE engine.

Policy to Monitor Timeout Service

This policy monitors the Timeout service from SAP nodes.

Policy name SPISAP 2204

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors count of the timeout events per

minute.

Default threshold 1200: The SPI for SAP sends an alert with the severity

Major when the estimated frequency per minute exceeds

1200.

Policy to Monitor WebContainer Service

This policy monitors the WebContainer service from SAP nodes.

Policy name SPISAP_2205

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the average value of the requested

processing time for the given time interval.

Default threshold 2147483647: The SPI for SAP sends an alert with the

severity Major when the processing time exceeds

2147483647.

Policies to Monitor the JMS Service

These policies monitor the JMS service from SAP nodes.

Policy name SPISAP_2207

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of connections of the JMS

service.

Default threshold 1000: The SPI for SAP sends an alert with the severity

Major when the number of connections exceed 1000.

Policy name SPISAP 2208

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of consumers using the

JMS service.

Default threshold 500: The SPI for SAP sends an alert with the severity

Major when the number of consumers exceed 500.

Policy name SPISAP_2209

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of producers using the

JMS service.

Default threshold 1000: The SPI for SAP sends an alert with the severity

Major when the number of producers exceeds 1000.

Policy to Monitor the Log Configurator Service

This policy monitors the Log Configurator service from SAP nodes.

Policy name SPISAP_2210

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the total number of log and trace files

excluding archive files.

Default threshold 524288: The SPI for SAP sends an alert with the severity

Major when the total log file size exceeds 524288.

Policies to Monitor the HTTP Provider Service

These policies monitor the HTTP Provider Service.

Policy name SPISAP_2216

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of currently used HTTP

threads.

Default threshold 500: The SPI for SAP sends an alert with the severity

Major when the Active Thread Count exceeds 500.

Policy name SPISAP 2217

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the rate used to configure the HTTP

threads.

Default threshold 90: The SPI for SAP sends an alert with the severity

Major when the Threads In Process Rate exceeds 90.

Policy name SPISAP_2218

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of failed P4 server

startup.

Default threshold 2147483647: The SPI for SAP sends an alert with the

severity Major when the failed request count exceeds

2147483647.

Policy name SPISAP_2219

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the percentage of used threads

compared to configured threads.

Default threshold 90: The SPI for SAP sends an alert with the severity

Major when the thread usage rate exceeds 90.

Policy to Monitor the Transaction Service

This policy monitors the Transaction Service from SAP nodes.

Policy name SPISAP 2226

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the ratio between committed

transaction count and total transaction count.

Default threshold 90: The SPI for SAP sends an alert with the severity

Major when the transaction success rate is below 90.

Policy to Monitor the IIOP Service

This policy monitors the IIOP service from SAP nodes.

Policy name SPISAP_2227

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the percentage of used threads

compared to configured IIOP threads.

Default threshold 90: The SPI for SAP sends an alert with the severity

Major when the IIOP thread usage rate exceeds 90.

Policies to Monitor the JMX Adapter Service

These policies monitor the JMX Adapter Service from SAP nodes.

Policy name SPISAP 2228

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors number of JMX notification listeners

registered with the MBean server to receive MBean server

notifications from remote cluster nodes.

Default threshold 0: The SPI for SAP sends an alert with the severity Major

when the ClusterWideNotificationListeners is below 0.

Policy name SPISAP 2229

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of MBeans registered

with the MBean server in the local cluster node.

Default threshold 2147483647: The SPI for SAP sends an alert with the

severity Major when the local MBean repository size

exceeds 2147483647.

Policies to Monitor the JNDI Registry Service

These policies monitor the JNDI Registry Service from SAP nodes.

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of objects bound in the

naming system at the present time.

Default threshold 10000: The SPI for SAP sends an alert with the severity

Major when bound objects count exceeds 10000.

Policy name SPISAP_2231

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the size of the naming system byte

array cache.

Default threshold 4000: The SPI for SAP sends an alert with the severity

Major when byte array cache size is below 4000.

Policy to Monitor the Security Service

This policy monitors the Security service from SAP nodes.

Policy name SPISAP 2232

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Services

Description This policy monitors the number of unsuccessful logon

attempts.

Default threshold 25: The SPI for SAP sends an alert with the severity

Major when the unsuccessful logon count exceeds 25.

Policies: the J2EE Engine - Performance Group

The J2EE Engine - Performance group of policies collects the performance monitor data of the J2EE engine. This group collects the data from the *Request performance* monitor group.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Performance

Description This policy collects data from the Average response time

monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with severity

Major when the number of JARM requests exceeds

1000000.

Policy name SPISAP_4202

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Performance

Description This policy collects data from the *Requests per second*

monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with severity

Major when the number of JARM request per second

exceeds 1000000.

Policy name SPISAP_4203

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Performance

Description This policy collects data from the Average CPU time

monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with severity

Major when the average CPU time exceeds 1000000.

Policy name SPISAP_4204

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Performance

Description This policy collects data from the *Average outbound data*

monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with severity

Major when the average outbound data exceeds 1000000.

Policy type Measurement Threshold

Policy group SPI for SAP > en >SAP NW Java Monitoring 7.1 > J2EE Engine -

Performance

Description This policy collects data from the *Component calls*

monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with severity

Major when the total number of component calls made by

JARM request exceeds 1000000.

Policy name SPISAP_4206

Policy type Measurement Threshold

Policy group SPI for SAP > en > SAP NW Java Monitoring 7.1 > J2EE Engine -

Performance

Description This policy collects data from the *Number of requests*

monitored unit.

Default threshold 1000000: The SPI for SAP sends an alert with severity

Major when the total number the of JARM requests

exceeds 1000000.

8 Service Views

The information in this section introduces you to the concept of Service Views and explains how they are used by both the SPI for SAP and HPOM for Windows to provide you with information that is specifically designed to help you manage your SAP NetWeaver landscape in a more efficient and more convenient way. You can find detailed information about the following topics:

- What are Service Views?
- Service Views in the SPI for SAP
- SPI for SAP Service View for Java Server

What are Service Views?

Service views provide you with a way of viewing the objects that make up your environment so that, you can better determine the effect of current problems or predict potential problems.

Use the capabilities of HPOM for Windows to perform the following tasks:


- Map messages to the services that they directly affect
- Generate a service model of your environment, which includes all relationships and dependencies between component objects
- Identify and select actions available for each object
- Define propagation rules, which can identify potential or present problems on objects and on related services

The scoping pane of the main window shows discovered services in addition to the usual HPOM for Windows managed nodes and applications. Click a service to display the navigation tree for the selected service in the scoping pane. In the tree, you can select any service or subservice and display a service graph.

In both the navigation tree and the service graph, the component services are color-coded according to the status. This color-coding of the tree elements matches the color-coding of messages in the console, which is determined by message severity level.

For instance, a service displayed in red indicates that a condition exists that has a critical effect on that service or on a related service. The action Get Root Cause traces the origin of a condition that has affected the status of a selected service.

The Service Map



Service Views in the SPI for SAP

The SPI for SAP provides a Service Auto-Discovery policy, which you can deploy on each managed node to analyze the SAP environment and generate a service view. The service view represents all existing ownership and dependency relationships between objects on the nodes, message-propagation rules, and any actions that are available for objects.

The service view reflects your individual setup. Each service view is a unique representation of the environment from which it is taken. In general, the SAP service view consists of several levels.

The first level is an accumulation object including all SAP systems. When you expand a first-level object, you see an object for each SAP NetWeaver system in your environment. The SAP Systems object changes status in response to a change of status in any of the objects that make up the instances that it contains.


The second level includes logical objects within each SAP system. Notice that none of the objects shown at this level have any messages mapped directly to them. They are logical objects, used to give a general overview of the status of the services provided by the SAP NetWeaver system. Expand an SAP NetWeaver system object to display the following logical objects:

- SAP NetWeaver Instances
- Database (<SID>)
- Environment (<*SID*>)
- Interface

- Batch
- Dialog
- Spool
- Update

Figure 24 shows an example SAP service view expanded to the logical object level.

Figure 24 Service Map of SAP Systems



When you expand the SAP NetWeaver Instance object, each SAP NetWeaver instance appears as an object in the tree. When you expand the environment object, the following three objects are displayed:

- Operating System
- Network
- Memory Management

These objects have messages mapped to them which would then be propagated to the environment object. The other objects have **use** relationships with objects contained within the processes object; an event that affects a related process would cause a change in status in these objects.

Service Views 341

🛃 1:HP Operations Manager : TCPC025\Services\Applications\SAP\R/3 Systems\R/3 System WA1\R/3 Insta Action View Favorites 🗢 🖈 🗈 📧 😭 😫 🕮 🛗 🛗 🚇 🥞 🧥 🧦 R/3 Instances View: Map - Contains or Uses Tree | Favorites | HP Operations View in display: Contains or Uses Services - 📆 Applications 🗓 💣 Operations R/3 Instances 💰 R/3 Systems R/3 System CIA
R/3 System EP7 aR/3 System SP6 📆 R/3 System T06 R/3 System WA1 DVEBMGS10 [WA1:10] 材 R/3 System WA1 Update [WA1:10] Batch [WA1:10] Database WA1 Environment [W Interface Spool [WA1:10] Dialog [WA1:10] 🕳 R/3 Instar 🕜 Update R/3 System WA4 Processes [WA1:10] Environment [WA1:10] Interface [WA1:10] 👿 Nodes

Figure 25 Service Map of an SAP Instance

The processes object can be expanded to show the following objects:


- Gateway
- Message
- Dialog work process
- Batch work process
- Spool work process
- Update work process

Line of Business Views

The SAP NetWeaver service view and the other service views available with HPOM for Windows provide graphical representations of the individual areas you are monitoring, for example SAP NetWeaver, a WAN or a LAN, or printer services. Business processes are not typically confined to any one of these areas and each business process depends on the services of several areas and is specific to the customer's defined processes.

For example, for an operator to enter orders and print acknowledgments, the printer, the network, and SAP NetWeaver Dialog Spool Service must all be available. To monitor order entry and printing at a particular location, you could set up a view that includes the WAN, the LAN at that location, the printer being used for the order acknowledgments, and the SAP NetWeaver dispatch, dialog, and spooling processes for the specific SAP NetWeaver instance.

Figure 26 Service Areas Affecting Order Entry



To create a line-of-business service view, you must first define the structure you want to see by generating a custom service view, in which you must define one or more logical objects (for example, Order Entry) to which messages will be propagated by the objects you include in the view

Using the Service Editor (which you can start by right-clicking a service object and browsing to the option; **Configure** > **Services** in the menu that pops up) obtain the service names of the objects you want to include and add use references and dependencies to them from your custom service view.

Be aware that the services should only be built on top of logical (not physical) service objects. For example, use the SAP Spool-Service object in a reference but not the underlying physical objects such as Spool Work Process. This ensures that your customization and Business Service Views remain working, even if new releases of SAP or the SPI for SAP change the dependencies between physical components, for example, as a result of architectural changes.

Configuring Service Views for SAP

To use the service-views feature of the SPI for SAP, you need to find out which services are running on the SAP servers you are monitoring and upload the discovered information to the HPOM for Windows database, as follows:

- 1 Ensure that the r3itosap.cfg file is available on all the managed nodes for which you want to generate a service view: typically, the managed nodes are the SAP servers, which you want to manage with the SPI for SAP. The service-discovery policy requires the information in the r3itosap.cfg file to complete its task successfully.
- 2 In the HP Operations Manager for Windows console, browse to the following folder:

Policy management > Policy groups > SPI for SAP

- 3 Select and right-click the following policy:
 - **r3sdisc** (Service auto-discovery)
- 4 Browse to the following option in the menu, which pops up:

All Tasks > Deploy on...

Service Views 343

In the Deploy Polices on... window, select the managed nodes (SAP servers) where you want to run the automatic discovery of SAP services. Click **OK**.



You can monitor the deployment in real time in the Deployment Jobs pane at the bottom of the HPOM for Windows console.

6 The service discovery starts as soon as the policy is successfully deployed to the managed node and, in addition, according to the schedule defined in the policy. The default schedule is once a day.

You can verify that the service discovery has completed successfully, by browsing to the Services folder in the HPOM for Windows console and checking for the presence of the SAP servers (where you ran the service discovery) and the associated services.

Troubleshooting Service Discovery

In normal circumstances, the SPI for SAP discovers SAP services automatically and without any problem. However, if for any reason the information the SPI for SAP is looking for is not present in the default locations, then the service-discovery process fails.

For example, the SPI for SAP needs to know the names of the hosts on which SAP instances are running and, in addition, the location of the SAP profile directory, which contains the SAP **default**, **instance**, and **startup** profiles. The SAP default and instance profiles are of particular interest as they contain SAP System- and instance-specific information, which the SPI for SAP uses to determine the SAP System IDs (SID) and SAP instance names as well as the SAP instance numbers, whose services it attempts to discover.

In the event that the service discovery fails, you can use the environment variables in Table 86 on the managed node to help the SPI for SAP find the information it needs to discover SAP services successfully. The SPI for SAP Service discovery tool looks for SAP profiles in the following locations on the SAP application servers:

UNIX operating systems

/sapmnt/<SID>/profile/

Microsoft Windows operating systems

\\<central instance host>\sapmnt\<SID>\SYS\profile\

On SAP application servers running Microsoft Windows operating systems, the path to the SAP profile includes the name of the host on which the SAP central instance is running, for example: <central_instance_host>. Note that you can use the long or short hostname, the IP address of the hostname, or the UNC notation.

Table 86 Service-discovery Environment Variables


Environment Variable	Description
SAPOPC_SAPPROFILEDIR	the path to the location of the SAP profiles. Like the PATH environment variable, it may contain a list of directories where the profiles could reside
SAPOPC_HOSTNAMES	Use on managed nodes in a high-availability cluster to define the list of physical and virtual hostnames (each separated by a space) to process with service- discovery

Service Views 345

SPI for SAP Service View for Java Server

The SPI for SAP provides a Service Auto-Discovery policy, which you can deploy on each managed node to analyze the SAP environment and generate a service view for the Java systems. The service view represents all existing ownership and dependency relationships between objects on the nodes, message-propagation rules, and any actions that are available for objects.

The service view reflects your individual setup. Each service view is a unique representation of the environment from which it is taken. In general, the Java service view consists of instances and availability.



Configuring Service Views for J2EE Server

To use the J2EE Server service-views feature of the SPI for SAP, you need to find out which services are running on the SAP servers you are monitoring and upload the discovered information to the HPOM database, as follows:

- 1 Deploy the SiteConfig file.
- 2 Configure Service Views for J2EE Server.

Deploy the SiteConfig File

In the HPOM console, open the policy dialog of the global_Siteconfig policy from Policy Groups \rightarrow SPI for SAP \rightarrow en.

- 2 Specify the value for every attribute for the Java Instances that you want to monitor.
- 3 Click Save and Close.

Deploy the global SiteConfig policy on the node.

Configuring Service Views for Java System

To configure the Service Views for Java systems:

In the HP Operations Manager for Windows console, browse to the following folder:

Policy management > Policy groups > SPI for SAP > en

- 2 Select and right-click the following policy:
 - r3j2eesdisc (Service auto-discovery)
- 3 Browse to the following option in the menu, which pops up:

All Tasks > Deploy on...

- 4 In the Deploy Polices on... window which appears, select the managed nodes (SAP servers) where you want to run the automatic discovery of SAP services. Click **OK**.
- 5 The service discovery starts as soon as the policy is successfully deployed to the managed node and, in addition, according to the schedule defined in the policy. The default schedule is once a day.

You can verify that the service discovery has completed successfully, by browsing to the Services folder in the HPOM for Windows console and checking for the presence of the SAP servers (where you ran the service discovery) and the Java systems.

Service Views 347

9 Service Reports

The information in this section introduces you to the concept of Service Reports and explains how you can use them in conjunction with both the SPI for SAP and HPOM for Windows to provide you with information that is specifically designed to help you manage your SAP NetWeaver landscape in a more efficient and more convenient way. You can find detailed information about the following topics:

- What Are Service Reports? on page 349
- Upgrading the SPI for SAP Reports on page 349
- Installing the SPI for SAP Reports on page 350
- Service Reports in the SPI for SAP on page 353
- SPI for SAP Report Metrics on page 361
- Removing the SPI for SAP Reports on page 363

What Are Service Reports?

Service reports are web-based reports that are produced by HP Reporter (Reporter) using default templates and viewed using a web browser. Reporter allows you to request both scheduled and on-demand versions of reports.

SPI for SAP service reports correlate the data extracted from either the HP Software Embedded Performance Component or the HP Performance Agent. You can use the correlated data to generate reports which display short-, medium-, or long-term views of your IT environment and supplement the detailed, real-time graphs available with Performance Manager. The combination of reports and graphs is a powerful tool for trend analysis. For example, you can perform the following tasks:

- Identify potential bottlenecks in your IT system, so that you can take action before problems become acute.
- Use the information presented in the reports to help you to make accurate predictions for future upgrades.
- Collect accurate information to use in measuring service levels.

Upgrading the SPI for SAP Reports

This section describes what you have to do if you upgrade the SPI for SAP software and the SPI for SAP R/3 Performance Agent and want to continue using the service-reporter functionality. Note that upgrading the SPI for SAP Service Reports is not the same as

upgrading the HP Reporter software. For more information about supported software versions, refer to HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows.

For more information about upgrading the SPI for SAP R/3 Performance Agent, which gathers performance data for the Service Reports, see Upgrading the SPI for SAP R/3 Performance Agent on page 202. For more information about upgrading the SPI for SAP itself, see "Upgrading the SPI for SAP" in the HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows.

The SPI for SAP comes with a Reporter-integration package containing improved and enhanced reports, some of which make use of new metrics lists. To upgrade the SPI for SAP reporter-integration, you have to remove the old Reporter-integration package and install the new one in its place, as follows:

1 Remove the old SPI for SAP reporter-integration package using the standard Windows method:

Start: Settings > Control Panel > Add/Remove Software

- 2 Install the new SPI for SAP reporter integration as described in Installing the SPI for SAP Reports on page 350.
- 3 Schedule and generate the new service reports as described in Generating SPI for SAP Reports on page 360.

Installing the SPI for SAP Reports

This section explains how to install the SAP NetWeaver service reports which come with the SPI for SAP and, in addition, provides information designed to help you prepare for the installation. The section covers the following topics:

- Before You Begin on page 350
- Installing SAP Service Reports on page 351

Before You Begin

Before you install and set-up for the SAP NetWeaver Service Reports, you must ensure that the following tasks have been completed:

1 Performance Agent

Either the HP Software Embedded Performance Component or the HP Performance Agent must be available on all SAP NetWeaver managed nodes for which you want to produce service reports.

The HP Performance Agent agent must also have been configured according to the instructions given in The SPI for SAP Performance Monitors on page 221.

2 Service Reports

The HP Reporter instance must be available. For more detailed information about the platforms the Reporter supports, see the Reporter product documentation.



HP Reporter light is no longer bundled with HPOM for Windows. You have to install and use the *full* version of the HP Reporter to view SPI for SAP reports.

If you want to edit existing (or create new) Service Reports for the SPI for SAP, make sure that Crystal Reports is running on the machine hosting the HP Reporter. For more information about required or supported software versions, see the *HP Operations Smart Plug-in for SAP Installation and Configuration Guide for Windows*.

Installing SAP Service Reports

The service reports for SAP NetWeaver are installed into the HP Reporter product as a snap-in using InstallShield on the HP Reporter system. During set-up you will be asked to select the common application path of HP Reporter. This is the folder where you installed HP Reporter. Setup attempts to discover this path automatically and indicate to you what it finds. In most circumstances you should avoid changing it and accept the suggested settings.

The set-up copies components to the directories as summarized in Table 87. All directory paths are relative to the HP Reporter common application path.

 Component
 Directory

 Configuration files
 \newconfig\

 Installation script
 \newconfig\

 Report template files
 \data\reports\Sap\

 Executables
 \bin\

Table 87 Locations of SAP Service Report Components

To install the SPI for SAP Service Reports:

1 Insert the product media and browse to the following directory:

```
\Disk2\SAP SPI Reporter Package
Double-click the sapspi_reporter.msi file, and select the Custom Setup option.
```

2 Follow the installation-wizard's instructions. During set-up of the SPI for SAP service reports you will be asked to confirm or specify the common application path for the HP Reporter. Accept the default to ensure that all automatic configuration steps are correctly executed without the need for manual re-configuration.



If you change the common application path, set-up will not be able to find its executables and will generate warning messages.

- 3 Set-up automatically performs the following tasks:
 - Creates SAP-specific report group: SAP_R3
 - Assigns metric list to the SAP_R3 report group
 - Assigns group reports to the SAP R3 report group
 - Assigns system reports to the SAP_R3 report group
- 4 Verify that the installation of the SPI for SAP service reports completed successfully by confirming that setup created the report and metrics groups mentioned in the previous step and listed in full in SPI for SAP Report Metrics on page 361. The installation should look similar to the example illustrated in Figure 27.
- 5 If you choose to add your SAP NetWeaver system to HP Reporter manually, you can use the following values in the Add System window replacing the example "host.name.com" with the real name of the system you want to add:

Service Reports 351


System: host.name.com
 Replace "host.name.com" with the real name of the system you want to add to HP Reporter.

Network: SAPDomain: SAP

Check that your SAP NetWeaver hosts have been added to the appropriate HP Reporter group, namely; SAP_R3. Hosts are automatically assigned to a report group according to the kind of data source (SAP NetWeaver) discovered on the monitored host.


- 6 Click **OK** to display the newly added systems in the Reporter's Details Pane.
- 7 Use the Reporter GUI to schedule the generation of the SPI for SAP reports or generate them now using the following option:

Actions > Run > Generate Reports



8 After you have successfully generated the SPI for SAP reports, you can view them with any standard web browser. For more information about how to view the SPI for SAP reports, see Viewing SPI for SAP Reports on page 361.

Figure 27 SPI for SAP Reports and Metrics



Service Reports in the SPI for SAP

The Smart Plug-in for SAP includes a package of service reports that use the data collected by the HP Software Embedded Performance Component and HP Performance Agent to generate reports, which display vital information about the health and availability of the Systems in your SAP landscape. The reports provided in the Smart Plug-in for SAP report package cover a wide variety of system- and business-critical areas.

The information in this section describes in detail the service reports, which are supplied with the SPI for SAP. You can find information about the following topics:

SAP Reports on page 354

A complete list of all the SAP-related reports provided with the SPI for SAP including the metrics used

Defining the Scope of SAP Service Reports on page 359

Hints to help you target more accurately the information you want to display in a report

Generating SPI for SAP Reports on page 360

Instructions for starting the generation of the SPI for SAP reports

Viewing SPI for SAP Reports on page 361

Instructions for viewing the SPI for SAP reports you have generated

The SPI for SAP service-report integration supports the remote-monitoring functionality, where SAP servers which are *not* HPOM for Windows managed nodes and do *not* have the SPI for SAP software installed, are monitored remotely from an HPOM for Windows managed node, where the SPI for SAP monitors are installed, configured, and running. You can generate service reports for SAP servers, which are managed remotely. For more information about remote monitoring feature, see Remote Monitoring with Alert Monitors on page 24, and Remote Performance Monitoring on page 214.

Service Reports 353

SAP Reports

Table 88 lists the SAP reports available with the Smart Plug-in for SAP. You can also find in the table details about the information displayed in the reports and the individual metrics used to generate the reports. For more information about the SPI for SAP performance monitors, see The SPI for SAP Performance Monitors on page 221.

Table 88 SAP Performance Reports

Report	Purpose	Metrics
Database Performance	Correlates and displays the most important database performance metrics	 Physical reads/writes Disk Physical IO Long Table Scans Sort Rows Sort in Memory Sort on Disk Redo block Written Redo Buffer Size
Database Quality	Shows important metrics, which taken together give a detailed picture of the quality of the database configuration	 Quality of data base buffer pool Quality of Data Dictionary cache Redo-Log faults Buffer Pool Size Dictionary Cache Size Redo log buffer size Buffer busy waits Buffer busy wait time
Enterprise Portal Performance Enterprise Portal Availability	Correlates and displays the most important status and performance metrics for the SAP Enterprise Portal	 Average response time Average CPU time Average Outbound data Average number of component calls per request Number of users making requests Requests running in different levels Percentage of requests not serviced
E2E Time	Shows the E2E Transaction Time of the configured transactions, divided into Response and Network Time	Response timeNetwork time

Table 88 SAP Performance Reports (cont'd)

Report	Purpose	Metrics
ICM Statistics - Overview ICM Statistics - Details	Shows an overview of the status of the Internet Communication Manager plus general information about queues, threads, and connections Shows a much more detailed view of the status of the Internet Communication Manager including up-time and down-time periods, plus statistics for request queues, work threads, and open connections	 ICM Status Max. number of threads Peak number of threads Current number of threads Max. number of connections Peak number of connections Current number of connections Max. number of queue entries Peak number of queue entries Current number of queue entries Current number of queue entries Number of running work threads Number of processed work threads Number of processed work threads
Job Overview	Shows the number of jobs for the SAP instances in the different, specified states (running, ready, released)	Number of Jobs in the status: Running Ready Scheduled Released Aborted Finished
Number of Spool Jobs	Shows the number of spool jobs and print requests in different status	 Total Number of Spool Jobs Number of Spool Jobs in status Archive Number of open print Requests Number of print Requests with errors Number of failed print requests
Amount of Update Tasks	Shows the amount of Update tasks	 total VB-update tasks initial VB-update tasks erroneous VB-update tasks update tasks having V1 executed update tasks having V2 executed
Work Process Overview	Compares the total number of the different work processes with the number of in use processes	 Dialog processes/processes in Use Batch processes/processes in Use Spool processes/processes in Use Update processes/processes in Use Update2 processes/processes in Use
Document Volume	Shows the total document volumes per module (BW, FA, QA) correlated with business-transaction metrics	GUI net timeResponse timeCPU timeDB Request time

Service Reports 355

Table 88 SAP Performance Reports (cont'd)

Report	Purpose	Metrics
Document & Lines	Shows the number of documents and the lines created per document, sorted by SAP application module	 Head - generic doc. information Detail - the average number of lines in the document. The larger the file, the longer it takes to commit to the database.
Document Volume by Module	Shows the volume of documents per application module	Number of documents
Workload Overview Count	Shows the number of steps for all task types in an SAP NetWeaver System, for example: Batch, Dialog, Spool, Update)	GUI net timeResponse timeCPU timeDB Request time
Workload Overview Response Time	Shows the average number of steps and response time (in seconds) for each SAP NetWeaver instance	 CPU Time Load Time Queue Time DB Read Time
Workload Overview Task Type	Shows the average number of steps and response time (in seconds) for each task type (AUTOABA, BCKGRD)	DB Read Time DB Update Time
Workload Overview DB Overview	Shows the work-load metrics based on database activity for a defined SAP NetWeaver system	Change CountChange TimeDB CallsDB Requests
Workload Overview DB Task Type	Shows the work-load metrics per task type and based on database activity for a defined SAP NetWeaver system	 DB Requests DB Time per Req. Read-Dir Count Read-Dir Time Read-Seq. Count Read-Seq. Time Requested Bytes
SAP R/3 Memory	Shows SAP memory use for the defined System	Extended MemoryPaging AreaRoll Area
SAP R/3 Users - Overview	Shows the number of users and user sessions per SAP client for a given SAP application server	Average UsersAverage Sessions

Table 88 SAP Performance Reports (cont'd)

Report	Purpose	Metrics
SAP R/3 Users - Workload	Shows the load for named SAP work process of users and user sessions (per SAP client/application server)	 Average Users Average Sessions Average Response Time CPU Time Dialog, Update, Spool, Batch steps
SAP R/3 Users - Document Statistics	Shows the document statistics per SAP module for users and user sessions (per SAP client/application server)	Average SessionsAverage UsersSAP Module (FA, MM, SD)
SAP R/3 Buffer Performance - Overview SAP R/3 Buffer Performance - Detailed Analysis	Shows general and detailed analyses of the use of SAP memory buffers by SAP users for a given instance and client.	 Buffer Name Hit Ration Allocated Size Free Space Free Space Percent Max. Dir Entry Free Dir Entry Free Dir Entry (Percent) Buffer Swaps Buffer Swaps (Delta) Database Accesses Database Accesses (Delta)
Threads usage rate for different ports	Shows the usage rate of different ports in the form of a bar graph.	 http http ssl iiop iiop ssl p4 p4 http tunneling p4 ssl telnet jms provider
Connections count	Shows the sum of connections of all types in the form of a bar graph.	 http connections p4 connections iiop connections jms connections telnet connections Other connections Free connections Maximum connections

Service Reports 357

Table 88 SAP Performance Reports (cont'd)

Report	Purpose	Metrics
Memory Consumption	Shows the average memory consumption in the form of a bar graph.	 Allocated memory Available memory Used memory
Sessions view	Shows the sum of the sessions of all types in the form of a line graph.	 Active sessions Total sessions Timed-out sessions Invalid sessions Logged-off sessions
Requests view	Shows the sum of the requests of all types in the form of a bar graph.	Web container all requestsp4 provider all requestshttp provider all requests
Comparison of application and system threads	Shows the sum of sizes of application threads of all types in the form of a line graph.	 Minimum Application thread pool size threads Maximum application thread pool size threads Initial application thread pool size threads Current application thread pool size threads Active applications threads Minimum system thread pool size threads Maximum system thread pool size threads Initial system thread pool size threads Current system thread pool size threads Current system thread pool size threads Active system threads
Comparison of application and system waiting tasks	Shows the states of the waiting task details between the application thread pool and system thread pool in the form of a line graph.	 Waiting application tasks Waiting application queue size tasks Waiting application queue overflow tasks Waiting system tasks Waiting system queue size tasks Waiting system queue overflow tasks

Table 88 SAP Performance Reports (cont'd)

Report	Purpose	Metrics
Opened Sessions	Shows the total number of security, web, and EJB sessions in the form of line graph.	Opened security sessions countOpened web sessions countOpened EJB sessions count
Transaction Count	Shows the total number of transactions in various states in the form of line graph.	 Committed Transactions count Open Transactions count Rolled Back Transactions count Suspended Transactions count Timedout Transactions count
Message Status in the Log Configurator	Shows the total number of warning, error, and fatal messages in the form of line graph.	AllWarningErrorFatal

The following table lists the reports supported on SAP Netweaver 7.0 and SAP Netweaver 7.1.

Table 89 SAP 7.0 and SAP 7.1 Reports

Report Name	SAP 7.0	SAP 7.1
Memory Consumption	Yes	Yes
Comparison of System and Application threads	Yes	Yes
Comparison of System and Application Waiting Tasks	Yes	Yes
Requests View	Yes	Yes
Sessions View	Yes	No
Threads usage for different ports	Yes	No
Connections count for different ports	Yes	No
Opened Sessions	No	Yes
Transaction Count	No	Yes
Message Status in the Log Configurator	No	Yes

Defining the Scope of SAP Service Reports

You can limit the scope of any service report by using the following criteria:

- Specify which systems to include, by using one of the following possible values:
 - all systems
 - a selected group of systems
 - a selected system

Service Reports 359

- Specify the period for which you want to include report data by using one of the following possible values:
 - a full *range* (up to the last 180 days)
 - last full month
 - last full week
 - yesterday

Generating SPI for SAP Reports

You can use the Reporter GUI either to schedule the generation of the SPI for SAP reports or manually generate them on demand. You should consider using the schedule option, if you need to generate a lot of reports and the reports involve collecting and processing data from multiple SAP Systems. To generate single reports or multiple reports, follow the steps described below:

- 1 Make sure you complete the installation and configuration steps described in Installing SAP Service Reports on page 351 before you start generating reports.
- 2 Use the Reporter GUI to schedule data collection for the SPI for SAP reports using the following menu option:


Report Administrator> Schedule > Gather

In the right pane, select and right-click the job whose schedule you want to view or change. To ensure that all data up to the current hour are included in the collection for the given host, use the -h option before the host name in the Parameters box of the Edit Schedule Entry window.



Due to differences between the way SAP and the SPI for SAP's performance-data sources (HP Software Embedded Performance Component and HP Performance Agent) handle time, avoid scheduling data collection to start between midnight (00:00) and 2 a.m. (02:00). Run data collection *after* 02:00 instead, as illustrated in Figure 28 on page 360.

Figure 28 Setting up Data Collection for Reports



3 Use the Reporter GUI to start the generation of the SPI for SAP reports using the following option:

Actions > Run > Generate Reports



Remember to allow enough time for the data-collection process to complete to ensure you have all the latest data for the reports.

Viewing SPI for SAP Reports

To view the SPI for SAP reports:

- First, ensure that the reports have been successfully generated. For more information about generating reports, see Installing SAP Service Reports on page 351.
- 2 Open a web browser.
- 3 Enter the following string in the location bar: http://<machine.name.com>/HPOV_reports/reports.htm
- 4 Navigate through the displayed reports to the report, which you want to examine more closely.

SPI for SAP Report Metrics

This section lists the metrics used by the reports for SAP R/3 and SAP Netweaver, which are installed as part of the SPI for SAP reporter package. For more information about the metrics listed in the section below, see The SPI for SAP Performance Monitors on page 221. For more information about the SPI for SAP reports, see Service Reports in the SPI for SAP on page 353.

SAP Report Metrics

The information in this section shows which performance metrics are used to gather the data that is used in the preparation of the performance-related reports for the SPI for SAP. Note that the name of the performance metric is often (but not always) the same as the monitor that collects the performance data. For example, the SPI for SAP performance monitor DBINFO_PERF uses the metrics list DBINFO_PERF; the performance monitor USER_PERF uses the metrics list SAP_USER_PERF.

Table 90 lists the metrics that are available to the SPI for SAP and shows which performance monitor uses the metric.

Table 90 SPI for SAP Performance-report Metrics

Report-metric Name	Referenced Monitor	Description
DBINFO_PERF	DBINFO_PERF	Collects database-performance analysis values
DOCSTAT_PERF	DOCSTAT_PERF	Collects the quantity-structure statistics (the document volume) for the last full hour
EP_PERF	EP_PERF	Monitors the status and performance of the SAP Enterprise Portal

Service Reports 361

Table 90 SPI for SAP Performance-report Metrics (cont'd)

Report-metric Name	Referenced Monitor	Description
JOBREP_PERF	JOBREP_PERF	Counts the number of jobs per state (scheduled, running, etc.)
SAPBUFFER_PERF	SAPBUFFER_PERF	Returns values for the use of SAP memory <i>buffers</i> for an SAP instance
SAPMEMORY_PERF	SAPMEMORY_PERF	SAP memory used by SAP users for an SAP instance
SAP_ICMSTAT_PERF	ICMSTAT_PERF	Monitors the status and performance of the SAP Internet Communication Manager
SAP_STATRECS_PERF	STATRECS_PERF	Returns the response/net times of defined transactions
SAP_SYSUP_PERF	SYSUP_PERF	Shows the status of the SAP NetWeaver instances
SAP_USER_PERF	USER_PERF	Monitors the number of users and user sessions per SAP client for a given SAP application server
SAP_WLSUM_PERF	WLSUM_PERF	Collects the performance-workload statistics
SPOOL_PERF	SPOOL_PERF	Counts the number of spool requests in different states
UPDATE_PERF	UPDATE_PERF	The number of update processes
WP_PERF	WP_PERF	Number of users/sessions per SAP client for an SAP application server

SAP Netweaver Report Metrics

The following list shows which performance metrics are used to gather the data that is used in the preparation of the performance-related reports for SPI for SAP Netweaver 7.0 and Netweaver 7.1.

SAP Netweaver 7.0

Uses the data source "SAPSPINW_RPT_METRICS" to gather data from SAP Netweaver 7.0 instances.

• SAP Netweaver 7.1

Uses the datasource "SAPSPINW_RPT_METRICS" to gather data from SAP Netweaver 7.1 instances. This data source is the same data source as used by Netweaver 7.0.

362 Chapter 9

Removing the SPI for SAP Reports

To completely remove the SPI for SAP reports and the integration with the HP Reporter, you need to perform the following steps described in this section in the order specified. This section covers the following topics:

- To Remove HP Reporter Snap-in Packages on page 363
- To Remove the SPI for SAP from the Reporter System on page 363

To Remove HP Reporter Snap-in Packages

Use the following instructions to help you remove the SPI for SAP snap-in package for the HP Reporter quickly and easily from the HP Reporter system:

1 In Reporter, browse to:

File > Configure > Reporter Packages

- 2 Select the following files from the Installed Packages window located in the right pane of the Configure Report Packages window:
 - SPI for SAP
- Double-click the left arrow button [<-] in the Available Packages window located in the left pane of the Configure Report Packages window.
- 4 Click **OK** to finish

To Remove the SPI for SAP from the Reporter System

To remove the SPI for SAP binaries from the HP Reporter system, you need to carry out the following steps on the HP Reporter system as the system administrator:

- 1 Go to the HP Reporter system.
- 2 Insert the HP Operations Smart Plug-in DVD in the DVD drive.
- 3 Chose to remove program.
- 4 Follow the on-screen instructions and select Reports under SAP SPI.
- 5 Follow the on-screen instructions to complete the removal process.

Service Reports 363

364 Chapter 9

A SPI for SAP Golden Metrics

Golden Metrics are the most important and fundamental metrics for monitoring the SAP and its environment. With the help of these metrics, you can monitor the health, availability, and performance of the ABAP and Java Stack of the SAP Netweaver system.

Table 91 Golden Metrics for ABAP

Metric Type	Monitor fetching the metric	Metric
Alert for ABAP	r3status	r3status - r3status: The SAP Status Monitor
	r3mondev	r3mondev - r3mondev: The SAP Trace-file Monitor
	r3monsec	r3monsec - r3monsec: The SAP Security Monitor
	r3monale	r3monale - r3monale: The iDOC-Status Monitor
	r3mondmp	r3mondmp - r3mondmp: The ABAP-Dump Monitor
	r3monjob	r3monjob - r3monjob: The Job-Report Monitor
	r3monupd	r3monupd - r3monupd: The Update Monitor
	r3monusr	r3monusr - r3monusr: The SAP-User Monitor

Table 92 Golden Metrics for Java

Metric Type	Metric
Alert for Java	nwstatus
	SPISAP_0207
	SPISAP_0219
	SPISAP_0233
	SPISAP_0234
	SPISAP_4201
	SPISAP_4202
	SPISAP_4203
	SPISAP_4204
	SPISAP_4206

In addition to the Alert metrics, the following are the important Netweaver ABAP and Java Performance metrics that you can use to log the data and view as Reports.

366 Chapter A

Table 93 Performance Metrics for ABAP

Metric Type	Monitor fetching the metric	Metric
Performance for ABAP	DBINFO_PERF	CPUUSAGE
	JOBREP_PERF	ABORTED
	SAPBUFFER_PERF	HITRATIO
	SAPMEMORY_PERF	CURRENT_USE_PERCENT
		ON_DISK
	SPOOL_PERF	OPEN_PR
		ERROR_PR
		FAILED_PR
	STATRECS_PERF	SAP_REC_COUNT
	WLSUM_PERF	RESPTI
		CPUTI
		CHNGCNT
		GUITIME
		GUINETTIME
	WP_PERF	LONG_RUNNING
	EP_PERF	AVG_RESP_TIME_EP
		AVG_CPU_TIME_EP
		AVG_CMPCALLPERREQ_EP

Table 94 Performance Metrics for Java

Metric Type	Metric
Performance for Java	SPISAP_2202 (Available memory)
	SPISAP_2201 (Allocated memory)
	SPISAP_2203 (Used memory)

368 Chapter A

B Data Store Details for SPI for SAP Reports

The SPI for SAP creates the following data store table for the metrics to enable data collection.

 $\textbf{DataSource Name:} \ \texttt{R3} \verb|<| SAP_Hostname>| <| SAP_SID>| <| SAP_Instance| \ \textit{Number>}| \ \texttt{DATA}| \\$

Spec File: r3statistics.DBINFO_PERF

Table Name and Report Details	Metric in the table	Metric Data Type
DBINFO_PERF	CPUUSAGE	R64
	BUFPREADS	I32
	BUFPWRITES	I32
	BUFQUAL	R64
	BUFSIZE	I32
	BUFWAITS	I32
	BUFWTIME	I32
	DICTSIZE	I32
	DDQUAL	R64
	LOGBLOCKS	I32
	LOGENTRIES	I32
	LOGSIZE	I32
	LOGFAULT	R64
	LOGALLOC	I32
	ROLLBACKS	I32
	SCANLONG	I32
	SORTDISK	I32
	SORTMEM	I32
	SORTROWS	I32
	HOSTNAME_DBINFO	UTF8
	SID_DBINFO	UTF8
	INSTANCE_DBINFO	UTF8
	KEY_DBINFO	UTF8

Spec File: r3statistics.DOCSTAT PERF

Table Name and Report Details	Metric in the table	Metric Data Type
DOCSTAT_PERF	APPMODE_DOC	UTF8
	CNTHEADER	I32
	CNTITEM	I32
	CNTDIV	I32
	CNTTOTAL	I32
	CNTLINE	I32
	CNTCHGDOC	I32
	CNTTEXT	I32
	HOSTNAME_DOCSTAT	UTF8
	SID_DOCSTAT	UTF8
	INSTANCE_DOCSTAT	UTF8
	KEY_DOCSTAT	UTF8

Spec File: r3statistics.EP_PERF

Table Name and Report Details	Metric in the table	Metric Data Type
EP_PERF	SID_EP	UTF8
	HOSTNAME_EP	UTF8
	START_TIME_EP	UTF8
	NO_REQ_EP	I32
	AVG_RESP_TIME_EP	R64
	AVG_CPU_TIME_EP	R64
	REQ_PER_SEC_EP	I32
	AVG_OUTBND_DATA_EP	I32
	ACC_RESP_TIME_EP	R64
	ACC_CPU_TIME_EP	R64
	OUTBND_DATA_REQ_EP	I32
	ACC_OUTBND_DATA_EP	I32
	NO_COMPCALLS_REQ_EP	I32
	AVG_CMPCALLPERREQ_EP	I32
	VALID_MONDATA_REQ_EP	I32
	REQ_NOT_CORR_CLSD_EP	I32
	REQCLSD_TOOMNYCMP_EP	I32
	REQS_RUNLEVEL_0_EP	I32
	REQS_RUNLEVEL_1_EP	I32
	REQS_RUNLEVEL_2_EP	132
	USRS_SINCE_1_REQ_EP	I32
	USRS_SINCE_LSTRST_EP	I32
	LST_REQ_RST_TSTMP_EP	UTF8
	LST_CMPREQ_TSTMP_EP	UTF8
	LST_USRREQ_TSTMP_EP	UTF8

Spec File: r3statistics.ICMSTAT_PERF

Table Name and Report Details	Metric in the table	Metric Data Type
ICMSTAT_PERF	ICM_Status	I32
	Max_Threads	I32
	Peak_Threads	I32
	Cur_Threads	I32
	Max_Connections	I32
	Peak_Connections	I32
	Cur_Connections	I32
	Max_QueueEntries	I32
	Peak_QueueEntries	I32
	Cur_QueueEntries	I32
	Running_Threads	I32
	Dead_Threads	I32
	Processed_Threads	I32
	HOSTNAME_ICMSTAT	I32
	SID_ICMSTAT	UTF8
	INSTANCE_ICMSTAT	UTF8
	KEY_ICMSTAT	UTF8

Spec File: r3statistics.JOBREP_PERF

Table Name and Report Details	Metric in the table	Metric Data Type
JOBREP_PERF	RUNNING	UTF8
	READY	I32
	SCHEDULED	I32
	RELEASED	I32
	ABORTED	I32
	FINISHED	I32
	PUT_ACTIVE	I32
	UNKNOWN_STATE	I32
	HOSTNAME_JOBREP	UTF8
	SID_JOBREP	UTF8
	INSTANCE_JOBREP	UTF8
	KEY_JOBREP	UTF8

Spec File: r3statistics.SAPBUFFER_PERF

Table Name and Report Details	Metric in the table	Metric Data Type
SAPBUFFER_PERF	BUFFER_NAME	UTF8
	HITRATIO	R64
	ALLOCATED_SIZE	I32
	FREE_SPACE	I32
	FREE_SPACE_PERCENT	R64
	MAXDIR_ENTR	I32
	FREEDIR_ENTR	I32
	FDIR_ENTR_PERCENT	R64
	BUFFER_SWAPS	I32
	BUFFER_SWAPS_DELTA	I32
	DB_ACCESSES	I32
	DB_ACCESSES_DELTA	I32
	HOSTNAME_SAPBUFFER	UTF8
	SID_SAPBUFFER	UTF8
	INSTANCE_SAPBUFFER	UTF8
	KEY_SAPBUFFER	UTF8

DataSource Name: R3_<SAP_Hostname>_<SAPSID>_<SAP_Instance_ Number>_DATA

Spec File: r3statistics.SAPMEMORY PERF

Table Name and Report Details	Metric in the table	Metric Data Type
SAPMEMORY_PERF	MEMORY_AREA	UTF8
	CURRENT_USE_PERCENT	R64
	CURRENT_USE	I32
	MAX_USE	I32
	IN_MEMORY	I32
	ON_DISK	I32
	HOSTNAME_SAPMEMORY	UTF8
	SID_SAPMEMORY	UTF8
	INSTANCE_SAPMEMORY	UTF8
	KEY_SAPMEMORY	UTF8

 $\textbf{Spec File:} \ \texttt{r3statistics.SPOOL_PERF}$

Table Name and Report Details	Metric in the table	Metric Data Type
SPOOL_PERF	ALL_SJ	I32
	SJ_ARCHIVE	I32
	PRINT_REQ	I32
	OPEN_PR	I32
	SUCCESS_PR	I32
	ERROR_PR	I32
	FAILED_PR	I32
	HOSTNAME_SPOOL	UTF8
	SID_SPOOL	UTF8
	INSTANCE_SPOOL	UTF8
	KEY_SPOOL	UTF8

DataSource Name: R3_<SAP_Hostname>_<SAPSID>_<SAP_Instance_ Number>_DATA

Spec File: r3statistics.STATRECS PERF

Table Name and Report Details	Metric in the table	Metric Data Type
SAP_STATRECS_PERF	SAP_TCODE	UTF8
	SAP_RESPONSE_T IME	I32
	SAP_NET_TIME	I32
	SAP_REC_COUNT	I32
	SAP_HOST_STATRECS	UTF8
	SAP_SID_STATRECS	UTF8
	SAP_INSTNO_STATRECS	UTF8
	SAP_KEY_STATRECS	UTF8

Spec File: r3statistics.SYSUP_PERF

Table Name and Report Details	Metric in the table	Metric Data Type
SYSUP_PERF	SYSTEM_STATUS	UTF8
	HOSTNAME_SYSUP	UTF8
	SID_SYSUP	UTF8
	INSTANCE_SYSUP	UTF8
	KEY_SYSUP	UTF8

 $\textbf{DataSource Name:} \ \texttt{R3} \verb|<| SAP_Hostname>| <| SAP_Instance| \ \textit{Number>} \verb|| DATA \\$

Spec File: r3statistics.UPDATE PERF

Table Name and Report Details	Metric in the table	Metric Data Type
UPDATE_PERF	ALL_TASKS	UTF8
	INITIAL_TASKS	I32
	ERRONOUS_TASKS	I32
	VB1	I32
	V2	I32
	HOSTNAME_UPDATE	UTF8
	SID_UPDATE	UTF8
	INSTANCE_UPDATE	UTF8
	KEY_UPDATE	UTF8

DataSource Name: R3_<SAP_Hostname>_<SAPSID>_<SAP_Instance_ Number>_DATA

Spec File: r3statistics.USER PERF

Table Name and Report Details	Metric in the table	Metric Data Type
USER_PERF	USER_CLIENT	UTF8
	USER_CNT	I32
	SESSION_CNT	I32
	HOSTNAME_USER	UTF8
	SID_USER	UTF8
	INSTANCE_USER	UTF8
	KEY_USER	UTF8

DataSource Name: R3_<SAP_Hostname>_<SAPSID>_<SAP_Instance_ Number>_DATA

Spec File: r3statistics.WLSUM PERF

Table Name and Report Details	Metric in the table	Metric Data Type
SAP_WLSUM_PERF	SAP_HOSTNAME_WLSUM	UTF8
	SAP_SID_WLSUM	UTF8
	SAP_INSTANCE_WLSUM	UTF8
	SAP_KEY_WLSUM	UTF8
	SAP_TASKTYPE	UTF8
	SAP_CNT	I32
	SAP_DBACTIVCNT	I32
	SAP_RESPTI	R64
	SAP_CPUTI	R64
	SAP_QUEUETI	R64
	SAP_LOADGENTI	R64
	SAP_COMMITTI	R64
	SAP_DDICTI	R64
	SAP_QUETI	R64
	SAP_CPICTI	R64
	SAP_ROLLINCNT	I32
	SAP_ROLLINTI	R64
	SAP_ROLLOUTCNT	I32
	SAP_ROLLOUTTI	R64
	SAP_READDIRCNT	I32
	SAP_READDIRTI	R64
	SAP_READSEQCNT	I32
	SAP_READSEQTI	R64
	SAP_CHNGCNT	I32
	SAP_CHNGTI	R64
	SAP_BYTES	I32
	SAP_GUITIME	R64
	SAP_GUICNT	I32
	SAP_GUINETTIME	R64

Spec File: r3statistics.WP_PERF

Table Name and Report Details	Metric in the table	Metric Data Type
WP_PERF	ALL_WP	I32
	SEMAPHORE_WP	I32
	DEBUG_WP	I32
	LONG_RUNNING	I32
	PRIVAT_WP	I32
	NOSTART_WP	I32
	DIA_IDLE	I32
	DIA_ALL	I32
	DIA_RUNNING	I32
	BTC_IDLE	I32
	BT_ALL	I32
	BTC_RUNNING	I32
	SPO_IDLE	I32
	SPO_ALL	I32
	SPO_RUNNING	I32
	ENQ_IDLE	I32
	ENQ_ALL	I32
	ENQ_RUNNING	I32
	UPD_IDLE	I32
	UPD_ALL	I32
	UPD_RUNNING	I32
	UPD2_IDLE	I32
	UPD2_ALL	I32
	UPD2_RUNNING	I32
	HOSTNAME_WP	UTF8
	SID_WP	UTF8
	INSTANCE_WP	UTF8
	KEY_WP	UTF8

DataSource Name: SAPSPINW_RPT_METRICS

Spec File: SAPNW_reporter.sp

Report Name	Metric in the table	Metric Data Type
SAPSPINW_RPT_METRICS	METRICID	I32
	VALUEID	I32
	VALUE	R64
	SORTID	UTF8
	SERVERNAME	UTF8
	OBJECTNAME	UTF8

Index

A	AlertMonPro Keyword, 27		
ABAP DUMP Monitor, 137	Configuration File, 27		
Aborted	Alerts CCMS monitoring in the CEN, 194		
condition in job monitor, 139	SAP security-audit, 94		
Agent Hostname for r3perfagent configuration, 217	Alert Thresholds		
AgentHostname keyword, 108	SAP-RFC alert types, 154		
AlerMonSyslog Keyword, 27 Configuration File, 27	SAP-RFC Parameter CONNECTION_TYPE, 154		
Alert classes in r3monal, 61	NAME, 154 transport alert types, 160		
Alert Collector, 101 history file, 102	vicinsport diete types, 100		
alert-collector monitor configuring remote monitor, 106			
Alert-Collector Monitors polling rates for r3moncol, 101 run interval for r3moncol, 101			
AlertDevMon Keyword, 27 Configuration File, 27			
AlertInstMonPro Keyword, 27 Configuration File, 27			
AlertMonFun Keyword, 26 Configuration File, 26			
AlertMonitor Parameter, 28, 109			
Alert Monitors command-line parameters for r3moncol, 106 configuration file for r3moncol, 108 error messages, 112 validating contents, 112 configuring remote monitor, 24 environment variables, 105 environment variables for r3moncol, 105 history file for r3moncol, 102 Order of Precedence, 23 Polling Rates, 49, 101 polling rates for, 49 Query Conditions, 102 query conditions for r3moncol, 102 remote monitoring with r3moncol, 106 ReportTypes for r3moncol, 101			
run interval for, 49			

the Alert Collector, 101

Alert type	RFCONNECT, 163
CHANGE_OPTION	TPTEST, 164
SAP R/3 (4.6x), 125	TRANS, 160
CHECK, 154	r3monupd
JOB_ABORTED, 146	configuring, 166
JOB_MAX_RUN_TIME, 142	UPDATE_ACTIVE, 167
JOB_MIN_RUN_TIME, 144	UPDATE_ERRORS_EXIST, 167
OBJECT_RELEASED, 136	r3monusr
OBJECT_USED, 134	configuring, 168
OLD_LOCKS, 149	USER_LOGGEDIN_MAX, 168
OM_SWITCH_OVERDUE, 151	r3monwpa
PRINT_ERROR_EXISTS, 158	configuring, 171
r3monale	WP_AVAILABLE, 172
configuring, 116	WP_CHECK_CONFIGURED, 177
IDOC_CURRENT_STATUS, 117	WP_IDLE, 174
r3monchg	WP_STATUS, 178
CHANGE_OPT (SAP R/3 4.6x), 125	REPAIR, 162
configuring, 124	REQUEST_CREATED, 130
r3monets	REQUEST_RELEASED, 130
configuring, 129	RFCONNECT, 163
OBJECT_RELEASED, 136	SPOOL_ENTRIES_RANGE, 156
OBJECT_USED, 134	SPOOL_ERROR_RANGE, 157
REQUEST_CREATED, 130	START_PASSED, 145
REQUEST_RELEASED, 131	TASK_CREATED, 133
TASK_CREATED, 133	TASK_RELEASED, 133
TASK_RELEASED, 133	TPTEST, 164
r3mondmp	TRANS, 160
ABAP4_ERROR_EXIST, 138	UPDATE_ACTIVE, 167
r3monjob	UPDATE_ERRORS_EXIST, 167
configuring, 142	USER_LOGGEDIN_MAX, 168
JOB_ABORTED, 146	WP_AVAILABLE, 172
JOB_MAX_RUN_TIME, 142	WP_CHECK_CONFIGURED, 177
JOB_MIN_RUN_TIME, 144	WP_IDLE, 174
START_PASSED, 145	WP_STATUS, 178
r3monlck	alert type
configuring, 149	r3monale monitor, 115
OLD_LOCKS, 149	r3monchg monitor, 123
r3monoms	r3moncts monitor, 128
configuring, 151	r3mondmp monitor, 138
OM_SWITCH_OVERDUE, 151	r3monjob monitor, 140
r3monrfc	r3monlck monitor, 148
CHECK, 154	r3monoms monitor, 150
configuring, 154	r3monrfc monitor, 153
r3monsec	r3monspl monitor, 155
DEFAULT_USERS, 78	r3montra monitor, 159
PRIVILEGED_USERS, 78	r3monupd monitor, 166
SAP_PARAMETERS, 76	r3monusr monitor, 167
r3monspl	r3monwpa monitor, 170
configuring, 156	
PRINT_ERROR_EXISTS, 158	Alerttype Parameter, 28, 109
SPOOL_ENTRIES_RANGE, 156	Alert Types
SPOOL_ERROR_RANGE, 157	r3monsec, 75
r3montra	and parameter value, 105
configuring, 160	anu parameter value, 100
REPAIR, 162	

APSERVER	command-line parameters, 106
OM_SWITCH_OVERDUE, 152	for r3moncol alert monitors, 106
USER_LOGGEDIN_MAX, 169	r3monale monitor, 116
WP_AVAILABLE, 173	r3monchg monitor, 124
WP_IDLE, 175	r3moncts monitor, 129
WP_STATUS, 178	r3mondmp monitor, 138
Audit	r3monjob monitor, 141
SAP Security Logs	r3monlck monitor, 149
monitoring with r3monal, 63	r3monoms monitor, 151
SAP security monitor, 93	r3monrfc monitor, 153
SAP security alerts, 94	r3monspl monitor, 156
on security arcres, or	r3montra monitor, 159
D	r3monupd monitor, 166
В	r3monusr monitor, 168
Batch service, 341	r3monwpa monitor, 171
Batch WP service, 342	r3ovo2ccms, 192
BehindSyncMessage	conditions
schedule synchronization for performance	query for r3moncol alert monitors, 102
monitor, 217	r3mondev monitor, 65
synchronize schedule of r3perfagent, 217	r3monpro monitor, 67
	configuration
C	global, 43
COMO	keywords
CCMS	AlerMonSyslog, 27
customizing message flow, 183	AlertDevMon, 27
message flow customization, 183	AlertInstMonPro, 27
Monitoring alerts in the CEN, 194	AlertMonFun, 26
CCMSAcknowledgeMessage for Alert Monitors, 31,	AlertMonPro, 27
57	local, 44
CCMS alert monitor, 51	monitors, 40
environment variables, 57	configuration file
file locations, 58	r3status.cfg, 72
Remote Monitoring, 58	
CCMSMonitorSet for Alert Monitors, 32, 52	
CEN	
Monitoring CCMS alerts centrally, 194 monitoring with r3monal, 64	
CHANGE_OPTION	
SAP R/3 4.6x, 125	
CHECK Alert Type for the r3monrfc monitor, 154	
Classes	
Alerts in r3monal, 61	
Coda	
migrating from MWA, 204	
Command	
r3ovo2ccms, 192	
command-line parameter options r3ovo2ccms, 193	

, ,	Configuring
AgentHostname keyword, 108 Alert Classes, 28 DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck keyword, 81 HistoryPathAIX keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 InstanceProfilePath keyword, 36, 83 Parameter AlertMonitor, 28, 109 Alerttype, 28, 109 Enable/Disable, 29, 109 Filemask, 29 Mode, 29 OPC MsgGroup, 29, 109 OPC Object, 29, 109 OPC Severity, 30, 109 Process Name, 30 ProcessNumber, 30 RFC Parameter, 30, 110 SAP Client, 30, 110 SAP Hostname, 31, 110	Configuring Security-Audit monitor, 94 Define security audits, 96 Enabling CCMS Security Monitoring, 96 Install security monitoring, 95 configuring performance monitor, 209 Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 Trace Level, 216 performance-monitor scheduler, 215 remote alert-collector monitor, 106 remote Alert Monitor, 24 remote monitoring with r3monsec, 79 remote performance monitor, 214 remote r3status monitor, 73 STATRECS_PERF, 233
SAP Number, 31, 110 SAP System, 31, 111 SyslogId, 31 RemoteMonitoring keyword, 37, 73, 108 trace file, 39, 72, 82 trace level, 40, 60, 72, 82	
configuration file for r3moncol HistoryPathAIX keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108	
configuration file for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112	
configuration file for r3perfagent Parameter RFC FUNCTION, 219	
configuration files r3itosap.cfg, 20, 71 r3monal.cfg, 58 r3mondev.cfg, 65 r3monpro.cfg, 67 r3perfagent.cfg, 213 r3status.cfg, 71 r3status.log, 70	

configuring Alert Types	customizing
r3monale, 116	alert collector monitoring conditions, 102
IDOC_CURRENT_STATUS, 117	changing severity level, 183
r3monchg, 124	disabling messages in SAP R/3, 184
CHANGE_OPT (SAP R/3 4.6x), 125	setting thresholds for messages in SAP R/3, 185
r3moncts, 129	
OBJECT_RELEASED, 136	D
OBJECT_USED, 134	1 ,
REQUEST_CREATED, 130	data
REQUEST_RELEASED, 131	gathering for SPI for SAP reports, 360
TASK_CREATED, 133	Database service, 340
TASK_RELEASED, 133	DBINFO_PERF Performance metrics, 221, 222, 361
r3mondmp	
ABAP4_ERROR_EXIST, 138	Delta
r3monjob, 142	condition in process monitor, 68
JOB_ABORTED, 146	Dialog service, 341
JOB_MAX_RUN_TIME, 142	Dialog WP service, 342
JOB_MIN_RUN_TIME, 144	,
START_PASSED, 145	DisableMonitoringWithSeverity
r3monlck, 149	keyword for alert monitors, 32
OLD_LOCKS, 149	DisableMonitoringWithSeverity keyword, 83
r3monoms, 151	Dispatcher-queue monitor
$OM_SWITCH_OVERDUE, 151$	File locations, 81
r3monrfc, 154	Dispatch-queue monitor, 80
CHECK, 154	
r3monsec	DOCSTAT_PERF Performance metrics, 221, 224,
DEFAULT_USERS, 78	361
PRIVILEGED_USERS, 78	DPQueueCheck keyword, 33, 82
SAP_PARAMETERS, 76	, ,
r3monspl, 156	E
PRINT_ERROR_EXISTS, 158	
SPOOL_ENTRIES_RANGE, 156	EM_PERF Performance metrics, 225
SPOOL_ERROR_RANGE, 157	Enable/Disable Parameter, 29, 109
r3montra, 160	EnableDPQueueCheck for Alert Monitors, 35, 72
REPAIR, 162	
RFCONNECT, 163	EnableDPQueueCheck keyword, 81
TPTEST, 164	Enqueue process, 147
TRANS, 160	Enqueue server
r3monupd, 166	monitoring with r3monal, 63, 87
UPDATE_ACTIVE, 167	configuration pre-requisites, 88
UPDATE_ERRORS_EXIST, 167	enabling CCMS alerts, 87
r3monusr, 168	, ,
USER_LOGGEDIN_MAX, 168	Enqueue-server monitor
r3monwpa, 171	Configuring, 88
WP_AVAILABLE, 172	Enterprise Portal
WP_CHECK_CONFIGURED, 177	monitoring with r3monal, 63, 89
WP_IDLE, 174	configuration pre-requisites, 90
WP_STATUS, 178	enabling CCMS alerts, 90
Configuring r3monsec, 75	Enterprise Portal monitor
CORRECTION AND TRANSPORT SYSTEM (CTS)	Configuring, 91
Monitor, 128	
,	Environment service, 340

```
environment variables
   CCMS alert monitor, 57
   for r3moncol alert monitors, 105
   process monitor, 67
   r3monale monitor, 116
   r3monal monitor, 57
   r3monchg monitor, 124
   r3moncts monitor, 129
   r3mondev monitor, 65
   r3mondmp monitor, 138
   r3monjob monitor, 141
   r3monlck monitor, 148
   r3monoms monitor, 151
   r3monpro monitor, 67
   r3monrfc monitor, 153
   r3monspl monitor, 156
   r3montra monitor, 159
   r3monupd monitor, 166
   r3monusr monitor, 168
   r3monwpa monitor, 171
   r3status monitor, 71
   SAPOPC_DRIVE, 57, 65, 67
   SAPOPC_HISTORYPATH, 57, 65, 67, 71
   SAPOPC_R3ITOSAP_CONFIGFILE, 71
   SAPOPC_R3MONAL_CONFIGFILE, 57
   SAPOPC_R3MONDEV_CONFIGFILE, 65
   SAPOPC_R3MONPRO_CONFIGFILE, 67
   SAPOPC_R3STATUS_CONFIGFILE, 71
   SAPOPC_RFC_TIMEOUT, 71
   SAPOPC_SAPDIR, 57, 65, 67
   SAPOPC_TRACEPATH, 57, 65, 67, 71
EP_PERF Performance metrics, 221, 361
Error messages
   configuring r3moncol alert monitors, 112
Exact
   condition in process monitor, 67
F
File
   Configuration
       AlerMonSyslog Keyword, 27
       AlertDevMon Keyword, 27
      AlertInstMonPro Keyword, 27
      AlertMonFun Keyword, 26
```

AlertMonPro Keyword, 27

Agent Hostname for r3perfagent configuration, 217 Alert Collector history, 102 configuration for Alert Monitors, 25, 49 Agent Hostname keyword, 108 Alert Types, 28 CCMSAcknowledgeMessage, 31, 57 CCMSMonitorSet, 32, 52 DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck keyword, 33, 72 EnableDPQueueCheck keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathWimNT keyword, 36, 72 HistoryPathWimNT keyword, 36, 72 HistoryPathUnix keyword, 36, 72 Tormoute Fring Out, 38, 58 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 Trace file, 39, 72, 82 Trace level, 40, 60, 72, 82 Txal syslog mode, 60 configuration for r3moncol HistoryPathWimNT keyword, 108 HistoryPathWimNT keyword, 108 HistoryPathWimNT keyword, 108 Gonfiguration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r5perfagent Agent Monitoring, 218 SyncBack, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 rereffMon with r3perfagent configuration, 218 r3monal.edg, 58 r3monal.edg, 58 r3monal.edg, 58 r3monal.edg, 58 r3monal.edg, 58 r3monal.edg, 116 r3monale.edg, 116 r3monale.edg, 116 r3monale.edg, 116 r3monale.edg, 116 r3monale.edg, 124	file	r3monlck, 148
Alert Collector history, 102 configuration for Alert Monitors, 25, 49 AgentHostname keyword, 108 Alert Types, 28 CCMSAcknowledgeMessage, 31, 57 CCMSMonitorSet, 32, 52 DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck keyword, 81 HistoryPathUnix keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathWinNT keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 Gonfiguration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3moncol Alert Monitors, 108 error messages, 117 race level, 216 history for r3moncol Alert Monitors, 102 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 rerfMon, 218 Remote Monitoring, 218 schedule synchronization for r3perfagent configuration, 218 ristosap cfg, 19, 71 configuring, 20 rismonal cfg, 58 rismonal-cfg, 58 rismonal-cfg, 116 rismonde, fg, 126 rismondev.fg, 129 rismondev.fg,	Agent Hostname for r3perfagent	
configuration for Alert Monitors, 25, 49 AgentHostname keyword, 108 Alert Types, 28 CCMSAcknowledgeMessage, 31, 57 CCMSMonitorSet, 32, 52 DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck, 85, 72 EnableDPQueueCheck keyword, 36, 72 HistoryPathIX keyword, 36, 72 HistoryPathWinX keyword, 36, 72 InstanceProfilePath keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathUnix keyword, 108 HistoryPathUnix keyword, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 218 r3monal.etg, 58 r3monal.etg, 58 r3monal.etg, 58 r3monal.etg, 58 r3monal.etg, 58 r3monal.etg, 58 r3monale.etg, 116 r3monone,etg, 171 race level for r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 218 race file itsel for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3perfagent configuration, 218 race file, 39, 71 race level, 206 ramonal.etg, 166 r3montypa.etg, 171 r3status.etg, 70 Remote Monitoring r3montypa.etg, 172 race level, 206 r3montypa.etg, 173 r3montypa.etg, 174 r3status.etg, 70 Remote Monitoring r3montypa.etg r3montypa.etg r3montypa.etg r3montypa.etg r3montypa.etg r3montypa.etg r	configuration, 217	r3monrfc, 153
AgentHostname keyword, 108 Alert Types, 28 CCMSAcknowledgeMessage, 31, 57 CCMSMonitorSet, 32, 52 DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck keyword, 81 HistoryPathUnix keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathUnix keyword, 36, 72 InstanceProfilePath keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathUnix keyword, 108 HistoryPathUnix keyword, 108 HistoryPathUnix keyword, 108 configuration for r3moncol Alert Monitors, 108 crror messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 Trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 218 r3monal.cfg, 58 r3monal.cfg, 58 r3monal.cfg, 58 r3monal.edg,	Alert Collector history, 102	r3monspl, 156
Alert Types, 28 CCMSAcknowledgeMessage, 31, 57 CCMSMonitorSet, 32, 52 DisableMonitoring WithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck keyword, 81 HistoryPathAlX keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 InstanceProfilePath keyword, 36, 72 InstanceProfilePath keyword, 36, 72 InstanceProfilePath keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathUnix keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace file, 108 trace file, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 configuration for r3moncol Alert Monitors, 108 error messages, 112 configuration, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for 1 sperfagent configuration, 217 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for 1 sperfagent configuration, 217 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for Alert-Monitor configuration, 216	configuration for Alert Monitors, 25, 49	r3montra, 159
CCMSAcknowledgeMessage, 31, 57 CCMSMonitorSet, 32, 52 DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck, 35, 72 HistoryPathUnix keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 HistoryPathWinNT keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RPCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathWinNT keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3monale.fg, 58 r3monale.fg, 58 r3monale.fg, 58 r3monale.fg, 58 r3monale.fg, 116 r3monole.cfg, 116 r3monorts.efg, 129 r3monnde.cfg, 129 r3monnde.cfg, 18 r3monale.efg, 116 r3monorts.efg, 159 r3mondev.exe, 65 r3mondisp.fg, 81 r3mondisp.fg	AgentHostname keyword, 108	r3monupd, 166
CCMSMonitoriest, 32, 52 DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck keyword, 81 HistoryPathAIX keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 HistoryPathWinNT keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace fle, 39, 72, 82 trace level, 40, 60, 72, 82 trace level, 40, 60, 72, 82 trace level, 40, 60, 72, 82 HistoryPathAIX keyword, 108 HistoryPathAIX keyword, 108 HistoryPathMinNT keyword, 108 configuration for 73moncol HistoryPathWinNT keyword, 108 trace file, 108 trace file, 108 cramper of respectively and the strate file, 108 trace file, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 SyncBack, 217 configuration, 218 SyncBack, 217 configuration, 218 r3monale.cfg, 159 r3monale.cfg, 159 r3monale.cfg, 171 r3status.log, 70 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 218 race for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 218 schedule synchronization, 39, 72, 82 trace for Alert-Monitor configuration, 39, 72, 82 trace for Alert-Monitor configuration, 216	Alert Types, 28	r3monusr, 168
DisableMonitoringWithSeverity keyword, 32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck keyword, 81 HistoryPathAlX keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathMinYT keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RPCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3monool HistoryPathWinNT keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 configuration for r3monool Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3monool Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuration, 218 r3itosap.cfg, 19, 71 configuration, 218 r3monal.efg, 58 r3monal.efg, 58 r3monal.efg, 58 r3monal.efg, 58 r3monal.efg, 58 r3monale.cfg, 116 r3monole, cfg, 114	CCMSAcknowledgeMessage, 31, 57	r3monwpa, 171
32, 83 DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck, 25, 72 EnableDPQueueCheck, 26, 72 Enmonteder, 26, 148 Enmonder, 26, 148 Enmonder, 26, 148 Enmonde, 26, 149 Enmonde, 26, 149 Enmonde, 26, 149 Enmonde, 26, 149 Enmonde, 26,	CCMSMonitorSet, 32, 52	r3moncts.cfg, 129
DPQueueCheck keyword, 33, 82 EnableDPQueueCheck, 35, 72 EnableDPQueueCheck keyword, 81 HistoryPathAIX keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 HistoryPathWinNT keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RPCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathWinNT keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace file, 108 trace file, 108 cronfiguration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.e.cg, 51 r3monde.cfg, 116 r3monohg.cfg, 114 r3mondisp.efg, 51 r3mondip.efg, 141 r3mondisp.efg, 51 r3mondip.efg, 141 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondip.efg, 141 r3mondisp.efg, 51 r3mondip.efg, 141 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondisp.efg, 51 r3mondip.efg, 141 r3mondisp.efg, 51 r3mondip.efg, 141 r3mondip.efg, 138 r3mondip.	DisableMonitoringWithSeverity keyword,	r3mondev.cfg, 65
EnableDPQueueCheck, 35, 72 EnableDPQueueCheck keyword, 81 HistoryPathAIX keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 HistoryPathWinNT keyword, 36, 83 RemoteMonitoring keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace lie, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathWinNT keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace file, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyneMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for 73moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3monal.efg, 58 r3monal.efg, 58 r3monal.efg, 58 r3monal.efg, 166 r3monchg.efg, 116 r3monchg.efg, 116 r3monale.log, 116 r3monale.gfg, 114 r3mondisp.efg, 138 r3mondisp.log, 81 r3mondisp.log, 14	32,83	r3mondev.exe, 65
EnableDPQueueCheck keyword, 81 HistoryPathAIX keyword, 36, 72 HistoryPathUnix keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 InstanceProfilePath keyword, 36, 72 InstanceProfilePath keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathWinNT keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace file, 108 error messages, 112 validating contents, 112 configuration for r3mencol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyneMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history or r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cig, 58 r3monal.cig, 58 r3monal.exe, 58 r3monale.cfg, 116 r3monnele.cfg, 124	DPQueueCheck keyword, 33, 82	r3mondev.his, 65
HistoryPathUnix keyword, 36, 72 HistoryPathUnix keyword, 36, 72 InstanceProfilePath keyword, 36, 83 RemoteMonitoring keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathUnix keyword, 108 HistoryPathUnix keyword, 108 trace file, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3moncol Alert Monitors, 108 error messages, 117 Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 Titosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.cg, 58 r3monal.his, 58 r3monal.log, 116 r3monale.og, 116	EnableDPQueueCheck, 35, 72	r3mondisp, 81
HistoryPathUnix keyword, 36, 72 HistoryPathWinNT keyword, 36, 72 InstanceProfilePath keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3merfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3monal.cfg, 58 r3monal.cfg, 58 r3monal.cfg, 58 r3monale.cfg, 116 r3monele,cfg, 124	EnableDPQueueCheck keyword, 81	r3mondisp.cfg, 81
HistoryPathWinNT keyword, 36, 72 InstanceProfilePath keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathUnix keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 Titosap.efg, 19, 71 configuration, 20 r3monal.efg, 58 r3monal.his, 58 r3monal.efg, 116 r3monelg.efg, 116 r3monelg.efg, 116 r3monelg.efg, 124	HistoryPathAIX keyword, 36, 72	r3mondisp.log, 81
InstanceProfilePath keyword, 36, 83 RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history or r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monal.exe, 58 r3monale.log, 116 r3monale, cfg, 124	HistoryPathUnix keyword, 36, 72	r3mondmp.cfg, 138
RemoteMonitoring keyword, 37, 73, 108 RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3monal.exe, 58 r3monal.exe, 58 r3monal.exe, 58 r3monale.ofg, 116 r3monhya.cfg, 150 r3monpro.cfg, 67 r3monpro.chis, 15 r3monsec, 75 r3monpro.chis, 15 r3monse	HistoryPathWinNT keyword, 36, 72	r3monjob.cfg, 141
RFCTimeOut, 38, 58 trace file, 39, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 error messages, 112 validating contents, 112 configuration for r3merfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuration, 218 r3monal.edg, 58 r3monal.edg, 58 r3monal.edg, 58 r3monal.edg, 58 r3monale.log, 116 r3monchg.cfg, 124	InstanceProfilePath keyword, 36, 83	r3monlck.cfg, 148
trace file, 39, 72, 82 trace level, 40, 60, 72, 82 trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monsec, 67 r3monsec, 67 r3monsec.cfg, 75 r3monsec.clg, 75 r3monsec.log, 75 r3monsecpmass r3monsec.log, 75 r3monsec.l	RemoteMonitoring keyword, 37, 73, 108	r3monoms.cfg, 150
trace level, 40, 60, 72, 82 XMI syslog mode, 60 configuration for r3moncol HistoryPathAlX keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 Trace file, 108 trace file, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuration, 218 r3monal.exe, 58 r3monal.exe, 58 r3monale.log, 116 r3monchg.cfg, 124	RFCTimeOut, 38, 58	r3monpro.cfg, 67
XMI syslog mode, 60 configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 Trace file, 108 HistoryPathWinNT keyword, 108 Trace file, 108 Trace level, 108 Trace level, 108 Trace level, 108 Trace file, 108 Trace level, 216 Trace level, 216 Trace level, 216 Trace level, 218 Trace level, 216 Trace level, 218 Trace level, 218 Trace level, 218 Trace level, 216 Trace file listed for each monitor, 41 Trace file listed for each monitor, 41 Trace file listed for each monitor, 41 Trace for Alert-Monitor configuration, 39, 72, 82 Trace level for r3perfagent Trace level for r3p	trace file, 39, 72, 82	r3monpro.exe, 67
configuration for r3moncol HistoryPathAIX keyword, 108 HistoryPathWinNT keyword, 108 HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuration, 218 r3monal.cfg, 58 r3monal.exe, 58 r3monale.log, 116 r3monchg.cfg, 124	trace level, $40, 60, 72, 82$	r3monpro.his, 67
HistoryPathAIX keyword, 108 HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 Trace file, 108 Trace file, 108 Trace file, 108 Trace level, 108 Trace level, 108 Trace level, 108 Trace level, 108 Trace file, 108 Trace file, 108 Trace level, 112 Trace level, 116 Trace level, 216 Trace for ramoncol configuration, 217 Trace file listed for each monitor, 41 Trace for Alert-Monitor configuration, 39, 72, 82 Trace for ramoncol configuration, 108 Trace level for raperfagent Trace for Alert-Monitor configuration, 108 Trace level for raperfagent Trace for Alert-Monitor configuration, 216 Trace for Palent-Monitor configuration, 216 Trace for Palent-Monitor configuration, 216 Trace for Tramoncol configuration, 217 Trace for Tramoncol configuration, 218	XMI syslog mode, 60	r3monrfc.cfg, 153
HistoryPathUnix keyword, 108 HistoryPathWinNT keyword, 108 Trace file, 108 Tramonspl.cfg, 156 Tramonspl.cfg, 159 Tramonupd.cfg, 166 Tramonupd.cfg, 166 Tramonupd.cfg, 166 Tramonupd.cfg, 166 Tramonupd.cfg, 171 Trace file, 108 Trace file file for each monitor, 41 Trace for ramonal cfg, 58 Tramonal cfg, 58 Tramonal cfg, 116 Trace file, 108 Trace file file fire file fire file file framonchg.cfg, 116 Trace file, 108 Tramonsec.log, 75 Tramonsec.log, 76 Tramonsec.log, 75 Tramonsec.log, 76 Tramonsec.log, 75 Tramonsec.log, 76 Tramonsec.log, 76 Tramonsec.log, 76 Tramonsec.log, 75 Tramonsec.log, 76 Tramonsec.log, 76 Tramonspl.cfg, 156 Tramonspl.cfg, 156 Tramonupd.cfg, 166 Tramonupd.cfg, 171 Trastatus.(exe), 70 Trasta	configuration for r3moncol	r3monsec, 75
HistoryPathWinNT keyword, 108 trace file, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuration, 218 r3monal.ekg, 58 r3monal.his, 58 r3monale.log, 116 r3monchg.cfg, 124	HistoryPathAIX keyword, 108	- -
trace file, 108 trace level, 108 trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.exe, 58 r3monal.exe, 58 r3monale.cfg, 116 r3monale.log, 116 r3monchg.cfg, 124	· · · · · · · · · · · · · · · · · · ·	- -
trace level, 108 configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3monal.cfg, 19, 71 configuring, 20 r3monta.cfg, 159 r3monupd.cfg, 166 r3monupd.cfg, 166 r3monupd.cfg, 166 r3monupd.cfg, 166 r3monupd.cfg, 167 r3monupd.cfg, 171 r3status.exe), 70 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 r3itosap.cfg, 19, 71 configuring, 20 r3monal.exe, 58 r3monal.his, 58 r3monale.log, 116 r3monale.log, 116 r3monchg.cfg, 124	· · · · · · · · · · · · · · · · · · ·	
configuration for r3moncol Alert Monitors, 108 error messages, 112 validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.exe, 58 r3monal.exe, 58 r3monale.log, 116 r3monale.log, 116 r3monale.log, 116 r3monale.log, 116 r3monale.gf, 51 expected for r3monol r3monol Alert Monitors, 108 r3monale.cfg, 124 r3status.log, 70 r3status.log, 70 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3monol configuration, 108 trace level for r3perfagent configuration, 216		
error messages, 112 validating contents, 112 r3status(.exe), 70 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monale.ofg, 116 r3monale.ofg, 116 r3monale.ofg, 124 r3status.leg, 70 r3status.leg, 71 r3status.leg, 70 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216		
validating contents, 112 configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3status.log, 70 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 Trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monal.exe, 58 r3monale.log, 116 r3monchg.cfg, 124		
configuration for r3perfagent Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monale.log, 116 r3monchg.cfg, 124 r3status.log, 71 r3status.log, 70 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216	- · · · · · · · · · · · · · · · · · · ·	
Agent Hostname, 217 BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3status.log, 70 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 TemSe, 179 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monal.his, 58 r3monale.log, 116 r3monchg.cfg, 124	<u> </u>	
BehindSyncMessage, 217 PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 217 TemSe, 179 PerfMon with r3perfagent configuration, 218 trace file listed for each monitor, 41 configuration, 218 trace for Alert-Monitor configuration, 39, 72, 82 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monal.his, 58 r3monale.log, 116 r3monchg.cfg, 124		e
PerfMon, 218 Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 217 TemSe, 179 PerfMon with r3perfagent configuration, 218 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monal.his, 58 r3monale.log, 116 r3monchg.cfg, 124 Remote Monitoring with r3perfagent configuration, 218 schedule synchronization for r3perfagent trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216		
Remote Monitoring, 218 SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3monal.cfg, 58 r3monal.exe, 58 r3monale.log, 116 r3monchg.cfg, 124 configuration, 218 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216		-
SyncBack, 217 trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monale.cfg, 116 r3monchg.cfg, 116 r3monchg.cfg, 124 schedule synchronization for r3perfagent configuration, 217 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216		
trace level, 216 history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monale.cfg, 116 r3monchg.cfg, 124 configuration, 216 configuration, 217 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216		· · · · · · · · · · · · · · · · · · ·
history for r3moncol Alert Monitors, 102 PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monale.cfg, 116 r3monchg.cfg, 124 TemSe, 179 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216		· · · · · · · · · · · · · · · · · · ·
PerfMon with r3perfagent configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monale.cfg, 116 r3monchg.cfg, 124 trace file listed for each monitor, 41 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncl configuration, 108 trace level for r3perfagent configuration, 216 ramonchg.cfg, 116 r3monchg.cfg, 124		- · · · · · · · · · · · · · · · · · · ·
configuration, 218 r3itosap.cfg, 19, 71 configuring, 20 r3monal.cfg, 58 r3monal.exe, 58 r3monale.cfg, 116 r3monale.log, 116 r3monchg.cfg, 124 trace for Alert-Monitor configuration, 39, 72, 82 trace for r3moncol configuration, 108 trace level for r3perfagent configuration, 216 trace for Alert-Monitor configuration, 39, 72, 82 trace for Alert-Monitor configuration, 208 trace for Alert-Monitor configuration, 39, 72, 82 trace for Alert-Monitor configuration, 208 trace for r3moncol configuration, 208 trace level for r3perfagent configuration, 216	· · · · · · · · · · · · · · · · · · ·	·
r3itosap.cfg, 19, 71		· · · · · · · · · · · · · · · · · · ·
configuring, 20 trace level for r3perfagent r3monal.cfg, 58 configuration, 216 r3monal.exe, 58 r3monal.his, 58 r3monale.cfg, 116 r3monale.log, 116 r3monchg.cfg, 124	-	
r3monal.cfg, 58 r3monal.exe, 58 r3monal.his, 58 r3monale.cfg, 116 r3monale.log, 116 r3monchg.cfg, 124		g ,
r3monal.exe, 58 r3monal.his, 58 r3monale.cfg, 116 r3monale.log, 116 r3monchg.cfg, 124		
r3monal.his, 58 r3monale.cfg, 116 r3monale.log, 116 r3monchg.cfg, 124		configuration, 210
r3monale.cfg, 116 r3monale.log, 116 r3monchg.cfg, 124		
r3monale.log, 116 r3monchg.cfg, 124		
r3monchg.cfg, 124	e,	
9 9		
r3moncol(.exe). 116	r3moncol(.exe), 116	
r3monchg, 124		
r3moncts, 129	- -	
r3mondmp, 138		
r3monjob, 141	= :	

file locations	HPOM
r3monal, 58	message customization, 181
r3monale monitor, 116	
r3monchg monitor, 124	
r3moncts monitor, 129 r3mondev, 65	ICMSTAT_PERF Performance metrics, 222, 227
r3mondisp, 81	installing
r3mondmp monitor, 138	SAP R/3 Performance Agent, 206
r3monjob monitor, 141	SPI for SAP service reports, 350
r3monlck monitor, 148	Installing the SPI for SAP Reports, 350
r3monoms monitor, 150	InstanceProfilePath keyword, 36, 83
r3monpro, 67 r3monrfc monitor, 153	Integration
r3monsec, 75	SPI for SAP and SAP Solution Manager, 187
r3monspl monitor, 156	pre-requisites, 187
r3montra monitor, 159	
r3monupd monitor, 166	Interface service, 340
r3monusr monitor, 168	Interval
r3monwpa monitor, 171	run for alert monitors, 49
r3status, 70	run for r3moncol Alert-Collector Monitors, 101
Filemask Parameter, 29	J
file monitor, 64	J2EE (Web AS Java) monitor, 84
frequency	Configuration pre-requisites, 85
r3status monitor run interval, 70	Configuring, 86
	Enabling CCMS Alerts, 84
G	GRMG monitoring, 85
Gateway service, 342	J2EE kernel, 85, 88, 90
gathering data for SPI for SAP reports, 360	J2EE services, 85, 88, 90
	J2EE system, 85
generating SPI for SAP service reports, 360	SAPCCMSR availability, 85
- · · · · · · · · · · · · · · · · · · ·	J2EE engine
generating SPI for SAP reports, 352	monitoring with r3monal, 63
global configuration, 23, 43	J2EE kernel
Golden Metrics, 365	monitoring in Web AS Java, 85, 88, 90
GRMG Monitoring	J2EE services
monitoring in J2EE (Web AS Java), 85	monitoring in Web AS Java, 85, 88, 90
	J2EE system
H	monitoring in Web AS Java, 85
history file, 42	JOB_ABORTED, 146
path, 42	JOB_MAX_RUN_TIME, 142
r3monal.his, 58	JOB_MIN_RUN_TIME, 144
r3moncol, 102	condition in job monitor, 139, 149
r3mondev.his, 65	JOBREP_PERF Performance metrics, 222, 228, 362
r3monpro.his, 67	
r3status.his, 71	JOBREPORT Monitor, 139
history file for r3moncol Alert Monitors, 102	K
HistoryPathAIX keyword, 36, 72, 108	
HistoryPathUnix keyword, 36, 72, 108	kernel J2EE
HistoryPathWinNT keyword, 36, 72, 108	monitoring in Web AS Java, 85, 88, 90

Keyword	message customization, 181
Monitor Configuration CCMSAcknowledgeMessage, 31, 57 CCMSMonitorSet, 32, 52 EnableDPQueueCheck, 35, 72 PerfMon for r3perfagent configuration, 218 RFCTimeOut, 38, 58 SAP Hostname, 110 TraceLevel, 60 XMI syslog mode, 60	messages changing severity level, 183 customizing message browser contents, 182 disabling in SAP R/3, 184 errors configuring r3moncol alert monitors, 112 setting thresholds in SAP R/3, 185 Message service, 342 Metrics
Keyword AlerMonSyslog, 27	performance
Keyword AlertDevMon, 27	DBINFO_PERF, 221, 222, 361 DOCSTAT_PERF, 221, 224, 361
Keyword AlertInstMonPro, 27	EM_PERF, 225
Keyword AlertMonFun, 26	EP_PERF, 221, 361
Keyword AlertMonPro, 27	ICMSTAT_PERF, 222, 227 JOBREF_PERF, 222, 228, 362 SAP_ICMSTAT_PERF, 362
L level trace for Alert-Monitor configuration, 40, 60, 72,	SAP_STATRECS_PERF, 362 SAP_SYSUP_PERF, 362 SAP_USER_PERF, 362
82 trace for r3moncol configuration, 108	SAP_WLSUM_PERF, 362 SAPBUFFER_PERF, 222, 229, 362
line of business service, 342	SAPMEMORY_PERF, 222, 231, 362 SPOOL_PERF, 231
local configuration, 23	STATRECS_PERF, 222, 232
Locations File r3mondisp, 81 r3monsec, 75	SYSUP_PERF, 222, 235 UPDATE_PERF, 222, 236, 362 USER_PERF, 222, 237 WLSUM_PERF, 222, 238 WP_PERF, 222, 240, 362
locations r3monal monitor configuration files, 58 r3mondev monitor configuration files, 65 r3monpro monitor configuration files, 67 r3status monitor configuration files, 70 LOCK CHECK Monitor, 147 Logs SAP Security-Audit monitoring with r3monal, 63	metrics SAP R/3 service reports, 361 SPI for SAP service reports, 361 migration performance data, 202 Coda, 204 MWA, 202 perflbd file, 203, 204 SPI for SAP service reports, 349
M	Min condition in process monitor, 67
Manager Solution Integration pre-requisites, 187 Integration with SPI for SAP, 187	Mode Parameter, 29
MAX USER_LOGGEDIN_MAX, 169	
Max condition in process monitor, 68	
Memory Management service, 341	
message browser, 103 customizing messages, 182	

Monitor

performance metrics DBINFO_PERF, 221, 222, 361 DOCSTAT_PERF, 221, 224, 361 EM_PERF, 225 EP_PERF, 221, 361 $ICMSTAT_PERF, 222, 227$ JOBREP_PERF, 222, 228, 362 SAP_ICMSTAT_PERF, 362 SAP_STATRECS_PERF, 362 SAP_SYSUP_PERF, 362 SAP_USER_PERF, 362 SAP_WLSUM_PERF, 362 SAPBUFFER_PERF, 222, 229, 362 SAPMEMORY_PERF, 222, 231, 362 SPOOL_PERF, 231 STATRECS_PERF, 222, 232 SYSUP_PERF, 222, 235 UPDATE_PERF, 222, 236, 362 USER_PERF, 222, 237 WLSUM_PERF, 222, 238 WP_PERF, 222, 240, 362

monitor	RFC Parameter, 30, 110
AgentHostname keyword, 108	SAP Client, 30, 110
Alert Classes, 28	SAP Hostname, 31, 110
alert-configuration file, 49	SAP Number, 31, 110
CCMSAcknowledgeMessage, 31, 57	SAP System, 31, 111
CCMSMonitorSet, 32, 52	SyslogId, 31
EnableDPQueueCheck, 35, 72	polling rates for alert monitors, 49
RFCTimeOut, 38, 58	polling rates for r3moncol alerts, 101
XMI syslog mode, 60	process, 66
CCMS alert, 51	query conditions for r3moncol alert monitors,
environment variables, 57	102
file locations, 58	r3monal, 51
Remote Monitoring, 58	r3monale, 115
command-line parameters for r3moncol alert	alert types, 115
monitors, 106	command-line parameters, 116
configuration file, 25	configuring alert types, 116
AgentHostname keyword, 108	environment variables, 116
Alert Classes, 28	file locations, 116
DisableMonitoringWithSeverity keyword,	IDOC_CURRENT_STATUS alert type, 117
32, 83	remote monitoring with, 116
DPQueueCheck keyword, 33, 82	type of, 115
EnableDPQueueCheck keyword, 81	r3monchg, 123
HistoryPathAIX keyword, 36, 72, 108	alert types, 123
HistoryPathUnix keyword, 36, 72, 100	CHANGE_OPT (SAP R/3 4.6x) alert type,
HistoryPathWinNT keyword, 36, 72, 108	125
InstanceProfilePath keyword, 36, 83	command-line parameters, 124
RemoteMonitoring keyword, 37, 73, 108	configuring alert types, 124
trace file, 39, 72, 82, 108	environment variables, 124
trace level, 40, 60, 72, 82, 108	file locations, 124
configuration file for r3moncol alerts, 108	parameter values, 124
error messages, 112	remote monitoring with, 124
- · · · · · · · · · · · · · · · · · · ·	
validating contents, 112	r3moncol
configuring, 40	parameter values, 104
DisableMonitoringWithSeverity keyword, 32, 83	r3moncts, 128
DPQueueCheck keyword, 33, 82	alert types, 128
EnableDPQueueCheck keyword, 81	command-line parameters, 129
environment variables for r3moncol alert	configuring alert types, 129
monitors, 105	environment variables, 129
file, 64	file locations, 129
history file for r3moncol alerts, 102	OBJECT_RELEASED alert type, 136
HistoryPathAIX keyword, 36, 72, 108	OBJECT_USED alert type, 134
HistoryPathUnix keyword, 36, 72, 108	remote monitoring with, 129
HistoryPathWinNT keyword, 36, 72, 108	REQUEST_CREATEDalert type, 130
InstanceProfilePath keyword, 36, 83	REQUEST_RELEASED alert type, 131
Parameter	TASK_CREATED alert type, 133
AlertMonitor, 28, 109	TASK_RELEASED alert type, 133
Alerttype, 28, 109	r3mondev, 64
Enable/Disable, 29, 109	r3mondmp, 137
Filemask, 29	ABAP4_ERROR_EXIST alert type, 138
Mode, 29	alert types, 138
OPC MsgGroup, 29, 109	command-line parameters, 138
OPC Object, 29, 109	environment variables, 138
OPC Severity, 30, 109	file locations, 138
Process Name, 30	remote monitoring with, 138
ProcessNumber, 30	r3monjob, 139

-1	
alert types, 140	environment variables, 159
command-line parameters, 141	file locations, 159
configuring alert types, 142	remote monitoring with, 160
environment variables, 141	REPAIR alert type, 162
file locations, 141	RFCONNECT alert type, 163
JOB_ABORTED alert type, 146	TPTEST alert type, 164
JOB_MAX_RUN_TIME alert type, 142	TRANS alert type, 160
JOB_MIN_RUN_TIME alert type, 144	r3monupd, 165
parameter values, 142	alert types, 166
remote monitoring with, 141	command-line parameters, 166
START_PASSED alert type, 145	configuring alert types, 166
r3monlck, 147	environment variables, 166
alert types, 148	file locations, 166
command-line parameters, 149	remote monitoring with, 166
configuring alert types, 149	UPDATE_ACTIVE, 167
environment variables, 148	UPDATE_ERRORS_EXIST, 167
file locations, 148	r3monusr, 167
OLD_LOCKS alert type, 149	alert types, 167
remote monitoring with, 149	command-line parameters, 168
r3monoms, 149	configuring alert types, 168
alert types, 150	configuring USER_LOGGEDIN_MAX, 168
command-line parameters, 151	environment variables, 168
configuring alert types, 151	file locations, 168
environment variables, 151	remote monitoring with, 168
file locations, 150	r3monwpa, 169
OM_SWITCH_OVERDUE alert type, 151	alert types, 170
remote monitoring with, 151	command-line parameters, 171
r3monpro, 66	configuring alert types, 171
r3monrfc, 152	environment variables, 171
alert types, 153	file locations, 171
CHECK alert type, 154	parameter values, 171
command-line parameters, 153	remote monitoring with, 171
configuring alert types, 154	RemoteMonitoring keyword, 37, 73, 108
environment variables, 153	report types for r3moncol alerts, 101
file locations, 153	run interval for r3moncol alerts, 101
parameter values, 154	run intervals for alert monitors, 49
remote monitoring with, 153	spooler data, 131
r3monsec	trace file, 39, 72, 82, 108
DEFAULT_USERS alert type, 78	trace level, 40, 60, 72, 82, 108
PRIVILEGED_USERS alert type, 78	
SAP_PARAMETERS alert type, 76	monitor Enqueue-server
r3monspl, 131, 155	Configuring, 88
alert types, 155	monitor Enterprise Portal
command-line parameters, 156	Configuring, 91
configuring alert types, 156	Monitoring
environment variables, 156	r3monal monitor Remotely, 58
	ramonal monitor itemotery, 56
file locations, 156	
PRINT_ERROR_EXISTS alert type, 158	
remote monitoring with, 156	
SPOOL_ENTRIES_RANGE alert type, 156	
SPOOL_ERROR_RANGE alert type, 157	
r3montra	
alert types, 159	
command-line parameters, 159	
configuring alert types, 160	

monitoring	Monitor type
remotely with r3moncol alert monitors, 106	r3monaco, 179
remotely with the Alert Monitors, 24	r3monchg, 123
remotely with the performance monitor, 214	r3moncts, 128
remotely with the r3monale monitor, 116, 117	r3mondmp, 138
remotely with the r3monchg monitor, 124	r3monjob, 140
remotely with the r3moncts monitor, 129	r3monlck, 148
remotely with the r3mondmp monitor, 138	r3monoms, 150
remotely with the r3monjob monitor, 141	r3monrfc, 153
remotely with the r3monlck monitor, 149	r3monspl, 155
remotely with the r3monoms monitor, 151	r3monupd, 166
remotely with the r3monrfc monitor, 153	r3monusr, 167
remotely with the r3monsec monitor, 76, 79	r3monwpa, 170
remotely with the r3monspl monitor, 156	• /
remotely with the r3montra monitor, 160	N
remotely with the r3monupd monitor, 166	
remotely with the r3monusr monitor, 168	Network service, 341
remotely with the r3monwpa monitor, 171	
remotely with the r3status monitor, 73	0
the performance-monitor scheduler, 215	OBJECT_RELEASED, 136
Monitoring CCMS alerts in the CEN, 194	OBJECT_USED, 134
monitoring conditions	OLD_LOCKS, 149
process monitor, 67	OM_SWITCH_OVERDUE, 151
r3mondev monitor, 65	APSERVER, 152
r3monpro monitor, 67	OVERDUE_TIME, 152
monitoring TEMSE file consistency, 179	OPC MsgGroup Parameter, 29, 109
monitor J2EE (Web AS Java), 84	, , ,
Configuration pre-requisites, 85	OPC Object Parameter, 29, 109
Configuring, 86	OPC Severity Parameter, 30, 109
Enabling CCMS Alerts, 84 GRMG Monitoring, 85	Operating System Service, 341
J2EE kernel, 85, 88, 90	OPERATION MODE Monitor, 149
J2EE services, 85, 88, 90	options
J2EE system, 85	command-line parameter
SAPCCMSR Availability, 85	r3ovo2ccms, 193
•	·
monitor SAP security audits, 93	Oracle
SAP security alerts, 94	Password
Monitor Type	r3monsecpw.msg, 75
Snapshot, 101	or parameter value, 105
MonitorType	other configuration and customization methods, 181
TimeFrame, 101	OVERDUE_TIME
	OM_SWITCH_OVERDUE, 152
	<u>-</u>

	command-line
Parameter AlertMonitor, 28, 109 Alerttype, 28, 109 AND or OR Comparison, 105 Blocks, 105 Delimiter, 103, 104 Enable/Disable, 29, 109 Filemask, 29 Line Breaks, 105 Monitor Configuration AlertMonitor, 28, 109 Alerttype, 28, 109 Enable/Disable, 29, 109 Filemask, 29 Mode, 29 OPC MsgGroup, 29, 109 OPC Object, 29, 109 OPC Severity, 30, 109 Process Name, 30 Process Name, 30 RFC Parameter, 30, 110 SAP Client, 30, 110 SAP Number, 31, 110 SAP System, 31, 111 SyslogId, 31 Name, 103 OPC MsgGroup, 29, 109 OPC Severity, 30, 109 Performance Monitor Configuration RFC FUNCTION, 219 Process Name, 30 Process Number, 30 RFC FUNCTION with r3perfagent, 219 RFC Parameter, 30, 110 SAP Client, 30, 110 SAP Client, 30, 110 SAP Hostname, 31 SAP Number, 31, 110 SAP Hostname, 31, 110 SAP Number, 31, 110 SAP Number, 31, 110 SAP System, 31, 111 SyslogId, 31	r3ovo2ccms, 192 with the r3monchg monitor, 124 command-line for r3monale monitor, 116 command-line for r3moncol alert monitors, 106 command-line parameter with the r3moncts monitor, 129 with the r3mondmp monitor, 138 with the r3monlok monitor, 141 with the r3monlok monitor, 149 with the r3monlok monitor, 151 with the r3monoms monitor, 153 with the r3monspl monitor, 156 with the r3monupd monitor, 156 with the r3monupd monitor, 166 with the r3monupd monitor, 168 with the r3monupa monitor, 168 r3monchg monitor, 124 r3moncol monitor, 104 r3monjob monitor, 104 r3monjob monitor, 154 r3monwpa monitor, 171 Password r3monsecpw.msg, 75 path history file, 42 perflbd file, 203, 204 PerfMon Keyword for r3perfagent configuration, 218 Performance Agent r3perfagent.cfg, 213 performance data migrating MWA, 202 migrating perflbd file, 203, 204 migration, 202

Parameter for monitor configuration Mode, 29

Performance metrics	performance monitor
DBINFO_PERF, 221, 222, 361	commands, 219
DOCSTAT_PERF, 221, 224, 361	configuring, 209
EM_PERF, 225	Agent Hostname, 217
EP_PERF, 221, 361	BehindSyncMessage, 217
ICMSTAT_PERF, 222, 227	PerfMon, 218
JOBREP_PERF, 222, 228, 362	Remote Monitoring, 218
SAP_ICMSTAT_PERF, 362	SyncBack, 217
SAP_STATRECS_PERF, 362	Trace Level, 216
SAP_SYSUP_PERF, 362	configuring remote monitor, 214
SAP_USER_PERF, 362	description, 221
SAP_WLSUM_PERF, 362	overview, 201
SAPBUFFER_PERF, 222, 229, 362	Parameter
SAPMEMORY_PERF, 222, 231, 362	RFC FUNCTION, 219
SAP R/3 service reports, 361	scheduler, 215
SPI for SAP service reports, 361	subagent files
SPOOL_PERF, 231	AIX, 207
STATRECS_PERF, 222, 232	HP-UX, 208
SYSUP_PERF, 222, 235	Windows, 208
UPDATE_PERF, 222, 236, 362	
USER_PERF, 222, 237	polling frequency r3status, 70
WLSUM_PERF, 222, 238	•
WP_PERF, 222, 240, 362	Polling Rates
Performance monitor	for alert-collector monitors, 101
DBINFO_PERF, 221, 222, 361	for alert monitors, 49
	polling rates for Alert Monitors, 49
DOCSTAT_PERF, 221, 224, 361	
EM_PERF, 225	polling rates for r3moncol alert-collector monitors, 101
EP_PERF, 221, 361	
ICMSTAT_PERF, 222, 227	Precedence
JOBREF_PERF, 222, 362 JOBREP_PERF, 228	Order of, 23
SAP_ICMSTAT_PERF, 362	PRINT_ERROR_EXISTS, 158
SAP_STATRECS_PERF, 362	process, 21
SAP_SYSUP_PERF, 362	-
SAP_USER_PERF, 362	process monitor, 66
SAP_WLSUM_PERF, 362	environment variables, 67
SAPBUFFER_PERF, 222, 229, 362	monitoring conditions, 67
SAPMEMORY_PERF, 222, 231, 362	Process Name Parameter, 30
SPOOL_PERF, 231	Process Number Parameter, 30
STATRECS_PERF, 222, 232	Profile
SYSUP_PERF, 222, 235	Security Audit
UPDATE_PERF, 222, 236, 362	Define, 96
USER_PERF, 222, 237	Define, 50
WLSUM_PERF, 222, 238	
WP_PERF, 222, 240, 362	Q
	Query Conditions, 102
	for r3moncol alert monitors, 102
	R
	r3itosap.cfg, 19, 71
	configuring, 20
	r3modev
	SAPOPC_HISTORYPATH, 65

r3monaco monitor	r3monale.log, 116		
type, 179	r3monale Monitor, 115		
r3monal alert classes, 61 file locations, 58 migrating from r3monxmi, 61	alert types, 115 command-line parameters, 116 environment variables, 116 file locations, 116		
monitor, 51 monitoring J2EE engine, 63 monitoring SAP Security-Audit Logs, 63	remote monitoring with, 116 type, 115		
monitoring the CEN, 64 monitoring the enqueue server, 63, 87 configuration pre-requisites, 88 enabling CCMS alerts, 87 monitoring the Enterprise Portal, 63, 89 configuration pre-requisites, 90 enabling CCMS alerts, 90 monitoring the J2EE engine, 63 Remote Monitoring, 58	r3monchg, 123 alert types CHANGE_OPT SAP R/3 4.6x, 125 configuring, 124 command-line parameters, 124 monitor alert types, 123 monitor environment variables, 124 monitor file locations, 124 parameter values, 124 remote monitoring with, 124		
run frequency of, 49	_ · · · · · · · · · · · · · · · · · · ·		
SAPOPC_DRIVE, 57 SAPOPC_HISTORYPATH, 57 SAPOPC_REMOVAL_CONFIGENEE, 57	r3monchg.cfg, 124 r3monchg Monitor		
SAPOPC_R3MONAL_CONFIGFILE, 57 SAPOPC_SAPDIR, 57 SAPOPC_TRACEPATH, 57 the Enqueue-server monitor Configuring, 88 the Enterprise-Portal monitor Configuring, 91	alert types, 123 command-line parameters, 124 environment variables, 124 file locations, 124 parameter values, 124 remote monitoring with, 124 r3monchg monitor		
the J2EE (Web AS Java) monitor, 84 Configuration pre-requisites, 85 Configuring, 86 Enabling CCMS Alerts, 84 GRMG Monitoring, 85 J2EE kernel, 85, 88, 90 J2EE services, 85, 88, 90 J2EE system, 85 SAPCCMSR Availability, 85 the security-audit monitor, 93 SAP security-alerts, 94	type, 123 r3moncol, 101 command-line parameters for, 106 configuration file for, 108 error messages, 112 validating contents, 112 environment variables for, 105 history file for, 102 parameter values, 104 query conditions for, 102 remote monitoring with, 106		
r3monal.cfg, 58 r3monal.exe, 58	ReportTypes for, 101 run frequency of, 101		
r3monal.his, 58	run interval for, 101		
	run locations for, 49		
r3monale, 115 alert types configuring, 116	r3moncol(.exe), 116, 124, 129, 138, 141, 148, 150, 153, 156, 159, 166, 168, 171		
IDOC_CURRENT_STATUS, 117 monitor alert types, 115 monitor command-line parameters, 116 monitor environment variables, 116 monitor file locations, 116 monitor type, 115 remote monitoring with, 116 r3monale.cfg, 116	r3moncol.cfg, 106		

r3moncts, 128	r3mondmp Monitor
alert types configuring, 129 OBJECT_RELEASED, 136 OBJECT_USED, 134	alert types, 138 command-line parameters, 138 environment variables, 138
REQUEST_CREATED, 130	file locations, 138
REQUEST_RELEASED, 131	remote monitoring with, 138
TASK_CREATED, 133	r3mondmp monitor type, 138
TASK_RELEASED, 133	r3monjob, 139
command-line parameters, 129	alert types
monitor alert types, 128	configuring, 142
monitor environment variables, 129 monitor file locations, 129	command-line parameters, 141
remote monitoring with, 129	monitor alert types, 140
r3moncts.cfg, 129	monitor environment variables, 141 monitor file locations, 141
r3moncts Monitor	parameter values, 142
alert types, 128	remote monitoring with, 141
command-line parameters, 129 environment variables, 129	type, 140
file locations, 129	r3monjob.cfg, 141
remote monitoring with, 129	r3monjob Monitor
type, 128	alert types, 140
r3mondev	command-line parameters, 141 environment variables, 141
default settings, 65	file locations, 141
environment variables, 65	parameter values, 142
file locations, 65	remote monitoring with, 141
monitor, 64 monitoring conditions, 65	r3monlck, 147
run frequency of, 49	alert types
SAPOPC_DRIVE, 65	configuring, 149
SAPOPC_R3MONDEV_CONFIGFILE, 65	command-line parameters, 149 monitor alert types, 148
SAPOPC_SAPDIR, 65	monitor environment variables, 148
SAPOPC_TRACEPATH, 65	monitor file locations, 148
r3mondev.cfg, 65	remote monitoring with, 149
r3mondev.exe, 65	r3monlck.cfg, 148
r3mondev.his, 65	r3monlck Monitor
r3mondisp	alert types, 148
R/3 queue monitor	command-line parameters, 149
File Locations, 81	environment variables, 148
run frequency of, 49 the dispatch-queue monitor, 80	file locations, 148
	remote monitoring with, 149
r3mondisp(.exe), 81	r3monlck monitor type, 148
r3mondisp.cfg, 81	r3monoms, 149
r3mondisp.log, 81	alert types
r3mondmp, 137	configuring, 151
command-line parameters, 138	command-line parameters, 151
monitor alert types, 138 monitor environment variables, 138	monitor alert types, 150
monitor file locations, 138	monitor environment variables, 151
remote monitoring with, 138	monitor file locations, 150 remote monitoring with, 151
r3mondmp.cfg, 138	r3monoms.cfg, 150
· •	15HI0H0HS.CIQ, 15U

r3monoms Monitor	r3monsec(.exe), 75
alert types, 150	r3monsec.cfg, 75
command-line parameters, 151 environment variables, 151	r3monsec.log, 75
file locations, 150	r3monsec monitor
remote monitoring with, 151	configuring remote monitoring with, 79
report type, 150	r3monsecpw.msg, 75
r3monoms monitor	- -
type, 150	r3monspl, 131, 155 alert types
r3monpro environment variables, 67 file locations, 67 monitor, 66 monitoring conditions, 67 SAPOPC_DRIVE, 67 SAPOPC_HISTORYPATH, 67 SAPOPC_R3MOPRO_CONFIGFILE, 67 SAPOPC_SAPDIR, 67 SAPOPC_TRACEPATH, 67	configuring, 156 PRINT_ERROR_EXIST, 158 SPOOL_ENTRIES_RANGE, 156 SPOOL_ERROR_RANGE, 157 command-line parameters, 156 monitor, 131 monitor alert types, 155 monitor environment variables, 156 monitor file locations, 156 remote monitoring with, 156
r3monpro.cfg, 67	r3monspl.cfg, 156
r3monpro.exe, 67 r3monpro.his, 67 r3monrfc, 152 alert types CHECK, 154 configuring, 154 command-line parameters, 153 monitor alert types, 153 monitor environment variables, 153 monitor file locations, 153 parameter values, 154	r3monspl Monitor alert types, 155 command-line parameters, 156 environment variables, 156 file locations, 156 remote monitoring with, 156 r3monspl monitor type, 155 r3montra alert types configuring, 160
remote monitoring with, 153	REPAIR, 162 RFCONNECT, 163
r3monrfc.cfg, 153 r3monrfc Monitor alert types, 153 command-line parameters, 153 environment variables, 153 file locations, 153 parameter values, 154 remote monitoring with, 153	TPTEST, 164 TRANS, 160 command-line parameters, 159 monitor alert types, 159 monitor environment variables, 159 monitor file locations, 159 remote monitoring with, 160 r3montra.cfg, 159
r3monrfc monitor	r3montra.cig, 139 r3montra Monitor
type, 153 r3monsec alert types DEFAULT_USERS, 78 PRIVILEGED_USERS, 78 SAP_PARAMETERS, 76 R/3 Security monitor, 75 Alert types, 75 Configuring, 75 File Locations, 75 run frequency of, 49	alert types, 159 command-line parameters, 159 environment variables, 159 file locations, 159 remote monitoring with, 160

r3monupd, 165 alert types configuring, 166 UPDATE_ACTIVE, 167 UPDATE_ERRORS_EXIST, 167 command-line parameters, 166 monitor alert types, 166 monitor environment variables, 166	r3monwpa Monitor alert types, 170 command-line parameters, 171 environment variables, 171 file locations, 171 parameter values, 171 remote monitoring with, 171
monitor file locations, 166 remote monitoring with, 166 r3monupd.cfg, 166	r3monwpa monitor type, 170 r3monxmi migrating to r3monal, 61
r3monupd Monitor alert types, 166 command-line parameters, 166 environment variables, 166 file locations, 166 remote monitoring with, 166 r3monupd monitor	r3mopro run frequency of, 49 r3ovo2ccms, 192 command-line parameter options, 193 command-line parameters, 192 r3perfagent.cfg, 213
type, 166 r3monusr, 167 alert types configuring, 168 USER_LOGGEDIN_MAX, 168 command-line parameters, 168 monitor alert types, 167 monitor environment variables, 168 monitor file locations, 168 remote monitoring with, 168	r3status R/3 Status monitor, 70 reporting SAP status, 73 run frequency of, 49 SAPOPC_HISTORYPATH, 71 SAPOPC_R3ITOSAP_CONFIGFILE, 71 SAPOPC_R3STATUS_CONFIGFILE, 71 SAPOPC_RFC_TIMEOUT, 71 SAPOPC_TRACEPATH, 71 r3status(.exe), 70
r3monusr.cfg, 168	r3status.cfg, 71
r3monusr Monitor alert types, 167 command-line parameters, 168 environment variables, 168 file locations, 168 remote monitoring with, 168	r3status.cfg r3status configuration file, 72 r3status.his, 71 r3status.his r3status history file, 71 r3status.log, 70 r3status monitor
r3monusr monitor type, 167 r3monwpa, 169 alert types configuring, 171	configuring remote monitor, 73 environment variables, 71 file locations, 70 polling frequency, 70 report type, 70
WP_AVAILABLE, 172	R/3 Instances service, 340
WP_CHECK_CONFIGURED, 177 WP_IDLE, 174 WP_STATUS 179	Remote Monitoring r3monal monitor, 58
WP_STATUS, 178 command-line parameters, 171 monitor alert types, 170 monitor environment variables, 171 monitor file locations, 171 parameter values, 171 remote monitoring with, 171 r3monwpa.cfg, 171	Remote monitoring with r3monsec, 79

remote monitoring	RFCTimeOut for Alert Monitors, 38, 58		
r3monale monitor, 116	roll/paging messages		
r3monchg monitor, 124	disabling in SAP R/3, example, 184		
r3moncts monitor, 129	Run Interval		
r3mondmp monitor, 138	for alert monitors, 49		
r3monjob monitor, 141	for r3moncol alert-collector monitors, 101		
r3monlck monitor, 149 r3monoms monitor, 151			
r3monrfc monitor, 153	S		
r3monspl monitor, 156			
r3montra monitor, 160	SAP_ICMSTAT_PERF Performance metrics, 362		
r3monupd monitor, 166	SAP_STATRECS_PERF Performance metrics, 362		
r3monusr monitor, 168	SAP_SYSUP_PERF Performance metrics, 362		
r3monwpa monitor, 171	SAP_USER_PERF Performance metrics, 362		
with the alert-collector monitor, 106			
with the alert-collector monitors, 106	SAP_WLSUM_PERF Performance metrics, 362		
with the Alert Monitors, 24	SAPBUFFER_PERF Performance metrics, 222, 229,		
with the performance monitor, 214	362		
with the r3status monitor, 73	SAPCCMSR Availability		
Remote Monitoring for r3perfagent configuration,	monitoring in J2EE (Web AS Java), 85		
218	SAP CEN		
RemoteMonitoring keyword, 37, 73, 108	monitoring with r3monal, 64		
remote monitoring with r3moncol alert monitors,	SAP Client Parameter, 30, 110		
106	SAP Hostname Parameter, 31, 110		
removing	SAPMEMORY_PERF Performance metrics, 222,		
SPI for SAP R/3 Performance Agent, 241	231, 362		
SPI for SAP service reports, 363	SAP Number Parameter, 31, 110		
REPAIR, 162	SAPOPC_DRIVE, 57, 65, 67		
reports .	SAPOPC_HISTORYPATH, 57, 65, 67, 71		
service			
gathering data, 360	SAPOPC_R3ITOSAP_CONFIGFILE, 71		
generating, 352 generating in SPI for SAP, 360	SAPOPC_R3MONAL_CONFIGFILE, 57		
installing in SPI for SAP, 350	SAPOPC_R3MONDEV_CONFIGFILE, 65		
metrics, 361	SAPOPC_R3MOPRO_CONFIGFILE, 67		
removing in SPI for SAP, 363	SAPOPC_R3STATUS_CONFIGFILE, 71		
SAP R/3 metrics, 361			
upgrading in SPI for SAP, 349	SAPOPC_RFC_TIMEOUT, 71		
viewing in SPI for SAP, 352, 361	SAPOPC_SAPDIR, 57, 65, 67		
report type r3status, 70	SAPOPC_TRACEPATH, 57, 65, 67, 71		
ReportTypes for the Alert Monitors, 101			
ReportTypes for the r3moncol Alert Monitors, 101			
REQUEST_CREATED, 130			
REQUEST_RELEASED, 131			
RFC-destination Monitor, 152			
RFC FUNCTION Alert Class			
with r3perfagent, 219			
RFCONNECT, 163			
RFC Parameter, 30, 110			
INTO I ATAINEVEL, OU, TIU			

SAP R/3	service
Dispatcher-queue monitor	batch, 341
File Locations, 81 Dispatch queue, 80	batch WP, 342 database, 340
J2EE (Web AS Java), 84	dialog, 341
Configuration pre-requisites, 85	dialog WP, 342
Configuring, 86	environment, 340
Enabling CCMS Alerts, 84	gateway, 342
GRMG Monitoring, 85	interface, 340
J2EE kernel, 85, 88, 90	line of business (LOB), 342
J2EE services, 85, 88, 90	memory management, 341
J2EE system, 85	message, 342
SAPCCMSR Availability, 85	network, 341
monitoring security audits, 93	operating system, 341
SAP security-alerts, 94 Security, 75	R/3 instances, 340 SAP R/3, 340
Alert Types, 75	spool, 341
Configuring, 75	spool, 811 spool WP, 342
File Locations, 75	update, 341
Status, 70	update WP, 342
SAP R/3 Admin, 40, 43	ServiceNavigator, 339
SAP R/3 Admin Local, 44	service report, 349
SAP R/3 service, 340	Service Reporter, 349
SAP status	service reports
determining with r3status, 73	gathering data, 360
SAP System Parameter, 31, 111	generating, 352
scheduler	generating SPI for SAP, 360
performance-monitor, 215	installing SPI for SAP, 350, 360
	metrics, 361
schedule synchronization for r3perfagent configuration, 217	removing SPI for SAP, 363 SAP R/3 metrics, 361
SyncBack for r3perfagent configuration, 217	upgrading SPI for SAP, 349
	viewing SPI for SAP, 352, 361
Security Audit Define security-audit profile, 96	Services
Enabling CCMS Security Monitoring, 96	J2EE
	monitoring in Web AS Java, 85, 88, 90
Security-Audit Logs monitoring with r3monal, 63	service view, 339
Security-Audit monitor, 93	setting thresholds, 185
Configuring, 94	SeverityCritical, 59
Define security audits, 96	severity level
Install Security Monitoring, 95	changing, 183
Enabling CCMS Security Monitoring, 96	6 0,
SAP security alerts, 94	Severity Major, 111
Security monitor, 75 Alert Types, 75	Severity Minor, 111
Configuring, 75	SeverityNormal, 59
File locations, 75	SeverityNull, 59
1110 1000010113, 10	SeverityWarning, 59
	Snapshot Monitor Type, 101
	Solution Manager Integration with SPI for SAP, 187 pre-requisites, 187

SPI for SAP	TPTEST, 164
Golden Metrics, 365 Solution-Manager integration, 187 pre-requisites, 187	trace file for Alert-Monitor configuration, 39, 72, 82 file for r3moncol configuration, 108
SPI for SAP R/3 Performance Agent installing, 206 removing, 241	level for Alert-Monitor configuration, 40, 60, 72, 82 level for r3moncol configuration, 108
SPOOL_ENTRIES_RANGE, 156	level for r3perfagent configuration, 216
SPOOL_ERROR_RANGE, 157	tracefile
SPOOL_PERF Performance metrics, 231	alert-monitor list, 41
SPOOLER Monitor, 155	TraceFile keyword for r3moncol alert collectors, 108
Spool service, 341	TraceLevel keyword
Spool WP service, 342	for alert monitors, 40
START_PASSED, 145	for r3moncol alert collectors, 108
condition in job monitor, 139, 149	TRANS, 160
STATRECS_PERF	type
configuring, 233	r3monaco monitor, 179 r3monchg monitor, 123
STATRECS_PERF Performance metrics, 222, 232	r3monets monitor, 128
Status monitor, 70	r3mondmp monitor, 138
status of SAP	r3monjob monitor, 140
reporting with r3status, 73	r3monlck monitor, 148 r3monoms monitor, 150
SyncBack synchronize schedule of r3perfagent, 217	r3monrfc monitor, 153
synchronization schedule for r3perfagent configuration, 217 schedule SyncBack for r3perfagent	r3monspl monitor, 155 r3monupd monitor, 166 r3monusr monitor, 167 r3monwpa monitor, 170
configuration, 217	r3status monitor report, 70
SyslogId Parameter, 31	U
System J2EE	
monitoring in Web AS Java, 85	UPDATE_ACTIVE, 167
SYSTEM CHANGE Monitor, 123	UPDATE_ERRORS_EXIST, 167
SYSUP_PERF Performance metrics, 222, 235	UPDATE_PERF Performance metrics, 222, 236, 362 UPDATE Monitor, 165
T	Update service, 341
TASK_CREATED, 133	Update WP service, 342
TASK_RELEASED, 133	upgrading
Temporary Sequential File see TEMSE, 179	performance monitor subagent, 202 SPI for SAP service reports, 349
TEMSE Monitoring the file, 179 report, 179	USER_LOGGEDIN_MAX, 168 APSERVER, 169 MAX, 169
threshold	USER_PERF Performance metrics, 222, 237
performance alert, 186	USER Monitor, 167
thresholds in SAP R/3, 185	

Time Frame monitor type, 101

V
values r3moncol monitor parameters, 104 r3monjob monitor parameters, 142 r3monrfc monitor parameters, 154 r3monwpa monitor parameters, 171 variable environment SAPOPC_DRIVE, 57, 65, 67 SAPOPC_HISTORYPATH, 57, 65, 67, 71 SAPOPC_R3ITOSAP_CONFIGFILE, 71 SAPOPC_R3MONAL_CONFIGFILE, 57 SAPOPC_R3MONDEV_CONFIGFILE, 65 SAPOPC_R3MONPRO_CONFIGFILE, 67 SAPOPC_R3TATUS_CONFIGFILE, 71 SAPOPC_R3TATUS_CONFIGFILE, 71 SAPOPC_RFC_TIMEOUT, 71
SAPOPC_RFC_TIMEOUT, 71 SAPOPC_SAPDIR, 57, 65, 67
SAPOPC_SAPDIR, 57, 65, 67 SAPOPC_TRACEPATH, 57, 65, 67, 71
variables r3monale monitor environment, 116 r3monal monitor environment, 57 r3monchg monitor environment, 124 r3moncol (alert-collectors) environment, 105 r3moncts monitor environment, 129 r3mondev monitor environment, 65 r3mondmp monitor environment, 138 r3monjob monitor environment, 141 r3monlck monitor environment, 148 r3monoms monitor environment, 151 r3monpro monitor environment, 153 r3monspl monitor environment, 156 r3montra monitor environment, 159 r3monupd monitor environment, 166 r3monusr monitor environment, 168 r3monwpa monitor environment, 171 r3status monitor environment, 71
viewing
SPI for SAP service reports, 352, 361
W
Web AS (J2EE) monitor, 84, 85 Configuring, 86 Enabling CCMS Alerts, 84 GRMG Monitoring, 85 J2EE kernel, 85, 88, 90 J2EE services, 85, 88, 90 J2EE system, 85 SAPCCMSR Availability, 85
WLSUM_PERF Performance metrics, 222, 238

WORKPROCESS Monitor, 169

WP_AVAILABLE, 172
APSERVER, 173
WP_CHECK_CONFIGURED, 177
WP_IDLE, 174
APSERVER, 175
WP_PERF Performance metrics, 222, 240, 362
WP_STATUS, 178
APSERVER, 178

X

XMI syslog mode for Alert Monitors, 60

We appreciate your feedback!

If an email client is configured on this system, by default an email window opens when you click on the bookmark "Comments".

In case you do not have the email client configured, copy the information below to a web mail client, and send this email to ${\bf docfeedback@hp.com}$

Product name:
Document title:
Version number:
Feedback: