
HP OpenView Configuration Management Configuration Server

for the Windows operating system

Software Version: 5.00

Configuration Server and Database Migration Guide





Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notices

© Copyright 2007 Hewlett-Packard Development Company, L.P.

Trademark Notices

Linux is a registered trademark of Linus Torvalds.

Microsoft®, Windows®, and Windows® XP are U.S. registered trademarks of Microsoft Corporation.

OpenLDAP is a registered trademark of the OpenLDAP Foundation.

PREBOOT EXECUTION ENVIRONMENT (PXE) SERVER

Copyright © 1996-1999 Intel Corporation.

TFTP SERVER

Copyright © 1983, 1993

The Regents of the University of California.

OpenLDAP

Copyright 1999-2001 The OpenLDAP Foundation, Redwood City, California, USA.

Portions Copyright © 1992-1996 Regents of the University of Michigan.

OpenSSL License

Copyright © 1998-2001 The OpenSSLProject.

Original SSLeay License

Copyright © 1995-1998 Eric Young (eay@cryptsoft.com)

DHTML Calendar

Copyright Mihai Bazon, 2002, 2003

Documentation Updates

This guide's title page contains the following identifying information:

- Software Version number, which indicates the software version
- Document release date, which changes each time the document is updated
- Software release date, which indicates the release date of this version of the software

To check for recent updates or to verify that you are using the most recent edition, visit the following URL:

ovweb.external.hp.com/lpe/doc_serv/

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

You can visit the HP Software support web site at:

www.hp.com/go/hpsoftwaresupport

This Web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online software support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract.

To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

To register for an HP Passport ID, go to:

http://h20229.www2.hp.com/passport-registration.html

Contents

1	Upgrading the CM Configuration Server and Database	7
	Installing the CM Configuration Server	7
	Upgrading the CM CS Database	7
	Pre-requisites for the CM CS Database Upgrade	8
	System Requirements for the CM CS Database	8
	Using the Verify Database Utility	
	Using the Database Difference Utility Creating Export Decks of Your Existing Database	11
	Comparing Databases	13
	Creating a New Database Directory	
	Importing the Class Deck	
	Running the Database Difference File	
	Importing the Instances and Resources to the Database	16
	CM OS Manager Updates	17
	Space Limitation Considerations	17
	CM 5.00 CORE Database Changes	19
2	Validating the CM CS Database	20
	Checking for Orphaned Resources	24
	Checking for Duplicate IDs	
In	ndex .	27

6 Contents

1 Upgrading the CM Configuration Server and Database

This guide will help you upgrade an existing CM Configuration Server (CM-CS) and CM CS Database to version 5.00.



Be sure to back up your existing database before beginning the upgrade process.

The upgrade process consists of two main steps:

- 1 Installing the Version 5.00 CM Configuration Server
- 2 Upgrading the existing CM CS Database to version 5.00. Version 5.00 CM CS Database is in UTF-8 format.

Follow the steps in this guide to successfully upgrade your CM Configuration Server and CM CS Database.

Installing the CM Configuration Server

Use the version 5.00 media to install the CM-CS. During the installation:

- Select the optional components CM OS Manager, CM Patch Manager and CM Usage Manager.
- Do not overwrite the existing CM-CS installation.

After you've installed the 5.00 CM-CS, remove the 5.00 CM CS Database, as this is not necessary for the migration process.

To remove the 5.00 CM CS Database

- 1 Stop the CM CS service.
- 2 Remove the DB folder, installed by default: C:\Program Files\Hewlett-Packard\CM\ConfigurationServer\DB

When you've finished installing the CM-CS, update the new CM CS Database.

Upgrading the CM CS Database

Before you upgrade your HP OpenView Configuration Management Configuration Server Database (CM CS Database), it is strongly recommended that you use the Verify Database Utility a non-invasive database analysis tool to check the status and integrity of the elements in the Database. In general, it is recommended that you periodically verify the status of your Database and perform any necessary maintenance or cleanup.

Once your existing Database has been verified and you have performed any recommended maintenance, use the Database Difference Utility to compare your existing CM CS Database class templates to the new CM CS Database class templates. This utility creates a file that

contains the verbs that will be used to update your Database. You should then review this file and specify what changes to include or exclude. When finished reviewing the file, complete the several procedures which are included in this chapter to create the new Database.

Pre-requisites for the CM CS Database Upgrade

• CM Configuration Server 5.00 or above

System Requirements for the CM CS Database

• You must have free space that is equal to three times the size of your CM CS Database. For space limitation considerations, see Space Limitation Considerations on page 17.

Platform Support

• See the release note document that accompanies this release for detailed platform support



The locations and directory names presented below are only suggestions used to help with the database upgrade procedure.

Using the Verify Database Utility

When using the Verify Database Utility to check the status and integrity of the elements in the Database, you will:

- Create a backup copy of your current CM CS Database.
- Run the Verify Database Utility to verify the contents of your Database.
- Review the resulting log and perform the recommended maintenance.


To use the Verify Database Utility

- 1 If running, stop the CM Configuration Server service.
- 2 Create a new directory, such as MyDatabase, that you will use to store a backup of your CM CS Database and a copy of the Verify Database Utility.
- 3 Copy your existing CM Configuration Server database directory to the newly created MyDatabase directory.

The default database location for previous CM CS installations was:

- C:\Novadigm\ConfigurationServer\DB.
- 4 Create another directory in MyDatabase to store the Verify Database Utility, such as UpdateDB.

Your directory structure should appear similar to the following figure.



- 5 Copy your original EDMPROF. DAT file to the UpdateDB directory.
- 6 Extract the contents of the Verify Database Utility zip file (win32_ams_vrfydb.zip located on the CM DVD in the

\management_infrastructure\configuration_server\migrate_db folder) to the UpdateDB directory.

This zip file contains:

- ZEDMAMS.exe
- Five DLLs
- 7 Use a text editor and open the EDMPROF.DAT file in the UpdateDB directory.
- 8 Go to the [MGR_DIRECTORIES] section and use the DBPATH argument to specify the path to the backup of your CM CS Database.

```
[MGR_DIRECTORIES]
DBPATH = C:\MyDatabase\DB
```

- 9 Save and close the file.
- 10 Open a command prompt and change to the directory where you stored the Verify Database Utility (such as C:\MyDatabase\UpdateDB).
- 11 To ensure the BEHAVIOR class follows standard naming conventions, run the following command against the database you will be migrating (such as c:\MyDatabase\DB):

```
ZEDMAMS VERB=EDIT_CLASS_PREFIX, FILE=PRIMARY, DOMAIN=SOFTWARE, CLASS=BEHAVIOR, PREVIEW=NO, KEEPDATE=YES, FIELD=CLASTYPE, VALUE=T
```

12 Run the Verify Database Utility. The following is a sample command that you might use to verify the integrity of all of the domains in the database:

ZEDMAMS VERB=VERIFY_DATABASE, DOMAIN=ALL, LOGFILE=VerifyDb.log, DEPTH= RESOURCE, ZFILE=VERIFYZFILE.BAT

Table 1 Parameters for Verify Database Utility

Parameter	Explanation	
VERB	Specifies the verb that you are running. In this case, you must use VERIFY_DATABASE.	
DOMAIN	Specifies the domain that you want to verify. DOMAIN=ALL	
	Verifies all domains, except for the PROFILE domain, which cannot be verified using this utility.	
	DOMAIN=DomainName Verifies the domain that you specify, such as SOFTWARE.	
LOGFILE	An optional parameter that can be used to specify the name of the log that contains information about the status of your database.	
	By default, the log file is ZEDMAMS.log. This log is stored in the same directory as the Verify Database Utility.	
DEPTH	Use the depth parameter to restrict the verification in the database. The following are acceptable values:	
	• resource	
	• instance	
	• class	
	• domain	
	Usage: depth=(Domain/class/instance/resource)	
ZFILE	Use the zfile parameter to create a batch file with all of the verbs reported in the veify_database log to fix the inconsistencies in the database. Output can be executed using the following command. (Note: ZFILE is case sensitive):	
	ZEDMAMS ZFILE (FILENAME)	
	Type a fully qualified path and filename to designate the batch file.	



The Verify Database Utility may run for several minutes or several hours depending on the size of your Database.

13 Open the log (VerifyDb.log from the example above) to review information about the state of your CM CS Database. For more information about any of the verbs in the recommended solutions see the HP Technical Support web site.



While reviewing output, note that two classes SVR4DEP and SDDEP will be removed. Be sure to allow these classes to be removed from your database by leaving those lines uncommented.

- 14 Review the newly created ZFILE batch file (VERIFYZFILE.BAT created when you ran ZEDMAMS with the ZFILE parameter in step 12).
- 15 When you are satisfied, run the file against the database using the following command: ZEDMAMS ZFILE "VERIFYZFILE.BAT"
- 16 After performing the recommended solutions, run the Verify Database Utility again and then review your ZEDMAMS.LOG file to ensure that the issues have been resolved.

Messages containing Improper Instance Name in the ZEDMAMS log file can be ignored. A sample message follows:

<18:02:04:308> Improper Instance Name <SAMPLE_INSTALL_REX> in Component
Class <PRIMARY.SOFTWARE.BEHAVIOR>



Run the Verify Database Utility as many times as needed to assist you in determining the health of your database.

If you continue to package and publish to your production Database, be sure to create another backup copy and run the Verify Database Utility again immediately before performing the upgrade. This ensures that all potential issues are analyzed.

After you start the CM Configuration Server with the migrated database, the Configuration Server log file may contain many duplicate object IDs within the Base Instance. These messages can be ignored. An example message follows:

```
ERROR, DUPLICATE OBJECT ID CDABCB40992AB> FOUND WHILE
ADDINGCPRIMARY.SOFTWARE.BEHAVIOR._BASE_INSTANCE_>
```

Using the Database Difference Utility

Use the Database Difference Utility to compare your existing CM CS Database class templates to the target CM CS Database class templates. You will need to do the following:

- Create export decks of your existing CM CS Database.
- Run the Database Difference Utility to compare your export decks (created from your backup Database) against the new 5.00 CM CS Database class template schema (CORE.XPC).
- Review and edit the resulting file, which contains the verbs that will be used to update the target Database.

Creating Export Decks of Your Existing Database

Create the following export decks from your existing Database:

- CM CS Database Classes (.XPC)
 Used with the Database Difference Utility to compare your existing CM CS Database against the new database.
- **CM CS Database Instances (.XPI)**This is the source instance deck that is imported into the new Database.
- CM CS Database Resources (.XPR)
 This is the source resource deck that is imported into the new Database.



Use the export decks as a:

- Base for your comparison against the CM CS Database.
- Back-up file of your current CM CS Database.

To create an export deck of your current CM CS Database

- 1 Create a new directory, such as ExpDeck.
- 2 If running, stop the CM Configuration Server service.

- Open a command prompt and change to the directory where you stored the Verify Database Utility, which contains the latest ZEDMAMS.EXE, such as UpdateDB.
- 4 Create three export decks, one deck for the classes, one deck for the resources and one deck for the instances in the directory that you created. After each command is run, review the ZEDMAMS.LOG (located in the directory where you stored the Verify Database Utility, such as C:\MyDatabase\UpdateDB) to ensure that there were no errors, and that your export completed with RC 0 or RC 4.



Each time you run ZEDMAMS, a new log file is created (by default ZEDMAMS . log). If you would like to save the individual log files from each ZEDMAMS session, either rename or move the default log file after you run ZEDMAMS, or use the ZEDMAMS LOGFILE parameter and specify a new log file name (see Table 1).

- For example, to create an export deck for your classes named oldexport.xpc, run: ZEDMAMS VERB=EXPORT_CLASS,FILE=PRIMARY,PREVIEW=NO,OUTPUT=C: \ExpDeck\OLDEXPORT.XPC
- For example, to create an export deck for your instances named oldexport.xpi, run:

ZEDMAMS VERB=EXPORT_INSTANCE,FILE=PRIMARY,PREVIEW =NO,OUTPUT=C:\ExpDeck\OLDEXPORT.XPI

— For example, to create an export deck for your resources named oldexport.xpr, you would run:

ZEDMAMS

VERB=EXPORT_RESOURCE,FILE=PRIMARY,PREVIEW=NO,OUTPUT=C:\ExpDeck\OLDEXPORT.XPR



You may receive the warning "no resource found". These warnings are reported on the instances, which have no resources (non data-bearing instances).

After each command is run, review the ZEDMAMS. LOG file (located in the directory where you stored the Verify Database Utility, (such as UpdateDB) to ensure that there were no errors, and that your export completed with $RC\ 0$ or $RC\ 4$.



It may take a long time to create export decks of your entire CM CS Database.

Replacing NULL Characters

In some instances, the newly created XPC files will contain NULL characters that must be replaced in order to import the XPC later. To remove these characters:

- Obtain the **null2blank.rxx** script from HP
- Run the script against your newly created XPC file. For example, to replace NULL characters in OLDEXPORT.XPC, you would run the following command:

radrexxw null2blank.rxx OLDEXPORT.XPC

Next, use the Database Difference Utility to compare your existing CM CS Database class templates with the target CM CS Database class templates.

Comparing Databases

Use the Database Difference Utility (dbdiffc.tcl) to compare the two class export decks.

To compare the databases

- Create a new directory, such as C:\MyDatabase\DBDiff.
- 2 Copy the following files into this directory.
 - Your .XPC file (such as OLDEXPORT.XPC)
 - Supplied .XPC file (CORE.XPC, located on the CM DVD in the \management_infrastructure\configuration_server\migrate_db folder)
 - Database Difference Utility (dbdiffc.tcl unzipped from win32_dbdiff.zip)
 - nvdkit.exe (unzipped from win32_dbdiff.zip)
- 3 Open a command prompt and navigate to the directory that you created (DBDIFF).
- 4 Run the Database Difference Utility. The following is an example of the command line:

```
nvdkit.exe dbdiffc.tcl SOURCE_CLASS_DECK=OLDEXPORT.XPC,
TARGET_CLASS_DECK=CORE.XPC,BATCH_OUT=OUTPUT.DAT,DELETE=N
```

Table 2 Required arguments for the Database Difference Utility

Argument	
SOURCE_CLASS_DECK	The filename of the export deck that you created from your existing Database.
TARGET_CLASS_DECK	The filename of the HP export deck (CORE.XPC).
BATCH_OUT	The name of the file that contains a list of the verbs to be executed after you review the file. Several text files will be created in the same directory where this file is stored. These files represent the new classes that will be added to the Database.
DELETE	If a field or class exists in the source XPC file, but does not exist in the HP supplied target XPC file (CORE.XPC):
	Set DELETE=Y to delete the fields or classes.
	Set DELETE=N to keep the fields or classes.

- Use a text editor to open the output file (specified in the BATCH_OUT argument), such as OUTPUT.DAT.
- 6 Review this file and determine what changes you would like to keep. If you want to exclude any changes, place an asterisk (*) in front of the verbs that you do not want to run. If you want to include changes that are currently excluded (denoted by an asterisk at the beginning of the line), remove the asterisk



While reviewing output, note that two classes SVR4DEP and SDDEP will be imported. In order to remove these classes, comment out the import class verbs.



The NOVADIGM domain will be imported by default. If this is not required for your implementation, comment out the appropriate import class verbs.

Below is a table that defines some of the most common ZEDMAMS verbs that you will encounter when reviewing the output file.

Table 3 Common Verbs in the Output File

Verb	Description
ADD_FIELD	Adds a variable at the end of a template. This verb has a KEEPDATE= option which allows for an update of a variable without updating the ZOBJDATE/ZOBJTIME of the Base_Instance.
CHANGE_FIELDNAME	Changes variable names in the class template. This verb has a KEEPDATE= option which allows for an update of the class without updating the ZOBJDATE/ZOBJTIME instance.
CHANGE_FLD_VALUE	Changes a template's variable length, type Configuration Server, and client flags. This verb has a KEEPDATE= option which allows for the value to be updated without updating the ZOBJDATE/ZOBJTIME instance.
CHANGE_INS_FIELD	Changes one field in each instance of a class and verifies connects. This verb has a KEEPDATE= option which allows for the field to be updated without updating the ZOBJDATE/ZOBJTIME instance.
CHANGE_INST_DATA	Globally changes data in instance records by class. This verb has a KEEPDATE= option which allows for the instance to be updated without updating the ZOBJDATE/ZOBJTIME instance.
COPY_FIELD	Copies attribute data to a new attribute or to an existing attribute. This verb has a KEEPDATE= option which allows for the field to be updated without updating the ZOBJDATE/ZOBJTIME instance.
DELETE_FIELD	Deletes an attribute from a template. This value does not alter the ZOBJDATE/ZOBJTIME instance.
DELETE_CLASS	Deletes a class from the database.

⁷ Save and close the file.

Once you have determined the differences between the CM CS Database class templates, you are ready to update your target CM CS Database.

Creating a New Database Directory

In this section, you will create a new directory for your new database.

To create a new database directory

- Navigate to newly installed CM Configuration Server directory. The default location is: C:\Program Files\Hewlett-Packard\CM\ConfigurationServer
- Create a new directory, such as C:\Program Files\Hewlett-Packard\CM\ConfigurationServer\New_DB.
- 3 Within this new directory, create two additional directories:
 - ${\tt C:\Program\ Files\Hewlett-Packard\CM\ConfigurationServer\New_DB\PRIMARY}$
 - C:\Program Files\Hewlett-Packard\CM\ConfigurationServer\New DB\RESOURCE

These directories must be named PRIMARY and RESOURCE and the names must be capitalized.

- 4 Backup your EDMPROF file.
- 5 Use a text editor to open EDMPROF file.
- 6 Find the argument DBPATH in the [MGR_DIRECTORIES] section and change the value to point to the new Database directory that you created.

```
MGR_DIRECTORIES] DBPATH = C:\Program Files\Hewlett-Packard\CM\ConfigurationServer\New DB
```

- 7 Save and close the file.
- 8 Copy the updated EDMPROF file to the UpdateDB directory.

Importing the Class Deck

In this section, you will import your target class deck (XPC) into the new database. This provides a starting point for your new Database.

To import the target deck into the Database

1 Change the current directory to the C:\MyDatabase\UpdateDB and run the following command:

```
ZEDMAMS VERB=IMPORT CLASS, FILE=C:\MyDatabase\DBDIFF\CORE.XPC, PREVIEW=NO
```

Be sure to include the correct fully qualified path to CORE.XPC in the command line.

- 2 Review the ZEDMAMS.LOG to ensure that there were no errors, and that your import completed with RC 0 or RC 4.
- 3 Save the log file (copy zedmams.log to zedmams.ImportXPC.log).



If the number of class connections in your existing database does not match the number of connections in CORE.XPC, to avoid breaking any existing connections you will need to manually adjust the connections within the newly imported database before you import your existing database classes.

Running the Database Difference File

In this section, you will run the Database Difference file that you created when you ran the Database Difference Utility.



Be sure that you have reviewed this file thoroughly and commented out any verbs that you do not want to be executed.



Also, be sure no CM Configuration Servers are running before you proceed with the following steps.

To run the text input file

- Go to the directory where your BATCH_OUT file is stored (such as C:\DBDiff). Remember, this directory will also contain several files that represent the new classes that will be added to the database.
- 2 Copy OUTPUT. DAT to the UpdateDB directory.



You do not need to copy the text files to the BIN directory. The OUTPUT. DAT file contains a fully qualified path for these files.

3 Change the current working directory to the UpdateDB directory and run the following: ZEDMAMS ZFILE "OUTPUT.DAT"

where OUTPUT.DAT is the name of the file that you specified in the BATCH_OUT parameter when you ran the Database Difference Utility. Note that ZFILE must be in all caps.

4 Review ZEDMAMS.LOG to ensure that there were no errors, and that your import completed with RC 0 or RC 4.

Importing the Instances and Resources to the Database

Finally, you must import the remaining source export decks that you created earlier, as well as the new supplied decks (CORE.XPI and CORE.XPR) to finish building the database.



Be sure no CM Configuration Server is running before you proceed with the following steps.

To import the instance and resource decks

- 1 Copy the .XPI and .XPR files from the ExpDeck directory to the UpdateDB directory.
- 2 Also copy CORE.XPI and CORE.XPR from the CM 5.00 DVD in the \management_infrastructure\configuration_server\migrate_db folder to the UpdateDB directory
- 3 Open a command prompt.
- 4 Change the directory to UpdateDB and run the following to import the new version 5.00 instances and resources:

ZEDMAMS VERB=IMPORT_INSTANCE, FILE=CORE.XPI, XPR=CORE.XPR, TIME=OLD, PREVIEW=NO, DUPLICATES=MANAGE, CONTINUE=YES, REPLACE=YES



Each time you run ZEDMAMS, a new log file is created (by default ZEDMAMS.log). If you would like to save the individual log files from each ZEDMAMS session, either rename or move the default log file after you run ZEDMAMS, or use the ZEDMAMS logfile parameter and specify a new log file name.


5 Run the following command to import your existing instances and resources:

ZEDMAMS VERB=IMPORT_INSTANCE, FILE=OLDEXPORT.XPI, XPR=OLDEXPORT.XPR, TIME=OLD, PREVIEW=NO, DUPLICATES=MANAGE, CONTINUE=YES, REPLACE=YES

The filename used in this example represents the name of the export deck that you created earlier.

- 6 Review the ZEDMAMS.LOG to ensure that there were no errors, and that your import completed with RC 0 or RC 4.
- Run the Verify Database utility and make sure no errors are reported in the log file other than Improper Instance Name errors, which can be ignored.
- 8 To confirm that the upgrade completed successfully, perform a CM Agent Connect (for example, open the CM Application Self-Service Manager catalog). If you receive the same results as you did prior to the upgrade, then the upgrade was successful.
- If you commented out the import class verbs for the NOVADIGM domain, the import instance will result in 504 errors (because the 5.00 CM CS Database does not contain the NOVADIGM domain).

Your CM CS Database upgrade is now complete.



The connection to the agent computer will fail if any object in storage is larger than 6k bytes. A CM Agent cannot receive a heap size larger than 6k bytes (or 247 attributes). This does note include the README field, since the README field is not included in the transfer.

Use the CM CSDB Editor to view actual instance sizes. Note that the object size may grow if more variables are added to the object.

To avoid an agent connection failure during data transfer:

Turn on the STATS [MGR_TRACE] option to print the size of the persistent object. The Configuration Server reports the object-size when it is deleted. Monitor this for any object that may grow larger than the current limit of 6k bytes. Additionally, the VAR trace option will display variable sizes that are being added to an object.

For more information, refer to the CM Configuration Server Guide.

CM OS Manager Updates

After you upgrade, any customizations made to rombl.cfg in the LSB package will be lost. Use the CSDB Editor to save the existing rombl.cfg-(right-click the file and use the Edit this Component shortcut menu option).

Space Limitation Considerations

This upgrade process requires space available up to three times the size of your existing CM CS Database. If free space is limited, the following considerations can be applied:

- Do not copy the original database to create export decks.
- Delete backup copy of the original database before updating the target database.

- Move existing database RESOURCE folder to the target database. This allows you to avoid creating and importing large XPR files.
- Before moving a RESOURCE folder, be sure there no extended ASCII characters in the domain or class names of the existing database.

CM 5.00 CORE Database Changes

- The 5.00 CM CS Database format is UTF-8.
- The NOVADIGM domain was removed in version 5.00.
- ZBITARCH attribute added to AUDIT.ZSERVICE and AUDIT.PACKAGE
- RPTCLASS and TIMEOUT attributes added to AUDIT.WBEM
- ZBITARCH attribute added to SOFTWARE.ZSERVICE and SOFTWARE.PACKAGE
- DIRPERMS attribute added to SOFTWARE.UNIXFILE

2 Validating the CM CS Database

The following errors provide information about structural issues that may be present in your Database.



Unmated instances are instances that exist with no connection to a resource.

Table 4 Domain Validation

ERROR MESSAGE	Suggested Solution
Impact	
VERIFY DOMAIN <> CANNOT VALIDATE DMA INSTANCE COUNT. High impact for DMA Customers. Low impact for non-DMA Customers.	Run: ZEDMAMS VERB=REFRESH_DMA,PREVIEW=NO
VERIFY DOMAIN < > DMA INSTANCE COUNT DOES NOT EQUAL ACTUAL INSTANCE COUNT. High impact for DMA Customers. Low impact for non-DMA Customers.	Run: ZEDMAMS VERB=REFRESH_DMA,PREVIEW=NO

Table 5 Class Validation

ERROR MESSAGE	Suggested Solution
Impact	
MISSING TEMPLATE IN CLASS < >.	Delete the class. Restore the class from
High impact for resolution process and integrity of the class.	the last known good template for that class.
CLASS < > HAS MISSING _BASE_INSTANCE.	Delete the class. Restore the class from
High impact for resolution process and integrity of the class.	the last known good template for that class.
CLASS < > HAS INVALID _BASE_INSTANCE.	Delete the class. Restore the class from
High impact for resolution process and integrity of the class.	the last known good template for that class.
VERIFY CLASS < > CANNOT READ DMA CLASS CONTROL INFORMATION. (INVALID	Delete the class. Restore the class from the last known good template for that
CLASS).	class.
High impact for resolution process and integrity of the class.	
CLASS < > PREFIX SIZE LESS THAN EXPECTED. (INVALID CLASS).	Delete the class. Restore the class from the last known good template for that
High impact for resolution process and integrity of the class.	class.

ERROR MESSAGE	Suggested Solution
Impact	
CLASS < > PREFIX CONTAINS INVALID DATES.	Delete the class. Restore the class from the last known good template for that
Low impact. For internal use only.	class.
CLASS < > PREFIX SIZE < > LESS THAN EXPECTED.	Delete the class. Restore the class from the last known good template for that
High impact for resolution process and integrity of the class.	class.
DATABASE VERSION MISMATCH FOR CLASS <>	Delete the class. Restore the class from the last known good template for that
High impact. Corrupt Class.	class.
CLASS TEMPLATE FIRST ENTRY NOT FOUND.	Delete the class. Restore the class from the last known good template for that
High impact for resolution process and integrity of the class.	class.
CLASS TEMPLATE < > TEMPLATE FIRST ENTRY NAME < > DOES NOT MATCH CLASS NAME.	Delete the class. Restore the class from the last known good template for that class.
CLASS < > TEMPLATE SIZE MISTMATCH.	Delete the class. Restore the class from
High impact for resolution process and integrity of the class.	the last known good template for that class.
CLASS < > HAS HEAP SIZE < > WHICH IS GREATER THAN SUPPORTED MAXIMUM.	Delete the class. Restore the class from the last known good template for that
High impact for resolution process and integrity of the class.	class.

Table 6 Class Validation

ERROR MESSAGE Impact	Suggested Solutions
CLASS <> HAS MISSING _NULL_INSTANCE. * Low impact.	Policy needs to be reviewed to see if the instance is used. Administrator can create a _NULL_ instance in the class if necessary.
CLASS < > HAS INVALID _NULL_INSTANCE.* High impact.	Delete the class. Restore the class from the last known good template for that class.
VERIFY CLASS < > INSTANCE COUNT IS ZERO. High impact. Affects the System Explorer and resolution process.	Run: ZEDMAMS VERB=REFRESH_DMA,PREVIEW=NO
VERIFY CLASS < > CANNOT VALIDATE DMA INSTANCE COUNT. High impact. Affects the System Explorer and resolution process.	Run: ZEDMAMS VERB=REFRESH_DMA,PREVIEW=NO

ERROR MESSAGE Impact	Suggested Solutions
VERIFY CLASS < > DMA INSTANCE COUNT DOES NOT EQUAL ACTUAL INSTANCE COUNT. High impact. Affects the System Explorer and resolution process.	Run: ZEDMAMS VERB=REFRESH_DMA,PREVIEW=NO
INSTANCE SIZE LESS THAN MINIMUM REQUIRED. High impact. Affects the System Explorer and resolution process.	Delete the class. Restore the class from the last known good template for that class.

Table 7 Instance Validation

Table 7 Instance Validation		
ERROR MESSAGE	Suggested Solution	
Impact		
INSTANCE SIZE DOES NOT MATCH CLASS TEMPLATE.	Delete the class. Restore the class from the last known good template for that class.	
High impact. The instance is corrupt.		
ZRSCDATE NOT FOUND BUT RESOURCE FLAG SET IN CONTROL INFO.	Delete the class. Restore the class from the last known good template for that class.	
No impact.		
WARNING: UNMATED INSTANCE < > DOES NOT HAVE CORRESPONDING DATA.	Determine the impact the resource has on your database. If the resource is non-critical, delete.	
Medium impact. Resource is missing for an instance	If the resource is critical, set the ZSERVICE.REMOVAL attribute to A and redeploy. (Setting the REMOVAL attribute to A abandons the resource, relinquishing CM control.)	
	Note: Deleting a resource may have adverse affects on other CM components. Before deleting a damaged resource, make sure it will not affect any existing components.	
RESOURCE < > SIZE < > IS INVALID FOR ASSOCIATED INSTANCE < >.	Determine the impact the resource has on your database.	
High impact. Damaged Resource.	If the resource is non-critical, delete.	
	If the resource is critical, set the ZSERVICE.REMOVAL attribute to A and redeploy. (Setting the REMOVAL attribute to A abandons the resource, relinquishing CM control.)	
	Note: Deleting a resource may have adverse affects on other CM components. Before deleting a damaged resource, make sure it will not affect any existing components.	

ERROR MESSAGE	Suggested Solution
Impact	
RESOURCE < > ACTUAL SIZE < > NOT EQUAL TO SIZE < > IN ASSOCIATED INSTANCE. High impact. Damaged Resource.	Determine the impact the resource has on your database. • If the resource is non-critical, delete. • If the resource is critical, set the ZSERVICE.REMOVAL attribute to A and redeploy. (Setting the REMOVAL attribute to A abandons the resource, relinquishing CM control.) Note: Deleting a resource may have adverse affects on other CM components. Before deleting a damaged resource, make sure it will not affect any existing components.
ERROR: OPENING RESOURCE <> FOR INSTNACE <>.	Delete the class. Restore the class from the last known good template for that class.
ERROR: UNABLE TO READ PREFIX FOR RESOURCE < > FOR ASSOCIATED INSTANCE < >.	Delete the class. Restore the class from the last known good template for that class.
RESOURCE < > ACTUAL SIZE < > DOES NOT MATCH EXPECTED SIZE < > FOR ASSOCAITED INSTANCE. High impact. Damaged Resource.	Determine the impact the resource has on your database. • If the resource is non-critical, delete. • If the resource is critical, set the ZSERVICE.REMOVAL attribute to A and redeploy. (Setting the REMOVAL attribute to A abandons the resource, relinquishing CM control.) Note: Deleting a resource may have adverse affects on other CM components. Before deleting a damaged resource, make sure it will not affect any existing components.
RESOURCE <> PREFIX CLASS NAME < > DOES NOT MATCH ITS ASSOCIATED INSTANCE <>. High impact. Damaged Resource.	Determine the impact the resource has on your database. • If the resource is non-critical, delete. • If the resource is critical, set the ZSERVICE.REMOVAL attribute to A and redeploy. (Setting the REMOVAL attribute to A abandons the resource, relinquishing CM control.) Note: Deleting a resource may have adverse affects on other CM components. Before deleting a damaged resource, make sure it will not affect any existing components.

ERROR MESSAGE	Suggested Solution
Impact	
RESOURCE <> PREFIX INSTANCE NAME <> DOES NOT MATCH ITS ASSOCIATED NAME <>. High impact. Damaged Resource.	Determine the impact the resource has on your database. • If the resource is non-critical, delete. • If the resource is critical, set the ZSERVICE.REMOVAL attribute to A and redeploy. (Setting the REMOVAL attribute to A abandons the resource, relinquishing CM control.) Note: Deleting a resource may have adverse affects on other CM components. Before deleting a damaged resource, make sure it will not affect any existing components.
RESOURCE <> COMPRESSED SIZE <> NOT EQUAL TO SPACE <> IN VARIABLE <> OF ASSOCIATED INSTANCE <>. Medium impact. ZCMPSIZE Variable may	Delete the class. Restore the class from the last known good template for that class.
be compromised. RESOURCE <> SIZE <> NOT EQUAL TO SIZE <> IN VARIABLE <> OF ASSOCIATED INSTANCE <>. Medium impact. ZRSCSIZE Variable may be compromised.	Delete the class. Restore the class from the last known good template for that class.
RESOURCE <> CRC <> NOT EQUAL TO CRC <> IN VARIABLE <> OF ASSOCIATED INSTANCE <>. Medium impact. ZRSCCRC Variable may be compromised.	Delete the class. Restore the class from the last known good template for that class.

Checking for Orphaned Resources

Orphaned resources are resources that exist with no parent instance. The following error provides information about orphaned resources.

Table 8 Orphaned Resource Check

ERROR MESSAGE Impact	Suggested Solution
FOUND ORPHANED RESOURCE – DATA DOES NOT HAVE A CORRESPONDING PARENT INSTANCE <>. THIS RESOURCE WAS PREVIOUSLY PARENTED BY <>.	Run: ZEDMAMS VERB=DELETE_RESOURCE, PREVIEW=NO
Low impact. This resource can be left OR you may choose to remove the unmated resource by using the ZEDMAMS VERB = DELETE_RESOURCE.	

Checking for Duplicate IDs

The following errors provide information about duplicate object IDs that may be present in your Database. Table $9\,\mathrm{Object}$ ID Check

ERROR MESSAGE	Suggested Solution		
Impact			
DUPLICATE OBJECT ID < > WITHIN < COMPONENT> CLASS < > BETWEEN INSTANCE < > AND < >. High impact. Possibility of corrupt data.	If either data is corrupted, use: ZEDMAMS VERB = DELETE_INSTANCE, PACKAGE=YES,PREVIEW=NO,DOMAIN=<>>, CLASS=< >, INSTANCE =<>>		
DUPLICATE OBJECT ID <	If both are from PACKAGE Class:		
> IN INSTANCES < > AND < >.	Duplicate Instance object ids in Package Class cannot be fixed. You will need to delete the package.		
	If class is NOT PACKAGE:		
	ZEDMAMS VERB= CHANGE_OBJECTID,FILE=PRIMARY,DOMAIN= <>,CLASS=<>,INSTANCE=<>,PREVIEW =NO		
DUPLICATE OBJECT ID <	If class is PACKAGE:		
> WITHIN < > CLASS < > BETWEEN INSTANCE < >.	Duplicate Instance object ids in Package Class cannot be fixed. You will need to delete the package.		
	If class is NOT PACKAGE:		
	ZEDMAMS VERB=CHANGE_OBJECTID,FILE=PRIMARY,DOMAIN= <>,CLASS=<>,INSTANCE=<>,PREVIEW =NO		

Index

A	restricted rights, 2 trademark, 2		
access levels, 4	warranty, 2		
ADD_FIELD verb, 13	LOG parameter, 10		
В	O		
BATCH_OUT argument, 13	output file, common verbs, 13 $ \begin{tabular}{l} P \\ \hline passport registration, 4 \\ \hline R \end{tabular}$		
С			
CHANGE_FIELDNAME verb, 13			
CHANGE_FLD_VALU verb, 13			
CHANGE_INS_FIEL verb, 14	resources, importing, 15		
CHANGE_INST_DATA verb, 14	restricted rights legend, 2		
CM CS Database	S		
prerequisites, 8			
COPY_FIELD verb, 14	SDDEP class, 10		
copyright notices, 2	SOURCE_CLASS_DECK, 13		
customer support, 4	${\rm support}, 4$		
D	SVR4DEP class, 10		
Database Difference Utility	T		
comparing databases, 12	TARGET_CLASS_DECK argument, 13		
required arguments, 13	technical support, 4		
using, 11	trademark notices, 2		
databases, comparing, 12	U		
dbdiffe.tel utility, 12	G		
DELETE argument, 13	updates to doc, 3		
DELETE_CLAS verb, 14 DELETE_FIELD verb, 14	V		
DEPTH parameter, 10	validating		
documentation updates, 3	domain, 19		
DOMAIN parameter, 10	instance, 21		
	VERB parameter, 9		
I	Verify Database Utility parameters, 9		
Improper Instance Name, 10	VERIFY_DATABASE, 9		
instances, importing, 15			
K	W		
KEEPDATE, 13	warranty, 2		
	Z		
L	ZEDMAMS.LOG, 10, 16		
legal notices, 2	ZFILE parameter, 10		
copyright, 2	= '		

ZOBJDATE, 13 ZOBJTIME, 13

28 Index