

HP Server Automation

Enterprise Edition

Software Version: 10.0

User Guide: Server Automation

Document Release Date: June 3, 2013

Software Release Date: June 2013



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notices

© Copyright 2001-2013 Hewlett-Packard Development Company, L.P.

Trademark Notices

Adobe® is a trademark of Adobe Systems Incorporated.

Intel® and Itanium® are trademarks of Intel Corporation in the U.S. and other countries.

Microsoft®, Windows®, Windows® XP are U.S. registered trademarks of Microsoft Corporation.

Oracle and Java are registered trademarks of Oracle and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

Support

Visit the HP Software Support Online website at:

<http://www.hp.com/go/hpsoftwaresupport>

This website provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support website to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

Support Matrices

For complete support and compatibility information, see the support matrix for the relevant product release. All support matrices and product manuals are available here on the HP Software Support Online website:

http://h20230.www2.hp.com/sc/support_matrices.jsp

You can also download the *HP Server Automation Support and Compatibility Matrix* for this release from the HP Software Support Online Product Manuals website:

<http://h20230.www2.hp.com/selfsolve/manuals>

Documentation Updates

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<http://h20230.www2.hp.com/selfsolve/manuals>

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details. See Document Change Notes for a list of any revisions.

Product Editions

There are two editions of HP Server Automation:

- HP Server Automation (SA) is the Enterprise Edition of Server Automation. For information about Server Automation, see the SA Release Notes and the SA User Guide: Server Automation.
- HP Server Automation Virtual Appliance (SAVA) is the Standard Edition of Server Automation. For more information about what SAVA includes, see the SAVA Release Notes and the SAVA at a Glance Guide.

Document Change Notes

The following table indicates changes made to this document since the last released edition.

Date	Changes
May 20, 2013	Original version of this document for release with SA 10.0.
June 3, 2013	Corrections to Valid Strings and Integer Values for the --os Option on page 305. Added Table 29, Allowable Platform Family Name Strings and Integer Values for --os Option , to support new options for OS-independent and platform-family-level packages.

Contents

1	Getting Started with the SA Client	17
	Overview of the SA Client	17
	About the SA Client Launcher	18
	SA Client and SA Client Launcher Requirements	18
	Installing the SA Client Launcher	19
	Running the SA Client	20
	SA Client Launcher Advanced Options	21
	SA Client User Interface	23
	Menus	24
	Navigation Pane	25
	Search Pane	26
	Content Pane	26
	Views in the Content Pane	27
	Columns in the Content Pane	29
	Filter Tool in the Content Pane	30
	Details Pane	30
	Status Bar	32
	Sharing SA Client Objects with Drag and Drop	32
	Copy and Paste Table Data	33
	Searching for Objects with the SA Client	33
	Performing a Simple Search	34
	About Advanced Searches	35
	Performing an Advanced Search	35
	Running a Saved Search Query	37
	Deleting a Saved Search	38
	Setting SA Client Options	38
	General Options	39
	SA Agent Installation - Installer Options	40
	SA Agent Installation - Protocols	40
	SA Agent Installation - Advanced Options	41
	Terminal and Shell Options	42
	Patch Policy Options	44
	Network Automation Options	45
	HP Service Automation Visualizer (SAV) Options	45
	Virtualization Settings	45
	Scan Time-Out Preference	46
	Discovery Settings	46
	Reset All Settings	46
	Browsing Job Logs	46

Recurring Job Schedules	48
Viewing and Deleting Recurring Job Schedules	48
Job Notification Emails	48
Finding Information in Job Results	49
Combined Device History Log	51
2 Exploring the SA Library	57
About Server Resources in the SA Library	57
About Managing Folders	58
About Folders and Permissions	59
Creating a Folder	60
Setting Folder Properties	60
Copying a Folder	62
Deleting a Folder	62
3 Exploring Servers and Device Groups in the SA Client	63
Exploring Servers in the SA Client	63
Server Status Icons	64
Device Group Status Icons	67
VM Template Status Icons	67
Running Server Communication Tests	68
Ways to Use the Device Explorer	68
Network and Storage Devices in the Device Explorer	68
Device Explorer Interface	69
Device Explorer Views Tabs	70
Accessing the Device Explorer	70
Opening a Remote Terminal	71
Information About Servers	71
Summary of Server Information	71
Properties of Servers	72
Custom Attributes Defined for a Server	75
History of Server Changes	75
Server Location	76
Server Management Policies	76
Compliance	76
Audits	78
Software Policies	78
Patch Policies	78
Configured Applications	78
Relationships with Other Devices	80
Storage Relationships	80
Inventory of Server Information	80
Hardware	81
Network	81
Storage	82
Disks	83
Virtualization View	83

Snapshot Specifications	85
Installed Packages	85
Patches for the Server.	85
Files on the Server	87
Windows COM+ Objects.	90
Windows Registry	90
Services (Windows and Linux).	91
Discovered Software	91
Windows IIS Metabase.	91
Windows IIS 7.0	92
Internet Information Server (IIS)	92
Local Security Settings.	93
Registered Software	93
Runtime State.	94
Windows .Net Framework Configuration	94
Users and Groups	95
Basic Server Management Tasks	95
Refreshing Server Status	95
Deactivating a Server	96
Rebooting a Server	96
Opening a Remote Terminal	97
Changing User Passwords on Managed Servers.	98
About Device Groups	99
Characteristics of Device Groups.	99
Device Groups and Subgroups	100
Public Device Groups	101
Private Device Groups	101
Static Device Groups	101
Dynamic Device Groups	101
Ways to Create Device Groups.	102
About Static Device Groups.	102
Creating a Static Device Group	102
Adding a Server to a Static Device Group.	103
Removing Servers from a Static Device Group.	105
About Dynamic Device Groups	106
Creating a Dynamic Device Group	106
Recalculating the Members of a Dynamic Device Group	107
About Rules for a Dynamic Device Group.	107
Configuring Multiple Rules for Dynamic Device Groups	109
Adding Rules for a Dynamic Device Group.	110
Modifying Rules for a Dynamic Device Group	111
Converting a Dynamic Group to a Static Group.	112
More Device Group Tasks	112
Creating a Device Group Using Search.	113
Moving a Device Group.	114
Duplicating a Device Group	115
Deleting a Device Group.	116

Device Group Explorer	116
4 Installing and Managing Server Agents	123
Permissions Required for Server Discovery and Agent Installation	123
Installing the SA Agent	123
Discovering Agentless Servers	125
Upgrading the Server Agent	127
Setting Agent Installation Defaults	127
Starting and Stopping a Server Agent	127
Viewing Server Agent Information	128
Searching for Servers Based on Agent Information	128
Security for Agents Running on Managed Servers	129
Agent Functionality on Managed Servers	129
Software and Hardware Inventory	130
Server Information that the Agent Tracks	130
About Server Discovery and Agent Installation	134
Setting Agent Installation Actions for Each Server	134
Specifying Login Settings	134
Agent Installer Command	134
Reports on Server Status	135
Troubleshooting Agent Installation Errors	136
Viewing Unmanaged Server Information	136
Opening a Remote Terminal Session on an Agentless Server	137
Reports on Agent Installation	138
About Communication between the Server and the SA Core	139
Running Server Communication Tests	139
About Server Communication Tests	140
Types of Server Communication Test	140
Running Server Communication Tests - SA Client	140
Communication Test Results	141
5 Creating and Managing Customers	143
About Customers	143
About Customers and Facilities	143
Predefined Customers	144
Customer Security, Authorizations and Permissions	144
Permissions to Create, Delete and Modify Customers	145
Customer Tasks - SA Client	145
Assigning a Server to a Customer - SA Client	145
Creating a New Customer - SA Client	145
Viewing or Modifying a Customer - SA Client	146
Deleting a Customer - SA Client	146
6 Running SA Extensions	149
Methods of Running Extensions	149
Run Extensions on Managed Servers	150
Running Extensible Discovery on Managed Servers	153

Running Extensible Discovery from the OGSH	154
Adding Scripts to Extensible Discovery	154
Scripts Provided with Extensible Discovery	155
Software Policies Provided with Extensible Discovery	155
Writing Your Own Scripts for Extensible Discovery	156
Adding Your Own Scripts to Extensible Discovery	157
Upgrading Your Scripts in Extensible Discovery	159
Removing Your Scripts from Managed Servers	160
Output from Extensible Discovery Scripts	160
Comparing Custom Fields and Custom Attributes	161
About Custom Fields	162
Data Types in Custom Fields	162
Creating a Custom Field with the Custom Field Management Web Extension	163
Deleting a Custom Field with the Custom Field Management Web Extension	164
Editing Custom Field Values	165
Creating and Managing Custom Attributes	165
7 Getting Started with the SA Web Client	167
SA Web Client	167
Supported Browsers for the SA Web Client	167
Browser Configuration Requirements	167
User Interface	168
Requirements for Logging In	168
Overview of the SA Web Client User Interface	168
Search	173
My Servers	173
Mouseover Icon Tooltips	173
8 Server Tracking in the SA Web Client	175
Server Tracking	175
Ways to Locate, List, and Display Servers	175
Tracked Server Properties	175
Supported Operating Systems for Managed Servers	176
SA Server Agent Supported Operating Systems	176
Server Lists	179
Types of Server Lists	179
Server Pool	179
Manage Servers List	180
Filters on the Manage Servers List	181
My Servers	182
Overview of My Servers	182
Adding Servers to My Servers	182
Removing Servers from My Servers	183
Server Search	183
Searching for a Server By Using the Search Box	183
Ways to Use Search	184
Searching for Servers or Other Resources	184

Rules for Server Search and for Creating Dynamic Device Groups	188
Line Break Workaround for Server Search.	195
Conditions for Searching with Multiple Rules	195
Server Searching by IP Address	196
Example: Server Search	196
Searching for a Server Group.	197
Server Identification	198
Overview of Server Identification	198
Ways that Servers are Identified by HP Server Automation	198
Customer Accounts in SA.	199
Server Histories and Reports	200
Overview of Server History	200
Viewing Server History	201
Time Stamp for Server Operations	201
Hardware Information for Managed Servers	202
Viewing Managed Server Hardware Information.	202
9 Server Management in the SA Web Client	205
Overview of Server Management	205
Communication Between Managed Servers and SA	206
Network Address Translation (NAT) for Managed Servers	206
Key Terms of SA Managed Server Communication	206
Locating the Management IP Address of a Managed Server.	207
Setting the Primary IP Address of a Server	208
NAT Table Mapping and Managed Servers	208
Server Groups	209
Overview of Server Groups.	209
Types of Server Groups	211
Public Group Modeling	212
Server Groups Tabs	214
Ways to Create Server Groups	215
Creating Static Groups by Using the New Group Option	215
Creating Static Groups by Using the Copy to Group Dialog	217
Creating Dynamic Groups by Using the New Group Option	217
Creating Groups by Using Search	218
Criteria for Search and Dynamic Group Rules	219
Adding a Server to Static Groups, Both Public and Private	225
Adding a Server to Dynamic Groups, Both Public and Private	226
Removing Servers from Static Groups, Both Public and Private.	226
Removing Servers from Dynamic Groups, Both Public and Private	227
Moving Servers from One Static Group to Another	227
Duplicating Server Groups.	227
Rules for Deleting Server Groups	229
Server Life Cycle	229
OS Provisioning and the Server Life Cycle	230
Server Properties	232
Server Management Tasks Related to the Server Life Cycle.	236

Editing the Properties of a Server	237
Tasks Associated with Deactivating a Server	238
Deactivating a Server	238
Deleting a Server from SA	238
Server Use Categories and Deployment Stage Categories	239
Changing the Server Use and Deployment Stage Values for Servers	239
Server Management Jobs	240
My Jobs	240
My Jobs Display Information	241
My Jobs in the SA Web Client	241
Jobs in SA Client	241
Viewing Job Details in the SA Web Client	242
Viewing My Job Details from inside the SA Client	243
Server Management Scheduling and Notification	243
Time-Outs for Server Management Jobs	246
Custom Fields for Servers	246
Editing Custom Field Values	248
Custom Attributes for Servers	248
Managing Custom Attributes	249
Adding Server Custom Attributes	249
Editing Server Custom Attributes	250
Deleting Server Custom Attributes	250
Service Levels	251
Overview of Service Levels	251
Adding a Service Level to the SA Web Client	251
Editing a Service Level	252
Ways to View the Service Level for Servers	252
Assigning a Server to a Service Level	254
Removing a Server from a Service Level	254
Network Configuration	255
Overview of the Server Network Configuration	255
Configuring Networking for an SA Managed Server	256
10 Script Execution	259
Overview of Script Execution	259
Script Execution Features	259
Script Execution Process	260
Types of Scripts	260
Managing Scripts	261
Creating a Script	261
Opening a Script in the SA Client	264
Editing Script Properties	266
Viewing All the Software Policies Associated with a Script	266
Viewing Script Version History	267
Locating Scripts in Folders	267
Exporting a Script	267
Renaming a Script	268

Deleting a Script	268
Executing Scripts	268
Ways to Open the Run Script Window	268
Running a Server Script (Saved Script or Ad-Hoc Script)	269
Running an OGFS Script	277
11 SA Global Shell	281
Overview of the Global Shell	281
SA Global File System (OGFS)	281
Remote SA Shell (rosh) Utility	281
Benefits of the Global Shell	281
Commands Available in the Global Shell	282
Differences Between the Global Shell and Unix Shells	282
Server Filtering in the OGFS	283
Global Shell Tutorial	284
Global Shell Examples	289
Opening a Global Shell Session	289
Finding Servers in the OGFS	289
Getting Server Information from the OGFS	290
Browsing a Server's File System or Registry	291
Managing Custom Attributes	291
Copying Files Within the OGFS	291
Copying Files Between the OGFS and a Development Server	292
Logging on to a Managed Server With rosh	292
Running OGFS Scripts on Managed Servers With rosh	293
Running Native Programs on Managed Servers With rosh	293
Character Encoding for the OGFS	294
Terminal Application Configuration	294
Data that Cannot Be Displayed	295
LANG and LC_CTYPE Environment Variables	295
Transcoded Data in a Managed Server	296
Disabling the Transcoding of Managed Server Data	296
Global Shell Error Messages	297
Remote Terminal	297
Prerequisite for a Remote Terminal	298
Opening a Remote Terminal	298
12 SA Command Line Interface (OCLI)	299
Overview of OCLI	299
Permissions and Customers	299
Upload Verification	299
Encoding Options for OCLI	300
RPM Uploads	300
Passwords and Environment Variables	300
Upload Examples	300
Installing the SA Command-line Interface (OCLI)	300
OCLI Command Syntax	302

Options Common to oupload and odownload	302
Valid Strings and Integer Values for the --os Option	305
Options Only for the oupload Command	307
Options Only for the odownload Command.	309
A Troubleshooting Server Communication Tests	311
Command Engine to Agent (AGT) Test	312
AGT – OK	312
AGT – Untested	312
AGT – Unexpected error.	312
AGT – Connection refused	313
AGT – Connection time-out	313
AGT – Request time-out.	313
AGT – Server never registered.	314
AGT – Realm is unreachable	314
AGT – Tunnel setup error.	315
AGT – Gateway denied access	315
AGT – Internal Gateway error	315
AGT – Gateway could not connect to server	315
AGT – Gateway time-out	315
Crypto Match (CRP) Test.	316
CRP – OK	316
CRP – Untested.	316
CRP – Unexpected error.	316
CRP – Agent certificate mismatch.	316
CRP – SSL negotiation failure	317
Agent to Command Engine (CE) Test.	317
CE – OK.	318
CE – Untested	318
CE – Unexpected error	318
CE – Connection refused	318
CE – Connection time-out	318
CE – DNS does not resolve.	319
CE – Old Agent version.	319
CE – Realm is unreachable	319
CE – No Gateway defined.	320
CE – Tunnel setup error.	320
CE – Gateway denied access	320
CE – Gateway name resolution error	320
CE – Internal Gateway error	321
CE – Gateway could not connect to server	321
CE – Gateway time-out	321
CE – No callback from Agent	321
Agent to Data Access Engine (DAE) Test.	322
DAE – OK	322
DAE – Untested	322
DAE – Unexpected error	322

DAE – Connection refused	323
DAE – Connection time-out	323
DAE – DNS does not resolve	323
DAE – Old Agent version	323
DAE – Realm is unreachable	324
DAE – No Gateway defined	324
DAE – Tunnel setup error	324
DAE – Gateway denied access	324
DAE – Gateway name resolution error	325
DAE – Internal Gateway error.	325
DAE – Gateway could not connect to server	325
DAE – Gateway time-out	325
Agent to Software Repository (SWR) Test	326
SWR – OK	326
SWR – Untested	326
SWR – Unexpected error	326
SWR – Connection refused.	327
SWR – Connection time-out	327
SWR – DNS does not resolve	327
SWR – Old Agent version.	327
SWR - Server identification error	328
SWR – Realm is unreachable.	328
SWR – No Gateway defined	329
SWR – Tunnel setup error	329
SWR – Gateway denied access	329
SWR – Gateway name resolution error	329
SWR – Internal Gateway error	330
SWR – Gateway Could not connect to server	330
SWR – Gateway time-out	330
Machine ID Match (MID) Test	331
MID – OK	331
MID – Untested	331
MID – Unexpected error.	331
MID – MID mismatch.	331
Common Troubleshooting Tasks	332
Verifying that an Agent is Running.	332
Verifying that a Port is Open on a Managed Server	333
Restarting a Server Agent	333
Checking Management IP of a Managed Server.	333
Checking Network Gateway Configuration.	334
Resolving Host Name	334
B Agent Installation and Upgrade Utilities	337
Agent Install Command.	337
Overview of Agent Installation Using the CLI	337
The Agent Installer Command.	338
Preparation for Agent Installation	338

Checklist Before Installing the SA Agent	339
Installing an Agent	341
Augmenting the Information for a Managed Server	347
Uninstalling an Agent on Unix and Windows	348
Uninstalling Earlier Versions of Agents on Unix	349
Uninstalling Earlier Versions of Agents on Windows	350
Agent Upgrade - SA Client	350
Agent Upgrade Command	352
Ways to Upgrade Agents	352
Prerequisites for Using the Agent Upgrade Tool	353
Upgrading the Agent on Managed Servers	353
Commands for the Agent Upgrade Tool	354
Options for the Agent Upgrade Tool	356
Example: Options for the Agent Upgrade Tool	357
Example: Commands and Output for Agent Upgrade Tool	358
Agent Upgrade - SA Web Client	358
Upgrading Agents with the Agent Upgrade Custom Extension	359
C Global Shell Utilities Syntax	363
aaa Utility	363
aaa Syntax	363
aaa Usage Rules	364
aaa Examples	365
Global Shell Operations (Permissions)	365
rosh Utility	367
rosh Syntax	367
rosh Usage Rules	368
rosh Operations	369
rosh Examples	370
swenc Utility	371
swenc Syntax	371
swenc Usage Rules	371
D OGFS Directories	373
Directories in the OGFS	373
root (/) Directory	373
/opsw Directory	374
/opsw/Server Directory	375
/opsw/Server/@ Directory	375
/opsw/Server/@Facility Directory	377
/opsw/Server/@Group Directory	377
/opsw/Library Directory	378
Other Directories Under /opsw	378
/opsw/Application Directory	378
/opsw/Facility Directory	379
/opsw/Group Directory	380
/opsw/Library	380

/opsw/OS Directory	381
/opsw/Permissions Directory	381
/opsw/Realm Directory	382
/opsw/Script/Shared Directory	383
/opsw/ServiceLevel Directory	383
Network Directories	384
/opsw/Network Directory	384
/opsw/Network/@Group Directory	385
/opsw/NetModel Directory	385
/opsw/NetOS Directory	386
/opsw/NetType Directory	386
/opsw/Script/Network Directory	386
Index	387

1 Getting Started with the SA Client

Overview of the SA Client

The SA Client is a powerful Java client for the HP Server Automation (SA) system. It provides the look-and-feel of a Microsoft Windows desktop application with the cross-platform flexibility of Java.

The SA Client provides the following capabilities:

- Server Discovery and Agent Deployment
- Server Explorer
- Virtualization
- Audit and Remediation
- Compliance
- HP Service Automation Visualizer (SAV)
- Storage Visibility and Automation
- Software Management
- Patch Management for Windows
- Patch Management for HP-UX
- Patch Management for Unix
- Patch Management for Solaris
- Application Configuration Management
- Global Shell
- NA/SA integration



To visualize networking information with Network Automation (NA) inside of HP Service Automation Visualizer (SAV), you must have both a licensed version of NA integrated with your SA core, plus an additional license to run SAV showing NA data.

To visualize storage data in the SA Client, your SA core must be configured to connect to Storage Essentials (SE). For information, see the *SA User Guide: Storage Visibility and Automation*.

About the SA Client Launcher

The SA Client Launcher allows you to run the SA Client and connect to any of your SA cores. The SA Client lets you view, automate, and manage the devices in your data center.

The SA Client Launcher is a self-contained Java application that allows you to access the SA Client from any core in your mesh. You can use the SA Client Launcher to log in to and download the latest version of the SA Client. If the SA Client has been upgraded on a specific core or on a core in a different mesh, you can choose which core you would like to use for downloading the SA Client.

You also have the option of choosing which core you want to use to download the latest version of the SA Client, separate from the core you log in to. For example, when you log into a core and that core has a new version of the SA Client, the new version will automatically be downloaded when you log in. Using the launcher, you can choose one core to log in to and a separate core to download the latest client. This gives you the freedom to not have to download the SA Client every time you log into a different core.

The SA Client Launcher also allows you to configure advanced settings, such as debug settings, locale settings, proxy server settings, and more. See [SA Client Launcher Advanced Options](#) on page 21.



If you are running the SA Client Launcher on Windows 2000, you may see a missing DLL error message when you log on. This error will not affect the log on procedure. To fix this so the error message does not appear, install this Microsoft update:

<http://support.microsoft.com/default.aspx?scid=kb;en-us;259403&Product=vc6>.

SA Client and SA Client Launcher Requirements

The SA Client is a Java application that installs and runs with its own Java Runtime Environment (JRE). The SA Client will not interfere with any other JRE versions installed on your system. The JRE will not be used (and is not usable) by any other Java application on the target computer, and it will not set itself as the default JRE on the target computer.

The SA Client is supported on the following Microsoft operating systems:

- Windows Server 2003
- Windows 2000
- Windows XP
- Windows Vista
- Windows Server 2008
- Windows 7

The minimum system requirements to run the SA Client are as follows:

- 1 GB of DRAM.
- 0.5 GB of disk space each for the SA Client and the SA Client Launcher.
- If using the SA Client to connect to a core with a residential DSL connection, a minimum 384 Kbps connection is recommended.
- You must be logged in as a user with sufficient permissions to install software on the computer. (You do not need to be an administrator user to install the launcher).

- Ensure that there are no running instances of the Launcher (if necessary, use the Windows Task Manager and kill all instances of `javaw.exe`).

You must download and install the SA Launcher (see the download link on the SAS Web Client Main Page). In order to install the launcher, you must be a Windows user that has permission to install applications on your system.



If you are upgrading, you must uninstall the previous SA Client Launcher version (using the Windows uninstall utility), and install the latest version.

Installing the SA Client Launcher

To run the SA Client, you first need to download and install the SA Client Launcher, which is a Java application that allows you to access the SA Client from any core in your mesh. When you install the SA Client Launcher, it installs all of the necessary Java applications (Java Web Start and JRE) you need to run the SA Client.


If you are upgrading, you will need to do the following:

- a Uninstall the previous version of the SA Client Launcher using the Windows uninstallation utility.
- b Ensure that there are no running instances of the Launcher.
- c Install the latest SA Client Launcher version, as described below.

To install the SA Client Launcher, perform the following steps:

- 1 Open any web browser and enter the URL to any SA core server. This displays the SA Web Client login page along with a link to download the SA Client launcher, as shown in Figure 1.

Figure 1 Downloading the SA Client Launcher




- 2 On the SA Web Client login page, click the Download Hewlett-Packard Launcher link.
- 3 Save the SA Client Launcher installation file. The installation file is typically named `hp_bsa_launcherinstaller_windows_x_x_x.exe`.
- 4 Locate and double-click the installation file to start the SA Client Launcher installer.
- 5 Follow the installation instructions.

Running the SA Client

To run the SA Client, perform the following steps:

- 1 Start the SA Client from one of two locations:
 - On your desktop, double-click the Server Automation Client icon.Or
 - From the **Start** menu, select † **All Programs** † **HP Business Service Automation** † **HP Server Automation Client**
- 2 The first time you log in to the SA Client, at the login window, enter the username `admin` and the password `opsware_admin`, and the IP address for the SA core server you want to log in to, as shown in [Figure 2](#). You will be asked to change the admin password.

Figure 2 SA Client Login Window



The user name is not case sensitive. If you have access to more than one core server in a mesh, you can enter the core server's IP address or name in the core server field. If you do not specify a port with the host:port notation, port 80 is used to download the SA Client.

If this is the first time you are logging in to a specific core, the launcher will download the latest version of the SA Client when you log in. If you would like to differentiate between the core you log in to and the core from which you download the latest version of the SA Client, you can change those options by clicking **More** in the log in window and configuring your Client Host Server. For information on this and other advanced SA Client Launcher options, see [SA Client Launcher Advanced Options](#) on page 21.

- 3 Click **Log In**.
- 4 If you are asked to accept the certificate from the core server, click **Yes**. The SA Client appears.

If the SA Client does not appear, check your proxy settings and other settings. See [SA Client Launcher Advanced Options](#) on page 21.

SA Client Launcher Advanced Options

You can configure the following advanced options for the SA Client:

- **Debug Settings:** Gives you control over the level of detail as well as the type of information included in SA Client log file.
- **Client Download Server:** Allows you to change the host server from which you want to download the SA Client.
- **Proxies:** Allows you to configure the SA Client proxy server settings.
- **Server Automation Home:** Allows you to change the default location SA Client is downloaded and saved on your local computer, and to delete the SA Client's cache, and to change the location of SA Client log files.

To configure the SA Client Launcher's advanced options, perform the following steps:

- 1 Start the SA Client Launcher from one of two locations:
 - On your desktop, double-click the SA Client Launcher iconOr
 - From the **Start** menu, select † **All Programs** † **HP Business Service Automation** † **HP Server Automation Client**
- 2 In the Log In to Server Automation window, you can set the following configuration:
 - **Username:** Enter your SA username.
 - **Password:** Enter your SA user password.
 - **Core Server:** Choose the SA core server to log in to.
- 3 Select the **More** button. In the expanded launcher window you can configure the following settings:
 - **Locale:** Select the version of the SA client to match your system's locale. English (en) is the default, but you can also select either Japanese (ja) or Korean (ko).

Note that this locale setting is only used on cores previous to SA version 9.10. As of SA version 9.10 this setting is ignored and the setting in the user profile is used instead. For complete information on setting the locale in the user profile for each individual user, see the *SA Administration Guide*.
 - **Debug Settings:** Debugging options that are captured in the following log file:
`<user_home>\Application Data\HP BSA\deployment\log\javaws*.log`
 - **Enable Debug Logging (Fine):** Enables debugging and sends SA Client operations and errors to the log file.
 - **Enable Server Method Call Logging:** Adds server method calls to the log file.
 - **Show Console:** Displays the Java Console window while the SA Client runs.
- 4 Click **Advanced Settings**.
- 5 In the Advanced Settings window, you can configure the following SA Client Launcher options:

Client Download Server

You can configure the SA Client Launcher so the default core you log in to is different from the core you use to access the latest version of the SA Client. This can be useful if you do not want to download a new version of the SA Client each time you log in to a different core running the same version of SA.

- **Use Core Server:** Select this option to download the SA Client from the same server you want to log in to.
- **Use:** Enter a core server you want to use to download the SA Client.



The SA Client uses two ports: port 80 to download the SA client; port 443 to connect to the core specified in the main log in window. If you select the Use Core Server option, the connect port (443) cannot be overridden. If you select the Use option, the download port (80) can be overridden in the Use field and the connect port can be overridden in the Core Server field in the main log in window.

If you do not specify a port with the host:port in the Use field, port 80 is used to download the SA Client. In the Core Server field in the main log in window, if you do not specify a host:port, then port 443 is used to connect to the core.

Proxies

By default, the SA Client uses the proxy server settings configured for the default browser on your local system. For example, if your default browser has no proxy server settings configured, neither will the SA Client. You can change those proxy server settings here:

- **None:** Do not use a proxy server to connect to the SA Client.
- **Use Browser:** Use the proxy server settings specified in your default browser.
- **Manual:** Enter the proxy server hostname and port.
- **No Proxy Hosts:** If you want to add proxy server overrides, add them here, separated by commas. (This is only enabled when proxy server settings is set to Manual.)

Server Automation Home

- **Location:** The location where the SA Client is downloaded and saved on your local computer, along with all log files generated when the SA Client runs.

Note that starting with SA 7.50, this location also controls where the SA Client data cache is stored.



The default home location is <user_home>\Application Data\HP BSA, which is private to each user. If you choose to change this location, be aware that other users may have access to the new directory. You are responsible for setting the permissions on the new directory if you want to prevent unwanted access to your SA Client home.

- **Delete Application Cache:** Clicking this completely removes all downloaded copies of the SA Client. This ensures the launcher will download the latest SA Client from the core the next time the user logs in.
- **Delete Logs:** Delete all log files created by previous sessions of the SA Client. (All SA Client log files are located at: <user_home>\Application Data\HP BSA\deployment\log\javaws*.log)


- 6 When you are finished setting the options, click **OK** to save your settings.
- 7 Click **Log In** to log in to the SA Client.

SA Client User Interface

The SA Client user interface has six main areas as shown in Figure 3.

- Menus
- Navigation Pane
- Search Pane
- Content Pane
- Details Pane
- Status Bar

Figure 3 SA Client User Interface



Menus


The SA Client includes the following menus:

- **File:** This enables you to open a new SA Client window, or close the current window, or exit all open SA Client windows.
- **Edit:** This enables you to cut, copy, paste, delete text, and copy SA Client URLs.
- **View:** This refreshes the current view and shows the latest information from the core that you are currently logged into (such as compliance test information for the compliance dashboard). You can also access SA Client features in the Navigation pane, such as Devices (groups of devices, managed and unmanaged servers), Reports (Compliance Dashboard, Reports) Software Library (application configuration, patch management), OS sequences and OS installation profiles, Jobs and Sessions (job logs and shell sessions), and Administration (patch settings and patch compliance rules). This also allows you to show or hide the Search pane and the Details pane.
- **Tools:** This enables you to open a Global Shell session, open the HP Service Automation Visualizer, or access the SA Client options.
- **Window:** This enables you to access multiple instances of SA Client windows, if more than one window is open.
- **Actions:** Depending on the feature that you have selected in the Navigation pane, this menu enables you to perform numerous functions related to all main SA Client features.
- **Help:** This menu provides help for the SA Client. Help F1 provides context-sensitive help relevant to the current feature window selected or opened (same as pressing the F1 key). The contents and index will open the SA Client help system to the main table of contents. (The About SA Client menu provides version and system information.)

Navigation Pane

The Navigation pane shown in [Figure 4](#) shows the tabs in the SA Client navigation pane. Each tab gives you access to one of the major areas of the SA Client. When you select an object, its contents appear in the top of the navigation pane and in the content pane. You can perform tasks related to the object with the right click menu and the Actions menu.

Figure 4 SA Client Navigation Pane




Search Pane

The Search pane allows you to search for any information in HP Server Automation, such as servers, device groups, folders in the SA library, jobs, software and software policies, patches and patch policies, application configurations, database and storage systems, audits, and snapshot results.

You can show or hide the Search pane by selecting the **View > Search Pane** menu item.

For more information on how to use the search tool, see [Searching for Objects with the SA Client](#) on page 33.

Figure 5 Search in the SA Client




Content Pane

Depending on the selection in the Navigation pane – Devices, Virtualization, Library, Reports, Jobs and Sessions, Administration – the Content pane lists the following information:

- All managed servers and device groups, including agentless servers — both physical and virtual
- Virtualization Services and the virtualization inventory under them
- Agent installation information
- Application Configurations and configuration templates
- Software Policies
- Storage objects and their attributes
- Audit and Remediation audits, audit policies, and snapshots
- Patches and patch policies
- OS installation profiles and OS sequences
- Packages
- Reports and the Compliance Dashboard
- Custom attributes
- Jobs that the user has run
- Access to the Global Shell sessions
- Patch configuration and patch compliance rules

[Figure 6](#) is an example of the Content pane for managed servers. You can perform actions on features in the Content area using the Action Menu, or you can right-click to perform various actions or double-click to open.

Figure 6 Content Pane Showing the Server History View




Views in the Content Pane

With the View drop-down list in the SA Client content pane, you can change the view of a selected feature. For example, you can select a server from the Content pane, and then from the View drop-down list, choose Software Policies. This shows all software policies attached to

the server, as shown in [Figure 7](#).

Figure 7 View Drop-down List




Columns in the Content Pane

You can click the column headings of the Content pane to sort data about a server. For example, for a managed server, you can sort by Hostname, IP address, Summary, OS, and so on. You can sort by additional columns by pressing the Ctrl key on the keyboard while clicking another column.

You can display more columns of information about the selected server by clicking the column selector and choosing the columns you want to display or hide, as shown in [Figure 8](#) below.


Figure 8 Column Selector - Columns Displayed for Each Server



Filter Tool in the Content Pane

With the SA Client filter tool, you can filter the information shown on the content pane by filtering on a single column with a substring search, as shown in [Figure 9](#) below.

Figure 9 Filter Tool



Details Pane


The Details pane allows you to preview information about servers, device groups, patches, and patch policies selected in the Content pane without having to open a new window.

You can use the Details pane to perform the following actions:

- Preview information about a server, device group, patch, or patch policy. To do so, select it in the Content pane.
- Select the type of information you view in the Details pane. From the top of the content area, choose a view from the View drop-down list.
- Deactivate the Details pane. To do so, from the **View** menu, select **Details Pane † Minimize**.

For example, if you are viewing Windows 2003 patches from the Library, you can select a patch in the Content pane and see information about the patch in the Details pane. This is shown in [Figure 10](#).

Figure 10 SA Client Showing Package Contents View in the Details Pane




To view other types of information about the selected patch, from the View drop-down list, choose a view.

Details Pane Show Filter

Some features displayed in the Details pane allow you to further filter the feature. Using the Show drop-down list, you can choose different views of the feature.

For example, if you are viewing all of the servers that the patch policy is attached to, in the Details pane, you can filter either Servers with Policies Attached or Servers with Policies Not Attached, as shown in [Figure 11](#).

Figure 11 Details Pane Show Drop-down List




Status Bar

At the bottom of the SA Client window, the status bar provides the following information:

- Information about the selected object
- A progress bar that shows progress on retrieving information from the core
- Your user ID
- The current time

Figure 12 SA Client Status Bar



Sharing SA Client Objects with Drag and Drop

You can easily drag and drop servers and other SA Client objects out of the SA Client and into an email, a chat window, or a document editor. When you drag an object out of the SA Client, a URL is constructed that enables you to launch the object in the SA Client.

You can share such SA Client objects as servers, application configurations, audits, a Business Application, Patch Policies, OS Profiles, and more — basically, any device (server, storage, network, and so on) or any object from in the SA Library that is searchable.

You can also use the URL that is created during drag and drop as a link on a web page, which gives you easy access to those SA objects you are most interested in.



In order to drag and drop networking devices from the SA Client, you must have a licensed version of Network Automation (NA) integrated with your SA core. Additionally, in order to drag and drop storage devices from the SA Client, SA core must be configured to connect to SE. For more information, contact your HP sales representative.

To drag and drop a SA Client object, perform the following steps:

- 1 From inside the SA Client, select a server, network or storage device, device group, Patch Policy, a Business Application, an audit, or any other object in a table.
- 2 CTRL+drag the selected object to one of the following locations:
 - Document editor
 - Chat window text entry box
 - Email
- 3 When you or another user clicks the link, you are asked to open or save the file. After the file is downloaded and saved, click **Open**.
- 4 In the Log In to Server Automation window, enter your SA user name, password, and the SA core server you want to log in to and click **OK**.

If the SA Client is already opened, and the object you are opening belongs to the core you are logged into, the object appears in its own window without requiring you to log in.

Besides CTRL+drag, you can also use the **Edit** † **Copy** menu, or SHIFT+CTRL+C to copy the link into the Windows clipboard, and then paste it into another application.

Copy and Paste Table Data

In this release, you can copy and paste data from tables inside the SA Client into other applications. For example, if you are viewing a list of managed servers, Windows Audits, Solaris 10 patches stored in the SA Client Library, or jobs scheduled to run in the next month, you can select one or more rows in the list, and then copy and paste them into a text file, email message, spreadsheet application, or other document processor.

The following restrictions to this capability:

- Column headings for a list are not selectable. This means that they are always copied.
- Values in the copied list might appear differently when pasted into a target application, depending on how the target application renders tables.
- The target application must understand a table description either in HTML format (with mimetype “text/html”) or as a tab/newline delimited string (with mimetype “text/plain”)

To copy and paste table data in the SA Client, perform the following steps:

- 1 From inside the SA Client, browse to the table that you want to copy.
- 2 Make sure that the application you want to paste the data into is open.
- 3 Select the rows you want to copy.
- 4 To copy the rows, perform one of the following actions:
 - d Press CTRL + C.
 - e From the **Edit** menu, select **Copy**.
 - f Use the cursor to drag the rows.
- 5 In the application you want to paste this data into, place the cursor and press CTRL + V or drop the rows if you are dragging them with the cursor. The data is copied.

Searching for Objects with the SA Client

In the SA Client, you can search for objects in your operational environment including physical and virtual servers, application configurations and templates, audits, business applications, device groups, SA extensions, folders, jobs, scripts, packages, patches, patch policies, snapshots, software policies, and many other objects.



To search for storage devices in the SA Client, your SA core must be configured to connect to Storage Essentials. For more information, contact Support.

With the SA Client search you can:

- Perform a simple search by using keywords.
- Perform advanced searches by creating search queries.
- Save and reuse search queries.
- Perform various actions based on search results.
- Email search results.
- Print search results.

- Customize the formatting of your search results.

Performing a Simple Search

A simple search locates objects containing the text you entered.





The search operation returns only items on which you have at least read permissions. To perform an action on an item, you must have write permission on that item. For more information on permissions, see the *SA Administration Guide*.

To perform a simple search, perform the following steps:

- 1 If the Search pane is hidden, select the **View > Search Pane** menu.
- 2 From the drop-down list in the Search Pane, select the type of object you want to search for, such as Software Policy, as shown in [Figure 13](#).

Figure 13 Simple Search in the SA Client



- 3 Enter the search text in the text field. The text field does not support wildcards and the search is not case sensitive.
- 4 Click  to perform the search. The results appear in the Content pane.
- 5 (Optional) Click on any column heading to sort the search results. You can also change the order of the columns by dragging the column heading and dropping it in the desired location.
- 6 (Optional) Click **Save** to save your search query. The Save As dialog appears. Enter the name of the search and then click **Save**. The name of the saved search cannot exceed 64 characters. See [Creating a Device Group Using Search](#) on page 113 for more information about saving a search query as a device group.
- 7 (Optional) Click **Export** to export search results to a csv or html file. The Export Results window appears. Enter the location, file name, and file type and then click **Export Results**.
- 8 (Optional) To perform an action on the search results, select an item from the Content pane and then from the **Actions** menu, select the appropriate action.

About Advanced Searches

With advanced search you can create complex search queries. You can specify multiple search rules and combine each rule with a logical “And” or logical “Or” operator. You cannot use both the “And” and “Or” operator in a single search query.



You can create more complex logical expressions using the SearchService interface in the com.opsware.search package of the SA Twister API. For more information on the SA Twister API, see the *SA Platform Developer Guide*.

Each rule is a combination of an attribute, operator, and value that enables you to search for a specific attribute value for the selected search item. Depending on the attribute that you select, the options for the operator and value are displayed. You can specify the attribute values by entering text or a numerical value in the text field, by selecting a value from the drop-down list, or by selecting multiple values from a list of values in the Select Values window.

The Select Values window appears when you need to specify multiple values for a rule containing an “equals” or “not equals” operator. In this window, you can select one or more values from a list of available values.

Format of Advanced Search Rules

Advanced search rules take the following form:

Search for: **<Item>**

Where: **<Attribute> <Operator> <Value>**

- **<Item>** is the object you are searching for, such as servers, patches, patch policies, storage devices, jobs, folders and other items in your managed environment.
- **<Attribute>** is data about the item you want the rule to examine.
- **<Operator>** is a comparison you want to perform between the **<Attribute>** and the **<Value>**.
- **<Value>** is the specific data you want to compare to the **<Attribute>** using the **<Operator>**.




The search operation returns only items on which you have at least read permissions. To perform an action on an item, you must have write permission on that item.


Performing an Advanced Search

To perform an advanced search, complete the following steps:



- 1 If the Search pane is hidden, select the **View > Search Pane** menu.
- 2 From the SA Client navigation pane, select **Advanced Search**. The Advanced Search page appears in the Content pane.
By default, the Search For “Server” item is selected in the first drop-down list and one search rule is added to the search.
- 3 From the Search For drop-down list, select the type of object you want to search for. [Figure 14](#) shows “Server” as the item to search for.

Figure 14 SA Client Search




- 4 Create a rule by selecting the attribute from the first “Where” drop-down list. The figure above shows “Agent Discovery Date” as the search attribute. Depending on the attribute that you select, the operators and values for the rule will change.
- 5 Select the operator from the second “Where” drop-down list. The operator selected defines how the search text is treated. [Figure 14](#) shows “Equals” as the operator.
- 6 Enter a value in the field or select a value from the drop-down list or click  to select one or more values from the **Select Values** window. [Figure 14](#) shows “02-04-09” as the value for the Agent Discovery Date.

The example in [Figure 14](#) will search for all servers on which the agent discovery date is Feb 4, 2009.

- 7 (Optional) Click  to add rules and repeat steps 3 to 5.
- 8 (Optional) Click  to delete any rules.
- 9 Select the Logic (logical And or logical Or) to be applied to the rules in the query.
- 10 Click **Search** or press Alt-S to run the search query. The search results appear in the Content pane.

[Figure 15](#) shows a search for all servers with unreachable agents that are running Red Hat Linux AS 3, with the Server Lifecycle value set to “Managed”.

Figure 15 Server Search Results for Servers with Unreachable Agents



- 11 (Optional) Click **Reset** to clear the search query rules or click **Cancel** to cancel the search operation.
- 12 (Optional) Click on any column heading to sort the search results. You can also change the order of the columns by dragging the column heading and dropping it in the desired location.
- 13 (Optional) Click **Save** to save your search query as a csv or html file. The Save As dialog appears. Enter the name of the search query and click **Save**. The name of the saved search cannot exceed than 64 characters. The saved search query appears in the Saved Searches drop-down list. See [Creating a Device Group Using Search](#) on page 113 for more information about saving a search query as a device group.
- 14 (Optional) Click **Export** to export search results to a csv or html file. The Export Results window appears. Enter the location, file name, and file type and then click **Export Results**.
- 15 (Optional) To perform an action on the search results, select an item from the Content pane and then from the **Actions** menu, select the appropriate action.

Running a Saved Search Query

To run a saved search query, perform the following steps:

- 1 If the Search pane is hidden, select the **View > Search Pane** menu.
- 2 From the Saved Searches drop-down list, select a search query. The query appears in the Advanced Search Content pane. The query is automatically executed and the search results appear in the Content pane.

Deleting a Saved Search

To delete a saved search query, perform the following steps:

- 1 If the Search pane is hidden, select the **View > Search Pane** menu.
- 2 From the Search pane, in the Saved Searches drop-down list, select a search query that has been previously saved. The saved search is displayed in the Advanced Search Content pane.
- 3 Click **Save** to display the Save As dialog box.
- 4 Select the saved search, right-click, and then select Delete.
- 5 In the “Delete existing search” dialog box, click **Delete**.
- 6 Click **Cancel** to exit the Save As dialog box.

Setting SA Client Options

You can configure the following options for the SA Client:

- **General Options:** This enables you to set options such as choosing the core you want to log into by default, how to handle caching, and so on.
- **SA Agent Installation - Installer Options:** This enables you to change the default behavior when installing server agents on your servers. The server agent enables SA to manage your servers. For more information, see [Installing and Managing Server Agents](#) on page 123.
- **Terminal and Shell Options:** This enables you to configure your Terminal (UNIX) and RDP (Windows) client for the Global Shell and Remote Terminal connections.
- **Patch Policy Options:** This enables you to specify that a confirmation message will display when you try to remove a patch policy or a patch policy exception from a managed server.
- **Network Automation Options:** This enables you to reset the name of the NA host that you log into, restore the previously saved (default) host name, and launch the NA login window.
- **HP Service Automation Visualizer (SAV) Options:** This enable you to specify timeout values for launching SAV and the manner in which you want SAV to scan virtual server relationships.

To set SA Client options, perform the following steps:

- 1 In the SA Client, select the **Tools** menu, then select **Options**.
- 2 From the left side of the Set Options window, choose a view.
- 3 From the right side of the Set Options window, modify the desired setting.
- 4 Select the Save button.

General Options

The following general options enable you to select your default core:

Core Server Defaults

Specify the port number of the SA Web Client host that you log into by default. The default port is 443.

Cache

This option enables you to configure the caching of data displayed inside the SA Client. You can configure the following cache settings:

- **Check for updates every <xx> minute(s):** This enables you to enter a value for how many minutes will lapse before the cache is refreshed.

Enter a time interval for how often you want the SA Client to check the core for new compliance information. This check applies to all information accessed from the core by the SA Client, not just to compliance information. A longer interval increases the likelihood that the information you are viewing is out of date. A shorter interval increases network traffic flowing to and from your core—this means you are viewing more recent information. For more information, see the *SA User Guide: Audit and Compliance*.

- **Update Cache:** This enables you to check instantly for new information from the core.
- **Reload Cache:** This enables you to immediately reload (refresh) the cache.

Progress Information

Check this option to show the progress of a job. When a job finishes, the Progress window closes.

'Equals' Operator Limit in Search and Reports

This sets limits on the number of available value selections in the Advanced Search and Reports interfaces. To prevent delays and excessive system load, the list of available values is not populated when the number of values exceeds this setting. Values are added by entering them in a text box.

Client Default View

Specify which client you want to be the default view, the SA Client or Application Deployment. See also the *SA User Guide: Application Deployment Manager*.

SA Agent Installation - Installer Options

In the SA Agent Installer Options pane, you can set options for the installation of a server agent on a server. The Installer Options window enables you to perform the actions listed below.

For more information on installing the agent on servers, see [Installing and Managing Server Agents](#) on page 123.

- **Start the Agent after installation:** This enables you to start the Server Agent after installing it on the server. By default, the Agent Installer does not start the server Agent.
- **Ignore prerequisite check failures:** This enables you to ignore prerequisite check failures and forces server Agent installation.
- **Set the server's time from the HP Server Automation Core:** This enables you to synchronize the time on the server in which the Server Agent is installed with the SA core.
- **Install Windows Installer (MSI) if required:** This enables you to install MSI along with the Server Agent. If MSI is already installed, this option has no effect.
- **Reboot Windows servers after agent installation if warranted:** This enables you to reboot Windows servers after the Server Agent installation is complete.
- **Install Red Hat Package Manager (RPM) on AIX and Solaris:** This enables you to install the RPM handler with the Server Agent. SA recommends that you always include this option when you install Server Agents on Solaris and AIX servers.
- **Reset agent configuration, if present:** This enables you to replace the existing Server Agent configuration.
- **Delete gateway address list, if present:** This enables you to delete the SA Gateway address list, if present and no longer required.
- **Overwrite staged Server Agent installer:** This enables you to overwrite the existing Server Agent Installer.
- **Log Level:** This enables you to set the log level for log messages. With this option, you can specify levels for Errors, Warnings, Info, and Trace.

SA Agent Installation - Protocols

In the SA Agent Installation Protocols pane, you specify the standard port to use to connect to the servers for deployment.

For more information on installing the agent on servers, see [Installing and Managing Server Agents](#) on page 123.

- **SSH:** This enables you to determine the standard port to connect to the servers for deployment using the SSH protocol.
- **Rlogin:** This enables you to determine the standard port to connect to the servers for deployment using the Rlogin protocol.
- **Telnet:** This enables you to determine the standard port to connect to the servers for deployment using the Telnet protocol.
- **SMB over NetBT:** This enables you to determine the standard port to connect to the servers for deployment using the Server Message Block over NetBT protocol.

- **WTS:** This enables you to determine the standard port to connect to the servers for deployment using the WTS protocol.

SA Agent Installation - Advanced Options

The SA Agent Installation Advanced options pane allows you to set the options listed below.

For more information on installing the agent on servers, see [Installing and Managing Server Agents](#) on page 123.

- **Immediately do a full hardware registration:** This enables you to force the Server Agent Installer to report full hardware information to the core.
- **Immediately do software registration:** This enables you to force the Server Agent Installer to report full software information to the core.
- **Suppress agent reachability check:** This enables you to disable this check during installation. By default, the installer triggers the core to check whether the server is reachable.
- **Disallow anonymous SSL connections if agent is dormant:** This enables you to configure the Server Agent so that browsers cannot connect without a valid certificate.
- **Force creation of new device record if conflict found:** This enables you to suppress this functionality. During registration, the Data Access Engine creates a new device record.
- **Fail if initial hardware registration fails (do not go dormant):** This enables you to ensure that the Server Agent does not become dormant, if it fails to report hardware information.
- **Do not open Windows Firewall for core-agent communications:** By default, the Server Agent Installer will modify the Windows Firewall configuration on Windows XP and Windows 2003 (r2) servers to allow the SA core to contact the managed server on port 1002. If you select this option, the firewall configuration will not be modified. In this case, the server might not be manageable by SA.
- **Remediate Software Policies:** This enables you to remediate the server against any software policies that are attached to the server.
- **Attach to Software Policy ID:** This enables you to attach the server to the software policy ID.
- **Extra installer options:** This enables you to specify any other installer options, such as:
 - `--log file <path>` allows you to specify the path to the installer log file. By default, the installer log files are placed in the `/tmp` on Unix or `%SYSTEMDRIVE%\WINDOWS\SYSTEM` on Windows.
 - `--workdir <path>` allows you to specify the path to the working directory to use while the installation is in progress.
- **Core certificate fingerprint:** Specifies the fingerprint of the core certificate.

If you specify a value for this option, the agent installer will verify that the Certificate Authority certificate used to sign the core's SSL certificate matches the value you provided. Specifying a value for this option increases security during the agent installation process by ensuring that the agent attaches itself to the correct core.

To obtain the correct value for the core certificate fingerprint option, log on to the core as root (you may need to have an SA System Administrator perform this task for you) and run the following command:

```
/opt/opsware/bin/openssl x509 -in /var/opt/opsware/crypto/agent/  
opsware-ca.crt -fingerprint -noout
```

The output looks like the following:

```
SHA1 Fingerprint=D2:3B:F8:72:B9:55:0D:  
DE:97:04:D5:C2:A5:6B:B2:09:5C:0A:0D:7F
```

The fingerprint is the string of hexadecimal numbers following the equal sign:

```
D2:3B:F8:72:B9:55:0D:DE:97:04:D5:C2:A5:6B:B2:09:5C:0A:0D:7F
```

- **nmap parameters:** This option allows you to specify parameters used when scanning for unmanaged servers, and to specify a different set of scan parameters if you find that SA is unable to locate and identify unmanaged servers due to network firewall configuration in your environment. The default values for the NMAP scan parameters in the SA Client can be set in the System Configuration menu by choosing the Opsware/adh product, and editing the contents of the `adh.scan.default_parameters` configuration parameter.

Terminal and Shell Options

These settings define the command that the SA Client invokes on your PC to open a Global Shell or start a remote terminal session. (For instructions on using an `ssh` client instead of the SA Client, see [Opening a Global Shell Session](#) on page 289.) See also [Opening a Remote Terminal Session on an Agentless Server](#) on page 137.

To view and change terminal and shell settings, perform the following steps.

- 1 In the SA Client, select the **Tools † Options** menu item. This displays the Set Options window.
- 2 In the View pane, select **Terminal and Shell**. This displays the commands that will be used when connecting to managed and unmanaged servers.

The following sections describe how the terminal and shell settings are used and how to set them.



In order to use remote login capabilities to access unmanaged servers using the Secure Shell (`ssh`) or Remote Login (`rlogin`) protocols, you will need to install a client program capable of communicating via these protocols. Once you have installed these programs, you must configure the SA Client to invoke those programs.

Terminal Client Command

This setting specifies the terminal client that the SA Client uses for remote terminal sessions on Unix managed servers, on unmanaged servers using `telnet` and for Global Shell sessions. This setting is used when you select a managed Unix server and select **Actions † Open With † Remote Terminal**. It is also used when you select an unmanaged server and select **Actions † Log in with † telnet**. It is also used when you run the Global Shell using **Tools † Global Shell**. The default value is:

```
cmd /c start /w cmd /c "(telnet %h %p || echo > nul) && echo %m && pause > nul"
```

The `telnet` program emulates a command-line terminal session. The `%h` represents the host and the `%p` is for the port number. See [Table 1 "Variables for the Terminal, RDP, Rlogin and SSH Client Options"](#) on page 44.

If you change the Terminal Client setting from the default value, make sure that the command blocks until the terminal application terminates. The terminal application must not run in the background. If you specify `cmd /c start`, include the `/w` switch to make `cmd` block until the underlying command (such as `telnet`) completes.

You are not required to use `telnet` as the terminal application. For example, you could use `putty`, the free Windows application that supports SSH, `rlogin` and `telnet`. To use a `putty` client, you could specify the following command:

```
"C:\\Program Files\\putty\\putty.exe" -telnet %h %p
```

RDP Client Command

This setting specifies the Remote Desktop Protocol (RDP) client that the SA Client uses for remote terminal sessions on Windows managed servers and unmanaged servers. This setting is used when you select a managed Windows server and select **Actions † Open With † Remote Terminal**. It is also used when you select an unmanaged server and select **Actions † Log in with † Windows Terminal Services**. The default value is the Microsoft Terminal Services Client:

```
mstsc "%r"
```

The specified terminal client must be installed on your PC. To verify the existence of the terminal client, click the **Test** button.

The command can include variables such as `%h` and `%p` representing the host name and port number, respectively. When the terminal client is launched, these variables are replaced with the values shown in [Table 1 "Variables for the Terminal, RDP, Rlogin and SSH Client Options" on page 44](#). To override a replacement value, specify a constant instead of a variable. For example, you might specify `435` for the port instead of `%p`.

Rlogin Client Command

This setting specifies the terminal client and configuration settings that the SA Client uses to remotely log in to unmanaged Unix servers. This setting is used when you select an unmanaged server and select **Actions † Log in with † rlogin**.

You must specify a client program that can communicate over the `rlogin` protocol. For example you could use `putty`, the free Windows application that supports SSH, `rlogin` and `telnet`.

For the Rlogin Client setting, specify the command line to invoke your `rlogin` client.

The following shows a sample `putty` command you can use to remotely log in to an unmanaged server using `rlogin`.

```
putty -rlogin -l %u -P %p %h
```

SSH Client Command

This setting specifies the terminal client and configuration settings that the SA Client uses to remotely log in to unmanaged Windows servers. This setting is used when you select an unmanaged server and select **Actions † Log in with † ssh**.

You must specify a client program that can communicate over the SSH protocol. For example you could use `putty`, the free Windows application that supports SSH, `rlogin` and `telnet`.

For the SSH Client setting, specify the command line to invoke your SSH client.

The following shows a putty command you can use to remotely log in to an unmanaged server over SSH.

```
putty -ssh -l %u -P %p %h
```

Table 1 Variables for the Terminal, RDP, Rlogin and SSH Client Options

Variable	Description	Replacement Value
%e	The character encoding.	For Remote Terminal sessions, the encoding of the managed server. For Global Shell sessions, the value of the Encoding field.
%h	The host name that the client is to connect to.	The value of the localhost of the managed server.
%m	A locale-specific message on how to close the window.	For English locales, click the Enter key to close this window.
%p	The port that the telnet client is to connect to.	A randomly chosen port.
%r	The name of the Remote Desktop (RDP) connection file. This variable is used only for the Microsoft Terminal Services Client (mstsc).	A temporary RDP file generated at runtime by the SA Client.
%t	The title displayed in the terminal window.	For Remote Terminal sessions, the name of the managed server. For Global Shell sessions, the string "Global Shell."
%u	The user name to pass to the client.	Specifying %u causes SA to display a dialog and request a user name. Enter the user name and select Log In. SA passes the specified user name to the client.

Encoding

This sets the encoding for Global Shell and the Remote Terminal sessions. This option is the replacement value of the %e variable in the command specified by the Terminal Client field. The default value of the Encoding option is UTF-8.

Patch Policy Options

This option allows you to specify that a confirmation message will display when you try to remove a patch policy or a patch policy exception from a managed server.

Network Automation Options

This options allows you to reset the name of the NA host that you log into, restore the previously saved (default) NA host name, and test whether SA can communicate with NA by using the new host name.

- **Host:** This option specifies the name of a server that is acting as a proxy for the NA host. Only the format of the host name is verified.
- **Restore Default:** This option restores the previously saved NA host name.
- **Test:** This option opens the NA login window to verify whether the host name is valid.

HP Service Automation Visualizer (SAV) Options

HP Service Automation Visualizer (SAV) allows you to manage the operational architecture and behavior of distributed business applications in your IT environment by displaying detailed application information in physical and logical drawings. For more information on SAV, see the *SA User Guide: Service Automation Visualizer*.

For SAV, you can specify the following options:

- [Virtualization Settings](#)
- [Scan Time-Out Preference](#)
- [Discovery Settings](#)
- [Reset All Settings](#)

Virtualization Settings

You can configure SA Client options that allow you to choose whether or not you want to perform a scan on any virtual servers or hypervisors related to the virtual server you want to open in SAV.

For example, if you want to visualize a VMware virtual machine (VM) or Solaris zone in SAV, by default you will be asked if you also want to scan any virtualization relationships — in other words, the system asks if you want SAV to also scan the hypervisor that is hosting the selected virtual server. Depending upon the virtual server you select, SAV might have to scan several related virtual servers in order to visualize a single virtual server in SAV.

Conversely, if you select a hypervisor to open in SAV, you are asked if you want to scan any virtualization relationships — in this case, SAV would need to scan all of the hosted virtual servers, which could take a long time to perform.



Even if you do not request a virtual relationship scan, SAV will display the virtual machines it discovers. However, certain details such as the operating systems on those virtual machines will not be displayed unless you request a virtual relationship scan.

By default, SAV will always ask you if you want to scan virtual relationships, but you can set your own default behavior for scanning related virtual servers with the following virtualization options:

- Ask each time if you want to scan related virtual and host servers.
- Always scan related virtual and host servers.

- Never scan related virtual and hypervisor servers.

To change the virtualization settings, perform the following steps:

- 1 From the **Edit** menu, select **Options**.
- 2 In the Set Options window, in the Views pane, select **Service Automation Visualizer**.
- 3 Specify your desired Virtualization Settings, then click **OK** when you are finished.

Scan Time-Out Preference

SAV is optimized to scan a maximum of 50 servers. A number of factors affect the time it takes for a scan to complete, including the load on the scanned servers and the load on SA. The default scan time-out is set to 300 seconds. You can reset this time-out value to a minimum of 30 seconds or to a maximum of 3600 seconds.

To change the scan time-out, perform the following steps:

- 1 From the **Edit** menu, select **Options**.
- 2 In the Set Options window, in the Views pane, select **Service Automation Visualizer**.
- 3 In the Scan Time-out section, move the slider to increase or decrease the number of seconds at which you want the scanning process to stop.
- 4 Click **OK** to save your changes or click **Cancel** to close the window without saving your changes.

Discovery Settings

If servers are scanned and it is determined that they are dependent on external IP addresses, when this option is selected SAV attempts to determine which servers or network devices those IP addresses refer to.

Keep in mind that this could cause scan time to increase, depending on the numbers of servers you selected for the scan and how many remote dependencies are discovered.

For recurring background business application snapshots, this detection is always done and cannot be turned off.

Reset All Settings

Restores all SAV settings to their defaults, including resizing and repositioning all tabbed views.

Browsing Job Logs

To view information about jobs that have run, select the Jobs and Sessions tab in the SA Client. This displays jobs that have run as well as jobs scheduled to run in the future.

A job is any major process run by the SA Client, such as Audit Servers, Create Snapshot, Create Virtual Zone, Deploy Application, Install Software, Push Configurations, Run Communication Test, Run OS Sequence, Scan Configuration Compliance, Uninstall Patch, and so on.

The Job Logs window shows all jobs that the user is configured to see, based on his permissions. It also displays jobs scheduled to run, including the job ID, the job type, the start and end times, the number of servers and groups affected by the job, the status of the job, the ticket ID, and the user name of the person who ran the job.

If the job status is Pending Approval, then the job is blocked until it is approved by a process that is external to HP Server Automation. If jobs are blocked indefinitely, the SA Administrator should check the settings of the Approval Integration window or the configuration of the backend connector.

The format of the Start Time and End Time for a job is determined by the original user preferences set in the SA Client. These preference may be different than those of the current user.



If you are working in multiple time zones, make sure the preferences for Start Time and End Time are set to include the time zone in the date display.

To see the details of a finished job, open the job. If the job is recurring (scheduled to be run), then opening the job will cause the Schedule Job window to display. You will only be able to modify the scheduled job if you created the job or have *Edit or Cancel Any Job* permissions. To obtain these permissions, contact your SA Administrator. See the *SA Administration Guide* for more information.

To view a job, select it, right-click, and select **Open**.




To cancel a non-recurring job, from the Job Logs window, right-click the job and select **End Job**. You cannot cancel a job while it is running (that is, when the job status is In Progress).

To cancel a recurring (scheduled) job, from the Recurring Schedules window, right-click the job and select **Delete Schedule**.



In order to view a job in the SA Client, you must have permissions to run or execute the feature action. For example, if you wanted to view Application Configuration Push jobs in the SA Client and you had the Manage Application Configurations permission set to Read, but not Write, you would not be able to see any Application Configuration Push jobs in the SA Client.

At the top of the Job Logs window, you can filter jobs by specifying the following criteria:

- **Job Time Frame:** Enables you to limit the search for a job by a time restriction, such as jobs run anytime, in the last 24 hours, last week, last month, last quarter, and so on. Or, for scheduled jobs, you can filter the jobs list by those jobs scheduled to run in the next 24 hours, next week, and so on.
- **Job Status:** Enables you to search based on the status of a job, such as Succeeded , Warning , Failed , Pending Approval, Cancelled, and so on.
- **Job Type:** Enables you to search for jobs by type, such as Audit Servers, Modify Virtual Zone, Reboot Server, Remediate Policies, Run OGFs Script, and so on. These are jobs that have already run or are scheduled to run.
- **Job ID:** Enables you to search by the job ID.
- **Ticket ID:** Enables you to search by the ticket ID, if one was given for the job.
- **User:** Enables you to enter a username to see only those jobs a certain user has run. Only users with the *View All Jobs* or *Edit or Cancel Any Job* permissions will be able to view jobs in the core. If you do not have these permissions, this filter will not appear.

You must click **Search** to update the list based on the current filter settings.

After setting the filter criteria, click the **Search** button to filter the job table.

To perform an advanced search, click drop-down list on the Search button and select **Advanced Search**. For more information, see [Performing an Advanced Search](#) on page 35 or [Searching for Objects with the SA Client](#) on page 33.

Recurring Job Schedules

The recurring schedules window shows all jobs that are scheduled to run on a recurring basis. You can choose to view all recurring jobs or filter the list of recurring jobs by specifying the following criteria:

- **Job Status:** Enables you to search for scheduled jobs by their status, such as Any Status, jobs that have been Cancelled, jobs that are Pending Approval, or all jobs that are Recurring.
- **Job Type:** Enables you to search scheduled jobs by their job type, such as Audit Servers, Create Snapshot, Push Configurations, and so on.
- **Job ID:** Enables you to search for recurring jobs by their job ID.
- **Ticket ID:** Enables you to search by the ticket ID, if one was given for the job.
- **User:** Enables you to enter a username to see only those jobs that a certain user has scheduled to run on a recurring basis. If a user is not specified, all recurring jobs will display.



Only users with View All Jobs or Edit or Cancel Any Job permissions will be able to view all jobs in the core. If you do not have these permissions, you will not be able to see all jobs.

- **Search:** Enables you to perform a search query of scheduled recurring jobs. Click **Search** to display the detailed results.

Viewing and Deleting Recurring Job Schedules

To view a recurring job schedule, select it, right-click, and select **Open**.

To delete a recurring job, select it, right-click, and select **Delete Schedule**.

Job Notification Emails


If a job was configured to send an email notification to a recipient when the job has finished, either on success, failure, or both, the email provides the following information:

- **Job Information:** Provides data about the job, such as the Job ID, Status, and start and end time.
- **Job Type Information:** Provides data relevant to the specific job type that was run. For example, if the job run was an Audit, the job notification email will provide information, such as Audit task ID and audit results ID.
- **Job Results URL:** The job results URL launches the specific job type window. For example, if the job was an audit, the job type URL launches the audit results window. Other information in the notification email provides job results details, such as number of differences found in the audit results, source and target server information, and so on.

Finding Information in Job Results

To easily find key information in the Job Status pane, you can filter, group, sort, search for, and highlight information in detailed job results.

Filtering the Display

Filtering enables you to control what displays in the Job Status table. You can narrow or expand the detailed job results. In the Job Status pane, in the filter box, click on the  filter menu to display a list of filtering criteria. The filter menu options display in the following 5 sections:

- 1 The first section is a list of the column names you can select to filter on. Depending on the Job type, the column names will vary. Select a column heading that you want to filter:

All

Item

Status

Only the following job types are filterable:

- Audit Servers
- Create Snapshot
- Deploy Application
- Install Software
- Push Configurations
- Remediate Audit Results
- Remediate Policies
- Reboot Server
- Restore Configurations
- Rollback Application
- Undeploy Application
- Uninstall Software

- 2 The next section is a list that specifies whether you want to filter with case sensitivity on or off:

Case sensitive

Case insensitive

- 3 This section specifies whether you want to filter using wildcards:

Use wildcards

If you enable wildcards, enter a string, using different wildcards, in the filter box. A wildcard is any character, including alpha, numeric, and special characters.

+ — The plus sign wildcard can be substituted for one or more of any character.

* — The asterisk wildcard character can be substituted for zero or more characters.

? — The question mark wildcard character can be substituted for one character.

- 4 This section specifies where in the field to match the string:
 - Match from start**
 - Match exactly** (This means you want to match the entire line.)
 - Match anywhere**
- 5 This section specifies how to keep the grouping when it filters a string. If neither is selected, it just keeps the rows that have the string:
 - Keep parent row if any of the children match** — This will display the parent row along with all the children rows that contain the string that the filter requested.
 - Keep the children if any of their ancestors match** — This will display the children rows along with all the parent rows that contain the string that the filter requested.

Grouping and Ungrouping Columns

You can group any one or multiple columns. When you group multiple columns, you create nested groups.

- 1 Right-click on the column heading you want to create a group of and then select **Group This Column**.
- 2 To ungroup a column, right-click on any column heading and then select **Ungroup Column <name>**.

Expanding and Collapsing Information in Columns

You can expand or collapse information in a column.

- 1 Right-click on a column heading and then select **Expand All**.
- 2 Right-click on a column heading and then select **Collapse All**.

Resizing Columns

You can auto resize one or all columns in the display.

- 1 To auto resize one column, right-click on the column heading and then select **Auto Resize This Column**.
- 2 To auto resize all columns, right-click on any column heading and then select **Auto Resize All Columns**.
- 3 (Optional) Double-click on the edge of a column heading in the job results display. This action will auto resize the column width to fit the data.
- 4 (Optional) You can also drag the vertical line between column headings to resize them.
- 5 (Optional) You can also drag-and-drop a column heading to change its horizontal position.

Sorting Columns

You can sort information displayed in a column.

- 1 To sort column information, click on the column heading.
- 2 To reverse sort column information, click on the column heading again.
- 3 To add a secondary, tertiary (and so on) sort, press CTL-Click.

Finding & Highlighting

You can use the **Find** tool to narrow your search and highlight what you see in the table or in the details pane.

- 1 To find key information in the table view, click in the table and then press CTRL-F to open the Find bar. Enter any string in the Find text box. This action finds the string you entered, whether it is an entire string or part of a string.
- 2 To find key information in the details pane, select a row in the table to open the details pane. Click in the details pane and then press CTRL-F to open the Find bar.

Example:

- a Enter “ORA” in the Find text box. This will highlight the first occurrence of “ora” in the details pane.

If you enter text that does not have any matches, “Phrase not found” will display next to the Find bar.

- b (Optional) You can have either one or both Find bars open at the same time. If you have both Find bars open simultaneously, one displays at the bottom of the table and the other one displays at the bottom of the details pane.
 - c (Optional) Click **Highlight** to highlight all occurrences of “ora”.
 - d (Optional) Click **Find Next** or **Find Previous** to jump forwards or backwards to the next occurrence of “ora” and highlight it.
 - e (Optional) Click **Match Case** to narrow the find to “ORA” database errors in this example.
- 3 To close the Find bar, click the **X** in front of the Find text box or position the cursor in the Find text box and then press **Esc**.

Combined Device History Log

The combined device history log records events performed on servers and network devices in your environment. These events are recorded in detail as actions performed on a certain date, by a certain user, on a certain server, or on a certain network device.

In many troubleshooting tasks, this type of information is critical because some of these actions (changes) might be the root cause of problems. This log provides detailed information, such as the date the action occurred, the name and type of the device that the action was performed on, and a description of the action, that can help you perform root cause analysis, capacity planning, and compliance remediation tasks.

For example, if an application in your environment has suddenly stopped running and you know exactly when it was previously running, you need to examine a combined event history log for the affected servers and network devices, for that time period. This information can help you determine why the application stopped working.

Viewing a Combined Device Event History Log

You can view a detailed list of events that occurred on a server or network device, such as all changes made to an application. You can narrow the time frame of the log display to see changes that occurred daily, weekly, monthly, quarterly, or in a custom range of dates. You can also dynamically filter the display of events by a certain date, device name, device type, event type, or by user name.

You can view a combined device history log for one or more managed servers or for a device group that contains managed servers and network devices.

To view a combined device history log for a device group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Group**, and select a device group.
- 2 In the Content pane, select one or more devices in the group.

Right-click and then select View History to list events that occurred on the selected devices.

Figure 16 Combined Device Event History

Date	Device Name	Device Type	Event	User
Mon Jun 26 04:...	im101.pr5.opsw...	Server	removed "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	cstarkey
Mon Jun 26 04:...	im106.pr5.opsw...	Server	removed "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	cstarkey
Mon Jun 26 04:...	co140.pr5.ops...	Server	removed "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	cstarkey
Mon Jun 26 04:...	im101.pr5.opsw...	Server	changed mode of "/amp/sitemap-dc76e9f0c0006e8f919e0c515...	cstarkey
Mon Jun 26 04:...	im105.pr5.opsw...	Server	changed mode of "/amp/sitemap-dc76e9f0c0006e8f919e0c515...	cstarkey
Mon Jun 26 04:...	im101.pr5.opsw...	Server	opened "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	cstarkey
Mon Jun 26 04:...	im106.pr5.opsw...	Server	changed mode of "/amp/sitemap-dc76e9f0c0006e8f919e0c515...	cstarkey
Mon Jun 26 04:...	im105.pr5.opsw...	Server	opened "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	cstarkey
Mon Jun 26 04:...	im106.pr5.opsw...	Server	opened "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	cstarkey
Mon Jun 26 04:...	im105.pr5.opsw...	Server	created "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	cstarkey
Mon Jun 26 04:...	im101.pr5.opsw...	Server	created "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	cstarkey
Mon Jun 26 04:...	im106.pr5.opsw...	Server	created "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	cstarkey
Mon Jun 26 04:...	co140.pr5.ops...	Server	changed mode of "/amp/sitemap-dc76e9f0c0006e8f919e0c515...	cstarkey
Mon Jun 26 04:...	co140.pr5.ops...	Server	opened "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	cstarkey
Mon Jun 26 04:...	co140.pr5.ops...	Server	created "/amp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	cstarkey
Mon Jun 26 01:...	sw1.pr5	Switch	Task Started	admin
Mon Jun 26 01:...	sw1.pr5	Switch	Last Used Device Password Changed	-
Mon Jun 26 01:...	sw1.pr5	Switch	Device Diagnostic Completed Successfully	admin
Mon Jun 26 01:...	sw1.pr5	Switch	Task Completed	admin
Sun Jun 25 22:0...	sw1.pr5	Switch	Device Snapshot	admin
Sun Jun 25 22:0...	sw1.pr5	Switch	Task Completed	admin
Sun Jun 25 22:0...	sw1.pr5	Switch	Last Used Device Password Changed	-
Sun Jun 25 22:0...	sw1.pr5	Switch	Task Started	admin
Sun Jun 25 19:0...	sw1.pr5	Switch	Task Started	admin
Sun Jun 25 19:0...	sw1.pr5	Switch	Last Used Device Password Changed	-
Sun Jun 25 19:0...	sw1.pr5	Switch	Device Diagnostic Completed Successfully	admin
Sun Jun 25 19:0...	sw1.pr5	Switch	Task Completed	admin
Sun Jun 25 16:0...	sw1.pr5	Switch	Device Snapshot	admin
Sun Jun 25 16:0...	sw1.pr5	Switch	Task Completed	admin
Sun Jun 25 16:0...	sw1.pr5	Switch	Last Used Device Password Changed	-

Viewing an Event History Log for Servers

To view a combined device history log for one or more managed servers, perform the following steps:

- 1 From the Navigation pane, select **Devices † All Managed Servers**.
- 2 In the Content pane, select one or more servers.

Right-click and select View History to list events that occurred on the selected server(s).

Figure 17 View History of Servers

Date	Device Name	Device Type	Event	User
Mon Jun 19 14: ...	m208.dev.opsw...	Server	Custom attribute 'AGENT_STAGE_STATUS' deleted.	127.0.0.1
Mon Jun 19 14: ...	m208.dev.opsw...	Server	Custom attribute 'AGENT_STAGE_STATUS' set to '32.0.1.59'.	127.0.0.1
Mon Jun 19 14: ...	m208.dev.opsw...	Server	Upgrade Opsware Agent to version 32.0.1.59: SUCCESS	bob
Mon Jun 19 14: ...	m208.dev.opsw...	Server	Stage Opsware Agent version 32.0.1.59: SUCCESS	bob
Mon Jun 19 14: ...	m234.dev.opsw...	Server	Upgrade Opsware Agent to version 32.0.1.59: SKIPPED (Agen...	bob
Mon Jun 19 14: ...	m234.dev.opsw...	Server	Stage Opsware Agent version 32.0.1.59: SKIPPED (Agent 32...	bob
Mon Jun 19 14: ...	m263.dev.opsw...	Server	Upgrade Opsware Agent to version 32.0.1.59: SKIPPED (Agen...	bob
Mon Jun 19 14: ...	m263.dev.opsw...	Server	Stage Opsware Agent version 32.0.1.59: SKIPPED (Agent 32...	bob
Mon Jun 19 23: ...	m208.dev.opsw...	Server	removed "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	removed "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	changed mode of "/tmp/sitemap-dc76e9f0c0006e8f919e0c515...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	opened "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	truncated file "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	changed mode of "/tmp/sitemap-dc76e9f0c0006e8f919e0c515...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	opened "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	truncated file "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	changed mode of "/tmp/sitemap-dc76e9f0c0006e8f919e0c515...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	opened "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	created "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	removed "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	removed "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	changed mode of "/tmp/sitemap-dc76e9f0c0006e8f919e0c515...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	opened "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	truncated file "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	changed mode of "/tmp/sitemap-dc76e9f0c0006e8f919e0c515...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	opened "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba3...	brian
Mon Jun 19 23: ...	m208.dev.opsw...	Server	created "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m234.dev.opsw...	Server	removed "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m234.dev.opsw...	Server	removed "/tmp/sitemap-dc76e9f0c0006e8f919e0c515c66dbba...	brian
Mon Jun 19 23: ...	m234.dev.opsw...	Server	changed mode of "/tmp/sitemap-dc76e9f0c0006e8f919e0c515...	brian



- 3 (Optional) In the View History window, select an option in the View drop-down list to list events by a time period, such as Last Day, Last Week, Last Month, or Custom Range.
 - 4 (Optional) In the View History window, use the search tool  to dynamically filter the display of events by a certain date, device name, device type, event type, or by user name.
- (Optional) To identify the device name and type for a certain event, double-click on the event listed in the View History window to display the Event Details window.


Figure 18 Event Details for a Selected Server



To view the combined device history log for a device group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Public**.
- 2 In the Content pane, select one or more devices in the group.
- 3 Right-click and then select View History to list events that occurred on the selected network devices.

Figure 19 View History of Network Devices





- 4 (Optional) In the View History window, select an option in the View drop-down list to list events by a time period, such as Last Day, Last Week, Last Month, or Custom Range.
- 5 (Optional) In the View History window, use the search tool  to dynamically filter the display of events by a certain date, device name, device type, event type, or by user name.
- 6 (Optional) To display details for a certain event, double-click on the event listed in the View History window to display the Event Details window.

Figure 20 Event Details for a Selected Network Device



Exporting a Combined Device History Log

If you need to use the log file in different applications, you can export the list of combined device history events to a .csv or an .html file.

To export the combined device history log, perform the following steps:

- 1 From the View History window, click **Export** to display the Export Dashboard window.
- 2 In the Look in field, enter the location of where you want to save the file.
- 3 (Optional) From the Encoding drop-down list, select a character encoding option. The default is Unicode (UTF-8).
- 4 In the File name field, enter a name for the file.
- 5 In the Files of type field, select .csv or .html.

Click **Export** to save the file in the selected format or click **Cancel** to close this window without saving.

2 Exploring the SA Library

The SA library provides a secure folder hierarchy for organizing and sharing all your server resources.

- The SA Library allows you to organize your server resources - packages, scripts, software policies, OS build plans, and many other server objects - in a folder hierarchy.
- Folder permissions enable you to control which user groups can view, use, and modify folder contents.
- Policies can specify various resources. Yet each resource can be located in any of various different folders. Because folder permissions determine user group access, each resource can be managed by an number of different user groups.

The ability to perform specific actions in SA is governed by your permission settings. For information about permissions, see the *SA Administration Guide*.

About Server Resources in the SA Library

The SA Library stores server resources such as OS build plans used for OS provisioning, software packages and policies for installing software, application configurations for configuring software, patches and patch policies for installing patches, scripts for running on your servers and many other resources for managing your servers quickly and efficiently. The SA Library is organized **by resource type** and **by folder location**. You can view server resources either by their type or by their location in the folder hierarchy.

- The **By type view** is organized by the type of object (policy, package, OS, patch, script). This view is a popular starting point for most of the software management activities, such as creating application configurations, running scripts, attaching policies to servers.
- The **By folder view** allows you to manage user group access to the software resources and is organized by operating system as a default. Folders can be added, moved, etc. It is where the admin can organize and manage permissions to shared resources. When you add or import resources, you specify a folder location. The location you specify will determine which user groups can access it.

When you install SA, the SA Library contains the default folders and resource types, as described below.

- The *Home* folder contains a folder for every SA user. Users can only see their own user directory under the home folder.
- A folder that contains the tools required to upload ISMs to SA.
- The *Package Repository* folder contains software packages that are organized by operating system families.
- In addition to using the default folders, you can create new folders in the library to manage your software resources. See [Creating a Folder](#) on page 60 for more information.

Default Resource Types:

- Application Configurations
- Audit and Remediation
- Business Applications
- Databases*
- Extensions
- OS Build Policies
- OS Installation Profiles
- OS Sequences
- Packages
- Patch Policies
- Patches
- Scripts
- Software Policies
- UNIX Users and Groups
- Windows COM +
- Windows Hyper-v Manager
- Windows IIS 7 Settings
- Windows IIS Metabase
- Windows Local Security Settings
- Windows Registry
- Windows Services
- Windows Users and Groups
- Web Applications*

*Except for Web Applications and Databases, all of these resources can be added to folders.


The SA Client search tools can find managed servers, software policies, folders, application configurations, patches, and software, and let you perform actions on the results.

About Managing Folders

The folder hierarchy in the SA Client provides a way to organize your software resources and allows you to define security permissions to control access to the contents of a folder. Folders can contain packages, patches, scripts, policies, server objects, and OS sequences. They can also contain other subfolders to form a hierarchal structure.

Use folders to organize and manage your software resources to correspond to your operational environment. For example, you can organize the folders by functionality (Finance, Engineering, Operations, or Marketing), by applications (Web Servers, Web Application Servers, Database Servers, or Middleware), or by operating system versions (Unix, or Windows).

Figure 21 Example of a Hierarchical Folder Structure in the SA Library



SA not only provides you with the flexibility of organizing folders based on functionality, applications, or OS versions, but it also allows you to share content among user groups. In this example, all policies related to database servers are organized in the Database folder. The Database folder contains subfolders for different versions of Oracle, which contain policies for different platforms.

Similarly, the Settlement Application subfolder contains the policies necessary for that functionality. The policies in this folder are organized based on operating system versions.

When you attach the Version 1 policy to a server, all the software in policy Version 1 is installed in addition to the software in policy Oracle, Redhat and Weblogic.

Folders cannot be attached to a server directly. Instead, you have to add the software resources in folders to a policy and attach the policy to a server. Folders also do not support inheritance, which means that the subfolders do not inherit the resources of a parent folder. See [Creating a Folder](#) on page 60.

About Folders and Permissions

Folders allow you to define security boundaries to control access to their content across user groups. You can assign permissions to folders to determine who can access the contents of the folder such as policies, packages, patches, server objects, and OS Sequences. A folder's permissions determine the user groups that can view, create, modify, and delete items within the folder. A folder's permissions apply only to the items directly under the folder. They do not apply to items lower down in the hierarchy, such as the subfolders and subfolders of subfolders (grandchildren).

In addition to the Folder permissions, a user must have the appropriate SA Client Feature permissions to access the contents of a folder. SA Client Feature permissions determine what actions users can perform with the SA Client, whereas the Folder permissions specify which folders users have access to.

You can assign the following permissions to a folder, by associating a user group with each folder:

- **List Contents of Folder:** Enables a user to navigate to the folder in the hierarchy, view the folder's properties, and view the names of the folder's children.
- **Read Objects Within Folder:** Enables a user to view and use the contents of a folder.
- **Write Objects Within Folder:** Enables a user to view, use, and modify the contents of a folder.
- **Edit Folder Permissions:** Enables a user to modify the folder permissions or add customers to a folder. This permission delegates the management of folder permissions to another user group.
- **Execute Objects Within Folder:** Enables a user to execute the scripts contained in the folder and view the names of the folder's children. This permission allows users to run scripts, but not to read or write them.

In addition to folder permissions, you can assign customer constraints to folders. See the *SA Administration Guide* for more information about folder permissions and customer constraints.

Creating a Folder

Perform the following steps to create a folder in the SA Client:

- 1 From the Navigation pane, select **Library † By Folders**.
- 2 From the **Actions** menu, select **New Folder**.

The name of the folder that you just created is New Folder (n), where n is a number based on the number of new folders already in existence.

- 3 Enter the name of the folder in the Content pane.
- 4 From the Navigation pane, select **Save** to save a folder.



To create a folder in a specific location, navigate to the desired location in the folder hierarchy and select **New Folder** from the **Actions** menu.



You can also rename, move, cut, and copy folders by selecting **Rename**, **Move**, **Cut**, and **Copy** from the **Actions** menu.

Setting Folder Properties


After you create a folder, you can view and modify the properties of the folder. You can view the folder properties, such as the SA user who created the folder, the date when the folder was created, the location of the folder in the Library, and the number of subfolders and feature objects present in the folder. You can also modify the name and the description of the folder.

You can also set the Folder permissions and Customer permissions on the folder. See the *SA Administration Guide* for information about setting Folder and Customer permissions.

Perform the following steps to manage the properties of a folder in the SA Client:

- 1 From the Navigation pane, select **Library † By Folders**.
All the folders in the Library appear in the Content pane.
- 2 From the Content pane, select a folder.
- 3 From the **Actions** menu, select **Folder Properties**. The Folder Properties window appears as shown in [Figure 22](#).

Figure 22 Setting Folder Properties in the SA Client



- 4 Select the General tab to view the folder properties, such as the location of the folder in the Library, the SA ID associated with the folder, and the features and subfolders contained in the folder.
- 5 In the Name field, modify the name of the folder. In the Description field, enter a description of the folder.
- 6 Click **OK** to save the changes or click **Cancel** to close this window without saving the changes.

Copying a Folder

You can copy and paste a folder in the SA Library which copies the contents of the folder to the new location, however, not all file types are copied.

Copying a folder copies the following types of files: audit policies, CML files, configuration files, OGFS script files, OS build plans, OS sequences, server scripts, and software policies. Other file types are not copied, such as zip files, RPM files, executable files, shell scripts, and files of unknown type. These types of files can be large and making copies can waste storage space. Proliferating copies of certain types of files can make keeping track of the official files more difficult. As a best practice, keep related files in one place for easier tracking.

Note that you can move a folder and all its contents by using cut and paste.

If you need to make a copy of a file, you can export the file to your local system, then import it to the new folder. Perform the following steps.

- 1 Locate the file in the SA Library and select it.
- 2 Right click or select the Actions menu and select Export Software. This displays a window where you can specify a location in which to store the file.
- 3 Specify the location where you want to save the file.
- 4 In the SA Client, navigate to the destination folder in the SA Library.
- 5 Right click or select the Actions menu and select Export Software. This displays a window where you can specify a location in which to store the file.
- 6 Use a similar process to import the file to the new location in the SA Library.

Deleting a Folder



To delete a folder containing subfolders, you must have the required permissions for the subfolders as well as the parent folder.

Perform the following steps to delete a folder in the SA Client:


- 1 From the Navigation pane, select Library † By Folders.
All the folders in the Library appear in the Content pane.
- 2 From the Content pane, select the folder that you want to delete.
- 3 From the **Actions** menu, select **Delete**. The Confirmation window appears.
- 4 Click **Delete** to delete the folder.

3 Exploring Servers and Device Groups in the SA Client

Exploring Servers in the SA Client

The SA Client allows you to view a list of all your servers in your data center, which can exist in various states of SA management. All your servers can be accessed from the Devices pane in the main SA Client interface, as shown in [Figure 23](#).

Figure 23 Servers in the Devices Pane



To visualize networking information with Network Automation (NA) inside of the SA Client, you must have both a licensed version of NA integrated with your SA core, plus an additional license for NA.

To view storage devices and SAN information inside of the SA Client, Storage Essentials (SE) version 6.1.1 or later and the Server Automation SE Connector component must be installed and configured your SA core. For more information, contact your HP SA sales representative.

Server Status Icons

In the SA Client, you can determine the status of a server by the type of icon next to the server, as defined in [Table 2](#). See the Server List in [Figure 23](#).

Table 2 Server Status Icons in SA






Server Icon	Description
	<p>Planned</p> <p>Indicates that a device record has been created for the server, but an OS Build Agent has not yet been installed on it. Servers in this stage cannot be provisioned until the OS Build Agent is installed.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Unprovisioned — Unreachable</p> <p>Indicates a server that has been registered with the core via the OS Build Agent, but has not reported as ready for provisioning recently. This may be due to networking problems between the server and the SA core or the server having been disconnected or powered off.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Unprovisioned — Reachable</p> <p>Indicates a server that has been registered with the core via the OS Build Agent and is available to have a target OS installed on it.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Provisioning — Unreachable</p> <p>Indicates a server on which the OS Provisioning feature was in the process of installing the target OS, but for some reason stopped because the server is unable to communicate with the SA core.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Provisioning — Reachable</p> <p>Indicates a server on which the OS Provisioning feature is in the process of installing the target OS.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>

Table 2 Server Status Icons in SA (cont'd)











Server Icon	Description
	<p>Provisioning Failed — Unreachable</p> <p>Indicates an available server on which an error occurred while the OS Provisioning Subsystem was installing a target OS, and that the server is not able to communicate with the SA core.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Provisioning Failed — Reachable</p> <p>Indicates an available server on which an error occurred while the OS Provisioning Subsystem was installing a target OS.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Agent Managed — Reachable</p> <p>Indicates a server has a Server Agent is running on it and that it is able to communicate with the SA core.</p> <p>In the SA Client, appears in the All Managed Servers list and Virtual Servers list.</p> <p>In the SA Web Client, appears in the My Jobs panel in the home page, in the list in the My Jobs page, in the Manage Servers list, and in the server lists in the SA wizards.</p>
	<p>Agent Managed — Unreachable</p> <p>Indicates a managed server cannot communicate with the SA core (it is Not Reachable).</p> <p>If you want to discover reasons why the managed server is unreachable, you can run a Communication Test. See Running Server Communication Tests on page 139 for more information.</p> <p>In the SA Client, appears in the All Managed Servers list and Virtual Servers list.</p> <p>In the SA Web Client, appears in the My Jobs panel in the home page, in the list in the My Jobs page, in the Manage Servers list, and in the server lists in the SA wizards.</p>





Table 2 Server Status Icons in SA (cont'd)

Server Icon	Description
	<p>Agentless</p> <p>Indicates the server does not have a Server Agent installed on it.</p> <p>For virtual servers, this means that someone created a virtual machine (VM) outside of SA so it does not have a Server Agent installed on it.</p> <p>For virtual servers, this state could also mean that the VM has not yet been provisioned, or that your user belongs to a group that does not have permissions to perform operations on this virtual server.</p> <p>For more information on installing a Server Agent on an unmanaged server, see Installing and Managing Server Agents on page 123.</p>
	<p>Deactivated</p> <p>Indicates a server that was deactivated in HP Server Automation by deactivating its SA Agent so that it is currently not managed and is no longer reachable.</p> <p>Appears in the Manage Servers list and in the server lists in the SA wizards (however, it is not selectable in the wizards).</p>
	<p>Scheduled</p> <p>Indicates a server that is scheduled for an operation (install software, uninstall software, and so forth).</p> <p>In the SA Client, appears in the Job Logs list.</p> <p>In the SA Web Client, appears in the My Jobs panel in the home page and in the list in the My Jobs page.</p>
	<p>Error</p> <p>Indicates a managed server on which an error occurred while HP Server Automation was installing or uninstalling software.</p> <p>Appears in the My Jobs panel in the home page and in the list in the My Jobs page.</p>
	<p>Warning</p> <p>Indicates a managed server on which a warning occurred while HP Server Automation was installing or uninstalling software.</p> <p>Appears in the My Jobs panel in the home page and in the list in the My Jobs page.</p>
	<p>Application Configuration Out of Sync</p> <p>Indicates a managed server on which the configuration file on the server is out of sync with the Application Configuration Template (SA model).</p> <p>Appears only in the Application Configuration feature and the server list in the SA Client.</p>

Device Group Status Icons

Device groups let you gather servers into logical sets to make performing actions on groups of servers easier and more efficient. The following table shows the icons displayed for device groups. See [About Device Groups](#) on page 99 for more information.



Table 3 Device Group Status and Icons

Device Group Icon	Description
	Static Device Group Indicates a static server group. The same states that apply to single servers apply to groups. See About Device Groups on page 99 for more information about the different types of server groups.
	Dynamic Device Group Indicates a dynamic server group. The same states that apply to single servers apply to groups.
	Public Static Device Group Indicates a public and static server group. The same states that apply to single servers apply to groups.
	Public Dynamic Device Group Indicates a public and dynamic server group. The same states that apply to single servers apply to groups.

VM Template Status Icons

The following table shows the icons displayed for virtual machine (VM) templates. VM templates are only visible and manageable from the Virtualization tab of the SA Client. For complete details, see the *SA User Guide: Virtualization Management*.

Table 4 VM Template Status Icons

VM Template Icon	Description
	Agent-Managed VM Template This template includes the SA agent. When you deploy a VM from this type of VM template, the resulting VM will be agent-managed. As a best practice, always use agent-managed VM templates and agent-managed VMs.
	Agentless VM Template This template does not include the SA agent. When you deploy a VM from this type of VM template, the resulting VM will not be agent-managed.

Running Server Communication Tests

You can run a set of communication tests to assess the connection between the SA core and your managed servers. For details, see [Running Server Communication Tests](#) on page 139.

Ways to Use the Device Explorer

The Device Explorer allows you to browse and manage servers, devices (such as network or storage), and groups of servers in your environment.

Using the Device Explorer you can perform the following actions on individual servers:

- Browse basic device system information, such as device, operating system, memory, Server Agent version, and more.
- View device compliance information and view the details of any policies attached to the server, such as all audits, patch policies, software policies, as well as any application configurations attached to the server.
- Run audits of the server, remediate any software policies attached to the server, and push application configurations on to a server.
- Browse live and up to date information about a server's file system, registry, hardware inventory, hardware, ethernet and SAN connections, installed software and patch lists, runtime state, user and user group membership, services, snapshots, and more
- View server group membership.
- View virtual server hypervisors and virtual machines (VMware, Solaris, and Microsoft Hyper-V).
- Add and delete custom attributes.



Some Device Explorer features are not available for VMware ESXi servers because SA does not install a Server Agent on ESXi servers. For more information on ESXi servers, see the *SA User Guide: Virtualization Management*. For more information on Server Agents, see [Installing and Managing Server Agents](#) on page 123.

Network and Storage Devices in the Device Explorer

For more information on the types of information you can view in the Device Explorer for network and storage devices, see the following:


- *SA Integration Guide* for network devices
- [Storage](#) on page 82

For more information on storage in the SA Client, see the *Storage Visibility and Automation User Guide*.

Device Explorer Interface

The Device Explorer consists of two main sections: the Views pane and the Content pane. The Views pane lists server objects from the managed server, and the Content pane displays content for each of the server's objects. When you select a server object in the Views pane, its corresponding content appears in the Content pane. See [Figure 24](#).

Figure 24 Device Explorer Interface



Device Explorer Views Tabs


The Device Explorer Views tabs organize four different types of information about your device:

- **Information About Servers:** Shows general property and system information, such as computer manufacturer, hardware type, system, processor and memory, OS version, Server Agent version and status (for those managed servers that have a Server Agent installed), SA customer assignment, history of changes to the server, and more.
- **Server Management Policies:** Displays a roll up of all compliance policies attached to the server, as well as compliance for individual compliance policies, such as audits, software and patch policies, application configurations, and any custom user-create policies. It also shows any custom attributes created on the server.
- **Relationships with Other Devices:** Shows all groups that the selected server is a member of and allows you to modify group membership (if your user has sufficient permissions).
- **Inventory of Server Information:** Displays a list of live server configuration objects and server modules captured directly from the server, such as registered hardware, network connections, snapshots taken of the server, installed packages, patches, discovered software, runtime information about processes running on a server, local security settings, users and groups memberships, and so on.

Accessing the Device Explorer

To access the Device Explorer, perform the following steps:

- 1 Launch the SA Client and then from the Navigation pane, select **Devices † All Managed Servers**.
- 2 A list of servers will display in the Content pane.

If the list of servers is long, use the filter tool  to locate a server (upper right corner) by name, IP address, OS, customer, facility, or description. If you filter by user name, the text entry is case insensitive.

You can also sort the list by clicking a column heading, such as name, IP address, OS, customer, and so on. To reverse sort, click the column heading a second time.

- 3 Open a server from the Content pane. This opens the Device Explorer. From the **Actions** menu, you can perform many types of operations, such as:
 - Open in HP Service Automation Visualizer (SAV) if your core is licensed to run SAV
 - Run a script on the server
 - Create or run an audit or snapshot of the server
 - Scan software, application configuration, or patch compliance
 - Add to a device group
 - Export patch information to a .csv file
 - And more

Action menu items change according to the server object selected.

For example, if you select the Configured Applications object from the server object tree, then from the **Actions** menu, you can add, remove, or open an application configuration, create a package, and so on.



For VMware ESXi servers, some actions are not available because the SA Server Agent is not deployed on VMware ESXi servers. For more information on ESXi servers, see *SA User Guide: Virtualization Management*. For more information on Server Agents, see [Installing and Managing Server Agents](#) on page 123.

Opening a Remote Terminal

You can open a remote terminal and log in to any managed server. Perform the following steps:

- 1 From the SA Client Navigation pane, select **Devices † All Managed Servers**.
- 2 Select a managed server.
- 3 Select the **Actions** menu or right click and select **Open With † Remote Terminal**.
- 4 Log in to the remote server.

See also the [SA Global Shell](#) on page 281.

Information About Servers

The Information tab for a server provides the following information:

- [Summary of Server Information](#)
- [Properties of Servers](#)
- [Custom Attributes Defined for a Server](#)
- [History of Server Changes](#)
- [Server Location](#)



For VMware ESXi servers, some Device Explorer information is not displayed because the SA Server Agent is not deployed on VMware ESXi servers. For more information on ESXi servers, see *SA User Guide: Virtualization Management*. For more information on Server Agents, see [Installing and Managing Server Agents](#) on page 123.

Summary of Server Information

The Summary view in the Device Explorer lists the following information:

- **System:** This displays operating system information.
- **Computer:** This displays server manufacturer, hardware, and system details.

- **Agent:** This displays communication status, the time when the server was last registered, the number of applications and patches registered with SA, and so on. Servers that do not use an SA agent, such as VMware ESXi, will not display agent information. For more information on ESXi servers, see *SA User Guide: Virtualization Management*.

Properties of Servers

The Properties view in the Device Explorer lists the following information for the server that you are viewing:

- [Management Information for Servers](#)
- [Custom Fields Defined for Servers](#)
- [Reported Information for Servers](#)
- [Server Modules](#)

Management Information for Servers

The Management Information view in the Device Explorer lists the following information about the server that you are viewing:

- **Name:** This displays the name of the managed server.
- **IP Address:** This displays the IP address of the managed server.
- **Description:** This displays a text description of the server.
- **Customer:** This displays an account within HP Server Automation that has access to designated resources, such as servers and software.
- **Facility:** This displays the location of the server. Users can manage servers in any facility from a SA Web Client.
- **Realm (link speed):** This displays the minimum bandwidth limit between the Server Agent and the core (if the agent is going through gateways).
- **Server Use** (sometimes abbreviated to just **Use**): This property displays how an organization is using the managed server; for example, a server could be a staging server, a production server, a development server, and so on. You can set this value for your servers and use it to group and filter servers for management tasks or as a condition for inclusion in dynamic groups. For example, you could use this property to quickly locate all your staging servers. The predefined values are:
 - Not Specified - This is the default value for all servers.
 - Development - Servers are being used to develop business services.
 - Staging - Servers are in preparation before going into production.
 - Production - Servers are in production providing business services.

You can add, delete or change the server use categories as follows:

- Log in to the SA Client as a user who has the Server Attributes permission set to Yes. This permission is required to change server use categories. For more information on permissions, see the *SA Administration Guide*.
- Select the Administration tab.

- c Select **Server Use** which is under the **Server Attributes** node in the navigation pane. This displays all your currently defined server use categories.
 - d Use the **Actions > New**, **Actions > Open** and **Actions > Delete** menus or the **New** and **Delete** icons to create, modify and delete server use categories. You cannot modify or delete the **Not Specified** category.
- **Server Lifecycle:** This displays the server's stage in the managed server lifecycle; for example, unprovisioned, available, managed, or deactivated.
 - **Reboot Required:** This indicates whether or not the server needs to be rebooted, for example because a patch has been installed.
 - **OS Version:** This displays the operating system (platform) that the managed server is running on.
 - **Deployment Stage** (sometimes abbreviate to just **Stage**): This property displays the stages of deployment for a server; for example, a server could be live or offline or in deployment. You can set this value and use it to group and filter servers for management tasks or as a condition for inclusion in dynamic groups. For example, you could use this property to quickly locate all servers that are offline. The predefined values are:
 - Not Specified - This is the default value for all servers.
 - Offline - Servers are not in use.
 - In Deployment - Servers are being prepared for use.
 - Ops Ready - Servers are ready to be used.
 - Live - Servers are being actively used.

You can add, delete or change the deployment stage categories as follows.

- a Log in to the SA Client as a user who has the **Server Attributes** permission set to **Yes**. This permission is required to change deployment stage categories. For more information on permissions, see the *SA Administration Guide*.
 - b Select the **Administration** tab.
 - c Select **Deployment Stage** which is under the **Server Attributes** node in the navigation pane. This displays all your currently defined deployment stage categories.
 - d Use the **Actions > New**, **Actions > Open** and **Actions > Delete** menus or the **New** and **Delete** icons to create, modify and delete deployment stage categories. You cannot modify or delete the **Not Specified** category.
- **Locale:** This displays the server's current locale setting.
 - **UUID:** A unique identifier for the managed server.
 - **Object ID:** This displays the internal identifier that SA uses to identify the server.
 - **Status:** This displays whether or not the server is reachable and thus managed by SA. "OK" means that the server (its Server Agent) is reachable; unreachable means that there is a communication problem and SA cannot communicate with the server.

Custom Fields Defined for Servers

This view lists the custom fields defined for the server and the value of each custom field and lets you edit the values.

SA can store a large amount of information about your managed servers. Custom fields provide a way for you to store additional information about your servers quickly and easily. Custom fields are data elements you can create for servers and other objects in SA.

For more information about custom fields, see [Comparing Custom Fields and Custom Attributes](#) on page 161 and [About Custom Fields](#) on page 162.



Custom attributes are similar to custom fields. For more information about custom attributes, see [Custom Attributes Defined for a Server](#) on page 75.

Reported Information for Servers

This view displays information about the server reported by the server agent. For more information on the server agent, see [Installing and Managing Server Agents](#) on page 123.

- **Reporting:** This displays information about the ability of the server's agent to communicate with the core. Statuses include Has not reported, OK, Registration in progress, and Reporting error.
- **Agent Version:** This displays the version number of the agent. This only applies to managed servers where a Server Agent is installed.
- **Hostname:** This displays the host name of the managed server.
- **Reported OS:** This displays the operating system (platform) that the managed server is running on.
- **MAC Address:** This displays the Media Access Control (MAC) address. This is the network interface card's unique hardware number. The MAC address is used as the server's physical address on the network.
- **Serial Number:** This displays the serial number of the system. HP Server Automation attempts to report a chassis ID if possible.
- **Chassis ID:** This displays a unique hardware-based identifier that the Server Agent discovers, typically derived from some property of the server's chassis. As a common source for this ID, HP Server Automation uses an interface's MAC address or the host ID on Solaris servers, or the serial number for one of the interfaces.
- **Encoding:** This displays the character encoding of the managed server, such as Shift_JIS (Japanese) or Windows 1252 (Western).

From this window, you can also open a remote terminal on the selected server.

Server Modules

Server Modules are software modules that work with and extend the server agent to provide additional management capabilities for your servers. Most server modules are installed and managed automatically by the SA core and the server agent and do not require any administration or maintenance.

For example, the extensible discovery software module is installed automatically on servers when you perform an extensible discovery operation. For more information about extensible discovery, see the [Running Extensible Discovery on Managed Servers](#) on page 153.


The software discovery server module discovers and creates an inventory of unlicensed software, unregistered software, custom-built software and nonstandard software on your servers. For more information about software discovery, see the *SA User Guide: Software Management*.

Custom Attributes Defined for a Server

This view displays the custom attributes attached to a server. You can add, edit or remove custom attributes from this view.

Custom attributes can be locally defined or inherited:

- **Inherited:** Custom attribute value inherits from another source, such as a customer, a facility, a software policy, ISM control, and so on.
- **Locally Specific Value:** Custom attribute is created directly on a servers.

To create a new custom attribute, click the Add  icon, and then enter a value.

Overriding Inherited Custom Attribute Values

For all custom attributes that a server inherits from another source, such as from a customer or facility or device group, you can choose to override the inherited attribute's value.

To override inherited custom attribute values, perform the following steps:

- 1 In the SA Client, select Devices All Managed Servers.
- 2 Select a server.
- 3 Select the Actions menu or right click the server and select Open. This displays information about the selected server.
- 4 Select the Information tab.
- 5 Select Custom Attributes in the navigation pane. This displays all the custom attributes defined for the server. The Source column indicates where the custom attribute is defined, whether it is defined locally on the server or is defined by and inherited from another object.
- 6 For the inherited custom attribute you want to override, from the Source column select Overridden with Specified Value from the drop down list.
- 7 Enter a value in the Value field.



Custom fields are similar to custom attributes. For more information and a comparison of custom fields and custom attributes, see [Comparing Custom Fields and Custom Attributes](#) on page 161 and [About Custom Fields](#) on page 162.

History of Server Changes

The History view shows changes made to the selected server. For example, it displays who modified a server, what change was made, when it was modified, and so on. Server History specifically shows when a user has performed one of the following actions:

- Added the server to a group
- Removed the server from a group
- Reassigned the server from one group to another
- Login sessions
- Jobs that were run on the server, such as snapshots, audits, patch and software policy remediations

- And more

Entries are generated when actions are performed for managed servers in the SA Web Client. The History is read-only. Double-click an entry to see more detailed information, such as:

- **Date:** The date when the last change occurred.
- **Device Name:** Name of the server or device where the change was made.
- **User:** The user who made the change.
- **Details:** A description of the change.

Use the View drop-down list to sort the server history list according to a range of time, such as last week, the last two months, and so on.

Server Location

The Server Location node shows an HP ProLiant server's (BL Models only) physical location. The General category displays the following information:

- **Rack:** Rack number
- **Enclosure:** Enclosure name
- **Bay:** Server bay number



Note: If the server is moved, the SA agent updates the server-location information during full hardware registration.

Server Management Policies

The Device Explorer — Management Policies provides the following information:

- [Compliance](#)
- [Audits](#)
- [Archived Audit Results](#)
- [Software Policies](#)
- [Patch Policies](#)
- [Configured Applications](#)

Compliance

The Compliance view of the Device Explorer displays overall compliance levels — a roll up of all compliance policies attached to the server — and compliance for individual compliance policies, such as audits, software and patch policies, application configurations, and any custom user-created policies.

You can select and expand a compliance category and view all tests in each category. For each test you can view policy details and remediate any tests that are out of compliance. Each compliance category contains an expandable list that contains all the policies of this type. The

top-level node shows the rollup compliance status of all policies in this category. If you expand the list, you can see each individual policy and its compliance status as well, for a detailed breakdown of compliance for the server.

You can also sort the list to show all policies, or filter it to show only the policies for one compliance categories, such as all Audit policies and their compliance statuses. You can also sort by status filter, such as, show all compliance tests that are compliant, non-compliance, are currently scanning, and so on.

For more information on server and device group compliance, see the *SA User Guide: Audit and Compliance*.

Compliance Categories

Compliance categories a server include:

- **Audit:** A roll up compliance status of all scheduled audit that target this server appears by on the top node of the Audit category in the Details pane. This category displays the overall compliance status of all recurring audits that run on this server. To see the individual audits that use this server as a target, expand the Audit list, which shows each audit's compliance status in the Status column.
- **Software:** A roll up compliance status of all software policies attached to the server appears the top node of the Software category in the Details pane. Software compliance indicates whether or not all software policies attached to the selected server are compliant with the actual server configuration.

A software policy can include installed packages and patches, application configurations, and other software policies. If the actual server configuration does not match the software policy definitions, then the server's software policies are considered out of compliance. To see the individual software policies attached to this server, expand the Software list, which shows each software policy's compliance status in the Status column.

- **App Config:** A roll up compliance status of all application configurations attached to the server appears the top node of the App Config category in the Details pane. An Application Configuration (App Config) policy defines how specific application configurations files should be configured on a managed server. Application Configuration compliance indicates whether or not all of the Application Configurations attached to a server are compliant with the actual application configuration files on the server. If the actual server configuration does not match the Application Configuration definitions, then the server's Application Configurations are out of compliance. To see the individual application configurations attached to this server, expand the App Config list, which shows each application configuration s compliance status in the Status column.

Patch: A roll up compliance status of all patch policies attached to the server appears the top node of the Patch category in the Details pane. Patch compliance determines whether all patches in a patch policy and a patch policy exception were installed successfully. To test patch compliance, servers are scanned to determine whether they conform to their attached policies and exceptions, based on compliance status and rules. If any of the patches defined in the patch policy do not match what is actually installed on the server, then the server's patch policies are out of compliance. To see the individual patch policies attached to this server, expand the Patch list, which shows each patch policy's compliance status in the Status column.

Audits

Audits view shows a list of all audits associated with the server, where the selected server is either the source or the target of an audit.

Show Options

- **Audit - Server is Target:** Shows all audits where the selected server is the target of an audit.
- **Audit - Server is Source:** Shows all audits where the selected server is used as the source of an audit.

For more information, see the *SA User Guide: Audit and Compliance*.

Archived Audit Results

This list displays all audits results associated with this server that have been deliberately archived by a user. In some cases, audits that run regularly can accumulate many audit results. In the main Audit and Remediation feature, you can select to archive audit results if you want to save them for later viewing. All audit results for the selected server are displayed here.

Software Policies

This window displays all software policies associated with the selected server (or device group). You can perform actions such as attaching a policy, detaching a policy, remediating a server, and scanning software compliance from the **Actions** menu.

For more information, see the *SA User Guide: Software Management*.

Patch Policies

This window displays all patch policies associated with the selected managed server (or groups of server group).

Show Options

The Show drop-down list displays the following patch policy information:

- **Policies Attached to the Server:** This displays all policies attached to the server, or policies attached to a server group to which the selected Windows managed server belongs.
- **Policies Not Attached to the Server:** This displays a list of all patch policies relevant to the selected server that are not attached to the server.

Configured Applications


The Configured Applications screen shows all the Application Configurations attached to the managed server. Each node under the Configured Applications node represents an application configuration attached to the server. Each subnode under each application configuration lists all the instances of the application configuration defined for the server.

You can edit the value sets at the server level and the server instance level.

- Selecting the Configured Applications node displays all the application configuration instances available to be pushed to the selected server.
- Selecting an application configuration displays the value set in the value set editor at the server level for the selected template.
- Selecting an instance of an application configuration displays the value set in the value set editor at the server instance level for the selected template.

For complete information on managing software and application configurations, see the *SA User Guide: Application Configuration*.

The example below shows two application configurations attached to the server m528 named myappcfg and WAS-app-config. Two instances are defined for WAS-app-config named “Primary Instance WAS-app-config” and “Secondary Instance WAS-app-config”.



Running a Script on the Server

The **Run Script** button executes the selected Application Configuration’s data-manipulation script. If the application configuration contains no data-manipulation script, the **Run Script** button is disabled. For more information, see the *SA User Guide: Application Configuration*.

Previewing an Application Configuration Push Operation

The Preview button compares the configuration file on the server with the configuration file defined by the selected instance and shows the two files. For more information, see the *SA User Guide: Application Configuration*.


Push an Application Configuration to the Server

This Push button saves any changes you have made to the Application Configuration and starts the Push Configurations wizard to push the selected instance of the configuration file to the server. For more information, see “About Pushing Application Configurations to Servers” in the *SA User Guide: Application Configuration*.

Relationships with Other Devices

The Relationships view of the Device Explorer lists all device groups of which this server is a member. Members of a group can include servers, network devices (for NA-enabled cores), storage devices and assets (for SE-enabled cores), and other device groups.

You can select a group, right-click and select **Open** to view its contents. You can also select to Add to Group to select other devices to add to the group.

If the list of groups is long, use the search tool  to locate a server (upper right corner) by name, description, access, type, modified by, and so on. If you search by device group name, the text entry is case insensitive.

Storage Relationships

If your core is configured to connect to SE, Device Explorer view also gives you viewing access to various storage objects such as SAN switches, SAN fabrics, storage targets, and databases. For more information on these storage objects and relationships, select an object and press F1, or see the *Storage Visibility and Automation User Guide*.

Inventory of Server Information

The Inventory tab provides the following information about the selected server:

- Hardware
- Network
- Storage
- Disks
- Virtualization View
- Snapshot Specifications
- Installed Packages
- Patches for the Server

- Files on the Server
- Windows COM+ Objects
- Windows IIS Metabase
- Windows IIS 7.0
- Internet Information Server (IIS)
- Windows Registry
- Services (Windows and Linux)
- Windows .Net Framework Configuration
- Local Security Settings
- Registered Software
- Runtime State
- Users and Groups

Hardware

The Hardware view lists all the reported hardware on the selected managed server. This includes the following information:

- **Processors:** This lists the processor information for all processors on the managed server.
- **Memory:** This lists the total amount and the types of memory on the managed server.
- **Storage:** This lists all storage devices on the managed server.
- **Network Interfaces:** This lists the network interfaces on the managed server, including Ethernet cards (NICs) and any Fibre Channel Adapters, ports—including the switch ports that a port is connected to as well as any zones.

Network

The Network view shows all network connections (or SAN, for Storage-enabled cores), providing the IP address, subnet mask, MAC address, duplex and speed settings, DHCP settings and the interface type for all network interfaces.

This view also shows the network configurations for the selected server including the host name, the DNS domain, the SA facility, the name and IP address of the management interface, the IP address of the gateway, the IP addresses of the DNS servers and the search domains.

Storage

If your core is configured to connect to SE, the Inventory tab includes a Storage view that provides information about SAN, NAS and DAS (Direct Attached Storage) assets related to the selected server.

This view also provides a summary of the storage (if applicable) consumed by and allocated to the selected server, as well as insight into Database storage (if applicable) consumed by the selected server.



In order to view storage devices and SAN information inside of the SA Client, Storage Essentials (SE) version 6.1.1 or later and the Server Automation SE Connector component must be installed and configured your SA core. For more information, contact your SA sales representative.

This Storage view provides details about the following storage assets:

- **File Systems:** Shows a list of local and remote file systems (SAN-based storage). It provides information such as mount location, type of file system, storage capacity and free space. From the View drop-down list, you can select four different views into File Systems:
 - **Properties:** Displays information like mount location, description for mount point; mount point, type of file system, storage capacity and free space.
 - **Volumes:** Displays a list of volumes based on the selected file system.
 - **Disks:** Displays a list of disks on which the selected file system is dependent.
 - **Connectivity:** Displays supply chain information for the selected file system in a tree format.
- **Volumes:** Shows a list of volumes consumed by the selected server. These volumes could be local or remote (SAN volumes). From the View drop-down list, you can select four different views into Volumes:
 - **Properties:** Displays the name, type, service type, status and storage capacity for the selected volume.
 - **Composition:** Displays *upstream* and *downstream* storage dependencies. Upstream storage dependency means that the storage asset depends on the selected volume; downstream storage dependency means that the selected volume is dependent upon other storage assets.
 - **Disks:** Displays the list of disks on which the selected volume is dependent.
 - **Access Path:** Displays data which is mostly interesting if the selected volume is a remote SAN volume. This sub-view provides LUN Mapping information for the remote SAN Volume — the target storage array, target storage array port, target storage volume, LUN number and initiator port.
 - **Connectivity:** Displays the supply chain information for a volume in a tree format. This view is useful in the context of remote SAN volumes.
- **Unmounted Volumes:** Shows a list of volumes that are available to the selected server but that are not used by the server. These volumes are typically remote SAN volumes which are mapped to the selected server but the server is not using them. From the View drop-down list, you can select four different views into Unmounted Volumes:
 - **Properties:** Displays name, type (raid type), service type, status, storage capacity and target device for the selected Unmounted volume.

- **Composition:** Displays *downstream* storage dependencies, which means that the unmounted volumes are dependent upon the selected storage asset.
- **Disks:** Displays the list of disks on which the selected unmounted volume is dependent.
- **Access Path:** Displays data which is mostly interesting if the selected unmounted volume is a remote SAN volume. This sub-view provides LUN Mapping information for the remote SAN Volume — the target storage array, target storage array port, target storage volume, LUN number and initiator port.
- **Connectivity:** Displays the supply chain information for a unmounted volume in a tree format. This view is useful in the context of remote SAN volumes.
- **Disks:** Shows information about local and remote (SAN-based) disks. Detailed information includes name, manufacturer, model, device (server), storage capacity, status and if its spare or not. From the View drop-down list, you can select two different views into Disks Volumes:
 - **Volumes:** Displays list of volumes based on the selected disk.
 - **File Systems:** Displays a list of file systems based on the selected disk.
- **Manager Software:** Shows information about Volume Manager software and MultiPath software on the selected server, including vendor, version and details about logical volumes managed like name, type (RAID Type), service type, status, storage capacity and number of paths.

Disks

The Disks views provides local disk information for the managed server, including such information as disks names, manufacturer, the device that contains the disk, model number of the disk, its capacity, its status (identifies the disk health, such as OK, ONLINE, Disable, Not Ready, Error, READONLY), and whether the disk is used as a spare (Yes) or not used as a spare (No).

Virtualization View

The Virtualization view displays information about virtual servers — both hypervisors and guest virtual servers. For example, for a hypervisor server, the Virtualization view displays all the virtual servers being hosted on the hypervisor server. For virtual servers, the Virtualization view displays all virtual server information as well as the hypervisor server that is hosting it.

For more information on managing virtual machines, hypervisors, and virtualization services, see the *SA User Guide: Virtualization Management*. For a list of icons and their meanings, see [Server Status Icons](#) on page 64.

Solaris Zones — Device Explorer

You can use the Device Explorer to view a Solaris global zone hypervisor and local zone server information. A global zone or local zone as seen through the Device Explorer looks nearly the same as a regular physical server, except that it has an extra property named “Virtualization,” which provides the following information:

- **Hypervisors:** When you view a Solaris global zone hypervisor in the Device Explorer, the Virtualization view shows all hosted local zones. From here, you can also stop and start the local zones.
- **Solaris Local Zones:** When you view a Solaris local zone in the Device Explorer, the Virtualization view indicates the name of its hypervisor, its reserved CPU shares, and virtual hardware information.

VMware ESX — Device Explorer

You can use the Device Explorer to view a VMware vCenter Server (virtualization service), a VMware ESX hypervisor's server information, and VM (virtual machine) information. A VM as seen through the Device Explorer looks nearly the same as a regular physical server, except that it has an extra property named "Virtualization," which provides the following information:

- **Virtualization Service:** For servers hosting a VMware vCenter Server, the Device Explorer gives the vCenter version, IP address, port number, user name, and other information about the server.
- **Hypervisors:** For servers hosting a VMware ESX hypervisor, the Device Explorer shows the virtualization service hosting the server, the connection state of the server, the virtual networks attached to the server, the datastores attached to the server, and other information about the server.
- **VMware VMs:** When you view a VMware VM in the Device Explorer, the Virtualization view shows you the hypervisor hosting the VM, the virtualization service managing the hypervisor, the VMs genealogy - how it was created, the VMs memory and CPU allocations, its virtual network configuration, its storage configuration, and other information about the VM.

Windows Hyper-V — Device Explorer

You can use the Device Explorer to view a Windows Hyper-V partition or a hypervisor's server information. A partition as seen through the Device Explorer looks nearly the same as a regular physical server, except that it has an extra property named "Virtualization," which provides the following information:

- **Virtualization Service:** For servers hosting a Microsoft System Center Virtual Machine Manager, the Device Explorer gives the SCVMM version, IP address, port number, user name, and other information about the server.
- **Hypervisors:** For servers hosting a Windows Hyper-V hypervisor, the Device Explorer shows the virtualization service hosting the server, the connection state of the server, memory information, the virtual networks attached to the server, and other information about the server.
- **Windows Hyper-V VM:** When you view a Windows VM in the Device Explorer, the Virtualization view shows you the Hyper-V hypervisor hosting the VM, the virtualization service managing the hypervisor, the VMs genealogy - how it was created, the VMs memory and CPU allocations, the power state, its virtual network configuration, its storage configuration, and other information about the VM.

Snapshot Specifications

The Snapshot Specifications view shows a list of all Snapshot Specifications where the selected server is listed as a target. To view the results of one of the Specifications, select it in the Contents pane (right side). When you select a Snapshot Specification, a list of all snapshot results appear in the pane below (for all servers that are targets of the Snapshot Specification).

To open a Snapshot Specification, select one, right-click, and select **Open** (or double-click it). To view the results of a snapshot, select one from the lower pane, right-click, and select **Open** (or, double-click it).

Installed Packages

The Installed Packages view enables you to view any installed packages on the selected managed server that are managed by SA. For each package, you can view name, type, size, last modified, and description. To sort the list by these categories, click the title of each column. See the *SA User Guide: Software Management* for information on how to create a package.

For information about using the Device Explorer to see packages that exist on the manager server but are not yet managed by SA, see [Patches for the Server](#) on page 85.

Patches for the Server

This window displays all patches associated with the selected managed server.

Show Options – Windows

You can use the Show drop-down list to filter the following types of patch information:

- **Patches Installed:** This option displays all patches that have been installed on the server.
- **Patches Recommended By Vendor:** This option displays all application and operating system patches that have been recommended by the Windows patch database for the selected server. If multiple patches have the same QNumber, Patch Management detects the application files that are already installed on a managed server and, subsequently, recommends the correct patch to install.
- **Patches with Policies or Exceptions:** This option displays patches in policies attached to the selected server, or patches that have ‘always install’ or ‘never install’ exceptions, *and* have one of the following conditions:
 - The patches are not currently installed and are recommended by the vendor.
 - The patches are currently installed.
- **Patches Needed:** This option displays all patches that should be installed on the selected server but are not. These include patches that are in policies attached to that server, or patches that have always install exceptions, *and* are recommended by the vendor.
- **Patches with Exceptions:** This option displays all patches that have exceptions (such as always install or never install) *and* have one of the following conditions:
 - The patches are not currently installed and are recommended by the vendor.

- The patches are currently installed.
- **All Patches:** This option displays all patches that are associated with the operating system of the server.

Show Options – UNIX

The Show options for UNIX patches display the following information:

- **All Patches:** This option displays all patches that are associated with the operating system of the server.
- **Patches Installed:** This option displays all patches that have been installed on the server.

Patch Contents – Windows

The Show options for Windows patches display the following information:

- **Icon:** A dimmed icon means that the patch has not yet been uploaded to the Software Library.
- **Name:** This is the QNumber of a patch that is a hotfix or an update rollup. Service pack patches do not have a QNumber.
- **Compliance:** This shows one of the following three levels of patch policy compliance, as defined by a patch administrator:
 - **Policy Only:** Compliance that includes the policy only.
 - **Policy and Exception:** Compliance that includes the policy and the policy exceptions.
 - **Customized:** Customized compliance.
 - **Non-Compliant** (red): This indicates that the patch is installed on the server, but is not in the policy, or that the patch is not installed on the server but is in the policy.
 - **Partial** (yellow): This indicates that the policy and exception do not agree, and the exception does not have data in the Reason field.
 - **Compliant** (green): This indicates one of the following conditions:
 - A patch is installed on the server and is in a policy, or a patch is not installed on the server and is not in a policy.
 - A patch is installed on the server and there are additional patches with the same QNumber in a patch policy or exception. In this case, all patches with the same QNumber are considered installed when Patch Management calculates patch compliance.
 - A patch is not installed on the server and is in a patch policy or has an always install exception, and is not recommended by the vendor. In this case, the patch has a never install exception, because it is not recommended by the vendor.

In the Preview pane, move the cursor over the icon or text in the Compliance column to view patch compliance information about a server.

- **Type:** This shows the type of patch, such as Windows Hotfix or Windows Update Rollup.
- **Bulletin:** (Optional) This shows the Microsoft Security Bulletin ID number for this patch.
- **Severity:** (Optional) This shows one of the following three Microsoft severity ratings for this patch:

- **Critical:** This indicates a patch whose exploitation could allow the propagation of an internet worm, without user action.
 - **Important:** This indicates a patch whose exploitation could result in a compromise of the confidentiality, integrity, availability of user data, or of the integrity or availability of processing resources.
 - **Moderate:** This indicates a patch whose exploitability is mitigated to a significant degree by certain factors, such as default configuration, auditing, or the difficulty of exploitation.
 - **Low:** This indicates a patch whose exploitation is extremely difficult, or whose impact is minimal.
- **Release Date:** This displays the date that Microsoft released this patch.
 - **Exception:** This displays the type of patch policy exception set for the selected server.
 - **Installed:** This shows if the patch is installed on the selected server.
 - **Recommended:** A check mark indicates that this patch was recommended by the vendor (Windows patch database) during the last software registration.
 - **Description:** This displays a description of the server.
 - **Opware ID:** (Optional) This displays a unique Opware ID that identifies the patch object.
 - **Locale:** (Optional) This displays the encoding of the patch contents.
 - **OS:** (Optional) This displays the operating system version of the server.

Patch Contents – UNIX

This shows the following Unix patch content information:

- **Icon:** A dimmed icon means that the patch has not yet been uploaded to the Software Library.
- **Type:** This shows the type of patch, such as Solaris Patch, HP-UX Patch Fileset, and so on.
- **Installed:** This shows if the patch is installed on the selected server.
- **Description:** This displays a description of the server.
- **Install Date:** This displays the date the patch was installed on the server.
- **Opware ID:** (Optional) This displays the unique Opware ID that identifies the patch object.
- **OS:** (Optional) This displays the operating system version of the server.

Files on the Server

The Files view enables you to browse the file system of a managed server. The File System has two main sections (similar to the Windows file system explorer): the server's directories and the contents of the selected directory.

The left side navigation panel of the Device Explorer shows all the directories of the selected server, and the right side of the Device Explorer lists the contents of the selected directory.

For each file, the SA Client lists the file's name, size, type, and date modified. To sort the files by any of these categories, click on the top of the column.



Depending upon your user permissions, you might not have access to a particular server's file system. In such a case, you cannot select and view the server's file system in the Device Explorer. If you have access to a server's file system, then you will see user names, such as Administrator, root, and Local System. These are user names used to access that server's file system as the selected user.

Viewing File Contents

To view file contents, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select **Devices † All Managed Servers**.
- 2 A list of servers will display in the Content pane. Select a server and open it. This opens the Device Explorer.
- 3 From the left side of the Device Explorer, select a File System object.
- 4 You are prompted to select a user name to log into the computer, such as Administrator, LocalSystem, or root. Select a user.
- 5 To view the contents of disk drives or folders, expand the icon. Select a directory.
- 6 From the **Actions** menu, select **View Contents**. The file content view pane appears at the bottom of the window.
- 7 To change the character encoding, select an item from the Encoding drop-down list.

Ways to Copy Files

You can copy files from a server to another directory on the same server, to a directory on another SA-managed server, or to your local computer (where the SA Client is running). You can also copy a file from your local computer to a directory on the managed server. A few restrictions apply when copying files on a managed server's file system using the Device Explorer:

- You cannot copy folders/directories.
- You can only copy to servers that you have permissions to write to and to view.
- You can only copy one file at a time.
- You cannot undo a deletion — once you delete a file, it's gone.

Copying Files Between Managed Servers

To copy files between managed servers, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select the **Devices † All Managed Servers**.
- 2 To launch the Device Explorer, open a server from the server list.
- 3 From the left side of the Device Explorer, select a File System object. To view the contents of disk drives or folders, expand the icon.
- 4 Navigate to the directory that contains the file that you want to copy and select it.
- 5 From the **Actions** menu, select **Copy To**.
- 6 In the Copy To dialog box, select from the following locations in the drop-down list:

- Managed Servers (other managed servers in the core)
 - This Server
 - Local File System
- 7 Navigate to the desired directory.
 - 8 Click **Select**.

Copying Files from Your Computer to a Managed Server

To copy files from your computer to a managed server, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select **Devices † All Managed Servers**.
- 2 To launch the Device Explorer, open a server from the server list.
- 3 From the left side of the Device Explorer, select a File System object.
- 4 Navigate to the target directory where you want to copy the file.
- 5 Use your system's file system explorer to select the file that you want to copy, then drag the file to the desired location in the Device Explorer.

Deleting Files

Once you delete a file, it cannot be recovered. (However, before you delete, you are prompted with a confirmation dialog box.)

To delete a file, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select the **Devices † All Managed Servers**.
- 2 To launch the Device Explorer, open a server from the server list.
- 3 From the left side of the Device Explorer, select a File System object.
- 4 Select a file to delete from the Content pane.
- 5 From the **Actions** menu, select **Delete**.
- 6 Click **Yes** in the confirmation dialog box.

Renaming Files

To rename a file, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select the **Devices † All Managed Servers**.
- 2 To launch the Device Explorer, open a server from the server list.
- 3 From the left side of the Device Explorer, select the File System object. To view the contents of a folder, expand the folder.
- 4 Select the file that you want to rename, and from the **Actions** menu, select **Rename**.
- 5 Enter a new name for the file, then press ENTER. Pressing the ESC key on your keyboard will cancel the rename operation.

Creating a Configuration Template from a File

For any file on a managed server, you can create a configuration template.

To create a configuration template from a file, select the file. From the **Actions** Menu, select **Create Configuration Template**. See the *SA User Guide: Application Configuration* for more information.

Creating a Package from a File

For any file on a managed server, you can create an installable software package. For each package, you can specify the customer assignment, the reboot requirements, and the pre/post install and pre/post uninstall scripts.

To create a package from a file on the managed server file system, select the file. From the **Actions** menu, select **Create Package**. See the *SA User Guide: Software Management* for information on how to create a package.

Windows COM+ Objects

This window displays a read-only view of all the COM+ objects on the selected managed server. In the Server Explorer window, the Views pane displays the following two folders for browsing COM+ objects:

- **All Objects:** This is a flat list of all the COM+ objects on the managed server.
- **Component Categories:** This contains an alphabetical list of all COM component categories.

To view the contents of a COM+ object, perform the following steps:

- 1 Select the All Objects or the Component Categories folder. In the Content pane, expand the folder until you reach an object.
- 2 To view the contents of a COM+ object, from the **Actions** menu, select **View Contents**. The contents will then display.
- 3 If the content of the COM+ object uses a different encoding, choose the appropriate encoding type from the Encoding drop-down list.
- 4 You must have specific user permissions to view Windows COM+ objects. If you are unable to access the Windows Registry, contact your SA administrator.

Windows Registry

This window displays a read-only view of the Windows registry on the selected Windows managed server. You can navigate to this registry much like the regedit tool on the Windows operating system.

Folders on the left side of the window represent keys in the registry. Clicking a folder on the left displays entries in a key in the right window.

To view Windows Registry items, select the top-level Windows Registry icon in the Server Explorer and select a user from the menu. Your user must have proper permissions to view Windows Registry keys. If your user is unable to access the Windows Registry for the selected managed server, contact your SA Administrator.



The HKEY_CLASSES_ROOT might have thousands of entries and can take time to load.

Services (Windows and Linux)

The Services window shows you a list of all running services on the selected managed server. Depending on the installed operating system, you can perform different operations on the services:

- For Windows services, you can start, stop, pause, resume, and restart a service. You can also set the service to start manually, to start automatically when the system is rebooted, or to be disabled altogether.
- For Linux servers (supported by Red Hat and SuSE versions), you can perform any action that a particular service supports. Supported actions may vary from service to service, for example, start, stop, restart, condrestart, or status. You can also specify the run levels that you want a service to run under.

To perform an operation on a service, select the service and right-click.

Discovered Software

The Discovered Software feature provides a signature-based software discovery mechanism for Windows and UNIX managed servers to help you manage applications and software that are not managed by SA.

Specifically, Discovered Software:

- Discovers unregistered software which is not currently managed by SA.
- Creates an inventory of software that is not installed as part of an OS-registered application, or that was custom built
- Provides system administrators the ability to create snapshots of the discovered software on a server and then periodically audits against the snapshots over time.
- Enables system administrators to track in-house or custom built software.
- Gives auditors a convenient method for discovering unsupported or unlicensed software installed on a server.

To enable this feature, you need to create an “inventory” snapshot of a server, which takes a picture all of the software and application information on the server. Additionally, you can also use an audit to capture the current state of a server’s software installations and, by running the audit on a regular schedule, you can monitor any installation changes over time.

For more information on creating an inventory snapshot, see the *SA User Guide: Audit and Compliance*.

Windows IIS Metabase

This window displays a read-only view of the IIS Metabase on the selected Windows managed server. You can use this window to browse the IIS Metabase much like one of the metabase browsing tools such as metaedit or the IIS Metabase Browser.

The left side of the Metabase window displays the hierarchical layout of the metabase tree. Selecting an item in the tree on the left shows the data items associated with the selected key in the right hand view. Clicking the (+) symbol to the left of a key item will expand the item's child keys.

To view Windows IIS Metabase items, select the top-level Windows Metabase icon in the Server Explorer, right-click, and select a user. Your user must have permissions to view Windows Metabase items. If your user is unable to access the Windows Registry, contact your SA Administrator.

Windows IIS 7.0

The Windows IIS 7.0 server module allows you to view various elements and configuration of a server's IIS 7.0 application, such as Application Pools, Web Sites, and Features.

Add to Library/Add to Software Policy

From inside a server's Device Explorer † Inventory, you can add selected IIS 7.0 configuration items to the SA library or to a software policy.

For example, you can expand the IIS 7.0 Application Pools hierarchy in the Device Explorer, select an AppPool, right-click, and select **Add to Software Policy**. Using software policies, you can create a policy based upon the Application Pool configuration, attach it to other servers, and then remediate (install) onto other servers running IIS 7.0 and force them to conform to your company's standards.

If you select Add to Library, the IIS 7.0 configuration item becomes accessible to other users on your data center, for use specifically in software policies.

For more information on using Software Policies, see the *SA User Guide: Software Management*.

Using with Audits and Snapshot Specifications

You can also use IIS 7.0 inside of audits and snapshot specifications. In a snapshot specification, you can capture the state of your IIS configuration on a server you know to have a good configuration (a "golden" server), and use that to compare against other "target" servers running IIS 7.0. If any target server IIS 7.0 configurations do not match the golden server's IIS 7.0 configuration, you can remediate those servers to ensure they are configured how you want them to be.

You can also use Audits to check a server's IIS 7.0 configuration on a time or regular basis, so you can keep track of a server's IIS 7.0 configuration, and remediate the server if it ever becomes "non-compliant."

For more information on creating audits and snapshot specifications for auditing and snapshotting IIS 7.0 configurations, see the *SA User Guide: Audit and Compliance*.

Internet Information Server (IIS)

The Internet Information Service (IIS) window allows you to view the real time information about IIS for a Windows server, including IIS 7.0 for Windows 2008. For a Windows server you can view IIS information such as Server name, Server type, Server state, Log file path, and Document file path.

For Windows 2008 servers running IIS 7.0, you can view Application Pools, Sites, and Features. You can select these objects and

To view the information for the Internet Information Service server object, you will need the appropriate permissions. See the *SA Administration Guide* for information about the permissions required for the server object.



When you access the Internet Information Server for the first time, it may take a few minutes to load the server object. Subsequent usage of the server object will be significantly faster.

Using the Audit and Remediation feature you can specify audit rules for the Internet Information Service to compare Internet Information Service configurations against a baseline server, or user-defined values, or a server snapshot. For more information, see the *SA User Guide: Audit and Compliance*.

Local Security Settings

The Local Security Settings window allows you to view the real time information about security settings for a Windows managed server. For every Windows server you can view security settings such as Password policy, Audit policy, User rights, and Security options.

To view the information for the Local Security Settings server object, you will need the appropriate permissions. See the *SA Administration Guide* for information about the permissions required for the server object.



When you access the Local Security Settings for the first time, it may take a few minutes to load the server object. Subsequent usage of the server object will be significantly faster.

In the SA Client you can manage the Local Security Settings information by adding it to a software policy or audit.

- Using the Software Management feature, you can deploy the Local Security Settings on a managed server. See the *SA User Guide: Software Management* for information.
- Using the Audit and Remediation feature you can specify the audit rules for the Local Security Settings and then remediate any differences found between the target server and the audit rule. See the *SA User Guide: Audit and Compliance*.

Registered Software

The Registered Software view allows you to view real time information of all the packages and patches installed on a managed server. For each package or patch you can view information such as Name, Version, Release, Unit Type, and Installed Unit.

To view the information for Registered Software, you will need the appropriate permissions. See the *SA Administration Guide* for information about the permissions required for the server object.



When you access Registered Software for the first time, it may take a few minutes to load the server object. Subsequent usage of the server object will be significantly faster.

Using the Audit and Remediation feature you can specify the audit rules for Registered Software to compare package and patch configurations against a baseline server, or user-defined values, or a server snapshot. For more information, see the *SA User Guide: Audit*

and Compliance.

Runtime State

The Runtime State window allows you to view real time information about the run time data for a managed server. It provides information about the DNS servers, Routes, and Processes for every managed server.

To view the information for the Runtime State server object, you will need the appropriate permissions. See the *SA Administration Guide* for information about the permissions required for the server object.



When you access the Local Security Settings for the first time, it may take a few minutes to load the server object. Subsequent usage of the server object will be significantly faster.

Using the Audit and Remediation feature you can specify the audit rules for the Runtime State to compare Runtime state configurations against a baseline server, or user-defined values, or a server snapshot For more information, see the *SA User Guide: Audit and Compliance*.

Windows .Net Framework Configuration

The Windows .Net Framework Configuration window allows you to view real time information about Assembly Cache and Configured Assembly List for a Windows server.

For each Assembly Cache you can view information such as Assembly Name, Version, Locale, Public Key Token, Cache file (GAC or ZAP), Processor Architecture, Custom, and File name.

For every Configured Assembly List, you can view information such as Assembly Name, Public key token, Codebases, Binding policy, File name, File data.

To view the information for the Windows .Net Framework Configuration server object, you will need the appropriate permissions. See the *SA Administration Guide* for information about the permissions required for the server object.



When you are accessing the Windows .Net Framework Configuration for the first time, it may take a few minutes to load the server object. Subsequent usage of the server object will be significantly faster.

In the SA Client you can manage Windows .Net Framework Configuration information by adding it to a software policy or audit.

- Using the Software Management feature, you can deploy the Windows .Net Framework Configuration on a managed server. See the *SA User Guide: Software Management* for more information.
- Using the Audit and Remediation feature you can specify the audit rules for assembly cache and configured assemble list and then remediate any differences found between the target server and the audit rule. For more information, see the *SA User Guide: Audit and Compliance*.

Users and Groups

The Windows Users and Group window allows you to browse and manage users and groups information on a Windows server. The Unix Users and Group window allows you to browse and manage users and groups information on a Unix server.

For every SA User you can view information such as Name, Description, Country code, Home directory, Password, Number of Logons, and Last logoff and logon time.

For every SA User Group you can view information such as Group Name and Description.

To view the information for the User's and Groups server object, you will need the appropriate permissions. See the *SA Administration Guide* for information about the permissions required for the server object.



When you access the Users and Groups for the first time, it may take a few minutes to load the server object. Subsequent usage of the server object will be significantly faster.

In the SA Client you can manage the Users and Group information by adding it to a software policy or audit.

- Using the Software Management feature, you can deploy the Users and Groups on a managed server. See the *SA User Guide: Software Management* for information about the Software Management feature.
- Using the Audit and Remediation feature you can specify the audit rules for the Users and Groups and then remediate any differences found between the target server and the audit rule. For more information, see the *SA User Guide: Audit and Compliance*.

Basic Server Management Tasks

You can perform the following basic server management tasks in the SA Client:

- [Refreshing Server Status](#) on page 95
- [Deactivating a Server](#) on page 96
- [Rebooting a Server](#) on page 96
- [Opening a Remote Terminal](#) on page 97
- [Changing User Passwords on Managed Servers](#) on page 98
- [Running Server Communication Tests](#) on page 139

Refreshing Server Status

Refresh a server to see if anything has changed on the server since you last looked at it in the SA Client. Refreshing a server retrieves the latest server information from the model repository and displays it. Refreshing a server's status is good idea from time to time to make sure you are looking at current data on the server.

For more information on server statuses, see [Ways to Use the Device Explorer](#) on page 68.

To refresh a server's status, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select **Devices**.

- 2 Select one of the server categories, such as Device Groups, All Managed Servers, Unprovisioned Servers, or Virtual Servers. (You cannot refresh server status of unmanaged servers or a device group.)
- 3 Select one or more servers.
- 4 Right-click or select the **Actions** menu and select **Refresh Server**.

Deactivating a Server

Deactivating a server removes the server from management by deactivating its SA Agent. You might want to deactivate a server, for example, if you are moving the server to a warehouse for storage. Or, you might want to deactivate a server when you need to rebuild it from scratch, without using the OS Provisioning feature.

When you deactivate a server, information about the server remains in the Model Repository for auditing purposes.

Deactivating a server accomplishes the following tasks:

- Removes custom attributes from the server.
- Deletes any configuration tracking policies from the server that are associated with backups.
- Sets the server life cycle value to Deactivated.

To deactivate a server, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select the **Devices † All Managed Servers**.
- 2 Select a server, right-click, and select **Deactivate Agent**.

Rebooting a Server

You can reboot a single server or a group of server immediately, or schedule the reboot for a later time. If you choose to reboot a group of servers, all servers contained in the group will be rebooted.





In order to be able to reboot a server, your user needs to belong to a user group that has the Reboot Server permission. For more information, contact your SA Administrator.



If you are rebooting a hypervisor server that is hosting other virtual servers, then all virtual servers being hosted by that hypervisor will be shut down as well. Whether or not the hosted virtual servers get rebooted depends upon the individual virtual server's configuration.

To reboot a server, perform the following steps:

- 1 Launch the SA Client. From the Navigation pane, select **Devices † All Managed Servers** or **† Device Groups**.
- 2 Select a server or group of servers, right-click, and select **Reboot Server**.
- 3 In the Reboot Server window, step one lists the server or servers you have selected to reboot. Click **Next**.

- 4 In the Scheduling page, choose if you want to reboot the server or group of servers immediately, or at some later time and date. To run the reboot at a later time, select **Analyze and Run Task At**, and then choose a day and time.
- 5 Click **Next**.
- 6 In the Notifications page, by default your user will not have a notification email sent when the reboot finishes, whether or not the reboot job is successful. To add an email notifier, click **Add Notifier** and enter an email address.
- 7 (Optional) You can specify if you want the email to be sent upon success of the reboot job () and/or failure of the reboot job ()
- 8 (Optional) You can specify a Ticket Tracking ID in the Ticket ID field. The ticket ID field is only used when SA Professional Services has integrated SA with your change control systems. It should be left blank otherwise.
- 9 Click **Next**.
- 10 In the Summary View page, click **Start Job** to reboot the selected server or group of servers. When the job has run, click **View Results** to view the results of the reboot job.
- 11 In the Job Status page, you can see the progress of the job if you ran the job immediately. If the job is scheduled to run, you can close the window, and to view the job details, from the left side of the SA Client, select **Jobs and Sessions** † **Job Logs**.

SA Tasks that Reboot a Server

There are a few other SA tasks that will initiate a server reboot, depending on the options set in the task:

- Installing or uninstalling a patch on Windows or UNIX servers. See the *SA User Guide: Server Patching* for more information.
- Remediating a Patch policy. See the *SA User Guide: Server Patching* for more information.
- Installing a package and remediating a software policy. See the *SA User Guide: Software Management* for more information.

Opening a Remote Terminal

To open a remote terminal for any managed server, perform the following steps:

- 1 From the SA Client navigation pane, select the **Devices** tab.
- 2 In the navigation pane, select **All Managed Servers**.
- 3 Select a managed server.
- 4 Select the Actions menu or right click and select **Open With †Remote Terminal**. For some operating systems, this displays a menu of users with which to log in, typically root, Administrator and root administrator. Otherwise this opens a window to the managed server.
- 5 If a menu of users is displayed, select the desired user to log in with. Otherwise skip this step.
- 6 Log in to the remote terminal.

Changing User Passwords on Managed Servers

You can change the password of any user on any of your managed servers using the SA Client. Perform the following steps.

- 1 In the SA Client, select the Devices tab. This displays the Device Groups node and the Servers node in the navigation panel.
- 2 Under the Servers node, select All Managed Servers or Virtual Servers. This displays all the corresponding servers. Select one or more servers
Or under Device Groups, select one or more device groups.
- 3 Select the **Actions** menu or right click and select **Run Extension † Change User Passwords for Selected Servers**.
Or, if **Run Extension † Change Passwords** is not shown, select **Run Extension † Select Extension**. This displays the Select Extension window and lists the available extensions. Select **Change User Passwords for Selected Servers** in the Select Extension window then select OK.
This displays the Run Program Extension window showing the servers and device groups you selected.
- 4 You can optionally add servers and device groups with the Include Devices button or remove selected servers and device groups with the Remove button.
- 5 Select the Next button to display the Program Properties with the name of the extension you are running. Verify that it is the Change User Passwords for Selected Servers extension.
- 6 Select the Next button to display the Options screen.
- 7 **Run as root or Administrator:** This setting specifies the login credentials to use on the managed servers to perform the change password action. Select Yes to use root or Administrator. Select No to perform the operation as the user whose password you are changing. If you selected No, you must enter the user's current password.
- 8 **User:** Enter the user name whose password you want to change. This user must be a valid user on all the selected servers.
- 9 **Current Password:** If you selected No for "Run as root or Administrator, enter the current password of the user whose password you want to change. If you selected Run as root or Administrator for the credentials, the current password is not needed.
- 10 **New Password:** and **Confirm New Password:** Enter the new password.
- 11 **Program Timeout:** This specifies how long to allow the job to run before aborting if it does not finish. This setting can be useful to ensure the job runs within a maintenance window.
- 12 To skip the remaining settings and start the job immediately, select Start Job. Otherwise, select the Next button to schedule when to run the password change job.
- 13 **Schedule** - Specify whether you want the job to run immediately or in the future. If you want the job to run in the future, specify the start time and date.
- 14 Select Next to display the Email Notifications screen.
- 15 **Email Notifications** - You can request that an email message be sent when the job finishes. Use Add Notifier and Remove to change the recipients.

You can optionally add a ticket identifier to the job for tracking purposes. The ticket identifier is retained with the job information.

- 16 Select Next to display the Job Status screen.
- 17 **Job Status** - Select the Start Job or Schedule Job button. This runs the job or schedules it to be run in the future and displays the Job ID number in the window banner. You can use the Job ID number to look up the job under the Jobs and Sessions tab.

Once the job finishes, you can view the results. Select a server to display the results for that server.
- 18 Select Close. At any time you can view the job results by selecting the Jobs and Sessions tab in the SA Client navigation panel and locating the job in the job history.

About Device Groups

Device groups let you organize servers and other types of network and storage devices into logical sets. A device group is simply a container of a set of servers and other devices. Grouping servers lets you perform actions such as installing patches or remediating servers on all of the servers in a device group simultaneously, instead of having to perform the action on each individual server one at a time.

Below are some recommended ways of grouping servers.

- Grouping servers by OS version
- Grouping servers by customer
- Grouping servers by facility
- Grouping servers by deployment stage category
- Grouping servers by server use category
- Group servers by virtual technology
- Grouping servers by operational boundaries, for example, grouping together all servers that require identical application configurations
- Grouping servers to control access, for example, creating device groups that are associated with a specific user group

Characteristics of Device Groups

Device groups contains the following characteristics listed in [Table 5](#):

Table 5 Device Group Characteristics


	Public Groups	Private Groups
Static Groups	Access: Visible to all. Membership: Fixed.	Access: Visible only to the owner. Membership: Fixed.
Dynamic Groups	Access: Visible to all. Membership: Based on rules.	Access: Visible only to the owner. Membership: Based on rules.

- All device groups are either public or private.

- **Public groups** are accessible to all users with the Manage Public Device Groups permission.
- **Private groups** are accessible only to the user who created the group.
- All device groups are either static or dynamic.
 - **Static groups** contain a fixed set of devices that you add manually to the group.
 - **Dynamic groups** contain all the servers that satisfy a set of rules that you define. Dynamic groups automatically add or remove servers based on whether or not the servers satisfy the defined rules.
- Individual servers can be included in multiple device groups or not included in any device groups.
 - Adding a server to a device group does not remove the server from the All Managed Servers list in the SA Client.

Figure 25 shows these four types of device groups in the SA Client. The group named “M1 group” is a private, dynamic group. The group named “Hardware Groups” is a public, static group.

Figure 25 Device Group Types



Device Groups and Subgroups

Device groups can contain other device groups, called subgroups. In other words, device groups are hierarchical, meaning they can be nested, with the following caveats:

- Private and public groups cannot be mixed in a hierarchy. That is, a private group cannot be a member of a public group and vice versa.
- Static and dynamic groups can be mixed in a hierarchy. That is, a static group can be a member of a dynamic group and vice versa.
- The rules for a dynamic group are not inherited from a parent dynamic group to a child dynamic subgroup. Each group defines its own set of rules, independent of whether or not it is part of another group.
- Groups do not inherit custom attributes from their parent groups.
- When you run an operation on a device group that contains subgroups, the operation also applies to all the servers in the subgroups. For example, remediating a device group remediates all servers in its subgroups, but the subgroups do not inherit the software policy attached to the device group. However, when an Application Configuration operation within the SA Client is applied to a device group that contains subgroups, the

operation does not apply to all the servers in the subgroups. It only applies to the servers in the group upon which the operation was directly applied.

Public Device Groups

Public groups are visible to all users, and can be used by any SA user. Public device groups can also be used for modeling. For more information on modeling, see [Public Device Group Modeling](#) below.

Public device groups can be created, edited, or deleted by any user who has Manage Public Device Groups permissions. Only users with Manage Public Device Group permission can add members to a static public device group or change the rules that govern the dynamic public device group.

Accessing servers in a public device group also depends on the Device Group permission in the SA Web Client. See the *SA Administration Guide* for more information about setting device group permissions.

Public Device Group Modeling

With SA modeling, the desired state of a server is defined and then applied to servers. In the case of public device groups (static and dynamic), you can define a model consisting of application configurations, patch policies, software policies, and custom attributes, which will be applied to all servers in the group. The modeling information is attached to the group, but not to any subgroups.

If the modeling information changes, the servers in the group are not affected until the remediation operation runs on those servers. If the model has already been remediated on that server when it is removed from the group, the installed material will be removed during the next remediation.

Private Device Groups

Each SA user automatically gets their own private device group area with the same name as their SA user name. Only the user who creates the private device groups can see and manage them. These groups are not visible to the other SA users. Private groups behave the same way as public groups, with the exception that modeling is not available for private groups.

Private device groups can be created by any user belonging to a user group that has access to the Servers list.

Static Device Groups

A static group has servers that are added to and removed from the group manually. When using static groups, you first create the group, and then select the servers to populate it.

Dynamic Device Groups

Dynamic device groups contain servers and other devices that are added to or removed from the group based on a set of user-defined rules. Once the rules have been created, SA will search for servers and devices that match the rules and add them to the group.

If the rules are changed and if the servers in the environment change or if servers are added to or removed from the managed environment, servers will be added to or removed from the group automatically. SA automatically recalculates dynamic group membership every hour.

Rules apply only to the group being created or modified and not to any of its subgroups.

Ways to Create Device Groups

In the SA Client, you can create a device group from the All Managed Servers list or by performing a server search, and saving the resulting list of servers or the rules as a group.

You can create the following types of device groups:

- [Creating a Static Device Group](#) on page 102
- [Creating a Dynamic Device Group](#) on page 106
- [Creating a Device Group Using Search](#) on page 113

About Static Device Groups

This section describes static device groups. Static device groups contain a fixed set of devices that you add manually to the group.

Creating a Static Device Group

This section describes how to create a static device group. Static groups contain a fixed set of devices that you manually add to or remove from the group. Static device groups must be either public or private.



To create a public static device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

To create a static device group, perform the following steps:

- 1 From the navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Content pane. All the public device groups are under Public. All your private device groups are under your user name.
- 2 Navigate to the location where you want to create your group.
 - To create a public group, select Public or an existing group under Public.
 - To create a private group, select your user name or an existing group under your user name.
- 3 From the **Actions** menu, select **Device Group † New Static Group**.

This creates an empty device group named New Device Group (n), where n is a number based on the number of new device groups already in existence.
- 4 You can rename the device group by selecting it and either right clicking on it and selecting **Rename** or by selecting the **Actions † Rename** menu item.

After you create a static device group, you can add servers to the group. See [Adding a Server to a Static Device Group](#) below.

Adding a Server to a Static Device Group

You can use either of the following two methods to add a server to a static device group: [Method 1 - Select Device Group First, then Servers](#) on page 103 or [Method 2 - Select Servers First, then Device Group](#) on page 104.




To add a server to a public static device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

Method 1 - Select Device Group First, then Servers

To add a server or device group to a static device group, perform the following steps:

- 1 From the Navigation pane, select **Devices** † **Device Group**. The device groups appear in the Content pane. You can distinguish between static and dynamic device groups by their icon. See [Table 3 Device Group Status and Icons](#) on page 67.
- 2 Navigate to the desired static device group. Select the device group in the Content pane, and from the **Actions** menu, select **Open**. The Device Group Explorer appears.
- 3 From the Views pane of the Device Explorer window, select Device Membership. This displays a list of servers in the group.
- 4 From the **Actions** menu, select **Add**. The Add Members to Static Group window appears.

Figure 26 The Add Members to Static Group Window in the SA Client



- 5 Select one or more servers to add to the static device group.

- 6 Click **Add to Group**. The selected servers are added to the device group and appear in the Device Group Browser.
- 7 From the **File** menu, select **Save** to save the device group.

Method 2 - Select Servers First, then Device Group

Perform the following steps to add a server to a static device group:

- 1 From the Navigation pane, select **Devices † All Managed Servers**. The list of managed servers appears in the Content pane.
- 2 From the Content pane, select one or more servers and then from the **Actions** menu, select **Add to Device Group**. The Add to Group window appears.
- 3 Select the static device group to add the servers to.
- 4 Select **Add to Group**. The selected servers are added to the static device group.

Method 3 - Import CSV File

You can add servers to a static device group by importing a CSV (comma-separated value) file containing the host names of the servers you want to add to the group. The CSV file contains a single column of string data representing server host names. The following characters have special meanings:

- The asterisk (*) indicates zero or more of any legal character (letters, numbers, the underscore character and dot).
- Lines that start with the “#” character are ignored. You can use them to insert comments.
- Blank lines are ignored.

For example, the following shows a CSV file that specifies a server named “myhost.hp.com”, all servers that start with the string “ca”, and all servers that end with “.mycustomer.com”:

```
# This is a comment line.
myhost.hp.com
ca*
*.mycustomer.com
```

The following shows a list of hosts and which hosts would be selected by this CSV file:

myhost.hp.com	This host would be selected.
myhost2.hp.com	This host would not be selected.
ca23.hp.com	This host would be selected.
ca28.hp.com	This host would be selected.
carl.hp.com	This host would be selected.
acam.hp.com	This host would not be selected.
host01.mycustomer.com	This host would be selected.

To add servers to a device group from a CSV file, perform the following steps.

- 1 From the Navigation pane, select **Devices † Device Group**. The device groups appear in the Content pane. You can distinguish between static and dynamic device groups by their icon. See [Table 3 Device Group Status and Icons on page 67](#).
- 2 Navigate to the desired static device group. Select the device group in the Content pane, and from the **Actions** menu, select **Open**. The Device Group Explorer appears.
- 3 From the Views pane of the Device Explorer window, select Device Membership. This displays a list of servers in the group.

- 4 From the **Actions** menu, select **Import...** The Import window appears.
- 5 Select the CSV file and click Open. This displays the Add Members to Static Group window that lists the servers that can be added to the device group.
- 6 Select the servers you want to add to the device group.
- 7 Select **Add to Group**. This adds the selected servers to the device group.

Removing Servers from a Static Device Group

In a static device group, servers must be removed manually. Removing a server only removes the server from the device group and not from the All Managed Servers list. Servers can belong to more than one device group, so if you want to remove a server from each device group that it belongs to, then you must locate and remove each instance of the server from all the device groups it is a member of.



To remove servers from a public device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

Method 1 - From the Device Group Explorer

To remove a server from a static device group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Content pane.
- 2 Navigate to the desired static device group. Select the device group in the Content pane, and from the **Actions** menu, select **Open**. The Device Group Explorer appears.
- 3 From the Views pane, select Device Membership. The list of servers in the device group appears in the Content pane.
- 4 Select the server you want to delete. From the **Actions** menu, select **Remove**. Or right click on the server and select Remove. The selected server is removed from the static device group.
- 5 From the **File** menu, select **Save** to save the device group.

Method 2 - From the SA Client

To remove a server from a static device group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Content pane.
- 2 Navigate to the desired static device group. Select the device group and double-click to display its members.
- 3 Select the server displayed in the Content pane. From the **Actions** menu, select **Remove Member**. The server selected is removed from the static device group.

Method 3 - From the Device Explorer

To remove a server from a static device group, perform the following steps:

- 1 From the Navigation pane, select **Servers † All Managed Servers**. The list of servers appears in the Content pane.

- 2 Navigate to the desired server. Select the server and double-click to display it in the device explorer window.
- 3 Select Relationships in the Navigation pane. This displays all the static groups the server belongs to.
- 4 Select a static device group from the Content pane.
- 5 From the **Actions** menu, select **Remove from Group**. Or right click the server and select Remove from Group. The server selected is removed from the static device group.

About Dynamic Device Groups

This section describes dynamic device groups. Dynamic device groups contain all the servers that satisfy a set of rules that you define. Dynamic groups automatically add or remove servers based on whether or not the servers satisfy the defined rules.

SA automatically recalculates the members of every device group every hour and whenever any device attribute changes or when a dynamic device group rule changes. SA examines the rules you have defined and determines which servers satisfy the rules. The SA Client displays when the last recalculation occurred in the Properties view for each dynamic device group.

Creating a Dynamic Device Group

Dynamic device groups are defined by one or more rules. The servers in a dynamic group are added or removed automatically based on the rules that you define. This section describes how to create a dynamic device group. The following section describes how to create rules that determine the members of the group.



To create a public dynamic device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

To create a dynamic device group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of existing device groups appears in the Content pane. All the public device groups are under Public. All your private device groups are under your user name.
- 2 Navigate to the group where you want to create your new group.
 - To create a public dynamic device group, select Public or navigate to a group under Public.
 - To create a private dynamic device group, select your user name or navigate to a group under your user name.
- 3 From the **Actions** menu, select **Device Group † New Dynamic Group**.

This creates an empty device group named New Device Group (n), where n is a number based on the number of new device groups already in existence.
- 4 You can rename the device group by selecting it and either right clicking on it and selecting **Rename** or selecting the **Actions † Rename** menu item. Enter the name of the device group in the Content pane.
- 5 After you create a dynamic device group, you need to define the rules for the group. For more information, see [About Rules for a Dynamic Device Group](#) below.

Recalculating the Members of a Dynamic Device Group

SA automatically recalculates the members of every device group every hour and whenever any device attribute changes or when a dynamic device group rule changes. SA examines the rules you have defined and determines which servers satisfy the rules. The SA Client displays when the last recalculation occurred in the Properties view for each dynamic device group.

You can also manually recalculate the members of a dynamic device group by performing the following steps.

- 1 In the SA Client, select the **Devices** tab.
- 2 Navigate to the desired device group under the Device Groups node in the navigation pane.
- 3 Select one or more dynamic device groups.
- 4 Select the **Actions** menu or right-click and select **Device Group † Recalculate**. SA examines the dynamic device group rules, determines all the managed servers that match the rules and updates the members of the device group.

About Rules for a Dynamic Device Group

Servers and other devices are automatically added to and removed from dynamic device groups by SA based on the rules you create for the group. You can change the membership of a dynamic group by adding, deleting, or modifying these rules. See also [Adding Rules for a Dynamic Device Group](#) on page 110 and [Modifying Rules for a Dynamic Device Group](#) on page 111.

A rule is a condition that specifies values for some attribute of servers such as IP address, server name, operating system, and many others. Servers either comply with each rule or not. For example, the following are example rules and example servers that demonstrate how servers would be included in the group or excluded from the group.

- All servers with a name that begins with the string “pro”. A server named “provision1.hp.com” would be included by this rule. A server named “approval4.hp.com” would not.
- All servers that are in the subnet 192.168. A server at IP address 192.168.123.7 would be included by this rule. A server at IP address 192.167.43.18 would not.
- All servers with operating system HP-UX version 11.31. All servers with this operating system would be included by this rule. Servers with any other operating system or any other version of HP-UX would not.
- All servers attached to a particular software policy named “AccountingDB”.
- All servers that have a particular patch installed.

You can define a wide variety of rules and create as many device groups as you need to make managing your IT environment faster, easier and more efficient.

Format of Rules for Dynamic Device Groups

Rules for dynamic device groups take the following form:

Search for: **<Device>**


Where: **<Attribute> <Operator> <Value>**

- *<Device>* is typically Server because device groups contain servers, but it can also be other kinds of devices.
- *<Attribute>* is some piece of data about the device you want the rule to examine.
- *<Operator>* is a comparison you want to perform between the *<Attribute>* and the *<Value>*.
- *<Value>* is the specific data you want to compare to the *<Attribute>* using the *<Operator>*.

Example Rule 1 - Servers Running a Particular OS

Figure 27 displays a dynamic device group rule that selects all servers running the AIX 6.1 operating system and places them into the device group:


Figure 27 Select All Servers Running AIX 6.1 Device Group Rule



Example Rule 2 - Servers Attached to a Software Policy

Figure 28 displays a dynamic device group rule that selects all servers attached to the software policy “HP-UX ISMTool”:


Figure 28 Servers Attached to a Software Policy Device Group Rule



Example Rule 3 - Servers with a Particular Name

Figure 29 displays a dynamic device group rule that selects all servers with a name beginning with the characters “pro”:

Figure 29 Servers with a Particular Name Device Group Rule




Example Rule 4 - Servers in a Subnet

You can create device groups containing servers on a particular subnet. You can use an IP address and either a **subnet mask** or a **CIDR number** to specify the network address of the subnet. When you select IP Address as the server attribute to search on and Within Subnet as the operator, you must enter an IP address and either a subnet mask or a CIDR number as follows:

- <IP address>/<Subnet mask>
- <IP address>/<CIDR number>


For example, both of the following examples specify a subnet of 192.168:

- Subnet mask: 192.168.0.0/255.255.0.0



The screenshot shows a 'Device Membership' search interface. The 'Search For' dropdown is set to 'Server'. The 'Where' section has 'IP Address (Any)' selected, the operator is 'Within Subnet', and the input field contains '192.168.0.0/255.255.0.0'.

- CIDR block: 192.168.0.0/16



The screenshot shows a 'Device Membership' search interface. The 'Search For' dropdown is set to 'Server'. The 'Where' section has 'IP Address (Any)' selected, the operator is 'Within Subnet', and the input field contains '192.168.0.0/16'.

Configuring Multiple Rules for Dynamic Device Groups

You can configure multiple rules and combine them with a logical And or a logical Or. Select to add a rule. Select to remove the selected rule or rules. Select either Logical And or Logical Or to logically combine the rules.




You can create more complex logical expressions using the SearchService interface in the com.opsware.search package of the SA Twister API. For more information on the SA Twister API, see the *SA Platform Developer Guide*.

Example of Multiple Rules

Figure 30 displays a dynamic device group rule two rules combined with a logical And to select all servers that both have a name that begins with the characters “pro” and run AIX 6.1:

Figure 30 Multiple Dynamic Device Group Rule



Adding Rules for a Dynamic Device Group

Rules determine which servers are included in a dynamic group.







To add a server to a dynamic public device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

To add a rule to a dynamic group, perform the following steps.

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Navigation pane and the Content pane.
- 2 In the Navigation pane, navigate to the dynamic device group you want to modify.
You can determine whether a device group is static or dynamic from the icon next to its name as described in [Table 3 Device Group Status and Icons on page 67](#).
- 3 From the Content pane, select the device group and then select the **Actions † Open** menu item. This opens a Group View window.
You can determine whether a group is static or dynamic from the Summary View, under Properties.
- 4 From the Views pane, select Device Membership. This displays the rules defined for the group in the Content pane. See [Figure 31](#) below.

Figure 31 Defining Rules for a Dynamic Device Group



- 5 Create a rule by first selecting the type of device you want to include in the device group from the “Search For:” drop-down list. Depending on the type of device you select, the other drop-down lists change to correspond to the device type. [Figure 31](#) shows Server selected.
- 6 Select the attribute to search on from the “Where:” drop-down list. Depending on the attribute that you select, options available for the operator and values for the rule in the remaining drop-down lists will change.
- 7 Select the operator from the next drop-down list.
- 8 Enter a value in the field, or select a value from the drop-down list, or click  to select one or more values from the Select Values window.
- 9 Click  to add additional rules and repeat steps 6 to 8. Click  to delete a rule.
- 10 Select the logic (logical And or logical Or) to be applied to the set of rules.
- 11 Click **Preview** to view the servers that satisfy all the rules and are therefore members of the device group.
- 12 From the **File** menu, click **Save** to save your rules in the dynamic device group.

Modifying Rules for a Dynamic Device Group

Rules determine which servers are included in a dynamic group. To modify a rule in a dynamic group, perform the following steps.



To modify rules for a dynamic public device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Navigation pane and the Content pane.

- 2 In the Navigation pane, navigate to the dynamic device group you want to modify.
You can determine whether a device group is static or dynamic from the icon next to its name as described in [Table 3 Device Group Status and Icons on page 67](#).
- 3 From the Content pane, select the device group and then select the **Actions † Open** menu item. This opens a Group View window.
You can determine whether a group is static or dynamic from the Summary View, under Properties, or from the Properties view next to Type.
- 4 From the Views pane, select Device Membership. This displays the rules defined for the group in the Content pane. See [Figure 31](#) below.
- 5 Modify the rules for the device group as needed. For more information on rules, see [About Rules for a Dynamic Device Group on page 107](#) and [Adding Rules for a Dynamic Device Group on page 110](#).
- 6 Click **Preview** to see the list of servers that satisfy all the rules and are therefore members of the device group.
- 7 From the **File** menu, click **Save** to save your rules in the dynamic device group.

Converting a Dynamic Group to a Static Group

You can convert a dynamic device group to a static device group. When a dynamic device group is converted to a static device group, all the servers that match the rules at that time are placed in the static device group, but the rules used to define the server membership are lost. To convert a dynamic group to a static group, perform the following steps.

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appear in the Content pane.
- 2 From the Navigation pane, navigate to a dynamic device group.
You can determine whether a device group is static or dynamic from the icon next to its name as described in [Table 3 Device Group Status and Icons on page 67](#).
- 3 From the Content pane, select the dynamic device group.
- 4 Select the **Actions † Open** menu item. This displays information about the device group in a new window.
- 5 In the Views navigation panel on the left, select Properties. This displays detailed information about the device group.
- 6 Locate the Type row and drop-down list next to it. In the drop-down list, select Static.
- 7 Select the **File † Save** menu item. This saves the group as a static group. All the rules that were used to define the dynamic group are lost.

More Device Group Tasks




This section describes additional tasks you can do with device groups.

Creating a Device Group Using Search




To create a public device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

You can create a search for servers and use the search results to create a device group. To create a device group using search, perform the following steps:

- 1 From the Navigation pane, select **Advanced Search**. The Advanced Search page appears in the Content pane.
For more information on advanced search, see the [About Advanced Searches](#) on page 35.
- 2 From the first drop-down list, select Server.
- 3 Create your search criteria by setting up a rule in the “Where:” line. Select a server attribute to search on from the first drop-down list. Depending on the attribute that you select, options in the remaining two drop-down lists (operator and value) will change.
- 4 Select the operator from the second drop-down list. The operator selected defines how the search value is treated.
- 5 Enter a value in the third field or select a value from the drop-down list or click  (only shown for some attributes) to select one or more values from the Select Values window.
- 6 Click  to add rules and repeat steps 3 to 6. Click  to delete any rules.
- 7 Select the logic (logical And or logical Or) to be applied the set of rules in the search.


[Figure 32](#) shows an advanced search with two conditions logically Anded together:

Figure 32 Advanced Search with Two Conditions Logically Anded Together



- 8 Click **Search** to run the search. The results appear in the Content pane.
- 9 Click **Save** to save your search. The Save Search window appears as shown in [Figure 33](#) below.
- 10 In the Search Type drop-down list, select Dynamic Device Group or Static Device Group.
- 11 Navigate to the location where you want to save the group, either under Private Groups or under Public Groups.
- 12 Enter the name of the new device group in the Save As text box.
- 13 Click **Save** to save your new device group.

Figure 33 The Save Search Window in the SA Client



- ▶ When you save the device group as a dynamic group, if the rules change or the servers in the environment change, servers will be added to or removed from the device group automatically. When you save the device group as a static group, the servers will be added to the device group, but all rules will be lost.
- ▶ If the search query does not return any results, then you can only save the device group as a dynamic device group.

Moving a Device Group

You can move device groups to a different location under Device Groups. You can move device groups from a private group to a public group, but you cannot move device groups from a public group to a private group. If you move a device group containing subgroups, the subgroups are also moved.

- ▶ To move a public device group or to move a private group to a public group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

To move a device group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Content pane.
- 2 From the Navigation pane, navigate to the desired group.
- 3 From the Content pane, select the device group you want to move.
- 4 From the **Actions** menu, select **Device Group † Move...**. The Move Group window appears.
- 5 Select the desired new location for the device group.
- 6 Click **Move Group**. The device group is moved to the new location.

Duplicating a Device Group

When you duplicate a device group, the servers are copied to a new group and they remain in the original group. In the SA Client, you can only select one device group at a time to duplicate.



To duplicate a public device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

To duplicate an existing device group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Content pane.
- 2 From the Navigation pane, navigate to the desired group.
- 3 From the Content pane, select the device group you want to duplicate.

- 4 From the **Actions** menu, select **Device Group † Duplicate**. This creates a copy of the device group.
- 5 You can rename the group by selecting it and selecting **Actions † Rename**.

Deleting a Device Group

Deleting a device group removes the group, but the servers in the group still remain in the All Managed Servers list and in any other groups they are members of.

A group cannot be deleted when any of the following conditions apply:

- The device group contains other device groups.
- Software policies or patch polices are attached to the group.
- Access controls are set for the group. For more information on controlling access to device groups, see “Setting the Device Group Permissions” in the *SA Administration Guide*.



To delete a public device group, you must have Manage Public Device Group permissions. To obtain these permissions, contact your SA Administrator.

To delete a server group, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Groups**. The list of device groups appears in the Content pane.
- 1 From the Navigation pane, navigate to the desired group.
- 2 From the Content pane, select the device group you want to delete.
- 3 From the **Actions** menu, select **Device Group † Delete**.
- 4 Click **Delete Selected Groups** on the confirmation dialog to delete the device group.

Device Group Explorer


The Device Group Explorer allows you to view and manage the properties of a device group in the SA Client. From the Device Group Explorer, you can perform the following actions:

- View the properties and members of a device group.
- Change a dynamic device group to a static device group.
- Add or remove members from a device group.
- View rollup compliance information for group members targeted by compliance policies such as Audit, Software, App Config, and Patch.
- Add application configurations to a device group.
- View and manage patches, patch policies and software policies associated with the servers in the group.
- Create an audit.
- Take a snapshot.
- View and create custom attributes.
- View server history.

To access a Device Group Explorer, perform the following steps:

- 1 From the Navigation pane, select **Devices † Device Groups**. The device groups appear in the Content pane.
- 2 Select a device group and from the **Actions** menu select **Open**. The Device Group browser appears as shown below.

Figure 34 The Device Group Explorer Window



- 3 To view the properties or perform an action on the device group, select one of the following views:
 - Summary
 - Properties
 - Compliance
 - Device Membership
 - Configured Applications
 - Patches for Device Groups
 - Patch Policies for Device Groups
 - Software Policies for Device Groups
 - Audits
 - Custom Attributes for Device Groups
 - History Properties for Device Groups

Summary

The Summary view lists the following information:

- **Properties:** This displays if the device group is Private, Public, Dynamic or Static.
- **Members:** This displays the total number of members in the device group.

Properties

The Properties view lists the following property information such as name, type, status, accessibility for the group of servers that you are browsing.

Compliance

The Compliance view provides a summary of how the servers in the device group comply with the patch, software, and audit policies attached to the device group. For more information, see the *SA User Guide: Server Patching*, the *SA User Guide: Software Management*, and the *SA User Guide: Audit and Compliance*.

Device Membership

From inside each device group, you can view all members — managed servers and other groups of servers and other devices — that belong to the group. For each server that belongs to the group, the system displays its name, IP address, OS, customer, facility, and any description.

Configured Applications

If the device group is public, then you can add an Application Configuration to the group. The Application Configuration applies to all servers and groups in this group.

- The Installed Configurations tab allows you to browse and edit all Application Configurations attached to the device group.
- The Backup Configurations tab provides a history of all changes made to the selected application configuration template, and allows you to revert to a previous version of the configuration.

See the *SA User Guide: Application Configuration* for more information.

Patches for Device Groups

For complete information on patching servers, see the *SA User Guide: Server Patching*.

This window displays all patches associated with the selected server group.

Show Options

You can use the Show drop-down list to filter the following types of patch information displayed in the Device Groups Explorer:

- **Patches with Exceptions (Windows Only):** This option displays all patches that have exceptions for Windows servers (such as always install or never install) *and* has one of the following conditions:
 - The patches are not currently installed and are recommended by the vendor.
 - The patches are currently installed.
- **All Patches:** This displays all patches that are associated with the operating system of a server.

Patch Contents

This section displays the following patch contents information:

- **Icon:** A dimmed patch icon indicates that the patch has not yet been uploaded to the Software Library.
- **Name:** The QNumber of a patch that is a hotfix or an update rollup. Service pack patches do not have a QNumber.
- **Compliance:** The patch compliance level, as defined by your patch administrator:
 - **Non-compliant** (red): The patch is installed on the server and is not in the policy or the patch is not installed on the server and is in the policy.
 - **Partial** (yellow): The policy and exception do not agree and the exception does not have data in the Reason field.
 - **Compliant** (green): This indicates any of the following conditions:
 - A patch is installed on the server and is in a policy or a patch is not installed on the server and is not in a policy.
 - A patch is installed on the server and there are additional patches with the same QNumber in a patch policy or exception. In this case, all patches with the same QNumber are considered installed when SA calculates patch compliance.
 - A patch is not installed on the server and is in a patch policy or has an always install exception, and is not recommended by the vendor. In this case, the patch has a never install exception because it is not recommended by the vendor.

In the Preview pane, move the cursor over the icon or text in the Compliance column to view patch compliance information about a server.

- **Type:** The type of patch, such as Windows Hotfix or Windows Update Rollup.
- **Bulletin:** (*Optional*) The Microsoft Security Bulletin ID number for this patch.
- **Severity:** (*Optional*) The Microsoft severity rating for this patch:
 - **Critical:** This indicates a patch whose exploitation could allow the propagation of an internet worm, without user action.
 - **Important:** This indicates a patch whose exploitation could result in a compromise of the confidentiality, integrity, or availability of user data, or of the integrity or availability of processing resources.
 - **Moderate:** This indicates a patch whose exploitability is mitigated to a significant degree by factors, such as default configuration, auditing, or difficulty of exploitation.
 - **Low:** This indicates a patch whose exploitation is extremely difficult or whose impact is minimal.
- **Release Date:** The date that Microsoft released this patch.
- **Exception:** The type of patch policy exception set for the selected server.
- **Installed:** Indicates whether the patch is installed on the selected server.
- **Recommended:** A check mark indicates that this patch was recommended by the vendor during the last software registration.
- **Description:** A brief description of the managed server.

Patch Policies for Device Groups

For complete information on patching servers with patch policies, see the *SA User Guide: Server Patching*.

This window displays all patch policies associated with the selected device group. You can use the Show drop-down list to filter the type of patch policies to display in the Server Explorer.

Show Options

This section displays the following patch information:

- **Policies Attached to Device Group:** This displays all policies attached to the device group, or policies attached to a server group to which the selected managed server belongs.
- **Policies Not Attached to the Server:** This displays a list of all patch policies relevant to the selected server group that are not attached to the group.

Patch Contents

This section displays the following patch content information:

- **Name:** This displays the name of the patch policy.
- **OS:** This displays the operating system associated with the patch policy.
- **Description:** This shows a description of the patch policy.

Software Policies for Device Groups

This Software Policies view displays all software policies associated with the selected server (or group of servers). You can perform actions such as attaching a policy, detaching a policy, remediating a server, and scanning software compliance from the **Actions** menu. For more information, see the *SA User Guide: Software Management*.


Audits



This window allows you to create and run audits and snapshots. For more information, see the *SA User Guide: Audit and Compliance*.

Custom Attributes for Device Groups

This window displays the custom attributes set to a server or device group. You also can add, edit or remove custom attributes from this window.

Custom attributes can be one of the following two types:

- Inherited  from another source, such as a customer, a software policy, group of servers, ISM control, and so on.
- Attached directly to the server.

To override inherited custom attribute values, click the inherited arrow icon  once, and enter a new value in the value field. Press ENTER. The inherited arrow changes  to indicate that the custom attribute value has been overridden.

History Properties for Device Groups

The History view shows changes made to the selected device group. Entries are generated when actions are performed on a device group in the SA Web Client. The History is read-only. Each entry shows the following information:

- **Date:** The date when the last change occurred.
- **Event:** A description of the change.
- **User:** The user who made the change.

Use the View drop-down list to sort the device group history list according to a range of time, such as last week, the last two months, and so on.

4 Installing and Managing Server Agents

This chapter describes the SA server agent and how to install it. The agent is software that is installed on most servers and it enables SA to manage your servers.



SA does not install a server agent on VMware ESXi servers. Instead, SA manages ESXi servers through a VMware vCenter virtualization service. For more information, see the *SA User Guide: Virtualization Management*.

There are four ways to install the agent on your server:


- By scanning IP addresses to locate agentless servers. Use the Devices tab, and Servers > SA Agent Installation. See [Discovering Agentless Servers](#) on page 125 and [Installing the SA Agent](#) on page 123.
- By locating agentless servers among your managed servers. Use the Devices tab, and Servers > All Managed Servers. See [Installing the SA Agent](#) on page 123.
- By locating agentless servers managed by your virtualization services. Use the Virtualization tab. [Installing the SA Agent](#) on page 123. see also the *SA User Guide: Virtualization Management*.
- By using the agent installation command. See [Agent Installation and Upgrade Utilities](#) on page 337.

Permissions Required for Server Discovery and Agent Installation

To discover agentless servers and install agents you must have certain permissions. See the *SA Administration Guide* for more information about the permissions. To obtain the required permissions for scanning and deploying agents, contact your SA administrator.

Installing the SA Agent

This section describes how to install the SA agent on servers to bring under SA management.


The SA Client shows agentless servers with the server icon . See [Server Status Icons](#) on page 64.

Agentless servers may be physical servers that are not running the agent, or they may be virtual machines (VMs) not running the agent, but managed by a virtualization service. For more information, see the *SA User Guide: Virtualization Management*.

- 1 In the SA Client, under **Devices > SA Agent Installation**, select the servers on which you want to install the SA agent. See [Discovering Agentless Servers](#) on page 125.

Or under **Devices > All Managed Servers**, select the servers on which you want to install the SA agent.


Or under the Virtualization tab, select the VMs on which you want to install the agent. All VMs are managed under a virtualization service.

The server icon  indicates agentless servers. See [Server Status Icons](#) on page 64.

The servers must be powered on. Otherwise the Install SA Agent menu item will be disabled.

- 2 From the **Actions** menu, select **Install SA Agent**. This displays the Install SA Agent dialog box as shown in [Figure 35](#).

Figure 35 Install SA Agent Dialog



- 3 Select the Target Realm from the Scan In: drop down list.
- 4 Supply an IP address (if the field is not already populated). If you have multiple NICs, there may be a drop down list of IP addresses to select from.
- 5 Click Scan. This scan must be performed in order to populate the protocol list
- 6 Select a network protocol to use for connecting to the server from the drop-down list.

In most cases, choosing *Select Automatically* to allow SA to select an appropriate protocol for each server is recommended.

For VMware ESXi servers where the Linux-based service console (COS) has been removed, you must choose VMware ESX Web Services. For more information on managing virtual servers, see the *SA User Guide: Server Automation*.

- 7 Enter a user name and password to use for logging into the agentless server.

For Windows-based systems, specify the Windows administrator user name and password. When connecting via SMB(CIFS) to a Windows XP machine you must disable Simple File Sharing on the XP machine. To disable Simple File Sharing go to My Computer and select the Tools menu, then the Folder Options menu option. In the Folder Options window go to the view tab, and scroll down in the Advanced Settings panel. Uncheck the Use simple file sharing (Recommended) option. Press Apply and then OK.

For Unix systems, specify a `root` user and password. If logging in as `root` is not permitted, select the checkbox `Become root (UNIX)`. Select `Supply root password` and enter the password, or select `Use sudo` if `sudo` access is enabled for that account.

If you log in using `sudo`, the `sudo` user's configuration file (typically `/etc/sudoers`) must allow the account to run any command with root privileges. This is typically accomplished by using the "ALL" alias in the `sudoers` file.

If you are unable to deploy the agent to a Unix server by logging in as `root`, the system you are deploying to may be configured to disallow direct root logins. In such cases SA allows you to log in as a non-root user and then escalates your privileges via either the "su" command or the "sudo" command.

Perform the following steps to deploy agents as a non-root user:

- a Enter the unprivileged user name in the Username field to log into the server.
 - b Enter the unprivileged password in the Password field.
 - c Select the `Become root (UNIX)` checkbox. Select "Supply root password" and enter the password or select "Use sudo". If you use `sudo`, the unprivileged account must be able to run any command as root.
- 8 Select one of the following deployment actions:
- Verify installation prerequisites.
 - Verify prerequisites and copy agent installer to servers.
 - Verify prerequisites, copy installer, and install agent.
- See [Setting Agent Installation Actions for Each Server](#) on page 134 for more information.
- 9 Specify the agent installer options to control the way the agent is installed on a server. See [Agent Installer Options](#) on page 343 for more information.
- 10 Select **OK** to perform your selected actions.
- 11 After the agent installation is complete, the SA Client displays the results and updates the status icons for the servers. You can view information on an unmanaged server and generate reports on agent installation status. See [Reports on Agent Installation](#) on page 138 for more information.

Discovering Agentless Servers

You can use the SA Client to install agents on a large number of servers. To discover agentless servers, you specify a location to scan for servers and a set of IP addresses. SA performs a network scan to locate and identify servers. Instead of performing a network scan, you can import a file containing of IP addresses or IP address ranges. When the scan is complete, SA displays a list of scanned servers.

SA determines the status of each server, its IP address, its host name, detected operating system, and open ports used to connect to the server.

To scan for agentless servers and install agents on them using the SA Client, perform the following steps.


- 1 From the SA Client navigation pane, select the `Devices` tab and then select `Servers > SA Agent Installation`.

- 2 Select a realm to scan for servers from the “Scan in” drop-down list. For more information about realms, see the *SA Administration Guide*.
- 3 Select “Supply IP Address Ranges” from the drop-down list to specify a set of IP address ranges to scan. Enter the IP address range in the From and To field. Click the plus (+) button (next to the To field) to add another IP address range. You can add a maximum of five IP address ranges. Click the minus (-) button to delete the IP address range field.

Or

Select “Explicit IPs/Hostnames” from the drop down list to specify the list of IP addresses to scan, separated by spaces (commas not supported). Click the ellipsis (...) button as shown in [Figure 36](#) to display a text editor that allows you to load and scan a file with IP ranges to scan.

Figure 36 Loading a File with IP Addresses



- 4 Click **Scan** to scan for servers. When the scan is complete, the list of servers is shown. For each server, SA determines the status of the server, its IP address, its host name, the detected operating system and open ports that can be used to connect to the server. You can click on any of the column headings to sort the server list by that column.



If you have a firewall enabled, SA may not be able to accurately detect a server’s actual installed operating system. Some firewalls can interfere with the methods SA uses to detect the operating system. SA must be able to access at minimum one open port and one closed port to gather the information needed to determine the operating system. If you find that SA has not identified any operating system or has misidentified the operating system, you may need to configure your firewall to allow network packets from the SA core.

[Figure 37](#) below shows the results of a network scan for servers. The actual operating system of the server can be only determined if SA is able to successfully log into the server.

Figure 37 Scan Results

	Scan in	from	to						
	MPCORE01	192.168.157.37	192.168.157.41	-	+				
	Supply IP Address Ranges								
	Scan								
	Hostname	IP Address	Detected OS	Accuracy	Actual OS	SSH	rlogin	Telnet	NetBT
	-	192.168.157.41	Linux Linux 2.6.X, Li...	98%	-	✓			
	-	192.168.157.37		0%	-				
	-	192.168.157.38		0%	-				
	-	192.168.157.40		0%	-				
	-	192.168.157.39	Microsoft Windows ...	100%	-				✓

- 5 Install the SA agent on these servers as described in [Installing the SA Agent](#) on page 123.



Due to several factors (network delays, firewalls, etc) the nmap scan utility can return inconclusive results for the Detected Operation System. In these cases, Agent deployment can fail. To resolve this issue, set the NMAP general-timing parameter (-T) to a higher scan accuracy. In the SA Client, choose **Tools > Options**, then select **SA Agent Installation > Advanced**. In the NMAP parameters text field, set the -T parameter.

The allowed values for the parameter, in increasing order of scan accuracy, are:

-T Aggressive|Normal|Polite|Sneaky

Re-run your unmanaged servers scan.

Upgrading the Server Agent

When a new version of HP SA is released, it may include a new version of the SA agent. The new agent may be required to gain access to some new functions in SA. For instructions on upgrading the SA agent, see [Agent Upgrade - SA Client](#) on page 350.



If you attempt to upgrade an agent on a server that acts as an SA Core host, you will see warning message. Core host agents are upgraded when the core itself is upgraded and you should not need to manually upgrade them.

Setting Agent Installation Defaults

The server agent enables SA to manage your servers. You can specify the default behavior for agent installation by selecting the **Tools > Options** menu in the SA Client. For more information, see [SA Agent Installation - Installer Options](#) on page 40, [SA Agent Installation - Protocols](#) on page 40, and [SA Agent Installation - Advanced Options](#) on page 41.

Starting and Stopping a Server Agent

Once the SA agent is installed and running on your managed servers, you rarely need to stop or restart them.

To start a server agent, log onto the managed server and enter one of the following commands.

Unix:

```
/etc/init.d/opsware-agent start
```

HP-UX:

```
/sbin/init.d/opsware-agent start
```

AIX:

```
/etc/rc.d/init.d/opsware-agent start
```

Windows:

```
net start opswareagent
```

To stop an agent, enter the same command, specifying `stop` instead of `start`.

Viewing Server Agent Information

You can view information about the agent in the SA Client by selecting a server, selecting the Properties view and scrolling to the Reported Information in the SA Client.

The Reporting field indicates the status of the Agent's reporting capability and tells you whether or not the agent is reporting regularly and successfully. The possible reporting states for the agent are as follows:

- **OK:** The Agent is reporting properly.
- **Registration in progress:** The Agent is currently registering server hardware information.
- **Reporting error:** The Agent encountered an error while trying to report hardware information.
- **Has not reported in <number> days:** This indicates when the Agent last reported.
- **Has not reported:** Indicates the Agent has not yet reported.

Searching for Servers Based on Agent Information

You can also perform an advanced search and specify the search criteria as Agent Discovery Date, Agent Encoding, Agent Reporting, Agent Status or Agent Version.

You can access Agent reporting information in Server Properties by using advanced search, and by viewing managed servers by Communication status. When viewing by Communication status, the SA Web Client user interface displays this information in the registration column.

If the Agent experiences an error in reporting, or has not reported within 24 hours, you can run a communication test to troubleshoot the problem. See [Running Server Communication Tests](#) on page 139 for more information.

If you modify the server hardware, it could take up to 12 hours for the change to appear in the SA Web Client user interface, depending on the time that the agent for that server contacted the core.

If you install or uninstall software on a managed server outside of HP Server Automation, it could take up to 24 hours for the change to appear in the SA Web Client user interface. For example, if you update the Microsoft Patch Database, it could take up to 24 hours for all managed servers to display whether they need new patches based on the updated Microsoft Patch Database.

In some cases, not all of a server's hardware information is reported. For example, if the agent was installed with its default settings, not all hardware information is reported to the SA Web Client until an hour after the agent is installed. There also might be a problem retrieving certain hardware information, such as a disk failure, that could prevent some hardware information from being reported. In these cases, the server's property page lists unreported information as not set.

If configuration tracking is enabled for a server, the agent sweeps through the managed server on a regular interval to see if any of the configurations being tracked are changed. If a tracked configuration is changed, the agent performs the action specified by the tracking policy, namely, writing the information to a log file, generating a backup, or sending an email message through SMTP to the email address specified in the tracking policy.

Security for Agents Running on Managed Servers

Agents act as both clients and servers when they communicate with the SA core. All communication is encrypted, integrity-checked, and authenticated using X.509v3 client certificates using SSL/TLS.

A small number of core components can issue commands to the agent over a well-defined TCP/IP port. The agent can also call back to core components, each with its own well-defined port.

Agent Functionality on Managed Servers

The server agent:

- Only discovers information about its own managed server and no others.
- Cannot make changes on a server unless explicitly instructed to do so by the SA core.

HP SA runs with administrator privileges (root on UNIX servers and Local System on Windows servers), because it performs tasks that require administrator privileges, such as installing patches and rebooting servers.

The core performs client authentication and checks to see if the presenting certificate belongs to that particular server. HP Server Automation does this by comparing the certificate to the server's IP address that is generated when the agent is initially installed. If the certificate is not valid or the originating IP address does not match the IP address stored in the Model Repository, authentication fails and the agent cannot continue communication with HP Server Automation.

If an unauthorized user were able to log on to a managed server with administrator privileges and compromise a server's security, the user would have only limited access to the following information in the SA core:

- The server's hardware inventory (already available to someone logged on with administrator privileges)
- The server's software inventory (already available to someone logged on with administrator privileges)
- The custom attribute information

Software and Hardware Inventory

When the server agent is first installed, it performs a full software and hardware inventory and stores this information in the SA core. It automatically performs the following inventories:

- Every 12 hours the agent performs a minimal hardware inventory and stores the updated information in the SA core. It reports information such as the OS version, the chassis ID, the SA agent version and the SA object ID.
- Every 7 days the agent performs a full hardware inventory and stores the updated information in the SA core. It reports all the information from the minimal hardware inventory plus information such as CPU, memory, storage and networking information.
- Every 24 hours, the agent performs a software inventory and stores the updated information in the core. It reports the software found on the server and the core determines any differences.
- A hardware inventory is also performed during software installation.

Server Information that the Agent Tracks

For each managed server, the agent reports software, networking, and hardware information, as shown in [Figure 38](#) and [Figure 39](#). By communicating with the core and reporting the installed hardware and software for the server, SA determines what software should be installed on a server.

Figure 38 Server Information - Summary





Figure 39 Server Information - Properties



Software Information

The software that installed on the server is recorded in SA Library. To display the list of software installed on the server, select the Inventory tab, then select Installed Packages. For more information, see the *SA User Guide: Software Management*.

Hardware Information

SA tracks hardware information in a variety of ways. [Table 6](#) shows how the agent obtains the server and hardware information about each managed server.

Table 6 Hardware Information that the Agent Reports for Servers

Attribute	Description	How Obtained
Name	The user-configurable name for the server. By default, HP Server Automation uses the configured host name of the server until a user edits it.	Windows: Uses the fully qualified DNS name of the server. Linux, Solaris, AIX, HP-UX: Uses the current host name of the server that the <code>hostname</code> command returns.
Reported OS	The version number of the server's operating system.	Windows: Uses the Windows version number as reported by the operating system. This information includes the major version number, the minor version number, the Windows build number, and the Service Pack level. Linux, Solaris, AIX, HP-UX: Uses the operating system version that the <code>uname</code> command returns.
OS Version	The OS version specified for the OS definition.	Specified by the user who prepared the OS with the Prepare Operating System Wizard. See the <i>SA User Guide: OS Provisioning</i> for more information.
Serial Number	The serial number of the system. HP Server Automation attempts to report a chassis ID, if possible.	Windows, Linux: Obtained from the system BIOS. Solaris, AIX, HP-UX: Obtained from the system ROM.
Manufacturer	The manufacturer of the server if available.	Windows, Linux: Obtained from the system BIOS. Solaris, AIX, HP: Obtained from the system ROM.
Model	The model of the server if available.	Windows, Linux: Obtained from the system BIOS. Solaris, AIX: Obtained from the system ROM. HP-UX: Output of <code>model</code> command (which is read from the system ROM).

Table 6 Hardware Information that the Agent Reports for Servers (cont'd)

Attribute	Description	How Obtained
Memory	The amount of physical RAM and the total amount of virtual memory paging space configured.	<p>Windows: Uses the Windows 2000 API <code>GlobalMemoryStatus()</code>.</p> <p>Linux: Obtained from information in the file <code>/proc/meminfo</code>.</p> <p>Solaris: Obtained from the <code>sysconf</code> and <code>swapctl</code> APIs.</p> <p>AIX: Uses the <code>lsattr</code> command for memory information and the <code>lspv</code> command for paging space.</p> <p>HP-UX: Uses the <code>pstat</code> system call.</p>
CPUs	Information about each of the processors in the system.	<p>Windows: If WMI is available, iterates over all instances of <code>Win32_Processor</code>. If WMI is not available, parses the registry key <code>HARDWARE\DESCRIPTION\System\CentralProcessor</code>. There is one sub-key for each processor.</p> <p>Linux: Obtained from information in the file <code>/proc/cpuinfo</code>.</p> <p>Solaris, HP-UX: Uses system APIs to enumerate the processors in the system.</p> <p>AIX: Uses the <code>lscfg</code> command.</p>
Storage	Information about each installed disk drive or RAID array.	<p>All Platforms: Uses system APIs to discover and probe disk drives and RAID arrays.</p>
Server ID or Object ID	The internal ID that HP Server Automation uses to identify the server.	<p>In most cases, the server ID is the same as the MID.</p>

In addition to hardware and software reporting, the agent reports networking information. See [Network Configuration](#) on page 255 for descriptions of the networking information reported and how you can modify that information using the Network tab in the SA Web Client.

About Server Discovery and Agent Installation

SA can install agents on a large number of servers through the SA Client. SA can identify servers on which to install an agent, specify the agent configurations for each server, select the login protocols to connect to each server, specify the agent installation options, install the agent and generate reports on agent installation status.

This section contains the following topics:

- [Setting Agent Installation Actions for Each Server](#)
- [Specifying Login Settings](#)
- [Agent Installer Command](#)
- [Reports on Server Status](#)

See [Discovering Agentless Servers](#) on page 125 for more information about how to install an agent.

Setting Agent Installation Actions for Each Server

Once you have identified the servers, you can perform the following deployment actions:

- Verify installation prerequisites including:
 - Checking for sufficient disk space for agent installation on the server.
 - Verifying that no other application is using port 1002.
 - Verifying if ports to the Gateway are accessible.
- Copy the agent installer to servers.
- Install the agent on the server.

Specifying Login Settings

When installing the SA agent, you can select the network protocols to connect to the server and specify the user name and password to log in to each server. Agent installation is performed as root on Unix operating systems and as administrator on Windows operating systems so. SA attempts to log in to each of the selected servers with the specified user name and password and performs the specified deployment actions.

The agent requires administrator-level privileges (root on Unix servers and administrator on Windows servers) to manage a server.









Agent Installer Command

You can use the agent installer command to manually install agents on servers. For more information, see [Agent Installation and Upgrade Utilities](#) on page 337.

Reports on Server Status

After the SA agent is installed, the SA Client displays the results and updates the status icons for the servers as shown in [Table 7](#)

Table 7 Server Status

Icons	Server Status
	The server is agentless, but reachable
	The server is agentless and unreachable
	The server is agent managed
	The server failed prerequisite checks
	The server passed prerequisite checks
	The server passed prerequisite checks and the agent installer was copied to the server
	The agent was successfully deployed
	The agent was not successfully deployed



A server is considered to be managed when SA determines that the agent is listening for TCP connections on port 1002.

For a failed deployment action, you can view the errors on each server. You can also log in to the server and correct the errors.

You can also create the following reports:

- All the servers in the current network scan
- Selected servers in the current network scan
- All the servers in the current network scan with successful deployments
- Servers in the current network scan with failed deployments

You can save and export the reports to a CSV, HTML, or text format file.

Troubleshooting Agent Installation Errors

After the agent is installed, you can review the results and generate reports. For a failed agent installation, you can view the errors on each server. You can also log into the server from SA and correct the errors.

This section discusses the following topics:

- Viewing Unmanaged Server Information
- Opening a Remote Terminal Session on an Agentless Server
- Reports on Agent Installation

Viewing Unmanaged Server Information


Unmanaged physical servers are any physical servers that do not have an SA agent installed on them.

Virtual machines (VMs) are always managed by a virtualization service. It is highly recommended that you make all virtual machines (VMs) agent-managed servers to have maximum visibility, control, and compliance for these VMs. For more information, see the *SA User Guide: Virtualization Management*.

To view information about unmanaged, agentless servers, perform the following steps.

- 1 From the SA Client navigation pane, select **Devices** and then select **SA Agent Installation**. This lets you search for agentless servers to install the SA agent on. For more information, see [Discovering Agentless Servers](#) on page 125.
- 2 From the SA Agent Installation screen, select an agentless server. From the **Actions** menu, select **Open**. This displays information about the agentless server as shown in [Figure 40](#) below.

Figure 40 Unmanaged Server Summary Page



The Summary View of an Unmanaged Server

The Summary view of the agentless server gives the following information.

- **Hostname:** The host name of the agentless server, if defined in the Domain Name System (DNS).

- **IP Address:** The IP address of the server.
- **Detected OS:** The operating system detected on the server after performing the network scan. The listed operating system is a “best guess” made by comparing the server’s response to a network probe of a list of known operating system “fingerprints”. The listed operating system may not always be accurate, for example when a firewall exists between the HP Server Automation Core and the server and does not allow or alters the network probe.
- **Actual OS:** The actual operating system detected on the server after the agent is installed. This entry will be blank until SA can successfully log on to the managed server and identify the operating system type and version.
- **MAC Address:** The Media Access Control (MAC) address, which is the network interface card’s unique hardware number of the server. The MAC address is used as the server’s physical address on the network. The MAC address is only detected if the server is on the same physical network as the Gateway.
- **NIC Vendor:** The vendor name for the Network Interface Card (NIC) driver. The NIC vendor is only detected if the server is on the same physical network as the Gateway.
- **Open Ports:** The discovered open ports on an unmanaged server. SA does not perform a comprehensive search for open ports. There may be open ports not listed.
- **Number of Deployment Attempts:** The number of attempts to install the SA agent on the server.
- **Last Deployment Attempt Date/Time:** The date and time of the last attempt to install the SA agent.
- **Last Deployment Attempt Message:** The message stating the possible cause for the failure of the last attempt to install the SA agent.

The History View of an Unmanaged Server

The History view of a server shows a history of all actions executed on the server.

Opening a Remote Terminal Session on an Agentless Server

You can open a remote terminal session on an agentless server and log in to the server using the appropriate protocol and correct any errors on the server or perform any other operations.

To open a remote terminal session on an agentless server perform the following steps.

- 1 Log into the SA Client.
- 2 From the navigation pane, select Devices and then select SA Agent Installation.
- 3 Select an agentless server.
- 4 Either right click or select the **Actions** menu, select **Log in with** and select the appropriate protocol.

The specific commands that SA uses to log in to the remote server are specified in the Terminal and Shell options, under the **Tools † Options** menu. For more information, see [Terminal and Shell Options](#) on page 42.

Reports on Agent Installation

You can create the following reports as described below.

- All the servers in the current network scan
- Selected servers in the current network scan
- Servers in the current network scan with successful deployments
- Servers in the current network scan with failed deployments


You can also save and export the reports to a CSV, HTML, or text file format.

Creating Reports on Failed Agent Installation

Perform the following steps to create reports:

- 1 Log in to the SA Client.
- 2 From the navigation pane, select Devices and then select SA Agent Installation.
- 3 From the SA Agent Installation page, select the agentless server. From the **Actions** menu, select **Export to** the desired report format. The Save Report dialog box appears.
- 4 From the drop-down list, select the type of report as shown in [Figure 41](#).

Figure 41 Generating Reports



- 5 Enter the location and file name to save the report.

Example Report

The following example shows a report of servers with failed deployments.

Server List:

```
Name : dhcp-183-154.aqua.qa.hp.com
Address : 192.168.183.154
Detected Operating System : Microsoft Windows 2008
Accuracy : 100%
Actual Operating System : Unknown
```

Open Ports : 3389
MAC Address : 00:50:56:8A:13:58
NIC Vendor : VMWare
of Deployment Attempts : 0
Last Deployment Message : "No Message"
Managed by HP Server Automation: No

About Communication between the Server and the SA Core

The server agent communicates with the SA core to provide information about the server to the core and to receive commands from the core.

- The server agent gathers information about the server and sends it to the SA core. The SA core stores this information about all managed servers.
- When you initiate an action on the server — for example, a software installation or removal, a patch installation, a software or hardware configuration change, an audit or any other server management action — the SA core sends a command to the server agent. The server agent receives the command from the core and initiates the corresponding actions on the server.

The server agent opens a secure communication channel to the core, presents its IP address and public-key certificate for authentication purposes. If properly authenticated, the agent updates the information about the server in the SA core.

Running Server Communication Tests

This section describes how to assess the communication between the SA core and your managed servers.

- [About Server Communication Tests](#) on page 140
- [Running Server Communication Tests - SA Client](#) on page 140
- [Communication Test Results](#) on page 141
- See also [Troubleshooting Server Communication Tests](#) on page 311.



The communication test is not available on VMware ESXi servers because SA does not install a server agent on ESXi servers. You can determine if an ESXi server is reachable from its virtualization service by selecting the server and selecting the Virtualization view. The Virtualization view displays the virtualization service managing the ESXi server and its connection state. For more information about virtual servers, see the *SA User Guide: Virtualization Management*.



The SA Web Client is deprecated for running server communication tests. Use the SA Client to run communication tests. See [Running Server Communication Tests - SA Client](#) on page 140.

About Server Communication Tests

Sometimes a server agent can become unreachable and the SA core cannot communicate with the agent. To identify managed servers that have unreachable agents, the SA core runs periodic communication tests with all managed servers and saves the results. You can check the reachability of agents by looking at the server's Properties or by viewing the current agent reachability status for all managed servers since the last communication test was run.

You can also manually run communication tests on one or more servers. When the test finishes, the results for each server are displayed. In some cases, the failure of one test might prevent other tests from being executed.

The results of each communication test job are saved under the Jobs and Sessions tab. You can search and view the results of previously run communication tests.

The communication test works by testing communication and data exchange between the specific components of the SA core and each managed server. To manage servers, the core needs to be able to communicate with the server agent on each managed server.

Types of Server Communication Test

The communication test performs the following diagnostic tests:

- **AGT Test** (Command Engine to Agent Communication) - Tests if the SA core can communicate with the SA agent running on the server.
- **CRP Test** (Crypto Match) - Tests the encryption and security of the connection between the SA core and the managed server. Checks that the agent's SSL cryptographic files are valid.
- **CE Test** (Agent to Command Engine Communication) - Tests if the server can retrieve commands to be executed from the SA core.
- **DAE Test** (Agent to Data Access Engine) - Tests if the server can retrieve its stored device information from the SA core.
- **SWR Test** (Agent to Software Repository Communication) - Tests if the server can retrieve software and patches from the SA core.
- **MID Test** (Machine ID Match) - Verifies that the server's machine ID is the same as the machine ID stored in the SA core.

Running Server Communication Tests - SA Client







You can run communication tests on one or more managed servers. Perform the following steps.

- 1 In the SA Client, select the Devices tab.
- 2 In the navigation pane, select one or more servers.
- 3 Either select the **Actions** menu or right click and select **Run † Communication Test**. This runs the communication test on the selected servers and displays the results in a separate Run Communication Test screen.
- 4 Optionally select the Run in Background button. This closes the Run Communication Test screen and redisplay it when the test completes.
- 5 If any tests fail, see [Troubleshooting Server Communication Tests](#) on page 311.

Communication Test Results

The icons shown in [Table 8](#) below indicate the success or failure of agent reachability test. For more information, see [Troubleshooting Server Communication Tests](#) on page 311.

Table 8 Agent Reachability Status Icons

Status Icons	Test Results
	The communication test passed. The server is reachable.
— or 	The communication test did not execute. This is typically because one of the other tests failed.
 or 	The communication test failed. The server is unreachable.
 or 	The communication test is still running.

5 Creating and Managing Customers

SA provides several ways to organize your managed servers:

- Creating **Customers** in SA and assigning servers to those customers. Customers provide a way to group your servers and provide access control boundaries.
- Creating **Device Groups** and placing servers in the device groups either manually or by a set of rules that automatically determine membership. Device groups provide a way to group your servers and provide access control boundaries. For more information about device groups, see [Exploring Servers and Device Groups in the SA Client](#) on page 63.
- Creating and modifying **Server Use** categories and **Deployment Stage** categories so you can identify categories of servers and what they are used for, as well as to describe their various stages of life cycle deployment. For more information, see [Server Use Categories and Deployment Stage Categories](#) on page 239.



The SA Web Client is deprecated for managing customers. You should use the SA Client for managing customers. See [Customer Tasks - SA Client](#) on page 145.

About Customers

Many enterprises have consolidated disparate IT operations into a single operation, yet they still need separate reporting, billing, and management for different business units, groups or customers. For example, one company may separate activities for their West Coast Office, East Coast Office, and London Office. A service provider company may organize their IT operations by their customers such as Customer A, Customer B, Customer C and so forth.

SA accommodates these requirements by letting you create separate **customers** and assign each managed server to a specific customer.

A customer in SA is a logical group into which you can place servers. You can then perform IT management tasks on all servers belonging to a customer. Customers also provide security and authorization boundaries. Each SA user must be given access to one or more customers to gain access to the servers belonging to each customer.

IT resources such as patches and patch policies, software packages and policies can also be assigned to customers. Only resources assigned to a customer can be used on servers assigned to the same customers. Resources assigned to a special category “Customer Independent” can be used on any servers regardless of their customer assignment.

About Customers and Facilities

A facility is all the servers managed by an SA core or satellite. You may have one facility or you may have multiple facilities. Each facility is managed by a separate SA core or satellite. If you have multiple cores and facilities, all your SA cores are connected in a multimaster

mesh for reliability, redundancy, scalability and performance. All cores and satellites communicate with each other to keep all your data redundantly stored. If one core goes down, the other cores automatically provide services to the servers managed by that core.

Customers are a way to organize your servers and provide access control boundaries based on the users of your servers. A customer represents a set of servers associated with a business organization, such as a division or a company. Typically a server is associated with a customer because it runs applications for that customer.

You can define as many customers as you need and assign managed servers to each customer. However, you must first associate a customer with one or more facilities before you can place servers from a facility into a customer. A customer can span more than one facility and a facility can contain one or more customers. To associate a customer with one or more facilities, see [Viewing or Modifying a Customer - SA Client](#) on page 146.

Predefined Customers

SA defines the following customers:

- **Not assigned:** The Not Assigned customer is the default “customer” that servers belong to when they are not assigned to a “real” customer. When you bring a server into SA, the server is associated with the Not Assigned customer.
- **Opware:** Servers belonging to the Opware customer are all the servers used by the SA core. This customer designation allows you to give these servers their own set of access controls to keep them logically separate from your other servers.
- **Customer Independent:** Resources such as software and patches can be specified as customer independent. Servers cannot be assigned to this “customer”. These customer independent resources can be installed on any managed server, no matter what customer the server is assigned to.

You can install software and patches that are Customer Independent on Not Assigned servers. However, you cannot install any resources associated with a customer on a server that is not assigned to a customer. That is, the resources and servers need to be owned by the same customers.

Customer Security, Authorizations and Permissions

Setting up separate customers and assigning servers and IT resources to separate customers allows you to set up security boundaries and user authorization capabilities. Only users who have permission to access a customer’s servers and IT resources are authorized to manage those servers and resources. A user who does not have access to a customer’s servers and IT resources can neither see nor manage that customer’s servers.

Access is granted or denied based on user groups. Each user belongs to one or more user groups. Each user group has access to one or more specific customers. This combination of customers and user groups gives you full control over security and authorization.

For more information on users, user groups and setting permissions, see the *SA Administration Guide*.

Permissions to Create, Delete and Modify Customers

An SA user must have the Super Administrator permissions to create or delete customers. An SA user must have the Customers Feature permission to modify customers. For more information on permissions, see the *SA Administration Guide*.

Customer Tasks - SA Client

This section describes how you can use SA customers to manage your servers through the SA Client.

Assigning a Server to a Customer - SA Client

All managed servers must be assigned to exactly one customer, even if they are assigned to the special customer “Not Assigned”. To assign the server to a different customer, perform the following steps.

- 1 In the SA Client, select the Devices tab.
- 2 Navigate to the desired server under the Servers node in the navigation pane.
- 3 Select the server.
- 4 Select the **Actions** menu or right click and select **Open**. This displays a new window with information about the server.
- 5 Select Properties in the navigation pane. This displays a list of management information about the server including the customer the server is assigned to.
- 6 Select the Change button next to the Customer field. This displays a list of available customers.
- 7 Select a customer.
- 8 Select the Select button.
- 9 Select the **File † Revert** menu to discard your changes.
- 10 Select the **File † Save** menu to save your changes.

Creating a New Customer - SA Client

To create a new customer, you need to log in as a super administrator. For more information on permissions, see the *SA Administration Guide*.

To create a new customer, perform the following steps.

- 1 Log in to the SA Client as a user with the Customers Feature permission.
- 2 Select the Administration tab in the navigation pane. This displays the Customers node at the top of the navigation pane.
- 3 Select the Customers node in the navigation pane. This displays all the customers that have been defined.
- 4 Select the **Actions † New** menu. This displays the new customer window. If you do not have the proper permissions, this menu will be grayed out.

- 5 Enter a name and a short name for the new customer. The name is the display name that is used throughout the SA Client. The short name is the name used internally by SA.
- 6 Optionally add one or more facilities by selecting the “+” icon. Only servers from facilities associated with the customer can be assigned to the customer. For more information, see [About Customers and Facilities](#) on page 143.
- 7 Select the **File** † **Save** menu to create the new customer.

Viewing or Modifying a Customer - SA Client

To modify a customer, you need appropriate permissions. For more information on permissions, see the *SA Administration Guide*.

To view or modify a customer, perform the following steps.

- 1 Log in to the SA Client as a user with the Customers Feature permission.
- 2 Select the Administration tab in the navigation pane. This displays the Customers node at the top of the navigation pane.
- 3 Select the Customers node in the navigation pane. This displays all the customers that have been defined.
- 4 Select the customer you want to view. Information is displayed in the lower pane.
- 5 From the View list, select either Properties or Custom attributes.
- 6 To open the customer in a separate window, select the **Actions** menu or right click and select the **Open** menu. This displays the customer in a separate window.
- 7 Select Properties to view or modify the name of the customer or to view or change the facilities associated with the customer.
- 8 Select Custom Attributes to view, modify or delete the custom attributes defined by the customer. Select the value of any custom attribute to modify it. Select the “+” icon to add a new custom attribute. Select one or more custom attributes and select the “-” icon to delete them.
- 9 Select the **File** † **Revert** menu to discard all your changes.
- 10 Select the **File** † **Save** menu to save your changes to the customer.

Deleting a Customer - SA Client

To delete a customer, you need appropriate permissions. For more information on permissions, see the *SA Administration Guide*.

To delete a customer, perform the following steps.

- 1 Log in to the SA Client as a user with the Customers Feature permission.
- 2 Select the Administration tab in the navigation pane. This displays the Customers node at the top of the navigation pane.
- 3 Select the Customers node in the navigation pane. This displays all the customers that have been defined.
- 4 Select one or more customers you want to delete.
- 5 Select the **Actions** menu or right click and select the **Delete** menu. This deletes the selected customers. If you do not have the proper permissions, this menu will be grayed out.

6 Running SA Extensions

Server Automation (SA) gives you the capability to extend its functionality by creating **Automation Program Extensions (APXs)**. This section describes the APX extensions feature and how to run extensions.



For information on how to create APX extensions, see “Extending SA with Automation Platform Extensions (APXs)” in the *SA Platform Developer Guide*.

APX extensions provide a framework that allows anyone familiar with script-based programming tools such as shell scripts, Python, Perl, and PHP, to extend the functionality of SA and create applications that are tightly integrated into SA. SA provides two types of APX extensions:

- **Program APX Extensions** run in the Global File System (OGFS) and can use all of the OGFS functionality. You can use typical programming practices to leverage the SA API and access a core’s Managed Servers to implement new custom functionality. For example, you could write an APX extension that gathers BIOS information from managed servers and populates custom fields using shell commands.
- **Web APX Extensions** allow you to create a web-based application, where either an Apache 2.x process or a CGI/PHP script is called using GET or POST URL. Web APX extensions can contain static web resources such as images, and can employ CGI or PHP for dynamic content generation.


APX extensions allow you to access data about your managed environment and share and process that data with web applications, scripts, programs and other custom applications.


Methods of Running Extensions

You can run extensions in any of the following ways.

- **From Managed Servers, by selecting a server first:** You can select one or more servers in the SA Client, then right click or select the **Actions** menu and select the **Run Extension** menu item. This applies only to certain program extensions. For details, see [Run Extensions on Managed Servers](#) on page 150.
- **From the SA Library, By Type:** In the SA Client you can run an extension by selecting Library, By Type, Extensions, Web or Program, selecting an extension, and doing one of the following.
 - Double click the extension.
 - Right click the extension and select **Run...**
 - Under the **Actions** menu, select **Run...**


- **From the SA Library, By Folder:** In the SA Client you can run an extension by selecting Library, By Folder, navigating to and opening an extension in the Library. Under the **Actions** menu, select **Run...**
- **From the Global Shell (program extensions only):** From the Global Shell, run `/opsw/apx/bin/<extension name>` where `<extension name>` is the unique name of the extension. Provide any parameters the extension requires. For more information on the Global Shell, see [SA Global Shell](#) on page 281.
- **From a web browser (web extensions only):** From a web browser, enter the URL `https://<SA core>/webapp/<extension name>` where `<SA core>` is the IP address or host name of your SA core and `<extension name>` is the unique name of the web extension.
- **From the SA API (program extensions only):** From the SA API, use the method `ProgramAPXService.startProgramAPX()`. For more information on the SA API, see the *SA Platform Developer Guide*.

 Most extensions cannot run on VMware ESXi hypervisor servers because SA does not install an agent on ESXi servers. Instead, SA manages ESXi servers through the VMware vCenter virtualization service. For more information, see the *SA User Guide: Virtualization Management*.

 When using the global shell to run an APX that seeks information on a managed server, such as the System Diagnostics APX, the agent for that server must be running. Attempting to run the APX when the agent is turned off will result in an error.

Run Extensions on Managed Servers

Some extensions take one or more managed servers as input and perform some operation or gather some information from those managed servers. For example, an extension could gather certain information about devices on the servers using a script. You can run this extension by selecting one or more servers and selecting the extension to run. This extension describes how to run extensions that take one or more managed servers as input to the extension.

 Only program extensions that implement the “com.hp.client.server.RightClickToRun” interface can be run using this method. This interface indicates that the extension takes one or more servers as input parameters.

Only extensions you have permission to execute will be shown in the SA Client. For more information on permissions, see the *SA Administration Guide*.

For details on creating extensions, the RightClickToRun interface and permissions, see “Extending SA with Automation Platform Extensions (APXs)” in the *SA Platform Developer Guide*.

To run an SA program extension by first selecting one or more servers, perform the following steps.

- 1 From the SA Client Navigation pane, select **Devices † All Managed Servers**.
- 2 Select one or more servers in the Contents pane.

- 3 Right click the server or select the **Actions** menu, then select **Run Extension † Select Extension...**


Or

Right click the server or select the **Actions** menu, then select **Run Extension †** and select a named extension, if any are shown in the menu.

The **Run Extension** menu lists all of the program extensions that have been run at least once before. You can select one of these extensions without having to use the **Select Extension...** window.

For example, the following shows the **Run Extension** menu item selected, two sample program extensions named **MyExtension** and **FindMyAppDates**, and the **Select Extension...** menu item.

Figure 42 The Run Extension Menu




▶ Extensions appear in the **Run Extension** menu only after they have been run at least once using the **Select Extension...** menu. That is, to make your extension appear in the **Run Extension** menu, you must first run your extension by choosing **Select Extension...** and then choosing your extension as described in step 4 below.

- 4 If you selected a particular extension from the **Run Extension** menu in [step 3](#) on page 151, skip ahead to [step 5](#) below.

If you chose the **Select Extension...** menu item, the SA Client displays the available extensions. The following screen shows three extensions MyExtension, FindMyAppDates and Extensible Discovery. Select the extension you want to run and click OK.


Figure 43 The Select Extension Window



- 5 Once you have chosen a particular extension to run, the SA Client displays the Run Program Extension screen as shown below. This screen shows the devices the extension will run against.

If you want to run the extension against more devices, select the Include Devices... button and select additional devices or device groups. To remove devices, select the devices and click Remove.

Figure 44 Select Devices on the Run Program Extension Window



- 6 Click the Next button. This displays the Program Properties and Program Execution Path. Optionally edit the program execution path and click Next to display the Runtime Options and Output Options.
- 7 Optionally change the Runtime Options and Output Options and click Next to display the Schedule Frequency and Time and Duration.

Or you can click Start Job to skip the remaining options and run the extension with default options.
- 8 Optionally specify how frequently to run the extension and click Next to display Email Notifications and Ticket Tracking.
- 9 Optionally change the email notifications and add a ticket ID and click Next to display the Job Status screen.
- 10 Click Start Job to run the extension. The Run Program Extension screen displays the progress of the extension. When the extension finishes, click the Close button.

Running Extensible Discovery on Managed Servers

SA can gather a large amount of information from your servers by default. Extensible Discovery lets you gather additional information about your servers quickly and easily. Extensible Discovery is a feature that you can customize and use to discover and obtain custom information about servers in your managed environment.

This section describes how to run Extensible Discovery. To customize Extensible Discovery and add your own scripts, see [Adding Scripts to Extensible Discovery](#) on page 154.

▶ To run Extensible Discovery, you must have write access to the managed servers where you want to run Extensible Discovery and you must have execute access to the Extensible Discovery folder in the SA Library. For more information on permissions, see the *SA Administration Guide*.

▶ You cannot run Extensible Discovery on VMware ESXi hypervisor servers because SA does not install an Agent on ESXi servers. Instead, SA manages ESXi servers through the VMware vCenter virtualization service. For more information, see the *SA User Guide: Virtualization Management*.

To run Extensible Discovery, perform the following steps.

- 1 Run the Extensible Discovery extension as described in [Run Extensions on Managed Servers](#) on page 150. This does the following:
 - a Remediates the software policies “Customer Provided Scripts” and “HP Provided Scripts” on the selected servers. This copies all the scripts in these policies to all the managed servers. It places the scripts on the managed servers.
 - b Runs all the scripts in the Extensible Discovery directory on the selected servers.
 - c Places the output from the scripts either in custom attributes or custom fields.

▶ The first time you run Extensible Discovery on a server will typically take longer than subsequent runs because it needs to install scripts on the server the first time you run it.

- 2 Examine the results by viewing the Custom Attributes or Custom Fields for each server.

If an error occurs, check the following custom attributes for more information.

 - **HPSW_ED_error**: If an error occurs on a server, this custom attribute will be created for the server and it will contain any relevant error messages. To determine which servers had an error, you can search for servers with this custom attribute.

If Extensible Discovery runs without errors on the server later, this custom attribute will be removed.
 - **HPSW_ED_warning**: This custom attribute will be created on servers where a non-fatal warning occurs.

If Extensible Discovery runs without warnings on the server later, this custom attribute will be removed.

For more information, see [Comparing Custom Fields and Custom Attributes](#) on page 161.

Running Extensible Discovery from the OGS

You can also run Extensible Discovery from the Global Shell (OGS) using the command interface as follows:

```
/opsw/apx/bin/com/opsware/extensible_discovery -d <server ids> -g <group ids>
```

The following table describes the options to this command. For more information on the Global Shell, see [SA Global Shell](#) on page 281.

Table 9 Options to the extensible_discovery Command

Option	Usage
-h --help	Displays help for this command.
-d <server ids> --deviceids=<server ids>	Specifies one or more server IDs or server names separated by commas. Runs Extensible Discovery on the specified servers.
-g <group ids> --groupids=<group ids>	Specified one or more device group IDs or device group names separated by commas. Runs Extensible Discovery on all the servers in the specified groups.

To find a server ID or a device group ID in the SA Client, display the server or device group and locate the ID in the Object ID column. The Object ID is an integer value.

Adding Scripts to Extensible Discovery

SA can gather a large amount of information from your servers by default. Extensible Discovery lets you gather additional information about your servers quickly and easily. Extensible Discovery is a feature that you can customize and use to discover and obtain custom information about servers in your managed environment. With Extensible Discovery you can:

- Write scripts that gather custom information from your servers and easily incorporate your scripts into Extensible Discovery.

- Schedule the execution of your scripts.
- Search and generate reports on the resulting custom information.
- Export the resulting information to other tools for further analysis and decision support.
- Automatically update all servers when your scripts change.

Scripts Provided with Extensible Discovery

The following scripts are included with Extensible Discovery. These scripts are automatically executed on the selected managed servers when you run Extensible Discovery.

Table 10 Scripts Included with Extensible Discovery

Script Name	Operating System	Description
get_oslevel.sh	AIX	Returns the operating system level. (Uses the AIX command <code>oslevel -s</code> .)
get_install_date.sh	HP-UX	Returns the date the operating system was installed. The date value is formatted to be placed in a custom attribute or a string type custom field, but not a date type custom field.
get_firmware_version.sh	Linux	Returns the BIOS version.
get_firmware_version.sh	Solaris	Returns the EEPROM (or OBP) version when run on Sparc servers. Otherwise returns the BIOS version.
get_firmware_version.vb	Windows	Returns the BIOS version.

These scripts will create custom attributes with the name `HPSW_ED_firmware_version` or `HPWS_ED_oslevel`. If you want the return values to be placed in custom fields, you must create custom fields named `HPSW_ED_firmware_version` and `HPWS_ED_oslevel` before running the extension, and the return values will be stored in the custom fields you created. If the custom fields don't exist, Extensible Discovery will create custom attributes on each server and place the data in the custom attributes.

These scripts are in the SA Library under `/Opware/Tools/Extensible Discovery/HP Provided Components`. To view these scripts, in the SA Client select **Library, By Folder** and navigate to the `HP Provided Scripts` folder. Select a .zip file and select **Actions † Export Software**.

If you do not want these scripts to execute on managed servers, remove them from the “HP Provided Scripts” software policy as described in [Software Policies Provided with Extensible Discovery](#) below.

Software Policies Provided with Extensible Discovery

Extensible Discovery uses two software policies that contain the scripts it runs to gather information from managed servers. Extensible Discovery automatically remediates these policies on managed servers and runs the scripts in them.

- **HP Provided Scripts:** This software policy contains the HP-provided scripts listed in [Table 10, "Scripts Included with Extensible Discovery"](#). It is located in the SA Library under `/Opware/Tools/Extensible Discovery/HP Provided Components`.
- **Customer Provided Scripts:** This software policy is initially empty. You can place your custom scripts in this software policy as described below and Extensible Discovery will use your scripts. It is located in the SA Library under `/Opware/Tools/Extensible Discovery/Customer Provided Components`.

When you run Extensible Discovery, it remediates these policies on the selected managed servers and runs all the scripts in these policies. If you don't want any of the scripts in these policies to run, remove them from the policy.

Extensible Discovery copies the scripts in these policies to the following directories on the managed servers:

- `/var/opt/opsware/extensible_discovery/scripts/` on UNIX systems.
- `%SYSTEMDRIVE%\Program Files\Common Files\Opware\extensible_discovery\scripts\` on Windows systems.

Extensible Discovery runs all the scripts in these directories regardless of how the scripts got there.

You can use these software policies or create your own software policies, but if you create your own, you must remediate them on managed servers where you want to run Extensible Discovery. For more information on software policies, see the *SA User Guide: Software Management*.

Writing Your Own Scripts for Extensible Discovery

This section describes requirements and guidelines for writing scripts for use with Extensible Discovery. For instructions on how to add your scripts to Extensible Discovery, see [Adding Your Own Scripts to Extensible Discovery](#) on page 157.

- HP provides several sample scripts you can use in the software policy "HP Provided Scripts". You can view these scripts in `/Library/Opware/Tools/Extensible Discovery/HP Provided Components`. For more information, see [Scripts Provided with Extensible Discovery](#) on page 155.
- A best practice is to store your script in a version control system.
- Your script needs to handle error situations within your script and return an accurate exit status. The following explains various error situations and how Extensible Discovery handles them.
 - The exit status of a shell script is the exit status of the last command in the script. A script that returns zero status is considered successful.
 - A script could return zero status but also send some output to `stderr`. This case is treated as a success. The output from `stderr` will be treated the same as `stdout`.
 - A script that returns zero status and outputs nothing to `stdout` or `stderr` will be considered a success and the blank value will be written to the appropriate custom attribute or custom field. You could use this method to set the custom attribute or custom field to "".
 - A script that returns a non-zero value is treated as an error. A message including the script's `stdout` and `stderr` will be stored in the `HPSW_ED_error` custom attribute.

- A script that is not executable or has syntax errors is treated as an error. A message including the script's stdout and stderr will be stored in the HPSW_ED_error custom attribute.
- If a script determines that it has nothing to collect on a server (for example, if the `get_eeprom_version.sh` is run on a Solaris x86 server, where there is no EEPROM), it should return an exit status of 3, which will be interpreted by Extensible Discovery as not applicable, and will return nothing for that particular data item.
- For UNIX shell scripts, if you want the script to fail when any individual command in the script fails, start the script with the line `#!/bin/sh -e`. For more information, see the documentation for the UNIX shell.

Adding Your Own Scripts to Extensible Discovery

To customize extensible discovery, you need to write one or more scripts that gather the custom data you want, then import your scripts into SA. For requirements and guidelines on writing scripts, see [Writing Your Own Scripts for Extensible Discovery](#) on page 156.



This section presumes you are familiar with software policies. For details on software policies, see the *SA User Guide: Software Management*.



To add scripts to Extensible Discovery, you must have write access to the Extensible Discovery folder and the ability to create software policies. For more information on permissions, see the *SA Administration Guide*.

To create and add your script to Extensible Discovery, perform the following steps.

- 1 Decide where you want the output of your script to go. It can go either in a custom attribute or in a custom field.
 - For more information on custom attributes, see [Custom Attributes for Servers](#) on page 248.
 - For more information on custom fields, see [Custom Fields for Servers](#) on page 246.
- 2 Decide on the name of the custom attribute or custom field. Extensible Discovery will place the output of your script in the named custom attribute or custom field.
 - For a custom attribute, the name will be in the following format: `HPSW_ED_<name>` where `<name>` is any string you choose.
 - For a custom field, use any value for the `<name>` of the custom field.

You must use the `<name>` string in the name of your script as described in the steps below.

- 3 Write your script such that the output of the script is the data you want to capture. You can write any of the following types of scripts:
 - UNIX shell scripts in a file ending with `.sh`.
 - Visual Basic scripts in a file ending with `.vbs`.
 - Windows batch scripts in a file ending with `.bat`.

For more information how to write these scripts for Extensible Discovery, see [Writing Your Own Scripts for Extensible Discovery](#) on page 156.

- 4 Test your script to make sure it is functioning properly.

- 5 Name your script `get_<name>.sh` or `get_<name>.vbs` or `get_<name>.bat`, where `<name>` is from [step 2](#) on page 157 above. Extensible Discovery uses `<name>` to locate the custom attribute or custom field for the output of the script.
- 6 Make sure your script file has execute permissions. For example, for UNIX scripts use the `chmod` command.
- 7 If you want the output to go into a custom attribute, skip this step and go to [step 8](#) below. Extensible Discovery creates and places the output in the custom attribute named `HPSW_ED_<name>` by default.

If you want the output to go to a custom field, you must create a custom field named “`<name>`” where `<name>` is the string you used in [step 2](#) and [step 5](#) above. Extensible Discovery first checks for an existing custom field of the specified name. If that custom field exists, Extensible Discovery places the script output there. If that custom field does not exist, Extensible Discovery creates and stores the output in a custom attribute named “`HPSW_ED_<name>`”.

For example, if you create a script named `get_mysysdata.sh`, the output from the script will be placed into the custom field named `mysysdata`, if it exists. Otherwise the output will be placed in the custom attribute named `HPSW_ED_mysysdata`.

For instruction on creating custom fields, see [About Custom Fields](#) on page 162.

- 8 Wrap your script into a `.zip` file. Include any other files your script needs in the `.zip` file.
As a best practice, include a version string in the name of your `.zip` file and increment the version string with each subsequent version of your script. For more information, see [Upgrading Your Scripts in Extensible Discovery](#) on page 159.
- 9 Import your `.zip` file into a package in SA.

For convenience, you can place your packages in `/Opsware/Tools/Extensible Discovery/Custom Provided Components`. Make sure your imported package specifies the proper target operating system.

For instructions on importing packages, see the *SA User Guide: Software Management*.

- 10 Open your package in the SA Client and set the Default Install Path property to one of the following and save your changes.
 - UNIX: `/var/opt/opsware/extensible_discovery/scripts`
 - Windows: `%ProgramFiles%\Common Files\Opsware\extensible_discovery\scripts\`.
SA replaces `%ProgramFiles%` with the appropriate system Program Files directory.
- 11 Add your package to a software policy. Add it either to the software policy named “Customer Provided Scripts” or add it to your own software policy.

Extensible Discovery remediates the “Customer Provided Scripts” policy by default whenever it runs.

Note that any user who has write access to the “Customer Provided Components” folder can run arbitrary code on any servers that Extensible Discovery is run on. For greater security, use your own software policy and set security on your software policy to meet your security requirements.

- 12 If you added your script to your own software policy, you must remediate your policy on all servers where you want Extensible Discovery to run.
If you added your script to the policy named “Customer Provided Scripts”, you can skip this step.
- 13 Run your script as described in [Running Extensible Discovery on Managed Servers](#) below.



If you intend to use a custom field but inadvertently run your script without having created the custom field and it creates custom attributes on many servers, you can use the following OGS command to remove the custom attributes from all servers.

```
rm /opsw/Server/@/*/*CustAttr/<custom attribute name>
```

For more information on the SA Global Shell (OGSH), see [SA Global Shell](#) on page 281.

Upgrading Your Scripts in Extensible Discovery

This section describes how to upgrade your scripts that are used with Extensible Discovery. The following steps presume you have already created and installed a script called `get_mysysdata.sh` and wrapped it in the file `get_windows_data_v1.0.zip` and imported it into Extensible Discovery as described in [Adding Your Own Scripts to Extensible Discovery](#) on page 157. To upgrade this script, perform the following steps.

- 1 Create the new version of your script and give it the same name as the original script file. For example, use `get_mysysdata.sh`. Follow the instructions in [Writing Your Own Scripts for Extensible Discovery](#) on page 156.
- 2 Wrap your script in a `.zip` file and increment the version string of the `.zip` file. For example, you could use `get_windows_data_v1.1.zip`.
- 3 Import your `.zip` file into a package in SA.

For convenience, you can place your packages in `/Opware/Tools/Extensible Discovery/Custom Provided Components`. Make sure your imported package specifies the proper target operating system.

For instructions on importing packages, see the *SA User Guide: Software Management*.

- 4 Open your package in the SA Client and set the Default Install Path property to one of the following and save your changes.
 - UNIX: `/var/opt/opsware/extensible_discovery/scripts`
 - Windows: `%ProgramFiles%\Common Files\Opware\extensible_discovery\scripts\`. SA replaces `%ProgramFiles%` with the appropriate system Program Files directory.
- 5 Open the software policy “Customer Provided Scripts”. If you have used another software policy, open that policy.
- 6 Remove the old `.zip` file from the policy, `get_windows_data_v1.0.zip` in this example.
- 7 Add your new `.zip` file to the policy, `get_windows_data_v1.1.zip` in this example.
- 8 If you are using the “Customer Provided Scripts” policy, run Extensible Discovery as described in [Running Extensible Discovery on Managed Servers](#) on page 153. This remediates your new script on the managed servers.

If you are using another policy, remediate the servers with that policy. This remediates your new script on the managed servers so Extensible Discovery can be run.

Removing Your Scripts from Managed Servers

When you run Extensible Discovery, it copies your scripts in “Customer Provided Scripts” to the specified managed servers. To remove the scripts from the managed servers, perform the following steps. For this scenario, assume you have a script named `get_mysysdata.sh` wrapped in the file `get_mysysdata_v2.5.zip`.

- 1 Create a new version of your `.zip` file with a new version number, for example `get_mysysdata_v2.6.zip`.
- 2 Copy everything from the old `.zip` file into the new `.zip` file, except for the script you want to remove from managed servers, `get_mysysdata.sh` in this example.
- 3 Import your `.zip` file into a package in SA.

For convenience, you can place your packages in `/Opsware/Tools/Extensible Discovery/Custom Provided Components`. Make sure your imported package specifies the proper target operating system.

For instructions on importing packages, see the *SA User Guide: Software Management*.

- 4 Open your package in the SA Client and set the Default Install Path property to one of the following and save your changes.
 - UNIX: `/var/opt/opsware/extensible_discovery/scripts`
 - Windows: `%ProgramFiles%\Common Files\Opsware\extensible_discovery\scripts\`. SA replaces `%ProgramFiles%` with the appropriate system Program Files directory.
- 5 Open the software policy “Customer Provided Scripts”. If you are using your own software policy, open your policy.
- 6 Remove the old `.zip` file, `get_mysysdata_v2.5.zip` in this example.
- 7 Add your new `.zip` file, `get_mysysdata_v2.6.zip` in this example.
- 8 If you are using the software policy “Customer Provided Scripts”, Run Extensible Discovery as described below. This removes your script from the managed servers.

If you are using your own software policy, remediate the managed servers. This removes the scripts from the managed servers.

Output from Extensible Discovery Scripts

Each script being used by Extensible Discovery provides output that is placed either in a custom attribute or a custom field. The maximum size of this output is 1000 bytes. To save more than 1000 bytes, perform the following steps.

- 1 Follow step 1 through [step 6](#) on page 158 under [Adding Your Own Scripts to Extensible Discovery](#) on page 157.
- 2 Create a configuration file the same name as your script except ending with “`.cfg`”. For example, if your script is named `get_mysysdata.sh`, create the file `get_mysysdata.cfg`.
- 3 Enter the following line in your configuration file.

```
MAXBYTESTOCAPTURE=<number of bytes>
```

where `<number of bytes>` is the maximum number of bytes your script will produce.
- 4 Wrap your script file and the configuration file into a `.zip` file.
- 5 Follow the remaining steps under [Adding Your Own Scripts to Extensible Discovery](#) on page 157.

Comparing Custom Fields and Custom Attributes

SA can store a large amount of information about your managed servers. Custom Attributes and Custom Fields provide a way for you to store additional information about your servers quickly and easily. Custom Attributes and Custom Fields are data elements you can create for servers and other objects in SA.

Custom Attributes and Custom Fields are similar but they have several differences as described in the following table. In general, you should use custom fields when all servers require the data to be stored and you should use custom attributes when only a subset of servers require the data to be stored. However, see the following table for other differences before you decide which to use.

Table 11 Comparison of Custom Attributes and Custom Fields

	Custom Attributes	Custom Fields
Data Type:	String only.	Typed. Must be one of the types listed in Table 12, "Custom Field Data Types" on page 162.
Objects Allowed for:	Allowed for any object: servers, device groups, customers, facilities, OS installation profiles, and software policies.	Allowed only for servers and device groups.
Number:	Each custom attribute is for one object only.	Each custom field creates an instance for all servers or device groups. All managed servers have the same named custom field, but the value can vary with each server. Similarly for device groups.
Searches Allowed:	Search is only allowed on the custom attribute name, not on its value. That is, you can search for all servers that define a particular custom attribute.	Search is allowed based on custom field values, including different matching criteria for different data types. For example, if you have a custom field of type date, you can search for all servers where the date value is one month old or older.
Inheritance:	Inherited from more general objects. For example, servers inherit custom attributes defined for device groups they belong to.	No inheritance.

Table 11 Comparison of Custom Attributes and Custom Fields

	Custom Attributes	Custom Fields
Permissions Required to View:	Read permission on the server, device group or other object.	Read permission on the server or device group.
Permissions Required to Modify the Value:	Write permission on the server, device group or other object.	Write permission on the server or device group.
Permissions Required to Create or Delete:	Write permission on the server or device group where you are creating the custom attribute.	Manage Virtual Columns permission. Write permission on the server or device group.

For more information on Custom Attributes and Custom Fields, see [Custom Fields for Servers](#) on page 246 and [Custom Attributes for Servers](#) on page 248.

About Custom Fields

SA can store a large amount of information about your managed servers. Custom Fields provide a way for you to store additional information about your servers quickly and easily. Custom Fields are data elements you can create for servers and device groups.

When you create a custom field for servers, every server in your managed environment gets an instance of the custom field. When you create a custom field for device groups, every device group gets an instance of the custom field. The value of the custom field can be different for each server or device group.

For example, if your managed environment contains 500 servers and you create a custom field for servers, you would have 500 separate custom fields, one for each server. If you had 75 device groups and you created a custom field for device groups, you would have 75 separate custom fields, one for each device group.

Custom attributes are another way to store additional information about your servers. For more information on custom attributes, see [Creating and Managing Custom Attributes](#) on page 165. See also [Comparing Custom Fields and Custom Attributes](#) on page 161.

Data Types in Custom Fields

Custom fields are typed. Each custom field you create must be of one of the following types.

Table 12 Custom Field Data Types

Custom Field Type	Description
String	Any characters, up to a maximum of 3999 characters.
Long String	Any characters. Use this type for strings longer than 3999 characters.
URI	A string representing a Uniform Resource Identifier.

Table 12 Custom Field Data Types

Custom Field Type	Description
Date	A date.
Number	A positive or negative integer.
File	An attached file.

Creating a Custom Field with the Custom Field Management Web Extension


The Custom Field Management web extension lets you create and delete custom fields.

- To create or delete custom fields, you must have the following permissions: Manage Virtual Columns, Execute permission on the Web Extensions folder in the Library, and Read access to at least one managed server. For more information on permissions, see the *SA Administration Guide*.

To create a custom field, perform the following steps.

- 1 In the SA Client navigation pane, select Library and the By Type tab.
- 2 Select Extensions, then select Web.
- 3 Select the Custom Field Management extension and either right click or select the **Actions** menu and select **Run...** This displays the Custom Field Management window as shown below.

Figure 45 Custom Field Management Web Extension - Create a Custom Field



- 4 In the first drop-down list, select the object you want the new custom field to be associated with. If you select Server, every server will get an instance of the custom field. If you select Device Group, every device group will get an instance of the custom field.

- 5 Enter the name of the new custom field in the text input field.
- 6 In the second drop-down list, select the data type of the custom field. See [Table 12, "Custom Field Data Types"](#) on page 162.
- 7 Select Process Input to create the custom field.

Deleting a Custom Field with the Custom Field Management Web Extension


The Custom Field Management web extension lets you create and delete custom fields. To delete a custom field, perform the following steps.



When you delete a custom field, you delete all the values stored by all the servers or device groups associated with the custom field.

- 1 In the SA Client navigation pane, select Library and the By Type tab.
- 2 Select Extensions, then select Web.
- 3 Select the Custom Field Management extension and either right click or select the **Actions** menu and select **Run...**. This displays the Custom Field Management window as shown in [Table 45, "Custom Field Management Web Extension - Create a Custom Field"](#) on page 163.
- 4 Select the "Delete a Custom Field" link. This displays the Delete a Custom Field Definition window as shown below.

Figure 46 Custom Field Management Web Extension - Delete a Custom Field



- 5 To delete a custom field defined for servers, select a custom field name in the first drop-down list. The example above shows the custom field FIRMWARE_VERSION selected.

To delete a custom field defined for device groups, select a custom field name in the second drop-down list.

- 6 To delete a custom field defined for servers, select Delete Custom Field Definition from Servers.

To delete a custom field defined for device groups, select Delete Custom Field Definition from Device Groups.

Editing Custom Field Values

To edit custom field values for a server, perform the following steps.

- 1 In the SA Client navigation pane, select the Devices tab.
- 2 Select the All Managed Servers node.
- 3 Select a server.
- 4 To view the custom fields and values, select Properties from the View drop-down selector. This displays several different properties of the server including all the custom fields defined for the server.
- 5 Open the server browser by selecting the **Actions** menu or right clicking on the server and selecting **Open**. This displays information about the server. Select the Information tab, then select Properties in the navigation pane. This displays several different properties of the server including all the custom fields defined for the server.
- 6 Locate the custom field you want to modify.
- 7 The way you modify the value of the custom field depends on the type of the custom field. Modify the value of the custom field.
- 8 Select **File † Revert** to discard all your changes to custom field values.
- 9 Select **File † Save** to save the modified custom field value.

Creating and Managing Custom Attributes

SA can store a large amount of information about your managed servers. Custom attributes provide a way for you to store additional information about your servers quickly and easily. Custom attributes are data elements you can create for servers and device groups.

You can create custom attributes for servers, device groups, customers, facilities, OS installation profiles, and software policies. Custom attributes values are string values.



Custom fields are another way to store additional information about your servers. For more information on custom fields, see [About Custom Fields](#) on page 162. See also [Comparing Custom Fields and Custom Attributes](#) on page 161.

To add, delete or modify the value of a custom attribute for a server, perform the following steps.

- 1 In the SA Client navigation pane, select the Devices tab.
- 2 Select the All Managed Servers node.
- 3 Select a server.

- 4 To view the custom attributes defined for the server, select Custom Attributes from the View drop-down selector. This displays all the custom attributes defined for the server.
- 5 Select the Actions menu or right click the server and select Open. This displays information about the server.
- 6 Select the Information tab in the navigation pane.
- 7 Select Custom Attributes in the navigation pane. This displays all the custom attributes defined for the server.
- 8 To add a new custom attribute, select the “+” icon and enter the name of the custom attribute.
- 9 To delete a custom attribute, select the custom attribute and select the “-” icon.
- 10 To change the value of a custom attribute, double click the value column in the appropriate row and enter the new value.
- 11 Select **File** † **Revert** to discard all your changes.
- 12 Select **File** † **Save** to save your changes.

7 Getting Started with the SA Web Client

SA Web Client

The following section describes [Supported Browsers for the SA Web Client](#) (a web application) and Browser Configuration Requirements.

Supported Browsers for the SA Web Client

The following table lists the supported browsers for the SA Web Client.

Table 13 Supported Browsers for the SA Web Client

Browser	Windows Vista	Windows 2000	Windows 2003	Windows XP
Microsoft Internet Explorer 5.5		X		
Microsoft Internet Explorer 6.0		X	X	X
Microsoft Internet Explorer 7.0	X	X	X	X
Microsoft Internet Explorer 8.0	X	X	X	X
Mozilla 1.6		X	X	X
Firefox 1.0		X	X	X
Firefox 2.0	X	X	X	X
Firefox 3.0, 3.5	X	X	X	X

Browser Configuration Requirements

To use the SA Web Client, your browser must be configured in the following manner:

- The browser must accept cookies and be able to use Java.
- The browser must support SSL and should provide 128-bit encryption (recommended).
- Using a pop-up blocker might prevent some functions from working correctly. Either disable the pop-up blocker completely or use the supported browser's native pop-up blocking function instead of a third-party product.

User Interface

The following section discusses getting started with the SA System and contains the following topics:

- [Requirements for Logging In](#)
- [Overview of the SA Web Client User Interface](#)
- [Search](#)
- [My Servers](#)
- [Mouseover Icon Tooltips](#)

Requirements for Logging In

To log in to the SA Web Client, your SA administrator must have created a user name and password for you, and assigned user permissions that control the features you can access, the actions you can perform, and the resources you can access.

Overview of the SA Web Client User Interface


The SA Web Client user interface consists of the five following sections:

- [Home Page](#)
- [Tasks](#)
- [My Jobs](#)
- [My Customers](#)
- [Navigation Panel](#)

Home Page

[Figure 47](#) shows the Home page as it appears when you log in or when you click the Home link in the navigation bar.

Figure 47 SA System Home Page



The time zone that appears in the upper right corner of the Home page is taken from the time zone preference that was defined for you when your profile was created. Consequently, the date and time information that displays throughout the SA Web Client is for that time zone. The occasional exceptions however are always labeled GMT.

Tasks

The Tasks area of the Home page displays links to the wizards that you have permissions to access. If you do not have permissions to a task in this area, the task name still displays, but it is italicized and it is not an active link. Figure 48 shows the Tasks area with all permissions enabled.

Figure 48 Tasks Area of the Home Page

Tasks		
OS Provisioning	Software Provisioning	Power Tools
Prepare OS	<i>Deploy Code</i>	Launch Opsware SAS Client Run Distributed Script Run Custom Extensions

My Jobs

The My Jobs area of the Home page is populated with details of the jobs that you have run, jobs that are currently in progress, or jobs that you have scheduled to run, including the name of the job, the start time, the number of servers affected by the job, and the status of the job. If there are more than six jobs, you can see the rest of them by clicking the See All link, which also shows the total number of jobs in parentheses, as Figure 49 shows.

If the job was run in the SA Client, then there will be a link next to the job that (when clicked) will launch the SA Client. You can view the more detailed information about the job in the SA Client.

Figure 49 My Jobs Area of the Home Page

My Jobs ?

< Job ID > All Job Types No Time Restrictions All Job Status Update

2 Total

	Job ID	Job Type	Start Time ▲	Servers	Groups	Status
	260003	Communication Test	Tue May 17 20:46:35 2005	1	0	Completed
	250003	Communication Test	Tue May 17 20:43:50 2005	1	0	Completed

My Customers

The My Customers area of the Home page is populated with customer information, including unreachable servers associated with a customer and the total number of servers associated with that customer. To select the customers to display in the My Customers area of the Home page, click **Edit** and select the check box next to the customer name. See [Figure 50](#).

Figure 50 My Customers Area of the Home Page

My Customers Edit

Customer	Unreachable Servers	Total Servers
Arnold	0	0
Industrial Machines	0	0
MASTERCUST	106	110
Opware	13	23
OPSWINC	0	0

Navigation Panel

The navigation panel on the left side of the SA Web Client shows all possible features, as shown in [Figure 51](#). The features you can access and the actions you can perform depend upon your user profile, as defined by the SA administrator.

Figure 51 Navigation Panel, All Permissions View



The items that appear in the navigation panel depend on the permissions the user has. Clicking an item on the navigation panel displays that feature in the main part of the Home page. For a user with all permissions, the following links appear:

Home: Displays the top level of the SA Web Client. The Home page is described in this section of the guide. Wizards are documented in their respective functional areas of the system.

My Jobs: Displays the My Jobs page, showing jobs completed during the previous 30 days, jobs currently in progress, and currently scheduled jobs. This page is an expanded view of the contents of the My Jobs area of the Home page and has the same effect as clicking **Show All** in the My Jobs area of the Home page.

Servers: Expands to display these selections:

- **My Servers:** Use to add any server or server group to your own personal view of servers. My Servers provides an efficient way to manage servers when your operational environment contains hundreds or thousands of servers.
- **Manage Servers:** Use filters to display a list of servers and perform operations on them such as edit server values, assign, run scripts, and add servers to My Servers. See [Server Management in the SA Web Client](#) on page 205 for more information.
- **Search:** Find specific servers using default criteria or user-defined criteria. See [Server Search](#) on page 183 for more information.
- **Server Pool:** Use filters to display a list of servers, install operating systems on the servers, and delete the servers. For more information, see the *SA User Guide: OS Provisioning*.

Software: Expands to display these selections:

- **Operating Systems:** Prepare operating systems for installation and delete existing operating systems. See the *SA User Guide: OS Provisioning* for more information.

Environment: Expands to display these selections:

- **Hardware:** A read-only view of servers categorized by the hardware manufacturer and model, and their related information. See [Hardware Information for Managed Servers](#) on page 202 for more information.
- **Service Levels:** Define service levels and custom attributes. See [Service Levels](#) on page 251 for more information.

Administration: Expands to display the following. For more information, see the *SA Administration Guide*.

- **Opsware Software:** Provides a view of the properties, custom attributes, installation order, and history of the software attached to the SA in the system.



The Administration set of features is only available if you are logged in as an SA administrator.

Navigation

Top-level navigation from the Home page is simple. To access any of the features in the navigation panel, click the feature name. To access any of the wizards or other features in the Tasks area of the Home page, click the name of the task.

After you select a task or a feature, other pages appear, which might have one or more of the following means of navigation:

- Clicking a hyperlinked name to display a page

For example, if you select Software † Scripts (assuming that you have the correct permissions), the page that appears shows all of the scripts that have been uploaded so far.

- Selecting a tab to display a page

For example, when you select Manage Servers and click one of the hyperlinked server names, the resulting page shows a row of tabs, like [Figure 52](#) shows.

Figure 52 Example of Tabs



Each tab displays a page, each with its own buttons and functionality.

- Clicking a button to display a page

For example, when you select the Custom Attributes tab, a page appears with several buttons: **Add**, **Delete**, and **Copy**, which are common to each page called by these tabs, and **Add Custom Attribute**, which is unique to this particular tab. You will find similar functionality on all tabbed pages in the SA System.

Search

At the top of the Home page open the dialog box as [Figure 53](#) shows.

Figure 53 Search Function

Show	Servers	named	<Enter search text here>	Go
Home	Jobs	Server Groups	Servers	

You can search for servers, jobs, and server groups, by making the selection from the drop-down list, and then entering an identifying string in the text box.

My Servers

The My Servers feature provides a convenient place to store a set of servers that have been selected and stored using the Add to My Servers function in Manage Servers. You might use it as a shortcut to the servers you work with most often, or as a way to gather a group of servers when you want to apply the same changes to all of them. All functions that are available in the Manage Servers page are also available from within My Servers.

Mouseover Icon Tooltips

When an icon appears on a page in the SA Web Client, a tooltip displays information about the icon when your mouse pointer hovers over it. For example, server icons display messages such as “Available or Build Failed” to describe the state of the server. Packages and patches display messages such as Available, Managed, Unmanaged, and so forth.

8 Server Tracking in the SA Web Client

Server Tracking

This section discusses the following topics:

- [Ways to Locate, List, and Display Servers](#)
- [Tracked Server Properties](#)
- [Supported Operating Systems for Managed Servers.](#)

Ways to Locate, List, and Display Servers

You can locate, list, and display servers in the SA Web Client in the following four ways:

- By searching when you know the name, host name, or IP address of the server you want to provision or manage.
- By viewing the Manage Servers list and Server Pool list when you want to see a complete list of all your servers. You can refine the lists by using filters.
- By viewing servers sorted by hardware category. (Click Environment † Hardware in the navigation panel.) The Servers tab in the Hardware pages shows each manufacturer and model that you have running in the operational environment. See [Hardware Information for Managed Servers](#) on page 202 for more information.
- You can also browse managed servers and server groups using the SA Client.

Tracked Server Properties

Every server that SA manages has the following properties:

- IP addresses, host name, and the server ID
- All software that *is installed* on the server. Select the Installed Packages tab from the Manage Servers: Server Properties page to display the list of software that is reportedly installed on the server.

SA is able to determine what software is installed on a server because the Server Agent communicates with the SA core and reports the installed hardware and software for the server.

In some cases, Solaris packages might only be partially installed. In these cases, the partially installed Solaris package does not show up in the installed list.

See [Server Information that the Agent Tracks](#) on page 130 for more information about a complete list of all the hardware and software information that SA tracks for managed servers.

Supported Operating Systems for Managed Servers

This section lists the supported operating systems for Server Agents and the SA Client.

SA Server Agent Supported Operating Systems

The following table lists the supported operating systems for SA Server Agents, which run on the servers managed by SA. Platforms with a (*) are deprecated. For more information on platform deprecation in SA in this release, see the *SA Release Notes* for this release.

Table 14 SA Server Agent Supported Operating Systems

Supported Operating System Versions for SA Server Agent	Architecture
AIX 5.2	POWER
AIX 5.3	POWER
AIX 6.1	POWER
HP-UX 11.11	PA-RISC (direct, nPartition)
HP-UX 11.23 (11i v2)	PA-RISC (direct, nPartition) Itanium (direct, nPartition)
HP-UX 11.31 (11i v3)	PA-RISC (direct, nPartition) Itanium (direct, nPartition)
Solaris 6* Solaris 6, 7, 8, 9, and 10 are supported running on Sun Dynamic System Domains.	Sun SPARC 4u
Solaris 7*	Sun SPARC 4u
Solaris 8*	Sun SPARC 4u
Solaris 9*	Sun SPARC 4u
Solaris 10 (Updates 1, 2, 3, 4, 5, and 6)	Sun SPARC (4u, 4v) and x86_64, x86_32 Solaris 10 is supported in guest logical domains.
Solaris 11	Sun SPARC (4u, 4v) and x86_64, x86_32 Solaris 11 is supported in guest logical domains.
Fujitsu Solaris 8*	Fujitsu SPARC
Fujitsu Solaris 9*	Fujitsu SPARC
Windows 2000 Server Family	x86_32
Windows Server 2003	x86_32, x86_64
Windows XP Professional	x86_32
Windows Server 2008	x86_32, x86_64
Red Hat Enterprise Linux 3 AS	x86_32, x86_64, Itanium

Table 14 SA Server Agent Supported Operating Systems (cont'd)

Supported Operating System Versions for SA Server Agent	Architecture
Red Hat Enterprise Linux 3 ES	x86_32, x86_64, Itanium
Red Hat Enterprise Linux 3 WS	x86_32, x86_64, Itanium
Red Hat Enterprise Linux 4 AS	x86_32, x86_64, Itanium
Red Hat Enterprise Linux 4 ES	x86_32, x86_64, Itanium
Red Hat Enterprise Linux 4 WS	x86_32 and x86_64, Itanium
Red Hat Enterprise Linux Server 5	x86_32, x86_64, Itanium
Red Hat Enterprise Linux Desktop 5	x86_32 and x86_64
Red Hat Enterprise Linux Server 6	x86_32, x86_64, Itanium
Red Hat Enterprise Linux Desktop 6	x86_32 and x86_64
SUSE Linux Enterprise Server 8	32 bit x86
SUSE Linux Standard Server 8	32 bit x86
SUSE Linux Enterprise Server 9	x86_32 and x86_64
SUSE Linux Enterprise Server 10	x86_32 and x86_64
SUSE Linux Enterprise Server 11	x86_32 and x86_64
VMware ESX Server 3.0	x86_32 and x86_64
VMware ESX Server 3.5	x86_32 and x86_64
VMware ESXi Server 3.5	x86_32 and x86_64



On Red Hat Enterprise Linux 4 AS, SA does not support SELinux (Security Enhanced Linux). By default, SELinux is enabled on Red Hat 4 AS. You must disable the SELinux feature on Red Hat 4 AS for the SA Agent to function correctly. SA supports SELinux (Security Enhanced Linux) on Enterprise Linux 5.

Support for HP-UX on HP vPars and HPVM

SA supports managed servers for HP-UX on HP vPars and HPVM technology. Specifically, SA supports the following as an equal to HP-UX support on individual physical systems:

- HP-UX 11i v2 & 11i v3 Integrity VM (HPVM) guests running on Integrity VM B.04.00 or later
- HP-UX 11i v2 & 11i v3 vPars running on vPars A.05.00 or later.

This support entails that, for the above supported HP-UX versions, all supported features are also supported on HP vPars and HPVM. The solution at this point does not have any support for creating, starting or stopping the vPars or HPVM virtual machines.

Required Operating System Packages/Patches for SA Agents

Table 15 Required Packages/Patches for SA Agents

Server Operating System	Required Patches
HP-UX (11.11/11i)	SW-DIST must be upgraded to the HP recommended patch level. You should continue to upgrade this package when HP recommends new versions.
Red Hat Linux AS 3.0 Red Hat Linux WS 3.0 Red Hat Linux ES 3.0	Red Hat Enterprise Linux 3 Update 3
Solaris 10, 9, 8, 7, and 6	SUNWadmc SUNWcsl SUNWcslr (If available, depending on version) SUNWcsu SUNWesu SUNWlibms SUNlibmsr (If available, depending on version) SUNWswmt It is strongly recommended not to remove packages from the SUNWCreq minimal required install cluster, since many packages are interdependent and operation beyond that of basic SA functionality may be affected.
Windows 2000	Service Pack 4

SA Client Supported Operating Systems

Table 16 lists the operating systems supported for the SA Client.

Table 16 SA Client Supported Operating Systems

Supported Operating Systems Versions for the SA Client	Architecture
Windows Vista	x86_32 and x86_64
Windows XP	x86_32
Windows 2003	x86_32
Windows 2000	x86_32

Server Lists

This section discusses the following topics:

- [Types of Server Lists](#)
- [Server Pool](#)
- [Manage Servers List](#)
- [Filters on the Manage Servers List](#)

Types of Server Lists

The SA Web Client displays lists for two types of servers, as [Figure 54](#) shows.

Figure 54 Servers Section in the Navigation Panel



Server Pool: Servers in the Server Pool have registered their presence with SA but do not have the target OS installed. An OS Build Agent is running on each server so that they can communicate with SA.

For more information on OS provisioning, see the *SA User Guide: OS Provisioning*.

Manage Servers: The Manage Servers list contains servers on which SA can perform management tasks, because Server Agents are installed on them. However, SA might not have provisioned all software running on the servers.

You begin the OS provisioning process by reviewing the servers in the Server Pool list. From the Server Pool, you can install a target OS by selecting a server and clicking **Install OS**.

Server Pool

The Server Pool provides the following information about each server waiting to be provisioned with the target OS:

- The host name set by booting the server for the first time over the network or by using an SA Boot Floppy
- The MAC address
- The manufacturer and model
- The OS that the OS Build Agent is running – DOS (Windows operating systems), Linux, or Solaris

You use this information to select the target OS for servers. If the server is in the process of installing an OS, this value might change.

- The last date and time that the Server Agent on the server communicated with SA (by submitting the server's hardware and software information)


If the server is in an unreachable state (that is, if the server icon has a red “x” on it), you can run a Communication Test to help you troubleshoot why that server is unreachable. See [Running Server Communication Tests](#) on page 139 for more information.

- The life cycle value, such as whether the server is available to have a target OS installed on it
- The facility in which the server is located
- The customer association
- Additional hardware information (Click the server name to open a window that displays specific hardware information.)



Manage Servers List

The Manage Servers list contains servers on which SA can perform management tasks because Server Agents are installed on them. When an existing operational server has an Server Agent installed successfully, it appears in the Manage Servers list and the server icon indicates that it is fully manageable, as [Figure 55](#) shows.

Figure 55 The Manage Servers List in the SA Web Client

Manage Servers (Summary View) 

Resource Edit View Tasks Configuration Tracking

<input type="checkbox"/>	Name ^	Host Name / IP Address	OS Version	Stage	Use	Facility	Customer
 Public Groups							
<input type="checkbox"/>	 m022.dev.opsware.com	m022.dev.opsware.com 192.168.197.91	Red Hat Enterprise Linux AS 2.1	Not Specified	Not Specified	C03	Not Assigned

See [Installing and Managing Server Agents](#) on page 123 for more information. By default, servers in the Manage Servers list are sorted by the Name column. However, you can re-sort the list based on any of the column headings. For example, you can click the Hostname / IP Address column heading to re-sort the list by host name or IP address.

If you have many servers that SA manages, the list of servers is grouped by pages. Click the page number links or the left arrow at the bottom of the list.

The Manage Servers list provides the following information about each server:

- The name of the server
 - By default, the server's host name appears in this field. However, you can edit it so that it is more descriptive or useful.
- The host name of the server determined by the Server Agent
- The IP address configured for the server, which users can edit by using the network configuration feature in the
- The reported OS, which is obtained by the Server Agent that is running on the server
- The stage of the server, which specifies the stages of deployment for servers
- The server's use
- The facility in which the server is located
- The customer association
- Additional hardware information (Click the server name to open a window that displays specific hardware information.)

Filters on the Manage Servers List

The Manage Servers list displays the following filters that you can specify to qualify the servers that the SA Web Client displays, as [Figure 56](#) shows.


Figure 56 Filters in the Manage Servers List

Manage Servers (Summary View)



- **Status:** Specifies the ability of SA to manage servers. SA automatically detects the status of servers; a server's status is OK or Not Reachable.
- **OS:** Specifies the operating system on the server, which is obtained by the Server Agent that is running on the server.
- **Stages:** Specifies the stages of deployment for servers; for example, a server is live or offline. Users set this property for servers. The values in this list are customizable by the SA administrator.
- **Uses:** Specifies how an organization is utilizing servers. For example, a server is a staging server. Users set this property for servers. The SA administrator can customize the values in this list.
- **Facilities:** Specifies the location of servers. From an SA Web Client, users can manage servers located in any facility. For example, a user could log in to the SA Web Client running in facility A and manage the server located in facility B.
- **Customers:** Specifies the customer associated with each server. Your SA administrator defines the options for customer selections by using the Administration pages.
- **Manufacturers:** Specifies the manufacturer for the server as reported by the OS Build Agent running on the server.
- **Models:** Specifies the model of the server as reported by the OS Build Agent running on the server.
- **Life cycles:** Specifies the various SA server life cycle values which include Managed, Available, Build Failed, Installing OS, and Deactivated.



You can change the filters displayed in the Manage Servers page. To change the filters you want to be displayed on the Manage Servers page, click on the edit icon  and specify the filters from the **Edit Filters** Menu.

[Figure 57](#) shows the filters that are in the Server Pool list.

Figure 57 Filters in the Server Pool List



- **Manufacturers:** Specifies the manufacturer for the server as reported by the OS Build Agent running on the server.
- **Models:** Specifies the model of the server as reported by the OS Build Agent running on the server.
- **Facilities:** Specifies the location of the server. Users can manage servers in any facility from an SA Web Client in any facility.

My Servers

This section contains the following topics:

- [Overview of My Servers](#)
- [Adding Servers to My Servers](#)
- [Removing Servers from My Servers](#)

Overview of My Servers

The My Servers feature provides an efficient way to manage servers when your operational environment contains hundreds or thousands of servers.

When you search for servers or browse the server lists, you can add servers to My Servers (similar to a shopping cart on an e-commerce site). Using My Servers allows you to view and perform actions on selected servers.

When you use the same browser and login to the SA Web Client running in the same facility, servers stay in My Servers for one year or until you explicitly remove them. Each time that you login to the SA Web Client, you see the servers that were in My Servers the last time that you logged in.

The My Servers feature is available only on a per-user basis. You cannot log in as an SA administrator to see the servers in the My Servers area of other SA users.

Adding Servers to My Servers

Perform the following steps to add a server to My Servers:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears. Browse the list to find the servers that you want to add to the My Servers.
Or
Search for the servers that you want to add to My Servers.
See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.
- 2 Select the servers that you want to add to My Servers.
- 3 Choose **Resource † Add to My Servers** from the menu above the Manage Servers list. The Add To My Servers window appears, which indicates that you added the chosen number of servers to My Servers.
- 4 Click **Close** to close the window.
- 5 Next, select the My Servers link at the top of the page. You see the selected servers added to My Servers, as [Figure 58](#) shows.

Figure 58 Servers in My Servers

My Servers (Summary View) ?

Resource	Edit	View	Tasks	Configuration Tracking			
<input type="checkbox"/>	Name ^	Host Name / IP Address	OS Version	Stage	Use	Facility	Customer
<input type="checkbox"/>	 m098.dev.opsware.com	m098.dev.opsware.com 192.168.192.67	SunOS 5.8	Not Specified	Production	C03	Opsware

You can perform the same server management tasks on servers in My Servers as on the servers in the Manage Servers list.

Removing Servers from My Servers

Perform the following steps to remove servers from My Servers:

- 1 Click the My Servers link in the navigation panel of the SA Web Client. The My Servers page appears that shows the servers currently added to it.
- 2 Select the servers that you want to remove from My Servers and choose **Edit † Remove from My Servers** from the menu above the Server list.

The My Servers page refreshes and displays the remaining servers in My Servers.

Server Search

This section provides information about Server Search and contains the following topics:

- [Searching for a Server By Using the Search Box](#)
- [Ways to Use Search](#)
- [Searching for Servers or Other Resources](#)
- [Rules for Server Search and for Creating Dynamic Device Groups](#)
- [Line Break Workaround for Server Search](#)
- [Conditions for Searching with Multiple Rules](#)
- [Server Searching by IP Address](#)
- [Example: Server Search](#)
- [Searching for a Server Group](#)

Searching for a Server By Using the Search Box

Perform the following steps to search for a server using the Search box:

- 1 On the Home page, click the down arrow in the top navigation panel to open the Search box, as [Figure 59](#) shows.

Figure 59 Search Text Box on the SA Web Client Home Page



- 2 Verify that the Servers option is selected in the list.
- 3 Type the server's IP address, host name, or name in the Search box and then click **Go**.

The search text that you enter can include an asterisk (*) wildcard character. However, the search feature automatically prepends and appends an asterisk to the text.

For example, you can type any of the following search queries:

```
192.168.68.6  
host02.coredev-val.sample.com  
192.168.*.19  
host1*.xyz.samplecompany.com
```

The resulting page contains one or more servers, depending on the type of search query that you specified. If no servers are found, the SA Web Client displays a message that indicates that no servers were found that matched your query.

See [Searching for Servers or Other Resources](#) on page 184 for more information on how to formulate complex, multiple rule search queries.

Ways to Use Search

By using the SA Web Client, you can perform searches in the following ways:

- From SA wizards

While using the SA wizards from the Tasks panel, you are prompted to select (by browsing or searching) servers or server groups, and operating systems, at specific points in the process.

What you can search for in the SA wizards is context sensitive to the type of operation that you are performing.

- From the navigation panel, click Servers † Search.

The Search page allows you to search for managed servers that match specified rules.

- While adding or modifying rules for a dynamic group (By clicking **Search** on the Rules tab for a group).

Searching for Servers or Other Resources

In the SA Wizards, you can browse for servers, operating systems, or search for these items.

Perform the following steps to search:

- 1 In an SA wizard, select the Search tab. The following Search page appears. See [Figure 60](#).

Figure 60 Search Tab in the Select Servers Step of an SA Wizard

Select Software
Select the software application(s) you wish to install.

Browse | **Search** (0) Software Selected
Match: if all rules are met

Name is Search

You can also use the Search tab at other steps in the wizards to search for operating systems, patches, applications, and templates.

Or

From the navigation panel, click Servers † Search. The Search page appears, as [Figure 61](#) shows.

Figure 61 Search Page

Search ?

Servers | **Groups**


▼ **Rules**
Match: if all rules are met

Search for servers whose:
Agent Discovery Date is after May 23 2005 Search Save... Reset

By default, one search rule is added to the search.


- 2 Specify the rule that you want to search for by selecting it from the first list, as [Figure 62](#) shows.

Figure 62 Search Rules List in the Search Page



Depending on the rule that you select, a popup window might appear in the page. For example, if you selected Deployment Stage, a popup window showing the stages appears in the page as [Figure 63](#) shows:

Figure 63 Search Popup Window with Values



You cannot search in Notes that contain line breaks. See [Line Break Workaround for Server Search](#) on page 195 for more information and a workaround.

If you are searching while using an SA wizard, the first search rule list might not have all the options. The list only includes the options that are relevant for the SA wizard that is being used. For example, the Install OS Wizard does not include options to search for installed patches on the servers.

- 3 In the second list, specify how you want SA to search by selecting a value. The operator selected defines how the search text is treated. Negative operators might not be available in all cases.

See [Rules for Server Search and for Creating Dynamic Device Groups](#) on page 188 for more information about the operator for each search rule.

- 4 Enter the text that you want to search for in the text box or choose a value from the list or popup window. The search text that you enter can include an asterisk (*) wildcard character. The search text is case insensitive. You can also use the SHIFT or CTRL key to select multiple values from the list or popup window.
- 5 (Optional) To add additional rules, click the plus (+) button as [Figure 64](#) shows and repeat Steps 2 through 4.

Figure 64 Multiple Rules in a Search

Search

Servers Groups

▼ Rules

Match: if all rules are met

Search for servers whose:

Deployment Stage Is In Deployment

Opware Display Name Contains marketing

Search Save... Reset

- 6 If you specified multiple rules for the search, select whether you want search results only if all rules are met or if any of the rules are met, as [Figure 65](#) shows.

Figure 65 Operator Controlling Search Results

Match: if all rules are met

if all rules are met

if any rules are met

By default, search results appear for servers that match all the search rules. If you are searching from an SA wizard, this field is set to the value if all rules are met; you can change the value when searching for servers, but you cannot change it when searching for patches, software, operating systems, and so on.

- 7 Click **Search**. The list of servers that match your search rules appears in the page, as [Figure 66](#) shows.

Figure 66 Displayed Search Results

Results						
Resource	Edit	Tasks	Configuration Tracking			
<input type="checkbox"/>	Name	Host Name	IP Address	OS Version	Facility	Customer
<input type="checkbox"/>	casela.snv1.corp.opsware.com Web Services test box	casela.snv1.corp.opsware.com	192.168.9.191	SunOS 5.9	C12	Opware
<input type="checkbox"/>	chamarel.snv1.corp.opsware.com Web Services test box	chamarel.snv1.corp.opsware.com	192.168.9.146	Red Hat Linux 7.3	C12	Opware

The search results include columns for Name, IP Address, OS Version, Facility, and Customer.

When you search for installed software or patches and include an asterisk in the search text, SA might take several minutes to display the search results.

Rules for Server Search and for Creating Dynamic Device Groups

The following table describes the rules that you can use to search for servers or to create dynamic device groups. Note that anywhere you can enter text, you can enter a wildcard (*) character to broaden your results.

Table 17 Rules for Server Search and for Creating Dynamic Groups

Rule Name and Description	Operators	Value
Properties		
Agent Discovery Date: The date that the Server Agent was installed.	<ul style="list-style-type: none"> • Is after • Is before 	Drop-down lists with the day, month, and year
	<ul style="list-style-type: none"> • Is within the last 	User-entered text
Agent Reporting: Whether the Server Agent is reporting to SA.	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • Has not reported • OK • Registration in progress • Reporting error
Agent Status: Whether the Server Agent is reachable by SA.	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • Not reachable • OK
Agent Version: The version of the Server Agent — such as 14.2.3b.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Application Configuration: Whether the server uses the Application Configuration feature.	<ul style="list-style-type: none"> • Is not used • Is used 	N/A
Configuration Tracking: Whether the Configuration Tracking feature is monitoring or backing up specific files or configurations on a server.	<ul style="list-style-type: none"> • Is off • Is on 	N/A
Custom Attribute (any): The name of a custom attribute that is associated with the server through attachment or inheritance.	<ul style="list-style-type: none"> • Contains • Is 	User-entered text
Custom Attribute (local): The name of a custom attribute that is locally attached to the server,	<ul style="list-style-type: none"> • Contains • Is 	User-entered text
Customer: The customer or account that the server is associated with.	<ul style="list-style-type: none"> • Is • Is not 	Window of customers

Table 17 Rules for Server Search and for Creating Dynamic Groups

Rule Name and Description	Operators	Value
Deployment Stage: The stage the server performs within a lifecycle environment.	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • In Deployment • Live • Not Specified • Offline <hr/> <p>The values that appear in this list are customizable; in addition to the values above, values specific to your environment might appear.</p> <hr/>
Display Name: The user-configurable name for the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	<p>User-entered text</p> <hr/> <p>By default, SA uses the configured host name of the server until a user edits it.</p> <hr/>
Facility: The collection of servers managed by an SA installation.	<ul style="list-style-type: none"> • Is • Is not 	<p>Window of facilities</p> <hr/> <p>When SA is running multimaster mode, the list can contain many facilities.</p> <hr/>
Group Membership: Whether the server belongs to a group.	<ul style="list-style-type: none"> • Is 	<p>Popup window of groups</p>
Host name: The host name of the server — such as m004.company.com.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	<p>User-entered text</p>
Lifecycle: The server states that are part of bringing a server into SA.	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • Available • Build Failed • Deactivated • Installing OS • Managed
Name (any): This enables searching for any name or IP address associated with a server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	<p>User-entered text</p>

Table 17 Rules for Server Search and for Creating Dynamic Groups

Rule Name and Description	Operators	Value
<p>Notes: The contents of the Notes field from the Properties tab for a server.</p>	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	<p>User-entered text</p>
<p>Server Use: How the server is being used — such as Development, Staging, Production.</p>	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • Development • Not Specified • Production • Staging <hr/> <p>You can customize values that appear in this list. In addition to the values above, values specific to your environment might appear.</p>
<p>Service Level: The user-defined category that can be used as an organizational tool.</p>	<ul style="list-style-type: none"> • Is • Is attached here or below 	<p>Popup window of service levels</p> <hr/> <p>Servers can be associated with multiple service levels.</p>
<p>Server ID: The internal ID SA uses to identify the server.</p>	<ul style="list-style-type: none"> • Is • Is not 	<p>User-entered text</p> <hr/> <p>In most cases, the Server ID is the same as the MID.</p>
<p>Software</p>		
<p>Attached Software: The software that is assigned or modeled through the SA installation process.</p>	<ul style="list-style-type: none"> • Is • Is attached here or below 	<p>Popup window of software</p>
<p>Attached Software Policies: The software policies that is assigned or modeled through the SA installation process.</p>	<ul style="list-style-type: none"> • is 	<p>Popup window of software policies</p>
<p>Installed Patches: Whether a patch is installed on the server.</p>	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	<p>User-entered text</p>

Table 17 Rules for Server Search and for Creating Dynamic Groups

Rule Name and Description	Operators	Value
Installed Software: The package reported installed on the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text <hr/> A package does not have to be installed by SA to be reported as installed on a server. <hr/>
OS Version: The OS version defined by OS definitions in the OS Provisioning feature.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of operating systems
Reported OS: For Windows —the version reported by the OS, for Unix — the version returned by the uname command.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Windows Service: The names of the Windows services that are reported to SA.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Network		
DNS Search Domains: The domains configured to be searched in the server’s network settings.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
DNS Servers: The IP addresses of the DNS servers configured in the server’s network settings.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Default Gateway: The IP address of the default router.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
IP Address: Any Internet Protocol address for the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text

Table 17 Rules for Server Search and for Creating Dynamic Groups

Rule Name and Description	Operators	Value
MAC Address: Any Media Access Control address, which is the network interface card's unique hardware number.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
WINS Servers: The Windows Internet Naming Servers configured in the server's network settings.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Hardware		
CPU Make and Model: The vendor name and CPU model for the server — such as GENUINEINTEL Intel(R) Pentium(R) 4 CPU 2.60GHz.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of CPU makes and models
CPU Speed: The Central Processing Unit speed in gigahertz [GHz].	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text <hr/> A 600 Mhz machine should be entered as 0.6. <hr/>
Make and Model: The vendor name and server model for the server — such as Compaq - DL360.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of server makes and models
Number of CPUs: The number of CPUs on the server.	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text
RAM: The amount of RAM on the server in megabytes [MB].	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text <hr/> To enter 1 Gigabyte, type 1024. <hr/>
Serial Number: The serial number of the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Storage Make and Model: The vendor name and storage model for the server — such as WDC - WD800BB-75DKA0.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of storage makes and models

Table 17 Rules for Server Search and for Creating Dynamic Groups

Rule Name and Description	Operators	Value
Custom Fields		
A Numeric field	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text
A String field	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
A URI field	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
A File field	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
A Date field	<ul style="list-style-type: none"> • Is after • Is before 	Drop-down lists with the day, month, and year
	<ul style="list-style-type: none"> • Is within the last 	User-entered text
	<ul style="list-style-type: none"> • Is today 	N/A

Line Break Workaround for Server Search

You cannot search in notes that contain line breaks. For example, you cannot search for text in a note when it is this type of text:

```
line1 <line break>
line2
```

For example, the following query does not return any results:

```
Any/all notes contain line1 <line break> line2
```


However, the following query does return all servers that have notes:

```
Any/all notes is not line1 <line break> line2
```

To work around this limitation, include an asterisk (*) where the line break occurs, as [Figure 67](#) shows. For example:

```
Any/all notes is line1*line2
```

Figure 67 Line Break Workaround in the Server Search Feature



The screenshot shows a web-based search interface. At the top, there is a 'Search' header with a help icon. Below it are two tabs: 'Servers' and 'Groups'. A 'Rules' section is expanded, showing a 'Match: if all rules are met' dropdown. Underneath, it says 'Search for servers whose:'. There is a dropdown menu set to 'Notes', followed by an 'Is' dropdown menu, and a text input field containing 'line1*line2'. To the right of the input field are three icons: a plus sign, a minus sign, and a plus sign. At the bottom right of the rule configuration area are three buttons: 'Search', 'Save...', and 'Reset'.

Conditions for Searching with Multiple Rules

When you perform a search with multiple rules, the following conditions apply to the way SA provides search results:

- When it evaluates rules, the Search feature considers each rule individually, finding servers (or operating systems, patches, and so forth) that match the individual rule, and then the results of each rule are combined.
- You must select at least one rule, and it must have a value. Default filter rules count as rules with a value.
- Empty rules are ignored in searches. Users do not have to manually remove them for the search to proceed.
- You cannot search for empty values. For example, you cannot search for all servers where the Notes field is empty.

At certain steps in the SA wizards, the Search feature provides default values based on previous selections in the wizard.



The wizards are flexible; for example, when you select multiple servers and applications, SA will install the correct applications on the servers, even if you selected different OS versions for the servers and applications in the respective steps. SA also matches the customer association for applications, operating systems, and templates with the customer association of servers.

If SA cannot find a match, an error message appears at the end of the wizard; therefore, use caution when modifying these default values.

Server Searching by IP Address

Users can search for servers by entering a specific IP address in the Search box in the top navigation or in the Search feature.

SA includes support for static Network Address Translation (NAT). This feature introduces the concept of a management IP, which might be different from any of the local IP addresses that the Server Agent reported for a server.

When searching for a server based on its IP address, the Search feature searches based on the server's primary IP address and based on the IP address for any interface that server has, including its management IP address. In the search results, an extra column is shown that lists all matching IP addresses for all interfaces. The management IP address is included if the server's networking is configured for static NAT.

See [Communication Between Managed Servers and SA](#) on page 206 for more information on how SA handles servers that are affected by static NAT.

Example: Server Search

Using the Search feature, a user creates a query with the following conditions:

- Installed Software contains qa
- Installed Software contains man
- If all rules are met is selected

The results of this search will be all servers that have at least one installed package with qa somewhere in its name and at least one installed package (not necessarily the same one) with man in its name.

The search results are not limited to packages that contain both qa and man in the package name.

Find all servers that have some version of Apache or some version of Java installed:

- Installed Package contains apache
- Installed Package contains java
- If any rules are met is selected

Searching for a Server Group

- 1 From the navigation panel, click Servers \dagger Search. The Search page appears. By default, the Servers tab is selected.

Select the Groups tab. The rules for server group search appear as [Figure 68](#) shows. By default, one search rule is added to the search.

Figure 68 Rules for Server Group Search

- 2 In the second list, specify how you want SA to search by selecting either “Contains” or “Is”. The operator selected defines how the search text is treated.
- 3 Enter the text that you want to search for in the text box. The search text that you enter can include an asterisk (*) wildcard character. (The search text is case sensitive. **Search** is not enabled until you enter text in the text box.)



When searching for a server group, you can only specify one rule for Group Name. The plus (+) button is disabled.

- 4 Click **Search**. The search results appear as [Figure 69](#) shows.

Figure 69 Server Group Search Results

Results									
Resource Edit Tasks Configuration Tracking									
	Name ^	Location	Members		Total Servers	Type	Model Attachments	Custom Attributes	Last Use
			Servers	Subgroups					
<input type="checkbox"/>	a test group	Public Groups	0	0	0	Dynamic	3	0	05-22-05 16:00:00

Server Identification

This section provides information on server identification within SA and contains the following topics:

- [Overview of Server Identification](#)
- [Ways that Servers are Identified by HP Server Automation](#)
- [Customer Accounts in SA](#)

Overview of Server Identification

SA uses the following IDs to track managed servers:

- **MID:** Machine ID. The unique identifier that SA uses to identify the server. The MID is usually equal to the server ID.

The MID is stored in a file on a server's disk so that the MID can persist and be read by the Server Agent.

The MID follows the hard disk, not the chassis, so system administrators can swap chassis for servers without affecting how SA tracks those servers.

See [Example: SA Swaps a Server's Hard Disk](#) on page 199 for more information about swapping hard disks.

- **Server ID:** The primary key in the Model Repository (database) that represents a given server. The Server ID is used internally in SA. Generally, users do not need this value for servers to manage them in SA.
- **MAC Address:** Media Access Control address, which is the network interface card's unique hardware number. The MAC is used as the server's physical address on the network.
- **Chassis ID:** A unique hardware-based identifier that the Server Agent discovers, typically derived from some property of the server's chassis. As a common source for this ID, SA uses an interface's MAC address or the host ID on Solaris servers, or the serial number for one of the interfaces.

Ways that Servers are Identified by HP Server Automation

Servers in the Manage Servers list are identified in the following ways when they register their hardware and software with SA:

- SA identifies each server by using the MID first.
- If the MID cannot be determined, the chassis ID is used to identify the server.
- If the server cannot be identified with the chassis ID, the MAC addresses are used to identify the server.

In the Server Pool, the MAC Address column displays values by which SA tracks the servers. The value used varies by platform:

- Intel x86 processor-based servers are identified by the MAC address of the server.
- Sun SPARC processor servers are identified by the host ID of the server.

The host ID for Sun SPARC processor servers appears in the MAC Address column in the Server Pool list.

To determine the value in the MAC Address column, SA uses the hardware address by which the server contacted the SA Build Manager (a component of the OS Provisioning feature).

Example: SA Swaps a Server's Hard Disk

The following steps show how SA handles swapping a hard disk for a server:

- 1 A system administrator swaps the hard disk of Server A (MID 1230001, chassis ID AB:08) with the hard disk of Server B (MID 98730001, chassis ID XY:96).
- 2 The Server Agent on Server A registers its hardware with SA. The MID for Server A equals 1230001 and the chassis ID equals XY:96.
- 3 SA locates Server A by using the MID.
- 4 SA updates the data it has for Server A. It sets the chassis ID equal to XY:96.
- 5 The Server Agent on Server B registers its hardware with SA. The MID for Server B equals 98730001 and the chassis ID equals AB:08.
- 6 SA locates Server B by using the MID.
- 7 SA updates the data it has for Server B. It sets the chassis ID equal to AB:08.

Customer Accounts in SA

Many enterprises have consolidated disparate IT operations into a single operation, yet they still need separate reporting, billing, and management for different business units, groups or customers. For example, one company may separate activities for their West Coast Office, East Coast Office, and London Office. A service provider company may organize their IT operations by their customers such as Customer A, Customer B, Customer C and so forth.

SA accommodates these requirements by letting you create separate **customers** and assign each managed server to a specific customer. For more information, see [Creating and Managing Customers](#) on page 143.

Server Histories and Reports

This section provides information on server histories and reporting with SA and contains the following topics:

- Overview of Server History
- Viewing Server History
- Time Stamp for Server Operations

Overview of Server History

By using the SA Web Client, you can view the history of changes made to a server. Each action performed on a managed server is logged in the history with the associated user who performed the action and the time of the action. You can view the history at any time, but you cannot change it. History is read-only.

Each History entry contains three pieces of information, as [Table 18](#) shows.

Table 18 Description of the Entries in the Server History Tab

History Entry	Description
Event Description	Description of the operation performed, for example: Run ISM Control: ad-hoc script (Job ID: 26190040) executed successfully.
Modified By	The name of the SA user who made the change.
Date Modified	The date and time the change was made, for example: Mon Aug 06 18:14:41 GMT+00:00 2001)

Time Stamps Used in History

Data is maintained for servers in SA for the following periods of time:

- The SA Web Client maintains the history of changes for the last three-month interval.
- Session logs are retained for 30 days, except for the last remediate session for a server, which is retained indefinitely.
- Server history is retained for 6 months.



If longer periods of time are required, HP recommends regular backups to enable offline storage of SA data.

SA deletes old data from the Model Repository, and does not copy the data before it removes it. However, you can retain information for longer periods of time, by using Oracle commands to manipulate the scheduled jobs. Contact your HP support representative for assistance in changing these retention periods.

Viewing Server History

Perform the following steps to view the server history:

- 1 From the navigation panel, click Servers † Manage Servers. The Manage Servers page appears. Browse the list to find the server whose history you want to view.

Or

Search for the server whose history you want to view.

See [Searching for Servers or Other Resources](#) on page 184 for more information. See [Server Searching by IP Address](#) on page 196 for more information.

- 2 Click the name of the server whose information you want to see. The Manage Servers: Properties page appears for that server.
- 3 Select the History tab.

By default, the view shows changes made within the past week.

Time Stamp for Server Operations

SA maintains a comprehensive audit trail of the software that the SA users install, configure, and remove from a server. By using the SA Web Client, you can view the history of the changes made to a server. Entries are generated when actions are performed for managed servers in the SA Web Client. The history is read-only. See [Server Histories and Reports](#) on page 200 for more information.

The time stamps for system events are determined based on the system clocks of the servers running the SA core components. To obtain accurate time stamps in server histories (displayed in the SA Web Client) and SA component logs, you must:

- Synchronize the system clocks on all servers running SA components so that all the servers are running with a common time.
- Set the time zone for all servers running SA components to Coordinated Universal Time (UTC).

See the *SA Simple/Advanced Installation Guide* for more information on facility time requirements.

Additionally, HP recommends that after installing an Server Agent on the server (so that it becomes managed by SA), you should synchronize the system clock on the server with the system clocks of the servers running the SA core components.

The time stamps appearing in the SA Web Client server History tab and the Server Agent logs are obtained from the SA core; however, you might need to review the server's logs (such as, stdout). Having a consistent time stamp in the server's logs and SA is essential for effective troubleshooting.

Hardware Information for Managed Servers

The Hardware link of the SA Web Client provides a read-only view of all servers in your managed environment categorized by hardware manufacturer and model. The Hardware link provides hardware related information for each server, such as:

- Manufacturer
- Model number
- MAC ID
- Serial number
- CPUs used on the server
- Memory
- Storage capacity

See [Server Information that the Agent Tracks](#) on page 130 for more information.


Viewing Managed Server Hardware Information

Viewing hardware information allows you to see all the servers in your managed environment by hardware vendor, and view such information as MAC ID, CPUs, memory, and so on.

To view hardware of managed servers:

- 1 From the navigation panel, click Environment † Hardware. You see the top level of the Hardware category in the managed environment, as shown in [Figure 70](#).

Figure 70 Top Level Hardware





Name	OS Version	Modified	Customer
SERVER	OS Independent	03-29-2005	Customer Independent

- 2 To view the servers in your managed environment, click the Servers link.
- 3 Drill down to the type of server you want to look at. For example, you might want to look at all Dell POWEREDGE 650s, as shown in [Figure 71](#).

Figure 71 Hardware Home Page for Dell POWEREDGE 650s

[Hardware](#) > [SERVER](#) > [DELL COMPUTER CORPORATION](#) > POWEREDGE 650

  **POWEREDGE 650**

No Sub-Nodes

Properties **Members 107**

Cannot edit or delete this Node. This Node is auto-generated. This Node is special and cannot be modified.

Name:	POWEREDGE 650
Customer:	Customer Independent
Operating System:	OS Independent
Locked:	No
Allow Servers:	Yes
ID:	1960003

- 4 Next, select the Members tab. You will see a list of all the Dell POWEREDGE 650s in your managed environment.
- 5 To view specific hardware information, from the **View** menu, choose **Hardware**. You now see more detailed information about all the Dell POWEREDGE 650s computers being managed by SA.

9 Server Management in the SA Web Client

This section does not document how to install operating systems, patches, or applications on servers. However, it does discuss how those tasks fit into the overall server life cycle, and it does provide cross-references to the appropriate topics in other sections.

Overview of Server Management

SA manages servers in an operational environment in the following ways:

- Provisioning servers with Microsoft Windows, Red Hat Linux, and Sun Solaris operating systems by using vendor-provided operating system bootstrapping technologies. Additionally, SA integrates with HP-UX Ignite installation technologies to provide a uniform method for OS provisioning across a heterogeneous environment.

See the *SA User Guide: OS Provisioning* for information about how SA provisions Microsoft Windows, Red Hat Linux, Sun Solaris, and VMware ESX operating systems on managed servers and how it integrates with HP-UX Ignite installation technologies.

- Automating the management and execution of server scripts.
See [Script Execution](#) on page 259 for more information.



To manage servers with SA, you do not need root access on Unix or administrator access on Windows. However, you will need permissions to use specific SA features, as well as permissions for customers and facilities associated with servers. To obtain these permissions, contact your SA administrator. For more information, see the Permissions Reference appendix in the *SA Administration Guide*.

Communication Between Managed Servers and SA

This section provides information about communication between managed servers and HP Server Automation and contains the following topics:

- [Network Address Translation \(NAT\) for Managed Servers](#)
- [Key Terms of SA Managed Server Communication](#)
- [Locating the Management IP Address of a Managed Server](#)
- [Setting the Primary IP Address of a Server](#)
- [NAT Table Mapping and Managed Servers](#)

Network Address Translation (NAT) for Managed Servers

To manage a server, SA requires that the server have a unique IP address that is routable from SA. However, in a large operational environment, all servers might not have unique IP addresses. In this case, SA supports static Network Address Translation (NAT) for managed servers.

Static NAT maps public IP addresses to hosts inside the internal network, which allows SA to manage all servers in the environment.

Unlike dynamic NAT, the mapping between SA and the servers under management is set ahead of time, not dynamically at runtime.

Key Terms of SA Managed Server Communication

To understand how SA communicates with managed servers, you must understand these three terms:

- **Management IP:** The IP address that SA uses to communicate with the Server Agent on the server.

During hardware registration for a server, the Server Agent opens a TCP/IP connection to SA. The connection contains the source IP (called peer IP) address of the server. By default, SA uses this peer IP address as the management IP for the server.

- **Management Interface:** When a server has more than one network interface, you can designate one of them as the management interface.
- **Primary IP:** The IP address of the management interface. When you change the management interface, the primary IP changes to the IP address of that interface. The primary IP address is a locally-configured IP address.

The Server Agents on servers communicate with each other by using the primary IP addresses, even though SA uses management IP addresses to communicate with the servers.



SA does not support managed servers that have IPv6 addresses.

When static NAT is being used, the management IP address for a server will *not* be the same as the primary IP address. When static NAT is being used, the management IP is the NAT-translated IP address for the server. When static NAT is *not* being used, the management IP address is always the same as the primary IP address.

Locating the Management IP Address of a Managed Server

In the SA Web Client, you can find the management IP address of a server and check whether it is using static NAT. You might need this information for troubleshooting any servers marked Not Reachable and to determine whether your NAT configuration is correct. The SA Web Client displays the management IP address of a managed server in the following two places:

- The Network tab of the Server Details page
- The Hardware view of the Manage Servers list

The Network tab shows (and allows the user to set) the management interface for the server by selecting it from a drop-down list, as [Figure 72](#) shows.

Figure 72 Management IP Address Information in the Network Tab

Properties	Network	Membership	Attached Nodes	Installed Packages	Custom Attributes	Config Tracking	History
NETWORK INFORMATION (as of Wed May 18 07:05:57 2005)							
Hostname:	core.tr3.opsware.com						
Management IP:	172.16.36.18						
Facility:	DATACENTER1						
Management Interface:	eth0						
Gateway:	172.16.36.17						
DNS Servers:	66.54.32.78 66.54.0.78						
Search Domains:	tr3.opsware.com opsware.com						
CONFIGURATION FOR: eth0							
Use DHCP Settings:	Static						
IP Address:	172.16.36.18						
MAC Address:	00:11:43:D7:2F:5F						
Interface Type:	ETHERNET						
Interface Speed:	(not set)						
Subnet Mask:	255.255.255.248						
CONFIGURATION FOR: eth1							
Use DHCP Settings:	Disabled						
IP Address:							
MAC Address:	00:11:43:D7:2F:60						
Interface Type:	ETHERNET						
Interface Speed:	(not set)						
Subnet Mask:							
<input type="button" value="Update"/> <input type="button" value="Revert"/>							

[Figure 73](#) shows the Hardware view in the Manage Servers list, which displays the management interface for the server in the Network Info column. (To access the Hardware view, choose **Hardware** from the **View** menu.)

Figure 73 Hardware Tab in the Manage Servers List

Resource	Name	Host Name / IP Address	Registration	Network Info	Hardware Info	Hardware Components
	Public Groups					
	core.tr3.opsware.com	core.tr3.opsware.com 172.16.36.18	OK	172.16.36.18 (eth0) N/A (eth1)	Man: DELL COMPUTER CORPORATION Mod: POWEREDGE 1850 Mac: 00:11:43:D7:2F:5F Ser: 2YLLP61	CPUs: Intel(R) Xeon(TM) CPU 2.80GHz, 2793 MHz, 1 MB Intel(R) Xeon(TM) CPU 2.80GHz, 2793 MHz, 1 MB Intel(R) Xeon(TM) CPU 2.80GHz, 2793 MHz, 1 MB Intel(R) Xeon(TM) CPU 2.80GHz, 2793 MHz, 1 MB Memory: 3.9 GB RAM 1.95 GB SWAP Stor: hda (CDROM) sda (SCSI DISK:68.24 GB)

The Network Info column shows the IP addresses and interfaces configured for each server in the list. If a server is using static NAT, the management IP is the first entry in this list and (NAT) appears after the IP address. If it is not using static NAT, the management IP is the same as the management interface, so it is already shown.

Setting the Primary IP Address of a Server

When a server has more than one network interface, users can specify one of them as the management interface and the IP address for this interface is designated the primary IP address. The primary IP address is used for Server Agent-to-Server Agent communication.

If static NAT is *not* being used, the management and primary IP addresses are the same. If static NAT is being used, the management IP is unaffected when a user changes the management interface.

Perform the following steps to set the primary IP address of a server:

- 1 From the navigation panel, click **Servers** † **Manage Servers**. The Manage Servers page appears. Browse the list to find the server whose management IP address you want to view.

Or

Search for the server whose management IP address you want to view.

- 2 Click the server name. The Manage Servers: Properties page appears.
- 3 Select the Network tab. The network information for the server appears.
The Network tab shows (and allows you to set) the server's management interface.
- 4 Set the management interface by selecting it from the Management Interface field. The IP address for this interface is designated the primary IP address.
- 5 Click **Update**.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

NAT Table Mapping and Managed Servers

Static, one-to-one NAT tables map routable IP addresses between SA and managed servers. Network administrators configure and maintain these NAT tables. After the static NAT tables are configured, you do not have to perform any additional setup for SA.

SA does not control these NAT tables and errors can occur if they are modified after SA-managed servers register their hardware information. The following errors can occur if the IP address mapping of a server changes:

- If the IP address on the SA side of the NAT mapping is modified, the server becomes unmanageable and might be marked Not Reachable on the Manage Servers: Status page. It stays in this state until the Server Agent requests another hardware registration and the server's management IP is updated.
- If an IP address mapped to a particular server is mapped to a different server, both servers become unmanageable and might be marked Not Reachable on the Manage Servers: Status page. This problem is resolved when one of the two servers reports its IP address during hardware registration. The other server remains unmanageable until the server registers with the Server Agent. Both servers eventually become manageable.

Server Groups

This section provides information on server groups within SA and discusses the following topics:

- [Overview of Server Groups](#)
- [Types of Server Groups](#)
- [Public Group Modeling](#)
- [Ways to Create Server Groups](#)
- [Adding a Server to Static Groups, Both Public and Private](#)
- [Removing Servers from Static Groups, Both Public and Private](#)
- [Duplicating Server Groups](#)
- [Rules for Deleting Server Groups](#)

Overview of Server Groups

The Server Groups feature is useful for gathering servers into collections. These groups can be used as a shortcut for performing the same action on all of the servers simultaneously, instead of performing the action on each individual server, one at a time. Server groups can also be used to simply organize groups of servers.

Server groups can be comprised of individual servers as well as other server groups.



The My Servers feature can also be used to gather servers and server groups, but it has different functionality than the Server Groups feature. You can add individual servers, server groups, and nested groups that you access frequently to My Servers. See [My Servers](#) on page 182 for more information.

Uses for Server Groups

Some recommended uses for server groups include:

- Grouping servers by OS version
- Grouping servers by customer
- Grouping servers by facility
- Grouping servers by deployment stage

- Grouping servers by use (Server Use in the Server Properties page)
- Grouping servers by operational boundaries, for example, grouping together all servers that require identical application configuration
- Grouping servers by access control boundaries, for example, creating server groups that are associated with a specific User Group

Permissions Required for Working with Server Groups

Users must have the permissions shown in [Table 19](#) in order to perform specific tasks related to server groups. Only administrators can set permissions.

Table 19 Permissions Required for Working with Server Groups

Name Of Permission	Where Selected	Enables You To:
Manage Servers		Create, edit, and delete private server groups, both static and dynamic.
Manage Public Server Groups	The Manage Servers Permissions section on the Other tab in Users and Groups	Create, edit, and delete public server groups, both static and dynamic.
Model Public Server Groups	The Manage Servers Permissions section on the Other tab in Users and Groups	Model public server groups. See Public Group Modeling on page 212 for more information.
Allow Run Refresh Jobs	The Manage Servers Permissions section on the Other tab in Users and Groups	Add or remove servers from groups before a scheduled job is run. This permission gives you the option to refresh group membership before a job is run so that it is only run on the servers that belong to the group when the job is actually run.

Characteristics of Server Groups

When using server groups, groups have the following characteristics:

- Individual servers can be included in as many groups as you want, or not included in any groups.
- Adding servers to a group does not remove those servers from the list of all servers that appears when you click **Servers** † **Manage Servers** in the navigation panel.
- Groups can contain servers and subgroups.
- Server groups are hierarchical (they can be nested) with these caveats:
 - Private and public groups cannot be mixed in a hierarchy, but static and dynamic groups can.
See [Types of Server Groups](#) on page 211 for more information about private and public groups.
 - The rules for a dynamic group are not inherited from a parent dynamic group to a dynamic subgroup.

See [Dynamic Groups](#) on page 212 for more information about the characteristics of dynamic groups.

- Groups do not inherit modeling data from their parents, including custom attributes.
- When you run an operation on a group that contains nested groups, the operation also applies to all the servers in the nested groups below the current group.
- When an Application Configuration operation within the SA Client is applied to groups, and those groups contain subgroups, the operation does not apply to all the servers in the subgroups. It only applies to the group upon which the operation was directly applied.

Types of Server Groups

There are private groups and public groups, and each can be either static or dynamic.

Private Groups

If you belong to a user group that has access to the Manage Servers list, you can create groups that you alone can see and work with. Only you see your private groups. Other SA users cannot see them. Private groups behave the same way as public groups, with the exception that modeling is not available for private groups. See [Public Group Modeling](#) on page 212 for information how the SA model affects groups.

When you create your first group, the default type will be Private Static, which can be changed to Private Dynamic, Public Static, or Public Dynamic. When you create a subgroup, the type of group is private if you are in a private group when you create the new group, and the type is public if you are in a public group when you create the new group. Public and private groups cannot be mixed in a hierarchy. In other words, if the parent group is public, the subgroups must be public, and if the parent group is private, the subgroups are also private.

Public Groups

Public groups can be created, edited, or deleted by anybody who has Manage Public Server Groups permissions. Public groups are visible to all users, and can be used by anybody, regardless of who created them, but only users with the Manage Public Server Groups permissions can change the rules that govern dynamic groups.

A link called Public Groups appears at the top of server lists. Clicking that link displays a list of available public groups.

Only public groups can be used for modeling.

Static Groups

Static groups can be either public or private, and no specific permissions are required for static groups. A static group has servers that are added to and removed from the group manually. When using static groups, you first create the group, and then select the servers to populate it.

Dynamic Groups

Dynamic groups contain servers that are added to or removed from the group based on a set of user-defined rules. If the rules are changed or the servers in the environment change, servers will be added to or removed from the group automatically. Rules apply only to the group being created or modified, not to any subgroups.

Once the rules have been created, SA will search for servers that match the criteria of that specific group, and add them to the group. When the rules are changed, SA will search again, and the resulting group members reflect the changed criteria. Consequently, as servers are added to or removed from management using SA, the members of the group will change automatically.

SA calculates server group membership each time any of the following actions occur:

- After users add, delete, or change the rules for dynamic server groups.
- When attributes of servers change such that dynamic group membership could change.

Additionally, SA automatically recalculates dynamic group membership every hour.

When a user schedules a job to run, dynamic group membership can be determined in either of the following ways:

- Based on the servers in the dynamic group when the job was scheduled.
- Based on the set of servers in the dynamic group when the job actually runs. The membership is recalculated at that time.

Public Group Modeling


With SA modeling, the desired state of a server is defined and then applied to servers. In the case of public server groups — static and dynamic — you can define a model consisting of applications, patches, service levels, and custom attributes, which will be applied to all servers in the group. The modeling information is attached to the group, but not to any subgroups.

If the modeling information changes, the servers in the group are not affected until the remediate operation runs on those servers. If the model has already been remediated on that server when it is removed from the group, the installed material will be removed at the next remediate process.

Manage Servers Display for Public and Private Groups

As [Figure 74](#) shows, server groups appear at the top of the Manage Server list. Public Groups appear as a link at the top of the list. Private groups, if any have been created, appear next, followed by the list of individual servers.

Figure 74 Manage Servers Displaying Public and Private Groups — Servers and Group View



The screenshot shows a web-based interface for managing servers. At the top, there are tabs for 'Resource', 'Edit', 'View', 'Tasks', and 'Configuration Tracking'. Below the tabs is a table with columns: 'Name', 'Host Name / IP Address', 'OS Version', 'Stage', 'Use', 'Facility', and 'Customer'. The table content is as follows:

<input type="checkbox"/>	Name	Host Name / IP Address	OS Version	Stage	Use	Facility	Customer
Public Groups							
<input type="checkbox"/>	barbar, 0 Servers (Static)						
<input type="checkbox"/>	barfoo, 0 Servers (Dynamic)						
<input type="checkbox"/>	dhcp-8-071.corp.opsware.com faisa1's desktop do not touch	dhcp-8-071.corp.opsware.com 192.168.8.71	Red Hat Enterprise Linux AS 3	Not Specified	Not Specified	C29	Opsware

Manage Servers List - Groups Only

When you select **View † Groups Only** from the menu, information about the number of servers in a group, the number of groups in a group, and whether the group is static or dynamic appears in the list of groups, as [Figure 75](#) shows.

Figure 75 Manage Servers List — Group Only View

Manage Servers (Summary View - Groups Only)								
OK [v] All Operating Systems [v] Update [E]								
Resource Edit View Tasks Configuration Tracking								
[]	Name ^	Members		Total Servers	Type	Model Attachments	Custom Attributes	Last Use
		Servers	Subgroups					
[]	Public Groups	0	113	222		0	0	
[]	A Group	0	1	0	Static	0	0	

You can modify your views of servers and server groups by selecting Summary, Hardware, Software, and Communications from the **View** menu. You can also elect to further modify your view by selecting Servers and Groups, Servers Only, or Groups Only.

Operations on Server Groups

Any operation that can be done to a server can be done to a server group, because the group acts as a container for a collection of servers, and so provides a shortcut to avoid having to repeat the same operation on each individual server.

When any of the following operations are performed on a group, they are actually performed on the servers within the group, not on the group itself.

- Run
 - Script
 - Custom Extension
 - Communication Test
- Customer
- Usage
- SA Client operations
 - Configure Application
 - Audit Application Configurations
 - Perform Server Audit
 - Create Server Snapshot
 - Install Patch
 - Install software

Also, some operations allow users to refresh the list of servers in the group (if the user has the Allow Run Refresh Jobs permissions). Users with the correct permissions schedule a job, and before the job is run, SA will update the members of the server groups upon which the operation is performed. The following actions allow refresh when scheduling a job:

- Run Script
- Run Custom Extension

Server Groups Tabs

When you view group properties, the information for the group appears in the page, as [Figure 76](#) shows.

You can view group properties in either of the following ways:

- By clicking the This Group link at the top of each server group list.
- By selecting a group in the list and choosing **Resource † Properties** from the menu.

Figure 76 Tabs Available for Server Groups

[Manage Servers](#) / [Public](#) / [All Windows Servers](#) / **Properties** ?

Properties

Rules

Custom Attributes 0

Service Levels 0

History

The following properties describe or restrict use of the current group. Edit

Name:	All Windows Servers
Description:	
Type:	Dynamic
Status:	Active
Accessibility:	Public
Servers (at this level):	7
Groups (at this level):	0
Unique servers for all levels:	7
Date last used (by a job):	
Device Group ID:	2530039

You can use these tabs to perform the following actions for a server group.

To perform any of these actions, you must have the correct SA permissions. See [Permissions Required for Working with Server Groups](#) on page 210 for more information.

- **Properties:** This displays information about the group, such as the type of group, the number of servers in the group, and the status of the group. Clicking **Edit** allows you to change the group name and description, and to convert a dynamic group to a static group.



A created static group without servers added yet — an empty static group — can be converted to a dynamic group. Conversely, a static group that has servers cannot be converted to a dynamic group.

- **Rules:** This appears when you are viewing a dynamic group. The rules tab displays the rules used by the dynamic group to determine group membership. The rules apply to the current group only and do not apply to subgroups. Click **Edit** to change the rules for the group.

See [Creating Groups by Using Search](#) on page 218 for more information about specifying rules for a dynamic group.

- **Custom Attributes:** This allows you to set custom attributes for a server group. Click **New** to add an attribute and then click **Edit** to change existing attributes. Custom attributes are not inherited by subgroups within a group hierarchy.
See [Custom Fields for Servers](#) on page 246 for more information about how custom attributes affect SA-managed servers.
- **Service Levels:** This allows you to attach service levels to a group.
See [Service Levels](#) on page 251 for more information.
- **History:** This allows you to view the changes to groups. For each action on the group (but not group members), the history displays a description, the date the action occurred, and the user who performed the action (if the group is public).

Ways to Create Server Groups

Server Groups can be created by:

- Using the New Group option from the Resource pull down menu on the Manage Servers page
- Clicking the Create Server Groups icon in the upper right corner of the Copy to Group dialog
- Performing a server search, and saving the resulting list of servers or the rules as a group

Creating Static Groups by Using the New Group Option

Static server groups require servers to be added to them manually. The servers in a static group also must be removed manually.



A created static group without servers added yet — an empty static group — can be converted to a dynamic group. Conversely, a static group that has servers cannot be converted to a dynamic group.

To create static server groups, perform the following steps:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
- 2 From the **Resource** menu, choose **New Group**. The New Private Static Group dialog appears, as shown in Figure 77.

Figure 77 Default New Private Static Group Dialog

Name	Type
Public Groups	Dynamic
Content Groups, Dynamic	Dynamic
Content Management Servers	Dynamic
Dynamic Content Servers	Dynamic

- 3 To create a Private Static group in the top level of Manage Servers, perform the following steps:
 - a Enter the name of the group in the Save As text box.
 - b Click **Save**.
- 4 To create a Private Static group below another group, perform the following steps:
 - a Navigate to the group below which you want to create a new group.
 - b Enter the name of the group in the Save As text box.
 - c Click **Save**.
- 5 To create a Public Static Group, perform the following steps:
 - a Click the Public Groups link in the Name and Type window, and navigate to the location in the group hierarchy where you want to create the group.
 - b Enter the name of the group in the Save As text box.
 - c Click **Save**.



The Save In drop down list is populated according to the location you drill down to in order to create your group. You can use the Save In drop down list to verify that you are in the correct location in the group hierarchy, and you can move to a different location in the hierarchy by selecting it from the Save In list.

Creating Static Groups by Using the Copy to Group Dialog

To create new server groups by copying existing server groups, perform the following actions:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
- 2 Navigate to the servers and groups that you want to copy and click the check boxes next to the servers and groups you want to copy.
- 3 From the **Edit** menu, choose **Copy to Group**. The Copy to Group dialog box appears.
- 4 Navigate to the place in the group hierarchy where you want to copy the servers and group then by clicking the group links displayed in the Name and Type field.
- 5 In the Options field, select either of the following options:
 - **Maintain Hierarchy**: Select this option to copy any server groups exactly as they are.
 - **Expand to a Flat List**: Select this option to copy only the servers within the group to the new group.

Each of those options displays the result of choosing that option by showing the numbers of servers and groups in the new group's hierarchy, or the number of unique servers in the flat list.



If you select the Expand to a Flat List option, and a server is a member of more than one group, that server will only appear in the list once.

- 6 (Optional) You can also create an entirely new group for the copied servers and groups by clicking the Create New Group icon in the upper right corner of the dialog.
A new dialog appears, prompting you to name your new group.
- 7 Enter the name of your newly-created group.
- 8 Click **OK**. The name dialog closes, and the Copy to Group dialog reappears.
- 9 Click **OK** on the Copy to Group dialog.

Creating Dynamic Groups by Using the New Group Option

Dynamic Server Groups are rule-based, and the servers in dynamic groups will be added or removed automatically based on the rules that you define.

The method for creating dynamic server groups is the same as for creating static server groups. The difference is that when dynamic is selected, you are presented with a page that allows you to define the rules for the group.



Dynamic groups can be converted to static groups, and all servers remain in the group, but all rules will be lost when they are converted.

To create dynamic groups using the New Groups Option, perform the following steps:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
- 2 From the **Resource** menu, choose **New Group**. The New Private Static Group dialog appears.

- 3 To create a private dynamic group, navigate to the place in the group hierarchy where you want to create the group by clicking the group links displayed in the Name and Type field.

Or


To create a public dynamic group, click the Public Groups link in the Name and Type field, and navigate to the location in the group hierarchy where you want to create the group.



The Save In drop down list is populated according to the location you drill down to in order to create your group. You can use the Save In drop-down list to verify that you are in the correct location in the group hierarchy, and you can move to a different location in the hierarchy by selecting it from the Save In list.

- 4 Enter the name of the group in the Save As text box.
- 5 In the Options field, select Dynamic.
- 6 Click **Create Rules**. The Manage Servers Properties page appears, with the Rules tab selected, as [Figure 78](#) shows.

Figure 78 Manage Servers Properties Page with Rules Tab Selected



- 7 Select the criteria that apply to the servers you would like the group to include.



Create as many lines of criteria as required to adequately describe your server group rules by clicking the plus button to add a new line. Conversely, to remove lines of criteria, click the minus button next to the line you want to remove.

- 8 From the Match drop down list select either “If all rules are met” or “If any rules are met.”
- 9 (Optional) Click **Search** to apply the rules to a server search to validate the results.
- 10 Click **Save** to save the rules that apply to your group.

Creating Groups by Using Search

To create groups by using search, perform the following steps:

- 1 From the navigation panel, click **Servers** † **Search**. The Search Rules page appears with the Servers tab displayed.

To search for servers, use this tab. To search for groups, select the Groups tab.

- 2 Use the criteria to create the rules used for a server search and to identify servers for dynamic groups. The options in the user interface for specifying dynamic group rules and for using Search are the same. See [Criteria for Search and Dynamic Group Rules](#) on page 219 for more information.



Create as many lines of criteria as required to adequately describe your server search or your server group rules by clicking the plus button to add a new line. Conversely, to remove lines of criteria, click minus button next to the line you want to remove.

- 3 If you are defining dynamic server group rules, click **Save** to save your rules. You can also click **Search** to use your rules to perform a server search.

Or

If you are doing a server search, click **Search** to perform the server search, or click **Save** to save the search as the rules for a dynamic group.

The New Dynamic Group dialog appears.

Criteria for Search and Dynamic Group Rules

The following table describes the rules that you can use to search for servers or to create dynamic server groups.

Note that anywhere you can enter text, you can enter a wildcard (*) character to broaden your results.

Table 20 Rules for Server Search and for Creating Dynamic Groups

Rule Name and Description	Operators	Value
Properties		
Agent Discovery Date: The date that the Server Agent was installed.	<ul style="list-style-type: none"> Is after Is before 	Drop-down lists with the day, month, and year
	<ul style="list-style-type: none"> Is within the last 	User-entered text
	<ul style="list-style-type: none"> Is today 	N/A
Agent Reporting: Whether the Server Agent is reporting to SA.	<ul style="list-style-type: none"> Is Is not 	<ul style="list-style-type: none"> Has not reported OK Registration in progress Reporting error
Agent Status: Whether the Server Agent is reachable by SA.	<ul style="list-style-type: none"> Is Is not 	<ul style="list-style-type: none"> Not reachable OK
Agent Version: The version of the Server Agent — such as 14.2.3b.	<ul style="list-style-type: none"> Contains Does not contain Is Is not 	User-entered text

Table 20 Rules for Server Search and for Creating Dynamic Groups (cont'd)

Rule Name and Description	Operators	Value
Custom Attribute (any): The name of a custom attribute that is associated with the server through attachment or inheritance.	<ul style="list-style-type: none"> • Contains • Is 	User-entered text
Custom Attribute (local): The name of a custom attribute that is locally attached to the server,	<ul style="list-style-type: none"> • Contains • Is 	User-entered text
Customer: The customer or account that the server is associated with.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of customers
Deployment Stage: The stage the server performs within a lifecycle environment.	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • In Deployment • Live • Not Specified • Offline <hr/> <p>The values that appear in this list are customizable; in addition to the values above, values specific to your environment might appear.</p> <hr/>
Facility: The collection of servers managed by an SA installation.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of facilities <hr/> When SA is running multimaster mode, the list can contain many facilities. <hr/>
Group Membership: Whether the server belongs to a group.	<ul style="list-style-type: none"> • Is 	Popup window of groups
Host name: The host name of the server — such as m004.company.com.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Name (any): This enables searching for any name or IP address associated with a server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text

Table 20 Rules for Server Search and for Creating Dynamic Groups (cont'd)

Rule Name and Description	Operators	Value
Notes: The contents of the Notes field from the Properties tab for a server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Display Name: The user-configurable name for the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text <hr/> By default, SA uses the configured host name of the server until a user edits it. <hr/>
Server Use: How the server is being used — such as Development, Staging, Production.	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • Development • Not Specified • Production • Staging <hr/> You can customize values that appear in this list. In addition to the values above, values specific to your environment might appear. <hr/>
Service Level: The user-defined category that can be used as an organizational tool.	<ul style="list-style-type: none"> • Is • Is attached here or below 	Popup window of service levels <hr/> Servers can be associated with multiple service levels. <hr/>
PROPERTIES		
Application Configuration: Whether the server uses the Application Configuration feature.	<ul style="list-style-type: none"> • Is not used • Is used 	N/A
Configuration Tracking: Whether the Configuration Tracking feature is monitoring or backing up specific files or configurations on a server.	<ul style="list-style-type: none"> • Is off • Is on 	N/A

Table 20 Rules for Server Search and for Creating Dynamic Groups (cont'd)

Rule Name and Description	Operators	Value
Lifecycle: The server states that are part of bringing a server into SA.	<ul style="list-style-type: none"> • Is • Is not 	<ul style="list-style-type: none"> • Available • Build Failed • Deactivated • Installing OS • Managed
Server ID: The internal ID SA uses to identify the server.	<ul style="list-style-type: none"> • Is • Is not 	User-entered text <hr/> In most cases, the Server ID is the same as the MID. <hr/>
SOFTWARE		
Attached Software: The software that is assigned or modeled through the SA remediate operation — the installation process.	<ul style="list-style-type: none"> • Is • Is attached here or below 	Popup window of software
Attached Software Policies: The software policies that is assigned or modeled through the SA installation process.	<ul style="list-style-type: none"> • is 	Popup window of software policies
Installed Patches: Whether a patch is installed on the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Installed Software: The package reported installed on the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text <hr/> A package does not have to be installed by SA to be reported as installed on a server. <hr/>
OS Version: The OS version defined by OS definitions in the OS Provisioning feature.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of operating systems
Reported OS: For Windows —the version reported by the OS, for Unix — the version returned by the uname command.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text

Table 20 Rules for Server Search and for Creating Dynamic Groups (cont'd)

Rule Name and Description	Operators	Value
Windows Service: The names of the Windows services that are reported to SA.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
NETWORK		
DNS Search Domains: The domains configured to be searched in the server's network settings.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
DNS Servers: The IP addresses of the DNS servers configured in the server's network settings.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Default Gateway: The IP address of the default router.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
IP Address: Any Internet Protocol address for the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
MAC Address: Any Media Access Control address, which is the network interface card's unique hardware number.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
WINS Servers: The Windows Internet Naming Servers configured in the server's network settings.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
HARDWARE		

Table 20 Rules for Server Search and for Creating Dynamic Groups (cont'd)

Rule Name and Description	Operators	Value
CPU Make and Model: The vendor name and CPU model for the server — such as GENUINEINTEL Intel(R) Pentium(R) 4 CPU 2.60GHz.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of CPU makes and models
CPU Speed: The Central Processing Unit speed in gigahertz [GHz].	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text <hr/> A 600 Mhz machine should be entered as 0.6. <hr/>
Make and Model: The vendor name and server model for the server — such as Compaq - DL360.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of server makes and models
Number of CPUs: The number of CPUs on the server.	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text
RAM: The amount of RAM on the server in megabytes [MB].	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text <hr/> To enter 1 Gigabyte, type 1024. <hr/>
Serial Number: The serial number of the server.	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
Storage Make and Model: The vendor name and storage model for the server — such as WDC - WD800BB-75DKA0.	<ul style="list-style-type: none"> • Is • Is not 	Popup window of storage makes and models
CUSTOM FIELDS		
A Numeric field	<ul style="list-style-type: none"> • Does not equal • Equals • Is greater than • Is less than 	User-entered text

Table 20 Rules for Server Search and for Creating Dynamic Groups (cont'd)

Rule Name and Description	Operators	Value
A String field	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
A URI field	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
A File field	<ul style="list-style-type: none"> • Contains • Does not contain • Is • Is not 	User-entered text
A Date field	<ul style="list-style-type: none"> • Is after • Is before 	Drop-down lists with the day, month, and year
	<ul style="list-style-type: none"> • Is within the last 	User-entered text
	<ul style="list-style-type: none"> • Is today 	N/A

Adding a Server to Static Groups, Both Public and Private

To add a server or a server group to a static group, perform the following steps:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
- 2 Navigate to the static group that you want to add servers and server groups to.
- 3 Click the check box next to the group and select **Edit † Add Servers**. The Select Servers and Groups to Add to [group name] window opens. The window is populated with the same servers and groups visible on the Manage Servers page. You can use the Status, OS, and Customer filters to change the servers and groups that appear on the list.



When you select **Edit † Add Servers** and then select a group, the servers in the group are added. The group itself is not added. If you want to add a group to a group, select **Edit † Copy to Group** from the menu.

- 4 Click the check box next to the servers and groups you want to add, and click **Add** at the bottom of the window.

Adding a Server to Dynamic Groups, Both Public and Private

Servers are added to dynamic server groups automatically, based on the rules created for the group. To change the membership of a dynamic group, add, delete, or update the dynamic group rules.

To update the rules for a dynamic group, perform the following steps:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
- 2 Navigate to the Properties page of the dynamic group that you want to update rules for; navigate by clicking the group links in Manage Server list.
- 3 Select the Rules tab.
- 4 Click **Edit**.
- 5 To add criteria to the existing rules, click the plus (+) button next to existing criteria. The fields for the criteria appear. Enter the values for the rule.
- 6 To delete criteria, click the minus (-) button next to the criteria you want to delete from the rules. The criteria are removed from the page.
- 7 Click **Save**.

Groups can be added manually to a dynamic group, in either of the following two ways:

- 1 Click the check box next to the name of the server group to which you want to add a server group, and select **Edit † Copy to Group**. Then follow the steps for creating a new group, either static or dynamic. See [Ways to Create Server Groups](#) on page 215 for more information.

Or

Navigate to the server group that you want to add a server group to.

- 2 Click the check box next to “This Group” and select **Resource † New Group**. Then follow the steps for creating a new group, either static or dynamic. See [Ways to Create Server Groups](#) on page 215 for more information.

Removing Servers from Static Groups, Both Public and Private

To remove a server from a static server group, perform the following steps:



A server does not need to be deactivated to be removed from a group. You can remove a server from a Static group at any time. The Membership tab for a server displays all the server groups of which the server is a member.

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
 - 2 Navigate to the static server group that you want to remove servers from until you reach the level where the servers in question are located.
-



Servers can belong to more than one group, so if you want to remove a server from each group it belongs to, you must locate and remove each instance of the server from all groups.

- 3 Click the check box next to the servers you want to remove and select **Edit † Remove from Group**.

As soon as you select that menu option, the server is removed and the screen refreshes to display the current members of the group.

Removing Servers from Dynamic Groups, Both Public and Private

Servers are removed from dynamic server groups automatically, based on the rules created for the group. To remove servers, you can create or update rules. To add rules to an existing server group, perform the following steps:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
- 2 Navigate to the Properties page of the dynamic group that you want to add rules to, by drilling down into the group and clicking the “This Group” link.
- 3 Select the Rules tab.
- 4 Click **Edit**.
- 5 Add one or more lines of criteria to the existing rules by following the procedure described in the “Creating Dynamic Server Groups by Using the New Group Option” topic, [step 3](#) on page 219.

Moving Servers from One Static Group to Another

The process of moving servers from one group to another is similar to copying servers from one group to another with the exception that with a move, the servers do not remain in the original group.



The **Edit † Move** menu option is disabled when you select servers in a dynamic group. To move servers in a dynamic group, choose the **Edit † Copy to Group** menu command. This menu command is also disabled for public groups when you do not have permission to manage public groups.

To move servers from one group to another, perform the following steps:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears.
- 2 Navigate to the group containing the servers you want to move and select those servers.
- 3 From the **Edit** menu, choose **Move**. The Move [group name] Group dialog box appears.
- 4 Navigate to the place in the group hierarchy where you want to create the group by clicking the group links displayed in the Name and Type field.
- 5 Click **Move**.

Duplicating Server Groups

Duplicating a group is similar to copying a group. To duplicate an existing group, perform the following steps:

- 1 Navigate to the group that you want to duplicate.


- 2 Click the check box next to the group name.



You can only select one group at a time to duplicate.

- 3 From the **Edit** menu, choose **Duplicate Group**. The Duplicate [group name] Group dialog appears as shown in Figure 79.

Figure 79 Duplicate Group Dialog Box



- 4 Select the location for the newly-duplicated group using the Duplicate In drop down list.



The Duplicate In drop down list's default location is the location of the group you select to duplicate. Navigate through the hierarchy of groups to find the location where you want the newly-duplicated group to reside.

- 5 Enter the name of the new group.
- 6 The values on the Options field will vary depending on whether the group duplicated is static or dynamic.
- 7 If the group is static, select one of the following options:
 - **Maintain Static group and <number> subgroups:** Selecting this option copies the group and its hierarchy as is.
 - **Convert group and <number> subgroups to a static flat list:** Selecting this option copies the group and flattens the hierarchy.
- 8 If the group is dynamic, select one of the following options:

- **Maintain rules & group hierarchy:** Selecting this option copies the group and leaves it as a dynamic group, it also copies any subgroups.
 - **Convert to static group, maintain hierarchy:** Selecting this option copies the group, but turns it into a static group with the current servers defined by the rules and also copies any subgroups.
 - **Convert group and <number> subgroups to a static flat list:** Selecting this option copies the group, and turns it into a static group and flattens any hierarchy.
- 9 Click **Duplicate**. The newly-duplicated group appears in the selected destination.

Rules for Deleting Server Groups

It's important to note the distinction between removing servers from a group, deleting a server, and deleting a group.

Removing servers from a group only removes the server from the selected static group, but the server itself remains in the global list of servers and is still managed by SA.

Deleting a server can only be performed on a server whose status is deactivated. Selecting the Delete Server option completely removes the server from within SA, although its history remains.

Deleting a server group removes the group, but the servers in the group still remain in the list of servers and in any other groups for which they are members.

A group cannot be deleted when any of the following conditions apply:

- Software is attached to the group or a subgroup of the group.
- Access control boundaries are attached to the groups or a subgroup of the group.
- Servers and groups are selected together for deletion.

Deleting a Server Group

To delete a server group, perform the following steps:

- 1 Click the check box next to the server group you want to delete.
- 2 From the **Edit** menu, choose **Delete Group**. A confirmation message appears, detailing the number of servers and server groups in the server group that you want to delete.
- 3 Click **OK** to complete the deletion of the server group.

The screen refreshes, showing the list of servers and groups without the deleted server group.

Server Life Cycle

This section provides information on the server life cycle within SA and contains the following topics:

- [OS Provisioning and the Server Life Cycle](#)
- [Server Properties](#)
- [Server Management Tasks Related to the Server Life Cycle](#)

- Changing the Server Use and Deployment Stage Values for Servers
- Editing the Properties of a Server
- Tasks Associated with Deactivating a Server
- Deactivating a Server
- Deleting a Server from SA
- Server Management Jobs

OS Provisioning and the Server Life Cycle

SA is designed to enable multiple teams to work together to provision servers. The OS Provisioning feature allows IT teams to separate the tasks of readying servers for provisioning (such as mounting servers in racks and connecting them to a network) from provisioning the servers with operating systems and applications.

For example, someone mounts a new server in a rack and connects it to the SA build network. Next, they boot the server for the first time by using an SA Boot Floppy or CD or by using the network.

At a later time, a different system administrator can select the available server from the Server Pool list and provision it with an OS. In the available state, servers do not have the target OS installed and might not have access to disk resources.

During OS Provisioning, servers progress through the SA life cycle state changes:

Unprovisioned (No OS Build Agent) † Available † Installing OS † Managed

Table 21 describes the SA server life cycle values.

Table 21 SA Life Cycle Values for Servers

Life Cycle Value	Description
Server Pool Values	
Planned	<p>Indicates that a device record has been created for the server, but an SA build agent has not yet been installed. Servers in this stage cannot be provisioned until an OS build agent is installed.</p> <p>For more information on this unprovisioned lifecycle value, see your SA Administrator.</p>
Available	<p>Indicates a server on which the OS Build Agent was installed and is running, but the target OS has not been installed on the server.</p> <p>The OS Build Agent is a small agent that can run in the memory of the bare-metal server.</p> <p>See the <i>SA User Guide: OS Provisioning</i> for more information about Operating System Provisioning.</p>
Installing OS	<p>Indicates that a user is installing the target operating system on the server.</p> <p>The server stays in the Server Pool list until the installation process finishes successfully. Then the server moves to the Manage Servers list.</p> <p>See the <i>SA User Guide: OS Provisioning</i> for more information about installing operating systems.</p>
Build Failed	<p>Indicates a server on which the OS Build Agent was installed and is running, but the installation of the target OS failed.</p> <p>The server remains in the Server Pool list with this status for 7 days before SA deletes the entry.</p> <p>See the <i>SA User Guide: OS Provisioning</i> for more information about Operating System Provisioning.</p>
Managed Server Values	
Managed	<p>Indicates a server that SA is managing. SA performs periodic reachability checks on managed servers.</p> <p>After a server reaches this life cycle state, the entry for the server moves from the Server Pool list to the Manage Servers list. On managed servers, you can use SA to install applications and patches.</p>
Deactivated	<p>Indicates an SA-managed server that was removed from service. However, the server's history still exists in SA. Deactivated servers are not reachable.</p>

Server Properties

Table 22 shows the server status icons and explains their meanings. It also describes server status in regard to server life cycles.

Table 22 Server Status Icons in SA






Server Icon	Description
	<p>Planned</p> <p>Indicates that a device record has been created for the server, but an SA OS Build Agent has not yet been installed on it. Servers in this stage cannot be provisioned until the OS Build Agent is installed.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Unprovisioned — Unreachable</p> <p>Indicates a server that has been registered with the core via the SA OS Build Agent, but has not reported as ready for provisioning recently. This may be due to networking problems between the server and the SA core or the server having been disconnected or powered off.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Unprovisioned — Reachable</p> <p>Indicates a server that has been registered with the core via the SA OS Build Agent and is available to have a target OS installed on it.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Provisioning — Unreachable</p> <p>Indicates a server on which SA OS Provisioning was in the process of installing the target OS, but for some reason stopped because the server is unable to communicate with the SA core.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Provisioning — Reachable</p> <p>Indicates a server on which SA OS Provisioning is in the process of installing the target OS.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>

Table 22 Server Status Icons in SA (cont'd)





Server Icon	Description
	<p>Provisioning Failed — Unreachable</p> <p>Indicates an available server on which an error occurred while the OS Provisioning Subsystem was installing a target OS, and that the server is not able to communicate with the SA core.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Provisioning Failed — Reachable</p> <p>Indicates an available server on which an error occurred while the OS Provisioning Subsystem was installing a target OS.</p> <p>In the SA Client, appears in the Unprovisioned Server list.</p> <p>In the SA Web Client, appears in the My Jobs panel home page, in the My Jobs page, and in the Server Pool list.</p>
	<p>Managed — Reachable</p> <p>Indicates a server has an An Server Agent is running on it and that it is able to communicate with the SA core.</p> <p>In the SA Client, appears in the All Managed Servers list and Virtual Servers list.</p> <p>In the SA Web Client, appears in the My Jobs panel in the home page, in the list in the My Jobs page, in the Manage Servers list, and in the server lists in the SA wizards.</p>
	<p>Managed — Unreachable</p> <p>Indicates a managed server cannot communicate with the SA core (it is Not Reachable).</p> <p>If you want to discover reasons why the managed server is unreachable, you can run a Communication Test. See Running Server Communication Tests on page 139 for more information.</p> <p>In the SA Client, appears in the All Managed Servers list and Virtual Servers list.</p> <p>In the SA Web Client, appears in the My Jobs panel in the home page, in the list in the My Jobs page, in the Manage Servers list, and in the server lists in the SA wizards.</p>

Table 22 Server Status Icons in SA (cont'd)







Server Icon	Description
	<p>Unmanaged</p> <p>Indicates the server is unmanaged, which means it does not have an Server Agent installed on it.</p> <p>For unmanaged virtual servers, this means that someone created a VMware Virtual Machine (VM) or Solaris local zone outside of SA and thus does not have an Server Agent installed on it.</p> <p>For virtual servers, this state could also mean that the VMware VM is has not yet been provisioned, or that your user belongs to a group that does not have permissions to perform operations on this virtual server.</p> <p>For more information on installing an Server Agent on an unmanaged server, see Installing the SA Agent on page 123.</p>
	<p>Deactivated</p> <p>Indicates a server that was deactivated in SA so that it is currently not managed and is no longer reachable.</p> <p>Appears in the Manage Servers list and in the server lists in the SA wizards (however, it is not selectable in the wizards).</p>
	<p>Scheduled</p> <p>Indicates a server that is scheduled for an operation (install software, uninstall software, and so forth).</p> <p>In the SA Client, appears in the Job Logs list.</p> <p>In the SA Web Client, appears in the My Jobs panel in the home page and in the list in the My Jobs page.</p>
	<p>Error</p> <p>Indicates a managed server on which an error occurred while SA was installing or uninstalling software.</p> <p>Appears in the My Jobs panel in the home page and in the list in the My Jobs page.</p>
	<p>Warning</p> <p>Indicates a managed server on which a warning occurred while SA was installing or uninstalling software.</p> <p>Appears in the My Jobs panel in the home page and in the list in the My Jobs page.</p>
	<p>Application Configuration Out of Sync</p> <p>Indicates a managed server on which the configuration file on the server is out of sync with the Application Configuration Template (SA model).</p> <p>Appears only in the Application Configuration feature and the server list in the SA Client.</p>

Table 22 Server Status Icons in SA (cont'd)






Server Icon	Description
	<p>Static Device Group</p> <p>Indicates a static server group. The same states that apply to single servers apply to groups.</p> <p>See Server Groups on page 209 for more information about the different types of server groups.</p>
	<p>Dynamic Device Group</p> <p>Indicates a dynamic server group. The same states that apply to single servers apply to groups.</p>
	<p>Public Static Device Group</p> <p>Indicates a public and static server group. The same states that apply to single servers apply to groups.</p>
	<p>Public Dynamic Device Group</p> <p>Indicates a public and dynamic server group. The same states that apply to single servers apply to groups.</p>

Figure 80 shows the Server Properties columns. Table 23 describes the server status for managed servers.

Figure 80 Server Properties Columns in the Manage Servers List



Manage Servers (Summary View) ?

All Statuses ▾
All Operating Systems ▾
All Stages ▾
All Uses ▾

All Customers ▾
All Manufacturers ▾
All Models ▾
Update 

Managed & Deactivated ▾



Resource
Edit
View
Tasks
Configuration Tracking

<input type="checkbox"/>	Name [▲]	Host Name / IP Address	OS Version	Stage	Use	Customer
Public Groups						
<input type="checkbox"/>	 core.tr3.opsware.com	core.tr3.opsware.com 172.16.36.18	Red Hat Enterprise Linux AS 3	Not Specified	Not Specified	Opsware
<input type="checkbox"/>	 m201.tr3.opsware.com	mh03 172.16.36.34	Windows 2000	Not Specified	Not Specified	Not Assigned

The Status property is represented by an icon in the first column in the Manage Servers list. Status (short for Agent Status) is set automatically by SA. SA toggles each server between OK and Not Reachable by reachability checks.

The Status value specifies the ability of SA to manage servers. SA automatically detects the status of servers. To verify the current status of a server, click Update in the Server Properties page for that server.

Table 23 Values for the Status Property for Managed Servers

Status Value	Description
OK	<p>Server is manageable by SA. Represented as text (OK) in the properties page for a server. Represented as an icon in the Manage Servers and Server Pool lists:</p> 
Not Reachable	<p>Server is unreachable by SA due to an error (for example, it cannot connect to the SA core); automatically set by SA. Represented as text (Not Reachable) in the properties page for a server. Represented as an icon in the Manage Servers list:</p>  <p>If you want to discover reasons why the managed server is unreachable, you can run a Communication Test. See Troubleshooting Server Communication Tests on page 311 for more information.</p>

Server Management Tasks Related to the Server Life Cycle

Managing servers in SA involves the following standard tasks:

- Bringing a new server into SA so that it appears in the Server Pool
See [Installing and Managing Server Agents](#) on page 123.
- Installing an operating system on a server
See the *SA User Guide: OS Provisioning* for more information about OS provisioning.
- Installing a patch
See the *SA User Guide: Server Patching* for more information on patching servers.
- Installing a software
See the *SA User Guide: Software Management* for more information on software management.
- Re provisioning a server with a new OS
See the *SA User Guide: OS Provisioning* for more information about OS Provisioning.
You can re provision Solaris and Linux servers so that they are running another version of the same OS so long as the hardware supports that new version of the OS.
You can re provision servers built by SA and SA-managed servers by using this feature.



You cannot re provision a Linux server so that it runs a Windows OS.

- Deactivating a managed server so that SA no longer manages it.

See [Tasks Associated with Deactivating a Server](#) on page 238 for more information.

You accomplish server management tasks by using the following menus in the Manage Servers list:

- Resource: Allows to create new server groups, view properties of servers.
- Edit: Allows you to add servers to a group, delete server groups, remove servers from a group, deactivate servers.
- View: Allows you to view the summary, hardware, and software information of servers and server groups.
- Tasks: Allows you perform tasks such as running scripts, custom extensions and running communication tests.
- Configuration Tracking: Allows you to edit, and reconcile tracking policies.

Editing the Properties of a Server



You can edit a server only if you have permission to access the customer the server is associated with. For more information on permissions, see the *SA Administration Guide*.

When you edit the properties of a server, the server itself does not change; how SA views it changes. Perform the following steps to edit the properties of a server:

- 1 From the navigation panel, click **Servers** † **Manage Servers**. The Manage Servers page appears. Browse the list to find the server whose properties you want to edit.

Or

Search for the server that you want to edit.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

- 2 Click the Server Display name. The Properties page for the server appears.
- 3 Change any of the following properties for the server:
 - To change the name that appears in the SA Web Client, edit the text in the Name field.
 - To change the description of the server, edit the Notes field.
 - To change the customer associated with the server, select a different customer from the list. Your SA administrator defines the options for customer selections. Contact your SA administrator if the list does not contain the customer that you want to associate with this server.
 - To change the Use or Stage of the server, make your changes in either of those lists. See [Table 22](#) for more information.
- 4 To save your changes, click **Save**.



To change the custom attributes of the server, select the Custom Attributes tab. The Manage Servers: Custom Attributes page appears. See [Managing Custom Attributes](#) on page 249 for more information.

Tasks Associated with Deactivating a Server

You will want to deactivate a server when SA removes the server from management. For example, you are moving the server to a warehouse for storage. Additionally, you might choose to deactivate a server when you need to rebuild it from scratch, without using OS Provisioning.

When you deactivate a server, information about the server remains in the SA Model Repository for auditing purposes.

When you deactivate a server, you accomplish the following tasks:

- Remove custom attributes from the server.
- Delete any configuration tracking policies from the server that are associated with backups.
- Set the server life cycle value to Deactivated.

Deactivating a Server

Perform the following steps to deactivate a server:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears. Browse the list to find the server that you want to deactivate.

Or

Search for the server that you want to deactivate.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

- 2 Select the servers that you want to deactivate.
- 3 Choose **Edit † Deactivate Server** from the menu above the Manage Servers list. A confirmation dialog box prompts you to confirm the deactivation.
- 4 Click **OK**. The Manage Servers list refreshes and the server appears with a deactivated icon.



You cannot deactivate an SA Core server, only managed servers.

Deleting a Server from SA

When you want to remove all record of a server from SA, you can delete it.



You must deactivate a server before you can delete it from SA.

When you delete a server from SA, it has these effects:

- Deletes all job information in the My Jobs feature
- Deletes the server from the Model Repository

Perform the following steps to delete a server:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears. Browse the list to find the server that you want to delete.

Or

Search for the server that you want to delete.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

- 2 Select the servers that you want to delete.
- 3 Choose **Edit † Delete Server** from the menu above the Manage Servers list. A confirmation dialog box prompts you to confirm the deletion.
- 4 Click **OK**. The Manage Servers list refreshes and the server disappears from the list.

Server Use Categories and Deployment Stage Categories

This section describes how you can use Server Use categories and Deployment Stage categories to group your servers into different life cycle phases for easier management.

- **Server Use** - This category describes what the server is being used for. You specify the meaning of each category for your own use. SA provides the following categories but you can add your own categories:
 - Not Specified - This is the default value.
 - Development - Servers being used to develop your business services.
 - Staging - Servers in preparation before going into production.
 - Production - Servers in production providing your business services.
- **Deployment Stage** - This category describes what stage of deployment the server is in. You specify the meaning of each category for your own use. SA defines the following categories but you can add your own categories:
 - Not Specified - This is the default value.
 - Offline - Servers are not in use.
 - In Deployment - Servers are being prepared for use.
 - Ops Ready - Servers are ready to be used.
 - Live - Servers are being actively used.

Changing the Server Use and Deployment Stage Values for Servers

Perform the following steps to change the Server Use and Deployment Stage values for multiple servers simultaneously:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears. Browse the list to find the server that you want to deactivate.

Or

Search for the server that you want to deactivate.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

- 2 Select the servers that you want different Use or Stage values for.
- 3 Choose **Edit † Usage** from the menu above the Manage Servers list. A window prompts you to select different values, as [Figure 81](#) shows.

Figure 81 Edit Server Popup Window

Server	Facility	Stage	Use
172.16.36.18 - core.tr3.opsware.com	DATACENTER1	current: Not Specified Not Specified ▾	current: Not Specified Not Specified ▾

Save Changes Cancel

- 4 Select the Use and Stage values from the lists.
- 5 Click **Save Changes**. The window closes and the Manage Servers list refreshes with the updated values.

Server Management Jobs

This section provides information about server management jobs within SA and contains the following topics:

- [My Jobs](#)
- [My Jobs Display Information](#)
- [My Jobs in the SA Web Client](#)
- [Jobs in SA Client](#)
- [Viewing Job Details in the SA Web Client](#)
- [Viewing My Job Details from inside the SA Client](#)

My Jobs

The My Jobs information is available only on a per-user basis. You cannot log in as an SA administrator to see the jobs that other SA users have run. The My Jobs information appears in two places in the SA Web Client:

- A panel on the SA Web Client home page that lists your most recent six jobs
- A page (accessed by clicking My Jobs in the navigation panel) that lists all the jobs that you have run

SA maintains information about the server operations that you have run for the last 30 days in the My Jobs list. By default, the jobs are deleted from the SA Model Repository after 30 days. (The bottom of the My Jobs page indicates how long this interval is set for the SA installation at your organization.)

My Jobs Display Information

For each job, the My Jobs lists display the following information:

- The name of the job, which is a link to a page that displays more detailed information about the job
- The date and time the job started or is scheduled to start (using your preference for time display)
- The number of servers that the job affects
- The status of the job:
 - Scheduled
 - In Progress
 - Completed
 - Completed with errors
 - Completed with warnings
- You can search for an existing Job by the Job's ID. On the Home page, select Job from the drop-down list and enter a Job ID and click **Go**.

My Jobs in the SA Web Client

The My Jobs feature in the SA Web Client provides information about the following Command Engine scripts:

- OS provisioning
- Distributed script execution
- Custom Extensions

Jobs in SA Client

Jobs feature in the SA Client displays job logs about the following SA Client jobs:

- Creating snapshots
- Pushing or Auditing an Application Configuration
- Auditing Servers
- Creating Server Snapshots
- Remediating policies
- Running OS Sequence
- Any jobs scheduled to be run at a future date

Jobs in the SA Client appear in the Jobs Logs feature window.

Viewing Job Details in the SA Web Client

Perform the following steps to view the job details:

- 1 From the SA Web Client home page, click the link in the My Jobs panel for the job that you want to view, as [Figure 82](#) shows.














Figure 82 My Jobs Panel in the SA Web Client Home Page

My Jobs See All (22)				
Name	Start Time	Servers	Groups	Status
 Run Custom Extension	(not set)	4	0	Cancelled
 Run Script	Wed Oct 31 21:45:00 2007	4	0	Scheduled
 Run Script	Tue May 31 21:22:06 2005	3	0	Completed with errors
 Audit Servers [Launch OCC Client]	Tue May 31 21:00:48 2005	2	0	Completed
 Create Snapshot [Launch OCC Client]	Tue May 31 20:57:05 2005	1	0	Completed
 Audit Servers [Launch OCC Client]	Tue May 31 20:50:09 2005	2	0	Completed with warnings

Or

From the navigation panel, click My Jobs and then click the link for the job to open a window that shows the details of the job, as [Figure 83](#) shows.

Figure 83 My Jobs Page Accessed from the Navigation Panel

< Job ID > All Job Types No Time Restrictions All Job Status Update						
30 Total						
	Job ID	Job Type	Start Time ^	Servers	Groups	Status
	1440666	Run Custom Extension	(not set)	4	0	Cancelled
	1450666	Run Script	Wed Oct 31 21:45:00 2007	4	0	Scheduled
	1700666	Audit Servers [Launch OCC Client]	Tue May 31 22:29:54 2005	2	0	Completed with errors
	560667	Audit Servers [Launch OCC Client]	Tue May 31 22:19:18 2005	2	0	Completed with errors
	550667	Audit Servers [Launch OCC Client]	Tue May 31 22:16:50 2005	2	0	Completed with errors
	1630666	Audit Servers [Launch OCC Client]	Tue May 31 22:12:26 2005	2	0	Completed with errors
	1580666	Audit Servers [Launch OCC Client]	Tue May 31 22:04:27 2005	2	0	Completed with errors
	1570666	Audit Servers [Launch OCC Client]	Tue May 31 22:00:17 2005	2	0	Completed with errors
	1560666	Audit Servers [Launch OCC Client]	Tue May 31 21:58:35 2005	2	0	Completed with errors
	1550666	Audit Servers [Launch OCC Client]	Tue May 31 21:57:33 2005	2	0	Completed with errors
	1460666	Run Script	Tue May 31 21:22:06 2005	3	0	Completed with errors
	1240666	Audit Servers [Launch OCC Client]	Tue May 31 21:00:48 2005	2	0	Completed
	1230666	Create Snapshot [Launch OCC Client]	Tue May 31 20:57:05 2005	1	0	Completed

The My Jobs page displays the operations that you performed.

- 2 Click **View Details** to see detailed information about the job. The My Jobs information contains a build log for the job. This build log contains any error messages that SA generates. See [Figure 84](#).


Figure 84 Communication Test Details Page in the My Job Window



Viewing My Job Details from inside the SA Client

You can also view job details from inside the SA Client. If the job was run from inside the SA Client, you will see a link next to the job named [Launch SA Client](#), as shown in [Figure 85](#).

Figure 85 My Jobs with link to SA Client



To launch the SA Client and view the job details, click the link.

Server Management Scheduling and Notification

This section contains the following topics:

- [Scheduling a Job](#)
- [Sending Email Notification](#)

The time used for the scheduled job is specified in the user's preferred time zone (which can be modified in My Profile). If the user does not have a preferred time zone set, the time zone is derived from the SA core server (usually UTC).

Scheduling a Job

Perform the following steps to schedule server management tasks:

- 1 In the Schedule and Notify page of an SA Wizard, choose the Run Now option to execute the operation immediately or choose the Specify Time Option to schedule the operation at a later date and time. See [Figure 86](#)



The time used for the scheduled job is specified in your preferred time zone which can be modified in My Profile. If you do not have the preferred time zone set, the time zone is derived from the SA core server (usually UTC).

- 2 When you schedule a job for a server group, you can specify how the members of the group are determined. The membership of a dynamic server group changes based on the changes in your operational environment. If you have “Allow Run Refresh Jobs” permissions, you will see additional options. Select either of the following options:
 - **Option 1:** Membership is determined based on the “Time of Confirm Selection.” Select this option to run the job on the servers that were in the group when you scheduled the job. Changes to the group membership do not affect the list of the servers that the job will run on.
 - **Option 2:** Membership is updated when the job runs. Select this option to recalculate the group membership prior to running the job. Changes to group membership are reflected in the list of servers that the job will run on.

Figure 86 Scheduling a Job in an SA Wizard

The screenshot shows a window titled "Run Custom Extension" with a sidebar on the left containing a numbered list of steps: 1. Select Extension, 2. Select Servers, 3. Specify Settings, 4. Confirm Settings, 5. Schedule and Notify (highlighted in green), and 6. Run Extension. The main area is titled "Schedule and Notify" and contains the following controls:

- Schedule:** Radio buttons for "Run Now" (selected) and "Specify Time". Below "Specify Time" are dropdowns for month (March), day (07), and year (2005), along with a calendar icon and time dropdowns (23, 45).
- Notify:** Radio buttons for "None" (selected) and "Condition". Below "Condition" is a dropdown menu set to "on any result" and a text box for "Recipients" containing "ssunderrajan@opsware.com".
- Options:** Radio buttons for "Run the job on the servers from the Groups based on the time of Confirm Selections." (selected) and "At the scheduled time, update the list of servers from the groups (0) selected prior to running the job." (unselected).

At the bottom of the window are three buttons: "Cancel", "< Previous", and "Run >".

- 3 Additionally, you can view a scheduled job in the My Jobs page and change the date and time for the job to run, or cancel the job entirely. (Click the name of a scheduled job to open a window to change the date or time that the job will run or cancel it.)

Sending Email Notification

The email notification feature provides you with an option to receive an email summarizing the job details when a job is over, and to notify others at the address they have registered with SA.

You have the option of sending the notification

- On the job success only
- On the job failure only
- On any result

You can also send notification to various people based on the condition of the job. For example, you can select to send the notification to your manager only on the job success, select to send the notification to yourself on any result of the job, and select to send the notification to support only on the job failure.

To send an email about the job details, choose the Condition option on the Schedule and Notify page and set the parameters to send an email when the operation is completed. You can choose to have an email sent on any result, if the operation fails, or if the operation is successful. To add another email recipient, click the plus (+) button next to the Recipients field. See [Figure 87](#).

Figure 87 Notifying about a Job in the SA Web Client

Install Template - Microsoft Internet Explorer

Install Template

- 1 Select Template
- 2 Select Servers
- 3 Confirm Selections
- 4 Preview
- 5 Schedule and Notify**
- 6 Install

Schedule and Notify

Select the time and date for this job to run. You can choose to be notified after the job runs.

Schedule: Run Now
 Specify Time
September 22 2004 11 30

Notify: None
 Condition
on any result

Recipients: ssunderrajan@opsware.com, +

Cancel < Previous Install >

Time-Outs for Server Management Jobs

Table 24 describes the time-out values that apply to the server management operations in SA.

Table 24 Time-Outs in SA

Time Out (Minutes)	SA Operation
420 (7 hours)	Reconciling software (installation and uninstallation).
2	Starting Command Engine sessions in response to a command. If the Server Agent does not start executing the command within this time, the command will time out and the Command Engine script will continue.
30	Responding to a command (for example, after a reboot, the maximum time to wait until a server responds) or sending a message to the Command Engine from the Server Agent. If the Server Agent does not respond to the Command Engine at least once during this interval, the command will time out and the Command Engine script will continue. SA polls the Server Agent every 15 minutes and if the Server Agent fails to respond two consecutive times, the command will time out.

Customizing the Monitor Time-Out Duration

If you would like to set a different monitor time-out duration, you can create a custom attribute named `OPSW_reconcile_monitor_timeout` and change the number of minutes before a time out occurs. For each type of hardware running in your operational environment, you can set a custom attribute with the time-out duration that you want. To set a time-out duration for a type of hardware, click **Environment † Hardware** in the navigation panel. Then, navigate to the type of hardware that you want to add a custom attribute for.

During remediate, a periodic heartbeat occurs between the Server Agent and the Command Engine to ensure that the agent is still responsive. This setting controls the maximum amount of time that can pass between these heartbeat messages. Typically, you only need to increase this setting if you install software that reboots the server, and the time that it takes for the server to reboot and for the agent to restart exceeds the default value.

Custom Fields for Servers



This section discusses how to manage custom fields with the SA Web Client. The SA Web Client is deprecated for managing custom fields. Use the SA Client for managing custom fields. For more information, see [About Custom Fields](#) on page 162 and [Comparing Custom Fields and Custom Attributes](#) on page 161.

SA can store a large amount of information about your managed servers. Custom fields provide a way for you to store additional information about your servers quickly and easily. Custom fields are data elements you can create for servers and device groups.

When you create a custom field for servers, every server in your managed environment gets an instance of the custom field. When you create a custom field for device groups, every device group gets an instance of the custom field. The value of the custom field can be different for each server or device group.

For example, if your managed environment contains 500 servers and you create a custom field for servers, you would have 500 separate custom fields, one for each server. If you had 75 device groups and you created a custom field for device groups, you would have 75 separate custom fields, one for each device group.

Custom fields can contain files, URLs, text strings, numbers, and dates.

You can also use custom fields to search for servers based on a value stored in the custom field. You can also use a custom field as criteria to create a dynamic server group.



Before the custom fields appear in the Managed Server: Properties page, you must first create a custom field. To create a custom field, you must install the `custFields.py` Custom Extension which is available only from the Content Starter Pack. Contact SA Technical Support for assistance in installing the `custFields.py` Custom Extension in SA.

Typed Data Supported for Custom Fields

The custom fields designated for your operational environment will vary. However, the custom fields created for your environment support values with the following data types:

- **Number:** The value provided must be a long integer.
- **Short String:** A text string that must be less than or equal to 4000 characters.
- **Long String:** A text string with no length restrictions. Custom fields with this type cannot be used in search or in the rules for dynamic server groups.
- **Date:** The value will be verified for correctness.
- **File:** Indicates a file attachment.
- **URI:** A Uniform Resource Identifier string, which is validated as a URI.

SA validates the value you enter in a custom field based on the data type specified for the field.

Uses of Custom Fields

You can use custom fields to accomplish any of the following goals:

- To store the date of patch installation
- To assign a severity rating between 1 and 10 to a Hotfix
- To store an ID from an internal bug tracking system with its associated patch
- To store a JPEG image of the back of a server and have that JPEG associated with that server
- To store a Microsoft Word document describing the disaster recovery steps for a server or group of servers
- To search for a server based on the value of a custom field

Editing Custom Field Values



You can also use the SA Client to edit custom field values. For more information, see [About Custom Fields](#) on page 162 and [Comparing Custom Fields and Custom Attributes](#) on page 161.

- 1 From the navigation panel, click **Servers** † **Manage Servers**. The Manage Servers page appears. Browse the list to find the server whose custom fields you want to change.

Or

Search for the server whose custom fields you want to change.

- 2 Click the server name. The Manage Servers: Properties page appears. Scroll to the Custom Fields section of the page. The custom fields that appear in the properties page are specific to your operational environment. [Figure 88](#) shows an example of the types of custom fields that can appear for a server.

Figure 88 Custom Fields That Appear for a Server

CUSTOM FIELDS	
Date to be installed	04 October 2004 [Calendar] 0 00 TVT [Unset]
External OSS system ID	CQ12345 [Browse] Enter up to 4000 characters in this field
Microsoft bulletin	http://www.microsoft.com/bulletin/hotfixes/Q23909.html [Edit] [Unset]
Severity	4 Please enter an integer with a maximum of 18 digits
Support document	support.doc [Remove] This is the support document for this patch.
[Save] [Cancel]	

- 3 To change a value in a field requires a number or text, enter the value in the field.
- 4 To add a file, click **Browse** and select the file from the dialog box.
- 5 To remove a file, click **Remove**.
- 6 To specify a URL, enter the URL in the field or click **Edit** to change an existing URL.
- 7 To add or change a date, click the [Calendar] icon and select the date or enter the date in the field by selecting the appropriate day, month, and year from the drop-down lists.
- 8 Click **Save**.

Custom Attributes for Servers



This section discusses how to manage custom attributes using the SA Web Client. You can also create and manage custom attributes with the SA Client. For more information, see [Creating and Managing Custom Attributes](#) on page 165 and [Comparing Custom Fields and Custom Attributes](#) on page 161.

SA can store a large amount of information about your managed servers. Custom attributes provide a way for you to store additional information about your servers quickly and easily. Custom attributes are data elements you can create for servers, device groups, customers, facilities, OS installation profiles, and software policies.

You can use custom attributes to facilitate server or application installation and configuration, scripting, or other purposes. You can write scripts that use custom attributes to perform a variety of tasks including network and server configuration, notifications, and CRON script configuration. Custom attributes can be accessed by software packages at installation time to configure software settings.

For information about how to set custom attributes required by the software running on a specific server, contact the group responsible for packaging your applications, as [Figure 89](#) shows.

Figure 89 Custom Attributes Set for a Server

[Return to Manage Servers](#)

Name	Value	Source
OPSW.reprovision_device_attributes_to_preserve	kernel_arguments reboot_c...	Operating Systems / Red Hat Enterprise Linux AS 3 / Not Assigned (Operating Systems)

Managing Custom Attributes



Do not edit or remove custom attributes without verifying that the change you are making does not impact other users or critical SA operations.

To set custom attributes that affect a specific server, use the Manage Servers list. After locating the server and displaying the server properties, select the Custom Attributes tab. The SA Web Client displays the currently defined custom attributes for the selected server.

When you add or edit server custom attributes using the SA Web Client, SA removes leading and trailing white space characters from custom attribute values.

See [Adding Server Custom Attributes](#) on page 249 for more information.

You can also set custom attributes to a software policy. See the *SA User Guide: Software Management* for more information.

Additionally, you can add custom attributes for a server group by viewing a server group, and then selecting the Custom Attributes tab for that group. The procedure to add custom attributes to a server group is the same as adding custom attributes to individual servers.

Adding Server Custom Attributes

For information about how to set custom attributes required by the software running on a specific server, contact the group responsible for packaging your applications.

Perform the following steps to add a custom attribute for a server:

- 1 From the navigation panel, click **Servers** † **Manage Servers**. The Manage Servers page appears. Browse the list to find the server for which you want to add custom attributes.

Or

Search for the server for which you want to add custom attributes.

- 2 Click the display name of the server. The Manage Servers: Server Properties page appears.

- 3 Select the Custom Attributes tab. The Manage Servers: Custom Attributes page appears.
- 4 Click **New**.
- 5 Enter the name and value for the custom attribute that you want to add.
- 6 Click **Save**.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

Editing Server Custom Attributes



If you want to change the name of a custom attribute entry, you need to create a new custom attribute and delete the old custom attribute.

Perform the following steps to edit custom attributes for a server:

- 1 From the navigation panel, click **Servers † Manage Servers** or **Server Pool**. The Manage Servers page appears. Browse the list to find the server for which you want to edit custom attributes.

Or

Search for the server for which you want to edit custom attributes.
- 2 Click the display name of the server. The Manage Servers: Server Properties page appears.
- 3 Select the Custom Attributes tab to change the custom attributes of the server. The Manage Servers: Custom Attributes page appears.
- 4 Click the attribute name link for the custom attribute that you want to change.
- 5 Update the value of the custom attribute.
- 6 Click **Save** to save your changes. The Manage Servers: Custom Attributes page reappears with the updated value.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

Deleting Server Custom Attributes

Perform the following steps to delete custom attributes for a server:

- 1 From the navigation panel, click **Servers † Manage Servers** or **Server Pool**. The Manage Servers page appears. Browse the list to find the server from which you want to remove custom attributes.

Or

Search for the server from which you want to remove custom attributes.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.
- 2 Click the display name of the server. The Manage Servers: Server Properties page appears.
- 3 Select the Custom Attributes tab. The Manage Servers: Custom Attributes page appears.

- 4 Select the check box for the custom attribute that you want to delete.
- 5 Click **Delete**. The SA Web Client displays a confirmation page.
- 6 Click **OK** to delete the custom attribute.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

Service Levels

This section provides information about service levels within SA and contains the following topics:

- [Overview of Service Levels](#)
- [Adding a Service Level to the SA Web Client](#)
- [Editing a Service Level](#)
- [Ways to View the Service Level for Servers](#)
- [Assigning a Server to a Service Level](#)
- [Removing a Server from a Service Level](#)

Overview of Service Levels

Service levels are user-defined categories that enable you to group servers in an arbitrary way and design your own organizational schemes. For example, you can organize your servers by functionality (finance, engineering, and so forth) or tier (Web, application, and database) or by ontogeny (development, staging, and production).

You can also create service levels to indicate the Service Level Agreement (SLA) for the servers that your IT organization manages. For example, you might create service levels to denote Silver, Gold, and Platinum services.

Please note that assigning servers to service levels does not cause SA to operate any differently with respect to those servers. When you first use service levels, the categories will be fairly empty and by default, when a Server Agent is installed on a server in the operational environment, the server will be added to the UNKNOWN Service Level.



Adding a Service Level to the SA Web Client

Perform the following steps to add a service level to the SA Web Client:

- 1 From the navigation panel, click **Environment † Service Levels**. The Service Levels page appears.
- 2 Navigate the hierarchy of service levels until you reach the point in the hierarchy where you want to add a new service level, as [Figure 90](#) shows.

Figure 90 Service Level Hierarchy

Service Levels > OTHER ?

  **OTHER** Details Add

No Sub-Nodes

Properties	Custom Attributes 0	Members 0	Config Tracking	Templates 0	History
Cannot edit or delete this Node. This Node is reserved.					
Name:	OTHER				
Description:	Other service level				
Customer:	Customer Independent				
Operating System:	OS Independent				
Locked:	No				
Allow Servers:	Yes				
ID:	50003				

- 3 Click **Add**. The Service Levels page refreshes and the ADD SUB-NODE TO Service Levels form appears in the page.
- 4 Enter a name for the service level (required), and (optionally) enter notes and a description for the service level.
- 5 Click **Save**. The service level is added to the hierarchy of service levels. The Edit Service Level page appears, where you can change the properties of the service level, such as the customer association.

Editing a Service Level

Perform the following steps to edit a service level:

- 1 From the navigation panel, click **Environment † Service Levels**. The Service Levels page appears.
- 2 Navigate the hierarchy of service levels until you reach the point in the hierarchy where you want to edit an existing service level.
- 3 Click **Edit** in the Properties tab. The page refreshes and an editable form appears for the service level properties.
- 4 Make changes to the service level name, description, notes, whether servers are allowed to be assigned to the service level, the associated customers and operating systems.
- 5 Click **Save**.

Ways to View the Service Level for Servers

Find the server whose service levels you want to view by searching or browsing the Manage Servers list.


- If you are browsing the Manage Server list, you can find the service level for a server by locating the value in the Environment column, as [Figure 91](#) shows.

Figure 91 Service Level Node Appearing in the Software Tab of the Server List




- If you searched for the server, click the server name and then select the Attached Nodes tab. You can find the service levels, as [Figure 92](#) shows.

Figure 92 Nodes Tab That Shows the Service Level to Which a Server is Assigned



- To view all the servers assigned to a particular service level, click **Environment † Service Levels** in the navigation panel. Navigate the hierarchy of service levels until you reach the one for which you want to see which servers are assigned. Select the Members tab, as [Figure 93](#) shows.

Figure 93 Manage Server Assigned to a Service Level




Assigning a Server to a Service Level

Perform the following steps to assign a server to a service level:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears. Browse the list to find the server you want to assign to a service level.
Or
Search for the server that you want to assign to a service level.
- 2 Select the servers that you want to assign to a service level.
- 3 Choose **Tasks † Assign Node** from the menu above the Manage Servers list. A window displays the categories of nodes, as [Figure 94](#) shows.

Figure 94 Assign Nodes Popup Window



- 4 Click the Service Levels link. The window refreshes to show the service levels created for your operational environment.
- 5 Navigate to the service level to which you want to assign the server.
- 6 Click **Assign**. The window closes and you are returned to the Manage Servers list.

Removing a Server from a Service Level

Perform the following steps to remove a server from a service level:

- 1 From the navigation panel, click **Servers † Manage Servers**. The Manage Servers page appears. Browse the list to find the server that you want to remove from a service level.
Or
Search for the server that you want to remove from a service level.
- 2 Select the server that you want to remove from a service level.
- 3 Choose **Tasks † Remove Node** from the menu above the Manage Servers list. A window displays the nodes to which the server is assigned, as [Figure 95](#) shows.

Figure 95 Remove Nodes Popup Window

Nodes: Remove Nodes

List of Server

IP	Hostname
192.168.218.189 -	dhcp-189.core2.custqa10.com

Select the Nodes to Remove

Select	Node
1	Operating Systems / SunOS 5.8 / SunOS 5.8 - SUNWXCali
<input type="checkbox"/>	Service Levels / joe-constraint-test-SL

†This Node Type cannot be removed. To change it, you must Re-Assign the Node.

Remove Cancel

- 4 Select the service level node from which you want to remove the server and click **Remove**. You are prompted to confirm that you want to remove the server from the service level.
- 5 Click **Confirm Remove**. The window closes and you are returned to the Manage Servers list.

Network Configuration

This section provides information about network configuration within SA and contains the following topics:

- [Overview of the Server Network Configuration](#)
- [Configuring Networking for an SA Managed Server](#)

Overview of the Server Network Configuration

You can configure SA to automatically specify network settings for a server after you install the OS.

For example, SA OS Provisioning can install operating systems using DHCP addresses. Because DHCP servers often assign temporary IP addresses to servers that boot over a network, system administrators typically need to assign static IP addresses (and other network properties) before the servers can be put into service. You can do this through the SA Web Client rather than logging onto the server manually after OS provisioning is complete.



SA does not support managed servers that have IPv6 addresses.

The Server Network Configuration feature allows you to configure the following settings on a server that are related to its network configuration:

- Host Name
- Domain Name System (DNS) servers
- Management interface (the interface that SA should use when managing the server)

See [Locating the Management IP Address of a Managed Server](#) on page 207 for more information.

- Gateway (the IP address of the default router)
- DNS search domains
- WINS (Windows Internet Naming Service) Servers
- Configuration for each network interface, including whether the interface is configured statically or with a Dynamic Host Configuration Protocol (DHCP) IP address, host name, and subnet mask

You can alter any of these options and then apply the settings to the managed server. SA updates the server and reboots it to cause the new settings to take effect.

Configuring Networking for an SA Managed Server

You can only use the Network Configuration feature for servers running

- Sun Solaris
- Red Hat Linux
- Microsoft Windows

Perform the following steps to configure networking for an SA managed server:

- 1 From the navigation panel, click **Servers** † **Manage Servers**. The Manage Servers page appears. Browse the list to find the server that you want to configure networking on.

Or

Search for the server that you want to configure networking on.

See [Searching for Servers or Other Resources](#) on page 184 and [Server Searching by IP Address](#) on page 196 for more information.

- 2 Click the name of the server that you want to configure networking for. The Manage Servers: Properties page appears for that server.
- 3 Select the Network tab. The network information for the server displays.
- 4 Modify any of the following settings to configure the server networking.

For all fields, the default value is the one currently configured on the server.

- **Host Name:** The host name configured on the managed server. This field only sets the name by which the server knows itself and does not update DNS records for the server.
- **Management Interface:** Instructs SA to use a particular network interface when contacting the server. This is useful, for example, when a server has multiple network interfaces, but not all of them are reachable by the SA core. Designating a particular interface as the management interface allows SA to know which interface to use for managing the server.
- **Gateway:** The IP address of the default router
- **DNS Servers:** A list of DNS name server IP addresses
- **Search Domains:** A list of DNS domains to search when attempting to resolve host names
- **WINS Servers:** Set for Windows only; a list of WINS server IP addresses

- **Interface Configuration** (for each network interface in the system):
 - **DHCP:** If DHCP is enabled for an interface, the system uses DHCP to configure this network interface. In this case, static configuration settings (IP address, host name, and subnet mask) are not relevant for this interface, and the SA Web Client makes those fields not editable. If DHCP is not enabled, then static settings are required.
 - **IP Address:** The IP address for this interface (unless DHCP is enabled).
 - **Host Name:** The local host name for the server. This item is only required for servers running Solaris. Like the Computer Name field, this setting only affects the name by which the managed server knows itself, and does not update DNS records.
 - **Subnet Mask:** The IP network mask to use for this interface.

In addition, SA displays the management IP address and MAC address for the server; however, you cannot change these values reported by the Server Agent.

- 5 Click **Update Server** at the bottom of the page.

(If you click **Revert**, it causes any changes that you made to the fields to be discarded.)

A confirmation dialog box appears that shows the changes that will be made to the server. The confirmation dialog box includes a check box that allows you to indicate that the server should revert to its old network configuration when it cannot contact the SA core after you save the new network configuration. By default, the Revert check box is selected.

The SA Web Client does not validate the network configuration changes that you make in the Network tab. Therefore, it is possible to provide a malformed IP address in the IP address field for an interface.

- 6 To have the server revert to its previous network configuration if an error occurs, ensure that the check box is selected in the confirmation dialog box.
- 7 Click **OK** to proceed with the configuration changes.

A progress dialog box appears that shows the progress of the operation. The process of setting a new network configuration involves rebooting the managed server. The operation might take several minutes.

You can wait for the operation to complete or close the progress dialog box and perform other work in the SA Web Client. The status of the task is available in the My Jobs user interface if you want to check the status of the network configuration update.

Details About Changing the Domain for Windows Servers

You cannot use the DNS Domain field to change the domain name for a Windows server.

SA does not change the domain name of a Windows server because changing the domain name of a server requires password authentication. Changing the domain name of a Windows server is a manual operation. See [Figure 96](#).

Figure 96 DNS Domain Field Displays in the Network Tab for a Server

[Return to Manage Servers](#)

Properties	Network	Membership	Attached Nodes	Installed Packages	Custom Attributes	Config Tracking	History
NETWORK INFORMATION (as of Tue May 24 19:21:06 2005)							
Hostname:		<input type="text" value="core.tr3.opsware.com"/>					
Management IP:		<input type="text" value="172.16.36.18"/>					
Facility:		<input type="text" value="DATACENTER1"/>					
Management Interface:		<input type="text" value="eth0"/>					
Gateway:		<input type="text" value="172.16.36.17"/>					
DNS Servers:		<input type="text" value="66.54.32.78"/> <input type="text" value="66.54.0.78"/>					
Search Domains:		<input type="text" value="tr3.opsware.com"/> <input type="text" value="opsware.com"/>					

10 Script Execution

Overview of Script Execution

The Script Execution feature allows you to automate the management and execution of scripts in the SA Client. It also allows you to organize your scripts in folders and define security permissions around them. From the SA Client, you can create or upload a script, set it up to run simultaneously across multiple Unix or Windows servers, and monitor it as it executes on each server. After a script is executed, you can view the results for every server and then export the script results. You can also modify, delete, and rename a script. You can also execute scripts in the Global Shell using the SA Client.

Script Execution Features

The Script Execution feature in the SA Client enables you to perform the following functions:

- Organize your scripts into folders and define security permissions to control access of their contents across different users and user groups.
- Create or upload scripts in the SA Client.
- Run scripts across multiple Unix or Windows servers or server groups.
- Execute scripts in the Global Shell.
- Schedule one time or recurring script execution jobs.
- Notify the status of the script execution job via email.
- Approve script execution jobs.
- View the script output against multiple servers in a tabular format.
- Export the script execution results.
- Search for scripts and script execution jobs.

Script Execution Process

The script execution process involves defining permissions, managing scripts, and executing scripts.

- **Defining Permissions**

In this phase, an SA Administrator assigns Folder permissions, Client feature permissions, and Customer constraints to define the security boundaries across various user groups. The permissions determines the actions the users in a user group can perform with the SA Client.

See the *SA Administration Guide* for more information about defining security permissions.

- **Managing Scripts**

In this phase, a policy setter or an advanced system administrator performs script management tasks such as creating or importing scripts, editing script properties, exporting scripts, and deleting scripts. See [Managing Scripts](#) on page 261 for more information.

- **Executing Scripts**

In this phase, a system administrator executes server scripts directly on servers or server groups and OGFS scripts in the Global Shell. A system administrator can also execute scripts by adding the scripts to a software policy and then remediating the servers against the software policy. See [Executing Scripts](#) on page 268 and the *SA User Guide: Software Management* for more information.

Types of Scripts

In the SA Client, the Script Execution feature supports two main types of scripts: Server scripts and OGFS scripts.

The Server script allows you to execute scripts on Unix and Windows servers managed by SA. The SA Client supports the following types of Server scripts for Unix and Windows operating systems: Unix/Linux shell, Windows batch (.BAT), Windows Visual Basic (VBScript), and Windows PowerShell.

The OGFS scripts allows you to execute scripts in the Global Shell from the SA Client. You can specify the directory path in the OGFS to execute the scripts. See the [SA Global Shell](#) on page 281.

The server scripts are further classified to Saved Scripts, and Ad-hoc Scripts.

- Saved scripts are accessible to all the users, if they have the appropriate permissions. You are required to have the appropriate permissions to create, view, edit, and execute shared scripts. Private scripts are only accessible to the user who created them. They can only be created, edited, deleted, or executed by the user who created the script.
- Ad-Hoc scripts are created or uploaded for one-time use and is not stored in HP Server Automation. Ad- Hoc script is created or uploaded and then immediately executed by a user and during this process, only one user has access to the script.

After you create a script and save it as a specific type of script in HP Server Automation, you cannot convert the script to the other type of script.

In the SA Client, you can specify to run a Server script as a Super User or as a specified user. A Super User script allows you to execute the script as root on UNIX or Local System on Windows servers without entering a password. If the script is not designated as a Super User Script, then you need to enter a user name and password to run the script. You also require the appropriate permissions to manage and run Super User Server Scripts. See the *SA Administration Guide* for information on the permissions required to run the Super User Server Scripts. All the OGFS scripts can only be executed as an SA User.

Managing Scripts

The script management tasks include:

- [Creating a Script](#)
- [Opening a Script in the SA Client](#)
- [Editing Script Properties](#)
- [Locating Scripts in Folders](#)
- [Exporting a Script](#)
- [Renaming a Script](#)
- [Deleting a Script](#)



You must have a set of permissions to create and manage a script. To obtain these permissions, contact your SA Administrator. See the *SA Administration Guide* for more information.

Creating a Script

In the SA Client, you can create a script from either the By Type or the By Folder view in the Library.

Script Creation Guidelines

HP Server Automation supports the following types of Server scripts for Unix and Windows operating systems: Unix/Linux shell, Windows batch (.BAT), Windows Visual Basic (VBScript), and Windows PowerShell.

When creating scripts you must adhere to the following guidelines:

- 4 MB is the maximum size allowable for a script.
- When you create a Unix shell script with a language other than the Bourne (sh) shell, use the sh-bang (!) format at the top of the script to specify the correct command interpreter. The command interpreter needs to be present on the managed server.

For example, if you are using Perl, the beginning of the script would contain the following line:

```
#!/usr/bin/perl
```

The following example shows a short Perl script (it displays “hello world”):

```
#!/usr/bin/perl
```

```
print "hello world\n"
```

- VBScripts are executed by the VBScript interpreter on the Windows server.
- To access command line parameters with Unix shell commands, use the following convention: \$1 \$2...
- To access command line parameters with Windows .BAT, use: %1 %2...
- Script lines do not need to be terminated in a specific way. But with Windows scripts, HP Server Automation converts all \n to \r\n. With Unix scripts, all \r\n are converted to \n.
- Scripts should be written to send error output to standard error.
- Scripts should use the standard convention of returning a zero code to indicate success. For other return codes, there is no standard code system to follow. Create unique non-zero return codes to handle each type of error.

Creating a Script from the By Type View in the Library

To create a script perform the following steps:

- 1 From the Navigation pane, select **Library † By Type † Scripts**. The three main types of scripts appear in the content pane.
- 2 Select the script type and then from the **Actions** menu, select **New script**. The Script window appears as shown in [Figure 97](#).

Figure 97 Script Window

Properties

Name: Simple BAT

Type: Windows .BAT

Location: / Select

Changes Server: Yes No

Run as super user: Yes No

Script Contents: Enter the script contents or import a script file Import Script File

```
dir c:\temp
```

Description: dir

Last Modified: Thu Aug 02 18:16:24 2007

Last Modified By: paul

Created: Thu Aug 02 18:16:18 2007

Created By: paul

Opware ID: 195380040

- 3 In the Name field, enter the name of the script.
- 4 (Windows only) Select the script type from the Type drop-down list.
- 5 Click **Select** to specify the location for the script in the folder hierarchy. The Select Folder window appears. Select a folder in the Library to specify the location of the script and then click **Select**.
- 6 In the Changes Server field, select Yes, if the script causes a change in the server configuration when executed.
- 7 In the Run as Super User field, select Yes if the script can be run as a Super User when executed. Selecting yes, allows you to run the script as a Super User without providing a password for the script.

This option is enabled only if you have to appropriate permission. See the *SA Administration Guide* for more information about script execution permissions.

- 8 In the Script Contents field, enter the contents of the script or click **Import Script File** to import a script.



If you import a script that uses Unicode (UTF8) encoding and your computer's regional language settings are set to English, and then you export the script and attempt to execute it, you may encounter errors because Unicode (UTF8) encoding may add a "." or other special character at the beginning of the script. If this occurs, simply edit the script to remove the extraneous characters.

- 9 In the Description field, enter text that describes the purpose or contents of the script.
- 10 To save the changes, select **Save** from the **File** menu.

Creating a Script from the By Folder View in the Library

To create a script perform the following steps:

- 1 From the Navigation pane, select **Library † By Folder**. The folder hierarchy in the Library appears in the Content pane.
- 2 Select the folder that should contain the script.
- 3 From the **Actions** menu, select **New †Script**. The Script window appears.
- 4 In the Name field, enter the name of the script.
- 5 Select the script type from the Type drop-down list.
- 6 Click **Select** to change the location for the script in the folder hierarchy. The Select Folder window appears. Select a folder in the Library to specify the location of the script and then click **Select**.
- 7 In the Changes Server field, select Yes, if the script causes a change in the server configuration when executed.
- 8 In the Run as Super User field, select yes if the script can be run as a Super user when executed. OGFS Scripts can only be executed as an SA User.

This option is enabled only if you have to appropriate permission. See the *SA Administration Guide* for more information about script execution permissions.
- 9 In the Script Contents field, enter the contents of the script or click **Import Script File** to import a script. In the Open window, select the script to import and then click **Open**.



If you import a script that uses Unicode (UTF8) encoding and your computer's regional language settings are set to English, and then you export the script and attempt to execute it, you may encounter errors because Unicode (UTF8) encoding may add a "." or other special character at the beginning of the script. If this occurs, simply edit the script to remove the extraneous characters.

- 10 In the Description field, enter text that describes the purpose or contents of the script.
- 11 To save the changes, select **Save** from the **File** menu.




The Library in the SA Client contains a Home directory and each user has a folder in the Home directory. You can save private scripts in this folder and later execute the script on managed servers.

Opening a Script in the SA Client

In the SA Client, there are several ways to open a script. You can open a script from:

- The Search option in the Navigation pane
- The By Type view in the Library
- The By Folder view in the Library
- The Device list in the Navigation pane

Opening a Script from Search

- 1 From the Navigation pane, select **Search**.
- 2 Select Server Script or OGFS Script from the drop-down list and then enter the name of the script in the text field.
- 3 Select . The search results appear in the Content pane.
- 4 From the Content pane, select the script and then select **Open** from the **Actions** menu. The Script window appears.

Opening a Script from the By Type view in the Library

- 1 From the Navigation pane, select **Library † By Type † Scripts**. The scripts appear in the Content pane.
- 2 From the Content pane, select the script and then select **Open** from the **Actions** menu. The Script window appears.

Opening a Script from the By Folder view in the Library

- 1 From the Navigation pane, select **Library † By Folder**. The folder hierarchy in the Library appears in the Content pane.
- 2 From the Content pane, select the script in a folder and then select **Open** from the **Actions** menu. The Script window appears.

Opening a Script from Devices

- 1 From the Navigation pane, select **Devices † Servers † All Managed Servers**. The server list appears in the Content pane.
Or
From the Navigation pane, select **Devices † Device Groups**. The device groups list appears in the Content pane.
- 2 From the Content pane, select a server and then from the **Actions** menu, select **Open**. The Server Explorer window opens.
- 3 From the Views pane, select **Management Policies † Software Polices**. The software policies attached to the server appear in the Content pane.
- 4 From the Content pane, select the software policy and then select **Open** from the **Actions** menu. The Software Policy window appears.
- 5 From the Views pane, select Policy Items. The policy items appear in the Content pane.
- 6 From the Content pane, select the script and then select **Open** from the **Actions** menu. The Script window appears.

Editing Script Properties

After you create a script, you can view and modify its properties. You can view properties such as the SA user who created the script, the date when it was created, and the Object ID of the script. You can also modify the name, description, contents, the Library folder location of the script and the script options.

To view and edit script properties, perform the following steps:

- 1 Open a script in the SA Client. See [Opening a Script in the SA Client](#) on page 264 for ways to open a script. The Script window appears.
- 2 In the Name field, edit the name of the script.
- 3 Click **Select** to change the location for the script in the folder hierarchy. The Select Folder window appears. Select a folder in the Library to specify the location of the script and then click **Select**.
- 4 In the Changes Server field, select Yes, if the script causes a change in the server configuration when executed.
- 5 In the Run as Super User field, select yes if the script can be run as a Super User when executed. Selecting yes, allows you to run the script as a Super User without providing a password for the script.

This option is enabled only if you have the appropriate permission. See the *SA Administration Guide* for more information about script execution permissions.
- 6 In the Script Contents field, edit the contents of the script or click **Import Script File** to import another script. In the Open window, select the script to import and then click **Open**.



If you import a script that uses Unicode (UTF8) encoding and your computer's regional language settings are set to English, and then you export the script and attempt to execute it, you may encounter errors because Unicode (UTF8) encoding may add a "." or other special character at the beginning of the script. If this occurs, simply edit the script to remove the extraneous characters.

- 7 In the Description field, edit the text that describes the purpose or contents of the script.
- 8 To save the changes, select **Save** from the **File** menu.

Viewing All the Software Policies Associated with a Script

In the SA Client, Server scripts can be added to a software policy. In the Scripts window, you can view all the software policies that contain the selected Server script. You cannot add OGFS script to a software policy.

To view the policy usage for a script, perform the following steps:


- 1 From the Navigation pane, select **Library † By Type † Scripts**.
- 2 From the Content pane, select the script and open it. The Scripts window appears.
- 3 From the Views pane, select Policy Usage. The list of software policies associated with the scripts appears in the Content pane.

Viewing Script Version History

To view the version history of a script perform the following steps:

- 1 From the Navigation pane, select **Library † By Type † Scripts**.
- 2 From the Content pane, select the script and open it. The Scripts window appears.
- 3 From the Views pane, select Version History. The events associated with the script will display in the Content pane. You can view the script content from different versions of a script. The **i*** indicates the current version of the script. You can view the script content from different versions of a script. See the [History of Server Changes](#) on page 75 for more information on server history.
- 4 To make any of the previous version of script current, select the script version and from the **Actions menu**, select **Set as Current Version** as shown is figure [Figure 98](#).

Figure 98 Script Version History



Locating Scripts in Folders

To locate a script in the folder hierarchy, perform the following steps:

- 1 From the Navigation pane, select **Library † By Type † Scripts**.
- 2 From the Content pane, select the script and then select **Locate in Folders** from the **Actions** menu. The folder hierarchy for the script appears in the Content pane.

Exporting a Script

To download a script, perform the following steps:

- 1 From the Navigation pane, select **Library † By Type † Scripts**. The scripts appear in the Content pane.
Or
From the Navigation pane, select **Library † By Folder** and then select the folder which contains the script.
- 2 From the Content pane, select a script to export.
- 3 From the **Actions** menu, select **Export Script**. The Export Software window appears.
- 4 In the Browse window, specify the location for the script to be exported to.
- 5 Click **Export**.

Renaming a Script

To rename a script perform the following steps:

- 1 From the Navigation pane, select **Library † By Type † Scripts**.
- 2 From the Content pane select the script, and then from the **Actions** menu select **Rename**.
- 3 Enter the new name for the script in the Content pane.

Deleting a Script

To delete a script perform the following steps:

- 1 From the Navigation pane, select **Library † By Type † Scripts**.
- 2 From the Content pane select the script, and then from the **Actions** menu select **Delete**. The Confirmation window appears.
- 3 Click **Delete** to delete the script.

Executing Scripts

In the SA Client, you can execute scripts in the following ways:

- Execute a server script directly on servers or server groups and execute scripts in the Global Shell. See [Running a Server Script \(Saved Script or Ad-Hoc Script\)](#) on page 269 and [Running an OGFS Script](#) on page 277 for more information.
- Add a script to a software policy and execute the script by attaching the software policy to the server and then remediating the server against the software policy. See the *SA User Guide: Software Management* for more information.

A software policy allows you to execute multiple scripts on a servers or server groups simultaneously, and execute a sequence of scripts on a server by specifying an install order in the software policy. See the *SA User Guide: Software Management* for information about software policies.



You must have a set of permissions to execute a script. To obtain these permissions, contact your SA Administrator. See the *SA Administration Guide* for more information. For security purposes, several permission-based scenarios can be experienced to run or copy scripts in folders, run super user scripts, run non-super user scripts, etc.

Ways to Open the Run Script Window

The Run Script window allows to you execute a script on managed servers. In the SA Client you can launch the Run Script window in the following ways:

- [From the Device List](#)
- [From the Device Explorer](#)
- [From the Library](#)

From the Device List

- 1 From the Navigation pane, select **Devices † Servers † All Managed Servers**. The server list appears in the Content pane.
Or
From the Navigation pane, select **Devices † Device Groups**. The device group list appears in the Content pane.
- 2 From the Content pane, select a server or device group.
- 3 From the **Actions** menu, select **Run Script**. The Run Script window appears.

From the Device Explorer

- 1 From the Navigation pane, select **Devices † Servers † All Managed Servers**. The server list appears in the Content pane.
- 2 From the Content pane, select a server.
- 3 From the Action menu, select **Open**. The Device Explorer appears.
- 4 From the **Actions** menu, select **Run Script**. The Run Script window appears.


From the Library

- 1 From the Navigation pane, select **Library † By Type † Scripts**. The scripts list appears in the Content pane.
- 2 From the Content pane, select a script.
- 3 From the **Actions** menu, select **Run**. The Run Script window appears.

Running a Server Script (Saved Script or Ad-Hoc Script)

The Run Script, as shown in [Figure 99](#), allows you to run a script on managed servers and consists of the following steps:

Figure 99 Run Server Script Window



- Servers and Groups
- Script
- Options
- Scheduling
- Notification
- Job Status

See [Ways to Open the Run Script Window](#) on page 268 on how to access the Run Script window. If you access the Run Script window from the Device list or Device Explorer, the first step in the window is Script. If you access the Run Script window from the Library, the first step in the Run Script window is Servers and Groups.

Servers and Groups

This step allows you to specify the servers or server groups for executing the script. In this step, you can add and remove servers or server groups from the list.

If you choose the option Now, then the membership is determined based on the time when you made the selection. As a result the script is executed on the servers that were in the group when you selected the option. Changes to the group membership does not affect the list of servers on which the script will be executed.

If you choose the option Runtime, then the membership is determined when the script execution job is run. The script is executed on the servers present in the server group when the job is run. Changes to group membership is reflected in the list of servers when is script is executed.



To be able to select the Runtime option, the “Allow Run Refresh Jobs” permission is required. See the *SA Administration Guide* for more information on permissions.

To select servers and groups perform the following steps :

- 1 Open the Run Script window from one of the methods described in [Ways to Open the Run Script Window](#) on page 268.
- 2 In the Run Script window, select the step Servers and Groups.
- 3 (Optional) Click **Include Server/Group** to add servers or server groups to the list or select a server or server group and click **Exclude** to remove servers from the list.
- 4 For a server group, in the Server Group Calculation field, select the option Now to execute the script on the servers that were in the group when you made the selection. Select the option Runtime to execute the script on the servers when the job is run.
- 5 Click **Next** to proceed to the Script step.

Script

This step allows to select a saved script or define an ad-hoc script to be executed on managed servers. See [Types of Scripts](#) on page 260 for information on the script types.

Saved Script

To select a saved script perform the following steps:

- 1 To select a saved script, select the option Select Saved Script.
- 2 From the Name drop-down list select the script or click **Select Script** to open the Select Script window. Select the script from the Select Script window.
- 3 The script properties such as version, type, location are displayed in the content pane. To view the contents on the script, click **View Script**. The contents of the script are displayed in the Run Script window.
- 4 Click **Next** to proceed to the Options step.

Ad-Hoc Script

To define an ad-hoc script perform the following steps:

- 1 To select an ad-hoc script, select the option Define Ad-hoc Script.
- 2 (Windows only) From the Type drop-down list, select the script type.
- 3 Enter the contents of the script in the Script Contents field or click **Import Script File** to import a script.



If you import a script that uses Unicode (UTF8) encoding and your computer's regional language settings are set to English, and then you export the script and attempt to execute it, you may encounter errors because Unicode (UTF8) encoding may add a "." or other special character at the beginning of the script. If this occurs, simply edit the script to remove the extraneous characters.

- 4 Click **Next** to proceed to the Options step.

Options

This step allows you to specify the runtime options and output options for executing a script. In this step you can specify whether to execute the script as root or Local System or as a specified user. You can also specify the script time-out value, any additional parameters for executing the script, and the output options for the script.

To specify the runtime and output options for a script perform the following steps:

- 1 In the Runtime User field select root (for Unix) or Local System (for Windows) to execute the script as root or local system. To execute the script as root or local system, you require the appropriate permissions. See the *SA Administration Guide* for information about the permissions required for executing scripts.

Or

- a Select Name and enter user name and password to execute the script as a specified user. To execute the script simultaneously across multiple servers or server groups, you must use the same user name and password across all the servers.
- b (Windows only) Enter the domain name in the domain field.
- 2 In the Script timeout field enter the script timeout value in minutes. The time out value is the amount of time required for a script to complete execution activities on a server. If the script is not executed when the timeout value is reached, then the script is stopped by SA and a script error occurs. Select a timeout value greater than the time required for execution to complete.
- 3 In the Specify any needed parameters for this script execution field, enter any parameters if required.
- 4 In the Output Options, select Discard all script output to discard script output or else select Retain script output.
- 5 Select the output size of the script from the Size of the output to retain drop-down list.
- 6 Click **Next** to proceed to the Scheduling step.

Scheduling

This step allows you to schedule the script execution job. You can choose to run the script execution job immediately, or on a specified date and time, or on a recurring basis.

To schedule a script execution job, perform the following steps:

- 1 In the Schedule Frequency section, choose to run the script once, daily, weekly, monthly, or on a custom schedule. Select any one of the following options:
 - **Once:** Choose this option to run the job immediately or only once at a specified date and time.
 - **Daily:** Choose this option to run the job on a daily basis at a specified time.
 - **Weekly:** Choose this option to specify the day or days of the week to run the job.
 - **Monthly:** Choose this option to specify the months to run the job, and the days of the month.
 - **Custom:** In the Custom Crontab string field, enter a string that indicates a time schedule. The crontab string can include serial (1,2,3,4) and range (1-5) values.
- 2 In the Time and Duration section, for each type of schedule, specify the start time for the job. You must also specify the start date and end date for the job.

- 3 In the Time Zone section, choose a time zone or accept the default, which is set according to the time zone settings in your user profile.
- 4 Click **Next** to proceed to the Notifications step.

Notifications

This step allows you to set email notifications to alert users on the success or failure of a job. You can also associate a Ticket ID with the job. This setting is optional.

To set email notifications, perform the following steps:

- 1 Click **Add Notifier**.
- 2 Enter the addresses in the Email Address of Recipient field.
- 3 For each recipient, select the check box for when to send an email notification:
 - On Success: sends email to recipient if the job succeeds.
 - On Failure: sends email to recipient if the job fails.
 - On Termination: sends email to recipient if the job is terminated.
 - Termination occurs when you stop an actively running job via the End Job action.
 - This notification does *not* apply to jobs that are cancelled before they are run.
- 4 Enter an ID to be associated with this job in the Ticket ID field.
- 5 Click **Next** to proceed to the Job Status step.

Job Status

This step allows you to start the job, view the job progress, the job results, the script output for a managed server, and export the script output from all the servers.

SA supports the following file formats for exporting script output results:

- A Zip file with folders for each managed server
- A Zip file containing no folders
- Consolidated raw text file
- Consolidated formatted text file
- Consolidated CSV file

You can also view jobs in the Jobs Log window of the SA Client. See [Browsing Job Logs](#) on page 46 for information about job logs.

To start a job, perform the following steps:

- 1 To start the job, click **Start Job**.

If you selected Immediately in the Scheduling step, the job will begin now. If you scheduled the job for a later time, the job will run later. You can then view the job in the Jobs Log window of the SA Client.
- 2 The job's progress information appears in the Job Status window. You can view the server on which the script was executed, the job status, and the exit code. If the exit code is zero, then it indicates that the script is executed successfully. If the exit code is non-zero, then it indicates an error during script execution.

If the job status is displayed as Pending Approval, then the job is blocked until it is approved by a process that is external to SA. See [Browsing Job Logs](#) on page 46 for information about job status.

- 3 (Optional) To view the script output from a managed server, select the managed server and script output appears below the table.
- 4 (Optional) To view the script output from all the managed servers, select the option Show output in table. The output for each server appears in the Output column in the table.
- 5 (Optional) To view the output for all the servers in separate columns, select the option Show output in table and enter the delimiter character in the Delimiter checkbox. The output for each server appears in separate columns in the table.
- 6 (Optional) To export the script output results, click **Export All Results**. In the Browse window specify the location and the file type and click **Export**.
- 7 Click **Close** to exit the Run Script window.

Terminating an Active Script Execution Job

You can stop a script job that is actively running. For example, you may need to stop a job that is producing erroneous results or will run beyond an allotted maintenance window. It should be noted that the termination process does not stop the script on a server or device where it is already running; it prevents the script from running on subsequent servers or devices.

You can terminate a script execution job from the Run Server Script window or from the SA Client Jobs and Sessions window.

Terminating an active script execution job has the following results:

- After the cancellation request is received, work is not started on any additional servers.
- If a script has already started on a server, it will be completed; however, it will not be started on additional servers.
- The Job Status view of the Run Server Script window will indicate the job status for each server on which the script was run:

Server Status	Explanation
Cancelled	The script did not run on the listed device.
Succeeded	The script completed running on the listed device.

- The Job Logs view of the SA Client Jobs and Sessions window will indicate the job status of the script:

Job Status	Explanation
Terminating	The termination request has been received and the job is in the process of ending.
Terminated	The termination process has completed.

Permissions for Terminating Active Jobs:

In general, users with the permission to start a job will be able also be able to terminate that job. In addition, users having *Edit or Cancel Any Job* permission are able to soft-cancel any running job.

See [Permissions Reference](#) in the *SA Administration Guide* for SA permissions details.

To terminate an active script execution job from the Run Server Script window:

- 1 Access the Run Server Script window and start the job.
See the following instructions for details:
 - [Ways to Open the Run Script Window](#) on page 268
 - [Running a Server Script \(Saved Script or Ad-Hoc Script\)](#) on page 269
 - [Running an OGFS Script](#) on page 277
- 2 From the Run Server Script window, click **End Job**. (This option only appears if the job is in progress.)
- 3 The End Job warning dialog will be displayed advising you that the job will complete the scripts that have been started on a server, but will not start any scripts on remaining servers.
- 4 Click **OK** to confirm that you wish to terminate the job. The Job Status window displays the progress of the termination.

If the job termination was successful on a particular device, it will be indicated by Cancelled status. Servers where the script completed will be indicated by Succeeded status. To see details about the server's status, select the server. Details will be displayed in the lower pane.
- 5 When the termination is complete, you can also view the job in the SA Client Job Log.

From the SA Client navigation pane, click **Jobs and Sessions**. The Job Logs view appears with your job listed with Terminated status.


To terminate an active script execution job from the SA Client Jobs and Sessions window:

- 1 From the SA Client navigation pane, click **Jobs and Sessions**. The Job Logs view appears.
- 2 From the Status filter, select In Progress to find running jobs.
- 3 Select **View † Refresh** from the menu to refresh the list. The content pane displays jobs with In Progress status.

You can additionally filter the list by the type of job (such as Run Server Script) from the Type filter.
- 4 In the content pane, select the job that you want to terminate.
- 5 Select **Action † End Job** from the menu. (This option only appears if the selected job is in progress.)

When the termination process is complete, the job will have Terminated status, as shown in [Figure 100](#).

Figure 100 Terminated Jobs from Job Log



Canceling a Scheduled Script Execution Job

You can cancel scheduled jobs that are not in progress from the SA Client Jobs and Sessions window. When you cancel a scheduled script execution job, the entire job is cancelled and it appears in the Job Log queue with Cancelled status.


To cancel a schedule job:

- 1 From the SA Client navigation pane, select **Jobs and Sessions**. The Job Logs window appears in the content pane.
- 2 In the Status filter, select: Scheduled.
- 3 Select the scheduled job that you want to cancel.
- 4 From the menu, select **Action** † **Cancel**. The job appears in the Job Log with Cancelled status.

Running an OGFS Script

The Run OGFS Script, as shown in [Figure 101](#), allows you to run an OGFS script and consists of the following steps:

Figure 101 Run OGFS Script Window



- Script
- Options
- Scheduling
- Notification
- Job Status

Script

This step allows to specify an OGFS script for execution.

To select an OGFS script perform the following steps:

- 1 From the Navigation pane, select **Library † By Type † Scripts**. The scripts list appears in the Content pane.
Or
From the Navigation pane, select **Library † By Folder**. The folder hierarchy in the Library appears in the Content pane.
- 2 From the Content pane, select an OGFS script.
- 3 From the **Actions** menu, select **Run**. The Run OGFS Script window appears.

- 4 In the Script Properties section, select script from the Name drop-down list or click **Select Script** to open the Select Script window. Select the script from the Select Script window.
- 5 The script properties such as version, type, location, description are displayed in the content pane. To view the contents on the script, click **View Script**. The contents of the script are displayed in the Run OGFS Script window.
- 6 In the Script Execution Path section, enter the OGFS directory path for executing the script or click **Browse** to specify the directory path in the OGFS.
- 7 Click **Next** to proceed to the Options step.

Options

This step allows you to specify the runtime options and output options for executing a script. In this step you can specify the script time-out value, any additional parameters for executing the script, and the output options for the script.

To specify the runtime and output options for a script perform the following steps:

- 1 In the Script timeout field enter the script timeout value in minutes. The time out value is the amount of time required for a script to complete execution activities. If the script is not executed when the timeout value is reached, then the script is stopped by SA and a script error occurs. Select a timeout value greater than the time required for execution to complete.
- 2 In the Specify any needed parameters for this script execution field, enter any parameters if required.
- 3 In the Output Options, select Discard all script output to discard script output or else select Retain script output.
- 4 Select the output size of the script from the Size of the output to retain drop-down list.
- 5 Click **Next** to proceed to the Scheduling step.

Scheduling

This step allows you to schedule the script execution job. You can choose to run the script execution job immediately, or on a specified date and time, or on a recurring basis.

To schedule a script execution job, perform the following steps:

- 1 In the Schedule Frequency section, choose to run the script once, daily, weekly, monthly, or on a custom schedule. Select any one of the following options:
 - **Once:** Choose this option to run the job immediately or only once at a specified date and time.
 - **Daily:** Choose this option to run the job on a daily basis at a specified time.
 - **Weekly:** Choose this option to specify the day or days of the week to run the job.
 - **Monthly:** Choose this option to specify the months to run the job, and the days of the month.
 - **Custom:** In the Custom Crontab string field, enter a string that indicates a time schedule. The crontab string can include serial (1,2,3,4) and range (1-5) values.
- 2 In the Time and Duration section, for each type of schedule, specify the start time for the job. You must also specify the start date and end date for the job. The Time Zone is set according to the time zone set in your user profile.
- 3 Click **Next** to proceed to the Notifications step.

Notifications

This step allows you to set email notifications to alert users on the success or failure of a job. You can also associate a Ticket ID with the job. This setting is optional.

To set email notifications, perform the following steps:

- 1 Click **Add Notifier**.
- 2 Enter the addresses in the Email Address of Recipient field.
- 3 To send email to the address if the job succeeds, select the checkbox On Success.
- 4 To send email if the job fails, select the select the checkbox On Failure.
- 5 Enter an ID to be associated with this job in the Ticket ID field.
- 6 Click **Next** to proceed to the Job Status step.

Job Status

This step allows you to start the job, view the job progress, view the job results, view the script output for a managed server, and export the script output from all the servers.

SA supports the following file formats for exporting script output results:

- A Zip file with folders for each managed server
- A Zip file containing no folders
- Consolidated raw text file
- Consolidated formatted text file
- Consolidated CSV file

You can also view jobs in the Jobs Log window of the SA Client. See [Browsing Job Logs](#) on page 46 for information about job logs.

To start a job, perform the following steps:

- 1 To start the job, click **Start Job**.
If you selected Immediately in the Scheduling step, the job will begin now. If you scheduled the job for a later time, the job will run later. You can then view the job in the Jobs Log window of the SA Client.
- 2 The job's progress information appears in the Job Status window. You can view the server on which the script was executed, the job status, and the exit code. If the job status is displayed as Pending Approval, then the job is blocked until it is approved by a process that is external to SA. See [Browsing Job Logs](#) on page 46 for information about job logs.
- 3 (Optional) To view the script output from all the managed servers, select the option Show output in table. The output for each server appears in the Output column in the table.
- 4 (Optional) To view the output for all the servers in separate columns, select the option Show output in table and enter the delimiter character in the Delimiter checkbox. The output for each server appears in separate columns in the table.
- 5 (Optional) To export the script output results, click **Export All Results**. In the Browse window specify the location and the file type and click **Export**.
- 6 Click **Close** to exit the Run OGFS Script window.

11 SA Global Shell

Overview of the Global Shell

The Global Shell is a command-line interface to the Global File System (OGFS). The command-line interface is a Unix shell such as `bash` that runs in a terminal window. The OGFS unifies the SA data model and the contents of managed servers, including files, into a single, virtual file system. You open a Global Shell session from within the SA Client Client or from a direct `ssh` connection in a terminal client on your desktop. With the Global Shell, you can automate repetitive system administration tasks by running scripts across multiple servers in a secure environment.

SA Global File System (OGFS)

The OGFS represents the SA data model as a hierarchical structure of file directories and text files. For example, in the OGFS, the `/opsw/Customer` directory contains details about SA customers and the `/opsw/Server` directory has information about managed servers. The `/opsw/Server` directory also contains subdirectories that reflect the contents (such as file systems and registries) of the managed servers. If you have the required permissions, in the Global Shell, you can view and even modify the file systems of managed servers.

Remote SA Shell (`rosh`) Utility

The Remote SA Shell (`rosh`) utility enables you to log on to managed servers and run native commands. You invoke `rosh` from within a Global Shell session. You can run `rosh` and enter native commands interactively, or you can specify the native commands as an option of `rosh`.

Benefits of the Global Shell

The Global Shell, OGFS, and `rosh` utility, offer the following benefits:

- **Security:** Logging on to managed servers is controlled by the HP Server Automation security framework.
- **Auditing:** Logins and commands on managed servers are recorded in audit log files.
- **Re-use of existing scripts:** Existing native scripts can run on managed servers with the `rosh` utility. For example, you can run `.BAT`, `.vbs`, and `.sh` scripts on managed servers. Scripts written in Unix shells will run within the Global Shell, which supports `bash`, `csch`, and other common shells.
- **Routine maintenance tasks on multiple servers:** By accessing the global view of the OGFS, system administration scripts can run iteratively on groups of servers.
- **Access to the HP Server Automation data model:** Global shell scripts can access information about managed servers, including custom attributes.

Commands Available in the Global Shell

The Global Shell offers the following types of Unix shells:

```
bash (default)
csh
ksh
sh
tcsh
```

Many common Unix commands (too numerous to list here) are available within the Global Shell. To display these commands, in a Global Shell session, list (ls) the contents of the following directories:

```
/bin /usr/bin
/opsw/bin
```

The /opsw/bin directory contains utilities (such as rosh) which are specific to SA. For more information, see [Global Shell Utilities Syntax](#) on page 363.

Differences Between the Global Shell and Unix Shells

The Global Shell is different from native Unix shells in the following ways:

- **Restricted command set:** Some Unix commands (such as cron) are unavailable in the Global Shell. To find out if a command is available, use the which command.
- **Limited recursion:** Commands cannot use recursion with the file systems of managed servers. Examples of recursive commands are find, ls -r, and rm -r.
- **SA user:** You log on to the Global Shell as an SA user, not as a Unix user.
- **SA permissions:** The operations that you can perform and the servers that you can access are limited by the SA permissions of your SA user group.
- **Private directories:** The following directories are accessible only by your SA user:

```
/tmp
/var/tmp
/usr/tmp
```

For example, the /tmp directory seen by the jdoe SA user is different than the /tmp seen by tjones.

- **SA data model in the OGFS:** Stored in the Model Repository, the data model consists of objects such as customers, facilities, and servers. End users manipulate these objects with the SA Client. The OGFS represents the data model in a file system that resembles a Unix file system. Changes to the data model appear as changes in the OGFS, and vice versa.
- **Axis (@) symbol in directory names:** In the OGFS, for example, this symbol appears in the following directories:

```
/opsw/Server/@
/opsw/Server/@Group
/opsw/Group/Public/group-name/@
```

The axis (@) symbol represents the end of the filtering criteria for managed servers.


Server Filtering in the OGFS

As you navigate down the OGFS tree, the path grows longer and more specific as fewer servers are visible in the `Server` directory. In the OGFS, the `/opsw` directory contains subdirectories for several types of objects in the SA model space, such as `Server`, `Group`, `Facility`, `OS`, `Application`, `Customer`, and so on.

In the Global Shell interface, you can filter your view of these object types in the `Server` directory by specifying an axis (`@`) in the path. A path in the SA model space can be a list of filtering criteria that selects objects of a given type. This path begins with the desired object type, such as `/Server`, and each filtering criteria begins with an `@`, such as `@Customer`. An ending `@` denotes the end of the filtering criteria.

[Figure 102](#) is graphical representation of related objects (customers and facilities) in a hierarchical `Server` directory. The small boxes represent managed servers. Examples of ways that you can filter this directory immediately follow the diagram.

Figure 102 Filtering in the Server Directory



Based on [Figure 102](#), the following examples illustrate ways to narrow your search for servers:

- To find all 16 servers, specify the following path:

```
ls /opsw/Server/@
```
- To find servers in the Atlanta facility, specify the following path:

```
ls /opsw/Server/@Facility/Atlanta/@
```
- To find servers that belong to customer Alpha, specify the following path:

```
$ ls /opsw/Server/@Customer/Alpha/@
```
- To find servers in the Atlanta facility that belong to customer Alpha, specify either of the following paths:

```
ls /opsw/Server/@Facility/Atlanta/@Customer/Alpha/@
```

```
ls /opsw/Server/@Customer/Alpha/@Facility/Atlanta/@
```

The following paths are filtered away by the OGFS, because they would yield a dead-end. There are no servers belonging to customer Gamma in the Atlanta facility.

```
ls /opsw/Server/@Facility/Atlanta/@Customer/Gamma/@  
ls /opsw/Server/@Customer/Gamma/@Facility/Atlanta/@
```



This same filtering logic can be applied to @Realm, @Group, and @Application.

Global Shell Tutorial

This tutorial covers just a few of the highlights of the OGFS and the Global Shell. After completing this tutorial, you will know how to navigate the directories of the OGFS and how to run commands on managed servers from within the Global Shell. Although the tutorial is organized into steps, after performing step 1, you can perform the remaining steps in any order.

Before starting the tutorial, you need the following capabilities:

- You can log on to the SA Client. As you work through this tutorial, you might find it helpful to compare the stdout of the Global Shell with information displayed by the SA Client.
- Your SA user has Read & Write permissions on at least one managed server. Typically assigned by a security administrator, permissions are discussed in the *SA Administration Guide*.
- Your SA user has all Global Shell permissions on the same managed server. For information on these permissions, see [aaa Utility](#) on page 363.

The example commands in this tutorial operate on a Windows server named `abc.opsware.com`. This server belongs to a device group named All Windows Servers. When trying out these commands, substitute `abc.opsware.com` with the host name of the managed server you have permission to access. Also, replace `jdoh` with your SA user name. If you wish to run the commands on a Unix managed server, replace `ipconfig` with `ifconfig`; and replace `Administrator` with `root`.

Now, let's get started with the tutorial:

- 1 Open a Global Shell session.

You can open a Global Shell session from within the SA Client. From the **Tools** menu, select **Global Shell**. You can also open a Global Shell session from a terminal client running on your desk top. For instructions, see [Opening a Global Shell Session](#) on page 289.

- 2 Check your session.

First, enter the `whoami` command, which displays the SA user name for this session:

```
$ whoami  
jdoh
```

You can enter the `ps` command to view the process status of your Global Shell session. The following `ps` command shows the session is running the default bash shell:

```
$ ps
PID TTY          TIME CMD
 7033 ?            00:00:00 bash
13712 ?            00:00:00 ps
```

Enter the `uname` command, which displays information about the server running the OGFS component of SA:

```
$ uname -a
Linux m171.dev.opsware.com 2.4.21-32.ELsmp #1 SMP Fri Apr 15 21:17:59 EDT
20 05 i686 GNU/Linux
```

If you log on to a Unix managed server with `rosh`, `uname` displays information about that managed server, not the server running the OGFS component. Run the `uname` command when you are not sure if you are interacting with the Global Shell or with the shell of a managed server accessed with `rosh`.

3 Confirm your home directory.

Every SA user has a home directory in the OGFS. The home directory has a `public/bin` subdirectory where you can store scripts to be executed by other users running Global Shell sessions. Each SA user also has a personal `/tmp` directory for temporary files. You cannot view or modify the `/tmp` directories of other users.

The following commands show some information about the directories of the `jdoue` user:

```
$ cd
$ pwd
/home/jdoe
$ ls -ld /home/jdoe/public/bin
drwxr-xr-x 2 jdoe jdoe 4096 2006-05-17 17:12 /home/jdoe/
public/bin
$ ls -ld /tmp
drwxrwxrwx 3 root root 4096 2006-06-09 23:37 /tmp
```

4 List all managed servers.

The `/opsw/Server` directory of the OGFS contains information about the servers managed by SA. This directory is an example of how the OGFS represents objects (in this case servers) of the SAdata model. Behind the scenes, SA stores this information in a database referred to as the Model Repository.

To view the names of the servers managed by SA, enter the following command:

```
$ ls /opsw/Server/@
abc.opsware.com      m33.opsware.com      gist.opsware.com
pal.opsware.com      hare.opsware.com      qv55.opsware.com
. . .
```

5 Examine server information.

Each managed server has a directory structure containing information about that server. The `attr` subdirectory contains text files that describe the server's attributes. The attribute name matches the file name and the attribute value is the file contents. The following `cat` command lists the OS version of the managed server named `abc.opsware.com`:

```
$ cd /opsw/Server/@/abc.opsware.com
$ cat attr/osVersion
Microsoft Windows 2000 Advanced Server Service Pack 4 Build 2195
(05-02-2006)
```

The Interface subdirectory has information about the server's network interfaces. Here's an example:

```
$ cat "Interface/Local Area Connection/info"
AdminEnabledFlg: no
CardIndex:
CardSerialNum:
CircuitId:
Collisions:
ConfiguredDuplex: AUTO
ConfiguredSpeed: AUTO
. . .
```

6 List the files of a managed server.

In addition to information about managed servers, `/opsw/Server` contains directories that correspond to the file systems of those servers. If you have the necessary permissions, in a Global Shell session you can access multiple servers from a single virtual file system, the OGFS.

The following command navigates to file system of the `abc.opsware.com` server:

```
$ cd /opsw/Server/@/abc.opsware.com/files
```

The next `ls` command displays OGFS subdirectories that correspond to native users of the managed server. Your security administrator specified these users (login names) when adding OGFS permissions. These are not SA users.

```
$ ls
Administrator LocalSystem
```

Native users might have different views of the managed server's file system. Therefore, under each user, the OGFS presents different file systems for each user. The following `cd` command drills down to the `Program Files` directory as seen by the Administrator user on the Windows server.

```
$ cd "Administrator/C/Program Files"
$ pwd
/opsw/Server/@/abc.opsware.com/files/Administrator/C/Program Files
```

Next, list the files in the `Program Files` directory:

```
$ ls -l
Accessories
Common Files
ComPlus Applications
Internet Explorer
Messenger
. . .
```

Although these files reside in a directory on the managed server's file system, you are in the OGFS, as shown by the preceding `pwd` command. To verify that you are in a Global Shell session (and not in a session running on the managed server), enter the following commands:

```
$ whoami jdoe
$ uname -a
Linux m171.dev.opsware.com 2.4.21-32.ELsmp #1 SMP Fri Apr 15 21:17:59 EDT
2005 i686 GNU/Linux
```

7 Copy a file from the OGFS to a managed server.

By entering the `cd` command, go to your home directory in the OGFS, for example:

```
$ cd
$ pwd
/home/jdoe
```

Next, create a simple text file in your home directory:

```
$ echo "this is text" > myfile.txt
$ cat myfile.txt
this is text
```

Copy the file that you just created to a directory in the file system of a managed server. The following command copies `myfile.txt` to the `C:\temp` directory of the `abc.opsware.com` server:

```
$ cp myfile.txt \
/opsw/Server/@/abc.opsware.com\
/files/Administrator/C/temp/afile.txt
```

Do not copy large files between the OGFS and managed servers. Copy only small files, such as configuration files.

8 Log on to a managed server with `rosh`.

In the preceding steps, you accessed the file system of a managed server from within a Global Shell session. In this step, from the Global Shell you log on to a managed server with `rosh`. After you log in, you interact with the command-line environment (MSDOS or Unix shell) of the managed server.

The following `rosh` command logs in as Administrator to a Windows managed server named `abc.opsware.com`:

```
$ cd /opsw/Server/@/abc.opsware.com
$ rosh -l Administrator
Microsoft Windows 2000 [Version 5.00.2195]
(C) Copyright 1985-2000 Microsoft Corp.
```

The prompt indicates that you are now in the command-line environment of the managed server. Enter the `ipconfig` and `hostname` commands:

```
C:\WINNT\system32>ipconfig
ipconfig
```

```
Windows 2000 IP Configuration
```

```
Ethernet adapter Local Area Connection:
```

```
Connection-specific DNS Suffix . : opsware.com
IP Address. . . . . : 192.168.8.217
Subnet Mask . . . . . : 255.255.254.0
Default Gateway . . . . . : 192.168.8.1
```

```
C:\WINNT\system32>hostname
hostname
abc
```

Terminate the remote login with the `exit` command:

```
C:\WINNT\system32>exit
```

Enter the `uname` command to verify that you have returned to the Global Shell session:

```
$ uname -a
```

9 Create a script that runs across servers.

A Global Shell script can iterate within the OGFS and run the `rosh` command to execute native commands on multiple servers. The example script shown in this step iterates through the servers of the public device group named All Windows Servers. On each server, the script runs the `ipconfig` command with the `rosh` command. In this example, substitute your SA user name for `jdoue`.

First, return to your home directory in the OGFS:

```
$ cd
$ cd public/bin
$ pwd
/home/jdoue/public/bin
```

Next, run the `vi` editor:

```
$ vi
```

In `vi`, insert the following lines to create a bash script:

```
#!/bin/bash
# This is simple_iterate.sh.
# Change jdoue to your user name.

OUTFILE="/home/jdoue/public/bin/ipconfig_all.txt"
rm -f $OUTFILE

cd "/opsw/Group/Public/All Windows Servers/@/Server"

for SERVER_NAME in *
do
    echo ---- $SERVER_NAME
    echo ---- $SERVER_NAME >> $OUTFILE
    rosh -n $SERVER_NAME -l Administrator \
        "ipconfig" >> $OUTFILE
done
# Last line in simple_iterate.sh.
```

Save the file in `vi`, naming it `simple_iterate.sh`. Quit `vi`.

Change the permissions of `simple_iterate.sh` with `chmod`, and then run it:

```
$ chmod 755 simple_iterate.sh
$ ./simple_iterate.sh
---- abc.opsware.com
---- gist.opsware.com
---- hare.opsware.com
---- m33.opsware.com
. . .
```

As the script runs, it echoes the name of each server to `stdout`, and redirects the output of the `ipconfig` command to the `ipconfig_all.txt` file. Enter the `more` command to view the contents of `ipconfig_all.txt`:

```
$ more ipconfig_all.txt
---- abc.opsware.com
Windows 2000 IP Configuration
Ethernet adapter Local Area Connection: . . .
```


10 Learn more.

Here are a few suggested tasks for learning more about the OGFS and the Global Shell:

- Explore the folders and contents under `/opsw/Library`, comparing them with the Library windows of the SA Client.
- If you have NA installed, navigate to the `/opsw/Net*` (network) directories. For descriptions of these directories, see [Network Directories](#) on page 384.
- On Windows servers, examine the `registry` and `complus` directories under `/opsw/Server/@/server-name`.
- List the files in the `method` directory, also under `/opsw/Server/@/server-name`. These files are the executables of the SA Command-Line Interface (OCLI), which enables you to perform SA functions from within the Global Shell. To learn how to run the CLI methods, see the *SA Platform Developer Guide*.

Global Shell Examples

The examples in this section use `bash`, the default shell of a Global Shell session. These are relatively simple examples. For more complex examples, including those with method invocations and search filters, see the *SA Platform Developer Guide*.

Opening a Global Shell Session

You can open a Global Shell session with an `ssh` client or from within the SA Client. When you open a session, the working directory is `/home/user-name`.

To open a Global Shell session with an `ssh` client, perform the following steps:

- 1 On a host that is not an SA core server or a managed server, open a terminal window.
- 2 In the terminal window, enter an `ssh` command with the following syntax:

```
ssh -p 2222 user-name@ogfs-host
```

To use this command, port 2222 must be open on the firewall that protects the OGFS server. The `user-name` is your SA user (login) and the `ogfs-host` is the host name (or IP address) of the core server running the OGFS. The SA user name is not case sensitive. After you enter the `ssh` command, the OGFS prompts for the password of the SA user.

To open a Global Shell session from within the SA Client, from the **Actions** menu, select **Global Shell**.

Finding Servers in the OGFS

List the names of all servers that you can manage with SA:

```
ls /opsw/Server/@
```

List the IDs of the servers:

```
ls -a /opsw/.Server.ID
```

Find all servers in the `.opsware.com` domain by specifying the wildcard character (`*`):

```
ls -d /opsw/Server/@/* .opsware.com
```

List all servers in the Atlanta facility:

```
ls /opsw/Server/@Facility/Atlanta/@
```

List the servers in the public device group named Alpha:

```
ls /opsw/Group/Public/Alpha/@/Server
```

List the servers in the All Windows Servers group, first with backslashes to escape the spaces in the group name, then by enclosing the option in single quotes:

```
ls /opsw/Group/Public/All\ Windows\ Servers/@/Server
ls '/opsw/Group/Public/All Windows Servers/@/Server'
```

List the servers of the Widget customer:

```
ls /opsw/Customer/Widget@/Server
```

The following two commands display the same output, the servers in the Atlanta facility that belong to the Green customer:

```
ls /opsw/Server/@Facility/Atlanta/@Customer/Green/@
ls /opsw/Server/@Customer/Green/@Facility/Atlanta/@
```

Getting Server Information from the OGFS

List the Object ID and of the server named `m256.opsware.com`:

```
cd /opsw/Server/@/m256.opsware.com
cat self:i ; echo
```

(The preceding `echo` command is optional. It generates a new line character, which makes the output easier to read. The semicolon separates bash statements entered on the same line.)

List the name of the server with an Object ID of 340039:

```
cat /opsw/.Server.ID/340039/self
```

By iterating through the server names with a `for` loop in bash, display the platform (operating system) name for each server:

```
cd /opsw/Server/@
for SERVER_NAME in *
do
    cat $SERVER_NAME/attr/platform
done
```

Display the amount of RAM in the server named `abc.opsware.com`:

```
cd /opsw/Server/@/abc.opsware.com
grep Quantity Memory/RAM/info
```

Display the network interfaces of a the server named `blizzard.opsware.com`:

```
cd /opsw/Server/@/glengarriff.snv1.dev.opsware.com/Interface
for INTERFACE_NAME in *
do
    echo ..... $INTERFACE_NAME .....
    grep Interface "$INTERFACE_NAME/info"
    echo ""
done
```

Browsing a Server's File System or Registry

List all of the files the C:\ Program Files directory of the Windows server named abc.opsware.com:

```
cd /opsw/Server/@/abc.opsware.com/files/Administrator
ls C/Program\ Files
```

List the registry keys of the abc.opsware.com server:

```
cd /opsw/Server/@/abc.opsware.com/registry/\ Administrator/
ls *
```

List the contents of the /var directory on the Unix server named m256.opsware.com:

```
/opsw/Server/@/m256.opsware.com/files/root
ls var
```

Managing Custom Attributes

On the server abc.opsware.com, create a custom attribute named MyGreeting with the value hello there:

```
cd /opsw/Server/@/abc.opsware.com/CustAttr
echo -n "hello there" > MyGreeting
cat MyGreeting
```

Execute runit.bat on the abc.opsware.com server, passing the value of the My Test custom attribute as a command-line parameter for runit.bat:

```
cd /opsw/Server/@/abc.opsware.com
TESTPARAM=`cat CustAttr/"My Test"`
rosh -l Administrator "C:\temp\runit.bat $TESTPARAM"
```

When you create or edit custom attributes within the OGFS, HP Server Automation preserves leading and trailing white space characters in custom attribute values.

Copying Files Within the OGFS

Do not use the techniques in this section to copy large files. The OGFS is not designed distribute large amounts of data. However, you can use these techniques for copying small files (such as configuration files) to and from managed servers.

Copy myfile.txt from the home directory in the OGFS of the jdoe user to the C:\temp directory of the Windows server named abc.opsware.com:

```
cp /home/jdoe/myfile.txt \
/opsw/Server/@/abc.opsware.com/files/Administrator/C/temp
```

Copy myfile.txt from the home directory in the OGFS of the jdoe user to the /tmp directory of the Unix server named m25.opsware.com6:

```
cp /home/jdoe/myfile.txt \
/opsw/Server/@/m256.opsware.com/files/root/tmp
```

Copy the C:\temp\myfile.txt file from the abc.opsware.com server to the m344.opsware.com server:

```
cp /opsw/Server/@/abc.opsware.com/files/\
Administrator/C/temp/myfile.txt \
```

```
/opsw/Server/@/m344.opsware.com/files/\
Administrator/C/temp/myfile.txt
```

Copying Files Between the OGFS and a Development Server

You can securely copy files between the OGFS and a server that is not part of HP Server Automation. To copy the files, perform the following steps:

- 1 On a host that is not an SA core server or a managed server, open a terminal window.
- 2 In the terminal window, enter either the `scp`, `sftp`, or `rsync` command and specify port 2222, your SA user name, and the host running the OGFS.

The following three `scp` examples perform the same operation: They copy the file `myscript.sh` from the local machine to the file `/home/jdoe/myscript.sh` in the OGFS. The SA user is `jdoe` and the host running the OGFS is `192.168.166.178`.

```
scp -P 2222 myscript.sh jdoe@192.168.166.178:myscript.sh
scp -P 2222 myscript.sh jdoe@192.168.166.178:/home/jdoe
scp -P 2222 myscript.sh jdoe@192.168.166.178:
```

The following example copies `myscript.sh` from the home directory of `jdoe` in the OGFS to the local machine:

```
scp -P 2222 jdoe@192.168.166.178:myscript.sh myscript.sh
```

The following `sftp` example copies `myscript.sh` from the local machine to the OGFS:

```
sftp -oPort=2222 jdoe@192.168.166.178
Connecting to 192.168.166.178...
```

```
Global Shell
```

```
jdoe@opsware's password:
sftp> put myscript.sh
```

```
. . . .
```

The following `rsync` example transfers files from `/path` on the local machine to `/other/path` in the OGFS:

```
rsync -av -e "ssh -p 2222" /path \
jdoe@192.168.166.178:/other/path
```

Logging on to a Managed Server With `rosh`

The next three `rosh` commands perform the same operation: logging on to the Windows server named `abc.opsware.com` as the Administrator user. After logging on, the current working directory on the remote shell is the default working directory of the Administrator Windows user. These `rosh` commands require different options, depending on the current working directory in the OGFS. For example, the first `rosh` command does not require the `-n` (server name) and `-l` (user) options because the option values can be inferred from the current working directory of OGFS. The options of the following three `rosh` commands differ because of the current working directory:

```
cd /opsw/Server/@/abc.opsware.com/files/Administrator
rosh
. . .
exit
. . .
```

```

cd /opsw/Server/@/abc.opsware.com
rosh -l Administrator
...
exit
. . .
cd /home/jdoe
rosh -n abc.opsware.com -l Administrator
...
exit

```

The next rosh command logs into the Unix server named `m256.opsware.com` as the root user with the current working directory of `/tmp`:

```
rosh -n m256.opsware.com -l root -d /tmp
```

Running OGFS Scripts on Managed Servers With rosh

The next sequence of commands create a `.BAT` script in the OGFS and then run the script on a Windows managed server. Created with `echo` statements, the `myfile.bat` script resides in the OGFS under `/home/jdoe/public/bin`. (Note that `myfile.bat` does not reside in the file system of the managed server.) The `myfile.bat` script contains three commands: `ipconfig`, `cd`, and `dir`. The rosh command runs `myfile.bat` on the server named `abc.opsware.com` as the Administrator Windows user. The following commands create a local `.BAT` script and run it remotely with rosh:

```

cd /home/jdoe/public/bin

echo ipconfig > myfile.bat
echo "cd c:\temp" >> myfile.bat
echo dir >> myfile.bat

rosh -n abc.opsware.com -l Administrator -s ./myfile.bat

```

Create a script named `who.sh` in the `/home/jdoe/public/bin` directory of the OGFS and then run `who.sh` on the server named `m256.opsware.com`:

```

cd /home/jdoe/public/bin

echo \#\!\\bin\sh > who.sh
echo "uname -n" >> who.sh
echo id >> who.sh
echo pwd >> who.sh

rosh -n m256.opsware.com -l root -s ./who.sh

```

Running Native Programs on Managed Servers With rosh

The next two rosh commands run the `dir` and `ipconfig` MSDOS commands on the Windows server named `abc.opsware.com`. Note that the native MSDOS commands are enclosed in quotes. Because the server name and user (login) can be inferred from the current working directory, the first rosh command omits the `-n` and `-l` options, as shown in the following code:

```

cd /opsw/Server/@/abc.opsware.com/files/Administrator
rosh "dir & ipconfig"
. . .
cd /home/jdoe

```

```
rosh -n abc.opsware.com -l Administrator "dir & ipconfig"
```

Run the `ipconfig` command on `abc.opsware.com` and redirect the output to a file in home directory of `jdoh` in the OGFS:

```
rosh -n abc.opsware.com -l Administrator "ipconfig" \  
> /home/jdoh/ipconfig_output.txt
```

On the Unix server named `m256.opsware.com`, run the `uname` and `ls` commands as root:

```
rosh -n m256.opsware.com -l root "uname -a; ls /tmp"
```

Within a for loop in bash, run the MSDOS `ipconfig` command on each server in the All Windows device group:

```
cd /opsw/Group/Public/All\ Windows\ Servers/@/Server  
  
for SERVER_NAME in *  
do  
    echo ..... $SERVER_NAME .....  
    rosh -n $SERVER_NAME -l Administrator "ipconfig"  
    echo ""  
done
```

Character Encoding for the OGFS

To support international environments, the OGFS can display information in different character encodings such as Shift-JIS (Japanese) and EUC-KR (Korean). You can control the encoding of Global Sessions in the following ways:

- To specify the encoding of your Global Shell sessions, in the Terminal and Shell Preferences of the SA Client, select an item from the Encoding drop-down list.
- To change the encoding of an active Global Shell session, run the `swenc` command with the `-e` option.

If you change the encoding of an active session, you must also change the encoding of the terminal application for that session. This procedure varies according to the terminal application.

Terminal Application Configuration

The terminal application that is hosting a Global Shell or Remote Terminal session must be configured to use the same encoding expected by the session. If the encodings do not match, the data might be displayed incorrectly.

When the SA Client launches the terminal application, it composes the command specified by the Terminal Client field in the Terminal and Shell Preferences. If the Terminal Client field includes the `%e` substitution variable, the SA Client replaces `%e` with an encoding name. For Global Shell sessions, this encoding name is specified by the Encoding field of the Terminal and Shell Preferences. For Remote Terminal sessions, this encoding name is the value of the Encoding field in the Properties section of the Device Explorer. If the terminal application does not support the encoding that replaces the `%e` variable, or if the `%e` variable is not specified, you must change the encoding manually in the terminal application after it starts.

Data that Cannot Be Displayed

Data that cannot be displayed might be from a managed server (such as the contents of files) or it might be the name of an object in the SA model. If the session's encoding does not support the data to be displayed, the data often appears as question marks. (However, it might appear as other characters such as exclamation points.) The session attempts to display this data with the current encoding. Usually, this data cannot be accessed. To access this data, select a compatible encoding for the session.

Objects in the SA model, such as Facility and Server, appear as file names in the OGFS. If these file names contain characters that cannot be represented by the encoding of the session, they are displayed as question marks, appended by the Object ID of the object. In the following example, the IDs are 10002 and 11002:

```
New York
Paris
Montr?al~10002
??~11002
```

If the model object does not have an ID, such as a custom attribute, then the session attempts to display the name with the current encoding.

LANG and LC_CTYPE Environment Variables

Many Unix commands (such as `ls`) rely on the character encoding, which is determined by the `LANG` or `LC_CTYPE` environment variables. In a Global Session, if the encoding is changed with the `swenc` command, the system attempts to reset these variables.

HP Server Automation determines the new value of the `LANG` variable with the following process:

- 1 The value of `LANG` is generated by combining the language of the user's profile in the SA Web Client with the current session encoding. For example, if the language is English and the session encoding is UTF-8, `LANG` is set to `en_US.utf8`.
- 2 The value determined by the preceding step is compared with the set of valid locales on the OGFS server (according to the output of `locale -a`). If the value is a valid locale, `LANG` is set to this value.
- 3 If the value is not a valid locale, the system attempts to find a valid locale that specifies the user's language without the encoding. For example, if the user's language is English and the session encoding is EUC-JP, and this combination does not form a valid locale, `LANG` is set to `en_US`. If no matching locale is found, `LANG` is left unspecified.

The new value of the `LC_CTYPE` variable is determined in the following order:

- 1 HP Server Automation attempts to find a valid locale that matches the session encoding, regardless of the language.
- 2 If a valid locale is found, `LC_CTYPE` is set to this locale. For example, if the session encoding is EUC-JP, the `LC_CTYPE` variable is set to `ja_JP.eucjp`.
- 3 If no matching locale is found, `LC_CTYPE` is left unspecified.
- 4 If HP Server Automation cannot set the `LANG` or `LC_CTYPE` variables with the preceding process, you should set them manually.

Transcoded Data in a Managed Server

Transcoding is the conversion of data from one character encoding to another. HP Server Automation automatically transcodes some of the data between Global Shell sessions and other sources of data. For example, the file names of managed servers are transcoded, but the contents of the files are not. To see which data is transcoded, see [Table 25](#). To display the transcoding mode of the current Global Shell session, enter the `swenc` command with no options.

Table 25 Data Transcoded for Global Shell Sessions

Data	Transcoding
Objects in the SA model space, such as Facility, Customer, and Server. These objects are stored in the SA Model Repository (database) in UTF-8.	Between UTF-8 and the session encoding.
File and directory names of managed servers.	Between the managed server encoding and the session encoding.
Metadata of managed servers, such as user names and registry key names.	Between the managed server encoding and the session encoding.
File contents of managed servers.	None
Contents of Windows registries, services, COM objects, and IIS metabases.	None
rosh: Contents of saved scripts executed on managed servers (a rosh push operation).	None
rosh: Ad-hoc scripts executed on managed servers.	None
rosh: Command-line arguments to programs executed on managed servers.	None
rosh: Data streams (such as stdin and stdout) of programs executed on managed servers.	None
rosh: Data streams of rosh jump operations.	None
OGFS home, tmp, and var/tmp directories.	None

Disabling the Transcoding of Managed Server Data

On Unix servers, file and directory names can contain characters in arbitrary encodings. When accessed through the OGFS, file and directory names are transcoded by HP Server Automation. If the encoding of the names does not match the default encoding of the managed server, the transcoded data might be unusable.

You can disable transcoding with the `swenc` command. To turn transcoding on or off, use the `-T` option:

```
swenc -T {on | off}
```

If transcoding is disabled, file and directory names are passed unmodified from the managed servers. Therefore, you must manually configure the encoding of the terminal application to display the names correctly.

Windows servers store their file system data internally in the UTF-16 encoding. Because the encoding is known, transcoding is performed correctly and does not need to be disabled. Therefore, the `-T` option of the `swenc` command has no effect on Windows servers. For more information, see [swenc Syntax](#) on page 371.

Global Shell Error Messages

The Global Shell feature provides the file system error messages that are described in [Table 26](#).

Table 26 Global Shell Errors

Error	Description	Action
Input/output error	Your session has exceeded the time-out limit or the Agent is not running.	Start a new session or check the status of the Agent.
Operation not permitted.	No password was found.	Verify that you have a valid password.
Permission denied.	You are not allowed to view a directory. This does not mean that the directory does not exist on a given server. See the <i>SA Administration Guide</i> for more information.	Verify that you have <code>readFileSystem</code> permissions.
RFS Specific error	You do not have permissions on the managed server. For example, this error will occur if you are trying to perform an operation on a managed server and you do not belong to the Administrators group that has the required permissions assigned to it.	You must have a set of permissions to perform operations on managed servers. To obtain these permissions, contact your SA administrator. See the <i>SA Administration Guide</i> for more information.

Remote Terminal

With HP Server Automation, you can log on to a managed server in a terminal window in two ways:

- Using the Remote Terminal, as described here.
- The `rosh` command entered in a Global Shell session.

The remote terminal opens a terminal window for Unix servers or an RDP client window for Windows servers. Unlike a Global Shell session, a remote terminal session does not provide access to the OGFS.

You can specify your terminal and RDP client preferences for remote terminal and Global Shell sessions in the Set Preferences window. See [Terminal and Shell Options](#) on page 42 for more information.

Prerequisite for a Remote Terminal

Logging into a remote server requires that you have SA login permissions on the managed server. See the *SA Administration Guide* for more information. You cannot log into a remote terminal with a user name or password that contains multi-byte characters.

To open a remote terminal session on a Windows managed server running Windows Firewall, you must set an exception that is not enabled by default. On the managed server, run Windows Security Center, then select Windows Firewall † Exceptions † Remote Desktop.

This feature must be able to establish a loopback connection on the machine running the SA Client. Some firewall and VPN utilities have settings that prevent loopback connections.

Opening a Remote Terminal

In the Device Explorer of the SA Client, perform the following steps:

- 1 Select a managed server.
- 2 Open the managed server.
- 3 From the **Actions** menu, select **Remote Terminal**.

12 SA Command Line Interface (OCLI)

Overview of OCLI

The SA Command Line Interface (OCLI) consists of two tools:

- `oupload` – Uploads files into the Software Repository
- `odownload` – Downloads files from the Software Repository

These commands help to automate the setup tasks for package management in HP Server Automation. For a list of supported package types, see the *SA User Guide: Software Management*.

OCLI runs on a server managed by SA. The operating system of this server can be one of the following: Oracle Sun Solaris, Linux, IBM AIX, HP-UX, and Microsoft Windows Server 2003, 2008 or 2008 R2 x64.

Permissions and Customers

When installing OCLI, you download the OCLI package to a managed server. To perform this download, you must have read permission on the customer named Opsware. To run `oupload` or `odownload`, you must have permissions on the customer associated with the server where you run OCLI. For more information on permissions, see the *SA Administration Guide*.

For `oupload`, you must have read permission on the customer associated with the server where you run OCLI. For `odownload`, you need write permission on this customer.

You can only upload or download packages for the customer associated with the server from which you are running the OCLI. Contact your SA Administrator to obtain the necessary access rights. If you must upload or download a package for a different customer, use the SA Client to change the customer association for the server. See [Information About Servers](#) on page 71 for more information about editing the properties of a server.

Servers cannot be associated with Customer Independent; therefore, if you need to upload a package associated with Customer Independent, you must upload it from a server associated with the SA customer. Associating a server with the SA customer can be a security issue; therefore, you should control the access to this server while it is associated with the SA customer.

Upload Verification

After you upload a package with OCLI, verify that the upload has been successful by locating the package with the SA Client. Typically, you add the uploaded package to a folder or a policy.

Encoding Options for OCLI

The `oupload` and `odownload` commands include options for specifying the encoding scheme of packages or customer display names. These options are required only when you want to override the default setting in the `LANG` environment variable of your shell.

RPM Uploads

For RPM packages, always remember to upload the source files after uploading a package. Uploading the source files is important from a maintenance perspective because it allows users to modify packages at a later date.

Passwords and Environment Variables

The `oupload` and `odownload` commands prompt for the SA user name and password when needed. Alternatively, you can set the `ISMTOOLUSERNAME` and `ISMTOOLPASSWORD` environment variables.

The `'ocli.conf'` configuration file located at the root of the OCLI installation can be edited to set a OCLI username and password for connecting to SA. If you provide username and password in the `ocli.conf` file, then the password will be encrypted in the file after the first run of the `oupload` or `odownload` command.

Upload Examples

To upload `mytoolkit.rpm` into the `/Kit Apps/Services` folder, enter the following command on a single line:

```
$ oupload --pkgtype RPM --os "Red Hat Enterprise Linux AS 3"
--folder "/Kit Apps/Services" mytoolkit.rpm
```

To upload `iPlanet_Web_Server-4.1sp19-LC~0.sparc64.rpm` for the customer Opsware and the operating system Solaris 5.11, enter the following command on a single line:

```
$ <installation_directory>/bin/oupload --pkgtype RPM --old --customer Opsware
--os "SunOS 5.11" iPlanet_Web_Server-4.1sp19-LC~0.sparc64.rpm
```

Be sure to enclose values containing spaces, such as `SunOS 5.11`, in quotes.

Installing the SA Command-line Interface (OCLI)

The SA Command-line Interface (OCLI) is shipped as a package in the Software Repository of SA. You can install and use the OCLI on Windows and Unix machines.

After you install the OCLI package, you can use the new `oupload` and `odownload` commands available to move software between a managed server and the Software Repository.



You must install the Server Agent and OCLI package on the host from where you will run OCLI.

To install the OCLI package:

- 1 Install a Server Agent on the managed server where you will run OCLI.
See [Installing and Managing Server Agents](#) on page 123 for instructions on how to install a Server Agent or download a package from the SA Web Client.
- 2 Verify that you have the required permissions.
For more information about permissions, see [Permissions and Customers](#) on page 299.
- 3 In the SA Client, search for the OCLI package that matches the platform of the managed server where you will run OCLI.
The file name of the package begins with `ocli`. The remainder of the name matches the version of OCLI and the operating system of the managed server, for example:
`ocli-32.1.1.6-win32-5.2.exe`.
- 4 In the SA Client, export the OCLI package to your local file system.
- 5 Copy the OCLI package from your file system to the host where you will run OCLI.
Perform the following steps, which vary by operating system:

For Unix

- a The file downloads as a non-executable file. Change the file mode to executable.
- b Execute the package as root by entering the following command:

```
<package_name> -d <installation_directory>
```

Specifying the installation directory is optional. By default, OCLI is installed in the current directory. No other steps to setup the environment are necessary.



For all UNIX, the `upload` and `odownload` scripts are invoked from the `/bin` directory.

For Windows

- a Execute the package as Administrator.
- b Launch a command window and enter the following command at the prompt:
- c In the command window, enter the following command on a single line:

```
<package_name> -d <installation_directory>
```

```
set PATH=%PATH%;<installation.dir>\ocli\scripts
```

```
set PATH=%PATH%;%SYSTEMDRIVE%\Program Files\Opsware\Agent\lcpython15
```

OCLI Command Syntax

The `oupload` and `odownload` commands have the following syntax. The *filenames* and *localpath* can contain a relative or absolute local file or directory path. If an option value contains spaces, enclose the value in quotes.

```
oupload [options] filenames
```

```
odownload [options] filenames localpath
```



When using the SA Command-line Interface (OCLI) on a UNIX server, the `oupload` and `odownload` scripts are invoked from the `/bin` directory:

```
<ocli_installation_directory>/bin/oupload.sh
```

```
<ocli_installation_directory>/bin/odownload.sh
```

Options Common to `oupload` and `odownload`

Table 27 Options Common to Both Commands

arguments	values	description
<code>--customer (-C)</code> <code><value></code>	String (customer name, wildcards accepted) or integer (customer ID)	<p>Specifies the customer of the file.</p> <p>Do not use the <code>--customer</code> option with the <code>--folder</code> option. To use <code>--customer</code>, the <code>--old</code> option is also required.</p> <p>If you specify <code>--old</code>, specifying <code>--customer</code> is required unless you are using <code>--patchtype</code> in <code>oupload</code>.</p> <p>When you upload an AIX LPP file, or an HP-UX Depot that contains patches, it is associated with “Customer Independent” and this option is ignored.</p> <p>When you upload an AIX Maintenance Level set of LPPs, you must associate them with “Customer Independent” so that all base filesets and update filesets contained in it are associated with the same customer.</p>
<code>--feedback (-Q)</code>	N/A	<p>Displays feedback while the command runs. By default, this option is enabled.</p> <p>Cannot specify this option with <code>-q</code></p>

Table 27 Options Common to Both Commands (cont'd)

arguments	values	description
<code>--forceoverwrite</code>	N/A	<p>This option forces like files to be overwritten.</p> <p>When used for oupload, if the file already exists in SA, it will be overwritten by the file being uploaded.</p> <p>When used for odownload, if the file already exists locally, it will be overwritten by the file being downloaded. In both cases, no input is required.</p>
<code>--forcenooverwrite</code>	N/A	<p>This option prevents like files from being overwritten.</p> <p>When used for oupload, if the file already exists in SA, the upload operation will be cancelled and the file will not be overwritten.</p> <p>When used for odownload, if the file already exists locally, the download operation will be cancelled and the file will not be overwritten.</p> <p>In both cases, no input is required.</p> <p>Note: If there are multiple files for upload/download and the forcenooverwrite option is given, the files that already exist will be skipped. the operation itself will not be canceled.</p>
<code>--fr (-f) <value></code>	<ul style="list-style-type: none"> • Alphanumeric • Period • Hyphen • Default = theword 	Specifies the host name or IP address of the Software Repository.
<code>--frport (-F) <port></code>	<p>Integer</p> <p>Default = 1003</p>	Specifies the port of the Software Repository.
<code>--fullhelp (-H)</code>	N/A	<p>Displays full help information.</p> <p>Cannot specify this option with <code>-h</code> or <code>-v</code></p>
<code>--help (-h)</code>	N/A	<p>Displays abbreviated help information.</p> <p>Cannot specify this option with <code>-H</code> or <code>-v</code></p>

Table 27 Options Common to Both Commands (cont'd)

arguments	values	description
<code>--nofeedback (-q)</code>	N/A	Does not display feedback while the command runs. Cannot specify this option with <code>-Q</code>
<code>--os (-O) <type></code>	String (OS name, wild cards accepted) See Allowable OS Name Strings and Integer Values for --os Option on page 305 in this chapter for more information	Specifies the operating system of the package. Specifying this option is required. If a value has a space in the name, enclose the entire name in quotes. For Fujitsu Solaris 2.8, use the value for Solaris 8. For Fujitsu Solaris 2.9, use the value for Solaris 9.
<code>--timeout (-z) <value></code>	Integer Default = 60	Sets the timeout to the server in seconds.
<code>--truthgw (-g) <value></code>	<ul style="list-style-type: none"> • Alphanumeric • Period • Hyphen • Default = spin 	Specifies the host name or IP address of the Data Access Engine.
<code>--truthgwport (-G) <port></code>	Integer Default = 1004	Specifies the port of the Data Access Engine.
<code>--verbose (-v)</code>	N/A	Displays debug information.
<code>--version (-V)</code>	N/A	Displays version information for the OCLI. Cannot specify this option with <code>-h</code> or <code>-H</code> .

Valid Strings and Integer Values for the --os Option

Table 28 Allowable OS Name Strings and Integer Values for --os Option

OS Name (String)	Internal ID (Integer)
AIX 6.1	120076
AIX 7.1	120077
CentOS 5	20076
CentOS 5 x86_64	50076
CentOS 6	50200
CentOS 6x86_64	50201
Citrix XenServer 5	100035
Citrix XenServer 6	100036
HP-UX 11.11	1080007
HP-UX 11.23	40774
HP-UX 11.31	40039
Oracle Enterprise Linux 5	180076
Oracle Enterprise Linux 5 x86_64	190076
Oracle Linux 6	180077
Oracle Linux 6 x86_64	190077
Red Hat Enterprise Linux Desktop 5	20056
Red Hat Enterprise Linux Desktop 5 x86_64	30056
Red Hat Enterprise Linux Server 5	10028
Red Hat Enterprise Linux Server 5 IA64	140076
Red Hat Enterprise Linux 5 PC64	230076
Red Hat Enterprise Linux 5 S390X	230078
Red Hat Enterprise Linux 5 x86_64	20028
Red Hat Enterprise Linux Client 6	170095
Red Hat Enterprise Linux Client 6	170096
Red Hat Enterprise Linux Server 6	10029
Red Hat Enterprise Linux Server 6 PPC64	70029
Red Hat Enterprise Linux Server 6 S390X	80029
Red Hat Enterprise Linux Server 6 x86_64	60029
Red Hat Enterprise Linux Workstation 6	170094
Red Hat Enterprise Linux Workstation 6 x86_64	170093

Table 28 Allowable OS Name Strings and Integer Values for --os Option (cont'd)

OS Name (String)	Internal ID (Integer)
SUSE Linux Enterprise Server 9	10100
SUSE Linux Enterprise Server 10	20100
SUSE Linux Enterprise Server 10 PPC64	90200
SUSE Linux Enterprise Server 10 S390X	90600
SUSE Linux Enterprise Server 10 x86_64	70100
SUSE Linux Enterprise Server 11	80100
SUSE Linux Enterprise Server 11 PPC64	90300
SUSE Linux Enterprise Server 11 S390X	90800
SUSE Linux Enterprise Server 11 x86_64	90100
SunOS 5.10	30007
SunOS 5.10 x86	10044
SunOS 5.11	427453
SunOS 5.11 x86	427452
VMware ESX Server 4	10096
VMware ESX Server 4.1	20096
VMware ESXi Server 3.5	30076
VMware ESXi Server 4	130076
VMware ESXi Server 4.1	130086
VMware ESXi Server 5	140086
VMware ESXi Server 5.1	150086
Windows Server 2003	10007
Windows Server 2003 x64	60100
Windows Server 2008	160076
Windows Server 2008 R2 x64	170092
Windows Server 2008 x64	170076
Windows Server 2012 x64	170099
Windows XP	10008

Table 29 Allowable Platform Family Name Strings and Integer Values for --os Option

Platform Family Name (String)	Internal ID (Integer)
OS Independent	1
UNIX	N/A
WINDOWS	N/A



Most of the package types in SA are not OS-agnostic (including ZIP packages). This is due to their path-like structures, such as the install path. As a result, using "OS Independent" as their platform is not recommended and might not be supported in future versions.

Options Only for the oupload Command

The following table lists options that apply only to the oupload command.

Table 30 Options Only for the oupload Command

arguments	values	description
<code>--filename-encoding (-e) <encoding></code>	String	Specifies the character set of the file name. See also Encoding Options for OCLI on page 300. When specifying non-ASCII characters in the value for the <code>--customer</code> argument, include the <code>-e</code> argument on the command line to tell HP Server Automation which character set to use when communicating with the Model Repository.
<code>--folder (-d) <folder-path></code>	String	Specifies the folder ID or folder path into which the package is uploaded. Wild cards in a folder path are allowed. For example, if the destination folder is <code>myfolder4pkgs</code> , you can specify <code>myfolder4*</code> . Do not specify <code>--folder</code> with <code>--customer</code> .
<code>--metainfo-encoding (-E) <encoding></code>	String	Specifies the character set of the meta-information in the package.
<code>--old (-o)</code>	N/A	Specifies that the operation behaves as in HP Server Automation 5.x. The file is not uploaded into a folder. The <code>--old</code> option is required if you specify <code>--customer</code> .

Table 30 Options Only for the oupload Command (cont'd)

arguments	values	description
--patchtype (-a) <type>	<ul style="list-style-type: none"> • AIX LPP • HP-UX Depot • Windows Hotfix • Windows Service Pack • Solaris Patch • Solaris Patch Cluster 	Cannot specify this option with -C.
--pkgtype (-t) <type>	<ul style="list-style-type: none"> • AIX LPP • HP-UX Depot • RPM • Windows Hotfix • Windows MSI • Windows Service Pack • Solaris Package • Solaris Patch • Solaris Patch Cluster • Microsoft Patch Database • OS Provisioning Install Hooks • ZIP 	<p>Specifies the type of file.</p> <p>Specifying either this option or the -patchtype option is required.</p> <p>Wildcards are accepted.</p> <p>The OCLI does <i>not</i> support uploading response files for the Solaris Package package type. Use SA Web Client to associate a response file with a Solaris Package.</p> <p>If a value contains spaces, you must enclose the value in quotation marks.</p>
-R<unit_id>	Integer	If a package with the same name already exists in the upload location, but it has different platforms assigned, you can use this option to replace the package specified by the <unit_id> along with the assigned platforms.

Options Only for the odownload Command

The following table lists options that apply only to the `odownload` command.

Table 31 Options Only for the odownload Command

argument	value	description
<code>--filename-encoding (-e)</code> <code><encoding></code>	String	Specifies the character set encoding in which to save the file name. See also Encoding Options for OCLI on page 300.

A Troubleshooting Server Communication Tests

This section describes the server communication tests in detail. For an overview, see [Running Server Communication Tests](#) on page 139.

The server communication test performs the following diagnostic tests to determine if a server is reachable:

- **Command Engine to Agent (AGT) Test:** Determines if the SA Command Engine can communicate with the agent. The Command Engine is the HP Server Automation core component that enables distributed programs to run across many servers. The Command Engine handles the storage and versioning of scripts into the SA Model Repository. SA stores scripts in the Model Repository.
- **Crypto Match (CRP) Test:** Checks that the SSL encryption files that the agent uses are valid.
- **Agent to Command Engine (CE) Test:** Verifies that the agent can connect to the Command Engine and retrieve a command for execution.
- **Agent to Data Access Engine (DAE) Test:** Checks whether or not the agent can connect to the Data Access Engine and retrieve its device record. The Data Access Engine provides an XML-RPC interface to the Model Repository that simplifies interaction with various clients such as the SA Web Client, system data collection, and monitoring agents on servers.
- **Agent to Software Repository (SWR) Test:** Determines if the agent can establish an SSL connection to the Software Repository. SA stores software in the Software Repository, including software packages for operating systems, applications, databases, customer code and software configuration information.
- **Machine ID Match (MID) Test:** Checks that the Machine ID (MID) on the server matches the MID registered in the Model Repository.

When the test run finishes, it returns results that show either success or failure for each test run on each server. For each failed test, the nature of failure is listed by error type in the error details column of the Communication Test window. In some cases, the failure of one test might prevent other tests from being executed.

See [Running Server Communication Tests](#) on page 139 for information about how to run a Communication Test.

Command Engine to Agent (AGT) Test

The Command Engine to Agent (AGT) communications test system checks that the Command Engine can initiate an SSL connection to the Agent and execute an XML/RPC request.

The thirteen possible results are:

- AGT – OK
- AGT – Untested
- AGT – Unexpected error
- AGT – Connection refused
- AGT – Connection time-out
- AGT – Request time-out
- AGT – Server never registered
- AGT – Realm is unreachable
- AGT – Tunnel setup error
- AGT – Gateway denied access
- AGT – Internal Gateway error
- AGT – Gateway could not connect to server
- AGT – Gateway time-out

AGT – OK

No troubleshooting necessary.

AGT – Untested

This result is returned when a functional area cannot be tested because of a previous failure that prevents further testing. For example, if the Command Engine cannot contact the Agent, then no other tests are possible.

What Can I Do If a Test Is Not Run During an AGT Test?

First resolve all tests that failed, and then run the Communication Test again.

AGT – Unexpected error

This result indicates that the test encountered an unexpected error.

What Can I Do If I Get an Unexpected Error?

First resolve all tests that failed, and then run the Communication Test again. If the unexpected error recurs, check to see if any additional details in the error message indicate the problem. If the error cannot be resolved, contact Hewlett Packard Customer Support.

AGT – Connection refused

This result indicates that the Command Engine is receiving a TCP reset packet when it attempts to connect to the Agent on port 1002. The likely cause is that the Agent is not running. A firewall might also be blocking the connection.

What Can I Do If the Connection is Refused During an AGT Test?

- 1 Log into the server and confirm that the Agent is running. See [Verifying that an Agent is Running](#) on page 332 in this appendix for more information.
- 2 If the Agent is not running, restart the Agent. See [Restarting a Server Agent](#) on page 333 in this appendix for more information.
- 3 From the managed server, use netstat to confirm that a socket is in listen mode on port 1002. If not, stop and restart the Agent.
- 4 From the server itself, use Telnet to connect to the IP address of the server where the Agent is installed and port (1002) that the Agent is listening on. If this does not succeed, stop and restart the Agent.
- 5 Verify that the Management IP address that HP Server Automation is using to reach the server is the correct address. See [Checking Management IP of a Managed Server](#) on page 333 in this appendix for more information. If the IP addresses do not match, stop and restart the Agent, then rerun the test.
- 6 If the previous steps are performed and the test still fails, the problem is likely caused by either a software-based firewall on the server itself or an external firewall blocking the connection.

AGT – Connection time-out

This result indicates that the Command Engine is not receiving any reply packets when it attempts to initiate a TCP connection to the Agent on port 1002. The likely cause is that the server is not running, or that the IP address that HP Server Automation is using to reach the Agent is incorrect. (A firewall might also be blocking the connection.) To check the IP address that HP Server Automation is using to reach the Agent, see [Checking Management IP of a Managed Server](#) on page 333.

What Can I Do If the Connection Times Out During an AGT Test?

Follow the same steps used to resolve this issue specified in [What Can I Do If the Connection is Refused During an AGT Test?](#) on page 313.

AGT – Request time-out

This result indicates that the Command Engine is able to successfully complete a TCP connection to the Agent on port 1002, but no response is received from the Agent in response to the XML-RPC request. The likely cause is that the Agent is hung.

What Can I Do If the Request Times Out During an AGT Test?

- 1 Log into the server and restart the Agent. See [Restarting a Server Agent](#) on page 333 in this appendix for more information.

- 2 Check to see whether or not some other process is consistently utilizing an excessive amount of the CPU on the server where the Agent is installed. Also check to see if the system is performing slowly due to a lack of available memory and/or excessive file IO. In any of these cases, the system might be performing too slowly to permit the Agent to respond to the test in a timely manner.

AGT – Server never registered

This test indicates that the server being tested has neither been registered with the Command Engine, nor can it communicate with the Command Engine. The cause of this could be any number of reasons similar to those in the [Agent to Command Engine \(CE\) Test](#) test. It is also possible (but unlikely) that the Agent was installed but never started.

What Can I Do If the Server Has Not Been Registered with the Command Engine During an AGT Test?

To troubleshoot this error, use the following procedures:

- 1 Ensure that the Agent is running. For these instructions, See [Verifying that an Agent is Running](#) on page 332 in this appendix for more information.
- 2 Ensure that the Agent can contact the Command Engine.
- 3 If the Agent is in a Satellite facility, ensure that its Gateways are properly configured and that it is properly configured to use those Gateways. See [Checking Network Gateway Configuration](#) on page 334 in this appendix for more information.
- 4 If the Agent is not in a Satellite:
 - Ensure the host name “way” (no quotes) resolves to its valid IP address. See [Resolving Host Name](#) on page 334 in this appendix for more information.
 - Verify that a connection can be established to port 1018 of way. Use the command “telnet way 1018” (or equivalent).

One (or more) of the above checks will fail. To solve that failure, refer to the corresponding error code for the [Agent to Command Engine \(CE\) Test](#) test on [page 317](#), or to the realm connectivity and configuration test.

AGT – Realm is unreachable

The Satellite realm where the managed server is located is unreachable. This means that a path of tunnels between the Gateways in the SA core and the realm of the managed server cannot be established.

What Can I Do If the Realm Is Unreachable During an AGT Test?

This error could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration. Contact Hewlett Packard Customer Support for assistance in troubleshooting the Gateway network.

AGT — Tunnel setup error

The Command Engine could not establish a connection through any of its defined Gateways. This could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration.

What Can I Do If I Get a Tunnel Setup Error During an AGT Test?

Contact your SA administrator.

AGT — Gateway denied access

The Gateway is working but refused to proxy the connection on behalf of the Agent. This error most likely means that the Gateway is misconfigured such that the Gateway will not allow the Command Engine access to the Agent.

What Can I Do If the Gateway is Denied Access During an AGT Test?

Contact your SA administrator.

AGT — Internal Gateway error

Due to an internal error, the Gateway was unable to proxy the connection. This typically occurs when the Gateway is overloaded.

What Can I Do If There is an Internal Gateway Error During an AGT Test?

Contact your SA administrator.

AGT — Gateway could not connect to server

The Gateway could not establish a connection to the Agent. This might be because the Agent is not running, or because a firewall might be blocking the connection.

What Can I Do If the Gateway Couldn't Connect to the Server During an AGT Test?

If you suspect the Agent is not running, see [Verifying that an Agent is Running](#) on page 332. To make sure that the Gateway can establish a connection to the IP address of the server where the Agent is installed, try to ping the IP address of the server where the Agent is installed.

AGT — Gateway time-out

The Gateways on the two ends of a tunnel could not communicate with each other, most likely due to a network connectivity problem.

What Can I Do If the Gateway Times Out During an AGT Test?

Ensure that network connectivity is available between the Gateways in the path between the realm of the managed server and the SA core.

Crypto Match (CRP) Test

This test checks that the SSL cryptographic files that the Agent uses are valid.

The five possible results are:

- CRP – OK
- CRP – Untested
- CRP – Unexpected error
- CRP – Agent certificate mismatch
- CRP – SSL negotiation failure

CRP – OK

No troubleshooting necessary.

CRP – Untested

This result is returned when a functional area cannot be tested because of a previous failure that prevents further testing. For example, if the Agent cannot be reached, then no other tests are possible.

What Can I Do If a Test Is Not Run During a CRP Test?

First resolve all tests that failed, and then run the Communication Test again.

CRP – Unexpected error

This result indicates that the test encountered an unexpected error.

What Can I Do If I Get an Unexpected Error During a CRP Test?

First resolve all tests that failed, and then run the Communication Test again. If the unexpected error recurs, check to see if any additional details in the error message indicate the problem. If the error cannot be resolved, contact Hewlett Packard Customer Support.

CRP – Agent certificate mismatch

This result indicates that the SSL certificate that the Agent is using (cogbot.srv) does not match the SSL certificate that is registered with HP Server Automation for that Agent.

What Can I Do If I Get a Certificate CN Mismatch During a CRP Test?

Use the Recert Agent Custom Extension to issue a new certificate to the Agent.

CRP – SSL negotiation failure

This result indicates that the Agent is not accepting SSL connections for the SA core. (The SA core is the entire collection of servers and services that provide HP Server Automation services.) The likely cause of this error is that one or more files in the Agent crypto directory are missing or are invalid.

What Can I Do If I Get an SSL Negotiation Failure During an CRP Test?

Run the Server Recert custom extension in the “set allow recert flag only” mode on the server, and then Run the Server Agent Installer with the “-c” switch.

Reinstalling the Agent with the “-c” option (“c” stands for “clean”) removes all certs on the server and also removes the MID file, which forces the Agent to retrieve a new MID from the Data Access Engine.

- See [Running Server Communication Tests](#) on page 139 for more information about how to install an Server Agent using the “-c” switch.

After you reinstall the Agent, run the test again to check if the Agent is now reachable.

Agent to Command Engine (CE) Test

This test checks that the Agent can connect to the Command Engine and retrieve a command for execution.

The sixteen possible results are:

- CE – OK
- CE – Untested
- CE – Unexpected error
- CE – Connection refused
- CE – Connection time-out
- CE – DNS does not resolve
- CE – Old Agent version
- CE – Realm is unreachable
- CE – No Gateway defined
- CE – Tunnel setup error
- CE – Gateway denied access
- CE – Gateway name resolution error
- CE – Internal Gateway error
- CE – Gateway could not connect to server

- CE – Gateway time-out
- CE — No callback from Agent

CE – OK

No troubleshooting necessary.

CE — Untested

This result is returned when a functional area cannot be tested because of a previous failure that prevents further testing. For example, if the Agent cannot reach the Command Engine, then no other tests are possible.

What Can I Do If a Test Is Not Run During a CE Test?

First resolve all tests that failed, and then run the Communication Test again.

CE – Unexpected error

This result indicates that the test encountered an unexpected condition.

What Can I Do If I Get an Unexpected Error During a CE Test?

First resolve all tests that failed, and then run the Communication Test again. If the unexpected error recurs, check to see if any additional details in the error message indicate the problem. If the error cannot be resolved, contact Hewlett Packard Customer Support.

CE – Connection refused

This result indicates that the Agent is receiving a TCP reset packet when attempting to connect to the Command Engine on port 1018. The likely cause is that the Agent is connecting to the wrong IP address. In other words, the Agent does not know the correct IP address of the Command Engine. It is also possible that a firewall might be blocking the connection.

What Can I Do If the Connection is Refused During a CE Test?

- 1 Check that the name “way” resolves to its correct IP address. For instructions on how to do this, see [Resolving Host Name](#) on page 334.
- 2 Check to make sure there isn't a firewall refusing the connection to this IP address.

CE – Connection time-out

This result indicates that the Agent is not receiving any reply packets when it attempts to initiate a TCP connection to the Command Engine on port 1018. The likely cause is that the Agent is connecting to the “wrong” IP address. In other words, the Agent doesn't know the correct IP address of the Command Engine. A firewall might also be blocking the connection.

What Can I Do If the Connection Times Out During a CE Test?

Follow the same steps specified in [What Can I Do If the Connection is Refused During a CE Test?](#).

CE – DNS does not resolve

This result indicates that the Agent cannot resolve the host name “way” to a valid IP address. In other words, the Agent does not know the correct IP address of the Command Engine.

What Can I Do If the Command Engine Name Does Not Resolve During a CE Test?

Log into the server and use a command such as Telnet to confirm that the host name “way” can resolve (for example: “telnet way 1018”). If not, check the DNS configuration of the server to make sure that the host name “way” is configured to its correct IP address. See [Resolving Host Name](#) on page 334 in this appendix for more information.

CE — Old Agent version

This result indicates that the Agent was unable to contact the Command Engine, but the test was unable to determine the exact cause because the Agent is out of date.

What Can I Do If the Agent is Out of Date During a CE Test?

If this error occurs, it will likely be for one of two reasons: either the host name of the Command Engine (“way”) did not resolve, or the connection was refused.

- If you believe that the host name of the Command Engine (“way”) did not resolve, then See [CE – DNS does not resolve](#) on page 319 in this appendix for more information.
- If you determine that the connection was refused, See [CE – Connection refused](#) on page 318 in this appendix for more information.

Alternatively, you can upgrade the Agent to the latest version (contact Hewlett Packard Customer Support) and re-run the test. See [Running Server Communication Tests](#) on page 139 for more information about how to install an agent.

CE – Realm is unreachable

The Satellite realm where the managed server is located is unreachable. This error means that a path of tunnels between the Gateways in the SA core and the realm of the managed server cannot be established.

What Can I Do if the Realm is Unreachable During a CE Test?

This error could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration. Contact your SA administrator for assistance in troubleshooting the Gateway network.

CE – No Gateway defined

The managed server is in a Satellite realm, but its Agent is not properly configured to use a Gateway. Agents located in satellites must use a Gateway to contact the core.

What Can I Do If No Gateway is Defined During a CE Test?

To troubleshoot this error, try the following:

- 1 Create or open the `opswgw.args` file on the managed server. The `opswgw.args` file is located on the managed server at:
 - **Unix/Linux:** `/etc/opt/opsware/agent`
 - **Windows:** `%SystemDrive%\Program Files\Common Files\Opware\etc\agent`
- 2 Make sure that this file contains a single line as shown:

```
opswgw.gw_list: <gw_ip_address>:<gw_port>,<gw_up_address>:<gw_port>
```

CE – Tunnel setup error

The Command Engine could not establish a connection through any of its defined Gateways. This could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration.

What Can I Do If A Tunnel Setup Occurs Error During a CE Test?

Contact your SA administrator.

CE – Gateway denied access

The Gateway is working, but refused to proxy the connection on behalf of the Agent. This error most likely means that the Gateway is misconfigured such that the Gateway will not allow the Agent to access the Command Engine.

What Can I Do if the Gateway is Denied Access During a CE Test?

Contact your SA administrator.

CE – Gateway name resolution error

The server running the Gateway in the SA core was unable to resolve the host name “way”. It must be able to do this in order to proxy connections on behalf of managed servers in Satellite realms.

What Can I Do if a Name Resolution Error Occurs on the Gateway During a CE Test?

Log into the server where the core Gateway is located and use a command such as `ping` or `host` to confirm that the host name “way” can be resolved (for example: “`host way`”).

If you cannot connect, contact your SA administrator so that you can check the DNS configuration of the core Gateway server.

CE – Internal Gateway error

Due to an internal error, the Gateway was unable to proxy the connection. This typically occurs when the Gateway is overloaded.

What Can I Do if an Internal Gateway Error Occurs During a CE Test?

Contact your SA administrator.

CE – Gateway could not connect to server

The Gateway could not establish a connection to the Command Engine. The situation might be because the Command Engine is not running, or because the Gateway is resolving the Command Engine host name (“way”) to the wrong IP address. It is also possible that a firewall might be blocking the connection.

What Can I Do if the Gateway Can’t Connect to Server During a CE Test?

Check that the name “way” resolves to the correct IP address and that the Gateway can establish a connection to port 1018 at that IP. See [Resolving Host Name](#) on page 334 and [Verifying that a Port is Open on a Managed Server](#) on page 333 in this appendix.

CE – Gateway time-out

The Gateways on the two ends of a tunnel could not communicate with each other, most likely due to a network connectivity problem.

What Can I Do if the Gateway Times Out During a CE Test?

Ensure that network connectivity is available between the Gateways in the path between the realm of the managed server and the SA core.

CE – No callback from Agent

The Command Engine was able to contact the Agent, but the Agent did not call back to retrieve its command. However, the Agent reports that it can connect to a Command Engine.

What Can I Do if There is No Callback from Agent?

Ensure network connectivity between the agent and the nearest agent gateway. For example, make sure no firewalls are preventing access. The default port for the agent gateway is 3001. For more information on gateway monitoring, see the *SA Administration Guide*. For information on configuring the agent gateway, see the *SA Standard/Advanced Installation Guide*.

Agent to Data Access Engine (DAE) Test

This test checks that the Agent can retrieve its device record from Data Access Engine. The fifteen possible results are:

- DAE – OK
- DAE – Untested
- DAE – Unexpected error
- DAE – Connection refused
- DAE – Connection time-out
- DAE – DNS does not resolve
- DAE – Old Agent version
- DAE – Realm is unreachable
- DAE – No Gateway defined
- DAE – Tunnel setup error
- DAE – Gateway denied access
- DAE – Gateway name resolution error
- DAE – Internal Gateway error
- DAE – Gateway could not connect to server
- DAE – Gateway time-out

DAE – OK

No troubleshooting necessary.

DAE – Untested

This result is returned when a functional area cannot be tested, because of a previous failure that prevents further testing. For example, if the Agent cannot reach the Data Access Engine then no other tests are possible.

What Can I Do If a Test Is Not Run During a DAE Test?

First resolve all tests that failed, and then run the Communication Test again.

DAE – Unexpected error

This result indicates that the test encountered an unexpected condition.

What Can I Do If I Get an Unexpected Error During a DAE Test?

First resolve all tests that failed, and then run the Communication Test again. If the unexpected error recurs, check to see if any additional details in the error message indicate the problem. If the error cannot be resolved, contact Hewlett Packard Customer Support.

DAE – Connection refused

This result indicates that the Agent is receiving a TCP reset packet when attempting to connect to the Data Access Engine on port 1004. The likely cause is that the Agent is connecting to the wrong IP address. A firewall might also be blocking the connection.

What Can I Do If the Connection is Refused During a DAE Test?

- 1 Check that the name “spin” resolves to its correct IP address. See [Resolving Host Name](#) on page 334 in this appendix for more information.
- 2 Check to make sure that a firewall is not refusing the connection to this IP address.

DAE – Connection time-out

This result indicates that the Agent is not receiving any reply packets when it attempts to initiate a TCP connection to the Data Access Engine on port 1004. The likely cause is that the Agent is connecting to the wrong IP address. In other words, the Agent does not know the correct IP address of the Command Engine. A firewall might also be blocking the connection.

What Can I Do If the Connection Times Out During a DAE Test?

Follow the same steps specified in [What Can I Do If the Connection is Refused During a DAE Test?](#) on page 323.

DAE – DNS does not resolve

This result indicates that the Agent cannot resolve the host name “spin” to a valid IP address. In other words, the Agent does not know the correct IP address of the Data Access Engine.

What Can I Do If the Data Access Engine Name Does Not Resolve During a DAE Test?

Log into the server and use a command such as Telnet to confirm that the host name “spin” can be resolved (for example: telnet spin 1004”). If not, check the DNS configuration of the server to make sure that the host name “spin” is configured to its correct IP address. See [Resolving Host Name](#) on page 334 in this appendix for more information.

DAE – Old Agent version

This result indicates that the Agent was unable to contact the Data Access Engine, and the test is unable to determine the exact cause, because the Agent is out of date.

What Can I Do If the Agent is Out of Date During an DAE Test?

If this error occurs, it will likely be for one of two reasons: either the host name of the Data Access Engine (“spin”) did not resolve, or the connection was refused.

- If you believe that the host name of the Data Access Engine (“way”) did not resolve, then see [DAE – DNS does not resolve](#) on page 323.
- If you determine that the connection was refused, see [DAE – Connection refused](#) on page 323.

Alternatively, you can upgrade the Agent to the latest version (contact Hewlett Packard Customer Support) and re-run the test. See [Running Server Communication Tests](#) on page 139 for information about how to install an agent.

DAE – Realm is unreachable

The Satellite realm where the managed server is located is unreachable. This error means that a path of tunnels between the gateways in the SA core and the realm of the managed server cannot be established.

What Can I Do if the Realm is Unreachable During a DAE Test?

This error could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration. Contact your SA administrator for assistance in troubleshooting the Gateway network

DAE – No Gateway defined

The managed server is in a Satellite realm, but its Agent is not properly configured to use a Gateway. Agents located in satellites must use a Gateway to contact the core.

What Can I Do If No Gateway is Defined During a DAE Test?

To troubleshoot this error, try the following:

- 1 Create or open the `opswgw.args` file on the managed server. The `opswgw.args` file is located on the managed server at:
 - **Unix/Linux:** `/etc/opt/opsware/agent`
 - **Windows:** `%SystemDrive%\Program Files\Common Files\Opsware\etc\agent`
- 2 Make sure this file contains a single line as shown:

```
opswgw.gw_list: <gw_ip_address>:<gw_port>,<gw_up_address>:<gw_port>
```

DAE – Tunnel setup error

The Data Access Engine could not establish a connection through any of its defined Gateways. This could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration.

What Can I Do if a Tunnel Setup Error Occurs During a DAE Test?

Contact your SA administrator.

DAE – Gateway denied access

The Gateway is working, but refused to proxy the connection on behalf of the Agent. This error most likely means that the Gateway is misconfigured such that the Gateway will not allow the Agent to access the Data Access Engine.

What Can I Do if the Gateway is Denied Access During a DAE Test?

Contact your SA administrator.

DAE – Gateway name resolution error

The server running the Gateway in the SA core was unable to resolve the host name “spin”. It must be able to do this in order to proxy connections on behalf of managed servers in Satellite realms.

What Can I Do if There is a Name Resolution Error on the Gateway During a DAE Test?

Log into the server where the core Gateway is located and use a command such as ping or host to confirm that the host name “spin” can be resolved (for example: “host spin”).

If you cannot connect, contact your SA administrator so that you can check the DNS configuration of the core Gateway server.

DAE – Internal Gateway error

Due to an internal error, the Gateway was unable to proxy the connection. This typically occurs when the Gateway is overloaded.

What Can I Do if an Internal Gateway Error Occurs During a DAE Test?

Contact your SA administrator.

DAE – Gateway could not connect to server

The Gateway could not establish a connection to the Data Access Engine. This might be because the Data Access Engine is not running, or because the Gateway is resolving the Data Access Engine host name (“spin”) to the wrong IP address. It is also possible that a firewall might be blocking the connection.

What Can I Do if the Gateway Can't Connect to Server During a DAE Test?

Check that the name “spin” resolves to the correct IP address and that the Gateway can establish a connection to port 1018 at that IP. See [Resolving Host Name](#) on page 334 in this appendix for more information and See [Verifying that a Port is Open on a Managed Server](#) on page 333 in this appendix for more information.

DAE – Gateway time-out

The Gateways on the two ends of a tunnel could not communicate with each other, most likely due to a network connectivity problem.

What Can I Do if the Gateway Times Out During a DAE Test?

Ensure that network connectivity is available between the Gateways in the path between the managed server's realm and the SA core.

Agent to Software Repository (SWR) Test

This test checks that the Agent can establish an SSL connection to the Software Repository.

There 16 possible results are:

- SWR – OK
- SWR – Untested
- SWR – Unexpected error
- SWR – Connection refused
- SWR – Connection time-out
- SWR – DNS does not resolve
- SWR – Old Agent version
- SWR - Server identification error
- SWR – Realm is unreachable
- SWR – No Gateway defined
- SWR – Tunnel setup error
- SWR – Gateway denied access
- SWR – Gateway name resolution error
- SWR – Internal Gateway error
- SWR – Gateway Could not connect to server
- SWR – Gateway time-out

SWR – OK

No troubleshooting necessary.

SWR – Untested

This result is returned when a functional area cannot be tested because of a previous failure that prevents further testing. For example, if the Agent cannot reach the Software Repository, then no other tests are possible.

What Can I Do If a Test Is Not Run During a SWR Test?

First resolve all tests that failed, and then run the Communication Test again.

SWR – Unexpected error

This result indicates that the test encountered an unexpected condition.

What Can I Do If I Get an Unexpected Error During a SWR Test?

First resolve all tests that failed, and then run the Communication Test again. If the unexpected error recurs, check to see if any additional details in the error message indicate the problem. If the error cannot be resolved, contact Hewlett Packard Customer Support.

SWR – Connection refused

This result indicates that the Agent is receiving a TCP reset packet when attempting to connect to the Software Repository on port 1003. The likely cause is that the Agent is trying to connect to the wrong IP address. A firewall might also be blocking the connection.

What Can I Do If the Connection is Refused During an SWR Test?

- 1 Check that the name “theword” resolves to the correct IP address. For this information, see [Resolving Host Name](#) on page 334.
- 2 Check to make sure that a firewall isn’t refusing the connection to this IP address.

SWR – Connection time-out

This result indicates that the Agent is receiving a TCP reset packet when attempting to connect to the Software Repository on port 1003. The likely cause is that the Agent is connecting to the wrong IP address. In other words, the Agent does not know the correct IP address of the Software Repository. A firewall might also be blocking the connection.

What Can I Do If the Connection Times Out During an SWR Test?

Follow the same steps specified in [What Can I Do If the Connection is Refused During an SWR Test?](#) on page 327.

SWR – DNS does not resolve

This result indicates that the Agent cannot resolve the host name “theword” to a valid IP address. In other words, the Agent does not know the correct IP address of the Software Repository.

What Can I Do If the Software Repository Name (“theword”) Does Not Resolve During an SWR Test?

Log into the server and use a command such as Telnet to confirm that the host name “theword” can be resolved (for example: “telnet theword 1003”). If not, contact your SA administrator so that you can check the DNS configuration of the server.

SWR – Old Agent version

This result indicates that the Agent was unable to contact the Software Repository, and the test is unable to determine the exact cause because the Agent is out of date.

What Can I Do If the Agent is Out of Date During an SWR Test?

If this error occurs, it will likely be for one of two reasons: either the host name of the Software Repository (“theword”) did not resolve, or the connection was refused.

- If you think that the host name of the Software Repository (“theword”) did not resolve, then see [SWR – DNS does not resolve](#) on page 327.
- If you determine that the connection was refused, see [SWR – Connection refused](#) on page 327.

Alternatively, you can upgrade the Agent to the latest version (contact Hewlett Packard Customer Support) and re-run the test. See [Installing and Managing Server Agents](#) on page 123 for information how to install a server agent.

SWR - Server identification error

Whenever an Agent makes a request of the Software Repository, the identity of the server is validated to confirm that the server should be allowed access to the information requested. This error indicates that the Software Repository was unable to identify the server being tested, or incorrectly identified that server.

What Can I Do If I Get a Server Identification Error?

The Software Repository identifies servers based on the incoming IP address of the request. To troubleshoot this error, try the following:

- 1 Check the Device Properties tab for the server in the SA Web Client to see if Network Address Translation (NAT) is in use. If it is, make sure that NAT is statically configured, and that only one server is using the NAT address. If multiple servers are using the same IP address, you will need to reconfigure the NAT device. See [Network Address Translation \(NAT\) for Managed Servers](#) on page 206 for more information.
- 2 If the Agent is installed on a cluster, check that each node in the cluster has a unique IP address at which it can be reached. You might have to add static routes to the server to ensure that connections made from that server to the SA core use the unique IP. If NAT is not in use, you can alternately mark the correct interface as the “primary” interface through the Network Configuration tab for the server in the SA Web Client. See [Network Address Translation \(NAT\) for Managed Servers](#) on page 206 for more information.
- 3 The server's IP address might have changed recently. If this is the case, stop and restart the Agent. For instructions on how to stop and start an Agent, see [Restarting a Server Agent](#) on page 333.

SWR – Realm is unreachable

The Satellite realm where the managed server is located is unreachable. This error means that a path of tunnels between the gateways in the SA core and the realm of the managed server cannot be established.

What Can I Do if the Realm is Unreachable During a SWR Test?

This error could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration. Contact your SA administrator for assistance in troubleshooting the Gateway network.

SWR – No Gateway defined

The managed server is in a Satellite realm, but its Agent is not properly configured to use a Gateway. Agents located in satellites must use a Gateway to contact the core.

What Can I Do If No Gateway is Defined During a SWR Test?

To troubleshoot this error, try the following:

- 1 Create or open the `opswgw.args` file on the managed server. The `opswgw.args` file is located on the managed server at:
 - **Unix/Linux:** `/etc/opt/opsware/agent`
 - **Windows:** `%SystemDrive%\Program Files\Common Files\Opware\etc\agent`
- 2 Make sure that this file contains a single line as shown:

```
opswgw.gw_list: <gw_ip_address>:<gw_port>,<gw_up_address>:<gw_port>
```

SWR – Tunnel setup error

The Data Access Engine could not establish a connection through any of its defined Gateways. This could be due to a network problem, a malfunctioning or failed Gateway, or a Gateway misconfiguration.

What Can I Do If a Tunnel Setup Error Occurs During a SWR Test?

Contact your SA administrator.

SWR – Gateway denied access

The Gateway is working but refused to proxy the connection on behalf of the Agent. This error most likely means that the Gateway is misconfigured such that the Gateway will not allow the Agent to access the Software Repository.

What Can I Do if the Gateway is Denied Access During a SWR Test?

Contact your SA administrator.

SWR – Gateway name resolution error

The server running the Gateway in the SA core was unable to resolve the host name “theword”. It must be able to do this in order to proxy connections on behalf of managed servers in Satellite realms.

What Can I Do if a Name Resolution Error Occurs on the Gateway During a SWR Test?

Log into the server where the core Gateway is located and use a command such as `ping` or `host` to confirm that the host name “theword” can be resolved (for example: “`host theword`”).

If you cannot connect, contact your SA administrator so that you can check the DNS configuration of the core Gateway server.

SWR – Internal Gateway error

Due to an internal error, the Gateway was unable to proxy the connection. This typically occurs when the Gateway is overloaded.

What Can I Do if an Internal Gateway Error Occurs During a SWR Test?

Contact your SA administrator.

SWR – Gateway Could not connect to server

The Gateway couldn't establish a connection to the Software Repository. This error might be because the Software Repository is not running, or because the Gateway is resolving the Software Repository host name (“theword”) to the wrong IP address. It is also possible that a firewall might be blocking the connection.

What Can I Do if the Gateway Can't Connect to Server During a SWR Test?

Check that the name “theword” resolves to the correct IP address and that the Gateway can establish a connection to port 1018 at that IP address. For more information, see [Resolving Host Name](#) on page 334 and [Verifying that a Port is Open on a Managed Server](#) on page 333.

SWR – Gateway time-out

The Gateways on the two ends of a tunnel could not communicate with each other, most likely due to a network connectivity problem.

What Can I Do if the Gateway Times Out During a SWR Test?

Ensure that network connectivity is available between the Gateways in the path between the realm of the managed server and the SA core.

Machine ID Match (MID) Test

This test checks whether the MID that the Agent reported matches that recorded in the Model Repository (SA data repository).

You can receive four possible errors from the Machine ID (MID) Communication Test:

- MID – OK
- MID – Untested
- MID – Unexpected error
- MID – MID mismatch

MID – OK

No troubleshooting necessary.

MID – Untested

This result is returned when a functional area cannot be tested, because of a previous failure that prevents further testing. For example, if the Agent cannot reach the Model Repository, then no other tests are possible.

What Can I Do If a Test Is Not Run During an MID Test?

First resolve all tests that failed, and then run the Communication Test again.

MID – Unexpected error

This result indicates that the test encountered an unexpected condition.

What Can I Do If I Get an Unexpected Error During an MID Test?

First resolve all tests that failed, and then run the Communication Test again. If the unexpected error recurs, check to see if any additional details in the error message indicate the problem. If the error cannot be resolved, contact Hewlett Packard Customer Support.

MID – MID mismatch

This result indicates that the MID that the Agent reported does not match the recorded MID in the Model Repository for that Agent. The likely cause is that the Command Engine is running the test against the wrong Agent.

What Can I Do If the MID is Mismatched During an MID Test?

To troubleshoot this error, try the following:

- 1 Check the Device Properties tab for the server in the SA Web Client to see if NAT is in use for this server. If it is, make sure that static, 1-to-1 NAT is being used. HP Server Automation requires that all managed servers be reachable on a distinct, consistent IP address, so configurations that assign addresses dynamically or use port-based translation are not supported.
- 2 If the Agent is installed on a cluster, check that each node in the cluster has a unique IP address at which it can be reached. You might have to add static routes to the server to ensure that connections made from that server to the SA core use the unique IP. If NAT is not in use, you can alternately mark the correct interface as the “primary” interface via the Network Configuration tab for the server in the SA Web Client.
- 3 The IP address might have changed recently. If this is the case, stop and restart the Agent. For these instructions, see [Restarting a Server Agent](#) on page 333.

Common Troubleshooting Tasks

The following list of troubleshooting tasks are common to more than one Communication Test error:

- [Verifying that an Agent is Running](#)
- [Verifying that a Port is Open on a Managed Server](#)
- [Restarting a Server Agent](#)
- [Checking Management IP of a Managed Server](#)
- [Checking Network Gateway Configuration](#)
- [Resolving Host Name](#)

Verifying that an Agent is Running

To verify that an Agent is running on a server, perform the following steps:

- 1 On Solaris, HP-UX, or AIX, enter this command:

```
/usr/ucb/ps auxwww | grep opsware
```

You should get this result if the Agent is running:

```
/opt/opsware/agent/bin/python /opt/opsware/agent/pylibs/shadowbot/  
daemonbot.pyc --conf /etc/opt/opsware/agent/agent.args
```

- 2 On Linux, enter this command:

```
ps auxwww | grep opsware
```

You should get the same result as the preceding step.

- 3 On Windows, from the Administrative Tools | Services, check to make sure that the opswareagent service is running.

Verifying that a Port is Open on a Managed Server

For some errors, you will need to verify that the port is open on the server where the Agent is installed. To do this, perform the following steps:

- 1 Check if the port is open.

- 2 On Solaris, HP-UX, AIX, or Linux enter:

```
netstat -an | grep 1002 | grep LISTEN
```

If the port is open on the box, you should get back the following:

```
*.1002    *.*      0        0 24576     0 LISTEN
```

- 3 On Windows, at the command prompt enter:

```
netstat -an | find "1002" | find "LISTEN"
```

If the port is open on the box, you should get back the following result:

```
TCP0.0.0.0:10020.0.0.0:0LISTENING
```

- 4 Confirm that the port is actually open. To do this, from the computer where the Agent is installed, Telnet to port 1002 by using both localhost and the external IP address of the server. Performing the Telnet will help you confirm that a connection refused message is being caused by the lack of an open port on the managed server rather than a problem with networking hardware between the core and the managed server.

Restarting a Server Agent

To restart a Server Agent, log onto the managed server and enter the following commands:

Unix:

```
/etc/init.d/opsware-agent restart
```

HP-UX:

```
/sbin/init.d/opsware-agent restart
```

AIX:

```
/etc/rc.d/init.d/opsware-agent restart
```

Windows:

```
net stop opswareagent  
net start opswareagent
```

Checking Management IP of a Managed Server

To check the Management IP of a managed server, perform the following steps:

- 1 To view the management IP of the managed server, log into the SA Web Client.
- 2 From the Navigation panel, click Servers † Manage Servers.
- 3 From the Manage Servers list, click the display name of the server for which you want to check the Management IP.
- 4 Select the Network tab of the server's properties.

- 5 Check to make sure that the Management IP address matches the IP address of the managed server.

Checking Network Gateway Configuration

To check the network Gateway configuration, perform the following steps:

- 1 On Solaris, enter this command to check routing table:

```
netstat -rn
```

Your results should look like this:

```
default          192.168.8.1      UG          1    5904
```

where 192.168.8.1 is the IP of the Gateway.

- 2 On Linux, enter this command to check routing table:

```
route -n
```

Your results should look like this:

```
0.0.0.0          192.168.8.1     0.0.0.0      UG    0    0    0 eth0
```

where 192.168.8.1 is the IP of the Gateway.

- 3 On Windows, enter this command to check routing table:

```
route print
```

Your results should look something like this:

```
0.0.0.00.0.0.0192.168.8.1192.168.8.12020
```

where 192.168.8.1 is the IP of the Gateway.

- 4 In each case, you should also ping 192.168.8.1 (IP) to confirm that you can actually reach the Gateway.

Resolving Host Name

All managed servers (those with agents) must be able to resolve unqualified HP Server Automation service names for the following components:

- spin (Data Access Engine)
- way (Command Engine)
- theword (Software Repository)

If you need to ensure that one of these host names resolves correctly, contact your SA administrator to find out what qualified host name or IP address these service names should resolve to.

- 1 Try to ping the host. For example, execute the following command if you wanted to resolve the host name, way:

```
ping way
```

- 2 If the host name cannot resolve, you will get the following errors:

Linux/Solaris/AIX/HP-UX:

```
ping: unknown host way
```

Windows:

Ping request could not find host way. Please check the name and try again.

- 3 If the host name can resolve, you might get back various permutations of these types of messages (OS independent):

way is alive

or

pinging way (ip) with 32 bytes of data

B Agent Installation and Upgrade Utilities

Agent Install Command

This section provides information on Agent installation using the Agent Installer CLI (Command Line Interface) and contains the following topics:

- Overview of Agent Installation Using the CLI
- The Agent Installer Command
- Preparation for Agent Installation
- Checklist Before Installing the SA Agent
- Obtaining the Agent Installer Package
- Agent Installer Options
- Example: Agent Installer Command and Options
- Starting an Agent After Installation
- Verifying Agent Functionality
- Augmenting the Information for a Managed Server
- Uninstalling an Agent on Unix and Windows
- Uninstalling Earlier Versions of Agents on Unix
- Uninstalling Earlier Versions of Agents on Windows

Overview of Agent Installation Using the CLI



When you install Agents on existing servers, you should synchronize the local time on the servers with an external time-server that uses a network time protocol (NTP).

The Agent Installer can be invoked from the command line or within a script and can be operated unattended because user interaction is not required. The Agent Installer also retrieves cryptographic material, retrieves configuration information, and writes a configuration file and a log file.

The Agent installer installs the SA agent on your servers and makes them known to HP Server Automation so that they can be managed.

Installing an Agent on a server with a pre-built OS into HP Server Automation enables:

- Baseline discovery of the operating system on the server.

- Managing the baseline operating system, including patch management, when the operating system is defined in HP Server Automation with the Prepare Operating System Wizard.
- Full provisioning and management capabilities for any new applications deployed on the server.

When installed, the Agent registers the server with the Model Repository. HP Server Automation assigns the server to a generic operating system that corresponds to the operating system that the Agent discovered during the installation. The server is assigned to a placeholder OS node. For each operating system, the SA Web Client contains a node `<operating_system_version>/Not Assigned`.



The Agent Installer can install Agents when a core is not available to a server. If a newly-installed Agent cannot contact a core, the Agent runs in a dormant mode. While dormant, it periodically attempts to contact the core. When the core becomes available, the Agent performs the initialization tasks, such as hardware and software registration, that usually take place when the Agent is first installed.

The server is tracked in the SA Client. However, the server operating system *cannot* be managed while the server is assigned to the generic operating system node. You must reassign the server to the operating system that was defined with the OS Provisioning feature.

The server is associated with the default facility for the local instance of HP Server Automation.

If the managed server's IP address does not fall within a specified IP range, the server is associated with the default IP range group (Default). The default group is associated with the customer Not Assigned.

See [Assigning a Server to a Customer - SA Client](#) on page 145 for information about how servers are associated with customers.

The Agent Installer Command

The Agent Installer command is available on any SA core server in the directory `/var/opt/opsware/agent_installers`. A different Agent Installer is provided for each different operating system version.

Preparation for Agent Installation

It is recommended that you set up a Windows file share to make the Agent Installer for various operating systems available from one place. Setting up a file share allows you to install Agents on servers quickly and easily. If this is not possible, the Agent Installer needs to be moved by using an alternate file transfer mechanism, such as SFTP.

At the completion of the Agent installation process, a server becomes a managed server and the hardware and software data that the Agent discovered are stored in the Model Repository.



To install patches on Windows 2000 servers, you must install Internet Explorer (IE) 6.0 or later on the server first because a patch utility depends on it. If you do not install IE 6.0 on the server first, the Agent Installer warns you that the Patch Management feature does not work as expected because it checks for IE 6.0 on all Windows servers. This prerequisite is not required for Windows 2003, because IE 6.0 is pre-installed for this operating system.

Checklist Before Installing the SA Agent

Before installing the agent, perform the following tasks on the server where it is to be installed. Performing these tasks is vital to installing the Agent quickly within maintenance windows.

- 1 Because the Agent runs on port 1002, verify that no other applications are using this port.

- On a Unix server, enter this command from a terminal window:

```
netstat -an | grep 1002 | grep LISTEN
```

- On a Windows server, enter this command from a terminal window:

```
netstat -an | find "1002" | find "LISTEN"
```

- 2 Check for sufficient disk space for Agent installation on the server.

The installer checks for the following amounts of free disk space in these directories:

- 100MB in /opt/opsware (Unix)
- 100MB in /var/opt/opsware (Unix)
- 30MB in %SystemDrive%\Program Files\Opware (Windows)
- 100MB in %SystemDrive%\Program Files\Common Files\Opware (Windows)

These default directories can be overridden with parameters at installation time.

These space requirements might not be enough. The `vardir` directory is used for dynamic content like logs and downloaded packages. If there is not enough disk space for the packages during remediation, it will fail.

- 3 On the Solaris operating system, check for legacy sun4m architecture. Currently, the Agent works only for sun4u architecture.

- 4 For Windows verify that the Windows Registry has the correct settings:

- a Start `regedit` and locate the following registry key:

```
HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\FileSystem
```

- b Select the `NtfsDisable8dot3NameCreation` entry.

- c On the **Edit** menu, click **DWORD** and verify that the value is set to 0. The value *must* be set to 0. If necessary (because the value is set to 1), change the value by following your organization's IT policies and reboot the server.

- 5 To install an Agent on a server running Solaris, you must also install the following Solaris packages:

For Python:

```
SUNWtoo
```

```
SUNWtoox
```

For showrev:

SUNCadm
SUNWlibC
SUNWlibCx
SUNWadmfw

- 6 Before you install an Agent on a server, the server must meet certain package and patch requirements that vary by operating system, as [Table 32](#) shows.

Table 32 Required Packages/Patches for SA Agents

Server operating system	Required patches
HP-UX (11.11/11i)	SW-DIST must be upgraded to the HP recommended patch level. You should continue to upgrade this package when HP recommends new versions.
Red Hat Linux AS 3.0 Red Hat Linux WS 3.0 Red Hat Linux ES 3.0	Red Hat Enterprise Linux 3 Update 3
Solaris 10, 9, 8, 7, and 6	SUNWadmc SUNWcsl SUNWcslr (If available, depending on version) SUNWcsu SUNWesu SUNWlibms SUNlibmsr (If available, depending on version) SUNWswmt It is strongly recommended not to remove packages from the SUNWCreq minimal required install cluster, since many packages are interdependent and operation beyond that of basic SA functionality may be affected.
Windows 2000	Service Pack 4

Installing an Agent

Perform the following tasks to install an Agent on an unmanaged server.

Obtaining the Agent Installer Package

The Agent needs administrator-level privileges (root on Unix servers and Local System on Windows servers) to manage a server. Therefore, Agent installation needs to be performed as root on Unix operating systems and as administrator on Windows operating systems.

You can install an agent on any server listed in [Supported Operating Systems for Managed Servers](#) on page 176.

Perform the following steps to download an Agent Installer for an unmanaged server.

From the Command Line

- 1 Log into the unmanaged server using a remote shell. On Unix, log in as root. On Windows, log in as administrator.
- 2 Locate the appropriate Agent Installer on a core server

From the command line: in the directory `/var/opt/opsware/agent_installers`. Each operating system version has a different package for the Agent Installer.

Unix:

```
opsware-agent-<version>-<system_name>-<system_version>
```

Red Hat Linux:

```
opsware-agent-<version>-<system_name>-5CLIENT-<system_version>
```

Note that Red Hat may use the terms *Client* and *Desktop* interchangeably.

Windows:

```
opsware-agent-<version>-<system_name>-<system_version>.exe
```

- 3 From the directory where the Agent Installer was copied, run the Installer by entering the correct executable and options for the installation environment. The options are listed under [Agent Installer Options](#) on page 343.

From the SA Client

If you do not have remote shell access to the SA Core from an unmanaged server, you may need to manually export the Agent Installer package locally on SA Core machine and copy it to the unmanaged server. To export the Agent Installer package, perform the following tasks.

- 1 Launch the SA Client.
- 2 From the Navigation pane, select **Library > Packages**.
- 3 Select the appropriate operating system from those listed under packages as shown in [Figure 103](#).

Select the SA Agent. The filename will be in the format:

Unix:

```
opsware-agent-<version>-<system_name>-<system_version>
```

Red Hat Linux:


```
opsware-agent-<version>-<system_name>-5CLIENT-<system_version>
```

Note that Red Hat may use the terms *Client* and *Desktop* interchangeably.

Windows:

opsware-agent-<version>-<system_name>-<system_version>.exe

Figure 103 Selecting an Agent Installer Package



- 4 Click the package name for the Agent Installer that you want to export. From the Actions menu, select Export Software. The Browse window appears.
- 5 In the Browse window, specify the download location for the package and Click Export. The package is exported to the specified location.
- 6 Copy the Agent Installer to the target server.

Example: Agent Installer Command and Options

The following example command installs the server agent on a Solaris 5.10 server in the default directories, connects to the gateway on the server core2.hp.com using port 2010, and logs the results of the installation in the log file named agent.log:

```
% opsware-agent-45.0.0.0.98-solaris-5.10 --logfile agent.log --loglevel info  
--opsw_gw_addr core2.hp.com:2010
```

Agent Installer Options

Use the options listed below with the Agent Installer command. You must use either the `--opsw_gw_addr` option or the `--no_opsw_gw` option. All others are optional.

Table 33 Agent Installer Options

Option	Description
<code>--auth_path</code>	Specifies the complete path to the file that contains the trusted authorities in PEM format.
<code>--coreinstall</code>	Install initialization scripts in the proper location for the core server.
<code>--customer_id <customer></code>	Assigns the managed server to the specified customer. This option requires the <code>--username</code> and <code>--password</code> options. For more information about customers see Creating and Managing Customers on page 143.
<code>--del_opsw_gw_addr_list</code>	Deletes the list of gateway addresses.
<code>-f</code>	<p>Forces the Agent to be installed even if environment check errors occur. This option is useful when the server is not connected to an SA core.</p> <p>When using the <code>-f</code> option, you must run the Agent installer as root on Unix operating systems and as the administrator on Windows operating systems.</p>
<code>--fingerprint</code>	<p>Specifies the fingerprint of the core certificate.</p> <p>If you specify a value for this option, the Agent installer will verify that the Certificate Authority certificate used to sign the core's SSL certificate matches the value you provided. Specifying a value for this option increases security during the Agent installation process by ensuring that the Agent attaches itself to the correct core.</p> <p>To obtain the correct value for the core certificate fingerprint option, log on to the core as root (you may need to have an SA System Administrator perform this task for you) and run the following command:</p> <pre>/opt/opsware/bin/openssl x509 -in /var/opt/opsware/crypto/agent/opsware-ca.crt -fingerprint -noout</pre> <p>The output looks like the following:</p> <pre>SHA1 Fingerprint=D2:3B:F8:72:B9:55:0D:DE:97:04:D5:C2:A5:6B:B2:09:5C:0A:0D:7F</pre> <p>The fingerprint is the string of hexadecimal numbers following the equal sign:</p> <pre>D2:3B:F8:72:B9:55:0D:DE:97:04:D5:C2:A5:6B:B2:09:5C:0A:0D:7F</pre>

Table 33 Agent Installer Options (cont'd)

Option	Description
--force_full_hw_reg	Causes a full hardware registration to be performed on the server after the Agent is installed. The default is for a minimal hardware registration to be performed. For more information, see Software and Hardware Inventory on page 130.
--force_sw_reg	Causes a software registration to be performed on the server after the Agent is installed. By default, the software registration is not performed until the regularly scheduled time. For more information, see Software and Hardware Inventory on page 130.
--force_virt_reg	Force full virtualization registration (default is no registration).
-h	Displays all the options available with the Agent installer command.
--logfile <path>	Specifies the path and file name of the Agent installer log file. By default, the current directory is set as the path. By default, the log file is: opsware-agent-installer-<date>.log
--loglevel <level>	Sets the log level for log messages. <level> must be one of the following: trace, info, warn, or error. The level error logs the least detail. The level trace logs all messages. By default, the log level is set to info.
--no_anonymous_ssl	Disables anonymous SSL. This option configures the Agent so that browsers cannot connect to its web interface without a valid certificate. This option applies to dormant Agents only. If specified, the dormant Agent will require clients that connect to its web interface to have a valid certificate.
--no_check_reachability	Suppresses a reachability check. The default is to perform a reachability check during fresh installs, and not to perform this check during upgrades.
--no_open_fw	Does not open the Windows firewall to communicate with the SA core. By default, the Agent installer will modify the Windows firewall configuration on Windows 2003 (r2) or Windows 2008 servers to allow the core to contact the managed server on port 1002. If you specify this option, the firewall configuration will not be modified and the server may not be manageable by SA.
--no_opsw_gw	Specifies that no gateway is needed. Either this option or the --opsw_gw_addr option must be specified.
--no_start_agent	Prevents the Agent from starting after installation. By default, the Agent is started immediately after installation. See also Starting an Agent After Installation on page 346.

Table 33 Agent Installer Options (cont'd)

Option	Description
--opsw_gw_addr <host:port>	Specifies the host and port number of the gateways used during Agent installation. Either this option or --no_opsw_gw must be specified.
--password <password>	Specifies the password for the user specified in the --username option. This option is only used by the --customer_id option.
--reboot	<p>Causes the server to be rebooted after the Agent is installed, but only if required.</p> <p>During Agent installation on a Windows server, the Agent installer copies the file ogshcap.dll to the following location:</p> <pre>%SystemRoot%\system32\ogshcap.dll</pre> <p>If the file is open or is in use, the Agent installer is unable to copy this file. The Agent installer then asks the user whether to restart the machine and copies the file after restart.</p> <p>You can also specify --reboot on the command line to initiate the reboot at the end of the Agent installation.</p>
--remediate	Remediates the server against any software policies attached to the server, including all software policies specified in the --software_policy option. For more information, see the <i>SA User Guide: Software Management</i> .
--resetconf -r	Resets the Agent configuration file to the default settings.
--rpm bin <path>	<p>Specifies the path to the RPM handler to use for RPM operations. Use this option, when an RPM handler is already installed on the server.</p> <p>If an RPM handler is not already installed on the server, use the --withrpm option instead to install one.</p> <p>It is not necessary to use this option with the --withrpm option.</p>
--settime -t	<p>Sets the time on the server to that of the core.</p> <p>If the managed server's clock is significantly ahead of the clock on the SA Core, the clock on the managed server will be set back. Since this can cause problems, do not use the --settime option unless you are sure that this scenario is not a problem in your environment.</p> <p>If a managed server's clock is significantly behind the clock on the core, the Agent installation might fail. To install an Agent successfully, use the --settime option or manually set the time and date on the managed server before retrying the Agent installation.</p>

Table 33 Agent Installer Options (cont'd)

Option	Description
--software_policy <ID>	Attaches the software policy <ID> to the server. <ID> must be the name of a software policy in the SA Library. If you want to remediate the software policy immediately, specify the --remediate option. For more information, see the <i>SA User Guide: Software Management</i> .
--spin_host	Specify the host name or IP address of the Data Access Engine component. If you specify this option, you must also specify the --no_opsw_gw option.
--username <name>	Specifies an SA user name. This option requires the --password option. This option is only used by the --customer_id option.
--withmsi	Installs Windows MSI 2.0 along with the Agent. If Windows MSI 2.0 is already installed, this option has no effect. Works with Windows 2000 and Windows 2003 or later.
--withrpm	<p>Installs the RPM handler with the Agent. By default, an Agent is not installed. It is recommended that you always include the --withrpm option when you install Agents on Solaris servers.</p> <p>Use this option only with the Agent installers for Solaris 5.8, 5.9 and 5.10. On Solaris 5.8 and 5.9, RPM 3.0.6 is installed in the directory /opt/opsware/rpm. On Solaris 5.10 x86, RPM 4.4.4 is installed in the directory /opt/opsware/rpm. The RPM database is installed in the directory /opt/opsware/rpm.</p> <p>On AIX, RPM 3.0.5 is installed in the directory /opt/freeware and the RPM database is installed in the directory /var/opt/freeware/lib/rpm.</p> <p>If an RPM handler is already installed, you can use the --rpm bin option.</p>
--workdir <path>	Specifies the path to the Agent installer temporary working directory. Use this option if the default working directory causes problems with installation.

Starting an Agent After Installation

You can manually start the Agent on a server as follows.

Unix:

```
/etc/init.d/opsware-agent start
```

HP-UX:

```
/sbin/init.d/opsware-agent start
```

AIX:

```
/etc/rc.d/init.d/opsware-agent start
```

Windows:

```
net start opswareagent
```

Verifying Agent Functionality

Perform the following steps to verify Agent functionality:

- 1 From the navigation panel in the SA Web Client, click Servers † Manage Servers. The Manage Servers page appears. Browse the list to find the server whose Agent installation you want to verify. If necessary, select the correct customer and facility for the server and click **Update**.

Or

Search for the server whose agent installation you want to verify.

- 2 Verify that the server appears in the Manage Servers list and has the correct properties. See [Searching for Servers Based on Agent Information](#) on page 128 and for more information.
- 3 If you want to discover reasons why a server is unreachable, you can run a Communication Test. See [Running Server Communication Tests](#) on page 139 for more information.

Augmenting the Information for a Managed Server



Use caution when you augment the discovery process for a managed server that is functioning in the operational environment. You might inadvertently install or uninstall software from the server. During the test remediate, verify what software will be uninstalled from the server before you perform the actual remediate operation.

Perform the following steps to augment the information for a managed server:

- 1 Model the OS and other applications running on the server in HP Server Automation by defining the OS with the Prepare Operating System Wizard and by creating nodes and templates for applications running on the managed server.
See the *SA User Guide: OS Provisioning* for more information about operating system definitions.
- 2 Move the server to the appropriate nodes for the OS and installed applications.
The server is tracked in the SA Web Client; however, the server operating system *cannot* be managed while the server is assigned to the generic operating system node. You must reassign the server to the operating system that was defined with the OS Provisioning feature.
- 3 Remediate the server.
- 4 If an IP range group was set up, servers are automatically associated with customers when users install an Agent on the servers. Otherwise, the servers are associated with the Not Assigned customer. To change the customer associated with a server, see [Editing the Properties of a Server](#) on page 237.
- 5 To specify the server's use, stage, and state, edit the server's properties. See [Editing the Properties of a Server](#) on page 237 for more information.

Discovery is complete. HP Server Automation assumes that the server should always be running the specific OS build it has been associated with. Any changes to the OS outside of HP Server Automation are not captured in the model.

Users can deploy and manage new applications on the server, just as if HP Server Automation initially provisioned the server. Users can also deploy OS level patches on the server, or rebuild the OS by using the OS build with which the server was associated.

Uninstalling an Agent on Unix and Windows



To uninstall Agents on Windows NT, Windows Scripting Host 5.1 or Internet Explorer 5.5 must be installed on Windows NT.

Perform the following steps to uninstall an Agent on Unix or Windows:

- 1 Log into Unix as root user. Log into Windows as Administrator.
- 2 Change directories to any directory other than the Agent's installation directory.
- 3 *On Unix*, enter the following command:

```
<installation_directory>/bin/agent_uninstall.sh
```

By default, for Solaris and AIX, the Agent Uninstaller will not remove the SA RPM package. For command line options for the agent uninstaller, including how to activate removal of the SA RPM package, See [Agent Uninstaller Options](#) on page 348 in this appendix for more information.

- 4 *On Windows*, enter the following command:

```
msiexec /x <installation_directory>\bin\agent_uninstall.msi
```

You can also use the Windows Control Panel's Add or Remove Programs option to remove the Agent.

- 5 As the uninstall proceeds, the *Unix* platform `stdout` shows the uninstallation progress. The *Windows* uninstall does not show uninstallation progress.

Agent Uninstaller Options

When you use the Agent Uninstaller, you can include the options that [Table 34](#) and [Table 35](#) show.

Table 34 Agent Uninstallation Unix Options

Option	Description
--uninstallerVersion	Show the uninstaller version.
--help	Show this help.

Table 34 Agent Uninstallation Unix Options (cont'd)

Option	Description
<code>--no_deactivate</code>	Do not deactivate the server; by default, the server is deactivated.
<code>--force</code>	Do not prompt for confirmation before deactivating the server.
<code>--delete_opsw_rpm</code>	Remove the OPSW RPM package (AIX, Solaris only). Use the following commands to remove the RPM package: Solaris: <code>pkgrm -n OPSWrpm</code> AIX: <code>installp -u rpm.rte</code>

Table 35 Agent Uninstallation Windows Options

Option	Description
<code>NO_DEACTIVATE="1"</code>	Do not deactivate the server; by default the server is deactivated.
<code>FORCE="1"</code>	Do not prompt for confirmation before deactivating the server.

During Agent Uninstallation on a Windows server, the Agent Installer removes the `ogshcap.dll` file from the following location:

```
%SystemRoot%\system32\ogshcap.dll
```

If the file is open or is in use, the Agent Installer is unable to remove the `ogshcap.dll` file. The Agent Installer then prompts the user to restart the machine and removes the file after restart.

Uninstalling Earlier Versions of Agents on Unix

Perform the following steps to uninstall Agents versions 5.1 and earlier:

- 1 Stop the Agent on the server by running the following command as root:

Linux:

```
/etc/rc.d/init.d/cogbot stop
```

Solaris:

```
/etc/init.d/cogbot stop
```

HP-UX:

```
/sbin/init.d/cogbot stop
```

AIX:

```
/etc/rc.d/init.d/cogbot stop
```

- 2 Deactivate or delete the server by using the **SA Web Client Server** menu.

- 3 For Linux servers only, run `chkconfig` to de-register the Agent initialization script:

```
% /sbin/chkconfig -del cogbot
```

- 4 As root, delete the following files and directories to remove the Agent files from the server:

Linux:

```
/etc/rc.d/init.d/cogbot
```

Solaris:

```
/etc/init.d/cogbot
```

```
/etc/rc2.d/S79cogbot
```

```
/etc/rc0.d/K44cogbot
```

HP-UX:

```
/sbin/init.d/cogbot
```

```
/sbin/rc2.d/cogbot
```

AIX:

```
/etc/rc2.d/init.d/cogbot
```

```
/etc/rc.d/S79cogbot
```

All Unix:

```
/opt/OPSW
```

```
/var/lc
```

Uninstalling Earlier Versions of Agents on Windows

Perform the following steps to uninstall earlier versions of Agents on Windows:

- 1 Stop the Agent by running the following command as administrator:

```
C:\> net stop shadowbot
```

- 2 Deactivate or delete the server by using the **SA Web Client Server** menu.

- 3 Deregister the Agent service by running the following command as administrator:

```
C:\> "%SystemDrive%\Program  
Files\Loudcloud\blackshadow\watchdog\watchdog.exe" -x
```

- 4 As administrator, delete the following directories to remove the Agent:

```
"%SystemDrive%\Program Files\Loudcloud"
```

```
"%SystemDrive%\Program Files\Common Files\Loudcloud"
```

Agent Upgrade - SA Client

This section describes how to upgrade the SA agent using the SA Client. The SA agent runs on managed servers and enables SA to communicate with and manage your servers.

For more information, see [Installing and Managing Server Agents](#) on page 123.

- 1 From the SA Client navigation pane, select the Devices tab. This displays the Device Groups and Managed Servers nodes.
- 2 Select either one or more managed servers or one or more device groups.

- 3 Right click or select the **Actions** menu and select **Run † Agent Upgrade**. This displays the agent upgrade wizard and the servers and device groups you selected.
- 4 Use the green + and red – buttons to add or remove servers and device groups.
- 5 If you selected any device groups you can specify when the members of the group are determined. For the Server Group Calculation setting:
 - Select Now to have the device group membership calculated once when the job is created. If you schedule the job to run in the future and the device group membership changes, the servers the job runs on will not change. It will only run on the servers in the device group at the time the job was created.
 - Select At Runtime to recalculate the group membership prior to running the job. If you schedule a recurring job, the job will recalculate the device group members each time the job runs.
- 6 Select Next to display the Options window.
- 7 Select the operation you want to perform:
 - Stage Package - Downloads the agent to the specified servers, but does not perform the upgrade.
 - Perform Upgrade - Downloads the agent to the specified servers, unless it was already downloaded, and performs the upgrade.
 - Verify Upgrade - Just checks the agents on the specified servers and reports if the servers have the specified agent version installed.
 - If you want the operation to be performed even if it has already been performed, check the box labelled “Perform stage/upgrade even if not needed.”
- 8 Select the agent version you want to install. You should typically select the highest version number.
- 9 Optionally specify additional parameters to the agent installer. For details, see [Agent Installer Options](#) on page 343.
- 10 At any time, select Start Job to accept the remaining defaults and run the job, or select Next to display the Scheduling window.
- 11 Specify when you want the agent upgrade job to run. Select Next to display the Notifications window.
- 12 Specify email addresses and conditions to receive notifications when the job finishes. Optionally specify a ticket identifier. Select Next to display the Job Status window.
- 13 Select the Start Job or Schedule Job button. This runs the job or schedules it to be run in the future and displays the Job ID number in the window banner. You can use the Job ID number to look up the job under the Jobs and Sessions tab.

When your job finishes, you can select any server to see the job results for that server.

- 14 To see the version of the agent running on a server, select the server in the SA Client and select the Properties view. Scroll down to the Reported Information to see the agent version. For more information, see [Reported Information for Servers](#) on page 74.



The server may not immediately display as reachable in the SA Client. You can wait for the server to display or issue a Communication Test which can shorten the time before the server displays as reachable. See [Running Server Communication Tests](#) on page 139 for more information.

Agent Upgrade Command

This section contains the following topics:

- [Ways to Upgrade Agents](#)
- [Prerequisites for Using the Agent Upgrade Tool](#)
- [Upgrading the Agent on Managed Servers](#)
- [Commands for the Agent Upgrade Tool](#)
- [Options for the Agent Upgrade Tool](#)
- [Example: Options for the Agent Upgrade Tool](#)
- [Example: Commands and Output for Agent Upgrade Tool](#)

Ways to Upgrade Agents

After you upgrade HP Server Automation running in a facility, you should upgrade the Agents on every managed server to the new version, so that you can use the new features in the newly-upgraded core.

HP Server Automation features continue to work on a managed server even when it is running an older Agent. However, new features in the new versions might not be available for that server.

Refer to the *SA Release Notes* for the new version for information about the compatibility of new features with older agents.

You can upgrade the Agents on managed servers in the following ways:

- Use the Agent Installer command to install a new Agent on one server at a time. See [Agent Install Command](#) on page 337 for information on how to use the Agent Installer.
- Use the Agent Upgrade Tool to upgrade Agents on groups of servers. Running the tool upgrades deployed Agents on managed servers. You can run the script simultaneously on many servers to upgrade large groups of Agents.

The Agent Upgrade Tool has the following characteristics:

- It is a command line interface that provides a flexible mechanism for selecting servers to upgrade, and for monitoring and reviewing upgrade operations.
- You can use it to upgrade many Agents on managed servers simultaneously.
- It runs within your preferred Unix shell, allowing it to leverage the power of standard Unix shells and text processing tools.
- You can use it to upgrade a server in any facility running HP Server Automation. You can run it from an OPSH shell attached to any HP Server Automation in any facility.

The OPSH shell is a program that authenticates users in HP Server Automation, starts the user's normal Unix shell (as specified in the standard password database). Use the OPSH shell to run the Agent Upgrade Tool.

Prerequisites for Using the Agent Upgrade Tool

- Locate the appropriate OPSH RPM package in the SA Library for your platform. These packages are named beginning with “OPSWopsh”.
- Download the OPSH RPM package to a core server. See “Exporting a Package” in the *SA User Guide: Software Management* for instructions on downloading a package.
- Install the OPSH RPM on the core server. This places the OPSH shell and the Agent Upgrade Tool in the directory `/opt/opsware/opsh/bin`.
- You need the correct permissions to upgrade Agents. Run the OPSH shell by specifying the SA admin user and password to ensure that you have the appropriate permissions. (Contact your SA administrator to obtain the password.)

When you start an OPSH shell to run the Agent Upgrade Tool, the user name and password are authenticated by HP Server Automation

- The server where you install the `opsh` RPM must be able to resolve the name `way.<facility-domain>` to the host running the Command Engine in the facility’s core. For example, if the Command Engine runs on a host in the `prod.opsware.com` domain, the servers must resolve the name `way.prod.opsware.com`. You specified the `facility-domain` when you installed the core.

Upgrading the Agent on Managed Servers

To upgrade the Agent, perform the following steps:

- 1 After you install the `opsh` RPM on a core server, enter the following command as root to start the OPSH shell:

```
opsh [username@]facility-domain
```

For example:

```
opsh admin@prod.opsware.com
```

See the preceding section for the name resolution requirement for `facility-domain`. See [Commands for the Agent Upgrade Tool](#) on page 354 for more information on `opsh`.

- 2 (Optional) To obtain information about the current Agents running on the managed servers before you upgrade them, enter any of the following commands and options:

```
opsh_agent query server-options
```

(Enter this command if you want to view a report of the Agent versions running on the servers before you upgrade them.)

```
opsh_agent verify server-options schedule-options \  
agent-version
```

(Enter this command if you want to verify the versions of the Agents running on the managed servers before you upgrade them.)

- 3 To upgrade Agents on specified servers, enter the following Agent Upgrade Tool commands and options:

```
opsh_agent stage server-options schedule-options \  
[--always] agent-version
```

(Enter this command if you want to download the package for the Agent to the managed server before you run the upgrade.)

```
opsh_agent upgrade server-options schedule-options \  
[--always] agent-version
```

- 4 (Optional) To review the status of the Agent upgrade, enter the following command and option:

```
opsh_agent review session-id
```

Commands for the Agent Upgrade Tool

- `opsh [username@]facility-domain`

This command starts an OPSH shell and authenticates the user name against the SA facility running at the specified domain.

If you do not specify a user name, the currently logged in user name is used. The OPSH shell prompts for a password.

A new Unix shell (which is attached to the specified SA core-domain) is started. (The password database for the user specifies which Unix shell to use.)
- `opsh_agent query server-options`

This command must be run from an OPSH shell started with the `opsh` command.

This command queries the reported version of Agents and any staging status for the specified servers by examining data in the Model Repository.

One line is printed to stdout for each server that shows device ID, IP address, current Agent version, and any staging status.

You can specify the servers by using the `--device`, `--customer`, `--facility`, and `--os` options.
- `opsh_agent stage server-options schedule-options \
[--always] agent-version`

You must run this command from an OPSH shell started with the `opsh` command.

This command contacts the Agent on each specified server and instructs it to download the package for the specified version of the Agent from the Software Repository.

If the download is successful, the staging status is written to the Model Repository for the server.

To download the package to the server even when this command was entered previously (recorded in the Model Repository), specify the `--always` option.

One line is printed to stdout for each server that shows the device ID, IP address, and a success or failure indicator.

You can specify the servers by using the `--server`, `--customer`, `--facility` and `--os` options.

A session is started and the session ID displays for later review. After the session ID displays, you can type CTRL-C and review the session later using the `opsh_agent review` command.
- `opsh_agent upgrade server-options schedule-options \
[--always] agent-version`

You must run this command from an OPSH shell started with the `opsh` command.

This command contacts the Agent on each specified server and instructs it to upgrade to the specified version. If the necessary package has not been downloaded on the server already (the `opsh_agent stage` command was entered), the package is downloaded from the Software Repository.

If the upgrade is successful, the package is removed from the server and the staging status is deleted from the Model Repository.

To upgrade the Agent even when the specified version of the Agent was already installed on the managed servers, enter the `--always` option. (The Model Repository records when Agents are upgraded on servers.)

One line is printed to stdout for each server that shows the device ID, IP address, and a success or failure indicator.

You can specify the servers by using the `--server`, `--customer`, `--facility`, and `--os` options.

A session is started and the session ID displays for later review. After the session ID displays, you can type CTRL-C and review the session later by using the `opsh_agent review` command.

- `opsh_agent verify server-options schedule-options \`
`agent-version`

You must run this command from an OPSH shell started with the `opsh` command.

This command contacts the Agent on each specified server to verify that it is running the specified version.

One line is printed to stdout for each server that shows the device ID, IP address, the word OLD, NEW, or CURRENT and the actual Agent version running on the server.

You can specify the servers by using the `--server`, `--customer`, `--facility`, and `--os` options.

A session is started and the session ID displays for later review. After the session ID displays, you can enter CTRL-C and review the session later by using the `opsh_agent review` command.

- `opsh_agent review session-id`

You must run this command from an OPSH shell started with the `opsh` command; although, not necessarily the same OPSH shell from which the original command was started.

This command attaches to a running `opsh_agent stage`, `opsh_agent upgrade` or `opsh_agent verify` session running on the Command Engine. It prints the same output to stdout that the original command would have printed if the user had not typed CTRL-C and terminated the command. If the session is complete, it shows the same results that were shown when the session completed.

Options for the Agent Upgrade Tool

Server-options: `--server|-S <svr-spec> --customer|-C <cust-spec>`
`--facility|-F <fac-spec> --os|-O <os-spec>`

If more than one of the `--customer`, `--facility`, or `--os` options is specified, only servers that match all options are selected. Any servers specified by using the `--server` option are added to (or subtracted from) the list specified by combining the `--customer`, `--facility`, and `--os` options.

Table 36 Options for the Agent Upgrade Tool

Long Option	Short Option	Value	Meaning
<code>--server</code>	<code>-S</code>	<code><svr-spec></code>	Server by device ID, IP address, or system name
<code>--customer</code>	<code>-C</code>	<code><cust-spec></code>	All servers associated with the customer specified by the customer ID or name
<code>--facility</code>	<code>-F</code>	<code><fac-spec></code>	All servers in the facility specified by the facility ID or name
<code>--os</code>	<code>-O</code>	<code><os-spec></code>	All servers running the operating system specified by the OS name

Schedule-options: `--when|-W when-time --until|-U until-time`

Table 37 Schedule Options

Long Option	Short Option	Value	Meaning
<code>--when</code>	<code>-W</code>	<code><when-time></code>	<p>Start time for a stage, upgrade, verify, or test operation in the format: MM/DD/YYYY-HH:MM</p> <p>If the <code>--when</code> option is used, the operation starts at the specified time, but the command displays a session ID and returns immediately.</p> <p>When you schedule an operation, you use the <code>review</code> command to review the results after the operation has run.</p> <p>If the <code>--when</code> option is not specified, the operation starts immediately and the command displays the output of the command.</p>

Table 37 Schedule Options (cont'd)

Long Option	Short Option	Value	Meaning
--until	-U	<until-time>	End time for a stage, upgrade, verify or test operation in the format: MM/DD/YYYY-HH:MM If the --until option is specified, the operation stops processing servers at the specified time. Any servers that are not complete are left in a consistent state; this might require that the session run past the specified time.

Miscellaneous options: --ip|-I --always|-A --parallel|-P --theword|-T

Table 38 Miscellaneous Options

Long Option	Short Option	Value	Meaning
--ip	-I	(N/A)	Display IP addresses instead of host names.
--always	-A	(N/A)	Always stage or upgrade servers even if the current version is staged or upgraded.
--parallel	-P	<Concurrency>	The maximum of concurrent commands. (Recommended default = 10)
--theword	-T	<hostname>	The host name or IP address to use when contacting the Software Repository from a server.

Example: Options for the Agent Upgrade Tool

The following table provides examples for running the Agent Upgrade Tool.

Table 39 Examples of Options for the Agent Upgrade Option

Example	Description
--server 1,2	Selects servers 1 and 2.
--facility Y,Z	Selects all servers (for all customers) in facilities Y and Z.

Table 39 Examples of Options for the Agent Upgrade Option (cont'd)

Example	Description
<code>--customer -A,-B --facility Z</code>	Selects all servers in facility Z except those owned by customers A and B.
<code>--server 1,2,-3,-4 --customer A,B --facility Y,Z</code>	Select servers 1 and 2 as well as all servers owned by customers A or B which are in facilities Y or Z except servers 3 and 4.
<code>--server 1,-2 --customer A,B --facility -Y,-Z --os SunOS 5.8</code>	Select server 1 and all servers owned by customers A or B, except those in facilities Y or Z and which are Solaris 5.8 machines excluding server 2.

Example: Commands and Output for Agent Upgrade Tool

```
# cd /opt/OPSWopsh/bin
# ./opsh admin@prod.opsware.com
admin@prod.opsware.com's password:
#
# ./opsh_agent verify --os "SunOS*" 14a.2.12.18
Session 37802500101L
Device ID Name/IP address Version Result Status Reason
410101L core2-1.prod.opsware.com 14a.2.12.18 CURRENT SUCCESS
^C
Interrupted review of running session 37802500101L
Use review 37802500101L command anytime to review session status
#
# ./opsh_agent review 37802500101L
Session 37802500101L
Device ID Name/IP address Version Result Status Reason
410101L d033.prod.opsware.com 14a.2.12.18 CURRENT SUCCESS
670101L dhcp-174.prod.opsware.com 14a.2.12.16 OLDER SUCCESS
1460100L emb218-37.manu.opsware.com 14a.2.12.18 CURRENT SUCCESS
20100L f001.manu.opsware.com 14a.2.12.18 CURRENT SUCCESS
10100L f002.manu.opsware.com 14a.2.12.21 NEWER SUCCESS
210100L m022.manu.opsware.com 14a.2.12.18 CURRENT SUCCESS
Session 37802500101L completed.
```

Agent Upgrade - SA Web Client



The SA Web Client is deprecated for upgrading agents. Use the SA Client to upgrade agents. See [Agent Upgrade - SA Client](#) on page 350 for instructions.

SA includes a custom extension (AgentUpgrade) that you can use to upgrade Agents from the previous three versions.

The Custom Extension feature is accessed through the Run Custom Extension Wizard. This Wizard allows a user to choose a custom extension to run, specify necessary input data for the extension, validate the data required to run the extension, run the extension, and view or download the results from the job. When a user runs a custom extension, the job shows up in My Jobs.

To access the Run Custom Extension Wizard, users must be assigned to a user group that has the permission Wizard: Opsware Extension. When users have this permission, they can run any custom extensions on the servers they have access to in the SA Web Client.

Any user who has the ability to run custom extensions can run the Agent Upgrade Custom Extension.

The Agent Upgrade custom extension only upgrades agents that are not up-to-date. Therefore, rerunning the custom extension on a group of servers will not affect servers that are already running the most recent version of the Agent.

Upgrading Agents with the Agent Upgrade Custom Extension

To run the Agent Upgrade custom extension, perform the following steps:

- 1 From the SA Web Client home page, click the Run Custom Extensions link in the Tasks panel.

Or

From the navigation panel, click Servers † Manage Servers. The Manage Servers list appears. Select the servers on which you want to run a custom extension and choose **Run Extension** from the **Tasks** menu.

The Run Custom Extension Wizard appears.

- 2 Select the “AgentUpgrade” custom extension and click **Next**.

If you have not already selected servers from the Manage Servers list, the Select Servers page appears.

- 3 If prompted, select the servers or groups on which you want to run the custom extension and click **Next**. You can find the servers that you want to run a custom extension on by browsing the list or by searching.

The Agent Upgrade Settings page appears as shown in [Figure 104](#):

Figure 104 Specify Settings Page for the Agent Upgrade Custom Extension

Specify Settings

Enter values for each field (**bold** items are required) to run this extension. Mouse over the note icon (📖) for directions on setting the values correctly.

AgentUpgrade

Operation Mode: Stage Package

Agent Version: 32a.0.1.78

Flags to pass to the agent installer:

Perform stage/upgrade even if not needed: Yes No

- 4 Specify the settings for the custom extension and click **Next**.
 - Select the Agent Upgrade action you want to perform:
 - **Stage Package:** Downloads the Agent Installer package (the binaries) but does not upgrade the Agent.
 - **Perform Upgrade:** Upgrades the servers to the specified Agent version by downloading the Agent Installer package (binaries) if not previously staged. If the Agent Installer package was already staged, upgrades the Agent version by using the staged version of package on the server.
 - **Verify Upgrade:** Check whether all the servers are running the selected Agent version.
 - Select the Agent version to upgrade to. All agent versions available in the Software Repository are displayed in the list. By default, the latest version available in the Software Repository is selected.
 - Enter additional parameters to pass to the Agent Installer. The Agent Upgrade custom extension does not validate the parameters you enter. See [Agent Installer Options](#) on page 343 for information about the parameters you can enter in this field.
 - Specify whether the custom extension should upgrade Agents even if the version of the currently running agent is equal to or greater than the version being upgraded to.

The Confirm Settings Screen appears and displays the selected options.

- 5 Review the values that you entered and the servers that you selected on which to run the Agent Upgrade custom extension. (You can remove servers from the list by deselecting their check boxes. Click the “Show remaining servers” link to display the complete list of selected servers.)
- 6 Click **Next**.
- 7 On the Schedule and Notify page, you have the following options:
 - **Notify:** Choose the Condition option and set the parameters to send an email when the operation is completed. You can choose to have an email sent on any result, if the operation fails, or if the operation is successful. To add another email recipient, click the plus (+) button next to the Recipients field.

- **Schedule:** Choose either **Run Now** to execute the operation immediately, or choose **Specify Time** to schedule the operation for a later time.

When you schedule a job for a server group, you can specify how the members of the group are determined. The membership of a dynamic server group changes based on the changes in your operational environment. If you have “Allow Run Refresh Jobs” permissions, you will see additional options. Select either of the following options:

- **Option 1:** Membership is determined based on the “Time of Confirm Selection.” Select this option to run the job on the servers that were in the group when you scheduled the job. Changes to the group membership do not affect the list of the servers that the job will run on.
- **Option 2:** Membership is updated when the job runs. Select this option to recalculate the group membership prior to running the job. Changes to group membership are reflected in the list of servers that the job will run on.



The time used for the scheduled job is specified in your preferred time zone which can be modified in My Profile. If you do not have the preferred time zone set, the time zone is derived from the SA core server (usually UTC).


- 8 Click **Run** to start the Custom Extension Wizard.

If you selected to run the job at that time, a progress bar appears for the servers on which the extension is running that shows the progress of the job.

- 9 When the custom extension finishes running, you can click **View Details** to see the results. The Custom Extension Results window appears. The results window contains a tab for the operation summary and a tab for the operation details.

By default, the Summary tab is displayed.


Figure 105 Summary Tab in the Details Window of the Agent Upgrade Custom Extension



The Details tab contains a table with one row for each server selected. The table in each tab includes the following columns:

- **Name:** The name of the server
- **Agent Version:** The agent version running on the server after the custom extension completes
- **Reason:** If an operation failed, a text description of the reason the operation failed
- **Result:** (Only shown for Verify operations) Shows the result of the verification:
 - **OLDER:** The agent on the server is older than the selected version
 - **UP TO DATE:** The agent on the server is up to date
- **Status:** The exit status of the command SUCCESS or FAILURE

Figure 106 Details tab in Results Window for the Agent Upgrade Custom Extension



- 10 When you are done viewing the results, click **Close** to close the window.

After you close the wizard, you can view the progress of the custom extension by viewing My Jobs (accessible from the Home page or the navigation panel). Each custom extension job is identified with the name Run Custom Extension. Click the name link to identify which extension was run.

See [Server Management Scheduling and Notification](#) on page 243 for information about the My Jobs feature.

C Global Shell Utilities Syntax

aaa Utility

The aaa utility grants and revokes permissions for operations that use the OGFS. For example, the aaa utility grants permission for the `readServerFilesystem` operation, allowing you to browse a server's file system in the SA Client. To run the aaa utility, you must belong to the Administrators user group.

The permissions granted and revoked by the aaa utility are stored in the `/opsw/Permissions` directory of the OGFS. For details on the contents of the directory, see [/opsw/Permissions Directory](#) on page 381.

aaa Syntax

The aaa utility has the following syntax:

```
aaa shell-perm (grant | revoke) -o operation [-u user-group]
[-f facility | -c customer | -g device-group [-s | -l login]]
```

[Table 40](#) describes the command options and [Table 41](#) lists the operations that can be granted or revoked the aaa utility.

Table 40 AAA Options

Option	Description
<code>-o operation</code>	The operation on which to grant or revoke the permission. For a list of allowed values, see the Operation column in Table 41 .
<code>-u user-group</code>	The SA user group that is assigned the permission. This value is inferred from the current working directory if it corresponds to a user group. If it cannot be inferred, specify a user group.
<code>-f facility</code>	The name, ID, or path to a facility, such as: <code>/opsw/Facility/Chicago</code> Permission will be granted to all servers in this facility.
<code>-c customer</code>	The name, ID, or path to a customer, such as: <code>/opsw/Customer/Alpha</code> Permission will be granted to all servers that belong to this customer.

Table 40 AAA Options (cont'd)

Option	Description
<code>-g device-group</code>	The name, ID, or path to a public device group, such as: /opsw/Group/Public/Unix Servers Permission will be granted to all servers that belong to this group. To specify the device group by name, omit the following: /opsw/Group/
<code>-l login</code>	A login account on the servers that are specified by the <code>-f</code> , <code>-c</code> , or <code>-g</code> option. On a Unix server, for example, the <code>login</code> is the Unix user name. Login accounts with multi-byte characters are not supported.
<code>-s</code>	The login account on the servers (specified by <code>-f</code> , <code>-c</code> , or <code>-g</code>) is the same as the SA user name. (Use of <code>-s</code> is also referred to as defining a reflexive permission.)

aaa Usage Rules

The following usage rules and recommendations apply to the `aaa` utility:

- For operations that are performed on a server, one of the `-f`, `-c`, or `-g` options is required.
- As a best practice, when you are granting permissions, use care when you select servers so that you do not capture more servers than you intend. This is particularly important when using the `-c` or `-f` option. For example, if you want to grant permission to the `loginToServer` operation for all servers in the `Chicago` facility as `root`, you could use the `-f` option to select all servers in a particular facility. However, this may also select Windows servers, which is probably not desired since the `root` user does not typically exist on Windows servers. In this case, you should define a public device group that only includes servers in the `Chicago` facility which are running a Unix operating system.
- If you specify the `-f`, `-c`, or `-g` option, you must also specify either the `-s` or `-l` option. The choice of the `-s` or `-l` option depends on the policies of your organization. If users log into managed servers with generic user names (such as `root`), then you should specify the `-l` option. If users log into managed servers with individual user names, which are the same as their SA user names, they should specify the `-s` option.
- The `-f` and `-c` options are provided as a convenience; however, in general, it is recommended that you define permissions based on device groups instead.
- The `revoke` command can only remove a permission that was previously granted. If the permission was not previously granted, the `revoke` command has no effect.
- The `revoke` command only removes a permission for a specific user group. If a user has overlapping permissions, revoking permissions from a single user group will not prevent the user from performing that operation. For example, suppose a user belongs to two user groups that both have the `launchGlobalShell` permission. If this permission is revoked from only one of those user groups, the user still has the `launchGlobalShell` permission.

aaa Examples

The following example gives all members of the Advanced Users group permission to open a Global Shell session:

```
aaa shell-perm grant -o launchGlobalShell \  
-u 'Advanced Users'
```

The following command allows members of the Advanced Users group to view the file systems as root of all Unix servers:

```
aaa shell-perm grant -o readServerFilesystem \  
-u 'Advanced Users' -g 'Public/All Unix Servers' -l root
```

The next example gives all members of the Unix Admin user group permission to log in as root to all servers in the Public/Trading Servers device group:

```
aaa shell-perm grant -o loginToServer -u 'Unix Admin' \  
-g 'Public/Trading Servers' -l root
```

The following example allows the Advanced Users group to run commands as root on servers associated with the Acme Inc customer.

```
aaa shell-perm grant -o runCommandOnServer \  
-u 'Advanced Users' -c 'Acme Inc' -l root
```

The next example removes the permission for the Unix Admin user group to log into servers that belong to the device group named Public/Unix Servers. The command applies to any login, because the -l option is not specified.

```
aaa shell-perm revoke -o loginToServer -u 'Unix Admin' \  
-g 'Public/Unix Servers'
```

The following example allows the Oracle Users group to log into servers that belong to the device group Oracle Servers as the login oracle. For instance, if the SA user joe belongs to the Oracle Users group, he can log into the servers as the server user oracle.

```
aaa shell-perm grant -u 'Oracle Administrators' \  
-o loginToServer -g '/opsw/Group/Public/Oracle Servers' \  
-l oracle
```

Instead of the -l option, the next example has the -s option, which allows the Oracle Users group to log into servers that belong to the device group Oracle Servers as the login that matches the SA user name. For instance, if the SA user joe belongs to the Oracle Users group, he can log into the servers as the server user joe.

```
aaa shell-perm grant -u 'Oracle Administrators' \  
-o loginToServer -g '/opsw/Group/Public/Oracle Servers' -s
```

Global Shell Operations (Permissions)

The actions that an SA user can perform within the Global Shell are determined by the operations specified by the aaa utility. Most of these operations, such as readServerFilesystem, can be granted on both managed servers and on a login basis. The login is the user name on the managed server, such as the Administrator user on Windows or root on Unix.

A login is not specific to a particular platform (operating system). For example, if the permissions specify that a user can read the file system as root, then root will appear under the files subdirectory, regardless of the platform. The Server Explorer of the SA Client displays the login names that you have been authorized to access that server's file system.

The operations are listed in the `/opsw/Permissions` directory of the OGFS.

Table 41 identifies and describes the server operations in Global Shell. In the table, the On Server column identifies which operations can be granted for a set of managed servers, and the On Login column identifies the operations that can be granted for specific logins (users).

Table 41 Global Shell Operations

Operation (Permission)	Description	On Server	On Login
<code>launchGlobalShell</code>	Launches the Global Shell.	No	No
<code>loginToServer</code>	Opens a shell session on a Unix server. In the SA Client, this is the Remote Terminal feature that opens a terminal window for a Unix server.	Yes	Yes
<code>readServerComplus</code>	Reads COM Plus objects as a specific login. In the SA Client, use the Server Explorer to browse these objects on a Windows server.	Yes	Yes
<code>readServerFilesystem</code>	Reads a managed server as a specific login. In the SA Client, use the Server Explorer to browse the file system of a managed server.	Yes	Yes
<code>readServerMetabase</code>	Reads IIS Metabase objects as a specific login. In the SA Client, use the Server Explorer to browse these objects on a Windows server.	Yes	Yes
<code>readServerRegistry</code>	Reads registry files as a specific login. In the SA Client, use the Server Explorer to view the Windows Registry.	Yes	Yes
<code>relayRdpToServer</code>	Opens an RDP session on a Windows server. In the SA Client, this is the Remote Terminal feature that opens an RDP client window for a Windows server.	Yes	No

Table 41 Global Shell Operations (cont'd)

Operation (Permission)	Description	On Server	On Login
runCommandOnServer	Runs a command or script on a managed server using a <code>rosh</code> operation, where that command or script already exist. In the SA Client, this is used for Windows Services when you use the Server Explorer.	Yes	Yes
runTrustedOnServer	Only for internal use by HP Server Automation. Do not use this operation. HP Server Automation uses this operation for scripts in <code>/opsw/Script/Shared</code> , which implement certain HP Server Automation features. These scripts are provided with HP Server Automation and cannot be created or modified by users.	Yes	Yes
writeServerFilesystem	Modifies files on a managed server as a specific login. In the SA Client, use the Server Explorer to modify the file system of a managed server.	Yes	Yes

rosh Utility

The Remote SA Shell (`rosh`) command makes a client connection that enables you to remotely run programs on managed servers. You invoke the `rosh` command from within a Global Shell session.

rosh Syntax

For servers, the `rosh` command has the following syntax:

```
rosh (-n server-name | -i server-id) [-d dir] [-l login-name]
[-s] [-t | -T] [command [arg ...]]
```

For network devices, the `rosh` command has the following syntax:

```
rosh (-n device-name | -i device-id) [-N] [-C comment]
[-L] [-P parameters] [-s] [-V variables] [command [arg ...]]
```

Table 42 describes the `rosh` options of the preceding syntax statements.

Table 42 Rosh Options and Commands

Option	Description
<code>-C comment</code>	A comment for the log of a network script invocation.
<code>-d dir</code>	Sets the working directory (path) on the remote server. The default is the remote user's home directory.
<code>-i server-id</code>	Specifies the server by its ID, which must already exist in the <code>/opsw/.Server.ID</code> directory.
<code>-l login-name</code>	Specifies the login name of the remote user who performs operations on a remote server, which must already exist in the <code>/opsw/Server</code> directory.
<code>-L</code>	The network script should be run line-by-line.
<code>-m</code>	Network device mode.
<code>-n server-name</code>	Specifies the server by its name, which must already exist in the <code>/opsw/Server</code> directory.
<code>-N</code>	The <code>-i</code> or <code>-n</code> option refers to a network device instead of a server.
<code>-P parameters</code>	Parameters for a network advanced script.
<code>-r</code>	Relays RDP data to a managed server (on Windows).
<code>-s script-name</code>	Treats a command as the name of a saved script that will be sent to and run on the remote server.
<code>-t</code>	Forces the remote session to run in a pseudo terminal (for Unix servers only).
<code>-T</code>	Forces the remote session to run without a pseudo terminal (for Unix servers only).
<code>-V variables</code>	Variables for a network command or advanced script.
<code>-w seconds</code>	Inactivity time out.
<code>-W seconds</code>	Overall time out.
<code>command</code> <code>[args . . .]</code>	Runs a program or saved script.

rosh Usage Rules

The following usage rules apply to the `rosh` program:

- Specify either the `-n` or `-i` option to log into or run programs on a managed server. These options are mutually exclusive, but if both are specified the `-i` option has precedence.
- If neither the `-n`, `-i`, and `id` options are specified, the managed server can be inferred if your working directory is at or below:


```
/opsw/Server/.../server-name/
```

Or

```
/opsw/.Server.ID/server-id/
```

- If `-r` is specified, no other option (excluding `-n` or `-i`) can be specified.
- If `-l` is not specified, the `login-name` can be inferred if your working directory is at or below:

```
/opsw/Server/.../server-name/files/login-name/
```

Or

```
/opsw/.Server.ID/server-id/files/login-name/
```

- If `-s` is specified and `command` is a saved shared script with a `setuid` policy, the `login-name` specified by the `-l` option will be overridden. In this case, the `-l` option may be omitted. These scripts are stored in `/opsw/Script/Shared`.
- If your working directory is not below `server/files/login-name` and `-d` is not specified, the `cwdpath` defaults to the home directory for `login-name`. To default to the home directory, you must specify `-l`.
- For network scripts, if your current working directory is below a network device directory in the OFGS, you do not need to specify the device with `-N`, `-n` or `-i`. The network device is implied by the current working directory.
- For network scripts, if the full path of the script is not specified, `rosh` uses the search path indicated by the `NETWORK_SCRIPT_PATH` environment variable. If this variable is not set, `rosh` searches for the script in these directories:

```
/opsw/Script/Network/Command/
```

```
/opsw/Script/Network/Diagnostic/
```

```
/opsw/Script/Network/Advanced/
```

rosh Operations

The `rosh` command establishes a client connection which enables you to remotely run programs on managed servers. The SA Global Shell feature provides the following modes of operation for `rosh`:

- **jump:** This operation starts a shell session in a pseudo-terminal on a managed server. This mode operates when you do not use the `-s` option and when you do not specify a command or a script. You must have the `loginToServer` permission on the managed server to jump.
- **reach:** This is a remote execution of commands that are native to the platform (operating system) of the managed server. This mode operates when you specify a command. You must have the `runCommandOnServer` permission on the managed server to reach.
- **push:** This is a remote execution of a script on a managed server. The script is stored in the OFGS and is sent to the managed server by `rosh`. You must have the `runCommandOnServer` permission on the managed server.

rosh Examples

The following examples illustrate what these operations look like for an SA user named `psi` at this path:

```
/opsw/Server/@/salish.snv1.corp.opsware.com/files/root/etc
```

```
[psi@m168 etc](538) $ uname -n; id; pwd
m168.dev.opsware.com
uid=59796(psi) gid=59796(psi) groups=59796(psi)
/opsw/Server/@/salish.snv1.corp.opsware.com/files/root/etc
```

The `rosh jump` command would display the following information about the managed server:

```
[psi@m168 etc](539) $ rosh
[root@salish etc]# uname -n; id; pwd
salish.snv1.corp.opsware.com
uid=0(root) gid=0(root)
groups=0(root),1(bin),2(daemon),3(sys),4(adm),6(disk),10(wheel),12(mail),7(lp),4(adm),9(kmem),6(disk),5(tty),3(sys),2(daemon),8(mem)
/etc
[root@salish etc]# logout
```

The `rosh reach` command displays the following information about the managed server:

```
[psi@m168 etc](541) $ rosh "uname -n; id; pwd"
salish.snv1.corp.opsware.com
uid=0(root) gid=0(root)
groups=0(root),1(bin),2(daemon),3(sys),4(adm),6(disk),10(wheel),12(mail),7(lp),4(adm),9(kmem),6(disk),5(tty),3(sys),2(daemon),8(mem)
/etc
```

The `rosh push` command displays the following information about the managed server:

```
[psi@m168 etc](544) $ cat /tmp/who.sh
#!/bin/sh
uname -n
id
pwd
```

```
[psi@m168 etc](543) $ rosh -s /tmp/who.sh
salish.snv1.corp.opsware.com
uid=0(root) gid=0(root)
groups=0(root),1(bin),2(daemon),3(sys),4(adm),6(disk),10(wheel),12(mail),7(lp),4(adm),9(kmem),6(disk),5(tty),3(sys),2(daemon),8(mem)
/etc
```

The following example runs a script on a network device:

```
$ cd /opsw/Network/@/sw-ee-1-2b
$ rosh -s -C 'Updating device location' \
-V 'Location=Opsware - Sunnyvale' 'Set Location'
run script task 8725081 completed successfully.
Results:
Script 'Set Location for Cisco IOS configuration (for drivers: Cisco switches, Catalyst 2950, 3550, 3750 & 8500 series, IOS version 12.x)' completed.
```

swenc Utility

The `swenc` command enables you to switch the character encoding within a Global Shell session.

swenc Syntax

The `swenc` command has the following syntax:

```
swenc [-e encoding] [-T {on | off}] [-E] [-x] [-c command]
```

Table 43 describes the `swenc` options.

Table 43 Swenc Options

Option	Description
<code>-c <i>command</i></code>	Executes <i>command</i> and exits, reverting the session encoding to its previous state.
<code>-E</code>	Lists the valid character encodings.
<code>-e <i>encoding</i></code>	Changes the character encoding of the current session.
<code>-T {on off}</code>	Turns on or off the transcoding of data from the Unix managed server. (Data from Windows servers does not need to be transcoded.) See Transcoded Data in a Managed Server on page 296.
<code>-x</code>	Prevents the launching of a sub-shell.

swenc Usage Rules

The following usage rules apply to the `swenc` utility:

- If you specify no options, `swenc` displays the character encoding and transcoding mode of the current session.
- Unless you specify the `-x` option, `swenc` starts a new sub-shell, which uses the encoding specified with the `-e` option. To leave the sub-shell and revert to the previous encoding, enter `exit`.
- Changing the encoding with `swenc` affects all processes in the current session, including background processes. If you change the encoding while background processes are running, the background processes might encounter errors.
- The `swenc` command affects only the current Global Shell session. For example, if you run the `rosh` command after the `swenc -e` command, the `rosh` command does not inherit the encoding that you changed with the `swenc` command.
- The `swenc` command does not change the working directory of the session, unless the working directory contains path names that cannot be represented in the new encoding. In this case, the working directory is the user's home directory.
- If you change the character encoding, make sure that the encoding of the terminal application that hosts the Global Shell and Remote Terminal sessions is set properly. To view or change the terminal client, go to the Terminal and Shell Preferences of the SA Client.

D OGFS Directories

Directories in the OGFS

The SA Global File System (OGFS) is accessible from within a Global Shell session. Many directories contain similar files. The `id` file contains the HP Server Automation unique identifier (primary key) for the object represented by the directory. The `attr` directory contains text files that describe the attributes of the managed server. The `info` file is deprecated in HP Server Automation 6. Instead of the `info` file, use the files in the `attr` directory. The `self` file represents this specific server object (instance). The `method` directory contains executables that invoke the methods in the SA API. For details on the executables in the `method` directory, see the *SA Platform Developer Guide*.

In the directory listings that follow, the italicized text represents variable paths (specific instances of objects in the data model). For example, *server-1* is the name of a specific managed server. The italicized text in parentheses contains comments.

For more information on the OGFS and the OGS, see [SA Global Shell](#) on page 281.

root (/) Directory

At the `root` level of the OGFS is a directory for each SA user. Each user directory and all files and directories under it are visible only to processes in an authenticated session. Each SA user has the following private directories:

- A home directory which is at `/home/user-name` (SA user name)
- Temporary directories located at `/tmp`, `/var/tmp` and `/usr/tmp`

Each user's home directory contains a `public` directory (`/home/user-name/public`) which is readable by all other SA users and can be used to share files with other SA users. The `root` directory has the following structure:

```
/. (root)
  bin/
  dev/
  etc/
  home/
  lc/
  lib/
  opsw/
  opt/
  proc/
  sys/
  tmp/
  usr/
  var/
```

/opsw Directory

The `opsw` directory represents the data model of HP Server Automation. For example, the `/opsw/Customer` directory represents customer objects in the data model. Global Shell scripts and other client applications can navigate within the data model in the OGFS. Except for the `api` and `bin` directories, all of the directories under the `opsw` directory represent objects. The `api` directory contains executables that invoke methods on the HP Server Automation API. The `bin` directory contains Global Shell utilities such as `rosh` and `aaa`.

For HP Server Automation, the top level of the `opsw` directory has the following structure:

```
/opsw/  
  api/  
  Application/  
  .Application.ID/  
  bin/  
  Customer/  
  .Customer.ID/  
  Facility/  
  .Facility.ID/  
  Group/  
  .Group.ID/  
  Hardware/  
  .Hardware.ID/  
  Library/  
  .Library.ID/  
  NetModel/  
  NetOS/  
  NetType/  
  Network/  
  .Network.ID/  
  OS/  
  .OS.ID/  
  Realm/  
  .Realm.ID/  
  Script/  
  Server/  
  .Server.ID/  
  ServiceLevel/  
  .ServiceLevel.ID/
```

The ID directories organize objects by their unique SA identifier. These directories are equivalent to those organized by name. For example, if a server with an ID 10043 is named `m44.opsware.com`, then the following directories contain the same information:

```
/opsw/.Server.ID/10043  
/opsw/Server/@/m44.opsware.com
```

If the NA is installed, the `/opsw` directory also contains several network directories. See [Network Directories](#) on page 384.

/opsw/Server Directory

The `Server` directory not only contains information about managed servers, but also organizes the servers by their associated objects. For example, the `/opsw/Server/@Group` directory organizes servers by device group.

At the top level, the `/opsw/Server` directory has the following structure:

```
/opsw/Server/  
  @/  
    server-1/  
    server-2/  
    . . .  
  @Application/  
    Application Servers/  
    Database Servers/  
    . . .  
  @Customer/  
    customer-1/  
    customer-2/  
    . . .  
  @Facility/  
    facility-1/  
    facility-2/  
    . . .  
  @Group/  
    Private/  
      private-group-1/  
      private-group-2/  
      . . .  
    Public/  
      public-group-1/  
      public-group-2/  
      . . .  
  @Hardware/  
  @OS/  
  @ServiceLevel/
```

The sections that follow list some of the directory structures under `/opsw/Server`.

/opsw/Server/@ Directory

This directory contains all managed servers. The `files` directory reflects the file system of the managed server. When you modify the file system beneath the `files` directory, you do so as a specific user (such as `login-1`) of the managed server.

The `Interface` directory contains information about the network interface of the server. This directory might contain symbolic links to a network device. See [/opsw/Network Directory](#) on page 384 for more information on these links.

The paths in the following directory structure are under /opsw/Server/@. For example, the full path name of *server-1* in the following structure is

/opsw/Server/@/server-1/.

```
server-1/  
  attr  
  ChangeLog  
  complus  
  CPU/  
    0  
    1  
    . . .  
  CustAttr/  
    custom-attribute-1  
    custom-attribute-2/  
    . . .  
  files/  
    login-1/  
      (file system as seen by login-1)  
    login-2/  
      (file system as seen by login-2)  
    . . .  
  info  
  Interface/  
    network-interface-1/  
    . . .  
  Memory/  
    RAM  
    SWAP  
  metabase/  
    login-1/  
      (metabase as seen by login-1)  
    login-2/  
      (metabase as seen by login-2)  
    . . .  
  method/  
  registry/  
    login-1/  
      (registry as seen by login-1)  
    login-2/  
      (registry as seen by login-2)  
    . . .  
  self  
  Storage/  
    storage-device-1/  
    . . .  
server-2/  
  . . .  
server-3/  
  . . .
```


/opsw/Server/@Facility Directory

This directory filters servers according to their facility:

```
facility-1/
  @ / (all servers in facility-1)
    server-1/
    server-2/
    . . .
  @Group/
    group-1/
      @ / (all servers in both facility-1 and group-1)
        server-1/
        . . .
    group-2/
    . . .
facility-2/
. . .
```

/opsw/Server/@Group Directory

This directory does not contain network devices. This directory filters servers according to their device groups:

```
group-1/
  @ / (all servers in group-1)
    server-1/
    . . .
  child-group-1/
    @ (all servers in child-group-1)
      server-1/
      . . .
  child-group-2/
  . . .
  @Facility/
    facility-1/
      @ (all servers in both group-1 and facility-1)
        server-1/
        . . .
group-2/
  @ / (all servers in group-2)
  . . .
```

/opsw/Library Directory

The Library directory contains information about folders and the objects within folders: application policies, OS sequences, and packages. This directory has the following structure:

```
/opsw/folder-path-1/@/
    AppPolicy/
        app-policy-1/
            attr/
            method/
            self
        app-policy-2/
        . . .
    attr/
    method/
    OSSequence/
        os-sequence-1/
            attr/
            method/
            self
        os-sequence-2/
        . . .
    Package/
        package-1/
            attr/
            method/
            self
        package-2/
        . . .
    self
/opsw/folder-path-2/
. . .
```

Other Directories Under /opsw

This section lists, in alphabetical order, the object directories under /opsw other than the Server, Library, and Net* (network) directories.

/opsw/Application Directory

This directory is deprecated in HP Server Automation 6.0.

This directory represents the SA Software Tree, a hierarchical structure for organizing applications:

```
/opsw/Application/
    Application Servers/
        application-1/
        @/
        CustAttr/
            custom-attribute-1
            custom-attribute-2
```

```

        . . .
        .id
        info
        child-application-1/
        @/
        . . .
        grandchild-application-1/
        @/
        . . .
        grandchild-application-2/
        . . .
        child-application-2/
        . . .
        application-2/
        . . .
Database Servers/
        application-1/
        . . .
Operating System Extras/
        application-1/
        . . .
Other Applications/
        application-1/
        . . .
System Utilities/
        application-1/
        . . .
Web Servers/
        application-1/
        . . .

```

[/opsw/Facility Directory](#)

Typically, a facility identifies the geographical location of a data center, such as a city or building. This directory contains information about facilities and the servers they manage:

```

/opsw/Facility/
        facility-1/
        @/
        attr
        CustAttr/
                custom-attribute-1
                custom-attribute-2
                . . .
        info
        method
        self
        Server/
                server-1/
                server-2/
                . . .
        facility-2/
        . . .

```

/opsw/Group Directory

This directory represents device groups. This directory also contains groups for network devices under the following conditions:

- NA is installed.
- The SA group has the NA-associated attribute set.
- The SA and NA group names are the same.

In the following structure, the *child-group* and *grandchild-group* reflect nested device groups:

```
/opsw/Group/  
    Public/  
        group-1/  
            @/  
                CustAttr/  
                    custom-attribute-1  
                    custom-attribute-2  
                    . . .  
            info  
            Server  
                server-1/  
                server-2/  
                . . .  
            child-group-1/  
                @/  
                    . . .  
                    grandchild-group-1/  
                        @/  
                            . . .  
                            grandchild-group-2/  
                                . . .  
                                child-group-2/  
                                    . . .  
                                    group-2/  
                                        . . .  
    Private/  
        group-1/  
        . . .  
        group-2/  
        . . .
```

/opsw/Library

This directory corresponds to the Library of folders displayed by the SA Client.

```
/opsw/Library/ct  
    folder-1/  
        @/  
            attr  
            method  
            OSSequence  
            self  
            Software
```

```

        SoftwarePolicy
        subfolder-1/
        @/
        . . .
        subfolder-2/
        . . .
        folder-2/
        @/
        . . .

```

/opsw/OS Directory

This directory contains information about the operating systems defined in SA. It does not contain the actual bits for the operating systems, which are stored in the OS Provisioning Media Server. The /opsw/OS directory has the following structure:

```

/opsw/OS/
  os-name-1/
    Not Assigned/
    @/
    CustAttr/
      custom-attribute-1
      custom-attribute-2
      . . .
    info
    Server-1/
      server-1/
      server-2/
      . . .
  os-name-2/
  . . .

```

/opsw/Permissions Directory

This directory contains information about the Global Shell permissions. The `info` directory contains a file for each operation (permission) that can be granted with the `aaa` utility. For each user group, the `operations` subdirectory contains a text file corresponding to an operation (such as `launchGlobalShell`) that have been granted to the group by `aaa`. The contents of these text files summarize the parameters of the permissions for that operation and user group.

For example, the `readServerFilesystem` text file is in the `operations` directory of the **Advanced Users group**:

```

/opsw/Permissions/UserGroups/Advanced Users/operations/
readServerFilesystem

```

The `readServerFilesystem` text file contains the following information:

```

Facility: C40(40) Login: sysadmin
Group: Unix Servers (2880040) Login: root

```

In this example, all members of the **Advanced Users group** can read the file system as user `sysadmin` on servers that belong to Facility `C40` (with ID `40`), and as user `root` on servers that belong to the device group `Unix Servers` (with ID `2880040`).

If a user group directory does not contain a text file for an operation, then the group does not have permission to perform that operation. If the text file is empty, the user group has permission to perform the operation, but the operation has no parameters. The `launchGlobalShell` operation, for example, has no parameters.

The `/opsw/Permissions` directory has the following structure:

```
/opsw/Permissions/
    info/
        launchGlobalShell
        loginToServer
        readServerComplus
        readServerFilesystem
        readServerMetabase
        readServerRegistry
        relayRdpToServer
        runCommandOnServer
        runTrustedOnServer
        writeServerFilesystem
    UserGroups/
        user-group-1/
            description
            operations/
                launchGlobalShell
                loginToServer
                . . .
        user-group-2/
            . . .
```

`/opsw/Realm Directory`

A realm is a logical name for a group of IP addresses that can be contacted by a particular set of SA Gateways. Typically, each Satellite and Facility has one or more distinct realms. To find out which managed servers belong to a realm, note the server names below the `realm/@/Server` subdirectory.

The `Realm` directory has the following structure:

```
/opsw/Realm/
    realm-1/
        @/
            info
            Server/
                server-1/
                server-2/
                . . .
    realm-2/
        . . .
```

/opsw/Script/Shared Directory

This directory contains utility scripts that are included with HP Server Automation. These scripts are not the same as the DSE shared scripts that are accessible with the SA Web Client. The contents of this directory cannot be changed by end users.

```
/opsw/Script/  
    Shared/  
        script-1/  
            description  
            policy  
            source  
            version  
        script-2/  
        . . .
```

/opsw/ServiceLevel Directory

This directory is deprecated in HP Server Automation 6.0.

Service levels are user-defined categories such as Silver, Gold, and Platinum. The /opsw/ServiceLevel directory has the following structure:

```
/opsw/ServiceLevel/  
    service-level-1/  
        @/  
            CustAttr/  
                custom-attribute-1  
                custom-attribute-2  
                . . .  
            .id  
            inf-1/o  
                . . .  
            child-service-level-1/  
                @/  
                . . .  
                grandchild-service-level-1/  
                    @/  
                    . . .  
            child-service-level-2/  
                . . .  
            Server/  
                @/  
                . . .  
    service-level-2/
```

Network Directories

For NA, the top level of the `opsw` directory includes the following subdirectories:

```
/opsw/  
  . . .  
  NetModel/  
  NetOS/  
  NetType/  
  Network/  
  .Network.ID/  
  . . .  
  Script/Network
```

`/opsw/Network` Directory

This directory organizes the devices by their model, OS, type, and group. All network devices are in the `/opsw/Network/@` directory. The `Changelog` directory contains time-stamped events for the device. The `Config` directory contains time-stamped configuration files.

At the top level, the `/opsw/Network` directory has the following structure:

```
/opsw/Network/  
  @/  
    device-1/  
      attr/  
      ChangeLog/  
      Config/  
      info  
      method/  
      Module/  
      Port/  
        port-1/  
          .id  
          info  
          Link/  
        port-2/  
        . . .  
      self  
      Vlan/  
    device-2/  
    . . .  
  @Group/  
  @NetModel/  
  @NetOS/  
  @NetType/
```

The `Port` and `VLAN` directories contain Layer 2 information. Within each subdirectory of the `Port` directory, an `info` file contains duplex information and other data for a specific network port. The `Link` directory contains a symbolic link to a server interface or a port on another network device (if the MAC address to the interface or port is available). In the following example, the `eth0` under `Network` is a symbolic link to `eth0` under `Server`:

```
/opsw/Network/@/sw-ee-1-2b/Port/FastEthernet0_1/Link/eth0  
  symbolic link to -->
```



```
/opsw/Server/@/m180.mycomp.com/Interface/eth0
```

Similarly, the Server directory can have a symbolic link to the corresponding entry under Network:

```
/opsw/Server/@/x.mycomp.com/Interface/eth0/Link/FastEthernet0_7
    symbolic link to -->
/opsw/Network/@/sw-ee-2-4a/Port/FastEthernet0_7/eth0
```

/opsw/Network/@Group Directory

This directory does not contain groups for managed servers. This directory filters network devices according to their groups:

```
group-1/
  @/ (all devices in group-1)
    device-1/
      . . .
  @NetModel/
  @NetOS/
  @NetType/
  child-group-1/
    @ (all devices in child-group-1)
      device-1/
        . . .
  child-group-2/
    . . .
group-2/
  @/ (all devices in group-2)
  . . .
```

/opsw/NetModel Directory

This directory contains subdirectories for vendors, for example, /opsw/NetModel/Cisco. The /opsw/NetModel directory has the following structure:

```
vendor-1/
  model-1/
    @/
    @Group/
    @NetOS/
    @NetType/
  model-2/
  . . .
vendor-2/
. . .
```

/opsw/NetOS Directory

This directory organizes devices by their operating system. The /opsw/NetModel directory has the following structure:

```
family-1/
  os-1/
    @/
    @Group/
    @NetOS/
    @NetType/
  os-2/
  . . .
. . .
family-2/
. . .
```

/opsw/NetType Directory

This directory organizes network devices by the following types:

```
Firewall
L3Switch
L4to7Switch
Proxy
Router
Switch
unknown
VPN
Wireless Access Point
WirelessAP
```

The /opsw/NetType directory has the following structure:

```
type-1/
  @/
  @Group/
  @NetOS/
  @NetType/
type-2/
. . .
```

/opsw/Script/Network Directory

This directory contains utility scripts for network devices. For information about these scripts, see the NA documentation.

```
/opsw/Script/Network/
  Advanced/
  Command/
  Diagnostic/
```

Index

A

aaa utility, 363

accessing

Device Explorer, 69

SA Client, 23

SA Web Client, 168

adding

custom attributes for servers, 249

servers and server groups, 225

servers to My Servers, 182

server to device groups, 103

service levels, SA Web Client to, 251

Agent

Agent upgrade tool, 352

installation and functionality, verifying, 347

Installer, 337

Installer options, 343

installing, 341

running, in a dormant mode, 338

Uninstaller options, 348

uninstalling, 348

Agent Installer

command line options, 343

uninstaller options, 348

Agent to Command Engine (CE)

connection time-out, 318

DNS does not resolve, 319

gateway

gateway could not connect to server, 321

gateway denied access, 320

gateway time-out, 321

internal gateway error, 321

name resolution error on gateway, 320

no gateway defined, 320

no callback from agent, 321

OK, 318

old agent version, 319

realm is unreachable, 319

tunnel setup error, 320

Agent to Data Access Engine (DAE)

connection refused, 323

connection time-out, 323

DNS does not resolve, 323

gateway

gateway could not connect to server, 325

gateway denied access, 324

gateway time-out, 325

internal gateway error, 325

name resolution error on gateway, 325

no gateway defined, 324

tunnel setup error, 324

OK, 322

old agent version, 323

realm is unreachable, 324

unexpected error, 322

untested, 322

Agent to Software Repository (SWR)

connection refused, 327

connection time-out, 327

DNS does not resolve, 327

gateway

gateway could not connect to server, 330

gateway denied access, 329

gateway time-out, 330

internal gateway error, 330

name resolution error on gateway, 329

no gateway defined, 329

internal setup error, 329

OK, 326

realm is unreachable, 328

server identification error, 328

unexpected error, 326

untested, 326

asset tracking, overview, 175

Audits, browsing, Device Explorer, 78

B

browsers

configuring, 167

supported, 167

browsing

job logs in the SA Client, 46

C

changing

custom field values, 248

use and stage values, servers for, 239

- character encoding
 - See encoding, 294
 - checking
 - management IP of managed server, 333
 - network gateway configuration, 334
 - cloning, servers, 240
 - COM+ objects
 - browsing, Device Explorer, 90
 - Command Engine to Agent (AGT)
 - connection
 - refused, 313
 - time out, 313
 - gateway
 - gateway could not connect to server, 315
 - gateway denied access, 315
 - gateway time-out, 315
 - internal gateway error, 315
 - OK, 312
 - realm is unreachable, 314
 - request time-out, 313
 - server not registered with Command Engine, 314
 - tunnel setup error, 315
 - unexpected error, 312
 - untested, 312
 - command line interface
 - commands, command options for, 302
 - common options, 302
 - unique options for oupload command, 304
 - Common Troubleshooting Tasks
 - checking, management IP of managed server, 333
 - checking, network gateway configuration, 334
 - resolving, hostname, 334
 - restarting, an Server Agent, 333
 - verify that agent is running, 332
 - verify that port is open on managed sever, 333
 - Communication Test
 - about, 140
 - errors, 141
 - types of, 140
 - components
 - Device Explorer of, 69
 - configuring, browsers, 167
 - Connection Refused
 - Agent to Command Engine (CE), 318
 - Agent to Data Access Engine (DAE), 323
 - Agent to Software Repository (SWR), 327
 - Command Engine to Agent (AGT), 313
 - Connection Time-out
 - Agent to Command Engine (CE), 318
 - Agent to Data Access Engine (DAE), 323
 - Agent to Software Repository (SWR), 327
 - Command Engine to Agent (AGT), 313
 - copying
 - files, Device Explorer's File System of, 88
 - creating
 - configuration template, 90
 - device groups using search, 113
 - dynamic device groups, 106
 - package, 90
 - reports, agent installation status on, 138
 - scripts, 261
 - server groups, 215
 - dynamic groups, 217
 - static groups, 215, 217
 - static device groups, 102
 - Crypto Match (CRP)
 - certificate mismatch, 316
 - OK, 316
 - SSL negotiation failure, 317
 - unexpected error, 316
 - untested, 316
 - custom attributes
 - adding, for servers, 249
 - deleting, for servers, 250
 - editing, for servers, 250
 - managing, overview, 249
 - overview, 172
 - customers
 - Customer Independent, definition of, 144
 - Not Assigned customer, definition of, 144
 - overview, 199
 - custom fields
 - changing value, 248
- ## D
- deactivating a server, 96
 - deleting
 - custom attributes, for servers, 250
 - device groups, 116
 - files, Device Explorer's File System of, 89
 - scripts, 268
 - servers, 238
 - Device Explorer
 - accessing, 69
 - compliance, overview, 76
 - creating, configuration template, 90
 - creating, package, 90

- File System
 - copying, files, 88
 - deleting, files, 89
 - renaming, files, 89
 - viewing, contents, 88
 - working with, 87
- installed patches, overview, 90
- main components, 69
- opening, remote terminal, 71, 97
- overview, 68
- server properties, overview, 72, 118
- server summary, overview, 71
- services, overview, 91
- Software Policies, overview, 78
- viewing
 - packages, 85
- Windows IIS Metabase, overview, 91
- Windows Registry, overview, 90
- device group
 - creating, 102, 106, 113
- device groups
 - about, 99
 - adding servers, 103
 - deleting, 116
 - device group explorer, 116
 - duplicating, 115
 - dynamic, 101
 - moving, 114
 - private, 101
 - public, 101
 - removing servers, 105
 - static, 101
- DHCP
 - configuring for servers, 257
- Discovery and Agent Deployment
 - creating reports, 138
 - installing, Server Agents, 125
 - opening remote terminal sessions, unmanaged server to, 137
 - permissions required, 123
 - specifying
 - deployment actions, 134
 - login settings, 134
- DNS, configuring for servers, 256
- DNS Does Not Resolve
 - Agent to Command Engine (CE), 319
 - Agent to Data Access Engine (DAE), 323
 - Agent to Software Repository (SWR), 327
- domains, changing for Windows servers, 258
- duplicating
 - device groups, 115
- duplicating, server groups, 227

- dynamic, server groups, 212
- dynamic device group, 101

E

- editing
 - custom attributes, for server, 250
 - server properties, 237
 - service levels, 252
- encoding
 - Global Shell and Remote Terminal, 44
 - managed server, 74
 - multi-byte characters, 298, 364
 - OGFS, 294
 - Terminal and RDP preferences, 44
 - transcoding, 296
 - viewing file contents, 88
- errors
 - Communication Test, 141
- examples
 - Agent Installer, commands & options, 342
 - searching, ways to, 196
 - swapping servers' disks, 199
- executing
 - OGFS script, 277
 - scripts, 268
 - server script, 269
- executing scripts, 268
- exporting
 - scripts, 267

F

- File System
 - copying, files, 88
 - deleting, files, 89
 - overview, 87
 - renaming, files, 89
 - viewing, contents, 88
- firewall, 289

G

- Gateway Could Not Connect to Server
 - Agent to Command Engine (CE), 321
 - Agent to Data Access Engine (DAE), 325
 - Agent to Software Repository (SWR), 330
 - Command Engine to Agent (AGT), 315
- Gateway Denied Access
 - Agent to Command Engine (CE), 320
 - Agent to Data Access Engine (DAE), 324
 - Agent to Software Repository (SWR), 329
 - Command Engine to Agent (AGT), 315

- Gateway Time-out
 - Agent to Command Engine (CE), 321
 - Agent to Data Access Engine (DAE), 325
 - Agent to Software Repository (SWR), 330
 - Command Engine to Agent (AGT), 315

- Global File System
 - accessing with ssh, 289
 - copying files to, 292

- Global Shell
 - error messages, 297
 - overview, 281
 - remote shell, 366
 - remote terminal, 297
 - server operations in, 366
 - setting, permissions, 363

H

- hard disks, swapping for servers, 199

- histories
 - viewing, for servers, 201

I

- IIS Metabase
 - browsing, Device Explorer, 90

- installing
 - Agents
 - augmenting for servers, 347
 - commands and options, examples, 342
 - preparing for, 338
 - using CLI, 341
 - verification of, 347
 - SA command line interface, 300
 - Server Agents
 - using ODAD, 125

- Internal Gateway Error
 - Agent to Command Engine (CE), 321
 - Agent to Data Access Engine (DAE), 325
 - Agent to Software Repository (SWR), 330
 - Command Engine to Agent (AGT), 315

- IP addresses
 - configuring for servers, 256
 - management IP
 - definition of, 206
 - viewing, 207
 - primary for servers, setting, 208
 - primary IP, definition of, 206
 - searching for servers by, 196
 - setting for servers, 208

- IP ranges
 - overview, 255

J

- jobs
 - scheduling for servers, 243
 - time outs for, 246

- jump, 369

L

- LANG environment variable, 295
- LC_CTYPE environment variable, 295
- loginToServer, 369

M

- Machine ID Match (MID)
 - MID mismatch, 331
 - OK, 331
 - unexpected error, 331
 - untested, 331

- management IP
 - definition of, 206

- managing
 - custom attributes, 249

- Microsoft Terminal Services, 44

- modeling, public server groups, 212

- moving
 - device groups, 114

- My Customers, overview, 170

- My Jobs
 - Browsing job logs in the SA Client, 46
 - overview, 169

- My Servers
 - overview, 173
 - servers, adding to, 182
 - servers, removing from, 183

N

- Name Resolution Error On Gateway
 - Agent to Command Engine (CE), 320
 - Agent to Data Access Engine (DAE), 325
 - Agent to Software Repository (SWR), 329

- NAT tables
 - changing, affects of, 208
 - See also* static NAT.

- navigating
 - SA Client, 23
 - SA Web Client, 170

- navigation panel, overview, 172

- network

- configuring for servers
 - overview, 256
- network scripts, 368, 369, 370
- no callback from Agent, Agent to Command Engine (CE), 321
- No Gateway Defined
 - Agent to Command Engine (CE), 320
 - Agent to Data Access Engine (DAE), 324
 - Agent to Software Repository (SWR), 329
- notifying, jobs, 245

O

- OK
 - Agent to Command Engine (CE), 318
 - Agent to Data Access Engine (DAE), 322
 - Agent to Software Repository (SWR), 326
 - Command Engine to Agent (AGT), 312
 - Crypto Match (CRP), 316
 - Machine ID Match (MID), 331
- Old Agent Version
 - Agent to Command Engine (CE), 319
 - Agent to Data Access Engine (DAE), 323
 - Agent to Software Repository (SWR), 327
- opening
 - remote terminal, 71, 97
 - remote terminal, managed server to, 298
 - remote terminal session, unmanaged server, 137
 - scripts, 264
- options
 - unmanaged servers, SA Client, 40
- overview
 - script execution, 259

P

- packages
 - viewing
 - installed packages, 85
- permissions
 - ODAD, required for, 123
 - scripts, 60
 - server groups, required for, 210
 - setting
 - Global Shell permissions, 363
- port open on managed server, verifying, 333
- preferences
 - general options, SA Client, 39
 - terminal and shell, SA Client, 42
- preparing, installing Agents, for, 338
- primary IP, definition of, 206

- private, server groups, 211
- private device groups, 101
- properties
 - editing for servers, 237
 - servers, overview, 232
- public, server groups, 211
- public device group, 101
- push, 369
- PuTTY, 43

Q

- QNumber, 85, 86, 119

R

- RDP, 43
- reach, 369
- Realm is Unreachable
 - Agent to Command Engine (CE), 319
 - Agent to Data Access Engine (DAE), 324
 - Agent to Software Repository (SWR), 328
 - Command Engine to Agent (AGT), 314
- rebooting a server, 96
- registry (Windows), browsing, Device Explorer, 90
- remote shell
 - modes of operation, 369
 - options and commands, 368
 - overview, 366
- remote terminal
 - opening
 - managed server for, 298
 - overview, 71, 97
 - unmanaged servers to, 137
 - overview, 297
- removing
 - Agent, UNIX and Windows, 348
 - earlier versions of Agents from servers
 - UNIX, 349
 - Windows, 350
 - servers
 - from My Servers, 183
 - from server groups, 226, 227
 - from service levels, 254
 - servers from a device group, 105
- renaming
 - scripts, 268
- renaming files, Device Explorer's File System of, 89
- reports
 - overview, 200

Request Time-out, (AGT), 313

resolving

hostname, 334

restarting, an Server Agent, 333

rosh. *See* remote shell.

rsync, 292

RunCommandOnServer, 369

S

SA

server attributes, 239

supported operating systems, 176

SA Client

accessing, 23

general options, 39

overview, 17

terminal and shell preferences, 42

unmanaged servers options, 40

SA model space, 283

SA Web Client

accessing, 168

administration features, 171

Environment, in navigation, 171

Home page, overview, 171

icons for servers, defined, 64, 232

icon tooltips, 173

My Customers, overview, 170

My Jobs

in navigation, 171

overview, 169

My Servers, overview, 173

navigating, overview, 172

navigation panel, overview, 170

Reports, in navigation, 171

server lists, filtering, 181

Servers, in navigation, 171

Software, in navigation, 171

tasks, overview, 169

ways to search, 184

SA Web Client. *See* SA Web Client.

scan timeout (SAV), 46

scheduling

server jobs, 243

time outs affecting, 246

scp, 292

script execution, 268

creating, 261

deleting, 268

editing scripts

editing

scripts, 266

executing OGFS script, 277

executing server script, 269

exporting, 267

opening a script, 264

overview, 259

process, 260

renaming, 268

types, 260

viewing script history, 267

scripts, 60

Distributed Scripts

overview, 149, 259

searching

details, 195

examples of, 196

IP addresses, 196

overview, search feature of, 173

Search box, 183

search feature, 184, 195

ways to, 184

security

Server Agents, on servers, 129

server management, 129

server

deactivating, 96

rebooting, 96

Server Agent

Communication Test, 139

installing, using ODAD, 125

limits of functionality on servers, 129

restarting, 333

server data tracked by, 130

starting and stopping, 127

server attributes

overview, 239

server groups

adding, servers and server groups to, 225

characteristics, 210

creating, 215

dynamic groups, 217

static groups, 215, 217

criteria for search, 219

duplicating, 227

modeling, public groups, 212

overview, 209

permissions, required, 210

removing, servers and server groups to, 226, 227

types

dynamic, 212

private, 211

public, 211

static, 211

- using, server search, 218
 - server life cycle, SA, 230
 - server lists
 - filtering, 181
 - overview, 179
 - server management
 - functions, 205
 - notifying, jobs, 245
 - scheduling, tasks, 243
 - server life cycle tasks, 236
 - Server Not Registered, Command Engine to Agent (AGT), 314
 - Server Pool
 - overview, 179
 - servers
 - asset tracking, overview, 175
 - assigning to service levels, 254
 - changing, use and stage values, 239
 - changing value, custom field for, 248
 - cloning, 240
 - custom attributes, deleting, 250
 - data tracked by Server Agents, 130
 - deactivating, 238
 - deleting from SA, 238
 - DHCP, configuring, 257
 - domains for Windows servers, changing, 258
 - filtering in server lists, 181
 - histories, viewing, 200
 - identifying, 198
 - installing Agents
 - augmenting, 347
 - verifying, 347
 - jobs
 - scheduling, 243
 - management of, 179
 - My Servers, removing from, 183
 - network configuration
 - configuring, 256
 - overview, 255
 - opening, remote terminal, 71, 97
 - opening remote terminal sessions, unmanaged server to, 137
 - preparing for installing Agents, 338
 - primary IP addresses, setting, 208
 - properties
 - editing, 237
 - overview, 232
 - Search box, using, 183
 - search feature, using, 184
 - searching by IP address, 196
 - searching for, 183
 - See also* server groups.
 - service levels, removing from, 254
 - swapping disks, examples, 199
 - viewing
 - packages, 85
 - server search, using, 218
 - Service Automation Visualizer (SAV)
 - virtualization settings, 45
 - service levels
 - adding individual, 251
 - assigning servers to, 254
 - editing, 252
 - overview, 251
 - removing, servers from, 254
 - ways to view for servers, 252
 - services
 - overview, 91
 - setting
 - Global Shell permissions, 363
 - primary IP address, server of, 208
 - setup for servers
 - preparation for installing Agents, 338
 - sftp, 292
 - Software Policies, browsing, Device Explorer, 78
 - specifying
 - deployment actions, ODAD in, 134
 - login settings, ODAD in, 134
 - ssh, 289
 - stage values, overview for servers, 239
 - static, server groups, 211
 - static device group, 101
 - static NAT
 - changing NAT tables, affects of, 208
 - supported, browsers, 167
 - supported operating systems
 - for managed servers, 176
- ## T
- telnet, 42
 - time outs
 - server management jobs, 246
 - transcoding, 296
 - troubleshooting
 - unreachable servers, 311
 - Tunnel Setup Error
 - Agent to Command Engine (CE), 320
 - Agent to Data Access Engine (DAE), 324
 - Agent to Software Repository (SWR), 329
 - Command Engine to Agent (AGT), 315
 - types of, server groups, 211

types of scripts, 260

U

Unexpected Error

- Agent to Command Engine (CE), 318
- Agent to Data Access Engine (DAE), 322
- Agent to Software Repository (SWR), 326
- Command Engine to Agent (AGT), 312
- Machine ID Match (MID), 331

uninstalling

- Agent, UNIX and Windows, 348
- earlier versions of Agents from servers
 - UNIX, 349
 - Windows, 350

Untested

- Agent to Command Engine (CE), 318
- Agent to Data Access Engine (DAE), 322
- Agent to Software Repository (SWR), 326
- Command Engine to Agent (AGT), 312
- Crypto Match (CRP), 316
- Machine ID Match (MID), 331

upload, options for CLI, 304

use values, overview for servers, 239

using, server search, 218

V

verifying

- agent is running, 332
- port is open on managed server, 333

viewing

- contents, Device Explorer's File System of, 88
- history
 - server, 201
- job details in the SA Client, 243
- job details in the SA Web Client, 242
- packages, 85
- script history, 267
- service levels, ways to, 252

Virtualization Director

- scan time out preference, 46
- virtualization settings, 45

W

Windows servers

- changing, domains, 258

wizards

- Distributed Script Execution, 259

working with

- Device Explorer's File System, 87