



# HP ALM

Software Version: 12.21

## Administrator Guide

Document Release Date: June 2015  
Software Release Date: June 2015

## Legal Notices

### Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

### Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

### Copyright Notice

© Copyright 2002 - 2015 Hewlett-Packard Development Company, L.P.

### Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

This product includes an interface of the 'zlib' general purpose compression library, which is Copyright © 1995-2002 Jean-loup Gailly and Mark Adler.

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to:  
<https://softwaresupport.hp.com>.

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to <https://softwaresupport.hp.com> and click **Register**.

## Support

Visit the HP Software Support Online web site at: <https://softwaresupport.hp.com>

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to: <https://softwaresupport.hp.com> and click **Register**.

To find more information about access levels, go to:  
<https://softwaresupport.hp.com/web/softwaresupport/access-levels>.

## HP Software Solutions & Integrations and Best Practices

Visit **HP Software Solutions Now** at <https://h20230.www2.hp.com/sc/solutions/index.jsp> to explore how the products in the HP Software catalog work together, exchange information, and solve business needs.

Visit the **Cross Portfolio Best Practices Library** at <https://hpln.hp.com/group/best-practices-hpsw> to access a wide variety of best practice documents and materials.

# Contents

Welcome to this Guide .....	12
How This Guide is Organized .....	12
 Part 1: Site Administration .....	13
Chapter 1: Site Administration at a Glance .....	15
Starting Site Administration .....	16
Understanding Site Administration .....	17
Defining Site Administrators .....	19
Chapter 2: Creating Projects .....	21
About Creating Projects .....	22
Understanding the Project Structure .....	22
Creating Domains .....	23
Creating Projects .....	24
Copying Projects .....	31
Importing Projects .....	37
Creating Template Projects .....	41
Creating a Template Project .....	43
Creating a Template from an Existing Template .....	47
Creating a Template from an Existing Project .....	52
Importing a Template Project .....	56
Linking a Template to Projects .....	60
Updating Project Details .....	61
Assigning Users to Projects .....	65
Assigning Project Administrators .....	66
Enabling Extensions for a Project .....	67
Chapter 3: Managing the Optimized Project Repository .....	71
Project Repository Cleanup .....	72
Browsing the Project Repository .....	72
Realigning Repositories .....	74
Chapter 4: Managing Projects .....	77
About Managing Projects .....	78
Querying Project Tables .....	78
Exporting Projects .....	79
Deactivating and Activating Projects .....	80
Enabling and Disabling Version Control for a Project .....	80
Pinging Projects .....	81
Renaming Projects .....	81
Converting Projects to Unicode .....	82
Removing Projects .....	84
Deleting Projects .....	85
Deleting Domains .....	85
Editing the Connection String .....	86

Restoring Access to Projects .....	86
Renaming the Defects Module for a Project .....	88
Limiting Records Displayed in Grids .....	89
Chapter 5: Upgrading Projects to a New Version .....	91
About Upgrading Projects .....	92
Understanding the Version/Patch Numbering Scheme .....	92
About Upgrading Projects for Major and Minor Versions .....	92
Verifying Domains and Projects .....	96
Verifying a Project .....	96
Verifying a Domain .....	97
Repairing Domains and Projects .....	98
Repairing a Project .....	99
Repairing a Domain .....	100
Upgrading Domains and Projects .....	102
Upgrading a Project .....	102
Upgrading a Domain .....	104
Defining an Exception File .....	105
Backing Up Projects .....	106
Restoring Projects .....	107
Restoring Projects from a Microsoft SQL Database Server .....	108
Restoring Projects from an Oracle Database Server .....	108
Restoring a Repository from the File System .....	109
Restoring LAB_PROJECT .....	109
Migrating the Repository .....	110
Repository Migration Status Window .....	111
Configure Migration Priority .....	113
LAB_PROJECT Post Upgrade Steps .....	113
About Upgrading Projects for Minor-Minor Versions .....	114
Setting Project Priorities for Upgrading Minor-Minor Versions .....	116
Chapter 6: Managing ALM Users .....	117
About Managing Users .....	118
Adding a New User .....	118
Importing Users from LDAP .....	120
Enabling LDAP over SSL .....	122
Defining LDAP Settings for Importing Users .....	123
Handling User Name Conflicts .....	125
Updating User Details .....	126
Deactivating and Activating Users .....	127
Creating and Changing Passwords .....	128
Locking Out Users .....	128
Enabling Authentication for Users .....	129
Assigning Projects to Users .....	131
Exporting User Data .....	132
Deleting Users .....	133
Chapter 7: Managing User Connections and Licenses .....	135
About Managing User Connections and Licenses .....	136

Monitoring User Connections .....	136
Sending Messages to Connected Users .....	137
Managing Licenses .....	138
Modifying Licenses .....	139
Assigning Licenses to Domains and Projects .....	140
Assigning Licenses to Users .....	141
PPU Licenses History .....	142
Chapter 8: Configuring Servers and Parameters .....	145
About Configuring Servers and Parameters .....	146
Configuring Server Information .....	146
Defining New Database Servers .....	148
Modifying Database Server Properties .....	150
Configuring Text Search .....	152
Enabling Text Search on Database User Schemas .....	152
Enabling Text Search in ALM .....	152
Selecting a Text Search Language for a Project .....	153
Defining Searchable Fields .....	154
Setting ALM Configuration Parameters .....	155
Setting the ALM Mail Protocol .....	156
Setting ALM Mail Restrictions .....	157
Chapter 9: Analyzing Site Usage .....	159
About Analyzing Site Usage .....	160
Monitoring Site Usage .....	160
Filtering Site Usage .....	161
Exporting Site Analysis Data to a File .....	162
Customizing the Site Analysis Line Chart Graph .....	162
Chapter 10: Scheduling Calculations for Project Planning and Tracking (PPT) .....	165
About Scheduling Calculations for PPT .....	166
Scheduling Calculations for a Site .....	166
Enabling or Disabling Automatic Calculations for a Project .....	166
Launching Calculations for a Project Manually .....	167
Project Planning and Tracking Tab .....	168
Chapter 11: ALM Advisor .....	171
About ALM Advisor .....	172
Collecting and Assessing ALM Data .....	176
Chapter 12: QC Sense .....	179
About QC Sense .....	180
QC Sense Configuration .....	180
QC Sense Monitors .....	182
Configuring QC Sense .....	182
QC Sense Server Configuration Window .....	183
Connection String Builder Dialog Box .....	186
Generating and Viewing QC Sense Reports .....	187
QC Sense Schema .....	188
PERF_CLIENT_OPERATIONS .....	188
PERF_CLIENT_METHODS_CALLS .....	189

PERF_CLIENT_REQUESTS .....	190
PERF_SERVER_THREADS .....	192
PERF_SERVER_SQLS .....	193
PERF_SERVER_GENERAL_MEASURES .....	193
PERF_SERVER_THREAD_TYPES .....	194
Chapter 13: Installing HP ALM Tools and Add-ins .....	197
<b>Part 2: Project Customization .....</b>	<b>199</b>
Chapter 14: Project Customization at a Glance .....	201
Starting Project Customization .....	202
Understanding the Project Customization Window .....	204
Saving Customization Changes .....	206
Chapter 15: Managing Users in a Project .....	207
About Managing Users in a Project .....	208
Adding a User to a Project .....	208
Assigning Users to a User Group .....	209
Removing a User from a Project .....	210
Chapter 16: Managing User Groups and Permissions .....	211
About Managing User Groups and Permissions .....	212
Adding User Groups .....	212
Assigning Users to Groups .....	213
Setting User Group Permissions .....	214
Setting Transition Rules .....	216
Owning ALM Objects .....	217
Hiding Data for a User Group .....	219
Renaming User Groups .....	220
Deleting User Groups .....	220
Understanding Permission Settings .....	221
Customizing Module Access for User Groups .....	222
Chapter 17: Customizing ALM Projects .....	223
About Customizing ALM Projects .....	224
Customizing Project Entities .....	224
Adding User-Defined Fields .....	228
Modifying System and User-Defined Fields .....	228
Deleting User-Defined Fields .....	229
Defining Input Masks .....	229
Customizing Project Requirement Types .....	231
Creating Requirement Types .....	233
Customizing Requirement Types .....	233
Renaming Requirement Types .....	235
Deleting Requirement Types .....	235
Customizing Project Lists .....	236
Creating Lists .....	237
Renaming Lists, Items, or Sub-Items .....	237
Deleting Lists, Items, or Sub-Items .....	238
Chapter 18: Configuring Automail .....	241

About Setting Automail .....	242
Designating Automail Fields and Conditions .....	242
Customizing the Subject of Defect Mail .....	244
Chapter 19: Customizing Risk-Based Quality Management .....	245
About Customizing Risk-Based Quality Management .....	246
Customizing Risk-Based Quality Management Criteria .....	246
Customizing criteria and Values .....	247
Customizing Weight Boundaries .....	248
Customizing Risk Calculations .....	251
Customizing Risk-Based Quality Management Constants .....	251
Chapter 20: Activating Alert Rules .....	253
About Activating Alert Rules .....	254
Setting Alert Rules .....	254
Chapter 21: Cross Project Customization .....	257
About Cross Project Customization .....	258
Cross Project Customization Overview .....	259
Updating Linked Projects .....	260
Updating Linked Project Details .....	261
Verifying Cross Project Customization .....	262
Applying Template Customization to Linked Projects .....	263
The Cross Project Customization Report .....	265
Updating Linked Template Details .....	266
Chapter 22: Customizing Project Planning and Tracking KPIs .....	269
About Customizing PPT KPIs .....	270
Project Planning and Tracking Page .....	270
Project Planning and Tracking - General Tab .....	271
Configure Transitions Dialog Box .....	273
Project Planning and Tracking - KPI Analysis Tab .....	274
Chapter 23: Project Report Templates .....	277
About Project Report Templates .....	278
Managing Project Report Templates .....	278
Creating a New Report Template .....	279
Editing a Report Template .....	280
Duplicating a Report Template .....	280
Deleting a Report Template .....	280
Designing Report Templates .....	281
About Designing Report Templates .....	282
Designing Document Templates .....	282
Designing Style Templates .....	283
Designing History Templates .....	283
Designing Section Templates .....	285
Guidelines for Creating Full-Page and Tabular Templates .....	287
Full-page templates .....	287
Tabular templates .....	287
Template Creator Tab .....	288
Chapter 24: Business Views .....	291



Business Views Overview .....	292
Creating and Managing Business Views .....	292
Working with DQL .....	294
Business Views User Interface .....	305
Business Views Page .....	306
Link Properties Dialog Box .....	309
Add Related Entity Dialog Box .....	310
Chapter 25: Configuring Business Process Testing .....	313
About Configuring Business Process Testing .....	314
Business Process Test Page .....	314
Chapter 26: Configuring Sprinter .....	317
About Configuring Sprinter .....	318
Sprinter Page .....	318
Chapter 27: Generating Workflow Scripts .....	321
About Generating Workflow Scripts .....	322
Customizing Defects Module Field Lists .....	323
Customizing Defects Module Dialog Boxes .....	325
Chapter 28: Managing Analysis Menus .....	329
 Part 3: Workflow Customization .....	 331
Chapter 29: Workflow Customization at a Glance .....	333
Chapter 30: Working with the Workflow Script Editor .....	335
About Working with the Workflow Script Editor .....	336
The Script Editor .....	336
Understanding the Script Editor Commands .....	338
Creating a Workflow Script .....	339
Adding a Button to a Toolbar .....	341
Setting the Properties of the Script Editor .....	343
Chapter 31: Workflow Event Reference .....	347
About ALM Events .....	348
Naming Conventions for ALM Event Procedures .....	348
Entity .....	349
Event .....	350
Reference for ALM Events .....	350
ActionCanExecute .....	352
AddComponentToTest .....	352
AfterPost .....	352
Attachment_CanDelete .....	353
Attachment_CanOpen .....	354
Attachment_CanPost .....	354
Attachment_New .....	354
CanAddComponentsToTest .....	354
CanAddFlowsToTest .....	355
CanAddTests .....	355
CanCustomize .....	355
CanDelete .....	356

CanDeleteGroupsFromTest .....	358
CanLogin .....	358
CanLogout .....	358
CanPost .....	358
CanReImportModels .....	359
CanRemoveComponentsFromTest .....	360
CanRemoveFlowsFromTest .....	360
CanRemoveTests .....	360
DefaultRes .....	360
DialogBox .....	361
EnterModule .....	361
ExitModule .....	361
FieldCanChange .....	362
FieldChange .....	363
GetDetailsPageName .....	364
GetNewBugPageName .....	364
GetNewReqPageName .....	365
GetReqDetailsPageName .....	365
MoveTo .....	366
MoveToComponentFolder .....	367
MoveToFolder .....	367
MoveToSubject .....	367
New .....	368
RemoveComponentFromTest .....	369
RunTests .....	369
RunTests_Sprinter .....	369
RunTestSet .....	370
RunTestsManually .....	370
Chapter 32: Workflow Object and Property Reference .....	371
About ALM Objects and Properties .....	372
Actions Object .....	373
Action Object .....	373
Fields Objects .....	374
Field Object .....	375
Lists Object .....	376
TDConnection Object .....	377
User Object .....	377
ALM Properties .....	378
ActiveModule Property .....	379
ActiveDialogName Property .....	379
Chapter 33: Workflow Examples and Best Practices .....	381
About the Workflow Examples .....	382
Best Practices for Writing Workflow Scripts .....	382
Checking Value Types Before Use .....	383
Recommendations .....	383
Anticipating Full Evaluation of Logical Expressions .....	384

Recommendations .....	384
Defining Default Behavior for Select Case and If-Then-Else Statements .....	385
Recommendations .....	385
Setting Return Values in Functions .....	386
Recommendations .....	386
Making Sure that Entity Properties Are Set Before an Entity Comes into Focus .....	386
Recommendations .....	387
Check if a Dialog Box is Open .....	387
Recommendations .....	388
Avoid Defining Duplicate Subroutines .....	388
Recommendations .....	389
Example: Customizing a Defects Module Dialog Box .....	389
SetFieldApp .....	389
FieldCust_AddDefect .....	390
Example: Changing Tab Names .....	391
Example: Adding a Template to a Memo Field .....	392
Example: Changing One Field Based on Another Field .....	393
Example: Changing a Field Based on the User Group .....	393
Example: Object Validation .....	394
Example: Field Validation .....	395
Example: Presenting a Dynamic Field List .....	395
Example: Changing Field Properties when a Field Changes .....	397
Example: Controlling User Permissions .....	397
Example: Adding Button Functionality .....	398
Example: Error Handling .....	398
Example: Obtaining Session Properties .....	399
Example: Sending Mail .....	400
Sending Mail when a Defect is Submitted .....	400
Sending Mail when a Test Plan Module Field Value Changes .....	400
Example: Storing the Last Values Entered .....	401
Example: Copying Field Values to Another Object .....	403
 Send Us Feedback .....	 405

## Welcome to this Guide

Welcome to HP Application Lifecycle Management (ALM). ALM empowers organizations to manage the core application lifecycle, from requirements through deployment, granting application teams the crucial visibility and collaboration needed for predictable, repeatable, and adaptable delivery of modern applications.

Throughout the application lifecycle management process, ALM projects are accessed by many users—including developers, testers, business analysts, and quality assurance managers. To protect, maintain, and control information in a project, users are assigned to groups with different access privileges. Only an ALM project administrator (belonging to the TDAdmin user group) has full privileges in an ALM project.

As an ALM site administrator, you use Site Administration to create and maintain domains and projects; manage users, connections, and licenses; define database servers; and modify configurations.

As an ALM project administrator, you use Project Customization to customize project entities and lists, set up user groups and permissions, configure mail, set alert rules, and configure the workflow in the ALM modules. You use Cross Project Customization to standardize customization across projects in your organization.

ALM is shipped without any passwords defined. To protect your data from unauthorized access, set your password early in the ALM process.

## How This Guide is Organized

The HP Application Lifecycle Management Administrator Guide contains the following parts:

Part	Description
<a href="#">"Site Administration" on page 13</a>	Describes how the site administrator uses Site Administration to manage ALM projects. This includes maintaining projects, users, connections, licenses, servers, configuration parameters, and site analysis.
<a href="#">"Project Customization" on page 199</a>	Describes how the project administrator uses the Project Customization window to control access to a project by defining the project users and their privileges. It also describes how to customize a project to meet the specific needs of the project users.
<a href="#">"Workflow Customization" on page 331</a>	Describes how to create workflow scripts to customize the ALM user interface and to control the actions that users can perform.

# Part 1: Site Administration



# Chapter 1: Site Administration at a Glance

Using HP Application Lifecycle Management (ALM) Site Administration, you create and maintain projects, users, servers, site connections, license usage, and parameters. You can also define site administrators and change site administrator passwords.

This chapter includes:

- [Starting Site Administration](#) ..... 16
- [Understanding Site Administration](#) ..... 17
- [Defining Site Administrators](#) ..... 19

## Starting Site Administration

Using Site Administration, you create and maintain your ALM projects.

### To start Site Administration:

1. Select one of the following:
  - Open your Web browser and type:  
`http://<ALM server name>[:<port number>]/qcbn`. The HP Application Lifecycle Management Options window opens. Click the **Site Administration** link.
  - Alternatively, open your Web browser and type your Site Administration URL: `http://<ALM server name>[:<port number>]/qcbn/SiteAdmin.jsp`.


The first time you start Site Administration, files are downloaded to your client machine. ALM then carries out a version check on the client files installed on your client machine. If there is a newer version on the server, updated files are downloaded to your client machine.

**Note:** If you run ALM over a virtual environment, such as Citrix or VMware, only the system administrator can install a new version.

If domains or projects were previously created with locale-specific symbols in their names on a localized ALM server's Site Administration, you may not be able to access Site Administration from a non-localized client machine. If this occurs, change the client machine locale to correspond to the ALM server's locale.

After the ALM version has been checked and updated if necessary, the HP Application Lifecycle Management Site Administration Login window opens.

**Note:** If you are an external authentication user, this window is bypassed and you are automatically logged in to Site Administration using your external authentication credentials.



2. In the **User Name** box, type the name of a user who is defined as a site administrator. The first time you log in to Site Administration, you must use the site administrator name that you specified



during the installation of ALM. After you log in to Site Administration, you can define additional site administrators. For more information, see ["Defining Site Administrators" on page 19](#).

3. In the **Password** box, type your site administrator password. The first time you log in to Site Administration, you must use the site administrator password that you specified during the installation of ALM.

To define or change the site administrator password, see ["Creating and Changing Passwords" on page 128](#).

4. Click **Login**. Site Administration opens.


## Understanding Site Administration

As an ALM site administrator, you create and maintain projects, users, and servers using Site Administration.

ALM Editions: Some functionality in Site Administration is unavailable for some editions. This includes the following:

- ALM template projects are not available for Quality Center Enterprise Edition.
- Functionality related to project planning and tracking is available for ALM Edition only.

For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.




This section includes:

- ["Masthead" below](#)
- ["Tools Menu" on the next page](#)
- ["Site Administration Tabs" on page 19](#)

### Masthead

The masthead includes options you can use throughout Site Administration.

Option	Description
<b>Tools</b>	Includes commands that you can run from any location in Site Administration. For details, see <a href="#">"Tools Menu" below</a> .
<b>Help</b>	<p>Enables you to open the HP Application Lifecycle Management Help and other additional online resources.</p> <p>To display version information for each ALM client component, select <b>Help</b>. Details appear on the right side of the window that is displayed.</p> <p><b>Tip:</b> To customize the <b>Help</b> menu, refer to the <i>HP Application Lifecycle Management Installation and Upgrade Guide</i>.</p>
<b>Site Administrator:</b> <b>&lt;user&gt;</b>	The current Site Administrator user.
	<p><b>Logout.</b> Logs you out of Site Administration.</p> <p><b>Note:</b> When ALM is accessed via an external authentication mode, you cannot log out using this button. To log out, you must close the client browser.</p>

## Tools Menu

The **Tools** menu, located on the masthead, contains the following options:

Option	Description
<b>Collect Information</b>	Creates the <b>ALM_CollectedInfo_&lt;number&gt;.html</b> file. This file contains diagnostic information about the ALM system. It is useful for when you contact ALM support. The <b>ALM_CollectedInfo_&lt;number&gt;.html</b> file is stored in the temp folder on the ALM server machine. To determine the folder location, open the Site Administration log file and locate the <b>java.io.tmpdir</b> field.
<b>Repository Migration Status</b>	Displays the status of project migration to the optimized project repository. For more information, see <a href="#">"Migrating the Repository" on page 110</a> .
<b>Set Project Upgrade Priorities</b>	Enables you to set priorities before upgrading projects to new minor-minor versions. For information, see <a href="#">"About Upgrading Projects for Minor-Minor Versions" on page 114</a> .
<b>Update Test Types</b>	<p>Updates custom test type definitions in active projects. This is required after registering custom test types with ALM. If your site contains many active projects, this may take some time. For more information, refer to the <i>HP ALM Custom Test Types Guide</i>.</p> <p><b>Note:</b> When you activate a project, custom test type definitions are updated automatically.</p>
<b>ALM Assessment</b>	Collects environment details to assess the current ALM deployment and recommend usage improvements. For more information, see <a href="#">"ALM Advisor" on page 171</a> .
<b>QC Sense</b>	<p>Includes the following options for working with QC Sense, the internal ALM monitoring tool:</p> <ul style="list-style-type: none"> <li>• <b>Reports.</b> Enables you to generate reports based on collected data.</li> <li>• <b>Configuration.</b> Enables you to configure QC Sense monitors to define the scope of data collected.</li> </ul> <p>For more information, see <a href="#">"QC Sense" on page 179</a>.</p>

## Site Administration Tabs

Site Administration contains the following tabs:

Tab	Description
<b>Site Projects</b>	Manage your ALM projects and templates. This includes adding new domains and projects, enabling extensions for projects, querying project data, restoring projects, renaming projects, and activating or deactivating projects. For more information, see <a href="#">"Managing Projects" on page 77</a> .  You can also upgrade projects from a previous Quality Center version to the current ALM version. For more information, see <a href="#">"Upgrading Projects to a New Version" on page 91</a> .
<b>Lab Management</b>	Manage the LAB_PROJECT details and define Lab Management administrators. For more information, refer to the <i>HP ALM Lab Management Guide</i> .
<b>Site Users</b>	Add new users and define user properties, including changing passwords. For more information, see <a href="#">"Managing ALM Users" on page 117</a> .  You can also define site administrators. For more information, see <a href="#">"Defining Site Administrators" below</a> .
<b>Site Connections</b>	Monitor the users currently connected to an ALM server. For more information, see <a href="#">"Managing User Connections and Licenses" on page 135</a> .
<b>Licenses</b>	Monitor the total number of ALM licenses in use and to modify the license key. For more information, see <a href="#">"Managing User Connections and Licenses" on page 135</a> .
<b>Servers</b>	Modify ALM server information, such as the log file. For more information, see <a href="#">"Configuring Servers and Parameters" on page 145</a> .
<b>DB Servers</b>	Manage your database servers. This includes adding a new database server, editing a database's connection string, and changing a database's default administrator user name and password. For more information, see <a href="#">"Configuring Servers and Parameters" on page 145</a> .
<b>Site Configuration</b>	Modify ALM configuration parameters, such as the mail protocol. For more information, see <a href="#">"Configuring Servers and Parameters" on page 145</a> .
<b>Site Analysis</b>	Monitor the number of licensed ALM users connected to your projects at specific points over a period of time. For more information, see <a href="#">"Analyzing Site Usage" on page 159</a> .
<b>Project Planning and Tracking</b>	Schedule project planning and tracking calculations for an ALM site. For more information, see <a href="#">"Scheduling Calculations for Project Planning and Tracking (PPT)" on page 165</a> .

## Defining Site Administrators

You can define ALM users as site administrators.


To secure the information in Site Administration, ensure that each user you add as a site administrator has a password defined. For more information, see ["Creating and Changing Passwords" on page 128](#).

**To define site administrators:**


1. In Site Administration, click the **Site Users** tab.
2. Click the **Site Administrators** button . The Site Administrators dialog box opens displaying




the Site Administrators list.

To change the sort order of the Site Administrators list from ascending to descending, click the **UserName** or **FullName** column heading. Click the column heading again to reverse the sort order.

You can search for a user in the Site Administrators list by typing the name of a user in the **Find** box, and clicking the **Find** button .

3. Click the **Add Site Administrators** button. The Users list is displayed in the right pane.



4. Select the users that you want to assign as site administrators. You can search for users by typing a search string in the **Find** box above the Users list, and clicking the **Find** button .
5. Click the **Add Selected Users** button . Alternatively, double-click a user. The selected users are moved to the Site Administrators list in the left pane.
6. To remove a site administrator from the Site Administrators list, select the user and click the **Remove Selected Site Administrators** button. Click **OK** to confirm. The user is removed from the Site Administrators list.
7. To refresh the Site Administrators list or Users list, click the **Refresh** button  above the appropriate list.

# Chapter 2: Creating Projects

You can create and configure HP Application Lifecycle Management (ALM) domains and projects in Site Administration.

For information on managing existing projects, see ["Managing Projects" on page 77](#). This includes querying project data, restoring projects, renaming projects, exporting projects, and activating or deactivating projects.

For information on upgrading projects from a previous Quality Center/ALM version, see ["Upgrading Projects to a New Version" on page 91](#).

This chapter includes:

• <a href="#">About Creating Projects</a> .....	22
• <a href="#">Understanding the Project Structure</a> .....	22
• <a href="#">Creating Domains</a> .....	23
• <a href="#">Creating Projects</a> .....	24
• <a href="#">Copying Projects</a> .....	31
• <a href="#">Importing Projects</a> .....	37
• <a href="#">Creating Template Projects</a> .....	41
• <a href="#">Linking a Template to Projects</a> .....	60
• <a href="#">Updating Project Details</a> .....	61
• <a href="#">Assigning Users to Projects</a> .....	65
• <a href="#">Enabling Extensions for a Project</a> .....	67

## About Creating Projects

To start working in ALM, you need to create a **project**. A project collects and stores data relevant to the application management process. You can select from the following:

- create an empty project
- create a project based on a template project
- copy the contents of an existing project to a new project
- import data from an exported project file

You can also create a template project. You can link a template project to other projects to enable cross project customization. For more information, see ["Cross Project Customization" on page 257](#).

After you create a project, you can add and remove users from the project.

**Note:** Users who are already logged into **Lab Management** need to re-enter the application to see changes you made in Site Administration.

Projects are grouped by **domain**. A domain contains a group of related projects and assists you in organizing and managing a large number of projects. Each domain contains a **Projects** folder and a **Template Projects** folder to organize your projects and template projects.

**ALM Editions:** Some functionality in Site Administration is limited per edition. For example, ALM template projects are not available with Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.


## Understanding the Project Structure

When you install ALM, the installation program creates a **project repository** on the application server's file system. By default, the project repository is located under the application deployment directory, at **C:\ProgramData\HP\ALM\repository** on Windows machines, and at **/var/opt/HP/ALM/repository** on UNIX machines.

The project repository contains the **sa** and **qc** sub-folders. The **sa** directory stores global XML files, style sheets, templates, and reports to be used by all projects in the project repository.

The **qc** directory is a working area for a group of domains that are shared by multiple users. Each domain stores projects. When you create a new project, you can add it to the default domain or to a user-defined domain.

The following diagram shows the structure of the repository.



Under the **qc** directory, each project directory contains the following subdirectories:

- **ProjRep.** A subdirectory that contains a repository of all project files, such as test scripts, reports, and attachments. For more information on the project repository, see ["Managing the Optimized Project Repository" on page 71](#).
- **dbid.xml.** An initialization file that stores project information required for restoring a connection to a project. For more information on restoring a connection to a project, see ["Restoring Access to Projects" on page 86](#).

Under the **sa** directory, the **DomsInfo** subdirectory contains the following information:

- **StyleSheets.** A subdirectory for storing global style sheets.
- **Templates.** A subdirectory for storing database templates used when creating new projects.

## Creating Domains

You can add new domains to Site Administration. You organize projects in the Projects list by domain.


### To create a domain:

1. In Site Administration, click the **Site Projects** tab.
2. Click the **Create Domain** button. The Create Domain dialog box opens.
3. Type a **Domain Name** and click **OK**.

The domain name cannot be longer than 30 characters, must begin with a letter, and can include only letters, digits, and underscores.

**Note:** Support of non-English national characters depends on the database settings used by the server. We do not recommend using non-English national characters in domain names.

The new domain is added to the Projects list in alphabetical order. In the right pane, under **Directories**, you can view the location of the domain.



4. To add a person's name as a contact when there are questions or problems with the domain or its projects, click the **Contact Name** link. In the Set Contact Name dialog box, type the name of the contact person and click **OK**.
5. To add the email address of the contact person for the domain, click the **Contact Email** link. In the Set Contact Email dialog box, type the email address and click **OK**.
6. To change the number of users allowed to connect concurrently to the domain, click the **User Quota** link. The Domain User Quota dialog box opens.

Choose **Maximum Connections** and type the maximum number of concurrent connections allowed. Click **OK**.

**Note:** In addition to changing the number of users allowed to connect concurrently to a domain, you can also change:

- the number of users allowed to connect concurrently to a project. For more information, see ["Updating Project Details" on page 61](#).
- the number of concurrent connections that can be opened on the database server by ALM for each project. For more information, see ["Configuring Server Information" on page 146](#).

7. To select a default database server when creating projects in the domain, select a default database server from the **Default DB Server** list.

## Creating Projects

You can create ALM projects in Oracle or Microsoft SQL. You can create a project in any of the following ways:

- Create an empty project.
- Create a project from a template. This option copies the customization of an existing template project. It does not copy project data from the template project.



ALM Editions: This option is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.


- Copy the contents of an existing project. For more information, see ["Copying Projects" on page 31](#).
  - Import data from an exported project file. For more information, see ["Importing Projects" on page 37](#).
- For information on creating template projects, see ["Creating Template Projects" on page 41](#).

**Note:**

- For information on the Oracle or Microsoft SQL permissions required by ALM, refer to the *HP Application Lifecycle Management Installation and Upgrade Guide*.
- If your database server is connected to ALM over a WAN, the project creation process can be very time-consuming.

**To create a project:**

1. In Site Administration, click the **Site Projects** tab.
2. Select the domain in which you want to create the project.
3. Click the **Create Project** button. The Create Project dialog box opens.



4. Select one of the following options:
  - **Create an empty project.** Creates a new project.
  - **Create a project from a template.** Creates a new project by copying the customization of an existing template project, but not the project data.

ALM Editions: This option is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

- **Create a project by copying data from an existing project.** For more information, see

["Copying Projects" on page 31.](#)


- **Create a project by importing data from an exported project file.** For more information, see ["Importing Projects" on page 37.](#)

5. Click **Next**.

If you selected **Create a project from a template**, the **Use Template Customization** dialog box opens.

ALM Editions: This dialog box is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you did not select **Create a project from a template**, proceed to step 7.



Select the **domain** and **template** you want to use to create the project.


6. Select **Link the project to the selected template** to link the new project to the template.

ALM Editions: This option is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

**Note:** After you link a project to a template, the template administrator must apply template customization to the project. This applies the customization from the template to the linked project, and sets the applied customization to read-only in the project. For more information, see ["Applying Template Customization to Linked Projects" on page 263.](#)

Click **Next**.


7. The following dialog box opens:

A screenshot of the 'Create Project' dialog box. It has a title bar with 'Create Project' and a close button. The main area contains two labels: 'Project Name :' followed by a text input field, and 'In Domain :' followed by a dropdown menu showing 'DEFAULT'. At the bottom, there are four buttons: 'Back' with a left arrow, 'Next' with a right arrow, 'Cancel', and 'Help'.

8. In the **Project Name** box, type a name for your project. The project name cannot be longer than 30 characters and can include only letters, digits, and underscores.

**Note:** Support of non-English national characters depends on the database settings used by the server. We do not recommend using non-English national characters in project names.

9. In the **In Domain** box, select a domain.  
10. Click **Next**. The following dialog box opens:

A screenshot of the second screen of the 'Create Project' dialog box. It has a title bar with 'Create Project' and a close button. The main area is divided into two sections. The first section is 'Database Type' with two radio buttons: 'Oracle' and 'MS-SQL', where 'MS-SQL' is selected. The second section is 'DB Server' with three labels: 'Server Name :' followed by a dropdown menu showing 'almsrv', 'DB Admin User :' followed by a text input field showing 'sa', and 'DB Admin Password :' followed by a text input field with masked characters. There is also a checkbox labeled 'Create as Unicode' which is currently unchecked. At the bottom, there are four buttons: 'Back' with a left arrow, 'Next' with a right arrow, 'Cancel', and 'Help'.


11. Under **Database Type**, select **Oracle** or **MS-SQL**.  
12. By default, the default values defined for the domain are displayed for **Server Name**, **DB Admin User**, and **DB Admin Password**. If additional database servers are defined, you can select another name from the **Server Name** list.  
13. Click **Create as Unicode** to create the project as Unicode.

**Note:** The **Create as Unicode** checkbox is only displayed when creating a new project from an empty project in an MS-SQL server. Unicode is a feature of MS-SQL that allows multi-language support. In Oracle, multi-language support is defined when installing the server.

14. Click **Next**.

If your selected database server does not have the text search feature enabled, a message box opens. The message indicates that after this process completes, you can enable the text search feature. For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).

15. If you are creating a Microsoft SQL project, proceed to step **16**. For an Oracle project, the following dialog box opens.




In the **Create in TableSpace** box, select a storage location that has sufficient space to store the new project. You should not use **UNDO** as the storage location.




In the **Temporary TableSpace** box, select a temporary storage location that has sufficient space to store the new project.

Click **Next**.

16. The Add Project Administrators dialog box opens.




**Selected Project Administrators** lists users that are assigned as project administrators. **Available Users** lists users available in the project. When you assign project administrators, they are moved from the Available Users list to the Selected Project Administrators list. Project administrator users can add and administer other users in the project.

- **Refresh.** Click the **Refresh** button  to refresh the list of available users.
- **Find.** Type the name of a user in the **Find** box, and click the **Find** button  to search the Available Users list.
- **Add Selected Users.** Select the users you want to assign as project administrators, and click the **Add Selected Users** button . Alternatively, double-click a user name. The selected users are moved to the Selected Project Administrators list.
- **Delete.** To remove a user from the Selected Project Administrators list, right-click the user name and click **Delete**.

You can also assign project administrators after you have created the project. For more information, see ["Assigning Project Administrators" on page 66](#).

17. Click **Next**. You can enable extensions that are available for your site's ALM edition.




Select the **Enable** check box for the extensions you want to enable.

#### Note

- You cannot disable an extension for a project after you enable it. We recommend enabling only the extensions you need. Enabling extra extensions can affect performance and consumes additional disk space.
- As you navigate from one extension to another, relevant license status information is displayed in the **License Status** section.  
Extensions for which there is no license on the server are displayed in gray. It is possible to enable an extension for which you do not yet have a license. You can utilize the extension's added functionality later, after receiving the license.
- To work with **Lab Management** or **Performance Center**, select **ALM Lab Extension**. For more information, refer to the *HP ALM Lab Management Guide*.
- You can also enable extensions for a project after you have created the project. For more information, see ["Enabling Extensions for a Project" on page 67](#).

18. Click **Next**. The following dialog box opens:



Verify the project details. To change any of the details, click **Back**.

19. Select **Activate Project** to activate the new project. Only activated projects are available to users in the HP Application Lifecycle Management Login window when they log in to a project. For more information, see ["Deactivating and Activating Projects" on page 80](#).
20. Select **Enable Versioning** to enable version control for the project. You can also enable version control after you have created the project. For more information, see ["Enabling and Disabling Version Control for a Project" on page 80](#).
21. Click **Create**. The new project is added to the Projects list.

## Copying Projects

You can create a new project by copying the contents of an existing project.


**Version Control:** If you copy a version control enabled project, the new project is created with version control enabled. Version history is also copied. Entities that are checked out in the source project are checked out in the new project. An administrator in the new project can undo those checkouts. For more information, see the *HP Application Lifecycle Management User Guide*.

### Note:


- If your ALM server becomes unavailable while copying, you can resume the copying process at a later stage. To resume copying, reopen Site Administration and select the project from the Projects list. In the right pane, click the **Click Here** link.
- The new project inherits the Unicode or ASCII definition of the copied project.
- Test run details are not be included in the Usage Reports in the copied project.
- Timeslot information and project settings are not copied.
- Result files associated with the original project are not copied.

### To copy a project:

1. Deactivate the project you want to copy. For more information, see ["Deactivating and Activating Projects" on page 80](#).
2. In Site Administration, click the **Site Projects** tab.
3. Select the domain in which you want to create the project.
4. Click the **Create Project** button. The Create Project dialog box opens.




5. Choose the **Create a project by copying data from an existing project** option and click **Next**. The following dialog box opens:





6. Under **Select Project To Copy From**, select the domain and project you want to copy and click **Next**. The following dialog box opens:



7. Select **Customization** to copy project lists, host data, system and user-defined fields, module access, workflow, and transition rules to the new project. If this option is selected, you can also choose to copy any of the following:

Option	Description
<b>Releases</b>	Copies release data from the project.
<b>Requirements</b>	Copies requirement data from the project.
<b>Risk-Based Quality Management</b>	Copies risk-based quality management customization settings from the project. For more information, see <a href="#">"Customizing Risk-Based Quality Management" on page 245</a> .
<b>Tests</b>	Copies test data and test resources from the project. If this option is selected, you can also choose the following option: <ul style="list-style-type: none"> <li>• <b>Test Sets</b>. Copies test set data from the project. If this option is selected, you can also choose to copy the following option:</li> <li>• <b>Runs</b>. Copies test run data from the project.</li> </ul>
<b>Defects</b>	Copies defect data from the project.
<b>Include History</b>	Copies history data for the options that are selected.
<b>Public Favorite Views</b>	Copies public favorite view data from the project. For more information, refer to the <i>HP Application Lifecycle Management User Guide</i> .
<b>Dashboard Public Entities</b>	Copies public analysis items and dashboard pages from the project. For more information, refer to the <i>HP Application Lifecycle Management User Guide</i> .
<b>Users and Groups</b>	Copies user and group information and permission settings. If this option is selected, you can also choose to copy the following options:

Option	Description
	<ul style="list-style-type: none"> <li>• <b>Dashboard Private Entities.</b> Copies private analysis items and dashboard pages from the project. For more information, refer to the <i>HP Application Lifecycle Management User Guide</i>.</li> <li>• <b>Private Favorite Views.</b> Copies private favorite view data and Excel report definitions from the project. For more information, refer to the <i>HP Application Lifecycle Management User Guide</i>.</li> <li>• <b>Mail Conditions.</b> Copies the mailing configuration data. For more information, see <a href="#">"Configuring Automail" on page 241</a>.</li> <li>• <b>Alerts and Follow up Flags.</b> Copies alerts and follow up flags. For more information, refer to the <i>HP Application Lifecycle Management User Guide</i>.</li> </ul>
<b>Sprinter</b>	Copies Sprinter data. This cannot be unselected.
<b>Analysis Extension</b>	Copies Analysis data. This cannot be unselected.
<b>Quality Center</b>	Copies Quality Center data. This cannot be unselected.


**Note:**

- If the project from which you are copying has extensions enabled, the extensions and their associated data are also copied to the new project.
- If the project from which you are copying contains libraries, the libraries are not copied to the new project. For information on importing libraries, see the *HP Application Lifecycle Management User Guide*.

To clear all options, click **Clear All**.


To select all options, click **Select All**.

- Click **Next**.
- In the **Project Name** box, type a name for your project. The project name cannot be longer than 30 characters and cannot include any of the following characters: = ~ ` ! @ # \$ % ^ & \* ( ) + | { } [ ] : ' ; " < > ? , . / \ -
- In the **In Domain** box, select a domain.
- Click **Next**. The following dialog box opens:



The 'Create Project' dialog box shows the 'Database Type' section with 'MS-SQL' selected. The 'DB Server' section contains three fields: 'Server Name' with a dropdown menu showing 'almsrv', 'DB Admin User' with the text 'sa', and 'DB Admin Password' with masked characters '\*\*\*\*\*'. At the bottom are buttons for 'Back', 'Next', 'Cancel', and 'Help'.

12. Under **Database Type**, select **Oracle** or **MS-SQL**.
13. By default, the default values defined for the domain are displayed for **Server Name**, **DB Admin User**, and **DB Admin Password**. If additional database servers are defined, you can select another name from the **Server Name** list.
14. Click **Next**.  
If your selected database server does not have the text search feature enabled, a message box opens. The message indicates that after this process completes, you can enable the text search feature. For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).
15. If you are creating a Microsoft SQL project, proceed to step 16. For an Oracle project, the following dialog box opens:




The 'Create Project' dialog box shows the 'Create in TableSpace' dropdown menu with 'USERS (31.2Mb Free)' selected. The 'Temporary TableSpace' dropdown menu has 'TEMP' selected. At the bottom are buttons for 'Back', 'Next', 'Cancel', and 'Help'.

In the **Create in TableSpace** box, select a storage location that has sufficient space to store the new project. You should not use **UNDO** as the storage location.




In the **Temporary TableSpace** box, select a temporary storage location that has sufficient space to store the new project.

Click **Next**.

16. The Add Project Administrators dialog box opens.




**Selected Project Administrators** lists users that are assigned as project administrators. **Available Users** lists users available in the project. When you assign project administrators, they are moved from the Available Users list to the Selected Project Administrators list. Project administrator users can add and administer other users in the project.

- **Refresh.** Click the **Refresh** button  to refresh the list of available users.
- **Find.** Type the name of a user in the **Find** box, and click the **Find** button  to search the Available Users list.
- **Add Selected Users.** Select the users you want to assign as project administrators, and click the **Add Selected Users** button . Alternatively, double-click a user name. The selected users are moved to the Selected Project Administrators list.
- **Delete.** To remove a user from the Selected Project Administrators list, right-click the user name and click **Delete**.

You can also assign project administrators after you have created the project. For more information, see ["Assigning Project Administrators" on page 66](#).

17. Click **Next**. The following dialog box opens:



- Verify the project details. To change any of the details, click **Back**.
18. Select **Activate Project** to activate the new project. Only activated projects are available to users in the HP Application Lifecycle Management Login window when they log in to a project. For more information, see ["Deactivating and Activating Projects" on page 80](#).
  19. Click **Create**. The new project is added to the Projects list.

## Importing Projects

You can import data from exported ALM project files created in the same ALM version. You can also import data from customized projects created by content providers. For example, you can import customized tests, requirements, and test sets for SAP testing, Siebel testing, and SOX compliance testing created by HP content providers.

If you import a project that was previously exported from the same server, ALM recognizes that the same project already exists on the server, based on the project ID. You can choose to replace the existing project, or cancel the import process.

**Note:** The new project inherits the Unicode or ASCII definition of the imported project.

Projects greater than 2 GB cannot be imported. They must be imported in sections.


**Version Control:** If you import an exported version control enabled project, the project is imported with version control enabled. Version history is also copied.


You can also import data from template projects. For more information, see ["Importing a Template Project" on page 56](#).

For more information on exporting projects, see ["Exporting Projects" on page 79](#).


### To import an ALM project:

1. In Site Administration, click the **Site Projects** tab.

2. You can do one of the following:
  - Select the domain to which you want to import a project, and click the **Import Project from Project File** button . Alternatively, right-click the domain and choose **Import Project**.
  - Click the **Create Project** button. The Create Project dialog box opens.



3. Choose the **Create a project by importing data from an exported project file** option, and click **Next**. The Select File for Import dialog box opens.



4. Click the browse button to the right of the **Import project from** box to locate the project that you want to import. The Open dialog box opens.
5. Locate the directory and select the ALM Project Export file that you want to import. Click **Open**. The selected file is displayed in the **Import project from** box.

**Note:** If the selected file is an ALM template project file, a new template project is created. The template project is added to the Projects list under **Template Projects**.

ALM Editions: Template projects are not available for **Quality Center Enterprise**


**Edition.** For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

Click **Next**.

6. In the **Project Name** box, type a name for your project. The project name cannot be longer than 30 characters and cannot include any of the following characters: = ~ ` ! @ # \$ % ^ & \* ( ) + | { } [ ] : ' ; " < > ? , . / \ -
7. In the **In Domain** box, select a domain.

**Tip:** After the project has been created, you can move it to a different domain in the Projects list using a drag-and-drop operation.

8. Click **Next**. The following dialog box opens:

The image shows a 'Create Project' dialog box with a blue title bar. It contains two sections: 'Database Type' with radio buttons for 'Oracle' and 'MS-SQL' (selected), and 'DB Server' with three text boxes: 'Server Name' (containing 'almsrv'), 'DB Admin User' (containing 'sa'), and 'DB Admin Password' (containing '\*\*\*\*\*'). At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

9. Under **Database Type**, select **Oracle** or **MS-SQL**.


By default, the default values defined for the domain are displayed for **Server Name**, **DB Admin User**, and **DB Admin Password**. If additional database servers are defined, you can select another name from the **Server Name** list.

**Note:** For more information on defining database servers, see ["Defining New Database Servers" on page 148](#).

10. Click **Next**.

If your selected database server does not have the text search feature enabled, a message box opens. The message indicates that after this process completes, you can enable the text search feature. For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).

11. If you are creating a Microsoft SQL project, proceed to step 12. For an Oracle project, the following dialog box opens:




The 'Create Project' dialog box has a title bar with a close button. It contains two dropdown menus: 'Create in TableSpace' with 'USERS (31.2Mb Free)' selected, and 'Temporary TableSpace' with 'TEMP' selected. At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

In the **Create in TableSpace** box, select a storage location that has sufficient space to store the new project. You should not use **UNDO** as the storage location.

In the **Temporary TableSpace** box, select a temporary storage location that has sufficient space to store the new project.

Click **Next**.

12. In the Add Project Administrators dialog box, select project administrators.






The 'Add Project Administrators' dialog box is a sub-dialog of 'Create Project'. It has a title bar and a section titled 'Add Project Administrators'. Below this is a 'Selected Project Administrators' list (currently empty) and an 'Available Users' list. The 'Available Users' list has a search bar with a 'Find' button and a list of users. The users are listed in a table with columns 'User Name' and 'Full Name'. At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'. A note at the bottom states: 'Note: You can also assign Project Administrators after creating a project.'

User Name	Full Name
alex_alm	Alex Smith
alice_alm	Alice Jones
cecil_alm	Cecil Davis
james_alm	James Johnson
michael_alm	Michael Brown
peter_alm	Peter Adams
robert_alm	Robert Phillips




**Selected Project Administrators** lists users that are assigned as project administrators. **Available Users** lists users available in the project. When you assign project administrators, they are moved from the Available Users list to the Selected Project Administrators list. Project administrator users can add and administer other users in the project.

- **Refresh.** Click the **Refresh** button  to refresh the list of available users.
- **Find.** Type the name of a user in the **Find** box, and click the **Find** button  to search the Available Users list.
- **Add Selected Users.** Select the users you want to assign as project administrators, and click the **Add Selected Users** button . Alternatively, double-click a user name. The selected users are moved to the Selected Project Administrators list.
- **Delete.** To remove a user from the Selected Project Administrators list, right-click the user name and click **Delete**.

You can also assign project administrators after you have created the project. For more information, see ["Assigning Project Administrators" on page 66](#).

13. Click **Next**. The following dialog box opens:



Verify the project details. To change any of the details, click **Back**.

14. Select **Activate Project** to activate the new project. Only activated projects are available to users in the HP Application Lifecycle Management Login window when they log in to a project. For more information, see ["Deactivating and Activating Projects" on page 80](#).
15. Click **Create**. The new project is added to the Projects list.

## Creating Template Projects

Template projects enable you to define and maintain a common set of project customizations for multiple projects. When you create a template, you can link it to projects. This enables the template administrator to apply template customization changes to the linked projects.

You create a new template project by creating an empty template, by copying an existing template or project, or by importing a template.

ALM Editions: Template projects are not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

This section includes:


- [Creating a Template Project](#) ..... 43
- [Creating a Template from an Existing Template](#) ..... 47
- [Creating a Template from an Existing Project](#) ..... 52
- [Importing a Template Project](#) ..... 56

## Creating a Template Project


You can create a new template project in Oracle or Microsoft SQL.

### To create a template:

1. In Site Administration, click the **Site Projects** tab.
2. Select the domain in which you want to create the template.
3. Click the **Create Template** button. The Create Template dialog box opens.




4. Select **Create an empty template** and click **Next**. The following dialog box opens.



5. In the **Template Name** box, type a name for the template. The template name cannot be longer than 30 characters and cannot include any of the following characters: = ~ ` ! @ # \$ % ^ & \* ( ) + | { } [ ] : ' ; " < > ? , . / \ -
6. In the **In Domain** box, select a domain.

**Tip:** After the template has been created, you can move it to a different domain in the Projects list using a drag-and-drop operation.

7. Click **Next**. The following dialog box opens.

The image shows a 'Create Template' dialog box. It has a title bar with 'Create Template' and a close button. The dialog is divided into two sections. The top section is labeled 'Database Type' and contains two radio buttons: 'Oracle' and 'MS-SQL'. The 'MS-SQL' radio button is selected. The bottom section is labeled 'DB Server' and contains three fields: 'Server Name' with a dropdown menu showing 'almsrv', 'DB Admin User' with a text box containing 'sa', and 'DB Admin Password' with a text box containing '\*\*\*\*\*'. There is also a checkbox labeled 'Create as Unicode' which is currently unchecked. At the bottom of the dialog are four buttons: 'Back', 'Next', 'Cancel', and 'Help'.

8. Under **Database Type**, select **Oracle** or **MS-SQL**.

The default values defined for the domain are displayed for **Server Name**, **DB Admin User**, and **DB Admin Password**. If additional database servers are defined, you can select another name from the **Server Name** list.


9. Click **Create as Unicode** to create the template as Unicode.

**Note:** The **Create as Unicode** checkbox is only displayed when creating a new template from an empty template in an MS-SQL server. Unicode is a feature of MS-SQL that allows multi-language support. In Oracle, multi-language support is defined when installing the server.

10. Click **Next**.

If your selected database server does not have the text search feature enabled, a message box opens. The message indicates that after this process completes, you can enable the text search feature. For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).

11. If you are creating a Microsoft SQL template, proceed to step 12. For an Oracle template, the following dialog box opens.




The 'Create Template' dialog box has a title bar with a close button. It contains two dropdown menus: 'Create in TableSpace' with 'USERS (31.2Mb Free)' selected, and 'Temporary TableSpace' with 'TEMP' selected. At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

In the **Create in TableSpace** box, select a storage location that has sufficient space to store the new template. You should not use **UNDO** as the storage location.

In the **Temporary TableSpace** box, select a temporary storage location that has sufficient space to store the new template.

Click **Next**.

12. The Add Template Administrators dialog box opens.






The 'Add Template Administrators' dialog box has a title bar with a close button. It is divided into two main sections: 'Selected Template Administrators' on the left, which is currently empty, and 'Available Users' on the right. The 'Available Users' section includes a search bar with a 'Find' button and a list of users with columns for 'User Name' and 'Full Name'. Below the list is a note: 'Note: You can also assign Template Administrators after creating a template.' At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

User Name	Full Name
alex_alm	Alex Smith
alice_alm	Alice Jones
cecil_alm	Cecil Davis
james_alm	James Johnson
michael_alm	Michael Brown
peter_alm	Peter Adams
robert_alm	Robert Phillips


**Selected Template Administrators** lists users that are assigned as template administrators. **Available Users** lists users available in the template. When you assign template administrators, the users are moved from the Available Users list to the Selected Template Administrators list.

Template administrator users can customize template projects and apply template customization to linked projects. For more information, see ["Cross Project Customization" on page 257](#).

- **Refresh.** Click the **Refresh** button  to refresh the list of available users.
- **Find.** Type the name of a user in the **Find** box, and click the **Find** button  to search the Available Users list.
- **Add Selected Users.** Select the users you want to assign as template administrators, and click the **Add Selected Users** button . Alternatively, double-click a user name. The selected users are moved to the Selected Template Administrators list.
- **Delete.** To remove a user from the Selected Template Administrators list, right-click the user name and click **Delete**.

You can also assign template administrators after you have created the template. For more information, see ["Assigning Project Administrators" on page 66](#).

13. Click **Next**. You can enable extensions that are available for your site's ALM edition.



The "Create Template" dialog box is shown. It has a title bar "Create Template" and a close button. The main area contains the text "Select extensions to activate for the project." followed by a red warning icon and the text "You can also enable extensions after creating a template, but you cannot disable extensions after a template is created." Below this is a table with two columns: "Extension Name" and "Enable". The table lists five extensions: "ALM Lab Extension", "Application Lifecycle Intelligence 2.6", "Application Model", "Enterprise Integration for SAP applications", and "Service Test Management Extension". Each extension has a corresponding "Enable" checkbox. Below the table are fields for "License Status" and "Description". At the bottom are four buttons: "Back", "Next", "Cancel", and "Help".


Extension Name	Enable
ALM Lab Extension	<input type="checkbox"/>
Application Lifecycle Intelligence 2.6	<input type="checkbox"/>
Application Model	<input type="checkbox"/>
Enterprise Integration for SAP applications	<input type="checkbox"/>
Service Test Management Extension	<input type="checkbox"/>

Select the **Enable** check box for the extensions you want to enable.

#### Note

- You cannot disable an extension for a project after you enable it. We recommend enabling only the extensions you need. Enabling extra extensions can affect performance and consumes additional disk space.
- As you navigate from one extension to another, relevant license status information is displayed in the **License Status** section.  
Extensions for which there is no license on the server are displayed in gray. It is possible to enable an extension for which you do not yet have a license. You can utilize the extension's added functionality later, after receiving the license.
- To work with **Lab Management** or **Performance Center**, select **ALM Lab Extension**. For more information, refer to the *HP ALM Lab Management Guide*.
- You can also enable extensions for a project after you have created the project. For more information, see ["Enabling Extensions for a Project" on page 67](#).

14. Click **Next**. The following dialog box opens.



Verify the template details. To change any of the details, click **Back**.

15. Select **Activate template** to activate the template. Only activated templates are available in the HP Application Lifecycle Management Login window. For more information, see ["Deactivating and Activating Projects" on page 80](#).
16. Select **Enable Versioning** to enable version control for the template. You can also enable version control after you have created the template. For more information, see ["Enabling and Disabling Version Control for a Project" on page 80](#).
17. Click **Create**. The new template is added to the Projects list under **Template Projects**.

## Creating a Template from an Existing Template


You can create a template project by copying an existing template. This option copies both customization and project data from the source template.

**Note:** The new template inherits the Unicode or ASCII definition of the copied project.


**Version Control:** If you copy a version control enabled template, the new template is created with version control enabled.

### To create a template from an existing template:

1. In Site Administration, click the **Site Projects** tab.
2. Select the domain in which you want to create the template.
3. Click the **Create Template** button. The Create Template dialog box opens.




4. Select **Create a template by copying customization from an existing template** and click **Next**. The Copy Template dialog box opens.



5. In the **Domain** box, select the domain where the template you want to copy is located.
6. In the **Template** box, select the template you want to copy.



7. Click **Next**. The following dialog box opens.




The 'Create Template' dialog box has a title bar with a close button. It contains two input fields: 'Template Name:' with an empty text box, and 'In Domain:' with a dropdown menu showing 'DEFAULT'. At the bottom, there are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

8. In the **Template Name** box, type a name for the template. The template name cannot be longer than 30 characters and cannot include any of the following characters: = ~ ` ! @ # \$ % ^ & \* ( ) + | { } [ ] : ' ; " < > ? , . / \ -
9. In the **In Domain** box, select a domain.

**Tip:** After the template has been created, you can move it to a different domain in the Projects list using a drag-and-drop operation.

10. Click **Next**. The following dialog box opens.




The second 'Create Template' dialog box shows the 'Database Type' section with radio buttons for 'Oracle' and 'MS-SQL' (which is selected). Below is the 'DB Server' section with three input fields: 'Server Name:' with a dropdown showing 'almsrv', 'DB Admin User:' with a text box containing 'sa', and 'DB Admin Password:' with a text box containing '\*\*\*\*\*'. At the bottom, there are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

11. Under **Database Type**, select **Oracle** or **MS-SQL**.  
The default values defined for the domain are displayed for **Server Name**, **DB Admin User**, and **DB Admin Password**. If additional database servers are defined, you can select another name from the **Server Name** list.
12. Click **Next**.

**Note:** If your selected database server does not have the text search feature enabled, a message box opens. The message indicates that after this process completes, you can enable the text search feature. For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).

If you are creating a Microsoft SQL template, proceed to step **13**. For an Oracle template, the following dialog box opens.




In the **Create in TableSpace** box, select a storage location that has sufficient space to store the new template.

You should not use **UNDO** as the storage location.




In the **Temporary TableSpace** box, select a temporary storage location that has sufficient space to store the new template.

Click **Next**.

13. The Add Template Administrators dialog box opens.




**Selected Template Administrators** lists users that are assigned as template administrators. **Available Users** lists users available in the template. When you assign template administrators, the users are moved from the Available Users list to the Selected Template Administrators list. Template administrator users can customize template projects and apply template customization to linked projects. For more information, see ["Cross Project Customization" on page 257](#).

- **Refresh.** Click the **Refresh** button  to refresh the list of available users.
- **Find.** Type the name of a user in the **Find** box, and click the **Find** button  to search the Available Users list.
- **Add Selected Users.** Select the users you want to assign as template administrators, and click the **Add Selected Users** button . Alternatively, double-click a user name. The selected users are moved to the Selected Template Administrators list.
- **Delete.** To remove a user from the Selected Template Administrators list, right-click the user name and click **Delete**.

You can also assign template administrators after you have created the template. For more information, see ["Assigning Project Administrators" on page 66](#).

14. Click **Next**. The following dialog box opens.



Verify the template details. To change of the details, click **Back**.

15. Select **Activate template** to activate the template. Only activated templates are available in the HP Application Lifecycle Management Login window. For more information, see ["Deactivating and Activating Projects" on page 80](#).
16. Click **Create**. The new template is added to the Projects list under **Template Projects**.

## Creating a Template from an Existing Project

You can create a template project by copying the customization of an existing project. This option copies customization from the project but does not copy project data.


You can choose to link the newly created template to the project from which it is copied. This enables the template administrator to apply template customization changes to the linked project.

### Note:


- If the project from which you create the template contains workflow scripts, the scripts must be converted after the template is created. This enables the template administrator to apply template workflow customization to linked projects. For more information, see [HP Software Self-solve knowledge base article KM494331](http://h20230.www2.hp.com/selfsolve/document/KM494331) (<http://h20230.www2.hp.com/selfsolve/document/KM494331>).
- **Version Control:** If you copy a version control enabled project, the new template is created with version control enabled.

### To create a template from an existing project:

1. In Site Administration, click the **Site Projects** tab.
2. Select the domain where you want to create the template.
3. Click the **Create Template** button. The Create Template dialog box opens.



4. Select **Create a template by copying customization from an existing project** and click **Next**. The Copy from Project Customization dialog box opens.




The 'Create Template' dialog box has a title bar with a close button. Below the title bar is a section titled 'Copy from Project Customization'. Under this section, it says 'Copy customization from the following project:'. There are two dropdown menus: 'Domain:' and 'Project:'. Below these is a checkbox labeled 'Link the selected project to this template'. At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

5. In the **Domain** box, select the domain where the project you want to copy is located.
6. In the **Project** box, select the project you want to copy.
7. Select **Link the selected project to this template** to link the project to the newly created template. This enables the template administrator to apply template customization changes to the linked project.

**Note:** After you link a project to a template, the template administrator must apply template customization to the project. This applies the customization from the template to the linked project, and sets the applied customization to read-only in the project. For more information, see ["Applying Template Customization to Linked Projects" on page 263](#).

8. Click **Next**. The following dialog box opens.




The 'Create Template' dialog box has a title bar with a close button. Below the title bar, there is a text input field for 'Template Name:'. Below that is a dropdown menu for 'In Domain:' with 'DEFAULT' selected. At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

9. In the **Template Name** box, type a name for the template. The template name cannot be longer than 30 characters and cannot include any of the following characters: = ~ ` ! @ # \$ % ^ & \* ( ) + | { } [ ] : ' ; " < > ? , . / \ -

10. In the **In Domain** box, select a domain.

**Tip:** After the template has been created, you can move it to a different domain in the Projects list using a drag-and-drop operation.

11. Click **Next**. The following dialog box opens.



The image shows a 'Create Template' dialog box with a blue title bar. It contains two sections: 'Database Type' and 'DB Server'. Under 'Database Type', there are two radio buttons: 'Oracle' and 'MS-SQL', with 'MS-SQL' selected. Under 'DB Server', there are three fields: 'Server Name' (a dropdown menu showing 'almsrv'), 'DB Admin User' (a text box containing 'sa'), and 'DB Admin Password' (a text box containing '\*\*\*\*\*'). At the bottom, there are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.


12. Under **Database Type**, select **Oracle** or **MS-SQL**.

The default values defined for the domain are displayed for **Server Name**, **DB Admin User**, and **DB Admin Password**. If additional database servers are defined, you can select another name from the **Server Name** list.

13. Click **Next**.

If your selected database server does not have the text search feature enabled, a message box opens. The message indicates that after this process completes, you can enable the text search feature. For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).

14. If you are creating a Microsoft SQL template, proceed to step 15. For an Oracle template, the following dialog box opens.




The "Create Template" dialog box has a title bar with a close button. It contains two dropdown menus: "Create in TableSpace" with the value "USERS (31.2Mb Free)" and "Temporary TableSpace" with the value "TEMP". At the bottom are four buttons: "Back" (with a left arrow), "Next" (with a right arrow), "Cancel", and "Help".

In the **Create in TableSpace** box, select a storage location that has sufficient space to store the new template. You should not use **UNDO** as the storage location.

In the **Temporary TableSpace** box, select a temporary storage location that has sufficient space to store the new template.

Click **Next**.

15. The Add Template Administrators dialog box opens.






The "Add Template Administrators" dialog box has a title bar with a close button. It is divided into two main sections: "Selected Template Administrators" on the left, which is an empty list box, and "Available Users" on the right. The "Available Users" section includes a "Find" text box with a magnifying glass icon and a list of users. The list has two columns: "User Name" and "Full Name". The users listed are alex\_alm (Alex Smith), alice\_alm (Alice Jones), cecil\_alm (Cecil Davis), james\_alm (James Johnson), michael\_alm (Michael Brown), peter\_alm (Peter Adams), and robert\_alm (Robert Phillips). At the bottom are four buttons: "Back" (with a left arrow), "Next" (with a right arrow), "Cancel", and "Help". A note at the bottom states: "Note: You can also assign Template Administrators after creating a template."

**Selected Template Administrators** lists users that are assigned as template administrators.


**Available Users** lists users available in the template. When you assign template administrators, the users are moved from the Available Users list to the Selected Template Administrators list.

Template administrator users can customize template projects and apply template customization to linked projects. For more information, see ["Cross Project Customization" on page 257](#).

- **Refresh.** Click the **Refresh** button  to refresh the list of available users.
- **Find.** Type the name of a user in the **Find** box, and click the **Find** button  to search the Available Users list.
- **Add Selected Users.** Select the users you want to assign as template administrators, and click the **Add Selected Users** button . Alternatively, double-click a user name. The selected users are moved to the Selected Template Administrators list.
- **Delete.** To remove a user from the Selected Template Administrators list, right-click the user name and click **Delete**.

You can also assign template administrators after you have created the template. For more information, see ["Assigning Project Administrators" on page 66](#).

16. Click **Next**. The following dialog box opens.



Verify the template details. To change any of the details, click **Back**.

17. Select **Activate template** to activate the template. Only activated templates are available in the HP Application Lifecycle Management Login window. For more information, see ["Deactivating and Activating Projects" on page 80](#).
18. Click **Create**. The new template is added to the Projects list under **Template Projects**.

## Importing a Template Project

You can create a template project by importing data from an exported template project file created in the current version. For more information on exporting projects, see ["Exporting Projects" on page 79](#).


If you import a template that was previously exported from the same server, ALM recognizes that the same template already exists on the server, based on the template ID. You can choose to replace the existing template, or cancel the import process. If you choose to replace the existing template when prompted, ALM overwrites the template, but does not overwrite connections to linked projects. The new template remains linked to the same projects.

**Note:** The new template inherits the Unicode or ASCII definition of the imported template.




### To import a template project:

1. In Site Administration, click the **Site Projects** tab.
2. Select the domain where you want to create the template.
3. Click the **Create Template** button. The Create Template dialog box opens.




4. Select **Create a template by importing data from exported template file**. The Create Template: Select File for Import dialog box opens.



5. Click the browse button to the right of the **Import template from** box to locate the template project that you want to import. The Open dialog box opens.
6. Locate the directory and select the ALM Project Export file that you want to import. Click **Open**. The selected file is displayed in the **Import template from** box.


7. Click **Next**. The following dialog box opens.



The image shows a Windows-style dialog box titled "Create Template". It has a standard title bar with a close button (X). The dialog is divided into two main sections. The first section, "Database Type", contains two radio buttons: "Oracle" and "MS-SQL". The "MS-SQL" radio button is selected. The second section, "DB Server", contains three input fields. The first is "Server Name", which is a dropdown menu showing "almsrv". The second is "DB Admin User", which is a text box containing "sa". The third is "DB Admin Password", which is a text box containing "\*\*\*\*\*". At the bottom of the dialog, there are four buttons: "Back" (with a left arrow), "Next" (with a right arrow), "Cancel", and "Help".

8. Under **Database Type**, select **Oracle** or **MS-SQL**.  
The default values defined for the domain are displayed for **Server Name**, **DB Admin User**, and **DB Admin Password**. If additional database servers are defined, you can select another name from the **Server Name** list.
9. Click **Next**.  
If your selected database server does not have the text search feature enabled, a message box opens. The message indicates that after this process completes, you can enable the text search feature. For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).

10. If you are creating a Microsoft SQL template, proceed to step 11. For an Oracle template, the following dialog box opens.




The 'Create Template' dialog box has a title bar with a close button. It contains two dropdown menus: 'Create in TableSpace' with 'USERS (31.2Mb Free)' selected, and 'Temporary TableSpace' with 'TEMP' selected. At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'.

In the **Create in TableSpace** box, select a storage location that has sufficient space to store the new template. You should not use **UNDO** as the storage location.

In the **Temporary TableSpace** box, select a temporary storage location that has sufficient space to store the new template.

Click **Next**.

11. The Add Template Administrators dialog box opens.






The 'Add Template Administrators' dialog box has a title bar with a close button. It features a 'Selected Template Administrators' list on the left and an 'Available Users' list on the right. The 'Available Users' list has a 'Find' search bar and a list of users with columns for 'User Name' and 'Full Name'. At the bottom are four buttons: 'Back' (with a left arrow), 'Next' (with a right arrow), 'Cancel', and 'Help'. A note at the bottom states: 'Note: You can also assign Template Administrators after creating a template.'

User Name	Full Name
alex_alm	Alex Smith
alice_alm	Alice Jones
cecil_alm	Cecil Davis
james_alm	James Johnson
michael_alm	Michael Brown
peter_alm	Peter Adams
robert_alm	Robert Phillips


**Selected Template Administrators** lists users that are assigned as template administrators. **Available Users** lists users available in the template. When you assign template administrators, the users are moved from the Available Users list to the Selected Template Administrators list.

Template administrator users can customize template projects and apply template customization to linked projects. For more information, see ["Cross Project Customization" on page 257](#).

- **Refresh.** Click the **Refresh** button  to refresh the list of available users.
- **Find.** Type the name of a user in the **Find** box, and click the **Find** button  to search the Available Users list.
- **Add Selected Users.** Select the users you want to assign as template administrators, and click the **Add Selected Users** button . Alternatively, double-click a user name. The selected users are moved to the Selected Template Administrators list.
- **Delete.** To remove a user from the Selected Template Administrators list, right-click the user name and click **Delete**.

You can also assign template administrators after you have created the template. For more information, see ["Assigning Project Administrators" on page 66](#).

12. Click **Next**. The following dialog box opens.



Verify the template details. To change any of the details, click **Back**.

13. Select **Activate template** to activate the template. Only activated templates are available in the HP Application Lifecycle Management Login window. For more information, see ["Deactivating and Activating Projects" on page 80](#).
14. Select **Enable Versioning** to enable version control for the template. You can also enable version control after you have created the template. For more information, see ["Enabling and Disabling Version Control for a Project" on page 80](#).
15. Click **Create**. The new template is added to the Projects list under **Template Projects**.

## Linking a Template to Projects

You link a template to projects as part of cross project customization. The template administrator uses cross project customization to apply template customization to the linked projects. You can link a template to multiple projects, but you can link a project to only one template. For more information, see ["Cross Project Customization" on page 257](#).


**Note:** After you link a template to a project, the template administrator must apply template

customization to the project. This applies the customization from the template to the linked project, and sets the applied customization to read-only in the project. For more information, see ["Applying Template Customization to Linked Projects" on page 263](#).

You can also link a template to a project when you create a project. For more information, see ["Creating Projects" on page 24](#). To link a template to a project when you create the template from an existing project, see ["Creating a Template from an Existing Project" on page 52](#).

#### To link a template to projects:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a template project. In the right pane, click the **Linked Projects** tab. The Linked Projects list is displayed.
3. Click the **Add** button. The Projects list is displayed in the right pane.



4. Select projects from the Projects list, and click the **Add Selected Projects** button. The selected projects are displayed in the Linked Projects list.
5. You can search for a project in the Linked Projects list by typing the name of a project in the **Find** box, and clicking the **Find** button. You can also click on a column heading to change the sort order of the projects in the Linked Projects list.
6. To remove a project from a template, in the Linked Projects list, select the project. To remove more than one project, press the CTRL key and select the projects. Click **Remove**. Click **OK** to confirm. This removes the project from the Linked Projects list, and the project is no longer linked to the template.
7. To refresh the Linked Projects list or the Projects list, click the **Refresh** button above the appropriate list.

## Updating Project Details

You can view project details such as database type and project directory from the Project Details tab. You can also edit various settings for the project. For example, you can edit the connection string, change the number of users allowed to connect concurrently to the project, and enable the automatic sending of defect email. Updated project details are written to the **dbid.xml** file, so that if a project is restored, the updated project data is used. For more information, see ["Restoring Access to Projects" on page 86](#).


**Tip:** You can move a project to a different domain in the Projects list using a drag-and-drop operation. This does **not** change the physical location of the project.

**Cross Project Customization:** If you are working with a template project, you update template details from the Template Details tab.

ALM Editions: Template projects are not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

#### To update project details:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project. In the right pane, select the **Project Details** tab. The project's details are displayed.



**Note:** If a project is inactive, the project icon is displayed in red. To activate, see ["Deactivating and Activating Projects" on page 80](#).

3. Under **Project Database**, view the following project details:

Field	Description
<b>Database Type</b>	The database type can be MS-SQL or Oracle.
<b>Database Name</b>	The project name, as defined in the database.
<b>Database Server</b>	The name of the database server on which the database is located.
<b>Created From Project</b>	The project was copied from this project. An <b>Empty Database</b> value indicates that the project was not copied. For more information, see <a href="#">"Copying Projects" on page 31</a> .
<b>Created From Template</b>	The project was copied from this template.

Field	Description
<b>Restored From Project</b>	The project was restored from this project. For more information, see <a href="#">"Restoring Access to Projects" on page 86</a> .
<b>Created From Domain</b>	The project was copied from this domain.
<b>Restored From Domain</b>	The project was restored from this domain. For more information, see <a href="#">"Restoring Access to Projects" on page 86</a> .
<b>Maintenance State</b>	Indicates whether a maintenance task is being performed on this project. Tasks include verifying, repairing, upgrading, and realigning a project. Possible values are: <ul style="list-style-type: none"> <li>• <b>Idle.</b> No maintenance is being performed on this project.</li> <li>• <b>Corrupted.</b> Maintenance cannot be completed because the project is corrupted. To resume, a backup copy of this project must be restored.</li> <li>• <b>Under maintenance task.</b> Maintenance is being performed on this project.</li> </ul> For more information on maintaining projects, see <a href="#">"Upgrading Projects to a New Version" on page 91</a> .
<b>Unicode Supported</b>	Indicates whether this project supports Unicode.
<b>Connection String</b>	The connection string. To modify the connection string, see <a href="#">"Editing the Connection String" on page 86</a> .
<b>DB User Password</b>	The user password for the Oracle server on which the database is located. To modify this password, see <a href="#">"Modifying Database Server Properties" on page 150</a> .
<b>Project Directory</b>	The location of the project repository in the file system.
<b>Search Language</b>	Indicates the search languages for performing a text search. For more information, see <a href="#">"Selecting a Text Search Language for a Project" on page 153</a> .
<b>Exception File</b>	Indicates the location of the exception file to be used when running the upgrade process. For more information, see <a href="#">"Upgrading Domains and Projects" on page 102</a> .

4. Under **Repository Cleanup**, promote or delay the scheduled project repository cleanup. For more details on the project repository cleanup, see ["Project Repository Cleanup" on page 72](#).

Click the available button:

- **Promote Repository Cleanup.** Instructs ALM to cleanup the repository of the current project as soon as possible.
- **Postpone Repository Cleanup.** Instructs ALM to postpone the repository cleanup of the current project, or to stop a cleanup that is in progress.

5. Under **Project Planning and Tracking**, view the following project details:

Field	Description
<b>Automatic Calculations</b>	Indicates whether the project is included in the automatic daily project planning and tracking calculations of your site. For more information, see <a href="#">"Enabling or Disabling Automatic</a>

Field	Description
State	<a href="#">Calculations for a Project" on page 166.</a>
Run Now	Enables you to manually trigger project planning and tracking calculations for a project in order to refresh its results without waiting for the next scheduled calculation. For more information, see <a href="#">"Launching Calculations for a Project Manually" on page 167.</a>

ALM Editions: Functionality related to project planning and tracking is available for ALM Edition only. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

- Under **Miscellaneous**, select **Send mail automatically** to enable the mail configuration settings for a project. This sends email to specified users every time set defect fields are updated. If this check box is not selected, mail configuration settings for the project have no effect and email is not sent. For more information on configuring mail, see ["Configuring Automail" on page 241.](#)


The defect messages are sent automatically, at specified time intervals. You can edit the time interval using the **MAIL\_INTERVAL** parameter in the **Site Configuration** tab. You can also specify if you want the email to include attachments and/or history. For more information, see ["Setting ALM Configuration Parameters" on page 155.](#)

To manually send the defect messages that have accumulated during the current time interval, click the **Send Email Now** button. If the **Send mail automatically** check box is not selected, defect messages do not accumulate, so this button has no effect.

- If you enable the **Text Search** link in the **DB Servers** tab after you have added a project to the Projects list in the Site Projects tab (for example, after creating, upgrading, or migrating a project), you must also click the **Enable/Rebuild Text Search** button. For more information, see ["Enabling Text Search in ALM" on page 152.](#)
- The **Linked to Template** field displays the name of the template that the project is linked to. For more information on linked templates, see ["Updating Linked Template Details" on page 266.](#)
- To change the number of users allowed to connect concurrently to the project, click the **User Quota** link. The Project User Quota dialog box opens.

Choose **Maximum connections** and type the maximum number of concurrent connections allowed. Click **OK**.

**Note:** The maximum number of users allowed to connect concurrently to the project should not exceed the number of users allowed to connect to its domain. For more information, see ["Creating Domains" on page 23.](#)

- To add a description for the project, click the **Description** link. In the Edit Project Description dialog box, type your description and click **OK**. By default, the project creation date is displayed.
- Click the **Refresh Projects List** button  to refresh the projects in the selected domain. To refresh projects in all domains, click the **Refresh Projects List** arrow and choose **Refresh All Domains**.
- To assign users to a project, see ["Assigning Users to Projects" on the next page.](#)



## Assigning Users to Projects

As a site administrator, you can control access to projects or template projects by defining the users that can log on to the project. You can assign users to projects from the Users list, or copy users from existing projects. You can also assign users as project administrators. For more information on assigning project administrators, see ["Assigning Project Administrators" on the next page](#).

When a user is no longer working on a project, remove the user from the project to ensure project security. Removing a user from a project does not delete the user from the Users list. To remove the user from the Users list, you must delete the user from the Site Users tab, as described in ["Deleting Users" on page 133](#).

### Note:

- As a project administrator, you can assign and remove users from projects, and change user privileges from the Project Customization window. For more information, see ["Managing Users in a Project" on page 207](#).
- You can assign projects to users from the Site Users tab. For more information, see ["Assigning Projects to Users" on page 131](#).
- Automatic email notification is sent to project administrators when users are assigned or removed from a project in Site Administration. You can make automatic notification unavailable by adding the **AUTO\_MAIL\_USER\_NOTIFICATION** parameter in the Site Configuration tab. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).


**Cross Project Customization:** If you are working with a template project, you assign users from the Template Users tab.

ALM Editions: Template projects are not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.




### To assign users to a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project. In the right pane, select the **Project Users** tab.

The users for the selected project are displayed.



You can click the **User Name** or **Full Name** column headers to change the sort order of user names or full names in the Project Users list from ascending to descending. You can also click the **Project Administrator** column header to group users by project administrators.

3. Click the **Add** button, and choose one of the following options:
  - **Add From The Users List.** The Users list is displayed to the right of the Project Users tab. Select the users that you want to assign to the project. You can search for users by typing a search string in the **Find** box above the Users list, and clicking the **Find** button .
  - **Copy From Another Project.** The Projects list is displayed to the right of the Project Users tab. To copy a user, click a project to expand the project directory, and select the user name check box. To copy all users from a project, select the project's check box. To clear all selected users, click **Clear All**.
4. Select users from the Users list or Projects list, and click the **Add Selected Users** button . Alternatively, double-click a user. The selected users are displayed in the Project Users list.
5. To remove a user from a project, select the user in the Project Users list and click the **Remove** button. Click **Yes** to confirm. The user is removed from the Project Users list.
6. To refresh the Project Users list or Users list, click the **Refresh** button  above the appropriate list.

## Assigning Project Administrators

After you add users to projects you can assign users as project administrators (belonging to the **TDAdmin** user group). Project administrators have full privileges in the project from the Project Customization window. For more information, see ["Managing User Groups and Permissions" on page 211](#).

When you copy users from other projects, they are added with the same user group privileges they had in the project from which they were copied, provided the user group exists in this project. If the user group does not exist in this project, the users are added with **Viewer** group privileges. If you copy a user from another project in which the user is a project administrator, the user is automatically assigned as a project administrator in this project.

When you add users to the project from the Users list, those users are added with Viewer group privileges (read-only privileges).

**Note:** You can also assign project administrators when you create a new project. For more information, see ["Creating Projects" on page 24](#).

**Cross Project Customization:** If you are working with a template project, you assign users as template administrators from the **Template Users** tab.

ALM Editions: Template projects are not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

### To assign Project Administrator privileges to a user:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project. In the right pane, select the **Project Users** tab.
3. In the Project Users list, select the **Project Administrator** check box for each user you want to assign as a project administrator.
4. To remove a user from the Project Administrator group, clear the **Project Administrator** check box, and confirm you want to remove the user from the group.

## Enabling Extensions for a Project

Extensions provide added functionality to ALM. If you have a license for an ALM extension, you can utilize its added functionality after enabling the extension on a per project basis.

To view the list of extensions available with ALM, or to download documentation for ALM extensions, visit the Add-ins page, available from **Help > Add-ins**.


**Cross Project Customization:** If an extension is enabled for a template project, the extension must also be enabled for the template's linked projects. Linked projects can have additional extensions enabled.

ALM Editions: Template projects are not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

You can also enable extensions for a project when you create a project. For more information, see ["Creating Projects" on page 24](#).

### To enable extensions for a project:


1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project. In the right pane, click the **Project Extensions** tab.



The Extensions list displays the extensions that are enabled for the selected project.

3. To enable one or more extensions for the project, click the **Enable Extensions** button. The Enable Extensions dialog box opens, displaying the list of extensions available for your ALM edition on the ALM server.

**Tip:** Extensions for which there is no license on the server are displayed in gray. It is possible to enable an extension for which you do not yet have a license. You can utilize the extension's added functionality later, after receiving the license.




4. Select the **Enable** check box for the extensions you want to enable.


**Note:** You cannot disable an extension for a project after you enable it. We recommend enabling only the extensions you need. Enabling extra extensions can affect performance and consumes additional disk space.

As you navigate from one extension to another, relevant license status information is displayed in the **License Status** section.

5. Click **Enable**. The selected extensions are enabled for the project, and the extension names are

displayed in the Extensions list.



6. To refresh the Extensions list, click the **Refresh** button .



# Chapter 3: Managing the Optimized Project Repository

ALM stores all project files in a project repository located under the **ProjRep** directory. The files in this directory are stored in an optimized folder structure that allows maximum storage space. In addition, any two files with identical content are stored only once in the **ProjRep** directory. For example, if you attach the same file to several ALM records, the file is stored only once in the project repository. This results in a significant reduction in disk space, and reduced time in copy operations.

This section includes:

- [Project Repository Cleanup](#) .....72
- [Browsing the Project Repository](#) ..... 72
- [Realigning Repositories](#) .....74

## Project Repository Cleanup

When you add a file to an entity, ALM checks whether an identical file exists in the project repository. If an identical file is located, no physical file is added to the repository.

When you delete a file from an entity, the file is not immediately deleted from the project directory, as it may still be used by other entities.

At regular intervals, the project repository is scanned for obsolete files that are no longer referenced by any entity. If the files remain unreferenced for a specified period, they are removed from the project repository. These intervals are set by default at seven days each. You can configure the intervals using the site configuration parameters below.

You can promote or postpone a project's repository cleanup. For more details, see ["Updating Project Details" on page 61](#).

You can define the following site configuration parameters to regulate the project repository cleanup process. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

- **REPOSITORY\_GC\_PROJECT\_CLEANUP\_INTERVAL.** Defines the time interval between cleanup processes of each project repository.
- **REPOSITORY\_GC\_DELAY\_CANDIDATE\_TIME.** Defines the time that elapses after obsolete files are detected in a scan, and before the obsolete files are removed.
- **REPOSITORY\_GC\_JOB\_PRIORITY.** Defines the speed at which the cleanup process is performed.
- **SUSPEND\_REPOSITORY\_GC.** Enables you to stop the project repository cleanup process.

## Browsing the Project Repository

You can browse and edit files in the project repository using an FTP client. Most standard FTP clients that support UTF-8 character encoding are compatible. The following clients are verified:

- Filezilla
- Total Commander Built-in FTP client
- FlashFXP

You can configure the FTP service for a secure connection. For more information, see ["Enabling Secure FTP Connections" on the next page](#).

**Caution:** Making changes to the folders, files, or file content directly in the **ProjRep** directory, not via an FTP client, will cause irreversible damage to the project repository.

When making changes to repository files via an FTP client, consider the following:

- It is safe to edit repository files via an FTP client. This will not damage the integrity of the optimized repository.
- Deleting a file will result in missing content in ALM entities.
- Renaming folders and files may result in missing content in ALM entities.



## To browse the project repository:

1. **Start the FTP service.** Add and configure the **FTP\_PORT** parameter in the **Site Configuration** tab. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).
2. **Connect to the FTP server.** In an FTP client, use the following connection values:

Field	Value
<b>Host</b>	The name or IP of the ALM server to which you want to connect.
<b>Port</b>	The FTP port. This should be the same value that you used for the <b>FTP_PORT</b> site parameter.
<b>User</b>	The username of an ALM site administrator.
<b>Password</b>	The password of the ALM site administrator.

3. **Browse and edit repository files.** After you connect to the FTP service, a list of the site domains is displayed. Select a domain, and then select a project. The FTP client displays the project repository directories.

## Enabling Secure FTP Connections

You can connect to the FTP server using a secure connection.

### To enable a secure FTP connection:

1. On the ALM server machine, generate a **keystore** file. Using the command line, go to **C:\Program Files\HP\HP Application LifeCycle Management <current version>\java\bin**. Type `keytool-genkey-keystore keystore.jks` to run the keystore utility, then follow the instructions.
2. Create an XML file, using the following format:

```
<ssl>

<keystore file="<keystore file path>" password="<keystore password>"/>

</ssl>
```

where `<keystore file path>` is the directory and file name of the keystore file, and `<keystore password>` is the password you defined for the keystore.

Save the XML file as **sslkeystore.xml**.

3. Place the **sslkeystore.xml** file in the following directory:  
**C:\ProgramData\HP\ALM\webapps\qcbn**.
4. Restart the FTP server by restarting the ALM service, or reconfiguring the **FTP\_PORT** site parameter.
5. In the FTP client, select the **FTPS** or **SSL** option. If you are using FileZilla, go to **File > Site Manager** and click **New Site**. For **Protocol**, select **FTP-File Transfer Protocol**, and for **Encryption**, select **Require implicit FTP over TLS**, and click **connect**.

## Realigning Repositories

ALM project repositories consist of the physical files that are stored in the file system, and database tables that index the files. When you create a backup of a project that is active, the time gap between the database and file system backups can cause discrepancies between the database file index and the physical files.

For details on backup, see ["Backing Up Projects" on page 106](#).

If you restore a project for online work from a backup that was performed while the project was active, you must realign the file system and database tables.

The realigning process performs the following actions:

- If a file is indexed in the database but is not located in the file system, the index of the file is removed from the database.
- If a file is stored in the file system but is not indexed in the database, the file is deleted from the file system.

In addition, the realigning process verifies the integrity of the relationship between the logical and physical database tables.

If an irrecoverable problem is detected, the project **Maintenance State** is changed to **Corrupted**. Check the log for details, and examine the database tables.


By default, the realigning process runs in non-silent mode. When running the process in non-silent mode, ALM may pause and prompt you for input when an error occurs. Instead, you can choose to run the process in silent mode. When an error occurs, ALM will abort the process without prompting you for input.


**Note:** Projects are deactivated while the realignment is in progress, and activated again after the realignment is complete.

### Realigning a Project

This section describes how to realign a single project.

#### To realign a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Maintain Project**  button and choose **Realign Repository**. The Realign Project dialog box opens.





4. To run the realigning process without any user interaction, select **Run in Silent Mode**.
5. To start the realigning process, click the **Realign Project** button. If the project is active, you are prompted to deactivate it. For more information, see ["Deactivating and Activating Projects" on page 80](#).
6. To save the messages displayed in the Realign Results pane to a text file, click the **Export Log** button. In the Export Log to File dialog box, choose a location and type a name for the file. Click **Save**.
7. To clear the messages displayed in the Realign Results pane, click the **Clear Log** button.
8. Click **Close** to close the Realign Project dialog box.

## Realigning a Domain

This section describes how to realign all projects in a domain.

### To realign a domain:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a domain.
3. Click the **Maintain Domain**  button and choose **Realign Repository**. The Realign Domain dialog box opens.



4. In the **Realign Settings** area, under **Realign Mode**, you can select the following options:
  - **Run in Silent Mode.** Runs the process without any user interaction.
  - **Continue to next project if realign failed.** Proceeds to the next project if the realign process fails. This is the default option.
5. In the **Realign Settings** area, under **After the Realign**, you can select one of the following options:
  - **Leave all projects deactivated.** Leaves all projects deactivated after the realign process completes.
  - **Activate all projects.** Activates all projects after the realign process completes.
6. To view the current version numbers of your projects, select the project names, or click **Select All** to view version numbers for all projects. Click the **Display Versions** button.  
The project version number is displayed in the **Version** column.
7. To realign your projects, select the project names, or click **Select All** to realign all projects. Click the **Realign Repository** button.
8. To save the messages displayed in the Realign Results pane in a text file, click the **Export Log** button. In the Export Log to File dialog box, choose a location and type a name for the file. Click **Save**.
9. To clear the messages displayed in the Realign Results pane, click the **Clear Log** button.
10. Click **Close** to close the Realign Domain dialog box.

# Chapter 4: Managing Projects

Site Administration enables you to manage and maintain HP Application Lifecycle Management (ALM) domains and projects.

This chapter includes:

• About Managing Projects .....	78
• Querying Project Tables .....	78
• Exporting Projects .....	79
• Deactivating and Activating Projects .....	80
• Enabling and Disabling Version Control for a Project .....	80
• Pinging Projects .....	81
• Renaming Projects .....	81
• Converting Projects to Unicode .....	82
• Removing Projects .....	84
• Deleting Projects .....	85
• Deleting Domains .....	85
• Editing the Connection String .....	86
• Restoring Access to Projects .....	86
• Renaming the Defects Module for a Project .....	88
• Limiting Records Displayed in Grids .....	89

## About Managing Projects

You manage ALM projects and template projects using Site Administration. After you create a project, you can export the project, query the contents of the project by defining and running SQL statements, deactivate/activate access to the project, and enable or disable version control for the project. You can also remove a project, and restore access to an existing project.

**Note:** Users who are already logged into **Lab Management** need to re-enter the application to see changes you made in Site Administration.

For more information on creating projects, see ["Creating Projects" on page 21](#).


ALM Editions: ALM template projects are not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

## Querying Project Tables

You can query specific data that is stored in your project or template project. You query a project by defining and running SQL queries. The following examples show SQL queries and the results that they return.

Query	Results
<pre>select * from BUG where BG_STATUS = 'Open'</pre>	All defects that are open.
<pre>select * from BUG where BG_RESPONSIBLE = 'james_alm' or BG_RESPONSIBLE = 'mary_alm'</pre>	All defects assigned to either James or Mary.
<pre>select count (*) from BUG where BG_RESPONSIBLE = 'mary_alm'</pre>	The number of defects assigned to Mary.
<pre>select * from BUG where BG_RESPONSIBLE='james_alm' and BG_STATUS='open'</pre>	All open defects assigned to James.

Using the first query example, the SQL query returns the following:



The screenshot shows the HP ALM interface with a SQL query window. The query is: `SELECT * FROM BUG WHERE BG_STATUS = 'Open'`. The results are displayed in a table with columns: BG\_BUG\_ID, BG\_STATUS, BG\_RESPONSIBLE, BG\_PROJECT, BG\_SUBJECT, BG\_SUMMARY, and BG\_ID. The results show 10 rows of open bugs assigned to either James or Mary.

BG_BUG_ID	BG_STATUS	BG_RESPONSIBLE	BG_PROJECT	BG_SUBJECT	BG_SUMMARY	BG_ID
3	Open	james_alm	Mercury Tours	78	The list of flight: Test	
5	Open	james_alm	Mercury Tours	78	The list of flight: Test	
6	Open	mary_alm	Mercury Tours	76	If error on subm If error	
7	Open	peter_alm	Mercury Tours	72	Incorrect time fr: Time	
10	Open	mary_alm	Mercury Tours	76	User profile is r: Test	
11	Open	mary_alm	Mercury Tours	76	User Profile reg: Test	
12	Open	mary_alm	Mercury Tours	76	User profile is r: Test	
13	Open	mary_alm	Mercury Tours	85	Changes to Emv: Test	
16	Open	peter_alm	Mercury Tours	80	The itinerary is: Test	
17	Open	peter_alm	Mercury Tours	80	The itinerary is: Test	
20	Open	mary_alm	Mercury Tours	71	Mercury Tours: Test	

### To query a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, double-click a project.
3. Select a table. ALM automatically runs the "SELECT \*" query for this table and displays all the data for the table in the SQL Query Results grid.
4. Define a query by typing an SQL statement in the SQL pane.

To navigate back to your previous SQL statement in the SQL pane, click the **Up** button .

To navigate forward to your next SQL statement in the SQL pane, click the **Down** button .

5. Click the **Execute SQL** button. The data returned by the query appears in the SQL Query Results grid.

**Tip:** To export query results, your database administrator can run the same queries on the project database and export the results for you. For details, see ["Exporting Projects" below](#).

## Exporting Projects


Exporting ALM projects or template projects enables you to take project data from an ALM server, and back it up to another location or another media device. For example, you may want to create self-contained project image files that are backed up on a USB storage device or DVD. You can send the media device to an ALM server in another location, and import the project files. When you export a project file, it is saved and exported in ZIP format.

Before exporting a project, consider the following guidelines:

- If you export an ALM project that has extensions installed, all data from the project is exported, including data for the extensions. You can only import such an exported project to a server that has the relevant extensions installed.
- You can only import ALM project files created in the same ALM version. For more information on importing projects, see ["Importing Projects" on page 37](#).
- The project database schema and project file system repository combined should not exceed 4 gigabytes.
- There must be adequate disk space available in your home directory on the ALM client machine to temporarily store the exported project file, even if you choose an alternate location for saving the file.
- You will not be able to import the project onto the original server, if a project with the same PUID exists on that server.
- If the project was not part of Lab Management, when restoring access to the project:
  - Details about test runs will not be included in the Usage Reports.
  - Timeslot information and project settings information are lost.

### To export a project:

1. In Site Administration, click the **Site Projects** tab.


2. In the Projects list, select a project, and click the **Export Project to Project File** or **Export Template to Project File** button . Alternatively, right-click the project and choose **Export Project** or **Export Template**. If the project is active, you are prompted to deactivate it. For more information, see ["Deactivating and Activating Projects" below](#).
3. The Save As dialog box opens. Select the directory where you want to save the project data. Type a name for the project in the **File name** box. By default, the data is saved as an ALM Project Export file (.qcp).
4. Click **Save** to save the project data as an ALM Project Export file.

## Deactivating and Activating Projects

You can deactivate or activate a project or template project. When you deactivate a project, the project name is removed from the **Projects** box in the ALM Login window. The project is not deleted from the server. Any users currently connected to the project are forced to log out when you deactivate.

**Note:** It is recommended that you deactivate a project before you change any data that may cause inconsistency for connected users.

### To deactivate a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Deactivate Project** or **Deactivate Template** button . A message box indicates that all connected users will be disconnected.
4. Click **OK** to confirm. The project is deactivated and the project icon is changed in the Projects list.

### To activate a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Activate Project** or **Activate Template** button . The project is activated and the project icon is changed in the Projects list.

## Enabling and Disabling Version Control for a Project

You can enable version control for a project or template project. For more information on version control, refer to the *HP Application Lifecycle Management User Guide*.

You can also disable version control for a project. When you disable version control for a project, ALM no longer stores previous versions, and deletes all version history for the project. If you enable version control for the project again, previous history is not available.

**Note:** After enabling version control for a project, you should review all its workflow scripts and




make adjustments for each checked in entity. This includes the following entities: **Req**, **Test**, **Resource**, and **Component**. For each checked in entity that includes a **Post** function in its script, you must modify the script. To modify, add a **Checkout** function before every **Post** function. Making this modification prevents the Check Out dialog box from opening each time a call to a **Post** function is made. For more information, see ["Workflow Event Reference" on page 347](#).

### To enable version control for a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Enable Versioning** button .
4. If the project is active, click **Yes** to deactivate it. Click **OK** to confirm.
5. When the process completes, click **OK**. Version control is enabled. ALM displays a lock icon  next to the project name in the Projects list.


### To disable version control for a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Disable Versioning** button .
4. If the project is active, click **Yes** to deactivate it. Click **OK** to confirm.
5. A message displays, indicating that when you disable version control, ALM deletes all version history. Click **OK** to confirm.
6. Click **Yes** to disable version control. Version control is disabled. ALM removes the lock icon next to the project name in the Projects list.

## Pinging Projects

You can check whether a project database or template project database is accessible from Site Administration.

### To ping a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Ping Project** or **Ping Template** button .
4. Click **OK** when prompted with a message that the ping was successful.

## Renaming Projects

You can rename a project or template project in the Projects list.

### To rename a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Rename Project** or **Rename Template** button. If the project is active, you are prompted to deactivate it. For more information, see ["Deactivating and Activating Projects" on page 80](#).
4. In the Rename Project dialog box, type the new name for the project and click **OK**.  
The project name cannot be longer than 30 characters and can include only letters, digits, and underscores.

**Note:** Support of non-English national characters depends on the database settings used by the server. We do not recommend using non-English national characters in project names.

The project is renamed in the Projects list.

## Converting Projects to Unicode

This section describes how to convert projects to Unicode. You can select a specific project to convert, or you can select a domain and convert its projects to Unicode.


Unicode is a feature of MS-SQL that allows multi-language support. In Oracle, multi-language support is defined when installing the server.

You can convert the following types of projects to Unicode:


- Projects that are version 11.5 or above.
- Projects created on an MS SQL server.
- Projects created in ASCII.

**Caution:** Unicode increases the memory required for the database server.

### To convert projects in a domain to Unicode:

1. In Site Administration, click the **Site Projects** tab and select the domain whose projects you want to convert.
2. Click the **Maintain Domain**  button and select **Convert to Unicode in Domain**. The Convert to Unicode Domain dialog box opens.

**Note:** **Convert to Unicode in Domain** is only available if projects that can be converted to Unicode exist in the selected domain.



3. Select the project or projects you want to convert and click **Convert to Unicode**. Under Convert to Unicode Results, a log is displayed.


**Tip:** Click **Display Versions** to display the versions of the selected projects.


**Note:** Projects with columns whose length is greater than 4000 cannot be converted to Unicode. The validation process fails and an error message is generated.

To fix the problem, either reduce the column length to 4000 or add the columns to the alm\_i18n\_exceptions.xml exception file before converting. System defined columns and system defined user fields must be reduced and cannot be added to the exception file.

4. To pause the conversion process, click the **Pause** button. To continue, click the **Resume** button.
5. To abort the conversion process, click the **Abort** button. Click **Yes** to confirm.
6. After the process has completed successfully or stopped due to failure, you can select one of the following:
  - **Clear Log.** Clears the text displayed in the Convert to Unicode Results area. This disables the **Export Log** button.
  - **Export Log.** Enables you to save the log as a .txt file. In the Export Log to File dialog box, select a location and type a name for the file. Click **Save**.
7. Click **Close** to close the Convert to Unicode Domain dialog box.

### To convert a project to Unicode:

1. In Site Administration, click the **Site Projects** tab and select the project you want to convert.
2. Click the **Maintain Project**  button and select **Convert Project to Unicode**. The Convert to Unicode dialog box opens.



3. Click **Convert to Unicode**. Under Convert to Unicode Results, a log is displayed.

**Note:** Projects with columns whose length is greater than 4000 cannot be converted to Unicode. The validation process fails and an error message is generated.

To fix the problem, either reduce the column length to 4000 or add the columns to the `alm_i18n_exceptions.xml` exception file before converting. System defined columns and system defined user fields must be reduced and cannot be added to the exception file.

4. To pause the conversion process, click the **Pause** button. To continue, click the **Resume** button.
5. To abort the conversion process, click the **Abort** button. Click **Yes** to confirm.
6. After the process has completed successfully or stopped due to failure, you can select one of the following:
  - **Clear Log.** Clears the text displayed in the Convert to Unicode Results area. This disables the **Export Log** button.
  - **Export Log.** Enables you to save the log as a `.txt` file. In the Export Log to File dialog box, select a location and type a name for the file. Click **Save**.
7. Click **Close** to close the Convert to Unicode dialog box.


## Removing Projects

You can remove a project or a template project from the Projects list in Site Administration. This does not delete the project from the server and you can restore the project if necessary. For more information on restoring access to a project, see ["Restoring Access to Projects" on page 86](#).

**Note:** If the project is currently in use, it cannot be removed. For information about how to manually remove a project, see HP Software Self-solve knowledge base article [KM1457081](http://h20230.www2.hp.com/selfsolve/document/KM1457081) (<http://h20230.www2.hp.com/selfsolve/document/KM1457081>).

### To remove a project from the Projects list:

1. In Site Administration, click the **Site Projects** tab.

2. In the Projects list, select a project.
3. Click the **Remove Project** or **Remove Template** button .
4. Click **OK** to confirm. If the project is still active, you are prompted to deactivate it. For more information, see "[Deactivating and Activating Projects](#)" on page 80.
5. Click **OK**.

## Deleting Projects

You can delete a project or template project from the Projects list in Site Administration. This deletes the contents of the project from the server and you cannot restore the project.

**Note:** If the project is currently in use, it cannot be deleted. For information about how to manually delete a project, see [HP Software Self-solve knowledge base article KM1457081](http://h20230.www2.hp.com/selfsolve/document/KM1457081) (<http://h20230.www2.hp.com/selfsolve/document/KM1457081>).

### To delete a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Delete Project** or **Delete Template** button.
4. Click **OK** to confirm. If there are active users connected to the project, you are prompted to disconnect them.  
  
The Database Admin Password dialog box opens. If you did not specify a database administrator user name or password, enter the database administrator's user name and password and click **OK**. If you previously specified a database administrator user name or password, these credentials are already entered in the dialog box.
5. Click **OK**.

## Deleting Domains

You can delete a domain. It is removed from the Projects list, and its contents are deleted from the server.

**Note:** You cannot delete a domain if it contains projects or template projects. To delete the domain, you must first delete the projects. For more information, see "[Deleting Projects](#)" above.


### To delete a domain:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a domain.
3. Click the **Delete Domain** button.
4. Click **Yes** to confirm.


## Editing the Connection String

You can edit the connection string of a project or a template project.

### To edit the connection string:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Edit Connection String** button  or the **Connection String** link. If the project is still active, you are prompted to deactivate it. For more information, see ["Deactivating and Activating Projects" on page 80](#).

The Connection String Editor dialog box opens.



4. In the **Connection String** box, modify the attributes of the connection string, such as the database server name and port number.
5. To test the connection string, click **Test Connection**. In the Ping Database Server dialog box, type the database administrator user name and password and click **OK**. If the connection is successful, a confirmation message displays. Otherwise, an error message displays.
6. Click **OK** to save your connection string modification and close the Connection String Editor.

## Restoring Access to Projects


You can restore access to an ALM project or template project that is not in your current Projects list in Site Administration. For example, you may want to access a project from another server. After you restore access to a project, it is added to the Projects list in Site Administration.


### Note:

- Before restoring the project, make sure that the database where the project resides exists in the **DB Servers** tab in Site Administration on your ALM server. The ALM server needs to access the contents of the restored project from the project's database. For more information, see ["Upgrading Projects to a New Version" on page 91](#).

- When restoring a project, you should select the **dbid.xml** file located in the project repository. This ensures that the project retains its original ID. If a project does not have its original ID, the following cross project features may not function properly: cross project customization, importing and synchronizing libraries, and cross project graphs.
- If you are restoring your project from a different directory, or if you renamed your schema or restored it to a different database, you must update the **dbid.xml** file accordingly. For details, see ["Updating the dbid.xml file" on the next page](#).
- You must first restore and upgrade any template projects before restoring and upgrading other projects. If the template project and its linked projects are in different databases, ensure that the template project's database is accessible when restoring any linked projects.
- If you were previously working with **Performance Center 11.00** or later, you must first restore and upgrade LAB\_PROJECT, and then any Performance Center template projects, before restoring and upgrading other Performance Center projects. For details, see ["Restoring LAB\\_PROJECT" on page 109](#).

### To restore access to an ALM project:

1. In Site Administration, click the **Site Projects** tab.
2. Click the **Restore Project** or **Restore Template** button . The Restore Project dialog box opens.
3. To locate the file that includes the project that you want to restore, click the browse button to the right of the **dbid.xml file location** box. The Open File dialog box opens.
4. Locate the file. For information on the location of the **dbid.xml** file, see ["Understanding the Project Structure" on page 22](#).
5. Select the **dbid.xml** file and click **Open**. The Restore Project dialog box opens and displays the database type, name, server, and the directory path of the project.



6. In the **Restore Into Domain** box, select the domain in which you want the restored project to be located.
7. Click **Restore**.
8. If your database server does not have the text search feature enabled, a message box opens. You

can enable the text search feature before or after this process completes.

- Click **Yes** to continue this process. After the process completes, you can enable the text search feature.
- Click **No** to stop this process. Enable the text search feature and then restart the process.

For more information on enabling the text search feature, see ["Configuring Text Search" on page 152](#).

9. When the restore process completes, click **OK**.
10. Click **Close** to close the Restore Project dialog box and view the restored project in the Projects list.

## Updating the dbid.xml file

If you are restoring your project from a different directory, or if you renamed your schema or restored it to a different database, for example, as part of the upgrade process, you must update the following values:

- **DB\_NAME**. Update to the database schema name as it appears in the database server.
- **DB\_CONNSTR\_FORMAT**. Update to the value of the the empty project created in ALM12.20. See the note for details.
- **DBSERVER\_NAME**. This is the name of the database server as defined in the **DB Servers** tab in Site Administration.
- **DB\_USER\_PASS**. Update if the encrypted passphrase differs between ALM 11.00 or later and ALM 12.20. If you are upgrading from Quality Center 10.00, this value is not relevant.
- **PHYSICAL\_DIRECTORY**. Update to the new location of the project repository. It must contain a backslash (\) at the end of the path.

### Note:

- In order to identify the values of **DB\_CONNSTR\_FORMAT** and **DB\_USER\_PASS**, it is recommended to create a new, empty project in ALM 12.20 Site Administration, open the project's **dbid.xml** file, and copy these values. You can later delete the empty project.
- Make sure not to copy/paste or change the value for **PR\_SMART\_REPOSITORY\_ENABLED**.
- If you are restoring **LAB\_PROJECT** or Performance Center projects as part of the upgrade process, make sure not to edit the **PROJECT\_UID** value. You must restore these projects with their original **PROJECT\_UID** value in order to maintain the links between **LAB\_PROJECT** and its associated Performance Center projects, important for shared data, such as timeslots, runs, and so on.

## Renaming the Defects Module for a Project

You can rename the Defects module for a specific project or template project. For example, you can change the name of the Defects module from Defects to Bugs. You rename the Defects module by adding a parameter to the **DATACONST** table of the project. For more information on modifying project tables, see ["Querying Project Tables" on page 78](#).

**Note:** You can rename any ALM module for all your projects by adding the **REPLACE\_TITLE**



parameter in the **Site Configuration** tab. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

### To rename the Defects module for a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, double-click the project for which you want to rename the Defects module.
3. Select the **DATACONST** table.
4. In the SQL pane, type an SQL INSERT INTO statement to insert a row into the table with the following values:
  - In the **DC\_CONST\_NAME** column, insert the parameter name REPLACE\_TITLE.
  - In the **DC\_VALUE** column, insert a string that defines the new name for the Defects module, in the following format:  

```
original title [singular];new title [singular];original title [plural];new title [plural]
```

For example, to change the name of the module from Defects to Bugs, type the following SQL statement into the SQL pane:

```
insert into dataconst values ('REPLACE_TITLE', 'Defect;Bug;Defects;Bugs')
```
5. Click the **Execute SQL** button. The new row is added to the **DATACONST** table. The ALM project displays the new Defects module name.

## Limiting Records Displayed in Grids

To optimize performance, the number of records retrieved and displayed in ALM grids is limited. The limits include:

- Maximum number of records displayed in a grid.
- Maximum number of records displayed for each group when a **group by** filter is applied to a grid.

To bypass the limit and display all relevant records, users can click the **Retrieve all <x> results** link in the window or dialog box.

You can change the default limits for all site projects, or individually for each project. When you change the limits for a project, they override default limits, or the values defined by the **FETCH\_LIMIT** or **GROUP\_FETCH\_LIMIT** parameters.

### To change the default number of records displayed in grids for all site projects:

Add and configure the **FETCH\_LIMIT** and **GROUP\_FETCH\_LIMIT** parameters in the **Site Configuration** tab. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

### To change the default number of records displayed in grids per project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, double-click the project for which you want to change the default limits for

records displayed in a grid.

3. Select the **DATACONST** table.
4. In the SQL pane, type an SQL INSERT statement to insert a row into the table with the following values:
  - In the **DC\_CONST\_NAME** column, insert the parameter name `FETCH_LIMIT` or `GROUP_FETCH_LIMIT`.
  - In the **DC\_VALUE** column, insert a value for the parameter.

For example, to change the value of the `FETCH_LIMIT` parameter to 50, type the following SQL statement into the SQL pane:

```
insert into dataconst values ('FETCH_LIMIT', '50')
```

5. Click the **Execute SQL** button. The new row is added to the **DATACONST** table.

# Chapter 5: Upgrading Projects to a New Version

To work in HP Application Lifecycle Management (ALM) 12.20 with projects created in previous Quality Center and ALM versions, you must upgrade your projects to align them with the required configurations of the current version of ALM.

**Performance Center:** To work with projects created in Performance Center versions 9.52 or earlier, you must migrate your projects to align them with the required configurations of ALM. For details, see the *HP ALM Performance Center Installation Guide*.

This chapter includes:

- [About Upgrading Projects](#) .....92
- [Understanding the Version/Patch Numbering Scheme](#) .....92
- [About Upgrading Projects for Major and Minor Versions](#) .....92
- [About Upgrading Projects for Minor-Minor Versions](#) ..... 114

## About Upgrading Projects

This section describes the process required for performing:

- Full upgrades of:
  - ALM projects from previous major and minor versions
  - Performance Center projects from ALM/Performance Center 11.00
- Upgrades of ALM projects from previous ALM 11.5x minor-minor versions

For details on understanding whether a version is major, minor, or minor-minor, see the information about understanding version numbering in ["Understanding the Version/Patch Numbering Scheme" below](#).

This chapter includes:

- ["Understanding the Version/Patch Numbering Scheme" below](#)
- ["About Upgrading Projects for Major and Minor Versions" below](#)
- ["About Upgrading Projects for Minor-Minor Versions" on page 114](#)

## Understanding the Version/Patch Numbering Scheme

Version numbering follows the format:

(Major)(Major).(Minor)(Minor-Minor).(Build)(Build)(Build)(Build)

### Examples

**Major version 11:** 11.00.0000

**Minor version 11.5:** 11.50.0000

**Minor-minor version 11.52:** 11.52.0000

**Patch 3 for major version 11:** 11.00.0003

For details on this format, see the information about the Obsolescence Policy on the HP Support Site. To access the site from within ALM, choose **Help > Software Support Online**. Alternatively, access the URL: [www.hp.com/go/hpssoftwaresupport](http://www.hp.com/go/hpssoftwaresupport).

## About Upgrading Projects for Major and Minor Versions

This section describes the process required for working with:

- Quality Center or ALM projects from previous versions
- Performance Center projects from previous versions

Before upgrading, verify and repair your projects to detect and correct errors in your database user schema and data.

**Note:**

- **Upgrade Methodology:** To upgrade from a previous Quality Center version with the minimum possible interruption to your system operations, you should be familiar with the considerations and recommendations involved in the upgrade process. For information on upgrade methodology, see the *HP Application Lifecycle Management Upgrade Best Practices Guide*.
- **Product Feature Movie:** To view a movie that presents the methodologies for upgrading to HP ALM from a previous version, choose **Help > Movies** in the ALM main window.
- This process describes upgrading projects for major and minor version upgrades. For details on understanding whether a version is major or minor, see the information about understanding version numbering in the ["Understanding the Version/Patch Numbering Scheme" on the previous page](#).
- For details on minor-minor version upgrades, see ["About Upgrading Projects for Minor-Minor Versions" on page 114](#).

This section includes:

- ["Upgrade Versions" below](#)
- ["Project Upgrade Considerations" on the next page](#)
- ["Repository Migration Considerations" on the next page](#)
- ["Upgrade Steps" on page 95](#)

## Upgrade Versions

The following table describes how to upgrade projects from previous Quality Center and ALM versions. Note that not all projects can be upgraded directly to ALM 12.20.

From version:	To ALM 12.20:
ALM 11.00 - 11.52	Upgrade projects directly to ALM12.20.
Quality Center 10.00	Projects must first be migrated to ALM 11.52. For details, see the <i>HP ALM 11.52 Installation and Upgrade Guide</i> .
Performance Center 11.00 - 11.52	Upgrade projects directly to ALM12.20.  <b>Note:</b> You must first upgrade <b>LAB_PROJECT</b> , and then any Performance Center template projects, before upgrading Performance Center projects.
Performance Center version 9.51	Projects must first be migrated to Performance Center 11.52. For details, see the <i>HP ALM Performance Center 11.52 Installation Guide</i> .
Performance Center versions 9.5 and earlier	Projects must first be migrated to Performance Center 9.51 and then to Performance Center 11.52. For details, see the <i>HP ALM Performance Center 11.52 Installation Guide</i> .
Quality Center 9.2	Projects must first be upgraded to ALM 11.00.
Quality Center 9.0	Projects must first be upgraded to Quality Center 10.00.

**Caution:** Before performing any upgrade, the current repository must be moved to the correct

location for the new version.

**Note:** If you are upgrading from Quality Center 10.00, 9.2, or 9.0, you must convert the rich text mechanism from Microsoft Word to HTML. For more information, see HP Software Self-solve knowledge base article [KM1116588](http://h20230.www2.hp.com/selfsolve/document/KM1116588) (<http://h20230.www2.hp.com/selfsolve/document/KM1116588>). (Requires HP Passport sign-in credentials.)

## Project Upgrade Considerations

Review the following before you upgrade projects to ALM 12.20:

- **Version Control:**
  - **Upgrading Quality Center 10.00 and ALM 11.00 or later version control enabled projects.** Version control enabled projects from Quality Center 10.00 or ALM 11.00 or later cannot be upgraded to ALM 12.20 while there are checked out entities. All entities must be checked in to the corresponding version of Quality Center or ALM. To determine if there are checked out entities, see HP Software Self-solve knowledge base article [KM00470884](http://h20230.www2.hp.com/selfsolve/document/KM00470884) (<http://h20230.www2.hp.com/selfsolve/document/KM00470884>). (Requires HP Passport sign-in credentials.)
  - **Upgrading from legacy version control projects.** To work with projects from Quality Center 9.0 or Quality Center 9.2 that use version control, you must first upgrade to ALM11.00, migrate legacy version control data, and then upgrade to ALM 12.20.
- **Server Locales:** Before upgrading a project, ensure that the system locale on the ALM server, database, and file servers, all match.
- **Performance Center:** If you were working with Performance Center 11.00 or later, before upgrading other Performance Center projects, you must first upgrade LAB\_PROJECT, and then any Performance Center **template** projects. For details, see "[Restoring LAB\\_PROJECT](#)" on page 109.

## Repository Migration Considerations

When upgrading projects from Quality Center 10.00, the project file repositories are migrated to a new optimized folder structure. Review the following to ensure that the file repositories are migrated successfully to the new structure:

- Allow for approximately twenty percent more space on the database.
- Before running the upgrade tool, make sure that all project files are saved in the default project directory.

To find out whether project files, such as tests and test resources, are outside the default project directory, log in to Site Administration. In the **Site Projects** tab, expand each project and click the **DATACONST** table. For each of the \*\_**directory** entries in the **DC\_CONST\_NAME** column, verify that the corresponding **DC\_VALUE** is a folder name in the default project directory, and not a path to another directory. For example, verify that the **DC\_VALUE** for **tests\_directory** is set as **tests**, and the **DC\_VALUE** for **resources\_directory** is set as **resources**.
- Move any folders or files from the project repository that are not connected to ALM (for example, backup folders, and scripts that are not part of workflow) to a directory outside the repository. Any unrelated files remaining in the repository will be accessible via FTP only after the migration is completed. For more details, see "[Browsing the Project Repository](#)" on page 72.

- Make sure the ALM server has full permissions to the file server.
- For information on configuring the resources allocated to building the index, see <http://h20230.www2.hp.com/selfsolve/document/KM862600>.
- Make sure there is no folder on the file system named **ProjRep**.
- During and after the repository migration, no direct access to the file system is allowed. After the migration is completed, you can browse and edit the optimized file system using an FTP client. For more details, see ["Browsing the Project Repository" on page 72](#).
- To backup a project during and after the repository migration, follow the guidelines in <http://h20230.www2.hp.com/selfsolve/document/KM1373517>.
- When restoring a project to the new version of ALM, be sure not to change the **<PR\_SMART\_REPOSITORY\_ENABLED>** property in the dbid.xml file.
- The space saving and performance benefits of the optimized repository are realized only after the repository is fully migrated. Therefore, you should resolve any errors or warnings that occur during the migration, and ensure the migration is complete.
- If the ALM, database or file servers are over WAN, the migration process takes many times longer than over LAN.

## Upgrade Steps

The upgrade workflow consists of the following steps:

1. **Verify project.** Detects problems in your environment, schema structure, and data integrity that could cause the project upgrade to fail.  
  
The verification process generates a report which indicates problems that can be repaired by ALM and problems that you should repair manually. For more information, see ["Verifying Domains and Projects" on the next page](#).
2. **Repair project.** Fixes data and schema issues found by the verification process. If the verification process finds problems that can cause data loss, the repair process does not fix them automatically. You need to repair these problems manually. For more information, see ["Repairing Domains and Projects" on page 98](#).  
  
Before you start the repair process, you should back up your project. For more information, see ["Backing Up Projects" on page 106](#).  
  
In the event that the repair fails, you must restore backed up projects before trying the repair process again. For more information, see ["Restoring Projects" on page 107](#).
3. **Upgrade project.** Upgrades your project to the current version of ALM. For more information, see ["Upgrading Domains and Projects" on page 102](#).  
  
Before you upgrade the project, back up your project. For information, see ["Backing Up Projects" on page 106](#).  
  
In the event that the upgrade fails, you must restore backed-up projects before trying the upgrade process again. For information, see ["Restoring Projects" on page 107](#).
4. **Manage project repository migration.** After upgrading a project from Quality Center 10.00 to ALM 12.20, ALM migrates the project repository directories to a new file structure in the default project repository location. If the migration process fails, you must fix the problems manually in the project repository. You can also configure the speed at which the migration is performed. For more information, see ["Migrating the Repository" on page 110](#).

For detailed information on the problems detected and fixed by the verification and repair processes, and help with repairing problems that cannot be fixed by ALM, refer to the *Upgrade Preparation Troubleshooting* appendix in the *HP Application Lifecycle Management Installation and Upgrade Guide*.

## Verifying Domains and Projects

Before you upgrade a project, you run the verification process to check the correctness of your database user schema and data. Although your database user schema and data may be correct for your previous Quality Center or ALM version, they may not be consistent with the specifications for the current version of ALM.

The verification process detects problems in your environment, settings, schema structure, and data integrity that could cause the upgrade to fail. It generates a verification report which alerts you to problems that can be repaired by ALM and problems that you should manually repair.

By default, the verification report is saved on the ALM server machine. To change this default location, use the **VERIFY\_REPORT\_FOLDER** site parameter.

After the project has been verified, you can still use it with a previous version of Quality Center or ALM.

For detailed information on the problems detected by the verification process, see the *HP Application Lifecycle Management Installation and Upgrade Guide*.

You can define an exception file to instruct ALM to ignore errors detected while running the verification, repair, or upgrade process. For more information, see ["Defining an Exception File" on page 105](#).


This section includes:

- [Verifying a Project](#) ..... 96
- [Verifying a Domain](#) ..... 97


### Verifying a Project

This section describes how to verify a single project.

**To verify a project:**

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. Click the **Maintain Project**  button and choose **Verify Project**. The Verify Project dialog box opens.







4. Click the **Verify Project** button to start the verification process. In the Verify Results pane, log messages are displayed.  
If an error occurs while running the process, a message box opens. Click the **Abort** or **Retry** buttons accordingly.
5. To pause the verification process, click the **Pause** button. To continue, click the **Resume** button.
6. To abort the verification process, click the **Abort** button. Click **Yes** to confirm.
7. To save the messages displayed in the Verify Results pane to a text file, click the **Export Log** button. In the Export Log to File dialog box, choose a location and type a name for the file. Click **Save**.
8. To clear the messages displayed in the Verify Results pane, click the **Clear Log** button.
9. When the verification process completes, the Verify Results pane displays the location of the verification report. By default, the file is located in the following directory: **<ALM Repository Path>\sa\DomsInfo\MaintenanceData\out\<Domain Name>\<Project Name>**.
10. Analyze the verification report. The report indicates both problems that can be repaired by ALM automatically, and the problems that you need to repair manually.
11. Click **Close** to close the Verify Project dialog box.

## Verifying a Domain

This section describes how to verify all projects in a domain.

### To verify a domain:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a domain.
3. Click the **Maintain Domain** button  and choose **Verify Domain**. The Verify Domain dialog box opens.



4. To view the current version numbers of your projects, select the project names, or click **Select All** to view version numbers for all projects. Click the **Display Versions** button.  
The project version number is displayed in the **Version** column.
5. To verify your projects, select the project names, or click **Select All** to verify all projects. Click the **Verify Projects** button.  
If an error occurs while running the process, a message box opens. Click the **Abort** or **Retry** buttons accordingly.
6. To pause the verification process, click the **Pause** button. To continue, click the **Resume** button.
7. To abort the verification process, click the **Abort** button. Click **Yes** to confirm.
8. To save the messages displayed in the Verify Results pane to a text file, click the **Export Log** button. In the Export Log to File dialog box, choose the location and type the name for the file. Click **Save**.
9. To clear the messages displayed in the Verify Results pane, click the **Clear Log** button.
10. When the verification process completes, the Verify Results pane displays the location of each verification report. By default, the files are located in the following directory: **<ALM Repository Path>\repository\sa\DomsInfo\MaintenanceData\out\<Domain Name>\<Project Name>**.
11. Analyze the verification report. The report indicates problems that can be repaired by ALM and the problems that you need to repair manually.
12. Click **Close** to close the Verify Domain dialog box.

## Repairing Domains and Projects

The repair process fixes most data and schema issues found by the verification process. If the verification process finds problems that can cause data loss, the repair process does not fix these

automatically. You need to repair these problems manually. To find out whether a particular issue is handled automatically or manually, refer to the verification report.

By default, the repair process runs in non-silent mode. When running the process in non-silent mode, ALM may pause and prompt you for input when an error occurs. Instead, you can choose to run the process in silent mode. When an error occurs, ALM aborts the process without prompting you for input.

After the project has been repaired, you can still use it with a previous Quality Center or ALM version.

For detailed information on the problems fixed by the repair process, and help with repairing problems that cannot be fixed by ALM, refer to the *Upgrade Preparation Troubleshooting* appendix in the *HP Application Lifecycle Management Installation and Upgrade Guide*.


This section includes:


- [Repairing a Project](#) .....99
- [Repairing a Domain](#) ..... 100

## Repairing a Project

This section describes how to repair a single project.

**To repair a project:**

1. Back up your project. For more information, see "[Backing Up Projects](#)" on page 106.
2. Repair problems that cannot be fixed by ALM, as indicated in your verification report (see Step 9 of "[Verifying a Project](#)" on page 96).
3. In Site Administration, click the **Site Projects** tab.
4. In the Projects list, select a project.
5. Click the **Maintain Project**  button and choose **Repair Project**. The Repair Project dialog box opens.



6. To run the repair process without any user interaction, select **Run in Silent Mode**.
7. To start the repair process, click the **Repair Project** button. If the project is active, you are prompted to deactivate it. For more information, see ["Deactivating and Activating Projects" on page 80](#).

If an error occurs while running the process in non-silent mode, a message box opens. Click the **Abort** or **Retry** buttons accordingly.


8. To pause the repair process, click the **Pause** button. To continue, click the **Resume** button.
9. To abort the repair process, click the **Abort** button. Click **Yes** to confirm.
10. To save the messages displayed in the Repair Results pane to a text file, click the **Export Log** button. In the Export Log to File dialog box, choose a location and type a name for the file. Click **Save**.
11. To clear the messages displayed in the Repair Results pane, click the **Clear Log** button.
12. Click **Close** to close the Repair Project dialog box.


## Repairing a Domain

This section describes how to repair all projects in a domain.

### To repair a domain:

1. Back up your projects. For more information, see ["Backing Up Projects" on page 106](#).
2. Repair problems that cannot be fixed by ALM, as indicated in your verification report (see Step 10 of ["Verifying a Domain" on page 97](#)).
3. In Site Administration, click the **Site Projects** tab.
4. In the Projects list, select a domain.

5. Click the **Maintain Domain**  button and choose **Repair Domain**. The Repair Domain dialog box opens.



**Repair Domain**

**Repair Settings**

Before you proceed, you should be familiar with all the aspects and implications of repairing a project. In particular, you should make sure that you have backed up all the relevant projects before you begin.

**Repair Mode**

☐ Run in silent mode  
☒ Continue to next project if Repair failed

**After the Repair**

☐ Leave all projects deactivated  
☒ Activate only currently active projects  
☐ Activate all projects

**Select projects to repair**

#	Project Name	Version
1	<input checked="" type="checkbox"/> Application_A	
2	<input type="checkbox"/> Application_B	
3	<input type="checkbox"/> Application_C	
4	<input type="checkbox"/> DEFECTS	
5	<input type="checkbox"/> Release	

Select All Clear All Display Versions

**Repair Results**

Repair Projects Pause Abort Clear Log Export Log Close Help

6. In the **Repair Settings** area, under **Repair Mode**, you can select the following options:
- **Run in Silent Mode.** Runs the process without any user interaction.
  - **Continue to next project if repair failed.** Proceeds to the next project if the repair process fails. This is the default option.
7. In the **Repair Settings** area, under **After the Repair**, you can select one of the following options:
- **Leave all projects deactivated.** Leaves all projects deactivated after the repair process completes.
  - **Activate only currently active projects.** Reactivates previously-activated projects after the repair process completes. This is the default option.
  - **Activate all projects.** Activates all projects after the repair process completes.
8. To view the current version numbers of your projects, select the project names, or click **Select All** to view version numbers for all projects. Click the **Display Versions** button.
- The project version number is displayed in the **Version** column.
9. To repair your projects, select the project names, or click **Select All** to verify all projects. Click the **Repair Projects** button.
- If an error occurs while running the process in non-silent mode, a message box opens. Click the **Abort** or **Retry** buttons accordingly.
10. To pause the repair process, click the **Pause** button. To continue, click the **Resume** button.
11. To abort the repair process, click the **Abort** button. Click **Yes** to confirm.
12. To save the messages displayed in the Repair Results pane in a text file, click the **Export Log** button. In the Export Log to File dialog box, choose a location and type a name for the file. Click

**Save.**

- 13. To clear the messages displayed in the Repair Results pane, click the **Clear Log** button.
- 14. Click **Close** to close the Repair Domain dialog box.

## Upgrading Domains and Projects

After the project has been verified and repaired, you can proceed to upgrade your project to the current version of ALM.

For more information on the overall upgrade process, including prerequisites, see ["About Upgrading Projects" on page 92](#).

By default, the upgrade process runs in non-silent mode. When running the process in non-silent mode, ALM may pause and prompt you for input when an error occurs. Instead, you can choose to run the process in silent mode. When running the process in silent mode, ALM aborts the process without prompting you for input.

After the project has been upgraded, you can no longer use the project with a previous version of Quality Center.

**Note:**

- During the upgrade process, the project directory must be accessible. For example, if your project directory is located on a file server, ensure that the server is running.
- **Version Control:** Version control enabled projects from Quality Center 10.00 or ALM 11.00 cannot be upgraded to ALM 12.20 while there are checked out entities. All entities must be checked in in the corresponding version of Quality Center or ALM.
- **Performance Center:** If you were working with Performance Center 11.00, before upgrading other Performance Center projects, you must first upgrade LAB\_PROJECT, and then any Performance Center **template** projects. For details on LAB\_PROJECT, refer to the *HP ALM Lab Management Guide*.

This section includes:


- [Upgrading a Project](#) ..... 102
- [Upgrading a Domain](#) .....104


## Upgrading a Project

This section describes how to upgrade a single project.

**To upgrade a project:**

- 1. If you have backed up your project during the repair process (see ["Repairing Domains and Projects" on page 98](#)), proceed to step 3.
- 2. Back up your projects. For more information, see ["Backing Up Projects" on page 106](#).
- 3. In Site Administration, click the **Site Projects** tab.
- 4. In the Projects list, select a project.

- Click the **Maintain Project**  button and select **Upgrade Project**. The Upgrade Project dialog box opens.





- To run the upgrade process without any user interaction, select **Run in silent mode**.
- To start the upgrade process, click the **Upgrade Project** button. If the project is active, you are prompted to deactivate it. For more information, see ["Deactivating and Activating Projects" on page 80](#).
- If an error occurs while running the process in non-silent mode, a message box opens. Click the **Abort** or **Retry** buttons accordingly.
- If the upgrade fails, ALM displays an error message with reasons for the failure and refers you to the log file. You must restore the backed up project before you try to upgrade again. For more information, see ["Restoring Projects" on page 107](#).
- To pause the upgrade process, click the **Pause** button. To continue, click the **Resume** button.
- To abort the upgrade process, click the **Abort** button. Click **Yes** to confirm.
- To save the messages displayed in the Upgrade Results pane to a text file, click the **Export Log** button. In the Export Log to File dialog box, choose a location and type a name for the file. Click **Save**.
- To clear the messages displayed in the Upgrade Results pane, click the **Clear Log** button.
- Click **Close** to close the Upgrade Project dialog box.

## Upgrading a Domain

This section describes how to upgrade all projects in a domain.

### To upgrade a domain:

1. If you have backed up your project during the repair process (see ["Repairing Domains and Projects" on page 98](#)), proceed to step 3.
2. Back up your projects. For more information, see ["Backing Up Projects" on page 106](#).
3. In Site Administration, click the **Site Projects** tab.
4. In the Projects list, select a domain.
5. Click the **Maintain Domain**  button and select **Upgrade Domain**. The Upgrade Domain dialog box opens.



6. In the **Upgrade Settings** area, under **Upgrade Mode**, you can select the following options:
  - **Run in Silent Mode.** Runs the process without any user interaction.
  - **Continue to next project if upgrade failed.** Proceeds to the next project if the upgrade process fails. This is the default option.
7. In the **Upgrade Settings** area, under **After the Upgrade**, you can select one of the following options:
  - **Leave all projects deactivated.** Leaves all projects deactivated after the upgrade process completes.
  - **Activate only currently active projects.** Reactivates previously-activated projects after the upgrade process completes. This is the default option.
  - **Activate all projects.** Activates all projects after the upgrade process completes.



8. To view the current version numbers of your projects, select the project names, or click **Select All** to view version numbers for all projects. Click the **Display Versions** button.

The project version number is displayed in the **Version** column.

9. To upgrade your projects, select the project names, or click **Select All** to verify all projects. Click the **Upgrade Projects** button.

If an error occurs while running the process in non-silent mode, a message box opens. Click the **Abort** or **Retry** buttons accordingly.

If the upgrade fails, ALM displays an error message with reasons for the failure and refers you to the log file. You must restore the backed up projects before you try to upgrade again. For more information, see ["Restoring Projects" on page 107](#).

10. To pause the upgrade process, click the **Pause** button. To continue, click the **Resume** button.
11. To abort the upgrade process, click the **Abort** button. Click **Yes** to confirm.
12. To save the messages displayed in the Upgrade Results pane in a text file, click the **Export Log** button. In the Export Log to File dialog box, choose a location and type a name for the file. Click **Save**.
13. To clear the messages displayed in the Upgrade Results pane, click the **Clear Log** button.
14. Click **Close** to close the Upgrade Domain dialog box.

## Defining an Exception File

If you have made changes to the schema such as the addition of tables or columns, the upgrade process may fail. You can define an exception file for objects that are added manually to the database user schema, and are not defined in the schema configuration file. This instructs ALM to ignore these changes during the upgrade process.

You can use the exception file to ignore warnings for extra tables, views, columns, and sequences. For any other problem that requires manual repair, consult with your database administrator.

You must use the same exception file when running the verification, repair, or upgrade process.

You can set an exception file for a single project or for all projects in Site Administration.

**Caution:** Using the exception file to ignore warnings for objects that are added manually to the schema may compromise the stability of your project upgrade and the validity of the database user schema.

### To define an exception file:

1. Copy the **SchemaExceptions.xml** file from the ALM installation directory. By default, the file is located in **<ALM installation path>\data\sa\DomsInfo\MaintenanceData**.
2. Create the exception file, for example, **my\_exceptions.xml**, and define the exceptions as follows:

#### Examples

- For an extra table:

```
<TableMissing>
    <object pattern="MY_Table" type="extra"/>
</TableMissing>
```

- For an extra view:

```
<ViewMissing>
    <object pattern="MY_VIEW" type="extra"/>
</ViewMissing>
```

- For an extra column:

```
<ColumnMissing>
    <object pattern="MY_COLUMN" type="extra"/>
</ColumnMissing>
```

- For an extra sequence:

```
<SequenceMissing>
    <object pattern="MY_SEQUENCE" type="extra"/>
</SequenceMissing>
```

3. To set an exception file for a single project:
  - a. In Site Administration, click the **Site Projects** tab.
  - b. In the Projects list, select a project. In the right pane, select the **Project Details** tab. The project's details are displayed.
  - c. Under **Project Database**, click **Exception File**. The Edit Exception File dialog box opens.
  - d. Type the file location. The file is located under  
**<ALM deployment path>\sa\DomsInfo\MaintenanceData**.
4. To set an exception file for all projects:
  - a. In Site Administration, click the **Site Configuration** tab.
  - b. Add the **UPGRADE\_EXCEPTION\_FILE** parameter to the list of parameters and define the exception file location. The file is located under  
**<ALM deployment path>\sa\DomsInfo\MaintenanceData**.

For more information on setting parameters, see ["Setting ALM Configuration Parameters" on page 155](#).

## Backing Up Projects

When you run the repair or upgrade process, ALM performs changes on your projects to align them with the specifications for the current version of ALM. You must back up your projects before you start to repair or upgrade them.

We strongly recommend that you deactivate projects before backing them up. If you must back up while your project is still active, you must back up the database before the file system. We also recommend backing up the file system as soon as possible after backing up the database.

To make sure the Garbage Collector does not delete obsolete files while the file system is pending backup, there is a one week grace period before deletion. For details, see the **REPOSITORY\_GC\_DELAY\_CANDIDATE\_TIME** site parameter.

**Note:**

- The repair process makes changes to the project database schema only. Before running the repair process, you should back up the project database schema on the database server, but you do not need to back up the project data in the file system.
- Before you run the upgrade process, perform a full backup of your projects that includes the project database schema and the project data.

**To back up the project database schema on the database server:**

- **Microsoft SQL database.** For information on backing up a schema on a Microsoft SQL database, see [HP Software Self-solve knowledge base article KM169526](http://h20230.www2.hp.com/selfsolve/document/KM169526) (<http://h20230.www2.hp.com/selfsolve/document/KM169526>).
- **Oracle database.** For information on backing up a schema on an Oracle database, see [HP Software Self-solve knowledge base article KM205839](http://h20230.www2.hp.com/selfsolve/document/KM205839) (<http://h20230.www2.hp.com/selfsolve/document/KM205839>).

**To back up the project data in the file system:**

- In the file system, ensure that all data, including automated tests scripts and results, and attachments, is saved in the project directory under the repository defined during the installation of ALM. Make a copy of this project directory including all subdirectories and files.
- **For upgrade from Quality Center 10.00:** If your automated tests are stored outside the project directory, make a copy of them.

**Tip:** To find out whether your tests are outside the project directory, log in to Site Administration. In the **Site Projects** tab, expand the project you want to back up and click the **DATACONST** table. Select the **DC\_CONST\_NAME** parameter with the value **tests\_directory** and verify the corresponding **DC\_VALUE**. If it is not set as **tests** but is set instead to some other location, then your tests are outside of the project folder.

## Restoring Projects

If the repair or upgrade process fails, you must restore the backed up projects before trying the process again. You can restore projects that were backed up on an Oracle or Microsoft SQL database server, and in the file system. A project you restore can be used only in the ALM/Quality Center version from which it was backed up.

If you are restoring projects as part of your overall upgrade process, for example – if you are moving to a new server or database, you must update the **dbid.xml** file accordingly. For details, see ["Restoring Access to Projects" on page 86](#).

If you were previously working with Performance Center 11.00, see ["Restoring LAB\\_PROJECT" on page 109](#).

This section includes:

- [Restoring Projects from a Microsoft SQL Database Server](#) .....108
- [Restoring Projects from an Oracle Database Server](#) ..... 108
- [Restoring a Repository from the File System](#) ..... 109
- [Restoring LAB\\_PROJECT](#) ..... 109

## Restoring Projects from a Microsoft SQL Database Server

This section describes how to restore a project backed up on a Microsoft SQL database server.

For more information, see [HP Software Self-solve knowledge base article KM169526](http://h20230.www2.hp.com/selfsolve/document/KM169526)  
(<http://h20230.www2.hp.com/selfsolve/document/KM169526>).

**To restore a project from a Microsoft SQL database server:**

1. From the SQL Server Enterprise Manager, navigate to the database and select **Tools > Restore Database**.
2. Navigate to the backup file, and follow the restore procedure to complete the data restore process.
3. In Site Administration, restore the project. If you are restoring your project from a different directory, or if you renamed your schema, you must update the **dbid.xml** file accordingly. For details, see ["Restoring Access to Projects" on page 86](#).
4. If the backup was performed while the project was active, realign the project repository. For more information, see ["Realigning Repositories" on page 74](#).

## Restoring Projects from an Oracle Database Server

This section describes how to restore a project backed up on an Oracle database server.

For more information, see [HP Software Self-solve knowledge base article KM205839](http://h20230.www2.hp.com/selfsolve/document/KM205839)  
(<http://h20230.www2.hp.com/selfsolve/document/KM205839>).

**To restore a project from an Oracle database server:**

1. Copy the backup file to the Oracle server machine.
2. Using the SQL\*Plus utility, log in to the Oracle server using the **system** account.
3. Create a user for the ALM project. Make sure you create it with the same name as the project name (or the Oracle user name) when the project was exported.

Use these SQL statements:

```
CREATE USER [<project name>] IDENTIFIED BY tdttdt DEFAULT TABLESPACE TD_data  
TEMPORARY TABLESPACE TD_TEMP;
```

```
GRANT CONNECT,RESOURCE TO [<project name>];
```

4. On the ALM installation DVD, locate the **Utilities\Databases\Scripts** directory. Open the **qc\_project\_db\_\_oracle.sql** file and follow the instructions.
5. Using the command line, type **imp** to run the import utility.
6. Follow the prompt, and log in to the Oracle server using the **system** account. Make sure you

import all the dump files.

After all tables have been successfully imported, a confirmation message displays.

7. In Site Administration, restore the project. If you are restoring your project from a different directory, or if you renamed your schema, you must update the **dbid.xml** file accordingly. For more information on restoring access to projects, see ["Restoring Access to Projects" on page 86](#).
8. If the backup was performed while the project was active, realign the project repository. For more information, see ["Realigning Repositories" on page 74](#).

## Restoring a Repository from the File System

This section describes how to restore a repository backed up in the file system.

### To restore a repository from the file system:

1. Copy the backed up repository to the ALM repository.
2. In Site Administration, restore the project. If you are restoring your project from a different directory, or if you renamed your schema, you must update the **dbid.xml** file accordingly. For more information on restoring access to projects, see ["Restoring Access to Projects" on page 86](#).
3. If the backup was performed while the project was active, you must restore the database and the file system from a backup that was created after the database backup was created, realign the project, and then activate the project. This procedure must always be performed during disaster recovery. For more information, see ["Realigning Repositories" on page 74](#). If this process is done in order to recover certain files or directories, you can skip the realignment.

## Restoring LAB\_PROJECT

If you were previously working with Performance Center 11.00, and ALM 12.20 is installed on a new server, you must restore your backed up projects on the new server. Before restoring and upgrading other Performance Center projects, you must first restore and upgrade LAB\_PROJECT, and then any Performance Center **template** projects.

You restore LAB\_PROJECT from the Lab Management tab in Site Administration. For details, refer to the *HP ALM Lab Management Guide*.

Restoring Performance Center 11.00 projects includes the following steps:

1. If a new Site Administration schema was created during installation, a new LAB\_PROJECT was created. To restore your Performance Center 11.00 LAB\_PROJECT, you must first remove the new LAB\_PROJECT from the ALM 11.50 server.
2. In ALM 12.20 Site Administration, restore your Performance Center 11.00 LAB\_PROJECT.
3. Proceed with the verify, repair, and upgrade of your LAB\_PROJECT. For details, see ["About Upgrading Projects" on page 92](#).

If the verification process fails and you receive an error message that project fields cannot be decrypted using the Confidential Data Passphrase, refer to the *Encrypted Values* section in the *Upgrade Preparation Troubleshooting* appendix in the *HP Application Lifecycle Management Installation and Upgrade Guide*.

4. Restore, verify, repair, and upgrade any Performance Center 11.00 **template** projects.

**Note:** Performance Center 11.00 **template** projects must be restored to the **DEFAULT** domain.

- 5. Restore, verify, repair, and upgrade your Performance Center 11.00 projects.

## Migrating the Repository

ALM versions 11.00 and later use a new project repository architecture, that is optimized to allow maximum storage space. For details on the new repository, see ["Managing the Optimized Project Repository" on page 71](#).

When upgrading projects from Quality Center 10.00 to ALM 11.50, the project repository is automatically upgraded to the optimized repository format. This is carried out in two stages:

1. The first stage is performed during the upgrade of the project. In this stage, all files in the repository are scanned, and their names are stored in a project table.
2. After upgrade is completed, the project is reactivated. The repository files are gradually migrated to the new system. In this stage, the files are moved from their old location to their new location in the optimized repository. Depending on various factors, such as the size of the repository and the network speed, the file migration may take up to several days.

This second phase of the repository migration is carried in the background. Users can work in the project even while it is in progress. New files that you add to a project after upgrade are saved in the new project repository.

**Note:**

- Until the migration process for a project is complete, you cannot export or copy the project.
- To back up a project before its migration is complete, you must suspend the migration process. For more details, see ["Configure Migration Priority" on page 113](#).

Monitor the migration progress in the Repository Migration Status window, and troubleshoot any problems that may occur.


In Site Administration, you can track the status of file migration for each project, and configure the number of resources allocated to performing the migration.

This section includes:

- [Repository Migration Status Window](#) ..... 111
- [Configure Migration Priority](#) ..... 113

## Repository Migration Status Window

This window lists all the site projects and displays the status of their migration to the optimized project repository.



To access	In Site Administration, select <b>Tools &gt; Repository Migration Status</b> .
See also	<ul style="list-style-type: none"><li>• <a href="#">"Migrating the Repository" on the previous page</a></li><li>• <a href="#">"Configure Migration Priority" on page 113</a></li><li>• <a href="#">"Managing the Optimized Project Repository" on page 71</a></li></ul>

User interface elements are described below:

UI Element	Description
	<p>Instructs ALM to resume the migration of the selected project.</p> <p>If an error or warning was detected during the migration of the selected project, fix the problem as described in the <b>Additional Information</b> field, and click <b>Resume</b>.</p> <p><b>Note:</b> If the migration process stopped due to missing files, after clicking <b>Resume</b>, you can no longer restore missing files.</p>
	<p>Downloads a log of the migration events associated with the selected project.</p>
	<p><b>Refresh.</b> Refreshes the display with the most up-to-date information.</p> <p><b>Note:</b> The grid updates automatically after the migration of every 1000 files.</p>
Domain Name	The domain to which the selected project belongs.
Project Name	The name of the selected project.
Project Status	Indicates the selected project's status in Site Administration. For example, <i>Active</i> or <i>Deactivated</i> .

UI Element	Description
	<p><b>Note:</b> Deactivating a project does not affect its repository migration.</p>
<b>Migration Status</b>	<p>The migration status of a project can be one of the following:</p> <ul style="list-style-type: none"> <li>• <b>None.</b> Project is not upgraded to ALM 12.20, and will not be migrated.</li> <li>• <b>Pending.</b> File migration is pending.</li> <li>• <b>Migrating.</b> File migration is in progress.</li> <li>• <b>Done.</b> File migration is complete.</li> <li>• <b>Error.</b> An error occurred during file migration, and migration could not be completed. See the cause of the error in the <b>Additional Information</b> panel. Fix the error, and click <b>Resume</b>.</li> <li>• <b>Warning.</b> A warning occurred during file migration. For details of the warning, and the actions you must take to resolve the problem, download the log files listed in the <b>Additional Information</b> panel. Resolve the problems as necessary, and click <b>Resume</b> to complete the migration.</li> </ul> <p><b>There are several possible causes for warnings:</b></p> <ul style="list-style-type: none"> <li>• One or more project files were not found in the project repository. This can result from missing or renamed files.</li> <li>• Redundant files are found in the repository. The migration cannot complete until the legacy repository is empty of files. Redundant files can be one of the following: <ul style="list-style-type: none"> <li>• Duplicate project files that could not be deleted. This can result from insufficient permissions.</li> <li>• Files unrelated to ALM that were manually saved in the project repository.</li> <li>• Unidentified project files.</li> </ul> </li> </ul>
<b>Migration Progress</b>	The number of project files migrated to the new repository, as a percentage of the total number of project files.
<b>Additional Information</b>	If a problem was detected, displays the cause of the problem, and links to log files. The log files describe the actions you must take to resolve the problem.
<b>Site Administrator Automail Options</b>	<p>ALM sends automail to Site Administrators upon events connected to repository migration. Select the following options:</p> <ul style="list-style-type: none"> <li>• <b>Send mail on success.</b> Sends mail when the migration of a project repository completes successfully.</li> <li>• <b>Send mail on warning.</b> Sends mail when a warning is detected during the migration of a project repository.</li> <li>• <b>Send mail on error.</b> Sends mail when an error is detected during the migration of a project repository.</li> <li>• <b>Include logs as attachments.</b> Attaches detailed log files to automail messages.</li> </ul>
<b>Summary</b>	Summary information of the migration status of all site projects.



## Configure Migration Priority

While the migration process does not interfere with your work on projects, the process may affect system performance as a whole. Use the following site configuration parameters to control the amount of system resources used by the migration process. For more information on setting parameters, see ["Setting ALM Configuration Parameters" on page 155](#).

- **REPOSITORY\_MIGRATION\_JOB\_PRIORITY.** Determines the speed at which files are copied from the old to the new project repository.
- **SUSPEND\_REPOSITORY\_MIGRATION.** Stops the repository migration on the entire site. Use this parameter temporarily, and only in special circumstances. For example, if you suspect that the migration process disrupts your system.

Additional parameters are available for configuring the resources allocated to the migration process. For more information, see [HP Software Knowledge base article KM862600](http://h20230.www2.hp.com/selfsolve/document/KM862600) (<http://h20230.www2.hp.com/selfsolve/document/KM862600>).

### Consider the following when configuring the migration priority:

- Allocating more resources to the migration process may slow down other processes.
- Allocating less resources extends the time in which the process is completed.
- Projects that are pending migration or in the process of migration cannot be exported or copied.

## LAB\_PROJECT Post Upgrade Steps

If you have upgraded a Performance Center 11.00 project, perform the following steps in the staging and production environments:

For more information regarding these steps, refer to the *HP ALM Lab Management Guide*.

1. Log into **Lab Management**.
2. Configure the external URL:
  - a. On the Lab Management sidebar, under **Servers**, select **PC Servers**.
  - b. On the toolbar, click the **ALM Connection** button. The ALM Connection dialog box opens.
  - c. Enter external URL information.
3. Add a Performance Center Server:
  - a. On the **PC Servers** toolbar, click the **New PC Server** button. The New PC Server dialog box opens.
  - b. Define new server information.
  - c. Click **OK**.
4. Update license details:
  - a. On the Lab Management sidebar, under **Performance Center**, select **PC Licenses**.
  - b. Define new license information.
5. Add, remove, or reconfigure hosts:
  - a. On the Lab Management sidebar, under **Lab Resources**, select **Hosts**.
  - b. Add, remove, or reconfigure hosts as needed.

## About Upgrading Projects for Minor-Minor Versions

This section describes the process for upgrading projects for minor-minor versions, including setting project priorities. Minor-minor versions can include changes to database schema.

**Note:** For details on understanding whether a version is major, minor, or minor-minor, see ["Understanding the Version/Patch Numbering Scheme" on page 92](#).

Automatic upgrades for minor-minor versions start when the ALM Server is restarted after installation of the new minor-minor version.

While a project is being upgraded, users cannot access the project.

This section includes:

- ["Candidates for Automatic Upgrades" below](#)
- ["Project Priority" below](#)
- ["How to Upgrade Minor-Minor Versions" below](#)

### Candidates for Automatic Upgrades

The automatic upgrade processes projects that meet all of the following criteria:

- Lab Management projects
- Projects whose major and minor version are identical to the major and minor version installed on the server, yet whose minor-minor version is less than the minor-minor version installed on the server.

#### Examples

Assume ALM version 15.25 is installed on the server:

- Version 15, 21, 15.22, 15.23, and 15.24 projects are automatically upgraded.
- Version 15.25 and 15.26 projects are not automatically upgraded.
- Version 14.00 projects are not upgraded.

### Project Priority

The upgrade processes projects in the following order:

- Template and Lab Management projects
- Projects with the highest priority, as set by the user
- Most active projects
- Most recent modification date
- Highest number of users

### How to Upgrade Minor-Minor Versions

1. Before upgrading the minor-minor version on the ALM Server, you can optionally set priorities to determine the order in which projects are upgraded using the Project Update Prioritization dialog

box in Site Administration. For user interface details, see "[Setting Project Priorities for Upgrading Minor-Minor Versions](#)" on the next page.

- 2. Back up the database.
- 3. Install the new minor-minor version on the ALM Server by following the instructions:
  - On the HP Software Support Web site. Choose **Help > Software Support Online**. The URL for this Web site is [www.hp.com/go/hpsoftwaresupport](http://www.hp.com/go/hpsoftwaresupport).
  - In the *HP Application Lifecycle Management Installation and Upgrade Guide*.


After the ALM Server is restarted, projects are upgraded automatically according to the defined priorities.

This section also includes:

- [Setting Project Priorities for Upgrading Minor-Minor Versions](#) ..... 116



## Setting Project Priorities for Upgrading Minor-Minor Versions

The Project Update Prioritization dialog box enables you to set project priorities for upgrading minor-minor versions.



<b>To access</b>	In Site Administration, select <b>Tools &gt; Set Project Upgrade Priorities</b> .
<b>Important information</b>	<ul style="list-style-type: none"> <li>Projects are listed in order of priority. Highest priority projects are at the top of the list.</li> <li>Lab and Template projects are always highest priority. You cannot change the priority for these projects.</li> <li>You can set priorities at any time. The changes affect the next minor-minor version upgrade. If such an upgrade is in progress, the changes affect only projects with <b>Pending Upgrade</b> status.</li> </ul>
<b>See also</b>	<ul style="list-style-type: none"> <li><a href="#">"Upgrading Projects to a New Version" on page 91</a></li> <li><i>HP Application Lifecycle Management Installation and Upgrade Guide</i></li> </ul>

User interface elements are described below:

UI Element	Description
 <b>Restore Defaults</b>	<b>Restore Defaults.</b> Resets project priorities to the default value <b>100</b> .  <b>Note: Restore Defaults</b> does not affect the priority of Lab or Template projects.
	<b>Find.</b> Enables you to navigate to a project in the grid using the adjacent <b>Project Name</b> text box.
<b>Domain Name</b>	Lists the domains.
<b>Project Name</b>	Lists the projects.
<b>Priority</b>	Displays the priority for the project for the next upgrade. <b>1</b> is highest priority. <b>100</b> is lowest priority.

# Chapter 6: Managing ALM Users

You manage HP Application Lifecycle Management (ALM) users in Site Administration. You can add new users, define user details, change user passwords, and define site administrators. You can also import users from LDAP and enable LDAP or external authentication for users. After you add users, you can assign projects to users.

This chapter includes:

• About Managing Users .....	118
• Adding a New User .....	118
• Importing Users from LDAP .....	120
• Updating User Details .....	126
• Deactivating and Activating Users .....	127
• Creating and Changing Passwords .....	128
• Locking Out Users .....	128
• Enabling Authentication for Users .....	129
• Assigning Projects to Users .....	131
• Exporting User Data .....	132
• Deleting Users .....	133

## About Managing Users

You use Site Administration to manage the users connected to your ALM projects. You begin by adding or importing new users to the Users list in Site Administration. You can then define user details and change or override a user's password. You can also enable users to log in to ALM using their LDAP passwords.

For each ALM user, you can select projects that the user can access. You can also define ALM users as site administrators. For more information, see ["Defining Site Administrators" on page 19](#).

**Note:** You can monitor the users currently connected to an ALM server. For more information, see ["Managing User Connections and Licenses" on page 135](#).

## Adding a New User

You can add new users to the Users list in Site Administration. After the user is added, you can view users and define user details. For more information on updating user details, see ["Updating User Details" on page 126](#).

You can also import new users from LDAP directories. For more information, see ["Importing Users from LDAP" on page 120](#).

**Note:** Creating a new user for an ALM project consists of two steps:

- Adding the user to the Users list in Site Administration (as described in this section).
- Assigning the user to a user group using Project Customization. Each user group has access to certain ALM tasks. For more information, see ["Managing Users in a Project" on page 207](#) and ["Managing User Groups and Permissions" on page 211](#).

## To add a new user:

1. In Site Administration, click the **Site Users** tab.

User Name	Full Name
alex_alm	Alex Smith
alice_alm	Alice Jones
alm_admin	David Banks
alm_admin2	Roy Fields
alm_admin3	Pamela Knight
cecil_alm	Cecil Davis
james_alm	James Johnson
kelly_alm	Kelly White
mary_alm	Mary River
michael_alm	Michael Brown
paul_alm	Paul Winter
peter_alm	Peter Adams
shelly_alm	Shelly Rivers

Total Users: 15

**User Details** | **User Projects**

User Name: alex\_alm

Full Name: Alex Smith

Status: Active

Deactivation Date:

E-mail:

Phone Number:

Description:

2. Click the **New User** button . The New User dialog box opens.
3. Type a **User Name** (maximum length 60 characters). A user name cannot include the following characters: ( ) @ \ / : \* ? " ` < > | + = ; , %
4. Type additional user information: **Full Name**, **E-mail**, **Phone Number**, and a **Description**. The email information is important, as it enables users to receive project information directly to their mailboxes.

**Note:** For smart card authentication, enter the email from the smart card in **E-mail** and the common name (CN) from the smart card in **Description**. For single sign-on (SSO) authentication, enter the email and the user name in **Description**.

You can update user information in the User Details tab. For more information, see ["Updating User Details" on page 126](#).

5. If LDAP Authentication is activated, select the LDAP server from the **LDAP Authentication Server** dropdown list. **Domain Authentication** is automatically valued with the LDAP distinguished name, but can be updated as needed.

**Note:** If **Domain Authentication** is valued incorrectly or is empty, it is automatically updated after the user successfully logs in.

6. Click **OK**. The new user is added to the Users list.
7. Assign the new user a password. For task details, see ["Creating and Changing Passwords" on page 128](#).

**Note:** A new user is created with a blank password.

## Importing Users from LDAP


You can import users from an LDAP directory to the Users list in Site Administration.


### Notes:


- Verify that the LDAP import settings are defined. For more information, see ["Defining LDAP Settings for Importing Users" on page 123](#).
- Working with LDAP through SSL requires that you perform additional steps. For more information, see ["Enabling LDAP over SSL" on page 122](#).
- The **LDAP\_TIMEOUT** parameter enables you to define a connection time-out between ALM and an LDAP server. By default, the value is set to 10 minutes. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

You select users either by filtering and browsing the LDAP directory base, or by searching for users by keyword.

### To browse the LDAP directory base:

1. In Site Administration, click the **Site Users** tab.
2. Click the **Import LDAP Users** button , and select **Import Users from LDAP Directory Tree**. The Import Users from LDAP Directory Tree dialog box opens.





3. In the **Server** box, select the LDAP server you want to browse.  
The LDAP directory base is filtered according to the filter set in the LDAP Settings dialog box. For details, see ["Defining LDAP Settings for Importing Users" on page 123](#).
4. To view LDAP details for a user, select an item and click the **Show LDAP Details** button .  
The LDAP User Details dialog box opens and displays the user attributes.




5. You can use the following options to import users:
  - To import a user, expand a directory and mark the user name by selecting the check box.
  - To import a group of users, use CTRL or SHIFT to highlight users to be included. Click the **Mark All Items** arrow and choose **Mark Selected Items** to select the check boxes of the highlighted users.
  - To import all users, click **Mark All Items**.
6. To clear the check boxes of highlighted users, click the **Mark All Items** arrow and choose **Clear Selected Items**. To clear all check boxes, click the **Mark All Items** arrow and choose **Clear All**.
7. Click **Import**. A confirm message box opens. Click **Yes** to continue.
  - If the users were imported successfully, a message box opens. Click **OK** and then click **Close** to close the Import Users from LDAP Directory Tree dialog box.
  - If the same user names exist in the Users list, the Handle Conflict dialog box opens. For more information, see ["Handling User Name Conflicts" on page 125](#).
8. Click **Close** to close the Import Users from LDAP Directory Tree dialog box.

### To search for users by keyword:

1. In Site Administration, click the **Site Users** tab.
2. Click the **Import LDAP Users** arrow , and select **Import LDAP Users by Keyword**. The Import LDAP Users by Keyword dialog box opens.



3. In the **Server** box, select the LDAP server you want to search.
4. In the **Find** box, type a keyword, and click the **Find** button .

ALM searches for the keyword in the following fields: **User Name**, **Full Name**, **Group**, **Description**, **Email**, **Phone**.

**Tip:** To broaden your search, enter partial values. For example, enter Mi to search for Michael and Mikhael.

5. Click **Import**. A confirm message box opens. Click **Yes** to continue.
  - If the users were imported successfully, a message box opens. Click **OK** and then click **Close** to close the Import LDAP Users by Keyword dialog box.

- If the same user names exist in the Users list, the Handle Conflict dialog box opens. For more information, see ["Handling User Name Conflicts" on page 125](#).
6. Click **Close** to close the Import LDAP Users by Keyword dialog box.

## Enabling LDAP over SSL

ALM supports LDAP communication transfer over secure sockets (SSL). This ensures that users' credentials (passwords) are not sent over the network in an unsecured way.

This section describes the configuration steps needed to enable LDAP communication over SSL.

### LDAP Server Configuration:

To use SSL for secure communication, the following must be preconfigured on the LDAP server:

- SSL must be enabled.
- A secure port must be set (the port is **636** by default).
- A server certificate must be installed.

Also, you must obtain a root certificate (and any intermediate) of the Certificate Authority (CA) that issued the LDAP server certificate.

### ALM Server Configuration:

The following must be pre-configured on the ALM server:


1. A certificate trust store.  
In most cases, the default trust store is used. The default trust store is **<JAVA\_HOME>/jre/lib/security/cacerts** (the default password is changeit), where **<JAVA\_HOME>** is the installation location for the JDK that comes with ALM (for example, C:\Program Files\HP\ALM\java\jre).
2. To establish trust to the CA that issued the LDAP server certificate, import the root CA certificate into the java trust store using the keytool utility.

**Note:** The keytool utility is located in the bin folder of the JAVA\_HOME (for example, C:\Program Files\HP\ALM\java\jre\bin).

For example, keytool -import -alias <your LDAP CA> -trustcacerts -file <LDAP CA cert> -keystore <JAVA\_HOME>/jre/lib/security/cacerts

If there are any intermediate Certificate Authorities, import their certificates as well.

### To define LDAP settings for SSL:

1. In Site Administration, click the **Site Users** tab.
2. Click the **User Settings** button  and select **Multi LDAP Settings**. The LDAP Settings dialog box opens.

3. In the **Directory provider URL** box, type the URL of the LDAP server (`ldaps://<server name>:<port number>`).

**Note:** The port must be enabled for SSL, as configured on the LDAP server. The default SSL port is **636**.

## Defining LDAP Settings for Importing Users

To enable you to import users from an LDAP directory to the Users list in Site Administration, you must define your LDAP import settings.

When you import users from an LDAP directory, ALM copies attribute values from an LDAP directory into ALM. For each imported user, the following attribute values are copied:

- **Distinguished name (DN).** A unique name that is made up of a sequence of relative distinguished names (RDN) separated by commas.

### Example


CN=John Smith, OU=QA, O=HP


CN is the common name; OU is the organizational unit; and O is the organization.

- **Userid (UID).** The name that identifies a user as an authorized user. The UID attribute value is mapped to the **User Name** field in ALM.
- **Full Name, Description, Email and Phone.** Optional attributes that are used to populate the Full Name, Description, Email, and Phone Number fields for each user imported from an LDAP directory.

**Note:** The optional **LDAP\_IMPORT\_ATTRIBUTE\_MASK** parameter enables you to define a regular expression that can be used to distinguish between different values for an LDAP attribute. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

**To define LDAP settings for importing users:**

1. In Site Administration, click the **Site Users** tab.
2. Click the **User Settings** button  and select **Multi LDAP Settings**. The LDAP Settings dialog box opens.



3. Click **New**. Enter the server name and click **OK**.  
**Server Name** is valued with the server name, and other fields are valued with default values.
4. In the **Directory provider URL** box, type the URL of the LDAP server (`ldap://<server name>:<port number>`).
5. Under **LDAP authentication type**:
  - Select **Anonymous** to enable you to import users from the LDAP server using an anonymous account.
  - Select **Simple** to enable you to import users from the LDAP server using an authorized (search-entitled) user account and password. If you select **Simple**, the following options are enabled:
    - In the **Authentication principal** box, type the authorized user name.
    - In the **Authentication credentials** box, type the password.
  - If you are using lightweight single sign-on, select **Use LWSSO** and enter the LDAP attribute name to be used as the lightweight single sign-on login name.
6. Click **Test Connection** to test the URL of the LDAP server.
7. In the **Directory base** box, type the LDAP directory name.

**Note:** The **Directory base** is a distinguished name of a node in the LDAP hierarchy and is used as a root for operations retrieving data. If this field is left empty, it dramatically increases the search time of a user in the LDAP tree.

8. In the **Base filter** box, define filter criteria.
9. In the **Result record limit** box, enter the maximum number of records to display in the **Import**

**LDAP Users by Keyword** dialog box. The default value is 100.

**Note:** A value less than the recommended minimum value of 100 can slow LDAP imports and searches. A value greater than the recommended maximum value of 10000 can cause the server to run out of memory.

10. Define the corresponding LDAP field names. Note that **User Name** is a required field.
11. To set the default values for the Active Directory, click **Use default values for:** and select **Active Directory**.
12. To set the default values for LDAP, click **Use default values for:** and select **LDAP**.
13. Click **Save** to save the LDAP directory.

As each LDAP directory is created, it is added to the **LDAP server** panel. You can add or delete LDAP directories from this panel.

**Note:** When a user logs in, ALM searches the LDAP directories in the order they are listed in the **LDAP server** panel until a match is found.

14. Click **Close** to close the LDAP Settings dialog box.

## Handling User Name Conflicts

When importing users from an LDAP directory to the Users list in Site Administration, you may encounter the following conflicts:

- **Same user.** A user with the same LDAP distinguished name already exists.
- **Same user name.** A user with the same user name already exists.

To resume the process of importing users, you can choose to skip the user, rename a user name, or update user information.

### To handle user name conflicts:

1. Import users (see ["Importing Users from LDAP" on page 120](#)). If conflicts occur, the Handle Conflict dialog box opens.

The dialog box titled "Handle Conflict" contains two sections for handling user conflicts. The first section, "Conflict: Same User", shows a table with columns "User Name" and "Solution", containing one row with "scarter" and "Skip". The second section, "Conflict: Same User Name", shows a table with columns "User Name", "Solution", and "New User Name", containing one row with "tmorris", "Skip", and an empty "New User Name" field. To the right of these tables is a text area with the following content:

**Conflict: Same User**  
User with the same distinguished name already exists.

**Conflict: Same User Name**  
User with the same user name already exists.

**Possible solutions:**  
Skip - Ignores the selected user.  
Update - Updates existing user information.  
Rename - Assigns a new name to the selected user.  
Auto Rename - Assigns a new name to the selected user by adding a suffix.

At the bottom of the dialog box are three buttons: "Continue", "Cancel", and "Help".

- If the conflict is listed under **Conflict: Same User**, you can choose one of the following options to resume the process:

Option	Description
<b>Update</b>	Updates existing user information. Click the corresponding <b>Solution</b> box. Click the browse button and choose <b>Update</b> .
<b>Skip</b>	Does not import the selected user (default).

- If the conflict is listed under **Conflict: Same User Name**, you can choose one of the following options to resume the process:

Option	Description
<b>Rename</b>	Assigns a new name to the selected user. Click the corresponding <b>Solution</b> box. Click the browse button and choose <b>Rename</b> . In the <b>New User Name</b> box, type the new name.
<b>Auto Rename</b>	Assigns a new name to the selected user by adding a suffix. Click the corresponding <b>Solution</b> box. Click the browse button and choose <b>AutoRename</b> . The new name is displayed in the <b>New User Name</b> box.
<b>Update</b>	Updates existing user information. Click the corresponding <b>Solution</b> box. Click the browse button and choose <b>Update</b> .
<b>Skip</b>	Does not import the selected user (default).


- Click **Continue**.

## Updating User Details


After you add a user, you can update user details. For example, you may need to update a user's full name or contact details. You can also define ALM users as site administrators. For more information, see ["Defining Site Administrators" on page 19](#).

### To update user details:

- In Site Administration, click the **Site Users** tab. In the right pane, click the **User Details** tab.



- Select a user from the Users list.

**Tip:** You can search for a user in the Users list by typing the name, or the first letter(s) of the name, of a user in the **Find** box, and clicking the **Find** button . The first user that matches the searched text is highlighted. Click the button again to search for other users containing the

searched text.

3. Edit the user detail fields.

**Note:** If the user was imported from an LDAP directory to Site Administration, **LDAP Authentication Server** displays the LDAP server and **Domain Authentication** displays the LDAP authentication properties of the imported user. If the user was not imported, these fields are not displayed. For more information, see ["Importing Users from LDAP" on page 120](#).

For smart card authentication, enter the email from the smart card in **E-mail** and the common name (CN) from the smart card in **Description**. For single sign-on (SSO) authentication, enter the email and the user name in **Description**.


4. To set the user's status, click the **Deactivate** or **Activate** button. For more information on user status, see ["Deactivating and Activating Users" below](#).
5. To assign projects to a user, click the **User Projects** tab. For more information, see ["Assigning Projects to Users" on page 131](#).
6. Click **Apply** to save your changes.

## Deactivating and Activating Users

You can deactivate or activate an ALM user. A deactivated user cannot log in to any project. The user is not deleted from the Users list, and all user permissions and settings are saved. This can be useful, for example, for contract workers that work intermittently for a set period of time.


**Caution:** A deactivated site administrator user cannot log in to Site Administration.

### To deactivate a user:

1. In Site Administration, click the **Site Users** tab.
2. Choose one of the following:
  - To deactivate users as of the next attempted login, select one or more Active users from the Users list, and click the **Deactivate** button  on the toolbar. The **Status** is set to **Inactive**, and the user icon is changed in the Users list. In addition, the **Deactivation Date** box is hidden. If a user is currently logged in to an ALM project, this does not terminate the user session. When the user next attempts to log in to a project, a message box displays stating that the user is deactivated and cannot log in.
  - To deactivate a user on a set date in the future, select an Active user from the Users list. Click the **User Details** tab. In the **Deactivation Date** box, click the drop-down arrow and select a date.

### To activate a user:

1. In Site Administration, click the **Site Users** tab.
2. Select one or more Inactive users from the Users list.

3. Click the **Activate** button  on the toolbar. The **Status** is set to **Active**, and the user icon is changed in the Users list.

## Creating and Changing Passwords

The site administrator can create, change, or override a user's password.

### Note:

- You can only change passwords for users that are set to log in to ALM using their ALM passwords. If LDAP passwords are in use, or if users log in to ALM using external authentication, this option is unavailable. For more information on LDAP authentication, see ["Defining LDAP Settings for Importing Users" on page 123](#).
- Users who are not administrators can change their passwords using the **User Properties** link in the Project Customization window. For more information, refer to the *HP Application Lifecycle Management User Guide*.
- For details on the old connection method to Site Administration for the purposes of backward compatibility, see the **BACKWARD\_SUPPORT\_SA\_DEFAULT\_USER** site parameter.

### To create or change a password:

1. In Site Administration, click the **Site Users** tab.
2. Select a user from the Users list.
3. Click the **Password** button. The Set User Password dialog box opens.
4. In the **New Password** box, type a new password (maximum length 20 characters).
5. In the **Retype Password** box, retype the new password.
6. Click **OK**.

## Locking Out Users

**Available in:** ALM 12.21

As the site administrator, you can determine the number of login attempts a user can make before being deactivated. By default, no limit is set. In addition, you can set a parameter that resets the count of failed logins if a specified amount of time passes after an attempted login.

You can set a time interval after which a deactivated user is reactivated automatically, or you can reactivate locked out users.

### To lock out users:

1. Set the **MAX\_INVALID\_LOGINS\_ATTEMPT\_TO\_LOCKOUT** Site Configuration parameter.  
If the user unsuccessfully tries to log in more times than the number you assign, the user is locked out.
2. You can also set the **INTERVAL\_BETWEEN\_INVALID\_LOGINS\_TO\_LOCKOUT** Site



Configuration parameter.

The default value for this Site Configuration parameter is 60 seconds. If the user waits longer than this amount of time between login attempts, the count of invalid login attempts resets to zero.

When a user is locked out, the user's status is set to **Inactive**. Activate the user, and the user can attempt to log in again. For more information, see ["Deactivating and Activating Users" on page 127](#).

To automatically allow users to attempt to log in again, set the **INTERVAL\_TO\_AUTO\_RELEASE\_LOCKOUT** Site Configuration parameter. Once the user waits the amount of time specified in this parameter, the user is activated and can attempt to log in again.

For more information on the Site Configuration parameters, see ["Setting ALM Configuration Parameters" on page 155](#).

## Enabling Authentication for Users

You can allow users to log in to ALM using their LDAP passwords or external authentication, instead of ALM passwords.

Working with LDAP through SSL requires that you perform additional steps. For more information, see [HP Software Self-solve knowledge base article KM188096](http://h20230.www2.hp.com/selfsolve/document/KM188096) (<http://h20230.www2.hp.com/selfsolve/document/KM188096>).


This section includes:


- ["Considerations" below](#)
- ["Enabling LDAP Authentication for Users" below](#)
- ["Enabling External Authentication for Users" on the next page](#)

### Considerations

- After LDAP authentication is enabled, authentication will be performed against the LDAP server. Make sure that the site administrator is set up as an LDAP user before switching to LDAP authentication, otherwise the site administrator will not be able to log in after the authentication type is switched.
- After you enable LDAP authentication, you need to disable the password reset option, by defining the **PASSWORD\_RESET\_DISABLE** Site Configuration parameter. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).


### Enabling LDAP Authentication for Users


1. In Site Administration, click the **Site Users** tab.
2. Click the **User Settings** button  and choose **Authentication Settings**. The Authentication Settings dialog box opens.




3. Under **Authentication type**, select **LDAP** to set the authentication type as LDAP for all users.
4. Click **OK**.

## Enabling External Authentication for Users

1. In Site Administration, click the **Site Users** tab.
2. Click the **User Settings** button  and choose **Authentication Settings**. The Authentication Settings dialog box opens.



3. Under **Authentication type**, select **External Authentication** to set external authentication for all users.
4. Click **Advanced Settings** to set the external authentication parameters. The External Authentication Advanced Settings dialog box opens.



5. From the dropdown list, select the **Authentication Type**.
  - a. **Email:** ALM extracts the user email from the header value and finds the ALM user with the same email address defined in ALM.
  - b. **Name:** ALM extracts the user name from the header value and finds the ALM user with the same name in the Description field.

- c. **Email + Name:** ALM Desktop Client extracts the user email and name from the header value. ALM first tries to match the email to an ALM user, and if this is unsuccessful tries to match the name to an ALM user.
6. Enter the **Pattern** - The format for extracting information from the header.  
If the **Pattern** is not defined, ALM uses the default pattern.  
For example, `.*[eE][^=]*=([^,]*@[^,]*)` extracts the email, such as `E=ben@domain.com`.
7. Click **OK**.
8. Click **OK** in the Authentication Settings dialog box.

## Assigning Projects to Users

As an ALM site administrator, you can control user access to ALM projects by defining the projects to which a user can log on. When a user is no longer working on a project, remove the user from the User Projects list.

When you add a user to a project, the user is automatically assigned to the project with Viewer privileges. For more information on user groups and group privileges, see ["Managing Users in a Project" on page 207](#) and ["Managing User Groups and Permissions" on page 211](#).

### Note:

- You can assign users to projects from the Site Projects tab. For more information, see ["Assigning Users to Projects" on page 65](#).
- ALM sends automatic email notification to project administrators when users are assigned or removed from a project in Site Administration. You can make automatic notification unavailable by adding the **AUTO\_MAIL\_USER\_NOTIFICATION** parameter in the Site Configuration tab. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

### To assign projects to a user:


1. In Site Administration, click the **Site Users** tab. In the right pane, select the **User Projects** tab. The Projects list for the selected user is displayed.

The screenshot shows the 'User Projects' tab for a user named 'alex\_alm'. The interface includes a 'Password' field at the top, followed by the username 'alex\_alm'. Below this, there are two tabs: 'User Details' and 'User Projects', with 'User Projects' being the active tab. The 'User Projects' tab contains a toolbar with 'Select Projects' (plus icon), 'Remove' (minus icon), 'Find' (magnifying glass icon), and a 'Group By Domain' checkbox. Below the toolbar is a table with two columns: 'Domain' and 'Project'. The table contains one row with 'DEFAULT' in the 'Domain' column and 'ALM\_Demo' in the 'Project' column. At the bottom of the window, it says 'Total Projects : 1'.

Domain	Project
DEFAULT	ALM_Demo

**Tip:** You can click the **Domain** column to change the sort order from ascending to descending domain names. You can also click the **Project** column to sort according to project instead of domain name.


2. In the Users list in the left pane, select a user.

**Tip:** You can search for a user by typing the name of a user in the **Find** box, and clicking the **Find** button .

The selected user's projects are displayed in the User Projects list.


To group user projects by domain, select **Group By Domain**. Clear the check box to remove the group by settings.

3. In the User Projects tab, click the **Select Projects** button. The ALM Projects list is displayed in a new pane to the right of the User Projects tab.



4. To select projects from the Projects list, expand the directory, and select the projects that you want to assign to the user.

To clear all selected projects, click **Clear All**.

5. Click the **Add current user to the selected projects** button . The selected projects are added to the User Projects list.
6. To remove a project from the User Projects list, select the project in the User Projects tab and click the **Remove** button. Click **OK** to confirm. The project is removed from the User Projects list.


**Note:** This does not delete the project from the server.

7. To refresh the User Projects list, click the **Refresh** button .

## Exporting User Data

You can export the user name and full name of all site users from the Users list to a text file.


**To export user data:**

1. In Site Administration, click the **Site Users** tab.
2. Click the **Export User Data To File** button . A confirm message box opens. Click **Yes** to continue. The Export Data To File dialog box opens.
3. Select the directory where you want to save the parameters, and type a name for the file in the **File name** box.
4. Click **Save** to export the data to a text file.

## Deleting Users

You can delete a user from the Users list.

### To delete a user:

1. In Site Administration, click the **Site Users** tab.
2. Select a user from the Users list.
3. Click the **Delete User** button .
4. Click **Yes** to confirm.



# Chapter 7: Managing User Connections and Licenses

In Site Administration, you can monitor user connections and modify license information.

This chapter includes:

- [About Managing User Connections and Licenses](#) ..... 136
- [Monitoring User Connections](#) .....136
- [Managing Licenses](#) .....138

## About Managing User Connections and Licenses

You use the **Site Connections** tab in Site Administration to monitor and manage the users connected to your HP Application Lifecycle Management (ALM) projects. For more information, see ["Monitoring User Connections" below](#).

You use the **Licenses** tab in Site Administration to view ALM license information and modify the license key. For more information, see ["Managing Licenses" on page 138](#).

## Monitoring User Connections

You can use the Site Connections tab to perform the following:

- Monitor the users currently connected to an ALM server. For each user, you can view the domain and project being used, the user's machine name, the time the user first logged in to the project, and the time the most recent action was performed. You can also view the client type connection to the ALM server.
- View the licenses that are used by each user.
- Send messages to users connected to your ALM projects. You can also disconnect users from projects.
- Modify access to an ALM project using the **Module Access** link. For more information, see ["Customizing Module Access for User Groups" on page 222](#).

### Note:

- To view the total number of licenses that are in use for each ALM module, click the **Licenses** tab. For more information, see ["Managing Licenses" on page 138](#).
- To view and analyze the number of licensed ALM users connected to your projects at specific points over a period of time, click the **Site Analysis** tab. For more information, see ["Monitoring Site Usage" on page 160](#).
- The ALM client can be inactive for a certain amount of time before it is disconnected from ALM. Disconnecting the client enables the license to be used by another ALM user. For more information, see the site administration configuration parameter **WAIT\_BEFORE\_DISCONNECT**.





### To monitor user connections:

1. In Site Administration, click the **Site Connections** tab.

Domain	Project Name	User Name	Host	Login Time	Last Action	Licenses in Use			
						Business Components	Enterprise Integration 2.0 and later for SAP	Full License Center	Performance Center
DEFAULT	ALM_Demo_2	alex_alm	VMFTRND25	7/21/2010 11:00:00	7/21/2010 9:00:00	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
DEFAULT	ALM_Demo_1	alice_alm	VMFTRND51	7/21/2010 4:00:00	7/21/2010 4:00:00	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
DEFAULT	ALM_Demo_2	shelly_alm	VMFTRND51	7/21/2010 4:00:00	7/21/2010 4:00:00	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
DEFAULT	ALM_Demo_1	alex_alm	VMFTRND51	7/21/2010 4:00:00	7/21/2010 7:00:00	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
DEFAULT	Template_Demo	alex_alm	ZHANOCH05	7/21/2010 7:00:00	7/21/2010 8:00:00	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>

Total Connections : 5

**Tip:** You can click any column heading to change the sort order of the column from ascending to descending.

2. To refresh the Connections list, click the **Refresh Connections List** button . To instruct ALM to automatically refresh the Connections list, click the **Refresh Connections List** arrow and choose **Automatic Refresh**. By default, the Connections list is automatically refreshed every 60 seconds. To change the automatic refresh rate, click the **Refresh Connections List** arrow and choose **Set Refresh Rate**. In the Set Refresh Rate dialog box, specify a new refresh rate in seconds.
3. You can group connected users by clicking the **Group By** arrow, and choosing a Group By option. To group connected users by project, choose **Group By Project**. To group connected users by user, choose **Group By User**. To clear the Group By settings, click the **Group By** arrow and choose **Clear Group By**.
4. You can send a message to a connected user or group of users by clicking the **Send Message** button. For more information on sending messages, see ["Sending Messages to Connected Users" below](#).
5. To disconnect a user or group of users from a project, select the row of the user or group and click the **Disconnect Users** button . Click **Yes** to confirm.

## Sending Messages to Connected Users

You can send messages to users connected to your ALM projects. This enables you to routinely inform connected users about important maintenance activities. For example, disconnecting a project, or restarting an ALM server.

When you send a message, a pop-up window automatically opens on the user's machine displaying the message text. The message box is displayed until the user closes it or disconnects from ALM. For more information, refer to the *HP Application Lifecycle Management User Guide*.

### To send messages to connected users:

1. In Site Administration, click the **Site Connections** tab.
2. Select the users to whom you want to send a message:
  - To send a message to a user or group of users, select the row of the user or group.
  - To send a message to multiple users, use **Ctrl** or **Shift** to highlight users to include.

- 3. Click the **Send Message** button. The Send Message dialog box opens.  
The **To** box displays the intended recipients of the message in the format [DOMAIN:Project Name:User Name].

**Example**  
[DEFAULT:ApplicationLifecycleManagement\_Demo:peter\_alm]

- 4. In the **Message Text** box, type a message.
- 5. Click **Send**. ALM sends the message to user machines within five minutes.

## Managing Licenses

In the Licenses tab, you can view the total number of licenses in use, the maximum number of licenses that you have for each ALM project or domain, and the expiration dates for the licenses. When other HP tools, such as UFT, are connected to an ALM project, you can view the total number of licenses in use for these tools. You can also add licenses. In addition, you can view the ALM edition installed on your server.

Within the Licenses tab, there are tabs for viewing and updating licenses:

- **Status.** You can modify licenses and link to the licensing portal to retrieve licenses.
- **License Assignments.** You can assign licenses to the various domains and projects.
- **Named Licenses.** You can assign named licenses to specific users.
- **PPU Licenses History.** You can view the current number of available PPU licenses and the history of their usage.

**Note:**

- To view the ALM licenses that are currently being used by each user, click the **Site Connections** tab. For more information, see ["Monitoring User Connections" on page 136](#).
- To view and analyze the number of licensed ALM users connected to your projects at specific points over a period of time, click the **Site Analysis** tab. For more information, see ["Monitoring Site Usage" on page 160](#).
- **Performance Center:** You can view additional Performance Center license information in Lab Management. For more information, refer to the *HP ALM Lab Management Guide*.

This section includes:

- [Modifying Licenses](#) ..... 139
- [Assigning Licenses to Domains and Projects](#) ..... 140
- [Assigning Licenses to Users](#) ..... 141
- [PPU Licenses History](#) ..... 142

## Modifying Licenses





In the Status tab, you can modify licenses and launch the HP Licensing portal to retrieve licenses.

### To modify licenses:

1. In Site Administration, click the **Licenses** tab.
2. Click the **Status** tab.

Status				
<a href="#">License Assignments</a>   <a href="#">Named Licenses</a>   <a href="#">PPU Licenses History</a>				
<a href="#">Modify License</a>   <a href="#">Hide expired licenses</a>   <a href="#">Launch Licensing Portal</a>				
License Name	Named	Expiration Date	In Use	Max
Business Components	No	Unlimited	7	10,000
Business Components	Yes	Unlimited	0	10,000
Enterprise Integration 2.0 and later for SAP	No	Unlimited	3	Unlimited
Full License	No	Unlimited	7	20,000
Full License	Yes	Unlimited	0	10,000
Performance Center	No	Unlimited	0	Unlimited
Edition : Application Lifecycle Management Model : CONCURRENT				

The Status tab includes the following UI elements:

UI Element	Description
	<b>Refresh.</b> Refreshes the screen.
	Enables you to modify the license by selecting one of the following: <b>Upload License.</b> Opens the Upload License dialog box, enabling you to browse for and select a license key. <b>Paste License.</b> Opens the Paste License dialog box, enabling you to paste the license key into a text box.
	Hides expired licenses in the table.
	Opens the HP Licensing portal in a new browser, enabling you to purchase licenses.
<b>License Name</b>	The ALM module name.
<b>Named</b>	Indicates whether the license is a named license assigned to a specific user.
<b>Expiration Date</b>	The expiration date of the license.
<b>In Use</b>	The total number of licenses in use.
<b>Max</b>	The maximum number of available licenses.
<b>Edition</b>	Indicates the ALM edition installed. For more information, refer to the <i>HP Application Lifecycle Management User Guide</i> .
<b>Model</b>	Indicates the license type. Possible values are: <b>CONCURRENT.</b> A license that allows perpetual usage of the purchased licenses until the license expiration date. <b>PPU.</b> A license that allows a month of actual usage of the purchased licenses. Used licenses expire at the end of the month in which they were used.

3. Click the arrow next to **Modify Licenses**.

4. Select **Upload License** or **Paste License**.

- Select **Upload License** to open the Upload License dialog box, enabling you to browse for and select a license key.
- Select **Paste License** to open the Paste License dialog box, enabling you to paste the license key into a text box.

**Note:** You cannot paste licenses in Internet Explorer 11. You must upload the license from a file.

5. To add licenses, click **Launch Licensing Portal**.

The HP Licensing portal opens in a new browser, enabling you to purchase licenses.

## Assigning Licenses to Domains and Projects






In the License Assignments tab, you can assign licenses to specific domains or projects to allow users assigned to each project to use the assigned licenses. The number of remaining, available licenses is shown towards the bottom of the tab. If a project needs more licenses than the number it is assigned, extra licenses can be taken from the domain or from the available licenses, until all available licenses are used.

**To assign licenses:**

1. In Site Administration, click the **Licenses** tab.
2. Click the **License Assignments** tab.

Status License Assignments Named Licenses PPU Licenses History				
Expand All Collapse All Show only assigned projects				
Domain/Project Name	Full License	Enterprise Integration 2...	Performance Center	Business Components
LAB_PROJECT	5	1	25	45
default	10		30	90
default1	15		35	55
default2	20		40	60
Available	19,950	0	29,870	9,790
Site Pool	20,000	1	30,000	10,000

The License Assignment tab includes the following UI elements:

UI Element	Description
	<b>Refresh.</b> Refreshes the screen.
	Saves changes.
	Expands the domains and displays all project names.
	Collapses the domains and hides the project names.
	Hides the domains and projects that do not have licenses assigned to them.
<b>Available</b>	Number of available unassigned site level licenses by license type remaining.

UI Element	Description
<b>Site Pool</b>	Total number of available site level licenses by license type.

3. Select the domain or project to which you want to assign licenses. and enter the number of licenses you want to assign in the project or domain row.
4. Enter the number of licenses you want to assign in the entry in the selected row, according to the type of licenses you are assigning.

The total of available licenses is reduced accordingly.

ALM validates that the total number of licenses assigned to the projects and domains does not exceed the number of licenses in the site pool.


5. Click **Save** to save the changes.

## Assigning Licenses to Users







You can assign named licenses to specific users. The user has exclusive access to this license, but cannot use licenses from the Site Pool. The user must use this license for thirty days. After thirty days, the license assignment can be removed from the user. Also, when a named license is assigned to a user, you have one hour to remove the assignment.




To assign a license to a user:


1. In Site Administration, click the **Licenses** tab.
2. Click the **Named Licenses** tab.
3. Click **Select Users** to open the Site Users area to the right of the screen.



The Named Licenses tab includes the following UI elements:


UI Element	Description
	<b>Refresh.</b> Refreshes the screen.
	Saves changes and updates the Assigned Time column.
	Hides any expired licenses in the table.
	Opens the Site Users area to the right of the screen.
	<b>Remove selected users.</b> Removes the selected users from the Assigned Users area.
	<b>Add selected users.</b> Adds the selected users to the Assigned Users area.

UI Element	Description
	<b>Apply filter.</b> Applies the filter typed in the Filter field. To return to the full list, leave the Filter field empty and click <b>Apply filter</b> again.
	Pages forward or back in the list of site users.
	Refreshes the list of site users.
<b>License Name</b>	The ALM module name.
<b>Expiration Date</b>	The expiration date of the license.
<b>In Use</b>	The total number of licenses in use.
<b>Max</b>	The maximum number of licenses that you have for each ALM module.
<b>User Name</b>	The name of the user.
<b>Full Name</b>	The full name of the user.
<b>Assignment Time</b>	The date and time that the user was assigned to the license.
<b>Reassignment Time</b>	The date and time that the license assignment can be removed from the user. Once a license is assigned to a user, you have one hour to remove the assignment. After that time, the assignment cannot be removed from the user for thirty days. During the first hour and after thirty days, this field is valued with <b>Reassignable</b> .
<b>Page</b>	Displays the current page in the list of site users.

4. In License Status, select the license name.
5. In Site Users, select the user.
6. Click **Add selected users**  to assign the user. The user name is displayed in the Assigned Users area.
7. Click **Save** to save the changes.

To remove a license assignment from a user:

**Note:** A license assignment can only be removed from a user when Reassignment Time has the value Reassignable.

1. In License Status, select the license.
2. In Assigned Users, select the user.
3. Click **Remove selected users**  to remove the user. The user name is no longer displayed in the Assigned Users area.
4. Click **Save** to save the changes.

## PPU Licenses History

The usage of Pay-Per-Use (PPU) licenses is determined by the peak number of concurrent license usage that is recorded during the month. You can track peak usage in the current month in the Site

Analysis tab. For more information, see ["Monitoring Site Usage" on page 160](#).

At the beginning of each month, the number of used PPU licenses is subtracted from the total number of available licenses. If the remaining number of available licenses goes below the number of licenses you require, you can load additional licenses to meet the demand.

In the PPU Licenses History tab, you can view the number of available PPU licenses and the history of PPU license usage.

The information in the tab includes the following transactions:

- New purchases of PPU licenses, increasing the number of available licenses.
- The automatic recalculation of licenses at the beginning of each month, decreasing the number of available licenses.

Status	License Assignments	Named Licenses	PPU Licenses History
<div> <div>Date</div> <div>Full License</div> <div>Performance Center</div> <div>Business Components</div> </div>			
<div> <div>Delta</div> <div>Available</div> <div>Delta</div> <div>Available</div> <div>Delta</div> <div>Available</div> </div>			
No historical PPU data is being collected since the current model is Concurrent.			
<div> <div>Available</div> <div>Unlimited</div> <div>Unlimited</div> <div>Unlimited</div> </div>			
<p><b>Available</b> is the number of available licenses (current quota).</p> <p><b>Delta</b> is the number of added or consumed licenses.</p>			

The PPU Licenses History tab includes the following UI elements:

UI Element	Description
<b>Date</b>	<p>The date on which a change in the number of available licenses is recorded. This occurs in one of the following cases:</p> <ul style="list-style-type: none"> <li>• Available licenses are calculated at the beginning of a month.</li> <li>• New licenses are added.</li> </ul>
<b>Delta</b>	<p>The number of licenses added or subtracted from the previous quota of available licenses. A Delta value is displayed separately for each module.</p> <ul style="list-style-type: none"> <li>• In the case of a calculation of available licenses, the delta displays a negative value, equal to the peak number of licenses that were used concurrently in the previous month.</li> <li>• In the case of adding new licenses, the delta displays a positive value, equal to the number of licenses added.</li> </ul>
<b>Available</b>	<p>The number of licenses available for concurrent use during the reported calendar month. An Available value is displayed separately for each module.</p> <p>The number of available licenses is equal to the number of available licenses in the previous row, plus the Delta value in the current row.</p> <p>The Available value can also indicate Unlimited, meaning there is no limit to the number of resources available.</p>
<b>Recommended to buy</b>	<p>A suggested number of additional licenses you should buy, assuming the same level of usage as in the previous month. A Recommended to buy value is displayed separately for each module.</p> <p>This value is equal to the number of licenses used in the previous month (Delta), minus the current amount of available licenses. If the amount is less than zero, nothing is displayed.</p> <p>Recommended to buy is not displayed if the number of licenses is unlimited.</p>





# Chapter 8: Configuring Servers and Parameters

You use Site Administration to configure HP Application Lifecycle Management (ALM) servers, define and modify database servers, configure the text search, set configuration parameters, and define the ALM mail protocol.

This chapter includes:

• About Configuring Servers and Parameters .....	146
• Configuring Server Information .....	146
• Defining New Database Servers .....	148
• Modifying Database Server Properties .....	150
• Configuring Text Search .....	152
• Setting ALM Configuration Parameters .....	155
• Setting the ALM Mail Protocol .....	156
• Setting ALM Mail Restrictions .....	157

## About Configuring Servers and Parameters

You use the **Servers** tab to configure ALM server information. You can set the server log files and maximum number of database handles. For more information, see ["Configuring Server Information" below](#).

You use the **DB Servers** tab to define database servers that were not defined during installation. For each database server, you enter the database type, database name, default connection string, and administrator user and password.

You also use the **DB Servers** tab to modify existing database server definitions. For more information, see ["Modifying Database Server Properties" on page 150](#). In addition, you can configure the text search option for a specified database server that has the text search feature installed and configured. For more information, see ["Configuring Text Search" on page 152](#).

You use the **Site Configuration** tab to add and modify ALM configuration parameters. For more information, see ["Setting ALM Configuration Parameters" on page 155](#). In addition, you can set the mail protocol to be used by all the server nodes in your ALM site. For more information, see ["Setting the ALM Mail Protocol" on page 156](#).

## Configuring Server Information


You can configure ALM server information. This includes:

- **Setting the ALM server log files.** ALM can write all ALM and Site Administration events to log files. The log files display the date and time a function was run. This is useful for when you contact ALM support.
- **Setting the maximum number of database connections.** ALM can open a number of connections for each project on a database server. You can set the maximum number of connections per active request that can be opened by ALM for each project.

ALM Editions: Functionality related to project planning and tracking (PPT) is available for ALM Edition only. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

### To configure ALM server information:

1. In Site Administration, click the **Servers** tab.



2. In the Server list, select a server.  
The **General Settings** area displays the server name.
3. You configure ALM and Site Administration log file settings under the **Client Log File Settings**, **Site Administration Log File Settings** and **Project Planning and Tracking Log File Settings** sections, respectively.

Click the **Log Level** link to configure the type of log file you want the server to create. Select one of the following options in the Log Level dialog box:

- **None.** Does not create a log file.
  - **Errors.** Records error events.
  - **Warnings.** Records potentially harmful situations.
  - **Flow.** Records informational messages that highlight the application flow.
  - **Debug.** Records events that are most useful for debugging.
4. Click the **Max. Log Lines** link to open the Maximum Log Lines dialog box and configure the maximum number of lines that ALM can write to the log file. ALM creates a new log file after the log file reaches the maximum number of lines. The default value is **10,000**.
  5. Click the **Max. Log Days** link to open the Maximum Log Days dialog box and configure the maximum number of days that the ALM server keeps the log file. ALM automatically deletes the log files once the maximum number of days is reached. The default value is **Unlimited**.
  6. Click the **Log File Location** link to change the directory path of the log file. In the Log File Location dialog box, type the new location for the log file.

Saving logs on a remote server may cause performance issues. It is therefore recommended that you save logs to the local file system. If the local file system has limited space, prepare a script which periodically moves the logs to network storage

7. You can set the maximum number of connections per active request that can be opened on the database server by the ALM server for each project. Click the **Max. Database Connections** link

to open the Maximum Database Connections dialog box and set the maximum number of concurrent connections. For information on maximum database connections, see <http://h20230.www2.hp.com/selfsolve/document/KM630397>.

**Note:** In addition to changing the number of connections that can be opened on the database server for each project, you can also change:

- The number of users allowed to connect concurrently to a domain. For more information, see ["Creating Domains" on page 23](#).
- The number of users allowed to connect concurrently to a project. For more information, see ["Updating Project Details" on page 61](#).

8. To remove an ALM server from the Server list, select it and click the **Delete Server** button



. Click **Yes** to confirm.

9. Click the **Refresh Servers List** button  to refresh the servers list.

## Defining New Database Servers

You can define additional database servers that were not defined during the installation process.

### Notes:

- For information on the Oracle or Microsoft SQL permissions required by ALM, refer to the *HP Application Lifecycle Management Installation and Upgrade Guide*.
- To make text search unavailable on a new database server, you must disable text search on the database server before you define the new database server in ALM.

### To define a new database server:

1. In Site Administration, click the **DB Servers** tab.

2. Click the **New Database Server** button . The Create Database Server dialog box opens.

The screenshot shows the 'Create Database Server' dialog box. The 'Database Type' is set to 'MS-SQL (SQL Auth.)'. Under 'Database Values', there are input fields for 'Database Name', 'DB Admin User', and 'DB Admin Password'. Under 'Default Connection String', the 'Connection String Parameters' option is selected, showing fields for 'Server Host', 'Port' (set to 1433), and 'Oracle Service Name'. The 'Connection String' option is unselected, and a text box below it contains 'jdbc:mercury:sqlserver://%HOST\_NAME%:1433'. At the bottom are 'OK', 'Cancel', 'Ping', and 'Help' buttons.

3. Under **Database Type**, select the type of database server you want to define:
  - **MS-SQL (SQL Auth.)**. Uses SQL authentication.
  - **MS-SQL (Win Auth.)**. Uses Microsoft Windows authentication.
  - **Oracle**.
4. Under **Database Values**, in the **Database Name** box, type the database name.
5. In the **DB Admin User** box, type the login name of the database administrator.
  - For Oracle database type, the default administrator user account enabling you to create ALM projects is **system**.
  - For MS-SQL (SQL Auth.) database type, the default administrator user account enabling you to create ALM projects is **sa**.
  - For MS-SQL (Win Auth.) database type, the **DB Admin User** box is unavailable. The login name of the database administrator is the Windows user that is set to run ALM as a service.
6. In the **DB Admin Password** box, type the password of the database administrator. This field is unavailable if you selected the **MS-SQL (Win Auth.)** database type.
7. Under **Default Connection String**, you can edit the default connection string parameters or the connection string, as follows:
  - To edit the default connection string parameters, choose **Connection String Parameters** and define the following parameters:

Parameter	Description
<b>Server Host</b>	The server name.
<b>Port</b>	The port number of the database server.
<b>Oracle Service Name</b>	The service name for an Oracle database server.


- To edit the connection string, choose **Connection String** and edit the connection string.

- For Oracle RAC support, enter a connection string, using the following example:

```
jdbc:company:oracle:TNSNamesFile=<ALM server>\tnsnames.ora;  
TNSServerName=OrgRAC
```

- **tnsnames.ora** is a file containing Oracle database addresses. For more details, refer to *HP Application Lifecycle Management Installation and Upgrade Guide*.
- **OrgRAC** is the address of the TNS server ALM should refer to.

**Note:** To enable Oracle RAC support, you must set the **ORACLE\_RAC\_SUPPORT** site administration parameter to "Y". For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

- To check whether you can connect to the database server, click the **Ping** button. The DB admin user and password you entered are displayed in the Ping Database Server dialog box. Click **OK**.
8. Click **OK** to close the Create Database Server dialog box.
9. If necessary, click the **Refresh Database Servers List** button  to refresh the database servers list.

## Modifying Database Server Properties


You can modify the database server properties.



### Notes:

- For information on the Oracle or Microsoft SQL permissions required by ALM, refer to the *HP Application Lifecycle Management Installation and Upgrade Guide*.
- You can configure the site administration database schema for Oracle RAC support. For more information, refer to the *HP Application Lifecycle Management Installation and Upgrade Guide*.
- For debugging issues related to closure, see the **DEBUG\_CLOSURE\_LOG\_DOM\_PROJ** site parameter.



**To modify database server properties:**

1. In Site Administration, click the **DB Servers** tab.



2. Select a database server in the Database Servers list.
3. To modify the connection string, click the **Edit Connection String** button , or click the **Connection String** link. Edit the connection string in the Connection String Editor and click **OK**. For more information on connection strings, see ["Defining New Database Servers" on page 148](#).
4. To modify the database administrator's login name, click the **Database Administrator User Name** link. In the Database Administrator User Name dialog box, type the new login name and click **OK**.  
For more information on defining a new login name for a database administrator, see step 5 under ["Defining New Database Servers" on page 148](#).
5. To modify the database administrator's password, click the **Database Administrator Password** button , or click the **Database Administrator Password** link. In the Database Administrator Password dialog box, type the new password and then retype it. Click **OK**.
6. To modify the default ALM user password for accessing the database schema, click the **Application Lifecycle Management User Password** link. In the User Password dialog box, type the new password and retype it. Click **OK**.

**Note:** If you change the ALM user password, you must update the user password in the database server accordingly.

7. To enable text search capabilities in ALM, click the **Text Search** link.  
If the text search is enabled, you can set the default text search language for the database server in the **Default Search Language** list.  
For more information on text search, see ["Configuring Text Search" on the next page](#).
8. To check whether you can connect to the database server, click the **Ping Database Server** button. The DB admin user and password you entered are displayed in the Ping Database Server dialog box. Click **OK**.
9. To delete a database server from the Database Servers list, select it and click the **Delete Database Server** button . Click **Yes** to confirm.
10. Click the **Refresh Database Servers List** button  to refresh the database servers list.

## Configuring Text Search

Text search allows users to enter keywords and search specific project fields in the Requirements, Test Plan, and Defects modules. For information on working with the text search feature, refer to the *HP Application Lifecycle Management User Guide*.

### To configure text search:

- Perform setups on each database user schema on which you want to enable text search. For more information, see ["Enabling Text Search on Database User Schemas" below](#).
- In Site Administration, enable text search and define the default search language for a specified database server in the DB Servers tab. For more information, see ["Enabling Text Search in ALM" below](#).
- To specify a different search language for a specific project, change the search language from the Site Projects tab. For more information, see ["Selecting a Text Search Language for a Project" on the next page](#).
- For a specific project, define the project fields to be included in the search from Project Customization. For more information, see ["Defining Searchable Fields" on page 154](#).

## Enabling Text Search on Database User Schemas

Before you enable text search in ALM, you must perform a set up step on each database user schema on which you want to enable text search.

### To enable text search on an Oracle database user schema:

As Admin user, run the following command:

```
GRANT CTXAPP to <database user schema>
```

### To enable text search on an SQL database user schema:

Enable full text indexing:

```
EXEC sp_fulltext_database 'enable'
```

## Enabling Text Search in ALM

In Site Administration, you can enable text search for a specified database server that has the text search feature installed and configured. You can enable text search on a database server before or after you add projects to your Projects list.

If you enable text search on a database server before you add projects, the projects that you add afterwards are text search enabled. If you enable text search on a database server after you have added projects, you must manually enable text search for each existing project.

After you have enabled the text search for a specified database server, you set the default search language for the database server. You can change the default search language for a specific project from the Site Projects tab. For more information, see ["Selecting a Text Search Language for a Project" on the next page](#).



### To enable text search on a database server before adding projects:

1. In Site Administration, click the **DB Servers** tab.
2. In the Database Servers list, select a database server.
3. Click the **Text Search** link.

**Caution:** You cannot disable the text search after you have enabled it.

Click **Yes** to confirm. The **Text Search** value changes from **Disabled** to **Enabled**.

4. In the **Default Search Language** list, set the default text search language for the database server.

### To enable text search on a database server after adding projects:

1. In Site Administration, click the **DB Servers** tab.
2. In the Database Servers list, select a database server.
3. Click the **Text Search** link.

**Caution:** You cannot disable the text search after you have enabled it.

Click **Yes** to confirm. The **Text Search** value changes from **Disabled** to **Enabled**.

4. In the **Default Search Language** list, set the default text search language for the database server.
5. Click the **Site Projects** tab, and select a project for which you want to enable text search.
6. In the **Project Details** tab, click the **Enable/Rebuild Text Search** button to enable and rebuild the text search indexes. Click **Yes** to confirm.

If the operation of enabling and rebuilding the text search indexes times out before it completes, you can change the default timeout value by defining the **TEXT\_SEARCH\_TIMEOUT** parameter. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

7. To enable text search for additional projects, repeat the previous two steps.

## Selecting a Text Search Language for a Project

For each project, you can specify a search language other than the default search language you set for the database server. For more information on enabling the text search and setting the default search language, see ["Enabling Text Search in ALM" on the previous page](#).

**Note:** Search languages are not available for a project created on a database server that does not have the text search feature enabled.

### To select a search language for a project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project. In the right pane, click the **Project Details** tab.
3. In the **Search Language** field, select a language for the project. For more information on updating project details in the Project Details tab, see ["Updating Project Details" on page 61](#).

## Defining Searchable Fields

For each project, you must define the fields to be included in the search in project customization. The searchable option is only available in the Requirement, Test, Business Component, Business Process Models, and Defect entities.


The following are available as searchable fields:


- User-defined fields with field type **Memo** or **String**
- The following system fields.

### Searchable System Fields

Entity	Searchable System Fields
<b>Business Component</b>	<ul style="list-style-type: none"><li>• Comments</li><li>• Component Folder</li><li>• Component Name</li><li>• Description</li><li>• Original Location</li><li>• Subtype ID</li></ul>
<b>Business Process Model Activities</b>	<ul style="list-style-type: none"><li>• Comments</li><li>• Description</li><li>• Text</li></ul>
<b>Business Process Models</b>	<ul style="list-style-type: none"><li>• Comments</li><li>• Description</li></ul>
<b>Defect</b>	<ul style="list-style-type: none"><li>• Comments</li><li>• Description</li><li>• Summary</li></ul>
<b>Requirement</b>	<ul style="list-style-type: none"><li>• Comments</li><li>• Description</li><li>• Name</li><li>• Rich Text</li></ul>
<b>Run</b>	<ul style="list-style-type: none"><li>• Comments</li></ul>
<b>Test</b>	<ul style="list-style-type: none"><li>• Comments</li><li>• Description</li><li>• Path</li><li>• Protocol Type</li><li>• Template</li><li>• Test Name</li></ul>

### To define a searchable field:

1. In the ALM main window, on the masthead, click  , then select **Customize**. The Project Customization window opens.
2. Click the **Project Entities** link. The Project Entities page opens. For more information on customizing project entities, see ["Customizing Project Entities" on page 224](#).
3. Expand an entity, and select a system or user-defined field that can be made searchable.



4. Select the **Searchable** check box.
5. Click **Save** to save your changes to the Project Entities page.

## Setting ALM Configuration Parameters


You can add, modify, and delete parameters in the Site Configuration tab. You can also export parameters to a text file.


### Note:

- You cannot add or delete default parameters. You can only modify them.
- You must reconnect to any open projects to work with the new settings.

### To set ALM parameters:

1. In Site Administration, click the **Site Configuration** tab.



2. To add a new parameter to the list, click the **New Parameter** button. The New Parameter dialog box opens. Type a name, value, and description for the parameter you want to add. Click **OK**.
3. To delete a parameter from the list, select it and click the **Delete Parameter** button. Click **Yes** to confirm.
4. To edit a parameter, select it from the list and click the **Edit Parameter** button. The Edit Parameter dialog box opens. Type a new value and value description, and click **OK**.
5. To export parameters from the site configuration grid to a text file, click the **Export** button. The Export Data To File dialog box opens. Select the directory where you want to save the parameters, and type a name for the file in the **File name** box. Click **Save**.
6. You can click the **Refresh Parameters List** button  to refresh the parameter list.

#### Note:

- The list of available site parameters can be found with the ALM manuals on the HP Software Support web site (<https://softwaresupport.hp.com>).
- ALM configuration parameters related to external authentication can be found in the *HP Application Lifecycle Management External Authentication Configuration Guide*.

## Setting the ALM Mail Protocol

ALM uses email to send project information to users. You can select the mail service to be used by all the server nodes in your ALM site. ALM supports the SMTP mail protocols.

For more information on setting the ALM mail protocol, refer to the *HP Application Lifecycle Management Installation and Upgrade Guide*. To view the protocol currently configured, see the **MAIL\_PROTOCOL** parameter in the **Site Configuration** tab in Site Administration. For more information, see ["Setting ALM Configuration Parameters" on the previous page](#).

### To set the ALM mail protocol:

1. In Site Administration, click the **Site Configuration** tab.
2. Click the **Settings** button and select **Set Mail Protocol**. The Set Mail Protocol dialog box opens.

3. Select one of the following options:
  - **None.** ALM does not send an email.
  - **SMTP Server.** ALM sends an email from an SMTP server on the network. Type the address of an SMTP server available on your local area network. For details, see the **MAIL\_SERVER\_HOST** parameter.
  - **Microsoft IIS SMTP Service.** ALM sends an email from the ALM server machines. This option is available if you installed Microsoft IIS SMTP Service on your ALM server machines during IIS installation.
4. Click **Test** to send a test email to your mailbox. The Test Mail dialog box opens. Type an email address and click **Send**. A pop-up message confirms whether the mail was sent successfully.
5. Click **OK** to close the Set Mail Protocol dialog box.

## Setting ALM Mail Restrictions

ALM uses email to send project information to users. You can restrict which users receive emails.

### To set ALM mail restrictions:

1. In Site Administration, click the **Site Configuration** tab.
2. Click the **Settings** button and select **Mail Restriction**. The Mail Restriction Definition dialog box opens.
3. Select the restriction level:
  - **All.** ALM sends an email to any address.
  - **Per Site Level.** ALM sends an email only to those users who are on the site.
  - **Per Project.** ALM sends an email only to those users who are assigned to the project.
4. Click **OK** to close Mail Restriction Definition dialog box.



# Chapter 9: Analyzing Site Usage

In Site Administration, you can track the number of licensed users that have connected to your HP Application Lifecycle Management (ALM) site at specific points over a period of time. You can also analyze ALM usage by filtering the number of licensed users by projects, users or license types.

This chapter includes:

- [About Analyzing Site Usage](#) .....160
- [Monitoring Site Usage](#) .....160
- [Filtering Site Usage](#) ..... 161
- [Exporting Site Analysis Data to a File](#) ..... 162
- [Customizing the Site Analysis Line Chart Graph](#) ..... 162

## About Analyzing Site Usage

You use the **Site Analysis** tab in Site Administration to monitor license usage for each time interval displayed. You can specify the time interval displayed along the x-axis. You can also specify what information appears in the graph by filtering the graph content by projects, users, or license types.

### Example:

You may want to charge each department in your organization according to license usage. You can filter by projects in a specific department to view license usage for the department. You can also view license usage for a specific group of users by filtering according to selected users.

If the **Site Analysis** tab is not displayed, you can make it available by editing the **SITE\_ANALYSIS** parameter in the Site Configuration tab in Site Administration. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).


## Monitoring Site Usage

You can monitor the number of licensed users that have connected to an ALM site over a selected period of time. You can analyze the usage level of each module and extension, and track the peak usage level in the current month. The data can be displayed in line graphs or data grids. In addition, you can filter records by projects, users, or license type, and save data to a file.

**Note:** You can also monitor the users currently connected to an ALM server. For more information, see ["Managing User Connections and Licenses" on page 135](#).

### To monitor site usage:

1. In Site Administration, click the **Site Analysis** tab.



2. In the **Type** box, select a display type:
  - **Line Chart.** Displays the data as a line graph.
  - **Data Grid.** Displays the data as a grid.
3. In the right pane under **Period**, select a set or custom period of time you want the line graph or



data grid to show.


4. Under **Level of Detail**, select the time period between each measurement.
5. Click the **Filter** button to open the Set Filter dialog box and filter the graph contents. For more information, see ["Filtering Site Usage" below](#).
6. To customize the appearance of a Line Chart graph, see ["Customizing the Site Analysis Line Chart Graph" on the next page](#).
7. If you chose Data Grid, you can save the contents of a data grid as a text file, Microsoft Excel spreadsheet, Microsoft Word document, or HTML document. To save, click the **Save As** button. For more information, see ["Exporting Site Analysis Data to a File" on the next page](#).
8. To refresh data in the graph, click the **Refresh** button.

## Filtering Site Usage


You can analyze the number of users that have connected to your ALM site at specific points over time by filtering by projects, users, or license types.

**To filter site usage:**

1. In Site Administration, click the **Site Analysis** tab.
2. Click the **Filter** button in the bottom right corner. The Set Filter dialog box opens.



3. Under **Filter By**, select the category that you want to filter:
  - **Projects.** Displays all the ALM domains and projects.
  - **Users.** Displays all the ALM site users.
  - **License Types.** Displays all the available license types.
4. Click the items you want to include in the filter.

- For **Projects**, double-click the domain folder to display the domain's projects, and select the projects you want to include. To filter all projects in the domain, select the domain folder.
  - For **Users**, select the users you want to include.
  - For **License Types**, select the licenses you want to include.
5. To clear the selected filter conditions, click the **Clear** button .
  6. Click **OK** to apply the filter and close the Set Filter dialog box. The new line chart or data grid is displayed.

## Exporting Site Analysis Data to a File

You can export site analysis data in a Data Grid as a text file, Microsoft Excel spreadsheet, Microsoft Word document, or HTML document.



### To export Site Analysis data to a file:









1. In Site Administration, click the **Site Analysis** tab.
2. In the **Type** field, select the **Data Grid** display type.
3. Select the analysis period and define a filter.
4. Click **Save as**, and select one of the following formats:
  - **Text Format.** Saves the data as a Text file.
  - **Excel Sheet.** Saves the data as an Excel sheet.
  - **Word Document.** Saves the data as a Word document.
  - **HTML Document.** Saves the data as an HTML document.
5. In the **Save in** box, choose a location for the file.
6. In the **File name** box, type a name for the file.

The **Save as type** box is automatically filled according to the format you selected.
7. Click **Save**.

## Customizing the Site Analysis Line Chart Graph

You can determine how information appears in the Line Chart graph using the line chart toolbar. The toolbar includes the following buttons:

Tool Element	Description
	<b>Show Total Values.</b> Toggles between displaying and hiding a total value in the graph.
	<b>Scroll to the Left.</b> Scrolls the graph to the left. (This button is enabled when the Zoom In and Zoom Out buttons are in use.)

Tool Element	Description
	<b>Scroll to the Right.</b> Scrolls the graph to the right. (This button is enabled when the Zoom In and Zoom Out buttons are in use.)
	<b>Show All.</b> Returns the graph to its normal size. (This button is enabled when the Zoom In and Zoom Out buttons are in use.)
	<b>Zoom In.</b> Increases the magnification of the selected portion of the graph.
	<b>Zoom Out.</b> Decreases the magnification of the selected portion of the graph.
	<b>Rotate Bottom Labels.</b> Toggles between displaying the text on the x-axis vertically and horizontally.
	<b>Set 2D/3D Graph.</b> Toggles the graph from two to three dimensions.
	<b>Copy Graph to Clipboard.</b> Copies the graph to the Clipboard.
	<b>Print Graph.</b> You can choose to print the graph in portrait or landscape view.



# Chapter 10: Scheduling Calculations for Project Planning and Tracking (PPT)

In Site Administration, you can schedule project planning and tracking (PPT) calculations for your HP Application Lifecycle Management (ALM) projects.

ALM Editions: Functionality related to PPT is available for ALM Edition only. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

This chapter includes:

- [About Scheduling Calculations for PPT](#) ..... 166
- [Scheduling Calculations for a Site](#) ..... 166
- [Enabling or Disabling Automatic Calculations for a Project](#) ..... 166
- [Launching Calculations for a Project Manually](#) ..... 167
- [Project Planning and Tracking Tab](#) ..... 168

## About Scheduling Calculations for PPT

PPT tracks application readiness and displays the status of your release in the form of a scorecard. The scorecard monitors and tracks how well each milestone is being met on a daily basis.

To view progress in the scorecard, you must run PPT calculations for your project. You can schedule calculations for your ALM site, and enable scheduled calculations for specific projects and include them in your daily progress calculations. In addition, you can manually trigger calculations for a selected project in order to refresh its results without waiting for an upcoming scheduled calculation.

For more details on PPT, refer to the *HP Application Lifecycle Management User Guide*.

**Note:** For information on configuring PPT log files, see ["Configuring Server Information" on page 146](#).

## Scheduling Calculations for a Site

This section describes how to schedule PPT calculations for an ALM site.

### To schedule calculations for a site:

1. In Site Administration, click the **Project Planning and Tracking** tab.
2. Schedule calculations in the Project Planning and Tracking tab. For user interface details, see ["Project Planning and Tracking Tab" on page 168](#).
3. Enable projects for automatic calculations. For more details, see ["Enabling or Disabling Automatic Calculations for a Project" below](#).


## Enabling or Disabling Automatic Calculations for a Project

This section describes how to enable PPT calculations for a project in order to include it in the automatic daily calculations of your site. When your business needs change, you can disable calculations for a project.

**Note:** PPT is enabled by default when creating a new project.

**To enable or disable automatic calculations for a project:**

1. In Site Administration, click the **Site Projects** tab.



2. In the Projects list, select a project.
3. In the Project Details tab, under **Project Planning and Tracking**, click **Automatic Calculations State**. Click **OK** to confirm.

## Launching Calculations for a Project Manually


This section describes how to manually trigger PPT calculations for a project in order to refresh its results without waiting for the next scheduled calculation.

**To launch calculations for a project manually:**

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, select a project.
3. In the Project Details tab, under **Project Planning and Tracking**, click the **Run Now** button.

# Project Planning and Tracking Tab


This tab enables you to manage PPT calculations for your entire site.





To access	In Site Administration, click the <b>Project Planning and Tracking</b> tab.
Important information	<ul style="list-style-type: none"><li>The database server time displayed on the bottom right-side of the Project Planning and Tracking tab is used when scheduling calculations.</li><li>By default, ALM performs calculations on a project that has been in use in the past 7 days. If a project has not been in use in the past 7 days, calculations are not performed. To change the number of days, edit the <b>PPT_RECENTLY_USED_PROJECTS_THRESHOLD_MINUTES</b> parameter in the Site Configuration tab in Site Administration. For more information, see <a href="#">"Setting ALM Configuration Parameters" on page 155</a>.</li><li>By default, if 10% or more of the KPI calculations within the release fail, ALM aborts project planning and tracking calculations on a release and skips to the next release in a project. To change the percentage value, edit the <b>PPT_KPI_FAILURES_PERCENTAGE_PER_RELEASE_FUSE</b> parameter in the Site Configuration tab in Site Administration. For more information, see <a href="#">"Setting ALM Configuration Parameters" on page 155</a>.</li></ul>

## Miscellaneous Elements

User interface elements are described below:

UI Elements	Description
	<p>This button includes the following options:</p> <p><b>Refresh Status.</b> Refreshes the Project Planning and Tracking tab so that it displays the most up-to-date information.</p> <p><b>Automatic Refresh.</b> Instructs ALM to automatically refresh the Project Planning and Tracking tab. By default, the tab is automatically refreshed every 60 seconds.</p>



UI Elements	Description
	<b>Set Refresh Rate.</b> Opens the Set Refresh Rate dialog box, enabling you to change the automatic refresh rate in seconds.
	Terminates all PPT activities.
	Enables PPT for your site.
<b>Current Status</b>	Includes the following options: <b>Enabled/Disabled.</b> Indicates whether PPT is enabled for your site. <b>Active/Inactive.</b> Indicates whether the scheduled calculation is currently running.
<b>Apply Settings</b>	Applies scheduling changes.

## Scheduling Area

This area enables you to schedule PPT calculations for your entire site.

User interface elements are described below:

UI Elements	Description
<b>Automatically Run Calculations On</b>	Indicates whether or not scheduled calculations are performed on your site.
<b>Daily Calculation Start Time</b>	Start time for scheduling PPT calculations.
<b>Calculation Recurrence</b>	Runs calculations periodically at a specified time.
<b>Abort Calculation After</b>	Ends scheduled calculations at a specified time.

## Purge Area

This area enables you to purge calculations after a specific time period.

User interface elements are described below:

UI Elements	Description
<b>Delete data older than X days</b>	Deletes data older than the defined value. The default value is set to 120 days.  <b>Note:</b> To retain the scorecards, the last five days of the results of the milestone are not purged.

## Advanced Area

This area enables you to increase the number of parallel calculations that are being performed on an entire site. You can also change the speed of scheduled calculations.

User interface elements are described below:

UI Elements	Description
<b>Override Settings</b>	Enables the advanced settings.
<b>Number of Engines</b>	Sets the number of parallel calculations that are being performed concurrently on an entire site.
<b>Engines Throttle</b>	Changes the speed that it takes for ALM to calculate the KPI data. <b>1</b> indicates a slower processing speed and minimum database stress. <b>10</b> indicates a faster processing speed and maximum database stress.

# Chapter 11: ALM Advisor

This chapter describes the ALM Advisor process for collecting and analyzing environment details in order to assess the current ALM deployment and to recommend usage improvements.

This chapter includes:

- [About ALM Advisor](#) .....172
- [Collecting and Assessing ALM Data](#) .....176

## About ALM Advisor

As an ALM site administrator, you can collect environment details to assess the current ALM deployment and recommend usage improvements. The collected data can also be helpful when contacting support.

The ALM Advisor process collects environment details, which are stored in a file in the following location: **C:\ProgramData\HP\ALM\Repository\productData\assessment**.

Once these details are collected, you can then access the ALM Advisor website to assess the deployment and recommend usage improvements.

**Note:** Some of the SQL Server properties require the site administrator for that database to have advanced options permissions. To ensure these permissions, run the following:

```
sp_configure 'show advanced options', 1
GO
RECONFIGURE
GO
```

The following table describes the collected details.

**Note:** For more information on EHCACHE, see [HP Software Self-solve knowledge base article KM00213910](http://h20230.www2.hp.com/selfsolve/document/KM00213910) (<http://h20230.www2.hp.com/selfsolve/document/KM00213910>).

Property Name	Description
<b>DB Common Data</b>	
<b>Name</b>	DB Server name
<b>Version</b>	DB Server version
<b>SQL Server Data</b>	
<b>productLevel</b>	The level of the version of the SQL Server instance
<b>edition</b>	The installed product edition of the SQL Server instance
<b>engineEdition</b>	Database Engine edition of the SQL Server instance installed on the server
<b>editionId</b>	The edition ID of the SQL Server instance
<b>isFullTextInstalled</b>	Indicates whether the full-text and semantic indexing components are installed on the current SQL Server instance
<b>collation</b>	Name of the default collation for the server
<b>osMachineName</b>	Windows computer name on which the server instance is running

Property Name	Description
<b>Oracle DB Data</b>	
<b>sga_max_size</b>	Hard limit up to which sga_target can dynamically adjust sizes
<b>processes</b>	The maximum number of operating system user processes that can simultaneously connect to Oracle
<b>sessions</b>	Maximum number of sessions that can be created in the system
<b>cpu_count</b>	The number of CPUs available for use by the Oracle database
<b>db_cache_size</b>	The size of the DEFAULT buffer pool for buffers with the primary block size
<b>log_buffer</b>	The amount of memory (in bytes) that Oracle uses when buffering redo entries to a redo log file
<b>shared_pool_size</b>	The size of the shared pool
<b>large_pool_size</b>	The size of the large pool allocation heap
<b>java_pool_size</b>	The size of the Java pool, from which the Java memory manager allocates most Java state during runtime execution
<b>pga_aggregate_target</b>	The target aggregate PGA memory available to all server processes attached to the instance
<b>optimizer_mode</b>	Establishes the default behavior for choosing an optimization approach for the instance
<b>optimizer_features_enable</b>	Acts as an umbrella parameter for enabling a series of optimizer features based on an Oracle release number
<b>compatible</b>	Allows using a new release of Oracle, while at the same time guaranteeing backward compatibility with an earlier release
<b>cursor_sharing</b>	Determines what kind of SQL statements can share the same cursors
<b>open_cursors</b>	Specifies the maximum number of open cursors (handles to private SQL areas) a session can have at once
<b>session_cached_cursors</b>	Specifies the number of session cursors to cache
<b>memory_max_target</b>	Specifies the maximum value to which a DBA can set the MEMORY_TARGET initialization parameter
<b>sga_target</b>	Specifies the total size of all SGA components
<b>NLS Parameters (NLS_CHARACTERSET, NLS_LANGUAGE, NLS_TERRITORY, NLS_LENGTH_SEMANTICS)</b>	Character set related information
<b>Site Usage Data</b>	
<b>usersCount</b>	Number of site users
<b>activeUsersCount</b>	Number of active site users
<b>operativeUsersCount</b>	Number of active site users who opened a session in the last 30 days

Property Name	Description
<b>projectsCount</b>	Number of projects
<b>activeProjectsCount</b>	Number of active projects
<b>operativeProjectsCount</b>	Number of active projects that had a session in the last 30 days
<b>Application Server Data</b>	
<b>maxDbConnectionsAllowed</b>	The maximum concurrent db connections allowed
<b>connectorName</b>	Jetty connector name
<b>maxConnectionsRequest</b>	The maximum number of connections requests
<b>maxConnectionsOpen</b>	The maximum number of open connections
<b>maxConnectionsDuration</b>	The maximum duration of connections
<b>Architecture Data</b>	
<b>activeNodes</b>	Number of active nodes- application servers
<b>totalNodes</b>	Total number of nodes
<b>serverName</b>	Application server name
<b>isActive</b>	Application server status
<b>General Site Data</b>	
<b>almEdition</b>	ALM edition
<b>almEditionDisplayName</b>	ALM edition display name
<b>informationCollectionTime</b>	Information collection time in milliseconds
<b>extensionName</b>	Extension name
<b>extensionDisplayName</b>	Extension display name
<b>version</b>	Extension version
<b>Cache Data</b>	
<b>cacheManagerName</b>	Name of the EHCache manager
<b>cacheName</b>	Name of the cache
<b>objectCount</b>	Number of items found in cache
<b>maxElementsInMemory</b>	Sets the maximum number of objects created in memory
<b>maxElementsOnDisk</b>	Sets the maximum number of objects maintained in the DiskStore
<b>memoryStoreEvictionPolicy</b>	Policy enforced upon reaching the maxElementsInMemory limit
<b>eternal</b>	Determines whether an element is eternal, meaning that timeouts are ignored and the element is never expired
<b>timeToldleSeconds</b>	Sets the time for an element to idle before it expires

Property Name	Description
<b>timeToLiveSeconds</b>	Sets the time for an element to live before it expires
<b>overflowToDisk</b>	Determines whether elements can overflow to disk when the memory store reaches the maxElementsInMemory limit
<b>diskPersistent</b>	Determines whether the disk store persists between restarts of the Virtual Machine
<b>diskSpoolBufferSizeMB</b>	The size to allocate the DiskStore for a spool buffer
<b>diskExpiryThreadIntervalSeconds</b>	The number of seconds between runs of the disk expiry thread
<b>statisticsAccuracy</b>	The accuracy of the cache statistics at the time the statistic was computed
<b>cacheHits</b>	The number of times a requested item was found in the cache
<b>onDiskHits</b>	The number of times a requested item was found in the Disk Store
<b>inMemoryHits</b>	The number of times a requested item was found in the Memory Store
<b>misses</b>	The number of times a requested element was not found in the cache
<b>averageGetTime</b>	The average get time
<b>evictionCount</b>	Gets the number of cache evictions since the cache was created or statistics were cleared
<b>Jvm Data</b>	
<b>jvmVersion</b>	Version of JVM being used
<b>usedHeapSize</b>	The total amount of memory in the Java virtual machine
<b>maxHeapSize</b>	The maximum amount of memory that the Java virtual machine attempts to use
<b>freeHeapSize</b>	The amount of free memory in the Java virtual machine
<b>nonHeapUsedSize</b>	The amount of used memory in bytes
<b>nonHeapInitSize</b>	The amount of memory in bytes that the Java virtual machine initially requests from the operating system for memory management
<b>nonHeapCommittedSize</b>	The amount of memory in bytes that is committed for the Java virtual machine to use
<b>nonHeapMaxSize</b>	The maximum amount of memory in bytes that can be used for memory management
<b>name</b>	The name representing this memory manager
<b>collectionElapseTime</b>	The approximate accumulated collection elapsed time in milliseconds
<b>innerCollectionCount</b>	The total number of collections that have occurred
<b>memoryPoolNames</b>	The names of memory pools that this memory manager

Property Name	Description
	manages
<b>architecture</b>	Architecture of the JVM being used
<b>is64Bit</b>	Whether the JVM being used has 64 bits architecture
<b>numberOfProcessorsAvailable</b>	Number of processors available for this JVM
<b>Machine Specification Data</b>	
<b>totalMemoryMB</b>	Total memory installed on the machine
<b>QCSense Data</b>	
<b>startGroupingTime</b>	Segment starting time
<b>endGroupingTime</b>	Segment ending time
<b>nodeName</b>	Name of the node for which the data was collected
<b>measurementName</b>	Name of the measurement collected during the segment
<b>weightedMeanAverageValue</b>	Weighted mean of the average value recorded during the segment
<b>minimumValue</b>	Minimum value recorded during the segment
<b>weightedMeanMinimumValue</b>	Weighted mean of the minimum value recorded during the segment
<b>maximumValue</b>	Maximum value recorded during the segment
<b>weightedMeanMaximumValue</b>	Weighted mean of the maximum value recorded during the segment
<b>measurementsInspectedNumber</b>	Number of records (measurement values) recorded during the segment


## Collecting and Assessing ALM Data


You can assess the current ALM deployment and recommend usage improvements based on the environment details collected.

**To collect environment details:**



1. In Site Administration, select **Tools > ALM Advisor**. The ALM Advisor dialog box opens.



2. Select **Data Protection** to protect sensitive data. Click  for more information on the data protection process.
3. Click **Collect** to begin the data collection process. An email is sent when the process is complete.

**Note:** The email may indicate that the data collection process did not complete successfully. In this case, ensure that all nodes are active and rerun the data collection process.

4. Once the data collection process is complete, log in to the ALM Advisor website. The link to the website is found in the email sent when the data collection process is complete, or click **Go to Site** in the ALM Advisor dialog box.
5. Follow the instructions on the website to upload the collected data and to complete the assessment process.



# Chapter 12: QC Sense

This chapter describes QC Sense, the internal monitoring tool for collecting and analyzing HP Application Lifecycle Management (ALM) usage and performance data.

This chapter includes:

- [About QC Sense](#) .....180
- [QC Sense Configuration](#) ..... 180
- [Generating and Viewing QC Sense Reports](#) ..... 187
- [QC Sense Schema](#) .....188

## About QC Sense

As an ALM site administrator, you can utilize usage and performance data collected by QC Sense to analyze ALM performance behaviors from the user perspective. For example, you can look at the time it takes from the user's click of a button until the desired response is received.

QC Sense collects data on user actions performed in the ALM user interface, and monitors all client and server activity resulting from those actions. You can examine a single user activity and its resulting server and database activities, as well as compare average system response analyzed by user action, server transaction, and many other parameters.

You can configure QC Sense to collect data based on a wide variety of actions and measures. This enables you to examine performance as it relates to different aspects of ALM, such as projects, users, types of actions, and workflow impact. You can examine and compare performance between components of the system, including application servers, database servers, the network, and the file system.

In addition to data on single user activity, you can configure QC Sense to collect information on the ALM servers in your site. QC Sense can collect data on server and network activity such as server threads, memory usage, active sessions, database access time, and file system access time.

QC Sense includes client and server monitors. Each monitor collects usage and performance data on a specific area within ALM. As an ALM site administrator, you can configure each monitor to customize the scope of data collected. All data collected by QC Sense is stored centrally in a site database so you can easily connect between client activity and the resulting server activity. For more information, see ["QC Sense Configuration" below](#).

QC Sense reports enable you to examine and compare performance to help identify the source of a problem. You can compare data between users who are experiencing different levels of performance, or you can clarify actions or behaviors that may be causing a sudden slowing in system responsiveness. For example, you can identify especially long operations, or examine which long operations occurred just before the general slowness on your site. For more information, see ["Generating and Viewing QC Sense Reports" on page 187](#).

The data collected by the QC Sense monitors is stored in the database according to the QC Sense schema. For more information, see ["QC Sense Schema" on page 188](#).

**Note:** QC Sense is not accessible when ALM is configured with external authentication.

## QC Sense Configuration

To configure QC Sense, access the QC Sense Server Configuration window from Site Administration.

The configuration options enable you to:

- set filters for each client and server monitor to define the scope of data that QC Sense collects
- enable or disable a QC Sense monitor
- define the location for storing QC Sense data

- define the maximum number of records stored per monitor
- set the frequency for transferring updated data to the database
- define the frequency at which the QC Sense tables are purged

This section includes:

- [QC Sense Monitors](#) ..... 182
- [Configuring QC Sense](#) ..... 182
- [QC Sense Server Configuration Window](#) .....183
- [Connection String Builder Dialog Box](#) .....186

## QC Sense Monitors

The following table lists the QC Sense monitors and describes the data that each monitor collects by default. For more information on the QC Sense database tables that store the collected data, see ["QC Sense Schema" on page 188](#).

Monitor Name	Database Table Description	Default Configuration
<b>Client Operation</b>	Contains raw data for user operations, such as submitting a defect, updating a requirement, or clicking the <b>Login</b> button.  For details, see <a href="#">"PERF_CLIENT_OPERATIONS" on page 188</a> .	<b>Partial.</b> Collects data on the following: <ul style="list-style-type: none"> <li>• <b>Login</b> operations that exceed two minutes.</li> <li>• <b>Create Entity</b> operations that exceed two minutes.</li> <li>• <b>Paste</b> operations that exceed two minutes.</li> <li>• All operations that exceed five minutes.</li> </ul>
<b>Client Method Call</b>	Contains raw data for ALM client methods monitored by QC Sense.  For details, see <a href="#">"PERF_CLIENT_METHODS_CALLS" on page 189</a> .	<b>Partial.</b> Collects data on the following: <ul style="list-style-type: none"> <li>• Calls to generate Analysis Items that exceed two minutes.</li> <li>• Calls to workflow events that exceed two minutes.</li> </ul>
<b>Client Request</b>	Raw data for requests sent by a client operation to the ALM server.  For details, see <a href="#">"PERF_CLIENT_REQUESTS" on page 190</a> .	<b>Partial.</b> Collects data on all requests that were sent to the server in the context of a filtered client operation or a filtered client method.
<b>Server General</b>	Aggregated data based on several server measures.  For details, see <a href="#">"PERF_SERVER_GENERAL_MEASURES" on page 193</a> .	<b>On</b>
<b>Server Thread Type</b>	Aggregated data on threads running on the server.  For details, see <a href="#">"PERF_SERVER_THREAD_TYPES" on page 194</a> .	<b>On</b>
<b>Server Thread</b>	Raw data for each thread run on the server.  For details, see <a href="#">"PERF_SERVER_THREADS" on page 192</a> .	<b>Off</b>
<b>Server SQL</b>	Raw data for each SQL statement run by the ALM server.  For details, see <a href="#">"PERF_SERVER_SQLS" on page 193</a> .	<b>Off</b>

## Configuring QC Sense


You can configure the global settings for QC Sense, such as specifying an alternate location for the QC Sense schema. You can also configure settings for each monitor to define the scope of data collected, and the maximum number of records stored for the monitor.

**To configure QC Sense:**

1. In Site Administration, select **Tools > QC Sense > Configuration**. The Login to <server> dialog box opens.
2. Enter login credentials for a site administrator user and click **OK**. The QC Sense Server Configuration window opens. For user interface details, see "[QC Sense Server Configuration Window](#)" below.

## QC Sense Server Configuration Window

This window enables you to configure QC Sense settings for an ALM server.




QC Sense configuration includes global settings, as well as settings you can configure for each monitor individually.

To access	In Site Administration, select <b>Tools &gt; QC Sense &gt; Configuration</b> . In the Login to <server> box, enter your site administrator password.
Important information	For details on the default configuration settings, see " <a href="#">QC Sense Monitors</a> " on the previous page.
See also	<ul style="list-style-type: none"><li>• "<a href="#">About QC Sense</a>" on page 180</li><li>• "<a href="#">Generating and Viewing QC Sense Reports</a>" on page 187</li></ul>



### Global Settings

Enables you to define general settings for QC Sense.



<b>To access</b>	In the monitor list located on the left side of the window, select <b>Global Settings</b> .
------------------	---

User interface elements are described below:

UI Element	Description
<b>Specify a storage location for QC Sense data</b>	<p>Includes the following options:</p> <ul style="list-style-type: none"> <li><b>Store data in Site Administration schema.</b></li> <li><b>Store data in another schema</b> (recommended). Specify an alternate location and connection information for storing QC Sense schema tables.</li> </ul> <p>To define the Connection String, click the browse button (  ). For details, see the "<a href="#">Connection String Builder Dialog Box</a>" on page 186. You can also enter all the necessary data manually.</p> <ul style="list-style-type: none"> <li><b>Native authentication.</b> For an SQL server, use Windows Authentication and not SQL Server authentication.</li> </ul> <p>For details on the QC Sense schema, see "<a href="#">QC Sense Schema</a>" on page 188.</p>
<b>Server Persist Job</b>	Defines the time interval, in minutes, at which updated information from QC Sense server monitors is written to the database.
<b>Server Purge Job</b>	Defines the time interval, in hours, at which QC Sense tables are cleaned.
<b>Client Persist Job</b>	Defines the time interval, in minutes, at which updated information from QC Sense client monitors is sent to the server.
	Restores default QC Sense configuration settings. Located in the bottom left of the configuration window.






## Monitor Settings

Enables you to define settings for QC Sense monitors. For details on the monitors, see "[QC Sense Monitors](#)" on page 182.

<b>To access</b>	In the monitor list located on the left side of the window, select a monitor to configure.
------------------	--




User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element	Description
<Monitor list>	<p>Located on the left side of the window, displays the QC Sense client and server monitors. Select a monitor to configure its options and filters.</p> <p> indicates an active monitor.</p> <p> indicates an inactive monitor. Data is not collected for this monitor.</p> <p>To activate or deactivate a monitor, right-click the monitor and select <b>Turn Monitor OFF/ON</b>.</p>
	<p>Enables you to set filter conditions to define the scope of data collected by the filter.</p> <p>Select a filter from the menu to add and configure. There are different filters available for each QC Sense monitor.</p>
	<p><b>Delete Data Filter.</b> Deletes the selected data filter. If there are no filters defined, QC Sense collects all data for the selected monitor.</p> <p><b>Note:</b> An SQL server must have at least one filter.</p>
	<p><b>Monitor Settings.</b> Enables you to define settings for the selected monitor. Includes the following settings:</p> <ul style="list-style-type: none"> <li>• <b>Maximum number of records in monitor database table:</b> Defines the maximum number of records for the monitor that can remain in the database after the database is cleaned by the server purge job.</li> <li>• <b>Time frame length.</b> Defines the time frame for which some measures are calculated. For example, the average server CPU time used for processing a thread, measured over a 15 minute period. Available for the following monitors: Server General, Server Thread Type</li> <li>• <b>Excluded Fields.</b> Monitor data is not saved for the selected fields. Available for the following monitors: Server SQL, Server Thread</li> </ul>
<b>Data Filters pane</b>	Lists the filters for the selected monitor.
<b>Data Filter Details</b>	<p>Displays details and enables you to set conditions for the selected data filter.</p> <p>For more information on the available fields for each monitor, see <a href="#">"QC Sense Schema" on page 188</a>.</p>
<b>Monitor Description</b>	Describes the selected monitor. Indicates the QC Sense schema table that stores data for the monitor.

## Connection String Builder Dialog Box

This dialog box enables you to build custom connection strings. It also enables you to use connection strings that are already defined in Site Administration.



To access	From the <b>Global Settings</b> window, under <b>Specify a storage location for QC Sense data</b> , click <b>Store data in another schema</b> , and then click  .
See also	<a href="#">"QC Sense Server Configuration Window" on page 183</a>

User interface elements are described below:

UI Element	Description
<b>Connection string parameters</b>	<p>This option enables you to build the connection string by selecting a database type and defining parameters.</p> <ul style="list-style-type: none"><li>• <b>Database Type.</b> The database type can be <b>MS SQL</b> or <b>Oracle</b>.</li><li>• <b>Server Host.</b> The server name.</li><li>• <b>Port.</b> The port number of the database server. The default ports are:<ul style="list-style-type: none"><li>• Oracle: 1521</li><li>• MS SQL: 1433</li></ul></li><li>• <b>SID.</b> The service ID for an Oracle database server. The SID field can be edited only for Oracle database type.</li></ul>
<b>Connection string from registered database server in Site Administration</b>	<p>This option enables you to select connection strings from registered database servers in Site Administration.</p> <ul style="list-style-type: none"><li>• <b>DB Server Name.</b> The database server name.</li><li>• <b>Use DB Admin credentials.</b> Use the database administrator credentials of the selected database server.</li></ul>

UI Element	Description
Custom connection string	This option enables you to define complex and non-standard connection strings directly here.

## Generating and Viewing QC Sense Reports

**Note:** The QC Sense reports are for debugging purposes only, and are disabled by default. You can generate QC Sense reports by configuring the **ENABLE\_PERFORMANCE\_MONITOR\_BIRT\_REPORTS** parameter in the Site Configuration tab in Site Administration. For more information, see ["Setting ALM Configuration Parameters" on page 155](#). If you generate QC Sense reports, it is recommended to disable the reports immediately after usage.

You can generate reports based on the data collected by QC Sense. For example, to examine the user experience, you can generate reports on the following:

- all operations performed by a specific user
- transactions of a specific type for all users, such as creating a requirement or clicking the **Login** button
- transactions longer than a set amount of time
- compare users who are experiencing different levels of performance

After you generate a report, you can print the report.

The following types of reports are available:

- **Client reports.** Based on data collected by the QC Sense client monitors. Reports provide information from the user experience perspective, representing user operations in the ALM user interface.
- **Server reports.** Based on data collected by the QC Sense server monitors.
  - Represent server activities invoked by user operations.
  - Server reports on general server activity.
- **Database table reports.** Enable you to access information in the QC Sense schema tables using standard SQL syntax.

### To generate and view reports:

1. In Site Administration, select **Tools > QC Sense > Reports**. The Login to <server> dialog box opens.
2. Enter login credentials for a site administrator user and click **OK**. The QC Sense Report page opens.
3. Click a report link. In the login window that opens, enter login credentials for a site administrator user.

**Note:** You can grant permissions to additional users who are not site administrators by configuring the **QC\_SENSE\_REPORTS\_USERS** parameter in the Site Configuration tab in Site Administration. For more information, see ["Setting ALM Configuration Parameters" on](#)

[page 155.](#)

4. In the report viewer, enter parameters to define the scope of the report you want to generate.

## QC Sense Schema

QC Sense has a single database schema per ALM site. The schema is created during the ALM installation, and stored by default in the Site Administration schema. However, the QC Sense schema is independent of the ALM Site Administration schema, and the tables can be stored in any database schema. For enterprise sites, we recommend storing the schema on another database server. For details on defining an alternate location for the QC Sense schema, see ["QC Sense Configuration" on page 180](#).

The QC Sense schema consists of the following tables:

Table Name	Data Source	Data Type
<a href="#">"PERF_CLIENT_OPERATIONS" below</a>	Client	Raw
<a href="#">"PERF_CLIENT_METHODS_CALLS" on the next page</a>	Client	Raw
<a href="#">"PERF_CLIENT_REQUESTS" on page 190</a>	Client	Raw
<a href="#">"PERF_SERVER_THREADS" on page 192</a>	Server	Raw
<a href="#">"PERF_SERVER_SQLS" on page 193</a>	Server	Raw
<a href="#">"PERF_SERVER_GENERAL_MEASURES" on page 193</a>	Server	Aggregated
<a href="#">"PERF_SERVER_THREAD_TYPES" on page 194</a>	Server	Aggregated

## PERF\_CLIENT\_OPERATIONS

This table stores the data collected by the **Client Operation** monitor.

The table contains one record for each client operation. A **client operation** is an action performed by the user in the ALM user interface. For example:

- clicking the **Authenticate** button in the Login window
- selecting the **Attachments** tab in the Defects module
- expanding a folder in the test plan tree

A client operation type is described by **type**, **data**, and **context**. The column prefix for the table is PCO. For example, PCO\_OPERATION\_ID.

COLUMN NAME	DESCRIPTION
<b>OPERATION_ID</b>	A unique GUID assigned to the operation.
<b>CLIENT_MACHINE_NAME</b>	The client host name in which the operation was performed.
<b>LOGIN_SESSION_ID</b>	The login session ID.

COLUMN NAME	DESCRIPTION
<b>PROJECT_SESSION_ID</b>	The project session ID.
<b>PROJECT</b>	The domain and project name, in the format <domain name>/<project name>.
<b>USER_NAME</b>	The user name.
<b>OPERATION_TYPE</b>	The type of the operation. For example: <ul style="list-style-type: none"> <li>• Button Clicked</li> <li>• Tab Selected</li> <li>• Tree Node Expanded</li> </ul>
<b>OPERATION_DATA</b>	The operation's data. For example: <ul style="list-style-type: none"> <li>• The clicked button label, such as <b>Login</b></li> <li>• The selected tab label, such as <b>Attachments</b></li> </ul>
<b>OPERATION_CONTEXT</b>	The path to the window in which the operation was performed. For example: <ul style="list-style-type: none"> <li>• <b>Module</b>: Business Components .Net; <b>View</b>: EntityTypeViewControl; <b>View</b>: ComponentStepsViewControl; <b>View</b>: DesignStepsViewControl</li> <li>• <b>Form</b>: Component Step Details</li> </ul>
<b>CLIENT_START_TIME</b>	The start time of the operation as a date time data type.
<b>CLIENT_END_TIME</b>	The end time of the operation as a date time data type.
<b>CLIENT_START_TIME_MS</b>	The start time of the operation as the number of milliseconds since <b>01/01/1970</b> .
<b>CLIENT_TOTAL_TIME</b>	The total milliseconds that passed from the start of the operation until the end of the operation.

## PERF\_CLIENT\_METHODS\_CALLS

This table stores the data collected by the **Client Method Call** monitor.

The table contains one record for each method call monitored by QC Sense. The methods that are monitored are predefined by QC Sense. Each method call is linked to the following related records:

- **Owner Operation.** The active operation when this method call was ran.
- **Owner Method Call.** The active monitored method when this method call ran. It can be null.
- **Called Methods.** Another monitored method called from this method call, directly or indirectly.
- **Requests.** Requests sent to the server from this method call, directly or indirectly.

The column prefix for the table is PCMC. For example, PCMC\_METHOD\_CALL\_ID.

COLUMN NAME	DESCRIPTION
<b>METHOD_CALL_ID</b>	A unique GUID assigned to the method call.
<b>LOGIN_SESSION_ID</b>	The login session ID.

COLUMN NAME	DESCRIPTION
PROJECT_SESSION_ID	The project session ID.
PROJECT	The domain and project name, in the format <domain name>/<project name>.
USER_NAME	The user name.
SEQUENCE	The sequence of the method call in the context of its owner operation.
OWNER_OPERATION_ID	The active client operation ID when the method call started.
OWNER_OPERATION_TYPE	The type of the owner operation.
OWNER_OPERATION_DATA	The data of the owner operation.
OWNER_OPERATION_CONTEXT	The context of the owner operation.
OWNER_METHOD_CALL_ID	The active method call ID when the method call started (can be null).
METHOD_NAME	The method name, for example, <b>Login</b> .
CLASS_NAME	The class name, for example, <b>ConnectionManagementService</b> .
MODULE_NAME	The module/assembly name, for example, <b>QCClient.Library.dll</b> .
ADDITIONAL_DATA	Additional data added by the method call.
CLIENT_START_TIME	The start time of the method call as a date time data type.
CLIENT_END_TIME	The end time of the method call as a date time data type.
CLIENT_START_TIME_MS	The start time of the operation as the number of milliseconds since <b>01/01/1970</b> .
CLIENT_TOTAL_TIME	The total milliseconds that passed from the start of the operation until the end of the operation.

## PERF\_CLIENT\_REQUESTS

This table stores the data collected by the **Client Request** monitor.

The table contains one record for each request sent from the client to the server. Each request is linked to the following related records:

- **Owner Operation.** The active operation when the request was sent to the server.
- **Owner Method Call.** The active monitored method when the request was sent to the server. It can be null.

The request record contains the following:

- client performance data, such as the time the client sent the request to the server
- server performance data, such as the time the request arrived at the server

The column prefix for the table is PCR. For example, PCR\_REQUEST\_ID.

COLUMN NAME	DESCRIPTION
REQUEST_ID	The request unique GUID.

COLUMN NAME	DESCRIPTION
	<b>Note:</b> This is also the GUID of the thread that handled the request in the server.
SEQUENCE	The sequence of the request in the context of its owner operation.
OWNER_OPERATION_ID	The active client operation ID when the request was sent to the server.
OWNER_METHOD_CALL_ID	The active monitored method when the request was sent to the server.
LOGIN_SESSION_ID	The login session ID.
PROJECT_SESSION_ID	The project session ID.
PROJECT	The domain and project name, in the format <domain name>/<project name>.
USER_NAME	The user name.
REQUEST_TYPE	The request type, for example, <b>PostBug</b> .
CLIENT_START_TIME	The time the request was sent to the server as a date time data type.
CLIENT_END_TIME	The time the response returned from the server as a date time data type.
CLIENT_START_TIME_MS	The time the request was sent to the server as the number of milliseconds since <b>01/01/1970</b> .
CLIENT_TOTAL_TIME	The total milliseconds that passed from the time the request was sent to the server until the response was received.
SERVER_MACHINE_NAME	The ALM server in which the request was processed.
SERVER_START_TIME	The time the server started processing the request as a date time data type.
SERVER_START_TIME_MS	The time the server started processing the request as the number of milliseconds since <b>01/01/1970</b> .
SERVER_TOTAL_TIME	The total time, in milliseconds, it took for the server to process the request.
SERVER_CPU_TIME	The total CPU time, in milliseconds, allocated for processing the request.
DB_TIME_AVG	The average time the database processed an SQL statement for this thread.
DB_TIME_MAX	The maximum time the database processed an SQL statement for this thread.
DB_TIME_MIN	The minimum time the database processed an SQL statement for this thread.
DB_TIME_COUNT	The number of SQL statements processed by the database for this thread.
FS_TIME_AVG	The average access time to the file system for this request.
FS_TIME_MIN	The minimum access time to the file system for this request.
FS_TIME_MAX	The maximum access time to the file system for this request.
FS_TIME_COUNT	The number of file system accesses (read/write or delete file) for this request.

## PERF\_SERVER\_THREADS

This table stores the data collected by the **Server Thread** monitor.

The table contains one record for each thread run on the server. There are four thread categories:

- **REQUEST.** Thread processing web-gate requests.
- **JOB.** Threads running ALM jobs.
- **ASYNC\_TASK.** Threads running ALM asynchronous tasks.
- **NONE.** All other threads, such as threads running the repository migration process.

The column prefix for the table is PCT. For example, PCT\_THREAD\_ID.

COLUMN NAME	DESCRIPTION
THREAD_ID	The thread unique GUID.
SERVER_MACHINE_NAME	The ALM server in which the thread was processed.
THREADY_CATEGORY	The thread category. Available categories: REQUEST, JOB, ASYNC_TASK, NONE.
THREAD_TYPE	The thread type. For example, request type – <b>PostBug</b> , Job Name – <b>CKeepAliveJob</b> , etc.
SERVER_START_TIME	The time the thread started to run as a date time data type.
SERVER_START_TIME_MS	The time the thread started to run as the number of milliseconds since <b>01/01/1970</b> .
LOGIN_SESSION_ID	The login session ID.
PROJECT_SESSION_ID	The project session ID.
PROJECT	The domain and project name, in the format <domain name>/<project name>.
USER_NAME	The user name.
SERVER_TOTAL_TIME	The total time, in milliseconds, it took for the server to process the thread.
SERVER_CPU_TIME	The total CPU time, in milliseconds, allocated for processing the thread.
DB_TIME_AVG	The average time the database processed an SQL statement for this thread.
DB_TIME_MAX	The maximum time the database processed an SQL statement for this thread.
DB_TIME_MIN	The minimum time the database processed an SQL statement for this thread.
DB_TIME_COUNT	The number of SQL statements processed by the database for this thread.
FS_TIME_AVG	The average access time to the file system for this thread.
FS_TIME_MIN	The minimum access time to the file system for this thread.
FS_TIME_MAX	The maximum access time to the file system for this thread.
FS_TIME_COUNT	The number of file system accesses (read/write or delete file) for this thread.



## PERF\_SERVER\_SQLS

This table stores the data collected by the **Server SQL** monitor.

You can examine the data in this table as it relates to the user actions that are performed (stored in the PERF\_CLIENT\_OPERATIONS table) and the resulting requests that are generated (stored in the PERF\_CLIENT\_REQUESTS table).

The table contains one record for each SQL statement run on the server. The column prefix for the table is PSS. For example, PSS\_SQL\_ID.

COLUMN NAME	DESCRIPTION
SQL_ID	The SQL unique GUID.
SERVER_MACHINE_NAME	The ALM server that ran this SQL statement.
THREAD_ID	The ID of the thread in the context of which the SQL statement was run.
THREAD_CATEGORY	The thread category.
THREAD_TYPE	The thread type.
PROJECT	The domain and project name, in the format <domain name>/<project name>.
USER_NAME	The user name.
SQL_TYPE	The type of SQL statement, for example: 'executeQuery' and 'executeUpdate'.
RECORD_COUNT	Number of records added, deleted or etched by this SQL statement.
START_TIME	The SQL statement start time as a date time data type.
START_TIME_MS	The SQL statement start time as the number of milliseconds since <b>01/01/1970</b> .
TOTAL_TIME	The total time, in milliseconds, that it took for the server to execute the SQL statement.
SQL_STRING	The actual SQL string.

## PERF\_SERVER\_GENERAL\_MEASURES

This table stores the data collected by the **Server General** monitor.

The table stores aggregated data about ALM server behavior. Each record describes a single measure on a single ALM node in a specific time frame. The column prefix for the table is PSGM. For example, PSGM\_SERVER\_MACHINE\_NAME.

COLUMN NAME	DESCRIPTION
SERVER_MACHINE_NAME	The ALM server from which the data was collected.
START_TIME	The start time of the record's time frame.
END_TIME	The end time of the record's time frame.
MEASURE_NAME	The measure name. Available values:

COLUMN NAME	DESCRIPTION
	<ul style="list-style-type: none"> <li>• MEMORY_USAGE</li> <li>• ACTIVE_THREADS</li> <li>• ACTIVE_PROJECT_SESSION</li> <li>• THREAD_TOTAL_TIME</li> <li>• THREAD_CPU_TIME</li> <li>• FREC_REQUEST_CALL_TOTAL_TIME</li> <li>• DB_TIME</li> <li>• FS_TIME</li> </ul>
<b>AVG</b>	The average value measured during the time frame.
<b>MIN</b>	The minimum value measured during the time frame.
<b>MAX</b>	The maximum value measured during the time frame.
<b>COUNT</b>	The number of times the measure was calculated during the time frame.

## PERF\_SERVER\_THREAD\_TYPES

This table stores the data collected by the **Server Thread Type** monitor.

The table stores aggregated data about server threads. Each record describes a single thread type behavior on a single ALM node in a specific time frame in a specific ALM project. The column prefix for the table is PSTT, for example, PSTT\_SERVER\_MACHINE\_NAME.

COLUMN NAME	DESCRIPTION
<b>SERVER_MACHINE_NAME</b>	The ALM server from which the data was collected.
<b>START_TIME</b>	The start time of the record's time frame.
<b>END_TIME</b>	The end time of the record's time frame.
<b>THREAD_CATEGORY</b>	The thread category. Available categories: REQUEST, JOB, ASYNC_TASK, NONE.
<b>THREAD_TYPE</b>	The thread type. For example, request type – <b>PostBug</b> , Job Name – <b>CKeepAliveJob</b> , etc.
<b>PROJECT</b>	The domain and project name, in the format <domain name>\<project name>.
<b>SERVER_TOTAL_TIME_AVG</b>	The average time, in milliseconds, it took for the server to process a thread.
<b>SERVER_TOTAL_TIME_MIN</b>	The minimum time, in milliseconds, it took for the server to process a thread.
<b>SERVER_TOTAL_TIME_MAX</b>	The maximum time, in milliseconds, it took for the server to process a thread.
<b>SERVER_TOTAL_TIME_COUNT</b>	The number of threads that run in the server.
<b>SERVER_CPU_TIME_AVG</b>	The average CPU time, in milliseconds, allocated for processing a thread.
<b>SERVER_CPU_TIME_MIN</b>	The minimum CPU time, in milliseconds, allocated for processing a thread.
<b>SERVER_CPU_TIME_MAX</b>	The maximum CPU time, in milliseconds, allocated for processing a thread.

COLUMN NAME	DESCRIPTION
<b>SERVER_CPU_TIME_COUNT</b>	The number of threads that run in the server.
<b>DB_TIME_AVG</b>	The average time for processing an SQL statement.
<b>DB_TIME_MIN</b>	The minimum time for processing an SQL statement.
<b>DB_TIME_MAX</b>	The maximum time for processing an SQL statement.
<b>DB_TIME_COUNT</b>	The number of SQL statements processed by the database.
<b>FS_TIME_AVG</b>	The average access time to the file system.
<b>FS_TIME_MIN</b>	The minimum access time to the file system.
<b>FS_TIME_MAX</b>	The maximum access time to the file system.
<b>FS_TIME_COUNT</b>	The number of file system accesses (read/write or delete file).



# Chapter 13: Installing HP ALM Tools and Add-ins

HP Application Lifecycle Management (ALM) offers integration and synchronization solutions with HP and third-party tools. To integrate ALM with other tools, you may need to install an add-in from the HP Application Lifecycle Management ALM Tools page or the HP Application Lifecycle Management Add-ins page.


**Note:** If you are integrating ALM with another tool, you can verify that you are using a supported version of the tool. Click **Help > What's New**, and choose the appropriate integrations matrix.

The following ALM tools are available:

- **HP ALM Connectivity.** Enables you to integrate ALM with other tools.
- **HP ALM Lab Service.** Enables you to trigger functional tests and maintenance tasks on a testing host using HP ALM. Install and configure the HP ALM Lab Service agent on functional testing tools (such as VAPI and QuickTest Professional) that need to connect to Lab Management.
- **HP ALM Client Registration.** Registers ALM components on the client machine, enabling you to work with HP testing tools as well as third-party and custom tools.
- **Shared Deployment for Virtual Environments.** Deploys ALM components on a shared location that can be accessed by all users. This is useful if users connect to ALM over a virtual environment, such as Citrix or VMware.
- **Webgate Customization.** Enables you to customize WebGate client components.

## To install an ALM Tool:

1. Choose **Help > ALM Tools** in the ALM main window. The HP Application Lifecycle Management Tools page opens.



## Application Lifecycle Management - Tools

---

**HP ALM Connectivity**  
Enables you to integrate HP ALM with other tools.

**HP ALM Lab Service**  
Enables you to remotely trigger functional tests and maintenance tasks on a testing host using HP ALM. Install and configure the HP ALM Lab Service agent on functional testing hosts (such as VAPI and United Functional Testing) that need to connect to Lab Management.

**HP ALM Client Registration**  
Deploys and registers ALM components on a client machine.

**Shared Deployment for Virtual Environments**  
Deploys ALM components on a shared location of a client machine.

**Webgate Customization**  
Customizes the WebGate client component.

**More HP ALM Add-ins**

Last Updated: February 2014

2. Click a tool link. A page with additional information about the tool opens.  
If you click the **More HP ALM Add-ins** link, the HP Application Lifecycle Management Resources Add-ins page opens, enabling you to select additional add-ins.
3. Click the tool link for instructions on using the tool.

**Tip:** You can also click an extension's link to view the extension's documentation.

4. Follow the instructions on your screen to download and install the tool.

### To install an ALM add-in:

Choose **Help > ALM Add-ins** in the ALM main window. The HP Application Lifecycle Management Resources Add-ins page opens, enabling you to select additional add-ins.

## Part 2: Project Customization





# Chapter 14: Project Customization at a Glance

As an HP Application Lifecycle Management (ALM) project administrator, you use Project Customization to control access to a project by defining the users who can access the project and by determining the types of tasks each user can perform. You can also customize a project to meet the specific requirements of your organization.

**Cross Project Customization:** As an ALM template administrator, you can customize a template project and apply the customization to one or more ALM projects using cross project customization. This enables you to standardize policies and procedures across projects in your organization. For more information, see "[Cross Project Customization](#)" on page 257.

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

This chapter includes:

- [Starting Project Customization](#) .....202
- [Understanding the Project Customization Window](#) .....204
- [Saving Customization Changes](#) .....206

## Starting Project Customization

You can customize your ALM projects using the Project Customization window.

**Note:** Users belonging to the Viewers group cannot view or change any settings in the Project Customization window, except settings on the User Properties page.

### To start project customization:

1. Open your Web browser and type your ALM URL  
`http://<ALM server name>[:port number]/qcbn`. The HP Application Lifecycle Management Options window opens.




2. Click the **ALM Desktop Client** link.

The first time you run ALM, files are downloaded to your client machine. Subsequently, ALM carries out a version check. If there is a newer version on the server, updated files are downloaded to your client machine.


- **Windows 7/2008R2/2012:** If you do not have administrator privileges on your machine, and a Security Warning displays, click **Don't Install**. You will be redirected to the Install screen.
- If file downloads are prohibited through your browser, you can install these files by using the HP ALM Client MSI Generator add-in, available from the HP Application Lifecycle Management Add-ins page (**Help > Add-ins**).
- If you run ALM over a virtual environment, such as Citrix or VMware, only the system administrator can install a new version.

After the ALM version has been checked and files have been updated if necessary, the ALM Login window opens.



The image shows the HP Application Lifecycle Management (ALM) login window. It features the HP logo in the top left corner. The title "Application Lifecycle Management" is centered at the top. Below the title, there are input fields for "Name:" and "Password:". To the right of the "Password:" field, there is a checkbox labeled "Automatically log in to my last domain and project on this machine" and a link labeled "Forgot password". Below these fields, there are two dropdown menus labeled "Domain:" and "Project:". At the bottom right, there are two buttons: "Authenticate" and "Login".

**Note:** If ALM was configured for external authentication, the Name and Password fields do not appear in this window. Continue with step 7.

3. In the **Login Name** box, type your user name.  
If you type a user name that does not have administrator privileges for a particular project, you are restricted to the customization functions available for that user group. For more information, see ["About Managing User Groups and Permissions" on page 212](#).
4. In the **Password** box, type your password. If you cannot remember your password, click the **Forgot Password** link. For more information, refer to the *HP Application Lifecycle Management User Guide*.  
After you log in to ALM, you can change your password from the Project Customization window. For more information, refer to the *HP Application Lifecycle Management User Guide*. In addition, site administrators can change a user's password from Site Administration. For more information, see ["Creating and Changing Passwords" on page 128](#).
5. Select the **Automatically log in to my last domain and project on this machine** check box if you want ALM to automatically log in to the last project in which you were working.
6. Click **Authenticate**. ALM verifies your user name and password and determines which domains and projects you may access. If you specified automatic login, ALM opens.
7. In the **Domain** list, select a domain. By default, the last domain in which you were working is displayed.
8. In the **Project** list, select a project. By default, the last project in which you were working is displayed.
9. Click **Login**. ALM opens and displays the module in which you last worked during your previous session.
10. On the masthead, click , then select **Customize**. For more information, see ["Understanding the Project Customization Window" on the next page](#).
11. To exit the Project Customization window and return to your ALM project, click the **Return** button located on the upper-right corner of the window.  
If you have made changes to Project Customization, the Customization Changes dialog box opens. For more information, see ["Saving Customization Changes" on page 206](#).

## Understanding the Project Customization Window

As an ALM project administrator, you can customize a project to meet the specific requirements of your organization in the Project Customization window.

For important considerations when making changes to project customization, see ["Saving Customization Changes" on page 206](#).

The Project Customization window contains the following links:

**Note:** If you are working in a template project, some links are displayed with **(Shared)** after the name. This indicates that the customization on that page is applied to linked projects. For more information, see ["Cross Project Customization" on page 257](#).

Link	Description
<b>User Properties</b>	<p>All users can use this option to change their user properties and password. For more information, refer to the <i>HP Application Lifecycle Management User Guide</i>.</p> <p>In Site Administration, a site administrator can override and change a user's properties and password from the <b>Site Users</b> tab. For more information, see <a href="#">"Updating User Details" on page 126</a>, and <a href="#">"Creating and Changing Passwords" on page 128</a>. A project administrator cannot change a user's properties from Project Customization, unless the <b>ALLOW_UPDATE_USER_PROPERTIES_FROM_CUSTOMIZATION</b> parameter is set to Y.</p>
<b>Project Users</b>	<p>You can add and remove users from an ALM project. You can also assign users to user groups to restrict user access privileges. For more information, see <a href="#">"Managing Users in a Project" on page 207</a>.</p> <p><b>Note:</b> You create ALM users and define user properties from Site Administration. For more information, see <a href="#">"Managing ALM Users" on page 117</a>.</p>
<b>Groups and Permissions</b>	<p>You can assign privileges to user groups by specifying permission settings. This includes specifying transition rules and hiding data. For more information, see <a href="#">"Managing User Groups and Permissions" on page 211</a>.</p>
<b>Module Access</b>	<p>You can control the modules that each user group can access. By preventing users from accessing unnecessary modules, you can better utilize your ALM licenses. For more information, see <a href="#">"Customizing Module Access for User Groups" on page 222</a>.</p>

Link	Description
<b>Project Entities</b>	You can customize your ALM project to suit your environment. A project can contain system fields and user-defined fields. System fields can be modified. User-defined fields can be added, modified, and deleted. For more information, see <a href="#">"Customizing Project Entities" on page 224</a> .
<b>Requirement Types</b>	You can add requirement types to your ALM project and define which fields are available and which fields are required for each requirement type. For more information, see <a href="#">"Customizing Project Requirement Types" on page 231</a> .
<b>Risk-Based Quality Management</b>	<p>You can customize criteria and criterion values for risk-based testing, and customize default testing efforts and testing levels. For more information, see <a href="#">"Customizing Risk-Based Quality Management" on page 245</a></p> <p>ALM Editions: The Risk-Based Quality Management link in Project Customization is not available for ALM Essentials Edition. For more information about ALM editions and their functionality, see the <i>HP Application Lifecycle Management User Guide</i>.</p>
<b>Project Lists</b>	You can add customized field lists to a project. A field list contains values that the user can enter in system fields or user-defined fields. For more information, see <a href="#">"Customizing Project Lists" on page 236</a> .
<b>Automail</b>	You can set up automatic mail notification rules to inform users via email about defect repair activity. For more information, see <a href="#">"Configuring Automail" on page 241</a> .
<b>Alert Rules</b>	You can activate alert rules for your project. This instructs ALM to create alerts and send email when changes occur in the project. For more information, see <a href="#">"Activating Alert Rules" on page 253</a> .
<b>Workflow</b>	<p>You can generate scripts to perform commonly needed customizations on the fields of the Defects module dialog boxes. For more information, see <a href="#">"Generating Workflow Scripts" on page 321</a>.</p> <p>In addition, you can write scripts to customize dialog boxes in any module, and to control the actions that users can perform. For more information, see <a href="#">"Workflow Customization at a Glance" on page 333</a>.</p>
<b>Project Planning and Tracking</b>	<p>You can create and customize the project planning and tracking (PPT) KPIs. For more information, see <a href="#">"Customizing Project Planning and Tracking KPIs" on page 269</a>.</p> <p>ALM Editions: The Project Planning and Tracking link in Project Customization is available for ALM Edition. For more information about ALM editions and their functionality, see the <i>HP Application Lifecycle Management User Guide</i>.</p>
<b>Project Report Templates</b>	You can create and customize report templates that project users can assign to template based reports. For more information, see <a href="#">"Project Report Templates" on page 277</a> .
<b>Business Process Testing</b>	You can configure Business Process Testing and BPT Packaged Apps Kit. For more information, see <a href="#">"Configuring Business Process Testing" on page 313</a> .
<b>Business Views</b>	You can create business views which can be used as a basis for creating reports in the Analysis View module. For more information, see <a href="#">Business Views</a> .
<b>Sprinter</b>	<p>You can configure settings for working with HP Sprinter for manual testing in ALM. For more information, see <a href="#">"Configuring Sprinter" on page 317</a>.</p> <p>ALM Editions: The <b>Sprinter</b> link in Project Customization is not available for ALM Essentials Edition or Performance Center Edition. For more information about ALM editions and their functionality, see the <i>HP Application Lifecycle Management User Guide</i>.</p>
<b>IDE Connector</b>	You can perform the necessary customizations to work with Application Lifecycle Intelligence.

Link	Description
Customizer	<b>Note:</b> This link is available only if you enable the ALM Dev Extension. For more details on enabling extensions, see <a href="#">"Enabling Extensions for a Project" on page 67</a> . To download documentation for IDE Connector Customizer, visit the HP ALM Add-ins page, available from <b>Help &gt; Add-ins</b> .

## Saving Customization Changes

As a project administrator, you can save a customization change as a major change or a minor change. The option you select determines if customization is reloaded when a user reconnects after a session expires.

- **Major change** (default). When a user session expires and the user reconnects, customization reloads.


We recommend that you use this option only for critical changes that must be made available to users as soon as possible. Limiting major changes enables users to quickly reconnect without reloading customization. For example, you might use this option when adding a required user-defined field.

- **Minor change**. When a user session expires and the user reconnects, customization does not reload.

If at least one major customization change has been made since the last login, customization is reloaded when a user reconnects, for details, see the **DISPLAY\_LAST\_USER\_INFO** site parameter. This includes all major and minor customization changes that have been made between the last time the user logged in and the current login time.

### To select a save option for a customization change:

1. After making changes to Project Customization, click the **Return** button to exit the Project Customization window. The Customization Changes dialog box opens.



2. Select a save option and click **OK** to exit Project Customization and return to your ALM project.

# Chapter 15: Managing Users in a Project

As an HP Application Lifecycle Management (ALM) project administrator, you can control access to a project by defining the users who can log in to the project and by specifying the types of tasks each user may perform.

This chapter includes:

- [About Managing Users in a Project](#) ..... 208
- [Adding a User to a Project](#) ..... 208
- [Assigning Users to a User Group](#) ..... 209
- [Removing a User from a Project](#) ..... 210

## About Managing Users in a Project

For each ALM project, you must select a list of valid users from the overall ALM users list.

**Note:** The users list is created in Site Administration. For more information, see ["Managing ALM Users" on page 117](#).

You then need to assign each project user to a user group. Each group has permissions to perform certain ALM tasks.

## Adding a User to a Project

You add new users to an ALM project.

**To add a user to a project:**

1. In the Project Customization window, in the left pane, click **Project Users**. The Project Users page opens.

The screenshot shows the 'Project Users' window. On the left is a table with two columns: 'Name' and 'Full Name'. The table lists several users, with 'alex\_alm' (Alex Smith) selected. To the right of the table is a 'Details' panel for the selected user. It contains fields for 'User Name' (alex\_alm), 'Full Name' (Alex Smith), 'E-mail', 'Phone Number', 'Status' (Active), and 'Deactivation Date'. There is also a 'Description' text area at the bottom.

Name	Full Name
alex_alm	Alex Smith
alice_alm	Alice Jones
cecil_alm	Cecil Davis
james_alm	James Johnson
kelly_alm	Kelly White
mary_alm	Mary River
michael_alm	Michael Brown
paul_alm	Paul Winter
peter_alm	Peter Adams
robert_alm	Robert Phillips
shelly_alm	Shelly Rivers

**Tip:** You can click the **Name** column to change the sort order from ascending to descending user names. You can also click the **Full Name** column to sort according to full names instead of user names.

2. Click the arrow to the right of the **Add User** button. Add users to the project using one of the following options:
  - To add an existing user by typing a user name, select **Add User By Name**. The Add User dialog box opens. Type the user name of a user that is defined in Site Administration for this project. Click **OK**.
  - To create a new user in the Site Users list and add the user to the project, select **Add New User to Site**. In the Add New User to Site dialog box, type the details for the new user and click **OK**.

**Note:** For smart card authentication, enter the email from the smart card in **E-mail** and the



common name (CN) from the smart card in **Description**. For single sign-on (SSO) authentication, enter the email and the user name in **Description**.

If this option is not available, you can enable it by setting the **ADD\_NEW\_USERS\_FROM\_PROJECT** parameter in Site Administration. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

- To add existing users from the Site Users list, select **Add Users from Site**. In the Add Users from Site dialog box, select the users you want to add to the project.

You can refresh the list of users with the **Refresh** button, and you can search for existing users by name with the **Find** button. Click **OK**.

The users are added to the Project Users list and the user details are displayed in the Details tab. User details are defined in Site Administration. For more information, see ["Updating User Details" on page 126](#).

3. Click **Save** to save your changes to the Project Users page.

## Assigning Users to a User Group

After you add a user to the project, you can assign the user to one or more user groups. By default, new users are assigned to the project as members of the **Viewer** user group.

You can assign a user to a default user group, or to a customized user group. For more information on customizing a user group, see ["Managing User Groups and Permissions" on page 211](#). You can change the access privileges for existing users at any time by changing the user group to which they are assigned.


**Tip:** You can also assign users to user groups from the **Groups and Permissions** page. For more information, see ["Assigning Users to Groups" on page 213](#).



### To assign a user to a user group:

1. In the Project Customization window, in the left pane, click **Project Users**. The Project Users page opens.
2. In the **Project Users** list, select the user you want to assign to a user group. The user properties are displayed (name, email, phone, and description) in the Details tab. The email information is important as it enables a user to receive defects, tests, requirements, and test set notifications directly to their mailbox.



The user details are defined in Site Administration. For more information, see ["Updating User Details" on page 126](#).

3. Select the **Membership** tab.



4. To assign the selected user to a user group, click a user group name in the **Not Member of** list and click the right arrow button .
5. To remove the user from the currently selected user group, click a user group name in the **Member of** list and click the left arrow button .

**Note:** The **Member of** list can never be empty. A user must always belong to at least one user group.

6. To move all the user groups from one list to the other, click the double arrow buttons  .
7. Click **Save** to save your changes to the Project Users page.

## Removing a User from a Project

To ensure the security of a project, remove any users who are no longer working on the project. Removing a user from a project does not delete the user from the ALM users list in Site Administration.

### To remove a user from a project:

1. In the Project Customization window, in the left pane, click **Project Users**. The Project Users page opens.
2. In the **Project Users** list, select the user you want to remove and click the **Remove User** button.
3. Click **OK** to confirm. The user is removed from the Project Users list.
4. Click **Save** to save your changes to the Project Users page.

# Chapter 16: Managing User Groups and Permissions

You can control access to HP Application Lifecycle Management (ALM) projects and modules by defining the user groups that can enter them, and by determining the types of tasks each user group performs according to permission levels.

This chapter includes:

• About Managing User Groups and Permissions .....	212
• Adding User Groups .....	212
• Assigning Users to Groups .....	213
• Setting User Group Permissions .....	214
• Setting Transition Rules .....	216
• Hiding Data for a User Group .....	219
• Renaming User Groups .....	220
• Deleting User Groups .....	220
• Understanding Permission Settings .....	221
• Customizing Module Access for User Groups .....	222

## About Managing User Groups and Permissions

To protect a project from unauthorized access, ALM enables you to assign each user to one or more groups. ALM includes predefined groups with default privileges. Each group has access to certain ALM tasks. The default user groups include: TDAdmin, QATester, Project Manager, Developer, and Viewer.

### Performance Center:

- The following additional default user groups are available: Performance Advisor, Performance Tester, Performance Test Specialist.

When a project requires that certain user groups have privileges that are outside the scope of their default permissions, you can add your own customized user groups and assign each group a unique set of privileges.


After you set user group permissions, you can also define the ALM modules to which you want to give a user group access. When a user group member logs in to a project, only the authorized modules are displayed.

### Groups and Permissions when Using Cross Project Customization

ALM template administrators use cross project customization to apply customization from a template project to one or more ALM projects. For information, see ["Cross Project Customization" on page 257](#).

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you are working with cross project customization, consider the following when setting permissions for groups:

- **Working with a Template Project:** If you are working with a template project, in Project Customization, you use the **Groups (Shared)** link to manage user groups and permissions. User groups created in a template project are created in the linked projects when you apply the template customization. The users assigned to the user group in the template project are not applied to linked projects. For more information on applying template customization, see ["Applying Template Customization to Linked Projects" on page 263](#).
- **Working with a Linked Project:** User groups defined by a template project are displayed with a template icon  in the linked project. You can assign users to user groups defined by the template project. You cannot modify, rename, or delete a user group defined by the template project. You can, however, limit the records that the user group can view. For more information, see ["Hiding Data for a User Group" on page 219](#).


## Adding User Groups

If you determine that the default user groups do not meet the needs of your project, you can create additional user groups for your project. When you add a new user group, you set the group's

permissions according to an existing user group.

**To add a user group:**

1. In the Project Customization window, in the left pane, click **Groups and Permissions**. The Groups and Permissions page opens.



2. Click the **New Group** button. A confirm message box opens. Click **Yes** to continue. The New Group dialog box opens.
3. In the **New Group Name** box, type a name for the group. A group name cannot include the following characters: ( ) @ \ / : \* ? " ' < > | + = ; , %
4. In the **Set As** list, assign the privileges of an existing user group to the new group.  
Choose an existing user group that has similar access privileges to the new user group you want to create. This minimizes the level of customization you need to do.
5. Click **OK**. The new group name is added to the group list in the Groups and Permissions page.
6. Click **Save** to save your changes to the Groups and Permissions page.

## Assigning Users to Groups

After you add a user to the project, you can assign the user to one or more user groups. By default, new users are assigned to the project as members of the **Viewer** user group.


You can assign a user to a default user group, or to a customized user group. You can change the access privileges for existing users at any time by changing the user group to which they are assigned.

**Tip:** You can also assign users to user groups from the **Project Users** customization module. For more information, see ["Managing Users in a Project" on page 207](#).





**To assign a user to a user group:**

1. In the Project Customization window, in the left pane, click **Groups and Permissions**. The Groups and Permissions page opens.
2. In the group list, select the group to which you want to assign a user.

3. Select the **Membership** tab to see which users belong to the group.



The users assigned to the group are displayed in the **In Group** pane of the Membership tab. Users not assigned to the group are displayed in the **Not in Group** pane of the Membership tab.

4. To assign a user to the currently selected user group, select a user in the **Not in Group** list and click the right arrow button .
5. To remove a user from the currently selected user group, select a user in the **In Group** list and click the left arrow button .
6. To move all the user groups from one list to the other, click the double arrow buttons  .
7. Click **Save** to save your changes to the Groups and Permissions page.


## Setting User Group Permissions

Every user group has a set of privileges, or permissions, which are defined by the ALM project administrator. For example, suppose a group of users called DOC has Viewer permissions. To work more effectively on the project, they need to add, modify, and delete defects. As the ALM project administrator, you can assign these privileges to the DOC group by specifying permission settings.

### Note:

- You cannot modify the privileges of a default user group. To view permissions for these groups, in the Groups and Permissions page, select the user group in the group list and click the **Permissions** tab. For more information, see ["Understanding Permission Settings" on page 221](#).
- If you upgrade a project, and the upgraded version contains a permission that was not present in the original version, ALM automatically assigns that permission to all users in the project.

### Cross Project Customization - Working with a Linked Project:

User groups defined by a template project are displayed with a template icon  in the linked project. If you are working with a project that is linked to a template project, you cannot modify the permissions of


a user group defined by the template project. You can, however, limit the records that the user group can view. For more information, see ["Hiding Data for a User Group" on page 219](#).

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

### To set user group permissions:

1. In the Project Customization window, in the left pane, click **Groups and Permissions**. The Groups and Permissions page opens.
2. In the group list, select the user group for which you want to set permissions, and click the **Permissions** tab.

A set of tabs are displayed in alphabetical order, one tab for each ALM module plus tabs for specific purposes, such as for administration. Permission levels (such as Create, Update, and Delete) for the entities available in each module are listed under the Permission Level column.



3. Click a module tab. If necessary, to see the permission levels for each entity, expand the entity.
  - If the permissions of an entity is dependent on, or impacts, the permissions of another entity, an **i** icon is displayed to the right of the **By Owner Only** column, and the Impacts pane at the bottom of the window displays information about the impact.
  - If additional options are available for a permission level, they are displayed in the Options pane at the right of the window.
  - If an entity's permission levels can only be modified by its owner, a check box appears in the **By Owner Only** column. For more information, see ["Owning ALM Objects" on page 217](#).
4. Select the checkbox for the permission levels that the selected user group should have for each entity. For more information on the available permissions, see ["Understanding Permission Settings" on page 221](#).
5. If a permission level has sublevels, expand the permission level to display the list of associated fields. Then select the fields that the selected user group can use.
6. Limit the capabilities of modifying a field as follows:
  - To limit the entities whose permission levels can only be modified by their owners, select the checkbox for the permission level in the **By Owner Only** column. For example, ensure that only the person who owns the record can delete the value by selecting the checkbox in the **By Owner Only** column, next to Delete in the Permission Level column. For more information, see

["Owning ALM Objects" on the next page.](#)

- To limit the values a user group can select from a lookup list type field, set transition rules of permissible field values in the Options pane. For more information, see ["Setting Transition Rules" below.](#)
7. Click the **Data-hiding** tab to hide data from the current user group by module. For more information, see ["Hiding Data for a User Group" on page 219.](#)
  8. Click **Save** to save your changes to the Groups and Permissions page.

## Setting Transition Rules

You can limit a group's modifying privileges by setting transition rules for modifying values in fields. These rules determine the values that the group can modify in fields that you specify. Transition rules can be set only for lookup and user list fields.

### Example

When modifying defect information, you can limit the items a user group can select in the Status field of a defect record. You can set a transition rule that only allows a user group to edit the Status field from **Fixed** to **Closed**.

**Note:** When Workflow has been used to change a list of values for a field that is set with transition rules, the field may only be modified in a way that satisfies both the workflow script and the transition rules. For more information, see ["Workflow Event Reference" on page 347.](#)


### To set transition rules:

1. In the Project Customization window, in the left pane, click **Groups and Permissions**. The Groups and Permissions page opens.
2. In the group list, choose the user group for which you want to set permissions.
3. Click the **Permissions** tab.
4. Click a module tab, such as **Defects**. The tab displays the entities available in the Defects module and their corresponding permission levels.
5. Expand and select an entity and its permission level. For example, expand **Defect** and then expand **Update**. The permission level expands and lists available fields.

For more information on the available entities and permission levels, see ["Understanding Permission Settings" on page 221.](#)



6. Select a field. For example, select **Status**. The Transition Rules grid appears in the Options pane on the right side of the window.



7. Click **Add Rule** to add a transition rule. The Add Transition Rules dialog box opens.
8. Under **From**, you can:
  - Select **\$ANY** to allow a user group to modify the field, irrespective of the currently displayed value.
  - Select a value from the list. A user group is able to modify the selected field only when the field displays the value you select. For example, to allow a user group to edit the Status field of a defect only if "Fixed" is the current value, select **Fixed**.
9. Under **To**, you can:
  - Select **\$ANY** to allow a user group to change the field to any value.
  - Select a value from the list. A user group is able to change the value of the selected field to only the value that you specify. For example, to allow a user group to change the value of the Status field only to "Closed", select **Closed**.
10. Click **OK** to save and close the Add Transition Rules dialog box. The new rules are displayed in the Transition Rules grid.
11. To modify a transition rule, select a rule from the Transition Rules grid and click the **Edit Rule** button. In the Edit Transition Rules dialog box, modify the rule. Click **OK**.
12. To delete a transition rule, select a rule from the Transition Rules grid and click the **Delete Rule** button. Click **OK** to confirm if prompted.
13. Click **Save** to save your changes to the Groups and Permissions page.

## Owning ALM Objects

When setting group permissions, you can limit the capabilities of modifying or deleting a field value so that only the user who owns the record can change or delete the value. The following table describes the objects in ALM and the users that are defined as the owners of the objects.

ALM Object	Owner
<b>Analysis folder</b>	The <b>Owner</b> field displays the user who created the analysis folder. The owner is updated to the current user if the analysis folder is moved (cut and paste) to the user's private folders.

ALM Object	Owner
<b>Analysis item</b>	The <b>Owner</b> field displays the user who created the analysis item. The owner is updated to the current user if the analysis item is moved (cut and paste) to the user's private folders.
<b>Baselines</b>	The <b>Created By</b> field displays the user who captured the baseline.
<b>Business Components</b>	The <b>Assigned To</b> field displays the user or user group responsible for the component.
<b>Business Process Model Elements</b>	The <b>Import By</b> field displays the user who imported the business process model elements.
<b>Business Process Model Models</b>	The <b>Created By</b> field displays the user who created the business process model models.
<b>Business Process Model Paths</b>	The <b>Created By</b> field displays the user who created the business process model paths.
<b>Dashboard folder</b>	The <b>Folder Owner</b> field displays the user who created the dashboard folder. The owner is updated to the current user if the dashboard folder is moved (cut and paste) to the user's private folders.
<b>Dashboard page</b>	The <b>Page Owner</b> field displays the user who created the dashboard page. The owner is updated to the current user if the dashboard page is moved (cut and paste) to the user's private folders.
<b>Defect</b>	The <b>Assigned To</b> field displays the user to which the defect has been assigned.
<b>Favorites</b>	The <b>Owner</b> field displays the user who created the favorite.
<b>Requirement</b>	The <b>Author</b> field displays the user who created the requirement.
<b>Test in the Test Plan module</b>	The <b>Designer</b> field displays the user who created the test in the test plan module.
<b>Resource in the Test Resources module</b>	The <b>Created By</b> field displays the user who created the resource in the test resources module.
<b>Test Configuration</b>	The <b>Created By</b> field displays the user who created the test configuration.
<b>Test in the Test Lab module</b>	The <b>Responsible Tester</b> field displays the user testing the test in the test lab module.
<b>Test run in the Test Lab module</b>	The <b>Tester</b> field displays the user testing the test run in the test lab module.

**Note:** You can change the owner of an ALM object by modifying the value of **TB\_OWNER\_FIELD\_NAME** in the **Tables** table. For more information on the **Tables** table, refer to the *HP ALM Project Database Reference*.

## Hiding Data for a User Group

You can instruct ALM to hide specific records that a user group can view. You can hide records related to defects, libraries, requirements, business components, resources, tests, and test sets. Hiding records includes the following options:



- **Filtering Data.** You can set filters for specific fields, limiting the records that the user group can view. For example, you can set the filter for the field **Assigned To** to "[CurrentUser]". This instructs ALM to display only the records that are assigned to the current user.

**Note:** If you are filtering requirements for a user group according to the **Req Parent** field, all requirements under the selected parent are displayed in the requirements grid. The requirements tree does not display any requirements.

For more information on filtering, refer to the *HP Application Lifecycle Management User Guide*.

- **Defining Visible Fields.** You can select which fields in a module the user group can see and which should be hidden. Users belonging to a specific user group need to view only data that relates to their work. For example, you may want to hide the Path field in the Test Plan module from user groups that should not be able to access test scripts from the file system. You cannot hide required fields.

### To hide data:

1. In the Project Customization window, in the left pane, click **Groups and Permissions**. The Groups and Permissions page opens.
2. In the group list, choose the user group for which you want to hide data.
3. Click the **Data-hiding** tab.
4. Click the entity for which you want to hide data. For example, click **Defect**. The pane at the right displays the filters currently set and the fields currently visible in the Defects module to the users of the selected group.
5. Click the **Set Filter/Sort**  button. The Filter <entity> dialog box opens.
6. Set one or more filters. The filter determines the records that a user group can view in ALM. For more information, refer to the *HP Application Lifecycle Management User Guide*.
7. Click **OK** to close the Filter <entity> dialog box. The filters you set are displayed.
8. Click the **Set Visible Fields**  button. The Select Columns dialog box opens.
9. Click the arrows to hide or display each field.
10. Click **OK** to close the Select Columns dialog box. The fields you set as visible are displayed.
11. Click **Save** to save your changes to the Groups and Permissions page.

### Cross Project Customization

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you are working with a project that is linked to a template project, you cannot hide data for any field defined by the template project.

For user groups defined by the template project, you can hide the data of user-defined fields defined by the project. In the Groups and Permissions page, select the user group in the group list, and click the **Data-hiding** tab to determine which data is visible.

## Renaming User Groups

You can rename a user group. All customization performed on the group remains.

**Cross Project Customization - Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot rename a user group defined by the template project.

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

### To rename a user group:

1. In the Project Customization window, in the left pane, click **Groups and Permissions**. The Groups and Permissions page opens.
2. In the group list, select a group name.
3. Click the **Rename Group** button. The Rename Group dialog box opens.
4. Type a new name for the group.
5. Click **OK** to save your changes.

## Deleting User Groups

You can delete user groups that were added to an ALM project.

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

**Cross Project Customization.** If you are working with cross project customization, consider the following:

- **Working with a Template Project:** If you delete a user group from a template project, ALM does not delete the group from the linked projects. After you next apply template customization to the linked projects, the user group is no longer read-only in the project and can be modified, renamed, or deleted by the project administrator.
- **Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot delete a user group defined by the template project.


### To delete a user group:

1. In the Project Customization window, in the left pane, click **Groups and Permissions**. The Groups and Permissions page opens.
2. In the group list, select a group name.
3. Click the **Delete Group** button.
4. Click **Yes** to confirm.

## Understanding Permission Settings

You can display the permissions of user groups in the Permissions tab. You can modify the permissions of custom user groups at any time. You cannot modify the permissions of the default user groups (TDAdmin, QATester, Project Manager, Developer, and Viewer).

To display permissions for a user group, in the Groups and Permissions page, select the user group in the group list, and click the **Permissions** tab.



When Performance Center is installed, the following additional default user groups are available:

- Performance Advisor
- Performance Tester
- Performance Test Specialist

**Note: ALM Editions:** Some permission settings may not be applicable, according to the available functionality with each edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you are working with a project that is linked to a template project, you cannot modify the permissions of user groups defined in the template. You can, however, limit the records that the user group can view. For more information, see ["Hiding Data for a User Group" on page 219](#).

**Note: ALM Editions:** Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

## Customizing Module Access for User Groups

For each ALM project, you can control the modules that each user group can access. you can better utilize your ALM licenses by preventing users from accessing unnecessary modules. For example, if a user group uses ALM only to add defects to a project, you can limit the group's access to the Defects module only.


You can specify module access for the following modules: Defects, Test Plan, Test Lab, Requirements, Dashboard, Business Components, Releases, Business Process Models, and Libraries.

If access to the Business Components module is not enabled for a user group, those users can still view existing business process tests in read-only mode.

**Note: Performance Center:** Module access customization is not supported in Lab Management.

### To customize module access for user groups:

1. In the Project Customization window, in the left pane, click **Module Access**. The Module Access page opens.



The screenshot shows the 'Module Access' window. It has a 'Save' button at the top left. Below it is a table with columns for 'Users Groups' and several modules: Defects, Test Plan, Test Lab, Requirements, and Dashboard. Each cell in the table contains a checkbox. The 'Users Groups' column has a checkbox for each row. The 'Defects' column has checkboxes for TDAdmin, QATester, Project Manager, Developer, and Viewer. The 'Test Plan' column has checkboxes for TDAdmin, QATester, Project Manager, and Developer. The 'Test Lab' column has checkboxes for TDAdmin, QATester, Project Manager, and Developer. The 'Requirements' column has checkboxes for TDAdmin, QATester, Project Manager, and Developer. The 'Dashboard' column has checkboxes for TDAdmin, QATester, Project Manager, and Developer.

Users Groups	Defects	Test Plan	Test Lab	Requirements	Da
TDAdmin	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
QATester	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Project Manager	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Developer	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Viewer	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

Checkmarks indicate the modules that a user group can access.

2. To select or clear a cell in the table, select the cell's checkbox.
3. To select or clear all modules for a user group, select the checkbox in the column to the right of the user group name.
4. To select or clear all user groups for a module, select the checkbox to the left of the module name (in the same cell).
5. To select or clear all user groups for all modules, select the checkbox in the column to the right of the heading "User Groups."
6. Click **Save** to save your changes.

# Chapter 17: Customizing ALM Projects

As an HP Application Lifecycle Management (ALM) project administrator, you can customize a project to meet the specific needs of your organization. For example, you can add or customize fields, customize requirement types, and create categories and lists that reflect the needs of your project.

This chapter includes:

- [About Customizing ALM Projects](#) ..... 224
- [Customizing Project Entities](#) ..... 224
- [Customizing Project Requirement Types](#) ..... 231
- [Customizing Project Lists](#) ..... 236

## About Customizing ALM Projects

Before you begin a project, you can customize your project to reflect your unique requirements. As a project progresses, you can further adjust the project to meet its changing needs.

ALM contains system fields in which you enter information about ALM entities. You can modify the behavior of these fields by restricting users to selecting values only from associated lists, by making entry into certain fields mandatory, and by preserving a history of values entered in the field. In addition, you can include data unique to your project by creating user-defined fields. You can associate these fields with ALM system and user-defined lists.

For example, if you are running tests on several builds of an application, you can add a **Detected in Build** field to the Add Defect dialog box. You can then create a selection list containing the values **Build1**, **Build2**, and **Build3**, and associate the list with the **Detected in Build** field.

In the Requirements module, you can also assign each requirement to a requirement type. A requirement type defines which fields are available and which fields are required for a requirement of that type. This enables you to make available for a requirement only the fields relevant to the type to which it is assigned.

## Customizing Project Entities

Using the Project Entities page, you can customize your ALM project to suit your environment.

The screenshot displays the 'Project Entities' configuration window. On the left, a tree view lists various entities under the 'Test' category, with 'TS\_USER\_01' under 'User Fields' highlighted. The main panel shows the configuration for 'TS\_USER\_01'. Fields include 'Name' (TS\_USER\_01), 'Label' (TS\_USER\_01), 'Type' (Lookup List), 'Length' (255), and 'Sanitization type' (None). There are checkboxes for 'History', 'Required', 'Masked', and 'Searchable'. Below these, a 'Lookup list' section shows 'Activity Status' as the selected list, with 'New List' and 'Goto List' buttons. At the bottom, there are checkboxes for 'Verify value' and 'Allow Multiple Values'.

Each ALM project is divided into project entities. **Entities** contain data entered by users for a specific application management process. The data is stored in tables.

### Project Entities Tree

The project entities tree displays the available project entities.



Each entity contains system fields and user-defined fields:

- **System fields.** These are ALM default fields. You cannot add or delete system fields, you can only modify them.
- **User fields.** These are fields that you can define and include in an ALM project to customize for your specific project needs. You can add, modify, and delete user-defined fields.

For details, see:

- ["Adding User-Defined Fields" on page 228](#)
- ["Modifying System and User-Defined Fields" on page 228](#)
- ["Deleting User-Defined Fields" on page 229](#)

For detailed information on ALM entities and fields, refer to the *HP ALM Project Database Reference*.

## The Settings Tab

The **Settings** tab displays the field properties. The following properties are available:

Properties	Description
<b>Name</b>	Indicates the field name used in the ALM database table. Read-only.
<b>Label</b>	Indicates the field name as it is displayed in ALM. You can type a new name or use the default name. The label cannot be blank and cannot include the following characters: ( ) @ \ / : * ? " ` < >   + = ; , %
<b>Type</b>	<p>Specifies the type of data that the user can enter in the field. It includes the following types:</p> <ul style="list-style-type: none"><li>• <b>Number.</b> Enables integer entry only.</li><li>• <b>Float.</b> Enables the entry of a floating point/real number.</li><li>• <b>String.</b> Enables the entry of any character string.</li><li>• <b>Date.</b> Enables the selection of a date.</li><li>• <b>Lookup List.</b> Displays the Lookup List area and enables the selection from a drop-down list.</li><li>• <b>User List.</b> Enables the selection of a user name from your ALM users list.</li><li>• <b>Memo.</b> Enables the entry of blocks of data. Note that by default, you can add up to five memo fields to each ALM entity.</li></ul> <p>In Site Administration's Site Configuration tab, you can edit the <b>EXTENDED_MEMO_FIELDS</b> parameter, which extends the number of memo fields you can add. For more information, see <a href="#">"Setting ALM Configuration Parameters" on page 155</a>.</p>
<b>Length</b>	<p>Indicates the field size. (Available only when the <b>String</b> type is selected.)</p> <div><b>Note:</b> The maximum field length is 255 characters.</div>
<b>Sanitization type</b>	<p>Specifies the sanitization type of the field. (Available only when the <b>String</b> type is selected.) It includes the following types:</p> <ul style="list-style-type: none"><li>• <b>None.</b> Returns the value as it is stored in the database.</li><li>• <b>HTML.</b> The value is sanitized according to a predefined white list for allowed HTML content.</li><li>• <b>Text.</b> The value is HTML encoded.</li></ul>
<b>History</b>	Preserves a log of values entered in the selected field.
<b>Required</b>	Indicates that a user must enter a value for the field.

Properties	Description
	<p><b>Note:</b> If you set a field as required in a project that already contains data, users do not need to enter a value for the field when they modify an existing record if the field is already empty.</p>
<b>Masked</b>	Indicates the input data mask for the field. (Available only when the <b>String</b> type is selected.) For more information, see <a href="#">"Defining Input Masks" on page 229</a> .
<b>Versioned</b>	<p><b>Version Control:</b> Indicates whether to save field values for each version of entities/fields under version control.</p> <p>This checkbox is selected, by default, for most fields. You can turn off versioning for user-defined fields and some system fields.</p> <p><b>Note:</b> In some cases, the checkbox is disabled—for example, if the field's parent entity is not version-controlled.</p> <p><b>Tip:</b> Turning off versioning for relevant fields enables workflow scripts and OTA scripts to run without requiring entities to be checked in.</p>
<b>Searchable</b>	Indicates a searchable field. (Available only when the <b>Text Search</b> option is enabled in the DB Servers tab in Site Administration. For more information, see <a href="#">"Defining Searchable Fields" on page 154</a> .)
<b>Lookup List</b>	Includes a list of predefined lists. (Available only when the <b>Lookup List</b> type is selected.) To associate a field with a predefined list, select a list from the <b>Lookup List</b> box. To view or modify the selected list, click the <b>Goto List</b> button.
<b>New List</b>	Creates a new list. (Available only when the <b>Lookup List</b> type is selected.) To associate a field with a new list, click the <b>New List</b> button. The Project Lists dialog box opens. For more information on customizing a list, see <a href="#">"Customizing Project Lists" on page 236</a> .
<b>Goto List</b>	Displays a predefined list. (Available only when the <b>Lookup List</b> type is selected.) To open a predefined list, select a list from the <b>Lookup List</b> box. Click the <b>Goto List</b> button. The Project Lists dialog box opens. For more information on customizing a list, see <a href="#">"Customizing Project Lists" on page 236</a> .
<b>Verify Value</b>	Limits the user to select a value only from the items that are listed in the list box. (Available when <b>Lookup List</b> or <b>User List</b> is selected.)
<b>Allow Multiple Values</b>	<p>For user-defined fields, this option allows the user to select more than one value in any field that is associated with a predefined lookup list. (Available only when the <b>Lookup List</b> type is selected.) For more information, see the <b>ALLOW_MULTIPLE_VALUES</b> site parameter.</p> <p>For example, if you create a <b>Language</b> user field in the Defect entity and enable the <b>Allow Multiple Values</b> option, a user can select <b>English</b>, <b>French</b>, and <b>German</b> language values at the same time when entering this field's value.</p> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>This option is not available in the TEST STEP entity.</li> <li>If you group a data grid or summary graph by a field containing multiple values, the information in each value is grouped as its entire value. This value is the category for grouping. For example, a value with <b>English</b> and <b>French</b> is grouped once as <b>English; French</b>, and not as part of separate <b>English</b> and <b>French</b> categories.</li> </ul> <p>For more information on customizing a list, see <a href="#">"Customizing Project Lists" on page 236</a>.</p>

## Cross Project Customization

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you are working with cross project customization, consider the following:

- **Working with a Template Project:** If you are working with a template project, you use the **Project Entities (Shared)** link to customize system fields and create user-defined fields. System and user-defined fields in a template project are applied to the linked projects when you apply the template customization. For more information on applying template customization, see "[Applying Template Customization to Linked Projects](#)" on page 263.
- **Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot modify system or user-defined fields that are defined by the template project.

This section includes:

• <a href="#">Adding User-Defined Fields</a> .....	228
• <a href="#">Modifying System and User-Defined Fields</a> .....	228
• <a href="#">Deleting User-Defined Fields</a> .....	229
• <a href="#">Defining Input Masks</a> .....	229

## Adding User-Defined Fields

You can customize an ALM project by adding up to 99 user-defined fields to each ALM entity.

**Cross Project Customization:** The template project and linked projects can each contain up to 99 user-defined fields for each ALM entity.

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

### To add a user-defined field:

1. In the Project Customization window, in the left pane, click **Project Entities**. The Project Entities page opens.
2. Under **Project Entities**, expand an entity.
3. Click the **User Fields** folder.
4. To add a user-defined field, you can:
  - Click the **New Field** button to add a number, string, date, or list type field.
  - Click the **New Field** arrow and choose **New Memo Field** to add a memo field. You can add up to 5 memo fields to each ALM entity.

**Note:** In Site Administration's Site Configuration tab, you can extend the number of memo fields you can add, by editing the **EXTENDED\_MEMO\_FIELDS** parameter. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).


5. In the **Settings** tab, set properties for the field. For more information, see ["Customizing Project Entities" on page 224](#).
6. Click **Save** to save your changes to the Project Entities page.

**Note:** If you add a user-defined field in the Requirements entity, you must assign the entity to a specific requirement type. For details, see ["Customizing Requirement Types" on page 233](#).

## Modifying System and User-Defined Fields

You can modify the properties of system and user-defined fields in your ALM project.

**Note:** Certain fields cannot be modified. For example, you cannot modify the **Type** or **Length** properties for system fields. In addition, for system fields of type **Lookup List**, you cannot modify which list is associated with the field, or allow multiple values to be selected. For more information, see ["Customizing Project Entities" on page 224](#).

**Cross Project Customization:** If you are working with a project that is linked to a template project, you cannot modify system or user-defined fields that are defined by the template project. Fields defined by a template project are displayed with a template icon .

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

**To modify a system or user-defined field:**

1. In the Project Customization window, in the left pane, click **Project Entities**. The Project Entities page opens.
2. Under **Project Entities**, expand an entity.
3. Expand the **System Fields** folder or the **User Fields** folder.
4. Click the field that you want to customize. The settings for that field appear in the Settings tab.
5. Modify the properties for the selected field. For more information, see "[Customizing Project Entities](#)" on page 224.
6. Click **Save** to save your changes to the Project Entities page.

## Deleting User-Defined Fields

You can delete user-defined fields from your ALM project.

**Cross Project Customization - Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot delete user-defined fields defined by the template project.

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

**To delete a user-defined field:**

1. In the Project Customization window, in the left pane, click **Project Entities**. The Project Entities page opens.
2. Under **Project Entities**, expand an entity.
3. Expand the **User Fields** folder.
4. Click the field that you want to delete and click the **Delete Field** button.
5. Click **OK** to confirm. The field is removed from the **User Fields** folder.
6. Click **Save** to save your changes to the Project Entities page.

## Defining Input Masks

The input mask option is used to prompt users for data input using a mask pattern. If the user attempts to enter a character that conflicts with the input mask, an error occurs. For example, to prompt the user to enter a phone number, you can define the following input mask:

!(000\ )000-0000

This input mask limits the user to numeric characters only. It is displayed in an edit box as follows:

( ) -

**Note:** You can define input masks for string type fields only.

**To define an input mask:**

1. In the Settings tab, select **Masked**. For more information, see ["Customizing Project Entities" on page 224](#).
2. Under **Masked Edit Attributes**, click the **Define** button. The Input Mask Editor dialog box opens.

Name	Sample	Mask
Phone	(415)555-1212	!(999\)000-0000
Extension	15450	!99999
Social Security	555-55-5555	000\-\00\-\0000
Short Zip Code	90504	00000
Long Zip Code	90504-0000	00000\-\9999
Date	06/27/04	!99/99/00
Long Time	09:05:15PM	!90:00:00>LL
Short Time	13:45	!90:00

3. In the **Input Mask** box, type an input mask or select a predefined mask.

You can use the following characters when defining input masks:


Mask Character	Description
!	A space for a leading or trailing blank.
#	A digit.
.	A decimal.
:	A time separator.
/	A date separator.
\	Treats the next character in the mask string as a literal. For example, you can include the (, ), #, &, A, and ? characters in the mask.
>	Converts all the characters that follow to uppercase.

Mask Character	Description
<	Converts all the characters that follow to lowercase.
A	An alphanumeric character (entry required). For example: a–z, A–Z, or 0–9.
a	An alphanumeric character (entry optional). For example: a–z, A–Z, or 0–9.
C	A character (entry required). Valid values are ANSI characters in the following ranges: 32-126 and 128-255.
c	A character (entry optional). Valid values are ANSI characters in the following ranges: 32-126 and 128-255.
L	An alphabetic character or space (entry required). For example: a–z or A–Z.
l	An alphabetic character or space (entry optional). For example: a–z or A–Z.
0	A digit (entry required). For example: 0–9.
9	A digit (entry optional). For example: 0–9.
_	Inserts spaces. When the user types characters in the field box, the cursor skips the _ character.

4. In the **Test Input** box, you can test the input mask.
5. Click **OK** to close the Input Mask Editor dialog box.
6. Click **Save** to save your changes to the Project Entities page.

## Customizing Project Requirement Types

Using the Requirement Types page, you can create requirement types for your project, and customize their properties.



You can assign each requirement in the Requirements module to a requirement type. A **requirement type** defines which fields are optional and which user-defined fields are available. This enables you to create user-defined fields that are only available for requirements of a specific type.

For example, you might create a requirement type *Security Requirement* for requirements connected to security. You could then create a user-defined field *Security Hazards* containing a list of possible security hazards a requirement might cover. This field is not relevant for requirements of types other than *Security Requirement*, so you would not make it available for any type except for *Security Requirement*.

Each requirement type has an associated icon, which is displayed next to the requirement in the Requirements module tree views, enabling you to easily identify to which type a requirement belongs. For each requirement type you can determine whether test coverage and risk-based quality management are available.

In addition, for each requirement type, you can define a rich text template to be used when adding or editing rich text within the Requirements module.

Cross Project Customization

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you are working with cross project customization, consider the following:

- **Working with a Template Project:** If you are working with a template project, you use the **Requirement Types (Shared)** link to create and customize requirement types. Requirement types defined in a template project are applied to the linked projects when you apply the template customization.
- **Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot modify the default requirement types or requirement types that are defined by the template project.

This section includes:

• <a href="#">Creating Requirement Types</a> .....	233
• <a href="#">Customizing Requirement Types</a> .....	233
• <a href="#">Renaming Requirement Types</a> .....	235
• <a href="#">Deleting Requirement Types</a> .....	235



## Creating Requirement Types

You can create a requirement type. ALM provides the default requirement types **Undefined**, **Folder**, **Group**, **Functional**, **Business**, **Testing**, and **Business Model**. For more information on these types, refer to the *HP Application Lifecycle Management User Guide*.

### To create a requirement type:

1. In the Project Customization window, in the left pane, click **Requirement Types**. The Requirement Types page opens.
2. Click the **New Type** button. The New Type dialog box opens.
3. In the **Name** box, type a name for the type.
4. In the **Create As** list, assign properties of an existing requirement type.

**Tip:** Choose an existing requirement type that has similar properties to the new type you want to create. This minimizes the level of customization you need to do.

5. Click **OK**. The New Type dialog box closes and the new type is added to the Types list.
6. Click **Save** to save your changes to the Requirement Types page.

## Customizing Requirement Types

You can customize a requirement type by changing its icon, by setting options for test coverage and risk analysis, and by defining which fields are available and which are required for each requirement type. You can also define a rich text template for each requirement type.

**Cross Project Customization - Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot modify the default requirement types or requirement types defined by the template project. For requirement types defined by the template project, you can choose which user-defined fields defined in the project are available to requirements of the type.

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

### To customize a requirement type:

1. In the Project Customization window, in the left pane, click **Requirement Types**. The Requirement Types page opens.
2. Select a requirement type.
3. In the **Details** tab, you can set the following:
  - **Type Icon.** To change the icon that is displayed in Requirements module tree views, next to the requirements of the selected type, select an icon from the **Type Icon** list. The icon is changed accordingly.

**Note:** You cannot change the icon for the default requirement types **Folder** and **Group**.

- **Risk-Based Quality Management.** To set risk-based quality management for the requirements of the selected type, select one of the following options from the **Risk-Based Quality Management** box:
  - **Perform Analysis.**
  - **Perform Assessment.**
  - **None.** Select this one if you do not want to enable risk-based quality management for requirements of the selected type.

For more information on risk-based quality management, see the *HP Application Lifecycle Management User Guide*.

- **Test Coverage.** To enable or disable test coverage of the requirements of the selected type, select or clear the **Test Coverage** check box.

**Note:** You cannot clear the **Testing Coverage** check box for a requirement type if there are requirements of that type which already have test coverage. To clear, you must either delete the requirements of that type with test coverage, remove the test coverage from those requirements, or change their type.

4. In the **System Fields** tab, you can make a system field a required field for the type. Select the check box in the **Required** column for the field. Note that all system fields are automatically included in every type, and that some system fields cannot be set as optional.

**Tip:** To set all system fields as required fields at one time, select the check box next to the Required column heading.

5. In the **User Defined Fields** tab, you can choose which user fields are available for requirements of the type, and which of these fields are required:
  - To make a user-defined field available for the type, select the check box in the **In Type** column for the field. For more information on user-defined fields, see ["Customizing Project Entities" on page 224](#).
  - To make a user-defined field that is available for the type a required field, select the check box in the **Required** column for the field.
6. In the **Rich Text Template** tab, use the HTML editor to define a page layout to be displayed as the initial view in the Rich Text tab of the Requirements module. For more information on the Rich Text tab, see the *HP Application Lifecycle Management User Guide*.

**Note:**

- You can only define one template per requirement type.
- You cannot include graphics in the template. You can only add graphics from within the Rich Text tab of the Requirements module.
- The template is applied automatically to all newly created requirements of the type.
- The template can also be applied manually to existing requirements from within the Rich Text tab. Applying the template overwrites any existing content.

7. Click **Save** to save your changes to the Requirement Types page.

## Renaming Requirement Types

You can rename a requirement type. You cannot rename the following default requirement type: **Folder**.

**Cross Project Customization - Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot rename the default requirement types or requirement types defined by the template project.

ALM Editions: Cross project customization is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

**To rename a requirement type:**

1. In the Project Customization window, in the left pane, click **Requirement Types**. The Requirement Types page opens.
2. Select a requirement type.
3. Click the **Rename Type** button. The Rename Type dialog box opens.
4. Type a new name for the requirement type.
5. Click **OK** to close the Rename Type dialog box. The requirement type name is updated.
6. Click **Save** to save your changes to the Requirement Types page.

## Deleting Requirement Types

You can delete a requirement type. You cannot delete a type if there are requirements of the type in your project. To delete a type, you must first delete all requirements of the type, or change their types. You cannot delete the following default requirement types: **Folder**, **Group**, and **Undefined**.

**Cross Project Customization - Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot delete the default requirement types or requirement types defined by the template project.

ALM Editions: Cross project customization is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.


**To delete a requirement type:**

1. In the Project Customization window, in the left pane, click **Requirement Types**. The Requirement Types page opens.
2. Select a requirement type.
3. Click the **Delete Type** button.
4. Click **OK** to confirm. The requirement type is deleted.
5. Click **Save** to save your changes to the Requirement Types page.

## Customizing Project Lists

Using the Project Lists page, you can create, rename, and delete user-defined lists. For details, see:

- ["Creating Lists" on the next page](#)
- ["Renaming Lists, Items, or Sub-Items" on the next page](#)
- ["Deleting Lists, Items, or Sub-Items" on page 238](#)



A list contains items, which are values that you can enter in a field. For example, the selection list for the Languages user-defined field may contain the items **English** and **European Languages**.

The list can also contain several levels of sub-items. For example, the item **English** can contain a sublist with the sub-items **English (Australia)**, **English (Canada)**, **English (Great Britain)**, and **English (US)**.

**Performance Center:** When creating project lists in Project Customization, sub-items are not supported.

You can allow the user to select more than one value from a list by enabling the **Allow Multiple Values** option for the relevant field in the Project Entities page. For more information, see the Field Settings table in ["Customizing Project Entities" on page 224](#).

**Note:** To associate a list with a field, see ["Customizing Project Entities" on page 224](#).

### Cross Project Customization

ALM Editions: Cross project customization is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you are working with cross project customization, consider the following:

- **Working with a Template Project:** If you are working with a template project, you use the **Project Lists (Shared)** link to create and customize user-defined lists. Project lists defined in a template

project are applied to the linked projects when you apply the template customization.

- **Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot modify, rename, or delete user-defined lists that are defined by the template project.

## Creating Lists

You can create a list to be assigned to one or more fields.

### To create a list:

1. In the Project Customization window, in the left pane, click **Project Lists**. The Project Lists page opens.
2. Click the **New List** button. The New List dialog box opens.
3. Type a name for the new list (maximum length 255 characters) and click **OK**.
4. To add an item to the new list or to an existing list, select the list name and click the **New Item** button. The New Item dialog box opens. Type a name for the item and click **OK**.

**Note:** You should not use a semi-colon (";") as part of any list item if the list is to be used in a multiple value field. For more information on multiple value fields, see the Field Settings table in ["Customizing Project Entities" on page 224](#).

5. To create a sub-item, select an item and click the **New Sub-Item** button. The New Sub-Item dialog box opens. Type a name for the sub-item and click **OK**.

**Performance Center:** Sub-items are not supported.

6. Click **Save** to save your changes to the Project Lists page.

## Renaming Lists, Items, or Sub-Items

You can rename user-defined lists, and system and user-defined items or sub-items.

**Note:** You cannot change some system list items. For example, the Y and N in the **YesNo** list. For more information on system items that cannot be changed, see [HP Software Self-solve knowledge base article KM206085](http://h20230.www2.hp.com/selfsolve/document/KM206085) (<http://h20230.www2.hp.com/selfsolve/document/KM206085>).

**Cross Project Customization - Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot rename lists, items, or sub-items defined by the template project.

ALM Editions: Cross project customization is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

### To rename a list:

1. In the Project Customization window, in the left pane, click **Project Lists**. The Project Lists page opens.

2. Select a list.
3. Click the **Rename List** button. The Rename List dialog box opens.
4. Type a new name for the list.
5. Click **OK** to close the Rename List dialog box.
6. Click **Save** to save your changes to the Project Lists page.

**To rename an item or sub-item:**

1. In the Project Customization window, in the left pane, click **Project Lists**. The Project Lists page opens.
2. Select a list.
3. Select an item.
4. Click the **Rename Item** button. The Rename List Item dialog box opens.
5. Type a new name for the item. Click **OK**.
6. Click **Save** to save your changes to the Project Lists page.

## Deleting Lists, Items, or Sub-Items

You can delete user-defined lists and system and user-defined items or sub-items.

**Note:**

- You cannot delete a user-defined list that is being used as a lookup list for a field.
- You cannot delete some system list items. For example, the Y and N in the **YesNo** list. For more information on system items that cannot be deleted, see [HP Software Self-solve knowledge base article KM206085](http://h20230.www2.hp.com/selfsolve/document/KM206085) (<http://h20230.www2.hp.com/selfsolve/document/KM206085>).

**Cross Project Customization - Working with a Linked Project:** If you are working with a project that is linked to a template project, you cannot delete lists, items, or sub-items defined by the template project.

ALM Editions: Cross project customization is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

**To delete a list:**

1. In the Project Customization window, in the left pane, click **Project Lists**. The Project Lists page opens.
2. Select a user-defined list name.
3. Click the **Delete List** button.
4. Click **Yes** to confirm.
5. Click **Save** to save your changes to the Project Lists page.

**To delete an item or sub-item:**

1. In the Project Customization window, in the left pane, click **Project Lists**. The Project Lists page opens.

2. In the left pane, select a list name.
3. In the right pane, select a list item.
4. Click the **Delete Item** button.
5. Click **Yes** to confirm.
6. Click **Save** to save your changes to the Project Lists page.





# Chapter 18: Configuring Automail

As an HP Application Lifecycle Management (ALM) project administrator, you can routinely inform your personnel about defect repair activity. You determine the conditions for sending defect messages to each recipient by defining a mailing configuration.

This chapter includes:

- [About Setting Automail](#) .....242
- [Designating Automail Fields and Conditions](#) .....242
- [Customizing the Subject of Defect Mail](#) .....244

## About Setting Automail

ALM enables you to automatically notify users through email each time changes are made to specified defect fields. Configuring mail for an ALM project involves the following steps:

- Click the **Automail** link in the Project Customization window to define the defect fields and specify the users and conditions. See ["Designating Automail Fields and Conditions" below](#).
- In Site Administration's **Site Projects** tab, enable the mail configuration for a project by selecting the **Send mail automatically** check box. You must select this check box for your mail configuration to work. For more information, see ["Updating Project Details" on page 61](#).
- In Site Administration's **Site Configuration** tab, you can edit the **MAIL\_INTERVAL** parameter, which defines the time interval for sending defect emails in all projects. You can also set parameters to define the format and character set of mail, and whether attachments or history are included in the mail. For more information, see **ATTACH\_MAX\_SIZE**, **AUTO\_MAIL\_WITH\_ATTACHMENT**, and **AUTO\_MAIL\_WITH\_HISTORY**.
- You can customize the subject line of defect email for all projects or for a specific project. For more information, see ["Customizing the Subject of Defect Mail" on page 244](#).
- In Site Administration's **Site Users** tab, make sure you have specified the email addresses of the users who should receive defect messages. For more information, see ["Updating User Details" on page 126](#).

## Designating Automail Fields and Conditions

When you designate a field as a mail field, any changes made to that field cause ALM to send an email message in the next time interval. For example, suppose you designate *Status* as a mail field and then update the *Status* field for a particular defect. In the next time interval, the details of the defect, including the updated status information, are sent to designated users.

Mail conditions determine when various users receive defect messages. For each user, you can define separate mail conditions. For example, you can specify that a user receives messages only for defects assigned an urgent priority.

**To designate Automail fields and conditions:**

1. In the Project Customization window, in the left pane, click **Automail**. The Automail page opens.

Selected	User	Condition
<input type="checkbox"/>	alex_alm	<no filter defined>
<input type="checkbox"/>	alice_alm	<no filter defined>
<input type="checkbox"/>	cecil_alm	<no filter defined>
<input type="checkbox"/>	james_alm	<no filter defined>
<input type="checkbox"/>	kelly_alm	<no filter defined>
<input type="checkbox"/>	mary_alm	<no filter defined>
<input type="checkbox"/>	michael_alm	<no filter defined>
<input type="checkbox"/>	paul_alm	<no filter defined>
<input type="checkbox"/>	peter_alm	<no filter defined>
<input type="checkbox"/>	robert_alm	<no filter defined>

**Available Defect Fields** contains the names of the fields that appear in the Defects Grid.  
**Selected Defect Fields** contains the names of fields currently assigned as mail fields.

2. Choose one or more fields and click the arrow buttons (> and <) to move the fields from one list to the other. Click the double arrow buttons (>> and <<) to move all the fields from one list to the other.
3. Select the users who should receive the email by selecting the checkbox next to each user name in the **To** area in the lower half of the window.

Selected	User	Condition
<input checked="" type="checkbox"/>	alex_alm	<no filter defined>
<input checked="" type="checkbox"/>	cecil_alm	<no filter defined>
<input checked="" type="checkbox"/>	james_alm	<no filter defined>
<input type="checkbox"/>	mary_alm	<no filter defined>
<input type="checkbox"/>	paul_alm	<no filter defined>
<input type="checkbox"/>	peter_alm	<no filter defined>
<input type="checkbox"/>	shelly_alm	<no filter defined>
<input type="checkbox"/>	Detected By	<no filter defined>
<input type="checkbox"/>	Assigned To	<no filter defined>

**Tip:** To see only the relevant selected users, select the **Show Only Selected Users** checkbox.

4. Click the **Filter** button to define a filter under which the selected user receives mail. If you define multiple filters, the selected user only receives mail if all of the conditions are met. For more information on filtering, refer to the *HP Application Lifecycle Management User Guide*.
5. Click **Save** to save your changes.

## Customizing the Subject of Defect Mail

You can customize the subject line of defect email sent automatically to users, for all projects or for a specific project. For example, you can define a subject line such as the following:

```
Defect # 4321 has been created or updated - Buttons on print dialog are not aligned
```

The line can contain the values of ALM fields. To include a field value from the defect that is being sent, prefix the field name with a question mark (?). Field names must be upper-case. For example:

```
Defect # ?BG_BUG_ID has been created or updated - ?BG_SUMMARY
```

You can customize the subject line for all your projects by adding the **AUTO\_MAIL\_SUBJECT\_FORMAT** parameter in the **Site Configuration** tab. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

### To customize the subject of defect mail for a specific project:

1. In Site Administration, click the **Site Projects** tab.
2. In the Projects list, double-click the project for which you want to customize the email subject line.
3. Select the **DATACONST** table.
4. In the SQL pane, type an SQL INSERT statement to insert a row into the table with the following values:
  - In the **DC\_CONST\_NAME** column, insert the parameter name **AUTO\_MAIL\_SUBJECT\_FORMAT**.
  - In the **DC\_VALUE** column, insert the strings and the names of fields to be placed in the subject line.

For example, type the following SQL statement into the SQL pane:

```
insert into dataconst values ('AUTO_MAIL_SUBJECT_FORMAT',  
'DEFAULT.TESTPROJ - Defect # ?BG_BUG_ID has been created or updated -  
?BG_SUMMARY')
```

The subject line you define is specific to the project, so you can include the project name in the line.

For more information on modifying project tables, see ["Querying Project Tables" on page 78](#).

5. Click the **Execute SQL** button. The row is added to the **DATACONST** table to set the email subject.

# Chapter 19: Customizing Risk-Based Quality Management

This chapter describes how to customize the criteria and the constant values used in risk-based quality management.

This chapter includes:

- [About Customizing Risk-Based Quality Management](#) ..... 246
- [Customizing Risk-Based Quality Management Criteria](#) .....246
- [Customizing Risk Calculations](#) ..... 251
- [Customizing Risk-Based Quality Management Constants](#) ..... 251

# About Customizing Risk-Based Quality Management

You use risk-based quality management to determine at which Testing Level to test each requirement in the Requirements module. ALM then calculates the total estimated Testing Time for an analysis requirement based on the Testing Levels of its child assessment requirements. You compare this with the resources you have available to test the analysis requirement, and if necessary, make adjustments to the Testing Levels for the requirement and its children. This enables you to plan the testing strategy for your requirements. For more information on risk-based quality management, see the *HP Application Lifecycle Management User Guide*.

The Testing Level is determined by the requirement's Risk and Functional Complexity. Risk is comprised of the Business Criticality and Failure Probability. You determine values for these factors by assigning values to a series of criteria associated with each factor. Each criterion has a number of possible values. You can customize these criteria and values and how ALM uses them to determine the Business Criticality, Failure Probability, and Functional Complexity. For more information, see ["Customizing Risk-Based Quality Management Criteria" below](#).

You can customize how Risk is calculated from the Business Criticality and Failure Probability. For more information, see ["Customizing Risk Calculations" on page 251](#).

You can also customize which Testing Time is associated by default with each Testing Level and Functional Complexity. In addition, you can customize how ALM determines the Testing Level with which to test a requirement based on the requirement's Risk and Functional Complexity. For more information, see ["Customizing Risk-Based Quality Management Constants" on page 251](#).

In addition, you can customize for each requirement type whether requirements of the type enable risk assessment, risk analysis, or do not enable risk-based quality management. For more information, see ["Customizing Requirement Types" on page 233](#).

## Customizing Risk-Based Quality Management Criteria

You can customize the criteria used to determine the Risk and Functional Complexity of a requirement, the possible values for each criterion and the weight assigned to each value. You can then define how the total of these weights determines the Risk and Functional Complexity Categories.

**Note:** If you already calculated the Risk or Functional Complexity for a requirement, modifying these criteria does not automatically recalculate the requirement's Risk or Functional Complexity Category. To recalculate, you must reassess the requirement and change at least one of its criterion values.

This section includes:

- [Customizing criteria and Values .....247](#)
- [Customizing Weight Boundaries .....248](#)

## Customizing criteria and Values

You can customize the criteria, criterion values, and weights used by ALM to determine the Risk and Functional Complexity Categories for each requirement. Risk is comprised of the Business Criticality and Failure Probability.

ALM provides a default set of criteria when you create a new project. You can delete these criteria if you do not want to use them.

### To customize criteria and values:

1. In the Project Customization window, in the left pane, click **Risk-Based Quality Management**. The Risk-Based Quality Management page opens.
2. Click one of the following tabs:
  - To customize criteria for determining Business Criticality, click the **Business Criticality** tab.
  - To customize criteria for determining Failure Probability, click the **Failure Probability** tab.
  - To customize criteria for determining Functional Complexity, click the **Functional Complexity** tab.

The selected tab displays the relevant criteria.

The screenshot shows the 'Risk-Based Quality Management' window with the 'Business Criticality' tab selected. The window has a menu bar with 'New', 'Delete', 'Move Down', and 'Move Up'. Below the menu bar is a table with two columns: 'Criterion' and 'Value'. The 'Criterion' column lists 'Type of process', 'Impact of failure', 'Frequency of use', and 'Number/Significance of affected users'. The 'Value' column lists 'Calculation/ Validation' (weight 30), 'Data Change' (weight 18), and 'Display' (weight 8). Below the table is a text area for the 'Description of Criterion: "Type of process"'. The description states: 'The type of process represented by the requirement. This criterion has the following possible values: Calculation/ Validation - The feature represented by the requirement is an important calculation or validation. Data Change - The feature represented by the requirement modifies application data.' At the bottom, there is a section for 'Calculation of Business Criticality value based on total weights' with three radio buttons: 'C - Nice to have', 'B - Important', and 'A - Critical'. The 'C - Nice to have' radio button is selected. Below the radio buttons are three input fields for the range: '32 <= TW < 52', '52 <= TW < 76', and '76 <= TW < 120'. The 'Save' and 'Help' buttons are at the bottom right.

Criterion	Value	Weight
Type of process	Calculation/ Validation	30
Impact of failure	Data Change	18
Frequency of use	Display	8
Number/Significance of affected users		

Description of Criterion: "Type of process"  
The type of process represented by the requirement.  
This criterion has the following possible values:  
Calculation/ Validation - The feature represented by the requirement is an important calculation or validation.  
Data Change - The feature represented by the requirement modifies application data.

Calculation of Business Criticality value based on total weights

Grade: C - Nice to have | B - Important | A - Critical

Range: 32 <= TW < 52 | 52 <= TW < 76 | 76 <= TW < 120

3. To add a new criterion, select the **Criterion** list and click the **New** button. A new row is added to the end of the **Criterion** list. Type a name for the criterion in the new row.
4. To add a description for a criterion, select the criterion from the **Criterion** list and type the description in the **Description of Criterion** box. This description is displayed in the Risk tab of the Requirements module when a user assesses Business Criticality, Failure Probability, and Functional Complexity. By providing a full description of each criterion, including an explanation of its available values, you help the user decide which value to assign to each criterion for a requirement.
5. To add a value for a criterion, select the criterion from the **Criterion** list and select the **Value** list. Click the **New** button. A new row is added to the **Value** list. Type a name for the value in the new

row.

**Note:** Each value for a criterion must be unique.

6. To assign a weight to a criterion value, select the criterion from the **Criterion** list and then select the value from the **Value** list. In the **Weight** column for the value, type the weight to assign to the value.

When ALM calculates the Business Criticality, Failure Probability, or Functional Complexity of a requirement, it checks the values assigned to each criterion and calculates the sum of the corresponding weights for each value. This sum determines the Business Criticality, Failure Probability, or Functional Complexity. For more information, see ["Customizing Weight Boundaries" below](#).

7. You can delete a criterion or a value for a criterion:
  - To delete a criterion, select the criterion from the **Criterion** list and click the **Delete** button. The criterion is deleted.
  - To delete a criterion's value, select the criterion from the **Criterion** list and the value from the **Value** list. Click the **Delete** button. The value is deleted.

**Note:** Business Criticality, Failure Probability, and Functional Complexity must each have at least one associated criterion defined. In addition, each criterion must have at least one possible value.

8. To change the order in which criteria are displayed in the **Criterion** list, select a criterion and click the **Move Up** or **Move Down** buttons. Note that values for a criterion are automatically ordered by their weights.
9. Click **Save** to save your changes to the Risk-Based Quality Management page.

## Customizing Weight Boundaries

You can customize how ALM uses the values assigned to risk-based quality management criteria to determine the Business Criticality, Failure Probability, and Functional Complexity for a requirement.

### Customizing Weight Boundaries for Business Criticality

For each requirement, ALM calculates the total of the weights (**TW**) of the values assigned to each of the Business Criticality criteria. ALM then uses this total to categorize the Business Criticality of the requirement as either **C - Nice to Have**, **B - Important**, or **A - Critical**. ALM automatically calculates the highest and lowest possible total weight and uses these to define the upper boundary of the **Critical** category and the lower boundary of the **Nice to Have** category. You define the boundaries between the **Nice to Have** and **Important** categories, and between the **Important** and **Critical** categories.

For example, suppose there are two criteria for Business Criticality, each with three possible values whose weights are 20, 60, and 100. The minimum total weight is therefore 40 (if both criteria are assigned the value with weight 20) and the maximum total weight is 200 (if both criteria are assigned the value with weight 100). ALM automatically calculates these totals and uses them to determine the lower and upper boundaries for the categories. You determine the boundaries between the categories by typing 100 in the **Nice to Have** box and 160 in the **Critical** box.



Calculation of Business Criticality value based on total weights			
Grade:	<b>C - Nice to have</b>	<b>B - Important</b>	<b>A - Critical</b>
Range:	40 ≤ TW ≤ <input type="text" value="100"/>	100 ≤ TW ≤ 160	<input type="text" value="160"/> ≤ TW ≤ 200

In this example, ALM determines the Business Criticality for a requirement as follows:

- If the sum of the weights of each of the criteria for a requirement is less than or equal to 100, the requirement will have **Nice to Have** Business Criticality. This could happen, for example, if the criteria have values with weights 20 and 60, so the total weight is 80.
- If the sum is greater than 100 but less than 160, the requirement will have **Important** Business Criticality. This could happen, for example, if the criteria have values with weights 60 and 60, so the total weight is 120.
- If the sum is greater than or equal to 160, the requirement will have **Critical** Business Criticality. This could happen, for example, if the criteria have values with weights 100 and 60, so the total weight is 160.

#### To customize weight boundaries for Business Criticality:

1. In the Project Customization window, in the left pane, click **Risk-Based Quality Management**. The Risk-Based Quality Management page opens.
2. Click the **Business Criticality** tab. The Business Criticality tab displays criteria used to determine Business Criticality.
3. Under **Calculation of Business Criticality value based on total weights**, define the boundaries between different Business Criticality values. To define these boundaries, type the relevant values in the **Nice to Have** and **Critical** boxes.
4. Click **Save** to save your changes to the Risk-Based Quality Management page.

### Customizing Weight Boundaries for Failure Probability

For each requirement, ALM calculates the total of the weights (**TW**) of the values assigned to each of the Failure Probability criteria. ALM then uses this total to categorize the Probability of the requirement as either **3 - Low**, **2 - Medium**, or **1 - High**. ALM automatically calculates the highest and lowest possible total weight and uses these to define the upper boundary of the **High** category and the lower boundary of the **Low** category. You define the boundaries between the **Low** and **Medium** categories, and between the **Medium** and **High** categories.

For example, suppose there are two criteria for Failure Probability, each with three possible values whose weights are 20, 60, and 100. The minimum total weight is therefore 40 (if both criteria are assigned the value with weight 20) and the maximum total weight is 200 (if both criteria are assigned the value with weight 100). ALM automatically calculates these totals and uses them to determine the lower and upper boundaries for the categories. You determine the boundaries between the categories by typing 100 in the **Low** box and 160 in the **High** box.

Calculation of Failure Probability value based on total weights			
Grade:	<b>3 - Low</b>	<b>2 - Medium</b>	<b>1 - High</b>
Range:	40 ≤ TW ≤ <input type="text" value="100"/>	100 ≤ TW ≤ 160	<input type="text" value="160"/> ≤ TW ≤ 200

In this example, ALM determines the Failure Probability for a requirement as follows:

- If the sum of the weights of each of the criteria for a requirement is less than or equal to 100, the requirement will have **Low** Failure Probability. This could happen, for example, if the criteria have

values with weights 20 and 60 so the total weight is 80.

- If the sum is greater than 100 but less than 160, the requirement will have **Medium** Failure Probability. This could happen, for example, if the criteria have values with weights 60 and 60 so the total weight is 120.
- If the sum is greater than or equal to 160, the requirement will have **High** Failure Probability. This could happen, for example, if the criteria have values with weights 100 and 60 so the total weight is 160.

#### To customize weight boundaries for Failure Probability:

1. In the Project Customization window, in the left pane, click **Risk-Based Quality Management**. The Risk-Based Quality Management page opens.
2. Click the **Failure Probability** tab. The Failure Probability tab displays criteria used to determine Failure Probability.
3. Under **Calculation of Failure Probability value based on total weights**, define the boundaries between different Failure Probability values. To define these boundaries, type the relevant values in the **Low** and **High** boxes.
4. Click **Save** to save your changes to the Risk-Based Quality Management page.

### Customizing Weight Boundaries for Functional Complexity

For each requirement, ALM calculates the total of the weights (**TW**) of the values assigned to each of the Functional Complexity criteria. ALM then uses this total to categorize the Functional Complexity of the requirement as either **3 - Low**, **2 - Medium**, or **1 - High**. ALM automatically calculates the highest and lowest possible total weight and uses these to define the upper boundary of the **High** category and the lower boundary of the **Low** category. You define the boundaries between the **Low** and **Medium** categories, and between the **Medium** and **High** categories.

For example, suppose there are two criteria for Functional Complexity, each with three possible values whose weights are 20, 60, and 100. The minimum total weight is therefore 40 (if both criteria are assigned the value with weight 20) and the maximum total weight is 200 (if both criteria are assigned the value with weight 100). ALM automatically calculates these totals and uses them to determine the lower and upper boundaries for the categories. You determine the boundaries between the categories by typing 100 in the **Low** box and 160 in the **High** box.

Calculation of Functional Complexity value based on total weights			
Grade:	<b>3 - Low</b>	<b>2 - Medium</b>	<b>1 - High</b>
Range:	40 <= TW < 100	100 <= TW < 160	160 <= TW < 200

In this example, ALM determines the Functional Complexity for a requirement as follows:

- If the sum of the weights of each of the criteria for a requirement is less than or equal to 100, the requirement will have **Low** Functional Complexity. This could happen, for example, if the criteria have values with weights 20 and 60 so the total weight is 80.
- If the sum is greater than 100 but less than 160, the requirement will have **Medium** Functional Complexity. This could happen, for example, if the criteria have values with weights 60 and 60 so the total weight is 120.
- If the sum is greater than or equal to 160, the requirement will have **High** Functional Complexity. This could happen, for example, if the criteria have values with weights 100 and 60 so the total weight is 160.

#### To customize weight boundaries for Functional Complexity:

1. In the Project Customization window, in the left pane, click **Risk-Based Quality Management**. The Risk-Based Quality Management page opens.
2. Click the **Functional Complexity** tab. The Functional Complexity tab displays criteria used to determine Functional Complexity.
3. Under **Calculation of Functional Complexity value based on total weights**, define the boundaries between different Functional Complexity values. To define these boundaries, type the relevant values in the **Low** and **High** boxes.
4. Click **Save** to save your changes to the Risk-Based Quality Management page.

## Customizing Risk Calculations

You can define how ALM calculates the Risk value of an assessment requirement.

#### To customize risk calculations:

1. In the Project Customization window, in the left pane, click **Risk-Based Quality Management**. The Risk-Based Quality Management page opens.
2. Click the **Risk Calculation** tab.

Risk Calculation Policy			
Business Criticality	Failure Probability		
	1 - High	2 - Medium	3 - Low
A - Critical	A - High	A - High	B - Medium
B - Important	A - High	B - Medium	C - Low
C - Nice To Have	B - Medium	C - Low	C - Low

3. In the **Risk Calculation Policy** grid, you can define the Risk policy for testing a requirement.  
To define Risk calculations based on Business Criticality and Failure Probability, click the arrow next to the cell in the grid corresponding to a particular Business Criticality and Failure Probability value. Select a value. The available values are **A - High**, **B - Medium**, and **C - Low**.

## Customizing Risk-Based Quality Management Constants

You can define the default estimated Testing Times required to test a requirement with each Functional Complexity value at each Testing Level. You can also define the default Testing Level used with each Risk and Functional Complexity Category. If the user does not enter different values for a requirement in the Requirements module, ALM uses these default values when calculating the estimated Testing Time for the requirement during the risk analysis.

**Note:** Modifying these criteria does not automatically affect the results of existing risk analyses. To update the results of a risk analysis, you must perform the analysis again.

#### To customize risk-based quality management constants:

1. In the Project Customization window, in the left pane, click **Risk-Based Quality Management**. The Risk-Based Quality Management page opens.
2. Click the **Risk Constants** tab. The Risk tab displays constants used by default when calculating the Testing Time and Testing Level for a requirement.

Risk-Based Quality Management

Business Criticality | Failure Probability | Risk Calculation | Functional Complexity | **Risk Constants**

Units used to measure Testing Effort:

**Default Testing Time and Testing Levels**

Testing Time (full) per Functional Complexity:

1 - High  Hours  
2 - Medium  Hours  
3 - Low  Hours

Testing level (Full = 100%, None = 0%):

Partial  %  
Basic  %

Calculated Testing Time (in Hours):

Testing Level	Complexity		
	1 - High	2 - Medium	3 - Low
Full (100%)	18	15	12
Partial (67%)	12	10	8
Basic (34%)	6	5	4
None (0%)	0	0	0

**Default Testing Policy (in Hours)**

Risk	Complexity		
	1 - High	2 - Medium	3 - Low
A - High	Full (18)	Full (15)	Full (12)
B - Medium	Partial (12)	Partial (10)	Partial (8)
C - Low	Basic (6)	Basic (5)	Basic (4)

3. In the **Units used to measure Testing Effort** box, select the unit of measurement that you want ALM to display when measuring Testing Time. The available units are **Hours**, **Days**, **Weeks**, and **Months**.

**Note:** If you change the units of measurement for a project, the Testing Time values are not updated automatically. For example, if a requirement has Testing Time 48 hours and you change the units of measurement from **Hours** to **Days**, the requirement has Testing Time 48 days and not 2 days.

4. Under **Testing Time (full) per Functional Complexity**, for each Functional Complexity value, type the estimated time required to fully test a requirement with the Functional Complexity value. The Calculated Testing Time grid is updated to reflect these changes.
5. Under **Testing level**, in the **Partial** and **Basic** boxes, type the default Testing Time required for partial testing and basic testing of a requirement. This should be expressed as a percentage of the time required for full testing. The Calculated Testing Time grid is updated to reflect these changes.
6. In the **Default Testing Policy** grid, you can define the default Testing Level for testing a requirement.

To define the default Testing Levels, click the arrow next to the cell in the grid corresponding to a particular Risk and Functional Complexity value. Select a Testing Level from the available Testing Levels. The available Testing Levels are **Full**, **Partial**, **Basic**, and **None**. Next to each Testing Level, you can see the estimated time needed to test a requirement at that level, based on the default Testing Times and Testing Levels you defined.

7. Click **Save** to save your changes to the Risk-Based Quality Management page.

# Chapter 20: Activating Alert Rules

As an HP Application Lifecycle Management (ALM) project administrator, you can activate alert rules for your project. This instructs ALM to create alerts and send email to notify those responsible when changes occur in your project that may impact the application management process.

This chapter includes:

- [About Activating Alert Rules](#) .....254
- [Setting Alert Rules](#) ..... 254

## About Activating Alert Rules

You can keep track of your requirements, tests, and defects as you perform your application management process. When an entity changes, you can instruct ALM to notify those responsible for any associated entities.

The alert rules you can activate are based on the following associations you can create in ALM:

- You can associate a test in the test plan tree with a requirement. This is performed by creating **requirements coverage** in the Test Plan module, or by creating **tests coverage** in the Requirements module.
- You can link a test with a defect. This is performed by adding a defect during a manual test run.
- You can create **traceability links** between requirements in the Requirements module.

After you have established associations in your project, you can then track changes using these associations. When an entity in your project changes, ALM alerts you of any associated entities that may be impacted by the change.

**Version Control:** ALM alerts associated entities only when a new version is checked in. The alert indicates that the version status has changed to **Checked In**. You can then compare the new version with the previous version. For more information on comparing versions, refer to the *HP Application Lifecycle Management User Guide*.

Notification involves two steps. ALM flags the associated entity, which can be seen by all users, and then sends an email to the user responsible for the entity.

There are four alert rules you can activate:

Rule	Change Made	Entities Flagged	User Notified
1	Requirement has any change, excluding changes in the <b>Direct Cover Status</b> field and the risk-based quality management fields.	Tests covering the requirement.	Test designer. Note that only the test designer can delete the alert.
2	Defect status changes to "Fixed".	Test instances associated with the defect.	Responsible tester for the test instance.
3	Test run status changes to "Passed".	Defects linked to the test instance.	User assigned to the defect.
4	Requirement is deleted or has any change, excluding changes in the <b>Direct Cover Status</b> field and the risk-based quality management fields.	The requirement's child requirements and traced to requirements.	Author of the requirement.


For more information on alerts, refer to the *HP Application Lifecycle Management User Guide*.

## Setting Alert Rules


You can activate four alert rules. For each rule, you can choose to alert the associated entity. The alert can be seen by all users. You can also choose to send an email notification to the user responsible for the entity.

**To set alert rules:**

1. In the Project Customization window, in the left pane, click **Alert Rules**. The Alert Rules page opens.



**Alert Rules**

 Save

Select the alert rules that you want to activate. For each rule, you can choose to alert the associated entity. The alert can be seen by all users. You can also choose to send an e-mail notification to the user responsible for the entity.

Rule Description	Alert Associated Entity	Send E-mail To
When a requirement is modified, alert the associated tests.	<input type="checkbox"/>	<input type="checkbox"/> Test Designer
When a defect status changes to "Fixed", alert the associated test instances.	<input type="checkbox"/>	<input type="checkbox"/> Responsible Tester
When a test runs successfully (status changes to "Passed"), alert the linked defects.	<input type="checkbox"/>	<input type="checkbox"/> Assigned To
When a requirement is modified or deleted, alert traced to requirements and child requiremen...	<input type="checkbox"/>	<input type="checkbox"/> Author

2. Select **Alert Associated Entity** to activate a rule. This instructs ALM to flag the entity when the associated entity changes.
3. Select **Send E-mail To** to instruct ALM to send a notification email to the specified user when the associated entity changes.
4. Click **Save** to save your changes.





# Chapter 21: Cross Project Customization

As an HP Application Lifecycle Management (ALM) template administrator, you use cross project customization to apply customization from a template project to one or more ALM projects. Cross project customization enables you to standardize policies and procedures across projects in your organization.

ALM Editions: Cross project customization is not available for Quality Center Enterprise Edition. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

This section includes:

- [About Cross Project Customization](#) ..... 258
- [Cross Project Customization Overview](#) ..... 259
- [Updating Linked Projects](#) ..... 260
  - [Updating Linked Project Details](#) ..... 261
  - [Verifying Cross Project Customization](#) ..... 262
  - [Applying Template Customization to Linked Projects](#) ..... 263
- [The Cross Project Customization Report](#) ..... 265
- [Updating Linked Template Details](#) ..... 266

## About Cross Project Customization

Cross project customization enables you to use a **template project** to define and maintain a common set of project customizations for multiple projects.

**Note:** Cross project customization cannot be implemented between a Unicode template project and ASCII projects. Also, when a template project is converted to Unicode, any linked ASCII projects cannot receive customization changes from the template.

A **template administrator** is any user that is assigned project administrator permissions for a template project. As template administrator, you can customize a template project to meet the needs of your organization.


You link a template project to one or more ALM projects. This enables you to apply template customization to the **linked projects**. As the needs of your organization change over time, you can update the customization in your template project, and then reapply the template customization to the linked projects.

A template project can be used to create additional projects or templates. When the Site Administrator creates a project or template based on a template project, the template customization is copied to the newly created project or template.

**Product Feature Movie:** To view a movie that demonstrates how to work with cross project customization, choose **Help > Movies** in the ALM main window.

## Cross Project Customization Overview

Implementing cross project customization involves the following steps:



- **Creating a Template Project.** The site administrator creates template projects and assigns template administrators in Site Administration. For more information, see ["Creating Template Projects" on page 41](#).
- **Linking the Template to Projects.** The site administrator selects projects to link to a template in Site Administration. For more information, see ["Linking a Template to Projects" on page 60](#).
- **Customizing the Template Project.** As template administrator, you customize a template project to meet the policy needs of your organization. The template customizations that are applied to linked projects include: user groups and permissions, module access, project entities, project requirement types, project lists, PPT, report templates, and workflow.
- **Verifying Cross Project Customization.** Before applying template customization to linked projects, you must verify that ALM can successfully apply customization from the template to the projects. For more information, see ["Verifying Cross Project Customization" on page 262](#).
- **Applying Customization to Linked Projects.** After defining or updating customization in the

template, you apply the customization to the linked projects. For more information, see ["Applying Template Customization to Linked Projects" on page 263](#).

### Cross Project Customization Examples

The following examples demonstrate how you can use cross project customization:

- **Set a standard for working with defects.**  
The QA manager wants to limit how testers can modify defects. For example, you want to allow testers to modify the status of defects to `Fixed`, but not to `Closed`, to allow the QA manager to review the defect before closing it. You can create a customized user group for testers in your template and set transition rules for the group. After applying the template customization to the linked projects, all testers can be assigned to this group.
- **Enable consistent reporting by managers.**  
Managers in all divisions of your organization are required to report on a standard set of measures, such as defect status or priority, or coverage status of requirements. As template administrator, you can customize project lists and fields, and set required fields in a template. Applying the template customization to the linked projects provides users with a common set of fields and values for consistent reporting.
- **Create unique policies for separate sectors of an organization.**  
Your organization has acquired a new company. The new company has a standard policy for working with defects, which is different from how your organization currently operates. Both sectors want to maintain their current policies. You can customize a template for each sector of your organization, and link each to the relevant projects for its sector.

## Updating Linked Projects

You manage template customization updates to linked projects in Project Customization.

This section includes:


- [Updating Linked Project Details](#) .....261
- [Verifying Cross Project Customization](#) .....262
- [Applying Template Customization to Linked Projects](#) .....263

## Updating Linked Project Details

You update linked project details in Project Customization.

### To update linked project details:



1. Log into ALM using the template project.
2. In the Project Customization window, in the left pane, click **Cross Project Customization**. The Cross Project Customization - Linked Projects page opens.



3. In the Linked Projects grid, view the projects linked to the template project. The Linked Projects grid contains the following information for each project:

Column	Description
	Indicates a request by the project administrator not to apply template customization changes to the project.
<b>Domain</b>	The domain of the linked project.
<b>Project</b>	The name of the linked project.
<b>Updated</b>	Indicates if the linked project is updated with current template customization. The current status can be one of the following: <ul style="list-style-type: none"> <li> <b>Not Updated</b> (default)</li> <li> <b>Updated</b></li> </ul>
<b>Verified</b>	Indicates if template customization has been verified and can be successfully applied to the linked project. By default, the status is <b>Not Verified</b> . The current status can be one of the following: <ul style="list-style-type: none"> <li> <b>Not Verified</b> (default)</li> <li> <b>Verified with Warnings</b></li> <li> <b>Verified</b></li> </ul>

Click on a column heading to change the sort order of the projects in the grid.

4. To refresh the data in the Linked Projects grid, click the **Refresh** button .
5. View additional details about a selected project on the right side of the Linked Projects page. For example, under **Project Status**, view the status of the project. If the project administrator has selected the **Request Suspension of Apply Customization** option in the linked project, **Requested suspension of Apply Customization** is displayed. The template administrator can choose to exclude the project from template customization updates.
6. In the **Comments** box, view comments added by the project administrator. Click **Add Comment** to add a comment to the project. The project administrator can view and add comments when viewing the project details.
7. Under **Project Details**, the names of project administrators are displayed. Click the **Send E-mail** button  to send mail to project or template administrators.
8. Under **Last Applied Customization**, view the date that template customization was last applied to the linked project. Click the **Applied Customization Report** link to view details. For more information, see ["The Cross Project Customization Report" on page 265](#).
9. Under **Last Verification**, view the date of the last verification. Click the **Verification Report** link to view details of the last verification. For more information, see ["The Cross Project Customization Report" on page 265](#).


## Verifying Cross Project Customization

Before you can apply template customization to linked projects, you must verify the customization. The verification process checks that ALM can successfully apply template customization to the linked projects. Verification must complete successfully before ALM can apply template customization to a linked project.

**Note:** For verification to complete successfully, the appropriate extensions must be enabled in linked projects. If an extension is enabled for a template project, the extension must also be enabled for the template's linked projects. Linked projects can have additional extensions enabled. For more information on enabling extensions, see ["Enabling Extensions for a Project" on page 67](#).

### To verify cross project customization:

1. In the Project Customization window, in the left pane, click **Cross Project Customization**. The Cross Project Customization - Linked Projects page opens.



2. Select a project from the grid, or press the CTRL key and select multiple projects. To display only those projects that are activated, select **Show only active projects**.
3. Click **Verify**. The Verification dialog box opens and displays progress.
4. To stop verification before it completes, click **Stop**. ALM completes the project that it is currently verifying and then stops. The remaining projects are not verified.
5. Click **Details** to view additional information during or after verification. When verification completes, click the **Report** link to view detailed results for a project.
6. When verification completes, click **Close** to close the Template Verification dialog box. The verification status for the projects is updated in the Linked Projects grid.
7. Under **Last Verification**, click the **Verification Report** link to view details of the verification. For more information, see ["The Cross Project Customization Report" on page 265](#).

## Applying Template Customization to Linked Projects

You can apply template customization to projects linked to the template. This applies the following customization: groups and permissions, module access, project entities, project requirement types, project lists, PPT, report templates, and workflow. When you apply template customization, the applied customization is set to read-only in the linked projects and cannot be edited.


### Note:

- When a new project is created based on a template and linked to the template, you must apply template customization in order to set the template customization as read-only in the linked project. For more information on creating a project based on a template, see ["Creating Projects" on page 24](#).
- The option for setting a report template as default is not applied to linked projects and can be set by a project administrator in the linked project.

Before you can apply template customization, you must verify the customization. For more information, see ["Verifying Cross Project Customization" on the previous page](#). Verification must complete successfully before ALM can apply template customization to a linked project.


### To apply template customization to linked projects:

1. In the Project Customization window, in the left pane, click **Cross Project Customization**. The Cross Project Customization - Linked Projects page opens.



2. Select a project from the grid, or press the CTRL key and select multiple projects. To display only those projects that are activated, select **Show only active projects**.
3. Click **Apply Customization**. If the project administrator of any of the selected projects has requested not to apply template customization changes, a warning is displayed. Click **OK** to apply template customization to all selected projects.

The Apply Customization Initialization dialog box opens.



4. Select **Send mail notification to project administrators** to instruct ALM to notify project administrators after the process completes.
5. Click **OK**. The Apply Customization dialog box opens and displays progress.
6. To cancel the process for projects that ALM did not yet update, click **Stop**. ALM completes the update to the current project and cancels the update to the remaining projects.
7. When the process completes, click **Close** to close the Apply Customization dialog box.
8. Under **Last Applied Customization**, click the **Applied Customization Report** link to view details of applied template customization. For more information, see "[The Cross Project Customization Report](#)" on the next page.



## The Cross Project Customization Report

The Cross Project Customization Report provides detailed results of the verification process, or of template customization applied to linked projects. For more information on verification, see ["Verifying Cross Project Customization" on page 262](#). For more information on applying template customization, see ["Applying Template Customization to Linked Projects" on page 263](#).

There are two types of Cross Project Customization Reports:

- **Verification Report.** Provides results of verification for the linked project.
- **Applied Customization Report.** Provides results of template customization applied to the linked project.

The Applied Customization Report includes the following sections:

- **Report Details.** Contains details about the type of report, the template, the linked project, the number of changes verified or applied to the linked project, and results.
- **Report by Customization Category.** A listing of all changes verified or applied to the linked project. This section lists changes by customization category including user groups, project entities, project lists, requirement types, and workflow scripts.

Report results are classified into several categories as follows:

Result category	Verification Report	Applied Customization Report
<b>Successful</b>	The change can be successfully applied to the linked project.	The change was successfully applied to the linked project.
<b>Warning</b>	<p>The change can be applied to the linked project, but may result in data loss.</p> <p>For example:</p> <ul style="list-style-type: none"><li>• reducing the length of a string type field</li><li>• deleting a user-defined field</li><li>• defining a field to be searchable and the <b>Text Search</b> option is not available in the linked project</li><li>• disabling test coverage for a requirement type while there are tests covering requirements of the type</li></ul>	The change was applied to the linked project but may have caused data loss.
<b>Failure</b>	<p>The change cannot be applied to the linked project.</p> <p>For example:</p> <ul style="list-style-type: none"><li>• Changing a field type from <b>Memo</b> type to <b>Number</b>, <b>String</b>, or <b>Date</b> type or the reverse.</li><li>• Naming a new field, or renaming an existing field, with a field name that already exists in the linked project.</li><li>• The report is too large for the default limit query size. For details, see the <b>MAX_QUERY_LENGTH</b> site parameter.</li></ul>	An error occurred during the Apply Customization process. The change was not successfully applied to the linked project.

**Tips:**

- To easily locate warnings or errors in the Cross Project Customization Report, click the **Find** button to open the browser's search tool, and search for the word **warning** or **error**.
- To preserve formatting when mailing a report to another user, save the file as an HTML archived web page by saving it with the **.mht** file extension.
- If transition rules are set for user groups in the linked or template projects, each rule is listed in the **Transition Rule** column in the format **<from state>, <to state>**. For example, **New, Open** **New, Rejected** **Open, Fixed** **Open, Rejected** indicates that the user group can change the field value from **New** to **Open** or **Rejected**, and from **Open** to **Fixed** or **Rejected**.

## Updating Linked Template Details

If you are working with a project that is linked to a template project, you can view details about the project and about the template project from the Linked Template page. You can view details about template customization applied to the project, send email to the template administrator, check for conflicts between customization in the project and customization in the template project, or make a request to block template customization updates.

**To update linked template details:**

1. Log into ALM using a project that is linked to a template.
2. In the Project Customization window, in the left pane, click **Cross Project Customization**. The Cross Project Customization - Linked Template page opens.

**Cross Project Customization**

Save Verify Send E-mail... Refresh

**Project Status**

Not Updated

☐ Request suspension of Apply Customization

Comments: [Add Comment](#)

**Template Details**

Template name: NEW\_DOMAIN\Template\_Demo

Template administrators: Alex Smith


**Last Applied Customization**

Date: N/A Applied Customization Report

**Last Verification**

Date: 7/21/2010 8:29:10 PM [Verification Report](#)

3. Under **Project Status**, view the following status information:
  - **Updated.** Customization in the template project is applied to the project.
  - **Not Updated.** Changes made to customization in the template project have not been applied to the project.

4. Select **Request suspension of Apply Customization** to make a request to block template customization updates. The request is displayed in the template project, and the template administrator can choose to exclude the project from template customization updates.
5. Click **Add Comment** to add a comment to the project. The comment is displayed in the Comments box. The Comments box also displays comments made by the template administrator. The template administrator can add and view comments when reviewing linked project details in the template project.
6. Under **Template Details**, view the name of the template project linked to the project, and the names of the template administrators. To send email to the project or template administrators, click the **Send E-mail** button .
7. Under **Last Applied Customization**, view the date of the last time template customization was applied to the project. Click the **Applied Customization Report** link to view details. For more information, see ["The Cross Project Customization Report" on page 265](#).
8. Under **Last Verification**, view the date of the last time customization was verified for the project. Click the **Verification Report** link to view details. For more information, see ["The Cross Project Customization Report" on page 265](#).
9. Click the **Verify** button to verify cross project customization for the project. For example, if you make changes to project customization, you can run template verification to check for conflicts between customization in the project and customization in the template project.
10. Click **Details** to view additional information during or after verification. When verification completes, you can click the **Report** link to view detailed results for the project.
11. When verification completes, click **Close** to close the Verification dialog box.



# Chapter 22: Customizing Project Planning and Tracking KPIs

This chapter describes how to customize KPIs for project planning and tracking (PPT).

ALM Editions: The Project Planning and Tracking link in Project Customization is available for ALM Edition only. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

This chapter includes:

- [About Customizing PPT KPIs](#) .....270
- [Project Planning and Tracking Page](#) ..... 270
- [Project Planning and Tracking - General Tab](#) .....271
- [Configure Transitions Dialog Box](#) .....273
- [Project Planning and Tracking - KPI Analysis Tab](#) .....274

# About Customizing PPT KPIs


PPT collects data from the milestones of your release using key performance indicators (KPIs). A **KPI** is a quantifiable measure designed to track a critical performance variable over time, and measure the essential outcome of quality assurance activities. You can customize each KPI to reflect your needs. You can customize system-defined KPIs or create user-defined KPIs.

When analyzing the overall health and deployment readiness of your release in the PPT scorecard, you can further enhance your output by customizing the KPI graphs displayed in your scorecard.

For more details on PPT, refer to the *HP Application Lifecycle Management User Guide*.





## Project Planning and Tracking Page

This page enables you to customize the PPT KPIs.



To access	In Project Customization, in the left pane, click <b>Project Planning and Tracking</b> .
Important information	ALM Editions: The Project Planning and Tracking tab is available for ALM Edition only. For more information about ALM editions and their functionality, see the <i>HP Application Lifecycle Management User Guide</i> .
See also	<a href="#">"About Customizing PPT KPIs" above</a>

User interface elements are described below (unlabeled elements are shown in angle brackets>):

UI Elements	Description
 Save	Saves your changes to the Project Planning and Tracking page.
 New	Opens the New KPI Type dialog box enabling you to define a new KPI by specifying a KPI name, an entity type, and measurement type.
 Create As	Opens the Create As dialog box enabling you to create a KPI based on a selected KPI.
 Delete	Deletes the selected KPI from the KPI Types list.  <b>Note:</b> A KPI type in use cannot be deleted.
<KPI types list>	Lists available KPI types.
Filter By	KPI types associated with the selected entity type are displayed in the KPI type list. To view all KPI types, select <b>None</b> .
General tab	Displays the properties of a selected KPI type. For more details, see <a href="#">"Project Planning and Tracking - General Tab" below</a> .
KPI Analysis tab	Displays the KPI drill down properties of a selected KPI type. For more details, see <a href="#">"Project Planning and Tracking - KPI Analysis Tab" on page 274</a> .

## Project Planning and Tracking - General Tab

This tab enables you to customize the properties of a selected KPI type.

General

KPI Analysis

Name:

Authored Tests

Entity Type:

Test

Description:

Number of tests authored, with status Ready.

Threshold Settings

KPI is better when values are:

Higher

Default Threshold OK Above :

80

Warning Range:

10

%

Measurement

Measurement Type:

Count

Function:

☒ Count
 ☐ Sum values of field:

Measured Entities:

Filter: Status[Ready]

☐ Consider Transitions
 

Configure...

<b>To access</b>	In Project Customization, in the left pane, click <b>Project Planning and Tracking</b> . Select a KPI type. The KPI properties are displayed in the General tab.
<b>Important information</b>	ALM Editions: The Project Planning and Tracking tab is available only for ALM Edition. For more information about ALM editions and their functionality, see the <i>HP Application Lifecycle Management User Guide</i> .

## General Area

User interface elements are described below:

UI Elements	Description
<b>Name</b>	The name of the selected KPI.
<b>Entity Type</b>	The entity type of the selected KPI. Possible values are <b>Requirement</b> , <b>Test</b> , <b>Test Instance</b> , and <b>Defect</b> .
<b>Description</b>	The description of the selected KPI.

## Threshold Settings Area

User interface elements are described below:

UI Elements	Description
<b>KPI is better when values are</b>	The expected growth direction of the values of the selected KPI. The <b>higher</b> or <b>lower</b> the value, the better it is. <b>Default value:</b> Higher
<b>Default Threshold OK Above/Below</b>	A value greater than the specified amount indicates a good KPI state.
<b>Warning Range</b>	A percentage value relevant to the <b>OK Above/Below</b> threshold. If a KPI is better when a value is higher and the <b>OK Above</b> threshold is set to <b>100</b> , and the warning range is set to <b>10%</b> , then any value between <b>90</b> and <b>100</b> will trigger a warning. Any value below <b>90</b> indicates a bad KPI state.

## Measurement Area




This area enables you to define how to measure the KPI values.

<b>Important information</b>	When defining the properties for the <b>Percentage</b> measurement type, the <b>Measure percentage of</b> section indicates the numerator to be used for percentage calculations. The <b>Out of</b> section indicates the denominator to be used for percentage calculations.
------------------------------	---

User interface elements are described below:


UI Elements	Description
<b>Measurement Type</b>	The method of measurement.
<b>Function</b>	Indicates one of the following:



UI Elements	Description
	<ul style="list-style-type: none"> <li>• <b>Count.</b> Counts the number of entities.</li> <li>• <b>Sum values of field.</b> Totals the values of a specified field for all the entities.</li> </ul>
<b>Measured Entities</b>	<p>Enables you to filter on entities of the type specified for the selected KPI:</p> <ul style="list-style-type: none"> <li>•  <b>Set Filter/Sort.</b> Opens the Filter dialog box enabling you to define a filter. For more details, see the <i>HP Application Lifecycle Management User Guide</i>.</li> <li>•  <b>Clear Filter.</b> Clears the defined filter.</li> </ul>
<b>Consider Transitions</b>	<p>Enables the <b>Configure</b> button.</p> <p>When transitions are configured, the KPI aggregates field changes instead of counting the changes.</p>
	<p>Opens the Configure Transitions dialog box, enabling you to define how field changes are counted when measuring KPI values. For more details, see "<a href="#">Configure Transitions Dialog Box</a>" below.</p>

## Configure Transitions Dialog Box

This dialog box enables you to define how field changes are aggregated when measuring KPI values.




The **Configure Transitions** dialog box is shown. It has a title bar with a close button. Inside, there are several sections:

- Measure changes in field:** A dropdown menu currently showing "Status".
- When value changes:**
  - from:** A text box containing "\$ANY" and an "Update List..." button.
  - to:** A text box containing "\$ANY" and an "Update List..." button.
- Accumulate changes:** Three radio buttons:
  - ☒ On a daily basis
  - ☐ For the duration of the milestone
  - ☐ For the duration of the release

At the bottom are "OK" and "Cancel" buttons.

<b>To access</b>	In Project Customization, in the left pane, click <b>Project Planning and Tracking</b> . Select a KPI type. In the <b>General</b> tab, select <b>Consider Transitions</b> and click the <b>Configure</b> button.
<b>Important information</b>	ALM Editions: The Project Planning and Tracking tab is available only for ALM Edition. For more information about ALM editions and their functionality, see the <i>HP Application Lifecycle Management User Guide</i> .

User interface elements are described below:

UI Elements	Description
<b>Measure changes in field</b>	Indicates the field used for aggregating field value changes.
<b>When value changes from</b>	Aggregates when the value changes from the specified field value. The value <b>\$ANY</b> aggregates irrespective of the currently displayed value.
<b>When value changes to</b>	Aggregates when the value changes to the specified field value. <b>\$ANY</b> aggregates irrespective of the currently displayed value.
	Opens the Measure Values dialog box, enabling you to select the values to be used when measuring changes.
<b>Accumulate changes</b>	Enables you to aggregate changes on a daily basis; for the duration of a milestone; or for the duration of a release.

## Project Planning and Tracking - KPI Analysis Tab

This tab enables you to define two additional breakdown graphs for inclusion in the KPI Drilldown graph. For more details, see the *HP Application Lifecycle Management User Guide*.

General KPI Analysis

In the Scorecard tab of the Releases module, you can click a cell in the scorecard to display the progress of a KPI as a graph. This graph page can contain up to two additional graphs. In this tab you can customized the graph page and determine whether or not to display these additional graphs.

☒ Graph 1

Name: Defects Grouped by Status

Function: ☒ Count ☐ Sum values of field: [dropdown]

Measured Entities: [text area]

Group By: Status

☐ Bar ☒ Pie ☐ Grid

☒ Graph 2

Name: Defects by Severity

Function: ☒ Count ☐ Sum values of field: [dropdown]



Measured Entities: Filter: Status[New Or Open Or Reopen]

Group By: Severity

☒ Bar ☐ Pie ☐ Grid

<b>To access</b>	In Project Customization, in the left pane, click <b>Project Planning and Tracking</b> . Select a KPI and click the <b>KPI Analysis</b> tab.
<b>Important information</b>	ALM Editions: The Project Planning and Tracking tab is available only for ALM Edition. For more information about ALM editions and their functionality, see the <i>HP Application Lifecycle Management User Guide</i> .

User interface elements are described below:

UI Elements	Description
<b>Graph 1/Graph 2</b>	Enables/disables the graph.
<b>Name</b>	The name of the graph.
<b>Function</b>	Choose one of the following: <ul style="list-style-type: none"><li>• <b>Count.</b> Counts the number of entities.</li><li>• <b>Sum values of field.</b> Totals the values of a specified field for all the entities.</li></ul>
<b>Measured Entities</b>	Enables you to filter on entities of the type specified for the selected KPI: <ul style="list-style-type: none"><li>•  <b>Set Filter/Sort.</b> Opens the Filter dialog box enabling you to define a filter. For more details, see the <i>HP Application Lifecycle Management User Guide</i>.</li><li>•  <b>Clear Filter.</b> Clears the defined filter.</li></ul>
<b>Group By</b>	Determines the fields by which ALM groups data in the graph.
<b>Bar/Pie/Grid</b>	Indicates the type of graph.



# Chapter 23: Project Report Templates

Project report templates determine the layout and style in which data is displayed in project reports.

For more details on project reports, refer to the *HP Application Lifecycle Management User Guide*.

This chapter includes:

- [About Project Report Templates](#) ..... 278
- [Managing Project Report Templates](#) ..... 278
- [Designing Report Templates](#) ..... 281

# About Project Report Templates

Project report templates are Microsoft Word files that determine the design of project reports. Users assign templates to project reports in the **Analysis View** module.

In the **Project Report Templates** page, as a project administrator, you manage report templates that are available to all project users.

**Note:**

- Depending on permissions, users can create and use custom report templates, in addition to the project report templates. For more information on custom templates, refer to the *HP Application Lifecycle Management User Guide*.
- Template fonts need to be installed on the client machine of the user generating the report in order for them to be properly visible in the generated document.

There are various types of templates that affect different aspects of template reports:

Template Type	Description
Document Templates	Define the outline of the report layout. For example, a document template dictates the design of the title page, whether the report includes a table of contents, page orientation, page numbering, and more.
Style Templates	Define the formatting (for example, tables, section headings, paragraphs) applied to Microsoft Word styles.
History Templates	Define the format in which history information is displayed in report sections.
Section Templates	Define the fields that are included in report sections, and the format in which they are displayed. Section templates are defined separately for each ALM entity.

Predefined templates are provided for each of the template types.

For more information on managing project report templates in Project Customization, see "[Managing Project Report Templates](#)" below.

You design report templates in Microsoft Word using the **Template Creator**. For more information, see "[Designing Report Templates](#)" on page 281.

# Managing Project Report Templates

As an ALM project administrator, you manage the templates that are available to project users for creating project reports.

This section includes:

- [Creating a New Report Template](#) ..... 279
- [Editing a Report Template](#) ..... 280


- [Duplicating a Report Template](#) ..... 280
- [Deleting a Report Template](#) ..... 280

## Creating a New Report Template

You can create a new report template, and make it available for users to assign to project reports.

**To create a new report template:**

1. In Project Customization, in the left pane, click **Project Report Templates**. The Project Report Template page opens.



2. In the templates tree, select a template type or category of the template you want to create.
3. Click the downward arrow on the **Template Creator** button, and select one of the following:
  - **Create From Default Style Template.** Creates a template file using the default style template. This is the default option if you click the button.
  - **Create From Style Template.** Creates a template file using a selected style template.
4. Design a new template file in Microsoft Word using the Template Creator tab. For details on designing template files, see ["Designing Report Templates" on page 281](#).
5. Save and close the file.
6. In Project Customization, in the left pane, click **Project Report Templates**, and select a template category.
7. Click **Add Template**, and select the template file that you created. The following fields are displayed for the project report template:

UI Elements	Description
<b>Name</b>	The name of the project report template.
<b>Last Modified By</b>	The name of the ALM user who last made changes to the project report template.
<b>File Modified Date</b>	The date and time on which changes were last made to the project report template.

UI Elements	Description
<b>Type</b>	Indicates whether the project report template is a full page or tabular template. <b>Full Page.</b> Defines the layout of ALM entity records on a page. <b>Tabular.</b> Defines the layout of ALM entity records in a table.

8. To set the new template as the default template for the category, select **Default <Category> Report Template**. When a user adds a section to a report, the default project template for the entity is initially selected.

## Editing a Report Template

You can make changes to an existing report template.

### To edit a report template:

1. In Project Customization, in the left pane, click **Project Report Templates**.
2. Select the template you want to edit, and click **Download Template**. A copy of the template file is saved on your computer file system, and the file opens in Microsoft Word.
3. Edit the template using the Template Creator tab. For details on designing template files, see ["Designing Report Templates" on the next page](#).
4. Save and close the template file.
5. In Project Customization, select the template, and click **Upload Template**.
6. Select the template file on your computer file system.

## Duplicating a Report Template

You can create a duplicate of a report template, and modify the duplicate template.

### To duplicate a template:

1. In Project Customization, in the left pane, click **Project Report Templates**.
2. Select the template you want to duplicate, and click **Duplicate**.
3. To edit the duplicated template, see ["Editing a Report Template" above](#).
4. To set the new template as the default template for the category, select **Default <Category> Report Template**.

## Deleting a Report Template

You can delete a report template.

**Note:** You cannot delete a template that is set as the default template in its category, or that is being used by one or more project reports.

### To delete a template:



1. In Project Customization, in the left pane, click **Project Report Templates**.
2. Select the template you want to delete, and click **Delete**.

# Designing Report Templates

Report templates are Microsoft Word files that contain the outline of report sections.

**Note:** Complete examples of report templates are provided in Project Customization. For more information, see ["Managing Project Report Templates" on page 278](#).

This section includes:

- [About Designing Report Templates](#) .....282
- [Designing Document Templates](#) .....282
- [Designing Style Templates](#) .....283
- [Designing History Templates](#) .....283
- [Designing Section Templates](#) .....285
- [Guidelines for Creating Full-Page and Tabular Templates](#) ..... 287
- [Template Creator Tab](#) .....288

## About Designing Report Templates

You design report template files in Microsoft Word. Document, history, and section templates are created using the **Template Creator** tab in Microsoft Word.

With the template creator, you select and arrange merge fields in a Microsoft Word document. **Merge fields** represent ALM field labels and values, or contain instructions for building the report. When you generate a report, the merge fields in the report templates are replaced by actual data.

For details on the template creator options, see ["Template Creator Tab" on page 288](#).

**Note:** To enable the template creator:

- Microsoft Office 2010 (32 bit) or Microsoft Office 2013 (32 bit) must be installed on your machine.
- You must allow macros in Microsoft Word. In Word, click the **Office Button**, and then click **Word Options**. Select **Trust Center** > **Trust Center Settings** > **Macro Settings**. Select **Enable all macros**.


## Designing Document Templates

In Document template files you define the outline of the report layout. For example, a Document template dictates the design of the title page, whether the report includes a table of contents, page orientation, page numbering, and more. You design document templates using the Template Creator tab in Microsoft Word.

The following elements are used in Document templates:


- **ReportName.** A merge field that is replaced in reports by the value of the report's **Name** field.
- **Custom fields.** Merge fields that represent information you want users to include in reports, for example `Author`, `Project`. You can use any string as a custom field. Users type actual values for custom fields when configuring project reports.
- **DocumentData.** A merge field that marks the point at which the report sections begin.
- **Document design.** Document formatting that you define in a Document template is used in project reports that use the Document template. This includes headers and footers, page numbers, and page layout.
- **Fixed text.** Fixed text that you type in a Document template is displayed in reports. For example, type your organization name on the cover page, or type `Created by:` before the custom field `Author`.

**To design a new Document template:**


1. Create a new template file using the template creator in Microsoft Word. For more information on accessing the template creator, see ["Template Creator Tab" on page 288](#).
2. Click **Template Type** , and select **Document**.
3. To include the report name, click **Insert Field Value** , and select **ReportName**. The

`ReportName` tag retrieves the report name from the **Name** field of the template based report.

4. To include customized information in areas such as the title page, headers and footers, click

**Insert Custom Field** . In the Custom Field dialog box, enter a custom field name (for example, Author). When you create a report, you enter actual values that are displayed on the report cover page.

Repeat the step to include additional custom fields.

5. Design the document with elements such as headers, footers, and page numbers.
6. Place the cursor at the point at which report data should begin, click **Insert Field Value** , and select **DocumentData**.

## Designing Style Templates

In Style template files you define the formatting that is applied to Microsoft Word styles in all sections of a report.

For example, in a Style template you define the formatting for the `Normal` style. As a result, text in section templates that is assigned the `Normal` style, is displayed in the format you defined in the Style template.

Style formatting that is defined in the Style template overrides the formatting defined in other templates used in a project report.

Consider the following for designing Style templates:

- **Heading styles.** The `Heading 1`, `Heading 2`, `Heading n` styles that you define in a Style template are automatically applied to report sections according to the level of the section in the report. For more details on applying heading styles in section templates, see ["Designing Section Templates" on page 285](#).
- **Table styles.** To ensure a uniform style for all data tables displayed in a report, define the **Project Report Table Style**. By default, tables you create in tabular templates use this style.
- **Text.** Any text that you type in a Style template is ignored by project reports.

## Designing History Templates

In History template files you define how history information is displayed in all report sections. You design History templates using the Template Creator tab in Microsoft Word.

### Notes:

- To display History information in project reports, section templates must include **History** merge fields.
- History templates can be only in **tabular** format. For more details, see ["Guidelines for Creating Full-Page and Tabular Templates" on page 287](#).

The following elements are used in History templates:

- **History fields.** Merge fields that represent history field labels and values.
- **Fixed text.** Fixed text that you type in a history template is displayed in reports. For example, type History in a heading row above the history merge fields.


**To design a new History template:**


1. Create a new template file using the template creator in Microsoft Word. For more information on accessing the template creator, see ["Template Creator Tab" on page 288](#).

2. Click **Template Type** , and select **History**.




3. Click **Formatting** , and select **Tabular**, to create a tabular template.

The Select Fields dialog box opens.



4. To include a field in the template, select a field in the Available Fields pane, and click the right arrow .

**Tip:** Use the CTRL or SHIFT key to select multiple fields.

5. To remove a field from the template, select a field in Selected Fields pane, and click the left arrow .
6. To move all fields from one pane to the other, click the double arrows  .
7. Click the **Reorder** buttons to change the order of fields in the template.
8. Click **Insert**. The fields you selected are inserted in tabular layout.

## Designing Section Templates

In section templates you define how information is displayed in report sections. You define separate section templates for each ALM entity that can be included in report sections. You design section templates using the Template Creator tab in Microsoft Word.

**Note:** Section templates can be in either a **full-page** or **tabular** format. For more information, see ["Guidelines for Creating Full-Page and Tabular Templates" on page 287](#).

The following elements are used in section templates:

- **Section Name.** A merge field that is replaced in reports by the value of a section's **Name** field.
- **Section Filter.** A merge field that displays the data filter applied to the report section.
- **Entity fields.** Merge fields that represent entity field labels and values.

**Note:** Date and time fields are formatted using a SHORT DATE/TIME format associated with the locale defined on the ALM server. The report designer cannot change these formats.

- **History.** A merge field that inserts history information of the entity record. Use the merge field in full-page templates, within the data area.
- **Graphs.** A merge field that inserts graphs that have been added to the report. By default graphs are added to the end of a report.

**Note:** You cannot include more than one graph field in the same template.

- **Fixed text.** Fixed text that you type in a section template is displayed in reports.


### To design a new section template:


1. Create a new template file using the template creator in Microsoft Word. For more information on accessing the template creator, see ["Template Creator Tab" on page 288](#).

2. Click **Template Type** , and select a section.





3. Click **Formatting** , and select either **Full Page** or **Tabular**, to create a full-page or a tabular template.

The Select Fields dialog box opens.






4. To include a field in the template, select a field in the Available Fields pane, and click the right arrow .

**Tip:** Use the CTRL or SHIFT key to select multiple fields.

5. To remove a field from the template, select a field in Selected Fields pane, and click the left arrow .
6. To move all fields from one pane to the other, click the double arrows  .
7. Click the **Reorder** buttons to change the order of fields in the template.
8. Click **Insert**. The fields you selected are inserted in full-page or tabular layout.
9. To include history information of records in a full-page template, place the cursor before the `Data` End tag, click **Insert Field Value** , and select **History**.

**Note:** History information is displayed according to the History template assigned to the report.

10. To include the section name, or details of the section filter, click **Insert Field Value** , and select **Section Name** or **Section Filter**. Make sure these fields are placed outside the data area.
11. A section template can be used at any level of a report. To ensure that a section header displays in a style appropriate to its level in the report, place the cursor on the **Section Name** merge field. Make sure the **Set Auto Heading Style** button  is pressed.
12. To ensure that tables use the uniform table style defined in the Style template, place the cursor in the table area. Make sure the **Set Table Style** button  is pressed.

# Guidelines for Creating Full-Page and Tabular Templates

Section templates can be designed in either full-page or tabular formats.

**Note:** Templates should consist of only one Word section. Only those text and fields in the first Word section are included in the generated report.

## Full-page templates

In a **full-page** template, you arrange fields of an entity across several lines of a page. Typically, merge fields of a field's label and value are displayed on the same line, separated by a colon or tab.

For example: Detected By Label : Detected By

In full page templates, the section of the template that is repeated for each record must be surrounded by **Data Start** and **Data End** merge fields.

**Example:**

«Section Name»

«Data Start»

«Defect ID Label»:	«Defect ID»
«Assigned To Label»:	«Assigned To»
«Detected By Label»:	«Detected By»
«Priority Label»:	«Priority»
«Status Label»:	«Status»

«Data End»

## Tabular templates

In a **tabular** template, you arrange fields of an entity in a two-row table. The top row of the table contains merge fields of field labels. The bottom row of the table contains merge fields of the corresponding field values.


In tabular templates, the first cell in the value row must begin with a **Table Start** merge field, and the last cell in the value row must end with a **Table End** merge field.

**Example:**








«Section Name»				
«Defect ID Label»	«Assigned To Label»	«Detected By Label»	«Priority Label»	«Status Label»
«Table Start»«Defect ID»	«Assigned To»	«Detected By»	«Priority»	«Status»«Table End»

## Template Creator Tab




The template creator enables you to design Document, History, and section templates in Microsoft Word.

<b>To access</b>	<p>You access the template creator either from <b>Project Customization &gt; Project Report Templates</b>, or from the project report Configuration tab.</p> <ul style="list-style-type: none"> <li>To create a new template file, select a project report template or section, and click <b>Template Creator</b>. Microsoft Word opens, and the applicable template type is selected in the Template Creator tab.</li> <li>To edit an existing template file, select a project report template, and click <b>Download Template</b> . The template opens in Microsoft Word.</li> </ul>
<b>Important information</b>	<p>To enable the template creator, you must first allow macros in Microsoft Word. In Word, click the <b>Office Button</b>, and then click <b>Word Options</b>. Select <b>Trust Center &gt; Trust Center Settings &gt; Macro Settings</b>. Select <b>Enable all macros</b>.</p>
<b>See also</b>	<p><a href="#">"Designing Report Templates" on page 281</a></p>

User interface elements are described below:

UI Elements	Description
	<p><b>Choose Template Type.</b> Lists the template types that you can create in the template creator. The selected template type is displayed in the button label, and determines the fields you can include in the template.</p>
	<p><b>Formatting.</b> Inserts selected fields in one of the following formats:</p> <ul style="list-style-type: none"> <li><b>Full Page.</b> Lists selected fields vertically across multiple lines. Field values are placed alongside their labels, separated by a colon and tab.</li> <li><b>Tabular.</b> Lists selected fields horizontally in a table. Field labels are listed in the top row of the table, and field values are listed below them.</li> </ul>
	<p><b>Insert Field Label.</b> Inserts a selected field label at the cursor position.</p>
	<p><b>Insert Field Value.</b> Inserts a selected field value at the cursor position.</p>
	<p><b>Insert Multiple Fields.</b> Opens the Select Fields dialog box, enabling you to insert field labels and values at the cursor location.</p> <p><b>Note:</b> The selected fields are inserted on separate lines.</p>
	<p><b>Insert Custom Field.</b> In a Document template, enables you to insert custom fields anywhere in the Document template. For example, add custom fields to the document title page, and to document headers and footers.</p> <p>When creating a report, users enter values that replace the custom fields in the report.</p>
	<p><b>Set Auto Heading Style.</b> Toggles the <b>Template Report Auto Heading</b> style to the selected paragraph. In report sections based on the template, the style is automatically replaced by the <b>Heading</b> style appropriate to the section level.</p> <p>In full-page templates, you can apply the <b>Template Report Auto Heading</b> style both to the section heading (before the <b>Data Start</b> merge field), and to the record heading. As a result, the section heading in a</p>



UI Elements	Description
	<p>report is displayed on a higher hierarchical level than the section records.</p> <p>In tabular templates, you can apply the <b>Template Report Auto Heading</b> style only to the section heading.</p>
	<b>Set Table Style.</b> Toggles the <b>Template Report Table</b> style to the selected table.
	<b>Connect to ALM.</b> Enables you to connect to a different ALM project. The template creator automatically retrieves the entity fields from the selected project.
	<b>Localize Strings.</b> Retrieves updated field labels from Project Customization.



# Chapter 24: Business Views

This section describes how to create and manage business views, which can be used as a basis for ALM's reporting tools.

This chapter includes:

• Business Views Overview .....	292
• Creating and Managing Business Views .....	292
• Working with DQL .....	294
• Business Views User Interface .....	305

## Business Views Overview

Business views are a semantic data layer that can be used as a basis for the various HP Application Lifecycle Management (ALM) reporting tools.

The views are based on project entities, and ensure that only information that is relevant to a business consumer is revealed in a report. For example, you can select only those defect related entity fields that represent some business value to a report consumer. You then create a unique view which can be used and reused as a report basis.

For example, a business view based on **Baselines** could contain the **Name**, **Description**, and **Baseline ID** fields. This is because these fields convey information that could be of importance to the graph consumer who needs to understand baseline information from a business perspective only. By the same logic, the same business view does not include the **Attachment** and **Auto complete type** fields, as they are of little business significance.

Creating reports based on business views ensures standardization across the reports, as different reports that are based on the same business view reflect a common frame of reference. This provides genuine business value to the reports consumer, thereby making the reports more meaningful.

**Note:** Reports are generated according to the permission levels of the user generating them. Therefore, information that is included in a business view that is not available to a user will not appear in any report that user creates.

Business views can be based on a single project entity (for example, defects), or can represent more complex relationships between several entities (for example, defects, requirements, and tests). ALM provides a set of pre-defined business views that are available for selection.


Business views must be designed by a user who understands the business requirements of the organization. In addition, the process of creating business views utilizes DQL, a domain query language that is a flavor of ANSI SQL. It is important that the business view designer be able to understand DQL queries. For more information on working with DQL, see ["Working with DQL" on page 294](#).

## Creating and Managing Business Views

This task describes how to create and manage business views.

To learn more about business views, see ["Business Views Overview" above](#).

### 1. Open the Business Views page

- a. On the ALM masthead, click , then select **Customize**. The Project Customization window opens.
- b. In the Project Customization window, click the **Business Views** link. The Business Views page opens. For user interface details, see ["Business Views Page" on page 306](#).

## 2. Create an empty business view

On the Business Views page toolbar, click **Add View**. The New View dialog box opens. Enter a technical name and label, and click **OK**.

## 3. Add project entities to the business view

- a. On the Business Views page, if it is not selected, select the **Query Designer** tab.
- b. On the Query Designer tab toolbar, click **Add Entity**. The Model tree opens in the right pane. The Model tree displays all project entities and fields in the current project.
- c. Select the entities you want to add to the new business view and drag them to the **Main** pane in the middle of the Query Designer tab. For each project entity you add, a <project entity> dialog box is added, displaying all available fields contained within the entity. You use the checkboxes next to the field names to select specific fields to include in the view.

**Note:** By default, all fields are selected and the checkboxes are unchecked.

## 4. Define relationships between selected entities

You create relationships between selected entities in one of the following ways:

- Select a <project entity> dialog box, and on the Query Designer tab toolbar click **Add Related Entity**. The Add Related Entity dialog box opens. For user interface details, see ["Add Related Entity Dialog Box" on page 310](#).
- When more than one entity has been selected, create the relationships manually by dragging a field from one entity to another.
- Enter the query directly in the DQL Query Builder.

## 5. Edit filter criteria - optional

You can edit and define filter criteria for selected fields in the selected fields grid below the Main panel.

**Tip:** You can change a field's label using the **Alias** column of the selected fields grid.

## 6. Edit entity relationships - optional

To edit relationships between entities, double click on a relationship line. The Link Properties dialog box opens. For user interface details, see ["Link Properties Dialog Box" on page 309](#).

## 7. Validate the business view

On the Query Designer tab toolbar, click **Validate**. Any warning or error messages are shown in the Query Results pane at the bottom of the Query Designer tab.

## 8. Preview the business view

On the Query Designer tab toolbar, click **Preview**. The Query Results pane opens at the bottom of the Query Designer tab.

## 9. Update the business view status

On the Query Designer tab toolbar, click the **Status** arrow and select **Published**.

## 10. Save the business view

On the Business Views page toolbar, click **Save**.

## Working with DQL

The process of creating business view queries utilizes DQL, a domain query language.

For the most part, DQL is an exact match to ANSI SQL 9.2, however there are some significant differences.

**Note:** DQL only supports SELECT statements.

This section includes:

- [Advantages of DQL](#)
- [Additions to SQL](#)
- [Supported Functions](#)

### Advantages of DQL

Building queries with DQL has the following advantages:

- DQL enforces data hiding in accordance with user's permission levels. In other words, reports are generated according to the permission levels of the user generating them. Information that is included in a business view that is not available to a user does not appear in any report that the user creates.
- The DQL query creates a database abstraction which is then used as a basis for the business view. Since the basis of the view is an abstraction of the database and not the database itself, you do not need to identify entity fields according to their actual names. Rather the query simplifies them and makes them easier to identify. For example, all fields that relate to an object's identification appear with the suffix "ID", such as Defect ID, Cycle ID, and Release ID.
- DQL queries run equally well on Oracle and SQL database servers.

### Additions to SQL

DQL provides the following options, which are not available in ANSI SQL:

- **Variables.** Three variables have been added:
  - **:me.** Returns information relevant to the user creating the report. Meaning different users who create reports based on the same business view will receive different results.
  - **:current\_project\_name.** Returns information relevant for the project from which the reports is created.
  - **:current\_domain\_name.** Returns information relevant for the domain from which the report is created.

Following is an example of the **Me** variable:

```
Select *
From defect
Where defect.detected_by = :me
```

- **Select Top.** This option enables you to limit the query results to a defined number of items.

## Supported Functions

The following table lists the DQL functions that are supported in ALM. DQL functions are converted to the corresponding SQL functions for use in the database. The table lists the conversions of the DQL functions to MS SQL and Oracle. For more information, refer to the MS SQL and Oracle documentation.

Function	Signature	Return Type	Description
<b>Aggregation</b>			
count	count(expression)	integer	Returns the number of rows in a query.
count_big	count_big(expression)	integer (bigint)	Returns the number of rows in a query. The only difference between <b>count</b> and <b>count_big</b> is their return values. In MS SQL, <b>count_big</b> always returns a bigint data type value, and <b>count</b> always returns an int data type value.  <b>Note:</b> In Oracle, the function is converted to <b>count</b> .
variance	variance(decimal)	decimal	Returns the variance of the expression .  <b>Note:</b> In MS SQL, the function is converted to <b>var</b> . In Oracle, the function is coded as <b>round (variance(&lt;decimal&gt;), 14)</b> .
var_pop	var_pop(expression)	decimal	Returns the population variance of a set of numbers after discarding the nulls in the set.  <b>Note:</b> In MS SQL, the function is converted to <b>varp</b> . In Oracle, the function is coded as <b>round (var_pop(&lt;expression&gt;), 14)</b> .
stddev	stddev(decimal)	decimal	Returns the standard deviation of a set of numbers.  <b>Note:</b> In MS SQL, the function is converted to <b>stdev</b> . In Oracle, the function is coded as <b>round (stddev(&lt;decimal&gt;), 14)</b> .
stddev_pop	stddev_pop(expression)	decimal	Computes the population standard deviation and returns the square root of the population variance.

Function	Signature	Return Type	Description
			<b>Note:</b> In MS SQL, the function is converted to <b>stdevp</b> . In Oracle, the function is coded as <b>round(stddev_pop(&lt;expression&gt;), 14)</b> .
avg	avg(expression)	decimal	Returns the average value of an expression.  <b>Note:</b> In Oracle, the function is coded as <b>round (avg(&lt;decimal&gt;), 14)</b> .
sum	sum(decimal)	decimal	Returns the summed value of an expression.
min	min(expression)	expression	Returns the minimum value of an expression.
max	max(expression)	expression	Returns the maximum value of an expression.
<b>String Manipulation</b>			
upper	upper(string)	string	Returns the given string with all letters converted to upper case.
lower	lower(string)	string	Returns the given string with all letters converted to lower case.
rtrim	rtrim(string)	string	Returns the given string with all trailing spaces removed from the right-hand side.
ltrim	ltrim(String)	string	Returns the given string with all leading spaces removed.
replace	replace(string, string_to_replace, replacement_string)	string	Returns the given string with all sequences of <b>&lt;string_to_replace&gt;</b> replaced with <b>&lt;replacement_string&gt;</b> .
substring	substring(string, int_start_position, int_length)	string	Returns a substring from the given string. <ul style="list-style-type: none"> <li><b>int_start_position.</b> The position from which to start extracting the substring.</li> <li><b>int_length.</b> The number of characters to extract.</li> </ul> <b>Note:</b> In Oracle, the function is converted to <b>substr</b> .
length	length(string)	decimal	Returns the length of the specified string.  <b>Note:</b> In MS SQL, the function is converted to <b>len</b> .
chr	chr(integer)	string	Converts an int ASCII code into a character.  <b>Note:</b> In MS SQL, the function is converted to <b>char</b> .
soundex	soundex(string)	string	Returns a phonetic representation of a string.
ascii	ascii(string)	integer	Returns the ASCII code value of the leftmost character of a character expression.



Function	Signature	Return Type	Description
concat	concat(string1, string2)	string	Concatenates two strings together .  <b>Note:</b> In MS SQL, the function is converted to <b>+</b> , and the function is coded as <b>&lt;string1&gt; + &lt;string2&gt;</b> .
leftstr	leftstr(string, integer)	string	Returns the left part of a character string with the specified number of characters.  <b>Note:</b> In MS SQL, the function is converted to <b>left</b> . In Oracle, the function is converted to <b>substr</b> and is coded as <b>substr(&lt;string&gt;, 1, &lt;integer&gt;)</b> .
lpad	lpad(string1, integer, string2)	string	Returns <b>&lt;string1&gt;</b> , left-padded to length <b>&lt;integer&gt;</b> characters with the sequence of characters in <b>&lt;string2&gt;</b> . This function is useful for formatting the output of a query.  <b>Note:</b> In MS SQL, the function is converted to the <b>left padding</b> expression, which implements the above logic.
reverse	reverse(string)	string	Returns the reverse of a string value.  <b>Note:</b> In Oracle, the function is coded as <b>reverse(to_char(&lt;string&gt;))</b> .
rightstr	rightstr(string, integer)	string	Returns the right part of a character string with the specified number of characters.  <b>Note:</b> In MS SQL, the function is converted to <b>right</b> . In Oracle, the function is converted to <b>substr</b> with the <b>right part</b> expression, which implements the above logic.
rpadd	rpadd(string1, integer, string2)	string	Returns <b>&lt;string1&gt;</b> , right-padded to length <b>&lt;integer&gt;</b> characters with <b>&lt;string2&gt;</b> , replicated as many times as necessary. This function is useful for formatting the output of a query.  <b>Note:</b> In MS SQL, the function is converted to <b>left</b> with the <b>right padding</b> expression, which implements the above logic.
stuff	stuff(string, integer, integer, string)	string	Inserts a string into another string. It deletes a specified length of characters in the first string at the start position, and then inserts the second string into the first string at the start position.  <b>Note:</b> In Oracle, the <b>stuff</b> function is converted to an expression that implements the above logic.

Function	Signature	Return Type	Description
in_string	in_string(string1, string2, integer_start_location)	integer	<p>Returns the location of substring <b>string2</b> in <b>string1</b>, if it exists. Otherwise, returns 0. The search starts at <b>integer_start_location</b>, which starts at 1.</p> <p><b>Note:</b> In MS SQL, the function is converted to <b>charindex</b>. In Oracle, the function is converted to <b>instr</b> and is coded as <b>instr(&lt;string2&gt;, &lt;string1&gt;, &lt;integer_start_location&gt;)</b>.</p>
replicate	replicate(string, integer)	string	<p>Repeats the <b>&lt;string&gt;</b> value the number of times given in the <b>&lt;integer&gt;</b> parameter.</p> <p><b>Note:</b> In Oracle, the function is converted to <b>rpadd</b> and is coded as <b>rpadd(&lt;string&gt;, length (&lt;string&gt;*&lt;integer&gt;), &lt;string&gt;)</b>.</p>
<b>Math</b>			
sin	sin(decimal)	decimal	<p>Returns the sine of the <b>decimal</b> parameter.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (sin(&lt;decimal&gt;), 14)</b>.</p>
asin	asin(decimal)	decimal	<p>Returns the arc sine of the <b>decimal</b> parameter. The argument must be in the range of -1 to 1.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (asin(&lt;decimal&gt;), 14)</b>.</p>
cos	cos(decimal)	decimal	<p>Returns the cosine of the <b>decimal</b> parameter.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (cos(&lt;decimal&gt;), 14)</b>.</p>
acos	acos(decimal)	decimal	<p>Returns the arc cosine of the <b>decimal</b> parameter. The argument must be in the range of -1 to 1.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (acos(&lt;decimal&gt;), 14)</b>.</p>
tan	tan(decimal)	decimal	<p>Returns the tangent of the <b>decimal</b> parameter.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (tan(&lt;decimal&gt;), 14)</b>.</p>
atan	atan(decimal)	decimal	<p>Returns the arc tangent of the <b>decimal</b> parameter.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (atan(&lt;decimal&gt;), 14)</b>.</p>
atan2	atan2(decimal1, decimal2)	decimal	<p>Returns the angle, in radians, between the positive x-axis and the ray from the origin to the point (y, x), where</p>

Function	Signature	Return Type	Description
			<p>x and y are the values of <b>decimal1</b> and <b>decimal2</b>.</p> <p><b>Note:</b> In MS SQL, the function is converted to <b>atn2</b>. In Oracle, the function is coded as <b>round (atan2(&lt;decimal1&gt;), 14)</b>.</p>
tanh	tanh(decimal)	decimal	<p>Returns the hyperbolic tangent of the <b>decimal</b> parameter.</p> <p><b>Note:</b> In MS SQL, the function is converted to the <b>tanh</b> expression, which implements the above logic. In Oracle, the function is coded as <b>round(tanh(&lt;decimal&gt;), 14)</b>.</p>
sqrt	sqrt(decimal)	decimal	<p>Returns the square root of decimal parameters.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (sqrt(&lt;decimal&gt;), 14)</b>.</p>
exp	exp(decimal)	decimal	<p>Returns <b>e</b> raised to the <b>decimal</b> parameter power, where e = 2.71828183.</p> <p><b>Note:</b> In Oracle, the function is coded as <b>round (exp(&lt;decimal&gt;), 14)</b>.</p>
sign	sign(decimal)	decimal	<p>Returns a value indicating the sign of a number. If the number &lt; 0, then <b>sign</b> returns -1. If the number = 0, then <b>sign</b> returns 0. If the number &gt; 0, then <b>sign</b> returns 1.</p> <p><b>Note:</b> In MS SQL, the function is converted to the <b>sign</b> expression, which implements the above logic, and is coded as <b>CAST(sign (&lt;decimal&gt;) AS int)</b>.</p>
floor	floor(decimal)	integer	<p>Returns the largest integer less than or equal to the specified decimal argument.</p>
ln	ln(decimal)	decimal	<p>Returns the natural logarithm of the decimal argument.</p> <p><b>Note:</b> In MS SQL, the function is converted to <b>log</b>. In Oracle, the function is coded as <b>round(ln (&lt;decimal&gt;), 14)</b>.</p>
abs	abs(decimal)	decimal	<p>Returns the absolute value of a number.</p>
round	round(decimal, integer)	decimal	<p>Returns <b>decimal</b> rounded to <b>integer</b> places to the right of the decimal point. The <b>integer</b> parameter can be negative to round off digits left of the decimal point.</p> <p><b>Note:</b> In MS SQL, the function is coded as <b>CAST(round(&lt;decimal&gt;, &lt;integer&gt;) AS int)</b> or as <b>CAST(round(&lt;decimal&gt;</b></p>

Function	Signature	Return Type	Description
			<b>&lt;integer&gt; AS float</b> ), depending on whether <b>integer</b> is valued with zero.
mod	mod(decimal1, decimal2)	decimal	Returns the remainder of <b>decimal1</b> divided by <b>decimal2</b> .  <b>Note:</b> In MS SQL, the function is converted to % and is coded as <b>&lt;decimal1&gt; % &lt;decimal2&gt;</b> .
trunc_number	trunc_number(decimal, integer)	decimal	Returns <b>decimal</b> truncated to <b>integer</b> decimal places. If <b>integer</b> is omitted, then <b>decimal</b> is truncated to 0 places.  <b>Note:</b> In MS SQL, the function is converted to the <b>truncation</b> expression, which implements the above logic. In Oracle, the function is converted to <b>trunc</b> .
str	str(decimal, integer1, integer2)	string	Returns character data converted from numeric data.  <b>Note:</b> In Oracle, the function is converted to the <b>string construction</b> expression, which implements the above logic.
ceil	ceil(decimal)	decimal	Returns the smallest integer greater than or equal to the decimal parameter.  <b>Note:</b> In MS SQL, the function is converted to <b>ceiling</b> .
<b>Cast</b>			
to_number	to_number(string)	decimal	Converts a string to a number.  <b>Note:</b> In MS SQL, the function is coded as <b>CAST(&lt;string&gt; AS float)</b> .
number_to_char	number_to_char(decimal)	string	Converts a number to a string.  <b>Note:</b> In MS SQL, the function is coded as <b>CAST(&lt;decimal&gt; AS varchar(50))</b> . In Oracle, the function is converted to <b>to_char</b> .
char_to_char	char_to_char(string)	string	Converts NCHAR, NVARCHAR2, CLOB, or NCLOB data to the database character set.  <b>Note:</b> In MS SQL, the function is coded as <b>CAST(&lt;string&gt; AS varchar(50))</b> . In Oracle, the function is converted to <b>to_char</b> .
datetime_to_char	datetime_to_char(expression)	string	Converts a date or datetime to a string.

Function	Signature	Return Type	Description
			<p><b>Note:</b> In MS SQL, the function is coded as <b>convert(varchar, &lt;date&gt;, 121)</b>. In Oracle, the function is converted to <b>to_char</b> and is coded as <b>to_char(&lt;date&gt;, 'YYYY-MM-DD HH24:MI:SS:FF3')</b>.</p>
<b>Miscellaneous</b>			
nullif	nullif(expression1, expression2)	expression	Compares <b>expression1</b> and <b>expression2</b> . If <b>expression1</b> and <b>expression2</b> are equal, the function returns NULL. Otherwise, it returns <b>expression1</b> .
coalesce	coalesce()	expression	Returns the first non-null expression among its arguments. The data type of the returned value is the data type of the parameter with the highest data type precedence.
isnull	isnull(check_expression, replace_expression)	expression	<p>Substitutes a value when a null value is encountered. If <b>check_expression</b> is null, then the function returns <b>replace_expression</b>.</p> <p><b>Note:</b> In Oracle, the function is converted to <b>nvl</b>.</p>
<b>Date</b>			
currentdate	currentdate()	date	<p>Returns the current date.</p> <p><b>Note:</b> In MS SQL, the function is coded as <b>CAST(CAST(getdate() AS date) AS datetime)</b>. In Oracle, the function is coded as <b>to_date(to_char(sysdate))</b>.</p>
dateadd	dateadd(integer, date)	date	<p>Adds days to date parameters:</p> <ul style="list-style-type: none"> <li><b>integer</b>. The numbers of days to add.</li> <li><b>date</b>. The date to add to.</li> </ul> <p><b>Note:</b> In MS SQL, the function is coded as <b>dateadd(DAY, &lt;int days&gt;, &lt;Date date&gt;)</b>. In Oracle, the function is converted to <b>+</b> and is coded as <b>&lt;int days&gt; + &lt;Date date&gt;</b>.</p>
datediff	datediff(start_date, end_date)	integer	<p>Returns the count (signed integer) of dates crossed between the specified <b>start_date</b> and <b>end_date</b>.</p> <p><b>Note:</b> In MS SQL, the function is coded as <b>datediff(DAY, &lt;date&gt;, &lt;date&gt;)</b>. In Oracle, the function is converted to <b>-</b> and is coded as <b>trunc(&lt;date&gt; - &lt;date&gt;, 0)</b>.</p>
get_time	get_time()	datetime	Returns the current date and time.

Function	Signature	Return Type	Description
			<p><b>Note:</b> In MS SQL, the function is converted to <b>getdate</b> and is coded as <b>convert(datetime, getdate(), 126)</b>. In Oracle, the function is converted to <b>LOCALTIMESTAMP</b>.</p>
trunc_date	trunc_date(date, string_format)	date	<p>Returns a date truncated to a specific unit of measure. <b>string_format</b> is the unit of measure to apply for truncating. The following formats are supported: year, y, yy, yyyy, q, quarter, mm, month, d, dd, day, hh, mi</p> <p><b>Note:</b> In MS SQL, the function is converted to <b>dateadd</b> and is coded as <b>dateadd(&lt;unquoted string_format&gt;, datediff(&lt;unquoted string_format&gt;, 0, &lt;date&gt;), 0)</b>. In Oracle, the function is converted to <b>trunc</b> and is coded as <b>trunc(&lt;date&gt;, &lt;string_format&gt;)</b>.</p>
to_date	to_date(string)	date	<p>Converts a string to a date.</p> <p><b>Note:</b> In MS SQL, the function is coded as <b>CAST(&lt;string&gt; AS datetime)</b>. In Oracle, the function is coded as <b>to_date(&lt;string&gt;, 'YYYY-MM-DD')</b>.</p>
timestamp_tz	timestamp_tz()	string	<p>Returns the current server time zone .</p> <p><b>Note:</b> In MS SQL, the function is converted to <b>sysdatetimeoffset</b>. In Oracle, the function is converted to <b>CURRENT_TIMESTAMP</b>. This function is not supported in MS SQL Server 2005.</p>
from_tz	from_tz(date, string)	date	<p>Converts a timestamp value (<b>date</b>) and a time zone (<b>string</b>) to a timestamp with time zone value.</p> <p><b>Note:</b> In MS SQL, the function is converted to the <b>time stamp</b> and <b>zone</b> expressions, which implement the above logic. This function is not supported in MS SQL Server 2005.</p>
sysdatetimeoffset	sysdatetimeoffset()	datetime with time zone	<p>Returns the system date, including fractional seconds, and the time zone of the system on which the database resides.</p> <p><b>Note:</b> In Oracle, the function is converted to <b>SYSTIMESTAMP</b>. This function is not supported in MS SQL Server 2005.</p>
getyear	getyear(date)	integer	<p>Returns an integer that represents the year of the specified date.</p> <p><b>Note:</b> In MS SQL, the function is converted to</p>

Function	Signature	Return Type	Description
			<p><b>year</b>. In Oracle, the function is converted to <b>to_char</b> and is coded as <b>CAST(to_char(&lt;date&gt;, 'yyyy') AS number)</b>.</p>
getmonth	getmonth(date)	integer	<p>Returns an integer that represents the month of the specified date.</p> <p><b>Note:</b> In MS SQL, the function is converted to <b>month</b>. In Oracle, the function is converted to <b>to_char</b> and is coded as <b>CAST(to_char (&lt;date&gt;, 'mm') AS number)</b>.</p>
getday	getday(date)	integer	<p>Returns an integer representing the day of the month of the specified date.</p> <p><b>Note:</b> In MS SQL, the function is converted to <b>day</b>. In Oracle, the function is converted to <b>to_char</b> and is coded as <b>CAST(to_char(&lt;date&gt;, 'dd') AS number)</b>.</p>
datepart	datepart(string_datepart, date)	integer	<p>Returns an integer that represents the specified <b>string_datepart</b> of the specified date.</p> <p><b>Note:</b> In MS SQL, the function is coded as <b>datepart(&lt;unquoted string_datepart&gt;, &lt;date&gt;)</b>. In Oracle, the function is converted to the <b>datepart</b> expression, which implements the above logic.</p>
datename	datename(string_datepart, date)	string	<p>Returns a character string that represents the specified <b>string_datepart</b> of the specified date. The following formats are supported: yyyy, yy, year, q, quarter, m, month, d, dd, day, hh, mi</p> <p><b>Note:</b> In MS SQL, the function is coded as <b>datename(&lt;unquoted string_datepart&gt;, &lt;date&gt;)</b>. In Oracle, the function is converted to the <b>datename</b> expression, which implements the above logic.</p>
<b>Case</b>			
decode	decode(expression, search, result [, search, result]... [, default] )	expression	<p>Has the functionality of an IF-THEN-ELSE statement. Compares the expression to each search value one by one. If the expression is equal to a search, then an Oracle Database returns the corresponding result. If no match is found, then Oracle returns <b>default</b>. If default is omitted, then Oracle returns <b>null</b>.</p> <p><b>Note:</b> In MS SQL, the function is converted to the <b>case-when-else</b> expression, which implements the above logic.</p>

Function	Signature	Return Type	Description
greatest	greatest()	expression	Returns the greatest of the list of parameters.  <b>Note:</b> In MS SQL, the function is converted to the <b>greatest</b> expression, which implements the above logic.
least	least()	expression	Returns the least of the list of parameters.  <b>Note:</b> In MS SQL, the function is converted to the <b>least</b> expression, which implements the above logic.
<b>Special Date</b>			
<b>Note:</b> For each function, the requested date is returned in the respective date format. In MS SQL, the requested date in yyyy-MM-dd format is cast as datetime. In Oracle, to_date(<requested date in dd-MMM-yy format>, DD-MON-YY)			
firstDayOfCurrentMonth	firstDayOfCurrentMonth()	date	Returns the date of the first day of the current month.
firstDayOfCurrentWeek	firstDayOfCurrentWeek()	date	Returns the date of the first day of the current week.
firstDayOfCurrentYear	firstDayOfCurrentYear()	date	Returns the date of the first day of the current year.
firstDayOfNextMonth	firstDayOfNextMonth()	date	Returns the date of the first day of the next month.
firstDayOfNextWeek	firstDayOfNextWeek()	date	Returns the date of the first day of the next week.
firstDayOfNextYear	firstDayOfNextYear()	date	Returns the date of the first day of the next year.
firstDayOfPreviousMonth	firstDayOfPreviousMonth()	date	Returns the date of the first day of the previous month.
firstDayOfPreviousWeek	firstDayOfPreviousWeek()	date	Returns the date of the first day of the previous week.
firstDayOfPreviousYear	firstDayOfPreviousYear()	date	Returns the date of the first day of the previous year.
lastDayOfCurrentMonth	lastDayOfCurrentMonth()	date	Returns the date of the last day of the current month.
lastDayOfCurrentWeek	lastDayOfCurrentWeek()	date	Returns the date of the last day of the current week.
lastDayOfCurrentYear	lastDayOfCurrentYear()	date	Returns the date of the last day of the current year.
lastDayOfNextMonth	lastDayOfNextMonth()	date	Returns the date of the last day of the next month.
lastDayOfNextWeek	lastDayOfNextWeek()	date	Returns the date of the last day of the next week.
lastDayOfNextYear	lastDayOfNextYear()	date	Returns the date of the last day of the next year.
lastDayOfPreviousMonth	lastDayOfPreviousMonth()	date	Returns the date of the last day of the previous month.
lastDayOfPreviousWeek	lastDayOfPreviousWeek()	date	Returns the date of the last day of the previous week.
lastDayOfPreviousYear	lastDayOfPreviousYear()	date	Returns the date of the last day of the previous year.




# Business Views User Interface

This section includes:


- [Business Views Page](#) .....306
- [Link Properties Dialog Box](#) .....309
- [Add Related Entity Dialog Box](#) ..... 310

## Business Views Page

The Business Views page enables you to create and manage business views.



### To access





1. On the masthead, click , then select **Customize**. The Project Customization page opens.
2. In the Project Customization window, in the left pane, click **Business Views**.







### See also

["Creating and Managing Business Views" on page 292](#)

## Business Views Page Common Elements

User interface elements are described below:







UI Element	Description
	Saves changes made in the Business Views page.
	<p>Opens the New View dialog box. Enter the following information:</p> <ul style="list-style-type: none"> <li>• <b>Label.</b> The name of the view which is used for identification purposes only. For example, in the Views tree, and when selecting views in the Analysis View module, views are listed according to their labels. You can change the label in the selected fields grid. For more information, see <a href="#">"&lt;selected fields grid&gt;" on page 308</a>.</li> <li>• <b>Technical name.</b> The name of the view which is used as part of the DQL query. The name cannot contain spaces.</li> </ul> <p>Click <b>OK</b>. The view is added to the Views tree.</p>
	Duplicates the selected view. The duplicated view is added to the Views tree.
	<p>Deletes the selected view.</p> <p><b>Note:</b> You will no longer be able to view reports or graphs based on the deleted view.</p>



UI Element	Description
	Validates all views.
	Opens the Save As dialog box, enabling you to save the selected view as an <b>.xml</b> file.  <b>Tip:</b> To select multiple views, press the CTRL key and select the desired views.
	Opens the Open dialog box enabling you to import views.  <b>Note:</b> By default, imported views are not valid.
<b>Views tree</b>	Displays pre-defined as well as user-defined views. The icon next to the view's name indicates the view's status. <ul style="list-style-type: none"> <li> The view is valid and is published.</li> <li> The view is valid and is not published.</li> <li> The view is not valid.</li> </ul> <b>Note:</b> Views are listed alphabetically according to their labels. Place the cursor over the label to view a tooltip displaying the view's technical name.

## Query Designer tab

This tab enables you to customize business views.

User interface details are described below (unlabeled elements are shown in angle brackets>):

UI Element	Description
	Determines the view of the Query Designer tab. Click the arrow to select the desired view: <ul style="list-style-type: none"> <li><b>QBE Only.</b> Hides the <b>DQL Query Builder</b>.</li> <li><b>DQL Only.</b> Displays only the <b>DQL Query Builder</b>.</li> <li><b>QBE and DQL.</b> Displays the entire Query Designer tab. This is the default view.</li> </ul>
	Opens the Model pane on the right of the tab, enabling you to select project entities to add to a view. For more information, see <a href="#">Model pane</a> .
	Opens the Add Related Entity dialog box, enabling you to define joins between selected entities.  For user interface details, see <a href="#">"Add Related Entity Dialog Box" on page 310</a> .
	Opens the Query Results pane at the bottom of the tab. For more information, see <a href="#">Query Results pane</a> .
	Validates the selected view. The following checks are performed: <ul style="list-style-type: none"> <li>That the DQL syntax is correct.</li> <li>That the query contains only fields from selected entities.</li> </ul>
	Defines whether the selected view is available for use in reporting. <ul style="list-style-type: none"> <li><b>Published.</b> The view is available.</li> </ul>

UI Element	Description
	<ul style="list-style-type: none"> <li>• <b>Not Published.</b> the view is not available.</li> </ul> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>• When changing a view from <b>Not Published</b> to <b>Published</b>, ALM first validates the view before changing the status.</li> <li>• When changing a view from <b>Published</b> to <b>Not Published</b>, you will no longer be able to view reports or graphs based on that view.</li> </ul>
	<p>Opens the SQL Query dialog box which displays the SQL query which is run against the database server.</p> <p><b>Invalid views.</b> The Messages tab displays details about problems with the view. Place the cursor over the message text to view a tooltip displaying the full message.</p>
<b>Main pane</b>	<p>Displays a &lt;Project entity&gt; dialog box for every entity that has been added to the view, as well as defined relationships between entities.</p> <ul style="list-style-type: none"> <li>• For more information about the &lt;Project entity&gt; dialog box, see <a href="#">&lt;Project entity&gt;_dialog_box</a>.</li> <li>• For information about defining relationships between entities, see <a href="#">"Creating and Managing Business Views" on page 292</a></li> </ul>
<b>&lt;project entity&gt; dialog box</b>	<p>Appears in the Main pane after you add a project entity to the view. The dialog box displays all available fields within the entity. Use the checkboxes to select fields to add to the view.</p> <p><b>Default:</b> All fields all included in the view. The checkboxes appear unchecked.</p>
<b>Model pane</b>	<p>Displays available project entities.</p> <p>To add an entity to the view, select it and click the <b>Add</b> button . Alternatively, you can add entities by dragging them to the Main pane.</p> <p><b>Note:</b> Entities are listed alphabetically according to their Labels, with their technical names in brackets.</p>
<b>&lt;selected fields grid&gt;</b>	<p>Enables you to define filter criteria for entity fields.</p> <p>To add a field to the grid, in the &lt;project entity&gt; dialog box in the Main pane, use the checkboxes to select the desired fields.</p> <p><b>Tip:</b> You can use the <b>Alias</b> column to change a field's label.</p> <p><b>Note:</b> You cannot change a label for a field in a sub-entity.</p>
<b>DQL Query Builder</b>	<p>Displays the business view query.</p> <p>The query updates automatically as you add entities and define relationships.</p> <p>You can create and edit a view by entering the query directly in the DQL Query Builder. For more information about working with DQL, see <a href="#">"Working with DQL" on page 294</a>.</p>
<b>Query Results pane</b>	<p>Appears when you click <b>Preview</b> on the Query Designer tab toolbar. Displays the following information:</p> <ul style="list-style-type: none"> <li>• <b>Query Results.</b> Valid views only. Displays a preview of the view.</li> </ul>

UI Element	Description
	<ul style="list-style-type: none"><li>• <b>Query Messages.</b> Invalid views only. Displays messages detailing problems with the view. Place the cursor over the message text to view a tooltip displaying the full message.</li></ul>

## Details Tab

This tab enables you to view or edit the selected view's details.

User interface details are described below:

UI Element	Description
<b>Label</b>	The name of the view which is used for identification purposes only. For example, in the Views tree, and when selecting views in the Analysis View module, views are listed according to their labels.  <b>Tip:</b> You can change the label in the selected fields grid. For more information, see " <a href="#">selected fields grid</a> " on the previous page.
<b>Technical name</b>	The name of the view which is used as part of the DQL query.  <b>Note:</b> The technical name cannot contain spaces.
<b>Description tab</b>	A description of the view. Click in the text box to display a toolbar for formatting and spell checking the text.

## Query Messages Tab


This tab enables you to view messages detailing problems with the view.

User interface details are described below:

UI Element	Description
<b>Message Severity</b>	The severity of the error.  <b>Note:</b> Business views with warning messages can be published. Business views with errors cannot be published. Some business views with warning messages can cause the business view reports not to be generated. For example, a business view created with duplicate fields or aliases generates a warning message, but no report is generated from this business view.
<b>Message Text</b>	The full error message.

## Link Properties Dialog Box

The Link Properties dialog box enables you to edit relationships between entities.




To access	Double-click a relation line between two related entities.
See also	<a href="#">"Creating and Managing Business Views" on page 292</a>

User interface elements are described below.

UI Element	Description
Left/Right Object	Displays the technical names of the joined entities.
Select all from left/right	Use the checkboxes to define if the relationship contains inner, left, right, or outer joins.
Join expression	Enables you to edit the join expression.

## Add Related Entity Dialog Box

The Add Related Entity dialog box enables you to define joins between project entities. The dialog box enables you to select from all entities related to the source entity.



To Access	<ul style="list-style-type: none"><li>In the Query Designer tab Main pane, select a &lt;project entity&gt; dialog box and on the toolbar, click <b>Add Related Entity</b>.</li><li>Opens automatically when you add an entity to the view that already has a defined relationship with another entity in the view.</li></ul>
See Also	<a href="#">"Creating and Managing Business Views" on page 292</a>

User interface elements are described below:

UI Element	Description
Source Entity	The currently selected entity.
Target Entity	Displays a drop-down list enabling you to select an available target entity. For each available entity, the entity label appears, with its technical name in brackets.
Relation Name	Displays the relation name given the source and target entities. If more than one relation name exists, you can choose the desired name from the drop-down list.





# Chapter 25: Configuring Business Process Testing

This chapter describes how to configure Business Process Testing for working with business components in HP Application Lifecycle Management (ALM).

This chapter includes:

- [About Configuring Business Process Testing](#) .....314
- [Business Process Test Page](#) .....314

## About Configuring Business Process Testing

You can set additional Business Process Testing options, such as automatic creation of manual design steps as business components are created.

For more information on working with Business Process Testing in ALM, refer to the *HP Business Process Testing User Guide*.


**Available in ALM 12.21:** As a project administrator, you can enable BPT Packaged Apps Kit features, such as:

- Learning tests and flows
- Detecting changes in your application

## Business Process Test Page

The Business Process Test customization page enables the project administrator to customize Business Process Testing.

**Available in ALM 12.21:** You can also customize BPT Packaged Apps Kit on this page.

<b>To access</b>	On the ALM masthead, click  , then select <b>Customize</b> . Select the <b>Business Process Test</b> sidebar entry.
<b>Relevant tasks</b>	<i>HP Business Process Testing User Guide</i> <b>Available in ALM 12.21:</b> <ul style="list-style-type: none"><li>• <i>HP Business Process Testing User Guide:</i></li></ul>

User interface elements are described below:

UI Element	Description
<b>Enable BPT Packaged Apps Kit</b>	<b>Available in ALM 12.21:</b> Enables you to use BPT Packaged Apps Kit features in ALM.
<b>Automatically create new component with manual implementation</b>	If checked, Business Process Testing assumes that new components should have a manual implementation and automatically prepares them for the creation of manual design steps when creating a business component.
<b>Include component instance iterations in the report</b>	If checked, Business Process Testing project reports list entries for all the iterations of a component.  If unchecked, Business Process Testing project reports list only one entry for each component, regardless of the iterations.
<b>Enable automatic promotion when creating a business component or flow parameter</b>	If checked, Business Process Testing gives you the option to automatically promote parameters to the next level(s) when you add a parameter. <ul style="list-style-type: none"><li>• When adding a component parameter, the parameter is promoted to any flow or test that contains the component.</li><li>• When adding a flow parameter, the parameter is promoted to any test that contains the flow.</li></ul>

UI Element	Description
<p><b>Enable automatic deletion of unused test/flow parameters when deleting a parameter at a lower level</b></p>	<p>If checked, Business Process Testing gives you the option to automatically delete the parameters from the next level(s) if the parameters are not used at those levels.</p> <p><b>Note:</b> This has no impact on other parameters that happen not to be in use. This affects only those parameters that were deleted at the component or flow level.</p> <p><b>Example</b></p> <p>A parameter called <b>LastLoginDate</b> exists in a component called <b>Login</b>. The <b>Login</b> component is contained within a flow called <b>LoginToSystem</b> and a test called <b>LoginToAllSystems</b> and at some point, <b>LastLoginDate</b> was promoted to the flow and test levels.</p> <p><b>LastLoginDate</b> is no longer needed. When you delete <b>LastLoginDate</b> from the component, the parameter is also deleted from <b>LoginToSystem</b> and <b>LoginToAllSystems</b>.</p>
<p><b>Set default On Failure behavior to</b></p>	<p>Business Process Testing sets the default behavior when a component in a test script fails to either:</p> <ul style="list-style-type: none"> <li>• <b>Continue.</b> The business process test will run the next business component or flow if a component fails. By default, this failure condition is defined for each component when it is added to a test.</li> <li>• <b>End.</b> The business process test run ends if a business component fails.</li> </ul>



# Chapter 26: Configuring Sprinter

This chapter describes how to configure HP Sprinter for running tests manually in HP Application Lifecycle Management (ALM).

ALM Editions: Sprinter functionality is not available with **ALM Essentials Edition** or **Performance Center Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

This chapter includes:

- [About Configuring Sprinter](#) .....318
- [Sprinter Page](#) ..... 318

# About Configuring Sprinter


As a project administrator, you can enable running tests manually in your project using Sprinter, using Manual Runner, or both. By default, running tests manually is enabled for both Sprinter and Manual Runner. You can also set additional options for working with Sprinter, such as default screen capture functionality.

For more information on running tests manually in ALM, refer to the *HP Application Lifecycle Management User Guide*. For full details on Sprinter, refer to the *HP Sprinter User Guide*, available from the HP Application Lifecycle Management Add-ins page (**Help > Add-ins**).

## Sprinter Page

This page enables you to activate or deactivate Sprinter features. Deactivated features are visible in the Sprinter user interface, but are inactive.

Sprinter

 Save

Enable manual tests to run with: 

☐ Manual Runner

☐ Sprinter

☒ Both Manual Runner and Sprinter

Screen Captures 

☐ Enable storing of all images during a test

☒ Enable storing of all images for a failed test

☐ Enable storing of all images for a failed step (tests with steps only)

☐ Disable storing of images

☒ Allow macros

☒ Allow Data Injection

☒ Allow editing steps in Sprinter Run mode

☐ Allow attaching movies to defects

Maximum movie length (minutes): 


2

☐ Show step snapshot as step attachment

To access	In Project Customization, in the left pane, click <b>Sprinter</b> .
Important	The settings available in the Sprinter page control which features are enabled in Sprinter. Users still need the correct permissions within ALM that allow them to perform various functions.

<b>information</b>	For example, suppose you select <b>Allow editing steps in Sprinter</b> . The features that allow step editing will be enabled in Sprinter. However, users that do not have test editing permissions in ALM will still be unable to edit steps in a test.
<b>See also</b>	<a href="#">"About Configuring Sprinter" on the previous page</a>

User interface elements are described below:

UI Elements	Description
	Saves Sprinter customization changes.
<b>Enable manual tests to run with</b>	Options include: <ul style="list-style-type: none"> <li>• <b>Manual Runner.</b> Enable manual tests to run with the Manual Runner only.</li> <li>• <b>Sprinter.</b> Enable manual tests to run with Sprinter only.</li> <li>• <b>Both Manual Runner and Sprinter. (Default)</b> Enable manual tests to run with Manual Runner or Sprinter.</li> </ul>
<b>Screen Captures</b>	<ul style="list-style-type: none"> <li>• Sprinter temporarily saves the screen captures of all the actions in your test. You indicate which images to capture during the run, in the <b>Run</b> pane in Sprinter's <b>Settings</b> dialog box.</li> <li>• The settings below control access to the corresponding images in the <b>Run</b> pane in Sprinter's <b>Settings</b> dialog box. They allow you to limit the amount of images saved during test runs: <ul style="list-style-type: none"> <li>• <b>Enable storing of all images during a test.</b> Enables the storing of all images during a run. <div data-bbox="454 1018 1372 1096" style="background-color: #f0f0f0; padding: 5px;"> <p><b>Note:</b> Storing all images during a test may cause a delay due to traffic and increase the storage needs on the ALM repository.</p> </div> </li> <li>• <b>Enable storing of all images for a failed test. (Default)</b> Enables the storing of all images for a failed test during a run.</li> <li>• <b>Enable storing of all images for a failed step (tests with steps only).</b> Enables the storing of all images for a failed step during a run.</li> <li>• <b>Disable storing of images.</b> Disables the storing of any images during a run.</li> </ul> </li> <li>• Regardless of your selection, you can always attach screen captures to defects, both during your test, and at the end of your test from the test results.</li> </ul>
<b>Allow macros</b>	Enable recording and running macros in Sprinter. Macros are available only for tests run in Sprinter using Power Mode.
<b>Allow Data Injection</b>	Enable Sprinter's Data Injection feature, allowing you to automatically enter data into fields in your test application. Data Injection is available only for tests run in Sprinter using Power Mode.
<b>Allow editing of steps in Sprinter</b>	Enable adding, deleting, and modifying the name or description of steps in a test. If this option is cleared, you are still able to modify the actual results of a step and add screen captures to steps.
<b>Allow attaching movies to defects</b>	Enable attaching movies to defects when opening a defect from Sprinter's Tools sidebar, Workspace Tools sidebar, or from the test results. <ul style="list-style-type: none"> <li>• <b>Maximum movie length (minutes).</b> The maximum length of the movie that you can attach to a defect. The movie length for each defect is set in Sprinter's Smart Defect Settings dialog box. You can attach a movie to a defect, of a size that is up to the length of time defined by this setting. The maximum allowable length of a movie is 10 minutes.</li> </ul>

UI Elements	Description
	<p><b>Note:</b></p> <ul style="list-style-type: none"><li>• Increasing the length of movies that can be attached to defects may cause a delay in the time it takes to submit a defect to ALM and increase the storage needs of your ALM server.</li><li>• The length of the movie you can attach to a defect may be limited by the maximum size of an attachment you are allowed to attach to a defect in ALM.</li></ul>
<b>Show step snapshot as step attachment</b>	Sprinter allows you to attach snapshots to test steps. This parameter enables ALM to show the snapshots created in Sprinter as attachments of the test steps.



# Chapter 27: Generating Workflow Scripts

ALM provides script generators to enable you to perform commonly needed customizations on the Defects module dialog boxes.

For information on writing workflow scripts to customize the user interface and to control user actions in any ALM module, see ["Workflow Customization at a Glance" on page 333](#).

**Note:** Workflow scripts run with the privileges of the logged-on user, not the privileges of the user who created the script. As a result, a script fails if it attempts any action or data change that the logged-on user is not privileged to perform, or if it accesses any restricted object that the user is not privileged to use. Therefore, a script developed by a privileged user should be tested with users that belong to the groups expected to trigger the script.

This chapter includes:


- [About Generating Workflow Scripts](#) .....322
- [Customizing Defects Module Field Lists](#) ..... 323
- [Customizing Defects Module Dialog Boxes](#) .....325

## About Generating Workflow Scripts

The Workflow page provides links to script generators and a script editor. You can use the script generators to perform customizations on the input fields of the Defects module dialog boxes. You can use the script editor to create scripts to control the workflow in any ALM module.

**Performance Center:** The Workflow page is not supported in Lab Management.

To open the Workflow page, click the **Workflow** link in the Project Customization window.



The Workflow page contains the following links:

- **Script Generator - List Customization for Defects Module.** Enables you to customize the field lists displayed for fields on the dialog boxes and in the Defects Grid of the Defects module. For more information, see "[Customizing Defects Module Field Lists](#)" on the next page.
- **Script Generator - Add Defect Field Customization.** Enables you to modify the appearance of the New Defect dialog box. For more information, see "[Customizing Defects Module Dialog Boxes](#)" on page 325.
- **Script Generator - Defect Details Field Customization.** Enables you to modify the appearance of the Defect Details dialog box. For more information, see "[Customizing Defects Module Dialog Boxes](#)" on page 325.
- **Script Editor.** Enables you to write VBScript code to customize the ALM workflow in any module. You place your code in the appropriate ALM event so that the script is triggered when the relevant user action takes place. You can also use the script editor to modify scripts created by the script generators. For more information, see "[Workflow Customization at a Glance](#)" on page 333.

### Cross Project Customization

If you are working with a template project, in Project Customization, you use the **Workflow (Shared)**

link to customize workflow. Workflow customization created in a template project is applied to the linked projects when you apply the template customization. For more information on customizing workflow scripts as a part of cross process customization, see ["The Script Editor" on page 336](#).

ALM Editions: Cross project customization is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

## Customizing Defects Module Field Lists

A field list is a list of values displayed in a drop-down list, from which the user can choose a value for the field.

You can specify that a different field list be used for a Defects module field, depending on the value of another field. For example, you can set the **Detected in Versions** list to change depending on the value in the **Project** field.

**Note:** This script generator can be used to customize field lists in the Defects module only.


To customize a field list, you must define the following rules:



- **Primary/Secondary Rule.** Select the primary and secondary fields. When a primary field value is changed, the list of values in the secondary field changes automatically. For example, you could select **Project** as the primary field and **Detected in Versions** as the secondary field.
- **List Match Rule.** Select the list that you want to display in the secondary field for each value of the primary field.


**Note:** When workflow customization has been used to change a list of values for a field that has transition rules defined, the field may only be modified in a way that satisfies both the workflow script and the transition rules. For more information, see ["Setting Transition Rules" on page 216](#).



### To customize a field list:

1. In the Project Customization window, in the left pane, click **Workflow**. The Workflow page opens.
2. Click the **Script Generator - List Customization for Defects Module** link. The Script Generator - List Customization dialog box opens.



3. Under **Primary/Secondary Rule**, select the primary field and the secondary field:
  - To set a rule, click **<select primary>** and select a field name. Click **<select secondary>** and select a field name.
  - To add a new rule, click the **Add Primary/Secondary Rule** button . Select field names for **<select primary>** and **<select secondary>**.
  - To delete a rule, select the rule and click the **Delete Primary/Secondary Rule** button . Click **Yes** to confirm.
4. Under **Primary/Secondary Rule**, select the primary/secondary rule for which you want to set list match rules.



5. Under **List Match Rule**, select the field list to be used in the secondary field for specific values entered into the primary field:
  - To set a rule for a defined primary field value, click **<select list>** and select a list name.
  - To set a rule for an undefined primary field value, click **<enter value>** and type a primary field value. Press **Enter**. Click **<select list>** and select a list name.
  - To add a new list match rule, click the **Add List Match Rule** button . Click **<enter value>** and type a primary field value. Click **<select list>** and select a list name.
  - To delete a list match rule, select the rule and click the **Delete List Match Rule** button . Click **Yes** to confirm.
6. To save your changes, do one of the following:
  - Click the **Apply Script Changes** button to save your changes and close the script generator.
  - Click the **Apply & View** button to save your changes and view the generated script in the Script Editor.

If you use the Script Editor to modify a script that was created by a script generator, your modifications are overwritten the next time you run that script generator. It is recommended that you name the generated script before you modify it. For more information on the Script Editor, see ["Working with the Workflow Script Editor" on page 335](#).

## Customizing Defects Module Dialog Boxes

You can modify the appearance of the New Defect and Defect Details dialog boxes by setting different fields to be visible for each user group. You can also sort the order in which the fields are displayed on the dialog box for each user group.

**Note:** This workflow customization example can be modified to display fields only to specific user groups. However, this example only covers changing the fields available in a dialog box. To set which fields are visible to specific user groups in a module grid, use the Groups and Permissions module in Customization. For task information, see ["Hiding Data for a User Group" on page 219](#).

For example, you may want the **Assigned To** and **Priority** fields to appear only for a user that has developer privileges. Also, you can customize the **Assigned To** field so that it is displayed before the **Priority** field for this user group.


**Note:** To make fields invisible, set the **ENABLE\_COLUMN\_VISIBILITY\_TRACKING** parameter in the Site Configuration tab. For more information, see ["Setting ALM Configuration Parameters" on page 155](#).

To perform a customization for all user groups, you can use the script editor to write a script. For more information, see ["Example: Customizing a Defects Module Dialog Box" on page 389](#).


**Note:** These script generators can be used to customize dialog boxes in the Defects module only.

### To customize Defects module dialog boxes by user group:

1. In the Project Customization window, in the left pane, click **Workflow**. The Workflow page opens.
2. To modify the appearance of the New Defect dialog box, click the **Script Generator - Add Defect Field Customization** link. The Script Generator - Add Defect Field Customization dialog box opens.





To modify the appearance of the Defect Details dialog box, click the **Script Generator - Defect Details Field Customization** link. The Script Generator - Defect Details Field Customization dialog box opens.



**Available Fields** contains the names of all the fields you can display. **Visible Fields** contains the names of the fields that can currently be seen by the selected user group, and their sorting priority.

3. From the **User Group** list, select the user group to which the customizations are to apply.
4. Choose field names and click the arrow buttons (> and <) to move a name between **Available Fields** and **Visible Fields**. Click the double arrow buttons (>> and <<) to move all the names from one list to the other. You can also drag the field names between lists.
5. In **Visible Fields**, to set a field as a required field, select the check box next to it. For a required

field, a value is mandatory. Its title is displayed in red in the Add Defect or Defect Details dialog box.

6. You can set the order in which fields are displayed for the selected user group by using the up and down arrows  . You can also drag the field names up or down.
7. You can set the Add Defect and Defect Details dialog boxes to include one or more input pages. By default, all fields are displayed on one page. Use the up and down arrows to move fields to the appropriate page.
8. To save your changes, do one of the following:
  - Click the **Apply Script Changes** button to save your changes and close the script generator.
  - Click the **Apply & View** button to save your changes and view the generated script in the Script Editor.

If you use the Script Editor to modify a script that was created by a script generator, your modifications are overwritten the next time you run that script generator. It is recommended that you rename the generated script before you modify it. For more information on the Script Editor, see ["Working with the Workflow Script Editor" on page 335](#).





## Chapter 28: Managing Analysis Menus

The Analysis View module's Analysis Menu tab enables you to manage the behavior of graphs and project reports that are generated from within the following modules: Requirements, Test Plan, Test Lab, Defects, and Business Components.

The tab lists all graphs and project reports grouped per module. You can perform the following tasks for each individual module:

- Add or remove graphs or project reports
- Configure graphs or project reports
- View graph or project report details
- Generate graphs or project reports
- Preview project reports



## Part 3: Workflow Customization




# Chapter 29: Workflow Customization at a Glance

You can write workflow scripts to customize the HP Application Lifecycle Management (ALM) user interface, and to control the actions that users can perform.

## To customize workflow:

1. In the Project Customization window, in the left pane, click **Workflow**. The Workflow page opens.



2. To customize a Defects module dialog box, click the appropriate **Script Generator** link on the Workflow page. You need not be familiar with VBScript, or with ALM events and objects to use this feature. For more information, see ["Generating Workflow Scripts" on page 321](#).
3. To write or modify scripts by entering code into the appropriate event procedures, open the Script Editor. To create workflow scripts, you must be familiar with VBScript. You can open the Script Editor either from a script generator or directly:
  - To write a script that is similar to a script created by a script generator, click the relevant **Script Generator** link and set the customization you want to perform. Click the **Apply & View** button on the script generator dialog box. The Script Editor opens to display the scripts that were generated.
  - To create your own scripts, click the **Script Editor** link. The Script Editor opens to display a Scripts Tree that lists the existing event procedures.

For more information on the Script Editor, see ["Working with the Workflow Script Editor" on page 335](#).

4. Decide which ALM event should trigger your script. You must place your code in the procedure of the appropriate module and event so that it is invoked for the relevant user action. For more information, see ["Workflow Event Reference" on page 347](#).
5. Decide which ALM objects your script must access. Your script performs customizations based on information obtained from the relevant objects. You customize the workflow by using the

methods and properties of the objects. For more information, see ["Workflow Object and Property Reference" on page 371](#).

6. Examine the sample scripts to find one that can be adapted for your use. Sample scripts are provided in this guide and in the HP Self-solve knowledge base. Scripts generated by the workflow script generators can also be used as a basis for your scripts.
  - For examples of common customizations that can be performed by using workflow scripts, see ["Workflow Examples and Best Practices" on page 381](#).
  - For an index to knowledge base articles that provide examples of workflow scripts, see [HP Software Self-solve knowledge base article KM183671](#) (<http://h20230.www2.hp.com/selfsolve/document/KM183671>).

**Tip:** Turning off versioning for relevant fields enables workflow scripts and OTA scripts to run without requiring entities to be checked in.

# Chapter 30: Working with the Workflow Script Editor

You can use the Script Editor to create workflow scripts to customize the user interface, and to control user actions.

This chapter includes:

- [About Working with the Workflow Script Editor](#) ..... 336
- [The Script Editor](#) ..... 336
- [Creating a Workflow Script](#) ..... 339
- [Adding a Button to a Toolbar](#) ..... 341
- [Setting the Properties of the Script Editor](#) ..... 343

## About Working with the Workflow Script Editor


You can use the Script Editor to create workflow scripts and to add a toolbar button to the window of an HP Application Lifecycle Management (ALM) module.

The Script Editor dialog box contains two tabs:

- **Script Editor tab.** You use the Script Editor tab to create and edit workflow scripts. The Script Editor assists you in placing your code in the appropriate ALM event procedure. For more information on using the Script Editor, see ["Creating a Workflow Script" on page 339](#).
- **Toolbar Button Editor tab.** You use the Toolbar Button Editor tab to add a toolbar button to the window of an ALM module. For more information, see ["Adding a Button to a Toolbar" on page 341](#).

## The Script Editor

You can use the Script Editor to modify scripts that have been generated by a script generator, or to create a user-defined workflow script. For information on opening the Script Editor, see ["Workflow Customization at a Glance" on page 333](#).



The Script Editor tab contains the following elements:

- **Script Editor toolbar.** Contains buttons used when creating scripts. For more information, see ["Understanding the Script Editor Commands" on page 338](#).
- **Scripts Tree.** Lists the event procedures to which you can add code. The event procedures are grouped by the module in which they are triggered. For more information, see ["Workflow Event Reference" on page 347](#).
- **Scripts pane.** Displays the code of the selected event procedure. To create or modify a script, you add VBScript code to the event procedure. For more information, see ["Creating a Workflow Script" on page 339](#).
- **Messages pane.** Displays any syntax errors encountered when you save or validate a script.



## Cross Project Customization

ALM Editions: Cross project customization is not available for **Quality Center Enterprise Edition**. For more information about ALM editions and their functionality, see the *HP Application Lifecycle Management User Guide*.

If you are working in a template or linked project, the Scripts Tree displays two sections under Workflow Scripts:

- **Template Scripts (Shared)**. Workflow scripts listed in this section are the scripts applied from the template to the linked project. For more information on applying template customization, see ["Applying Template Customization to Linked Projects" on page 263](#).

If you are working with a linked project, this section is displayed only when there are template scripts defined in the template. The template scripts cannot be edited in the linked project. If you remove a project from a template, the template scripts remain in the project and are editable.

- **Project Scripts**. Workflow scripts listed in this section apply only to the template or linked project in which you are working. Scripts in this section of a template are not applied to linked projects.

When running workflow scripts for a linked project, ALM combines template scripts and project scripts into one script. Duplicate variables or functions in the template scripts and projects scripts can cause conflicts.

Additional considerations when working in a template project:

- Scripts generated by one of the script generators are created under **Template Scripts (Shared)**.
- ALM adds the prefix **Template\_** to events in template scripts. By default, ALM triggers template event procedures. The project event procedure is triggered if the template event procedure does not exist, or if you instruct the template event procedure to call the project event procedure.

Each template event includes a commented call to the parallel project event. For example, the Template\_Bug\_New event in the template script is displayed as follows:

















```
Sub Template_Bug_New
  On Error Resume Next
  `call Bug_New
  On Error Go To 0
End Sub
```





To instruct the template script to call the project event, remove the comment marker to activate the call to the project event, as follows:

```
Sub Template_Bug_New
  On Error Resume Next
  call Bug_New
  On Error Go To 0
End Sub
```

## Understanding the Script Editor Commands

The Script Editor toolbar, menu bar, and right-click menu contain the following buttons and menu commands:

UI Element	Description
	<b>Save.</b> Saves the changes made to scripts in the selected module.
	<b>Print.</b> Prints the displayed script.
	<b>Undo.</b> Reverses the last command or deletes the last entry you typed.
	<b>Redo.</b> Reverses the action of your last <b>Undo</b> command.
	<b>Cut.</b> Removes the selected text and places it on the Clipboard.
	<b>Copy.</b> Copies the selected text to the Clipboard.
	<b>Paste.</b> Inserts the contents of the Clipboard at the insertion point.
	<b>Delete.</b> Deletes the selected text.
	<b>Find.</b> Searches for specified text in the scripts of the selected module.
	<b>Find Next.</b> Finds the next occurrence of the text specified in the Find Text dialog box.
	<b>Replace.</b> Replaces the specified text with replacement text.
	<b>Synchronize Tree with Script.</b> Refreshes the Scripts Tree to reflect procedures you have added, deleted or renamed.
	<b>Field Names.</b> Displays a list of field names in the project that you can insert into your script.
	<b>Code Complete.</b> Displays a list of objects, properties, methods, or field names that you can insert into your script.
	<b>Code Template.</b> Displays a list of templates for commonly used VBScript statements that you can insert into your script.
	<b>List Value.</b> Opens the Select Value From List dialog box, to enable you to choose an item from a project list.


UI Element	Description
	<b>Syntax Check.</b> Validates the syntax of your script and displays any messages in the Messages pane.
	<b>Show/Hide Scripts Tree.</b> Displays or hides the Scripts Tree. If you have opened the Script Editor from a script generator, this is not available.
	<b>Show/Hide Messages Pane.</b> Displays or hides the Messages pane.
	<b>Properties.</b> Opens the Properties dialog box, enabling you to change the properties of the Script Editor. For more information, see <a href="#">"Setting the Properties of the Script Editor" on page 343</a> .
<b>Save All</b>	To save script changes in all modules, choose <b>File &gt; Save All</b> .
<b>Revert to Saved</b>	To return to a saved version of a module, select a changed module and choose <b>File &gt; Revert to Saved</b> .
<b>Select All</b>	To select all text in the scripts pane, choose <b>Edit &gt; Select All</b> .
<b>Expand All</b>	To expand all nodes in the Scripts Tree, choose <b>View &gt; Expand All</b> .
<b>Collapse All</b>	To collapse all nodes in the Scripts Tree, choose <b>View &gt; Collapse All</b> .
<b>Go to Line Number</b>	To jump to a specific line in the Script Editor, choose <b>Search &gt; Go to Line Number</b> .
<b>Clear Messages</b>	To clear syntax messages displayed in the messages pane, choose <b>Tools &gt; Clear Messages</b> .
<b>Sort Field Names by Field Labels</b>	When you choose the <b>Field Names</b> option, the Script Editor sorts the list by the field name used in the ALM database table (for example, <b>BG_BUG_ID</b> ). To sort the fields by the field label (for example, Defect ID) right-click the script pane and choose <b>Sort Field Names by Field Labels</b> .
<b>VBScript Home Page</b>	To get help for the VBScript language, choose <b>Help &gt; VBScript Home Page</b> .

## Creating a Workflow Script

You use the Script Editor to add VBScript code to an ALM event procedure, or to create user-defined procedures that can be called from an ALM event procedure.

To create a workflow script:

1. In the Workflow window, click the **Script Editor** link. The Script Editor opens.






For more information on the Script Editor window, see ["The Script Editor" on page 336](#).

2. In the Scripts Tree, select the node of the module for which you need to customize the workflow.  
The Scripts Tree contains the **Common script** node in addition to the nodes for specific modules. When you create user-defined procedures that must be accessible from several modules, place them under the **Common script** node. To declare a global variable that can be used across all modules, declare the variable under the **Common script** node, outside of any function.
3. Expand the node and select the event procedure to which you need to add code, depending on when you want your code to be triggered. The existing script for this event procedure is displayed in the Scripts pane.

For a description of ALM event procedures, see ["Workflow Event Reference" on page 347](#).





4. Add your VBScript code to the script.

**Note:** A red indicator  next to a module name in the Scripts Tree indicates that there are unsaved script changes in that module.

5. To use the code complete feature instead of typing in the names of ALM objects, properties, methods, and fields, place the insertion point at the location where you want to insert an object name and click the **Code Complete**  button. For information about ALM objects, see ["Workflow Object and Property Reference" on page 371](#).
6. To use the code template feature instead of typing in commonly used VBScript statements, place the insertion point where you want to insert the code and click the **Code Template**  button. Choose one of the following items from the code template list:

Template	Code Added to Script
<b>FVal:</b> Fields value access	Fields.Field(" ").Value

Template	Code Added to Script
<b>List:</b> QualityCenter list access	<code>Lists.List()</code>
<b>IfAct:</b> Action "switch" If Block	<code>If ActionName = "" Then End IF</code>
<b>Act:</b> Actions access	<code>Actions.Action("")</code>
<b>Func:</b> Function template	<code>Function     On Error Resume Next     On Error GoTo 0 End Function</code>
<b>Sub:</b> Sub Template	<code>Sub     On Error Resume Next     On Error GoTo 0 End Sub</code>
<b>Err:</b> Error Handler	<code>On Error Resume Next</code>


- To insert an item from a field list defined in the project, place the insertion point at the location where you want to add the item. Click the **List Value**  button. In the **Lists** box of the Select Value From List dialog box, choose the name of the list. In the **List Items** box, select the list value.
- To insert an ALM field name, place the insertion point at the location where you want to add the field name. Click the **Field Names**  button. Select a name from the list of system and user-defined fields in the ALM project.
- To validate the syntax of the script, click **Syntax Check** . Any messages are displayed in the Messages pane.
- Click the **Save** button  to save the script.
- Close the Script Editor.

## Adding a Button to a Toolbar

You can use the Toolbar Button Editor to define a toolbar button to be displayed on the window of an ALM module, or on the Manual Runner dialog box.

To add a button to a toolbar:

1. In the Script Editor, click the **Toolbar Button Editor** tab.



2. From the **Command bar** list, select the toolbar to which you want to add a button:

Option	Toolbar Location
Requirements	Requirements module window.
TestPlan	Test Plan module window.
TestLab	Test Lab module window.
ManualRun	Manual Runner dialog box.
Defects	Defects module window.
Component	Business Components module window. This option depends on your ALM license.
Releases	Releases module window.
Resources	Test Resources module window.
Analysis	Analysis module window.
Dashboard	Dashboard module window.
BusinessModels	Business Models module window.
Libraries	Libraries module window.
TestRuns	Test Runs module window.

3. Click **Add**. A default command name for the button is added to the **Commands** list.
4. In the **Caption** box, type a new command name for the button, or use the default name.
5. In the **Hint** box, type a tooltip for the button.
6. In the **Action Name** box, type a new action name for the button, or use the default name.
7. Under **Images**, select an icon for the button.
8. Click **Apply** to apply your changes.

9. To delete a button that you have created, select its command name in the Commands list, and click **Remove**.



10. Click the **Save** button to save the new button definition.
11. Click the **Script Editor** tab.
12. In the Scripts Tree of the Script Editor, select the **ActionCanExecute** event procedure located in the common script section.
13. In the procedure displayed in the scripts pane of the Script Editor, add statements to be performed if the user initiates an action with the action name you defined for the button. Set the return value to True or False.

For example, the following code opens a message box when the user clicks the Requirements\_Action1 button on the tool bar of the Requirements module:

```
Function ActionCanExecute(ActionName)
    On Error Resume Next
    ActionCanExecute = True
    If ActionName = "UserDefinedActions.Requirements_Action1" Then
        MsgBox "You clicked the Action1 button."
    End If
    On Error GoTo 0
End Function
```

For more information, see ["Example: Adding Button Functionality" on page 398](#).



14. Click the **Save** button to save the script.


## Setting the Properties of the Script Editor

You can customize the behavior of the Script Editor.

**To set the properties of the Script Editor:**



1. In the Script Editor, click the **Properties** button or choose **Options > Editor Properties**. The Properties dialog box opens.



2. In the **Editor** tab, you can set the following options:

Option	Description
<b>Auto indent mode</b>	Places the cursor under the first non-blank character of the preceding non-blank line when you press <b>Enter</b> .
<b>Smart tab</b>	Tabs to the first non-blank character in the preceding non-blank line. If <b>Use tab character</b> is selected, this option is cleared.
<b>Use tab character</b>	Inserts a tab character. If cleared, inserts space characters. If <b>Smart tab</b> is selected, this option is cleared.
<b>Backspace unindents</b>	Aligns the insertion point to the previous indentation level when you press <b>Backspace</b> , if the cursor is on the first non-blank character of a line.
<b>Show line numbers</b>	Displays line numbers. If this option is selected, <b>Show line numbers on gutter</b> is enabled.
<b>Show line numbers on gutter</b>	Displays line numbers in the gutter instead of in the left margin. If <b>Show line numbers</b> is selected, this option is enabled.
<b>Group undo</b>	Reverses your last editing command and any subsequent editing commands of the same type, if you press <b>Alt+Backspace</b> or choose <b>Edit &gt; Undo</b> .
<b>Cursor beyond EOF</b>	Enables you to place the insertion point after the last line of code.
<b>Cursor beyond EOL</b>	Enables you to position the cursor after the end of the line.
<b>Selection beyond EOL</b>	Enables you to select characters beyond the end of the line.



Option	Description
<b>Keep trailing blanks</b>	Keeps any blank spaces you have at the end of a line.
<b>Persistent blocks</b>	Keeps marked blocks selected, even when the cursor is moved using the arrow keys, until a new block is selected.
<b>Overwrite blocks</b>	Replaces a marked block of text with new text. If <b>Persistent Blocks</b> is also selected, text you enter is appended following the currently selected block.
<b>Double click line</b>	Highlights the line when you double-click any character in the line. If disabled, only the selected word is highlighted.
<b>Find text at cursor</b>	Places the text at the cursor into the <b>Text To Find</b> list box in the Find Text dialog box when you choose <b>Search &gt; Find</b> .
<b>Force cut and copy enabled</b>	Enables the <b>Cut</b> and <b>Copy</b> commands, even when there is no text selected.
<b>Use syntax highlight</b>	Displays script elements according to colors and attributes defined in the <b>Display</b> tab and <b>Colors</b> tab.
<b>Overwrite cursor as block</b>	Controls the appearance of the caret when using the Overwrite mode.
<b>Disable dragging</b>	Disables dragging and dropping text.
<b>Block indent</b>	Specifies the number of spaces to indent a marked block.
<b>Tab stops</b>	Specifies the locations to which the cursor moves when you press <b>Tab</b> .
<b>Keymapping</b>	Sets the keyboard mappings in the Script Editor. Supports the following keyboard mappings: Default, Classic, Brief, Epsilon, and Visual Studio.

3. In the **Display** tab, you can set the following options:

Option	Description
<b>Editor gutter</b>	Enables you to set the visibility, width, color, and style of the gutter.
<b>Editor margin</b>	Enables you to set the visibility, width, color, style, and position of the right margin.
<b>Use mono font</b>	Displays only monospaced screen fonts, such as Courier, in the Editor font box.
<b>Editor font</b>	Lists the available text fonts.
<b>Editor color</b>	Lists the available background colors.
<b>Size</b>	Lists font sizes.
<b>Use Read-Only Color</b>	Enables you to select a color for displaying read-only text from the Read-Only Color box.
<b>Draw Special Symbols</b>	Sets special characters for displaying end-of-file, end-of-line, space, and tab characters.

4. In the **Colors** tab, you can set the following options:

Option	Description
<b>Color SpeedSetting</b>	Enables you to configure the Script Editor display using predefined color combinations.

Option	Description
<b>Element</b>	Specifies syntax highlighting for a particular code element.
<b>Foreground color</b>	Sets the foreground color for the selected code element.
<b>Background color</b>	Sets the background color for the selected code element.
<b>Use defaults for</b>	Displays the code element using default system colors for the foreground, background, or both.
<b>Text attributes</b>	Specifies format attributes for the code element.
<b>Open</b>	Loads a color scheme from your computer .
<b>Save</b>	Saves a color scheme to your computer.

# Chapter 31: Workflow Event Reference

You can write workflow scripts to customize the actions that HP Application Lifecycle Management (ALM) users can perform, and the fields that are available to users in dialog boxes. To write a workflow script, you add VBScript code to event procedures that are triggered by user actions.

This chapter includes:

- [About ALM Events](#) ..... 348
- [Naming Conventions for ALM Event Procedures](#) ..... 348
- [Reference for ALM Events](#) ..... 350

## About ALM Events

During an ALM user session, as the user initiates various actions, ALM triggers event procedures. You can place code in these procedures to customize the execution of the associated user actions.

The Script Editor lists the event procedures for each ALM module, and allows you to add your code to the appropriate procedure. For more information, see ["Working with the Workflow Script Editor" on page 335](#).

The code you add to the event procedures can access ALM objects. For more information, see ["Workflow Object and Property Reference" on page 371](#).

Event procedures can be functions or subroutines:

- **Event functions.** These procedures are triggered by ALM to check whether the user's action should be performed. You can place code in these functions to determine whether ALM may execute the user's request. If your code returns a value of `False`, ALM does not proceed with the action.

For example, when a user clicks the **Submit** button on the Add Defect dialog box, ALM invokes the function `Bug_CanPost` before posting the defect to the database on the server. You can add code to the `Bug_CanPost` function to control whether ALM posts the defect. For example, you can ensure that a user cannot reject a defect without adding a comment. For example, see ["Example: Object Validation" on page 394](#).

- **Event subroutines.** These procedures are triggered to perform actions when an event takes place.

For example, when a user opens the Add Defect dialog box, ALM invokes the subroutine `Bug_New`. You can add code to the `Bug_New` subroutine to perform actions that should be performed when a user opens the dialog box. For example, you can change the value of the **Detection Mode** field to `BTW` if the user is not in the `QA Tester` user group. For example, see ["Example: Changing a Field Based on the User Group" on page 393](#).

**Version Control:** After enabling version control for a project, you should review all its workflow scripts and make adjustments for each checked in entity. This includes the following entities: **Req**, **Test**, **Resource**, and **Component**. For each checked in entity that includes a **Post** function in its script, you must modify the script. To modify, add a **Checkout** function before every **Post** function. Making this modification prevents the Check Out dialog box from opening each time a call to a **Post** function is made. For more information about the Post and Checkout functions, see the *HP ALM Open Test Architecture Reference*.

For more information on version control, refer to the *HP Application Lifecycle Management User Guide*.

## Naming Conventions for ALM Event Procedures

The naming convention for an event procedure is as follows:

<entity>\_<event>

See ["Entity" on the next page](#) and ["Event" on page 350](#) for more details.

**Note:**

- For backwards compatibility, the previous naming convention, including the module name, is still supported. However, we recommend you use the new naming conventions instead.
- Some event procedure names do not include an entity name. For example, the `GetDetailsPageName` event name does not include an entity name.

## Entity

An **Entity** can be one of the following:

Entity	Description
Release	Release data
Release Folder	Release folder data
Cycle	Release cycle data
Library	Library data
Library Folder	Library folder data
Baseline	Baseline data
Req	Requirement data
Test	Test data
DesignStep	Design step data
Resource	Test resource data
Resource Folder	Test resource folder data
TestSet	Test set data
TestSetTests	Test instance data
Run	Test run data
Bug	Defect data
Step	Test run step data
AnalysisItem	Reports and graphs data
AnalysisItemFolder	Reports and graphs folder data
DashboardFolder	Dashboard folder data
DashboardPage	Dashboard page data
Component	Business component data
ComponentStep	Business component step data
ComponentFolder	Business component folder data
BusinessModel	Business model data
BusinessModelActivity	Business model activity data

Entity	Description
<b>BusinessModelPath</b>	Business model path data
<b>BusinessModelFolder</b>	Business model folder data

## Event

The **Event** can be either a function name or a subroutine name. The event names are listed in ["Reference for ALM Events" below](#).

## Reference for ALM Events

This section contains an alphabetical reference of the ALM event functions and subroutines. It includes the event name, description, syntax, type (Function or Sub), the value returned by a function, and the entities for which the event procedure is available.

For information on the naming conventions for event procedures, see ["Naming Conventions for ALM Event Procedures" on page 348](#).

The following event functions are available:

Function Name	When the Function is Triggered
<a href="#">"ActionCanExecute" on page 352</a>	before performing a user action
<a href="#">"Attachment_CanDelete" on page 353</a>	before deleting an attachment
<a href="#">"Attachment_CanOpen" on page 354</a>	before opening an attachment
<a href="#">"Attachment_CanPost" on page 354</a>	before updating an attachment
<a href="#">"CanAddTests" on page 355</a>	before adding tests to a test set
<a href="#">"CanCustomize" on page 355</a>	before opening Customization window
<a href="#">"CanDelete" on page 356</a>	before deleting an object from the server
<a href="#">"CanLogin" on page 358</a>	before a user logs in to the project
<a href="#">"CanLogout" on page 358</a>	before a user logs out of the project
<a href="#">"CanPost" on page 358</a>	before posting an object to the server
<a href="#">"CanRemoveTests" on page 360</a>	before removing tests from a test set
<a href="#">"CanAddComponentsToTest" on page 354</a>	before adding business components to a test of type Flow or Business-Process
<a href="#">"CanAddFlowsToTest" on page 355</a>	before adding flows to a test of type Business-Process
<a href="#">"CanRemoveComponentsFromTest" on page 360</a>	before removing business components from a test of type Flow or Business-Process
<a href="#">"CanRemoveFlowsFromTest" on page 360</a>	before removing flows from a test of type Business-Process

Function Name	When the Function is Triggered
"CanDeleteGroupsFromTest" on page 358	before deleting groups from a test of type Flow or Business-Process
"CanReImportModels" on page 359	before importing business models
"DefaultRes" on page 360	before resetting project defaults
"FieldCanChange" on page 362	before changing a field value
"GetDetailsPageName" on page 364	before displaying Defect Details dialog box
"GetNewBugPageName" on page 364	before displaying Add Defect dialog box (for backward compatibility)
"GetNewReqPageName" on page 365	before displaying New Requirement dialog box (for backward compatibility)
"GetReqDetailsPageName" on page 365	before displaying Requirement Details dialog box (for backward compatibility)

The following event subroutines are available:

Subroutine Name	When the Subroutine is Triggered
"AddComponentToTest" on the next page	a component has been added to a test of type Flow or Business-Process
"AfterPost" on the next page	an object has been posted to the server
"Attachment_New" on page 354	an attachment is added
"DialogBox" on page 361	a dialog box is opened or closed
"EnterModule" on page 361	user switches modules
"ExitModule" on page 361	user exits a module
"FieldChange" on page 363	a field value changes
"MoveTo" on page 366	user changes focus
"MoveToComponentFolder" on page 367	user moves to the specified component folder in the business component tree (for backward compatibility)
"MoveToFolder" on page 367	user clicks a folder in the test sets tree (for backward compatibility)
"MoveToSubject" on page 367	user clicks a subject in the test plan tree (for backward compatibility)
"New" on page 368	an object is added
"RemoveComponentFromTest" on page 369	user removes a component from a test of type Flow or Business-Process
"RunTests" on page 369	user clicks <b>Run</b> in the Test Lab module (provided that Sprinter is not installed and none of the tests is automated)
"RunTests_Sprinter" on page 369	user clicks <b>Run</b> in the Test Lab module (provided that Sprinter is installed and at least one test is automated)
"RunTestSet" on page 370	user clicks <b>RunTest Set</b> in the Test Lab module
"RunTestsManually" on page 370	user clicks <b>Run &gt; Run Manually</b> in the Test Lab module

## ActionCanExecute

This event is triggered before ALM performs an action that has been initiated by the user, to check whether the action can be executed.

You can add code to this event procedure to perform actions when the user has initiated a particular action, or to prevent the action from being executed in specific cases. For example, see ["Example: Controlling User Permissions" on page 397](#).

<b>Syntax</b>	<b>ActionCanExecute(ActionName)</b> where <b>ActionName</b> is the action that the user has initiated. Actions are in the format <b>context.action</b> .  <b>Note:</b> The previous format for this event is supported for purposes of backward compatibility. We recommend you use ActionCanExecute instead.  User-defined actions start with the prefix <code>UserDefinedActions</code> .
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	ActionCanExecute (all modules)

**Tip:** To obtain the name of an action, see the sample code on ["Action Object" on page 373](#).

## AddComponentToTest

This event is triggered when the user adds a component to a test of type Flow or Business-Process in the Test Script tab.

**Version Control:** Changing components checked in or checked out by another user, using the AddComponentToTest event, is not supported.

<b>Syntax</b>	<b>AddComponentToTest</b>
<b>Type</b>	Sub
<b>Availability</b>	AddComponentToTest

## AfterPost

This event is triggered after an object has been posted to the server.

Project fields should not be changed after they have been posted, because then the new value is not stored in the database.

<b>Syntax</b>	<b>&lt;entity&gt;_AfterPost</b>
<b>Type</b>	Sub



<b>Availability</b>	<ul style="list-style-type: none"> <li>• AnalysisItem_AfterPost</li> <li>• AnalysisItemFolder_AfterPost</li> <li>• Baseline_AfterPost</li> <li>• Bug_AfterPost</li> <li>• BusinessModel_AfterPost</li> <li>• BusinessModelFolder_AfterPost</li> <li>• BusinessModelPath_AfterPost</li> <li>• Component_AfterPost</li> <li>• ComponentFolder_AfterPost</li> <li>• Cycle_AfterPost</li> <li>• DashboardFolder_AfterPost</li> <li>• DashboardPage_AfterPost</li> <li>• Library_AfterPost</li> <li>• LibraryFolder_AfterPost</li> <li>• Release_AfterPost</li> <li>• ReleaseFolder_AfterPost</li> <li>• Req_AfterPost</li> <li>• Resource_AfterPost</li> <li>• ResourceFolder_AfterPost</li> <li>• Run_AfterPost</li> <li>• Step_AfterPost</li> <li>• Test_AfterPost</li> <li>• TestConfiguration_AfterPost</li> <li>• TestFolder_AfterPost</li> <li>• TestSet_AfterPost</li> <li>• TestSetFolder_AfterPost</li> </ul>
---------------------	--

## Attachment\_CanDelete

This event is triggered before ALM deletes an attachment from the server, to check whether that attachment can be deleted.

<b>Syntax</b>	<b>Attachment_CanDelete(Attachment)</b> where <b>Attachment</b> is the <b>IAttachment</b> interface. For more information, refer to the <i>HP ALM Open Test Architecture API Reference</i> .
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	Attachment_CanDelete (all modules)

## Attachment\_CanOpen

This event is triggered before ALM opens an attachment from the server, to check whether the attachment can be opened.

<b>Syntax</b>	<b>Attachment_CanOpen(Attachment)</b> where <b>Attachment</b> is the <b>IAttachment</b> interface. For more information, refer to the <i>HP ALM Open Test Architecture API Reference</i> .
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	Attachment_CanOpen (all modules)

## Attachment\_CanPost

This event is triggered before ALM updates an existing attachment on the server, to check whether the attachment can be updated.

<b>Syntax</b>	<b>Attachment_CanPost(Attachment)</b> where <b>Attachment</b> is the <b>IAttachment</b> interface. For more information, refer to the <i>HP ALM Open Test Architecture API Reference</i> .
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	Attachment_CanPost (all modules)

## Attachment\_New

This event is triggered when an attachment is added to ALM.

<b>Syntax</b>	<b>Attachment_New(Attachment)</b> where <b>Attachment</b> is the <b>IAttachment</b> interface. For more information, refer to the <i>HP ALM Open Test Architecture API Reference</i> .
<b>Type</b>	Sub
<b>Availability</b>	Attachment_New (all modules)

## CanAddComponentsToTest

This event is triggered before ALM adds business components to a test of type Flow or Business-Process, to check whether the specified components can be added.

<b>Syntax</b>	<b>CanAddComponentsToTest(Components)</b> where <b>Components</b> is an array of component IDs.
---------------	--

<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanAddComponentsToTest

## CanAddFlowsToTest

This event is triggered before ALM adds flows to a test of type Business-Process, to check whether the specified flows can be added.

<b>Syntax</b>	<b>CanAddFlowsToTest(Flows)</b> where <b>Flows</b> is an array of flow IDs.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanAddFlowstoTest

## CanAddTests

This event is triggered before ALM adds tests to a test set, to check whether the specified tests can be added.

<b>Syntax</b>	<b>&lt;entity&gt;_CanAddTests(Tests)</b> where <b>Tests</b> is an array of Test IDs.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	TestSet_CanAddTests

## CanCustomize

This event is triggered when a user attempts to open the Customization window, to check whether the specified user can customize the specified project.

<b>Syntax</b>	<b>CanCustomize(DomainName, ProjectName, UserName)</b> where <b>DomainName</b> is the domain name, <b>ProjectName</b> is the project name, and <b>UserName</b> is the user name.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanCustomize (all modules)

## CanDelete

This event is triggered before ALM deletes an object from the server, to check if the object can be deleted.

<b>Syntax</b>	<b>&lt;entity&gt;_CanDelete(Entity)</b>
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	<ul style="list-style-type: none"> <li>• AnalysisItem_CanDelete</li> <li>• AnalysisItemFolder_CanDelete</li> <li>• Baseline_CanDelete</li> <li>• Bug_CanDelete</li> <li>• BusinessModel_CanDelete</li> <li>• BusinessModelFolder_CanDelete</li> <li>• BusinessModelPath_CanDelete</li> <li>• Component_CanDelete</li> <li>• ComponentFolder_CanDelete</li> <li>• Cycle_CanDelete</li> <li>• DashboardFolder_CanDelete</li> <li>• DashboardPage_CanDelete</li> <li>• Library_CanDelete</li> <li>• LibraryFolder_CanDelete</li> <li>• Release_CanDelete</li> <li>• ReleaseFolder_CanDelete</li> <li>• Req_CanDelete</li> <li>• Resource_CanDelete</li> <li>• ResourceFolder_CanDelete</li> <li>• Test_CanDelete</li> <li>• TestConfiguration_CanDelete</li> <li>• TestFolder_CanDelete</li> <li>• TestSet_CanDelete</li> <li>• TestSetFolder_CanDelete</li> </ul>

## Additional Syntax for Backward Compatibility

For purposes of backward compatibility, the following syntaxes are also available for certain objects. However, we recommend you use `CanDelete` instead.

- The syntax for tests or test subject folders:

<b>Syntax</b>	<b>Test_CanDelete(Entity, IsTest)</b> where: <ul style="list-style-type: none"> <li><b>Entity</b> is the test or subject folder.</li> <li>If <b>IsTest</b> is <code>True</code>, <b>Entity</b> refers to an <code>ITest</code> object.</li> <li>If <b>IsTest</b> is <code>False</code>, <b>Entity</b> refers to an <code>ISubjectNode</code> object. For more information on <code>ITest</code> and <code>ISubjectNode</code>, refer to the <i>HP ALM Open Test Architecture API Reference</i>.</li> </ul>
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	<code>Test_CanDelete</code>

- The syntax for test sets or test set folders:

<b>Syntax</b>	<b>TestSet_CanDelete(Entity, IsTestSet)</b> where: <ul style="list-style-type: none"> <li><b>Entity</b> is the test set or test set folder.</li> <li>If <b>IsTestSet</b> is <code>True</code>, <b>Entity</b> refers to an <code>ITestSet</code> object.</li> <li>If <b>IsTestSet</b> is <code>False</code>, <b>Entity</b> refers to an <code>ITestSetFolder</code> object. For more information on <code>ITestSet</code> and <code>ITestSetFolder</code>, refer to the <i>HP ALM Open Test Architecture API Reference</i>.</li> </ul>
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	<code>TestSet_CanDelete</code>

- The syntax for business components or business component folders:

<b>Syntax</b>	<b>Component_CanDelete(Entity, IsComponent)</b> where: <ul style="list-style-type: none"> <li><b>Entity</b> is the component or component folder.</li> <li>If <b>IsComponent</b> is <code>True</code>, <b>Entity</b> refers to an <code>IComponent</code> object.</li> <li>If <b>IsComponent</b> is <code>False</code>, <b>Entity</b> refers to an <code>IComponentFolder</code> object. For more information on <code>IComponent</code> and <code>IComponentFolder</code>, refer to the <i>HP ALM Open Test Architecture API Reference</i>.</li> </ul>
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	<code>Component_CanDelete</code>

## CanDeleteGroupsFromTest

This event is triggered when a user removes groups from a test of type Flow or Business-Process, to check whether the specified groups can be removed.

<b>Syntax</b>	<b>CanDeleteGroupsFromTest(Groups)</b> where <b>Groups</b> is an array of group IDs.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanDeleteGroupsFromTest

## CanLogin

This event is triggered to check whether the specified user can log in to the specified project.

<b>Syntax</b>	<b>CanLogin(DomainName, ProjectName, UserName)</b> where <b>DomainName</b> is the domain name, <b>ProjectName</b> is the project name, and <b>UserName</b> is the user name.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanLogin (all modules)

## CanLogout

This event is triggered to check whether the current user can log out of the current project.

<b>Syntax</b>	<b>CanLogout</b>
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanLogout (all modules)

## CanPost

This event is triggered before ALM posts an object to the server, to check whether the object can be posted.

You can add code to this event procedure to prevent an object from being posted in specific cases. For example, see ["Example: Object Validation" on page 394](#).

<b>Syntax</b>	<b>&lt;entity&gt;_CanPost</b>
---------------	-------------------------------

Type	Function
Returns	True or False
Availability	<ul style="list-style-type: none"> <li>• AnalysisItem_CanPost</li> <li>• AnalysisItemFolder_CanPost</li> <li>• Baseline_CanPost</li> <li>• Bug_CanPost</li> <li>• BusinessModel_CanPost</li> <li>• BusinessModelFolder_CanPost</li> <li>• BusinessModelPath_CanPost</li> <li>• Component_CanPost</li> <li>• ComponentFolder_CanPost</li> <li>• Cycle_CanPost</li> <li>• DashboardFolder_CanPost</li> <li>• DashboardPage_CanPost</li> <li>• Library_CanPost</li> <li>• LibraryFolder_CanPost</li> <li>• Release_CanPost</li> <li>• ReleaseFolder_CanPost</li> <li>• Req_CanPost</li> <li>• Resource_CanPost</li> <li>• ResourceFolder_CanPost</li> <li>• Run_CanPost</li> <li>• Step_CanPost</li> <li>• Test_CanPost</li> <li>• TestConfiguration_CanPost</li> <li>• TestFolder_CanPost</li> <li>• TestSet_CanPost</li> <li>• TestSetFolder_CanPost</li> <li>• TestSetTests_CanPost (does not appear in the Scripts Tree)</li> </ul>

## CanReImportModels

This event is triggered when attempting to import the specified business process models that already exist in ALM, to check if the business process models can be reimported.

Syntax	<b>&lt;entity&gt;_CanReImportModels(Models)</b> where <b>Models</b> is an array of Model IDs.
Type	Function
Returns	True or False
Availability	CanReImportModels

## CanRemoveComponentsFromTest

This event is triggered when a user removes components from a test of type Flow or Business-Process, to check whether the specified components can be removed.

<b>Syntax</b>	<b>CanRemoveComponentsFromTest(Components)</b> where <b>Components</b> is an array of component IDs.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanRemoveComponentsFromTest

## CanRemoveFlowsFromTest

This event is triggered when a user removes flows from a test of type Business-Process, to check whether the specified flows can be removed.

<b>Syntax</b>	<b>CanRemoveFlowsFromTest(Flows)</b> where <b>Flows</b> is an array of flow IDs.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	CanRemoveFlowsFromTest

## CanRemoveTests

This event is triggered to check whether the specified tests can be removed from a test set.

<b>Syntax</b>	<b>&lt;entity&gt;_CanRemoveTests(Tests)</b> where <b>Tests</b> is an array of Test Instance IDs.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	TestSet_CanRemoveTests

## DefaultRes

This function is used to determine the default return value for ALM functions, such as FieldCanChange. All ALM workflow functions call this function (unless explicitly omitted by user) to determine the default return value. DefaultRes can be used to quickly replace the default return values of all ALM workflow functions.

<b>Syntax</b>	<b>DefaultRes</b>
---------------	-------------------



<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	DefaultRes (all modules)

## DialogBox

This event is triggered when a dialog box is opened or closed.

<b>Syntax</b>	<b>DialogBox(DialogBoxName, IsOpen)</b> where <b>DialogBoxName</b> is the name of the dialog box, and <b>IsOpen</b> indicates whether the dialog box is open.
<b>Type</b>	Sub
<b>Availability</b>	DialogBox (all modules)

**Note:** For purposes of backward compatibility, this event is also triggered using backward compatible values for defect details (**DialogBoxName="Details"**) and test instance details (**DialogBoxName="TestInstanceDetails"**). These backward compatible values are not recommended.

## EnterModule

This event is triggered when the user enters or switches to an ALM module. It is also triggered when the user logs in to ALM.

You can add code to this event procedure to perform an action whenever the user switches to the specified module.

<b>Syntax</b>	<b>EnterModule</b>
<b>Type</b>	Sub
<b>Availability</b>	EnterModule (all modules)

## ExitModule

This event is triggered when the user exits the specified module.

<b>Syntax</b>	<b>ExitModule</b>
<b>Type</b>	Sub
<b>Availability</b>	ExitModule (all modules)

## FieldCanChange

This event is triggered before ALM changes a field value, to determine whether the field can be changed.

You can add code to this event procedure to prevent a field from being changed in specific cases. For example, see ["Example: Field Validation" on page 395](#).

<b>Syntax</b>	<b>&lt;entity&gt;_FieldCanChange(FieldName, NewValue)</b> where <b>FieldName</b> is the name of the field and <b>NewValue</b> is the field value.
<b>Type</b>	Function
<b>Returns</b>	True or False
<b>Availability</b>	<ul style="list-style-type: none"> <li>• AnalysisItem_FieldCanChange</li> <li>• AnalysisItemFolder_FieldCanChange</li> <li>• Baseline_FieldCanChange</li> <li>• Bug_FieldCanChange</li> <li>• BusinessModel_FieldCanChange</li> <li>• BusinessModelActivity_FieldCanChange</li> <li>• BusinessModelFolder_FieldCanChange</li> <li>• BusinessModelPath_FieldCanChange</li> <li>• Component_FieldCanChange</li> <li>• ComponentFolder_FieldCanChange</li> <li>• ComponentStep_FieldCanChange</li> <li>• Cycle_FieldCanChange</li> <li>• DashboardFolder_FieldCanChange</li> <li>• DashboardPage_FieldCanChange</li> <li>• DesignStep_FieldCanChange</li> <li>• Library_FieldCanChange</li> <li>• LibraryFolder_FieldCanChange</li> <li>• Release_FieldCanChange</li> <li>• ReleaseFolder_FieldCanChange</li> <li>• Req_FieldCanChange</li> <li>• Resource_FieldCanChange</li> <li>• ResourceFolder_FieldCanChange</li> <li>• Run_FieldCanChange</li> <li>• Step_FieldCanChange</li> <li>• Test_FieldCanChange</li> <li>• TestConfiguration_FieldCanChange</li> <li>• TestFolder_FieldCanChange</li> <li>• TestSet_FieldCanChange</li> </ul>

	<ul style="list-style-type: none"><li>• TestSetFolder_FieldCanChange</li><li>• TestSetTests_FieldCanChange</li></ul>
--	--

The code for hiding a field that depends on another field should be placed in the FieldChange event procedure (not in the FieldCanChange event procedure).

## FieldChange

This event is triggered when the value of the specified field changes.

Every change of value triggers the field change event when the field loses focus.

You can add code to this event procedure to perform an action when the value of a particular field is changed. For example, you can hide or display one field depending on the value the user enters into another field. For example, see ["Example: Changing One Field Based on Another Field" on page 393](#).

<b>Syntax</b>	<b>&lt;entity&gt;_FieldChange(FieldName)</b> where <b>FieldName</b> is the name of the field.
<b>Type</b>	Sub
<b>Availability</b>	<ul style="list-style-type: none"><li>• AnalysisItem_FieldChange</li><li>• AnalysisItemFolder_FieldChange</li><li>• Baseline_FieldChange</li><li>• Bug_FieldChange</li><li>• BusinessModel_FieldChange</li><li>• BusinessModelActivity_FieldChange</li><li>• BusinessModelFolder_FieldChange</li><li>• BusinessModelPath_FieldChange</li><li>• Component_FieldChange</li><li>• ComponentFolder_FieldChange</li><li>• ComponentStep_FieldChange</li><li>• Cycle_FieldChange</li><li>• DashboardFolder_FieldChange</li><li>• DashboardPage_FieldChange</li><li>• DesignStep_FieldChange</li><li>• Library_FieldChange</li><li>• LibraryFolder_FieldChange</li><li>• Release_FieldChange</li><li>• ReleaseFolder_FieldChange</li><li>• Req_FieldChange</li><li>• Resource_FieldChange</li><li>• ResourceFolder_FieldChange</li><li>• Run_FieldChange</li><li>• Step_FieldChange</li></ul>

	<ul style="list-style-type: none"> <li>• Test_FieldChange</li> <li>• TestConfiguration_FieldChange</li> <li>• TestFolder_FieldChange</li> <li>• TestSet_FieldChange</li> <li>• TestSetFolder_FieldChange</li> <li>• TestSetTests_FieldChange</li> </ul>
--	---

When a user changes a field value using the **Find/Replace** command, workflow events are not triggered. If restrictions implemented in workflow scripts are critical, consider disabling the **Replace** command for specific user groups, to ensure that your restrictions cannot be bypassed.

## GetDetailsPageName

This event is triggered by ALM to retrieve the name of the page (tab) that has the index number specified in **PageNum** in the following dialog boxes:

- The Details dialog box for an entity
- The New <entity> dialog box for an entity

You can add code to this event procedure to customize the tab names for the Details dialog box. For example, see ["Example: Changing Tab Names" on page 391](#).

<b>Syntax</b>	<b>GetDetailsPageName(PageName, PageNum)</b> where <b>PageName</b> is the default page (tab) name (for example, Page 1) and <b>PageNum</b> is the page (tab) number. <div> <b>Note:</b> The page number is the absolute page number, regardless of the page's relative position in relation to the other displayed pages in the dialog box.         </div>
<b>Type</b>	Function
<b>Returns</b>	String containing the page name
<b>Availability</b>	GetDetailsPageName (all modules)

## GetNewBugPageName

This event is triggered by ALM to retrieve the name of the New Defect dialog box page (tab) that has the index number specified in PageNum.

You can add code to this event procedure to customize the tab names on the New Defect dialog box. For example, see ["Example: Changing Tab Names" on page 391](#).

<b>Syntax</b>	<b>GetNewBugPageName(PageName, PageNum)</b> where <b>PageName</b> is the default page (tab) name (for example, Page 1) and <b>PageNum</b> is the page (tab) number. <div> <b>Note:</b> The page number is the absolute page number, regardless of the page's relative position in relation to the other displayed pages in the New Defect dialog box.         </div>
---------------	--

<b>Type</b>	Function
<b>Returns</b>	String containing the page (tab) name
<b>Availability</b>	GetNewBugPageName

**Note:** The GetNewBugPageName event is not listed in the Scripts Tree of the Script Editor. This event is triggered for backward compatibility purposes only. GetDetailsPageName should be used instead.

## GetNewReqPageName

This event is triggered by ALM to retrieve the name of the New Requirement dialog box page (tab) that has the index number specified in PageNum.

You can add code to this event procedure to customize the tab names on the New Requirement dialog box. For example, see ["Example: Changing Tab Names" on page 391](#).

<b>Syntax</b>	<b>GetNewReqPageName(PageName, PageNum)</b> where <b>PageName</b> is the default page (tab) name (for example, Page 1) and <b>PageNum</b> is the page (tab) number.  <b>Note:</b> The page number is the absolute page number, regardless of the page's relative position in relation to the other displayed pages in the New Defect dialog box.
<b>Type</b>	Function
<b>Returns</b>	String containing the page name
<b>Availability</b>	GetNewReqPageName

**Note:** The GetNewReqPageName event is not listed in the Scripts Tree of the Script Editor. This event is triggered for backward compatibility purposes only. GetDetailsPageName should be used instead.

## GetReqDetailsPageName

This event is triggered by ALM to retrieve the name of the Requirement Details dialog box page (tab) that has the index number specified in PageNum.

You can add code to this event procedure to customize the tab names on the Requirement Details dialog box. For example, see ["Example: Changing Tab Names" on page 391](#).

<b>Syntax</b>	<b>GetReqDetailsPageName(PageName, PageNum)</b> where <b>PageName</b> is the default page (tab) name (for example, Page 1) and <b>PageNum</b> is the page (tab) number.  <b>Note:</b> The page number is the absolute page number, regardless of the page's relative position in relation to the other displayed pages in the New Defect dialog box.
<b>Type</b>	Function

<b>Returns</b>	String containing the page name
<b>Availability</b>	GetReqDetailsPageName

**Note:** The GetReqDetailsPageName event is not listed in the Scripts Tree of the Script Editor. This event is triggered for backward compatibility purposes only. GetDetailsPageName should be used instead.

## MoveTo

This event is triggered when the user changes focus from one object to another.

You can add code to this event procedure to perform actions when the user changes the focus. For example, see ["Example: Presenting a Dynamic Field List" on page 395](#).

**Tip:** When moving from one object to another in a tree, the MoveTo event is not triggered. However, it is possible to trigger the event for Requirement trees. For details, see the **ENABLE\_ENTITY\_SELECTION\_TREE\_REQ\_MOVE\_TO** site parameter.

<b>Syntax</b>	<entity>_MoveTo
<b>Type</b>	Sub
<b>Availability</b>	<ul style="list-style-type: none"> <li>AnalysisItem_MoveTo</li> <li>AnalysisItemFolder_MoveTo</li> <li>Baseline_MoveTo</li> <li>Bug_MoveTo</li> <li>BusinessModel_MoveTo</li> <li>BusinessModelActivity_MoveTo</li> <li>BusinessModelFolder_MoveTo</li> <li>BusinessModelPath_MoveTo</li> <li>Component_MoveTo</li> <li>ComponentFolder_MoveTo (formerlyMoveToComponentFolder)</li> <li>ComponentStep_MoveTo</li> <li>Cycle_MoveTo</li> <li>DashboardFolder_MoveTo</li> <li>DashboardPage_MoveTo</li> <li>DesignStep_MoveTo</li> <li>Library_MoveTo</li> <li>LibraryFolder_MoveTo</li> <li>Release_MoveTo</li> <li>ReleaseFolder_MoveTo</li> <li>Req_MoveTo</li> <li>Resource_MoveTo</li> <li>ResourceFolder_MoveTo</li> </ul>

	<ul style="list-style-type: none"><li>• Run_MoveTo</li><li>• Step_MoveTo</li><li>• Test_MoveTo</li><li>• TestConfiguration_MoveTo</li><li>• TestFolder_MoveTo</li><li>• TestSet_MoveTo</li><li>• TestSetFolder_MoveTo</li><li>• TestSetTests_MoveTo</li></ul>
--	---

## MoveToComponentFolder

This event is triggered when the user moves to the specified component folder in the business component tree.

<b>Syntax</b>	<b>MoveToComponentFolder(Folder)</b> where <b>Folder</b> is the <b>IComponentFolder</b> interface. For more information, refer to the <i>HP ALM Open Test Architecture API Reference</i> .
<b>Type</b>	Sub
<b>Availability</b>	MoveToComponentFolder

**Note:** The MoveToComponentFolder event is not listed in the Scripts Tree of the Script Editor. This event is supported for purposes of backward compatibility. We recommend you use ComponentFolder\_MoveTo event instead.

## MoveToFolder

This event is triggered when the user moves to the specified test set folder in the test sets tree.

<b>Syntax</b>	<b>MoveToFolder(Folder)</b> where <b>Folder</b> is the <b>ISysTreeNode</b> interface. For more information, refer to the <i>HP ALM Open Test Architecture API Reference</i> .
<b>Type</b>	Sub
<b>Availability</b>	MoveToFolder

**Note:** The MoveToFolder event is not listed in the Scripts Tree of the Script Editor. This event is supported for purposes of backward compatibility. We recommend you use MoveToFolder instead.

## MoveToSubject

This event is triggered when the user moves to the specified subject in the test plan tree.

<b>Syntax</b>	<b>MoveToSubject(Subject)</b>
---------------	-------------------------------

	where <b>Subject</b> is the <b>ISysTreeNode</b> interface. For more information, refer to the <i>HP ALM Open Test Architecture API Reference</i> .
Type	Sub
Availability	MoveToSubject

**Note:** The MoveToSubject event is not listed in the Scripts Tree of the Script Editor. This event is supported for purposes of backward compatibility. We recommend you use MoveToSubject instead.

## New

This event is triggered when an object is added to ALM.

You can add code to this event procedure to perform an action when a new object is added. For example, see ["Example: Customizing a Defects Module Dialog Box" on page 389](#).

Syntax	<entity>_New
Type	Sub
Availability	<ul style="list-style-type: none"><li>AnalysisItem_New</li><li>AnalysisItemFolder_New</li><li>Baseline_New</li><li>Bug_New</li><li>BusinessModelFolder_New</li><li>BusinessModelPath_New</li><li>Component_New</li><li>ComponentFolder_New</li><li>ComponentStep_New</li><li>Cycle_New</li><li>DashboardFolder_New</li><li>DashboardPage_New</li><li>DesignStep_New</li><li>Library_New</li><li>LibraryFolder_New</li><li>Release_New</li><li>ReleaseFolder_New</li><li>Req_New</li><li>Resource_New</li><li>ResourceFolder_New</li><li>Step_New</li><li>Test_New</li><li>TestConfiguration_New</li></ul>



	<ul style="list-style-type: none"><li>• TestFolder_New</li><li>• TestSet_New</li><li>• TestSetFolder_New</li></ul>
--	--

## RemoveComponentFromTest

This event is triggered when the user removes a component from a test of type Flow or Business-Process in the Test Script tab.

**Version Control:** Changing components checked in or checked out by another user, using the RemoveComponentFromTest event, is not supported.

<b>Syntax</b>	<b>RemoveComponentFromTest</b>
<b>Type</b>	Sub
<b>Availability</b>	RemoveComponentFromTest

## RunTests

This event is triggered when the user clicks the **Run** button to run tests in the Test Lab module, provided that Sprinter is not installed and none of the tests is automated.

<b>Syntax</b>	<b>RunTests(Tests)</b> where <b>Tests</b> is an array of Test Instance IDs.
<b>Type</b>	Sub
<b>Availability</b>	RunTests

## RunTests\_Sprinter

This event is triggered:

- When the user clicks the **Run** arrow and chooses **Run with** Sprinter to run tests in the Test Lab module.
- When the user clicks the **Run** button to run tests in the Test Lab module, if Sprinter is installed and all the tests are manual.

<b>Syntax</b>	<b>RunTests_Sprinter(Tests)</b> where <b>Tests</b> is an array of Test Instance IDs.
<b>Type</b>	Sub
<b>Availability</b>	RunTests_Sprinter

## RunTestSet

This event is triggered when the user clicks the **RunTest Set** button to run a test set in the Test Lab module.

<b>Syntax</b>	<b>RunTestSet(Tests)</b> where <b>Tests</b> is an array of Test Instance IDs.
<b>Type</b>	Sub
<b>Availability</b>	RunTestSet

## RunTestsManually

This event is triggered when the user clicks the **Run** arrow and chooses **Run Manually** to run tests in the Test Lab module.

<b>Syntax</b>	<b>RunTestsManually(Tests)</b> where <b>Tests</b> is an array of Test Instance IDs.
<b>Type</b>	Sub
<b>Availability</b>	RunTestsManually

# Chapter 32: Workflow Object and Property Reference

Workflow scripts can reference HP Application Lifecycle Management (ALM) objects to obtain information and to change project values. They can also use properties that return information about the current module and dialog box. This chapter lists the ALM objects and properties that are available to workflow scripts.

• About ALM Objects and Properties .....	372
• Actions Object .....	373
• Action Object .....	373
• Fields Objects .....	374
• Field Object .....	375
• Lists Object .....	376
• TDConnection Object .....	377
• User Object .....	377
• ALM Properties .....	378

## About ALM Objects and Properties

Workflow scripts can obtain information, make decisions based on that information, and change values in the project based on those decisions.

You can obtain information such as the user group to which the current user belongs, and the value of a field, by accessing objects such as the **User** object or the **Field** object.

You can also obtain information about the active module and active dialog box using workflow properties. For more information on these properties, see ["ALM Properties" on page 378](#).

Your script can change the value of a field or field list. To do so, the script modifies the **Value** property or the **List** property of the appropriate **Field** object.

For information on the event procedures in which you place VBScript code to create workflow scripts, see ["Workflow Event Reference" on page 347](#).

The following table lists the ALM objects that are available when you write a script.

Object	Description
<b>Actions</b>	The list of actions that are available. See <a href="#">"Actions Object" on the next page</a> .
<b>Action</b>	The <b>Action</b> object is handled by the <b>Actions</b> object. See <a href="#">"Action Object" on the next page</a> .
<b>Fields</b>	Includes the objects that provide access to specific fields. See <a href="#">"Fields Objects" on page 374</a> .
<b>Field</b>	The <b>Field</b> object is handled by the <b>Fields</b> objects. See <a href="#">"Field Object" on page 375</a> .
<b>Lists</b>	Includes the lists that are available in an ALM project. See <a href="#">"Lists Object" on page 376</a> .
<b>TDConnection</b>	Provides access to open test architecture (OTA) objects. See <a href="#">"TDConnection Object" on page 377</a> .
<b>User</b>	Includes the properties of the current user. This object is available in all modules. See <a href="#">"User Object" on page 377</a> .

**Note:** In some cases, a function returns the object itself instead of the ID property of the object. For example, after the following statement has been executed, `testsetf` is a reference to a **TestSetFolder** object:

```
Set testsetf = TestSet_Fields("CY_FOLDER_ID").Value.
```

For information on the Script Editor used to write workflow scripts, see ["Working with the Workflow Script Editor" on page 335](#).

For each ALM object, this chapter lists the properties of the object. The list includes the property name, a description, and the data type of the property. It indicates whether the property is read-only (R) or whether your script can modify it (R/W).

**Version Control:** After enabling version control for a project, you should review all its workflow scripts and make adjustments for each checked in entity. This includes the following entities: **Req**, **Test**, **Resource**, and **Component**. For each checked in entity that includes a **Post** function in its script, you must modify the script. To modify, add a **Checkout** function before every **Post** function. Making this modification prevents the Check Out dialog box from opening each time a call to a

**Post** function is made. For more information about the Post and Checkout functions, see the *HP ALM Open Test Architecture Reference*.

For more information on version control, refer to the *HP Application Lifecycle Management User Guide*.

## Actions Object

You can use the **Actions** object to manipulate toolbar buttons, menu commands, and dialog boxes.

The **Actions** object has the following property:

Property	R/W	Type	Description
<b>Action</b>	R	Object	Allows access to every action in a list. The index for this property is the action name.

## Action Object

You can use the **Action** object to verify whether a button or command is enabled, checked, or visible. You can also use it to execute actions.

For example, to set the Defect Details dialog box to open automatically when the user moves from one defect to another in the Defects Grid, place the following code in the Bug\_MoveTo event procedure:

```
Set NewDefectAction=Actions.Action("Defects.DefectDetails")
NewDefectAction.Execute
```

To obtain the name of an action, add the following lines to the ActionCanExecute event procedure, perform the action, and note the action name that is printed in the message:

```
Sub ActionCanExecute(ActionName)
    On Error Resume Next
    MsgBox "You have performed an action named: " & ActionName
    On Error GoTo 0
End Sub
```

This object has the following properties:

Property	R/W	Type	Description
<b>Checked</b>	R/W	Boolean	Indicates whether an action is checked in ALM.
<b>Enabled</b>	R/W	Boolean	Indicates whether an action is enabled. A disabled action cannot be invoked by the user, but can be invoked from the workflow script.
<b>Visible</b>	R/W	Boolean	Indicates whether an action is visible in ALM.

The **Action** object includes the following method:

Method	Description
<b>Execute</b>	Executes the action.

When a workflow script invokes an action using the **Execute** method of the **Action** object, the workflow events that would be triggered if a user initiated the action from a dialog box are by default not triggered. Therefore, when using **Action.Execute**, you must ensure that you do not bypass the site policies you are enforcing with workflow events.

To enable workflow events to be triggered from within a dialog box, set the value of the **AllowReentrancy** flag to **true**. To restore the default settings, so that these events are not triggered, set the value of the **AllowReentrancy** flag to **false**. For example, to set the Add Defect dialog box to open automatically when a user enters the Defects module, place the following code in the **EnterModule** event procedure:

```
AllowReentrancy=true
Set NewDefectAction=Actions.Action("Defects.DefectDetails")
NewDefectAction.Execute
AllowReentrancy=false
```

If the value of the **AllowReentrancy** flag is set to **false**, the dialog box opens as usual, but workflow customizations will not work in the dialog because the workflow events for the dialog box are not triggered.

**Caution:** Consider carefully the implications of setting the value of this flag to **true**. If you set the value of the flag to **true**, you enable a function to call another function which may call the original function. This can cause an endless loop. This can also occur when functions call internal functions which call the original function.

## Fields Objects

You can use the following objects in workflow scripts to access the fields of ALM modules:

Object	Description
<b>AnalysisItem_Fields</b>	Provides access to the fields of the reports and graphs in the Dashboard module.
<b>AnalysisItemFolder_Fields</b>	Provides access to the fields of the report and graph folders in the Dashboard module.
<b>Baseline_Fields</b>	Provides access to the fields of the baselines in the Libraries module.
<b>Bug_Fields</b>	Provides access to the fields of the defects in the Defects module and the Manual Runner dialog box.
<b>Component_Fields</b>	Provides access to the fields of components in the Business Components module.
<b>ComponentStep_Fields</b>	Provides access to the fields of component steps in the Business Components module.
<b>Cycle_Field</b>	Provides access to the fields of cycles in the Releases module.
<b>DashboardFolder_Fields</b>	Provides access to the fields of dashboard page folders in the Dashboard module.
<b>DashboardPage_Fields</b>	Provides access to the fields of dashboard pages in the Dashboard module.
<b>DesignStep_Fields</b>	Provides access to the fields of the design steps in the Test Plan module.
<b>Library_Fields</b>	Provides access to the fields of the libraries in the Libraries module.

Object	Description
<b>LibraryFolder_Fields</b>	Provides access to the fields of the library folders in the Libraries module.
<b>Release_Fields</b>	Provides access to the fields of the releases in the Releases module.
<b>ReleaseFolder_Fields</b>	Provides access to the fields of the release folders in the Releases module.
<b>Req_Fields</b>	Provides access to the fields of the Requirements module.
<b>Resource_Fields</b>	Provides access to the fields of the resources in the Test Resources module.
<b>ResourceFolder_Fields</b>	Provides access to the fields of the resource folders in the Test Resources module.
<b>Run_Fields</b>	Provides access to the fields of the test runs in the Manual Runner dialog box.
<b>Step_Fields</b>	Provides access to the fields of the steps in the Manual Runner dialog box.
<b>Test_Fields</b>	Provides access to the fields of tests in the Test Plan module.
<b>TestSet_Fields</b>	Provides access to the fields of the test sets in the Test Lab module.
<b>TestSetTest_Fields</b>	Provides access to the fields of the test instances in the Test Lab module.

For example, to set a certain property for all fields in the **Req\_Fields** object, you can refer to each field by its ID number (**Req\_Fields.FieldById**). To set all fields to be visible (**IsVisible**) in a dialog box, you can use the following code:

```
For i = 1 to Req_Fields.Count
    Req_Fields.FieldById(i).IsVisible = True
Next
```

These objects have the following properties:

Property	R/W	Type	Description
<b>Count</b>	R	Long	Returns the number of fields in the current object.
<b>Field (FieldName)</b>	R	Object	Accesses the fields by field name or field label.
<b>FieldById (FieldID)</b>	R	Object	Accesses the fields by the field ID number.

**Tip:** To avoid errors if your script attempts to access a non-active or a non-existing field, include **On Error Resume Next** in the script.

## Field Object

You can use the **Field** object to access the properties of an entity field.

For example, to display a message box when a user does not have permission to change a value in the **Status** field, you can use the following code:

```
Msgbox "You do not have permission to change "_
& "Bug_Fields.Field("BG_STATUS").FieldLabel field."
```

The **Field** object has the following properties:

Property	R/W	Type	Description
<b>FieldLabel</b>	R	String	The displayed label of the field.
<b>FieldName</b>	R	String	The logical name of the field.
<b>IsModified</b>	R	Boolean	Specifies whether the value was modified.
<b>IsMultiValue</b>	R	Boolean	Specifies whether the field can contain multiple values from a lookup list.
<b>IsNull</b>	R	Boolean	Specifies whether the field value is absent.
<b>IsReadOnly</b>	R/W	Boolean	Specifies whether the field is read-only.
<b>IsRequired</b>	R/W	Boolean	Specifies whether a field value is required. This enables you to override field customization information. To modify the <b>IsRequired</b> property of a field, the <b>IsVisible</b> property must be <b>True</b> . Changes to <b>IsRequired</b> are ignored if the field is not visible.  Users must always enter a value for a field that is set as required by the workflow. This applies whether they are modifying an existing record or adding a new record, and even if the field is already empty.
<b>IsVisible</b>	R/W	Boolean	Specifies whether the field is displayed.
<b>List</b>	R/W	List	Sets or retrieves the field list attached to a field of type lookup list.
<b>PageNo</b>	R/W	Integer	Sets or retrieves the page (tab) on which the field is displayed in the New Defect and Defect Details dialog boxes.
<b>Value</b>	R/W	Variant	Sets or retrieves the value of the field.
<b>ViewOrder</b>	R/W	Integer	Sets or retrieves the order in which the fields are displayed in the New Defect and Defect Details dialog boxes. You must set the value for every field in the dialog box.

## Lists Object

You can use the **Lists** object to limit field input to a specific list of values.

For example, to set the list in the **Planned Closing Version** field, depending on the **Project** field value, you can use the following code:

```
If Bug_Fields.Field("BG_PROJECT").Value = "Project 1" Then
    Bug_Fields.Field("BG_PLANNED_CLOSING_VER").List _
    = Lists("All Projects")
    ...
End If
```

For more information, see ["Example: Presenting a Dynamic Field List" on page 395](#).

The **Lists** object can be used only with fields that are defined as the **Lookup List** type or the **String** type in Project Customization of project entities.

The **Lists** object has the following properties:

Property	R/W	Type	Description
<b>List</b>	R	ISysTreeNode	Accesses the ALM lists.



**Note:** When workflow customization has been used to change a list of values for a field that has transition rules defined, the field may only be modified in a way that satisfies both the workflow script and the transition rules. For more information, see ["Setting Transition Rules" on page 216](#).

## TDConnection Object

In workflow scripts, the only objects that are available are the objects of the module in which the code is written and a limited number of global objects. One of the global objects is the **TDConnection** object. **TDConnection** provides access to the open test architecture (OTA) objects.

You can use the **TDConnection** object to access objects from other modules, and to access general session parameters. You can access **TDConnection** properties in any procedure, from any module.

For more information about the **TDConnection** object, and a list of **TDConnection** properties, refer to the *HP ALM Open Test Architecture API Reference*.

For examples of using the **TDConnection** object in workflow scripts, see ["Workflow Examples and Best Practices" on page 381](#).

## User Object

You can access the **User** object to retrieve the user name of the current user and to check whether the user belongs to a particular user group. You can retrieve or modify the first and last name of the user.

For example, to have a message box open when the user has project administrator permissions, use the following code:

```
If User.IsInGroup("TAdmin") Then
    MsgBox "The user " & User.FullName & _
        " has administrative permissions for this project."
End If
```

For more information, see ["Example: Changing a Field Based on the User Group" on page 393](#), and ["Example: Controlling User Permissions" on page 397](#).

To access user properties that cannot be accessed by the **User** object, you can use the **TDConnection** object of the ALM open test architecture (OTA).

The **User** object has the following properties:

Property	R/W	Type	Description
<b>FullName</b>	R/W	String	Sets or retrieves the first and last name of the current user.
<b>IsInGroup (GroupName)</b>	R	Boolean	Checks whether or not the current user is a member of a predefined/user-defined group.
<b>UserName</b>	R	String	Returns the user name used when logging in to ALM.

# ALM Properties

You can use the **ActiveModule** and **ActiveDialogName** properties to obtain information about the active module and dialog box.

This section includes:

- [ActiveModule Property](#) .....379
- [ActiveDialogName Property](#) .....379

## ActiveModule Property

The **ActiveModule** property returns the name of the active ALM module. The following values can be returned:

- Releases
- Libraries
- Analysis
- Dashboard
- Requirements
- Business Models
- Test Resources
- Business Components
- Test Plan
- Test Lab
- Test Runs
- Defects

### Example

To open a message box displaying the module name when you move to a new module, use the following code:

```
Sub EnterModule
    On Error Resume Next
    msgbox "You have just entered the " & ActiveModule & _
        " module."
    On Error GoTo 0
End Sub
```

## ActiveDialogName Property

The **ActiveDialogName** property returns the name of the active dialog box.

### Example

To open a message box displaying the dialog box name when you open a new dialog box, use the following code:

```
Sub DialogBox(DialogBoxName, IsOpen)
    On Error Resume Next
```

```
        msgbox "You have just opened the " & ActiveDialogName & _  
        " dialog box."  
    On Error GoTo 0  
End Sub
```

# Chapter 33: Workflow Examples and Best Practices

This chapter provides considerations and examples for workflow scripts.

• About the Workflow Examples .....	382
• Best Practices for Writing Workflow Scripts .....	382
• Example: Customizing a Defects Module Dialog Box .....	389
• Example: Changing Tab Names .....	391
• Example: Adding a Template to a Memo Field .....	392
• Example: Changing One Field Based on Another Field .....	393
• Example: Changing a Field Based on the User Group .....	393
• Example: Object Validation .....	394
• Example: Field Validation .....	395
• Example: Presenting a Dynamic Field List .....	395
• Example: Changing Field Properties when a Field Changes .....	397
• Example: Controlling User Permissions .....	397
• Example: Adding Button Functionality .....	398
• Example: Error Handling .....	398
• Example: Obtaining Session Properties .....	399
• Example: Sending Mail .....	400
• Example: Storing the Last Values Entered .....	401
• Example: Copying Field Values to Another Object .....	403

## About the Workflow Examples

The workflow examples presented in this chapter perform several types of tasks. The following table lists the examples that illustrate each type of task.

Workflow Task	See Examples
dialog box customization	"Example: Customizing a Defects Module Dialog Box" on page 389 "Example: Changing Tab Names" on page 391
field value automation	"Example: Adding a Template to a Memo Field" on page 392 "Example: Changing One Field Based on Another Field" on page 393 "Example: Changing a Field Based on the User Group" on page 393
data validation	"Example: Object Validation" on page 394 "Example: Field Validation" on page 395
dynamic field customization	"Example: Presenting a Dynamic Field List" on page 395 "Example: Changing Field Properties when a Field Changes" on page 397
user permission control	"Example: Controlling User Permissions" on page 397
functionality	"Example: Adding Button Functionality" on page 398
error handling	"Example: Error Handling" on page 398
using OTA to obtain session parameters	"Example: Obtaining Session Properties" on page 399
sending mail	"Example: Sending Mail" on page 400
using the <b>Settings</b> object	"Example: Storing the Last Values Entered" on page 401
copying values between modules	"Example: Copying Field Values to Another Object" on page 403

## Best Practices for Writing Workflow Scripts

This section describes best practices for writing workflow scripts and making sure the scripts run as expected. In addition to the best practices provided in this section, you can refer to the Microsoft Developer Network VBScript Language Reference at <http://msdn.microsoft.com/en-us/library/>.

The following best practices are described in this section:

### General VBScript Tips and Best Practices

- "Checking Value Types Before Use" on the next page
- "Anticipating Full Evaluation of Logical Expressions" on page 384
- "Defining Default Behavior for Select Case and If-Then-Else Statements" on page 385
- "Setting Return Values in Functions" on page 386

### ALM Workflow Tips and Best Practices

- ["Making Sure that Entity Properties Are Set Before an Entity Comes into Focus" on page 386](#)
- ["Check if a Dialog Box is Open" on page 387](#)
- ["Avoid Defining Duplicate Subroutines" on page 388](#)

## Checking Value Types Before Use

VBScript is a "weakly-typed" programming language. This means that you can create, use, and access data values without initially declaring their types. However, certain operations can be performed only on values of a specific type. Therefore, it is important to check the type of the data before performing any operations on them.

Values of different types behave differently in different statements. Object value behavior is even more unpredictable because the behavior depends on the object's implementation. For example, the object in the call `<entity>_CanDelete(Entity)` can either be text or a subject node.

## Recommendations

To avoid unpredictable results:

- Check value types before use, especially for object types. When checking an object type, also check that the object has the properties you access.

**Note:** In the examples provided in this chapter, only object types are checked before use.

- Assume as little as possible—do not assume that a value is of a certain type. Write scripts that can handle all possibilities by using Else statements and Select Case statements.
- Always check parameter types before use with various VBScript functions, such as `IsArray`, `IsDate`, `IsNull`, `IsEmpty`, `IsNumeric`, and `IsObject`.
- Do not assume an object's default property is of a specific type; the type can vary from object to object.
- Use VBScript built-in conversion functions to achieve a degree of type safety.
- When working with objects, check that the value you receive is neither Null or Empty by calling the `IsNull` and `IsEmpty` functions.

## Examples

For the purposes of the following examples, assume the field values are declared as in the table below.

Field Values	Type
Bug_Fields["BG_BUG_ID"].Value	Integer
Bug_Fields["BG_SUMMARY"].Value	String
Bug_Fields["BG_SUBJECT"].Value	Object implementing the ISysTreeNode interface

In the following example, statement usage is correct. The integer is converted to a string.

```
If Bug_Fields["BG_BUG_ID"].Value = "10" Then...
```

In the following example, statement usage is correct. The strings are comparable.

```
If Bug_Fields["BG_SUMMARY"].Value = "some text" Then...
```

In the following example, statement usage is incorrect. This code can work only when the value of BG\_SUBJECT field is neither Empty or Null. VBScript also assumes that this objects's default value (meaning, the default property) is either of string type or is comparable with the string type, which is not always the case.

```
If Bug_Fields["BG_SUBJECT"].Value = "My Tests" Then...
```

## Anticipating Full Evaluation of Logical Expressions

The VBScript programming language does not short-circuit evaluation of Boolean conditions. VBScript evaluates all the terms in a Boolean logical expression, even if the expression can be established as True or False without evaluating all its terms. For example, in the following example, both <statement1> and <statement2> are evaluated, even if <statement1> resolves to False:

```
<statement 1> AND <statement 2>
```

## Recommendations

To avoid errors, check that all values and objects are not Null before attempting to use them.

### Examples

The following examples:

- demonstrate incorrect and correct usage of logical expressions
- take into consideration how logical expressions are evaluated

#### Incorrect Usage

value.Name is evaluated even when its value is Null. This causes an error.



```
Sub namecheck(value)
    If Not IsNull(value) And value.Name = "aName" Then
        ' ...
    End If
End Sub
```

#### **Correct Usage**

The code is correct on the condition that `value` is an object that contains the `Name` property. The code runs without errors.

```
Sub namecheck(value)
    If Not IsNull(value) And Not IsEmpty(value) Then
        If value.Name = "aName" Then
            ' ...
        End If
    End If
End Sub
```

## Defining Default Behavior for Select Case and If-Then-Else Statements

Unpredictable results can occur when no default action is defined for Select Case statements or If-Then-Else statements.

### Recommendations

To avoid unpredictable results, always define default behavior when using Select Case or If-Then-Else statements.

#### **Example**

The following are examples of incorrect and correct ways to define default behavior for situations not covered by the existing Select Case and If-Then-Else statements.

#### **Incorrect Usage**

The author of this subroutine intends for the `BG_USER_01` field to be visible only if the status of the defect is Open, New, or Reopen. However, if the `IsVisible` property of a Closed or Fixed defect was set to True prior to the instance of this subroutine, that Closed or Fixed defect will also be visible. This is because there is no case statement defined specifically for Closed and Fixed defects.

```
Sub Bug_FieldChange(FieldName)
    If FieldName="BG_STATUS" Then
        Select Case Bug_Fields(FieldName).Value
            Case "Open", "New", "Reopen" _
                Bug_Fields("BG_USER_01").IsVisible = True
        End Select
    End If
End Sub
```

### **Correct Usage**

This subroutine effectively handles all possible cases.

```
Sub Bug_FieldChange(FieldName)
    If FieldName="BG_STATUS" Then
        Select Case Bug_Fields(FieldName).Value
            Case "Open", "New", "Reopen"
                Bug_Fields("BG_USER_01").IsVisible = True
            Case Else
                Bug_Fields("BG_USER_01").IsVisible = False
        End Select
    End If
End Sub
```

## Setting Return Values in Functions

If a function ends without a return value, unpredictable and inconsistent results may occur. Also, it is difficult to debug behavior if a return code is not set.

### Recommendations

To avoid unpredictable results, set a default return value at the beginning of each function.

## Making Sure that Entity Properties Are Set Before an Entity Comes into Focus

It is common practice to set entity properties (such as `IsVisible`, `IsRequired`, and `List`) when creating or modifying a new entity (New or FieldChanged). When writing ALM workflow scripts, it is also important to set entity properties when the entity comes into focus (meaning, when the user navigates to that entity in the ALM graphical user interface). When an entity comes into focus, the `MoveTo` event is called.

If entity values are not set in the `MoveTo` event, the end user experience is unpredictable—for example, incorrect values might be displayed in drop-down lists.

## Recommendations

To avoid unpredictable results, such as a drop-down list not containing the most up-to-date set of values:

- Make sure that all entity properties are set in the MoveTo event—not just in the New or FieldChanged events.
- Isolate entity properties customization code into a separate routine and call that routine from all relevant events.

### Example

The following table provides an example of how to make sure that properties of a defect are set appropriately when the defect is in focus—and not just when it is modified or added.

```
Sub SetupBugFields(Context1, Context2)
    ' Code for customizing defect properties is entered here,
    ' such as set IsVisible, IsRequired, IsReadOnly, Label, List...
    If Context1="Focus" Then
        ' Code for handling the focus event is entered here
    ElseIf Context1="FieldChange" Then
        If Context2="RQ_USER_01" Then
            ' Code for handling the FieldChange event
            ' is entered here
        ElseIf Context2="RQ_REQ_STATUS" Then
            ' ... Enter your code here
        Else
            ' ... Enter your code here
        End If
    End If
End Sub

Sub Req_FieldChange(FieldName)
    If FieldName = "RQ_REQ_STATUS" Then
        SetupBugFields("FieldChange", FieldName)
    Else
        ' ...Enter your code here
    End If
End Sub

Sub Req_MoveTo
    SetupBugFields("Focus")
End Sub
```

## Check if a Dialog Box is Open

It is helpful to track whether a dialog box is open before performing certain actions. For example:

- Dialog boxes do not need to be refreshed but grid displays do.
- Certain workflow events are not allowed when a dialog box is open.

The DialogBox event can be used to track the visibility of dialog boxes.

## Recommendations

To avoid unpredictable results, determine if a dialog box is open before any events occur.

### Example

The following example checks whether the dialog box for creating a new defect is open. This is relevant because the BG\_USER\_01 field can only be modified for a new defect. If a different dialog box is open, such as the dialog box for editing a defect, the BG\_USER\_01 field cannot be modified.

```
' Declare a global variable for each dialog box of interest
Dim NewDefectDialogIsOpen
' Initialize the global variable
NewDefectDialogIsOpen = False
Sub DialogBox(DialogBoxName, IsOpen)
    If DialogBoxName="New Bug" Then
        NewDefectDialogIsOpen = True
    Else
        NewDefectDialogIsOpen = False
    End If
End Sub
Function Bug_FieldCanChange(FieldName, NewValue)
' Initialize the function's return value to avoid
' unpredictable behavior.
Bug_FieldCanChange = True
' The BG_USER_01 field can only be modified for a new defect.
If FieldName="BG_USER_01" Then
    If NewDefectDialogIsOpen Then
        Bug_FieldCanChange = True
    Else
        Bug_FieldCanChange = False
    End If
End If
End Function
```

## Avoid Defining Duplicate Subroutines

If you define a subroutine in one section and then add another subroutine with the same name in another section, the subroutines will conflict. One of them will be ignored.

**Example:** If you define the subroutine, **MySub**, in the Test Lab module script section, and then define another subroutine, MySub, in the Manual Runner script section, one of your defined subroutines will be ignored.

## Recommendations

To avoid unpredictable conflicts when defining subroutines, always check if another subroutine with the same name already exists in your project.

## Example: Customizing a Defects Module Dialog Box

This example shows how you can customize the field layout and other field properties in the Add Defect dialog box. You can create similar code to arrange the layout of the Defect Details dialog box.

This example illustrates a solution that customizes field properties for all user groups. You can also use the script generators to customize the layout of the Defects module dialog boxes. If you use the script generators, you must perform customization separately for each user group. For information on these script generators, see ["Customizing Defects Module Dialog Boxes" on page 325](#).

This example involves the following procedures:

- `SetFieldApp` is a general purpose procedure that receives a field name and its properties as parameters, and assigns the properties to the field. See ["SetFieldApp" below](#).
- `FieldCust_AddDefect` calls `SetFieldApp` for each field in the Add Defects dialog box, to set the properties of the field. For some of the fields, `FieldCust_AddDefect` checks the user group to which the current user belongs, and customizes the field properties accordingly. A call to `FieldCust_AddDefect` is placed in the `Bug_New` event procedure. See ["FieldCust\\_AddDefect" on the next page](#).

**Note:** To implement this example, you can run the **Add Defect Field Customization** script generator and then modify the resulting scripts.

- Rename the generated function `WizardFieldCust_Add` to `FieldCust_AddDefect` and modify it as necessary. (Before you modify a generated script, you must rename it so that it is not overwritten the next time you run the script generator.)
- The script generator places a call to `WizardFieldCust_Add` in the event procedure `Bug_New`. Change this to `FieldCust_AddDefect`.
- The function `SetFieldApp` is generated when you run the script generator. You do not need to rename or modify this function.

## SetFieldApp

The subroutine `SetFieldApp` receives a field name and its properties as parameters, and assigns the properties to the field.

The subroutine assigns the following field properties: field visibility, whether the field is required, the number of the page (tab) on which the field should be displayed, and the view order (from left to right and from top to bottom).

Add a call to the subroutine `SetFieldApp` in the user-defined function `FieldCust_AddDefect`. For more information on this function, see ["FieldCust\\_AddDefect" on the next page](#).

```
Sub SetFieldApp(FieldName, Vis, Req, PNo, VOrder)
  On Error Resume Next
  With Bug_Fields(FieldName)
    .IsVisible = Vis
    .IsRequired = Req
    .PageNo = PNo
    .ViewOrder = VOrder
  End With
  PrintError "SetFieldApp"
  On Error GoTo 0
End Sub
```

## FieldCust\_AddDefect

The user-defined function FieldCust\_AddDefect calls the function SetFieldApp.

The function first sets all fields to be invisible, not required, and to appear on page 100 at location 0. This ensures that if you add a new field using the **Project Entities** link on the Project Customization window, the layout will not be changed.

Add a call to FieldCust\_AddDefect in the Bug\_New event procedure so that it will be triggered when a user adds a new defect:

```
Sub Bug_New
  FieldCust_AddDefect
End Sub
```

First, the code handles the fields that are common to all user groups. It uses conditional statements for the fields that will appear in the dialog box only for specific user groups, or that will have different properties for different users.

```
Sub FieldCust_AddDefect
  On Error Resume Next
  ' Initialize the fields of the defect
  For i= 0 To Bug_Fields.Count -1
    SetFieldApp Bug_Fields.FieldByID(i).FieldName, _
      False, False, 100, 0
  Next
  ViewNum = 0
  PageNum = 0
  ' Set fields that are in common for all user groups
  SetFieldApp "BG_BUG_ID", True, True, PageNum, ViewNum
  ViewNum = ViewNum + 1
  SetFieldApp "BG_DESCRIPTION", True, False, PageNum, ViewNum
  ViewNum = ViewNum + 1
  SetFieldApp "BG_SUMMARY", True, True, PageNum, ViewNum
  ViewNum = ViewNum + 1
  SetFieldApp "BG_DETECTED_BY", True, True, PageNum, ViewNum
  ViewNum = ViewNum + 1
  SetFieldApp "BG_DETECTION_DATE", _
```

```
True, True, PageNum, ViewNum
ViewNum = ViewNum + 1
SetFieldApp "BG_DETECTION_VERSION", True, True, PageNum, _
ViewNum
ViewNum = ViewNum + 1
SetFieldApp "BG_SEVERITY", True, True, PageNum, ViewNum
ViewNum = ViewNum + 1
SetFieldApp "BG_PRIORITY", True, True, PageNum, ViewNum
ViewNum = ViewNum + 1
SetFieldApp "BG_PROJECT", True, False, PageNum, ViewNum
ViewNum = ViewNum + 1
SetFieldApp "BG_REPRODUCIBLE", True, False, PageNum, ViewNum
ViewNum = ViewNum + 1
SetFieldApp "BG_STATUS", True, False, PageNum, ViewNum
ViewNum = ViewNum + 1
' Set fields that are different for different user groups.
' Since one user can belong to multiple user groups,
' or none of these groups, there is no need for an Else statement.
If User.IsInGroup("Developer") Then
    SetFieldApp "BG_PLANNED_CLOSING_VERSION", True, False, _
    PageNum, ViewNum
    ViewNum = ViewNum + 1
    SetFieldApp "BG_PLANNED_FIX_TIME", True, False, PageNum, _
    ViewNum
    ViewNum = ViewNum + 1
End If

If User.IsInGroup("QATester") Then
    PageNum = PageNum + 1
    SetFieldApp "BG_USER_01", True, False, PageNum, ViewNum
    ViewNum = ViewNum + 1
    SetFieldApp "BG_USER_02", True, False, PageNum, ViewNum
    ViewNum = ViewNum + 1
End If

SetFieldApp "BG_ACTUAL_FIX_TIME", True, False, PageNum, _
ViewNum
ViewNum = ViewNum + 1
' ...
PrintError "FieldCust_AddDefect"
On Error GoTo 0

End Sub
```

## Example: Changing Tab Names

You can change the names of the tabs on the Add Defect dialog box. This example sets the tabs to General, Environments, and Business Case.

Add the following code to the `GetNewBugPageName` event procedure, which is triggered before ALM opens the Add Defect dialog box. To change the tab names on the Defect Details dialog box, add similar code to the `Defects_GetDetailsPageName` event procedure.

```
Sub Bug_New
    On Error Resume Next

        Bug_Fields.Field("BG_ACTUAL_FIX_TIME").PageNo = 1
        Bug_Fields.Field("BG_ESTIMATED_FIX_TIME").PageNo = 2

    On Error GoTo 0
End Sub


Function GetDetailsPageName(PageName,PageNum)
    On Error Resume Next

    if ActiveDialogName = "New Bug" then
        Select case PageNum
            case "1"
                GetDetailsPageName="General"
            case "2"
                GetDetailsPageName="Environments"
            case else
                GetDetailsPageName="Business Case"
        End Select
    end if

    On Error GoTo 0
End Function
```

## Example: Adding a Template to a Memo Field

You can use workflow scripts to add a default template to a memo field. This example adds text to a memo field called **Business Case** to display the following template:





Perform this customization by placing the HTML code for the text into the **BG\_USER\_25** field when a defect is added. This example assumes that the user-defined field **BG\_USER\_25** stores a business case string.

Add the code to the `Bug_New` event procedure, which is triggered when a user adds a new defect.

```
Sub Bug_New
    On Error Resume Next
    Bug_Fields("BG_USER_25").value = _
    "<html><body><b>Step by step scenario:</b>" & _
    "<br><br><br><b>How it affects the user:</b></body></html>"
    PrintError "Bug_New"
    On Error GoTo 0
End Sub
```

## Example: Changing One Field Based on Another Field

This example demonstrates how you can change a field value based on the value entered into another field.

For example, you can cause defects to be assigned to user **alex\_qc** when `UI Suggestion` is typed into the **Category** field, and to user **alice\_qc** when `Security Issues` is typed.

The example assumes that the user-defined field **BG\_USER\_05** is used to store the category. When the **Category** field is changed in the Defects module, the **BG\_RESPONSIBLE** field is assigned the appropriate value.

Add the code to the `Bug_FieldChange` event procedure so that it is triggered when a user changes a field value for a defect.

```
Sub Bug_FieldChange(FieldName)
    On Error Resume Next
    If FieldName = "BG_USER_05" then
        Select case Bug_Fields("BG_USER_05").Value
            case "UI Suggestion"
                Bug_Fields("BG_RESPONSIBLE").value="alex_qc"
            case "Security Issue"
                Bug_Fields("BG_RESPONSIBLE").value="alice_qc"
            Case Else
                Bug_Fields("BG_RESPONSIBLE").value="non-assigned"
        End Select
    End If
    PrintError "Bug_FieldChange"
    On Error GoTo 0
End Sub
```

## Example: Changing a Field Based on the User Group

This example demonstrates how you can change a field value according to the user group of the user entering the defect.

In this example, the user-defined field **BG\_USER\_01** is a detection mode field in which the user who detected the defect can enter the way in which it was discovered. Possible values are Formal testing, Informal testing, and BTW.

The example sets the value of the detection mode field to BTW when a defect is opened by a user who is not in the QA Tester group. If the defect is opened by a user who is in the QA Tester group, the default value Formal testing is set.

Add the code to event procedure Bug\_New, so that it is triggered when a defect is added.

```
Sub Bug_New
    On Error Resume Next
    If not User.IsInGroup("QATester") then
        Bug_Fields("BG_USER_01").Value = "BTW"
    Else
        Bug_Fields("BG_USER_01").Value = "Formal testing"
    End If
    PrintError "Bug_New"
    On Error GoTo 0
End Sub
```

## Example: Object Validation

This example demonstrates how you can perform validations of all fields by using the CanPost event procedure. For example, this code segment ensures that a user cannot reject a defect without adding a comment.

In this example, a user may not post a defect where the defect status (**BG\_STATUS**) has been changed to Rejected unless some explanatory text has been typed in the **R&D Comment** field (**BG\_DEV\_COMMENTS**).

Add the code to the Bug\_CanPost event procedure so that the check is performed when the user attempts to submit the defect.

```
Function Bug_CanPost
    ' Initialize the function's return value
    ' to avoid unpredictable behavior.
    Bug_CanPost = False
    On Error Resume Next
    If Bug_Fields("BG_STATUS").IsModified and _
        Bug_Fields("BG_STATUS").Value = "Rejected" and _
        not Bug_Fields("BG_DEV_COMMENTS").IsModified then
        Bug_CanPost = False
        msgbox "You must enter a comment when rejecting a defect."
    Else
        Bug_CanPost = True
    End If
    PrintError "Bug_CanPost"
    On Error GoTo 0
End Function
```

## Example: Field Validation

This example demonstrates how to validate a single field value. For example, the following code segment shows how you can ensure that a user in a specific group cannot lower the priority of a defect.

In this example, if the user is in the **QATester** group and the **BG\_PRIORITY** field is being modified, the new value of the **BG\_PRIORITY** field cannot be lower than the current value.

This example assumes that in the **Priority** field list for the project, lower priorities come first when the values are sorted in ascending order. For example, the list meets this requirement if the elements are as follows: 1-Low, 2-Medium, 3-High.

Add the code to the `Bug_FieldCanChange` event procedure so that it is triggered when the user attempts to change a defect field value.

```
Function Bug_FieldCanChange(FieldName, NewValue)
    ' Initialize the function's return value
    ' to avoid unpredictable behavior.
    Bug_FieldCanChange = True
    On Error Resume Next
    If User.IsInGroup("QATester") and FieldName = "BG_PRIORITY" _
    Then
        If NewValue < Bug_Fields("BG_PRIORITY").Value then
            Bug_FieldCanChange = False
            msgbox "You do not have permission to lower " _
            & "defect priority."
        Else
            Bug_FieldCanChange = True
        End If
    Else
        ' Enter your code here.
    End If
    PrintError "Bug_FieldCanChange"
    On Error GoTo 0
End Function
```

## Example: Presenting a Dynamic Field List

This example demonstrates how you can present a different field list in a field, depending on the value of another field.

The user-defined function `SW_SetLists_Environment` checks the value of the **Environment Specification** field and assigns the appropriate field list to the **Environment Type** field.

This example assumes that the field lists have been defined in the project. For more information, see ["Customizing Project Lists" on page 236](#).

**Note:** To use workflow scripts to change or create lists that can be assigned to fields, you must

use the Open Test Architecture (OTA) interface.

Add code to the `Bug_MoveTo` event procedure so that the user-defined function `SW_SetLists_Environment` is called when the user changes focus in the defects module.

```
Sub Bug_MoveTo()  
    On Error Resume Next  
    SW_SetLists_Environment  
    PrintError "Bug_MoveTo"  
    On Error GoTo 0  
End Sub
```

Add code to the `Bug_FieldChange` event procedure so that the user-defined function `SW_SetLists_Environment` is called when a user changes the value of the **Environment Type** field in the Defects module.

```
Sub Bug_FieldChange(FieldName)  
    On Error Resume Next  
    If FieldName = "BG_USER_01" then  
        SW_SetLists_Environment  
    Else  
        ' Enter your code here.  
    End If  
    PrintError "Bug_FieldChange"  
    On Error GoTo 0  
End Sub
```

The user-defined function `SW_SetLists_Environment` checks the value of the **Environment Specification** field (**BG\_USER\_02**) and assigns the appropriate field list to the **Environment Type** field (**BG\_USER\_01**).

```
Sub SW_SetLists_Environment()  
    Dim listName  
    On Error Resume Next  
    Select Case Bug_Fields("BG_USER_01").Value  
    Case "Browser"  
        listName = "Browsers"  
    Case "Database Type"  
        listName = "Database Type"  
    Case "Operating System"  
        listName = "Platform"  
    Case "Web Server"  
        listName = "Web Server"  
    Case Else  
        listName = "Environment Specification"  
    End Select  
    Bug_Fields("BG_USER_02").List = Lists(listName)  
    PrintError ("Set Environment List")  
    On Error GoTo 0  
End Sub
```

## Example: Changing Field Properties when a Field Changes

This example demonstrates how you can change the properties of a field when a different field is changed.

In this example, if the status of the defect (**BG\_STATUS**) is changed to **Closed**, the user must provide a value in the field **Closed in Build (BG\_CLOSING\_VERSION)**.

Add the code to the `Bug_FieldChange` event procedure, to make the **Closed in Build** field a required field if the status is changed to **Closed**.

```
Sub Bug_FieldChange(FieldName)
    On Error Resume Next
    If FieldName= "BG_STATUS" then
        If Bug_Fields("BG_STATUS").value="Closed" then
            Bug_Fields("BG_CLOSING_VERSION").IsRequired=True
        Else
            Bug_Fields("BG_CLOSING_VERSION").IsRequired=False
        End If
    Else
        ' Enter your code here.
    End If
    PrintError "Bug_FieldChange"
    On Error GoTo 0
End Sub
```

## Example: Controlling User Permissions

This example demonstrates how you can prevent members of specific user groups from performing an action.

The code allows a user to replace a defect field value only if the user belongs to the **Admin** user group.

Add the code to the `ActionCanExecute` event procedure so that the check is performed when a user attempts to execute an action.

```
Function ActionCanExecute(ActionName)
    ' Initialize the function's return value
    ' to avoid unpredictable behavior.
    ActionCanExecute = False
    On Error Resume Next
    If ActionName = "UserDefinedActions.BugReplaceAction1" _
        And Not User.IsInGroup("Admin") then
        ActionCanExecute = False
        msgbox "You do not have permission to perform this action"
    Else
```

```
        ActionCanExecute = True
    End If
    PrintError "ActionCanExecute"
    On Error GoTo 0
End Function
```

## Example: Adding Button Functionality

This example opens a calculator when a user clicks a button defined with action name `Calculator`. For more information about adding user-defined buttons, see ["Adding a Button to a Toolbar" on page 341](#).

Add the code to the `ActionCanExecute` event procedure, so that it is triggered when a user initiates an action.

For information about the **Wscript.Shell** object, refer to the Microsoft documentation. To access help for the VBScript language, choose **Help > VBScript Home Page** in the Script Editor.

```
Function ActionCanExecute(ActionName)
    ' Initialize the function's return value to
    ' avoid unpredictable behavior.
    ActionCanExecute = DefaultRes
    On Error Resume Next
    If ActionName = "UserDefinedActions.Calculator" Then
        Set shell = CreateObject("Wscript.Shell")
        shell.Run "Calc"
        Set shell = Nothing
    End If
    ActionCanExecute = DefaultRes
    PrintError "ActionCanExecute"
    On Error GoTo 0
End Function
```

## Example: Error Handling

This example demonstrates how you can display a standard error message. Error handling should be added to each workflow script that you write, because errors that are not detected by the workflow code can cause the user's browser to crash.

The user-defined function `PrintError` receives the name of the calling procedure as a parameter. If an error has occurred, `PrintError` prints out the error number, description and severity, and the name of the procedure in which the error occurred.

You do not need to create an **Err** object, because it is intrinsic to VBScript. For more information about the **Err** object, refer to the Microsoft documentation.

```
Sub PrintError(strFunctionName)
    If Err.Number <> 0 Then
        MsgBox "Error #" & Err.Number & ": " & Err.Description, _
            vbOKOnly+vbCritical, _
```

```
        "Workflow Error in Function " & strFunctionName  
    End If  
End Sub
```

The following code segment illustrates how you can add error handling to your subroutines.

```
Sub <sub_name>()  
    On Error Resume Next  
    ...  
    [Your code here]  
    ...  
    PrintError "<sub_name>"  
End Sub
```

The following code segment illustrates how you can add error handling to your functions.

```
Function <function_name>()  
    On Error Resume Next  
    ...  
    [Your code here]  
    ...  
    PrintError "<function_name>"  
End Function
```

## Example: Obtaining Session Properties

This example demonstrates how to use the **TDConnection** object to obtain the properties of the current session. Add the code to the procedure where these properties are needed. The properties do not depend on each other, so each of the properties can be retrieved separately.

The following are examples of session properties:

```
TDConnection.ServerName  
TDConnection.ServerTime  
TDConnection.DomainName  
TDConnection.ProjectName  
User.UserName
```

Note that there is no need to use **TDConnection** to retrieve the user name because the workflow has a predefined **User** object. For more information, see ["TDConnection Object" on page 377](#).

The example below tests the first five characters of the server URL to determine whether the user is connected to the server using HTTP or HTTPS:

```
If Left(UCase(TDConnection.ServerName), 5) = "HTTPS" Then  
    MsgBox "You are currently connected to the server using SSL."  
Else  
    MsgBox "You are not using SSL."  
End If
```

## Example: Sending Mail

These examples demonstrate how to use the **TDConnection** object to send mail when a defect is submitted, and to send mail when a field value changes in the Test Plan module.

### Sending Mail when a Defect is Submitted

This example sends mail when a defect is submitted.

Add a call to the `SendDefect` procedure in the `Bug_AfterPost` event procedure.

**Note:** If the `SendDefect` procedure is called before the defect is submitted, the values that were changed in the current modification will not be included. The database is updated with the new values only after the defect is posted.

```
Sub SendDefect (iObjectId, strTo, strCc, strSubject, strComment)
    On Error Resume Next
    Dim objBugFactory, objBug
    Set objBugFactory = TDConnection.BugFactory
    Set objBug = objBugFactory.Item(iObjectId)
    objBug.Mail strTo, strCc, 2, strSubject, strComment
    Set objBug = Nothing
    Set objBugFactory = Nothing
    PrintError "SendDefect"
    On Error GoTo 0
End Sub
```

The constant 2 in the call to `objBug.Mail` indicates that the history should be included with the mail. For a list of the constants that can be used to customize email, refer to the `tagTDMAIL_FLAGS` enumeration in the *HP ALM Open Test Architecture API Reference*. In workflow scripts, use numeric constants and not the enumeration values.

### Sending Mail when a Test Plan Module Field Value Changes

The example below demonstrates mail notification when the value of the status field is changed in the Test Plan module.

The code is added to the `Test_FieldChange` event procedure. It constructs a subject and comment for the email, and calls a user-defined function, `SendTest`. `SendTest` sends mail from the Test Plan module. You can code `SendTest` similarly to the `SendDefect` subroutine shown in ["Sending Mail when a Defect is Submitted" above](#).

```
Sub Test_FieldChange(FieldName)
    On Error Resume Next
    Dim strSubject, strComment
    If FieldName = "TS_STATUS" Then
        strSubject = "Test Change Notification" & _
            " for project " & TDConnection.ProjectName & _
```



```
        " in domain " & TDConnection.DomainName  
        strComment = "The user " & User.FullName & _  
        " changed the status of the test " & _  
        Test_Fields("TS_NAME").Value & _  
        " to " & Test_Fields("TS_STATUS").Value  
        SendTest Test_Fields("TS_TEST_ID").Value, _  
        Test_Fields("TS_RESPONSIBLE").Value, "[QA Testers]", _  
        strSubject, StrComment  
    End If  
End Sub
```

## Example: Storing the Last Values Entered

This example shows how to use the **TDConnection** object to implement persistent data between actions. The lifetime of a variable in a routine is only for the routine run. Therefore, persistent data must be stored if it must be available later. It is recommended that you use the ALM API to store persistent data whenever possible instead of using external objects, files, or the registry.

In this example, a user-defined function `SW_KeepLastValue` uses the **Settings** object to save the values typed into the fields **BG\_DETECTION\_VERSION**, **BG\_USER\_01**, and **BG\_USER\_03** when a user posts a defect. These values are retrieved and assigned as default values when this user adds a new defect.

The user-defined function is called with the SET action from `Bug_CanPost`, before a new defect is posted by the user. The values in the fields are stored.

```
Function Bug_CanPost()  
    ' Initialize the function's return value to  
    ' avoid unpredictable behavior.  
    Bug_CanPost = True  
    If Bug_Fields("BG_BUG_ID").Value = "" Then  
        SW_KeepLastValue ("SET")  
    End If  
End Function
```

The function is called with the GET action from the `Bug_New` event procedure. When a user adds a new defect, the values stored in the fields for this user are entered into these fields.

```
Sub Bug_New()  
    SW_KeepLastValue ("GET")  
End Sub
```

Depending on the action passed as a parameter, the user-defined function `SW_KeepLastValue` stores the values of the fields in the common settings table for the current user, or reads the values from the **Settings** object and assigns the values to the appropriate fields.

```
Sub SW_KeepLastValue(action)  
    Dim tdc, vals, flds  
    Dim uset, pairs, pair  
    Dim bld  
    On Error Resume Next
```

```
bld = ""
Set tdc = TDConnection
Set uset = tdc.UserSettings
If action = "SET" Then
    flds = Array("BG_DETECTION_VERSION", _
        "BG_USER_01", "BG_USER_03")
    vals = ""
    For i = 0 To UBound(flds)
        If vals <> "" Then vals = vals & ";"
        vals = vals & flds(i) & "=" & _
            Bug_Fields(flds(i)).Value
    Next
    'Open category KeepLValueSetting
    uset.Open ("KeepLValueSetting")
    'Setting KeepValueFields in category KeepLValueSetting
    uset.Value("KeepValueFields") = vals
    uset.Close
End If 'SET
If action = "GET" Then
    uset.Open ("KeepLValueSetting")
    vals = uset.Value("KeepValueFields")
    If vals <> "" Then
        pairs = Split(vals, ";")
        For i = 0 To UBound(pairs)
            pair = Split(pairs(i), "=")
            If UBound(pair) = 1 Then
                Select Case pair(0)
                    Case "BG_USER_03"
                        bld = pair(1)
                    Case Else
                        If Bug_Fields(pair(0)).Value = "" Then
                            Bug_Fields(pair(0)).Value = pair(1)
                        End If
                End Select
            End If
            If Bug_Fields("BG_DETECTION_VERSION").Value _
                <> ""
                And bld <> "" Then
                SW_SetLists_VersionsBuilds _
                    "BG_DETECTION_VERSION", _
                    "BG_USER_03"
                Bug_Fields("BG_USER_03").Value = bld
                If Err.Number <> 0 Then Err.Clear
            End If 'Bug_Fields
        End If 'UBound(pair)
    Next
End If 'vals <> ""
End If 'GET
uset.Close
PrintError ("Keep Last Value (" & action & ")")
```

```
        On Error GoTo 0  
End Sub
```

## Example: Copying Field Values to Another Object

This example shows how to use the **TDConnection** object to copy the value from the **Build Number** field of a Run (**RN\_USER\_02**) to the **Last Ran On Build** field of a Test in a Test Set (**TC\_USER\_03**).

Add the code to the Run\_AfterPost event procedure.

```
Sub Run_AfterPost  
    On Error Resume Next  
    Dim tdc  
    set tdc = TDConnection  
    Dim TSFact 'As TestSetFactory  
    Set TSFact = tdc.TestSetFactory  
    Dim TstSet 'As TestSet  
    Set TstSet = TSFact.Item(Run_Fields("RN_CYCLE_ID").Value)  
    MsgBox TstSet.Name  
    Dim TSTestFact 'As TSTestFactory  
    Set TSTestFact = TstSet.TSTestFactory  
    Dim TSTst 'As TSTest  
    Set TSTst = _  
        TSTestFact.Item(Run_Fields("RN_TESTCYCL_ID").Value)  
    MsgBox TSTst.Name  
  
    TSTst.Field("tc_user_03").value = _  
        Run_Fields("RN_USER_02").Value  
    TSTst.Post  
  
    PrintError ("Run_AfterPost")  
    On Error GoTo 0  
End Sub
```



## Send Us Feedback



Can we make this Administrator Guide better?

Tell us how: [SW-Doc@hp.com](mailto:SW-Doc@hp.com)

