

HP Universal CMDB

Universal Discovery Content Guide - Third Party Integrations

Document Release Date: June 2014

Software Release Date: June 2014



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notice

© Copyright 1996 - 2014 Hewlett-Packard Development Company, L.P.

Trademark Notices

Adobe® and Acrobat® are trademarks of Adobe Systems Incorporated.

AMD and the AMD Arrow symbol are trademarks of Advanced Micro Devices, Inc.

Google™ and Google Maps™ are trademarks of Google Inc.

Intel®, Itanium®, Pentium®, and Intel® Xeon® are trademarks of Intel Corporation in the U.S. and other countries.

Java and Oracle are registered trademarks of Oracle Corporation and/or its affiliates.

Microsoft®, Windows®, Windows NT®, Windows® XP, and Windows Vista® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

- This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).
- This product includes OpenLDAP code from OpenLDAP Foundation (<http://www.openldap.org/foundation/>).
- This product includes GNU code from Free Software Foundation, Inc. (<http://www.fsf.org/>). This product includes JiBX code from Dennis M. Sosnoski.
- This product includes the XPP3 XMLPull parser included in the distribution and used throughout JiBX, from Extreme! Lab, Indiana University.
- This product includes the Office Look and Feels License from Robert Futrell (<http://sourceforge.net/projects/officeInfs/>).
- This product includes JEP - Java Expression Parser code from Netaphor Software, Inc. (<http://www.netaphor.com/home.asp>).

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to: <http://h20230.www2.hp.com/selfsolve/manuals>

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to: <http://h20229.www2.hp.com/passport-registration.html>

Or click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

Visit the HP Software Support Online web site at: <http://www.hp.com/go/hpsupport>

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services

- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

HP Software Solutions Now accesses the HPSW Solution and Integration Portal Web site. This site enables you to explore HP Product Solutions to meet your business needs, includes a full list of Integrations between HP Products, as well as a listing of ITIL Processes. The URL for this Web site is **<http://h20230.www2.hp.com/sc/solutions/index.jsp>**

Contents

Chapter 1: Aperture VISTA Integration	10
Overview	11
Supported Versions	11
Topology	11
How to Use the Aperture VISTA Integration Adapter	12
Aperture VISTA by SQL Adapter	13
Discovery Mechanism	14
Chapter 2: Atrium Integration	16
Overview	17
Supported Versions	17
How to Work with the Data Push to Atrium Adapter	18
How to Work with the Population from Atrium Adapter	22
Atrium Push Job	27
Data Push into Atrium Adapter	27
Import Data from Atrium Job	29
Population from Atrium Adapter	29
Mapping Files	31
Mapping Files Overview	31
Mapping File Structure	31
Mapping File Elements	32
Troubleshooting and Limitations	36
Chapter 3: CA CMDB Integration	37
Overview	38
Supported Versions	38
Integration Mechanism	38
How to Work with the CA CMDB Push Adapter	39
Integration Query	41
Troubleshooting and Limitations	41

Chapter 4: CiscoWorks LAN Management Solution Integration	43
Overview	44
Supported Versions	44
Topology	44
How to Discover CiscoWorks LMS	45
CiscoWorks LMS Database Ports Job	46
Adapter	46
Trigger Query	46
Parameters	46
Network Devices from CiscoWorks LMS Job	46
Adapter	46
Trigger Query	46
Layer 2 Topology from CiscoWorks LMS Job	47
Adapter	47
Trigger Query	47
Discovery Flow	48
CiscoWorks NetDevices Adapter	48
CiscoWorks Layer 2 Adapter	49
Discovery Mechanism	52
Troubleshooting and Limitations	54
Chapter 5: EMC Control Center (ECC) Integration	55
Overview	56
Supported Versions	56
Topology	56
How to Run the ECC/UCMDB Integration Job	57
ECC Integration Job	59
Views	62
Impact Analysis Rules	67
Reports	69
Chapter 6: IDS Scheer ARIS Integration	73
Overview	74

Supported Versions	74
Topology	74
How to Run the ARIS Integration Job	75
Import CIs from ARIS Job	81
Chapter 7: Importing Data from External Sources	83
Overview	84
Comma Separated Value (CSV) Files	84
CSV Files with Column Titles in First Row	85
Databases	85
Properties Files	85
How to Import CSV Data from an External Source – Scenario	86
How to Convert Strings to Numbers	91
Custom Converters	92
External_source_import Package	92
Import from CSV File Job	93
Import from Database Job	96
Import from Properties File Job	101
External Source Mapping Files	102
Troubleshooting and Limitations	103
Chapter 8: Import from Excel Workbook Discovery	104
Overview	105
Supported Versions	105
Topology	105
How to Import Data from Excel Workbook	105
How to Set Up an Import File in Excel	107
Import from Excel Workbook Job	116
Troubleshooting and Limitations	119
Chapter 9: Microsoft SCCM/SMS Integration	121
Overview	122
Supported Versions	122
SMS Adapter	122

How to Populate the CMDB with Data from SCCM/SMS	124
How to Federate Data with SCCM/SMS	125
How to Customize the Integration Data Model in UCMDB	126
Predefined Query for Population Jobs	127
SCCM/SMS Integration Package	127
SMS Adapter Configuration Files	130
Troubleshooting and Limitations	131
Chapter 10: NetApp SANscreen/OnCommand Insight Integration	132
Overview	133
Supported Versions	133
Topology	133
How to Discover NetApp SANscreen (NetApp OnCommand Insight)	134
SANscreen Integration by WebServices Job	135
Adapter	135
Parameters	136
Integration Flow	136
SANscreen Adapter	136
Troubleshooting and Limitations	138
Chapter 11: ServiceNow Integration	139
Overview	140
Supported Versions	140
Push Integration with ServiceNow	140
How to Push Data from UCMDB to ServiceNow	140
Push Integration Mechanism	142
Sample Integration Push Query	143
Supported CITs	144
Pushing Additional CITs	144
Population from ServiceNow	145
How to Populate UCMDB with Data from ServiceNow	146
Population Flow	148
Jython Scripts for Population	148

Mapping Files for Population Flow	149
Supported CITs	151
Troubleshooting and Limitations	152
Chapter 12: Storage Essentials (SE) Integration	153
Overview	155
Supported Versions	155
How to Perform the SE Integration	155
Storage Essentials Integration Packages	156
Adapter Parameters	156
Discovered CITs and Relationships	157
Node Details	159
SAN Topology	160
Storage Topology	161
Views	162
Storage Array Details	162
FC Switch Details	162
FC Switch Virtualization	163
Storage Pool Details	163
Host Storage Details	164
SAN External Storage	164
SAN Topology	165
Storage Topology	166
FC Port to FC Port	166
Impact Analysis Rules	167
FC Port to FC Port	167
FC Switch Devices to FC Switch	168
Host Devices to Host	168
Logical Volume to Logical Volume	169
Storage Array Devices to Storage Array	169
Reports	170
Storage Array Configuration	170

Host Configuration	170
Storage Array Dependency	171
Host Storage Dependency	171
Storage Pool Configuration	171
Troubleshooting and Limitations	172
Chapter 13: Troux Integration	173
Overview	174
Integration Overview	174
Supported Versions	175
Use Cases	175
How to Work with the Troux Push Adapter	175
How to Run a Troux Population Job	181
Chapter 14: UCMDB to XML Adapter	183
Overview	184
Integration Mechanism	184
How to Export UCMDB to XML	184
Adapter	185
Troubleshooting and Limitations	186

Chapter 1: Aperture VISTA Integration

This chapter includes:

Overview	11
Supported Versions	11
Topology	11
How to Use the Aperture VISTA Integration Adapter	12
Aperture VISTA by SQL Adapter	13
Discovery Mechanism	14

Overview

Aperture VISTA is used to model datacenter information, including the exact location of a physical server in a rack, row, space, and floor of a datacenter. VISTA also contains detailed information about the power supply to racks and individual servers. This enables impact analysis from a power supply point of view, and with integration it becomes possible to analyze the impact of power failure on applications, business services and lines of business in UCMDB.


Integration is accomplished by running SQL queries on the Aperture VISTA SQL database.

Supported Versions

UCMDB supports integration with Aperture VISTA version 600. Aperture Integration Management Software Package version 2.0 or later is required.

Topology

The following image displays datacenter topology from VISTA.



Note: For a list of discovered CITs, see ["Discovered CITs" on the next page](#).

How to Use the Aperture VISTA Integration Adapter

1. Prerequisite - Scripts

The following scripts should be run on the VISTA database:

- **v600_VIP_DAL_DV_Devices.sql**
- **v600_Device_to_PDU.sql**

The scripts are located in the discovery probe at
<hp>\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\VistaScripts

2. Prerequisite - Credentials

Population is accomplished using SQL queries over JDBC. The following credentials should be defined:

- Generic DB Protocol (SQL)

For credential information, see "Supported Protocols" in the *HP Universal CMDB Discovery and Integration Content Guide - Supported Content* document.

3. Run the job

- a. Run **Range IPs by ICMP** to discover the IP address of the SQL Server used by Aperture VISTA.
- b. Run **Database TCP Ports** to discover SQL Server ports on the IP addresses discovered above.
- c. Run **MSSQL Connection by SQL** to discover the SQL Server instance used by Aperture VISTA.
- d. Run **MSSQL Topology by SQL** to discover database instances in the SQL Server instance discovered above.
- e. Create a new integration point, and use the **Aperture VISTA by SQL** adapter to discover datacenter and power infrastructure from VISTA.


Aperture VISTA by SQL Adapter

This section contains details about the adapter.

Input CIT

Microsoft SQL Server

Input Query



Triggered CI Data

Name	Value
credentialsId	\${SOURCE.credentials_id}
ip_address	\${SOURCE.application_ip}
port	\${PROCESS.application_port}

Used Script

Aperture_Vista_by_SQL.py

Discovered CITs

- Chassis
- Composition
- Containment
- Datacenter

- DatacenterResource
- Node
- PowerDistributionUnit
- Rack
- RemotePowerPanel
- Usage

Discovery Mechanism

Aperture VISTA uses a Microsoft SQL Server database as its data repository. The Aperture Integration Management software package (v2.0 or greater) adds some views to the VISTA database, and this integration adapter collects information by running SQL Queries against these views.

The integration adapter in this package is triggered by SQL Server instances in UCMDB that have a database instance with **vista** in their name. Out-of-the-box discovery jobs may be used to discover these SQL Server database instances.

The adapter works as follows:

1. Datacenter and Power Infrastructure Details

It runs the following SQL query to get details on Datacenter and Power infrastructure from the Aperture VISTA data repository:

```
SELECT device_name, device_serial_number, device_asset_class, device_manufac  
turer, device_model, device_model_info, rack_name, rack_asset_number, rack_s  
erial_number, row_name, grid_location, space_name, floor, building_name, pa  
rent_name, parent_serial_number
```

```
FROM vista.dbo.vip_dal_dv_devices
```

```
WHERE device_asset_class='SERVER' OR device_asset_class='PDU' OR device_asse  
t_class='RPP' OR device_asset_class='CHASSIS' OR device_asset_class='RACK'
```

```
GROUP BY device_name, device_serial_number, device_asset_class, device_manuf  
acturer, device_model, device_model_info, rack_name, rack_asset_number, rack_  
serial_number, row_name, grid_location, space_name, floor, building_name, pa  
rent_name, parent_serial_number
```

```
ORDER BY device_asset_class, device_name
```

2. Identification of Power Supply Routing

After all the infrastructure, power, and server CIs are created, the adapter uses the following query to identify power supply routing to servers:

```
SELECT downstream_device_name, downstream_device_serial_number, upstream_device_name, upstream_building_name

FROM vista.dbo.vip_dal_pwr_device_power_sources

WHERE (downstream_device_name IS NOT NULL OR downstream_device_serial_number IS NOT NULL) AND upstream_device_name IS NOT NULL AND upstream_building_name IS NOT NULL AND upstream_node_type='PDU'

GROUP BY downstream_device_name, downstream_device_serial_number, upstream_device_name, upstream_building_name

ORDER BY downstream_device_name
```

Chapter 2: Atrium Integration

This chapter includes:

- Overview 17
- Supported Versions 17
- How to Work with the Data Push to Atrium Adapter 18
- How to Work with the Population from Atrium Adapter 22
- Atrium Push Job 27
- Data Push into Atrium Adapter 27
- Import Data from Atrium Job 29
- Population from Atrium Adapter 29
- Mapping Files 31
 - Mapping Files Overview 31
 - Mapping File Structure 31
 - Mapping File Elements 32
- Troubleshooting and Limitations 36

Overview

UCMDB-Atrium integration consists of two independent, bi-directional parts: the **Data Push into Atrium** and the **Population from Atrium**.

- The **Data Push into Atrium** in UCMDB replicates CIs and relationships to Atrium and Remedy.

The out-of-the-box integration does not transfer a specific list of CIs and relationships, but does enable you to replicate any CI or relationship from UCMDB to Remedy or Atrium.

For examples of enabling the integration with commonly used CIs and relationships, see ["How to Work with the Data Push to Atrium Adapter" on the next page](#).

- The **Population from Atrium** in UCMDB pulls CIs and relationships from Atrium to UCMDB.

Supported Versions

HP Universal CMDB integrates with the following BMC products:

- BMC Remedy Service Desk (Remedy) versions 7.0, 7.1, 7.5, and 7.6
- BMC Atrium CMDB (Atrium) versions 2.0, 2.1, 7.5.x, 7.6.x and earlier, 8.1

How to Work with the Data Push to Atrium Adapter

This task includes the following steps:

- ["How to Work with the Data Push to Atrium Adapter" above](#)
- ["How to Work with the Data Push to Atrium Adapter" above](#)
- ["How to Work with the Data Push to Atrium Adapter" above](#)
- ["How to Work with the Data Push to Atrium Adapter" above](#)
- ["How to Work with the Data Push to Atrium Adapter" above](#)
- ["How to Work with the Data Push to Atrium Adapter" above](#)
- ["How to Work with the Data Push to Atrium Adapter" above](#)
- ["How to Work with the Data Push to Atrium Adapter" above](#)

1. Prerequisite - Set up protocol credentials

Make sure that you have set up the Remedy protocol. For credential information, see "Supported Protocols" in the *HP Universal CMDB Discovery and Integration Content Guide - Supported Content* document.

2. Configure the Properties file

Configure the **push.properties** file: **Data Flow Management > Adapter Management > Resources > Packages > AtriumPushAdapter > Configuration Files > push.properties.**

Property	Description
jythonScript.name	The name of the Jython script that is invoked by this push adapter.
mappingFile.default	The default XML mapping file used by mapping if a specific XML mapping file is not defined for an integration query. At least one default mapping file must be present in every adapter.
DebugMode	If this value is set to true , the CI and relationships being pushed to Remedy/Atrium are also saved to XML files on the Data Flow Probe, under the following folder: /discoveryResource/AtriumPushAdapter/work.

Property	Description
smartUpdateIgnoreFields	A comma separated list of attributes (transferred from UCMDB to Atrium) that should not be used to check whether a CI has changed in Atrium. For example, as updateTime always changes, you would not want to update a CI in Atrium just because this attribute has changed.
sortCSVFields	Parameter that includes the TQL results of CSV aggregated fields that must always be sorted. When child attribute values are mapped and aggregated as CSV, the results are not sorted. This can trigger an update, even though nothing has changed in Atrium. To prevent an update, add here the CSV aggregated fields that must always be sorted.
testConnNameSpace	Must be set to the BMC NameSpace being used for test connection purposes (for example, BMC.CORE).
testConnClass	Must be set to the name of a BMC class, to query for connection test purposes (for example, BMC_ComputerSystem).

3. Configure the Data Flow Probe

- a. **For Atrium 7.6.04 and earlier versions:** Copy the JAR and DLL files listed below from the BMC server to the following directory on the Data Flow Probe server:
C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\AtriumPushAdapter.

For Atrium 8.1: Copy the files **arapi81_build001.jar** and **cmdbapi.jar** from the BMC server to the following directory on the Data Flow Probe server:
C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\AtriumPushAdapter.

The directory

C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\AtriumPushAdapter is automatically created once the **AtriumPushAdapter** package is deployed on the UCMDB Server. If it is not present, ensure that the **AtriumPushAdapter** package has been correctly deployed on the UCMDB Server.

For details on deploying packages, see "Package Manager" in the *HP Universal CMDB Administration Guide*.

JAR Files	DLL Files
arapi75.jar	arapi75.dll
arutil75.jar	arencrypt75.dll
cmdbapi75.jar	arjni75.dll
commons-beanutils.jar	arpc75.dll
commons-codec-1.3.jar	arutiljni75.dll
commons-collections-3.2.jar	arutil75.dll
commons-configuration-1.3.jar	arxmlutil75.dll
commons-digester-1.7.jar	cmdbapi75.dll
commons-lang-2.2.jar	cmdbjni75.dll
log4j-1.2.14.jar	icudt32.dll
oncrpc.jar	icuinbmc32.dll
spring.jar	icuucbmc32.dll
	Xalan-Cbmc_1_9.dll
	XalanMessagesbmc_1_9.DLL
	xerces-cbmc_2_6.dll
	xerces-depdombmc_2_6.dll

Note:

- The AR System Java API is forward and backward compatible with other versions of the AR System, except Atrium version 7.6.0.4 where you must use the SDK of the same version. For a complete compatibility matrix, refer to the "API Compatibility" section in the *BMC Remedy/Atrium Developer Reference Guide*.
- The arencrypt*.dll files are only required if encryption is enabled on the Remedy server.

- Edit the **WrapperGateway.conf** file (or **WrapperManager.conf** if the Probe Manager and Gateway are running in separate mode) in the following directory:
C:\hp\UCMDB\DataFlowProbe\bin.

Add the following line after the **wrapper.java.library.path.2=%content_dll%** line:


```
wrapper.java.library.path.3=%runtime%/probeManager  
/discoveryResources/AtriumPushAdapter
```

- c. **For Atrium 7.6.04 and earlier versions only:** Add the complete path to the Atrium DLL files (for example, **C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\AtriumPushAdapter**) to the Windows system path on the Data Flow Probe machine.
- d. Restart the Data Flow Probe service.

4. Configure synchronization queries

The CIs and relationships to be pushed to Remedy/Atrium must be queried from UCMDB. Create queries (of type **Integration**) to query the CIs and relationships that have to be pushed to Remedy/Atrium.

An example of such a query (**atrium_push_sample_query**) is included with the Atrium package. To access the query, navigate to **Modeling > Modeling Studio > Root > Integration > Atrium**.



5. Create XML mapping files

For every query created in the step above, create an XML mapping file with the same name as the integration query (the name must have the same case) in the following directory:

C:\hp\UCMDB\UCMDBServer\runtime\fcmdb\CodeBase\AtriumPushAdapter\mappings

A sample mapping file (**atrium_push_sample_query.xml**) is provided out-of-the-box with the Atrium package.

For more details, see ["Mapping Files" on page 31](#).

6. Create an integration point

For details about creating an integration point, see "Integration Point Pane" in the *HP Universal CMDB Data Flow Management Guide*.

- a. In the Integration Studio, create an integration point, selecting the **Data Push into Atrium** adapter. Enter the following information:

Name	Description
Credentials	<ul style="list-style-type: none">◦ Select Remedy Protocol.◦ Select the credentials to be used with this integration point. <p>For credential information, see "Supported Protocols" in the <i>HP Universal CMDB Discovery and Integration Content Guide - Supported Content</i> document.</p>
Hostname/IP	The host name or IP address of the BMC Remedy server.
Integration Name	The name you give to the integration point.
Is Integration Activated	Select this check box to create an active integration point. You clear the check box if you want to deactivate an integration, for instance, to set up an integration point without actually connecting to a remote machine.
Port	The port number of the BMC Remedy server.
Data Flow Probe	Select the Data Flow Probe that should run this integration.

- b. Test the connection. If a connection is not successfully created, check the integration point parameters and try again.
- c. Save the integration point.

7. Define a Job

For details, see "New Integration Job/Edit Integration Job Dialog Box" in the *HP Universal CMDB Data Flow Management Guide*.

Select the queries that will synchronize data between UCMDB and Remedy/Atrium. Save the job definition and the integration point.

8. Invoke a full run of the job

In the Integration Studio, on the Job Definition tool bar, click  to run a full discovery job. For details, see "Integration Jobs Pane" in the *HP Universal CMDB Data Flow Management Guide*.

How to Work with the Population from Atrium Adapter

This task includes the following steps:

- ["Prerequisites - File preparation" below](#)
- ["Prerequisites - Set up protocol credentials" on page 25](#)
- ["Prerequisites - Create XML mapping files" on page 25](#)
- ["Run the job" on page 25](#)

1. **Prerequisites - File preparation**

- a. **For Atrium 7.6.04 and earlier versions:** Locate the files listed below on the Remedy ARS and Atrium system, and copy them to:

C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\AtriumImportAdapter

Note: All the files listed below are required.

For Atrium 8.1: Locate the files **arapi81_build001.jar** and **cmdbapi.jar** on the Remedy ARS and Atrium system and copy them to:

C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\AtriumImportAdapter

JAR Files	DLL Files
arapi75.jar	arapi75.dll
arutil75.jar	arencrypt75.dll
cmdbapi75.jar	arjni75.dll
commons-beanutils.jar	arpc75.dll
commons-codec-1.3.jar	arutiljni75.dll
commons-collections-3.2.jar	arutil75.dll
commons-configuration-1.3.jar	arxmlutil75.dll
commons-digester-1.7.jar	cmdbapi75.dll
commons-lang-2.2.jar	cmdbjni75.dll
log4j-1.2.14.jar	icudt32.dll
oncrpc.jar	icuinbmc32.dll
spring.jar	icuucbmc32.dll
	Xalan-Cbmc_1_9.dll
	XalanMessagesbmc_1_9.DLL
	xerces-cbmc_2_6.dll
	xerces-depdombmc_2_6.dll

Note:

- The AR System Java API is forward and backward compatible with other versions of the AR System, except Atrium version 7.6.0.4 where you must use the SDK of the same version. For a complete compatibility matrix, refer to the "API Compatibility" section in the *BMC Remedy/Atrium Developer Reference Guide*.
- The arencrypt*.dll files are only required if encryption is enabled on the Remedy server.

- Edit the **WrapperGateway.conf** file (or **WrapperManager.conf** if the Probe Manager and Gateway are running in separate mode) in the following directory:
C:\hp\UCMDB\DataFlowProbe\bin.

Add the following line after the **wrapper.java.library.path.2=%content_dll%** line:

```
wrapper.java.library.path.3=%runtime%/probeManager  
/discoveryResources/AtriumPushAdapter
```

- c. **For Atrium 7.6.04 and earlier versions only:** Add the complete path to the Atrium DLL files (for example, **C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\AtriumImportAdapter**) to the Windows system path on the Data Flow Probe machine.
- d. Restart the Data Flow Probe service.

2. Prerequisites - Set up protocol credentials

Configure a generic protocol with the ARS server's username and password.

Note: While creating the generic protocol, set the protocol description to **atrium**.

3. Prerequisites - Create XML mapping files

This step involves creating XML mapping files (in the **<probe>\runtime\probeManager\discoveryResources\TQLE\export\Atrium\data** directory). These files map the BMC Atrium classes, attributes and relationships to their UCMDB equivalents. To create the XML mapping files for the topology requires identification of the topology to be imported from Atrium, and ensuring an equivalent topology exists in UCMDB. For more details, see ["Mapping Files" on page 31](#).

4. Run the job

In the Integration Studio, create a new integration point.

- a. Provide a name and description for the integration point.
- b. Under **Integration Properties > Adapter**, select the **Population from Atrium** adapter.
- c. Configure the following adapter properties:
 - o **ARS_Server**
 - o **ARS_Port**
 - o **BMC_NameSpace**
- d. Under **Adapter Properties > Data Flow Probe**, select the Data Flow Probe to be used for the integration.
- e. Under **Adapter Properties > Trigger CI instance** select:
 - i. **Select Existing CI** (if you have a valid, existing CI). The **Select Existing CI** pane appears. Select the CI, or

- ii. **Create New CI** (if you need to create a new CI). The **Topology CI Creation Wizard** appears. Complete the creation of the CI using the Wizard.

Note: For details on the Topology CI Creation Wizard, see "Topology CI Creation Wizard" in the *HP Universal CMDB Data Flow Management Guide*.

- f. Save the integration point.
- g. Run the job.

Note: For details on running an integration job, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

Atrium Push Job

Adapter

This discovery uses the adapter called **Data Push into Atrium**.

Integration Flow

Integration includes the following activities:

1. **Querying the UCMDB for CIs and relationships.** When an ad-hoc integration job is run in the Integration Studio, the integration process:
 - a. Receives the names of the integration queries that are defined in the job definition for that integration point.
 - b. Queries UCMDB for the results (new, updated, or deleted CIs and relationships) of these defined queries.
 - c. Applies the mapping transformation according to the pre-defined XML mapping files for every query.
 - d. Pushes the data to the Data Flow Probe.
2. **Sending the data to BMC Remedy/Atrium.** On the Data Flow Probe, the integration process:
 - a. Receives the CI and relationship data sent from the UCMDB Server.
 - b. Connects to the BMC Remedy/Atrium server using the Java API.
 - c. Transfers the CIs and relationships.

Data Push into Atrium Adapter

This section contains details about the adapter.

Used Script

pushToAtrium.py

Parameters

Parameter	Description
credentialsId	The credentials ID to use for Atrium connection.
host	The host name or IP address of the remote Atrium server.
port	The Atrium server's connection port (if not using portmapper).
probeName	An internal setting which UCMDB automatically replaces.

Import Data from Atrium Job

Adapter

This job uses the adapter called **Population from Atrium**.

Integration Flow

The integration flow has the following steps:

1. **Querying the Atrium server**

In this step, the integration adapter connects to the Atrium server and queries it for classes, attributes and relationships, described in the XML mapping files. The result of this step is the creation of intermediate XML files (in the `<probe>\runtime\probeManager\discoveryResources\TQLE\export\Atrium\inter` directory).

2. **Mapping the data**

In this step, the data collected from the previous step and stored in the intermediate XML file, is converted into the UCMDB data format based on the mappings defined in the XML mapping files.

3. **Pushing the data to the UCMDB server**

In this final step, after being mapped into the UCMDB object state holder vector format, the data is sent to the UCMDB server.

Population from Atrium Adapter

This section contains details about the adapter.

Input CIT

The input CIT for this adapter is **discoveryprobegateway**. The job uses an instance of the Discovery Probe Gateway which has access to connect to the remote BMC Atrium server.

Used Scripts

The adapter uses the following scripts:

Script	Description
<code>atrium_query.py</code>	Used to query BMC Atrium for data.
<code>atrium_map.py</code>	Used to map the queried data into data UCMDB can use.

Script	Description
atrium_to_ucmdb.py	Used to push imported data into UCMDB.

Discovered CITs

This integration can discover any CIT or relationship which is (a) mapped in the integration and (b) can be queried and converted to its UCMDB equivalent.

Parameters

Parameter	Detail
ARS_Port	The port for connecting to the ARS server. If portmapper is being used, this should be left as 0. Otherwise, specify the TCP port.
ARS_Server	The hostname or IP address of the BMC ARS server.
BMC_NameSpace	The BMC NameSpace to use. (For example: BMC.CORE.)
ChunkSize	The chunk size in which data should be retrieved from the remote server.
DateParsePattern	Set the date pattern to parse Atrium date strings.
DebugMode	Set to true to run integration in debug mode; this does not send data to UCMDB.

Mapping Files

This section includes:

Mapping Files Overview	31
Mapping File Structure	31
Mapping File Elements	32

Mapping Files Overview

A mapping file is an XML file that defines which CIT or relationship in UCMDB is mapped to which CIT or relationship in the target data repository.

Mapping files:

- Control which CITs and relationships are to be pushed.
- Control the attributes for the CITs and relationships that are to be mapped.
- Map attribute values from multiple CIs to one target CI.
- Map attributes of children CIs (those having a **containment** or **composition** relationship) to the parent CI in the target data repository. For example:
 - Set a **Number of CPUs** value for a target **node** CI.
 - Set a **Total Memory** value for a target **node** CI.
- Map attributes of parent CIs (those having a **containment** or **composition** relationship) in the target data repository CI. For example, in the Atrium target data repository, set the value of a **Container Server** attribute on the **Installed Software** CIT by retrieving the value of the UCMDB **Installed Software** CI container node.

Mapping File Structure

Every mapping file has the following skeletal structure:

```
<?xml version="1.0" encoding="UTF-8"?>
<integration>
  <info>
    <source ... .. />
    <target ... .. />
  </info>
  <source_ci_type name="...">
```

```
<target_ci_type name="...">
  <targetprimarykey>
    <pkey>...</pkey>
  </targetprimarykey>
  <target_attribute name="..." datatype="..." >
    <map type="..." />
  </target_attribute>
</target_ci_type>
</source_ci_type>
</integration>
```

Note: An ellipsis (...) signifies a configurable section.

Mapping File Elements

This section includes:

Main Parent Elements

- **<integration>**. The root element of the XML file. This element has no attributes.
- **<info>**. The source and target data repositories being used, for example:

```
<info>
<source name="Atrium" versions="7.6" vendor="BMC" />
<target name="UCMDB" versions="9.0" vendor="HP" />
</info>
```

- **<targetcis>**. The element that encapsulates the mapping for all CI types.
- **<targetrelations>**. The element that encapsulates the mapping for all relationship types.

CI Type Mapping Elements

- **<source_ci_type>**. The element that defines a CI type of the source data repository, for example:

```
<source_ci_type name="BMC_ComputerSystem" nameSpace="BMC.CORE" query="" mode="update_else_insert">
```


- **Attribute: name.** Defines the name of the source CI type.
- **Attribute: namespace.** Defines the namespace in the Atrium system that the CI type is associated with.

- **Attribute: query.** Allows applying an additional filter to the query result.

For example, query="\"DatasetId\"="BMC.ASSET" AND 'AssetLifecycleStatus'!=8\".

- **Attribute: mode.** Defines the mode of the update in the target data repository. The possible values are: **update**, **insert**, and **update_else_insert**.

- **<target_ci_type>.** The element that defines the target CIT, for example:

```
<target_ci_type name="unix">
```

- **Attribute: name.** Defines the name of the target CIT.

- **<targetprimarykey>.** The element that defines a list of all primary keys of the target CIT, for example:

```
<targetprimarykey>  
  <pkey>host_key</pkey>  
</targetprimarykey>
```

- **<target_attribute>.** The element that defines an attribute mapping from the source CI type to the target CI type attribute. Attribute mapping can be of the following types:

- **Constant.** This type enables setting a constant value on the target attribute:

```
<target_attribute name="data_note" datatype="string" length="127">  
  <map type="constant" value="ATRIUM DATA" />  
</target_attribute>
```

- **Direct.** This type enables setting a direct value of a source data repository attribute on the target data repository:

```
<target_attribute name="name" datatype="string">  
  <map type="direct" source_attribute="Name" />  
</target_attribute>
```

- **Compound String.** This type enables the use of the above mapping types together to form more complex values for the target attribute, for example:

```
<target_attribute name="Bunch_0_Data" datatype="char" length="510" option="uppercase">
  <map type="compoundstring">
    <source_attribute name="name"/>
    <constant value="_UNIX_Server, IP="/>
    <childattr name="ip_address" source_attribute="ip_address" aggregation="csv"/>
    <constant value=", CPU="/>
    <childattr name="cpu" source_attribute="display_label" aggregation="csv"/>
  </map>
</target_attribute>
```

Relationship Type Mapping Elements

- **<link>**. The element that defines a relationship mapping from the source data repository to a target data repository, for example:

```
<link source_link_type="composition"
      target_link_type="BMC_HostedSystemComponents"
      source_ci_type_end1="unix"
      source_ci_type_end2="cpu"
      role1="Source"
      role2="Destination"
      mode="update_else_insert">
  <target_ci_type_end1 name="BMC_ComputerSystem"
    superclass="BMC_System" />
  <target_ci_type_end2 name="BMC_Processor"
    superclass="BMC_SystemComponent" />
  ... Relationship attribute mapping elements similar to the CI type attribute mapping elements ...
</link>
```

- **Attribute: source_ci_type_end1.** The **End1** CI type of the source link.
- **Attribute: source_ci_type_end2.** The **End2** CI type of the source link.
- **Attribute: source_link_type.** Defines the name of the source link. To specify namespace, use the following format: "NAMESPACE:CLASSNAME". For example: BMC.J2EE:BMC_J2EEApplicationServer. The same format applies to <antecedent> and <dependent> elements.
- **Attribute: target_link_type.** Defines the name of the target link. To specify namespace, use the following format: "NAMESPACE:CLASSNAME". For example: BMC.J2EE:BMC_J2EEApplicationServer. The same format applies to <antecedent> and <dependent> elements.

- **<target_ci_type_end1>**. Used to specific the value of the target links end1 CI type.
- **<target_ci_type_end2>**. Used to specific the value of the target links end2 CI type.

Troubleshooting and Limitations

The integration mapping file enables the mapping only of concrete CI types and relationships to the CI types and relationships in BMC Remedy/Atrium. That is, a parent CIT cannot be used to map children CIs. For example, if **UCMDB Node** is mapped to **BMC_ComputerSystem**, any Node CIT of type **Unix** is not transferred. A mapping must be separately created for **Unix** to **BMC_ComputerSystem**.

Chapter 3: CA CMDB Integration

This chapter includes:

- Overview 38
- Supported Versions 38
- Integration Mechanism 38
- How to Work with the CA CMDB Push Adapter 39
- Integration Query 41
- Troubleshooting and Limitations 41

Overview

The UCMDB - CA CMDB integration adapter allows pushing CIs and relationships from UCMDB into CA CMDB.

This is achieved by querying the UCMDB for CIs and Relationships based on queries defined in the push integration adapter. The output of the queried CIs and Relationships are saved in an XML file.

GRLoader, a utility provided with CA CMDB, transfers the CIs and Relationship data stored in the XML file into CA CMDB. An XML mapping file is used to define how the CIs and Relationships in UCMDB are related to the CIs and Relationships in CA CMDB.

The CA CMDB integration package is bundled in **CACmdbPushAdapter.zip**.

Supported Versions

UCMDB supports integration with CA CMDB R12.5 and R12.0.

Integration Mechanism

This section describes the UCMDB - CA CMDB integration mechanism:

1. UCMDB is queried for CIs and Relationships

- a. When an ad-hoc job is run from the defined integration point, the integration receives the names of the integration queries that have been defined in the job definition for that integration point.
- b. The integration process queries UCMDB for the results of these queries (new/updated/deleted CIs and Relationships), and applies the mapping transformation according to the pre-defined XML mapping files for every query.
- c. It then pushes the data to the Data Flow Probes.

2. Queried data is converted into temporary XML files on the Data Flow Probe system

On the Data Flow Probe side, the integration process receives the CI and Relationship data sent from the UCMDB server, and converts it into a format which can be used as input XML for the GRLoader, a utility provided with CA CMDB used to transfer the CI and Relationship data into CA CMDB.

3. CA CMDB GRLoader utility is invoked on the Data Flow Probe system

The integration process programmatically invokes the CA CMDB GRLoader utility on the Data Flow Probe system with the necessary parameters (for example, CA CMDB server, port, username, and password), using the input XML file created in the previous step to transfers the CIs and Relationship data into CA CMDB.

How to Work with the CA CMDB Push Adapter

The CA CMDB push adapter allows replication of CIs and Relationships from UCMDB to CA CMDB.

This task includes:

- ["Prerequisite - Other" below](#)
- ["Prerequisite - Set up the CA CMDB protocol" below](#)
- ["Configure integration queries" below](#)
- ["Create the XML mapping files" on the next page](#)
- ["Create an integration point" on the next page](#)

1. Prerequisite - Set up the CA CMDB protocol

This integration uses the **CA CMDB protocol**. For credential information, see "Supported Protocols" in the *HP Universal CMDB Discovery and Integration Content Guide - Supported Content* document.

2. Prerequisite - Other

Data Flow Probe System:

- a. Copy all of the files in the CA CMDB system's **%NX_ROOT%\java\lib** directory to the **CaCmdbPushAdapter** directory on the data flow probe system:

```
<UCMDB Installation>\DataFlowProbe\runtime\probeManager\  
discoveryResources\CaCmdbPushAdapter
```

- b. Locate the file, **NX.ENV**, in the **CaCmdbPushAdapter** directory. If the file does not exist, create it in the **CaCmdbPushAdapter** directory and add the following text to it:

```
@NX_LOG=C:/CA/java/lib/log
```

- c. Open **<UCMDB Installation>\DataFlowProbe\runtime\probeManager\discoveryConfigFiles\globalSettings.xml**, locate the following line, and add **",CaCmdbPushAdapter/*.*)" as illustrated in bold:**

```
db/oracle/*.*;db/mssqlserver/*.*;db/db2/*.*;db/sybase/*.*;nnm/*.*;Atrium  
PushAdapter/*.*;CaCmdbPushAdapter/*.*
```

- d. Restart the Data Flow Probe service.

3. Configure integration queries

Create integration queries to query the CIs and Relationships that must be pushed from UCMDB to CA CMDB.

For an example of such an integration query, see ["Integration Query" on the next page](#).

4. Create the XML mapping files

For every integration query that you create, create an XML mapping file with the exact same name as the integration query (case-sensitive). Create the XML files in the following directory:

```
<UCMDB Installation>\UCMDBServer\runtime\fcmdb\CodeBase\  
CaCmdbPushAdapter\mappings
```

For more information about mapping files, see "Prepare the Mapping Files" in the *HP Universal CMDB Developer Reference Guide*.

Note: A sample mapping file, **Unix_SW_to_CACMDB.xml**, is provided out-of-the-box with the integration package.

5. Create an integration point

In UCMDB create an integration point. (For details, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.)

Include the following details:


- a. Provide a name and description for the integration point.
- b. Provide the following details for the **CaCmdbPushAdapter** adapter:

Attribute	Description
Hostname/IP	The host name or IP address of the CA CMDB server.
Port	The port number of the CA CMDB server.
Credentials	The CA CMDB credential that was created in the prerequisites section above
Data Flow Probe	The name of the Data Flow Probe on which the integration runs.

- c. Test the connection to the target CMDB server.
- d. Add a job definition to the integration point, selecting the queries to use to synchronize data between UCMDB and CA CMDB. Define a synchronization schedule, if required.
- e. Invoke the ad hoc job, **Full Topology Sync**, for a full synchronization of the data.

Integration Query

The integration query, **Unix_SW_to_CACMDB**, is included with the CA CMDB integration package. This is an example of a query that can be used to query the CIs and relationships that must be pushed from UCMDB to CA CMDB. This query is accessible from UCMDB's Modeling Studio, among the query resources. For details, see "Modeling Studio Page" in the HP Universal CMDB Modeling Guide.



Troubleshooting and Limitations

This section describes troubleshooting and limitations related to UCMDB - CA CMDB integration.

- **Debug Mode**

To create an XML dump of the CIs and links being sent to the CA CMDB server for debug purposes, in **<UCMDB installation>\DataFlowProbe\runtime\probeManager\discoveryConfigFiles\CaCmdbPushAdapter\push.properties**, set the value of the **debugMode** property to **true** and restart the Data Flow Probe service.

This ensures that every time the integration is invoked, a set of XML files is created in the **<UCMDB installation>\DataFlowProbe\runtime\probeManager\discoveryResources\CaCmdbPushAdapter\work** directory. These files are time-stamped and contain the CIs and links that UCMDB is trying to push to CA CMDB. This information can be helpful in debugging a problem with the integration:

- If data is not being sent from UCMDB, there is a problem on the UCMDB side.
- If data is not being processed by CA CMDB's GRLoader utility, there might be a reconciliation issue or some other issue on the CA CMDB side.
- During the export of more than 4,000 CIs (this is default UCMDB configuration) the export TQL

result is divided into chunks. To make sure that chunks are created properly, you must configure the export TQL as follows: In the container node's properties, set the **Element Name** field to **Root**.

Chapter 4: CiscoWorks LAN Management Solution Integration

This chapter includes:

- Overview 44
- Supported Versions 44
- Topology 44
- How to Discover CiscoWorks LMS 45
- CiscoWorks LMS Database Ports Job 46
 - Adapter 46
 - Trigger Query 46
 - Parameters 46
- Network Devices from CiscoWorks LMS Job 46
 - Adapter 46
 - Trigger Query 46
- Layer 2 Topology from CiscoWorks LMS Job 47
 - Adapter 47
 - Trigger Query 47
 - Discovery Flow 48
- CiscoWorks NetDevices Adapter 48
- CiscoWorks Layer 2 Adapter 49
- Discovery Mechanism 52
- Troubleshooting and Limitations 54

Overview

CiscoWorks LAN Management Solution (LMS) is a suite of management tools that simplify the configuration, administration, monitoring, and troubleshooting of Cisco networks.

This integration involves synchronizing devices, topology, and hierarchy of network infrastructure in UCMDB, and also synchronizes relationships between various hardware and logical network entities to enable end-to-end mapping of the data network infrastructure. The integration enables change management and impact analysis across all business services mapped in UCMDB, from a data network point of view.


Supported Versions

This integration supports CiscoWorks LAN Management Solution Version 3.x.

Topology

The following image displays the CiscoWorks LAN Management Solution topology.

Note: For a list of discovered CITs, see ["Discovered CITs" on page 48](#).



How to Discover CiscoWorks LMS

1. Prerequisites - Set up protocol credentials

Add credentials for the Sybase database instances used by CiscoWorks LMS (**RMENGDB** and **ANIDB**) to the Generic DB (SQL) protocol.

For credential information, see "Supported Protocols" in the *HP Universal CMDB Discovery and Integration Content Guide - Supported Content* document.

2. Run the discovery

- a. Discover IP addresses of the Sybase databases **RMENGDB** and **ANIDB** used by CiscoWorks LMS.
- b. Run the **CiscoWorks LMS Database Ports** job to discover the TCP ports at which the Sybase databases used by CiscoWorks LMS are listening.
- c. Create a new integration point, and use the **CiscoWorks NetDevices** adapter to discover network device information from CiscoWorks.
- d. Create a new integration point, and use the **CiscoWorks Layer 2** adapter to discover node (server) information from CiscoWorks.

Steps 2a and 2b are optional (although highly recommended - see note below) since CiscoWorks adapters are available in the Integration Studio, allowing manual creation of the necessary **IpAddress**, **Node** and **IpServiceEndpoint** CIs.

Note: The CiscoWorks Layer 2 job requires additional data about CIs created by the **CiscoWorks NetDevices** adapter and already in UCMDB. This information is provided by the Input Query, which contains CI types (**NetDevice** and **PhysicalPort**) that provide this data in addition to CI types required to identify the integration target (**IpServiceEndpoint**).

For this reason, it is highly recommended to execute steps 2a and 2b. If steps 2a and 2b are not executed, creating the integration target CIs (while creating an integration point using the **CiscoWorks Layer 2** adapter) requires the creation of **Node** and **PhysicalPort** CIs.

CiscoWorks LMS Database Ports Job

Adapter

This job uses the TCP Ports Discovery adapter

Trigger Query

- **Trigger CI:** IpAddress
- **Trigger Query:**



- **CI attribute conditions:**

CI	Attribute Value
IpAddress	NOT IP Probe Name is null

Parameters

Ports: 43443, 43455

Network Devices from CiscoWorks LMS Job

Adapter

This job uses the CiscoWorks_NetDevices adapter

Trigger Query

- **Trigger CI:** IpServiceEndpoint
- **Trigger Query:** CiscoWorks RME DB Port



- **CI attribute conditions:**


CI	Attribute Value
IpServiceEndPoint	NetworkPortNumber Equal 43455

Layer 2 Topology from CiscoWorks LMS Job Adapter

This job uses the CiscoWorks_Layer2 adapter

Trigger Query

- **Trigger CI:** IpServiceEndpoint
- **Trigger Query:** CiscoWorks Campus DB Port



- **CI attribute conditions:**

CI	Attribute Value
IpServiceEndPoint	NetworkPortNumber Equal 43443
IpAddress	NOT IP Probe Name Is null
NetDevice	NOT Name Is null
PhysicalPort	NOT Name Is null AND NOT Port VLAN Is null AND NOT PortIndex Is null AND NOT Container Is null

Discovery Flow

Add IP addresses of the Sybase databases **RMENGDB** and **ANIDB** used by CiscoWorks LMS to a discovery probe range:

1. Range IPs by ICMP
2. CiscoWorks LMS Database Ports
3. CiscoWorks NetDevices
4. CiscoWorks Layer 2

CiscoWorks NetDevices Adapter

This section contains details about the adapter.

Input CIT

IpServiceEndpoint: the TCP port at which the **RMENGDB** Sybase instance is listening. (The default is 43455.)

Used Scripts

- ciscoworks_utils.py
- CiscoWorks_NetDevices.py

Discovered CITs

- Composition
- Containment
- HardwareBoard

- Interface
- IPAddress
- IpSubnet
- Layer2Connection
- Membership
- Node
- PhysicalPort
- Realization
- Vlan

Parameters

Parameter	Description
allowDnsLookup	If an IP address is not available for a node, setting this to true enables DNS lookup using the node name. Default: false.
ignoreNodesWithoutIP	If set to false , CIs for nodes without IPs are created with the storage system's internal ID as host_key . Note: this may result in duplicate nodes. Default: true.
rmeDbName	The name of the CiscoWorks Resource Manager Essentials database in Sybase. Default: rmengdb.
queryChunkSize	The number of network devices to query at a time. Default: 250.

CiscoWorks Layer 2 Adapter


This section contains details about the adapter.

Input CIT

IpServiceEndpoint: the TCP port at which the **ANIDB** Sybase instance is listening. (The default is 43443.)

Input Query

CiscoWorks LMS Campus DB with PhysicalPorts



Node Conditions

Node Name	Condition
SOURCE (IpServiceEndPoint)	NetworkPortNumber Equal 43443
IpAddress	NOT IP Probe Name Is null
NetDevice	NOT Name Is null
PhysicalPort	NOT Name Is null AND NOT Port VLAN Is null AND NOT PortIndex Is null AND NOT Container Is null

Triggered CI Data

Name	Value
db_port	\${SOURCE.network_port_number}
ip_address	\${IpAddress.ip_address}
netdevice_cmdbid	\${NetDevice.global_id}
netdevice_name	\${NetDevice.name}
port_cmdbid	\${PhysicalPort.global_id}
port_container_cmdbid	\${PhysicalPort.root_container}

Name	Value
port_index	\${PhysicalPort.port_index}
port_name	\${PhysicalPort.name}
port_vlan	\${PhysicalPort.port_vlan}

Used Scripts

- ciscoworks_utils.py
- CiscoWorks_Layer2.py

Discovered CITs

- Composition
- Containment
- HardwareBoard
- Interface
- IpAddress
- IpSubnet
- Layer2Connection
- Membership
- Node
- PhysicalPort
- Realization
- Vlan

Parameters

Parameter	Description
allowDnsLookup	If an IP address is not available for a node, setting this to true enables DNS lookup using the node name. Default: false.
ignoreNodesWithoutIP	If set to false , CIs for nodes without IPs are created with the storage system's internal ID as host_key . Note: this may result in duplicate nodes. Default: true.
campusDbName	The name of the CiscoWorks Campus database in Sybase. Default: anidb.
queryChunkSize	The number of nodes to query at a time. Default: 1,000.

Discovery Mechanism

The adapters in this package connect to the Sybase databases used by CiscoWorks LMS using JDBC, and run SQL queries to retrieve information. The Sybase database instances are used as part of the trigger for jobs in this package. This allows the jobs to be included in UCMDb's spiral discovery schedule.

The package includes two adapters:

- **CiscoWorks NetDevices**, and
- **CiscoWorks Layer 2**.

CiscoWorks NetDevices triggers off the CiscoWorks Resource Manager Essentials database, and retrieves network devices, VLAN and layer two infrastructure from it.

CiscoWorks Layer 2 triggers off the CiscoWorks Campus Manager database, and retrieves nodes (servers). It associates them with VLANs and layer two infrastructure retrieved by **CiscoWorks NetDevices**.

Database queries executed by this package on the CiscoWorks databases are as follows:

Note: The following query is used by the **CiscoWorks NetDevices** and **CiscoWorks Layer 2** adapters on the **RMENGDB** and **ANIDB** database instances

Get the database name to verify that queries are run on the correct database:

```
SELECT db_name()
```

Note: The following queries are used by the **CiscoWorks NetDevices** adapter on the **RMENGDB** database instance

Get a count of the number of network devices in the database (This is required to determine the number of chunks to query. For details on chunking, see ["Parameters" on page 49.](#))

```
SELECT COUNT(1) FROM lmsdatagrpf.NETWORK_DEVICES
```

Get information on network devices managed by CiscoWorks LMS

```
SELECT netdevices.Device_Id,  
deviceState.NetworkElementID, netdevices.Device_Display_Name,  
netdevices.Host_Name, netdevices.Device_Category,  
netdevices.Device_Model, netdevices.Management_IPAddress,  
deviceState.Global_State  
FROM lmsdatagrpf.NETWORK_DEVICES netdevices JOIN dba.DM_Dev_State  
deviceState ON netdevices.Device_Id=deviceState.DCR_ID
```

Get additional details on each network device.

```
SELECT * FROM dba.PhysicalTypeEnum  
  
SELECT ne.ElementName, ne.ReportedHostName, ne.DNSDomainName, ne.Description, ne  
.PrimaryOwnerContact, ne.ElementLocation, os.OSName, os.Version, os.ROMVersion,  
pe.Manufacturer, pe.SerialNumber  
FROM dba.OperatingSystem os, dba.PhysicalElement pe, dba.networkelement ne  
WHERE os.NetworkElementID=<networkDeviceID> AND ne.NetworkElementID=<networkDevi  
ceID> AND pe.NetworkElementID=<networkDeviceID> AND LOWER(pe.PhysicalType)=<phys  
icalType> AND pe.PhysicalElementId IN (1, 2)
```

Get port and VLAN information for each network device.

```
SELECT phyPort.PhysicalPortID, phyPort.SNMPPhysicalIndex, phyPort.ParentRelPos,  
port.PORT_NAME, port.PORT_DESC, port.PORT_DUPLEX_MODE, port.PORT_TYPE, port.POR  
T_SPEED, port.VLAN_NAME, port.VLANID, interface.EndpointID, interface.Descriptio  
n, interface.Alias, interface.MediaAccessAddress  
FROM lmsdatagrpf.PORT_INVENTORY port JOIN dba.PhysicalPort phyPort ON port.PORT_N  
AME=phyPort.PortName JOIN dba.IFEntryEndpoint interface ON port.PORT_NAME=interf  
ace.EndpointName  
WHERE phyPort.NetworkElementID=<networkDeviceID> AND interface.NetworkElementID=  
<networkDeviceID> AND port.DEVICE_ID=<networkDeviceID> AND phyPort.PortName=port  
.PORT_NAME
```

Get IP Address details for each network device.

```
SELECT IPAddress, SubnetMask FROM dba.IPProtocolEndPoint WHERE NetworkElementId=  
<networkDeviceID>
```

Get information on modules in each network device.

```
SELECT MODULE_NAME, SW_VERSION, FW_VERSION, SLOT_NUMBER FROM lmsdatagrpf.MODULE_INVENTORY WHERE DEVICE_ID=<networkDeviceID>
```

Note: The following queries are used by the **CiscoWorks Layer 2** adapter on the **ANIDB** database instance.

Get a count of the number of nodes (servers) in the database (This is required to determine if chunking is required. See ["Parameters" on page 52.](#))

```
SELECT COUNT(1) FROM lmsdatagrpf.End_Hosts
```

Get information on nodes managed by or known to CiscoWorks LMS.

```
SELECT HostName, DeviceName, Device, MACAddress, IPAddress, SubnetMask, Port, PortName, VLAN, VlanId, associatedRouters FROM lmsdatagrpf.End_Hosts WHERE HostName IS NOT NULL AND NOT HostName='' AND IPAddress IS NOT NULL AND NOT IPAddress=''
```

Troubleshooting and Limitations

If there is a database connection failure, copy the Sybase JDBC driver (**jconnectnn.jar** or similar JAR file) from the Sybase system to the

<hp>\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\db\sybase directory on the DFM probe file system.

If the database connection failure occurs after the driver is copied, it may be necessary to change the driver classes in **globalSettings.xml** from:

<Sybase>com.sybase.jdbc.SybDriver</Sybase>

to

<Sybase>com.sybase.jdbc3.SybDriver</Sybase>

Chapter 5: EMC Control Center (ECC) Integration

This chapter includes:

Overview	56
Supported Versions	56
Topology	56
How to Run the ECC/UCMDB Integration Job	57
ECC Integration Job	59
Views	62
Impact Analysis Rules	67
Reports	69

Overview

Integration between ECC and DFM involves synchronizing devices, topology, and hierarchy of storage infrastructure in the UCMDB database (CMDB). This enables Change Management and Impact Analysis across all business services mapped in UCMDB from a storage point of view.

DFM initiates discovery on the ECC database. Synchronized Configuration Items (CIs) include Storage Arrays, Fibre Channel Switches, Hosts (Servers), Storage Fabrics, Storage Zones, Logical Volumes, Host Bus Adapters, Storage Controllers, and Fibre Channel Ports. The integration also synchronizes physical relationships between hardware, and logical relationships between Logical Volumes and hardware devices, to enable end-to-end mapping of the storage infrastructure.

You integrate ECC with UCMDB using Data Flow Management.


The integration includes the **ECC_Integration.zip** package, which contains the trigger TQL, DFM script, adapter, and job for ECC integration.

Supported Versions

Target Platform	OS Platform	DFM Protocol	ECC Version
EMC Control Center	All	Generic DB (SQL) over JDBC, SSL optional	6.0 and 6.1

Topology

The following diagram illustrates the storage topology and shows the relationships between logical volumes on a storage array and those on servers:



How to Run the ECC/UCMDB Integration Job

This task includes the steps to run the ECC/UCMDB integration job.

Note: For details on running an integration job, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

In the Integration Studio, create a new integration point.

1. Provide a name and description for the integration point.
2. Under **Integration Properties > Adapter**, select the **EMC Control Center** adapter.
3. Under **Adapter Properties > Data Flow Probe**, select the **Data Flow Probe**.
4. Under **Adapter Properties > Trigger CI instance** select:
 - a. **Select Existing CI** (if you have a valid, existing CI). The **Select Existing CI** pane appears. Select the CI or
 - b. **Create New CI** (if you need to create a new CI). The **Topology CI Creation Wizard** appears. Complete the creation of the CI using the Wizard.

Note: For details on the Topology CI Creation Wizard, see "Topology CI Creation Wizard" in the *HP Universal CMDB Data Flow Management Guide*.

5. Verify the credentials for the chosen CI instance. Right-click on **Trigger CI instance** and select **Actions > Edit Credentials Information**.

Note: For details about the credentials, see ["How to Run the ECC/UCMDB Integration Job" on the previous page](#)

6. Save the integration point.
7. Run the job.

Tip: You can include the ECC job in the DFM schedule. For details, see "New Integration Job/Edit Integration Job Dialog Box" in the *HP Universal CMDB Data Flow Management Guide*.

To connect to the ECC Oracle database with SSL communication, see ["How to Run the ECC/UCMDB Integration Job" on the previous page](#).

ECC Integration Job

This section includes:

- ["ECC Integration Mechanism" below](#)
- ["Trigger Query" on the next page](#)
- ["Adapter" on page 61](#)
- ["Discovered CITs and Relationships" on page 62](#)

ECC Integration Mechanism

The following workflow explains how the **ECC Integration by SQL** job discovers the storage topology of ECC. The job:

1. Connects to the ECC Oracle database instance using credentials from the Generic DB Protocol (SQL). For details, see ["How to Run the ECC/UCMDB Integration Job" on page 57](#).

2. Queries for fibre channel switches and ports on each switch and creates **Fibre Channel Switch** CIs:

```
SELECT switch.st_id, switch.st_sn, switch.st_alias, switch.st_model, switch.st_version, switch.st_vendor, switch.sw_managementurl, switch.sw_domain, switch.sw_portcount, switch.sw_portcount_free FROM stssys.sts_switch_list switch WHERE LOWER(switch.sw_principal) = 'true'
```

3. Queries for fibre channel adapters and ports on each Fibre Channel Switch and creates **Fibre Channel HBA** and **Fibre Channel Port** CIs:

```
SELECT port.port_id, port.port_number, port.port_type, port.adport_alias, port.port_wwn, port.port_status, port.conn_port_wwn FROM stssys.sts_switch_port port WHERE port.st_id = switch.st_id from above query
```

4. Queries for storage arrays and creates **Storage Array** CIs:

```
SELECT array.st_id, array.st_sn, array.st_alias, array.st_type, array.st_model, array.st_vendor, array.st_microcode, array.sy_microcode_patch, array.sy_microcode_patchdate FROM stssys.sts_array_list array
```

5. Queries for Fibre Channel ports, Fibre Channel host bus adapters (HBA), and logical volumes on each storage array, and creates **Fibre Channel Port**, **Fibre Channel Port HBA**, and **Logical Volume** CIs:

```
SELECT port.port_id, port.port_number, port.port_type, port.adport_alias, port.port_wwn, port.port_status FROM stssys.sts_array_port port WHERE port.st_id = array.st_id from above query  
SELECT hba.port_id, hba.ad_id, hba.ad_name FROM stssys.sts_array_port hba
```

```
WHERE hba.st_id = array.st_id from above query
SELECT logicalVolume.sd_id, logicalVolume.sd_name, logicalVolume.sd_alias, logicalVolume.sd_size, logicalVolume.sd_type FROM stssys.sts_array_device logicalVolume WHERE logicalVolume.st_id = array.st_id from above query
```

6. Queries for hosts/servers and creates appropriate **Computer**, **Windows**, or **Unix** CIs. Results of this query are used to create host resource CIs, such as **CPU**, if this information is available:

```
SELECT host.host_id, host.host_name, host.host_alias, host.host_domain, host.host_model, host.host_ip, host.host_vendorname, host.host_cpucount, host.host_installedmemory, host.host_os, host.host_osversion, host.host_oslevel, host.host_osclass FROM stssys.sts_host_list host
```

7. Queries for Fibre Channel ports, Fibre Channel host bus adapters (HBA), and logical volumes on each host/server and creates **Fibre Channel Port**, **Fibre Channel Port HBA**, and **Logical Volume** CIs:

```
SELECT port.port_id, port.port_number, port.adport_alias, port.port_wwn FROM stssys.sts_host_hba port WHERE port.host_id = host.host_id from above query
SELECT hba.ad_id, hba.ad_name, hba.fibread_nodewwn, hba.ad_vendor, hba.ad_revision, hba.ad_model, hba.port_id, hba.ad_driver_rev FROM stssys.sts_host_hba hba WHERE hba.host_id = host.host_id from above query
SELECT logicalVolume.hd_id, logicalVolume.hd_name, logicalVolume.hd_type, logicalVolume.hd_total FROM stssys.sts_host_device logicalVolume WHERE logicalVolume.hd_id IS NOT NULL AND logicalVolume.arrayjbod_type = 'Array' AND logicalVolume.host_id = host.host_id from above query
```

8. Queries for logical volume mapping between logical volumes on hosts/servers and logical volumes on storage arrays, and adds **Dependency** relationships between hosts/servers and storage arrays:

```
SELECT sd_id FROM stssys.sts_host_shareddevice WHERE hd_id = logicalvolume.hd_id from above query
```

9. Queries for paths between hosts/servers and storage arrays and adds **Fibre Channel Connect** relationships between respective hosts/servers, switches, and storage arrays:

```
SELECT port.port_wwn, port.conn_port_wwn FROM stssys.sts_array_port_connection port WHERE port.port_wwn IS NOT NULL AND port.conn_port_wwn IS NOT NULL
SELECT port.port_wwn, port.conn_port_wwn FROM stssys.sts_switch_port port WHERE port.port_wwn IS NOT NULL AND port.conn_port_wwn IS NOT NULL
```

Trigger Query

Trigger CI: ECC Oracle database

Adapter

The following table gives details of the adapter parameters.

Parameter	Description
allowDNSLookup	<p>If a node in the ECC database does not have an IP address but has a DNS name, it is possible to resolve the IP address by the DNS name.</p> <ul style="list-style-type: none">• True: If a node does not have an IP address, an attempt is made to resolve the IP address by DNS name (if a DNS name is available). <p>Default: False</p>
ignoreNodesWithoutIP	<p>Defines whether or not nodes in ECC without IP addresses should be pulled into UCMDB.</p> <ul style="list-style-type: none">• True. Nodes without IPs are ignored.• False. A Node CI is created with an ECC ID as the node key attribute. <div><p>Note: Setting this parameter to False may result in duplicate CIs in the CMDB.</p></div> <p>Default: True</p>

Discovered CITs and Relationships

- CPU
- Containment
- Composition (link)
- Dependency (link)
- Fibre Channel Connect (link)
- Fibre Channel HBA
- Fibre Channel Port
- Fibre Channel Switch
- Node
- IpAddress
- Logical Volume
- Membership (link)
- Storage Array
- Storage Processor
- Unix
- Windows

Views

The **Storage_Basic** package contains views that display common storage topologies. These are basic views that can be customized to suit the integrated ECC applications.

To access the Storage_Basic package, go to **Administration > Package Manager**. For details, see "Package Manager" in the *HP Universal CMDB Administration Guide*.

This section includes:


- ["Storage Array Details" on the next page](#)
- ["FC Switch Details" on page 64](#)
- ["Host Storage Details" on page 65](#)

- ["SAN Topology" on page 66](#)
- ["Storage Topology" on page 66](#)

Storage Array Details


This view shows a Storage Array and its components including Logical Volumes, HBAs, Storage Processors, and Fibre Channel Ports. The view shows each component under its container Storage Array and groups Logical Volumes by CI Type.

Storage Array does not require all components in this view to be functional. Composition links stemming from the Storage Array have a cardinality of zero-to-many. The view may show Storage Arrays even when there are no Logical Volumes or Storage Processors.



FC Switch Details


This view shows a Fibre Channel Switch and all connected Fibre Channel Ports.



Note: Although shown in the preceding graphic, the ECC job does not discover Storage Fabrics. The view represented by this query is populated without Storage Fabrics.


Host Storage Details

This view shows only Hosts that contain a Fibre Channel HBA or a Logical Volume. This keeps the view storage-specific and prevents hosts discovered by other DFM jobs from being included in the view.




SAN Topology

This view maps physical connections between Storage Arrays, Fibre Channel Switches, and Hosts. The view shows Fibre Channel Ports below their containers. The view groups the Fibre Channel Connect relationship CIT to prevent multiple relationships between the same nodes from appearing in the top layer.



Storage Topology

This view maps logical dependencies between Logical Volumes on Hosts and Logical Volumes on Storage Arrays. There is no folding in this view.



Impact Analysis Rules

The **Storage_Basic** package contains basic impact analysis rules to enable impact analysis and root cause analysis in UCMDB. These impact analysis rules are templates for more complex rules that you can define based on business needs.

All impact analysis rules fully propagate both Change and Operation events. For details on impact analysis, see "Impact Analysis Manager Page" and "Impact Analysis Manager Overview" in the *HP Universal CMDB Modeling Guide*.

To access the Storage_Basic package: **Administration > Package Manager**. For details, see "Package Manager" in the *HP Universal CMDB Administration Guide*.


Note: Impact analysis events are not propagated to Fibre Channel Ports for performance reasons.

This section includes:

- ["Storage Array Devices to Storage Array" below](#)
- ["Host Devices to Host" on the next page](#)
- ["Logical Volume to Logical Volume" on the next page](#)
- ["FC Switch Devices to FC Switch" on the next page](#)
- ["FC Port to FC Port" on page 69](#)


Storage Array Devices to Storage Array

This impact analysis rule propagates events between Logical Volumes, Storage Processors, Fibre Channel HBAs, and Storage Arrays.




Host Devices to Host

This impact analysis rule propagates events between Fibre Channel HBAs and Hosts, and Logical Volumes on the Host.




Logical Volume to Logical Volume

This impact analysis rule propagates events on a Logical Volume contained in a Storage Array to the dependent Logical Volume on the Host.



FC Switch Devices to FC Switch


This impact analysis rule propagates events from a Fibre Channel Port to and from a Switch. The event is also propagated to the associated Storage Fabric.



Note: Although shown in the preceding graphic, the ECC job does not discover Storage Fabrics. The rule represented by this query is used without Storage Fabrics.

FC Port to FC Port

This rule propagates events on a Fibre Channel Port to another connected Channel Port.



Example Scenario of HBA Crashing on a Storage Array

- The event propagates from the HBA to the Storage Array and the Logical Volumes on the Array because of the Storage Devices to Storage Array rule.
- The impact analysis event on the Logical Volume then propagates to other dependent Logical Volumes through the Logical Volume to Logical Volume rule.
- Hosts using those dependent Logical volumes see the event next because of the Host Devices to Host rule.
- Depending on business needs, you define impact analysis rules to propagate events from these hosts to applications, business services, lines of business, and so on. This enables end-to-end mapping and impact analysis using UCMDB.

Reports

The **Storage_Basic** package contains basic reports that can be customized to suit the integrated ECC applications.

In addition to the system reports, Change Monitoring and Asset Data parameters are set on each CIT in this package, to enable Change and Asset Reports in UCMDB.


To access the Storage_Basic package: **Administration > Package Manager**. For details, see "Package Manager" in the *HP Universal CMDB Administration Guide*.

This section includes:

- ["Storage Array Configuration" on the next page](#)
- ["Host Configuration" on page 71](#)
- ["Storage Array Dependency" on page 71](#)
- ["Host Storage Dependency" on page 72](#)


Storage Array Configuration

This report shows detailed information on Storage Arrays and its sub-components including Fibre Channel Ports, Fibre Channel Arrays, and Storage Processors. The report lists Storage Arrays with sub-components as children of the Array.




Host Configuration

This report shows detailed information on hosts that contain one or more Fibre Channel HBAs, Fibre Channel Ports, or Logical volumes. The report lists hosts with sub-components as children of the host.



Storage Array Dependency


This report maps dependencies on a Storage Array. The report also displays information on switches connected to it.



Note: Although shown in the preceding graphic, the ECC job does not discover Storage Fabrics. The report represented by this query is populated without Storage Fabrics.

Host Storage Dependency

This report shows detailed information on storage infrastructure dependencies of a Host. The report lists hosts and dependent components.



Note: Although shown in the preceding graphic, the ECC job does not discover Storage Fabrics. The report represented by this query is populated without Storage Fabrics.

Chapter 6: IDS Scheer ARIS Integration

This chapter includes:

- Overview 74
- Supported Versions 74
- Topology 74
- How to Run the ARIS Integration Job 75
- Import CIs from ARIS Job 81

Overview

UCMDB integration with IDS Scheer ARIS IT Architect (ARIS) involves synchronizing business services/processes and Enterprise Architecture (EA) information from ARIS to the UCMDB database. This enables end-to-end Change Management and Impact Analysis from the IT infrastructure (at the data center level) to the business service/process level.

The integration involves a UCMDB initiated pull of information from an XML export generated by ARIS. Synchronized configuration items (CIs) include Business Service, Business Process, Business Process Step, Ownership information and Business Application (software). The integration requires manual reconciliation of business application instances in UCMDB.

ARIS_Integration.zip, contains the views, scripts, adapters, and jobs for the IDS Scheer ARIS Integration.


Supported Versions

This integration supports ARIS IT Architect version 7.1.

Topology

The following image is a sample topology showing relationships between the IT infrastructure (data center layer) and Business Processes/Services.

Note: For a list of discovered CITs, see ["Discovered CITs" on page 81](#).



How to Run the ARIS Integration Job

This task includes the steps to run the ARIS integration job, to integrate the IDS Scheer ARIS IT Architect CIs into UCMDB.

This task includes the following steps:

- ["Export the ARIS model to an XML file" below](#)
- ["Set up the ARIS-UCMDB mapping" below](#)
- ["Run the job" on page 80](#)

1. Export the ARIS model to an XML file

This integration solution uses an XML output file generated by ARIS. It is recommended to export the ARIS model to a minimal XML file for use by the UCMDB integration job.

When exporting the data:

- The output XML file should NOT be compressed.
- The language of the output file must be the same as the language used for UCMDB.
- Configure settings as follows:
 - Assignments: No assignments
 - Connections: n connections, with a connection level of 1
 - Select to perform a minimum export
 - Options to export users and groups and group structures should NOT be selected.

Note: Save the exported file to a location accessible to the Data Flow Probe.

For more details on exporting XML files in ARIS, contact your IDS Scheer support representative or ARIS IT Architect documentation.

2. Set up the ARIS-UCMDB mapping

Data flow is initiated by UCMDB reading the XML file generated by ARIS. The integration job reads the data in this file and creates CIs.

A user configurable mapping file (also in XML format) may be used to customize mapping of:

- ARIS Object Types to UCMDB CI types
- ARIS links to UCMDB relationships

This mapping XML file, **ARIS_To_UCMDB.xml**, is located in the following folder:

```
<UCMDB installation>\UCMDB\DataFlowProbe\runtime\ probeManager\discoveryResources\TQLExport\ARIS\data
```

To set up the ARIS Object Type - UCMDB CI Type mapping:

Note: These mapping instructions are followed by an illustrated example.

- a. For each ARIS object type that you want to map, in the exported ARIS XML file (the **source XML**) locate the relevant **ObjDef** tag, and note the **TypeNum** and **AttrDef.Type** values.
- b. In the mapping file, **ARIS_To_UCMDB.xml**, locate the **<targetcis>** section and enter these values into the **source_CI_type** **namesource_attribute** attributes respectively.


Example:

In the following image of the source XML file, the object, **ObjDef.4hzv--y----p--**, has the following attribute values:

- TypeNum = **OT_IS_FUNC**
- AttrDef.Type = **AT_NAME**



These values are entered in the mapping file's **source_CI_type** name and **source_attribute** attributes, as illustrated below:



Note: The section marked as **Must be present for all CI Types** must exist for ALL CI type mappings defined in the mapping file. This section populates the unique object ID used by ARIS in the "data_externalid" attribute of the UCMDDB CI type.

To set up the ARIS Link - UCMDDB Relationship mapping:


Note: These mapping instructions are followed by an illustrated example.

- c. For each ARIS link that you want to map, note the following values in the source XML file:
 - Locate the relevant **CxnDef** tag and note the **CxnDef.Type** attribute.
 - Locate the CxnDef tag's parent, **ObjDef**. Note the **TypeNum** value under this ObjDef.
 - Under CxnDef, note the **ToObjDef.IDRef** attribute, and search for an ObjDef tag with the identical value. Then, under this ObjDef, note the **TypeNum** attribute.
- d. In the mapping file, **ARIS_To_UCMDDB.xml**, locate the **<targetrelations>** section and enter the source link's values as follows:
 - For **source_link_type**, enter the CxnDef.Type attribute
 - For **source_ci_type_end1**, enter the TypeNum value of the CxnDef tag's parent.
 - For **source_ci_type_end2**, enter the TypeNum value of the ObjDef that is equivalent to the ToObjDef.IDRef

Example:

In the following image of the source XML file, the link,
CxnDefn CxnDef.ID=CxnDef.mpb---1g---q--, has the following attribute values:

- CxnDef.Type = **CT_CAN_SUPP_1**
- CxnDef's parent's **TypeName** attribute = **OT_APPL_SYS_TYPE**
- ToObjDef.IdRef = **ObjDef.4hzv--y----p--**. The equivalent ObjDef, **ObjDef.4hzv--y----p--**, was found in line 1112, and its **TypeName** attribute is **OT_IS_FUNC**.



These values are entered in the mapping file's <link> tag, in the **source_link_type**, **source_ci_type_end1**, and **source_ci_type_end2** attributes respectively, as illustrated below:

```

34  <target_attribute name="name" datatype="StrProp
35  <map type="direct" source_attribute="AT_NAM
36  </target_attribute>
37  </target_ci_type>
38  </source_ci_type>
39  </targetcis>
40
41  <targetrelations>
42  <!-- ARIS link --> UCMDB relationship -->
43  <link source_link_type="CT_CAN_SUPP_1"
44  <target_link_type="usage"
45  <nameSpace=""
46  <mode="update_else_insert"
47  <source_ci_type_end1="OT_APPL_SYS_TYPE"
48  <source_ci_type_end2="OT_IS_FUNC"
49  <query="">
50  <apioutputseq>4</apioutputseq>
51  <target_ci_type_end1 name="business_application"/>
52  <target_ci_type_end2 name="business_function"/>
53  <targetprimaryKey>
54  <pkey>name</pkey>
55  </targetprimaryKey>
56  </link>
57  </targetrelations>
58
59  </integration>

```

3. Run the job

In the Integration Studio, create a new integration point.

- a. Provide a name and description for the integration point.
- b. Under **Integration Properties > Adapter**, select the **Software AG ARIS** adapter.
- c. Fill in the value for **ARIS_XML_file**. Set the value as the path to the XML file containing the exported ARIS data. See ["Export the ARIS model to an XML file" on page 75](#).
- d. Copy the DTD file, **ARIS-Export.dtd** from **<ARIS server>\Program Files\ARIS7.1\aml** to the directory where you saved the exported ARIS XML.
- e. Under **Adapter Properties > Data Flow Probe**, select the Data Flow Probe.
- f. Under **Adapter Properties > Trigger CI instance** select:
 - o **Select Existing CI** (if you have a valid, existing CI). The **Select Existing CI** pane appears.
 - o **Create New CI** (if you need to create a new CI). The **Topology CI Creation Wizard** appears. Complete the creation of the CI using the Wizard.

Note: For details on the Topology CI Creation Wizard, see "Topology CI Creation Wizard" in the *HP Universal CMDB Data Flow Management Guide*.


- g. Save the integration point.
- h. Run the job.

Note: For details on running an integration job, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

Import CIs from ARIS Job

Trigger Query

- Trigger CI: Probe
- Trigger query:



Adapter

- Input query: There is no input query for this job.

Discovered CITs

The UCMDB-ARIS integration discovers the following CITs:

- BusinessApplication
- BusinessFunction
- BusinessService
- Containment
- Node
- Organization

- Ownership
- Person

Note: To view the topology, see ["Topology" on page 74](#).

Chapter 7: Importing Data from External Sources

This chapter includes:

- Overview 84
- Comma Separated Value (CSV) Files 84
 - CSV Files with Column Titles in First Row 85
- Databases 85
- Properties Files 85
- How to Import CSV Data from an External Source – Scenario 86
- How to Convert Strings to Numbers 91
 - Custom Converters 92
- External_source_import Package 92
- Import from CSV File Job 93
- Import from Database Job 96
- Import from Properties File Job 101
- External Source Mapping Files 102
- Troubleshooting and Limitations 103

Overview

Your data is probably stored in several formats, for example, in spreadsheets, databases, XML documents, properties files, and so on. You can import this information into HP Universal CMDB and use the functionality to model the data and work with it. External data are mapped to CIs in the CMDB.

The following external data sources are currently supported:

- ["Comma Separated Value \(CSV\) Files" below](#)
- ["Databases" on the next page](#)
- ["Properties Files" on the next page](#)


Comma Separated Value (CSV) Files

A *.csv file has a format that stores tabular data. Each row in a CSV file represents a set of values delimited with a particular delimiter. All rows are homogeneous, that is, each row has the same number of values. Values from all rows with the same index create a column. Values in a single column represent the same type of data. Therefore a CSV file represents a table of data (with rows and columns).

The default delimiter for CSV files is the comma, but any symbol can be used as a CSV delimiter, for example, a horizontal tab.

Note: Microsoft Office Excel includes native support for the CSV format: Excel spreadsheets can be saved to a CSV file and their data can then be imported into UCMDB. CSV files can be opened in an Excel spreadsheet.

Example of a CSV file:



CSV Files with Column Titles in First Row

CSV files often include column headings in the first row. When data is imported from these files, the titles are considered data and a CI is created for this row. To prevent a CI being created, you can define which row DFM should start at when importing data from a CSV file:

1. Select **Adapter Management > Resources pane > Packages > External_source_import > Adapters > Import_CSV**.
2. In the **Adapter Definition** tab, locate the **Adapter Parameters** pane.
3. Locate the **rowToStartIndex** parameter.

By default, the value is **1**, that is, DFM retrieves data from the first row.

4. Replace **1** with the number of the row at which to start retrieving data. For example, to skip the first row and start with the second row, replace **1** with **2**.

Databases

A database is a widely used enterprise approach to storing data. Relational databases consist of tables and relations between these tables. Data is retrieved from a database by running queries against it.


The following databases are supported: Oracle, Microsoft SQL Server, MySQL, and DB2.

Properties Files

A properties file is a file that stores data in the **key = value** format. Each row in a properties file contains one key-to-value association. In code terms, a properties file represents an associative array and each element of this array (key) is associated with a value.

A properties file is commonly used by an application to hold its configuration. If your application uses a configuration file, you can model the application in UCMDB.

Example of a properties file:



How to Import CSV Data from an External Source – Scenario


The UCMDB administrator must model a vehicle catalog that is stored in a CSV file.

This task includes the following steps:

- ["Prerequisites" below](#)
- ["Create a CIT" below](#)
- ["Create a mapping file" on the next page](#)
- ["Run the job" on page 89](#)
- ["Add the discovered Shell CI to the job" on page 90](#)
- ["Result" on page 90](#)

1. Prerequisites

The admin opens the CSV file and analyzes the data:



The file includes the name, model, year of manufacture, and the date when the car was purchased, that is, there are four columns of data:


1	Name	string
2	Model	string
3	Year of manufacture	integer
4	Date of purchase	date

There are three rows to the file, which means that the admin expects three CIs to be created in UCMDB.

2. Create a CIT

The admin creates a CIT.

- a. The admin creates a CIT named **Car** to hold the attributes that are to be mapped to the data in the CSV file (name, model, and so on):



For details, see "Create a CI Type" in the *HP Universal CMDB Modeling Guide*.

- b. During the creation of the CIT, the admin adds these attributes as follows:

Key	Name	Display Name	Type
BODY_ICON	BODY_ICON	BODY_ICON	string
root_candidatefordel...	Candidate For Deleti...	date	date
date_of_purchase	Car Date of Purchase	date	date
model	Car Model	string	string
name	Car Name	string	string
year_of_manufacture	Car Year of Manufa...	integer	integer

For details, see "Attributes Page" in the *HP Universal CMDB Modeling Guide*.

3. Create a mapping file

The admin uses the template, **mapping_template.xml**, to create a mapping file that makes the information available to the **Import_CSV** adapter. The mapping file is located in the following folder: **Adapter Management > Resources pane > External_source_import > Configuration Files**.

- a. For each attribute, the admin adds a **<map>** marker:

```
<?xml version="1.0" encoding="UTF-8"?>
<mappings xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:noName
spaceSchemaLocation=".\\mapping_schema.xsd"
parserClassName="com.hp.ucmdb.discovery.library.
```

```
communication.downloader.cfgfiles.CiMappingConfigFile">
  <ci type="car">
    <map>
      <attribute>name</attribute>
      <column>1</column>
    </map>
    <map>
      <attribute>model</attribute>
      <column>2</column>
    </map>
    <map>
      <attribute>year_of_manufacture</attribute>
      <column>3</column>
    </map>
    <map>
      <attribute>date_of_purchase</attribute>
      <column>4</column>
    </map>
  </ci>
</mappings>
```

- b. The admin then adds information about the attribute type:

```
<?xml version="1.0" encoding="UTF-8"?>
<mappings xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:noName
spaceSchemaLocation=".\\mapping_schema.xsd"
parserClassName="com.hp.ucmdb.discovery.library.
communication.downloader.cfgfiles.CiMappingConfigFile">
  <ci type="">
    <map>
      <attribute>name</attribute>
      <column>1</column>
    </map>
    <map>
      <attribute>model</attribute>
      <column>2</column>
    </map>
    <map>
      <attribute>year_of_manufacture</attribute>
      <column>3</column>
      <converter module="import_converters">stringToInteger</converter>
    </map>
    <map>
      <attribute>date_of_purchase</attribute>
      <column>4</column>
      <converter module="import_converters">stringToDate</converter>
    </map>
  </ci>
</mappings>
```



```
</map>  
</mappings>
```

All conversions between the values in the CSV file and the CI attributes are done by a converter. Several converter types are included in the package by default. For details, see ["How to Convert Strings to Numbers" on page 91](#).

4. Run the job

How you run this job depends on the software version being used.

UCMDB 9.04 (and later), with CP10

In the Integration Studio, create a new integration point.

- Provide a name and description for the integration point.
- Under **Integration Properties > Adapter**, select the **Import from CSV** adapter.
- Under **Adapter Properties > Data Flow Probe**, select the Data Flow Probe.
- Under **Adapter Properties > Trigger CI instance** select:
 - **Select Existing CI** (if you have a valid, existing CI). The **Select Existing CI** pane appears. Select the CI; or
 - **Create New CI** (if you need to create a new CI). The **Topology CI Creation Wizard** appears. Complete the creation of the CI using the Wizard.

Note: For details on the Topology CI Creation Wizard, see "Topology CI Creation Wizard" in the *HP Universal CMDB Data Flow Management Guide*.

- Save the Integration Point.
- Run the job.

Note: For details on running an integration job, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

UCMDB 9.03 (and earlier)

This job uses the **Shell Trigger** CIT to discover the CSV file on a remote machine. The Input CIT is **Shell** and the discovered CIT is declared as **IT Universe**. However, the actual discovered CIs depend on the mapping configuration.

The admin activates the following job: **Import from CSV file**.

For details on activating jobs, see "Discovery Modules Pane" in the *HP Universal CMDB Data Flow Management Guide*.


5. Add the discovered Shell CI to the job

Note: This step only applies if using **UCMDB 9.03** and earlier.

After activation, the admin locates the **Shell** CI (of the machine where the `cars.csv` file is located) and adds it to the job. For details, see "Choose CIs to Add Dialog Box" in the *HP Universal CMDB Data Flow Management Guide*.

6. Result

The admin accesses the CIT Manager and searches for instances of the **Car** CIT. UCMDB finds the three instances of the CIT:



How to Convert Strings to Numbers

Converters enable you to specify the way data should be converted between the external source and a CI's attributes.

A CSV file contains records of type `string`. However, some of the record values need to be handled as numbers. This is done by adding a **converter** element to the **map** element (in `[your mapping file name].xml`):

```
<converter module="import_converters"></converter>
```

The **import_converters.py** file (**Adapter Management > Resources pane > Packages > External_source_import > Scripts**) contains a set of the most commonly needed converters and types:

- `toString`
- `stringToInt`
- `stringToLong`
- `stringToFloat`
- `stringToBoolean`
- `stringToDate`
- `stringToDouble`
- `skipSpaces`
- `binaryIntToBoolean`
- `stringToByteArray`
- `stringToZippedByteArray`

Example of a Converter

A CSV file contains the following row:

Usain, 21, Male

This row must be mapped to the **Person** CIT that includes name (Usain), age (21), and gender (Male) attributes. The age attribute should be of type **integer**. Therefore, the string in the CSV file must be converted to an integer in the CIT to make it compliant with the CIT attribute type, before the Person CIs can retrieve the age values.

This is done by adding a **converter** element to the **map** element:

```
<map>  
  <attribute>age</attribute>
```

```
<column>2</column>  
<converter module="import_converters">stringToInt</converter>  
</map>
```

module="import_converters". This attribute specifies from which module the converter is to be retrieved. A module is a Jython script file that contains a set of converter methods, in this case, `import_converters.py`.

stringToInt. The name of the converter. In the `import_converters.py` file, the method is written as follows:

```
def stringToInt(value):  
    if value is not None:  
        return int(value.strip())  
    else:  
        return 0
```

Custom Converters

You can write your own custom converters: Add a new method to the `import_converters.py` file or create your own script and add a set of converter methods to it. Call the method with the name of the script, for example:

```
<converter module="your_converter_script">[your_converter_method]  
</converter>
```

External_source_import Package

The **External_source_import** package consists of three jobs and three adapters. There is one job and one adapter for each external source (CSV file, properties file, database):

External Source	Job	Adapter
CSV file	Import from CSV file	Import_CSV
Properties file	Import from Properties file	Import_Properties_file
Database	Import from Database	Import_DB

The adapters are located in the **Integration Studio** and are accessed when creating or editing an Integration Point.

Import from CSV File Job

This section includes the following topics:

- ["Job Details" below](#)
- ["Adapter Parameters" below](#)
- ["Delimiters, Quotes, and Escaping Characters" on page 95](#)

Job Details

The job details are as follows:

- Adapter: Import from CSV
- Input CI Type: Shell
- Discovered CIs: ConfigurationItem
- Required Protocols: SSH, NTCMD, Telnet

This job has no Trigger queries associated with it. That is, this job is not triggered automatically (nor are the `Import from Properties` file and the `Import from Database` jobs). After you activate the job, you must manually add input CIs to the job so that it runs against a particular destination. For details, see ["Add the discovered Shell CI to the job" on page 90](#).

Adapter Parameters

The following parameters are included by default:

Parameter	Description
bulkSize	This parameter only works if the parameter flushObjects is true , in which case, when sending discovery results, it sets the size of chunks used to that number of CIs. The default is 2,000 CIs.
ciType	The CIT name. This job creates and reports CIs of this type to UCMDB, based on data in the CSV file. For example, if the CSV file contains records for UNIX hosts, you must set the ciType parameter to unix .
csvFile	The full path to the CSV file on the remote machine. The job uses the Shell CI type as input to reach this path on the remote machine.
delimiter	The delimiter used in the CSV file. The comma (,) delimiter is the default but other delimiters are supported. For details, see "Delimiters" on page 95 .

Parameter	Description
flushObjects	<p>This parameter allows customization of the reporting mechanism.</p> <p>If true, the probe divides the discovery result into chunks, and sends each chunk to the UCMDB Server. This helps prevent out-of-memory issues where a large amount of data is sent. The chunk size can be configured with the bulkSize parameter.</p> <p>If false (the default value), the probe sends the discovery result without dividing it into chunks.</p>
mappingFile	For details of the mapping file, see "External Source Mapping Files" on page 102 .
mappingString	<p>The string containing mapping information used to map the CSV column indexes and attributes to import. You define this mapping in the following format:</p> <ul style="list-style-type: none">• mapping elements should be separated by commas• each mapping element should be specified in a <column number>:<attribute name> format, for example: <p>The string 0:host_key,1:name defines the mapping of two attributes of a host CI, where the host's host_key attribute is taken from the value in the first column (0) and the name attribute is taken from the value in the second column (1).</p>
quoteSymbol	<p>Quoting symbol used in the CSV file.</p> <p>Default symbol: "</p>
rowToStartIndex	For details on setting the row at which DFM starts collecting data, see "CSV Files with Column Titles in First Row" on page 85 .
skipEmptyValues	This flag determines whether to skip empty values. If true , empty column values are not sent.

For details on overriding an adapter parameter, see "Override Adapter Parameters" in the *HP Universal CMDB Developer Reference Guide*.

Mapping Information for the Import from CSV File Job

You can specify mapping information for the **Import from CSV File** job with one of the following methods:

- In an external XML file. You must specify the **mappingFile** parameter. For details, see ["External Source Mapping Files" on page 102](#).

- Directly in a job's **ciType** and **mappingString** parameters, without using an external file.

Note: When using this mapping method, you cannot specify attribute types or converters.

If the **mappingFile** parameter is specified, the job tries to retrieve mapping information from the XML file. If it is not specified, the job uses the mapping information specified in the **ciType** and **mappingString** parameters.

Delimiters, Quotes, and Escaping Characters

- Delimiters

The delimiter divides values in the same row of a CSV file. Supported delimiters are:

- **Single symbol.** Any symbol can be used as a delimiter, for example, the pipe sign (`|`), the letter `O`. Delimiters are case sensitive.
- **ASCII code.** If an integer number is used as the value for a delimiter parameter, this value is treated as ASCII code, and the related symbol is used as the delimiter. For example, `9` is a valid delimiter because `9` is the ASCII code for the horizontal tab.
- **Known character sequence.** A sequence of characters can be used to represent special characters. For example, `\t` represents the horizontal tab.

- Quotation Marks

You can use double or single quotes in values, that is, all values residing between the two quotes are treated as a single value.

- If a delimiter symbol is used in a value, the value must be surrounded with quotation marks. For example, the following row includes a comma inside a value, so the value must be quoted:

```
Morganfield, "25 Hope Road, Kingston", Jamaica
```

- If a quote character is used in a value, the character must be escaped by inserting a backslash before it:

```
McKinley \"Muddy Waters\" Morganfield, \"April 4, 1915\"
```

This row contains two values:

- McKinley "Muddy Waters" Morganfield

- April 4, 1915.

- Escaping Characters

The following characters must always be quoted or escaped:

- Backslash
- Single quote
- Double quote
- Delimiter, that is, the delimiter used in the same CSV file.

Import from Database Job

This job uses a database table or database query as the source of the information, maps the information to CIs, and imports the CIs into UCMDB.

This section includes the following topics:

- ["Job Details" below](#)
- ["Discovery Adapter Parameters" on the next page](#)
- ["Tables and Queries" on the next page](#)
- ["Database, Schema, and Table Names" on page 98](#)
- ["Importing Data with an SQL Query" on page 99](#)
- ["Column Types" on page 99](#)
- ["Importing CIs with Root Container Attribute" on page 100](#)

Job Details

The job details are as follows:

- Adapter: Import from DB
- Input CI Type: Database
- Discovered CIs: ConfigurationItem
- Required Protocol: SQL

This job has no trigger queries associated with it. The job tries to get the Instance name and Port using the attributes **Name** and **Application Listening Port Number** of the **Input Database CI**. If these attributes are empty, it uses the Instance Name and Port number defined in Generic DB Protocol (SQL) credentials.

Discovery Adapter Parameters

The following parameters are included by default:

Parameter	Description
bulkSize	This parameter only works if the parameter flushObjects is true , in which case, when sending discovery results, it sets the size of chunks used to that number of CIs. The default is 2,000 CIs.
ciType	Name of CIT to import.
flushObjects	This parameter allows customization of the reporting mechanism. If true , the probe divides the discovery result into chunks, and sends each chunk to the UCMDB Server. This helps prevent out-of-memory issues where a large amount of data is sent. The chunk size can be configured with the bulkSize parameter. If false (the default value), the probe sends the discovery result without dividing it into chunks.
mappingFile	XML file containing the mapping from column to attribute.
mappingString	The string containing mapping information used to map the Database column names and the attributes to import. You define this mapping in the following format: <ul style="list-style-type: none">• mapping elements should be separated by commas;• each mapping element should be specified in a <column name>:<attribute name> format, Example: A_IP_ADDRESS:ip_address, A_IP_DOMAIN:ip_domain
schemaName	The name of the database schema.
sqlQuery	If a SQL query is specified, mapping is performed against its result. This parameter is ignored if tableName is defined.
tableName	If a table name is specified, mapping is performed against the table's columns.

For details on overriding an adapter parameter, see "Override Adapter Parameters" in *HP Universal CMDB Developer Reference Guide*.

Tables and Queries

The following use cases are supported by the Import from Database job (a single SQL query is performed):

- Import data using the schema name and table name parameters:

Adapter Parameters	
+ ✖ ✎	
Name	
ciType	
mappingFile	
mappingString	
schemaName	ddmi_servers
sqlQuery	
tableName	servers

The SQL query is generated from these parameters.

- Import data specifying an arbitrary SQL query as the source of the data:

Adapter Parameters	
+ ✖ ✎	
Name	
ciType	
mappingFile	
mappingString	
schemaName	
sqlQuery	SELECT servers.* FROM servers LEFT JOIN disks C
tableName	

The SQL query is generated from the defined query. For more details, see ["Importing Data with an SQL Query" on the next page](#).

Database, Schema, and Table Names

SQL naming conventions suggest a usage of a <database.schema.table> syntax for the fully qualified name of a table. Note, however, that each vendor treats the specification in a different way. DFM uses the following notation:

- The **schemaName** parameter specifies the name of a database.
- The **tableName** parameter specifies the name of a table.
- A schema name cannot be specified in a parameter but can be included in a SQL query.

For Oracle, the SQL query is:

```
SELECT * FROM <schemaName.tableName>
```

For Microsoft SQL Server, the SQL query is:

```
SELECT * FROM dbo.tableName
```

Note: The default dbo schema is used for Microsoft SQL Server.

Importing Data with an SQL Query

You can use arbitrarily-complex SQL query expressions, for example, joins, sub-selects and other options, as long as the query is valid and complies with the database usage. Currently, you must use a fully-qualified table name in the query according to the specific database.

Column Types

Types enable you to specify, in the mapping file, the type of column that exists in the external source. For example, a database includes information about column types, and the value of this type needs to be included in the CI's attributes. This is done by adding a **type** element to the **map** element (in `mapping_[your mapping file name].xml`):

```
<column type="int"></column>
```

Supported type attributes are:

- string
- Boolean
- date
- int
- long
- double
- float
- timestamp

Note:

- You use the **type** attribute for database mapping only.
- If the column element does not include a type attribute, the element is mapped as a string.

Example of adding a type attribute

A database column has an integer type and can be either 0 or 1. This integer must be mapped to a Boolean attribute of a CIT in UCMDB. Use the `binaryIntToBoolean` converter, as follows:

```
<map>
  <attribute>cluster_is_active</attribute>
  <column type="int">cluster_is_active</column>
  <converter module="import_converters">binaryIntToBoolean</converter>
</map>
```

type="int". This attribute specifies that the value of `cluster_is_active` should be retrieved as an integer, and that the value passed to the converter method should be an integer.

If the `cluster_is_active` attribute of the CIT is of type integer, the converter is not needed here, and the mapping file should say:

```
<map>
  <attribute>cluster_is_active</attribute>
  <column type="int">cluster_is_active</column>
</map>
```

Importing CIs with Root Container Attribute

The main purpose of the **Import from database** job is importing CIs that do not require a root container attribute. For example: Node, IP address, etc. However, there are many CIs that depend on root CIs (for example: CPUs, SQL servers, etc) that cannot be deployed into UCMDB without the Node on which they are installed. In such cases, it is better to use a different discovery approach. For example, by importing data from Excel, you can import CIs with corresponding relationships (including the composition relationship). You can import such CIs using the **Import from database** job only if all of the following apply:

1. The root CI (for example: Node) was already populated into UCMDB.
2. It is possible to construct an SQL query to select the UCMDB ID of already imported root CIs from an external database.

In such cases, you can map the selected UCMDB ID of the root CI to the root container attribute of the contained CI.

Note: Validation of data (checking if the root CI already exists in UCMDB) is not supported. It is your responsibility to correctly configure the population of the root container attribute.

Import from Properties File Job

This job imports information from a properties file, maps the information to one CI, and imports that CI into UCMDB.

This section includes the following topics:

Job Details

The job details are as follows:

- Adapter: Import from properties file
- Input CI Type: Shell
- Discovered CIs: ConfigurationItem
- Required Protocols: SSH, NTCMD, Telnet

This job has no Trigger queries associated with it.

Discovery Adapter Parameters

The following parameters are included by default:

Parameter	Description
bulkSize	This parameter only works if the parameter flushObjects is true , in which case, when sending discovery results, it sets the size of chunks used to that number of CIs. The default is 2,000 CIs.
ciType	The name of the CIT to import.
flushObjects	This parameter allows customization of the reporting mechanism. If true , the probe divides the discovery result into chunks, and sends each chunk to the UCMDB Server. This helps prevent out-of-memory issues where a large amount of data is sent. The chunk size can be configured with the bulkSize parameter. If false (the default value), the probe sends the discovery result without dividing it into chunks.
mappingFile	For details of the mapping file, see "External Source Mapping Files" on the next page .

Parameter	Description
mappingString	<p>The string containing mapping information used to map the column indexes and attributes to import. You define this mapping in the following format:</p> <ul style="list-style-type: none">• mapping elements should be separated by commas• each mapping element should be specified in the format: <parameter name> :<attribute name> <p>For example, for CIT ip_address:</p> <p>ip_address:ip_address,name:name,ip_address_type:ip_address_type</p>
propertyFile	<p>The full path to the properties file located on a remote machine. The Input CI runs the Shell discovery that is used to access this file on the remote machine</p>

For details on overriding an adapter parameter, see "Override Adapter Parameters" in the *HP Universal CMDB Developer Reference Guide*.

Keys and Values

Keys cannot contain the equals symbol (=).

Each value must be set out in a single line. Use **backslash+n** (\n) to specify a new line. Values can contain anything, including \n for a new line, quotes, tabs, and so on.

Comments in Properties Files

To create a commented line in a properties file, add the pound sign (#) as the first character in a line. The job ignores commented lines.

External Source Mapping Files

The data in the external source is mapped to a CI's attributes in UCMDB by means of a mapping file. The mapping files are located in the **Adapter Management > Resources pane > Packages > External_source_import > Configuration Files** folder:

- **mapping_template.xml**. A template that serves as a source for creating the mapping file.
- **mapping_schema.xsd**. The XML schema used to validate the XML mapping file. The XML mapping file must be compliant with this schema.
- **mapping_doc.xml**. A file that contains Help on creating a mapping file, including all valid elements.

The mapping file describes the mapping only and does not include information about how data should be obtained. In this way, you can use one mapping file across different jobs.

All the adapter files in the **External_source_import** package include a `mappingFile` parameter, for example:

```
<parameter name="mappingFile" type="string" description="Mapping file located in  
"Configuration Files" folder of this package" />
```

name="mappingFile". The value of this parameter is the mapping XML file. The mapping file is always located on the server and is downloaded to the Data Flow Probe machine upon job execution.

Troubleshooting and Limitations

- **Problem:** When CIs imported from a CSV file are displayed in the Statistics Results pane, one more CI than expected is included in the results. This is because the first row of the CSV file contains column headings that are considered as CIs.

Solution: For details on defining from which row DFM should read the CSV file, see ["CSV Files with Column Titles in First Row" on page 85](#).

- **Problem:** When importing large CSV or properties files on the network, there may be time-out issues.

Solution: Make sure the files are not large.

- **Limitation:** When importing data from an external database, and the data includes a null value, it is sent to UCMDB with an attribute value of None.
- **Limitation:** The DFM Probe breaks down the imported data into 20 KB chunks. This can cause identification issues.

Chapter 8: Import from Excel Workbook Discovery

This chapter includes:

Overview	105
Supported Versions	105
Topology	105
How to Import Data from Excel Workbook	105
How to Set Up an Import File in Excel	107
Import from Excel Workbook Job	116
Troubleshooting and Limitations	119

Overview

This chapter describes the usage and functionality of the XLS_Import discovery package developed for importing UCMDB topology from a Microsoft Excel (*.xls, *.xlsx) file.

Supported Versions


This discovery supports

- Microsoft Excel files, versions 97, 2000, XP, and 2003 (*.xls)
- Office Open XML format for Excel 2007 (*.xlsx)

Topology

The following image displays the topology of the Import from Excel discovery.

Note: The topology discovered by the Import from Excel Workbook job relies on import file content, so only root objects are enumerated as discovered CITs. For a list of discovered CITs, see ["Discovered CITs" on page 119](#).



How to Import Data from Excel Workbook

This task describes how to run the Import from Excel discovery. The Import from Excel Workbook job imports data from the Probe's file system (or accessible network share), so no credentials are required.

Note:

- The Import from Excel Sample job is similar to the Import from Excel Workbook job. It differs only by reference to the sample import file.
- This integration is configured to run in remote process.

This task includes the following steps:

1. **Prerequisite- Set up the Import file in Excel**

For details on setting up the import file, see ["How to Set Up an Import File in Excel" on the next page](#).

2. **Prerequisite - Set up permissions**

Give the Data Flow Probe read permissions on the location on the file system where the import files are stored.

3. **Run the discovery**

In the Integration Studio, create a new integration point.

- a. Provide a name and description for the integration point.
- b. Under **Integration Properties > Adapter**, select the **Import topology from Excel Workbook** adapter.
- c. Under **Adapter Properties > Data Flow Probe**, select the Data Flow Probe.
- d. Under **Adapter Properties > Trigger CI instance** select one of the following:
 - **Select Existing CI** (if you have a valid, existing CI). The **Select Existing CI** pane appears. Select the CI and click OK.
 - **Create New CI** (if you need to create a new CI). The **Topology CI Creation Wizard** appears. Create the CI using the Wizard.

Note: For details on the Topology CI Creation Wizard, see "Topology CI Creation Wizard" in the *HP Universal CMDB Data Flow Management Guide*.

- e. Save the Integration Point.
- f. Run the job.

Note: For details on running an integration job, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

How to Set Up an Import File in Excel

This section describes how to define an import file. The following topology is created:

- Two hosts
- Two IPs contained by each host
- Network (the IPs mentioned above are members of the network)
- An application with a corresponding process running on the host

This task includes the following steps:

- ["Prerequisite" below](#)
- ["Add a CI type" below](#)
- ["Create Comment sheets - optional" on the next page](#)
- ["Define CI key attributes " on the next page](#)
- ["Create Comment columns - optional" on page 110](#)
- ["Add CIs with containers" on page 110](#)
- ["Define relationships" on page 112](#)
- ["Add relationship attributes" on page 114](#)
- ["Convert attribute types to UCMDDB attribute types" on page 115](#)

1. Prerequisite

Open a new Excel file and name it **tutorial.xls**.

2. Add a CI type

Double-click the **Sheet1** tab and rename it with the desired CI type. For this tutorial, use the name **node**.


Note:

- Only use the CI type name, not the display name.
- Type names are case sensitive.

3. Create Comment sheets - optional

You can create Comment sheets that will not be imported into UCMDB, but that can be used to describe the data contained in the imported document.

Double-click one of the Sheet tabs and rename it **#Comment sheet**.



Note: Comment sheet names must begin with the # sign.

4. Define CI key attributes

Depending on the CIT, to store a CI in UCMDB, you must specify CI key attributes or attributes that participate in reconciliation rules. The names of the imported attributes can be defined as the column headings.

Our **node** object only has one key attribute - **host_key**.

Key	Display Name	Name
	Host Key	host_key
	Host Model	host_model
	Host Name	host_hostname

To import a node CI into UCMDB, you must set the **host_key** attribute. You may do this by one of the following methods:

- Set **host_key** in the view **<IP address> <Domain>**. (For example: 192.168.100.100 DefaultDomain.) This is enough to import a node CI into UCMDB.
- Set **host_key** as the lowest MAC address of the attached network interface. This is not enough to import a node CI into UCMDB. You must also configure the following attributes:
 - i. Set **host_iscomplete** to **true**.
 - ii. Set values for the node attributes that allow the node to be identified by the reconciliation rule. Note that the node reconciliation rule also allows identification of the nodes linked to this node IP address or network interface CIs. If you prefer to identify nodes by linked CIs, you must ensure the Excel document also has the imported IP/Network interface CIs, and the relationships between node CIs and IP/ network interface CIs.

Note:

- The column headings must be attribute names, not display names.
- Attribute names are case sensitive.

You can show the node name and the operating system.

	A	B	C
1	host_key	name	discovered_os_name

- a. Define two nodes.

	A	B	C
1	host_key	name	discovered_os_name
2	192.168.100.100 MyDomain	SampleHost	Windows XP
3	192.168.100.200 MyDomain	SampleServer	Windows 2008

Note: Each row in the sheet (except the first one) represents a single CI.

- b. Use the same procedure to define IP addresses in a second Excel sheet, for example, **Sheet2**.

	A	B	C
	ip_address	routing_domain	name
	192.168.100.100	MyDomain	192.168.100.100
	192.168.100.101	MyDomain	192.168.100.101
	192.168.100.200	MyDomain	192.168.100.200
	192.168.100.201	MyDomain	192.168.100.201

- c. Use the same procedure to define a network CI in a third Excel sheet, for example, **Sheet3**.

	A	B	C	D	E
1	name	network_netmask	routing_domain	network_netclass	ip_prefix_length
2	192.168.100.0	255.255.255.0	MyDomain	C	1

running_software and process definitions are described in ["Add CIs with containers"](#) on the next page

5. Create Comment columns - optional

If you want to have a **Comment** column with explanations of data, use the **#** sign before the column heading. Any data placed in this column will not be imported into UCMDB.

	A	B	C	D
1	host_key	name	discovered_os_name	#Comment
2	192.168.100.100 MyDomain	SampleHost	Windows XP	PC near the entrance
3	192.168.100.200 MyDomain	SampleServer	Windows 2008	Our server

6. Add CIs with containers

Objects that are contained within other objects cannot exist without them. For example, processes and running software cannot exist without the node they are running on. To show this relationship, a **root_container** attribute is needed. Because the container is in another CI, a reference to it is needed.

Objects can be referenced in one of the following ways:

- **By creating an Excel definition reference to the object.**

The Excel definition referencing style is recommended because only the tab name (CI type name) and row number (the row number of the CI defined on the tab) are needed to identify any imported CI - the presence or absence of any key fields is not necessary, reconciliation rules are defined in UCMDB, and so on.

Typical links appear as **=node!A2**, meaning that the **node** tab on the CI defined at row **2** is being referenced. It does not matter which column you are referencing; only the rows numbers are significant.

Note: Such references cannot be used if the Excel file was created from a CSV file or using some other non-Excel format.

For more information about references, see Microsoft Excel documentation.

- **By setting a composition of the desired object key fields divided by the pipe symbol ('|').**

For example, to reference an IP address, the **ip_address** and **routing_domain** attributes are needed: **192.168.100.100|MyDomain**.

Note:

- The order of the key fields in the definition is important!
- Many objects have no keyed attributes and are identified with reconciliation rules. For this reason, Excel references are preferred.

- **By creating an Excel definition reference to the object.**

The Excel definition referencing style is recommended because only the tab name (CI type name) and row number (the row number of the CI defined on the tab) are needed to identify any imported CI - the presence or absence of any key fields is not necessary, reconciliation rules are defined in UCMDB, and so on.

Typical links appear as **=node!A2**, meaning that the **node** tab on the CI defined at row **2** is being referenced. It does not matter which column you are referencing; only the rows numbers are significant.

Note: Such references cannot be used if the Excel file was created from a CSV file or using some other non-Excel format.

For more information about references, see Microsoft Excel documentation.


- **By setting a composition of the desired object key fields divided by the pipe symbol ('|').**

For example, to reference an IP address, the **ip_address** and **routing_domain** attributes are needed: **192.168.100.100|MyDomain**.

Note:

- The order of the key fields in the definition is important!
- Many objects have no keyed attributes and are identified with reconciliation rules. For this reason, Excel references are preferred.

a. Create a **running_software** using Excel references.



	A	B
1	discovered_product_name	root_container
2	Business app	=node!A2
3		

Note: To define an Excel reference, type an equal sign (=) in a cell, select the desired reference cell, and press ENTER.

- b. Create a **process** using a composite key.

	A	B	C
1	name	process_cmdline	root_container
2	Sample	C:\sample.ddm	192.168.100.100 MyDomain

ip_subnet process running_software #Com

7. Define relationships

To define relationships, create a sheet called **relationships**.

Note: You cannot import relationship CIs.

All links (relationships) in UCMDB are directed. This means each link has a start and end point. Also, links have names that might have some attributes similar to other CIs.

A link definition in an import file looks as follows:

Start object reference -> link name -> End object reference [-> Attributes]

Link attribute definitions are described in ["Add relationship attributes" on page 114](#).

The first row (column headings) displays the reason for the information. On this sheet, only the order of the parameters is important.

- a. Using Excel references, add informative captions and define member links between the IP subnet and first two IP addresses.

	A	B	C
1	start	relation_type	end
2	=ip_subnet!A2	membership	=ip_address!A2
3	=ip_subnet!A2	membership	=ip_address!A3

relationships node ip_address ip_subnet process

In this image, defined formulas are displayed (for example, **=ip_address!A2**). In actuality, the values of referenced cells are shown.

- b. Using key composition, define the relationships between the two IP addresses and their routing domains as follows:

IP key fields are ip_address and routing_domain. The composite key looks like **192.168.100.100|MyDomain**.

The relationship tab looks as follows:

	A	B	C
1	start	relation_type	end
2	192.168.100.0	membership	192.168.100.100 MyDomain
3	192.168.100.0	membership	192.168.100.101 MyDomain
4	192.168.100.0	membership	192.168.100.200
5	192.168.100.0	membership	192.168.100.201


Note:

- Any type of reference can be chosen. You can use only one reference type in a cell.
- Since the IP subnet CI has no key attributes in UCMDB 9.0x, they can be referenced only by Excel reference.

- c. Add a **containment** reference from **node** to **ip_address** and add a **dependency** reference from **running_software** to **process**:

	A	B	C
1	start	relation_type	end
2	192.168.100.0	membership	192.168.100.100 MyDomain
3	192.168.100.0	membership	192.168.100.101 MyDomain
4	192.168.100.0	membership	192.168.100.200
5	192.168.100.0	membership	192.168.100.201
6	192.168.100.100 MyDomain	containment	192.168.100.100 MyDomain
7	192.168.100.100 MyDomain	containment	192.168.100.101 MyDomain
8	192.168.100.200 MyDomain	containment	192.168.100.200
9	192.168.100.200 MyDomain	containment	192.168.100.201
10	Business app	dependency	C:\sample.ddm

After importing this Excel file, the topology appears as follows:



8. Add relationship attributes

Note: This use case is not widespread, but the Import from Excel Workbook job offers such capability.

Since many different types of links can be defined on the **relationships** tab in Excel, it is impossible to name columns with attribute names. For this purpose, the following notation is used:

<Attribute name>< relationship_attr_delimiter><Attribute value>

By default, for **relationship_attr_delimiter**, a pipe symbol ('|') is used.

The description definition for the link **dependency** from running_software to process looks like **description|The Business app depends from the Sample process.**

Now the **relationships** tab appears as follows:

	A	B	C	D
1	start	relation_type	end	
2	192.168.100.0	membership	192.168.100.100	
3	192.168.100.0	membership	192.168.100.101	
4	192.168.100.0	membership	192.168.100.200	
5	192.168.100.0	membership	192.168.100.201	
6	192.168.100.100 MyDomain	containment	192.168.100.100	
7	192.168.100.100 MyDomain	containment	192.168.100.101	
8	192.168.100.200 MyDomain	containment	192.168.100.200	
9	192.168.100.200 MyDomain	containment	192.168.100.201	
10	Business app	dependency	C:\sample.ddm	description The Business app depends from the Sample process'

If many attributes must be added, they must be defined in additional columns in the **dependency** row.

Note: On the **relationships** tab, no captions are needed for the attribute columns. If the column heading is present, these columns are treated as **comment** columns.

9. Convert attribute types to UCMDB attribute types

At the importing stage, each attribute is converted to the type defined in the UCMDB class model. This means that if an attribute is defined in UCMDB with a text value (for example, the attribute **port** in Service Address), but in the Excel file it has an integer value (for example, **5**), it will be converted to the corresponding type.

The following UCMDB attribute types are supported:

boolean	date	double	enumerations
float	integer	integer_list	long
string	string_list	xml	

Note: If the attribute cannot be converted to the type defined in UCMDB, it is skipped and you receive a warning in the UI.

Two list types exist in UCMDB: **integer_list** and **string_list**. To import such types, the value delimiters are intended. They are **integer_list_delimiter** and **string_list_delimiter** respectively. The default values are separated by a comma (','), but this can be changed to a job parameter.

If there is an attribute named **some_int_list** and it needs to be set using an integer list from 1 to 5, the cell in the **relationships** tab will look like:

`some_int_list|1,2,3,4,5`

■ Enumerate attribute types


Enumeration data types are supported for attributes. The job assumes the enumeration has been entered in human readable form and performs a search of the internal integer representation used in UCMDB.

If a value is entered that is not an enumeration value, it is ignored and you receive a warning in the log.

Because enumeration values are case sensitive in UCMDB, they are also case sensitive in Excel.

For example, if **SSN** in the image below had been written in lower case letters, **ssn**, the job

would send an error message because it would not find the **ssn** string in UCMDB.



M
tst_enum
SSN
Employee-ID
EMAIL
I.D No

Import from Excel Workbook Job

Note: The Import from Excel Sample job is similar to the Import from Excel Workbook job. It differs only by reference to the sample import file.

This section includes:

- ["Discovery Mechanism" below](#)
- ["Trigger Query" on the next page](#)
- ["Job Parameters" on the next page](#)
- ["Adapter" on page 118](#)
- ["Created/Changed Entities" on page 118](#)
- ["Discovered CITs" on page 119](#)

Discovery Mechanism

Each tab in the Excel file reflects a specific CI type. The CIT must be defined in the UCMDB data model prior to importing file content. If only out-of-the-box CITs are imported, you do not have to create the CITs because they already exist in UCMDB.

All attributes defined for a CIT must also already exist in UCMDB or the data will be rejected. Any special rules for attributes—such as data type, obligation, formatting, and so on—must also be acceptable by UCMDB for the data to be successfully imported into UCMDB.

The data type of the attribute—string, long, integer, boolean, and so on—depends on the UCMDB data model. You do not need to set attribute types manually. You must specify the attribute name in the document header line.

Discovery performs the following validations:

1. Verifies that the CITs on the tabs in the Excel spreadsheet exist in UCMDB.
2. Verifies that the attributes (the column names in the Excel spreadsheet) exist in UCMDB.
3. Checks the presence of key attributes on the Excel spreadsheet.

4. Processes all CITs that contain a **root_container** attribute after CITs that do not have this type of attribute. This helps to ensure that the parent CI is created before a contained CI.
5. Processes the **relationships** tab last to create relationships between CIs that do not use the containment (**container_f**) relationship.

For the relationship to be created, the keyed attributes of a CI must be used in the relationships tab.

6. Relation attributes also must exist in the UCMDB class model.
7. Verifies that the CITs on the tabs in the Excel spreadsheet exist in UCMDB.
8. Verifies that the attributes (the column names in the Excel spreadsheet) exist in UCMDB.
9. Checks the presence of key attributes on the Excel spreadsheet.
10. Processes all CITs that contain a **root_container** attribute after CITs that do not have this type of attribute. This helps to ensure that the parent CI is created before a contained CI.
11. Processes the **relationships** tab last to create relationships between CIs that do not use the containment (**container_f**) relationship.

For the relationship to be created, the keyed attributes of a CI must be used in the relationships tab.

12. Relation attributes also must exist in the UCMDB class model.

Trigger Query

The Import from Excel Workbook job has no trigger query. Therefore, you must manually add the Probe that imports the data. For details, see "Probe Selection Pane" in the *HP Universal CMDB Data Flow Management Guide*.

Job Parameters

Parameter	Description
file_name	The import file name. An absolute path accessible from the used probe must be used. For details on setting up this file, see "How to Set Up an Import File in Excel" on page 107 .
integer_list_delimiter	The delimiter used to handle values in the spreadsheet that are to be treated as the UCMDB data type integer_list .
string_list_delimiter	The delimiter used to handle values in the spreadsheet which would be mapped as the UCMDB data type string_list .

Parameter	Description
relationship_attr_delimiter	On the Relationship tab of the source file object, the linked attributes could be added. The default is attribute_name attribute_value (a pipe symbol is used between the attribute name and value). This should be aligned with actual data.

Adapter

- Input Query

Input CIT: discoveryprobemanager

Input query: Because the Import from Excel Workbook job's input CIT is Discovery Probe Gateway, there is no need to supply an input TQL query.

- Scripts Used

The following scripts are used to import data from an Excel workbook.

- import_from_excel.py
- xlsutils.py

Note: The Import from Excel Workbook job may also use library scripts supplied in the Auto Discovery content package.

Created/Changed Entities

Entity Name	Entity Type	Entity Description
Import from Excel Workbook	Job	Main importing job
Import from Excel Sample	Job	Sample job that imports the predefined sample import file
XLS_Parser	Adapter	Discovery adapter
import_from_excel.py	Script	Main import script
xlsutils.py	Script	Contains utility methods for class model validation and fetching objects from Excel worksheets

Entity Name	Entity Type	Entity Description
ciimports_for9.xls	Resource	Sample import file
poi-3.7-beta1-20100620.jar	Resource	Java library for working with Excel 97-2003 file format
poi-ooxml-3.7-beta1-20100620.jar	Resource	Java library for working with Excel 2007 file format
poi-ooxml-schemas-3.7-beta1-20100620.jar	Resource	Java library with XML schemas used in Excel 2007 files
geronimo-stax-api_1.0_spec-1.0.jar	Resource	Geronimo implementation of standard XML processing API (used by POI)
xmlbeans-2.3.0.jar	Resource	Library for accessing XML by binding it to Java types (used by POI)

Discovered CITs

- ConfigurationItem
- Managed Relationship

Note: To view the topology, see ["Topology" on page 105](#).

Troubleshooting and Limitations

- **Problem:** Import from Excel Workbook job compile time errors and problems working with the Excel files.

Solution: Verify that you have performed the instructions in the Prerequisite section of the this discovery. For details, see ["Prerequisite - Set up permissions" on page 106](#).

- **Problem:** Importing a CI with the qualifier **RANDOM_GENERATED_ID_CLASS**, but without defined reconciliation rules, leads to duplicating such CIs.

Solution: Currently this problem is not resolvable on the job side. This can only be resolved by defining reconciliation rules.

- **Problem:** Import from Excel Workbook job date errors.

Solution: The date cannot be imported if it is represented in text format. This issue is not resolvable because of localization. Represent the date in numerical format.

- **Limitation:** The DFM Probe breaks down the imported data into 20 KB chunks. This can cause identification issues.

Chapter 9: Microsoft SCCM/SMS Integration

This chapter includes:

- Overview 122
- Supported Versions 122
- SMS Adapter 122
- How to Populate the CMDB with Data from SCCM/SMS 124
- How to Federate Data with SCCM/SMS 125
- How to Customize the Integration Data Model in UCMDB 126
- Predefined Query for Population Jobs 127
- SCCM/SMS Integration Package 127
- SMS Adapter Configuration Files 130
- Troubleshooting and Limitations 131

Overview

This document includes the main concepts, tasks, and reference information for integration of Microsoft System Center Configuration Manager (SCCM)/Systems Management Server (SMS) with HP Universal CMDB.

Integration occurs by populating the UCMDB database with devices, topology, and hierarchy from SCCM/SMS and by federation with SCCM/SMS supported classes and attributes.

According to UCMDB reconciliation rules, if a CI (in SCCM/SMS) is already mapped to a CI in the CMDB, it is updated; otherwise, it is added to the CMDB.

Microsoft System Center Configuration Manager/Systems Management Server are used by IT administrators to manage client computers and servers.

SCCM/SMS enable you to:

- Manage computers that roam from one location to another
- Track deployment and use of software assets, and use this information to plan software procurement and licensing
- Provide IT administrators and management with access to data accumulated by SCCM/SMS
- Provide scalable hardware and software management
- Manage security on computers running Windows operating systems, with a minimal level of administrative overhead

Supported Versions

Integration has been developed and tested on HP Universal CMDB version 8.03 or later, with SCCM versions 2007 and 2012, and SMS version 2003.

SMS Adapter

Integration with SCCM/SMS is performed using an SMS adapter, which is based on the Generic DB Adapter. This adapter supports full and differential population for defined CI types as well as federation for other CI types or attributes.

The SMS Adapter supports the following features:

- Full replicating of all instances of the selected CI types.
- Identifying changes that have occurred in SCCM/SMS, to update them in the UCMDB.
- Simulating the touch mechanism capabilities:

When a CI is removed from SCCM/SMS, it is physically deleted from the database and there is no way to report about it. The SMS Adapter supports a full synchronization interval. This means that the adapter transfers data for which the aging mechanism has been enabled, and provides the time interval to run a full synchronization that simulates the touch mechanism.

- Federation of selected CI types and attributes.

Out-of-the-box integration with SCCM/SMS includes population of the following classes:

- Node (some of the attributes are populated and some are federated)
- Layer2 connection
- Location that is connected to the node
- IP address
- Interface

In addition, the following classes can be defined as federated from SCCM/SMS:

- CPU
- File system
- Installed software
- Windows service

The following classes and attributes should be marked as federated by the SCCM/SMS adapter for the proper functionality of the Actual State feature of Service Manager:

- Classes
 - CPU
 - Installed software
 - Windows service
- Node attributes
 - DiscoveredOsVendor
 - DiscoveredModel
 - Description
 - DomainName
 - NetBiosName

Note: Avoid marking the **LastModifiedTime** attribute as federated, as it may lead to unexpected results.



How to Populate the CMDB with Data from SCCM/SMS

This task describes how to install and use the SMS adapter.

This task includes the following steps:

- ["Define the SMS integration" below](#)
- ["Define a population job \(optional\)" on the next page](#)
- ["Run the population job" on the next page](#)

1. Define the SMS integration

- In UCMDB, navigate to **Data Flow Management > Integration Studio**.
- Click the **New Integration Point**  button to open the new integration point Dialog Box.
 - Click , select the Microsoft SMS adapter, and click **OK**.

Each out-of-the-box adapter comes predefined with the basic setup needed to perform integration with UCMDB. For information about changing these settings, see "Integration Studio Page" in the *HP Universal CMDB Data Flow Management Guide*.

- Enter the following information, and click **OK**:

Name	Description
Credentials	Allows you to set credentials for integration points. For credential information, see "Supported Protocols" in the <i>HP Universal CMDB Discovery and Integration Content Guide - Supported Content</i> document.
Hostname/IP	The host name of the machine where the database of SCCM/SMS is running.
Integration Name	The name you assign to the integration point.

Name	Description
Is Integration Activated	Select this check box to create an active integration point. You clear the check box if you want to deactivate an integration, for instance, to set up an integration point without actually connecting to a remote machine.
Port	The port through which you access the MSSQL database.

- c. Click **Test connection** to verify the connectivity, and click **OK**.
- d. Click **Next** and verify that the following message is displayed: **A connection has been successfully created**. If it does not, check the integration point parameters and try again.



2. Define a population job (optional)

The Microsoft SMS adapter comes out-of-the-box with the **hostFromSMS Population** job, which runs the following predefined query: **hostDataFromSMS**. For details about this query, see ["Predefined Query for Population Jobs" on page 127](#). This job runs according to a default schedule setting.

You can also create additional jobs. To do this, select the Population tab to define a population job that uses the integration point you defined in ["Define the SMS integration" on the previous page](#). For details, see "New Integration Job/Edit Integration Job Dialog Box" in the *HP Universal CMDB Data Flow Management Guide*.

3. Run the population job

Activate the population job in one of the following ways:

- To immediately run a full population job, click . In a full population job, all appropriate data is transferred, without taking the last run of the population job into consideration.
- To immediately run a differential population job, click . In a differential population job, the previous population time stamp is sent to SCCM/SMS, and SCCM/SMS returns changes from that time stamp to the present. These changes are then entered into the UCMDB database.
- To schedule a differential population job to run at a later time or periodically, define a scheduled task. For details, see "Define Tasks that Are Activated on a Periodic Basis" in the *HP Universal CMDB Administration Guide*.

Note: the replicated CIs are controlled by the integration TQL that is used. You can create additional TQL queries that contain different topologies for use in other jobs.

How to Federate Data with SCCM/SMS

The following steps describe how to define the CI types that will be federated with SCCM/SMS.

1. In UCMDB, navigate to **Data Flow Management > Integration Studio**.
2. Select the integration point that you defined in ["Define the SMS integration" on page 124](#).
3. Click the **Federation** tab. The panel shows the CI types that are supported by the SMS adapter.
4. Select the CI types and attributes that you want to federate.
5. Click **Save**.

Note:

- CI types that populate UCMDB should not be selected for federation. Specifically, avoid federating node, IP address, interface, location, and Layer2, which populate UCMDB out-of-the-box.
- Other CI types can be used in federation only after the node data has been replicated to CMDB by the hostDataImport query. This is because the default reconciliation rule is based on node identification.

How to Customize the Integration Data Model in UCMDB

Out-of-the-box CIs for SCCM/SMS integration can be extended in one of the following ways:

To add an attribute to an existing CI type:

If the attribute you want to add does not already exist in the CMDB, you need to add it. For details, see "Add/Edit Attribute Dialog Box" in the *HP Universal CMDB Modeling Guide*.

1. Go to the **orm.xml** file as follows: **Data Flow Management > Adapter Management > SMS Adapter > Configuration Files > orm.xml**.
2. Locate the **generic_db_adapter.[CI type]** to be changed, and add the new attribute.
3. Ensure that the TQL queries that include this CI type have the new attribute in their layouts as follows:
 - a. In the Modeling Studio, right-click the node where you want to include the attribute.
 - b. Select **Query Node Properties**.
 - c. Click **Advanced Layout Settings** and select the new attribute.

For details about selecting attributes, see "Layout Settings Dialog Box" in the *HP Universal CMDB Modeling Guide*. For limitations on creating this TQL query, see ["Troubleshooting and Limitations" on page 131](#).

To add a new CI Type to the Generic DB Adapter:

1. In UCMDB, create the CI Type that you want to add to the adapter, if it does not already exist. For details, see "Create a CI Type" in the *HP Universal CMDB Modeling Guide*.
2. Go to the **orm.xml** file as follows: **Data Flow Management > Adapter Management > SMS Adapter > Configuration Files > orm.xml**.
3. Map the new CI type by adding a new entity called **generic_db_adapter.[CI type]**.

For more details, see "The orm.xml File" in the *HP Universal CMDB Developer Reference Guide*.

4. Create queries to support the new CI types that you have added. Make sure that all mapped attributes are selected in the Advanced Layout settings:
 - a. In the Modeling Studio, right-click the node where you want to include the attribute.
 - b. Select **Query Node Properties**.
 - c. Click **Advanced layout settings** and select the new attribute.

For details about selecting attributes, see "Layout Settings Dialog Box" in *HP Universal CMDB Modeling Guide*. For limitations on creating this TQL query, see ["Troubleshooting and Limitations" on page 131](#).

5. In UCMDB, navigate to **Data Flow Management > Integration Studio**.
6. Edit the SMS integration point to support the new CI type by selecting it either for population or for federation.
7. If the new CI type is for population, edit the population job that you created above.

Predefined Query for Population Jobs

The following TQL query is provided out-of-the-box if you use the Microsoft SMS adapter when you create an integration point:

- **hostDataFromSMS**. Imports nodes and their related data. Information also includes each node's IP address and interface.

SCCM/SMS Integration Package

This section includes:

- ["Transformations" on the next page](#)
- ["SCCM/SMS Plug-in " on page 129](#)
- ["Reconciliation" on page 130](#)

Transformations

Following is the list of transformations that are applied to values when they are transferred to or from the SCCM/SMS database:

CMDB Class	Attribute	Transformation
windows	nt_servicepack	Represents number of the Windows service pack. SCCM/SMS DB: Service Pack 2 UCMDB: 2.0 Transformer: standard GenericEnumTransformer, mapped in the nt.nt_servicepack.transformer.xml file.
node	host_isdesktop	A Boolean value that determines whether a machine is a desktop or a server. SCCM/SMS DB: Workstation or Server UCMDB: true or false Transformer: standard GenericEnumTransformer, mapped in the node.host_isdesktop.transformer.xml file.
node	host_os	Represents the node's operation system. SCCM/SMS DB. Microsoft Windows XP Professional UCMDB. Windows XP Transformer. Standard GenericEnumTransformer , mapped in the node.discovered_os_name.transformer.xml file. If the SCCM/SMS operation system value is not listed in the transformer.xml file, the original value is sent to UCMDB. By default, only Windows operating systems are mapped.

CMDB Class	Attribute	Transformation
node	host_osinstalltype	<p>Represents the Windows OS edition.</p> <p>SCCM/SMS DB. Microsoft Windows XP Professional</p> <p>UCMDB. Professional</p> <p>Transformer. Standard GenericEnumTransformer, mapped in the host.host_osinstalltype.transformer.xml file.</p> <p>Note: The same column in the SCCM/SMS database is mapped to two different UCMDB attributes, using different transformers.</p>
disk device	name	<p>Represents the partition name.</p> <p>SCCM/SMS DB. C:</p> <p>UCMDB. C</p> <p>Transformer. standard AdapterToCmdbRemoveSuffixTransformer that removes the colon.</p>
interface	interface_macaddr	<p>Represents the MAC address of NIC.</p> <p>SCCM/SMS DB. AB:CD:EF:01:23:45</p> <p>UCMDB. ABCDEF012345</p> <p>Transformer. custom SmsMacAddressTransformer that removes the colons from the SCCM/SMS MAC address while making it compatible with the UCMDB MAC addresses.</p>

SCCM/SMS Plug-in

The **SmsReplicationPlugin** provides enhanced functions to those found in the Generic Database Adapter. It is called when:

- full topology is requested (**getFullTopology**) – this returns all the CIs that were found in the external SCCM/SMS database.
- topology layout is requested (**getLayout**)
- topology of changes is requested (**getChangesTopology**) – this returns only the CIs that are modified or added after a specific time. The topology of the changes is calculated as follows:
 - There is a specific date (**fromDate**) after which all changes are requested.
 - Most of the entities in the SCCM/SMS database contain a Timestamp column that contains the date and time of the last modification. This Timestamp column is mapped to the **root_**

updatetime attribute of a CI. Currently, some entities do not contain any creation time information. The entities that have a timestamp column must be listed in the **replication_config.txt** file.

- In the integration TQL query, the node CI is named **Root**.
- Using the plug-in, the integration TQL query is dynamically modified so that each **Root** entity and all entities that are listed in the **replication_config.txt** file have an additional condition causing the value of the **root_updatetime** attribute to be greater than or equal to the **fromDate** value.
- This modified TQL query is then used to obtain the data.

Reconciliation

The adapter uses the default reconciliation rule-based mapping engine.

SMS Adapter Configuration Files

The adapter includes the following configuration files:

- **orm.xml**. The Object Relational mapping file, which maps between SCCM/SMS database tables and columns, and UCMDB classes and attributes. Both CIs and links are mapped.
- **fixed_values.txt**. Used by the Generic DB Adapter to set the **ip_domain** of IP Address CIs to **DefaultDomain**.
- **plugins.txt**. Contains configuration information for the Generic DB Adapter. Also defines three plug-ins that are used during replication: **getFullTopology**, **getChangesTopology**, and **getLayout**.
- **transformations.txt**. Contains the configuration for transformation of attribute values. For a list of the transformations, see "[Transformations](#)" on page 128.
- **node.discovered_os_name.transformer.xml**. Mapping used by the transformer for the **host_isdesktop** attribute.
- **node.host_osinstalltype.transformer.xml**. Mapping used by the transformer for the **host_os** attribute.
- **host.host_osinstalltype.transformer.xml**. Mapping used by the transformer for the **host_osinstalltype** attribute.
- **nt.nt_servicepack.transformer.xml**. Mapping used by the transformer for the **nt_servicepack** attribute.
- **replication_config.txt**. Contains a comma-separated list of non-root CIs and relations types that have a **timestamp** condition in the SCCM/SMS database. This status condition indicates the last time the entity was updated.
- **reconciliation_types.txt**. Defines the CI types that are used for reconciliation.

For details on adapter configuration, see "Developing Generic Database Adapters" in the *HP Universal CMDB Developer Reference Guide*.

Troubleshooting and Limitations

- Queries that are used in population jobs should contain one CI type that is labeled with a Root prefix, or one or more relations that are labeled with a Root prefix.

The root node is the main CI that is synchronized; the other nodes are the contained CIs of the main CI. For example, when synchronizing the Node CI Type, that graph node is labeled as Root and the resources are not labeled Root.

- The TQL graph must not have cycles.
- A query that is used to synchronize relations should have the cardinality 1...* and an OR condition between the relations.
- The adapter does not support compound relations.
- Entities that are added in SCCM/SMS are sent as updates to UCMDB by the SMS Adapter during differential population.
- ID conditions on the integration TQL query are not supported.
- The TQL graph should contain only CI types and relations that are supported by the SCCM/SMS adapter.

Chapter 10: NetApp SANscreen/OnCommand Insight Integration

This chapter includes:

- Overview 133
- Supported Versions 133
- Topology 133
- How to Discover NetApp SANscreen (NetApp OnCommand Insight) 134
- SANscreen Integration by WebServices Job 135
 - Adapter 135
 - Parameters 136
 - Integration Flow 136
- SANscreen Adapter 136
- Troubleshooting and Limitations 138

Overview


Integration between NetApp SANscreen and DFM involves a UCMDB initiated integration adapter on the SANscreen WebService API, and synchronizes devices, topology, and hierarchy of storage infrastructure in UCMDB. This enables Change Management and Impact Analysis across all business services mapped in UCMDB from a Storage point of view.

Supported Versions


SANscreen integration supports version 5.1.2 (275) of NetApp SANscreen and version 6.2x, 6.3, and 6.4 of the product which has been renamed NetApp OnCommand Insight.

Topology

The following diagram illustrates the storage topology and shows the relationships between logical volumes on a storage array and those on servers:



The following diagram illustrates the SAN Topology and shows the fiber channel paths between storage arrays, switches, and servers:



How to Discover NetApp SANscreen (NetApp OnCommand Insight)

This task includes the following steps:

1. Prerequisite - Shell Connectivity

Ensure there is Shell connectivity to one or more nodes of the SANscreen domain.

For credential information, see "Supported Protocols" in the *HP Universal CMDB Discovery and Integration Content Guide - Supported Content* document.

2. Prerequisite - Update Jar Files

- On the NetApp server, navigate to the following location: **<SANscreen root folder>\jboss\server\onaro\tmp<...\onaro-home.war>\WEB-INF\lib\java-sdk.jar**.

where **<SANscreen root folder>** is the location where you installed NetApp.

- Rename **java-sdk.jar** to **sanscreen_api.jar**.

- c. Stop the Data Flow Probe.
- d. On the Data Flow Probe, navigate to the following location:
<DataFlowProbe>
\\root\\lib\\collectors\\discoveryProbe\\discoveryResources\\SANscreen\\sanscreen_api.jar.

where **<DataFlowProbe>** is the location where you installed the Data Flow Probe.
- e. Replace the file on the Data Flow Probe with the renamed file from the NetApp server.
- f. Restart the Data Flow Probe.

3. Run the Discovery

- a. Run the **Range IPs by ICMP** job in order to discover the target IPs.
- b. Run the **TCP Ports** job in order to discover SANscreen WebService ports.

4. Define the integration point

In **Data Flow Management > Integration Studio**, define a new integration point:

- a. Provide a name and description
- b. Select the **NetApp SANscreen/On Command Insight** adapter and enter the required properties as follows:

Attribute	Description
ChunkSize	The number of CIs to pull from SANscreen/OnCommand Insight per query. The default is 1000.
Data Flow Probe	Select the name of the Probe on which this integration will run.
Trigger CI Instance	Select the IpServiceEndpoint at which the SANscreen/OnCommand Insight service is running.

A predefined job appears by default. Define a synchronization schedule if required. Jobs can also be run without a schedule.

- c. Save the job definition and then the integration point.
- d. Run a full synchronization for each job at least once.

SANscreen Integration by WebServices Job Adapter

This job uses the **NetApp SANscreen/OnCommand** integration adapter.

Parameters

ChunkSize

Default: 1000

Integration Flow

The adapter works as follows:

1. Connect to the SANscreen WebService API using credentials from the SANscreen protocol.
2. Query for storage arrays and create STORAGE ARRAY CIs.
3. Query for logical volumes, fiber channel adapters (Host Bus Adapters), and fiber channel ports on each storage array and create LOGICAL VOLUME, HBA, and FC PORT CIs.
4. Query for fiber channel switches and create FC SWITCH CIs.
5. Query for fiber channel adapters and ports on each fiber channel switch and create HBA and FC PORT CIs.
6. Query for hosts/servers and create appropriate COMPUTER, WINDOWS, or UNIX CIs.
7. Query for logical volumes, fiber channel adapters (Host Bus Adapters), and fiber channel ports on each host/server and create LOGICAL VOLUME, HBA, and FC PORT CIs.
8. Query for paths between hosts/servers and storage arrays and add FCCONNECT relationships between respective hosts/servers, switches, and storage arrays.
9. Query for logical volume mapping between logical volumes on hosts/servers and logical volumes on storage arrays and add DEPEND relationships between respective hosts/servers and storage arrays.

SANscreen Adapter

This section contains information about the SANscreen adapter.

Input CIT

IpServiceEndpoint

Input Query



SOURCE

Triggered CI Data

Name	Value
ip_address	\${SOURCE.bound_to_ip_address}
port	\${SOURCE.network_port_number}

Used Script

SANscreen_Discovery.py

Discovered CITs

- Composition
- Containment
- Cpu
- Dependency
- FabricZoneSet
- FiberChannelZone
- Fiber Channel Connect
- Fibre Channel HBA
- Fibre Channel Port
- Fibre Channel Switch
- IpAddress
- LogicalVolume
- Membership
- Node
- Storage Array
- Storage Fabric
- Storage Processor
- Unix
- Windows

Global Configuration Files

None

Parameters

ChunkSize: The number of CIs to pull from SANscreen/OnCommand Insight per query. The default is 1,000.

Troubleshooting and Limitations

Problem: Depending on the version of NetApp SANscreen or OnCommand Insight in use, discovery may fail with the following error message in the Probe wrapper logs:

```
SANscreen: Internal error. Details: java.lang.ClassCastException: com.sun.xml.messaging.saaj.soap.ver1_1.Message1_1Impl
```

Solution: In this case, replace

<DDM>\root\lib\collectors\discoveryProbe\discoveryResources\SANscreen\sanscreen_api.jar with the corresponding file from the SANscreen server in use.

Chapter 11: ServiceNow Integration

This chapter includes:

- Overview 140
- Supported Versions 140
- Push Integration with ServiceNow 140
 - How to Push Data from UCMDB to ServiceNow 140
 - Push Integration Mechanism 142
 - Sample Integration Push Query 143
 - Supported CITs 144
- Population from ServiceNow 145
 - How to Populate UCMDB with Data from ServiceNow 146
 - Population Flow 148
 - Jython Scripts for Population 148
 - Mapping Files for Population Flow 149
 - Supported CITs 151
- Troubleshooting and Limitations 152

Overview

ServiceNow-UCMDB integration consists of two independent, bi-directional parts: **Data Push into ServiceNow** and **Population from ServiceNow**.

The jobs enable you to integrate CIs and relationships between UCMDB and ServiceNow. The integrations both use XML mapping frameworks that enable you to dynamically map CI types between UCMDB and ServiceNow, without requiring code changes.

- **Data Push into ServiceNow** provides the ability to push CIs and relationships from UCMDB to ServiceNow.
- **Population from ServiceNow** provides the ability to import CIs and relationships from ServiceNow into UCMDB.

Supported Versions

This integration solution supports pushing CIs to ServiceNow from HP Universal CMDB version 9.02 and later and populating UCMDB with CIs from HP Universal CMDB version 10.01 and later

Push Integration with ServiceNow

This section includes:

How to Push Data from UCMDB to ServiceNow	140
Push Integration Mechanism	142
Sample Integration Push Query	143
Supported CITs	144
How to Push Data from UCMDB to ServiceNow	140
Push Integration Mechanism	142
Sample Integration Push Query	143
Supported CITs	144
Pushing Additional CITs	144

How to Push Data from UCMDB to ServiceNow

1. Configure queries

The CIs and relationships to be pushed to ServiceNow have to be queried from UCMDB using TQL queries. Create integration type queries to query the CIs and relationships that have to be

pushed to ServiceNow.

An example of such a query, [ServiceNowSampleQuery](#), is included with this integration package, and can be viewed in the Modeling Studio. For details on viewing queries in the Modeling Studio, see the *HP Universal CMDB Modeling Guide*.

2. Create XML mapping files

For every query created in the step above, create an XML mapping file with exactly the same name (case-sensitive) as the integration query in the following directory:

<UCMDB>\UCMDBServer\runtime\fcmdb\CodeBase\ServiceNowPushAdapter\mappings

A sample mapping file for this integration, **ServiceNowSampleMapping.xml**, is provided out of the box with the package.


For more information about mapping files, see the *HP Universal CMDB Developer Reference Guide*.

3. Create the integration point

Define the integration point as follows:

- a. In UCMDB, go to **Data Flow Management > Integration Studio**.
- b. In the New Integration Point dialog box, enter a name and description for the integration point.

Ensure the **Is Integration Activated** option is enabled.


- c. In the Adapter field click the **Select Adapter**  button.
- d. In the Select Adapter list, select **Push to Service-Now** and click **OK**.
- e. In the Adapter Properties section, enter the following required properties:

Field	Value
Service-Now Domain	Domain name used to access the ServiceNow instance. Usually service-now.com .
Service-Now Instance	The ServiceNow instance being used. For the demonstration instance, enter demo .
Port	Default 443, for HTTPS.

Field	Value
Protocol	HTTP or HTTPS.
Proxy Server Name/IP	If an HTTP(S) proxy service is used to access the Internet, enter the proxy server name.
Proxy Server Port	HTTP(S) proxy server port.
Credentials	Define the ServiceNow instance username and password in the Generic Protocol. For the demonstration website, use admin/admin . For credential information, see Supported Protocols in the <i>HP UCMDB Discovery and Integrations Content Guide</i> .
Data Flow Probe	Select the name of the Data Flow Probe to run this integration.

- f. Test the connection to the target CMDB server. If the connection fails, verify that the information provided is correct.
- g. Click **OK** to save the integration point.
- h. Add a new job definition to the integration point. Provide a name for the job definition and select the queries to use to synchronize data from UCMDB to ServiceNow. Define a synchronization schedule if required.

Note: Jobs can also be run without a schedule.

- i. Save the job definition, and then the integration point.
- j. Click  to run a full synchronization for each job at least once.

Push Integration Mechanism

The components responsible for the ServiceNow integration are bundled in the ServiceNow Integration package, **ServiceNow_Integration.zip**.

The integration mechanism works as follows:

1. The Integration job queries UCMDB for CIs and relationships.

When an ad-hoc job is run from the integration point in the Integration Studio, the integration receives the names of the integration queries defined in the job definition, for that integration point.

It queries UCMDB for the results of these queries (new, updated and deleted CIs and relationships) and then applies the mapping transformation according to the predefined XML mapping files for every TQL query.

It then pushes the data to the Data Flow Probes.


2. The integration job sends the data to ServiceNow.

Next, on the Data Flow Probe side, the integration process receives the CI and relationship data sent from the UCMDB server, connects to the ServiceNow server using the Direct Web Services SOAP API, and transfers the CIs and relationships.

Since the ServiceNow coalescing (CI reconciliation) mechanism is not available for the Direct Web Services API, a mapping of UCMDB CI IDs to ServiceNow SysIds is maintained on the Data Flow Probe. This mapping is used to update and delete CIs and relationships in ServiceNow.

Sample Integration Push Query

The following image displays a sample query to be pushed to ServiceNow:



Supported CITs

The following CIs and their relationships are supported out-of-the-box for push integrations:

- Apache Tomcat
- Apache
- DB2
- ESX Server
- Host
- IIS Web Server
- Interface
- Ip Address
- JBoss AS
- MySQL
- Net Device
- Oracle
- SQL Server
- Switch
- Unix Server
- Weblogic AS
- WebSphere AS
- Windows Server

Pushing Additional CITs

To push additional CITs, these CITs should be added to the mapping file. For details, see the *HP Universal CMDB Developer Reference Guide*.

Pushing additional CI Types requires corresponding JAR files to be generated using the WSDL URL for each CI Type. The WSDL URL can be generated using information from the **Direct Web Services** section at:

http://wiki.service-now.com/index.php?title=SOAP_Web_Service.

The resulting JAR files should be placed in the following directory on the UCMDB Data Flow Probe server:

<hp>\UCMDB\DataFlowProbe\runtime\probeManager\discoveryResources\Service-Now

Note: JAR files should be re-generated following CI Type updates in ServiceNow.

JAR files may be generated using WSDL2JAVA or other similar utilities. An example using this utility is at :

<http://roseindia.net/webservices/axis2/axis2-client.shtml>.

For CIs containing reference fields, the target data type of the attribute being mapped to a reference field should be set to the name of the reference table. For example, to populate the **Manufacturer** field on a **Windows Server** CI, the data type should be the reference table name **core_company** as shown below:

```
<source_ci_type name="nt" namespace="" query="">
  <target_ci_type name="cmdb_ci_win_server">
    <targetprimarykey>
      <pkey>ID</pkey>
    </targetprimarykey>
    <target_attribute name="virtual" datatype="boolean">
      <map type="direct" source_attribute="host_isvirtual" />
    </target_attribute>
    <target_attribute name="category" datatype="String">
      <map type="direct" source_attribute="os_family" />
    </target_attribute>
    <target_attribute name="short_description" datatype="String">
      <map type="direct" source_attribute="discovered_description" />
    </target_attribute>
    <target_attribute name="correlation_id" datatype="String">
      <map type="direct" source_attribute="global_id" />
    </target_attribute>
    <target_attribute name="model_number" datatype="String">
      <map type="direct" source_attribute="discovered_model" />
    </target_attribute>
    <target_attribute name="name" datatype="String">
      <map type="direct" source_attribute="display_label" />
    </target_attribute>
    <target_attribute name="os" datatype="String">
      <map type="direct" source_attribute="discovered_os_name" />
    </target_attribute>
    <target_attribute name="model_id" datatype="cmdb_model">
      <map type="direct" source_attribute="discovered_model" />
    </target_attribute>
    <target_attribute name="manufacturer" datatype="core_company">
      <map type="direct" source_attribute="discovered_vendor" />
    </target_attribute>
  </target_ci_type>
</source_ci_type>
```

Population from ServiceNow

This section includes:

How to Populate UCMDB with Data from ServiceNow	146
Population Flow	148

Jython Scripts for Population	148
Mapping Files for Population Flow	149
Supported CITs	151
How to Populate UCMDB with Data from ServiceNow	146
Population Flow	148
Jython Scripts for Population	148
Mapping Files for Population Flow	149
Supported CITs	151

How to Populate UCMDB with Data from ServiceNow

1. Prerequisites

Install the **ServiceNow_pull_integration_patch.zip** patch on the Data Flow Probe. Note the address and port of the HTTP/HTTPS proxy server between the Probe machine and the ServiceNow instance.

To install the patch, extract the patch archive into the Probe installation folder. As a result, the folder **<probe_installation_folder>/jython/suds** is created, and two files, **<probe_installation_folder>/jython/httplib.py** and **<probe_installation_folder>/jython/urllib2.py** should be updated. You do not need to restart the Probe.

Patch content:

- **jython/suds** – a library to work with WSDL-based web-services.
- **jython/suds/mx/appender.py** – this script is modified to properly handle ServiceNow query parameters, such as **_use_view**, **_encoded_query**. See line 191.
- **jython/httplib.py**, **jython/urllib2.py** – modified Jython 2.5.3 scripts, the following patch is applied:

<http://bugs.python.org/issue1424152>

2. Create XML Mapping Files.



The XML mapping file describes the topology that should be pulled from the ServiceNow instance and how it should be mapped to the UCMDB class model. Place one or more mapping files into the folder **<probe_installation_folder>\runtime\probeManager\discoveryConfigFiles\ServiceNow** on the Probe.

3. Create credentials for the ServiceNow Protocol.

Create entries only for the username and password fields.

4. Create the Integration Point.

Define the integration point as follows:

- a. In UCMDB, go to **Data Flow Management > Integration Studio**.
- b. Click the **New Integration Point**  button.
- c. In the New Integration Point dialog box, enter a name and description for the integration point.
- d. In the Adapter field click the **Select Adapter**  button.
- e. In the Select Adapter list, select **ServiceNow to UCMDB** and click OK.
- f. In the Adapter Properties section, enter the following required properties:

Field	Value
Credentials ID	Select the credential entries you created in step 3 for the ServiceNow Protocol.
HTTPs Proxy	Enter the IP address of the proxy server used to connect to the ServiceNow instance. If you are not using a proxy, leave this field empty.
Mapping File	The name of the XML mapping file you created in step 2, located in the \discoveryConfigFiles\ServiceNow folder. Leave blank if you want all the mapping files in this folder to be processed.
ServiceNow Instance URL	The address where the ServiceNow instance can be reached, including the protocol prefix and port. For example, https://demo.service-now.com .
Data Flow Probe	Select the Probe on which the integration will run.
Trigger CI Instance	Select the DataFlowProbe CI, which refers to the same Probe as Data Flow Probe property above.

- g. Click **OK** to save the integration point. At this point, a default integration job definition is automatically created.

5. Define a synchronization schedule for the integration job, if desired.

Jobs can also be run manually, without a schedule.

6. Run full data synchronization.

Click  to synchronize all data.

Population Flow

The following stages comprise the flow of populating UCMDB with CIs from ServiceNow:

- Querying CIs

The integration job reads the mapping files to identify which CIs and relationships should be pulled from ServiceNow. It then connects to ServiceNow's Web Service API.

- a. A SOAP client is created for each CI type and relationship type defined in the mapping file, for example, **`https://demo.service-now.com/cmdb_ci_unix_server.do?wsdl`**.
- b. The `getRecords([query])` method is invoked to obtain instances of this CI type or relationship.

- Mapping data

CIs that are obtained from ServiceNow are mapped to UCMDB CIs.

- Querying relationships

The integration job uses **`https://demo.service-now.com/cmdb_rel_type.do?wsdl`** and **`https://demo.service-now.com/cmdb_rel_ci.do?wsdl`** to link CIs.

- Sending topology to UCMDB

The topology is sent from the Data Flow Probe to UCMDB.

Jython Scripts for Population

The following Jython scripts are used:

- **`mapping_interfaces.py`** – major interfaces involved in the integration workflow.
- **`replication.py`** – replication algorithm.
- **`mapping_implementation.py`** – basic implementation of some of the mapping interfaces.
- **`mapping_file_manager.py`** – abstract entity to represent mapping file.
- **`old_mapping_file_manager.py`** – mapping file parser.
- **`connection_data_manager.py`** – an entity that encapsulates pieces of data required to establish connection to ServiceNow instance.
- **`decorators.py`** – internal functions.
- **`pull_from_service_now.py`** – actual integration implementation script. All ServiceNow-related code is encapsulated inside the `ServiceNowSourceSystem` class.

Mapping Files for Population Flow

- **Query** – You can use a ServiceNow query to filter replicated CIs.

```
...  
<source_ci_type name="cmdb_ci_vcenter_datacenter" query="name=prod">  
...
```

For details on creating queries, see

http://wiki.servicenow.com/index.php?title=Embedded:Encoded_Query_Strings.

- **Foreign keys** – Sometimes CIs in ServiceNow do not have a relationship defined between them, but one CI keeps the `sys_id` of another CI in one of its attributes. For example, `cmdb_ci_network_adapter` has the attribute `cmdb_ci`, which contains the `sys_id` of the host where this adapter resides. To handle this situation in the mapping file, use the special `__Reference` type of link, and provide the name of the attribute with the foreign `sys_id`

```
<link source_link_type="__Reference" reference_attribute="cmdb_ci" target_  
link_type="composition"  
source_ci_type_end1="cmdb_ci_unix_server" source_ci_type_end2="cmdb_ci_net  
work_adapter">  
  <target_ci_type_end1 name="unix"/>  
  <target_ci_type_end2 name="interface"/>  
</link>
```

By using the special `__Reference` link type, you can split one ServiceNow CI into multiple UCMDB CIs. For example, `cmdb_ci_esx_server` in ServiceNow should be transformed into a pair ESX -> Hypervisor in UCMDB. To do that, create a mapping file like this:

```
?<?xml version="1.0" encoding="UTF-8"?>  
<integration>  
  <info>  
    <source name="ServiceNow" versions="" vendor="ServiceNow" />  
    <target name="UCMDB" versions="10.x" vendor="HP" />  
  </info>  
  <targetcis>  
    <source_ci_type name="cmdb_ci_esx_server">  
      <target_ci_type name="vmware_esx_server">  
        <target_attribute name="name">  
          <map type="direct" source_attribute="name" />  
        </target_attribute>  
      </target_ci_type>  
    </source_ci_type>  
    <source_ci_type name="cmdb_ci_esx_server">  
      <target_ci_type name="hypervisor">
```

```
<target_attribute name="name">
  <map type="direct" source_attribute="name" />
</target_attribute>
<target_attribute name="product_name">
  <map type="const" value="vmware_hypervisor" />
</target_attribute>
</target_ci_type>
</source_ci_type>
</targetcis>
<targetrelations>
  <link source_link_type="__Reference" reference_attribute="sys_id" t
target_link_type="composition"
source_ci_type_end1="cmdb_ci_esx_server" source_ci_type_end2="cmdb_ci_esx_se
rver">
    <target_ci_type_end1 name="vmware_esx_server"/>
    <target_ci_type_end2 name="hypervisor"/>
  </link>
</targetrelations>
</integration>
```

Note that `cmdb_ci_esx_server` is mapped into two UCMDB CIs: `vmware_esx_server` and `hypervisor`. There is a relationship definition, that leverages the `__Reference` link type and `sys_id` as a foreign key. This means that when using `sys_id` as a reference attribute, the CI references itself. This allows you to map `cmdb_ci_esx_server` to two CIs and create a relationship between them.

- **Attribute mapping types:**

- **direct** – Takes the attribute value of a ServiceNow CI and sets it to a UCMDB CI attribute unchanged.
- **const** – Sets a UCMDB attribute to some constant value.

```
<source_ci_type name="cmdb_ci_esx_server">
  <target_ci_type name="hypervisor">
    <target_attribute name="name">
      <map type="direct" source_attribute="name" />
    </target_attribute>
    <target_attribute name="product_name">
      <map type="const" value="vmware_hypervisor" />
    </target_attribute>
  </target_ci_type>
</source_ci_type>
```

- **Link failure policy** – Sometimes relationships are mandatory and you do not want certain CIs

to enter UCMDB unless they have required relationships. To enforce this behavior, use `failure_policy` to define what to do, such as when a relationship cannot be created between a particular pair of CIs. Possible values are `exclude_end1`, `exclude_end2`, `exclude_both` and `ignore` (this is the default).

```
<link source_link_type="Defines resources for::Gets resources from" target_link_type="composition"
source_ci_type_end2="cmdb_ci_vcenter_cluster" source_ci_type_end1="cmdb_ci_esx_resource_pool"
failure_policy="exclude_end1" direction="reverse">
  <target_ci_type_end1 name="vmware_resource_pool"/>
  <target_ci_type_end2 name="vmware_cluster"/>
</link>
```

- **Link direction** – If you need relationship to go into the opposite direction than it is defined in ServiceNow, you can use the `direction="reverse"` attribute on a link mapping definition. Note that `target_ci_type_end1` and `target_ci_type_end2` should not be switched when this attribute is applied (see the previous example).
- **Validators** – Use validators when it is necessary to validate an attribute's values before sending topology to UCMDB. The following example filters out all `cmdb_ci_ip_address` instances where the attribute name is not actually, a valid IP address.

```
<target_attribute name="ip_netmask">
  <map type="direct" source_attribute="netmask" />
  <validators>
    <validator>validators.mandatory</validator>
    <validator>netutils.isValidIp</validator>
  </validators>
</target_attribute>
```

A validator's value is actually any Python function that returns a Boolean result. You can either use existing functions for validation, such as `netutils.isValidMac`, or write your own validation functions to get the most flexibility. The package contains a Jython script called `validators.py`, where you can add your custom validation functions.

Supported CITs

The population integration supports any CI and relationship that is available in ServiceNow.

Troubleshooting and Limitations

This section describes troubleshooting and limitations for the ServiceNow-UCMDB integrations.

Push integration

- **Limitation:** The integration mapping file only allows mapping concrete CITs and relationships to the CITs and relationships in ServiceNow. That is, a parent CIT cannot be used to map its children CIs.
- **Limitation:** Since this adapter uses the ServiceNow Direct Web Services API, which does not support CI coalescing (reconciliation), if some CIs being pushed from UCMDB are already present in the ServiceNow CMDB, before the integration with UCMDB is installed, and if those CIs are (a) also in UCMDB; and (b) pushed into ServiceNow by the integration, those CIs are duplicated. (This is because UCMDB does not know these CIs are already in the ServiceNow CMDB.) After the adapter is installed, UCMDB keeps track of the CIs it pushes to ServiceNow, to prevent duplication.
- **Limitation:** ServiceNow Web Service Import Sets are currently not supported.

Population integration

- **Limitation:** Data replication in chunks is not supported.
- **Limitation:** Only full synchronization is supported (not delta synchronization).
- **Limitation:** Integration only works with Jython 2.5.3 and later.

Chapter 12: Storage Essentials (SE) Integration

This chapter includes:

Overview	155
Supported Versions	155
How to Perform the SE Integration	155
Storage Essentials Integration Packages	156
Adapter Parameters	156
Discovered CITs and Relationships	157
Node Details	159
SAN Topology	160
Storage Topology	161
Views	162
Storage Array Details	162
FC Switch Details	162
FC Switch Virtualization	163
Storage Pool Details	163
Host Storage Details	164
SAN External Storage	164
SAN Topology	165
Storage Topology	166
FC Port to FC Port	166
Impact Analysis Rules	167
FC Port to FC Port	167
FC Switch Devices to FC Switch	168
Host Devices to Host	168
Logical Volume to Logical Volume	169
Storage Array Devices to Storage Array	169
Reports	170
Storage Array Configuration	170
Host Configuration	170

Storage Array Dependency 171

Host Storage Dependency171

Storage Pool Configuration 171

Troubleshooting and Limitations 172

Overview

Integration involves synchronizing devices, topology, and the hierarchy of a customer storage infrastructure in the Universal CMDB database (CMDB). This enables Change Management and Impact Analysis across all business services mapped in UCMDB from a storage point of view.

You integrate SE with UCMDB using Data Flow Management (DFM).

When you activate the Storage Essentials integration, DFM retrieves data from the SE Oracle database and saves CIs to the Universal CMDB database. Users can then view SE storage infrastructure in UCMDB.

The data includes information on storage arrays, fibre channel switches, hosts (servers), storage fabrics, logical volumes, host bus adapters, storage controllers, and fibre channel ports. Integration also synchronizes physical relationships between the hardware, and logical relationships between logical volumes, storage zones, storage fabrics, and hardware devices.

Supported Versions

The integration procedure supports SE versions 6.x, 9.4, 9.41 and 9.5.

How to Perform the SE Integration

This task includes the steps to perform SE-UCMDB integration.

1. Prerequisites.

- a. Add the Storage Essentials server IP address to the DFP IP ranges.
- b. Define credentials for the SE database using the Generic DB Protocol.
- c. Run the **Range IPs by ICMP** job.
- d. Run the **Database TCP Ports** job.
- e. Run the **Oracle Database Connection by SQL** job.

2. Create a new integration point.

For details on running integration jobs, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

- a. Provide a name and description for the integration point.
- b. Under **Integration Properties > Adapter**, select the **Storage Essentials** adapter.
- c. Under **Adapter Properties > Data Flow Probe**, select the Data Flow Probe.

- d. Under **Adapter Properties > Trigger CI instance** select:
 - i. **Select Existing CI** (if you have a valid, existing CI). The **Select Existing CI** pane appears. Select the CI or
 - ii. **Create New CI** (if you need to create a new CI). The **Topology CI Creation Wizard** appears. Complete the creation of the CI using the Wizard.

Note: For details on the Topology CI Creation Wizard, see "Topology CI Creation Wizard" in the *HP Universal CMDB Data Flow Management Guide*.

- e. Verify the credentials for the chosen CI instance. Right-click **Trigger CI instance** and select **Actions > Edit Credentials Information**.
- f. Save the integration point.

3. **Run the HP Storage Essentials job.**

Storage Essentials Integration Packages

The integration includes two UCMDB packages:

- **SE_Discovery.zip**. Contains the trigger query for SE discovery, discovery script, adapter, and job.
- **Storage_Basic.zip**. Contains the new CI Type definitions, views, reports, and impact analysis rules. This package is common to all Storage Management integration solutions.

Tip: You can include the SE job in the DFM schedule.

For details, see "New Integration Job/Edit Integration Job Dialog Box" in the *HP Universal CMDB Data Flow Management Guide*.

Adapter Parameters

This job runs queries against Oracle materialized views that are installed and maintained by Storage Essentials in the Oracle database. The job uses a database CI as the trigger.

A switch or server in SE inherits from a Node CIT in UCMDB based on the following adapter parameters:

Parameter	Description
allowDNSLookp	<p>If a node in the SE database does not have an IP address but has a DNS name, it is possible to resolve the IP address by the DNS name.</p> <p>True: If a node does not have an IP address, an attempt is made to resolve the IP address by DNS name (if a DNS name is available).</p> <p>Default: False</p>
ignoreNodesWithoutIP	<p>Defines whether or not nodes in SE without IP addresses should be pulled into UCMDB.</p> <ul style="list-style-type: none">• True. Nodes without IPs are ignored.• False. A Node CI is created with an SE ID as the node key attribute. <div><p>Note: Setting this parameter to False may result in duplicate CIs in the CMDB.</p></div> <p>Default: True</p>
ignorePortsWithoutWWN	<p>If set to true, the integration ignores Fiber Channel Ports that do not have a WWN.</p> <p>Default: True</p>

Discovered CITs and Relationships

This section describes SE storage entities in UCMDB:

- **Fibre Channel Connect.** Represents a fibre channel connection between fibre channel ports.
- **Fibre Channel HBA.** Has change monitoring enabled on parameters such as state, status, version, firmware version, driver version, WWN, and serial number. A Fibre Channel HBA inherits from the Node Resource CIT.
- **Fibre Channel Port.** Has change monitoring enabled on parameters such as state, status, WWN, and trunked state. Since a Fibre Channel Port is a physical port on a switch, it inherits from the Physical Port CIT under the NodeElement Resource CIT.
- **Fibre Channel Switch.** Falls under the Node CIT because SE maintains an IP address for each switch. Parameters such as status, state, total/free/available ports, and version are change monitored.

This package retrieves Fibre Channel Switch details from the **mvc_switchsummaryvw** and **mvc_switchconfigvw** views. The job retrieves detailed information about Fibre Channel Ports on each switch from the **mvc_portsummaryvw** view.

- **Logical Volume.** Represents volumes on storage arrays and hosts with change monitoring on availability, total/free/available space, and storage capabilities.
- **Storage Array.** Represents a storage array with change monitoring on details such as serial number, version, and status. Since a storage array may not have a discoverable IP address, it inherits from the Network Device CIT.
- **NetApp Filer.** This is a specialized storage array from the NetApp application.


Both Storage Array and NetApp Filer CITs retrieve details from the **mvc_storagesystemsummaryvw** view. DFM retrieves detailed information on Storage Processors and HBAs from the **mvc_storageprocessorssummaryvw** and **mvc_cardsummaryvw** tables respectively.

The SE database may possibly not be able to obtain IP address information on storage arrays for a variety of technical and policy related reasons.

Since Fibre Channel Ports may be present on a storage array, Storage Processor, or HBA, DFM uses three separate queries to retrieve Fibre Channel Ports for each storage array. Detailed information about Fibre Channel Ports on each array is retrieved from the **mvc_portsummaryvw** view. Since this view uses a container ID as the key, DFM queries the view by container ID for each storage array, each Storage Processor on a storage array, and each HBA on a storage array.


DFM retrieves detailed information about Logical Volumes on each storage Array from the **mvc_storagevolumesummaryvw** view.

Results from these queries populate a map as shown below:



- **Storage Fabric.** Inherits from the Network Resource CIT and represents a storage fabric. This CIT has no change monitoring enabled.
- **Storage Processor.** Represents other storage devices such as SCSI controllers, and inherits from the Host Resource CIT. A Storage Processor CIT monitors change on parameters such as state, status, version, WWN, roles, power management, and serial number.
- **Storage Pool.** Storage Pool information is also collected from each storage array using the query below.

Results from this query populate a map as shown below:



Node Details

DFM retrieves Host details from the **mvc_hostsummaryvw** view and detailed information on HBAs from the **mvc_cardsummaryvw** view.

SE maintains information on Operating Systems, IP address, and DNS name on each host. DFM uses this information to create Node CIs (UNIX or Windows) and IPAddress CIs.


Since UCMDB uses the IP address of a node as part of its primary key, DFM attempts to use the IP address from SE for this purpose. If an IP address is not available, DFM then attempts to resolve

the hosts IP address using a DNS name. If neither an IP address nor a DNS name is available, DFM ignores the host (see ["Adapter Parameters" on page 156](#)).

Similar to Storage Arrays, a node may have Fibre Channel Ports directly associated with itself or on HBAs on the host. The DFM job uses three separate queries to retrieve Fibre Channel Ports for each host. The job retrieves detailed information about Fibre Channel Ports on each host from the **mvc_portsummaryvw** view. Since this view uses a ContainerID attribute as the key, the job queries the view by containerID for each host, and each HBA on a host.

Finally, DFM retrieves detailed information about Logical Volumes on each host from the **mvc_hostvolumesummaryvw** and **mvc_hostcapacityvw** views. The **mvc_hostcapacityvw** view maintains capacity information for each volume over multiple instances in time, and the job uses only the latest available information.


Results from these queries populate a map as shown below:



SAN Topology

SAN Topology consists of the Fibre Channel network topology and includes (fibre channel) connections between Fibre Channel Switches, Hosts, and Storage Arrays. SE maintains a list of WWNs that each Fibre Channel Port connects to, and this package uses this list of WWNs to establish Fibre Channel Connection links.


Results from these queries populate a map as shown below:



Storage Topology

Storage topology consists of relationships between Logical Volumes on a host and Logical Volumes on a Storage Array. DFM uses multiple tables to identify this relationship as shown in the query below. This view is a summary of all of the above information.

Results from these queries populate a map as shown below:




Views

The SE package contains views that display common storage topologies. These are basic views that can be customized to suit the integrated SE applications.

Storage Array Details


This view shows a Storage Array and its components including Logical Volumes, HBAs, Storage Processors, and Fibre Channel Ports. The view shows each component under its container Storage Array and groups Logical Volumes by CI Type.

Storage Array does not require all components in this view to be functional. Composition links stemming from the Storage Array have a cardinality of zero-to-many. The view may show Storage Arrays even when there are no Logical Volumes or Storage Processors.




FC Switch Details

This view shows a Fibre Channel Switch and all connected Fibre Channel Ports.




FC Switch Virtualization

FC Switch Virtualization consists of a physical switch or chassis, partitioned into multiple logical switches. Unlike Ethernet virtualization, physical ports are not shared among multiple virtual switches. Rather, each virtual switch is assigned one or more dedicated physical ports that are managed independently by the logical switches.




Storage Pool Details

This view shows Storage Pools with associated Storage Arrays and Logical Volumes.



Host Storage Details


This view shows only Hosts that contain a Fibre Channel HBA or a Logical Volume. This keeps the view storage-specific and prevents hosts discovered by other DFM jobs from being included in the view.



SAN External Storage


External storage configuration consists of a storage array presenting a logical volume that, in reality, belongs to another storage array. This is typically used in configurations where high-end, more expensive, front-end arrays present volumes from back-end, cheaper, storage to servers. The

goal of this type of virtualization is to virtualize multiple disk arrays from different vendors, scattered over the network, into a single monolithic storage device that can be managed uniformly.




SAN Topology

This view maps physical connections between Storage Arrays, Fibre Channel Switches, and Hosts. The view shows Fibre Channel Ports below their containers. The view groups the Fibre Channel Connect relationship CIT to prevent multiple relationships between the same nodes from appearing in the top layer.




Storage Topology

This view maps logical dependencies between Logical Volumes on Hosts and Logical Volumes on Storage Arrays. There is no folding in this view.



FC Port to FC Port

This rule propagates events on a Fibre Channel Port to another connected Channel Port.



Example of HBA crashing on a Storage Array:

- The event propagates from the HBA to the Storage Array and the Logical Volumes on the Array because of the Storage Devices to Storage Array rule.
- The impact analysis event on the Logical Volume then propagates to other dependent Logical Volumes through the Logical Volume to Logical Volume rule.
- Hosts using those dependent Logical volumes see the event next because of the Host Devices to Host rule.
- Depending on business needs, you define impact analysis rules to propagate events from these hosts to applications, business services, lines of business, and so on. This enables end-to-end mapping and impact analysis using UCMDB.

Impact Analysis Rules


This package contains basic impact analysis rules to enable impact analysis and root cause analysis in UCMDB. These impact analysis rules are templates for more complex rules that you can define based on business needs.

All impact analysis rules fully propagate both Change and Operation events. For details on impact analysis, see "Impact Analysis Manager Page" and "Impact Analysis Manager Overview" in the *HP Universal CMDB Modeling Guide*.

Note: Impact analysis events are not propagated to Fibre Channel Ports for performance reasons.


FC Port to FC Port

This impact analysis rule propagates events between related fiber channel ports.




FC Switch Devices to FC Switch

This impact analysis rule propagates events from a Fibre Channel Port to and from a Switch. The event is also propagated to the associated Storage Fabric.




Host Devices to Host

This impact analysis rule propagates events between Fibre Channel HBAs and Hosts, and Logical Volumes on the Host.




Logical Volume to Logical Volume

This impact analysis rule propagates events on a Logical Volume contained in a Storage Array to the dependent Logical Volume on the Host.



Storage Array Devices to Storage Array

This impact analysis rule propagates events between Logical Volumes, Storage Processors, Fibre Channel HBAs, and Storage Arrays.




Reports

The SE package contains basic reports that can be customized to suit the integrated SE applications.

In addition to the system reports, Change Monitoring and Asset Data parameters are set on each CIT in this package, to enable Change and Asset Reports in Universal CMDB. For details see "[Storage Array Configuration](#)" below, "[Host Configuration](#)" below, "[Storage Array Dependency](#)" on the next page, and "[Host Storage Dependency](#)" on the next page.


Storage Array Configuration

This report shows detailed information on Storage Arrays and its sub-components including Fibre Channel Ports, Fibre Channel Arrays, and Storage Processors. The report lists Storage Arrays with sub-components as children of the Array.




Host Configuration

This report shows detailed information on hosts that contain one or more Fibre Channel HBAs, Fibre Channel Ports, or Logical volumes. The report lists hosts with sub-components as children of the host.




Storage Array Dependency

This report maps dependencies on a Storage Array. The report also displays information on switches connected to it.




Host Storage Dependency

This report shows detailed information on storage infrastructure dependencies of a Host. The report lists hosts and dependent components.



Storage Pool Configuration

This report shows detailed information on Storage Pool configuration.



Troubleshooting and Limitations

This section describes troubleshooting and limitations of Storage Essentials Integration.

- **Problem:** If the SE system has duplicate entries for nodes, switches or arrays, the job produces the following error message: "**Process validator error: multiple updates in bulk...**".

Solution: This is expected behavior and does not affect population of valid CIs into UCMDB. To prevent this error message, duplicates must be removed from the SE system.

- **Error message:** "Please use the SE database with SID 'REPORT' for this integration."

Solution: For integration with SE 9.4 or higher, you should configure the integration point for a REPORT database instance (and not for an APPIQ instance as applied for SE versions up to and including 6.3).

- **Limitation:** The credentials used for integration with SE should have access to the relevant materialized view status table as detailed below:

Storage Essentials	Materialized View Status Table
Version 6.03 and earlier	appiq_system.mview_status
Later than Version 6.03 and earlier than Version 6.1	appiq_system.mviewcore_status and appiq_system.mview_status
Later than Version 6.1 and earlier than Version 9.4	appiq_system.mview_module_status
Version 9.4 and later	appiq_system.mv_report_user_status

- **Limitation:** If the discovery does not find a valid IP address and serial number for a VMWare ESX server in the HP Storage Essentials database, that VMWare ESX server is not reported to UCMDB.

Chapter 13: Troux Integration

This chapter includes:

- Overview174
- Integration Overview 174
- Supported Versions 175
- Use Cases175
- How to Work with the Troux Push Adapter175
- How to Run a Troux Population Job 181

Overview

Troux is a vendor in the EA (Enterprise Architecture) tools market. EA tools allow business users to understand the gaps between business demands and initiatives. Reviewing how your fixed budget aligns to business capabilities and how your discretionary spending is allocated across initiatives. Future-state scenario investigation can be accomplished prior to locking down your roadmap.

Although many use cases can be achieved using EA tools, two specific use cases were chosen for the UCMDB-Troux integration. This does not preclude additional use cases in the future.


Depending on the use case, a provider of record is determined. For example, UCMDB would be the provider of record for inventory information such as the server operating system, server hardware, database, and other infrastructure CIs. Troux on the other hand provides component lifecycles for server operating system, server hardware, and database versions.

Integration Overview

UCMDB-Troux integration consists of two independent, bi-directional parts: the **Troux Push Adapter**, and the **Troux Population Adapter**.

- The Troux Push Adapter in UCMDB replicates CIs and relationships to Troux. The Troux Push Adapter is necessary to achieve both the Technology Standards Assessment and Business Impact Analysis use cases discussed in the introduction above. The adapter also allows the user to push to Troux CIs that are aged out of UCMDB or deleted.
- The Troux Population Adapter pulls CIs and relationships from Troux to UCMDB. It is necessary only for the Business Impact Analysis use-case.

Data transfer occurs using XML files between configured directories. Mapping files are used to apply conversion from TUX format to UCMDB and vice versa.



Supported Versions

Supported versions of the products are listed below.

Target Platform	DFM Protocol	UCMDB Version
Troux 9.x	None	9.02 and later

Use Cases

The use cases chosen for UCMDB-Troux integration are:

- **Technology Standards Assessment.** The ability to look at a lifecycle of software products to determine viability within an enterprise.
- **Business Impact Analysis.** Definition of the definitive source of application CIs to align IT with business. These application CIs in Troux are related to server operating system, server hardware, database, and other CIs discovered by UCMDB. Impact Analysis can be determined using application, business function, and organization for planned change or unplanned disruption of service.

How to Work with the Troux Push Adapter

This adapter allows replication of CIs and links from UCMDB to Troux. This is accomplished by definition of queries and mapping files that define the CIs to be transferred and the naming/mapping

of CIs and attributes to Troux components. This adapter also allows the user to push to Troux CIs that are aged out of UCMDB or deleted.

This task includes the following steps:

Define queries

1. Create a query that defines the CIs and attributes you want to replicate to Troux. Two example queries are supplied in the **Integration > Troux** folder.

For details, see "Topology Query Language" in the *HP Universal CMDB Modeling Guide*.

2. Define the properties of each of the CITs.


Note: This step is critical to the operation of the push adapter. You must define the attributes that will be transferred to Troux.

For details, see "Query Node/Relationship Properties Dialog Box" in the *HP Universal CMDB Modeling Guide*.

- a. Define the criteria for the Query Node properties
- b. Define the advanced properties for each of the attributes.
- c. Select attributes to be transferred to Troux.

Example: Computers_for_Troux

In this example, the query requests UCMDB to send all computers with installed software to Troux. You must define the mapping file with the same name as the query in order for the push adapter to recognize the query.



Create mapping files

A mapping file is the translation template that defines the CITs and the relationships to be converted from UCMDB to Troux. For the push adapter to create output, this mapping file must have definitions for the attributes and CITs or relationships for export. The mapping file is located in:


UCMDB\UCMDBServer\runtime\fcmdb\CodeBase\<adapter>\mappings

where <adapter> is the name of the adapter.

The example mapping file and query (Servers_with_Software) included with the content package sends Windows computers with installed software to Troux, as expected by Troux. If your environment uses different CIs with Troux, make sure Troux handles those component types.

When you create the mapping file, give it exactly the same name as your query. For details about the mapping file options, see "Prepare the Mapping Files" in the *HP Universal CMDB Developer Reference Guide*. Use the example mapping files as reference examples for the mapping file creation.

Note: The definitions in the mapping file (<adapter>.xml) must be the direct CITs and relationships to be transferred to Troux. The mapping does not support inheritance of class types. For example, if the query is transferring nt CITs, the mapping file must have definitions for nt CITs, and not for general nodes or computers. That is, the definition must be an exact match for what to transfer.




Example

```
<integration>
  <info>
    <source name="UCMDB" versions="9.0" vendor="HP" />
    <target name="Troux" versions="9.0" vendor="Troux" />
  </info>
  <targetcis>
    <!-- UCMDB computers to Troux Server -->
    <source_ci_type name="nt" namespace="" query="">
      <apioutputseq>1</apioutputseq>
      <target_ci_type name="Server">
        <targetprimarykey>
          <pkey>name</pkey>
        </targetprimarykey>
        <target_attribute name="action" datatype="char" >
          <map type="constant" value="find" />
        </target_attribute>
        <target_attribute name="name" datatype="char" >
          <map type="direct" source_attribute="name" />
        </target_attribute>
        <target_attribute name="External ID" datatype="char" >
          <map type="direct" source_attribute="id" />
        </target_attribute>
        <target_attribute name="description" datatype="char" >
          <map type="direct" source_attribute="discovered_os_name" />
        </target_attribute>
      </target_ci_type>
    </source_ci_type>
    <!-- UCMDB Installed Software to Troux Software Module -->
    <source_ci_type name="installed software" namespace="" merge="">
```

Create an integration point

This section describes how to create and run the job that replicates the data from UCMDB to Troux.

1. In UCMDB, navigate to **Data Flow Management > Integration Studio**.
2. Click the **New Integration Point** button to open the new integration point Dialog Box.
 - a. Click  , select the **Data Push into Troux** adapter and click **OK**.
 - b. Enter the following information:

Name	Description
Integration Name	The name you give to the integration point.

Name	Description
Is Integration Activated	Select this check box to create an active integration point. You clear the check box if you want to deactivate an integration, for instance, to set up an integration point without actually connecting to a remote machine.
allowedComponentstodelete	The name of the component which is to be deleted and pushed to Troux. The default is Server . UCMDB is the system of record for servers. The default value of Server is important to note because the Troux system model may not allow deletion of other CITs. If you modify this property, you must verify (a) the mapping file is setup correctly to send the deleted CIT to Troux, and (b) Troux is setup to handle the delete for the CIT you specify. Deletion of Server is the only OOTB CIT that has been verified.
Data Flow Probe	The name of the Data Flow Probe.
TUX path	The location of the TUX output file (created when the integration job is run).

- c. Click **Test connection** to verify the connectivity, and click **OK**. If the connection fails, verify the provided information is correct.

Define an integration job


You use the Integration tab to define a job that uses the integration point that you just defined. For details, see "New Integration Job/Edit Integration Job Dialog Box" in the *HP Universal CMDB Data Flow Management Guide*.

1. Select the queries that you defined in ["Define queries" on page 176](#).
2. To enable deletion, select the **Allow Deletion** check box. This is a master delete **on/off** flag for the job that turns on and off the capability to send deletes.

Note: Deleted CITs are pushed depending on the changes to them in UCMDB. For example, if UCMDB discovers a computer, and that computer is deleted in UCMDB, this indicates a change of a deleted computer. And if this computer is part of the push query for Troux, with delete enabled, a delete is pushed to Troux the next time the push job is run.

3. Specify the job's schedule.
4. Click **OK**.
5. In the Integration Point pane, click **Save**. A full data push job will run according to schedule.

The Troux output file (TUX) is generated in the path that you specified in the Integration Properties for the job.

Note: To run the job again, click .

How to Run a Troux Population Job

This task has the following steps:

Prerequisite - Create a mapping file

Create a mapping file that enables mapping of Troux components and relationships to UCMDB CITs and relationships.


The top section of the file defines the object or CIT mapping from Troux to UCMDB. The lower section defines the relationship mapping.

The out-of-the-box mapping file, **Troux_to_UCMDB.xml** (located in **\DataFlowProbe\runtime\probeManager\discoveryResources\TQLEXP\Troux\data**) contains the typical definitions for mapping the components and CITs with relationships.



```
<integration>
  <info>
    <source name="Troux" versions="9.0" vendor="Troux" />
    <target name="UCMDB" versions="9.0" vendor="HP" />
  </info>
  <targetcis>
    <!-- Troux Application -> UCMDB Application -->
    <source_ci_type name="Application" namespace="" query="">
      <apioutputseq>1</apioutputseq>
      <target_ci_type name="business_application">
        <targetprimarykey>
          <pkey>name</pkey>
        </targetprimarykey>
        <target_attribute name="name" datatype="StrProp" >
          <map type="direct" source_attribute="name" />
        </target_attribute>
        <target_attribute name="data_externalid" datatype="StrProp" >
          <map type="direct" source_attribute="uuid" />
        </target_attribute>
        <target_attribute name="data_origin" datatype="StrProp" >
          <map type="direct" source_attribute="extalias" />
        </target_attribute>
      </target_ci_type>
    </source_ci_type>
    <!-- Troux Person -> UCMDB Person -->
    <source_ci_type name="Person" namespace="" query="">
      <apioutputseq>1</apioutputseq>
      <target_ci_type name="person">
        <targetprimarykey>
          <pkey>given_name</pkey>
        </targetprimarykey>
        <target_attribute name="name" datatype="StrProp" >
          <map type="direct" source_attribute="name" />
        </target_attribute>
      </target_ci_type>
    </source_ci_type>
  </targetcis>
</integration>
```

Component to CIT map



Run the job

Note: For details on running an integration job, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

In the Integration Studio, create a new integration point.

1. Provide a name and description for the integration point.
2. Under **Integration Properties > Adapter**, select the **Population from Troux** adapter.
3. Edit the **TUX path** field, if required; this sets the location of the TUX output file.
4. Under **Adapter Properties > Data Flow Probe**, select the Data Flow Probe.
5. Under **Adapter Properties > Trigger CI instance** select:
 - a. **Select Existing CI** (if you have a valid, existing CI). The **Select Existing CI** pane appears. Select the CI or
 - b. **Create New CI** (if you need to create a new CI). The **Topology CI Creation Wizard** appears. Complete the creation of the CI using the Wizard.

Note: For details on the Topology CI Creation Wizard, see "Topology CI Creation Wizard" in the *HP Universal CMDB Data Flow Management Guide*.

6. Save the integration point.
7. Run the job.

Chapter 14: UCMDB to XML Adapter

This chapter includes:

Overview	184
Integration Mechanism	184
How to Export UCMDB to XML	184
Adapter	185
Troubleshooting and Limitations	186

Overview

By using the UCMDB to XML adapter, it is possible to export the results (CIs and relationships) of TQL queries and convert these to XML files.

Integration Mechanism

After defining an integration point with the UCMDB to XML adapter, TQL queries can be added to the jobs of that integration point.

The adapter exports the result of the TQL queries into XML format, and creates XML files in the Export Directory (as predefined in the integration point).

How to Export UCMDB to XML

1. Prerequisite - General

- a. Create a directory on the UCMDB data flow probe system to which the adapter will write the exported XML files.
- b. In the Modeling Studio, create integration TQL queries for the data to be exported to XML. Ensure the queries return valid results.

2. Prerequisite - Create an integration point and integration job


In the Integration Studio, create a new integration point.

- a. Provide a name and description for the integration point.
- b. Under **Integration Properties > Adapter**, select **UCMDB to XML** adapter.
- c. Under **Adapter Properties > Export Directory** type an absolute path of the directory on the probe system where the adapter should export the XML files to.
- d. Under **Adapter Properties > Data Flow Probe Name**, select the name of the Data Flow Probe to be used.
- e. Click the **Test Connection** button to ensure the adapter can validate the defined export directory.
- f. Save the integration point.
- g. Under **Integration Jobs** add a new integration job. Edit the job to add integration queries under the job's definition.

For details on integration points, see **Integration Studio > Work with Data Push Jobs > Create an integration point** in the *HP Universal CMDB Data Flow Management Guide*.

- h. Click **OK** to save the integration job.
- i. Click the **Save** button to save the integration point.

3. Run the job

- a. To run the job ad hoc, select the integration job and click the  button. The job can also be configured to run on a schedule.
- b. Check the defined export directory on the probe system for the exported XML data, to ensure the queries create valid XML files.

Note: The XML files have time stamps in the format **YYMMDDHHMMSSZZZ**. If the integration query returns a large number of CIs, the export is by chunks of 1,000 CIs. Each chunk is a separate XML file, with the file for the last chunk having the string **EOD** (end of data) appended to it.

For details on running an integration job, see "Integration Studio" in the *HP Universal CMDB Data Flow Management Guide*.

Adapter

This job uses the adapter **UCMDB to XML** (XmlPushAdapter).

Used Script

pushToXml.py

Parameters

Parameter	Description
Export Directory	The absolute path (on the probe system) of the directory where the XML files will be exported to.
probeName	The name of the data flow probe to be used.

Troubleshooting and Limitations

Problem: UCMDB to XML discovery fails with a timeout exception, with the following error in Data Flow Probe logs:

```
com.mysql.jdbc.PacketTooBigException: Packet for query is too large (14070323 > 10485760). You can change this value on the server by setting the max_allowed_packet' variable.
```

- **Cause of problem:** There is not enough DFM probe resources to export a large amount of CIs/relationships.

- **Solution #1:**

Decrease the **replication.chunk.size** setting for the XmlPushAdapter, as follows:

- a. In UCMDB, go to **Data Flow Management > Adapter Management**.
- b. In the list of resources, go **XMLExportAdapter > Adapters > XmlPushAdapter**.
- c. Right-click on **XmlPushAdapter** and choose **Edit Adapter source** from the pop-up menu.
- d. In the XML Editor that opens, find the adapter setting **replication.chunk.size** and decrease the from the current value. For example, if **replication.chunk.size** is currently 1000, you can decrease it to 100 as follows:

```
<adapter-settings>  
  <adapter-setting name="replication.chunk.size">1000</adapter-setting>  
</adapter-settings>
```

and decrease the chunk size. For example:

```
<adapter-settings>  
  <adapter-setting name="replication.chunk.size">100</adapter-setting>  
</adapter-settings>
```

- e. Click **Save**, and rerun the integration point.

- **Solution #2:**

Instead of one large integration job, create a few smaller jobs. To do this, create a few export TQL queries that will cover all the CIs to export and will be the basis of the smaller integration jobs.