

HP OpenView Smart Plug-in for UNIX® Operating Systems

Installation Guide

Version: A.03.10

For HP-UX and Solaris OpenView Operations Management Servers



Manufacturing Part Number: None

October 2004

© Copyright 2004 Hewlett-Packard Development Company, L.P.

Legal Notices

Warranty.

Hewlett-Packard makes no warranty of any kind with regard to this manual, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. Hewlett-Packard shall not be held liable for errors contained herein or direct, indirect, special, incidental or consequential damages in connection with the furnishing, performance, or use of this material.

A copy of the specific warranty terms applicable to your Hewlett-Packard product can be obtained from your local Sales and Service Office.

Restricted Rights Legend.

Use, duplication or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause in DFARS 252.227-7013.

Hewlett-Packard Company
United States of America

Rights for non-DOD U.S. Government Departments and Agencies are as set forth in FAR 52.227-19(c)(1,2).

Copyright Notices.

©Copyright 2004 Hewlett-Packard Development Company, L.P.,

No part of this document may be copied, reproduced, or translated to another language without the prior written consent of Hewlett-Packard Company. The information contained in this material is subject to change without notice.

Trademark Notices.

Windows® and MS Windows ® are U.S. registered trademarks of Microsoft Corporation.

Microsoft® is a U.S. registered trademark of Microsoft Corporation.

UNIX® ia a registered trademark of The Open Group.

All other product names are the property of their respective trademark or service mark holders and are hereby acknowledged.

1. Installing the OSSPI

| | |
|-----------------------------------|----|
| Upgrading the OSSPI | 9 |
| Installing the OSSPI | 10 |
| Using the Installer Scripts | 10 |
| Unattended Installation | 10 |
| Using the SD Installer | 12 |

2. Verifying Installation of the OSSPI

| | |
|--|----|
| Software Bundles | 17 |
| Verifying Installation of the OSSPI Software | 19 |
| Installed File Locations | 22 |

3. Uninstalling the OSSPI

| | |
|---|----|
| In this Section | 26 |
| Removing the OSSPI from the Managed Node | 27 |
| Removing the OSSPI from the Management Server | 29 |

Contents

Support

Please visit the HP OpenView web site at:

<http://www.managementsoftware.hp.com/>

This web site provides contact information and details about the products, services, and support that HP OpenView offers.


You can also go directly to the support web site at:


<http://support.openview.hp.com/>


HP OpenView online software support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valuable support customer, you can benefit by using the support site to:

- Search for knowledge documents of interest
- Submit and track progress on support cases
- Manage a support contract
- Look up HP support contacts
- Review information about available services
- Enter discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and log in. Throughout the site, access levels are indicated by the following icons:

 HP Passport

 Active contract

 Premium contract

To find more information about access levels, go to the following URL:

http://support.openview.hp.com/access_level.jsp

To register for an HP Passport ID, go to the following URL:

<https://passport.hp.com/hpp2/newuser.do>

1 **Installing the OSSPI**

You can install the Smart Plug-in for UNIX Operating Systems (OSSPI) on HP OpenView Operations (OVO) 7.x and 8.10 management servers. The procedure for upgrading an earlier version of OSSPI, and installing OSSPI on both versions of OVO is described in the following sections.

The management server versions, the managed node operating system versions, and the performance product versions that are supported by OSSPI are listed in the *HP OpenView Smart Plug-in for UNIX Operating Systems Release Notes*. Before you proceed with the installation of OSSPI, make sure that supported versions are installed on your setup.

Upgrading the OSSPI

You can upgrade an earlier version of OSSPI to this version, by uninstalling the previous version and installing the new version. If you have customized any components of the earlier version of OSSPI, and wish to retain it, follow the procedure given below:

1. Make a copy of the customized components with a unique name (for example, add "-" at the end for each name).
2. Uninstall the previous version of OSSPI.
3. Install the new version of OSSPI.
4. Repeat the modification on the components installed with the new version of OSSPI.

Backup the components by copying and downloading the configuration. Refer to *HP OpenView Operations Administrator's Reference Volume I* for more information on copying and downloading configuration. Once you install the new version of OSSPI, you can upload the downloaded data (with changed names) and refer to them for customizing the new components.

Installing the OSSPI

You can choose to install the Smart Plug-in for UNIX Operating Systems either by invoking the installer scripts or by launching the HP-UX SD installer (`swinstall`). See the sections below for installing OSSPI using either of these options.

Using the Installer Scripts

You can choose to install the Smart Plug-in for UNIX Operating Systems software on the OVO 8.10 management server during the OVO installation procedure. You will be prompted to mount the HP OpenView Smart Plug-in CD-ROM. Mount the CD-ROM and follow the instructions.

If you choose to install the Smart Plug-in for UNIX Operating Systems later, do the following:

Step 1. Log on to the OVO management server as `root` user.

Step 2. Set the `LANG` variable as appropriate for the environment.

If the database is configured for the Japanese character set, Japanese templates of OSSPI are uploaded on the management server.

Step 3. Mount the HP OpenView Smart Plug-in CD-ROM. Use the CD that contains the OSSPI management server installation packages (HP OpenView Smart Plug-ins for *OVO/UNIX*). Refer to the *HP OpenView Smart Plug-ins for OVO/UNIX Release Notes* for more information.

Step 4. Set the environment variable `OSSPI_INSTALLER_HOME` to the installables' directory, `/<mount_point>/OV_DEPOT`

Step 5. Type the following:

```
/<mount_point>/OV_DEPOT/UNIXOSSPI/unix_osspi_setup
```

You will be prompted to select the components you want to install. Installation will proceed based on the options you select.

Unattended Installation

You can configure OSSPI to be installed in the unattended mode, where the install script will not prompt you for input.

To install OSSPI in the unattended mode, follow the procedure, from Step 1 through 4, detailed in “Using the Installer Scripts” on page 10. Then type the following command:

```
<mount_point>/OV_DEPOT/UNIXOSSPI/unix_osspi_setup
-unattended
```

This command will install the OSSPI sub-products on your system. To selectively install the OSSPI sub-products, edit the configuration file, /var/opt/OV/installation/osspi_install.defaults. You can refer to the sample configuration file, /var/opt/OV/installation/osspi_install.defaults.sample, as illustrated in Example 1-1, for the format of osspi_install.defaults.

Example 1-1 The osspi_install.defaults.sample file

```
#####
# The contents of the file osspi_install.defaults under /var/opt/ov/installation
# define what subproducts are installed when you select the unattended mode of
# installation for UNIX OS SPI. This sample file specifies the format of the file
# osspi_install.defaults.
#
# List down the subproducts you want to install in osspi_install.defaults
# in the directory /var/opt/ov/installation.
#
# The following rules must be followed while listing the subproducts to be
# installed:
#
# 1) Either SPI-OSUX-OVO.CORE-OSUX-SOL or SPI-OSUX-OVO.CORE-OSUX-HP must be
# installed, depending on whether the the management server is on Solaris or
# HP-UX respectively. Both the subproducts cannot be installed on the same
# management server
#
# 2) If you are installing the SPI-OSUX-OVO.SCS-OSUX-SOL subproduct,
# then SPI-OSUX-OVO.AGT-OSUX-SOL must also be installed
#
# 3) If you are installing the SPI-OSUX-OVO.VCS-OSUX-SOL subproduct,
# then both SPI-OSUX-OVO.AGT-OSUX-SOL and SPI-OSUX-OVO.AGT-OSUX-HP must also
# be installed
#
# 4) If you are installing the SPI-OSUX-OVO.SG-OSUX-HP subproduct, then the
# SPI-OSUX-OVO.AGT-OSUX-HP subproduct must also be installed
#####

SPI-OSUX-OVO.CORE-OSUX-SOL
SPI-OSUX-OVO.CORE-OSUX-HP
SPI-OSUX-OVO.DOC-OSUX-SOL
SPI-OSUX-OVO.DOC-OSUX-HP
SPI-OSUX-OVO.AGT-OSUX-HP
SPI-OSUX-OVO.AGT-OSUX-SOL
SPI-OSUX-OVO.AGT-OSUX-LNX
SPI-OSUX-OVO.AGT-OSUX-AIX
SPI-OSUX-OVO.AGT-OSUX-TRU64
SPI-OSUX-OVO.VCS-OSUX-SOL
SPI-OSUX-OVO.SCS-OSUX-SOL
SPI-OSUX-OVO.SG-OSUX-HP
```

The file `osspi_install.defaults` is created when OSSPI is first installed on your system. Once created, this file lists all the OSSPI sub-products installed on the OVO management server. To replicate the existing OSSPI setup on other OVO installations, place `osspi_install.defaults` on the target management server. Place the file in the directory `/var/opt/OV/installation/` and run the `unix_osspi_setup` script with the `-unattended` option.

For a custom unattended install, remove or add the names of OSSPI subproducts to the subproduct list in the file.

Using the SD Installer

To install the Smart Plug-in for UNIX Operating Systems software bundle on the OVO 7.x management server, do the following:

Step 1. Log on to the OVO management server as `root` user.

Step 2. Set the `LANG` variable in the environment.

If the database is configured for the Japanese character set, Japanese templates of OSSPI are uploaded on the management server.

Step 3. Mount the HP OpenView Smart Plug-in CD-ROM. Use the CD that contains the management server installation packages (HP OpenView Smart Plug-ins for OVO/*UNIX*). Refer to the *HP OpenView Smart Plug-ins for OVO / UNIX Release Notes* for more information.

Step 4. Use `swinstall` to install the OSSPI subproducts. Refer to the *HP OpenView Smart Plug-ins for OVO / UNIX Release Notes* for more information about product locations and valid platform names.

HP-UX (*not* part of an MC/ServiceGuard cluster)

On an HP-UX system, use the `swinstall` graphical user interface:

1. Type the following: `/usr/sbin/swinstall -s\
/<mount_point>/OV_DEPOT/<platform>.sdtape`

The SD Install - Software Selection window appears.

2. Highlight SPI-OSUX-OVO.
3. Select Actions: Mark for Install from the menu bar.
4. Select Actions: Install (Analysis) from the menu bar.
5. Verify that the analysis phase of the installation completes without errors by clicking on **Logfile**. This displays the `/var/adm/sw/swagent.log` log file. Correct any errors that appear.
6. Click on **OK** to continue with the installation.
7. Exit `swinstall` after the installation completes.

Or on an HP-UX system, use the command line:

1. Type the following: `/usr/sbin/swinstall -s\
/<mount_point>/OV_DEPOT/<platform>.sdtape SPI-OSUX-OVO`
2. Check the `/var/adm/sw/swagent.log` log file and correct any errors that appear.

HP-UX (part of an MC/ServiceGuard cluster)

On the *active* node in the MC/ServiceGuard Cluster (the node on which the OVO management server is running), use the command line:

1. Type the following: `/usr/sbin/swinstall -s\
/<mount_point>/OV_DEPOT/<platform>.sdtape\
SPI-OSUX-OVO`
2. Check the `/var/adm/sw/swagent.log` log file for any errors.

On each of the *inactive* nodes in the MC/ServiceGuard Cluster (the nodes on which the OVO management server is *not* running), use the command line:

1. Type the following: `/usr/sbin/swinstall -s\
/<mount_point>/OV_DEPOT/<platform>.sdtape\s
SPI-OSUX-OVO.SPI-OS-SRV-HP11`
2. Check the `/var/adm/sw/swagent.log` log file and correct any errors that appear.

Please refer to Appendix A, About MC/ServiceGuard of the *HP OpenView VantagePoint Operations Administrator's Reference* for information on MC/ServiceGuard.

Solaris

On a Solaris system, use the command line:

1. Type the following: `/usr/sbin/swinstall -s\
/<mount_point>/OV_DEPOT/SOLARIS.sdtape SPI-OSUX-OVO`

The `swinstall` application is installed with OVO (`swinstall` is also referred to as SD or Software Distributor).

2. Check the `/var/adm/sw/swagent.log` log file for any errors.

2

Verifying Installation of the OSSPI

This chapter provides information that is designed to help you verify the installation of the OSSPI software. You can find information on the

following topics:

- “Software Bundles” on page 17
- “Verifying Installation of the OSSPI Software” on page 19
- “Installed File Locations” on page 22

Software Bundles

The following tables list the bundles, products, and filesets that make up the OSSPI and explain what the contents are. Table 2-1 shows the contents of the Smart Plug-in for UNIX Operating Systems software depot (SD) file set.

Table 2-1 The OSSPI Software Depot (SD)

| Software Depot | Description |
|----------------|---|
| SPI-OSUX-OVO | OSSPI server software – contains everything necessary to run the OSSPI for HP-UX and Solaris (executables, shell scripts, etc.) |

Table 2-2 describes the contents of the Smart Plug-in for UNIX Operating Systems server and agent sub-products.

Table 2-2 The OSSPI Server and Agent Sub-products

| Sub-product | Contents |
|----------------|---|
| AGT-OSUX-AIX | OSSPI agent filesets for AIX |
| AGT-OSUX-HP | OSSPI agent filesets for HP-UX |
| AGT-OSUX-LNX | OSSPI agent filesets for Linux |
| AGT-OSUX-SOL | OSSPI agent filesets for Solaris |
| AGT-OSUX-TRU64 | OSSPI agent filesets for Tru64 UNIX |
| CORE-OSUX-HP | Core OSSPI agent filesets |
| DOC-OSUX-HP | OSSPI documentation |
| SCS-OSUX-SOL | OSSPI filesets for Sun cluster on Solaris |
| SG-OSUX-HP | OSSPI filesets for MC/ServiceGuard on HP-UX |
| VCS-OSUX-SOL | OSSPI filesets for VERITAS cluster on HP-UX and Solaris |

Table 2-3 describes the contents of the Smart Plug-in for UNIX Operating Systems server and agent filesets.

Table 2-3 The OSSPI Server and Agent File Sets

| SD File Set | Contents |
|------------------------------|--|
| SPI-OS-AGT-AIX | OSSPI agent files for AIX |
| SPI-OS-CORE | Core OSSPI agent files |
| SPI-OS-AGT-HP | OSSPI agent files for HP-UX |
| SPI-OS-AGT-LNX | OSSPI agent files for Linux |
| SPI-OS-AGT-SOL | OSSPI agent files for Solaris |
| SPI-OS-AGT-TRU64 | OSSPI agent files for Tru64 UNIX |
| SPI-OS-SRV-HP11 ^a | OSSPI management server files for HP-UX |
| SPI-OS-SRV-SOL ^b | OSSPI management server files for Solaris |
| SPI-OS-DOC | OSSPI documentation |
| SPI-OS-SCS-SOL | OSSPI Sun cluster files for Solaris |
| SPI-OS-SG-HP | OSSPI MCSG files for HP-UX |
| SPI-OS-VCS-SOL | OSSPI VERITAS Cluster Server files for Solaris |
| SPI-OS-VxVM-HP | OSSPI VERITAS Volume Manager files for HP-UX |
| SPI-OS-VxVM-SOL | OSSPI VERITAS Volume Manager files for Solaris |

a. present only on HP-UX management server

b. present only in Solaris management server

Verifying Installation of the OSSPI Software

To verify that the installation of the Smart Plug-in for UNIX Operating Systems completed successfully on the OVO management server, carry out the steps in the following list:

1. On the command line, enter: `swlist`, and look for one of the following entries in the output displayed

```
SPI-OSUX-OVO A.03.00
```

2. In the OVO GUI, check that the following elements have been added to the respective windows:

Application Groups:

Unix OS SPI, containing:

- OSSPI Discovery
- OSSPI Supportability
- AIX
- HP-UX
- Linux
- Solaris
- Tru64
- HP Performance Products
- Sun Cluster Applications
- Veritas

Message Groups:

OSSPI-FS
OSSPI-Internal
OSSPI-Kernel
OSSPI-Services

Message-Source Templates:

Operating System SPIs,
containing:

- IBM AIX
- HP UX

Node Groups:

- Linux
 - Sun Solaris
 - Tru64 UNIX
- OSSPI-AIX

OSSPI-Discovery

OSSPI-HPUX

OSSPI-Linux

OSSPI-Removal

OSSPI-Solaris

OSSPI-Tru64

User Profiles:

AIX Admin

AIX Operator

HPUX Admin

HPUX Operator

Linux Admin

Linux Operator

Solaris Admin

Solaris Operator

Tru64 Admin

Tru64 Operator

Veritas Admin

Veritas Operator

Sun Cluster Admin

Sun Cluster Operator

Supportability

Performance

Janitor

3. If any of these steps fails to produce the desired results, use the `swverify` command to ensure that all rules and dependencies were applied during the installation of the OSSPI software. Enter:

```
swverify -x autoselect_dependencies=false SPI-OSUX-OVO
```

- a. Check the following log files for more specific information relating to installation problems:
 - `/var/adm/sw/swagent.log`
 - `/var/adm/sw/swinstall.log`
- b. Check your installation with the details in Table 2-4, “OSSPI File Locations on the OVO Management Server,” on page 22.

Installed File Locations

The installation process copies the necessary files to the OVO management server. Table 2-4 shows the directories that the installation process creates on the OVO 8.10 management server for the OSSPI server.

Table 2-4 OSSPI File Locations on the OVO Management Server

| File Type | Directory Location |
|-----------------------|--|
| Binaries | /opt/OV/lbin/osspi/ |
| Documentation | /opt/OV/doc/C/osspi/ |
| Log files | /var/opt/OV/share/osspi/log/ |
| Temporary and Runtime | /var/opt/OV/share/osspi/tmp/ |
| OVO integration | /var/opt/OV/share/tmp/OpC_appl/ |
| - AIX: | /var/opt/OV/share/tmp/OpC_appl/unix_osspi_appl/osspi_AIX |
| - Core: | pl/osspi_AIX |
| - HP-UX: | /var/opt/OV/share/tmp/OpC_appl/unix_osspi_appl/osspi_CORE |
| - Linux: | pl/osspi_CORE |
| - Solaris: | /var/opt/OV/share/tmp/OpC_appl/unix_osspi_appl/osspi_HPUX |
| - Tru64: | pl/osspi_HPUX |
| - Bitmaps: | /var/opt/OV/share/tmp/OpC_appl/unix_osspi_appl/osspi_LINUX |
| | /var/opt/OV/share/tmp/OpC_appl/unix_osspi_appl/osspi_SOLARIS |
| | /var/opt/OV/share/tmp/OpC_appl/unix_osspi_appl/osspi_TRU64 |
| | /etc/opt/OV/share/symbols/C/OSSPI |

Table 2-5 and Table 2-6 show the directory locations for the installed OSSPI files on an OVO 8.10 managed node. These are the standard locations for OVO commands, actions, and monitors on DCE and HTTPS agents respectively.

Table 2-5 OSSPI File Locations for the OVO Managed Node on DCE Agents

| File Type | OS | Directory Location |
|---------------------------|---|---------------------------|
| Binaries | AIX | /var/lpp/OV/OpC/ |
| | HP-UX, Linux, Solaris, Tru64 UNIX | /var/opt/OV/bin/OpC/ |
| Default Configuration | AIX | /var/lpp/OV/conf/ossapi/ |
| | HP-UX, Linux, Solaris, Tru64 UNIX | /var/opt/OV/conf/ossapi/ |
| Configuration & Discovery | AIX | /usr/lpp/OV/conf/ossapi/ |
| | HP-UX, Linux, Solaris, Tru64 UNIX | /var/opt/OV/conf/ossapi/ |
| Logs | AIX | /var/lpp/OV/log/ossapi/ |
| | HP-UX, Linux, Solaris, Tru64 UNIX | /var/opt/OV/log/ossapi/ |

Table 2-5 OSSPI File Locations for the OVO Managed Node on DCE Agents

| File Type | OS | Directory Location |
|---------------------|---|---------------------------|
| Temporary & Runtime | AIX | /var/lpp/OV/tmp/ossapi/ |
| | HP-UX, Linux, Solaris, Tru64 UNIX | /var/opt/OV/tmp/ossapi/ |

Table 2-6 OSSPI File Locations for the OVO Managed Node on HTTPS Agents

| File Type | OS | Directory Location |
|---------------------------|-----------------------------|----------------------------------|
| Binaries | HP-UX, Linux, Solaris | /var/opt/OV/bin/instrumentation/ |
| Default Configuration | HP-UX, Linux, Solaris | /var/opt/OV/conf/ossapi/ |
| Configuration & Discovery | HP-UX, Linux, Solaris | /var/opt/OV/conf/ossapi/ |
| Logs | HP-UX, Linux, Solaris | /var/opt/OV/log/ossapi/ |
| Temporary & Runtime | HP-UX, Linux, Solaris | /var/opt/OV/tmp/ossapi/ |

3 **Uninstalling the OSSPI**

This chapter describes how to remove the OSSPI software from the OVO managed node and the OVO management server.

In this Section

This section describes how to remove the OSSPI software quickly and cleanly. The information provided in this section covers the following areas:

- “Removing the OSSPI from the Managed Node” on page 27
- “Removing the OSSPI from the Management Server” on page 29

Removing the OSSPI from the Managed Node

To remove the OSSPI software from the OVO managed node, you should carry out the following steps in the order specified:

1. In the OVO GUI, *de-assign* the OSSPI policies from *all* those OSSPI managed nodes from which you want to uninstall the OSSPI software by moving the nodes (not copying them) from the OSSPI-AIX, OSSPI-HPUX, OSSPI-Linux, OSSPI-Solaris, or OSSPI-Tru64 Node Group in which they reside to the OSSPI-Removal Node Group. This includes the OVO management server if it is also a managed node and you want to uninstall the OSSPI software.

The OSSPI-Removal Node Group has only the monitor policy OSSPI-alarmdef_write_1 assigned to it.

2. Use the OVO GUI to *distribute* the OSSPI-alarmdef_write_1 policy to the OSSPI-Removal Node Group. This de-activates and removes any remaining OSSPI policy definitions from the managed nodes present in the OSSPI-Removal Node Group and, in addition, de-activates any alarm definitions.

NOTE

This step should be carried out regardless of whether OV Performance or GlancePlus is running on the managed nodes.

3. Remove any OSSPI configuration data from the managed nodes by running the OSSPI's Clean Node application on the managed nodes in the OSSPI-Removal Node Group:
 - a. In the OVO Application Bank window, open the OSSPI application group OSSPI Supportability
 - b. In the OSSPI Supportability application-group window, select the Clean Node application, drag it across to the OVO Node Bank window, and drop it onto the OSSPI-Removal node group icon. The application prompts you to confirm the activation of the clean-up operation:

Are you sure you want to delete the OSSPI from the Node [Yes/No]

To remove configuration data used by the OSSPI enter: **Yes**

4. Remove the managed nodes manually from the OSSPI-Removal Node Group using the following menu option:

Actions > Node > Remove from this group

Removing the OSSPI from the Management Server

To remove the OSSPI software completely, you should first carry out the steps described in “Removing the OSSPI from the Managed Node” on page 27 and then remove the OSSPI components from the OVO management server, as follows:

1. Remove the OSSPI software from the OVO management server by using the following command in a shell on the OVO management server itself:

`unix_osspi_remove`
2. Remove the OSSPI configuration data from the OVO management server using the OSSPI Clean Server application, which you can find in the OSSPI Supportability application-group window. To run the application, double click the Clean Server icon.
3. Remove any remaining OSSPI-specific actions, commands, and monitors by distributing the actions, commands, and monitors to *all* managed nodes.
4. Remove all OSSPI components manually from the OVO GUI, for example:
 - Node Groups
 - Application Groups
 - Message Groups
 - Policies and Policy Groups
 - Users and User Profiles

NOTE

The `unix_osspi_remove` script will not remove the service discovery depot (`SPI-SVCDISC-OVO`) that is needed for the discovery functionality to work, and is installed along with the OSSPI. Before you remove the service discovery depot, make sure that no other programs are using the service discovery framework.

Uninstalling the OSSPI

Removing the OSSPI from the Management Server