

HP Network Node Manager i-Series Software

For the Windows®, HP-UX, Linux, and Solaris operating systems

Software Version: NNMi 8.10

[Online Help: Help for Operators](#)

Document Release Date: November 2008

Software Release Date: November 2008



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

For information about third-party license agreements, see the license-agreements directory on the product installation media.

Copyright Notices

© Copyright 2008 Hewlett-Packard Development Company, L.P.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>). Portions Copyright © 1999-2003 The Apache Software Foundation. All rights reserved.

This product includes ASM Bytecode Manipulation Framework software developed by Institute National de Recherche en Informatique et Automatique (INRIA). Copyright © 2000-2005 INRIA, France Telecom. All Rights Reserved.

This product includes Commons Discovery software developed by the Apache Software Foundation (<http://www.apache.org/>). Copyright © 2002-2008 The Apache Software Foundation. All Rights Reserved.

This product includes Netscape JavaScript Browser Detection Library software, Copyright © Netscape Communications 1999-2001

This product includes Xerces-J xml parser software developed by the Apache Software Foundation (<http://www.apache.org/>). Copyright © 1999-2002 The Apache Software Foundation. All rights reserved.

This product includes software developed by the Indiana University Extreme! Lab (<http://www.extreme.indiana.edu/>). Xpp-3 Copyright © 2002 Extreme! Lab, Indiana University. All rights reserved.

Trademark Notices

DOM4J® is a registered trademark of MetaStuff, Ltd.

HP-UX Release 10.20 and later and HP-UX Release 11.00 and later (in both 32 and 64-bit configurations) on all HP 9000 computers are Open Group UNIX 95 branded products.

Java™ is a US trademark of Sun Microsystems, Inc.

Oracle® is a registered trademark of Oracle Corporation and/or its affiliates.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

Oracle Technology — Notice of Restricted Rights

Programs delivered subject to the DOD FAR Supplement are 'commercial computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the licensing

restrictions set forth in the applicable Oracle license agreement. Otherwise, programs delivered subject to the Federal Acquisition Regulations are 'restricted computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the restrictions in FAR 52.227-19, Commercial Computer Software-Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

For the full Oracle license text, see the license-agreements directory on the NNMi product DVD.

Table of Contents

Legal Notices	2
Table of Contents	4
Using Network Node Manager	12
Access NNM 6.x and 7.x Features	13
Learning Your Network Inventory	14
Filter Views by Node or Interface Group	15
Nodes View (Inventory)	15
Interfaces View (Inventory)	16
IP Addresses View (Inventory)	17
IP Subnets View (Inventory)	18
VLANs View (Inventory)	19
Layer 2 Connections View	19
Nodes By Device Category View (Inventory)	20
Interfaces by IfType View (Inventory)	20
Custom Nodes View (Inventory)	21
Custom Interfaces View	22
Router Redundancy Group View (NNMi Advanced)	22
Custom IP Addresses View (Inventory)	23
Node Groups View (Inventory)	23
Interface Group View	24
Management Stations View (Inventory)	24
Accessing Device Details	26
Node Form	27
Node Form: General Tab	32
Node Form: IP Addresses Tab	32
Node Form: Interfaces Tab	32
Node Form: VLAN Ports Tab	33
Node Form: Ports Tab	33
Node Form: Capabilities Tab	33
Node Capabilities Provided by NNMi	34
Node Capability Form	36
Node Form: Custom Attributes Tab	37

Node Custom Attributes Form.....	37
Node Form: Node Groups Tab.....	38
Node Form: Component Health Tab.....	38
Node Component Form.....	38
Node Component Form: Health Attributes Tab.....	40
Health Attribute Form.....	41
Node Component Form: Incidents Tab.....	42
Node Component Form: Status Tab.....	43
Node Component Form: Conclusions Tab.....	44
Node Form: Diagnostics Tab (NNM iSPI NET).....	44
Node Diagnostic Results Form (Flow Run Result) (NNM iSPI NET).....	45
Node Form: Incidents Tab.....	46
Node Form: Status Tab.....	47
Node Form: Conclusions Tab.....	48
Node Form: Registration Tab.....	48
SNMP Agent Form.....	49
SNMP Agent Form: Status Tab.....	52
SNMP Agent Form: Conclusions Tab.....	52
SNMP Agent Form: Incidents Tab.....	53
SNMP Agent Form: Registration Tab.....	53
Device Profile Form.....	54
Device Family Form.....	56
Device Vendor Form.....	56
Device Category Form.....	57
Device Profile Author Form.....	57
Interface Form.....	58
Interface Form: General Tab.....	61
Interface Form: IP Addresses Tab.....	62
Interface Form: VLAN Ports Tab.....	63
Interface Form: Link Aggregation Tab (NNMi Advanced).....	63
Interface Form: Capabilities Tab.....	65
Interface Capabilities Provided by NNMi.....	65
Interface Capability Form.....	67
Interface Form: Custom Attributes Tab.....	68
Interface Custom Attributes Form.....	68

Interface Form: Interface Groups Tab.....	68
Interface Form: Performance Tab (NNM iSPI for Performance).....	69
Interface Form: Incidents Tab.....	70
Interface Form: Status Tab.....	70
Interface Form: Conclusions Tab.....	71
Interface Form: Registration Tab.....	72
IP Address Form.....	72
IP Address Form: Incidents Tab.....	74
IP Address Form: Status Tab.....	74
IP Address Form: Conclusions Tab.....	75
IP Address Form: Capabilities Tab.....	76
IP Address Capabilities Provided by NNMi.....	77
IP Address Capability Form.....	77
IP Address Form: Registration Tab.....	78
Router Redundancy Group Form (NNMi Advanced).....	78
Router Redundancy Group Form: Router Redundancy Members Tab (NNMi Advanced).....	79
Router Redundancy Member Form (NNMi Advanced).....	80
Router Redundancy Member Form: Tracked Objects Tab (NNMi Advanced).....	82
Tracked Objects Form (NNMi Advanced).....	82
Router Redundancy Group Form: Virtual IP Addresses Tab (NNMi Advanced).....	83
Virtual IP addresses Form (NNMi Advanced).....	84
Router Redundancy Group Form: Incidents Tab (NNMi Advanced).....	84
VLAN Form.....	85
VLAN Form: Ports Tab.....	85
Port Form.....	86
Port Form: VLANs Tab.....	86
Node Group Form.....	87
Node Group Form: Device Filters Tab.....	88
Node Device Filter Form.....	88
Node Group Form: Additional Filters Tab.....	89
Node Group Form: Additional Nodes Tab.....	89
Additional Node Form.....	90
Node Group Form: Child Node Groups Tab.....	91
Node Group Hierarchy (Child Node Group) Form.....	91
Node Group Form: Status Tab.....	92

Interface Group Form.....	93
Interface Group Form: IfType Filters Tab.....	94
IfType Filter Form.....	95
IfType (Interface Type) Form.....	95
Interface Group Form: Additional Filters Tab.....	95
Management Station Form.....	96
Viewing Maps (Network Connectivity).....	97
Node Group Maps.....	98
Navigating within a Node Group Map.....	99
Position Nodes on a Node Group Map.....	100
Node Group Overview Map.....	100
Network Overview Map.....	101
Networking Infrastructure Devices Map.....	101
Routers Map.....	102
Switches Map.....	102
Display the Layer 2 Neighbor View.....	103
Layer 2 Connection Form.....	105
Layer 2 Connection Form: Interfaces Tab.....	106
Layer 2 Connection Form: Incidents Tab.....	106
Layer 2 Connection Form: Status Tab.....	107
Layer 2 Connection Form: Conclusions Tab.....	108
Layer 2 Connection Form: Link Aggregation Tab (NNMi Advanced).....	108
Layer 2 Connection Form: Registration Tab.....	110
Display the Layer 3 Neighbor View.....	110
IP Subnet Form.....	112
IP Subnet Form: IP Addresses Tab.....	112
IP Subnet Form: Registration Tab.....	112
Path Between Two Nodes that Have IPv4 Addresses.....	113
Path Calculation Rules.....	114
Path View Limitations.....	116
Investigate Errors and Performance Issues.....	116
Enhanced Path View (NNMi Advanced).....	116
Monitoring Devices for Problems.....	118
Monitor with Table Views.....	118
Critical Interfaces View.....	118

Critical Nodes View.....	119
Critical Component View.....	119
Non-Normal Interfaces View.....	120
Non-Normal Nodes View.....	120
Non-Normal Router Redundancy Group View (NNMi Advanced).....	121
Not Responding Address View.....	122
Nodes by Status View.....	122
Interfaces by Status View.....	123
Interfaces by Administrative State View.....	123
Interfaces by Operational State View.....	123
IP Addresses by State View.....	124
Component by Status View.....	124
Interface Performance View (NNM iSPI for Performance).....	125
Node Groups View (Monitoring).....	125
Monitor with Map Views.....	126
Watch Status Colors.....	126
Determine Problem Scope.....	127
Access a Problem Device.....	127
Access Node Details.....	127
Access All Related Incidents.....	128
Monitoring Incidents for Problems.....	130
Organize Your Incidents.....	131
Incident Form.....	132
Incident Form: General Tab.....	134
Incident Form: Correlated Parents Tab.....	138
Incident Form: Correlated Children Tab.....	138
Incident Form: Custom Attributes Tab.....	138
Custom Incident Attribute Form.....	139
Incident Form: Diagnostics Tab (NNM iSPI NET).....	140
Incident Diagnostic Results Form (Flow Run Result) (NNM iSPI NET).....	140
Incident Form: Registration Tab.....	141
Manage Incident Assignments.....	142
Own an Incident.....	142
Assign an Incident.....	143
Unassign an Incident.....	143

Keep Your Incidents Up to Date.....	144
About the Incident Lifecycle.....	144
Track an Incident's Progress.....	145
Display a Map from an Incident.....	146
Island Node Group Map.....	146
Incident Views Provided by NNMi.....	147
My Open Incidents View.....	148
Key Incident Views.....	148
Open Key Incidents View.....	149
Unassigned Open Key Incidents View.....	151
Open Key Incidents by Severity View.....	151
Open Key Incidents by Priority View.....	152
Open Key Incidents by Category View.....	154
Open Key Incidents by Family View.....	155
Closed Key Incidents View.....	156
Key Incidents by Lifecycle State View.....	157
Root Cause Incidents.....	158
Root Cause Incidents View.....	159
Open Root Cause Incidents View.....	159
Service Impact Incidents View.....	160
Stream Correlation Incidents View.....	160
Incidents by Family View.....	161
Custom Incidents View.....	161
NNM 6.x/7.x Events View.....	162
NNM 6.x/7.x Events by Category View.....	162
SNMP Traps View.....	162
SNMP Traps by Family View.....	163
Analyze Trap Information.....	164
Investigate and Diagnose Problems.....	165
Verify Device Configuration Details.....	165
View the Monitoring Configuration Details.....	166
Verify Current Status of a Device.....	168
Interpret Root Cause Incidents.....	168
Address Disabled.....	169
Address Not Responding.....	170

Aggregator Interface Degraded (NNMi Advanced).....	170
Aggregator Interface Down (NNMi Advanced).....	171
Aggregator Connection Degraded (NNMi Advanced).....	172
Aggregator Connection Down (NNMi Advanced).....	172
Buffer has Insufficient Capacity or is Malfunctioning.....	173
Connection Down.....	173
Connection Partially Unresponsive.....	174
CPU Utilization is too High.....	175
Fan is Malfunctioning.....	175
Interface Down.....	175
Interface Disabled.....	176
Interface Unmanageable.....	177
Remote Site Containing Node <Source Node Name> is Unreachable.....	178
Memory has Insufficient Capacity or is Malfunctioning.....	178
Node Down.....	178
Node or Connection Down.....	180
Non-SNMP Node Unresponsive.....	181
Number of SNMP Traps Persisted in the Database has Reached or Exceeded Trap Limit.....	181
Power Supply is Malfunctioning.....	182
SNMP Agent Not Responding.....	182
Temperature Sensor is Out of Range.....	182
Voltage is Out of Range.....	183
Interpret Service Impact Incidents.....	183
Primary Device in Router Redundancy Group Switched (NNMi Advanced).....	184
No Primary Device in Router Redundancy Group (NNMi Advanced).....	184
Multiple Primary Devices in Router Redundancy Group (NNMi Advanced).....	185
No Secondary Device in Router Redundancy Group (NNMi Advanced).....	185
Multiple Secondary Devices in Router Redundancy Group (NNMi Advanced).....	185
Router Redundancy Group Degraded (NNMi Advanced).....	185
Interpret Threshold Incidents (NNM iSPI for Performance).....	185
Input and Output Utilization Incidents (NNM iSPI for Performance).....	186
Input and Output Error Rate Incidents (NNM iSPI for Performance).....	187
Input and Output Discard Rate Incidents (NNM iSPI for Performance).....	188
Find a Node.....	189
Find the Attached Switch Port (NNM iSPI NET).....	190

Display End Nodes Attached to a Switch (NNM iSPI NET).....	190
Test Node Access (Ping).....	191
Find the Route (traceroute).....	192
Establish Contact with a Node (telnet).....	193
Check Status Details for a Node Group.....	194
Checking the Status of NNMi.....	196
Appendix A. Glossary Terms.....	197
Appendix B: Index.....	199

Using Network Node Manager

NNMi enables you to quickly detect, isolate, and troubleshoot abnormal network behavior. Using NNMi, you can also record what has been done to date to troubleshoot or resolve a problem.

The following table describes some of the ways that NNMi assists in making your job easier and the help topics that would be most valuable for accomplishing those tasks.

Task	Help Topic
Rapidly detect, isolate, and correct the problem	"Monitoring Devices for Problems" (on page 118) and "Investigate and Diagnose Problems" (on page 165)
Annotate information for future diagnosis	"Accessing Device Details" (on page 26)
Look for historical information to proactively monitor the network	"Monitoring Incidents for Problems" (on page 130)
View an inventory of what is being managed	"Learning Your Network Inventory" (on page 14)

Access NNM 6.x and 7.x Features

Your NNMi administrator might have configured NNMi so that you are able to view incidents that are being forwarded from an NNM 6.x or 7.x management station.

If your NNMi administrator has configured any NNM 6.x or 7.x management stations, you are able to view this information using the **Inventory** workspace. The **Management Stations** view in the **Inventory** workspace is useful for identifying all of the NNM 6.x or 7.x management stations that might be forwarding incidents to your NNMi incident views. See "[Management Stations View \(Inventory\)](#)" (on page 24) for more information.

If an NNM 6.x or 7.x management station has been configured, you are also able to access the following NNM 6.x or 7.x features from the NNMi **Actions** menu:

Note: You can only launch the 6.x/7.x ovw action if ovw is running on the NNM 6.x/7.x management station.

From Incident Views

- **Actions** → **6.x/7.x Neighbor View**
- **Actions** → **6.x/7.x Details**
- **Actions** → **6.x/7.x ovw**

From Management Station Views

- **Actions** → **6.x/7.x Home Base**
- **Actions** → **6.x/7.x ovw**
- **Actions** → **6.x/7.x Launcher**
- **Actions** → **SNMP Viewer**
- **Actions** → **Alarms**


Note: You can only access NNM 6.x/7.x features by selecting incidents generated from NNM 6.x/7.x events.


Learning Your Network Inventory

After NNMi discovers your network (or rediscovers it on a regular basis), you have several options for exploring what was discovered. See up-to-date information for each of the following:


Types of Views Provided by NNMi


Object Type	Purpose
Nodes	Identify all nodes being managed.
Network interfaces	Identify all network interfaces being managed, their associated node, and any interfaces that are disabled or otherwise unavailable.
IP addresses	Identify the IP addresses associated with each node being managed.
IP Subnets	Identify all of the networks within NNMi's management domain. Browse for large and small subnets.
VLANs	Identify all of the switch port VLANs configured in your network environment. NNMi ignores VLAN-1, but higher numbered VLANs are discovered.

Within any table view, you can quickly view a few additional properties of your network devices. To do so, click the  Quick View icon within the row representing a network object. Quick View provides information at a glance for some pre-determined object attributes.

Forms are a way to gain a more in depth understanding of a particular object instance. To view the form for the object's attributes, from a table view, click the  Open icon that precedes the object information. The form containing the information for the object's attributes appears.

To view all of the text for an attribute value within the form, click the attribute label of interest. The attribute value appears in a popup window. This option is useful when not all of the text is viewable within the form field.

You can also access another form from the current one for any related objects. Related objects in a form appear as lookup fields. Each  Lookup field includes a drop-down menu that lets you open the form for that object.

Views can be filtered by pre-defined Node Groups and Interface Groups. Select a filter by using the  drop-down filter selection. See [Filter by Node or Interface Group](#) for more information about filters.

In the form for that object, you can view or edit the information for the selected object as described in [Working with Objects](#).

Related Topics

["Nodes View \(Inventory\)" \(on page 15\)](#)

["Interfaces View \(Inventory\)" \(on page 16\)](#)

["IP Addresses View \(Inventory\)" \(on page 17\)](#)

["IP Subnets View \(Inventory\)" \(on page 18\)](#)

Filter Views by Node or Interface Group

When monitoring your network, you might be interested in only viewing information for a particular set of nodes or interfaces. Your network administrator is able to group sets of nodes or interfaces into node or interface groups. An example of a Node Group could be all important Cisco routers, or all routers in a particular building. As another example, all interfaces used for Voice-Over-IP might be grouped together in a Node Group.

Note: Node Group filters are not available for the **NNM 6.x/7.x Events** view.

You can filter the following kinds of views by Node Group:

- Node views
- Interface views
- IP address views
- Incident views

You can filter the following views by interface group:

- Interface views
- IP address views

If a view includes filtering by both node and interface groups, NNMi lists the Node Groups first, followed by all of the interface groups. Each list appears in alphabetical order.

To filter a view by node or interface group:

1. Navigate to the view of interest
 - a. From the workspace navigation panel, select the workspace that contains the view you want to use; for example **Inventory**.
 - b. Select the view of interest; for example **Nodes**.
2. In the group selector drop-down list, select the Node or Interface Group you want to use as a filter.

Nodes View (Inventory)

Tip: See "[Node Form](#)" (on page 27) for more details about the node attributes that appear in this view's column headings.

The Nodes view in the Inventory workspace is useful for identifying all of the nodes being managed by NNMi.

For each node displayed, you can identify its overall status (for example, **Normal**, **Warning**, **Minor**, **Major**, **Critical**, or **Unknown**), device category (for example, **Switch**), name, hostname, management address, system location (the current value of the sysLocation MIB variable), device profile, date indicating the last time the node status was modified, and any notes included for the node.

Note: Your NNMi administrator is able to delete nodes and other objects from the NNMi database. If you are viewing an object, such as a node, that has recently been deleted by another user, the node appears in your view until your view is refreshed. See [Refresh a View](#) for information about refreshing a view.

Node views are useful for quickly identifying items described in the following table.

Uses for Nodes Views

Use	Description

View all problem nodes	Sort the view by Status so that you can be quickly alerted to existing and potential problems. You can also access the Critical Nodes view provided by NNMi. See " Critical Nodes View " (on page 119) for more information.
View all device types being managed	Sort the view by the Device Profile attribute.
Identify whether the problem can be isolated to a particular area of your network	Sort the view by System Location . This is the current value of the sysLocation MIB variable.
View address and subnet information associated with a selected node to better determine the scope of the problem	From the Nodes view, open the Node form. Select the Addresses tab.
Access a map view of a selected node and its surrounding topology	Select the node of interest and use the Actions menu from the main toolbar to select either the Layer 2 or Layer 3 Neighbor View. See Using Table Views for more information
View the statuses of interfaces on the node	If a node is not completely down, you might want to see which interfaces are down for the selected node. To do so, open the Node form and select the Interfaces tab.
The number of devices that are served by this node.	Select the node you want and access the Layer 2 or Layer 3 Neighbor View using the Actions menu.
View the status of all of the nodes that have been grouped together in a nodes group; for example, all of your important Cisco routers.	Your NNMi administrator can create Node Groups. These groups might contain only the nodes important to you. See Filter Information in a Table View for more information.

Related Topics:

[Using Table Views](#)

["Node Form" \(on page 27\)](#)

[Print Table Information](#)

Interfaces View (Inventory)

Tip: See "[Interface Form](#)" (on page 58) for more details about the interface attributes that appear in this view's column headings.

The Interfaces view is useful for identifying the network interfaces managed by NNMi.

For each interface displayed in the view, you can identify the interface's overall status (for example, **Normal**, **Warning**, **Minor**, **Major**, **Critical**, or **Unknown**), its administrative (**AS**) and operational (**OS**) status, associated node Name value (**Hosted On Node**), the interface name, interface type, interface speed, input speed, output speed, the date the interface information was last changed, its description, the ifAlias value, and any notes included for the interface.

If you see several blank columns for an interface in a table view, the interface might be an interface on a non-SNMP node or a Nortel private interface. Click here for more information.

For interfaces on non-SNMP nodes, note the following:

- The interface index (ifIndex) value is always set to **0** (zero).
- The interface type (ifType) is set to **Other**.
- The interface Name (ifName), if none is available, is set to **Pseudo Interface**.
- If the interface hosts an IP address, the interface Alias (ifAlias) is set to the IP address. Otherwise, the interface Alias (ifAlias) is set with information from neighboring SNMP devices.
- NNMi obtains the MAC address if the IP address can be resolved using ARP cache.

Note the following about **Pseudo** interfaces: NNMi attempts to obtain additional information using a variety of discovery protocols.

For Nortel SNMP interfaces, note the following:

- The ifIndex value is set according the Nortel private MIB.
- NNMi tries to collect the MAC address and interface name using Nortel's private MIBs.

Interface views are useful for quickly identifying items described in the following table.

Uses for Interfaces Views

Use	Description
View all network interfaces per node	Sort the view by Hosted On Node . This is the current value in NNMi's database for the Name attribute of the host device.
Determine the health of each of the managed interfaces	Sort the view by the Status attribute. To view only those interfaces whose status is Critical , use the Critical Interfaces view provided by NNMi. See "Critical Interfaces View" (on page 118) for more information.
Access a map view of the network interface and its surrounding topology.	Select the interface of interest and use the Actions menu to select either the Layer 2 or Layer 3 Neighbor view. See Using Table Views for more information.
View the status of all of the interfaces that have been grouped together in a node or an interfaces group; for example, all of the interfaces on the important Cisco routers or all of the Voice-Over-IP interfaces within your network.	Your NNMi administrator can create nodes and interface groups. These groups might include only those nodes or interfaces important to you. Now you can filter the interfaces view by a node or an interface group. See Filtering a View by a Node or Interface Group for more information.

Related Topics:

[Using Table Views](#)

["Interface Form" \(on page 58\)](#)

[Print Table Information](#)

IP Addresses View (Inventory)



Tip: See ["IP Address Form" \(on page 72\)](#) for more information about the IP address attributes that appear in this view's column headings.

The IP Addresses view in the Inventory workspace is useful for identifying all of the IP addresses being managed by NNMi.

For each IP address displayed, you can identify its status, state, IP address, interface name (**In Interface**), associated node Name value (**Hosted On Node**), the subnet prefix (**In Subnet**) and prefix length (**PL**), and any notes included for the IP address.

The IP Address view is useful for quickly identifying items described in the following table.

Uses for the IP Addresses View

Use	Description
View all IP addresses per node	Sort the view on Hosted On Node attribute.
View the addresses per interface	Sort the view on the Interface name (In Interface) attribute.
View the addresses per subnet	Sort the view on the subnet (In Subnet) attribute.
View the subnet information for a selected IP address	To access a subnet from this view: <ol style="list-style-type: none"> 1. Select the IP address of interest. 2. Open the IP Address form 3. Navigate to the In Subnet attribute. Click the  Lookup icon and select  Open to access the IP Subnet form.
View the status of all of the addresses for the nodes that have been grouped together in a nodes group; for example, all of your important Cisco routers.	Your NNMi administrator can create node or interface groups. These groups might include only those nodes or interfaces important to you. Now you can filter the addresses view by a node or interface group. See Filtering a View by a Node or Interface Group for more information.

Related Topics:

[Use Table Views](#)

["IP Address Form" \(on page 72\)](#)

[Print Table Information](#)

IP Subnets View (Inventory)

Tip: See ["IP Subnet Form" \(on page 112\)](#) for more details about the IP subnet attributes that appear in this view's column headings.

The IP Subnets view is useful for identifying all of the networks within your management domain.

For each IP subnet displayed, you can identify its name, the subnet prefix (**In Subnet**) and prefix length (**PL**), the date and time its status was last changed, and any notes included for the subnet.

The IP Subnets view is useful for quickly identifying items described in the following table.

Uses for the Subnets View

Use	Description
Determine all nodes within a subnet	Use the Layer 3 Neighbor view to easily see the number of problem nodes within a subnet.
Browse for large and small subnets	Scan the Name column to view the list of available subnets.

You can identify empty subnets by opening the form for a selected subnet and viewing the IP addresses table.

Related Topics:

[Use Table Views](#)

["IP Subnet Form" \(on page 112\)](#)

[Print Table Information](#)

VLANs View (Inventory)

A virtual local area network (VLAN) is a logical network within a physical network. The VLAN creates a reduced broadcast domain. Participating devices can physically reside in different segments of a LAN. The participating VLAN member devices behave "as if" they were all connected to one LAN.

Several VLANs can co-exist within a network. A device can participate in multiple VLANs. And a trunk port can participate in multiple VLANs.

There are several types of VLANs. NNMi supports switch port VLANs.

Note: NNMi does not currently support protocol-based VLANs and MAC-based VLANs.

To display the VLAN view:

1. In the **Workspaces** navigation pane, select the **Inventory** workspace.
2. Select the **VLANs** view.

Note: NNMi ignores VLAN-1, but higher numbered VLANs are discovered.

3. Use the VLAN view to quickly identify all of the switch port VLANs configured in your network environment:

For each VLAN, the VLAN view displays the VLAN identification value, name, hostname of a representative node, IfName of a representative interface on the node, and member node count.

If your VLAN view contains two or more VLANs with the same name, those VLANs exist in separate broadcast domains.

Related Topics:

["VLAN Form" \(on page 85\)](#)

[Print Table Information](#)

Layer 2 Connections View

Tip: See "[Layer 2 Connection Form](#)" ([on page 105](#)) for more details about the Layer 2 connection attributes that appear in this view's column headings.

The Layer 2 Connections view in the Inventory workspace is useful for identifying all of the connections being managed by NNMi. Sorting this view by Topology Source lets you easily identify all user added connections.

For each connection displayed in the view, you can identify the status, name, the data source or protocol (Topology Source) used to create the connection (for example **CDP** or **USER**), the date and time the connection was last modified, and any notes related to the connection.

Related Topics


[Print Table Information](#)

Nodes By Device Category View (Inventory)

Tip: See "[Node Form](#)" (on page 27) for more details about the node attributes that appear in this view's column headings.

The **Nodes by Device Category** view lets you filter your view by the device category value. Examples of device categories include **Firewall**, **Gateway**, **Hub**, and **Load Balancer**.

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



Use this view to monitor a specific category of devices. If your NNMi administrator set up Node Groups or Interface Groups to identify important elements of your environment, you can filter this view to show only devices of a certain category that are within a certain group of nodes. Using the device category and Node Group filters might be useful for troubleshooting purposes, so that you can take the same approach for devices in the same category.

Note: If you filter your view using additional filters, such as Node Groups, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each node displayed, you can identify its overall status (for example, **Normal**, **Warning**, **Minor**, **Major**, **Critical**, or **Unknown**), name, hostname, management address, system location (the current value of the sysLocation MIB variable), device profile, date indicating the last time the node status was modified, and any notes included for the node.

Related Topics

[Use Table Views](#)

[Filter a Table View](#)


[Print Table Information](#)

Interfaces by IfType View (Inventory)

Tip: See "[Interface Form](#)" (on page 58) for more details about the interface attributes that appear in this view's column headings.

The Interface by IfType view lets you filter your view by the Interface Type value. The list of interface types contains the industry standard known values for MIB II interface types. Examples of interface types include: **asynch**, **atm**, **bsc**, and **ces**.

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



Use this view to monitor a specific type of interfaces. If your NNMi administrator set up Node Groups or Interface Groups to identify important elements of your environment, you can filter this view to show only

certain types of interfaces within a certain group of nodes. Using the type and Node Group filters might be useful for troubleshooting purposes.

Note: If you filter your view using additional filters, such as Node Groups, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each interface displayed in the view, you can identify the interface's overall status (for example, **Normal**, **Warning**, **Minor**, **Major**, **Critical**, or **Unknown**), its administrative (**AS**) and operational (**OS**) status, associated node Name value (**Hosted On Node**), the interface name, interface speed, its description, its ifAlias value, the date the interface status was last modified, the name of the Layer 2 connection associated with the interface, and any notes that exist for the interface.

If you see several blank columns for an interface in a table view, the interface might be an interface on a non-SNMP node or a Nortel private interface. Click here for more information.

For interfaces on non-SNMP nodes, note the following:

- The interface index (ifIndex) value is always set to **0** (zero).
- The interface type (ifType) is set to **Other**.
- The interface Name (ifName), if none is available, is set to **Pseudo Interface**.
- If the interface hosts an IP address, the interface Alias (ifAlias) is set to the IP address. Otherwise, the interface Alias (ifAlias) is set with information from neighboring SNMP devices.
- NNMi obtains the MAC address if the IP address can be resolved using ARP cache.

Note the following about **Pseudo** interfaces: NNMi attempts to obtain additional information using a variety of discovery protocols.

For Nortel SNMP interfaces, note the following:

- The ifIndex value is set according the Nortel private MIB.
- NNMi tries to collect the MAC address and interface name using Nortel's private MIBs.

Related Topics

[Using Table Views](#)

[Print Table Information](#)

Custom Nodes View (Inventory)

Tip: See "[Node Form](#)" ([on page 27](#)) for more details about the node attributes that appear in this view's column headings.

The Custom Nodes view enables you to create a customized view of nodes. This view includes most of the attributes available for the node so that you can decide which are most important for you to display. See [Use Table Views](#) for more information about sorting, filtering, and hiding attributes within a view.

The Custom Nodes view includes the node's overall status (for example, **Normal**, **Warning**, **Minor**, **Major**, **Critical**, or **Unknown**), device category (**DC**), name, fully-qualified hostname (including the domain name, if available), management address, system location (the current value of the sysLocation MIB variable), device profile, date indicating the last time the node status was modified, any notes that exist for the node, its system name, system contact name, a system description, the management mode, the system object ID (MIB II sysObjectID), the name of its SNMP agent, its discovery state, whether the node is SNMP supported, the creation date, and the date the node was last modified.

See "[Nodes View \(Inventory\)](#)" ([on page 15](#)) for more information about ways to use a node view.

Related Topics:

[Use Table Views](#)

[Print Table Information](#)

Custom Interfaces View

Tip: See "[Interface Form](#)" (on page 58) for more details about the interface attributes that appear in this view's column headings.

The **Custom Interfaces** view lets you choose the columns of interface information, to better meet your needs. For example, you might want to filter the view to display only the interfaces related to a particular set of devices.

This view includes most of the attributes available for the incident so that you can decide which are most important for you to display. See [Use Table Views](#) for more information about sorting, filtering, and hiding attributes within a view.

For each interface displayed, you can view its state, its administrative and operational state, the associated hostname (Hosted On Node), its interface name, type, speed, description, the value of its alias, the date and time the status was last modified, the name of the Layer 2 connection associated with the interface, any notes related to the interface, its direct management mode, its node management mode, the physical address, the interface index, the creation date, and the date and time the interface was last modified.

If you see several blank columns for an interface in a table view, the interface might be an interface on a non-SNMP node or a Nortel private interface. [Click here](#) for more information.

For interfaces on non-SNMP nodes, note the following:

- The interface index (ifIndex) value is always set to **0** (zero).
- The interface type (ifType) is set to **Other**.
- The interface Name (ifName), if none is available, is set to **Pseudo Interface**.
- If the interface hosts an IP address, the interface Alias (ifAlias) is set to the IP address. Otherwise, the interface Alias (ifAlias) is set with information from neighboring SNMP devices.
- NNMi obtains the MAC address if the IP address can be resolved using ARP cache.

Note the following about **Pseudo** interfaces: NNMi attempts to obtain additional information using a variety of discovery protocols.

For Nortel SNMP interfaces, note the following:

- The ifIndex value is set according the Nortel private MIB.
- NNMi tries to collect the MAC address and interface name using Nortel's private MIBs.

See [Filter a Table View](#) for more information about how to filter information displayed in a table.

Related Topics:

[Use Table Views](#)

[Print Table Information](#)


Router Redundancy Group View (NNMi Advanced)

Tip: See "[Router Redundancy Group Form \(NNMi Advanced\)](#)" (on page 78) for more details about the Router Redundancy Group attributes that appear in this view's column headings.

Your network administrator might have set up groups of redundant routers to help ensure that information packets reach their intended destination. Use the Router Redundancy Group view to see all of the available groups of redundant routers in your network.

For each Router Redundancy Group displayed in the view, you can identify the Router Redundancy Group status, Router Redundancy Group name, the Router Redundancy Group protocol (for example, HSRP), and the date the Router Redundancy Group status was last modified.

To see the incidents related to a Router Redundancy Group:

1. Click the  Open icon that precedes the Router Redundancy Group of interest to open the form.
2. Navigate to the **Incidents** tab to see the incidents associated with the selected Router Redundancy Group.

To view the members that belong to this group:

Click the  Open icon that precedes the Router Redundancy Group of interest to open the form.

On the **Router Router Redundancy Members** tab, you should see a table view of the nodes and interfaces that belong to the selected Router Redundancy Group.

Related Topics

["Non-Normal Router Redundancy Group View \(NNMi Advanced\)" \(on page 121\)](#)

["Router Redundancy Group Form \(NNMi Advanced\)" \(on page 78\)](#)

[Print Table Information](#)

Custom IP Addresses View (Inventory)

Tip: See ["IP Address Form" \(on page 72\)](#) for more details about the IP address attributes that appear in this view's column headings.

The Custom IP Addresses view displays most IP address attribute columns. Sort and filter this IP address view to meet your needs, if the out-of-the-box views provided by NNMi don't provide exactly what you want.

See [Use Table Views](#) for more information about sorting, filtering, and hiding attribute columns within a view.

For each address displayed in the view, you can identify the status, state, address, the name of the interface (**In Interface**), associated node Name value (**Hosted On Node**), the subnet in which the address is contained, the subnet prefix length (**PL**), the date the address status was last modified (**Status Last Modified**), any notes that exist for the IP address, its direct management mode, date the state of the address was last modified (**State Last Modified**), date the address was created, date the address was last modified.

See ["IP Address Form" \(on page 72\)](#) for more information about the IP address attributes.

Related Topics

[Use Table Views](#)

[Print Table Information](#)

Node Groups View (Inventory)

Tip: See the context-sensitive link for the Node Groups form for more details about the Node Group attributes that appear in this view's column headings

When checking your network inventory, you might be interested in only viewing information for a particular set of nodes. Your network administrator is able to group sets of nodes into node groups. An example node group could be all important Cisco routers, or all routers in a particular building. See [About Node and Interface Groups](#) for more information about how your administrator sets up node groups. See [Filter by Node or Interface Group](#) for more information about filtering views using node groups.

To find the definition for a particular Node Group filter, navigate to the Inventory workspace, and select the Node Groups view.

For each node group displayed in the view, you can identify the node group status, name, whether the node group appears in the filter list for node and interface views, whether the node group is available as a filter in NNM iSPI for Performance, and any notes about the node group.

Related Topics

[Print Table Information](#)

Interface Group View

Tip: See ["Interface Form" \(on page 58\)](#) the "Using the Interface Groups Form" context-sensitive link for more details about the Interface Group attributes that appear in this view's column headings.

When checking your network inventory, you might be interested in only viewing information for a particular set of interfaces. Your network administrator is able to group sets of interfaces into interface groups. See [About Node and Interface Groups](#) for more information about how your administrator sets up interface groups. See [Filter by Node or Interface Group](#) for more information about filtering views using interface groups.

To find the definition for a particular Interface Group filter, navigate to the Inventory workspace, and select the Interface Groups view.

For each interface group displayed in the view, you can identify the interface group name, whether the interface group appears in the filter list for interface views, whether the interface group is available as a filter in NNM iSPI for Performance, and any notes about the interface group.

Related Topics

[Print Table Information](#)

Management Stations View (Inventory)

Your NNMi administrator might have configured NNMi so that you are able to view incidents that are being forwarded from a NNM management station (from either an NNM 6.x or 7.x management stations). If your NNMi administrator configured any NNM management stations, you are able to view this information using the **Inventory** workspace.

To view attribute information for any NNM management stations that have been configured:

From the **Workspaces** navigation pane, select **Inventory** → **Management Stations**.

The **Management Stations** view in the **Inventory** workspace is useful for identifying all of the NNM 6.x or 7.x management stations that might be forwarding incidents to your NNMi incident views, as well as launching directly to the NNM 6.x/7.x management station.

For each management station displayed, you can identify its name, the version of NNMi that is running on that machine (either 6.x or 7.x), the IP address for the machine, the OpenView Application Server (ovas) port number, the Web server port number, and a description for the management station that was provided by your NNMi administrator.

Network Node Manager (NNMi 8.10) Online Help: Using the Console
Learning Your Network Inventory

Note: If an NNM management station has been configured, you are also able to access the following 6.x or 7.x features from the NNMi **Actions** menu: Home Base, ovw , Launcher, and Alarms. See ["Access NNM 6.x and 7.x Features" \(on page 13\)](#) for more information.


Related Topics

[Print Table Information](#)

Accessing Device Details

NNMi provides forms that help you easily view all details associated with a managed object, such as a node, SNMP agent, interface, address, subnet, or connection. NNMi also provides a Quick View that displays a small subset of information about an object.


From a table view, to view all details associated with an object:

1. From the workspace navigation panel, select a workspace containing a view of the object of interest.
2. Select a view that contains the specific object (for example, **Inventory** → **Nodes**).
3. Click the  Open icon within the row representing the object.
4. The form displays, containing details of all information related to the object.
5. View or edit the details of the selected object:
 - ["Node Form" \(on page 27\)](#)["SNMP Agent Form" \(on page 49\)](#)
 - ["Interface Form" \(on page 58\)](#)
 - ["IP Address Form" \(on page 72\)](#)
 - ["Layer 2 Connection Form" \(on page 105\)](#)
 - ["IP Subnet Form" \(on page 112\)](#)
 - ["VLAN Form" \(on page 85\)](#)

Tip: A form is also available for incidents, see ["Incident Form" \(on page 132\)](#).

Note: NNMi also provides forms for SNMP Agent and Port objects. The SNMP Agent form is accessed from the Node form. The Port form is accessed from the VLAN form.



From a map view, to view all details associated with an object:

1. Display a map using the **Troubleshooting** workspace, or the **Actions** → menu.
2. Select the object and click the  Open icon in the menu bar.
3. The form displays, containing details of all information related to the object.
4. View or edit the details of the selected object:
 - ["Node Form" \(on page 27\)](#)["SNMP Agent Form" \(on page 49\)](#)
 - ["Interface Form" \(on page 58\)](#)
 - ["IP Address Form" \(on page 72\)](#)
 - ["Layer 2 Connection Form" \(on page 105\)](#)
 - ["IP Subnet Form" \(on page 112\)](#)
 - ["VLAN Form" \(on page 85\)](#)

Tip: A form is also available for incidents, see ["Incident Form" \(on page 132\)](#).

To access the Quick View for a selected object:

1. From the workspace navigation panel, select a workspace containing a view of the object of interest.
2. Select a table view that contains the specific object (for example, **Inventory** → **Nodes**).
3. In a table view, do one of the following:

- Click the  Quick View icon within the row representing the object.
 - Using your mouse, hover over the  Quick View icon.
4. In a map view, using your mouse, hover over the object of interest.

The Quick View window displays, containing some of the details of the object.

Related Topics:

[Using Table Views](#)

[Using Map Views](#)

Node Form

The Node form provides details about the selected node. It also provides details about the [interfaces](#), the [IP addresses](#), the [VLANs](#), the [ports](#), the [SNMP agent](#), the [device profile](#), and the [incidents](#) associated with this node.

If your role allows, you can use this form to modify the [Management Mode](#) for a node (for example to indicate it will be temporarily out of service) or add [notes](#) to communicate information about this node to your team.

For information about each tab:

Basic Attributes












Attribute	Description
Name	<p>The name assigned to this device (according a strategy created by your NNMi administrator). The name might be a hostname determined by the hostname resolution strategy used in your environment (such as DNS), a MIB II sysName, or an address. Contact your NNMi administrator if you have questions.</p> <p>This name is used in table views and maps. This name cannot be modified in the Node form.</p>







Attribute	Description
Hostname	<p>The fully-qualified hostname for this device (according to any hostname resolution strategy currently in use in your network environment; for example, DNS).</p> <p>Note: NNMi converts hostnames to all lowercase.</p> <p>If a device has multiple hostnames or no hostname, NNMi follows a set of rules to determine the hostname. Click here for details.</p> <ol style="list-style-type: none">1. If a hostname is available, it must resolve to a valid IP address. NNMi stores the fully-qualifiedhostname in the database as all lowercase characters.2. If more than one address is associated with a node, the loopback address¹ is used with the following exceptions:<ul style="list-style-type: none">■ NNMi prefers loopback interfaces for management communication, where possible. However, NNMi automatically filters out addresses in the reserved loopback network range 127/24 (127.*.*).■ NNMi ignores any address that is virtual (HSRP/VRRP) or an Anycast Rendezvous Point IP Address².3. If a node has multiple loopback addresses, NNMi uses the loopback address with the lowest number that resolves to a hostname (for example, 10.16.42.197 is a lower number than 10.16.197.42).4. If no loopback address resolves to a hostname and the device supports SNMP, NNMi uses the current value from the Management Address attribute on the Node form.5. If the device does not support SNMP, the IP address or DNS name found during the current rediscovery cycle is used as the hostname. <p>This sequence is repeated during each rediscovery cycle. The hostname could change from cycle to cycle (for example, if an address did not respond to SNMP queries due to network problems or node reconfiguration).</p> <p>This name cannot be modified in the Node form.</p>

¹The address associated with the loopback interface. The loopback interface is a virtual interface on a device that provides a route for internal communication. Many vendors provide a specially configured loopback for management purposes. Exact details of how loopbacks are configured varies by vendor and model. See each device's documentation for details. NNM identifies these loopback addresses by using IfType 24, softwareloopback from the IANA ifType-MIB.

²Rendezvous Point addresses are loopback addresses used for routers in multi-cast network configurations

Attribute	Description
Notes	<p>Provided for network operators to use for any additional notes required to further explain the node. Information might include why the node is important, if applicable, or to what customer, department, or service the node is related. Additional information might include where the nodes is located, who is responsible for it, and its serial number. You might also track maintenance history using this attribute.</p> <p>Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p> <p>Note: You can sort your node table views based on this value. Therefore, you might want to include keywords for this attribute value.</p>

Attribute	Description
Status	<p>Overall status for the current node. NNMi follows the ISO standard for status classification. See the "Node Form: Status Tab" (on page 47) for more information. Possible values are:</p> <ul style="list-style-type: none">  No Status  Normal  Disabled  Unknown  Warning  Minor  Major  Critical <p>The status of all IP addresses and the SNMP Agent associated with this node contribute to node status. For information about how the current status was determined, see the Conclusions tab. Status reflects the most serious outstanding conclusion. See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p>Note: The icons are displayed only in table views.</p>
Node Management Mode	<p>Indicates whether the current node is being managed. This field also lets you specify whether a node is temporarily out of service. Possible values are:</p> <ul style="list-style-type: none">  Managed – Indicates the node is managed by NNMi.  Not Managed – Indicates the node is intentionally not managed. For example, the node might not be accessible because it is in a private network. NNMi does not update discovery information or monitor these nodes.  Out of Service – Indicates a node is unavailable because it is out of service. NNMi does not update discovery information or monitor these nodes. <p>This attribute is useful for notifying NNMi when a device has been temporarily out of service, or should never be managed.</p>
<p>SNMP Agent State Attributes</p>	
SNMP Supported	<p>Indicates whether the node responded to SNMP requests to determine whether the node has an SNMP agent.</p>


Attribute	Description
State	<p>Indicates whether the SNMP Agent assigned to this node is available and how NNMi is using SNMP to interact with this SNMP Agent. Possible values are:</p> <p> Normal – Indicates that the agent responded to an SNMP query.</p> <p> Unresponsive – Indicates that the SNMP agent did not respond to an SNMP query.</p> <p>Note: State is determined by the State Poller Service. The current state contributes towards the status calculation for the node. See the Status tab for more information.</p>
State Last Modified	Indicates the date and time when the State value was last modified.
SNMP Agent	<p>IP address of the SNMP Agent assigned to the current node. This can be the address of either the SNMP agent on the device or an SNMP Proxy Server configured to pass along information from that SNMP agent.</p> <p>Click the  Lookup icon and select  Open to display the the "SNMP Agent Form" (on page 49) for more information.</p>
Discovery Attribute	
Device Profile	<p>Name of the device profile that determines how devices of this type are managed and the icon and background shape displayed on maps.</p> <p>Click the  Lookup icon and select  Open to display the "Device Profile Form" (on page 54) for more information.</p>
Discovery State	<p>Current discovery status for the node. Possible values are:</p> <p>Newly Created – Indicates the node and its IP addresses are in the NNMi database, but further information needs to be collected before state and status are determined.</p> <p>Discovery Completed – Indicates that all of the discovery information for the node has been collected.</p> <p>Rediscovery in Process – Indicates discovery is updating information that has been collected for the node.</p>
Last Completed	Time of the last discovery cycle.
Notes	<p>Provided for network operators to use for any additional notes required to further explain the node. Information might include why the node is important, if applicable, or to what customer, department, or service the node is related. Additional information might include where the nodes is located, who is responsible for it, and its serial number. You might also track maintenance history using this attribute.</p> <p>Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p> <p>Note: You can sort your node table views based on this value. Therefore, you might want to include keywords for this attribute value.</p>

Node Form: General Tab

The "[Node Form](#)" (on page 27) provides details about the selected node.

For information about each tab:

SNMP Values


Attribute	Description
System Name	<p>The MIB II sysName value returned from the device's SNMP agent. This attribute is set by the device administrator.</p> <p>If sysName is part of the strategy used to populate the node Name attribute value, NNMi avoids populating the NNMi database with multiple devices having the same manufacturer's default name by following a set of rules. Click here for details.</p> <p>For each device type, NNMi has a Device Profile that includes a record of the manufacturer's default sysName. Other settings within the Device Profile can change the way NNMi determines sysName values.</p> <p>To view the Device Profile associated with this node, locate the Device Profile attribute in the Basics section of the Node form, and click the  Lookup icon. Your NNMi administrator can make changes to a Device Profile, if necessary.</p>
System Contact	Optional MIB II sysContact value. This attribute is set by the device administrator. It usually includes the contact person for the managed node as well as information about how to contact this person.
System Description	Optional MIB II sysDescr value for the device description. This attribute is set by the device administrator.
System Object ID	MIB II sysObjectID value provided by the vendor. This value identifies the device vendor, type, and model. For example, all Cisco 6509 devices have the same system object ID.
System Location	Optional MIB sysLocation value for the physical location of the current node. For example, Building K, 3rd floor. This attribute is set by the device administrator.

Node Form: IP Addresses Tab

The "[Node Form](#)" (on page 27) provides details about the selected node.

For information about each tab:

IP Addresses Table


Attribute	Description
IP Addresses	<p>Table view of the IP addresses associated with the selected node. You can use this table to determine the status, state, address, interface, and subnet for each address associated with the selected node.</p> <p>Click the  Open icon to open the "IP Address Form" (on page 72) and view more information about a specific address.</p>

Node Form: Interfaces Tab

The "[Node Form](#)" (on page 27) provides details about the selected node.

For information about each tab:

Interfaces Table


Attribute	Description
Interfaces	<p>Table view of all of the interfaces associated with the current node. You can use this table to determine the status, administrative state, operational state, name, type, interface speed, and Layer 2 connection for each interface associated with the selected node.</p> <p>Click the  Open icon to open the "Interface Form" (on page 58) and view more information about a specific interface.</p>

Node Form: VLAN Ports Tab

The ["Node Form" \(on page 27\)](#) provides details about the selected node.

For information about each tab:

VLAN Ports Table


Attribute	Description
VLAN Ports	<p>Table view of all of the VLAN ports associated with the current node. Use this table to determine all port and VLAN combinations associated with this node.</p> <p>Click the  Open icon to open the Port form and view more information about a specific VLAN port.</p>

Node Form: Ports Tab

The ["Node Form" \(on page 27\)](#) provides details about the selected node.

For information about each tab:

Ports Table

Attribute	Description
Ports	<p>Table view of all of the ports associated with the current node. You can use this table to determine the VLAN membership of each port associated with the selected node.</p> <p>Click the  Open icon to open the "Port Form" (on page 86) and view more information about a specific port.</p>

Node Form: Capabilities Tab

The Node Form: Capabilities Tab displays a table view of any capabilities added to the node object by NNMi or an external application. Capabilities enable NNMi and application programmers to provide more information about a node than is initially stored in the NNMi database. For example, NNMi Advanced uses the capability `com.hp.nnm.capability.rrp.hsrp` when a node is a member of an HSRP group.

Note: Because the values are generated by NNMi or an external application, Capability values cannot be modified.

For information about each tab:

Capabilities Table

Attribute	Description
Capability	The name of the capability added to a node object by either NNMi or an external application. For more information, see: <ul style="list-style-type: none"> • "Node Capability Form" (on page 36) • "Node Capabilities Provided by NNMi" (on page 34)
Unique Key	The database identifier for the capability that either NNMi or an external application added to this node. <p>Note: Capabilities added by NNMi use a Unique Key value that begins with the prefix: <code>com.hp.nnm.capability</code>. See "Node Capabilities Provided by NNMi" (on page 34) for a description of the capabilities provided by NNMi that might appear on the Node Form: Capabilities Tab.</p>

Node Capabilities Provided by NNMi

The Node Form: Capabilities Tab displays a table view of any capabilities added to the node object. Capabilities that begin with `com.hp.nnm.capability` represent capabilities that NNMi provides. External applications can also add node capabilities.

Note: NNMi also provides Capabilities on the Interface form **Capabilities** tab, additional abilities assigned to an interface by either NNMi or an external application. Capabilities enable NNMi and application programmers to provide more information about an interface than is initially stored in the NNMi database.

The following table includes the node capabilities NNMi provides to assist in determining node component health metrics. See ["Node Form: Component Health Tab" \(on page 38\)](#) for more information about health metrics.

Virtual Router Redundancy Protocol (VRRP) or Hot Standby Router Protocol (HSRP)

NNMi Node Capabilities

Capability	Unique Key	Description
CHASSISMGREXT-MIB MIB	<code>com.hp.nnm.capability.metric.cme</code>	The node supports the indicated MIB.
CISCO-ENHANCED-BUFFER-MIB	<code>com.hp.nnm.capability.metric.ceb</code>	The node supports the indicated MIB.
CISCO-ENHANCED-MEMORY-POOL-MIB	<code>com.hp.nnm.capability.metric.cem</code>	The node supports the indicated MIB.
CISCO-ENVMON-MIB	<code>com.hp.nnm.capability.metric.cenv</code>	The node supports the indicated MIB.
Cisco Env Fan	<code>com.hp.com.capability.metric.cisco.env.fan</code>	The node supports CISCO-ENVMON-MIB.
Cisco Env Power	<code>com.hp.com.capability.metric.cisco.env.power</code>	The node supports CISCO-ENVMON-MIB.

Capability	Unique Key	Description
Cisco Stack Fan	com.hp.nnm.capability.metric.cisco.stack.fan	The node supports CISCO-STACK-MIB.
Cisco Stack Power	com.hp.nnm.capability.metric.cisco.stack.power	The node supports CISCO-STACK-MIB.
CISCO-MEMORY-POOL-MIB	com.hp.nnm.capability.metric.cmp	The node supports the indicated MIB.
CISCO-PROCESS-MIBv1	com.hp.nnm.capability.metric.cpm1	The node supports the indicated MIB.
CISCO-PROCESS-MIBv2	com.hp.nnm.capability.metric.cpm2	The node supports the indicated MIB.
CISCO-SYSTEM-EXT-MIB	com.hp.nnm.capability.metric.cse	The node supports the indicated MIB.
HOST-RESOURCES-MIB	com.hp.nnm.capability.metric.hr	The node supports the indicated MIB.
IP Forwarding (Layer 3)	com.hp.nnm.capability.node.ipforwarding	Value that indicates NNMi identified the selected node as a router that forwards Layer 3 data. NNMi evaluates SNMP MIB-II sysServices and other clues to determine this value and set the symbols in map views. The NNMi administrator can override this value using the Device Profile form, Force Device attribute (see "Device Profile Form" (on page 54)).
LAN Switching (Layer 2)	com.hp.nnm.capability.node.lanswitching	Value that indicates NNMi identified the selected node as a switch for Layer 2 data. NNMi evaluates SNMP MIB-II sysServices and other clues to determine this value and set the symbols in map views. The NNMi administrator can override this value using the Device Profile form, Force Device attribute (see "Device Profile Form" (on page 54)).

Capability	Unique Key	Description
Nortel Passport Metrics	com.hp.nnm.capability.metric.rc	The node is a Nortel Passport device.
Nortel BayStack Metrics	com.hp.nnm.capability.metric.s5	The node is a Nortel BayStack devices.
OLD-CISCO-BUFFER-MIB	com.hp.nnm.capability.metric.ocb	The node supports the indicated MIB.
OLD-CISCO-CPU-MIB	com.hp.nnm.capability.metric.occ	The node supports the indicated MIB.
OLD-CISCO-MEMORY-MI	com.hp.nnm.capability.metric.ocm	The node supports the indicated MIB.

NNMi Advanced Additional Capabilities

Capability	Unique Key	Description
FDVRRP	com.hp.nnm.capability.rrp.fdvrrp	<i>NNMi Advanced.</i> The node is a member of a Foundry Virtual Router Redundancy Protocol (FDVRRP) group.
HPVRRP	com.hp.nnm.capability.rrp.hpvrp	<i>NNMi Advanced.</i> The node is a member of an HP Virtual Router Redundancy Protocol (HPVRRP) group.
HSRP	com.hp.nnm.capability.rrp.hsrp	<i>NNMi Advanced.</i> The node is a member of an Hot Standby Router Protocol (HSRP) group.
RCVRRP	com.hp.nnm.capability.rrp.rcvrrp	<i>NNMi Advanced.</i> The node is a member of a Nortel Rapid City Virtual Router Redundancy Protocol (RCVRRP) group.
VRRP	com.hp.nnm.capability.rrp.vrrp	<i>NNMi Advanced.</i> The node is a member of a Virtual Router Redundancy Protocol (VRRP)group.

Node Capability Form

This form describes a capability added to the node object by NNMi or an external application. Capabilities enable NNMi and application programmers to provide more information about a node than what is initially stored in the NNMi database. For example, NNMi Advanced uses the capability `com.hp.nnm.capability.rrp.hsrp` to identify when a node is a member of an HSRP group.

Note: Because the values are generated by NNMi or an external application, Capability values cannot be modified.

Each of the Capability attributes is described in the table below.

Basics Attributes

Attribute	Description
Capability	Label used to identify the Capability that was added to the node object. The Capability value is listed in the table on the Capabilities tab in a Node form. See "Node Form: Capabilities Tab" (on page 33) .
Unique Key	Used as a unique identifier for the Capability. Any capability provided by NNMi begins with the prefix <code>com.hp.nnm.capability</code> . Note: Capabilities added by NNMi use a Unique Key value that begins with the prefix: <code>com.hp.nnm.capability</code> . See "Node Capabilities Provided by NNMi" (on page 34) for a description of the capabilities provided by NNMi that might appear on the Node Form: Capabilities Tab.

Node Form: Custom Attributes Tab

Custom Attributes enable an NNMi administrator to add information to the Node object. Custom Attributes can also be set by external applications that have been integrated with NNMi.

The Node Form: Custom Attributes Tab displays a table view of any Custom Attributes that have been added to the selected node. For example, your NNMi administrator might have added **Serial Number** as another attribute for the nodes in your network.

Note: If your role allows, you can edit a Custom Attribute. Only user accounts with NNMi Administrator role can add a Custom Attribute.

For information about each tab:

Custom Attributes Table

Attribute	Description
Name	Name used to identify the Custom Attribute.
Value	The actual value for the Custom Attribute for the selected node. For example, the value for the Serial Number attribute might be: UHF536697J3

Node Custom Attributes Form

Custom Attributes enable an NNMi administrator to add information to a node object. For example, your NNMi administrator might have added **Serial Number** as another attribute for the nodes in your network. Custom Attributes can also be set by external applications that have been integrated with NNMi.

The Custom Attributes form displays the Name and Value for each of the Custom Attributes that were added to the node object. Each of these attributes is described in the table below.

Basics Attributes


Attribute	Description
Name	Name used to identify the Custom Attribute. This name appears in the table view on the Custom Attributes tab in Node forms.
Value	Value assigned to the Custom Attribute for the selected node. For example, the value for the Serial Number attribute might be: UHF536697J3 .

Node Form: Node Groups Tab

The "[Node Form](#)" (on page 27) provides details about the selected node.

For information about each tab:

Node Groups Table

Attribute	Description
Node Groups	Table view of all Node Groups to which this node belongs. Click the  Open icon to view more information about a specific Node Group filter configuration.

Node Form: Component Health Tab

The "[Node Form](#)" (on page 27) provides details about the selected node.

The Node Form: Component Health tab displays information about node health related to the following fault metrics:


- Fan
- Power Supply
- Temperature
- Voltage

NNM iSPI for Performance. If the NNM iSPI for Performance is installed and configured within your environment, the Node Form: Component Health tab also displays information about node health related to the following performance metrics:

- CPU utilization
- Memory utilization
- Buffer utilization
- Buffer miss rate
- Buffer failure rate

For information about each tab:

Component Health Table

Attribute	Description
Component Health	Table view of the health metrics associated with the current node. You can use this table to determine the Status, Name, and Type for each health metric associated with the selected node. Click the  Open icon to open the " Node Component Form " (on page 38) and view more information about a specific metric and its monitored attributes.

Node Component Form

This form describes the fault and performance metrics used to monitor node component health. NNMi obtains fault metrics from the node's MIB files. The NNMi administrator can set threshold values for each of the performance health metrics displayed.

Fault metrics include the following:









- Fan
- Power Supply
- Temperature
- Voltage

NNM iSPI for Performance. The following performance metrics require an NNM iSPI for Performance license:

- CPU utilization
- Memory utilization
- Buffer utilization
- Buffer failures
- Buffer misses

For information about each tab:

Basic Attributes

Attribute	Description
Status	<p>Overall status for the current node. NNMi follows the ISO standard for status classification. See the "Node Component Form: Status Tab " (on page 43) for more information. Possible values are:</p> <ul style="list-style-type: none"> No Status Normal Disabled Unknown Warning Minor Major Critical

For information about how the current status was determined, see the [Conclusions tab](#). Status reflects the most serious outstanding conclusion. See ["Watch Status Colors" \(on page 126\)](#) for more information about possible status values.

Note: The icons are displayed only in table views.

Attribute	Description
Name	<p>Name of the node component whose health attribute is being measured, For example, NNMi measures fault metrics for Fan, Power Supply, Temperature, and Voltage node components.</p> <p><i>NNM iSPI for Performance.</i> If licensed and installed, NNM iSPI for Performance also measures performance metrics for CPU, memory, and buffer utilization, as well as for buffer failures and misses.</p> <p>When possible, NNMi obtains the Name value for the node component from the associated MIB file. The number of MIBs available and subsequently the number of health attributes that are measured for each node component vary. For example, if the node component is of type Buffer, up to five MIBs that contain information about the Buffer component are available (Small, Medium, Large, Big, and Huge). NNMi collects information from each MIB that is available and lists a node component Name value for each. For example, If all five MIBs are available, you see the following node components listed in the Component Health table: Small Buffers, Medium Buffers, Large Buffers, Big Buffers, and Huge Buffers.</p> <p>Note: If the associated MIB file does not provide a name value, NNMi uses the value contained in the Type attribute.</p>
Type	<p>Identifies the aspect of node health that is being monitored. Possible values include:</p> <ul style="list-style-type: none"> ● Fan ● Power Supply ● Temperature ● Voltage <p><i>NNM iSPI for Performance.</i> The following performance types require an NNM iSPI for Performance license:</p> <ul style="list-style-type: none"> ● CPU utilization ● Memory utilization ● Buffer utilization ● Buffer failures ● Buffer misses
Hosted On Node	<p>Node on which the health metric is being measured. This is the current value in NNMi's database for the Name attribute of the host device. The value could be a DNS name, a MIB II sysName, or an address (depending on how your NNMi administrator configured the discovery process).</p>

Node Component Form: Health Attributes Tab


The "[Node Component Form](#)" (on page 38) provides details about the monitored attributes for the current node.

For information about each tab:

Attributes Table

Description

Table view of the Name and State of each monitored attribute associated with the health metric for the selected node component. Use this view to determine the State of the monitored attributes for the selected node.

Click the  Open icon to open the "[Health Attribute Form](#)" (on page 41) and view more information about a specific attribute.

Health Attribute Form

The Health Attribute form displays information about node component health related to the selected attribute .

Fault metrics are available for the following node components

- Fan
- Power Supply
- Temperature
- Voltage

NNMi obtains fault metric information from the associated MIB.

NNM iSPI for Performance. If the NNM iSPI for Performance is installed and configured within your environment, the Node Form: Component Health tab also displays information about node health related to the following performance metrics. The NNMi administrator sets the threshold for node components related to performance metrics:

- CPU utilization
- Memory utilization
- Buffer utilization
- Buffer miss rate
- Buffer failure rate

Basics Attributes












Attribute	Description
-----------	-------------

Name	Name used to identify the attribute being monitored.
------	------------------------------------------------------

The number of health attributes available vary depending on the number of MIBs available for the current node component. See "[Node Component Form](#)" (on page 38) for more information.

The Name of each health attribute identifies the attribute being measured as well as the type of MIB used to gather this information. For example, when monitoring CPU utilization, NNMi uses values measured for 1-minute, 5-minute, and 5-second intervals. Each of these values might be available from an old, standard, or most recent (revised) MIB file. The following example health attribute names indicate the CPU measurement interval as well as the fact that the information was collected from the most recent (revised) MIB:

- CPU Revised 1 Minute
 - CPU Revised 5 Minute
 - CPU Revised 5 Second
-

Attribute	Description
State	<p>Normalized value used to indicate the State of the health attribute on the selected node. Possible values are listed below.</p> <p>Note: The NNMi State Poller interprets and normalizes the State value returned for the monitored attribute to handle the differences between vendor-specific nodes.</p> <ul style="list-style-type: none"> Normal - Indicates there are no known problems related to the associated object. Warning - Indicates there may or may not be a problem related to the associated object. Minor - Indicates NNMi has detected problems related to the associated object that require further investigation. Major - Indicates NNMi detected problems that could precede a critical situation. Critical - Indicates NNMi detected problems that require immediate attention. <p>One of following States is returned when the monitored attribute is not polled or when the State data returned for the monitored attribute is either unavailable or in error:</p> <ul style="list-style-type: none"> Not Polled - Indicates that this health attribute is intentionally not polled, based on current Monitoring Configuration settings, current Communication Configuration settings, or because the parent Node is set to Not Managed or Out of Service No Polling Policy - No polling policy exists for this monitored attribute. Unavailable - Unable to determine the State. For example, the value returned might be outside the range of possible values. <p>Note: State is determined by the State Poller Service. The current state contributes towards the status calculation for the node. See the Status tab for more information.</p> <p><i>NNM iSPI for Performance.</i> Additional States for performance metrics include the following (Warning and Critical states are not used for performance metrics):</p> <ul style="list-style-type: none"> High - The High threshold was crossed. Low - The Low threshold was crossed. None - The threshold value returned is zero.

Node Component Form: Incidents Tab

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in the incident view's column headings.


The "[Node Component Form](#)" (on page 38) provides details about the monitored attributes for the selected node.

For information about each tab:

Incidents Table

Description

Table view of the incidents associated with the selected monitored attribute. These incidents are sorted by creation time so that you can view the incidents in chronological order. Use this view to determine which incidents are still open for the monitored attribute.









Click the  Open icon to open the "[Incident Form](#)" (on page 132) and view more information about a specific incident.

Node Component Form: Status Tab

The "[Node Component Form](#)" (on page 38) provides details about the selected health metric for the current node.

For information about each tab:

Overall Status

Attribute	Description
Status	<p>Overall status for the current node. NNMi follows the ISO standard for status classification. Possible values are:</p> <ul style="list-style-type: none"> No Status Normal Disabled Unknown Warning Minor Major Critical

Note: Your NNMi administrator might have disabled polling of Node Component Health using the Monitoring Configuration workspace.

The status of the health metric associated with this node contributes to the node's overall status. For information about how the current status was determined, see the "[Node Component Form: Conclusions Tab](#)" (on page 44). Status reflects the most serious outstanding conclusion. See "[Watch Status Colors](#)" (on page 126) for more information about possible status values.

Note: The icons are displayed only in table views.


Status Last Modified	Date and time indicating when the status was last set.
----------------------	--------------------------------------------------------

Node Component Form: Conclusions Tab

The "[Node Component Form](#)" (on page 38) provides details about the selected health metric for the current node.

For information about each tab:

Outstanding Status Conclusions Table

Attribute	Description
Status Conclusions	<p>The dynamically generated list of summary statuses of the monitored attribute at points in time that contributed to the current overall status of the selected node. Status is set by the Causal Engine.</p> <p>Each conclusion listed is outstanding and contributes to the current overall status.</p> <p>This view is useful for obtaining a quick summary of the problem description for the current monitored attribute that led up to the node's most current status.</p> <p>The status value is correlated based on the most critical conclusions.</p> <p>To see more information about a specific conclusion:</p> <ol style="list-style-type: none"> 1. Select the conclusion of interest by checking the <input checked="" type="checkbox"/> selection box that precedes the object information. 2. Click the  Open icon to view more information about a specific conclusion.

Node Form: Diagnostics Tab (NNM iSPI NET)

The "[Node Form](#)" (on page 27) provides details about the selected node.

When you access the Node Form: Diagnostics Tab, you can view the history of all the NNM iSPI NET Diagnostic reports that have been run for this Node. Diagnostics are sets of automated commands specific to one or more device types, including Cisco routers and switches, Cisco switch/routers, and Nortel switches.

To generate a new instance of these Diagnostics reports, click **Actions** → **Run Diagnostics**.

For information about each tab:

Diagnostics Table

Attribute	Description
Start Time	Date and time NNM iSPI NET created this instance of the Diagnostics report. NNM iSPI NET uses the locale of the client and the date and time from the NNMi management server.
Definition	The name of the NNM iSPI NET Diagnostics report definition.

Attribute	Description
Status	<p>The current status of this NNM iSPI NET Diagnostics report. Possible values include:</p> <p>New - The Diagnostic is in the queue, but is not yet running</p> <p>In Progress -The Diagnostic has been submitted and is not finished running</p> <p>Completed - The Diagnostic has finished running</p> <p>Not Submitted - An error condition prevented the Diagnostic from being submitted</p> <p>Timed Out - NNMi was unable to submit or run the Diagnostic due to a time out error. The time out limit for submitting a Diagnostic is one hour. The time out limit for running a Diagnostic is four hours.</p> <p>Example error conditions include the following:</p> <ul style="list-style-type: none"> • The number of Diagnostics in the queue might prevent NNMi from submitting the Diagnostic. • A configuration error, such as an incorrect user name or password, might prevent NNMi from accessing the required Operations Orchestration server. <p>Contact your NNMi administrator for Diagnostic log file information.</p>
Report	<p>Click this link to open the actual report.</p> <p>Note: You might be prompted to provide a user name and password to access the Operations Orchestration software. See the <i>iSPI NET Planning and Installation Guide</i> for more information.</p>
Last Update Time	<p>Date and time NNM iSPI NET last updated this instance of the Diagnostics report. NNM iSPI NET uses the locale of the client and the date and time from the NNMi management server.</p>

Node Diagnostic Results Form (Flow Run Result) (NNM iSPI NET)

NNM iSPI NET automatically prepares diagnostic reports about the source node when certain incidents are generated and when using **Actions** → **Run Diagnostics**. This form shows details about the currently selected diagnostic report instance.

Note: Because the values on this form are generated by NNM iSPI NET, these attribute values cannot be modified.

See "[Node Form: Diagnostics Tab \(NNM iSPI NET\)](#)" (on page 44) for more information.

Diagnostic Results Details

Attribute	Description
Start Time	The time that NNM iSPI NET created the selected diagnostic report instance.
Definition	The name of the flow as defined in NNM iSPI NET.

Attribute	Description
Status	<p>The current status of this NNM iSPI NET Diagnostics report. Possible values include:</p> <p>New - The Diagnostic is in the queue, but is not yet running</p> <p>In Progress -The Diagnostic has been submitted and is not finished running</p> <p>Completed - The Diagnostic has finished running</p> <p>Not Submitted - An error condition prevented the Diagnostic from being submitted</p> <p>Timed Out - NNMi was unable to submit or run the Diagnostic due to a time out error. The time out limit for submitting a Diagnostic is one hour. The time out limit for running a Diagnostic is four hours.</p> <p>Example error conditions include the following:</p> <ul style="list-style-type: none"> • The number of Diagnostics in the queue might prevent NNMi from submitting the Diagnostic. • A configuration error, such as an incorrect user name or password, might prevent NNMi from accessing the required Operations Orchestration server. <p>Contact your NNMi administrator for Diagnostic log file information.</p>
Report	<p>NNM iSPI NET uses this text string to display the selected instance of the diagnostics report in a browser window.</p>
Lifecycle State	<p>The Incident's Lifecycle State that determines when this Diagnostic runs. Possible values include:</p> <ul style="list-style-type: none"> • Registered • In Progress • Completed • Closed <p>See About the Incident Lifecycle for more information about Lifecycle State.</p> <p>When the Incident is set to this Lifecycle State, the selected Diagnostics (Flow Definitions) is automatically run on each applicable Source Node in the specified Node Group.</p>
Last Update Time	<p>Date and time NNM iSPI NET last updated this instance of the Diagnostics report. NNM iSPI NET uses the locale of the client and the date and time from the NNMi management server.</p>

Node Form: Incidents Tab

Tip: See "[Incident Form](#)" ([on page 132](#)) for more details about the incident attributes that appear in the incident table view's column headings.


The "[Node Form](#)" ([on page 27](#)) provides details about the selected node.

For information about each tab:

Incidents Table

Description

Table view of the incidents associated with the selected node. These incidents are sorted by creation time so that you can view the incidents in chronological order. Use this view to determine which incidents are still open for the selected node.









Click the  Open icon to open the ["Incident Form" \(on page 132\)](#) and view more information about a specific incident.

Node Form: Status Tab


The ["Node Form" \(on page 27\)](#) provides details about the selected node.

For information about each tab:

Overall Status

Attribute	Description
Status	<p>Overall status for the current node. NNMi follows the ISO standard for status classification. Possible values are:</p> <ul style="list-style-type: none"> No Status Normal Disabled Unknown Warning Minor Major Critical <p>The status of all IP addresses and the SNMP Agent associated with this node, and well as interface health contribute to node status. For information about how the current status was determined, see the "Node Form: Conclusions Tab" (on page 48). Status reflects the most serious outstanding conclusion. See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p>Note: The icons are displayed only in table views.</p>
Status Last Modified	Date and time indicating when the status was last set.

Status History Table


Attribute	Description
Status History	List of up to the last five changes in status for the selected node. This view is useful for obtaining a quick summary of the node status so that you can better determine any patterns in node behavior and activity. Click the  Open icon to view more information about a specific status.

Node Form: Conclusions Tab

The "Node Form" (on page 27) provides details about the selected node.

For information about each tab:

Outstanding Status Conclusions Table

Attribute	Description
Status Conclusions	The dynamically generated list of summary statuses of the node at points in time that contributed to the current overall status of the selected node. Status is set by the Causal Engine. Each conclusion listed is still outstanding and applies to the current overall status. This view is useful for obtaining a quick summary of the status and problem description for the current node's interfaces that led up to the node's most current status. Examples of conclusions that might appear together are listed below: <ul style="list-style-type: none">● SNMP Agent Not Responding● Interface Down● Address Down The status value is correlated based on the most critical conclusions. Click the  Open icon to view more information about a specific conclusion.

Node Form: Registration Tab

The "Node Form" (on page 27) provides details about the selected node.

For information about each tab:

Registration

Attribute	Description
Created	Date and time the selected object instance was created. NNM uses the locale of the client and the date and time from the NNMi management server.
Last Modified	Date the selected object instance was last modified. NNM uses the locale of the client and the date and time from the NNMi management server.

SNMP Agent Form

The SNMP Agent form provides details about the SNMP Agent assigned to the currently selected node. This form is useful when you want to view more details about the SNMP Agent, including the agent's status. You can also use the form to determine all of the attributes in the NNMi database associated with the SNMP Agent.

For information about each tab:

Basic Attributes

Attribute	Description
Name	Name used to identify the agent. By default, this name is the DNS resolved hostname for the node.






Attribute	Description
Management Address	<p>IP address NNMi uses to communicate with this SNMP agent.</p> <p>: The NNMi administrator can specify an address (Communication Configurations workspace, Specific Node settings tab), or NNMi can dynamically select one.</p> <p>When NNMi determines the Management Address, NNMi handles cases where the SNMP agent supports multiple IP addresses by following a set of rules. Click here for details.</p> <ol style="list-style-type: none"> If the node has only one loopback address¹, that address is used with the following exceptions: <ul style="list-style-type: none"> NNMi prefers loopback interfaces for management communication, where possible. However, NNMi automatically filters out addresses in the reserved loopback network range 127/24 (127.*.*). NNMi ignores any address that is virtual (HSRP/VRRP), an Anycast Rendezvous Point IP Address², or whose interface is administratively down. If an SNMP agent supports multiple loopback addresses, NNMi uses the loopback address with the lowest number to which this SNMP agent responds (for example, 10.16.42.197 is a lower number than 10.16.197.42). If no loopback address is supported, NNMi uses the address that meets the following criteria: <ul style="list-style-type: none"> During initial discovery, NNMi uses the first address to which the associated SNMP agent responded. <p>Note: The <i>first address</i> might be <i>either</i> a discovery seed address or an ARP cache address gathered in the path to this node.</p> During any other discovery cycle, NNMi uses the current Management Address value. <p>For this sequence, if the SNMP agent does not respond to any of the above addresses, NNMi automatically repeats the sequence with SNMPv2c, SNMPv1, and SNMPv3 (according to the current NNMi Communication Configuration settings established by your NNMi administrator).</p> <p>This sequence is repeated during each configuration polling cycle. And the address could change over time (for example, if an address did not respond to SNMP queries due to network problems or node reconfiguration).</p>
Protocol Version	Version of the SNMP protocol in use. NNMi supports SNMP version 1 and 2.

¹The address associated with the loopback interface. The loopback interface is a virtual interface on a device that provides a route for internal communication. Many vendors provide a specially configured loopback for management purposes. Exact details of how loopbacks are configured varies by vendor and model. See each device's documentation for details. NNM identifies these loopback addresses by using IfType 24, softwareloopback from the IANA ifType-MIB.

²Rendezvous Point addresses are loopback addresses used for routers in multi-cast network configurations

Attribute	Description
Read Community String	Community string value that was discovered for the selected SNMP agent. Note: The community string is an SNMPv1 or SNMPv2c password. The actual community string is only visible if you are assigned to the Administrator role.
UDP Port	User Datagram Protocol port configuration for this SNMP agent. Default 161. Port NNMi is instructed to use when contacting this SNMP agent to collect SNMP data. Both the Discovery Process and the State Poller Service use this setting.
SNMP Proxy Address	<i>Prerequisite:</i> The NNMi administrator must specify one or more SNMP Proxy Servers in the NNMi Communication Configuration settings. The IP address of the server that is acting as the SNMP Proxy Server for this SNMP agent. Your NNMi administrator might have set up one or more SNMP Proxy Servers to allow communication with nodes that otherwise might be unreachable. For example, when a node to be managed is behind a firewall. The SNMP Proxy Server enables NNMi to manage these nodes in the same way as nodes that provide SNMP access directly.
SNMP Proxy Port	<i>Prerequisite:</i> The NNMi administrator must specify one or more SNMP Proxy Servers in the NNMi Communication Configuration settings. The port number on the server that is acting as the SNMP Proxy Server for this SNMP Agent. See SNMP Proxy Address (previous attribute) for more information.
SNMP Time-out	(Seconds:Milliseconds) Time that NNMi waits for a response to an SNMP query before reissuing the request.
SNMP Retries	Maximum number of retries that NNMi issues for an SNMP query before determining the query result to be "unresponsive". Zero means no retries.

SNMP Agent State Attributes










State	Indicates whether the SNMP agent is available and how NNMi is using SNMP to interact with this SNMP agent. Possible values are:  Normal – Indicates that the agent is being polled and responded to SNMP queries.  Unresponsive – Indicates that the agent is being polled, but did not respond to SNMP queries. Note: NNMi's State Poller sets this state. The current state contributes towards the status calculation for the agent. See " SNMP Agent Form: Status Tab " (on page 52) for more information.
State Last Modified	Indicates the date and time when the State value was last modified.
Hosted On Node	Node on which the SNMP Agent resides. This is the current value in NNMi's database for the Name attribute of the host device. The value could be a DNS name, a MIB II sysName, or an address (depending on how your NNMi administrator configured the discovery process). Click the  Lookup icon and select  Quick View or  Open to display more information about the node.

SNMP Agent Form: Status Tab

The "[SNMP Agent Form](#)" (on page 49) provides details about the SNMP Agent of the selected node or interface.

For information about each tab:

Status


Attribute	Description
Status	<p>Overall status for the current SNMP agent. NNMi follows the ISO standard for status classification. Possible values are:</p> <ul style="list-style-type: none">  No Status  Normal  Disabled  Unknown  Warning  Minor  Major  Critical <p>For information about how the current status was determined, see "SNMP Agent Form: Conclusions Tab" (on page 52). Status reflects the most serious outstanding conclusion.</p>
Status Last Modified	Date and time indicating when the status was last set.
Status History	<p>List of the changes in the status for the SNMP agent.</p> <p>Click the  Open icon to view more information about a specific status.</p>

SNMP Agent Form: Conclusions Tab

The "[SNMP Agent Form](#)" (on page 49) provides details about the SNMP Agent of the selected node or interface.

For information about each tab:

Conclusions Table


Attribute	Description
Outstanding Status Conclusion	<p>The dynamically generated list of summary statuses for the SNMP agent at points in time that contributed to the current overall status of the selected SNMP agent. Status is set by the Causal Engine.</p> <p>Each conclusion listed is still outstanding and applies to the current overall status.</p> <p>This view is useful for obtaining a quick summary of the status and problem description for the current node's interfaces that led up to the node's most current status.</p> <p>Examples of conclusions that might appear together are listed below:</p> <ul style="list-style-type: none">● SNMP Agent Not Responding● Interface Down● Some Unresponsive Addresses In Node● Address Not Responding <p>The status value is correlated based on the most critical conclusions.</p> <p>Click the  Open icon to view more information about a specific conclusion.</p>

SNMP Agent Form: Incidents Tab

The "[SNMP Agent Form](#)" (on page 49) provides details about the SNMP Agent of the selected node or interface.

For information about each tab:

Incidents Table

Attribute	Description
Associated Incidents	<p>Table view of the incidents associated with the selected SNMP agent. These incidents are sorted by creation time so that you can view the incidents in chronological order. Use this view to determine which incidents are still open for the selected SNMP agent.</p> <p>Click the  Open icon to open the "Incident Form" (on page 132) and view more information about a specific incident.</p>

SNMP Agent Form: Registration Tab

The "[SNMP Agent Form](#)" (on page 49) provides details about the SNMP Agent of the selected node or interface.

For information about each tab:

Registration





Attribute	Description
Created	Date and time the selected object instance was created. NNM uses the locale of the client and the date and time from the NNMi management server.
Last Modified	Date the selected object instance was last modified. NNM uses the locale of the client and the date and time from the NNMi management server.

Device Profile Form

According to industry standards (RFC 1213, MIB II), each combination of vendor, device type, and model number is assigned a unique SNMP system object ID (sysObjectID). For example, all Cisco 6500 series switches have the same sysObjectID prefix: .1.3.6.1.4.1.9.* See the [Basic Attributes](#).

NNMi uses the [Advanced Settings](#) to make decisions about how devices are discovered and depicted on the NNMi maps.

Basic Attributes

Attribute	Description
Device Model	Device model name or number designator, determined by the vendor.
SNMP Object ID	MIB II sysObjectID number issued for this device type. These numbers are unique across all vendors.
Description	The description, based on information from the MIB II sysDescr string provided by the vendor. Maximum length 255 characters. Alpha-numeric, punctuation, spaces, and underline characters allowed.
Device Family	Device family name provided by the vendor; for example Cisco Catalyst 6500 Series Switches or HP AdvanceStack Routers. Click the  Lookup icon to access the "Device Family Form" (on page 56) for more details.
Device Vendor	Name of the vendor that manufactures the device. Click the  Lookup icon to access the "Device Vendor Form" (on page 56) for more details.
Device Category	The value of this attribute determines which background shape NNMi uses for the map icon representing devices of this type. See "About Map Symbols" for more information about the possible values. Click the  Lookup icon to access the "Device Category Form" (on page 57) for more details.
OUI	Organizationally unique identifier. The first three octets of the MAC address for the device that identify the device's vendor.
Author	Indicates who created the device profile. All profiles provided by NNMi have the value "HP Network Node Manager". Click the  Lookup icon to access the "Device Profile Author Form" (on page 57) for more details.

Advanced Settings Tab

Attribute	Description
Use of SNMP SysName for Node Name Resolution	

Attribute	Description
Never Use sysName	<p>If <input checked="" type="checkbox"/> enabled, Spiral Discovery does not allow a MIB II sysName value for the Name attribute for discovered Nodes of this type. If sysName is part of the current node Name strategy, NNMi uses the next designated node Name choice in the strategy established by your NNMi administrator.</p> <p>If <input type="checkbox"/> disabled, MIB II sysName can potentially be used as the Name attribute value for nodes of this type.</p>

Do not Use sysName Starting With	<p>The vendor's default sysName text string, from MIB II sysName.</p> <p>If the SNMP agent responds to a sysName request with a value that matches or starts with the entry in this field (case-sensitive), Spiral Discovery ignores the sysName and considers sysName to be unset. As a result, NNMi instead tries to find a DNS name or IP address for this node (according to the strategy established by your NNMi administrator).</p> <p>For example, when an SNMP agent responds with a default sysName, NNMi's maps might display multiple icons with the same name (one for every device of that type in your environment that responded to an SNMP query with the default sysName). Usually, the device administrator changes the default sysName value to something more meaningful, so this problem is avoided.</p>
----------------------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

Device Behaviors

Force Device	<p>This attribute enables the NNMi administrator to override the IP Forwarding (Layer 3) and LAN Switching (Layer 2) settings provided by Spiral Discovery (displayed on the "Node Form: Capabilities Tab" (on page 33)).</p> <p>Possible values are:</p> <ul style="list-style-type: none"> ● Force to router ● Force to switch ● Force to end node ● Force to switch and router <p>Reasons the NNMi administrator might want to use this attribute to override the IP Forwarding (Layer 3) and LAN Switching (Layer 2) capabilities setting for the device include the following:</p> <ul style="list-style-type: none"> ● The sysServices setting in the MIB that is used to determine the IP Forwarding (Layer 3) and LAN Switching (Layer 2) capability during discovery is not accurate due to an IOS defect on the device ● The device serves as a router, switch, or switch and router and the NNMi administrator wants to force the device to be treated as only one of the following: 1) a router, 2) a switch, or 3) a switch and router. <p>Devices whose Force Device attribute is set to either of the following are included in Layer 3 Neighbor View maps: 1) Force to router or 2) Force to switch and router.</p> <ul style="list-style-type: none"> ● The device serves as a virtual router, but should not be managed as a router. <p>Setting the Force Device attribute to Force to end node enables the NNMi administrator to configure discovery so NNMi ignores this device.</p>
--------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

Attribute	Description
Interface Reindexing Type	When an interface within a device changes (old one removed, new one added), the interface index number changes. State Poller uses the attribute specified here to detect the change. Your NNMi administrator chooses which interface attribute indicates a change: ifIndex, ifName, ifDescr, ifAlias, or a combination of ifName and ifDescr. See the General Interface Attributes (SNMP Values) in Interface Form for more information.

Device Family Form

The Device Family attribute value indicates the family name assigned by the vendor when the device was manufactured; for example, the Cisco Catalyst 6500 Series Switches.

- NNMi monitoring behavior can potentially be configured differently for each family.
- Membership in a Node Group can potentially be determined by device family.

This form is accessed from the ["Device Profile Form" \(on page 54\)](#).

Device Family Definition

Attribute	Description
Label	Device family name. For example, Cisco Catalyst 6500 Series Switches or HP Advance-Stack Routers. Maximum length 255 characters. Alpha-numeric, punctuation, spaces, and underline characters allowed.
Unique Key	The required unique identifier that is important when exporting and importing device profile information within NNMi. The value must be unique. One possible strategy is to use the Java name space convention. For example: <code>com.<your_company_name>.nnm.deviceProfile.family.<family_label></code> Maximum length 80 alpha-numeric characters. Periods allowed. No spaces allowed.
Management URL	<i>Optional.</i> The URL to the device's management page (provided by the vendor). This page is used to provide configuration information for the device and is usually organized by device family.

Device Vendor Form

The Device Vendor attribute value indicates the name of the manufacturer of this device type; for example, HP or Cisco.

- NNMi monitoring behavior can potentially be configured differently for each vendor.
- Membership in a Node Group can potentially be determined by device vendor.

This form is accessed from the ["Device Profile Form" \(on page 54\)](#).

Device Vendor Definition

Attribute	Description
Label	Vendor name. Maximum length 255 characters. Alpha-numeric, punctuation, spaces, and underline characters allowed.
Unique Key	The required unique identifier that is important when exporting and importing device profile information within NNMi. The value must be unique. One possible strategy is to use the Java name space convention. For example: <code>com.<your_company_name>.nnm.deviceProfile.vendor.<vendor_label></code> Maximum length 80 alpha-numeric characters. Periods allowed. No spaces allowed.

Device Category Form

The Device Category attribute value indicates the category of this device; for example, router, switch, or printer. This attribute:

- In Map views, determines which background shape NNMi uses for the icon representing devices of this type.
- In table views, the category value can be used when sorting/filtering the Category column.
- During discovery, NNMi behavior changes based on the device category. For example, routers and switches are discovered by default.
- NNMi monitoring behavior can potentially be configured differently for each category.
- Membership in a Node Group can potentially be determined by device category.

This form is accessed from the ["Device Profile Form" \(on page 54\)](#).

Device Category Definition

Attribute	Description
Label	Category name. Maximum length 255 characters. Alpha-numeric, punctuation, spaces, and underline characters allowed.
Unique Key	The required unique identifier that is important when exporting and importing device profile information within NNMi. The value must be unique. One possible strategy is to use the Java name space convention. For example: <code>com.<your_company_name>.nnm.deviceProfile.category.<category_label></code> Maximum length 80 alpha-numeric characters. Periods allowed. No spaces allowed.

Device Profile Author Form

The Author attribute value indicates who created the device profile.

This form is accessed from the ["Device Profile Form" \(on page 54\)](#).

Device Category Author

Attribute	Description
Label	<p>Author name. If your NNMi administrator modified the default Device Profile provided by NNMi, a value other than HP Network Node Manager should appear.</p> <p>Maximum length 255 characters. Alpha-numeric, punctuation, spaces, and underline characters allowed.</p>
Unique Key	<p>The required unique identifier that is important when exporting and importing device profile information within NNMi.</p> <p>The value must be unique. One possible strategy is to use the Java name space convention. For example:</p> <pre>com.<your_company_name>.nnm.deviceProfile.author.<author_label></pre> <p>Maximum length 80 alpha-numeric characters. Periods allowed. No spaces allowed.</p>

Interface Form

The Interface form provides details about the network interface selected. From this form you can access more details about the parent [node](#), [addresses](#), current [network connection](#), and [incidents](#) associated with this interface.

If your role allows, you can use this form to modify the [Management Mode](#) for an interface (for example to indicate it will be temporarily out of service) or add [notes](#) to communicate information about this interface to your team.












If you see several blank fields for an interface in a form, the interface is a Nortel private interface. This means the following:







- The interface has no information in the MIB file.
- NNMi is not able to access the information that is normally available for other interfaces. Only limited attributes can be determined. Possible attribute values that might be collected include the MAC address and interface index.

For information about each tab:







Basic Attributes












Attribute	Description
Name	<p>The most accurate interface name available to the initial discovery process. First choice is the IF MIB <code>ifName</code> value. Second choice is the <code>ifAlias</code> value. Third choice is a combination of the <code>ifType[ifIndex]</code> value (for example, <code>ethernetCsmacd[17]</code>).</p>

Attribute	Description
Status	<p>Overall status for the current interface. NNMi follows the ISO standard for status classification. See the "Interface Form: Status Tab" (on page 70) for more information. Possible values are:</p> <ul style="list-style-type: none">  No Status  Normal  Disabled  Unknown  Warning  Minor  Major  Critical <p>Interface status is derived from SNMP polling results for ifAdminStatus and ifOperStatus, as well as from any conclusions. Status reflects the most serious outstanding conclusion. See the "Interface Form: Conclusions Tab" (on page 71) for information about how the current status was determined. See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p>Note: The icons are displayed only in table views.</p>
Management Mode	<p>The calculated Management Mode for the interface. This value should reflect the management mode assigned to the node on which the selected interface resides. For example, if the node's management mode is Managed, and the Direct Management Mode of the interface is Inherited, the interface's Management Mode value is Managed.</p>
Direct Management Mode	<p>Indicates whether the current interface is being managed. This attribute is set by the administrator and specifies whether an interface should be managed or whether an interface is temporarily out of service. Possible values are:</p> <ul style="list-style-type: none">  Inherited – Used to indicate that the interface should inherit the Management Mode from the node on which it resides.  Not Managed – Used to indicate that NNMi does not discover or monitor the interface. For example, the interface might not be accessible because it is in a private network.  Out of Service – Used to indicate an interface is unavailable because it is out of service. NNMi does not discover or monitor these interfaces. <p>This attribute is useful for notifying NNMi when an interface is temporarily out of service, or should never be managed.</p> <p>Note: If you change the Direct Management Mode, NNMi updates the calculated Management Mode on the form. If you manually set the Direct Management Mode and then Save your changes, the Management Mode value is not updated until you refresh the form.</p>

Attribute	Description
Hosted On Node	<p>Node on which the interface resides. This is the current value in NNMi's database for the Name attribute of the host device. The value could be a DNS name, a MIB II sysName, or an address (depending on how your NNMi administrator configured the discovery process).</p> <p>Click the  Lookup icon and select  Quick View or  Open to display more information about the node.</p>
Physical Address	<p>The interface's address at the physical layer, also known as the MAC address. This is the globally unique serial number assigned to each interface at the factory.</p>
Layer 2 Connection	<p>Used to indicate whether the selected interface is part of a Layer 2 connection. If the interface is part of a connection, use this attribute to access information about its Layer 2 connection and the neighboring device. Click here for instructions.</p> <ol style="list-style-type: none"> 1. Navigate to the Layer 2 Connection attribute. Click the  Lookup icon, and select  Open. 2. In the Layer 2 Connection form, locate the Interfaces tab. 3. Click the  Open icon of the other interface participating in this connection. 4. In the Interface form, locate the Hosted On Node attribute. 5. The Node form contains all known information about the neighboring node.

Interface State Attributes

Administrative State	<p>Either the current MIB II ifAdminStatus value (set by the device's administrator) or a value calculated by the State Poller Service. The current Administrative State contributes towards the status calculation for this interface. See the "Interface Form: Status Tab" (on page 70) for more information.</p> <p>Possible values are:</p> <ul style="list-style-type: none">  Up – The SNMP agent responded with an ifAdminStatus value of Up.  Down – The SNMP agent responded with an ifAdminStatus value of Down.  Testing – The SNMP agent responded with an ifAdminStatus value of Testing.  Other – The SNMP agent responded with a value for ifAdminStatus that is not recognized.  Not Polled – Indicates that this interface is intentionally not polled, based on current Monitoring Configuration settings, current Communication Configuration settings, or because the Interface or parent Node is set to Not Managed or Out of Service.  Agent Error – Indicates an SNMP error was returned in response to an SNMP query to this agent.
----------------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

Attribute	Description
Operational State	<p>Either the current MIB II ifOperStatus value or a value calculated by the State Poller Service. The current Operational State contributes towards the status calculation for this interface. See the "Interface Form: Status Tab" (on page 70) for more information.</p> <p>Possible values are:</p> <ul style="list-style-type: none">  Up – The SNMP agent responded that the interface is operationally up, ready to receive and send network traffic.  Down – The SNMP agent responded that the interface is operationally down.  Testing – The SNMP agent responded that the interface is in test mode.  Other – The SNMP agent responded with a value for ifOperStatus that is not recognized.  Unknown – The SNMP agent responded with an ifOperStatus value of Unknown.  Dormant – Indicates the SNMP agent responded that the interface is in a "pending" state, waiting for some external event.  Not Present – Indicates that the interface is missing some hardware component.  Lower Layer Down – Indicates the interface is down due to the state of lower-level interfaces.  Unavailable – The SNMP agent responded, but returned a null value for the ifOperStatus request.  Not Polled – Indicates that this interface is intentionally not polled, based on current Monitoring Configuration settings, current Communication Configuration settings, or because the parent Node or Interface is set to Not Managed or Out of Service.  Agent Error – Indicates an SNMP error was returned in response to an SNMP query to this agent.
State Last Modified	<p>Indicates the date and time when the Administrative State, Operational State, or both were last modified.</p>
Notes	<p>Provided for network operators to use for any additional notes required to further explain the interface. Information might include to what service or customer the interface is connected.</p> <p>Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p> <p>Note: You can sort your interface table views based on this value. Therefore, you might want to include keywords for this attribute value.</p>

Interface Form: General Tab

The ["Interface Form" \(on page 58\)](#) provides details about the selected network interface.

For information about each tab:

General SNMP Values


Attribute	Description
IfName	Optional Interface MIB variable for ifName assigned to the interface by the vendor. If no IfName value is provided, SNMP uses the ifType+ifIndex which is dynamically configured and can change. This name is not guaranteed to be unique or consistent across reboots.
IfAlias	Optional Interface MIB variable for ifAlias assigned to the interface. This value is set by the device administrator. An ifAlias could be useful if the interface vendor did not provide an ifName value.
IfDescription	Optional Interface MIB variable for ifDescr for the interface. This attribute is set by the device administrator.
IfIndex	Interface MIB variable for the row number in the interface table (ifTable) for this interface. The row number can change with each reboot. Note: Interfaces on non-SNMP nodes have an ifIndex value of 0 (zero).
IfSpeed	Interface MIB variable for the interface's bandwidth in bits per second. Depending on the device vendor, this value may indicate current speed or potential speed.
IfType	Interface MIB variable for the physical link protocol type of the interface. Possible values include: Ethernet and frameRelay. Note: Interfaces on non-SNMP nodes have an ifType value of other .
Input Speed	Indicates the speed at which an interface is capable of receiving data in bits per second ("Gbps", "Mbps"). You can type a value to override the ifSpeed value returned by the device's SNMP agent. NNMi retains the value you enter. A reason you might want to override this value include the following: Sometimes the value returned by the device's SNMP agent is not accurate or causes problems when NNMi calculates performance monitoring. For example, the input speed might be restricted due to circumstances in your environment, or bandwidth controls might limit the connection speed regardless of what the physical connection is capable of (such as within a WAN).
Output Speed	Indicates the speed at which an interface is capable of transmitting data in bits per second ("Gbps", "Mbps"). You can type a value to override the output speed value returned by the device's SNMP agent. NNMi retains the value you enter. A reason you might want to override this value include the following: Sometimes the value returned by the device's SNMP agent is not accurate or causes problems when NNMi calculates performance monitoring. For example, the output speed might be restricted due to circumstances in your environment, or bandwidth controls might limit the connection speed regardless of what the physical connection is capable of (such as within a WAN).

Interface Form: IP Addresses Tab

The ["Interface Form" \(on page 58\)](#) provides details about the selected network interface.

For information about each tab:

IP Addresses Table


Attribute	Description
IP Address	Table view of the IP addresses associated with the selected interface. You can use this table to determine the state and address for each IP address. Click the  Open icon to open the "IP Address Form" (on page 72) and view more information about a specific address.

Interface Form: VLAN Ports Tab

The ["Interface Form" \(on page 58\)](#) provides details about the selected network interface.

For information about each tab:

VLAN Ports Table

Attribute	Description
VLAN Ports	Table view of all of the VLAN ports associated with the current interface. Use this table to determine all port and VLAN combinations associated with this interface. Click the  Open icon to open the Port Form and view more information about a specific VLAN port.

Interface Form: Link Aggregation Tab (NNMi Advanced)

The ["Interface Form" \(on page 58\)](#) provides details about the selected network interface.

For more information about each tab:



The Interface Form: Link Aggregation Tab appears if the selected interface participates in a **Link Aggregation**¹ protocol. The contents of the tab differ based on the Interface's role in the Link Aggregation (Member or Aggregator).

A Member Interface's Link Aggregation Tab displays the Link Aggregation protocol and a reference to the Aggregation's Aggregator Interface. Click here for more details about the attributes displayed.

Link Aggregation Tab


Attribute	Description
Aggregator	Name of the Aggregator Interface for the selected physical Member Interface. The Aggregator Interface represents the collection of physical interfaces for one end of a Link Aggregation. See Layer 2 Neighbor View Map Objects for more information.

¹A Link Aggregation is a collection of member interfaces that are aggregated into a single logical interface. This is done by the Link Aggregation Control Protocol (LACP). The Link Aggregation Tab displays the Link Aggregation protocol and a reference to the Aggregation's Aggregator Interface. Click here for more details about the attributes displayed.

Attribute	Description
Aggregator	<p>Name of the Aggregator Interface for the selected physical Member Interface. The Aggregator Interface represents the collection of physical interfaces for one end of a Link Aggregation.</p> <p>See Layer 2 Neighbor View Map Objects for more information.</p> <p>This name will be the most accurate interface name available to the initial discovery process. First choice is the IF MIB <code>ifName</code> value. Second choice is the <code>ifAlias</code> value. Third choice is a combination of the <code>ifType[ifIndex]</code> value (for example, <code>eth-ernetCsmacd[17]</code>).</p> <p>Click the  Lookup icon, and choose  Open to open the form for the Aggregator Interface.</p>

The Aggregator Interface's Link Aggregation Tab lists the Member Interfaces of its end of the Link Aggregation and provides cumulative bandwidth statistics. Click here more details about the attributes displayed.

Link Aggregation Tab

Attribute	Description
Link Aggregation Protocol	<p>Protocol used to create the Link Aggregation, including the Aggregator Interface and its physical Members.</p> <p>Possible values include:</p> <ul style="list-style-type: none"> • Cisco Systems Port Aggregation Protocol (pagp) • Multi-Link Trunk technology (mlt) • Split Mutli-Link Trunk technology (smlt) • Inter-switch trunk that is part of a Split Multi-Link Trunk configuration (istMlt)
Available Bandwidth	<p>Sum of the interface Input Speed attribute values of the Member Interfaces whose MIB II <code>ifOperStatus</code> is not <code>Down</code>. If the sum of the interface Output Speed attribute values is different, NNMi displays separate Available Input Bandwidth and Available Output Bandwidth attributes.</p>
Maximum Bandwidth	<p>Sum of the interface Input Speed attribute values of the Member Interfaces, regardless of MIB II <code>ifOperStatus</code> . If the sum of the interface Output Speed attribute values is different, NNMi displays separate Maximum Input Bandwidth and Maximum Output Bandwidth attributes.</p>
Available Bandwidth Percentage	<p>Percentage value computed using Available Bandwidth divided by the Maximum Bandwidth.</p>
Members	<p>Table view of the physical Member Interfaces.</p> <p>Click the  Open icon to view more information about a specific interface.</p>

Interface Form: Capabilities Tab

The Interface Form: Capabilities Tab displays a table view of any capabilities added to the interface object by NNMi or an external application. For example, NNMi uses the capability feature to identify interfaces for which NNMi can obtain only limited information. Examples of these interfaces include Nortel interfaces as well as any interface on a non-SNMP node. To help identify these interfaces, NNMi assigns the interface the capability of `com.hp.nnm.capability.iface.private`.

Note: Because the values are generated by NNMi or an external application, Capability values cannot be modified.

For information about each tab:

Capabilities Table

Attribute	Description
Capability	The name of the capability added to an interface object by either NNMi or an external application. For more information, see: <ul style="list-style-type: none">• "Interface Capability Form" (on page 67)• "Interface Capabilities Provided by NNMi" (on page 65)
Unique Key	The database identifier for the capability that either NNMi or an external application added to this interface. Note: Capabilities added by NNMi use a Unique Key value that begins with the prefix: <code>com.hp.nnm.capability</code> . See "Interface Capabilities Provided by NNMi" (on page 65) for a description of the capabilities provided by NNMi that might appear under the Interface Form: Capabilities Tab.

Interface Capabilities Provided by NNMi

The Interface Form: Capabilities Tab displays a table view of any capabilities that have been added to the interface object. Capabilities that begin with `com.hp.nnm.capability` represent capabilities that NNMi provides. External applications can also add interface capabilities.

NNMi Interface Capabilities

Capability	Unique Key	Description
Private	com.hp.nnm.capability.iface.private	<p>Indicates the interface was discovered in either a non-SNMP node or a Nortel node. Private interfaces are not monitored for Status.</p> <p>For interfaces on non-SNMP nodes, note the following:</p> <ul style="list-style-type: none"> • The interface index (ifIndex) value is always set to 0 (zero). • The interface type (ifType) is set to Other. • The interface Name (ifName), if none is available, is set to Pseudo Interface. • If the interface hosts an IP address, the interface Alias (ifAlias) is set to the IP address. Otherwise, the interface Alias (ifAlias) is set with information from neighboring SNMP devices. • NNMi obtains the MAC address if the IP address can be resolved using ARP cache. <p>Note the following about Pseudo interfaces: NNMi attempts to obtain additional information using a variety of discovery protocols.</p> <p>For Nortel SNMP interfaces, note the following:</p> <ul style="list-style-type: none"> • The ifIndex value is set according the Nortel private MIB. • NNMi tries to collect the MAC address and interface name using Nortel's private MIBs.

NNMi Advanced. The capabilities in the following table identify whether the interface participating in a Link Aggregation is an aggregator or member.

NNMi Advanced. Link Aggregation Interface Capabilities: Roles

Capability	Unique Key	Description
Aggregate Interface	com.hp.nnm.capability.lag.aggregator	<p>Indicates the interface represents the collection of physical interfaces for one end of an Aggregator Link.</p> <p>See Layer 2 Neighbor View Map Objects for more information.</p>
Aggregate Member	com.hp.nnm.capability.lag.member	<p>Indicates the interface is a physical interface that is a member of an Aggregator Interface.</p> <p>See Layer 2 Neighbor View Map Objects for more information.</p>

NNMi Advanced. The capabilities in the following table are used to identify the Link Aggregation protocol used.

***NNMi Advanced.* Link Aggregation Interface Capabilities: Protocols**

Capability	Unique Key	Description
Cisco Port Aggregation Protocol	<code>com.hp.nnm.capability.lag.protocol.pagp</code>	Indicates an interface using Cisco Systems Port Aggregation Protocol.
Inter-Switch Trunk MLT	<code>com.hp.nnm.capability.lag.protocol.istmlt</code>	Indicates an inter-switch trunk that is part of a Split Multi-Link Trunk configuration.
Nortel Multi-Link Trunking	<code>com.hp.nnm.capability.lag.protocol.mlt</code>	Indicates an interface using the Multi-Link Trunk technology.
Split MLT	<code>com.hp.nnm.capability.lag.protocol.smlt</code>	Indicates an interface using Split Multi-Link Trunk technology.
Static/Manual Configured Link Aggregation	<code>com.hp.nnm.capability.lag.protocol.static</code>	Indicates the Cisco device has been manually configured for aggregation.

Interface Capability Form

This form describes a capability added to the interface object by NNMi or an external application. For example, NNMi uses the capability feature to identify interfaces for which NNMi can obtain only limited information. Examples of these interfaces include Nortel interfaces as well as any interface on a non-SNMP node. To help identify these interfaces, NNMi assigns the interface the capability of `com.hp.nnm.capability.iface.private`.

Note: Because the values are generated by NNMi or an external application, Capability values cannot be modified.

Each Capability attribute is described in the table below.

Basics Attributes

Attribute	Description
Capability	Label used to identify the Capability that was added to the interface object. The Capability value is listed in the table on the Capabilities tab in an Interface form. See "Interface Form: Capabilities Tab" (on page 65) .
Unique Key	Used as a unique identifier for the Capability. Any capability provided by NNMi begins with the prefix <code>com.hp.nnm.capability</code> . Note: Capabilities added by NNMi use a Unique Key value that begins with the prefix: <code>com.hp.nnm.capability</code> . See "Interface Capabilities Provided by NNMi" (on page 65) for a description of the capabilities provided by NNMi that might appear under the Interface Form: Capabilities Tab.

Interface Form: Custom Attributes Tab

Custom Attributes enable an NNMi administrator to add information to the Interface object. Custom Attributes can also be set by external applications that have been integrated with NNMi.

The Interface Form: Custom Attributes Tab displays a table view of any Custom Attributes that have been added to the interface object. For example, your NNMi administrator might have added **Role** as another attribute for the interfaces in your network.

Note: If your role allows, you can edit a Custom Attribute. Only user accounts with NNMi Administrator role can add a Custom Attribute.

Custom Attributes Table

Attribute	Description
Name	Name used to identify the Custom Attribute. This name appears in the table view on the Custom Attributes tab in Interface forms.
Value	The actual value for the Custom Attribute for the selected interface. For example, the value for Role might be WAN interface to the London office . For more information, see " Interface Capabilities Provided by NNMi " (on page 65).

Interface Custom Attributes Form

Custom Attributes enable an NNMi administrator to add information to the interface object. For example, your NNMi administrator might have added **Role** as another attribute for the interfaces in your network. Custom Attributes can also be set by external applications that have been integrated with NNMi.

The Custom Attributes form displays the Name and Value for each of the Custom Attributes that were added to the interface object. Each of these attributes is described in the table below.

Basics Attributes


Attribute	Description
Name	Name used to identify the Custom Attribute. This name appears in the table view on the Custom Attributes tab in the Interface forms.
Value	Value assigned to the Custom Attribute for the selected interface object. For example, the value for Role might be WAN interface to the London office .

Interface Form: Interface Groups Tab

The "[Interface Form](#)" (on page 58) provides details about the selected network interface.

For information about each tab:

Interface Groups Membership Table

Attribute	Description
Interface Groups	Table view of Interface Groups to which the selected interface belongs. Interface groups are based on specific characteristics of interfaces.
	Click the  Open icon to view more information about a specific Interface Group.








Interface Form: Performance Tab (NNM iSPI for Performance)

The "Interface Form" (on page 58) provides details about the selected network interface.

For information about each tab:

The Performance tab displays data if the NNM iSPI for Performance is installed and configured within your environment. The NNMi administrator can configure an optional high/low threshold.

The icons on the Performance tab indicate the value of the most recent interface performance states:

 High - The High threshold was crossed.	 Not Polled - Indicates that this interface is intentionally not polled. Possible reasons are: Performance Monitoring is not enabled, because of current Communication Configuration settings in NNMi, or because the parent Node or Interface is set to Not Managed or Out of Service.
 Nominal - Measured within healthy range. (Or no thresholds are being monitored.)	 Unavailable - Unable to compute the performance state or the computed value is outside of the valid range (0.00 - 100.00).
 Low - The Low threshold was crossed.	 Agent Error - The SNMP agent responded with an error, rather than a value.
 None - The value returned was zero.	

Performance Results Table

Attribute	Description
Input Utilization	<p>The total number of incoming octets traversing the interface as a percentage of the total possible number of octets (based on the ifSpeed value). From Interface to Interface, the exact MIB variables queried vary based on interface speed and whether the system supports the high speed counters for interfaces.</p> <p>Tip: Sometimes the value returned by the device's SNMP agent is not accurate and causes problems when NNMi calculates input utilization. NNMi lets you manually override the ifSpeed provided by the SNMP agent for this interface. See Input Speed.</p>
Output Utilization	<p>For full-duplex interfaces, the total number of outbound octets traversing the interface as a percentage of the total possible number of octets (based on the ifSpeed value). From Interface to Interface, the exact MIB variables queried vary based on interface speed and whether the system supports the high speed counters for interfaces.</p> <p>Tip: Sometimes the value returned by the device's SNMP agent is not accurate and causes problems when NNMi calculates output utilization. NNMi lets you manually override the output speed provided by the SNMP agent for this interface. See Output Speed.</p>
Input Error Rate	<p>Percentage based on the reported change in the number of input packets on the interface and the packet error count. What constitutes an error is system specific, but likely includes such issues as bad packet checksums, incorrect header information, and runt packets.</p>


Attribute	Description
Output Error Rate	Percentage based on the reported change in the number of output packets on the interface and the packet error count. What constitutes an error is system specific, but likely includes such issues as collisions and buffer errors.
Input Discard Rate	Percentage based on the reported change in the number of input packets on the interface and the discarded packet count. Packets may be discarded because of a variety of issues, including receive buffer overflows, congestion, or system specific issues.
Output Discard Rate	Percentage based on the reported change in the number of output packets on the interface and the discarded packet count. Packets may be discarded because of a variety of issues, including transmission buffer overflows, congestion, or system specific issues.

Interface Form: Incidents Tab

The "[Interface Form](#)" (on page 58) provides details about the selected network interface.

For information about each tab:

Incidents Table










Attribute	Description
Associated Incidents	<p>Table view of the incidents associated with the selected interface. These incidents are sorted by creation time so that you can view the incidents in chronological order. Use this view to determine which incidents are still open for the selected interface.</p> <p>Click the  Open icon to open the "Incident Form" (on page 132) and view more information about a specific incident.</p>

Interface Form: Status Tab

The "[Interface Form](#)" (on page 58) provides details about the selected network interface.

For information about each tab:

Status Tab


Attribute	Description
Status	<p>Overall status for the current interface. NNMi follows the ISO standard for status classification. Possible values are:</p> <ul style="list-style-type: none">  No Status  Normal  Disabled  Unknown  Warning  Minor  Major  Critical <p>Interface status is derived from SNMP polling results for ifAdminStatus and IfOperStatus, as well as any conclusions. For information about how the current status was determined, see the "Interface Form: Conclusions Tab" (on page 71). Status reflects the most serious outstanding conclusion. See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p><i>NNMi Advanced.</i> If the interface is an Aggregator Interface, the Status is calculated using the Status of the Aggregator Interface members. Click here for more information.</p> <p>A Status of Minor indicates the Status of at least one of the Aggregator Interface members is Critical. A Status of Critical indicates the Status of all the Aggregator Interface members is Critical.</p> <p>Also see Layer 2 Neighbor View Map Objects.</p> <p>Note: The icons are displayed only in table views.</p>
Status Last Modified	Date and time indicating when the status was last set.
Status History	<p>List of up to the last five changes in the status for the interface.</p> <p>Click the  Open icon to view more information about a specific status.</p>

Interface Form: Conclusions Tab

The "[Interface Form](#)" (on page 58) provides details about the selected network interface.

For information about each tab:

Conclusions Table for Status Calculations

Attribute	Description
Outstanding Status Conclusions	<p>The dynamically generated list of summary statuses of the interface at points in time that contributed to the current overall status of the selected interface. Status is set by the Causal Engine.</p> <p>Each conclusion listed is still outstanding and applies to the current overall status.</p> <p>This view is useful for obtaining a quick summary of the status and problem description for the current node's interfaces that led up to the node's most current status.</p> <p>Examples of conclusions that might appear together are listed below:</p> <ul style="list-style-type: none"> ● SNMP Agent Not Responding ● Interface Down ● Address Down <p>The status value is correlated based on the most critical conclusions.</p> <p>Click the  Open icon to view more information about a specific conclusion.</p>

Interface Form: Registration Tab

The "[Interface Form](#)" (on page 58) provides details about the selected network interface.

For information about each tab:

Registration

Attribute	Description
Created	Date and time the selected object instance was created. NNM uses the locale of the client and the date and time from the NNMi management server.
Last Modified	Date the selected object instance was last modified. NNM uses the locale of the client and the date and time from the NNMi management server.

IP Address Form








The IP Address form provides information for the IP address selected. This form is useful for troubleshooting purposes because you can access additional information about the [node](#), [interface](#), [subnet](#), and [incidents](#) associated with this address.






If your role allows, you can use this form to modify the [Management Mode](#) for an address (for example, to indicate it will be temporarily out of service) or add [notes](#) to communicate information about this address to your team.

For information about each tab:

Basic Attributes

Attribute	Description
Address	An IP address provided by your NNMi administrator as a discovery seed or an IP address gathered by Spiral Discovery.

Attribute	Description
Prefix Length	The number of significant bits in the subnet prefix associated with this IP address. For IPv4 addresses, this value is derived from the subnet mask.
Status	Overall status for the current IP address. NNMi follows the ISO standard for status classification. See "IP Address Form: Status Tab" (on page 74) .
Management Mode	The calculated Management Mode for the address used to indicate whether the current IP address is being managed. This value should reflect the management mode assigned to the node on which the selected address resides as well as on any associated interfaces. For example, if the node's management mode is Managed , and the Management Mode of the interface is Inherited , the Management Mode value for the address is Managed .
Direct Management Mode	This attribute is set by the administrator and specifies whether an address should be managed or is temporarily out of service. Possible values are:  Inherited – Used to indicate that the address should inherit the Management Mode from the associated interface, if any. Otherwise the address inherits the Management Mode of the node on which it resides.  Not Managed – Used to indicate that you do not plan to manage the address. For example, the address might not be accessible because it is in a private network. NNMi does not discover or monitor these addresses.  Out of Service – Used to indicate the address is unavailable because it is out of service. NNMi does not discover or monitor these addresses. This attribute is useful for notifying NNMi when an address is been temporarily out of service, or should never be managed. Note: If you change the Direct Management Mode, NNMi updates the calculated Management Mode on the form. If you manually set the Direct Management Mode and then Save your changes, the Management Mode value is not updated until you refresh the form.
State	Indicates whether the IP address is available and how NNMi is using SNMP to interact with this IP address. Possible values are:  Responding – Indicates that the IP address is being polled and is responding to an ICMP ping.  Not Responding – Indicates that the IP address is being polled, but is not responding to an ICMP ping. Note: NNMi's State Poller determines the State. The current state contributes towards the status calculation for the address. See the Status tab for more information.
State Last Modified	Indicates the date and time when the State value was last modified.
In Interface	MIB II ipAddrTable value indicating the interface that owns this IP address. Click the  Lookup icon and select  Open to display more information about the interface.

Attribute	Description
Hosted On Node	<p>Node on which the address resides. This is the current value in NNMi's database for the Name attribute of the host device. The value could be a DNS name, a MIB II sysName, or an address (depending on how your NNMi administrator configured the discovery process).</p> <p>Click the  Lookup icon and select  Quick View or  Open to display more information about the node.</p>
In Subnet	<p>Subnet on which the IP address resides. NNMi derives this subnet based on the IP address and the subnet prefix information. Click the  Lookup icon and select  Open to display more information about the IP subnet.</p>
Notes	<p>Provided for network operators to use for any additional notes required to further explain the IP address. Information might include whether the address is a backup address. You might also use this attribute to track which geographical group might use the address.</p> <p>Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p> <p>Note: You can sort your IP address table views based on this value. Therefore, you might want to include keywords for this attribute value.</p>


IP Address Form: Incidents Tab

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in the incident view's column headings.

The "[IP Address Form](#)" (on page 72) provides details about the selected IP address.

For information about each tab:

Incidents Table










Description
<p>Table view of the incidents associated with the selected address. These incidents are sorted by creation time so that you can view the incidents in chronological order. Use this view to determine which incidents are still open for the selected address.</p> <p>Click the  Open icon to open the "Incident Form" (on page 132) and view more information about a specific incident.</p>

IP Address Form: Status Tab

The "[IP Address Form](#)" (on page 72) provides details about the selected IP address .

For information about each tab:

Status of this IP Address


Attribute	Description
Status	<p>Overall status for the current IP address. NNMi follows the ISO standard for status classification. Possible values are:</p> <ul style="list-style-type: none"> No Status Normal Disabled Unknown Warning Minor Major Critical <p>IP address status is derived from ICMP ping results, as well as any conclusions. For information about how the current status was determined, see the "IP Address Form: Conclusions Tab" (on page 75). Status reflects the most serious outstanding conclusion. See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p>Note: The icons are displayed only in table views.</p>
Status Last Modified	<p>Indicates the date and time when the Status value was last modified.</p>
Status History	<p>List of up to the last five changes in status for the selected IP Address. This view is useful for obtaining a quick summary of the IP address status so that you can better determine any patterns in node behavior and activity.</p> <p>Click the  Open icon to view more information about a specific status.</p>

IP Address Form: Conclusions Tab

The ["IP Address Form" \(on page 72\)](#) provides details about the selected IP address .

For information about each tab:

Conclusions Table

Attribute	Description
Outstanding Status Conclusions	<p>The dynamically generated list of summary statuses of the IP address at points in time that contributed to the current overall status of the selected IP address. Status is set by the Causal Engine.</p> <p>Each conclusion listed is still outstanding and applies to the current overall status.</p> <p>This view is useful for obtaining a quick summary of the status and problem description for the current node's interfaces that led up to the node's most current status.</p> <p>Examples of conclusions that might appear together are listed below:</p> <ul style="list-style-type: none"> ● SNMP Agent Not Responding ● Interface Down ● Address Down <p>The status value is correlated based on the most critical conclusions. Click the  Open icon to view more information about a specific conclusion.</p>

IP Address Form: Capabilities Tab

The ["IP Address Form" \(on page 72\)](#) provides details about the selected IP address .

For information about each tab:

The IP Address Form: Capabilities tab displays a table view of any capabilities added to the IP Address object by NNMi or an external application. For example, NNMi uses the capability feature to identify an **Anycast Rendezvous Point IP Address**¹ so it is not polled. NNMi assigns the Anycast Rendezvous Point IP address the following capability: `com.hp.nnm.capability.address.anycast`.

Note: Because the values are generated by NNMi or an external application, Capability values cannot be modified.

Capabilities Table

Attribute	Description
Capability	<p>The name of the capability added to an IP address object by either NNMi or an external application. For more information, see:</p> <ul style="list-style-type: none"> ● "IP Address Capability Form" (on page 77) ● "IP Address Capabilities Provided by NNMi" (on page 77)
Unique Key	<p>The database identifier for the capability that either NNMi or an external application added to this interface.</p> <p>Note: Capabilities added by NNMi use a Unique Key value that begins with the prefix: <code>com.hp.nnm.capability</code>. See "IP Address Capabilities Provided by NNMi" (on page 77) for a description of the capabilities provided by NNMi that might appear under the IP Address Form: Capabilities Tab.</p>

¹Rendezvous Point addresses are loopback addresses used for routers in multi-cast network configurations

IP Address Capabilities Provided by NNMi

The IP Address Form: Capabilities Tab displays a table view of any capabilities that have been added to the IP Address object. Capabilities that begin with `com.hp.nnm.capability` represent capabilities that NNMi provides. External applications can also add IP address capabilities.

NNMi IP Address Capabilities

Capability	Unique Key	Description
loopback	<code>com.hp.nnm.capability.address.loopback</code>	Used to identify a loopback address ¹ .
anycast	<code>com.hp.nnm.capability.address.anycast</code>	Used to identify a loopback address that is an Anycast Rendezvous Point IP Address ² . Anycast Rendezvous Point IP Addresses are loopback addresses used for routers in multi-cast network configurations. These duplicate IP addresses are excluded from monitoring.

IP Address Capability Form

This form describes a capability added to the IP address object by NNMi or an external application. For example, NNMi uses the capability feature to identify an **Anycast Rendezvous Point IP Address**³. To help identify the Anycast Rendezvous Point IP addresses so they are not polled, NNMi assigns the IP address the following capability:`com.hp.nnm.capability.address.anycast`.

Note: Because the values are generated by NNMi or an external application, Capability values cannot be modified.

Each Capability attribute is described in the table below.

Basics Attributes

Attribute	Description
Capability	Label used to identify the Capability that was added to the IP address object. The Capability value is listed in the table on the Capabilities tab in an IP Address form. See " IP Address Capability Form " (on page 77).

¹The address associated with the loopback interface. The loopback interface is a virtual interface on a device that provides a route for internal communication. Many vendors provide a specially configured loopback for management purposes. Exact details of how loopbacks are configured varies by vendor and model. See each device's documentation for details. NNM identifies these loopback addresses by using IfType 24, softwareloopback from the IANA ifType-MIB.

²Rendezvous Point addresses are loopback addresses used for routers in multi-cast network configurations

³Rendezvous Point addresses are loopback addresses used for routers in multi-cast network configurations

Attribute	Description
Unique Key	Used as a unique identifier for the Capability. Any capability provided by NNMi begins with the prefix <code>com.hp.nnm.capability</code> . Note: Capabilities added by NNMi use a Unique Key value that begins with the prefix: <code>com.hp.nnm.capability</code> . See "IP Address Capabilities Provided by NNMi" (on page 77) for a description of the capabilities provided by NNMi that might appear under the IP Address Form: Capabilities Tab.

IP Address Form: Registration Tab

The ["IP Address Form" \(on page 72\)](#) provides details about the selected IP address .

For information about each tab:

Registration

Attribute	Description
Created	Date and time the selected object instance was created. NNM uses the locale of the client and the date and time from the NNMi management server.
Last Modified	Date the selected object instance was last modified. NNM uses the locale of the client and the date and time from the NNMi management server.






Router Redundancy Group Form (*NNMi Advanced*)

The Router Redundancy Group Form provides details about the Router Redundancy Group selected. This form is useful for troubleshooting purposes. You can access information about the name, status, and Router Redundancy Members (routers) associated with this Router Redundancy Group.

For information about each tab:

Basics Attributes

Attribute	Description
Name	The name assigned to this Router Redundancy Group. This name is the virtual IP address protected by this group and used by the router that is actively routing information packets (for example, HSRP Active or VRRP Master).

Attribute	Description
Status	<p>Router Redundancy Group Status reflects the most serious Severity value of the incidents associated with the Router Redundancy Group. Possible values are:</p> <ul style="list-style-type: none">  Normal  Warning  Minor  Major  Critical <p>See "Watch Status Colors" (on page 126) for more information about Severity values.</p> <p>Note: The icons are displayed only in table views.</p>
Group Number	The group number that was configured for the current Router Redundancy Group.
Number of Members	Specifies the number of members that belong to the current Router Redundancy Group.

Related Topics

["Router Redundancy Group View \(NNMi Advanced\)" \(on page 22\)](#)

["Non-Normal Router Redundancy Group View \(NNMi Advanced\)" \(on page 121\)](#)

["Router Redundancy Member Form \(NNMi Advanced\)" \(on page 80\)](#)

Router Redundancy Group Form: Router Redundancy Members Tab (NNMi Advanced)

The table on this tab lists all routers and the associated interface that currently belong to the Redundancy Router Group. The ["Router Redundancy Group Form \(NNMi Advanced\)" \(on page 78\)](#) provides details about the selected Router Redundancy Group.


For information about each tab:

Router Redundancy Members Table

Attribute	Description
Current State	<p>The current HSRP or VRRP state for the selected Router Redundancy Group Member.</p> <p>See "Router Redundancy Member Form (NNMi Advanced)" (on page 80) for more information about the possible state values.</p>
Previous State	<p>The previous HSRP or VRRP state for the selected Router Redundancy Group Member.</p> <p>See "Router Redundancy Member Form (NNMi Advanced)" (on page 80) for more information about the possible state values.</p>
Priority	<p>Number used to rank the Router Redundancy Members. The member with the numerically higher priority becomes the Active (HSRP) or Master (VRRP).</p>

Attribute	Description
Hosted On Node	Name of the selected router that is a member of the current Router Redundancy Group. The name is the hostname assigned to the router. See "Node Form" (on page 27) for more information about node names.
Redundancy Interface	The interface that is being used by the router to participate in the Router Redundancy Group.

To see more details about a particular Router Redundancy Member:

Click the  Open icon that precedes the Router Redundancy Member of interest to open the ["Router Redundancy Group Form \(NNMi Advanced\)" \(on page 78\)](#).




Router Redundancy Member Form (NNMi Advanced)













The Router Redundancy Member form provides details about a router in the Router Redundancy Group.

This form is useful for troubleshooting purposes. You can access information about the router name and status, as well as conclusions information to assist you in understanding the router's HSRP or VRRP state. You can also see the name of each tracked object associated with the router. A tracked object represents the interface responsible for delivering the outbound information packet that was originally sent to the current Router Redundancy Member.

For information about each tab:

Basics Attributes

Attribute	Description
Name	Name of the selected router and its associated interface that is a member of the current Router Redundancy Group. Note: NNMi determines this Name value. The name includes the fully qualified DNS name assigned to the router and the Name assigned to the interface. This name appears in the following format: <fully qualified hostname assigned to the router>[Interface Name:group_number] For example: HSRPRouter1.xyz.ab.com[Se1/1:1] See "Node Form" (on page 27) for more information about node names.
Redundancy Interface	The interface that is being used by the router to participate in the Router Redundancy Group. To find out more information about this interface: Click the  Lookup icon and choose one of the following options: <ul style="list-style-type: none">  Quick View to view a summary of the interface details.  Open to open the interface form.

Attribute	Description
Current State	<p>HSRP or VRRP State of the Router Redundancy Member. Possible states for routers using the HSRP or VRRP protocol are listed below.</p> <p>HSRP States</p> <p> Active - Indicates the router is forwarding packets that are sent to the router redundancy group.</p> <p> Initial - Indicates HSRP is not running. This state occurs when an interface first comes up.</p> <p> Learn - Indicates the router has not yet determined the virtual IP address. This state occurs when the router is waiting to hear from the active router.</p> <p> Listen - Indicates the router knows the virtual IP address, but it is neither the active or standby router. In this state, the router is waiting for a message from the active and standby routers.</p> <p> Speak - Indicates the router knows the virtual IP address. In this state, the router sends periodic messages and is ready to become an active or standby router.</p> <p> Standby - Indicates the router is a candidate to become the next active router.</p> <p>VRRP States</p> <p> Initialize - Indicates the router is not running VRRP. This state occurs when an interface first comes up.</p> <p> Master - Indicates the router is forwarding packets that are sent to the router redundancy group.</p> <p> Backup - Indicates the router is a candidate to become the next master router.</p> <p>If NNMi is unable to poll the interface used to identify the selected router in the Router Redundancy Group, one of the following states is set for the selected router's interface:</p> <p> Agent Error – Indicates an SNMP error was returned in response to an SNMP query to the interface's SNMP agent.</p> <p> Other – The SNMP agent on the interface responded with a value for the MIB variable used to determine the Router Redundancy Member State that is not recognized.</p> <p> Unavailable – The SNMP agent on the interface responded, but returned a null value for the request to the MIB variable used to determine the Router Redundancy Member State.</p>
Previous State	<p>The previous HSRP or VRRP State of the Router Redundancy Member. Possible values are described under Current State.</p>
Priority	<p>Number used to rank the Router Redundancy Members. The member with the numerically higher priority becomes the Active (HSRP) or Master (VRRP).</p>

Router Redundancy Member Form: Tracked Objects Tab (NNMi Advanced)

A tracked object is the outbound interface responsible for delivering the outbound information packet that was originally sent to a selected inbound interface on a router that is part of the Router Redundancy Group. A Router Redundancy Member can have one or more associated tracked objects

The "[Router Redundancy Member Form \(NNMi Advanced\)](#)" (on page 80) provides details about the selected Router Redundancy Member. Each Router Redundancy Member is a router in the Router Redundancy Group.

For information about each tab:

Tracked Objects Table




Attribute	Description
Track Priority	<p>Number used to rank the tracked object. This number is used indirectly in the calculation that determines the next Active or Master member of the Router Redundancy Group whenever a State change occurs.</p> <p>When a tracked object goes down, the priority of the tracked object (Track Priority) is subtracted from its Router Redundancy Member Priority value to produce a smaller member Priority number. If this new Priority number is smaller than one of the other member Priority numbers, the member with the highest Priority value becomes the new Master or Active router in the current Router Redundancy Group.</p> <p>For example, if an interface whose Track Priority is 20 goes down on a Router Redundancy Member whose member Priority is 250:</p> <ul style="list-style-type: none"> • The Track Priority (20) is subtracted from its member Priority (250-20=230). • The new member Priority (230) is then compared to the Priority value of the other members in the Router Redundancy Group. • If one of the members in the Router Redundancy Group has a higher member Priority, for example, 240, that member becomes the Active or Master router in the group.
Name	<p>Name of the selected router and its associated interface that is a member of the current Router Redundancy Group.</p> <p>Note: NNMi determines this Name value.</p> <p>The name includes the fully qualified DNS name assigned to the router and the name assigned to the interface.</p> <p>See "Tracked Objects Form (NNMi Advanced)" (on page 82) for more information about tracked objects.</p> <p>This name appears in the following format:</p> <p><i><fully qualified hostname assigned to the router>[Interface Name]</i></p> <p>For example: HSRPRouter1.xyz.ab.com[Se1/1]</p> <p>See "Node Form" (on page 27) for more information about node names.</p>

Tracked Objects Form (NNMi Advanced)

Your network administrator might have set up groups of redundant routers to help ensure that information packets reach their intended destination. A tracked object is the outbound interface responsible for delivering the outbound information packet that was originally sent to a selected inbound interface on a router

that is part of the Router Redundancy Group. A Router Redundancy Member can have one or more associated tracked objects.

Basics Attributes

Attribute	Description
Tracked Object	<p>Name used to identify the selected tracked object. The name includes the fully-qualified DNS name assigned to the router and the name assigned to its associated tracked object .</p> <p>This name appears in the following format:</p> <p><i><fully qualified hostname assigned to the router>[Interface Name]</i></p> <p>For example: <code>HSRPRouter1.xyz.ab.com[Se1/1]</code></p> <p>To find out more information about this interface:</p> <p>Click the  Lookup icon and choose one of the following options:</p> <ul style="list-style-type: none"> Quick View to view a summary of the interface details. Open to open the Interface form.
Track Priority	<p>Number used to rank the tracked object. This number is used indirectly in the calculation that determines the next Active or Master member of the Router Redundancy Group whenever a State change occurs.</p> <p>When a tracked object goes down, the priority of the tracked object (Track Priority) is subtracted from its Router Redundancy Member Priority value to produce a smaller member Priority number. If this new Priority number is smaller than one of the other member Priority numbers, the member with the highest Priority value becomes the new Master or Active router in the current Router Redundancy Group.</p> <p>For example, if an interface whose Track Priority is 20 goes down on a Router Redundancy Member whose member Priority is 250:</p> <ul style="list-style-type: none">The Track Priority (20) is subtracted from its member Priority (250-20=230).The new member Priority (230) is then compared to the Priority value of the other members in the Router Redundancy Group.If one of the members in the Router Redundancy Group has a higher member Priority, for example, 240, that member becomes the Active or Master router in the group.

Router Redundancy Group Form: Virtual IP Addresses Tab (NNMi Advanced)

Tip: See "[IP Address Form](#)" ([on page 72](#)) for an explanation of the columns in the Virtual IP Addresses table view.

The "[Router Redundancy Group Form \(NNMi Advanced\)](#)" ([on page 78](#)) provides details about the selected Router Redundancy Group.


For information about each tab:

Virtual IP Addresses Table View

Description

The Virtual IP addresses Tab displays a table view of the virtual IP addresses associated with the selected Router Redundancy Group. The virtual IP address is the IP address protected by this group and used by any router that is actively routing information packets (for example, HSRP Active or VRRP Master). For each virtual IP address displayed, you can see the IP address value.

To see more information about a specific IP address:

1. Select the IP address of interest by checking the selection box that precedes the object information.
2. Click the  Open icon to open the ["IP Address Form" \(on page 72\)](#) and view more information about the specific IP address.

Virtual IP addresses Form (NNMi Advanced)

A virtual IP address is an address protected by the Router Redundancy Group and used by the router that is actively routing information packed (for example, HSRP Active or VRRP Master).

Basic Attributes

Virtual IP Addresses

Attribute	Description
Value	IP address value for the virtual IP address.

Router Redundancy Group Form: Incidents Tab (NNMi Advanced)

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in the incident view's column headings.

The ["Router Redundancy Group Form \(NNMi Advanced\)" \(on page 78\)](#) provides details about the selected Router Redundancy Group.


For information about each tab:

Incidents Table

Description

Table view of the incidents associated with the selected Router Redundancy Group. These incidents are sorted by creation time so that you can view the incidents in chronological order. Use this view to determine which incidents are still open for the selected Router Redundancy Group.

To see more information about an incident:

1. Select the incident of interest by checking the selection box that precedes the object information.
2. Click the  Open icon to open the ["Incident Form" \(on page 132\)](#) and view more information about a specific incident.

VLAN Form

The VLAN form provides details about the selected virtual local area network, and lists all ports known to participate in this VLAN.

Note: A trunk port can participate in multiple VLANs.

For information about each tab:

Basic Attributes

Attribute	Description
VLAN Id	The identification value for the current VLAN. This value is taken directly from the MIB file provided by the Vendor.
Name	The name value from the MIB provided by the Vendor. If no name is provided in the MIB file, the same string as the VLAN Id is used.
Member Node [Interface]	<p>NNMi selects a representative Member Node and Member Interface for the current VLAN. These members help to distinguish VLANs that use the same identification number.</p> <p>NNMi selects the Member Node using the following criteria:</p> <ul style="list-style-type: none">• The node is a member of the VLAN.• The node has the lexicographically ordered first node hostname. <p>NNMi selects the Member Interface using the following criteria:</p> <ul style="list-style-type: none">• The interface must be on the Member Node.• The interface is a member of the VLAN.• The interface has the lexicographically ordered first interface name.
Member Node Count	Specifies the number of nodes that belong to the current VLAN.

Related Topics:


["VLANs View \(Inventory\)" \(on page 19\)](#)

VLAN Form: Ports Tab

Note: A trunk port can participate in multiple VLANs.

The ["VLAN Form" \(on page 85\)](#) provides details about the selected VLAN.

Ports Associated with this VLAN

Attribute	Description
Ports	<p>Table view of the ports associated with the selected VLAN. Use this table to access information about each port associated with the selected VLAN across all member devices.</p> <p>Click the  Open icon to open the "Port Form" (on page 86) and view more information about a port.</p>

Related Topics:







["VLANs View \(Inventory\)" \(on page 19\)](#)

Port Form

The Port form provides details about the port you selected on the Node form or VLAN form. The following table describes the fields included on the Port form.

For information about each tab:

Basic Attributes

Attribute	Description
Name	The port name consists of <Card-number / Port-number>.
Hosted on Node	Node on which the port resides. This is the current value in NNMi's database for the Name attribute of the host device. The value could be a DNS name, a MIB II sysName, or an address (depending on how your NNMi administrator configured the discovery process). Click the  Lookup icon and select  Quick View or  Open to display more information about the node.
Associated Interface	The current value from the Name attribute on the Interface form. The most accurate interface name available to the initial discovery process: IF MIB ifName, ifAlias, or ifType+ifIndex values. Click the  Lookup icon and select  Quick View or  Open to display more information about the interface.

Related Topics:

["Node Form" \(on page 27\)](#)


["VLAN Form" \(on page 85\)](#)

Port Form: VLANs Tab

The Port form provides details about the port you selected on the Node form or VLAN form. The following table describes the fields included on the Port form.

The ["Port Form" \(on page 86\)](#) provides details about the selected VLAN.

VLANs Attributes

Attribute	Description
VLANs	Table view of the VLANs to which the selected port belongs. You can use this table to determine the VLAN ID number and name for each VLAN associated with the selected port. Click the  Open icon to open the "VLAN Form" (on page 85) and view more information about a specific VLAN.

Related Topics:

["Node Form" \(on page 27\)](#)

["VLAN Form" \(on page 85\)](#)

Node Group Form

Note: Island Node Groups are a special kind of Node Group that NNMi manages internally. Therefore, NNMi administrators should not modify Island Node Group configurations. NNMi overrides any user changes the next time NNMi updates the Island Node Group discovery information. See "Help for Administrators" for more information about Island Node Groups.

Membership in each node group is determined by a number of factors specified on the Node Group form. The NNMi administrator can create and modify Node Group definitions. The NNMi administrator can also configure Node Groups as filters in table views. NNMi monitors the status of each Node Group over time. NNMi also provides a map of each Node Group.

Each node group includes one or more of the following:

- Device Filters (by any combination of category, vendor, family, profile)
- Additional Filters
- Additional Nodes (specific nodes identified by Hostname)

If Device Filters and Additional Filters are in use, nodes must match *both* the Device Filters and the Additional Filters specifications to belong to this Node Group. Nodes that are specified as Additional Nodes are *always* included in the Node Group.

For information about each tab:

Tip: [Special Actions are available](#) within the Node Group view and Interface Group view.

Depending on your role, Node Groups can be used in several ways:

Node Group Basic Settings

Attribute	Description
Name	The name of this group (text string specified by the NNMi administrator).
Status	Overall status for the specified node group. NNMi follows the ISO standard for status classification. See the " Node Group Form: Status Tab " (on page 92) for more information.
Add to View Filter List	If disabled <input type="checkbox"/> , this node group does not appear in any node group filter lists for node, interface, IP address, and incident views. If enabled <input checked="" type="checkbox"/> , this node group is available as a filter for all node, interface, IP address, and incident views.
Notes	<i>Optional.</i> If your role allows, enter any information that might be useful to you and your team. Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.

NNM iSPI for Performance. Node Group Settings

Attribute	Description
Add to Filter List	<p>NNM iSPI for Performance. Using this feature is entirely optional. The NNM iSPI for Performance can monitor your network without any exported filter.</p> <p>Enable only for groups that are needed as filters in performance reports. It may take up to an hour before the results are visible in NNM iSPI for Performance reports. Choose wisely because establishing a filter requires significant NNM iSPI for Performance processing time.</p> <p>If disabled <input type="checkbox"/>, this group is not available as a filter in NNM iSPI for Performance reports.</p> <p>If enabled <input checked="" type="checkbox"/>, this group appears in the Optional Filters selection panel of NNM iSPI for Performance reports.</p>

Node Group Form: Device Filters Tab

Optional: Determine Node Group members by vendor, family, model, or other device characteristics such as SNMP object identifiers.


If any hostname wildcards or device filters are in use:

- By default, when the hostname wildcard or device filter list is empty, no nodes match the criteria. To match all nodes, use the * (asterisk) wildcard.
- When either or both hostname wildcard and device filters are enabled, nodes must match ALL specifications to belong to this node group.

The "[Node Group Form](#)" (on page 87) provides details about the selected node group.

For information about each tab:

Device-Characteristic Filters Table

Attribute	Description
Device Filter	<p>Table view of the device category, vendor, product family, or product model filters associated with the selected node group.</p> <p>Click the  Open icon to open the "Node Device Filter Form" (on page 88) and view more information about a filter specification.</p>





Node Device Filter Form

Optional: Node Group definitions can specify membership by device vendor, family, model, or SNMP object identifiers.

When using node Device Filters, note the following:

- If Device Filters and Additional Filters are in use, nodes must match *both* the Device Filters and the Additional Filters specifications to belong to this Node Group.
- Nodes that are specified as Additional Nodes *always* pass any filters.

Device Attribute Filters Table

Attribute	Description
Device Category	<i>Optional:</i> A particular category of devices. The drop-down list displays all available choices.
Device Vendor	<i>Optional:</i> A particular vendor. The drop-down list displays all available choices.
Device Family	<i>Optional:</i> A particular family of devices. To see all available choices, click the  Open icon and use the  Quick Find icon.
Device Profile	<i>Optional:</i> A particular device model or SNMP object ID. To see all available choices, click the  Open icon and use the  Quick Find icon.

Node Group Form: Additional Filters Tab

Tip: If you are an NNMi Administrator, see the "Help for Administrators" for more information about how to use the Additional Filters Editor.

The Additional Filters tab enables the NNMi administrator to use expressions to further define which nodes to include in a Node Group.

If any Additional Filters are created:

- NNMi first evaluates any hostname filters and device filters. Nodes must match *at least one* specification to belong to this Node Group.
- NNMi then evaluates any Additional Filter expression. Nodes *must also match all* Additional Filters expression specifications to belong to this Node Group.

The "[Node Group Form](#)" (on page 87) provides details about the selected Node Group.

For information about each tab:

If an NNMi administrator created any Additional Filters for the selected Node Group, NNMi displays the Additional Filters expression.

Node Group Form: Additional Nodes Tab


Optional: Determine Node Group members by specifying each device hostname (or address when hostname is not available).

Nodes that are specifically listed are *always* included in this node group.

The "[Node Group Form](#)" (on page 87) provides details about the selected node group.

For information about each tab:

Specific-Device Filters Table

Attribute	Description
Node Hostname	Table view of the hostnames for the additional nodes added to the selected Node Group. Note: NNMi always converts hostnames to all lowercase. Click the  Open icon to open the " Additional Node Form " (on page 90) and view more information about a filter specification.

Additional Node Form

Optional: Node Group definitions can identify specific devices by hostname (or address when hostname is not available).

Nodes that are specified as Additional Nodes are *always* included in the Node Group.

The "[Node Group Form](#)" (on page 87) provides details about the selected Node Group.

Specific Device Filter

Attribute	Description
Node Hostname	<p>The Hostname attribute value on the Node form of the discovered node must match what is entered here (see the Hostname attribute the "Node Form" (on page 27) for more information).</p> <p>Note: NNMi always converts hostnames to all lowercase.</p> <p>If a device has multiple hostnames or no hostname, NNMi follows a set of rules to determine the hostname. Click here for details.</p> <ol style="list-style-type: none">1. If a hostname is available, it must resolve to a valid IP address. NNMi stores the fully-qualified hostname in the database as all lowercase characters.2. If more than one address is associated with a node, the loopback address¹ is used with the following exceptions:<ul style="list-style-type: none">■ NNMi prefers loopback interfaces for management communication, where possible. However, NNMi automatically filters out addresses in the reserved loopback network range 127/24 (127.*.*).■ NNMi ignores any address that is virtual (HSRP/VRRP) or an Anycast Rendezvous Point IP Address².3. If a node has multiple loopback addresses, NNMi uses the loopback address with the lowest number that resolves to a hostname (for example, 10.16.42.197 is a lower number than 10.16.197.42).4. If no loopback address resolves to a hostname and the device supports SNMP, NNMi uses the current value from the Management Address attribute on the Node form.5. If the device does not support SNMP, the IP address or DNS name found during the current rediscovery cycle is used as the hostname. <p>This sequence is repeated during each rediscovery cycle. The hostname could change from cycle to cycle (for example, if an address did not respond to SNMP queries due to network problems or node reconfiguration).</p>

¹The address associated with the loopback interface. The loopback interface is a virtual interface on a device that provides a route for internal communication. Many vendors provide a specially configured loopback for management purposes. Exact details of how loopbacks are configured varies by vendor and model. See each device's documentation for details. NNM identifies these loopback addresses by using IfType 24, softwareloopback from the IANA ifType-MIB.

²Rendezvous Point addresses are loopback addresses used for routers in multi-cast network configurations

Node Group Form: Child Node Groups Tab

The "[Node Group Form](#)" (on page 87) provides details about the selected Node Group.

Child Node Groups can be created to associate groups of nodes in a hierarchy. For example, a hierarchical set of Node Groups might be based on geographical location. The Parent Node Group might be named **United States** to represent all of the nodes in the United States. Additional Node Groups might exist for each state in which your business offices reside (for example **Colorado** and **California**). Each of these individual state Node Groups are added as Child Node Group of the **United States** Node Group.

For information about each of the columns displayed in the Child Node Groups table, see "[Node Group Hierarchy \(Child Node Group\) Form](#)" (on page 91)

By default, each Child Node Group is represented by a hexagon that appears with the other Node objects of the Parent Node Group in the Node Group Map. Child Node Group objects can be moved and have their locations saved with other Node objects in the map. Unlike other Node objects, double-clicking a Child Node Group object displays a map of the nodes in the Child Node Group rather than the object's form.

An NNMi administrator alternatively can configure the map to display all nodes in a Child Node Group as though its contents are directly in the Parent Node Group by setting the **Expand Child in Parent Node Group Map** attribute. An NNMi administrator must set this option for each Child Node Group that should be expanded. See "[Node Group Hierarchy \(Child Node Group\) Form](#)" (on page 91) for more information.

For information about each tab:

["Node Group Hierarchy \(Child Node Group\) Form" \(on page 91\)](#) **Related Topics**

["Node Group Maps" \(on page 98\)](#)

["Navigating within a Node Group Map" \(on page 99\)](#)


["Position Nodes on a Node Group Map" \(on page 100\)](#)

Node Group Hierarchy (Child Node Group) Form

Child Node Groups associate groups of nodes in a hierarchical order. For example, the Parent Node Group might be named **United States** to represent all of the nodes in the United States. Additional Node Groups might exist for each state in which your business offices reside (for example **Colorado** and **California**). Each of these individual state Node Groups can be a Child Node Group of the **United States** Node Group.

The following table describes each of the **Basics** attributes in the **Node Group Hierarchy** form.

Basics Attributes

Attribute	Description
Child Node Group	<p>Indicates the name of a Node Group that is below the current Node Group in the hierarchical order. For example, Colorado could be a Child Node Group to a Node Group named United States.</p> <p>Note: This attribute appears as the Name column in the Child Node Groups table view.</p>
Expand Child in Parent Node Group Map	<p>Used to indicate whether all of the nodes contained in a Child Node Group are displayed in the Node Group Map as though they were directly contained in the parent node group.</p> <p>If enabled, each node in the group appears as a separate node on the Node Group Map.</p> <p>If disabled, a single object represents a Child Node Group on the Node Group Map.</p> <p>Note the following:</p> <ul style="list-style-type: none"> ● If the current Node Group has one or more Child Node Groups, each Child Node Group is also displayed. Child Node Groups are indicated using a hexagon as shown below: <ul style="list-style-type: none"> ■  ● If any Child Node Group is a parent to other Child Node Groups, those Child Node Groups are also displayed on the map as follows: <ul style="list-style-type: none"> ■ If the Child Node Group has the Expand Child in Parent Node Group Map attribute disabled, the Child Node Group appears as a hexagon. ■ If any Child Node Group has the Expand Child in Parent Node Group Map attribute enabled, NNMi displays each of the nodes in that Child Node Group. <p>Note: This attribute appears in the ECiNM column in the Child Node Groups table view.</p>

Related Topics

["Node Group Maps" \(on page 98\)](#)

["Position Nodes on a Node Group Map" \(on page 100\)](#)










Node Group Form: Status Tab

The Node Group status is calculated based on the status of the nodes within the group.

The ["Node Group Form" \(on page 87\)](#) provides details about the selected Node Group.

For information about each tab:

Status Attributes

Attribute	Description  Minor — At least 20 percent of the nodes in the Node Group have a Status of Minor .
<p>Status</p> <p>The Node Group status is calculated based on the status of the nodes within the group. NNMi follows the ISO standard for status classification. Possible values are:</p> <p>Note: Your NNMi administrator can configure how a Node Group Status is calculated. The percentages listed below represent the default percentages, which might have been changed. By default, NNMi sets up the Node Group status so that it is equal to the most severe Status of any node in the Node Group. See "Help for Administrators" for more information.</p> <ul style="list-style-type: none">  No Status — The Node Group has just been added and NNMi has not yet calculated the status.  Normal — All nodes in the Node Group have a status of Normal or the threshold specified for this Target Status has not been reached.  Unknown — All nodes within the Node Group have a status of Unknown.  Warning — At least 30 percent of the nodes within the Node Group have a status of Warning.  Minor — At least 20 percent of the nodes in the Node Group have a Status of Minor.  Major — At least 10 percent of the nodes within the Node Group have a status of Major.  Critical — At least 5 percent of the nodes in the group have a status of Critical. <p>Note: When the percentages for more than one Status has been exceeded, NNMi propagates the most severe status. For example, if 40 percent of the nodes in a Node Group are in Warning Status and 30 percent are in Minor Status, NNMi assigns the Node Group a Status of Minor.</p> <p>See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p>Note: The icons are displayed only in table views.</p>	
<p>Status Last Modified</p>	<p>Date and time indicating when the status was last set.</p>
<p>Status History</p>	<p>List of up to the last five changes in status for the selected node. This view is useful for obtaining a quick summary of the node status so that you can better determine any patterns in node behavior and activity.</p> <p>Click the  Open icon to view more information about a specific status.</p>

Interface Group Form

Each interface group can include one or more interface-type specifications (based on industry-standard IANA ifType-MIB variables). The NNMi administrator can create and modify interface group definitions. The NNMi administrator can also configure interface groups as filters in table views.

For information about each tab:

Tip: [Special Actions are available](#) within the Node Group and Interface Group views.

Depending on your role, Interface Groups can be used in several ways:

Interface Group Basics

Attribute	Description
Name	The name of this group (text string specified by the NNMi administrator).
Add to View Filter List	<p>If disabled <input type="checkbox"/>, this interface group does not appear in any interface group filter lists for interface and IP address views.</p> <p>If enabled <input checked="" type="checkbox"/>, this interface group is a filter for all interface and IP address views.</p>
Node Group	<i>Optional.</i> If configured, this Interface Group is associated with a Node Group and serves as a filter for that Node Group.
Notes	<p><i>Optional.</i> If your role allows, enter any information that might be useful to you and your team.</p> <p>Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p>

NNM iSPI for Performance. Interface Group Settings

Attribute	Description
Add to Filter List	<p><i>NNM iSPI for Performance.</i> Using this feature is entirely optional. The NNM iSPI for Performance can monitor your network without any exported filter.</p> <p>Enable only for groups that are needed as filters in performance reports. It may take up to an hour before the results are visible in NNM iSPI for Performance reports. Choose wisely because establishing a filter requires significant NNM iSPI for Performance processing time.</p> <p>If disabled <input type="checkbox"/>, this group is not available as a filter in NNM iSPI for Performance reports.</p> <p>If enabled <input checked="" type="checkbox"/>, this group appears in the Optional Filters selection panel of NNM iSPI for Performance reports.</p>

Interface Group Form: IfType Filters Tab


Interface Group members are filtered by industry-standard IANA ifType-MIB variables.

Note: To be included in this Interface Group, interfaces must match *ALL* criteria listed on this tab.

The "[Interface Group Form](#)" (on page 93) provides details about the selected interface group.

For information about each tab:



IfType Filters Table

Attribute	Description
IfType Filters	<p>Table view of all IfType filters associated with the selected interface group.</p> <p>Click the  Open icon to open the "IfType Filter Form" (on page 95) and view more information about a filter specification.</p>

IfType Filter Form

Displays the specification of the selected interface-type filter. This filter is based on an industry-standard IANA ifType-MIB variable.

IfType Specification






Attribute	Description
IfType	<p>Click the  Lookup icon and select  Open to display the "IfType (Interface Type) Form" (on page 95) and view more information about the specified IANA ifType-MIB variable.</p> <p>If your role allows, you can easily choose from a list of all known industry-standard IANAif-Type-MIB variables (as of the time NNMi was released). You can also add a new value. (For more information, see http://www.iana.org/assignments/ianaiftype-mib)</p>

IfType (Interface Type) Form

Displays information about the selected industry-standard IANA ifType-MIB variable.

The NNMi administrator can change these settings.

Interface Type Definition

Attribute	Description
IfType	<p>Text string. The IANA ifType TEXTUAL-CONVENTION values extracted from the IANA ifType-MIB. This text string displays as the Interface Type attribute value in Interfaces views. (For more information, see http://www.iana.org/assignments/ianaiftype-mib.)</p> <p>If your role allows, click the  Lookup icon and select one of the options from the drop-down menu:</p> <ul style="list-style-type: none"> Quick View to display summary information for the currently selected IfType. Quick Find to view and select from the list of all existing IfTypes. Open to display the details of the currently selected IfType. New to create a new SNMPv3 Setting.
Number	Industry-standard number assigned to this ifType.
Description	<p><i>Optional.</i> If your role allows, provide any description that would be useful for communication purposes within your team.</p> <p>Type a maximum of 2048 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p>

Interface Group Form: Additional Filters Tab

Additional Filters enable the NNMi administrator to use expressions to further define which interfaces to include in an Interface Group.

If any Additional Filters are created:

- NNMi first evaluates any ifType filters. Interfaces must match *all* specifications to belong to this Interface Group.
- NNMi then evaluates any Additional Filters expression. Interfaces *must also match all* Additional Filters expression specifications to belong to this Interface Group.

Note: The Additional Filters Editor requires that your user name be assigned a role of Administrator. If you are an NNMi Administrator, see the "Help for Administrators" for more information about how to use the Additional Filters Editor.

The ["Interface Group Form" \(on page 93\)](#) provides details about the selected Interface Group.

For information about each tab:

If an NNMi administrator created any Additional Filters for the selected Interface Group, NNMi displays the Additional Filters expression.

Management Station Form

Management Station configurations are used for a variety of purposes:

- Enable NNM 6.x or 7.x to forward events to NNMi.
- Enable access to NNM 6.x or 7.x features from incidents that were forwarded from NNM 6.x/7.x. (See ["Access NNM 6.x and 7.x Features" \(on page 13\)](#) for more information.)
- Filter incident views by NNM 6.x or 7.x Management Station.

NNM 6.x or 7.x Management Station Attributes

Name	Description
Name	The name your team uses to identify this remote NNM 6.x or 7.x management station.
NNM Version	The version of NNM (6.x or 7.x) in use on this remote management station.
IP Address	The IP address used for communication with this remote NNM 6.x or 7.x management station.
ovas Port (OpenView Application Server)	The port number used by the OpenView Application Server (ovas) on this NNM 6.x or 7.x management station. The port number is usually 7510.
Web Server Port	The port number used by the web server on this NNM 6.x or 7.x management station: <ul style="list-style-type: none"> ● For NNM 7.x management stations on all operating systems, the port number is usually 3443. ● For NNM 6.x management stations running UNIX, the port is usually 3443. ● For NNM 6.x management stations running Windows systems, it is usually 80.
Description	<i>Optional.</i> Notes your NNMi administrator added about this NNM 6.x or 7.x management station. Maximum length 255 characters. Alpha-numeric, punctuation, spaces, and underline characters allowed.

Viewing Maps (Network Connectivity)

NNMi provides several views that display maps of how a specific device is connected to the rest of the network. You can access these views in the Troubleshooting workspace or by using the **Actions** → menu. These views include:

- [Layer 2 Neighbor View](#)
- [Layer 3 Neighbor View](#)
- [Path View](#)
- ["Node Group Maps" \(on page 98\)](#)

The OSI initiative identified seven layers for communication and computer network protocol design. The [Layer 2](#)¹ and [Layer 3](#)² Neighbor Views display data according to the Open Systems Interconnection (OSI) model.

The Path view combines real-time data about both Layer 2 and Layer 3 information.


On the maps, the lines between devices indicate the connections.

In Layer 2 Neighbor View maps, interfaces that are connected to a neighbor are indicated by little squares around the background shape of the parent node. Pay special attention to the color of the lines, which represent connections. For example:



See [About Status Colors](#) for more information.

In Layer 3 Neighbor View maps, addresses connected to neighbors within the same IP subnet are indicated by little hexagons around the background shape of the parent node. The lines indicate the subnets, so the lines are beige (no status). For example:



Node Group Maps show the members of a Node Group (defined by the NNMi administrator). The map displays the status and connectivity of each member. Your NNMi administrator can also specify a background image (for example, a map of North America). Child Node Groups display the hierarchy of nodes in a Node Group.

¹Refers to the Data Link layer of the multilayered communication model, Open Systems Interconnection (OSI). The Data Link layer moves data across the physical links in the network. The switches and bridges are devices that redirect data messages at the layer 2 level, using the destination Media Access Control (MAC) address to determine where to direct the message.

²Refers to the Network layer of the multilayered communication model, Open Systems Interconnection (OSI). The Network layer is concerned with knowing the address of the neighboring nodes in the network, selecting routes and quality of service, and recognizing and forwarding incoming messages to local host domains. The router and switch-router are the devices that redirect data messages at the Layer 3 level. Everything in a subnet is connected at the Layer 3 (IP) level.

Node Group Maps

Node Group Maps enable you to see the members of a Node Group (defined by the NNMi administrator). The map displays the status and connectivity of each member. Your NNMi administrator can specify a background image (for example, a map of North America).

Note: If your role allows, you can configure the settings for a Node Group map, including selecting the background image. To do so, use the **File** → **Open Node Group Map Settings** option. See "Help for Administrators" for more information.

Because node membership is based on the Node Group, not connectivity, one or more nodes might not be connected on a Node Group Map.

To display a Node Group Map using the Troubleshooting workspace:

1. From the **Workspaces** navigation panel, select the **Troubleshooting** workspace.
2. Select **Node Group Map**.
3. In the **Node Group** field, enter the name of the Node Group whose map you want to display.


Note: As you start typing the first few letters (case-sensitive) of the name of the node group you want to use, you will view a list that includes all potential node groups with names that match the letters as you enter them.

To display a Node Group Map using the Actions menu:

1. From the **Workspaces** navigation panel, select the **Incident**, **Monitoring** or **Inventory** workspace.
2. From the **Incident** or **Monitoring** workspace, select **Node Groups**.
3. From the **Incident Management** or **Incident Browsing** workspace, select the Island Node Group incident view of interest.
Note: Incidents whose Source Object is an Island Node Group include **Remote site** in the incident message. See ["Island Node Group Map" \(on page 146\)](#) for more information.
4. In the Node Group or Incident view, click the selection box that precedes the Node Group or Island Node Group incident of interest.
5. Select **Actions** → **Node Group Map**.

Note: When you use the Actions menu to display a map, each unique map appears in a new window. See [Using Actions to Perform Tasks](#) for more information.



When viewing nodes on a Node Group Map, keep in mind the following:


- By default, each Child Node Group is represented by a single hexagon that appears with the other Node objects of the Parent Node Group in the Node Group Map. Child Node Group objects can be moved and have their locations saved with other Node objects in the map. Unlike other Node objects, double-clicking a Child Node Group object displays a map of the nodes in the Child Node Group rather than the object's form.
- To display the nodes within a Child Node Group, do one of the following:
 - Double-click the Child Node Group object.
 - Select the Child Node Group object and do one of the following:
 - Click the  **Open Node Group Map** icon.
 - Select **Actions** → **(Child Node Group Name) Map**.
- An NNMi administrator alternatively can configure the map to display all nodes in a Child Node Group as though its contents are directly in the Parent Node Group by setting the **Expand Child in Parent Node Group Map** attribute. An NNMi administrator must set this option for each Child Node Group

that should be expanded. See ["Node Group Hierarchy \(Child Node Group\) Form" \(on page 91\)](#) for more information.

- To view more information about the selected Node Group, open the Node Group form using the **File** → **Open Node Group for Map** option.
- NNMi enlarges any node on a Node Group map that has an open root cause incident associated with it. To view an associated incident for a node on a Node Group map, double-click the node of interest. In the Node form, select the Incidents tab.

To disable the open root cause indicator, clear the **Indicate Root Cause Incidents** check box in the map view toolbar.

To refresh node and Node Group status at any time, use the  **Refresh Status** icon. See [Refresh Only Node Status on a Map](#) for more information. You can also refresh connectivity, map objects, as well as node and Node Group status using the  **Refresh All** icon.

To return to the previous Node Group map, click the  **Back to Previous Node Group** icon. See ["Navigating within a Node Group Map" \(on page 99\)](#) for more information about ways to navigate within a Node Group Map. ["Navigating within a Node Group Map" \(on page 99\)](#)

NNMi provides the following Node Group Map views:

- ["Node Group Overview Map" \(on page 100\)](#)
- ["Network Overview Map" \(on page 101\)](#)
- ["Important Nodes Map"](#)
- ["Networking Infrastructure Devices Map" \(on page 101\)](#)
- ["Routers Map" \(on page 102\)](#)
- ["Switches Map" \(on page 102\)](#)



Related Topics

["Navigating within a Node Group Map" \(on page 99\)](#)


["Position Nodes on a Node Group Map" \(on page 100\)](#)

Navigating within a Node Group Map

Navigation and accessing node details on a Node Group Map are the similar to those for the Layer 2 Neighbor and Layer 3 Neighbor maps with the following exceptions:

- To display a Node Group map of a Child Node Group in the same window:
 - a. Double-click the Child Node Group object:

 - b. Select the Child Node Group object and click the  **Open Node Group Map** icon.
- To display a Node Group Map for a Child Node Group in a new window, use **Actions** → **Node Group Map**.



Note: The Child Node Group map must be unique to be displayed in a new window. See [Using Actions to Perform Tasks](#) for more information.

- To return to the previous Node Group Map, use the  **Back to Previous Node Group** icon .
- To open the Node Group form for a Node Group map, select **File** → **Open Node Group for Map**.

- To open the Node Group Map Settings form from a Node Group map, select **File** → **Open Node Group Map Settings**.
- You can manually reposition the nodes on the background image, and, if your role allows, save the map for later use. See ["Position Nodes on a Node Group Map" \(on page 100\)](#) for more information.
- If **Indicate Key Incidents** is enabled, NNMi enlarges any node on a Node Group map that has an open Key Incident associated with it. To view an associated incident for a node on a Node Group map, double-click the node of interest. In the Node form, select the Incidents tab.

To enable the Key Incident indicator, select the **Indicate Key Incidents** check box in the map view toolbar.

To disable the Key Incident indicator, clear the **Indicate Key Incidents** check box in the map view toolbar.


As in other maps, clicking the  Open icon after selecting a node on the map, displays the Node form. Clicking the  Open icon after selecting a Child Node Group, opens the Child Node Group form. See [Use Map Views](#) and [Access More Details \(Quick View and Forms\)](#) for more information.


Position Nodes on a Node Group Map

You can manually reposition the nodes on the map, and, if your role allows, save the map. NNMi users see your change the next time the map is refreshed.

Note: If your role allows, to return to the original layout that NNMi automatically determines, use **File** → **Clear Layout**.

To position and save node locations on a Node Group Map view:

1. Navigate to the Node Group Map:
 - a. From the workspace navigation panel, select the **Inventory** or **Monitoring** workspace.
 - b. Select **Node Groups**.
 - c. In the Node Group view, click the selection box that precedes the Node Group of interest.
 - d. Select **Actions** → **Node Group Map**.
2. Manually re-position the node locations by dragging and dropping the nodes to the location you want.
3. If your role allows, select  **Save Layout** from the toolbar menu to save all node locations on the map.

Note: Each time you select  **Save Layout**, NNMi deletes any previous node location information for the map.

Node Group Overview Map

This Node Group map displays all top-level Node Groups that have been configured for your network.

Use this view when you want to do any of the following tasks:

- Determine the Node Groups created for your network.
- Determine the Node Group hierarchy for the Node Groups created for your network.

To display the Node Group Overview map using the Topology Maps workspace:

1. From the workspace navigation panel, select the **Topology Maps** workspace.
2. Select **Node Group Overview**.

Related Topics

[Views Provided by NNMi](#)

[Node Group Map Objects](#)

Network Overview Map

Displays a map containing the most highly connected nodes in the Layer 3 network. This map periodically updates both topology and status. The update interval is more frequent when the topology is changing, and less frequent when the topology is not changing.

Note: Automatic refresh cancels any modifications, such as selecting or zooming, you make to this view.

Use this view when you want to do any of the following tasks:

- View a high level overview of your network
- Determine the most highly connected nodes in the Layer 3 network
- Determine discovery progress

To display the Network Overview map using the Topology Maps workspace:

1. From the workspace navigation panel, select the **Topology Maps** workspace.
2. Select **Network Overview**.

Related Topics

[Views Provided by NNMi](#)

[Node Group Map Objects](#)

Networking Infrastructure Devices Map

Tip: Your NNMi administrator can add or delete maps from the Topology Maps workspace. If the Networking Infrastructure Devices map is not available, your NNMi administrator might have chosen to remove this map from the Topology Maps workspace.

The Networking Infrastructure Device map provides representative Node Groups for the Switches and for the Routers in your network. Each of the following device types, if applicable, are also included on the map:

- Chassis
- Firewalls
- Voice Gateways

To view the connectivity within each device type (Node Group), click the Node Group of interest. See ["Node Groups View \(Inventory\)" \(on page 23\)](#) for more information about Node Groups.

Use this view when you want to do any of the following tasks:

- Determine the types of devices in your network.
- View the connectivity within a group of devices of the same type.
- Determine the number of devices of a specific type.

To display the Networking Infrastructure Devices map using the Topology Maps workspace:

1. From the workspace navigation panel, select the **Topology Maps** workspace.

2. Select **Networking Infrastructure Devices**.

Related Topics

[Views Provided by NNMi](#)

[Node Group Map Objects](#)

Routers Map

Tip: Your NNMi administrator can add or delete maps from the Topology Maps workspace. If the Routers Map is not available, your NNMi administrator might have chosen to remove this map from the Topology Maps workspace.

The Routers map shows a graphical representation of the Layer 3 connectivity in your network. Connector devices on Layer 3 maps are routers, switch-routers, and gateways. (See [About Map Symbols](#) for more information.)

Note: If the number of nodes in your network is greater than the maximum number of nodes configured to be displayed on the map, NNMi filters the map to display routers that have interfaces with addresses in the largest number of overall subnets in the network. This means that routers with little or no connectivity are only displayed for smaller networks.

Use this view when you want to do any of the following tasks:

- Understand the router connectivity between your devices.
- Determine the routers that are connected to the largest number of subnets.

To display the Routers map using the Topology Maps workspace:

1. From the workspace navigation panel, select the **Topology Maps** workspace.
2. Select **Routers**.

Related Topics

[Views Provided by NNMi](#)

[Node Group Map Objects](#)

Switches Map

Tip: Your NNMi administrator can add or delete maps from the Topology Maps workspace. If the Switches map is not available, your NNMi administrator might have chosen to remove this map from the Topology Maps workspace.

The Switches map shows a graphical representation of the Layer 2 connectivity in your network. Connector devices on Layer 2 maps are switches, ATM switches, and switch-routers. (See [About Map Symbols](#) for more information.)

Note: If the number of nodes in your network is greater than the maximum number of nodes configured to be displayed on the map, NNMi filters the map to display switches that are the most highly connected.

Use this view when you want to do any of the following tasks:

- Understand the switch connectivity between your devices.
- Determine the switches that are connected to the largest number of devices.

To display the Switches map using the Topology Maps workspace:

1. From the workspace navigation panel, select the **Topology Maps** workspace.

2. Select **Switches**.

Related Topics

[Views Provided by NNMi](#)

[Node Group Map Objects](#)

Display the Layer 2 Neighbor View

The [Layer 2](#)¹ Neighbor View shows a graphical representation of the selected device and any connections with other devices within a specified number of hops from the selected device. Connector devices on Layer 2 are switches and bridges. (See [About Map Symbols](#) for more information.)

Use this neighbor view when you want to do any of the following tasks:

- Understand the switch connectivity between your devices.
- Assist in finding the cause of a connectivity problem (see which device along the communication chain has a status other than normal).
- Identify the highly-connected nodes in your environment.
- Determine what else might be affected by a problem device, such as a problem interface.

To display the Layer 2 Neighbor View using the Troubleshooting workspace:

1. From the workspace navigation panel, select the **Troubleshooting** workspace.
2. Select **Layer 2 Neighbor View**.
3. In the **Node or IP** field, type the name or IP address of a node in your network. (NNMi provides a case-sensitive drop-down list to help speed up your selection.)
4. A hop is a node representing any network device, such as a workstation, gateway, or switch, which is connected by a link with no intermediate nodes.

Click the **Number of Hops** drop-down list, and select the number of hops to display (1-9). The default number of hops is 1.

5. All devices connected to the initial object within the specified number of hops are displayed.

The color of the line between the devices indicates the health of the connection (See "[Viewing Maps \(Network Connectivity\)](#)" (on page 97)).

A mesh connection represents the location of multiple devices interconnected with each other. A mesh is represented by the following icon:



To display the Layer 2 Neighbor View using the Actions menu in a table view or in a form:

1. From the workspace navigation panel, select the table view of interest.

¹Refers to the Data Link layer of the multilayered communication model, Open Systems Interconnection (OSI). The Data Link layer moves data across the physical links in the network. The switches and bridges are devices that redirect data messages at the layer 2 level, using the destination Media Access Control (MAC) address to determine where to direct the message.

Network Node Manager (NNMi 8.10) Online Help: Using the Console Viewing Maps (Network Connectivity)

For example the **Inventory** → **Nodes** view.

2. Select the object instance of interest (node, interface, or address).

For example, click the selection box that precedes the node of interest from the **Nodes** view.

3. Select **Actions** → **Layer 2 Neighbor View**. The starting node appears with a bold label on a map.

Note: When you use the **Actions** menu to display a map, each unique map appears in a new window. See [Using Actions to Perform Tasks](#) for more information.

4. A hop is node representing any network device, such as a workstation, gateway, or switch, which is connected by a link with no intermediate nodes.

Click the **Number of Hops** drop-down list, and select the number of hops to display (1-9). The default number of hops is 1.



5. All devices connected to the initial object within the specified number of hops are displayed.

The color of the line between the devices indicates the health of the connection (See "[Viewing Maps \(Network Connectivity\)](#)" (on page 97)).


A mesh connection represents the location of multiple devices interconnected with each other. A mesh is represented by the following icon:



To see more information about a specific connection on the map:

1. Select the line or  (mesh connection) icon of interest.
2. Click the  Open icon on the map toolbar.
3. The Layer 2 Connection form displays, showing all information for the connection. See "[Layer 2 Connection Form](#)" (on page 105) for information.

To view the addresses for a particular interface:

1. Click to select the interface of interest.
Note: If the interface is difficult to select, use the + (plus) key to zoom in on the map.
2. From the map view toolbar, select the  Open icon.
3. In the **Interface** form, select the **Addresses** tab.
4. Each address associated with the interface appears in the IP addresses table.

To view the port number for an interface:

Click the interface of interest.

The port number for the interface appears as a new label.

To view the interface name at each end of a connection:

Click the line representing the connection.

The interface name for each end of the connection appears as a new label.

Tip: Use Ctrl-Click to select multiple lines and display more interface names.

Related Topics:

[Using Map Views](#)









["Layer 2 Connection Form" \(on page 105\)](#)

Layer 2 Connection Form

The Layer 2 Connection form provides details about a managed connection. These details include the interfaces that make up the connection, the protocol used to create this connection, and the current status of the connection. For example, if all interfaces are down within a connection, the connection status is listed as Critical.

For information about each tab:

Basic Attributes

Attribute	Description
Name	Name that NNMi assigned to the Layer 2 Connection. This name contains the list of member interface names separated by a comma. Each interface name appears in the format: <i>Node_Name[Interface_Name]</i> .
Status	<p>Overall status for the current connection. NNMi follows the ISO standard for status classification. See the "Layer 2 Connection Form: Status Tab" (on page 107) for more information. Possible values are:</p> <ul style="list-style-type: none"> No Status Normal Disabled Unknown Warning Minor Major Critical <p>For information about how the current status was determined, see the "Layer 2 Connection Form: Conclusions Tab" (on page 108). Status reflects the most serious outstanding conclusion. See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p>Note: The icons are displayed only in table views.</p>


Attribute	Description
Topology Source	<p>Indicates the data source used to create this connection:</p> <p>CDP - Cisco Discovery Protocol</p> <p>EDP - Extreme Discovery Protocol</p> <p>ENDP - Enterasys Discovery Protocol (also known as CDP - Cabletron Discovery Protocol)</p> <p>FDB - Forwarding Database (also known as AFT - Address Forwarding Table on a bridge/switch)</p> <p>FDP - Foundry Discovery Protocol</p> <p>LLDP - Link Layer Discovery Protocol</p> <p>MLT - Multi-Link Trunk technology (<i>NNMi Advanced</i>)</p> <p>PagP - Cisco Systems Port Aggregation Protocol (<i>NNMi Advanced</i>)</p> <p>SONMP - SynOptics Network Management Protocol</p> <p>SUBNET CONNECTION - Subnet Connection Rule. See "Help for Administrators" for more information.</p> <p>USER - This connection was configured by your NNMi administrator (using the Connection Editor). See "Help for Administrators" for more information.</p>
Notes	<p>Provided for network operators to use for any additional notes required to further explain the Layer 2 connection. Information might include when a cable was last replaced.</p> <p>Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p>

Layer 2 Connection Form: Interfaces Tab

The "[Layer 2 Connection Form](#)" (on page 105) provides details about a managed connection. These details include the interfaces that make up the connection, the protocol used to create this connection, and the current status of the connection. For example, if all interfaces are down within a connection, the connection status is listed as Critical.

For information about each tab:

Interfaces Table


Attribute	Description
Interfaces	<p>Table view of both of the interfaces that are part of the current connection. You can use this table to determine the status, administrative state, operational state, name, type, interface speed, and Layer 2 connection for each interface associated with the selected Layer 2 Connection.</p> <p>Click the  Open icon to view more information about a specific interface.</p>

Layer 2 Connection Form: Incidents Tab

The "[Layer 2 Connection Form](#)" (on page 105) provides details about a managed connection.

For information about each tab:

Incidents Table









Attribute	Description
Associated Incidents	<p>Table view of the incidents associated with the selected Layer 2 connection. These incidents are sorted by creation time so that you can view the incidents in chronological order. Use this view to determine which incidents are still open for the selected connection.</p> <p>Click the  Open icon to open the "Incident Form" (on page 132) and view more information about a specific incident.</p>


Layer 2 Connection Form: Status Tab

The "[Layer 2 Connection Form](#)" (on page 105) provides details about a managed connection.

For information about each tab:

Status Attributes

Attribute	Description
Status	<p>Overall status for the current connection. NNMi follows the ISO standard for status classification. Possible values are:</p> <ul style="list-style-type: none">  No Status  Normal  Disabled  Unknown  Warning  Minor  Major  Critical <p>For information about how the current status was determined, see "Layer 2 Connection Form: Conclusions Tab" (on page 108). Status reflects the most serious outstanding conclusion. See "Watch Status Colors" (on page 126) for more information about possible status values.</p> <p><i>NNMi Advanced.</i> If the Layer 2 Connection is an Aggregator Link, the Status is calculated using the Status of the Aggregator Interface members. Click here for more information.</p> <p>An Aggregator Link Status of Minor indicates the Status of at least one of the Aggregator Interfaces that is a member of the Aggregator Link is Minor. A Status of Critical indicates the Status of at least one of the Aggregator Interfaces that is a member of the Aggregator Link is Critical.</p> <p>Also see Layer 2 Neighbor View Map Objects.</p> <p>Note: The icons are displayed only in table views.</p>
Status Last Modified	Date and time indicating when the status was last set.


Attribute	Description
Status History	List of up to the last five changes in status for the selected connection. This view is useful for obtaining a quick summary of the connection status so that you can better determine any patterns in connection behavior and activity. Click the  Open icon to view more information about a specific status.

Layer 2 Connection Form: Conclusions Tab

The "[Layer 2 Connection Form](#)" (on page 105) provides details about a managed connection.

For information about each tab:

Conclusions Table (for Status)

Attribute	Description
Status Conclusions	The dynamically generated list of summary statuses of the connection at points in time that contributed to the current overall status of the selected connection. Status is set by Causal Engine. Each conclusion listed is still outstanding and applies to the current overall status. This view is useful for obtaining a quick summary of the status and problem description for the current connection that led up to the connection's most current status. Examples of conclusions that might appear together are listed below: <ul style="list-style-type: none">• SNMP Agent Not Responding• Interface Down• Address Down The status value is correlated based on the most critical conclusions. Click the  Open icon to view more information about a specific conclusion.

Layer 2 Connection Form: Link Aggregation Tab (NNMi Advanced)

The "[Layer 2 Connection Form](#)" (on page 105) provides details about the selected Layer 2 connection.

For information about each tab:



The Layer 2 Connection Form: Link Aggregation Tab provides information about the **Link Aggregation**¹ in which the Layer 2 Connection belongs. This tab only appears if the selected Layer 2 Connection participates in a Link Aggregation protocol. The contents of the tab differ based on the Layer 2 Connection's role in the Link Aggregation (Member or Aggregator).

A Member Layer 2 Connection's Link Aggregation Tab displays the Link Aggregation protocol and a

¹A Link Aggregation is comprised of an Aggregator Link, Aggregator Interface, and the physical interfaces and connections that they represent. An Aggregator Link object represents many-to-many physical connections. For example, two nodes might be connected with four physical connections. These four physical connections are depicted as a single Aggregator Link object using a thick line on the Layer 2 Neighbor View map. The interface depicted at each end of the Aggregator Link object is an Aggregator Interface object. An Aggregator Interface object represents the collection of physical interfaces for one end of an Aggregator Link.

reference to the Aggregation's Aggregator Layer 2 Connection. Click here for more details about the attributes displayed.


Link Aggregation Tab

Attribute	Description
Link Aggregation Protocol	<p>Protocol used to create the Link Aggregation, including the Aggregator Layer 2 Connection and its physical Members. Possible values include:</p> <ul style="list-style-type: none"> ● Cisco Systems Port Aggregation Protocol (pagp) ● Multi-Link Trunk technology (mlt) ● Split Mutli-Link Trunk technology (splitMlt) ● Inter-switch trunk that is part of a Split Multi-Link Trunk configuration (istMlt) <p>Note: In rare cases, it is possible for a Layer 2 Connection to connect sets of Aggregator/Member Interfaces that are configured using different Link Aggregation protocols. In these cases, the Layer 2 Connection's Link Aggregation Protocol attribute value contains multiple protocols separated with a slash (/).</p>
Aggregator	<p>Name of the Aggregator Layer 2 Connection that is part of the Link Aggregation. The Aggregator represents the collection of physical Layer 2 Connections that are Members of the Link Aggregation.</p> <p>See Layer 2 Neighbor View Map Objects for more information.</p> <p>The name value is the Name that the NNMi administrator provided to identify this Layer 2 Connection.</p> <p>Click the  Lookup icon, and choose  Open to open the form for the Aggregator Link.</p>

The Aggregator Layer 2 Connection's Link Aggregation Tab lists the Member Layer 2 Connections of the Link Aggregation and provides cumulative bandwidth statistics for the Link Aggregation Layer 2 Connections. Click here for more details of the attributes displayed.

Link Aggregation Tab

Attribute	Description
Link Aggregation Protocol	<p>Protocol used to create the Link Aggregation, including the Aggregator Interface and its physical Members. Possible values include:</p> <ul style="list-style-type: none"> ● Cisco Systems Port Aggregation Protocol (pagp) ● Multi-Link Trunk technology (mlt) ● Split Mutli-Link Trunk technology (splitMlt) ● Inter-switch trunk that is part of a Split Multi-Link Trunk configuration (istMlt) <p>Note: In rare cases, it is possible for a Layer 2 Connection to connect sets of Aggregator/Member Interfaces that are configured using different Link Aggregation protocols. In these cases, the Layer 2 Connection's Link Aggregation Protocol attribute value contains multiple protocols separated with a slash (/).</p>
Available Bandwidth	<p>The lowest Available Bandwidth value of the Aggregator Interfaces connected by this Layer 2 Connection.</p>

Attribute	Description
Maximum Bandwidth	The lowest Maximum Bandwidth value of the Aggregator Interfaces connected by this Layer 2 Connection.
Available Bandwidth Percentage	Percentage value computed using the Available Bandwidth divided by the Maximum Bandwidth values.
Members	Table view of the Layer 2 Connections that are Members of the selected Aggregator Link. Click the  Open icon to view more information about a specific Layer 2 Connection.

Layer 2 Connection Form: Registration Tab

The "[Layer 2 Connection Form](#)" (on page 105) provides details about a managed connection.

For information about each tab:

Registration

Attribute	Description
Created	Date and time the selected object instance was created. NNM uses the locale of the client and the date and time from the NNMi management server.
Last Modified	Date the selected object instance was last modified. NNM uses the locale of the client and the date and time from the NNMi management server.

Display the Layer 3 Neighbor View

The [Layer 3](#)¹ Neighbor View is a graphical representation of the subnets in which the starting node participates, and the health of the routers in those subnets. Connector devices on Layer 3 are routers and switch/routers. (See [About Map Symbols](#) for more information.)

Use this neighbor view when you want to do any of the following tasks:

- Determine whether a subnet is down.
- Understand the router connectivity between your devices.
- Assist in finding the root cause of a connectivity problem (see which device along the communication chain has a status other than normal).
- Identify the highly-connected nodes in your environment.

To display a Layer 3 Neighbor View using the Troubleshooting workspace:

1. From the workspace navigation panel, select the **Troubleshooting** workspace.
2. Select **Layer 3 Neighbor View**.

¹Refers to the Network layer of the multilayered communication model, Open Systems Interconnection (OSI). The Network layer is concerned with knowing the address of the neighboring nodes in the network, selecting routes and quality of service, and recognizing and forwarding incoming messages to local host domains. The router and switch-router are the devices that redirect data messages at the Layer 3 level. Everything in a subnet is connected at the Layer 3 (IP) level.

3. In the **Node or IP** field, type the name or IP address of a node in your network. (NNMi provides a case-sensitive drop-down list to help speed up your selection.)
4. A hop represents any network device, such as a workstation, gateway, or switch, that is connected by a link with no intermediate nodes.


Click the **Number of Hops** drop-down list, and select the number of hops to display (1-9). The default number of hops is 1.

5. All devices connected to the initial object within the specified number of hops are displayed.
The color of the line between the devices indicates the health of the subnet between the devices (see ["Viewing Maps \(Network Connectivity\)" \(on page 97\)](#)).

To display the Layer 3 Neighbor View using the Actions menu in a table view or in a form:

1. From the workspace navigation panel, select the table view of interest.
For example the **Inventory** → **Nodes** view.
2. Select the initial object of interest.
For example, click the selection box that precedes the node of interest from the **Nodes** view.
3. Select **Actions** → **Layer 3 Neighbor View**.
Note: When you use the **Actions** menu to display a map, each unique map appears in a new window. See [Using Actions to Perform Tasks](#) for more information.
4. A hop represents any network device, such as a workstation, gateway, or switch, that is connected by a link with no intermediate nodes.
Click the **Number of Hops** drop-down list, and select the number of hops to display (1-9). The default number of hops is 1.
5. All devices connected to the initial object within the specified number of hops are displayed.
The color of the line between the devices indicates the health of the connection (see ["Viewing Maps \(Network Connectivity\)" \(on page 97\)](#)).

To see more information about a specific subnet on the map:

1. Select the line that represents the subnet of interest.
2. Click the  Open icon on the map toolbar.

The IP Subnet form displays, showing all details of the subnet. See ["IP Subnet Form" \(on page 112\)](#) for more information.

To view address information for an interface at each end of a connection:

Click the line representing the connection of interest.

The IP address for each interface appears as a new label.

Tip: Use Ctrl-Click to select multiple lines and display more IP addresses.

Related Topics:

[Using Map Views](#)

IP Subnet Form

The IP Subnet form provides details about the selected subnet.

If your role allows, you can add notes to communicate information about this subnet to your team.

For information about each tab:

Basic Attributes


Attribute	Description
Name	Subnet for the IP network. This value is determined by the discovery process (calculated from IP Addresses and the subnet prefix information).
Prefix	The value of the prefix for the current subnet (also known as the subnet address).
Prefix Length	The number of significant bits in the subnet prefix. This value is used to determine the size of the subnet.
Notes	<p>Provided for network operators to use for any additional notes required to further explain the subnet. Information might include its use; for example, point to point for dialup. You might also use this attribute to track which geographical group might use the subnet.</p> <p>Type a maximum of 1024 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p> <p>Note: You can sort your subnet table views based on this value. Therefore, you might want to include keywords for this attribute value.</p>

IP Subnet Form: IP Addresses Tab

The "[IP Subnet Form](#)" (on page 112) provides details about the selected subnet.

For information about each tab:

IP Addresses Table

Attribute	Description
IP Addresses	<p>Table view of the IP addresses associated with the selected subnet. You can use this table to determine the state, address, and interface, and parent node for each address associated with the selected subnet.</p> <p>Click the  Open icon to open the "IP Address Form" (on page 72) and view more information about a specific address.</p>

IP Subnet Form: Registration Tab

The "[IP Subnet Form](#)" (on page 112) provides details about the subnet selected.

For information about each tab:

Registration

Attribute	Description
Created	Date and time the selected object instance was created. NNM uses the locale of the client and the date and time from the NNMi management server.

Attribute	Description
Last Modified	Date the selected object instance was last modified. NNM uses the locale of the client and the date and time from the NNMi management server.

Path Between Two Nodes that Have IPv4 Addresses

Note: If NNMi Advanced is licensed and installed, also see ["Enhanced Path View \(NNMi Advanced\)" \(on page 116\)](#).

Path View calculates the route that data flows between two nodes, and provides a map of that information. The two nodes can be any combination of end nodes, switches, or routers.

Note: End nodes are the primary use case for this view. If you specify switches or routers as the Source or Destination, the path is a best effort.

Each connection between the two nodes is a line on the map. If more than one route is possible, NNMi uses a set of rules to choose the displayed route (see ["Path Calculation Rules" \(on page 114\)](#)). NNMi indicates there is more than one possible path under either of the following conditions:


- *NNMi Advanced.* NNMi finds more than one Active router in a Router Redundancy Group. See ["Router Redundancy Group View \(NNMi Advanced\)" \(on page 22\)](#) for more information about Router Redundancy Groups. See ["Path Calculation Rules" \(on page 114\)](#) for more information about Active router paths.
- *NNMi Advanced.* HP Router Analytics Management System (RAMS) determines more than one equal cost path and, therefore, cannot determine which path is in use. See ["Enhanced Path View \(NNMi Advanced\)" \(on page 116\)](#) for more information.



Note: Your NNMi administrator can configure Path View connections using a `PathConnections.xml` file. This file enables Path View to traverse undiscovered regions of your network. Each time NNMi determines a node in the Path View, NNMi checks whether the node is specified as a Start node in the `PathConnections.xml` file. If the node is specified as a Start node, each path segment configured in `PathConnections.xml` is inserted in the Path View map.

NNMi Advanced. When RAMS data is used to determine the router paths, NNMi ignores the `PathConnections.xml` file. See ["Enhanced Path View \(NNMi Advanced\)" \(on page 116\)](#) for more information.

Path View is a *flow diagram* rather than a *connection diagram*. It displays the flow of network traffic rather than all of the available connections. To view all possible connections between nodes, use the Layer 2 Neighbor View. See ["Display the Layer 2 Neighbor View" \(on page 103\)](#) for more information.


Note: Intermediate devices that are physically connected might appear in a Path View. For example, if two end nodes connect to the same switch, but exist in different VLANs, the path includes the access router where the VLAN and subnet determination is made.

Path View is useful for diagnosing connectivity problems. Path View shows each switch (and the port on that switch) that participates in the current path. You can quickly identify problematic switch ports that need to be shut down. Select any map symbol and click the  Open icon to display all known details about that object. Mouse over any object on the map to access the Quick View information about that object.


Tip: Click the  Swap icon to switch the **Source** and **Destination** values, and then click the  Compute Path. Sometimes NNMi can detect more information from one direction or the other.

Using Path View from the Troubleshooting workspace:

1. From the workspace navigation panel, select the **Troubleshooting** workspace.

2. Select **Path View**.
3. In the **Source** field, type the name or IPv4 address of a node in your network. (NNMi provides a case-sensitive drop-down list to help speed up your selection.)
4. *Optional.* In the **Destination** field, type a node name or IPv4 address.
If a **Destination** value is not provided, NNMi displays the path from the **Source** node to its access router.
5. Click the  Compute Path icon.

Using Path View from the Actions menu in a table view or in a form:

1. Access a table view of nodes, interfaces, or IPv4 addresses.
2. Decide which object you want to use as the starting point in the path (**Source**). Click the selection box in the row representing that object.
3. *Optional.* Decide which object you want to use as the destination point in the path (**Destination**). Click the selection box in the row representing that object.
If a **Destination** value is not provided, NNMi displays the path from the **Source** node to its access router.
4. In the menu bar, select **Actions** → **Path View**.
Note: When you use the **Actions** menu to display a map, each unique map appears in a new window. See [Using Actions to Perform Tasks](#) for more information.
5. Click the  Compute Path icon to display the map of the path.

Related Topics:

["Path Calculation Rules" \(on page 114\)](#)

["Investigate Errors and Performance Issues" \(on page 116\)](#)

["Access Node Details" \(on page 127\)](#)

Path Calculation Rules

Note: If NNMi Advanced is licensed and installed, also see ["Enhanced Path View \(NNMi Advanced\)" \(on page 116\)](#)

Path View calculates the active flow of data between devices at the time the view is requested. The active path includes the following devices:

- Source and destination nodes
- Layer 2 devices between the source node and its access router
- Layer 2 devices between the destination node and its access router
- Layer 2 and Layer 3 routing core between the two access routers


Note: The path calculated can include one or more VLANs when applicable.

NNMi starts with the specified source and follows the active path to the specified destination. If no missing connections are detected, the Path View shows the source node, destination node, and each router and switch in between.

Note: Your NNMi administrator can configure Path View connections using a `PathConnections.xml` file. This file enables Path View to traverse undiscovered regions of your network. Each time NNMi determines a node in the Path View, NNMi checks whether the node is specified as a Start node in

the `PathConnections.xml` file. If the nodes is specified as a Start node, each path segment configured in `PathConnections.xml` is inserted in the Path View map.


NNMi Advanced. When RAMS data is used to determine the router paths, NNMi ignores the `PathConnections.xml` file. NNMi also shows all Equal Cost Multi-Paths (ECMP). See "[Enhanced Path View \(NNMi Advanced\)](#)" (on page 116) for more information.

A  cloud symbol can represent the following types of information. The map can include multiple cloud symbols:

- If a missing connection is detected (no response to SNMP and no entry in `PathConnections.xml`), the cloud symbol appears in the routing core between the access routers.
- If the port connecting the end node to the first switch is forwarding more than one MAC address, this indicates an intermediate device (such as a hub or one or more undiscovered switches). A cloud appears at that location in the path.

When interpreting Path View results, note the following:

- The Source and Destination nodes must meet **either** of the following criteria:
 - Support SNMP and be previously discovered by NNMi (recorded in the topology database)
 - Have traceroute available
- All access routers and any Layer 2 devices between the Source and Destination nodes must meet the following criteria:
 - Support SNMP
 - Be previously discovered by NNMi (recorded in the topology database)
- *Optional.* Each router and switch is monitored by NNMi.
- The time stamp provided in the final Path View is the time at which the final active path was determined.
- *NNMi Advanced.* If the Router Redundancy Group has more than one Active router, NNMi selects one Active router for the path. To indicate there is more than one possible path, NNMi connects any additional Active routers to the chosen router as shown in the following example:



NNMi iSPI for Performance. You can access performance data from Path Views that contain single or multiple paths. See "[Investigate Errors and Performance Issues](#)" (on page 116) for more information.

Related Topics:

[Use Map Views](#) (and accessing Quick View information)

["Path View Limitations"](#) (on page 116)

Path View Limitations

Path View cannot calculate accurate paths if you have two or more areas of your network which are separated by undiscovered devices. Your NNMi administrator must use the `PathConnections.xml` file to specify areas of your network that are separated by undiscovered devices. See "Help for Administrators" for more information.

Path View uses a variety of sources for information to calculate an accurate path. These sources of information do, however, have limitations:

- SNMP ipRoute tables. If the Source or Destination node represents a device other than a router and the device does not support SNMP or does not return valid ipRoute table information, NNMi depends on traceroute to follow the path to find the nodes's access router.

Note: *NNMi Advanced*. NNMi can use RAMS data to determine router paths. When RAMS data is used to determine the router paths, NNMi ignores the `PathConnections.xml` file. See "[Enhanced Path View \(NNMi Advanced\)](#)" (on page 116) for more information.

- Open Shortest Path First protocol or Cisco Global Load Balancing protocol. Path View shows the access router selected by one of these routing protocols. If two or more access routers communicate with a device, only one access router is shown (usually the one with the shortest path).
- Cisco Express Forwarding protocol. This protocol bypasses some of the data that Path View needs. If any routers in the path are using this protocol, Path View might display an incorrect router path.

Investigate Errors and Performance Issues

The color of the background shape of each map symbol conveys the most recent health status. Select an object on the Path View map that has a status color other than green (see "[Watch Status Colors](#)" (on page 126) for more information about interpreting non-normal status colors). You can access the following types of information about each node:

- "[Access Node Details](#)" (on page 127)
- "[Access a Problem Device](#)" (on page 127)
- "[Access All Related Incidents](#)" (on page 128)

See "[Interpret Root Cause Incidents](#)" (on page 168) for more information about interpreting the incident information displayed.

NNM iSPI for Performance. Click here for more information about additional tools for accessing performance data.

To access performance data from a Path View map:

Select **Actions** → **Reporting - Path Health**.

If the Path View map contains multiple possible paths from the Source to Destination Node, NNMi alerts and guides you to select a single, unambiguous path for analysis before it can present a Path Health Report. You can bypass this interaction by pre-selecting enough map objects (for example, connections) to resolve any ambiguities before selecting **Actions** → **Reporting - Path Health**.

Enhanced Path View (*NNMi Advanced*)

NNMi Advanced uses any of the following when calculating a Path View:

- Hot Standby Router Protocol (HSRP) nodes
- Virtual Router Redundancy Protocol (VRRP) nodes

- HP Router Analytics Management System (RAMS) data

Note: When using RAMS data in Path View, NNMi ignores the `PathConnections.xml` file. See "Help for Administrators" for more information.

When using NNMi Advanced, more than one path might appear if HP Router Analytics Management System (RAMS) determines more than one equal cost path and, therefore, cannot determine which path is in use. Also see [RAMS Data and Path View](#) below.

HSRP and VRRP and Path View

If NNMi Advanced is licensed and installed, by default, NNMi monitors state and priority information for any discovered HSRP and VRRP objects in the network. NNMi Advanced can then include these virtual HSRP and VRRP devices when calculating the Path View. The routers included are the Active or Master router in the HSRP or VRRP Group.

RAMS Data and Path View

If your NNMi Administrator configured one or more RAMS, NNMi Advanced calculates the Path View using RAMS data. (RAMS is an IP Route Analytics tool that listens to routing protocols and builds a real-time routing topology map.)

RAMS enhances NNMi's ability to trace the route path between the source and destination node in the following ways:

- NNMi Advanced does not use SNMP to calculate the router path. This means that NNMi Advanced does not need to wait for SNMP responses and can calculate the Path View more quickly.
- NNMi Advanced displays equal cost paths when calculating the router path.

Monitoring Devices for Problems

NNMi offers several out-of-the-box views to assist you in monitoring your network. When using views, you can choose to do either of the following:

- Monitor views that contain your critical nodes and interfaces.
- Watch an incident view for incidents with an abnormal status, such as **Warning**, **Minor**, **Major**, or **Critical**.
- Watch a map view for any icons that change color to yellow or red.

No matter which way you prefer, you can navigate from a map to a table view or from a table view to a map.

Related Topics:

["Filter Views by Node or Interface Group" \(on page 15\)](#)

["Monitor with Table Views" \(on page 118\)](#)

["Monitor with Map Views" \(on page 126\)](#)

Monitor with Table Views

NNMi provides the following out-of-the-box node and interface views to assist you in monitoring the network for problems. These views help you quickly identify the nodes and interfaces that need your more immediate attention:

["Critical Interfaces View" \(on page 118\)](#)

["Critical Nodes View" \(on page 119\)](#)

["Non-Normal Interfaces View" \(on page 120\)](#)

["Non-Normal Nodes View" \(on page 120\)](#)

["Not Responding Address View" \(on page 122\)](#)

Critical Interfaces View

Tip: See ["Interface Form" \(on page 58\)](#) for more details about the interface attributes that appear in this view's column headings.

The Critical Interfaces view is provided so that you can view all of your interfaces whose status is **Critical**.

For each interface displayed in the view, you can identify the interface's status, administrative (**AS**) and operational (**OS**) state, associated node Name value (**Hosted On Node**), the interface name, interface type, interface speed, its description, the interface alias, the date the interface status was last modified, the name of the Layer 2 connection associated with the interface, and any notes related to the interface.

By default, this view is sorted by the date the interface status was last modified (**Status Last Modified**).

See ["Interfaces View \(Inventory\)" \(on page 16\)](#) for more information about ways to use an interface view.

Related Topics

[Use Table Views](#)

Critical Nodes View

Tip: See "[Node Form](#)" (on page 27) for more details about the node attributes that appear in this view's column headings.

The Critical Nodes view in the Monitoring workspace is useful for identifying all of the nodes whose status is critical. Sorting the view by system location (the current value of the sysLocation MIB variable) might help you identify whether the problem can be isolated to a particular area of your network. You can also use this view to obtain the contact information for a problem node in case you need more background information to troubleshoot the problem.

For each node displayed, you can identify its status, device category, name, hostname, management address, system location, device profile, the date and time its status was last changed, and any notes included for the node.

The device profile information determines how devices of this type are managed and the icon and background shape displayed on maps.

By default, this view is sorted by the date the node status was last modified (**Status Last Modified**).

Node views are useful for quickly identifying items described in the following table.

Uses for the Nodes Views

Use	Description
View all device types being managed	Sort the view by the Device Profile attribute.
Identify whether the problem can be isolated to a particular area of your network	Sort the view by System Location . This is the current value of the sysLocation MIB variable.
View address and subnet information associated with a selected node to better determine the scope of the problem	From the Nodes view, open the Node form. Then access the Address tab. See " Node Form " (on page 27) and " IP Subnet Form " (on page 112) for more information.
Access a map view of a selected node and its surrounding topology	Select the node of interest and use the Actions menu from the main toolbar. See " Viewing Maps (Network Connectivity) " (on page 97) for more information.
View the statuses of interfaces associated with a node	If a node is not completely down, you might want to see which interfaces are down for the selected node. To do so, open the Node form and select the Interfaces tab. See " Interface Form " (on page 58) for more information about interface attributes.
View the number of devices that are served by this node.	Select the node you want and access the Layer 2 or Layer 3 Neighbor View using the Actions menu.

Critical Component View

Tip: See "[Node Form](#)" (on page 27) for more details about the attributes that appear in this view's column headings.

The Critical Component view in the Monitoring workspace is useful for identifying all of the nodes whose status is Critical due to a problem with a node component. Examples of node components include temperature, fan, and memory.

For each component displayed, you can see its status, name, type, and the node on which it resides.

Non-Normal Interfaces View

Tip: See "[Interface Form](#)" (on page 58) for more details about the interface attributes that appear in this view's column headings.

The Non-Normal Interfaces view in the Monitoring workspace is useful for identifying all of the network interfaces that might need operator attention. Possible statuses for these interfaces include:

- Warning
- Major
- Minor
- Critical

Note: Interfaces displayed in this table all have the Administrative State equal to Up.

For each interface displayed in the view, you can identify its status, operational state, associated node Name value (**Hosted On Node**), the interface name, type, speed, a description of the interface, the ifAlias value, the date and time the status of the interface was last modified, the name of the Layer 2 connection associated with the interface, and any notes included for the interface.

By default, this view is sorted by the date the interface status was last modified (**Status Last Modified**).

Interface views are useful for quickly identifying items described in the following table.

Use	Description
View all network interfaces per node	Sort the view by Hosted On . This can help you organize your interfaces per node, so that you can identify the nodes that might need attention.
Determine the health of each of the managed interfaces	Sort the view by the Status attribute. To view only those interfaces whose status is Critical , use the Critical Interfaces view provided by NNMi. See " Critical Interfaces View " (on page 118) for more information.
Determine the types of interfaces that are being managed.	Sort on the IfType (interface type) attribute.
Access a map view of the network interface and its surrounding topology.	Select the interface of interest and use the Actions menu to select either the Layer 2 or Layer 3 Neighbor View. See Use Table Views for more information.

Non-Normal Nodes View

Tip: See "[Node Form](#)" (on page 27) for more details about the node attributes that appear in this view's column headings.

The Non-Normal Nodes view in the Monitoring workspace is useful for identifying all of the nodes that might need your attention. Possible statuses for these nodes include:

-  Warning
-  Minor
-  Major
-  Critical

For each node displayed, you can identify its status, device category (for example, Switch), hostname, management address, system location (the current value of the sysLocation MIB variable), device profile, the date and time its status was last changed, and any notes included for the node.

The device profile information determines how devices of this type are managed and the icon and background shape displayed on maps.

By default, this view is sorted by the date the node status was last modified (**Status Last Modified**).

Node views are useful for quickly identifying items described in the following table.

Use	Description
View all problem nodes	Sort the view by Status so that you can be quickly alerted to existing and potential problems. You can also access the Critical Nodes view provided by NNMi. See "Critical Nodes View" (on page 119) for more information.
Identify whether the problem can be isolated to a particular area of your network	Sort the view by System Location . This is the current value of the sysLocation MIB variable.
View all device types being managed	Sort the view by the Device Profile attribute.
View address and subnet information associated with a selected node to better determine the scope of the problem	From the Nodes view, open the Node form. Then access the Address tab. See "Node Form" (on page 27) and "IP Subnet Form" (on page 112) for more information.
Access a map view of a selected node and its surrounding topology	Select the node of interest and use the Actions menu from the main toolbar. See Use Table Views for more information.
View the statuses of interfaces associated with a node	If a node is not completely down, you might want to see which interfaces are down for the selected node. To do so, open the Node form and select the Interfaces tab.
The number of devices that are served by this node.	Select the node you want and access the Layer 2 or Layer 3 Neighbor View using the Actions menu.


Non-Normal Router Redundancy Group View (NNMi Advanced)

Tip: See the context-sensitive link for the ["Router Redundancy Group Form \(NNMi Advanced\)" \(on page 78\)](#) for more details about the Router Redundancy Group attributes that appear in this view's column headings.

Your network administrator might have set up groups of redundant routers to help ensure that information packets reach their intended destination. When monitoring your network, use the Non-Normal Router Redundancy Group view to see those router groups whose status is other than Normal. This means there is a problem with one or more interfaces or IP addresses on the routers in the router groups.

For each redundant routers group displayed in the view, you can identify the Router Redundancy Group status, Router Redundancy Group name, the Router Redundancy Group protocol (for example, HSRP), and the date the Router Redundancy Group status was last modified.

To see the incidents related to a Router Redundancy Group:

1. Click the  Open icon that precedes the Router Redundancy Group of interest to open the form.
2. Select the **Incidents** tab.

To view the members that belong to this group:

Click the  Open icon that precedes the Router Redundancy Group of interest to open the form.

On the **Router Router Redundancy Members** tab, you should see a table view of the nodes and interfaces that belong to the selected Router Redundancy Group.

Related Topics

["Router Redundancy Group View \(NNMi Advanced\)" \(on page 22\)](#)

["Router Redundancy Group Form \(NNMi Advanced\)" \(on page 78\)](#)

["Router Redundancy Group View \(NNMi Advanced\)" \(on page 22\)](#)

Not Responding Address View

Tip: See ["IP Address Form" \(on page 72\)](#) for more details about the node attributes that appear in this view's column headings.

The **Not Responding Address** view in the **Monitoring** workspace is useful for identifying all of the addresses whose state is **Not Responding**. A **Not Responding** state indicates that the address is not responding to ICMP ping.

Note: Because all addresses in this view have a state of **Not Responding**, the **State** column is not displayed in this view.


For each address displayed in the view, you can identify the status, address, associated node Name value (**Hosted On Node**), interface, the subnet prefix (**In Subnet**) and prefix length (**PL**), and any notes included for the IP address.

Nodes by Status View

Tip: See ["Node Form" \(on page 27\)](#) for more details about the node attributes that appear in this view's column headings.

The Nodes by Status view in the Monitoring workspace lets you filter your view by the **Status** value. Examples of **Status** values include **Normal**, **Warning**, **Minor**, **Major**, and **Critical**.

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



If your NNMi administrator set up Node Groups or Interface Groups to identify important elements of your environment, you can filter this view to show only the nodes that need your immediate attention. For example, by using the status and node group filters, you can display all nodes that have a Status value of **Critical** and are related to a certain group of nodes.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each node displayed, you can view its status, device category, name, hostname, management address, system location (the current value of the sysLocation MIB variable), device profile, the date the node's status was last modified, and any notes that exist for this node.

By default, this view is sorted by the date the node status was last modified (**Status Last Modified**).

Interfaces by Status View

Tip: See "[Interface Form](#)" (on page 58) for more details about the node attributes that appear in this view's column headings.

The **Interface by Status** view lets you filter your view by the **Status** value. Examples of **Status** values include **Normal**, **Warning**, **Minor**, **Major**, and **Critical**.

You can use this view to help identify the status of the interfaces that you are monitoring. If your network administrator has set up node or interface groups, by using the status and Node Group filters, you can display the status for only your important interfaces.

For each interface displayed, you can view the status, administrative state, the operational state, associated node Name value for the computer on which the interface resides (**Hosted On Node**), the interface name, type, speed, input speed, output speed, the date the status was last modified, an interface description, the ifAlias value, and any related notes.


By default, this view is sorted by the date the interface status was last modified (**Status Last Modified**).

Interfaces by Administrative State View

Tip: See "[Interface Form](#)" (on page 58) for more details about the interface attributes that appear in this view's column headings.

The **Interface by Administrative State** view lets you filter your view by the administrative state value. Examples of **Administrative State** include **Up**, **Down**, and **Testing**.

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



You can use this view to help identify the administrative state of your interfaces. If your network administrator has set up node or interface groups for those nodes or interfaces important to you, by using the administrative state and Node Group filters, you can check the state set by your administrator for each of the interfaces that is important to you. This might be useful for proactively monitoring your network and checking for those interfaces whose state indicates there might be a potential problem.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each interface displayed, you can view its status, the operational state, associated node Name value for the computer on which the interface resides (**Hosted On Node**), interface name, type, speed, input speed, output speed, the date the status was last modified, a description of the interface, the ifAlias value, and any notes that exist about the interface.


By default, this view is sorted by the date the interface status was last modified (**Status Last Modified**).

Interfaces by Operational State View

Tip: See "[Interface Form](#)" (on page 58) for more details about the interface attributes that appear in this view's column headings.

The **Interface by Operational State** view lets you filter your view by the operational state value. Examples of Operational State include **Up**, **Down**, and **Testing**.

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



You can use this view to help identify the operational state of your interfaces. If your network administrator has set up node or interface groups for those nodes or interfaces important to you, by using the operational state and Node Group filters, you can check the operational state for each of the interfaces that is important to you. This might be useful for proactively monitoring your network and checking for those interfaces whose state indicates there might be a potential problem.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each interface displayed, you can view its status, the administrative state, associated node Name value of the computer on which the interface resides (**Hosted On Node**), the interface name, type, speed, input speed, output speed, the date the status was last modified, a description of the interface, the ifAlias value, and any notes that exist about the interface.


By default, this view is sorted by the date the interface status was last modified (**Status Last Modified**).

IP Addresses by State View

Tip: See ["IP Address Form" \(on page 72\)](#) for more details about the IP address attributes that appear in this view's column headings.

The IP Addresses by State view in the Monitoring workspace lets you filter your view by the **State** value. Examples of **State** include: **Responding**, **Not Responding**, and **Not Polled**.

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



You can use this view to help identify the state of your IP addresses. If your network administrator has set up node or interface groups for those nodes or interfaces important to you, by using the state and node or interface group filters, you can check the state for only the important addresses.

Note: If you filter your view using additional filters, such as Node Groups, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each address displayed in the view, you can see its status, address, the name of the pertinent interface, associated node Name value (**Hosted On Node**), the subnet in which the address is contained, the subnet prefix length (**PL**), the date the status of the address was most recently modified, and any notes included about the IP address.


Component by Status View

Tip: See ["Node Form" \(on page 27\)](#) for more details about the attributes that appear in this view's column headings.

Use the Component by Status view in the Monitoring workspace to help identify the status of node components. Examples of node components include temperature, fan, and memory.

This view lets you filter your view by the **Status** value. Examples of **Status** include: **Critical, Warning, Major, Minor, and No Status**.

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



If your network administrator has set up node or interface groups for those nodes or interfaces important to you, by using the status and node or interface group filters, you can check the status for the components for only the important nodes.

Note: If you filter your view using additional filters, such as Node Groups, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each component displayed, you can see its status, name, type, and the node on which it resides.

Interface Performance View (*NNM iSPI for Performance*)

NNM iSPI for Performance. Data appears in this view only if the NNM iSPI for Performance is installed and your NNMi administrator enables performance monitoring.

The interface performance view helps you identify the over and under utilized interfaces for the nodes in your managed network. Sort this view by Hosted On Node to help you identify potential problem nodes that are over utilized.

If your network administrator has set up node or interface groups for those nodes or interfaces important to you, you can check the interface status for each interface that is important to you. This might be useful for proactively monitoring your network and checking for those interfaces whose input or output utilization, error, or discard rate indicate there might be a potential problem.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each interface displayed, you can view its input and output utilization rates, input and output error rates, input and output discard rates, associated node Name value of the computer on which the interface resides (**Hosted On Node**), the interface name, speed, input speed, output speed, and any notes that exist about the interface.

Tip: See ["Interface Form" \(on page 58\)](#) for more details about the interface attributes that appear in this view's column headings.

Node Groups View (Monitoring)

Tip: See the context-sensitive link for the Node Groups form for more details about the Node Group attributes that appear in this view's column headings.

When monitoring your network, you might be interested in only viewing information for a particular set of nodes. Your network administrator is able to group sets of nodes into node groups. An example node group could be all important Cisco routers, or all routers in a particular building. See [About Node and Interface Groups](#) for more information about how your administrator sets up node groups. See [Filter by Node or Interface Group](#) for more information about filtering views using node and interface groups.

To find the definition for a particular Node Group filter, navigate to the Inventory workspace, and select the Node Groups view.

For each node group displayed in the view, you can identify the node group status, name, whether the node group appears in the filter list for node and interface views, whether the node group is available as a filter in NNM iSPI for Performance, and any notes about the node group.

Monitor with Map Views

NNMi provides three kinds of map views that show a graphical representation of a selected device and the devices connected to it (Layer 2 Neighbor View, Layer 3 Neighbor View, and Path View).


Map views are useful for the following tasks:

- Identify important connector devices, such as a switch that might be a single connection to a main office or campus.
- Identify how many devices are served by a node or interface.
- Identify routing issues.
- Identify network issues between two nodes.

Each node on the map is represented by a map symbol. Each map symbol has a background shape and a foreground image. The background shape conveys two pieces of information:

- The type of device indicated by shape. See [About Map Symbols](#).
- The most recent health status represented by the background color. See [About Status Colors](#).

The foreground image assists in identifying the device model. NNMi uses first the Family, then Vendor, and then the Category device profile information to determine the foreground image to be displayed. If there is no image defined for any of these attributes, NNMi displays ***no* icon** in the map node.

Note: Your NNMi administrator is able to delete nodes and other objects from the NNMi database. If you are viewing a node that has recently been deleted by another user, the node appears in your view until your view is refreshed. To refresh a map view, click  from the map view toolbar.

To monitor your network using a network map:

- ["Watch Status Colors" \(on page 126\)](#)
- ["Determine Problem Scope" \(on page 127\)](#)
- ["Access Node Details" \(on page 127\)](#)

Related Topics:

[Use Map Views](#)

["Display the Layer 2 Neighbor View" \(on page 103\)](#)

["Display the Layer 3 Neighbor View" \(on page 110\)](#)









["Path Between Two Nodes that Have IPv4 Addresses" \(on page 113\)](#)

Watch Status Colors

When monitoring the network using a map view, watch for nodes whose status color is non-normal. The background shapes of the map symbols change color based on the current health status of the represented device.

The following table describes the meaning for each status color that might appear on a map.

Status Colors

Color	Meaning	Description
	Unknown	Indicates one of the following: <ul style="list-style-type: none">• The node was just added to the NNMi database, and health status is not yet calculated.• The node is unreachable and cannot be polled.
	Normal	Indicates there are no known problems related to the associated object.
	Warning	Indicates there may or may not be a problem related to the associated object.
	Minor	Indicates NNMi has detected problems related to the associated object that require further investigation.
	Major	Indicates NNMi detected problems that could precede a critical situation.
	Critical	Indicates NNMi detected problems that require immediate attention.
	Disabled	Indicates the object is administratively "disabled". (The current value of MIB II ifAdminStatus is "disabled".)
	No Status	Indicates that NNMi monitoring configuration specifically excludes this device. The Status is either not calculated or the device is Not Managed/Out Of Service.

Determine Problem Scope

Maps are a useful tool for determining the scope of a problem. Scan the map to determine the scope of the problem. For example, look for large clusters of non-normal color icons to determine if there is a large-scale outage.

If your naming scheme is based on node location, you might also be able to determine if the problem is isolated to a particular site or store.

Access a Problem Device

Using NNMi's **Actions** menu you can access the following commonly used tools to investigate device access and configuration information:

- Verify that the node can be reached by using ping, see ["Test Node Access \(Ping\)" \(on page 191\)](#).
- Launch telnet to access the device and determine more information, see ["Establish Contact with a Node \(telnet\)" \(on page 193\)](#).
- Use traceroute to view traffic paths, see ["Find the Route \(traceroute\)" \(on page 192\)](#).

Note: Access to these commands depends on the NNMi role assigned to your user account. If you are unable to access an action, contact your NNMi administrator.

Access Node Details


Select any node symbol on the map, and display all of the information related to that specified node. The Node form is useful for troubleshooting purposes:

- List of the conclusions that led to the current status, and information about status calculations for the node over time.

- Status of each interface contained in the node. For example, if the node is not completely down, you might want to see which interfaces are down.
- Status of each address associated with this node.
- System contact information.
- All of the incidents associated with the node.

NNMi also provides a Quick View that displays a small subset of information about a selected object.

To view all details associated with a map object:

1. In a map view, select the object.
2. Click the  Open icon in the menu bar.
3. The form displays, containing details of all information related to the object.
4. View or edit the details of the selected object.

To access the Quick View for a map object:

1. Using your mouse, hover over the object of interest.
The Quick View window displays, containing a read-only subset of details about the object.
2. To close the Quick View, move your mouse away from the object.

Related Topics:

["Node Form" \(on page 27\)](#)



["Interface Form" \(on page 58\)](#)

["IP Address Form" \(on page 72\)](#)

Access All Related Incidents

If you are using a map view to monitor your network, there are times when you might want to switch to an incident view for more information. Information available from an incident view includes the first time a notification was received, the description of the problem (for example, **Node Down** or **Address Not Responding**), and the incident category. The incident category helps to identify the type of problem, such as fault, performance, or security.

To display all incidents related to an object on a map:

1. Click to select the node or interface of interest.
2. Click the  Open icon to open the form.
3. Select the **Incidents** tab.
4. The incidents table includes all incidents associated with the node or interface. Click the  Open icon in the row representing the incident that you want to examine. See ["Incident Form" \(on page 132\)](#)

Related Topics:

[Using Views to Display Data](#)

[Working with Objects](#)

[Use Table Views](#)

Monitoring Incidents for Problems

Tip: See "[Incident Form](#)" (on page 132) for more details about the Incident attributes that appear in an incident's view column headings.

NNMi actively notifies you when an important event occurs. The event is reflected by a change of background color of a node in a network map and is reported through incident views.

Many services (background processes) within NNMi gather information and generate NNMi incidents. In addition, an SNMP agent might send information to NNMi. For example, an SNMP agent detects that a managed critical server is overheating and about to fail. The SNMP agent forwards a trap to NNMi.








Incidents might also be reporting on information that was requested by NNMi. For example, NNMi might generate an "Address Not Responding" incident after using ICMP to check whether communication channels are open to a device (using ping).

For most incident views displayed, you can identify its overall severity (**Normal**, **Warning**, **Minor**, **Major**, **Critical**, and **Unknown**), lifecycle state, source node, source object, and its message.

Note: Some incidents may have a value of **<none>** for the source object or source node. This happens when the source node or object cannot be resolved. For example, an incident that is being forwarded from an NNM 6.x or 7.x management station has a source node value of **<none>**. An SNMP trap whose source is not monitored can be displayed as **<none>**.

The following table describes the severity icons used by NNMi.

Incident Severity Icons

Icon	Meaning	Icon	Meaning	Icon	Meaning	Icon	Meaning
	Normal		Minor		Critical		Disabled
	Warning		Major		Unknown		No Status

Note: NNMi provides management mode attributes that determine whether a node, interface, or address is discovered and monitored. Your administrator is able to set some of these management mode attribute values. Any object whose management mode is set so that it is no longer discovered and monitored might still have incidents associated with it that existed before the object was no longer managed. To check whether a node associated with an incident is being managed, open the form for the incident and then open the form for the source node associated with the incident. See [Working with Objects](#) for more information.

Incident views are useful for quickly identifying items described in the following table.

Incident View Uses

Use	Description
Identify potential or current problems	Within a view, each incident has a corresponding icon that indicates its severity so that you are immediately notified of potential or current problems. You can filter incidents so that you only view incidents whose severity is Critical or you can choose to filter incidents to view all incidents whose severity is greater than Normal.
Identify problem nodes	You can sort incidents by node to help you quickly identify the problem nodes.

Determine the cause of the problem	<p>You can sort an incident view by description so that you are able to see all incidents reporting a node or interface that is disabled or otherwise unavailable.</p> <p>You can also use the child incidents attribute to view all of the incidents that are a result of the root cause problem reported.</p>
Determine historical information	<p>You can sort your incidents by notification date to determine whether a group of nodes went down within a specified time frame.</p> <p>You can also filter your list of incidents according to notification date to view only those incidents received within the last hour.</p> <p>To track historical information for a specific node, sort your incidents by First Occurrence. Then, filter your view by node Name. This lets you view a chronological list of the kinds of errors (indicated by Origin) that have occurred for the current node.</p> <p>You can then open the Incident form to use the child incidents attribute to view all of the incidents that are a result of the root cause problem reported.</p>
Identify only the incidents important to you	<p>You can filter an incident view so that you see only those incidents of interest. For example, you might filter incidents so that you only view incidents whose status is Critical or only those incidents assigned to you. You can also view only those incident associated with a Node Group. Your NNMi administrator creates node groups. For example, your NNMi administrator might choose to group all of your important Cisco routers into a node group. See Node/ Interface Group Filters for more information.</p>

Your NNMi administrator can define the format of incident messages so they are most useful to you and your team.

Your team can use the Notes attribute of the incident views to notify everyone else about which issues are being covered.

Tasks Performed from an Incident View

You can perform the following tasks from an incident view:

["Organize Your Incidents" \(on page 131\)](#)

["Own an Incident" \(on page 142\)](#)

["Assign an Incident" \(on page 143\)](#)

["Unassign an Incident" \(on page 143\)](#)

["Keep Your Incidents Up to Date" \(on page 144\)](#)

["Track an Incident's Progress" \(on page 145\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

Related Topics:

["Incident Views Provided by NNMi" \(on page 147\)](#)

Organize Your Incidents

You can organize your incidents in one of three ways:

1. Sort them according to the column of interest. For example, you might want to sort your incidents by status.

2. Filter them according to the values for a particular column or attribute. For example, filtering by status lets you filter out the status values that are not of interest to you. Filtering by the **Assigned To** attribute lets you view only the incidents assigned to you.
3. Filter them according to a Node Group. Your network administrator is able to group sets of nodes into Node Groups. An example Node Group could be all important Cisco routers, or all routers in a particular building. See [Node/Interface Group Filters](#) for more information about filtering a view by Node Group.

Note: See the help topic for each incident view for more details about how you might want to sort or filter a specific incident view.

For information about sorting and filtering, see [Use Table Views](#).






Incident Form
















The Incident form provides details for troubleshooting purposes. From this form you can access more details about the [node](#) involved, and the [Source Object](#) attribute provides more information about the interface, IP Address, connection, or SNMP Agent that is contributing to the problem.

If your role allows, you can use this form to update the [priority](#) and [state](#) of the incident, [assign](#) a team member to investigate the problem, or add [notes](#) to communicate solutions or workaround information.

For information about each tab:

Basic Attributes

Attribute	Description
Message	A description of the problem that you want NNMi to display.
Severity	Seriousness that NNMi calculates for the incident. Possible values are: <ul style="list-style-type: none"> Normal Warning Minor Major Critical See About Status Colors for more information about severity values. Note: The icons are displayed only in table views.

Attribute	Description
Priority	<p>Used to communicate the urgency of resolving the selected incident. You control this value. NNMi sets this value to null by default. The lower the number the higher the priority. Possible values are:</p> <ul style="list-style-type: none"> 5  None 4  Low 3  Medium 2  High 1  Top <p>Note: The icons are displayed only in table views.</p>
Lifecycle State	<p>Identifies where the incident is in the incident lifecycle. You control this value.</p> <ul style="list-style-type: none">  Registered – Indicates that an incident arrived in the queue and is stored in the database.  In Progress – State selected to indicate the incident is being addressed.  Completed – State selected to indicate completion of the incident investigation, and implementation of a solution.  Closed – Indicates that NNMi confirmed that the problem reported by this Incident is no longer a problem. For example, when you remove an interface from a device, all incidents related to the interface are automatically Closed. <p>See "About the Incident Lifecycle" (on page 144) for more information about Lifecycle State.</p> <p>Note: The icons are displayed only in table views.</p>
Source Node	<p>Name assigned to the node associated with the incident. Click the  Lookup icon and select  Quick View or  Open to display more information about the node. See "Node Form" (on page 27) for more information.</p> <p>Note: If NNMi is unable to resolve the node, the source node value is <none>. For example, an incident that NNMi receives from a 6.x or 7.x management station, does not have a source node value.</p>
Source Object	<p>Name used to indicate the configuration item that is malfunctioning on the source node. Click the  Lookup icon and select  Quick View or  Open to display more information about the interface, IP address, connection, or SNMP agent.</p> <p>Note: All incidents forwarded to NNMi by a 6.x or 7.x NNM management station have a Source Object value of none.</p>
Assigned To	<p>Name of the user to which this incident is assigned. This value must be a valid user account name (determined by the NNMi administrator). See "Manage Incident Assignments" (on page 142) for more information.</p>








Attribute	Description
Notes	<p>Provided for communication among your team (for example, explanations or workarounds). Information might include reasons why the status was changed, what has been done to troubleshoot the problem, or who worked on resolving the incident.</p> <p>Type a maximum of 255 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.</p> <p>Note: You can sort your incident table views based on this value. Therefore, you might want to include keywords for this attribute value.</p>

Incident Form: General Tab











The "[Incident Form](#)" (on page 132) provides details for troubleshooting purposes.

For information about each tab:

General Attributes

Attribute	Description
Name	Name of the rule used to configure the incident. This name is initially created by NNMi.
Category	<p>Generated by NNMi to indicate the problem category. Possible values include:</p> <ul style="list-style-type: none">  Accounting - Used to indicate problems related to usage statistics and allocation of costs associated with the billing of time and services provided by devices. This category is not used by NNMi with default configurations, but it is available for incidents you define.  Application Status - Indicates there is a problem with the health of the NNMi software. Examples of these kinds of events include license expiration or that a certain NNMi process lost connection to the Process Status Manager.  Configuration Indicates there is a problem with the configuration of a managed device; for example there is a physical address mismatch  Fault – Indicates a problem with the network, for example Node Down  Performance – Indicates a threshold has been exceeded; for example a utility has exceeded 90 percent  Security – Indicates there is a problem related to authentication; for example an SNMP authentication failure  Status - Often indicates some status change has occurred on a device. For example, when a Cisco device is powered up or powered down. <p>Note: The icons are displayed only in table views.</p>

Attribute	Description
Origin Occurrence Time	The time at which an event occurred that caused the incident to be created.; for example, the time held in the trap.

Attribute	Description
Origin	<p>Identifies how the incident was generated. Possible values are:</p> <ul style="list-style-type: none">  Management Software – Indicates the incident was generated by NNMi processes  Manually Created – Indicates the incident was created from the user interface.  Remotely Generated – Indicates the incident was forwarded from an NNM 6.x or 7.x management station  SNMP Trap – Indicates the incident was forwarded from an SNMP Agent  Syslog – Indicates the information was gathered from a syslog Agent. This Origin is not used by NNMi. <p>Note: The icons are displayed only in table views.</p>
Correlation Nature	<p>This incident's contribution to a root-cause calculation, if any. Possible values are:</p> <ul style="list-style-type: none">  Root Cause – Indicates the incident is a root cause of the reported problem. For example, node down is a root cause problem.  Secondary Root Cause – Indicates the incident is related to root cause, but is not the primary problem. Secondary root cause incidents often begin as primary root cause incidents. For example, when an interface goes down, it becomes a primary root cause incident. If a connection associated with the interface goes down, the connection down becomes the root cause, and the interface down becomes a Secondary Root Cause.  Symptom – Indicates any incidents that were generated from a trap notification related to the root cause incident. For example, a Link Down incident generated from a Link Down trap notification might appear as a Symptom to an Interface Down incident in the root cause incidents view.  Stream Correlation – Stream correlations are created as NNMi analyzes events and traps to determine the root cause incident for a problem. Examples of stream correlations include Dedup (duplication of events) Rate (occurrence of events by time), and Pairwise (occurrence of events using incident pairs) correlations.  Service Impact - Indicates a relationship between incidents in which a network service is effected by other incidents. For example, an Interface Down incident can effect a Router Redundancy Group that is part of an HSRP service. This Correlation Nature is available for use by NNM iSPIs (HP Smart Plug-ins). See "Help for Administrators" for more information about HP Smart Plug-ins. <p>Note: The icons are displayed only in table views.</p>

Attribute	Description
Duplicate Count	<p data-bbox="354 281 1341 428">Lists the number of duplicate incidents that NNMi encountered for the selected incident. This number is incremented only in the associated deduplication incident that is generated by NNMi. Deduplication incidents are generated by NNMi to inform the operator of incidents needing attention because they are reoccurring according to the deduplication criteria specified in the incident's deduplication configuration.</p> <p data-bbox="354 449 1341 596">For example, incidents generated from SNMP traps will not have their deduplication count incremented. If the deduplication criteria was configured for the SNMP trap, NNMi generates a deduplication incident specifying that the SNMP trap is reoccurring according to the deduplication criteria specified in the incident's associated deduplication configuration. This incident is the one that increments and displays the Duplicate Count value.</p> <p data-bbox="354 617 558 642">Note the following:</p> <ul data-bbox="370 663 1341 1020" style="list-style-type: none"><li data-bbox="370 663 1341 726">● By default, NNMi updates the Duplicate Count every 30 seconds. This interval cannot be changed.<li data-bbox="370 737 1341 936">● NNMi continues to update the duplicate count regardless of an incident's lifecycle state. For example, if an incident's Lifecycle State is set to Closed, the duplicate count continues to be incremented. See "About the Incident Lifecycle" (on page 144) for more information. This behavior helps you identify situations in which the incident is not yet fixed. Take note if the Duplicate Count is incremented after a lengthy time period has elapsed; this might indicate there is a new problem with the node, interface, or address.<li data-bbox="370 957 1341 1020">● Duplicates are configured by the NNMi administrator using the Incident Configuration form available from the Configuration workspace.
RCA Active	<p data-bbox="354 1041 1341 1125">Used by NNMi to identify whether NNMi considers the incident to be active or inactive. If set to True, the incident is considered to be active. If set to False, the incident is considered to be inactive.</p> <p data-bbox="354 1146 1341 1209">NNMi considers an incident to be active when the root cause analysis (RCA) engine is actively evaluating the problem reported by this incident.</p> <p data-bbox="354 1230 1341 1314">NNMi considers an incident to be inactive when NNMi confirmed that the problem reported by this incident is no longer a problem. For example, the device is now functioning properly.</p> <p data-bbox="354 1335 1341 1419">NNMi initially sets an incident's RCA Active attribute to True and the Lifecycle State to Registered. When NNMi sets the RCA Active attribute to False, it also sets the incident's Lifecycle State to Closed.</p> <p data-bbox="354 1440 1179 1465">Examples of when an incident's RCA Active attribute is set to False include:</p> <ul data-bbox="370 1486 1341 1566" style="list-style-type: none"><li data-bbox="370 1486 1341 1512">● When an interface goes up, NNMi closes the InterfaceDown incident.<li data-bbox="370 1522 1341 1566">● When a node goes up, NNMi closes the NodeDown incident.
Correlation Notes	<p data-bbox="354 1587 1341 1852">Stores notes about the correlation status of the incident. NNMi provides information in the Correlation Notes field when it sets an incident's Lifecycle State to Closed. This information includes the reason the incident was closed; for example, an Interface Up might cancel an Interface Down incident and subsequently close the Interface Down incident. For this example, Interface Up would be included in the Correlation Notes field as a reason for why the incident was closed. As another example, if a LinkUp was configured to cancel a LinkDown incident, the message generated by NNMi would be: <code>Incident autoclosed by Event System Pairwise Correlation: CiscoLinkDown, CiscoLinkUp</code>.</p>


Attribute	Description
First Occurrence Time	Used when suppressing duplicate incidents. Indicates the first notification for a set of duplicate incidents.
Last Occurrence Time	Used when suppressing duplicate incidents. Indicates the timestamp of the latest notification for a set of duplicate incidents. If there are no duplicate incidents, this date is the same as the First Occurrence Time.
Origin Occurrence Time	The time at which an event occurred that caused the incident to be created.; for example, the time held in the trap.

Incident Form: Correlated Parents Tab

The "Incident Form" (on page 132) provides details for troubleshooting purposes.

For information about each tab:

Correlated Parents Table


Attribute	Description
Correlated Parents	If the current incident is a child incident, any correlated parent incidents of the child appears in this table view. For example, parent incidents are created when a root cause problem is detected. A Node Down root cause incident is a parent of an Interface Down incident. Therefore, on an Interface Down Incident form, a Node Down incident might appear under the Correlated Parents tab. Click the  Open icon to view more information about a specific incident.

Incident Form: Correlated Children Tab

The "Incident Form" (on page 132) provides details for troubleshooting purposes.

For information about each tab:

Correlated Children Table


Attribute	Description
Correlated Children	If the current incident is a parent incident, any correlated child incident of the parent appears in this table view. For example, an Interface Down incident would be correlated as a child under a Node Down root cause incident. Therefore, on a Node Down incident form, an Interface Down incident would appear on the Correlated Children tab. Click the  Open icon to view more information about a specific incident.

Incident Form: Custom Attributes Tab

The "Incident Form" (on page 132) provides details for troubleshooting purposes.

For information about each tab:



Custom Attributes Table

Attribute	Description
Custom Incident Attributes	<p>Used by NNMi to add additional information to the incident that NNMi makes available for viewing. Each CIA includes a name, type, and value group that can be populated differently for different types of incidents. Varbind values that accompany SNMP traps are a common use for this attribute.</p> <p>Click the  Open icon to open the "Custom Incident Attribute Form" (on page 139) and view more information about a specific attribute.</p>

Custom Incident Attribute Form

The Custom Incident Attributes (CIAs) form provides extended information that NNMi gathered about the incident. For example, if the incident is reporting an SNMP trap, the Varbind values are stored as CIAs. Each CIA includes a name, type, and value group that can be populated differently for different types of incidents.

To view custom incident attribute information:

1. Navigate to the **Incident** form.
 - a. From the workspace navigation panel, select the **Incidents** workspace.
 - b. Select the incident view that contains the incident of interest; for example, **Root Cause Incidents**.
 - c. To open the Incident form, click the  Open icon that precedes the incident whose information you want to view.
2. In the **Incident** form, select the **Custom Attributes** tab.
3. Click the  Open icon that precedes the custom incident attribute row of interest.

See the table below for an explanation of the Name, Type, and Value attributes displayed.

Note: All varbind values are stored as CIAs in NNMi.

Custom Incident Attributes

Attribute	Description
Name	<p>Name used to identify the CIA.</p> <p>For SNMP traps and events forwarded from NNM 6.x or 7.x management stations, the name is the object identifier (oid) of the forwarded trap or event.</p> <p>Note: If different varbinds have the same oid, NNMi appends a number to the original oid; for example: 1.2.3.4.5.6.2.7.1_1 and 1.2.3.4.5.6.2.7.1_2</p>
Type	<p>Describes the type of data that is stored for the CIA. Examples of types include:</p> <p>Double - Used to describe real numbers; for example 12.3</p> <p>Integer - Used for integer numeric values; for example 1, 2, or 3</p> <p>String - Used for character values</p> <p>Boolean - Used to store true or false values</p> <p>Note: All SNMP trap and NNM 6.x or 7.x management station events types begin with asn. If the CIA represents a varbind value, you may view additional types, such as Counter.</p>

Attribute	Description
Value	For SNMP traps and events forwarded from an NNM 6.x or 7.x management station, the CIA value is the varbind value in the forwarded event or trap. For management events that are generated from NNMi, this value is the CIA value in the incident that was provided by NNMi.

Incident Form: Diagnostics Tab (NNM iSPI NET)

The "[Incident Form](#)" (on page 132) provides details for troubleshooting purposes.

When you access the Incident Form: Diagnostics Tab, you can view the history of all the NNM iSPI NET Diagnostic reports that have been run for the incident's Source Node. Diagnostics are sets of automated commands specific to one or more device types, including Cisco routers and switches, Cisco switch/routers, and Nortel switches.

To generate a new instance of these Diagnostics reports, click **Actions** → **Run Diagnostics**.

For information about each tab:

Diagnostics Table

Attribute	Description
Start Time	Date and time NNM iSPI NET created this instance of the Diagnostics report. NNM iSPI NET uses the locale of the client and the date and time from the NNMi management server.
Definition	The name of the NNM iSPI NET Diagnostics report definition.
Status	The current status of this NNM iSPI NET Diagnostics report, such as <i>Running</i> or <i>Complete</i> .
Report	Click this link to open the actual report. Note: You might be prompted to provide a user name and password to access the Operations Orchestration software. See the <i>iSPI NET Planning and Installation Guide</i> for more information.
Lifecycle State	The Diagnostic runs if the incident is currently set to this Lifecycle State.
Last Update Time	Date and time NNM iSPI NET last updated this instance of the Diagnostics report. NNM iSPI NET uses the locale of the client and the date and time from the NNMi management server.

Incident Diagnostic Results Form (Flow Run Result) (NNM iSPI NET)

NNM iSPI NET automatically prepares diagnostic reports when certain incidents are generated and when using **Actions** → **Run Diagnostics**. This form shows details about the currently selected diagnostic report instance.

Note: Because the values on this form are generated by NNM iSPI NET, these attribute values cannot be modified.

See "[Incident Form: Diagnostics Tab \(NNM iSPI NET\)](#)" (on page 140) for more information:

Diagnostic Results Details

Attribute	Description
Start Time	The time that NNM iSPI NET created the selected diagnostic report instance.
Definition	The name of the flow as defined in NNM iSPI NET.
Status	<p>The current status of this NNM iSPI NET Diagnostics report. Possible values include:</p> <p>New - The Diagnostic is in the queue, but is not yet running</p> <p>In Progress -The Diagnostic has been submitted and is not finished running</p> <p>Completed - The Diagnostic has finished running</p> <p>Not Submitted - An error condition prevented the Diagnostic from being submitted</p> <p>Timed Out - NNMi was unable to submit or run the Diagnostic due to a time out error. The time out limit for submitting a Diagnostic is one hour. The time out limit for running a Diagnostic is four hours.</p> <p>Example error conditions include the following:</p> <ul style="list-style-type: none">• The number of Diagnostics in the queue might prevent NNMI from submitting the Diagnostic.• A configuration error, such as an incorrect user name or password, might prevent NNMI from accessing the required Operations Orchestration server. <p>Contact your NNMi administrator for Diagnostic log file information.</p>
Report	NNM iSPI NET uses this text string to display the selected instance of the diagnostics report in a browser window.
Lifecycle State	<p>The Diagnostic runs if the incident is currently set to this Lifecycle State.</p> <p>Possible values include:</p> <ul style="list-style-type: none">• Registered• In Progress• Completed• Closed <p>See About the Incident Lifecycle for more information about Lifecycle State.</p> <p>When the Incident is set to this Lifecycle State, the selected Diagnostics (Flow Definitions) is automatically run on each applicable Source Node in the specified Node Group.</p>
Last Update Time	Date and time NNM iSPI NET last updated this instance of the Diagnostics report. NNM iSPI NET uses the locale of the client and the date and time from the NNMi management server.

Incident Form: Registration Tab

The "[Incident Form](#)" (on page 132) provides details for troubleshooting purposes.

For information about each tab:

Registration

Attribute	Description
Created	Date and time the selected object instance was created. NNM uses the locale of the client and the date and time from the NNMi management server.
Last Modified	Date the selected object instance was last modified. NNM uses the locale of the client and the date and time from the NNMi management server.

Manage Incident Assignments

One of the first things to do with an incident is to assign it to yourself or to another operator. The following table displays the ways you can assign or un-assign an incident and the NNMi user role that is required for each.

Tasks Related to Assigning Incidents

Task	How	Required Minimum NNMi User Role
Own an incident	Select an incident and use Actions → Own Incident . See "Own an Incident" (on page 142) for more information.	Level 1 Operator
Assign an incident to someone else	Use the Incidents form and select a user in the Assigned To field. See "Assign an Incident" (on page 143) for more information.	Level 2 Operator
Un-assign an incident	Select an incident and use Actions → Unassign Incident . See "Unassign an Incident" (on page 143) for more information.	Level 1 Operator

Own an Incident

NNMi lets you own an incident. When you specify that you want to own an incident, the incident is assigned to you.

To own an incident:

- Navigate to the incident view of interest.
 - From the workspace navigation panel, select the **Incidents** workspace.
 - Select the incident view of interest; for example **Unassigned Open Key Incidents**.
- Click the selection box that precedes the incident you want to own.
- Select **Actions** → **Own Incident**.

Your user account name then appears in the **Assigned To** column of the incident view.






Note: If you are using the **Unassigned Open Key Incidents** view, the incident is deleted from the view because it is no longer unassigned. Open the **My Open Incidents** view to verify that the incident was successfully assigned to you.

As an operator you are able to view incidents assigned to yourself and to others. If you want to view only those views assigned to or owned by you, use the **My Open Incidents** view. See ["My Open Incidents View" \(on page 148\)](#) for more information.

Assign an Incident

If you are an NNMi user with a Level 2 Operator role, you can assign an incident to yourself or to another operator. If it is already assigned to another operator, you can unassign it or assign it to another operator.

To assign an incident:

1. Navigate to the incident view of interest.
 - a. From the workspace navigation panel, select the **Incidents** workspace.
 - b. Select the incident view of interest; for example **Unassigned Open Key Incidents**.
2. Click the  Open icon that precedes the incident you want to own.
3. In the **Assigned To** lookup field, do one of the following:
 - Type in the valid account user name to which you want to assign the incident.
Note: Using the auto completion feature, NNMi should complete entering the account user name for you after you enter a few characters.
 - Click the  Lookup icon and select  Quick Find to display a list of valid user account names. Then, select the account name you want to use.
4. From the main menu, click  **Save** to save your changes or  **Save and Close** to save your changes and exit the form..

The user account name you entered or selected then appears in the **Assigned To** column of the current incident view for the selected incident.

Note: If you are using the **Unassigned Open Key Incidents** view, the incident is deleted from the view because it is no longer unassigned.

Unassign an Incident





If you are an NNMi user with a user role of Level 1 Operator, you are able to unassign an incident for yourself or for another user. You can unassign an incident in one of two ways:



- Using **Actions** → **Unassign Incident**.
- Using the Assigned To lookup field

To unassign an incident using the Actions menu:

1. Navigate to the incident view of interest.
 - a. From the workspace navigation panel, select the **Incidents** workspace.
 - b. Select the incident view of interest; for example **Unassigned Open Key Incidents**.
2. Click the selection box that precedes the incident you want to own.
3. Select **Actions** → **Unassign Incident**.

To unassign an incident using the Assigned To lookup field:

1. Navigate to the incident view of interest.
 - a. From the workspace navigation panel, select the **Incidents** workspace.
 - b. Select the incident view of interest; for example **My Open Incidents**.
2. Click the  Open icon that precedes the incident you want to unassign.
3. Navigate to the **Assigned To** attribute. Click the  Lookup icon and select  **Quick Find**.
4. Click the  **Make Empty** icon.

5. From the main menu, click  **Save** to save your changes or  **Save and Close** to save your changes and exit the form.

The user account name should no longer appear in the **Assigned To** column of the incident view.

Note: The incident should appear in the **Unassigned Open Key Incidents** view.



Keep Your Incidents Up to Date

NNMi provides the **Notes** attribute to help you keep your incident information up-to-date. Use the **Notes** field to explain steps that were taken to date to troubleshoot the problem, workarounds, solutions, and ownership information.

To update an incident:

1. If you do not have an incident open, from the Workspace navigation panel, select the incident view you want to open; for example **Open Key Incidents**.
2. From the incident view, open the incident you want to update.
3. Type the annotations that you want to be displayed within the **Notes** field. Type a maximum of 255 characters. Alpha-numeric, punctuation, spaces, and underline characters are allowed.
4. If you need more space to type in your information, click the **Notes** label, and type the information into the window that appears.

Note: NNMi might add information to the **Correlation Notes** field to explain why an incident **Lifecycle State** was changed to **Closed**.

5. From the main menu, click  **Save** to save your changes or  **Save and Close** to save your changes and exit the form.

You also want to keep your incident lifecycle information up-to-date. See ["Track an Incident's Progress" \(on page 145\)](#) for more information.

About the Incident Lifecycle

NNMi provides the Lifecycle State attribute to help you track an incident's progress. See ["Track an Incident's Progress" \(on page 145\)](#) for more information about possible lifecycle states.

In some cases, NNMi updates an incident's Lifecycle State for you. For example, NNMi initially sets an incident's Lifecycle State to **Registered**. It also sets an incident's Lifecycle State to **Closed**. NNMi considers an incident to be **Closed** when NNMi has confirmed that the problem reported by this incident is no longer a problem. For example, the device is now functioning properly. Examples of when NNMi sets an incident Lifecycle State to **Closed** include:

- When an interface goes up, NNMi closes the Interface Down incident.
- When a node goes up, NNMi closes the Node Down incident.

When it sets an incident's Lifecycle State to **Closed**, NNMi adds information to the Correlation Notes field to explain why the incident was closed. In such cases, NNMi inserts the information in front of any existing information provided. For example, Interface Up would be included in the Correlation Notes field as a reason for why an Interface Down incident was closed.

Another way to help you identify those incidents closed by NNMi is by looking at the RCA Active attribute value. When NNMi considers an incident to be **Closed**, it sets the RCA Active attribute value to **False**. This means NNMi's root cause analysis (RCA) engine is no longer actively evaluating the problem reported by this incident.

Note: NNMi continues to update the duplicate count regardless of an incident's Lifecycle State. For example, if an incident's Lifecycle State is set to **Closed**, the Duplicate Count continues to be incremented. This behavior helps you identify situations in which the incident is not yet fixed. Take note if the Duplicate Count is incremented after a lengthy time period has elapsed; this might indicate there is a new problem with the node, interface, or address.

After closing a primary root cause incident, any incidents that are correlated and marked as secondary root cause become primary root cause.

Track an Incident's Progress

NNMi provides the **Lifecycle State** attribute to help you track an incident's progress. The table below describes each lifecycle category and possible values. Your network administrator might have additional or different guidelines for their use.

Incident Lifecycle States

Lifecycle State	Description
Registered	Indicates that an incident has arrived in the queue and has been stored in the database.
In Progress	State selected by a user to indicate the incident is being addressed.
Completed	State selected by the user to indicate the incident investigation is complete and a solution has been implemented.
Closed	Indicates that NNMi confirmed that the problem reported by this incident is no longer a problem. For example, when you remove an interface from a device all incidents related to the interface are automatically Closed.

You should know your guidelines for lifecycle states so that you can keep your incidents updated accordingly.


To update your lifecycle state, use the **Actions** menu or a form.

To update your lifecycle state using the Actions menu from a view:

1. If you do not have an incident open, from the workspace navigation panel, select the incident view you want to open.
2. From the incident view, click the selection box that precedes the incident whose lifecycle state you want to change.
3. From the main menu toolbar, select **Actions** and then the lifecycle state you want, for example, **In Progress**.

To update your lifecycle state from a form:

1. If you do not have an incident open, from the workspace navigation panel, select the incident view you want to open.
2. From the incident view, open the incident you want to update.
Under the **Basics** pane, select the lifecycle state you want from the drop-down menu.

From the main menu, click **Save** to save your changes or  **Save and Close** to save your changes and exit the form.

From the form menu, select **Actions** and then the lifecycle state you want. For example, select **Completed**.

The action takes effect immediately. This means you do not have to select **Save**.

After performing an action on a form that modifies the object being viewed, you must refresh the form before you can save any additional changes.

Display a Map from an Incident

If you are using incident views to monitor your network, there are times when you might want to switch to a map view to determine more information. For example, you might want to view the connectivity for a selected node.

To display a map from an incident:

1. Select the incident of interest by checking the selection box that precedes the object information.
2. Select **Actions** → **Node Group Map** in the main toolbar.

Note the following:

- This action displays the lowest level Node Group map to which the Source Node belongs. For example, if the node belongs to a Child Node Group, the Child Node Group displays.
- If the Source Node is a member of more than one Node Group at the lowest level, NNMi prompts you to select the Node Group map you want to display.
- If you select **Node Group Map** and the Source Node is not a member of a Node Group, NNMi informs you that no Node Group map is available.

The map launches based on the source node of the selected incident.

Note: If the incident is associated with an Island Node Group, NNMi displays the associated Island Node Group map. See ["Island Node Group Map" \(on page 146\)](#) for more information.

Note: The current values of the management mode attributes determine whether NNMi discovers and monitors a node, interface, or address. Your NNMi administrator sets some of these management mode attribute values. Map symbols with the color set to **No Status** are not currently being monitored.

Related Topics:

[Use Map Views](#)

["Display the Layer 2 Neighbor View" \(on page 103\)](#)

["Display the Layer 3 Neighbor View" \(on page 110\)](#)

["Path Between Two Nodes that Have IPv4 Addresses" \(on page 113\)](#)

["Node Group Overview Map" \(on page 100\)](#)

["Routers Map" \(on page 102\)](#)

["Switches Map" \(on page 102\)](#)

["Networking Infrastructure Devices Map" \(on page 101\)](#)

Island Node Group Map

An Island Node Group is a group of connected nodes that NNMi discovers and that are not connected to the rest of the topology. An example of an environment with multiple Island Node Groups is a financial institution or retail store with many branches or stores. Each branch or store might be connected to other

branches or stores with a WAN (Wide Area Network) connection. Each branch or store appears as an isolated island of nodes in the NNMi topology.

The Island Node Group map contains the Island Node Group that is the Source Object for the selected incident.

Note: Incidents whose Source Object is an Island Node Group include **Remote site** in the incident message.

To display an Island Node Groups Map from an incident:

1. Select an incident view from the **Incident Management** or **Incident Browsing** workspace.
2. Check the selection box () that precedes the Island Node Group incident whose map you want to display.
3. Select **Actions** → **Node Group Map**.

Related Topics

[Node Group Map Objects](#)

Incident Views Provided by NNMi

You and your team can easily monitor the posted incidents and take appropriate action to preserve the health of your network. To assist you, NNMi provides the following out-of-the-box views for listing incident information:

- ["My Open Incidents View" \(on page 148\)](#)
- ["Open Key Incidents View" \(on page 149\)](#)
- ["Unassigned Open Key Incidents View" \(on page 151\)](#)
- ["Open Key Incidents by Severity View" \(on page 151\)](#)
- ["Open Key Incidents by Priority View" \(on page 152\)](#)
- ["Open Key Incidents by Category View" \(on page 154\)](#)
- ["Open Key Incidents by Family View" \(on page 155\)](#)
- ["Closed Key Incidents View" \(on page 156\)](#)
- ["Key Incidents by Lifecycle State View" \(on page 157\)](#)
- ["Root Cause Incidents View" \(on page 159\)](#)
- ["Stream Correlation Incidents View" \(on page 160\)](#)
- ["Custom Incidents View" \(on page 161\)](#)
- ["NNM 6.x/7.x Events View" \(on page 162\)](#)
- ["NNM 6.x/7.x Events by Category View" \(on page 162\)](#)
- ["SNMP Traps View" \(on page 162\)](#)
- ["SNMP Traps by Family View" \(on page 163\)](#)

The most useful view for proactively monitoring your network for problems are the **Key Incident** views. These views include root cause incidents generated for the devices being managed by NNMi, along with their associated symptoms.

NNMi's Causal Engine uses ICMP and SNMP to constantly monitor your network. The Causal Engine uses the data collected from all the devices on your network to determine the root cause of known and potential problems.

Note: The **Custom Incidents** view lets you use sorting and filtering to customize additional views while maintaining the out-of-the-box views provided by NNMi. This view includes most of the attributes available for the incident so that you can decide which are most important for you to display. See [Use Table Views](#) for more information about sorting, filtering, and hiding attributes within a view.

For each incident generated, you can view the **Correlated Parents** and **Correlated Children** tab information to assist you in understanding how the problem was detected.

NNMi also enables you to access the following 6.x/7.x features by selecting only incidents generated from 6.x/7.x events: (See for more information.) You cannot access these features for any non-6.x/7.x incidents.

- Actions → NNM 6.x/7.x Neighbor View
- Actions → NNM 6.x/7.x Details
- Actions → NNM 6.x/7.x ovw

Other useful tasks from the incident view, include the following:

- ["Display a Map from an Incident" \(on page 146\)](#)
- ["Node Form" \(on page 27\)](#)

Related Topics:

[Accessing Groups of Views \(Workspaces\)](#)

[About the NNMi Console](#)

My Open Incidents View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings.

The **My Open Incidents** view displays all of the open incidents that have been assigned to you. This view is useful for identifying the incidents for which you are responsible. It displays all incidents assigned to you whose lifecycle state is **Registered**, **In Progress**, or **Completed**. As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the open incidents assigned to you that have occurred within the last week.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Completed**), the date and time the incident last occurred, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, Management Software or SNMP Trap), its Correlation Nature (for example, **Symptom** or **Root Cause**), the message used to describe the incident, and any related notes.

See ["Monitoring Incidents for Problems" \(on page 130\)](#) for more information about ways to use incident views.

Key Incident Views

Tip: See ["IP Address Form" \(on page 72\)](#) ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in a root cause incident view's column headings.

The Key Incident views are useful for identifying incidents that are most important to the network Operator and that often require more immediate action. The Key Incidents views includes those incidents whose Correlation Nature is any of the following:

Incident Correlation Nature	Description
None	Indicates there is no incident correlation for this incident. For example, a Correlation Nature of None is used for license violations.
Root Cause	Indicates the incident that reports the root cause of a problem.
Service Impact	Indicates a relationship between incidents in which a network service is effected by other incidents. By default, NNMi generates Service Impact incidents for Router Redundancy Groups. For example, an Interface Down incident can effect a Router Redundancy Group that is part of an HSRP service. The Service Impact incident helps to identify the service that is affected. This Correlation Nature is available for use by NNM iSPIs (HP Smart Plug-ins). See "Help for Administrators" for more information about HP Smart Plug-ins.

Some Key Incident views are filtered according to lifecycle state values, which can be set by the user. For example, the **Open Key Incidents** view displays the Key Incidents whose lifecycle state value is **Registered**, **In Progress**, or **Completed**. The **Closed Key Incidents** view displays only the Key Incidents whose lifecycle state value is **Closed**. NNMi also provides an **Unassigned Open Key Incidents** view that is filtered using the **Lifecycle State** values of **Registered**, **In Progress**, and **Completed** as well as the **Assigned To** attribute

NNMi provides the following Key Incident views:

- ["Open Key Incidents View" \(on page 149\)](#)
- ["Unassigned Open Key Incidents View" \(on page 151\)](#)
- ["Open Key Incidents by Severity View" \(on page 151\)](#)
- ["Open Key Incidents by Priority View" \(on page 152\)](#)
- ["Open Key Incidents by Category View" \(on page 154\)](#)
- ["Open Key Incidents by Family View" \(on page 155\)](#)
- ["Closed Key Incidents View" \(on page 156\)](#)
- ["Key Incidents by Lifecycle State View" \(on page 157\)](#)

Related Topics

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

Open Key Incidents View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings.

The **Open Key Incidents** view shows the incidents that are most important to network Operators and that often require more immediate action. This view displays the Key Incidents whose lifecycle state value indicates that the incident has not yet been closed. This view is useful for identifying the Key Incidents that need to be resolved. As with all incident views, you can filter this view by time period. The default time

period is **Last Week** so that you can view all of the Key Incidents that have remained open within the last week.

This view includes those incidents whose Correlation Nature is any of the following:

Incident Correlation Nature	Description
None	Indicates there is no incident correlation for this incident. For example, a Correlation Nature of None is used for license violations.
Root Cause	Indicates the incident that reports the root cause of a problem.
Service Impact	Indicates a relationship between incidents in which a network service is effected by other incidents. By default, NNMi generates Service Impact incidents for Router Redundancy Groups. For example, an Interface Down incident can effect a Router Redundancy Group that is part of an HSRP service. The Service Impact incident helps to identify the service that is affected. This Correlation Nature is available for use by NNM iSPIs (HP Smart Plug-ins). See "Help for Administrators" for more information about HP Smart Plug-ins.
Stream Correlation	Indicates the correlations that NNMi's event pipeline establishes as it recognizes patterns in the flow of events through the pipeline. Correlations are created as NNMi analyzes events and traps to determine the root cause incident for a problem. Examples of stream correlations include Dedup (duplication of events) and Rate (occurrence of events by time) correlations.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, the name of the person to which the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), its **Correlation Nature** (for example, **Root Cause**), the message used to describe the incident, and any related notes.

See "[Monitoring Incidents for Problems](#)" (on page 130) for more information about ways to use incident views.

You can also access additional views from this one using the Actions menu as described in [Use Table Views](#). One example of an action available from an open root cause incident view is the ability to access a map view of the node(s) related to the incident.

Related Topics

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Open Key Incidents by Severity View" \(on page 151\)](#)

["Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Category View" \(on page 154\)](#)

["Open Key Incidents by Family View" \(on page 155\)](#)

["Closed Key Incidents View" \(on page 156\)](#)

["Key Incidents by Lifecycle State View" \(on page 157\)](#)

Unassigned Open Key Incidents View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings.

The **Unassigned Open Key Incident** view displays all of the open unassigned Key Incidents. This view is useful for identifying the Key Incidents that are open and must still be assigned to someone. As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the incidents that have remained unassigned with the last day.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress**), the date and time the incident last occurred, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), its Correlation Nature (for example, **Root Cause**), the message used to describe the incident, and any related notes.

See ["Monitoring Incidents for Problems" \(on page 130\)](#) for more information about ways to use incident views.

Related Topics

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Open Key Incidents View" \(on page 149\)](#)

["Open Key Incidents by Severity View" \(on page 151\)](#)

["Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Category View" \(on page 154\)](#)

["Open Key Incidents by Family View" \(on page 155\)](#)

["Closed Key Incidents View" \(on page 156\)](#)

["Key Incidents by Lifecycle State View" \(on page 157\)](#)


Open Key Incidents by Severity View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings

The Open Key Incidents by Severity view lets you filter your view by the Severity value. Possible Severity values include:

- Normal
- Warning
- Minor
- Major
- Critical

Note: By default, NNMi uses the first value in the Quick Filter filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



If your NNMi administrator set up Node Groups or Interface Groups to identify important elements of your environment, you can filter this view to show only the incidents that need your immediate attention. For example, by using the severity and node group filters, you can display all incidents that have a Severity value of **Critical** and are related to a certain group of nodes.

As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the open incidents of a specified severity that have occurred within the last week.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each incident displayed, you can view its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), its Correlation Nature (for example, **Root Cause**), the message used to describe the incident, and any related notes.

Related Topics

["Key Incident Views" \(on page 148\)](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Open Key Incidents View" \(on page 149\)](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Category View" \(on page 154\)](#)

["Open Key Incidents by Family View" \(on page 155\)](#)

["Closed Key Incidents View" \(on page 156\)](#)

["Key Incidents by Lifecycle State View" \(on page 157\)](#)


Open Key Incidents by Priority View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The **Open Key Incidents by Priority** view lets you filter your view by the Priority value. Possible Priority values include:

- None
- Low
- Medium
- High
- Top

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



If your NNMi administrator set up Node Groups or Interface Groups to identify important elements of your environment, you can filter this view to show only the incidents that need your immediate attention. For example, by using the priority and Node Group filters, you can display all incidents that have a **High** or **Top** priority and are related to a certain group of nodes.

As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the open incidents of a specified priority that have occurred within the last week.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each incident displayed, you can view its severity, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), its Correlation Nature (for example, **Root Cause**), the message used to describe the incident, and any related notes.

Related Topics

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Open Key Incidents View"](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Open Key Incidents by Severity View" \(on page 151\)"Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Category View" \(on page 154\)](#)

["Open Key Incidents by Family View" \(on page 155\)](#)

["Closed Key Incidents View" \(on page 156\)](#)

["Key Incidents by Lifecycle State View" \(on page 157\)](#)


Open Key Incidents by Category View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings

The **Open Key Incidents by Category** view lets you filter your view by the Category value. Possible Category values include:

- Accounting
- Application Status
- Fault
- Performance
- Security
- Status

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



You can use this view to help you determine the types of incidents that are in the queue. For example, you might want to look at only incidents related to faults or to performance to help guide you in making troubleshooting decisions.

As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the open incidents by a specified category that have occurred within the last week.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), the message used to describe the incident, and any related notes.

Related Topics

["Key Incident Views" \(on page 148\)](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Open Key Incidents View" \(on page 149\)](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Open Key Incidents by Severity View" \(on page 151\)"Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Family View" \(on page 155\)](#)

["Closed Key Incidents View" \(on page 156\)](#)

["Key Incidents by Lifecycle State View" \(on page 157\)](#)


Open Key Incidents by Family View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings

The **Open Key Incidents by Family** view lets you filter your view by the Family value. Possible Family values include:

- Address
- Aggregated Ports
- BGP
- Board
- Chassis
- Component Health
- Connection
- Correlation
- HSRP
- Interface
- License
- Node
- OSPF
- RAMS
- RMON
- RRP
- STP
- Syslog
- Trap Analysis
- VLAN
- VRRP

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



You can use this view to help you determine the types of incidents that are in the queue. For example, you might want to look at only incidents related to addresses or interfaces to help guide you in making troubleshooting decisions.

As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the open incidents of a specified Family that have occurred within the last week.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its origin (for example, **Management Software** or **SNMP Trap**), the message used to describe the incident, and any related notes.

Related Topics

["Key Incident Views" \(on page 148\)](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Open Key Incidents View"](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Open Key Incidents by Severity View" \(on page 151\)](#)

["Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Category View" \(on page 154\)](#)["Open Key Incidents by Family View" \(on page 155\)](#)

["Closed Key Incidents View" \(on page 156\)](#)

["Key Incidents by Lifecycle State View" \(on page 157\)](#)

Closed Key Incidents View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings.

The **Closed Key Incidents** view displays the Key Incidents whose lifecycle state indicates that the incident has been closed. This view is useful for identifying the Key Incidents that have been resolved. This view might be particularly useful for reporting on how many incidents were closed within a given time period.

As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the incidents that have been closed within the last 24 hours. To select a more specific time range within a time period, you can filter the view using Last Occurrence Time values.

For each incident displayed, you can view its severity, the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), the message used to describe the incident, and any related notes.

See ["Monitoring Incidents for Problems" \(on page 130\)](#) for more information about ways to use incident views.

Related Topics:

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Open Key Incidents View" \(on page 149\)](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Open Key Incidents by Severity View" \(on page 151\)](#)

["Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Category View" \(on page 154\)](#)

["Open Key Incidents by Family View" \(on page 155\)](#)

["Key Incidents by Lifecycle State View" \(on page 157\)](#)


Key Incidents by Lifecycle State View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings

The **Key Incidents by Lifecycle State** view lets you filter your view by the Lifecycle State value. Possible Lifecycle State values include:

- Registered
- In Progress
- Completed
- Closed

Note: By default, NNMi uses the first value in the Quick Filter list. If your view is empty, change the filter value. Here is an example of a Quick Filter list:



Filter this view by the **Registered** Lifecycle State to view all new incidents. If your NNMi administrator set up Node Groups or Interface Groups to identify important elements of your environment, you can filter this view using the lifecycle state and Node Group filters. For example, you can display all of the incidents that are **In Progress** and are related to a certain group of nodes.

As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the incidents of a specified lifecycle stat that have occurred within the last week.

Note: If you filter your view using multiple filters, NNMi uses the AND operator to combine the filters you have selected. See [Filter a Table View](#) for more information.

For each incident displayed, you can view its severity, its priority, the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Address** or **Connection**), its origin (for example, **Management Software** or **SNMP trap**), the message used to describe the incident, and any related notes.

Related Topics

["Key Incident Views" \(on page 148\)](#)

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Key Incident Views" \(on page 148\)](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Open Key Incidents View" \(on page 149\)](#)

["Open Key Incidents by Severity View" \(on page 151\)](#)

["Open Key Incidents by Priority View" \(on page 152\)](#)

["Open Key Incidents by Category View" \(on page 154\)](#)

["Open Key Incidents by Family View" \(on page 155\)](#)

["Closed Key Incidents View" \(on page 156\)](#)["Key Incidents by Lifecycle State View" \(on page 157\)](#)

Root Cause Incidents

Tip: See ["IP Address Form" \(on page 72\)](#)["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in a root cause incident view's column headings.

Root Cause Incidents identify the root cause determined by NNMi's Causal Engine, along with their associated symptoms.

The Causal Engine uses ICMP and SNMP to constantly monitor your network. NNMi's Causal Engine uses the data collected from all the devices on your network to determine the root cause of known and potential problems. NNMi notifies you if it encounters any of the following situations:

- ["Node Down" \(on page 178\)](#)
- ["Node Down" \(on page 178\)](#)
- ["Interface Down" \(on page 175\)](#)
- ["Address Not Responding" \(on page 170\)](#)

NNMi provides the following Root Cause Incidents views:

- ["Root Cause Incidents View" \(on page 159\)](#)
- ["Open Root Cause Incidents View" \(on page 159\)](#)

When using root cause incident views, note the following:

- Your administrator may choose to configure particular incidents so that they appear as root cause incidents in your root cause views. To distinguish these incidents from those that NNMi itself identifies as root cause, the **Correlation Nature** value for incidents configured to be root cause by the NNMi administrator is **User Root Cause**.
- Any root cause view includes incidents that have a **Root Cause** value for **Correlation Nature**.
- Your administrator also determines whether to configure deduplication for particular incidents.

See ["Monitoring Incidents for Problems" \(on page 130\)](#) for more information about ways to use incident views.

Related Topics:

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

Root Cause Incidents View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings.

The Root Cause Incident view displays all of the root cause incidents. This view is useful for identifying the number of root cause incidents in the queue. You might then choose to narrow your focus by filtering this information according to one or more attribute values, such as all root cause incidents whose status is Critical, or all root cause incidents whose description is Node Down.

As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the root cause incidents that have occurred within the last 24 hours.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), the message used to describe the incident, and any related notes.

See ["Monitoring Incidents for Problems" \(on page 130\)](#) for more information about ways to use incident views.

Open Root Cause Incidents View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings.

The **Open Root Cause Incidents** view displays the root cause incidents whose lifecycle state value indicates that the incident has not yet been closed. This view is useful for identifying the Root Cause Incidents that need to be resolved. As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the Root Cause Incidents that have remained open within the last week.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), the message used to describe the incident, and any related notes.

You can also access additional views from this one using the Actions menu as described in [Use Table Views](#). One example of an action available from an open root cause incident view is the ability to access a map view of the node(s) related to the incident.

Related Topics:

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Monitoring Incidents for Problems" \(on page 130\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

["Unassigned Open Key Incidents View" \(on page 151\)](#)

["Closed Key Incidents View" \(on page 156\)](#)

["Root Cause Incidents View" \(on page 159\)](#)

Service Impact Incidents View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The **Service Impact Incidents** view displays all of the incidents whose Correlation Nature is **Service Impact**. Service Impact incidents indicate a relationship between incidents in which a network service is effected by other incidents. By default, NNMi generates Service Impact incidents for Router Redundancy Groups. For example, an Interface Down incident can effect a Router Redundancy Group that is part of an HSRP service. This view is useful for identify a service that is affected.

Note: The **Service Impact** Correlation Nature is available for use by NNM iSPIs (HP Smart Plug-ins). See "Help for Administrators" for more information about HP Smart Plug-ins.

As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the Service Impact incidents that have occurred within the last 24 hours.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), the message used to describe the incident, and any related notes.

See "[Monitoring Incidents for Problems](#)" (on page 130) for more information about ways to use incident views.

Stream Correlation Incidents View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The Stream Correlation Incidents view contains correlations that NNMi's event pipeline establishes as it recognizes patterns in the flow of events through the pipeline. Contact your NNMi administrator for more information about NNMi's event pipeline. Correlations are created as NNMi analyzes events and traps to determine the root cause incident for a problem. Examples of stream correlations include Dedup (duplication of events) and Rate (occurrence of events by time) correlations.

This view is useful for proactively identifying potential problems before they become critical or serious root cause incidents. Keeping these correlations in a separate view also reduces the number of root cause incidents in the queue.

As with all incident views, you can filter this view by time period. The default time period is **Last Week** so that you can view all of the correlations that have occurred within the last week.

For each correlation displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the correlation last occurred, to whom the correlation incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), the message used to describe the correlation incident, and any related notes.

See "[Monitoring Incidents for Problems](#)" (on page 130) for more information about ways to use incident views.

Incidents by Family View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The **Incidents by Family** view displays all of the incidents filtered by a specified Family; for example **Interface** or **Connection**. This view is useful for identifying the incidents of a particular type. As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the incidents of a specified Family that have occurred within the last 24 hours.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its origin (for example, **Management Software** or **SNMP Trap**), its Correlation Nature (for example, **Symptom** or **Root Cause**), the message used to describe the incident, and any related notes.

See "[Monitoring Incidents for Problems](#)" (on page 130) for more information about ways to use incident views.

Custom Incidents View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The **Custom Incidents** view lets you choose the columns of incident information, to better meet your needs. For example, you might want to filter the view to display only the incidents related to a particular set of devices. You might also want to filter the view to display only the incidents assigned to you.

This view includes most of the attributes available for the incident so that you can decide which are most important for you to display. See [Use Table Views](#) for more information about sorting, filtering, and hiding attributes within a view. As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the incidents of interest that have occurred within the last 24 hours.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, to whom the incident is assigned, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its origin (for example, **Management Software** or **SNMP Trap**), its Correlation Nature (for example, **Symptom** or **Root Cause**), the message used to describe the incident, and any related notes. You can also view the duplicate count to indicate any duplicate occurrences of this incident, the name of the custom incident, an indicator of whether the NNMi root cause analysis (RCA) engine considers this incident to be active, any Correlation Notes that exist for the incident, the date and time the first instance of this incident occurred (if suppressing incidents), the date and time the original event that triggered the incident occurred, the date and time the incident was created, and the date and time the incident was last modified.

See [Filter a Table View](#) for more information about how to filter information displayed in a table.

See "[Monitoring Incidents for Problems](#)" (on page 130) for more information about ways to use incident views.

See "[Incident Form](#)" (on page 132) for more information about incident attributes.

Related Topics:

[Use Table Views](#)

["Organize Your Incidents" \(on page 131\)](#)

["Display a Map from an Incident" \(on page 146\)](#)

NNM 6.x/7.x Events View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The **NNM 6.x/7.x Events** view displays the incidents forwarded from Network Node Manager 6.x and 7.x management stations in your network environment.

You can use this view to monitor the health of devices being managed by previous versions of NNM, including NNM 6.x and NNM 7.x. You can also use this view to access the following 6.x/7.x features:

- **Actions** → **NNM 6.x/7.x Neighbor View**
- **Actions** → **NNM 6.x/7.x Details**
- **Actions** → **NNM 6.x/7.x ovw**

See "[Access NNM 6.x and 7.x Features](#)" (on page 13) for more information.

Note: You can only access 6.x/7.x features by selecting incidents generated from 6.x/7.x events.

For each incident displayed, you can view its severity, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, the name of its source node, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its Correlation Nature (for example, **Symptom** or **Root Cause**), the message used to describe the incident, and any related notes.

As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the incidents of interest that have occurred within the last 24 hours.

NNM 6.x/7.x Events by Category View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The **NNM 6.x/7.x Events** by Category view displays the incidents forwarded from Network Node Manager 6.x and 7.x management stations in your network environment. This view enables you to filter the view by the Incident Category; for example **Fault**. As with all incident views, you can also filter this view by time period. The default time period is **Last Week** so that you can view all of the NNM 6.x or 7.x incidents that have occurred within the last week..

You can use this view to monitor the health of devices being managed by previous versions of NNM, including NNM 6.x and NNM 7.x.

For each incident displayed, you can view its severity, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, the name of its source node, its family (for example, **Interface** or **Connection**), its Correlation Nature (for example, **Symptom** or **Root Cause**), the message used to describe the incident, and any related notes.

SNMP Traps View

Tip: See "[Incident Form](#)" (on page 132) for more details about the incident attributes that appear in this view's column headings.

The **SNMP Traps** view is useful for identifying all of the traps that were received from devices in your network environment. Your NNMi administrator must configure specific traps before they are displayed within NNMi incident views. As with all incident views, you can filter this view by time period. The default time period is **Last Hour** so that you can view all of the incidents of interest that have occurred within the last 24 hours.

For each incident displayed, you can view its severity, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its family (for example, **Interface** or **Connection**), its Correlation Nature (for example, **Symptom** or **Root Cause**), the message used to describe the incident, and any related notes.

SNMP Traps by Family View

Tip: See ["Incident Form" \(on page 132\)](#) for more details about the incident attributes that appear in this view's column headings.

The **SNMP Traps by Family** view displays all of incidents whose source is an SNMP trap filtered by a specified Family; for example **Interface** or **Connection**. This view is useful for identifying the incidents of a particular type. As with all incident views, you can filter this view by time period. The default time period is **Last Day** so that you can view all of the incidents of a specified Family that have occurred within the last 24 hours.

For each incident displayed, you can view its severity, its priority, its lifecycle state (for example **In Progress** or **Closed**), the date and time the incident last occurred, the name of its source node, its source object, its category (for example, **Fault** or **Security**), its Correlation Nature (for example, **Symptom** or **Root Cause**), the message used to describe the incident, and any related notes.

See ["Monitoring Incidents for Problems" \(on page 130\)](#) for more information about ways to use incident views.

Analyze Trap Information

By default, NNMi measures the rate of incoming traps, including the following:

- The rate of incoming SNMP traps from each device
- The rate of each incoming trap for each trap object identifier (OID)

NNMi monitors this trap information to determine whether any incoming traps exceed the threshold. If a threshold is exceeded, NNMi blocks the traps until the number of traps falls below the minimum threshold.

Note: The NNMi administrator can configure the threshold value using the `nnmtrapconfig.ovpl` script.

NNM iSPI NET. You can obtain reports about this trap information according to the following criteria:

- Within a specific time period
- For a specific node
- According to a specific trap identifier (trap OID)

For more information about this NNM iSPI NET tool, [click here](#).

When analyzing traps, NNMi looks at both the most common traps as well as the most common source nodes from which the traps are received. This SNMP trap analytics data is logged to the `trap-analytics.0.0.log` file. Information in the log file is organized according to the following criteria:

- Trap rate in number of traps per second
- The top 10 addresses that are generating traps
- The top 10 traps that are being generated

To make this data more easily available, use the `nnmtrapdump.ovpl` command. This NNM iSPI NET tool enables you to extract the data in which you are most interested from the `trapanalytics.0.0.log` file.

See the [nnmtrapdump.ovpl](#) Reference Page for more information (**Help** → **Documentation Library** → **Reference Pages**, in the *User Commands* category).

Investigate and Diagnose Problems

NNMi offers several ways for you to investigate and diagnose network problems.

- Use the Actions menu to gather the latest information about multiple aspects of a node (rather than waiting for the next regularly scheduled collection time).
 - ["Verify Device Configuration Details" \(on page 165\)](#)
 - ["View the Monitoring Configuration Details" \(on page 166\)](#)
 - ["Verify Current Status of a Device" \(on page 168\)](#)
- The Causal Engine keeps track of changes in your network, and alerts you to the root cause of problems and potential problems. See ["Interpret Root Cause Incidents" \(on page 168\)](#) for more information.
- The Actions menu also provides an easy way to launch troubleshooting commands to diagnose node connectivity and access problems:
 - ["Display End Nodes Attached to a Switch \(NNM iSPI NET\)" \(on page 190\)](#)
 - ["Test Node Access \(Ping\)" \(on page 191\)](#)
 - ["Find the Route \(traceroute\)" \(on page 192\)](#)
 - ["Establish Contact with a Node \(telnet\)" \(on page 193\)](#)
 - ["Check Status Details for a Node Group" \(on page 194\)](#)
 - ["Access NNM 6.x and 7.x Features" \(on page 13\)](#)
- Use the Tools menu to find a problem node. You can also use the Tools menu to verify that NNMi, itself, is running properly. This includes checking the status of NNMi processes and services:
 - ["Find a Node" \(on page 189\)](#)
 - ["Find the Attached Switch Port \(NNM iSPI NET\)" \(on page 190\)](#)
 - ["Checking the Status of NNMi" \(on page 196\)](#)

Verify Device Configuration Details

Before you begin diagnosing a problem, you might want to gather current information about a node to update information in views and NNMi maps.

Note: NNMi automatically gathers this information according to the Rediscovery Interval setting that was set by your administrator. The minimum allowed Rediscovery Interval setting is 1 hour. The default value set by NNMi is 24 hours.

To update your discovery information for a node:

1. Navigate to the view or form of interest and select the node whose discovery information you want to update.



To navigate to a table view and select a node

- a. From the workspace navigation panel, select the workspace of interest; for example, **Inventory**.
- b. Click the view that contains the node whose communication settings you want to check; for example **Nodes**.
- c. From the table view, click the selection box that precedes the node whose configuration you want to check.

To navigate to a map view and select a node:

- a. Navigate to the table view.
- b. From a table view, click the selection box that precedes the node of interest.
- c. Select **Actions**.
- d. From the drop-down menu, select the map view of interest.
- e. From the map view, click the node whose configuration you want to check.

To select a node from a form:

- a. From a table view, click the  Open icon that precedes the node of interest.
- b. From a map view, click the node of interest on the map and click the  Open icon.

2. Select Actions → Configuration Poll.

As the node is polled, NNMi displays the status messages for the Layer 3 discovery information. A Layer 2 connectivity analysis is also started. Information collected includes the node's IP address, subnet, contact name, location, and description.

View the Monitoring Configuration Details

Use the **Actions → Monitoring Settings** menu item to display the current monitoring configuration settings for a particular node, interface, address, Router Redundancy Member, Tracked Object, or Node Component.

NNMi can be configured to monitor several aspects of each device, and provide a wealth of information to help you do your job. After fault polling is enabled, several NNMi processes work together to detect problems and quickly calculate the device status and the root cause of any problems for you.

NNM iSPI for Performance. The NNM iSPI for Performance can monitor performance statistics and thresholds for each interface.

Monitoring Possibilities

Attribute	Description
Node Group	The name of any Node Groups to which this device belongs. See About Node and Interface Groups for more information.
Fault Polling (SNMP and ICMP)	If enabled, State Poller monitors all managed interfaces, IP addresses, and SNMP agents by issuing ICMP pings and SNMP read-only queries for MIB II ifAdminStatus and ifOperStatus. (ifAdminStatus is set by the device administrator. ifOperStatus indicates the overall health of the device and is supplied by the SNMP Agent.) If disabled: <ul style="list-style-type: none">● Devices that were already discovered remain with the last calculated state/status.● Newly discovered devices are set to "No Status" with map-symbol background shape color set to beige.
Fault Polling Interval	The time that State Poller waits between issuing queries to gather information.



Attribute	Description
Performance Polling	<p><i>NNM iSPI for Performance.</i></p> <p>If enabled, the NNM iSPI for Performance is installed. The NNM iSPI for Performance is accessed from the Action menu within map views and table views.</p> <p>If disabled, network performance data is not currently available.</p>
Performance Polling Interval	<p><i>NNM iSPI for Performance.</i></p> <p>The time that NNM iSPI for Performance waits between issuing queries to gather information.</p>

To view the monitoring configuration for a Node, Interface, or IP address:



1. Navigate to the view for that object (for example, **Inventory** → **Nodes**).
2. Select the object of interest by selecting the check box that precedes the object information.
3. Select **Actions** → **Monitoring Settings**.

Note: This menu item also is available on any object's form.


To view the monitoring configuration for a Router Redundancy Member:

1. Navigate to a Router Redundancy Group view (for example, **Inventory** → **Router Redundancy Groups**).
2. Click the  Open icon that precedes the Router Redundancy Group of interest.
3. From the Router Redundancy Members tab, click the  Open icon that precedes the Router Redundancy Group Member of interest.
4. Select **Actions** → **Monitoring Settings**.

To view the monitoring configuration for a Tracked Object:

1. Navigate to a Router Redundancy Group view (for example, **Inventory** → **Router Redundancy Groups**).
2. Click the  Open icon that precedes the Router Redundancy Group of interest.
3. From the Router Redundancy Members tab, click the  Open icon that precedes the Router Redundancy Group Member of interest.
4. Select the Tracked Object of interest by selecting the check box that precedes the object information.
5. Select **Actions** → **Monitoring Settings**.

To view the monitoring configuration for a Node Component:

1. Navigate to a Node view (for example, **Inventory** → **Nodes**).
2. Click the  Open icon that precedes the Node of interest.
3. Select the **Component Health** tab.
4. Select the Node Component of interest by selecting the check box that precedes the object information.
5. Select **Actions** → **Monitoring Settings**.

Note: This menu item is also available on any **Node Component** form.

Verify Current Status of a Device

NNMi calculates the status of devices each time additional information is gathered from various sources. You can request a status poll at any time to gather current information and update the data in views and NNMi maps.

To update status information about a node:

1. Navigate to the view of interest and select the node whose status information you want to update.

To navigate to a table view and select a node:

- a. From the workspace navigation panel, select the workspace of interest; for example, **Inventory**.
- b. Click the view that contains the node whose status you want to update; for example **Nodes**.
- c. From the table view, click the selection box that precedes the node whose status you want to update.

To navigate to a map view and select a node:








- a. Navigate to the table view.
- b. From a table view, click the selection box that precedes the node of interest.
- c. Select **Actions**.
- d. From the drop-down menu, select the map view of interest.
- e. From the map view, click the node whose status you want to update.

2. Select **Actions** → **Status Poll**.

As the node is polled, NNMi displays a report about which information is being gathered. When the poll completes, check the status icons in views and forms (see the Status tab information in ["Node Form" \(on page 27\)](#)). You can also check the status colors of map icons for changes (["Watch Status Colors" \(on page 126\)](#)).

Interpret Root Cause Incidents

The Causal Engine keeps track of changes in your network, and alerts you to the root cause of problems and potential problems. The Causal Engine sets an object's status using an object's outstanding conclusions. Every outstanding conclusion has a status, such as **Normal** or **Critical**. The highest status for an object's outstanding conclusions becomes the object's status. The order of status from lowest to highest is listed below:

-  No Status
-  Normal
-  Disabled
-  Unknown
-  Warning
-  Minor
-  Major

 Critical

Incident views explain the situation. Click here for examples of the type of information you can obtain from incidents. The information in the Incident helps you solve the problem quickly and efficiently:

- A router, switch, server, or other monitored device is down (see ["Node Down" \(on page 178\)](#))
- A node or connection might be down and need your attention (see ["Node or Connection Down" \(on page 180\)](#))
- An interface is operationally down (see ["Interface Down" \(on page 175\)](#))
- An address is no longer responding (see ["Address Not Responding" \(on page 170\)](#)).
- The connection between two important devices is down (see ["Connection Down" \(on page 173\)](#) and ["Connection Partially Unresponsive" \(on page 174\)](#))

Map views provide a quick way to view status. Click here for more information. As problems are detected for specific devices, the Causal Engine changes the status color of that device's icon on the maps. See ["Watch Status Colors" \(on page 126\)](#) for more information about status color.

The sequence of color changes indicates increasing levels of trouble. Red, the most severe, indicates that a network element is not functioning. You generally want to intervene and solve problems before they cause a complete node failure.

For more information about root cause scenarios, see the following:

- ["Node Down" \(on page 178\)](#)
- ["Address Not Responding" \(on page 170\)](#)
- ["Address Disabled" \(on page 169\)](#)
- ["Interface Down" \(on page 175\)](#)
- ["Interface Disabled" \(on page 176\)](#)
- ["Interface Unmanageable" \(on page 177\)](#)
- ["Connection Down" \(on page 173\)](#)
- ["Connection Partially Unresponsive" \(on page 174\)](#)
- ["Node or Connection Down" \(on page 180\)](#)
- ["SNMP Agent Not Responding" \(on page 182\)](#)
- ["Non-SNMP Node Unresponsive" \(on page 181\)](#)

Address Disabled

NNMi generates an **Address Disabled** conclusion when its interface becomes disabled. (An interface is disabled when its Administrative State (MIB II ifAdminStatus) is set to **Down**. See ["Interface Disabled" \(on page 176\)](#) for more information.)

Note: When the Administrative State is set to **Down**, the State of the address is set to **Not Responding**. If the interface's Administrative State changes to **Up**, but the Operational State remains **Down**, the address State remains set to **Not Responding**.

In the **Conclusions** list, trouble with an address is indicated by the following:

```
AddressesDisabled
```

An **Address Disabled** conclusion does not generate an incident, but appears in the information that is accessible from the Conclusions tab in the IP Address form.

Address Not Responding

NNMi periodically uses an ICMP ping command to check each address. If there is no response, NNMi's Causal Engine determines that the address is not responding:

On the source Node form, NNMi updates information on the following tabs:

- **Addresses**
- **Interfaces**
- **Status**
- **Conclusions**
- **Incidents**

In the **Conclusions** list, trouble with an address is indicated by the following:

```
SomeUnresponsiveAddressesInNode (node status = Minor)
```

Note: If you view an `AllUnresponsiveAddressesInNode` conclusion, see ["Node Down" \(on page 178\)](#) for more information.

On the maps, the icon for the Node is set to yellow (status = Minor), and any Interfaces that are using this address are updated.

Note: If the interface has more than one address, the address symbol might stay green (status = normal):



Aggregator Interface Degraded (NNMi Advanced)

NNMi generates an Aggregator Interface Degraded incident when the Status of at least one of the physical interfaces that is a member of an Aggregator Interface is set to **Critical**. See [Layer 2 Neighbor View Map Objects](#) for more information about Aggregator Interfaces.

An Aggregator Interface Degraded incident has a Severity set to **Minor**.

On the **Incident form**, Information on the following tabs is updated:

- Correlated Parents
- Correlated Children

Note: When an Interface Up occurs for all of the physical interfaces whose Status is **Critical**, NNMi updates Information in the **Correlation Notes** attribute and closes the incident.

On the **Interface form for the Aggregator Interface**, the Interface **State** attributes are updated. Information on the following tabs is updated:

- Addresses (if the interface has one or more addresses)
- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble with each physical interface that is a member of the Aggregator Interface is indicated by the following:

```
InterfaceDown (Interface status = Critical)
```

See ["Interface Down" \(on page 175\)](#) for more information about Interface Down incidents.

On **Layer 2 Neighbor View maps**, the icon for the Aggregator Interface is yellow:



Aggregator Interface Down (NNMi Advanced)

NNMi generates an Aggregator Interface Down when the Status of all physical interfaces that are members of the Aggregator Interface are set to **Critical**.

An Aggregator Interface may become Critical when NNMi determines either of the following:

- The Aggregator Interface exists in the interface table and its MIB II ifOperStatus is Down.
- All of the physical interfaces that are members of the Aggregator Interface have a MIB II ifOperStatus of Down.

See [Layer 2 Neighbor View Map Objects](#) for more information about Aggregator Interfaces.

An Aggregator Interface Down incident has Severity set to **Critical**

On the **Incident form**, Information on the following tabs is updated:

- Correlated Parents
- Correlated Children

Note: When an Interface Up occurs for any of the physical interfaces, NNMi updates Information in the **Correlation Notes** attribute and closes the incident.

On the **Interface form for the Aggregator Interface**, the Interface **State** attributes are updated. Information on the following tabs is updated:

- Addresses (if the interface has one or more addresses)
- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble with each physical interface that is a member of the Aggregator Interface is indicated by the following:

InterfaceDown (Interface status = Critical)

See ["Interface Down" \(on page 175\)](#) for more information about Interface Down incidents.

On **Layer 2 Neighbor View maps**, the icon for the Aggregator Interface is red:



Aggregator Connection Degraded (NNMi Advanced)

NNMi generates an Aggregator Connection Degraded incident when the Status of at least one of the Aggregator Interfaces that is a member of a Link Aggregation is set to **Minor**. See [Layer 2 Neighbor View Map Objects](#) for more information about Aggregator Connections. Also see "[Aggregator Interface Degraded \(NNMi Advanced\)](#)" (on page 170).

An Aggregator Connection Degraded incident has a Severity set to **Minor**.

On the Incidents form, Information on the following tabs is updated:

- Correlated Parents
- Correlated Children

Note: When an Interface Up occurs for all of the physical interfaces whose Status is **Critical**, NNMi updates Information in the **Correlation Notes** attribute and closes the incident.

On the Layer 2 Connection form for the Aggregator Connection, the Interface **State** attributes are updated. Information on the following tabs is updated:


- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble with each physical interface that is a member of the Link Aggregation is indicated by the following:

InterfaceDown (Interface status = Critical)

See "[Interface Down](#)" (on page 175) for more information about Interface Down incidents.

On Layer 2 Neighbor View maps, the thick line for the Aggregator Connection is yellow:



Aggregator Connection Down (NNMi Advanced)

NNMi generates an Aggregator Connection Down incident when the Status of at least one of the Aggregator Interfaces that is a member of the Link Aggregation is set to **Critical**. See [Layer 2 Neighbor View Map Objects](#) for more information about Aggregator Interfaces and Aggregator Connections. Also see "[Aggregator Interface Down \(NNMi Advanced\)](#)" (on page 171).

An Aggregator Connection Down incident has Severity set to **Critical**.

On the Incident form, Information on the following tabs is updated:

- Correlated Parents
- Correlated Children

Note: When an Interface Up occurs for any of the physical interfaces, NNMi updates Information in the **Correlation Notes** attribute and closes the incident.

On the Layer 2 Connection form for the Aggregator Connection, the Interface **State** attributes are updated. Information on the following tabs is updated:


- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble with each physical interface that is a member of the Link Aggregation is indicated by the following:

InterfaceDown (Interface status = Critical)

See "[Interface Down](#)" (on page 175) for more information about Interface Down incidents.

On **Layer 2 Neighbor View maps**, the thick line indicating the Aggregator Connection is red:



Buffer has Insufficient Capacity or is Malfunctioning

A **Buffer has Insufficient Capacity or is Malfunctioning** incident indicates the buffer pool for the source node is either exhausted or cannot meet the demand for use.

A **Buffer has Insufficient Capacity or is Malfunctioning** incident is generated with Severity set to **Critical**.

On the Source Node form, information on the following tabs is updated:

- **Correlated Children**
- **Status**
- **Conclusions**

The Correlated Children tab includes any associated traps.

On the map, the Causal Engine sets the color of the Source Node to yellow.

Connection Down

NNMi periodically uses SNMP to check the interface on each end of a connection. NNMi's Causal Engine uses this information to determine the status of the connection. If both ends of the connection are down, the Causal Engine determines that the connection is down.

A **Connection Down** incident is generated with Severity set to **Critical**. The information on the following tab is updated:

- **Correlated Children**


On the **Connections** form, information on the following tabs is updated:






- **Interfaces**
- **Status**
- **Conclusions**

In the **Conclusions** list, trouble with a connection is indicated by the following:

- ConnectionDown (connection status = Critical)

On the maps, the Causal Engine sets the color of the line between the devices according to the following criteria (the line indicates the connection):



-  Red: neither interface is responding.
-  Green: Both interfaces are responding.
-  Yellow: the interface on one end is not responding. The interface on the other end is responding.
-  Light Blue: due to other network problems, the status of one interface cannot be determined at this time.
-  Dark Blue: due to other network problems, the status of both interfaces cannot be determined at this time.

Connection Partially Unresponsive

NNMi periodically uses SNMP to check the interface on each end of a connection. NNMi's Causal Engine uses this information to determine the status of the connection. If NNMi cannot determine the status of one end of a connection and the other end of the connection is up, the Causal Engine determines that the connection is partially unresponsive. In the case of multiple end points within a connection, at least one end point must be up. The remaining end points must be a combination of up and unresponsive (meaning NNMi cannot determine the status of the end point).

Reasons NNMi might not be able to determine the status of an interface is that a problem exists in an ATM or FrameRelay cloud that is between one interface and the other.

A **Connection Partially Unresponsive** incident is generated with Severity set to **Critical**.

On the **Connections** form, information on the following tabs is updated:


- **Interfaces**
- **Status**
- **Conclusions**

In the **Conclusions** list, trouble with a connection is indicated by the following:

- `ConnectionPartiallyUnresponsive` (connection status =Warning)

If the source node is in the Important Nodes Group, the Node Down incident appears as a correlated child under the Connection Partially Unresponsive incident. (Your administrator decides what nodes belong in the Important Nodes group.)

On the maps, the Causal Engine sets the color of the line between the devices as follows (the line indicates the connection):



CPU Utilization is too High

A **CPU Utilization is too High** incident indicates any of the following utilization averages is too high:

- 5 second
- 1 minute
- 5 minute

A **CPU Utilization is too High** incident is generated with Severity set to **Critical**.

On the Source Node form, information on the following tabs is updated:

- **Correlated Children**
- **Status**
- **Conclusions**

The Correlated Children tab includes any associated traps.

On the map, the Causal Engine sets the color of the Source Node to yellow.

Fan is Malfunctioning

A **Fan is Malfunctioning** incident indicates the identified fan on the Source Node is not operating correctly.

A **Fan is Malfunctioning** incident is generated with Severity set to **Critical**.

On the Source Node form, information on the following tabs is updated:

- **Correlated Children**
- **Status**
- **Conclusions**

The Correlated Children tab includes any associated traps.

On the map, the Causal Engine sets the color of the Source Node to yellow.

Interface Down

NNMi periodically uses SNMP to check each interface. If an SNMP agent reports that an interface is down (MIB II ifOperStatus), NNMi's Causal Engine takes the following actions:

An Interface Down incident is generated with Severity set to **Critical**. Information on the following tabs is updated:

- Correlated Parents
- Correlated Children
- Custom Attributes

Information in the **Correlation Notes** attribute is updated on an Interface Up.

Note: You might find relevant traps as Correlated Children on the Correlations tab.

On the **Interface** form, the **Interface State** attributes are updated. Information on the following tabs is updated:

- Addresses (if the interface has one or more addresses)
- Status

Network Node Manager (NNMi 8.10) Online Help: Using the Console

Investigate and Diagnose Problems

- Conclusions
- Incidents

In the **Conclusions** list, trouble with an interface is indicated by the following:

`InterfaceDown` (Interface status = Critical)

On the source Node's form, the information on the following tabs is updated:

- Addresses
- Interfaces
- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble with an interfaces is indicated by the following:

`InterfacesDownInNode` (node status = Minor)

On the maps, the icons for the node and its interfaces are updated:



Interface Disabled

NNMi periodically uses SNMP to check each interface. If an SNMP agent reports that an interface is administratively down (MIB II `ifAdminStatus`), NNMi's Causal Engine takes the following actions:

Note: Interface Disabled incidents are not generated by default. Your NNMi administrator must configure these incidents to be generated.

An Interface Disabled incident is generated with Severity set to **Critical**. Information on the following tabs is updated:

- Correlated Children
- Custom Attributes

Information in the **Correlation Notes** attribute is updated on an Interface Enabled.

Note: You might find relevant traps on the **Correlations** tab.

On the **Interface** form, the **Interface State** attributes are updated. Information on the following tabs is updated:

- Addresses
- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble with an interface is indicated by the following:

`InterfaceDisabled` (Interface status = **Disabled**)

On the source Node's form, the information on the following tabs is updated:

- Addresses
- Interfaces
- Status
- Conclusions
- Incidents

On the maps, the icons for any of the node's disabled interfaces are updated and displayed as grey (disabled):



Interface Unmanageable

NNMi periodically uses SNMP to check each interface. If an SNMP agent is not responding, NNMi's Causal Engine takes the following actions:

One `InterfaceUnmanageable` message is generated for each interface within the node.

On each **Interface** form, the **Interface State** attributes are updated. The information on the following tabs is updated:

- Addresses
- Status
- Conclusions

In the **Conclusions** list, trouble with the interface is indicated by the following:

`InterfaceUnmanageable` (Interface status = Unknown)

On the source node's form, the **SNMP Agent State** attributes are updated. The information on the following tabs is updated:

- Addresses (if the interface has one or more IP addresses)
- Interface
- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble with an interface is indicated by the following:

`UnresponsiveAgentInNode` (status = Minor)

Note: There is one `InterfaceUnmanageable` message for each interface within the node.

On the maps, the icons for the node and its interfaces are updated:

If the interface is unmanageable because the SNMP agent is down:



If the interface is unmanageable because of a node down situation:



Remote Site Containing Node <Source Node Name> is Unreachable

A Remote Site is Unreachable incident is generated when all of the nodes in an Island Node Group do not respond to ICMP or SNMP queries.

An Island Node Group is a group of connected nodes that NNMi discovers and that are not connected to the rest of the topology. An example of an environment with multiple Island Node Groups is a financial institution or retail store with many branches or stores. Each branch or store might be connected to other branches or stores with a WAN (Wide Area Network) connection. Each branch or store appears as an isolated island of nodes in the NNMi topology.

NNMi automatically creates Island Node Groups whenever it detects changes in Layer 2 connections.

NNMi selects a representative node in each Island Node Group as the Source Node associated with the Remote Site incident. The Source Object is the Island Node Group.

Memory has Insufficient Capacity or is Malfunctioning

A **Memory has Insufficient Capacity or is Malfunctioning** incident indicates the memory pool for the Source Node is exhausted or cannot meet the demand for use.

A **Memory has Insufficient Capacity or is Malfunctioning** incident is generated with Severity set to **Critical**.

On the Source Node form, information on the following tabs is updated:

- **Correlated Children**
- **Status**
- **Conclusions**

The Correlated Children tab includes any associated traps.

On the map, the Causal Engine sets the color of the Source Node to yellow.

Node Down

An unresponsive device within your network can cause a variety of problems. If the troubled device is a router, switch, or server, many devices could be unreachable. You receive a Node Down incident when NNMi analyzed the situation and determined any of the following:

- [A node with two or more connections is truly down.](#)
- [An SNMP node that has no discovered connections is unreachable.](#)
- [A node belongs to the Important Nodes Group and has become unreachable.](#) Your NNMi administrator assigns devices to this Node Group (these devices can have any number of connections).
- [A non-SNMP node is unreachable.](#)

A Node Down incident is generated with Severity set to **Critical**, and the map icon is set to red (see [Map Displays](#)). Any Interface Down incident on neighbors that are one hop from the node are correlated under the Node Down incident.

If the device becomes responsive again, the Node Down incident is automatically closed. In the correlation Notes attribute, an annotation explains exactly why it was closed.

Note: When NNMi cannot determine whether the node or connection is down, it generates a **Node or Connection Down** incident. See "[Node or Connection Down](#)" (on page 180) for more information.

NNMi does not generate a Node Down incident under the following conditions:

- If the node is in the shadow of another problem that causes the to be unreachable.
- If the node is in an ATM or FrameRelay cloud that causes the node to be unreachable.

When the Node Has Two or More Connections

The Causal Engine uses the following criteria to verify which node is actually down:

Note: If the addresses are not being polled, only the last two criteria are used.

Stand-Alone Problem	Side Effect of Another Problem	Criteria
+	+	100% of the addresses assigned to this node are unreachable.
+	+	The SNMP agent installed on this machine is not responding.
+	-	At least two of the neighboring devices can be reached and are reporting problems with connectivity to this node. Therefore, this is not a "Shadow" problem, but is truly a problem with the identified node.

In the device's Node form, the Conclusions tab shows the relevant combination of conclusions, which might include any of the following:

- AllUnresponsiveAddressesInNode (status = Minor) - (Appears only when addresses are being polled)
- UnresponsiveAgentInNode (status = Minor)
- NodeWithAtLeastTwoNeighborsUp (status = Normal)

When the SNMP Node has No Discovered Connections and is Unreachable

The Causal Engine generates a Node Down incident for an SNMP node when an unconnected node is unreachable. (No connections have been discovered for the node.)

When a Node is in the Important Nodes Group

When a Node in the Important Node Group is unreachable, NNMi issues a Node Down incident.

Nodes in the Important Nodes Group may or may not have two or more connections. See "[Connection Partially Unresponsive](#)" (on page 174) for more information about how nodes in an Important Node Group are handled when the connection is partially unresponsive.

When a non-SNMP Node is Unreachable

The Causal Engine generates a Node Down incident for a non-SNMP node under the following conditions:


- The interface on an SNMP node at one end of a connection is Down.
- The non-SNMP end node on the other end of the connection does not respond to ping.

Map Displays


The Status of the Node Down device for an SNMP node changes to **Critical** and the device's map icon color changes to red (Router 3 in the illustration below). The status of each unreachable interface changes to **Unknown** and the interface map icon color changes to blue.

Any other devices that are unreachable *because of this problem* are in the "shadow" of the problem:

- The unreachable shadow devices' map icons change to blue.
- Members of the Important Nodes group's map icons change to red (Switch 1 in the illustration below).



The Status of the Node Down device for a non-SNMP node changes to **Critical** and the device's map icon color changes to red. The Status of the interface on each end of the connection also changes to **Critical** and each interface's map icon color changes to red.



Node or Connection Down

If a node is not responding to ICMP and SNMP queries, and only one neighbor is down, the Causal Engine cannot determine whether the node itself is down or whether the connection to the node is down.

A Node or Connection Down incident is generated with Severity set to **Critical**.

On the source node's form, the information on the following tabs is updated:

- Addresses
- Interface
- Status
- Conclusions
- Incidents

In the **Conclusions** list, trouble is indicated by the following message:

NodeOrConnectionDown (node status = **Critical**)

On the maps, the icon for the node is set to red:



Non-SNMP Node Unresponsive

NNMi generates a **Non-SNMP Node Unresponsive** incident under the following conditions:

- A node does not have an SNMP agent
- NNMi is unable to ping all of the addresses for the non-SNMP node

Reasons NNMi might not be able to ping all of the addresses for a node include one or more devices between the non-SNMP node and its neighbor device are down.

Note: If a node does not have an SNMP agent, NNMi is able to gather only the address information for the node.

A **Non-SNMP Node Unresponsive** incident is generated with Severity set to **Critical**.

On the node form, information on the following tabs is updated:

- **Status**
- **Conclusions**

In the **Conclusions** list, trouble with a connection is indicated by the following:

- Non-SNMPNodeUnresponsive (node status =Critical)

On the maps, NNMi's Causal Engine sets the color of the node to red:



Number of SNMP Traps Persisted in the Database has Reached or Exceeded Trap Limit

A **Number of SNMP Traps Persisted in the Database has Reached or Exceeded Trap Limit** incident indicates the number of SNMP traps has reached or exceeded the maximum limit. By default, the SNMP trap limit is 100,000.

Note: When the maximum limit is reached, NNMi no longer accepts traps from the Event system. The NNMi administrator can reduce the number of traps in the NNMi database. See the `nnmtri-mincidents.ovpl` Reference Page (**Help** → **Documentation Library** → **Reference Pages**, in the *Administrator Commands* category).

A **Number of SNMP Traps Persisted in the Database has Reached or Exceeded Trap Limit** incident is generated with Severity set to **Critical**.

Power Supply is Malfunctioning

A **Power Supply is Malfunctioning** incident indicates the Source Node's specified power supply is not operating correctly.

A **Power Supply is Malfunctioning** incident is generated with Severity set to **Critical**.

On the Source Node form, information on the following tabs is updated:

- **Correlated Children**
- **Status**
- **Conclusions**

The Correlated Children tab includes any associated traps.

On the map, the Causal Engine sets the color of the Source Node to yellow.

SNMP Agent Not Responding

NNMi periodically uses SNMP to check the availability of each SNMP Agent in your network environment. If an SNMP Agent is not responding (for example, the SNMPv1 or SNMPv2c community string for this agent changed, or the SNMPv3 user name for this agent changed, and the NNMi communication configuration settings have not yet been updated):

On the source node's form, the **SNMP Agent State** attributes are updated. The information on the following tabs is updated:

- Interface
- Status
- Conclusions

In the **Conclusions** list, trouble with an SNMP agent is indicated by the following:

`UnresponsiveAgentInNode` (status = Minor)

On the maps, the icons for the monitored node (status = Minor) and its interfaces (status = **Unknown**) are updated:



Temperature Sensor is Out of Range

A **Temperature Sensor is Out of Range** incident indicates the Source Node's temperature sensor is either too hot or too cold.

A **Temperature Sensor is Out of Range** incident is generated with Severity set to **Critical**.

On the Source Node form, information on the following tabs is updated:

- **Correlated Children**
- **Status**
- **Conclusions**

The Correlated Children tab includes any associated traps.

On the map, the Causal Engine sets the color of the Source Node to yellow.

Voltage is Out of Range

A **Voltage is Out of Range** incident indicates the specified voltage on one of the Source Node's power supplies is out of range.

A **Voltage is Out of Range** incident is generated with Severity set to **Critical**.

On the Source Node form, information on the following tabs is updated:

- **Correlated Children**
- **Status**
- **Conclusions**

The Correlated Children tab includes any associated traps.

On the map, the Causal Engine sets the color of the Source Node to yellow.

Interpret Service Impact Incidents

Service Impact incidents indicate a relationship between incidents in which a network service is affected by other incidents. The Service Impact incident helps to identify the service that is affected. Any associated incidents that have contributed to the reason for the Service Impact appear under the Conclusions tab for the Service Impact incident.

A Service Impact incident is indicated using the incident Correlation Nature attribute.

Note: NNMi determines the Correlation Nature for an incident.

NNMi Advanced. As an example of a Service Impact incident and its relationship between additional incidents: an Interface Down incident on an interface that is part of a Router Redundancy Group can effect the integrity of a Router Redundancy Group that is part of an HSRP service. To continue the example, A Router Redundancy Group Degraded incident might be the Service Impact incident used to indicate there is a problem with your HSRP service. The Interface Down incident would appear under the Conclusions tab for the Router Redundancy Degraded incident to indicate that it is part of the reason the Router Redundancy Group (and subsequent HSRP service) has become degraded.

NNMi provides the following incidents whose Correlation Nature is Service Impact:

- ["Primary Device in Router Redundancy Group Switched \(NNMi Advanced\)" \(on page 184\)](#)
- ["No Primary Device in Router Redundancy Group \(NNMi Advanced\)" \(on page 184\)](#)
- ["Multiple Primary Devices in Router Redundancy Group \(NNMi Advanced\)" \(on page 185\)](#)
- ["No Secondary Device in Router Redundancy Group \(NNMi Advanced\)" \(on page 185\)](#)
- ["Multiple Secondary Devices in Router Redundancy Group \(NNMi Advanced\)" \(on page 185\)](#)
- ["Router Redundancy Group Degraded \(NNMi Advanced\)" \(on page 185\)](#)

Note: NNMi determines the Correlation Nature for an incident.

See ["Router Redundancy Group View \(NNMi Advanced\)" \(on page 22\)](#) for more information about Router Redundancy Groups.

Primary Device in Router Redundancy Group Switched (*NNMi Advanced*)

A Primary Device in Router Redundancy Group Switched incident means NNMi determined a primary role (for example, HSRP Active or VRRP Master) moved from one device to another in a Router Redundancy Group.

Note: The group is routing packets properly.

Reasons for this incident include one or more of the following:

- A router or interface in the Router Redundancy Group has gone down.
- A tracked object (interface or IP address) in the Router Redundancy Group has gone down.

When a Primary Device in Router Redundancy Group Switched incident is generated, the Router Redundancy Group maintains its current status.

A Primary Device in Router Redundancy Group Switched incident has Severity set to **Critical**.

No Primary Device in Router Redundancy Group (*NNMi Advanced*)

A No Primary Device in Router Redundancy Group incident means NNMi determined no primary device (for example, HSRP Active or VRRP Master) is identified in a Router Redundancy group.

This typically indicates one of the following:

- Too many routers are down.
- Protocol specific communication between routers in the group is malfunctioning.

A No Primary Device in Router Redundancy Group incident has Severity set to **Critical**.

Multiple Primary Devices in Router Redundancy Group (NNMi Advanced)

A Multiple Primary Devices in Router Redundancy Group incident means NNMi determined multiple primary devices (for example, HSRP Active or VRRP Master) are identified in a Router Redundancy Group.

This incident typically indicates that protocol specific communication between routers in the group is malfunctioning.

A Multiple Primary Devices in Router Redundancy Group incident has Severity set to **Critical**.

No Secondary Device in Router Redundancy Group (NNMi Advanced)

A No Secondary Device in Router Redundancy Group incident means NNMi determined no secondary device (for example, HSRP Standby or VRRP Backup) is identified in a Router Redundancy Group.

This incident typically indicates the following:

- Protocol-specific communication between routers in the group is malfunctioning.
- The group is routing packets properly because a single primary device has been identified.

A No Secondary Device in Router Redundancy Group incident has Severity set to **Warning**.

Multiple Secondary Devices in Router Redundancy Group (NNMi Advanced)

A Multiple Secondary Devices in Router Redundancy Group incident means NNMi determined more than one secondary device (for example, HSRP Standby) is identified in a Router Redundancy Group.

Note: This incident applies to only Router Redundancy Groups using the HSRP protocol. VRRP allows multiple secondary (VRRP Backup State) routers.

This incident typically indicates that protocol specific communication between routers in the group is malfunctioning.

A Multiple Secondary Devices in Router Redundancy Group incident has Severity set to **Critical**.

Router Redundancy Group Degraded (NNMi Advanced)

This incident only occurs in Router Redundancy Groups using the HSRP protocol and with more than two members.

Note: The group is routing packets properly.

A Router Redundancy Group Degraded incident means NNMi determined the following:

- The Router Redundancy Group has a primary and secondary device.
- The remaining devices in the group are not in an expected protocol-specific state. For example, in HSRP, devices other than the Standby and Active devices are expected to be in the "Listen" state.
- Protocol-specific communication between routers in the group is malfunctioning.

A Router Redundancy Group Degraded incident has Severity set to **Warning**.

Interpret Threshold Incidents (NNM iSPI for Performance)

NNM iSPI for Performance. If the NNMi administrator configures performance measurement thresholds, NNMi monitors interfaces for acceptable operations ranges or threshold violations. NNMi can be configured to create incidents when performance outside the acceptable range is detected. When the

performance returns to within an acceptable range, NNMi closes the incident. NNM iSPI for Performance provides exceptions reports to track the frequency of threshold violations.

The following table describes possible threshold incidents.

Note: Performance thresholds can affect the status of an interface, connection, or node. For example, if an interface error rate is high, the interface status becomes **Critical**. NNMi's Causal Engine returns the node status of **Warning** for any nodes whose interfaces are outside one or more threshold boundaries.

Tip: See "[Incident Form](#)" (on page 132) for more information about each performance measurement.

Threshold Incidents

Performance Measurement	Interface Performance State	Message	Incident Severity
Input Utilization	HIGH	Interface Input Utilization High	Critical
	LOW	Interface Input Utilization Low	Minor
	NONE	Interface Input Utilization None	Major
Output Utilization	HIGH	Interface Output Utilization High	Critical
	LOW	Interface Output Utilization Low	Minor
	NONE	Interface Output Utilization None	Major
Input Error Rate	HIGH	Input Error Rate High	Critical
Output Error Rate	HIGH	Output Error Rate High	Critical
Input Discard Rate	HIGH	Input Discard Rate High	Critical
Output Discard Rate	HIGH	Output Discard Rate High	Critical

Input and Output Utilization Incidents (*NNM iSPI for Performance*)

Utilization incidents are available if NNM iSPI for Performance is installed and your administrator configured performance measurement thresholds.

Input and output utilization incidents enable you to identify interfaces that are over- or under-utilized.

You receive input and output utilization incidents when performance is not within the allowable range set by your administrator. Reasons for setting utilization thresholds include:

- Monitor for under-utilization which wastes money
- Monitor for over-utilization, which may result in performance bottlenecks or service provider surcharges (over a pre-specified percentage)

The severity of utilization incidents depends on whether the measured value is over or under the allowable range. The following table describes the meaning of HIGH, NOMINAL, LOW, and NONE.

Utilization Value	Description	Incident Severity
NONE	The measured value is zero.	Minor
LOW	The measured value is less than the allowable range.	Minor
NOMINAL	The measured value is within the allowable range. This incident cancels any related HIGH, LOW, or NONE incidents.	Not applicable. No incident is generated.
HIGH	The measured value is greater than the allowable range	Critical

Information under the following Incident tabs is updated:

- Correlated Parents
- Correlated Children
- Custom Attributes

The following table describes a combination of conclusions leading to utilization errors. These appear in the Conclusions lists on the associated interface and connection or node forms.

Possible Conclusion Combinations for Utilization Incidents (Interface and Connection)

Form	Conclusion	Status
Interface	InterfaceOutputUtilizationHigh	Critical
Connection	SomeConnectionThreshold ValuesHigh	Minor

Possible Conclusion Combinations for Utilization Incidents (Interface and Node)

Form	Conclusion	Status
Interface	InterfaceOutputUtilizationHigh	Critical
Node	SomeInterfacesOutsideThresholdBoundariesInNode	Minor

Input and Output Error Rate Incidents (*NNM iSPI for Performance*)

Error rate incidents are available if NNM iSPI for Performance is installed and your administrator configured performance measurement thresholds.

Input and output error rate incidents allow you to identify interfaces that are dropping data.

You receive input and output error rate incidents when an error rate threshold is not within the allowable range set by your administrator. For example, the error rate must not exceed 10 percent. Reasons for setting error rate thresholds include:

- Check for corrupted data packets
- Detect configuration mismatches
- Detect faulty hardware

Only error rates that exceed the allowable range generate an incident. The severity of error rate incidents is **Critical**.

Information on the following Incident tabs is updated:

- Correlated Parents
- Correlated Children
- Custom Attributes

The following table describes a combination of conclusions leading to error rate incidents. These appear in the Conclusions lists on the associated interface and connection or node forms.

Possible Conclusion Combinations for Error Rate Incidents (Interface and Connection)

Form	Conclusion	Status
Interface	InterfaceInputErrorRateHigh	Critical
Connection	SomeConnectionThreshold ValuesHigh	Minor

Possible Conclusion Combinations for Error Rate Incidents (Interface and Node)

Form	Conclusion	Status
Interface	InterfaceInputErrorRateHigh	Critical
Node	SomeInterfacesOutsideThresholdBoundariesInNode	Minor

Input and Output Discard Rate Incidents (NNM iSPI for Performance)

NNM iSPI for Performance. Prerequisite, your NNMi administrator configured performance measurement thresholds.

Input and output discard rate incidents enable you to identify interfaces that have transmission buffer overflows or are bottlenecks.

You receive input and output discard rate incidents when a discard rate is not within the allowable range set by your administrator. For example, the discard rate must not exceed 10 percent. Reasons for setting discard rate thresholds include:

- Check for large data packets
- Monitor bottlenecks
- Detect faulty hardware

Only discard rates that exceed the allowable range generate an incident. The severity of discard rate is **Critical**.

Information on the following Incident tabs is updated:

- Correlated Parents
- Correlated Children
- Custom Attributes

The following table describes a combination of conclusions leading to discard rate incidents. These appear in the Conclusions lists on the associated interface and connection or node forms.

Possible Conclusion Combinations for Discard Rate Incidents (Interface and Connection)

Form	Conclusion	Status
Interface	InterfaceInputDiscardRateHigh	Critical
Connection	SomeConnectionThreshold ValuesHigh	Minor

Possible Conclusion Combinations for Discard Rate Incidents (Interface and Node)

Interface	InterfaceInputDiscardRateHigh	Critical
Node	SomeInterfacesOutsideThresholdBoundariesInNode	Minor

Find a Node

As part of the investigation and diagnosis process, you might want to access the details for a specific node. One way is to use the **Tools** → **Find Node** option. This option is particularly useful when you want to search for a node by any of its IP addresses.

You can find a node based on the values described in the following table.

Find Node Attribute

Possible Values	Description
Hostname	The fully-qualified DNS name or the IP address, whichever is available. (This is the name that appears in the Hostname field on Node forms.)
IP address of any interface	The IP address for any interface on the node.
System name	The full system name; for example <code>cisco5500.abc.xyz.com</code> that is obtained from the node's SNMP agent. (This is the name that appears in the System Name field on Node forms.)
Name	The type of name your administrator has configured using the Node Name Resolution attribute during discovery configuration. For example, this might be the short DNS name, or short system name. (This is the name that appears in the Name field on Node forms.)

To find a node using the node's hostname, IP address, system name, or name attribute value:

1. From the console, select **Tools** → **Find Node**.
2. At the **Node Name** field of the **Specify Node** dialog, enter the hostname, an IP address, system name, or Name value for the node of interest.

Note: Names are case-sensitive.

3. Click **Find**.

NNMi searches the database to find a matching value using each of the attributes listed in the preceding table.

NNMi shows the node form for the node you specified. If no node is found, NNMi shows an error message. If multiple nodes are found, NNMi shows the first node it finds.

See ["Access Node Details" \(on page 127\)](#) for more information about the kind of information that appears in the Node form. See [Access More Details \(Quick View and Forms\)](#) for a description of additional ways to access node details.

Find the Attached Switch Port (*NNM iSPI NET*)

As part of the investigation and diagnosis process, you might need to determine the switch to which a problem node is connected. For example, if a node in your network has a potential virus, you want to identify the switch to which it is connected so that you can prevent the virus from moving to other nodes in your network. One way to identify a switch port attached to a problem node is to use the **Tools** → **Find Attached Switch Port** option.

You can find the attached switch and the port that is connected from the switch to the problem node using any of the values described in the following table. Each of these values is for the problem node.

Note: The node whose information you provide does not have to be discovered by NNMi.

Find Attached Switch Port Attribute

Possible Values	Description
Hostname	The fully-qualified DNS name of the node whose attached switch port you are trying to identify. (This is the name that appears in the Hostname field on Node forms.)
IP address of any interface	The IP address for any interface on the node whose attached switch port you are trying to identify.
MAC address	The MAC (Media Access Control) address of any interface on the node whose attached switch you are trying to identify.

To find a the switch port that is attached to a node:

1. From the console, select **Tools** → **Find Attached Switch Port**.
2. At the **End Node Name** field of the **Specify Hostname, IP Address, or MAC Address** dialog, enter the hostname, an IP address, or the interface MAC address for the node of interest.
Note: Names are case-sensitive.
3. Click **Find**.

NNMi searches the database to find a matching value using the hostname, IP address, or MAC address provided.

NNMi shows the hostname of the node and the name of the node's interface or port number. Click the node name to open the Node form for the switch attached to the node you specified. Click the interface name to open the Interface form. If the node or attached switch port is not found, NNMi shows an error message. If multiple attached switches are found, NNMi shows the first attached switch it finds.

See ["Access Node Details" \(on page 127\)](#) for more information about the kind of information that appears in the Node form. See [Access More Details \(Quick View and Forms\)](#) for a description of additional ways to access node details.

Display End Nodes Attached to a Switch (*NNM iSPI NET*)

As part of the investigation and diagnosis process, you might need to determine the end nodes attached to a switch. For example, if you need to upgrade a switch, you might need to check which servers are

attached to the switch so that you can fill out the change request properly.

You can display the end nodes attached to a switch using the NNMi console **Actions** menu.

1. Navigate to the view or form of interest and select the switch whose attached end nodes you want to display.



To navigate to a table view and select a switch:

- a. From the workspace navigation panel, select the workspace of interest; for example, **Inventory**.
- b. Click the view that contains the switch whose attached end nodes you want to display; for example **Nodes**.
- c. From the table view, click the selection box in the row that represents the switch of interest.

To navigate to a map view and select a switch:

- a. Navigate to the table view.
- b. From the table view, click the selection box in the row that represents the switch of interest.
- c. Select **Actions** → **Layer 2 Neighbor View**, **Layer 3 Neighbor View**, **Node Group Map**, or **Path View**.
- d. In the map, click the map symbol representing the switch of interest.

To navigate to a form:

- a. From a table view, click the  Open icon in the row that represents the switch of interest.
- b. From a map view, click the switch of interest on the map and click the  Open icon.

2. Select **Actions** → **Show Attached End Nodes**.

NNMi displays the following for each end node that it determines is attached to the switch:

- Resolved hostname
- MAC address of the connected interface
- IP address

Note the following:

- If the end node does not have a resolvable hostname, NNMi repeats the node's IP address.
- If NNMi is unable to locate any information about end nodes attached to the selected switch, NNMi displays a message that it was unable to locate any entries for the switch.

6. Click any object name link to open the form for the selected object.

Note: If the object name appears without a link, this indicates NNMi has not discovered the node or interface.

Related Topics

["Find the Attached Switch Port \(NNM iSPI NET\)" \(on page 190\)](#)

Test Node Access (Ping)

You can verify that a node or IP address is reachable using the ping command from the NNMi console **Actions** menu.

Note: NNMi uses the packet size used by the current operating system.

From an incident view:

1. Click the selection box that precedes the incident whose source node you want to ping.
2. Select **Actions** → **Ping (from server)**.

Note: NNMi pings the source node of the incident. It does not ping the source object. For example, if the incident is related to an interface, NNMi pings the node on which the interface resides, not the interface itself.

From other views or forms:

1. Navigate to the view or form of interest and select the node or IP address you want to ping.



To navigate to a table view and select a node:

- a. From the workspace navigation panel, select the workspace of interest; for example, **Inventory**.
- b. Click the view that contains the node or IP address that you want to verify is reachable; for example **Nodes**.
- c. From the table view, click the selection box in the row that represents the node or IP address.

To navigate to a map view and select a node:

- a. Navigate to the table view.
- b. From the table view, click the selection box in the row that represents the node or IP address.
- c. Select **Actions** → **Layer 2 Neighbor Views**, **Layer 3 Neighbor Views** or **Path View**.
- d. In the map, click the map symbol representing the node of interest.

To navigate to a form:

- a. From a table view, click the  Open icon in the row that represents the node or IP address of interest.
- b. From a map view, click the node of interest on the map and click the  Open icon.

2. Select **Actions** → **Ping (from server)**

NNMi displays the ping results, including reply times and ping statistics.

Find the Route (traceroute)

When investigating and diagnosing network problems, you might want to trace the route path using the traceroute command. Using traceroute also lets you identify bottlenecks along the destination path provided. You can access the traceroute command from the NNMi console Actions menu.

Note: You can also use Path View to display the routing path between two nodes that have IPv4 addresses. See ["Path Between Two Nodes that Have IPv4 Addresses" \(on page 113\)](#) for more information.

Note: The starting node is the NNMi management server on which you are running the trace route command.

To access the trace route command:

1. From an incidents view, select the incident whose source node on which you want to use trace route.
Or from a nodes view, select the node on which you want to use trace route.
2. Select **Actions** → **Trace Route (from server)**.

NNMi displays the output from trace route, including the lists of routers that are traversed to reach the destination node.



To navigate to a table view and select a node:

1. From the workspace navigation panel, select the workspace of interest; for example, **Inventory**.
2. Click the view that contains the node whose communication settings you want to check; for example **Nodes**.
3. From the table view, click the selection box that precedes the node whose configuration you want to check.

To navigate to a map view and select a node:

1. Navigate to the table view.
2. From a table view, click the selection box that precedes the node of interest.
3. Select **Actions**.
4. From the drop-down menu, select the map view of interest.
5. From the map view, click the node whose configuration you want to check.

To navigate to a form:

1. From the table view, click the  Open icon that precedes the node of interest.
2. From a map view, click the node of interest on the map and click the  Open icon.

Establish Contact with a Node (telnet)

When investigating and diagnosing network problems, you might need to establish a connection to a node to view or change configuration information. You can establish a connection to a node using the telnet command from the NNMi console Actions menu.

Note: To access telnet from Microsoft Internet Explorer, you must first tune the FEATURE_DISABLE_TELNET_PROTOCOL registry entry as described in: <http://msdn2.microsoft.com/en-us/library/ms537169.aspx>. More specifically, you will want to add the following registry key: [HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Internet Explorer\Main\FeatureControl\FEATURE_DISABLE_TELNET_PROTOCOL] to have the value: "iexplore.exe"=dword:00000000. HP recommends that you back up your registry before making any changes. For information about how to back up and edit your registry, see the Microsoft Knowledge Base article at <http://support.microsoft.com/kb/322756>.

To establish contact with a node using telnet:

From an incident view:

1. Click the selection box that precedes the incident whose source node you want telnet.
2. Select **Actions** → **Telnet (from client)**.

Note: NNMi telnets the source node of the incident. It does not telnet the source object. For example, if the incident is related to an interface, NNMi telnets to the node on which the interface resides, not to the interface itself.

From other views or forms:

1. Navigate to the view or form of interest and select the node to which you want to telnet.



To navigate to a table view and select a node:

- a. From the workspace navigation panel, select the workspace of interest; for example, **Inventory**.
- b. Click the view that contains the node whose communication settings you want to check; for example **Nodes**.
- c. From the table view, click the selection box that precedes the node whose configuration you want to check.

To navigate to a map view and select a node:

- a. Navigate to the table view.
- b. From a table view, click the selection box that precedes the node of interest.
- c. Select **Actions**.
- d. From the drop-down menu, select the map view of interest.
- e. From the map view, click the node whose configuration you want to check.

To navigate to a form:

- a. From a table view, click the  Open icon that precedes the node of interest.
 - b. From a map view, click the node of interest on the map and click the  Open icon.
2. Select **Actions** → **Telnet (from client)**.

NNMi displays a browser window and a telnet window.

Check Status Details for a Node Group

When diagnosing and troubleshooting problems, you might want to check the status for only a particular set of nodes. Your network administrator is able to group sets of nodes into Node Groups. An example Node Group could be all important Cisco routers, or all routers in a particular building. See [About Node and Interface Groups](#) for more information about how your administrator sets up Node Groups. See [Filter by Node or Interface Group](#) for more information about filtering views using Node Groups.

You can view Node Group status information using the Nodes Group View or Node Group Map view. See "[Node Groups View \(Inventory\)](#)" (on page 23) or "[Node Groups View \(Monitoring\)](#)" (on page 125) as well as "[Node Group Maps](#)" (on page 98) for more information. When you want more details about the number of nodes that have a particular status within the Node Group, use the **Actions** menu.

Note: The Status Details window automatically refreshes Status Detail information every 5 minutes.

To check the status details for a Node Group using a table view:

1. Navigate to the Node Groups view of interest. For example, select **Monitoring** → **Node Groups**.
2. Click the selection box that precedes the Node Group of interest.
3. Select **Actions** → **Status Details**.

For the Node Group selected, NNMi shows the following information:

- Node Group name
- Overall Node Group status
- Number of nodes in the group with each possible status
- Percentage of nodes in the group with each possible status

To check the status details for a Node Group using a map view:

1. From the workspace navigation panel, select the **Inventory** or **Monitoring** workspace.
2. Select **Node Groups**.
3. In the Node Group view, click the selection box that precedes the Node Group of interest.
4. Select **Actions** → **Node Group Map**.

See [About Map Status](#) for more information about status colors.

Checking the Status of NNMi

To confirm that NNMi is running properly, check NNMi status. If one or more of the NNMi processes or services are not running, contact your NNMi administrator to have the process or service restarted.

To check the health of NNMi:

1. From the NNMi console, select **Tools** → **NNM Status**.

NNMi displays a list showing the status of each process and service.

Each process and service should be running. If one is not, contact your NNMi administrator.

You can also check the health of the State Poller.

To check the health of the State Poller:

1. From the NNMi console, select **Help** → **About HP Network Node Manager i-series**.

NNMi displays the status of the State Poller as well as State Poller collection and queue information.

Appendix A. Glossary Terms

A

Anycast Rendezvous Point IP Address

Rendezvous Point addresses are loopback addresses used for routers in multi-cast network configurations

L

Layer 2

Refers to the Data Link layer of the multilayered communication model, Open Systems Interconnection (OSI). The Data Link layer moves data across the physical links in the network. The switches and bridges are devices that redirect data messages at the layer 2 level, using the destination Media Access Control (MAC) address to determine where to direct the message.

Layer 3

Refers to the Network layer of the multilayered communication model, Open Systems Interconnection (OSI). The Network layer is concerned with knowing the address of the neighboring nodes in the network, selecting routes and quality of service, and recognizing and

forwarding incoming messages to local host domains. The router and switch-router are the devices that redirect data messages at the Layer 3 level. Everything in a subnet is connected at the Layer 3 (IP) level.

Link Aggregation

A Link Aggregation is comprised of an Aggregator Link, Aggregator Interface, and the physical interfaces and connections that they represent. An Aggregator Link object represents many-to-many physical connections. For example, two nodes might be connected with four physical connections. These four physical connections are depicted as a single Aggregator Link object using a thick line on the Layer 2 Neighbor View map. The interface depicted at each end of the Aggregator Link object is an Aggregator Interface object. An Aggregator Interface object represents the collection of physical interfaces for one end of an Aggregator Link.

loopback address

The address associated with the loopback interface. The loopback interface is a virtual interface on a device that provides a route for internal communication. Many vendors

provide a specially configured loopback for management purposes. Exact details of how loopbacks are configured varies by vendor and model. See each device's documentation for details. NNM identifies these loopback addresses by using IfType 24, softwareloopback from the IANA ifType-MIB.

Appendix B: Index**A**

abnormal network behavior, troubleshooting	12
accessing	
device details	26, 54
node details	127
old NNM features	13
Path View	113
performance data	116
problem devices	127
related	
incidents	128
traceroute command	192
Actions menu	
accessing	
maps	98-99, 146, 194
performance data	116
investigating devices	127
monitoring configuration settings	166
Path View	113
running diagnostics	44-45, 140
troubleshooting network problems	103, 110, 165
unassigning incidents	143
updating lifecycle states	145
active paths	114
adding	
maps	102
node	
capabilities	36
subnet notes	112
Additional Filters tab	89, 95
Additional Node form	90
Additional Nodes tab	89

Address Disabled	169
Address Not Responding	170
addresses	
configuration settings	166
customizing views	23
disabled	169
identifying non-responsive	122
not	
responding	170
polling policy	72, 78
administrative states	123
Advanced, NNMi	
Aggregator Interface Degraded	170
Aggregator Interface Down	171
Aggregator Link Degraded	172
Aggregator Link Down	172
enhanced Path View	116
interface capabilities	65
Interface form	63, 70
Layer 2 Connection form	108
Management Stations view	24
Multiple Primary Device	185
Multiple Secondary Device	185
No Primary Device	184
No Secondary Device	185
node capabilities	34
Primary Device	184
RAMS	113
Router Redundancy Group	
form	79, 83-84
view	22
Router Redundancy Group Degraded	185
Router Redundancy Member form	80, 82
Service Impact incidents	183
Tracked Objects form	82

Index: agents, SNMP – Capabilities tab

Virtual IP Addresses form	84	Lifecycle State	144
agents, SNMP		Management Stations form	96
not responding	182	Node Capability form	36
Aggregator Interface Degraded incidents	170	Node Component form	38, 40, 42-44
Aggregator Interface Down incidents	171	Node Custom Attributes form	37
Aggregator Link Degraded incidents	172	Node Device Filter form	88
Aggregator Link Down incidents	172	Node Diagnostic Results form	45
alerts, network	168	Node form	27, 32-33, 37-38, 44, 46-48
annotating information	12	Node Group form	87-89, 92
Assigned To lookup field	143	Node Group Hierarchy form	91
assigning		nodes	189
incidents	142-143	Port form	86
attached switch ports, finding	190	RCA Active	144
attribute values		Router Redundancy Group form	78-79
Additional Node form	90	Router Redundancy Member form	80, 82
device		SNMP Agent form	49, 52-53
author	57	Tracked Objects form	82
category	57	Virtual IPAddresses form	84
family	56	VLAN form	85
profile	54	attributes	
vendor	56	IP addresses	23
Find Attached Switch Port	190	Notes	144
Health Attribute form	41	Author form	57
IfType Filter form	95		
IfTypes form	95	B	
Incident Diagnostic Results form	140	broadcast domain, reduced	19
Incident form	132, 134, 138, 140-141	Buffer has Insufficient Capacity or is Malfunctioning incident	173
incidents	139		
Interface Capability form	67	C	
Interface Custom Attributes form	68	calculation rules, Path View	114
Interface form	58, 61-63, 65, 68-72	capabilities	
Interface Group form	93-94	interface	65
IP Address form	72, 74-75, 78	node	34
IP Subnet form	112	Capabilities tab	
Layer 2 Connection form	105-108, 110	Interface form	65
		Node form	33-34

categories		Node Component form	44
devices	57	Node form	48
incidents	154, 162	SNMP Agent form	52
Causal Engine	147, 158, 165, 168, 178	configuration	
causes, root		monitoring settings	166
connectivity problems	103, 110	verifying device	165
incident		configuring	
messages	168	device profiles	54
views	151, 156, 158-159	connecting to nodes	193
checking		connection	
NNMi status	196	mesh	103
node group status details	194	Connection Down incident	173
Child Node Group		Connection Partially Unresponsive incident	174
attribute	91	connectivity	
displaying	99	troubleshooting problems	103, 110
Child Node Groups tab	91	viewing network maps	97
CIAs	139	Correlated Children tab	138
Cisco		Correlated Parents tab	138
protocols	116	Correlation Nature attribute	183
routers	15	CPU Utilization is Too High incident	175
Closed Key Incidents view	156	creating	
colors		attributes	
device connections	97	Author	57
status	126	Device Category	57
commands		Device Family	56
ping	191	Device Vendor	56
traceroute	116, 192	criteria	
Component Health		node down	178
tab	38	Critical Interfaces view	118
components		Critical Nodes view	119
Causal Engine	147, 158, 165, 168	Critical status	118, 170-172, 181
Conclusions tab		custom attributes	
Interface form	71	for nodes	37
IP Address form	75	Custom Attributes tab	138
Layer 2 Connection form	108	Interface form	68

Index: Custom Incident Attributes – displaying

Node form	37	categories	15, 20
Custom Incident Attributes	139	connections	103
Custom Incidents view	147, 161	families	56
Custom Interfaces view	22	identifying	113, 126
Custom IP Addresses view	23	managed	26
Custom Nodes view	21	profiles	54
customer network	116	types	54
customizing views		verifying	
nodes	21	configuration details	165
		status	168
		VLANs	19
		diagnosing network problems	165
		diagnostic results, node	45
		Diagnostics tab	44-45, 140
		diagrams, flow	113
		disabled	
		address	169
		interface	176
		discard rate incidents	188
		discovering networks	14
		updating information	165
		Discovery, Spiral	54
		displaying	
		incidents	128, 146
		key incidents closed	156
		Layer 2 connectivity	103
		Layer 3 connectivity	110
		network connectivity maps	97
		Network Infrastructure Devices Overview map	101
		Node Group map	98-99
		Node Group Overview map	100
		paths between nodes	113
		root cause incidents	158-159
		category	154
		closed	156
D			
database			
deleting objects	15		
determining SNMP Agent attributes	49, 52-53		
SNMP trap limit	181		
defining			
interface groups	93		
degraded aggregator			
interface	170		
link	172		
deleting			
abnormal network behavior	12		
maps	102		
nodes	15		
detecting abnormal network behavior	12		
determining			
problem scopes	127		
Device Category form	57		
Device Family form	56		
Device Filters tab	88		
Device Profile form	54		
Device Vendor form	56		
devices			
accessing problem	127		
active path	114		

Index: General tab – identifying

Device Profile	54	groups	
Device Vendor	56	defining	
Health Attribute	41	interface	93
IfType Filter	95		H
IfTypes	95	Health Attribute	
Incident	132, 134, 138, 140-141, 170-172	form	41
Incident Diagnostic Results	140	tab	40
Interface	58, 61-63, 65, 68-72	health, component	38
Interface Capability	67	health, network	
Interface Custom Attributes	68	verifying	196
Interface Group	93-95	historical information	12
IP Address	72, 74-75, 78	HSRP	
IP Subnet	112	nodes	116
Layer 2 Connection	105-108, 110		I
Management Stations	96	ICMP	
navigating	165, 191-193	displaying root cause incidents	158
Node	27, 32-34, 37-38, 44, 46-48	incidents	147
Node Capability	36	ping command	170
Node Component	38, 40, 42-44	icons	
Node Custom Attributes	37	Interface form	69
Node Device Filter	88	node status	43
Node Diagnostic Results	45	severity	130
Node Group	87-89, 91-92	identifying	
Node Group Hierarchy	91	critical nodes	119
Port	86	devices	113
Router Redundancy Group	78-79, 83-84	interface performance	125
Router Redundancy Member	80, 82	IP addresses	17, 23, 124
SNMP Agent	49, 52-53	networks	
Tracked Objects	82	interfaces managed by NNMI	16
updating lifecycle state	145	management domain	18
Virtual IPAddresses	84	nodes	
VLAN	85	by status	122
	G	managed	15
General tab	32, 61, 134	non-normal	
Global Load Balancing, Cisco	116	interfaces	120

nodes	120	key views	148
non-responsive addresses	122	lifecycle	144-145
IfType Filter		monitoring	130
form	95	No Primary Device in Router Redundancy Group	184
tab	94	No Secondary Device in Router Redundancy Group	185
IfTypes		Node Down	178
form	95	Node or Connection Down	180
important nodes		Non-SNMP Node Unresponsive	181
critical status	174, 178	Number of SNMP Traps Persisted in the Database has Reached or Exceeded	
Incident Diagnostic Results form	140	open	148
Incident form	132, 134, 138, 140-141, 170-172	open root cause	159
incidents		organizing	131
Address Not Responding	170	owning	142
Aggregator Interface Degraded	170	Power Supply is Malfunctioning	182
Aggregator Interface Down	171	Service Impact	183
Aggregator Link Degraded	172	SNMP Agent Not Responding	182
Aggregator Link Down	172	Temperature Sensor is Out of Range	182
assigning	142-143	threshold	185
attributes	139	tracking	
Buffer has Insufficient Capacity or is Malfunctioning ¹		progress	145
Connection Down	173	troubleshooting	132, 134, 138, 140-141, 160, 168
Connection Partially Unresponsive	174	unassigning	143
CPU Utilization is Too High	175	updating	144
displaying		views	147
map	146	categories	154
Fan is Malfunctioning	175	custom	161
input and output		families	155
discard rate	188	lifecycle state	157
error rate	187	management stations	24
utilization	186	NNM 6.x/7.x events	162
Interface Disabled	176	priorities	153
Interface Down	175	related	128
Interface Unmanageable	177	root cause	158
key	149	router redundancy group	22

Index: Incidents by Family view – Interfaces by Operational State view

severities	151	status	16
SNMP traps	162	viewing	
Voltage is Out of Range	183	all	16
Incidents by Family view	161	non-normal	120
Incidents tab		Interface by Administrative State view	123
Interface form	70	Interface by IfType view	20
IP Address form	74	Interface Capability form	67
Layer 2 Connection form	106	Interface Custom Attributes form	68
Node Component form	42	Interface Disabled incident	176
Node form	46	Interface Down incident	175
Router Redundancy Group form	84	Interface form	58
SNMP Agent form	53	Capabilities tab	65
input		Conclusions tab	71
discard rate	69, 188	Custom Attributes tab	68
error rate	69, 187	General tab	61
utilization	69, 186	Incidents tab	70
insufficient		Interface Groups tab	68
buffer capacity	173	IP Addresses tab	62
memory	178	Link Aggregation tab	63
interface		Performance tab	69
configuration settings	166	Registration tab	72
customizing views	22	Status tab	70
disabled	169	VLAN Ports tab	63
filtering		Interface Group	
administrative states	123	form	93-95
operational states	123	view	24
status	123	interface groups	
identifying non-normal	120	defining	93
monitoring		filters	15, 24
views	118	viewing	
notes	16	details	24
out-of-box		Interface Groups tab	68
capabilities	65	Interface Performance view	125
performance states	69	Interface Unmanageable incident	177
polling policy	58	Interfaces by Operational State view	123

Interfaces by Status view	123	iSPis	
Interfaces tab		NNM iSPI for Performance	
Layer 2 Connection form	106	configuration monitoring	166
Node form	32	Health Attribute form	41
Interfaces view	16	incidents	185-188
interpreting threshold incidents	185	interfaces	24, 93, 125
inventory		nodes	23, 38, 87
network	14	performance issues	116
Inventory workspace		K	
Interfaces view	16	Key Incident views	148
Layer 2 Connections view	19	key incidents, viewing	149, 151, 153-156
Management Stations view	13	L	
Nodes view	15	LANs, virtual	19, 85
investigating		Layer 2 Connection form	105
network problems	165	Conclusions tab	108
IP Address form	72, 78	Incidents tab	106
Conclusions tab	75	Interfaces tab	106
Incidents tab	74	Link Aggregation tab	108
Status tab	74	Registration tab	110
IP Addresses		Status tab	107
tab	62	Layer 2 Connections view	19
IP Addresses by State view	124	Layer 2 Neighbors view	97, 103
IP Addresses tab		Layer 3 Neighbors view	97, 110
IP Subnet form	112	Layer 3 networks	101
Node form	32	Level 1 Operator role	143
IP Addresses view	17	Level 2 Operator role	143
IP Subnet form	112	lifecycle, incidents	144-145, 157
IP Addresses tab	112	limits	
Registration tab	112	Path View	116
IP Subnets view	18	SNMP traps in database	181
ipRoute tables	116	Link Aggregation tab	
IPv4 addresses	113	Interface form	63
Island Node Group	87, 146	Layer 2 Connection form	108
isolating abnormal network behavior	12	local area networks, virtual	85
		logical networks	19

Index: MAC-based VLANs – network

M			
MAC-based VLANs	19	Routers	102
malfunctioning		Switches	102
buffer	173	Maps	
fan	175	Island Node Group	146
memory	178	memory, insufficient or malfunctioning	178
power supply	182	mesh connection	103
managed device, viewing details	26	messages, incidents	
management mode		root causes	168
interface	58	monitoring	
IP addresses	72	configuration settings	166
nodes	27	devices	20
management network	116	incidents	130
Management Stations		interface	
form	96	administrative states	123
view	13, 24	operational states	123
managing		network	
incident assignments	142	problems	118, 126, 130
map objects, viewing details	127	node groups	125
map views		Multiple Secondary Devices in Router Redundancy Group root cause message	
checking node group	194	multiple	
determining problem scopes	127	VLANs	19
Device Profiles	54	Multiple Primary Devices in Router Redundancy Group root cause message1	
incidents	146	My Open Incidents view	142, 148
monitoring network problems	126	N	
navigating	165, 168, 191-193	navigating	
network connectivity	97, 113	forms	165, 191-193
node groups	126	map views	165, 168, 191-193
status colors	126, 168	maps	99
viewing object details	26	table views	165, 168, 191-193
maps		neighborhood view maps	97
Network Infrastructure Devices Overview	101	network	
Network Overview	101	abnormal behavior	12
Node Group	98-100	alerts	168
Node Group Overview	100	connectivity maps	97
		customer	116

Index: Network Infrastructure Devices Overview map – Node form

discovering	14	Management Stations view	24
identifying issues	126	Multiple Primary Devices	185
interfaces	16	Multiple Secondary Devices	185
inventory	14	No Primary Devices	184
investigating problems	165	No Secondary Device	185
management	116	node capabilities	34
monitoring		Primary Device	184
health	196	RAMS	113
problems	118	Router Redundancy Group Degraded	185
protocol design	97	Router Redundancy Group form	79, 83-84
Network Infrastructure Devices Overview map	101	Router Redundancy Group view	22
Network Overview map	101	Router Redundancy Member form	80, 82
NNM iSPI for Performance	125	Service Impact incidents	183
configuration monitoring	166	Tracked Objects form	82
Health Attribute form	41	Virtual IP Addresses form	84
incidents	185-188	checking status	196
interfaces	24, 93, 125	using	12
nodes	23, 38, 87	No Primary Device in Router Redundancy Group incident	184
performance issues	116	No Secondary Device in Router Redundancy Group incident	185
NNMi		Node Capability form	36
6.x/7.x		Node Component configuration settings	166
Events by Category view	162	Node Component form	38
Events view	162	Conclusions tab	44
features	13	Health Attributea tab	40
viewing incidents	147	Incidents tab	42
viewing remote management stations	96	Status tab	43
Advanced		Node Custom Attributes form	37
Aggregator Interface Degraded	170	Node Device Filter form	88
Aggregator Interface Down	171	Node Diagnostic Results form	45
Aggregator Link Degraded incidents	172	Node Down incident	178
Aggregator Link Down	172	Node form	27, 32
enhanced Path View	116	Capabilities tab	33-34
interface capabilities	65	Component Health tab	38
Interface form	63, 70	Conclusions tab	48
Layer 2 Connection form	108		

Index: Node Group – Nortel

Custom Attributes tab	37	displaying	
Diagnostics tab	44	paths between	113
Incidents tab	46	errors	116
Interfaces tab	32	filtering	
IP Addresses tab	32	status	122
Node Groups tab	38	finding	189
Ports tab	33	HSRP	116
Registration tab	48	identifying	
Status tab	47	critical	119
VLAN Ports tab	33	non-normal	120
Node Group		Layer 2 connectivity	103
form	87-89, 91-92	Layer 3 connectivity	110
Node Group Hierarchy form	91	monitoring	
Node Group map	98	views	118
displaying	99	notes	15
positioning nodes	100	out-of-box	
Node Group Overview Map	100	capabilities	34
node groups		polling policy	49, 52-53, 165, 168
checking status	194	saving map locations	100
filters	15, 23, 131	selecting	192
maps	126	status	15
monitoring	125	testing whether reachable	191
viewing		unresponsive	181
details	23	updating status	168
Node Groups		views	15, 119
tab	38	VRRP	116
view	23, 125	Nodes by Device Category view	20
Node or Connection Down incident	180	Nodes by Status view	122
nodes		Nodes view	15
accessing details	127	Non-Normal Interfaces view	120
attributes	189	Non-Normal Nodes view	120
configuration settings	166	Non-Normal Router Redundancy Group view	121
connecting to	193	Non-SNMP Node Unresponsive incidents	181
customizing views	21	Nortel	
device category	15	private interface	20, 22, 58

SNMP interfaces	16	views	14, 118, 147-148
Not Responding Address view	122	out of range	
notes		temperature sensor	182
interfaces	16	voltage	183
nodes	15	output	
subnets	112	discard rate	69, 188
Notes attribute	144	error rate	69, 187
Number of SNMP Traps Persisted in the Database has		utilization	69, 186
		owning incidents	142
	O		P
objects		parent node group	91
viewing		Path View	113
device details	26	calculation rules	114
incidents	128	enhanced	116
node details	127	limitations	116
open incidents	148	performance issues	116
Open Key Incidents by Category view	154	paths	
Open Key Incidents by Family view	155	displaying between nodes	113
Open Key Incidents by Priority view	153	finding route	192
Open Key Incidents by Severity view	151	performance	
Open Key Incidents view	149	interface	125
open root cause incidents	159	Path View issues	116
Open Shortest Path First protocol	116	states	69
Open Systems Interconnection model	97	Performance tab	69
operational states	123	ping command	170, 191
operator		polling policy	
roles		address	72, 78
Level 1	143	interface	58
Level 2	143	node	49, 52-53, 165, 168
organizing incidents	131	Port form	86
OSI model	97	ports	
out-of-box		details	86
interface		finding attached switch	190
capabilities	65	trunk	85
node			
capabilities	34		

Index: Ports tab – root causes

Ports tab		RCA messages	
Node form	33	Failover in Router Redundancy Group	184
VLAN form	85	Multiple Primary Device in Router Redundancy Group	185
position nodes on group map	100	Multiple Secondary Devices in Router Redundancy Group	185
Power Supply is Malfunctioning incident	182	No Primary Device in Router Redundancy Group	184
priority, open root cause	153	No Secondary Device in Router Redundancy Group	185
problems		Router Redundancy Group Degraded	185
accessing devices	127	Registration tab	141
determining scope	127	Interface form	72
incidents	130, 160	IP Subnet form	112
interface	103	Layer 2 Connection form	110
investigating network	165	Node form	48
monitoring network	118	SNMP Agent form	53
node down	178	related incidents, displaying	128
root cause		reporting performance	116
messages	168	resolved root cause incidents	156
views	158	results	
subnets	110	Path View	114
profiles, device	54	roles	
progress		operator	
incident	145	Level 1	143
protocols		Level 2	143
network	97	updating incidents	132
router	116	Root Cause Incidents view	158-159
VLAN	19	root cause messages	
pseudo interfaces	22	Failover in Router Redundancy Group	184
		Multiple Primary Devices in Router Redundancy Group	185
		Multiple Secondary Devices in Router Redundancy Group	185
		No Primary Device in Router Redundancy Group	184
		No Secondary Device in Router Redundancy Group	185
		Router Redundancy Group Degraded	185
		root causes	
		connectivity problems	103, 110
		incident	
		messages	168
Q			
Quick Filter	20, 122-124, 151, 154-155, 157		
Quick View	26, 127		
R			
RAMS data and Path View	116		
ranges			
temperature sensor	182		
voltage	183		
RCA Active attribute	144		

views	147, 151, 153-159	values	32, 61
route path, finding	192	SNMP Agent form	49
Router Redundancy Group		Conclusions tab	52
form	78-79, 83-84	Incidents tab	53
root cause message	184	Registration tab	53
view	22, 121	Status tab	52
Router Redundancy Group Degraded incident	185	SNMP Agent Not Responding incident	182
Router Redundancy Member		SNMP ipRoute tables	116
configuration settings	166	SNMP Traps by Family view	163
form	80, 82	SNMP Traps view	162
tab	79	sorting	
routers		incidents	131
Cisco	15	IP addresses	23
identifying issues	126	Spiral Discovery	54
monitoring	114	State Poller	
protocols	116	checking health	196
subnet	110	service	54
Routers		states	
map	102	administrative	123
rules, path calculation	114	operational	123
		performance	69
	S	status	
saving map layouts	100	colors	126
selecting		filtering interface	123
nodes	192	node groups	92
sensor, temperature	182	nodes	122
Service Impact incidents	183	verifying	
services		device	168
State Poller	54	NNMi	196
severity, incident	130, 151	node groups	194
SNMP		Status tab	92
displaying traps	158, 162-163	Interface form	70
incidents	147	IP Address form	74
interfaces	16	Layer 2 Connection form	107
traps	181	Node Component form	43
unresponsive non-SNMP node	181		

Index: Stream Correlation Incidents view – track priority

Node form	47	Custom Attributes	37, 68, 138
SNMP Agent form	52	Device Filters	88
Stream Correlation Incidents view	160	Diagnostics	44-45, 140
subnet		General	32, 61, 134
adding notes	112	Health Attribute	40
details	112	IfType Filters	94
naming	112	Incidents	42, 46, 53, 70, 74, 84, 106
routers	110	Interface Groups	68
view	18	Interfaces	32, 106
viewing details	112	IP Addresses	32, 62, 112
switch		Link Aggregation	63, 108
connectivity between devices	103	Node Groups	38
finding attached port	190	Performance	69
monitoring	114	Ports	33, 85
routers	110	Registration	48, 53, 72, 110, 112, 141
Switches map	102	Router Redundancy Members	79
		Status	43, 47, 52, 70, 74, 92, 107
		Tracked Objects	82
		Virtual IPAddresses	83
		VLAN Ports	63
		VLANs	86
		tasks	
		assigning incidents	142
		incident view	130
		troubleshooting	12
		telnet	193
		Temperature Sensor is Out of Range incident	182
		testing nodes	191
		threshold	
		incidents	185
		tools menu	165
		Topology Maps workspace	100-102
		Topology Source	19
		traceroute command	116, 192
		track priority	82
T			
table views			
capabilities added to node object	34		
checking node groups	194		
monitoring	118		
navigating	165, 168, 191-193		
Path View	113		
types	14		
viewing object details	26		
tables, SNMP ipRoute	116		
tabs			
Additional Filters	89, 95		
Additional Nodes	89		
Capabilities	33-34, 65		
Child Node Groups	91		
Component Health	38		
Conclusions	44, 48, 52, 71, 75, 108		
Correlated Children	138		
Correlated Parents	138		

Tracked Objects		lifecycle states	145
form	82	node status	168
monitoring configuration	166	utilization	
tab	82	CPU	175
tracking		incidents	186
incidents			
progress	145	V	
traps, SNMP		varbind values	139
displaying	162-163	vendor devices	
troubleshooting		defining	56
abnormal network behavior	12	verifying	
connectivity problems	103, 110	device	
determining problem scopes	127	configuration details	165
devices	20	status	168
incidents	130, 132, 134, 138, 140-141, 160	network health	196
interface	58, 61-63, 68-71	viewing	
IP addresses	72, 74-75, 78	incidents	128, 139
network		interface group	
alerts	168	details	24
problems	118, 165	managed device details	26
node groups	194	network connectivity maps	97
nodes	27, 32-33, 38, 40-48, 178	node details	127
Troubleshooting workspace	103, 110, 113	node group	
trunk ports	85	details	23
		views	
U		Closed Key Incidents	156
Unassigned Key Incidents view	151	Critical Interfaces	118
Unassigned Vital Incidents view	142-143	Critical Nodes	119
unassigning incidents	143	Custom Incidents	147, 161
unmanageable interface	177	Custom Interfaces	22
unresponsive		Custom IP Addresses	23
incident	174	Custom Nodes	21
nodes	181	filtering	15, 122
updating		device categories	20
discovery information	165	interface types	20
incidents	144-145	Incidents by Family	161

Index: Virtual IPAddresses – workspaces

Interface by Administrative State	123	SNMP Traps by Family	163
Interface by IfType	20	Stream Correlation Incidents	160
Interface Group	24	types	14
InterfacePerformance	125	Unassigned Key Incidents	151
interfaces	16	Unassigned Vital Incidents	142-143
Interfaces by Operational State	123	updating lifecycle state	145
Interfaces by Status	123	Vital Incidents by Lifecycle State	157
IP Addresses	17	VLANs	19
IP Addresses by State	124	Virtual IPAddresses	
IP Subnets	18	form	84
Key Incident	148	tab	83
Layer 2 Connections	19	virtual LANs	19, 85
Layer 2 Neighbors	103	Vital Incidents by Lifecycle State view	157
Layer 3 Neighbors	110	VLAN	
Management Stations	24	form	85
My Open Incidents	142, 148	view	19
NNM 6.x/7.x Events	162	VLAN Ports tab	
NNM 6.x/7.x Events by Category	162	Interface form	63
Node Groups	23, 125	Node form	33
nodes	15	VLANs tab	
Nodes by Device Category	20	Port form	86
Nodes by Status	122	Voice-Over-IP	15
Non-Normal Interfaces	120	Voltage is Out of Range incident	183
Non-Normal Nodes	120	VRRP	
Non-Normal Router Redundancy	121	nodes	116
Not Responding Address	122	W	
Open Key Incidents	149	watching status colors	126
Open Key Incidents by Category	154	workspaces	
Open Key Incidents by Family	155	Topology Maps	100-102
Open Key Incidents by Priority	153		
Open Key Incidents by Severity	151		
out-of-box	14, 118, 147		
Root Cause Incidents	158-159		
Router Redundancy Group	22		
SNMP Traps	162		