

# HP OpenView GlancePlus Pak

## Installation Guide

Software Version: C.03.85

for HP-UX 11.0 and Beyond Systems



**Manufacturing Part Number: B3701-90036**

**June 2004**

© Copyright 2004 Hewlett-Packard Development Company, L.P.

## Legal Notices

### Warranty

*Hewlett-Packard makes no warranty of any kind with regard to this document, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. Hewlett-Packard shall not be held liable for errors contained herein or direct, indirect, special, incidental or consequential damages in connection with the furnishing, performance, or use of this material.*

A copy of the specific warranty terms applicable to your Hewlett-Packard product can be obtained from your local Sales and Service Office.

### Restricted Rights Legend

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause in DFARS 252.227-7013.

Hewlett-Packard Company  
United States of America

Rights for non-DOD U.S. Government Departments and Agencies are as set forth in FAR 52.227-19(c)(1,2).

### Copyright Notices

© Copyright 2004 Hewlett-Packard Development Company, L.P.

No part of this document may be copied, reproduced, or translated into another language without the prior written consent of Hewlett-Packard Company. The information contained in this material is subject to change without notice.

### Trademark Notices

UNIX® is a registered trademark of The Open Group.

Windows® and Windows NT® are U.S. registered trademarks of Microsoft Corporation.

Adobe® and Acrobat® are trademarks of Adobe Systems Incorporated.

Motif® is a registered trademark of the Open Software Foundation in the U.S. and other countries.

All other product names are the property of their respective trademark or service mark holders and are hereby acknowledged.

## Publication History

New editions are complete revisions of the manual. The publication dates for each edition are listed below.

Edition 1	04/99	B3701-90005
Edition 2	10/99	B3701-90007
Edition 3	07/00	B3701-90014
Edition 4	12/01	B3701-90022
Edition 5	06/02	B3701-90028
Edition 6	12/02	B3701-90031
Edition 7	06/04	B3701-90036

## Revisions

The version number on the title page of this document indicates software version. The print date on the title page changes each time this document is updated.

You will receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details. The following table indicates changes made to this document since the last released version.

### Changes in this Document Version

Chapter	Changes
Revisions and Support Prefaces	Added these prefaces.
<a href="#">Hardware on page 14</a>	Updated system and display requirements.
<a href="#">Software on page 15</a>	Updated the software requirements.

# Support

Please visit the HP OpenView web site at:

<http://openview.hp.com/>

There you will find contact information and details about the products, services, and support that HP OpenView offers.

You can go directly to the support web site at:

<http://support.openview.hp.com/>

The support web site includes:

- Downloadable documentation
- Troubleshooting information
- Patches and updates
- Problem reporting
- Training information
- Support program information

# contents

<b>Chapter 1</b>	<b>GlancePlus Pak Components</b> .....	7
	Introduction .....	7
	GlancePlus .....	8
	OV Performance Agent .....	10
<b>Chapter 2</b>	<b>Licensing</b> .....	11
	Introduction .....	11
	GlancePlus Pak Licensing Agreement .....	11
<b>Chapter 3</b>	<b>Installation Requirements</b> .....	13
	Introduction .....	13
	Hardware .....	14
	System Requirements .....	14
	Display Requirements .....	14
	Disk Requirements .....	14
	Software .....	15
<b>Chapter 4</b>	<b>Installing GlancePlus Pak</b> .....	17
	Introduction .....	17
	Installation Instructions .....	18
	Results of Installation .....	19
	Successful Installations .....	19
	Incomplete Installations .....	19
	Removing GlancePlus Pak .....	20
	Removing ITO-SE that Remained from a Previous GlancePlus Pak Version .....	21

<b>Chapter 5</b>	<b>Running the GlancePlus Components</b> .....	23
	Introduction .....	23
	Starting OV Performance Agent .....	24
	Starting GlancePlus .....	25
<b>Chapter 6</b>	<b>Checking GlancePlus Pak Status</b> .....	27
	Introduction .....	27
	Checking the Status of All Components .....	27
<b>Chapter 7</b>	<b>Documentation</b> .....	29
	Introduction .....	29
	Printable Files .....	30
	Release Notes .....	31
	Documentation on the Web .....	32
<b>Index</b> .....		33

# GlancePlus Pak Components

## Introduction

GlancePlus Pak combines products into one package:

- [GlancePlus](#)
- [OV Performance Agent](#)

Together, these two products offer node-level management capabilities that keep you informed of a system's performance and availability. The specific ways that these products help you manage a GlancePlus Pak-installed system are explained in the sections that follow.




HP OpenView IT/Operations Enterprise Edition (ITO-EE) has been renamed to HP OpenView Operations for UNIX (OVO).

# GlancePlus

GlancePlus is a powerful real-time system performance monitoring and diagnostic tool. It provides immediate performance information about your system. It lets you easily examine system activities, identify and resolve performance bottlenecks, and tune your system for more efficient operation. GlancePlus helps you be sure that your users are more productive and your business applications run more smoothly.

**Figure 1 GlancePlus Motif-mode interface**



There are two ways to access GlancePlus: **gpm**, a Motif®-based graphical interface and **glance**, a character mode interface. Both modes provide the same set of performance data.

The Motif®-based GlancePlus interface, **gpm**, provides graphs that immediately draw your attention to system activity. It allows you to:

- View the system performance graphs in easily understood formats. You can also look at multiple windows to get a more complete view of a problem.



- View alarms and dynamic system performance graphs within an icon so you can efficiently keep an eye on your system's performance while attending to other tasks.
- Configure the product to best suit your needs and work style.
- Graphically display the resource use of the allocations groups set up by HP Process Resource Management software on HP 9000 systems.
- Learn how to use the product quickly. You can start using the product and interpreting performance data without having to search through volumes of manuals. The award-winning online help system includes hyperlinks and context sensitive features. You can click on a window (On-window) or an item (On-item) to display information that is relevant to the area of the product you are using.

The GlancePlus character-mode interface, **glance**, shows GlancePlus data as ASCII text and involves less system overhead, but offers fast transmission over serial lines. It allows you to:

- Monitor the system remotely or when an X-terminal is not available.
- Monitor the system when memory resources are critical.
- Monitor performance over serial data communications.
- View alerts to potential problems with real-time performance metric alarms.

## OV Performance Agent

OpenView Performance Agent gathers a system's resource and performance data into log files. It time stamps the data, summarizes it, and uses it to detect alarm conditions. The data and alarm information available through OpenView Performance Agent can also be easily used by other products (such as OpenView Performance Manager for UNIX and OpenView Operations for UNIX) for analysis and problem detection.

Using OpenView Performance Agent, you can pinpoint trends in system activities, obtain information that enables you to balance work loads and accurately plan for future system growth. OpenView Performance Agent also allows you to integrate your system into an OpenView Operations- or OpenView Performance Manager-based framework for centralized management of your distributed environment.

OpenView Performance Agent can gather data on measured end-to-end response times for instrumented transactions as they are executed within the system. Using its data source integration (DSI) technology, you can configure OpenView Performance Agent to collect data from sources outside the system. OpenView Performance Agent data can be integrated into other products for analysis, problem detection, and alarming.

Specifically, OpenView Performance Agent lets you:

- Characterize the workloads in the environment and analyze resource use, allowing you to more effectively balance the system workloads.
- Perform trend analyses based on historical data to isolate and identify bottlenecks.
- Perform service-level management based on transaction response time and respond to error conditions.

# Licensing

## Introduction

This chapter briefly discusses the GlancePlus Pak licensing agreement. Please refer to the licensing terms and conditions for a more complete description of the licensing conditions.

## GlancePlus Pak Licensing Agreement

GlancePlus Pak is licensed to be installed and used on one system only.



# Installation Requirements

## Introduction

Before installing GlancePlus Pak, be sure that your system meets the minimum requirements for:

- [Hardware](#)
- [Software](#)

# Hardware

## System Requirements

- HP 9000 and Integrity Servers and HP Workstations
- 32 MB RAM, 64MB virtual memory

## Display Requirements

The following is required for running the GlancePlus Motif interface, `gpm` and character mode interface, `glance`:

- `gpm`: HP X-terminal or X-workstation display
- `glance`: any terminal supported by the curses library

## Disk Requirements

- 50 MB in the `/opt/perf/` directory for first-time installations of GlancePlus and OpenView Performance Agent
- 50 MB in the `/var/opt/perf/` directory for OpenView Performance Agent
- Total: 100 MB

## Software

- HP-UX 11.0 and beyond with X-Windows libraries X11R6 and Motif libraries 2.1
- System patch requirements: Refer to the product Release Notes in `/opt/perf/ReleaseNotes`.





# Installing GlancePlus Pak

## Introduction

Installing GlancePlus Pak addresses the following topics:

- [Installation Instructions](#)
- [Results of Installation](#)
- [Removing GlancePlus Pak](#)
- [Removing ITO-SE that Remained from a Previous GlancePlus Pak Version](#)

## Installation Instructions

Follow the steps below using the GlancePlus Pak source media. The installation should complete in 30 minutes or less. If you have a factory-integrated system with the software already installed, skip the steps and read “Running the Components” in this guide.

- 1 Log on to the system as `root`.
- 2 If you have previously installed GlancePlus Pak, GlancePlus, or OV Performance Agent:

- Run `perfstat` to check for active performance tools:

```
/opt/perf/bin/perfstat
```

- Ask anyone currently running `glance` or `gpm` to exit these programs.
- Stop OV Performance Agent (if running), all ARM-instrumented applications, and all performance tool daemons by entering:

```
/opt/perf/bin/mwa stop  
/opt/perf/bin/midaemon -T  
/opt/perf/bin/ttd -k
```

Before you stop `ttd`, be sure to close any ARM-instrumented applications as well. Otherwise, results in collecting transaction data are unpredictable.

- Run `perfstat` again to make sure all the performance tools have been stopped.

If this is a new installation of GlancePlus Pak:

- Verify you have a minimum of 83 MB of disk space in the directory `/opt/`. If you do not have this much space, create a new `<path>/perf` directory in a location where you do have the space. Symbolically link the directory to `/opt/perf/`.

- 3 Run `swinstall` as shown here. Change the source to point to your installation media and select the GlancePlus Pak Software bundle.

```
swinstall -s <hostname>:<depot_path> <product_bundle_ID>
```

## Results of Installation

The analysis phase of `swinstall` checks the following:

- operating system version
- disk space
- RAM and swap space
- kernel parameters

You can view the results in the logfile `/var/adm/sw/swagent.log`.

## Successful Installations

Installation of GlancePlus Pak automatically updates files used by `/etc/profile` and lets users access the product and its man pages without manually updating their shell environment variables. You need to log in again for the changes in `/etc/profile/` to become active. Most executable files reside in `/opt/perf/bin/`. The man pages reside in `/opt/perf/man/`.

## Incomplete Installations

If the installation does not complete successfully, the cause could be that system requirements are not being met or a performance tool (for example, OpenView Performance Agent) is still running when it should have been stopped. Check the `swinstall` log file `/var/adm/sw/swagent.log` for possible causes.

## Removing GlancePlus Pak

To remove GlancePlus Pak, you need to follow the procedure below.

1 Log on as root.

2 Run `perfstat` to check for active performance tools. Enter:

```
/opt/perf/bin/perfstat
```

If anyone is currently running `glance`, `gpm`, or any ARM-instrumented applications, ask them to exit these programs.

3 If OpenView Performance Agent is running, stop it and all performance tool daemons. Enter:

```
/opt/perf/bin/mwa stop
```

```
/opt/perf/bin/midaemon -T
```

```
/opt/perf/bin/ttd -k
```

If any ARM-instrumented applications are still running when you stop `ttd`, transaction data collection results are unpredictable.

4 Run `perfstat` again to make sure all the performance tools have been stopped.

5 Remove GlancePlus Pak. Enter:

```
swremove <file_ProductID>
```

If the system is an OV Operations for UNIX managed node, the OV Operations Agent will not be removed.

## Removing ITO-SE that Remained from a Previous GlancePlus Pak Version

You would only remove ITO-SE from GlancePlus Pak, if it remained on the machine from a previous GlancePlus Pak version (C.03.55 is the last version of GlancePlus Pak that contained ITO-SE).

To remove ITO-SE from GlancePlus Pak, follow the procedure below.

1 Log on as root.

2 Run `perfstat` to check if node is managed. Enter:

```
/opt/perf/bin/perfstat -v
```

- If the system is an OpenView Operations for UNIX managed node, the OpenView Operations (ITO) Agent will not be removed.
- If the system is running the OpenView Database Pak 2000 product, the script will not remove ITO-SE or the MeasureWare Integration Templates.

If you are updating GlancePlus Pak on an 11.0 system and the Database Pak is on the system, it relies on ITO-SE. Removing any of the ITO-SE components would remove reporting capabilities of the Database Pak Smart PlugIn.

3 Remove ITO-SE and MeasureWare Agent Integration Templates. Enter:

```
/opt/perf/bin/itose.remove
```



# Running the GlancePlus Components

## Introduction

After you have installed GlancePlus Pak, it will require manual intervention to start the OV Performance Agent data gathering and alarm activation. Start the agent with this command:

```
/opt/perf/bin/mwa start
```



If you updated the GlancePlus Pak to the June 2002 release, the functionality provided by ITO-SE and MeasureWare Integration templates within the GlancePlus Pak 2000 will no longer be supported by HP. If you had these two components on your system prior to updating to the June 2002 release, they will remain on your system. You can remove these components by following the procedures in [Removing ITO-SE that Remained from a Previous GlancePlus Pak Version](#) on page 21.

The sections that follow are sequenced according to how you should proceed.

- [Starting OV Performance Agent](#)
- [Starting GlancePlus](#)

## Starting OV Performance Agent

To allow you to customize its data collection in the `/var/opt/perf/parm` file and its alarm configuration in the `/var/opt/perf/alarmdef` file, OV Performance Agent does not start up automatically. Applications are defined in the `/var/opt/perf/parm` file.

To customize the `parm` file to suit the system use, refer to the *HP OpenView Performance Agent User's Manual*, Chapter 2, “Application Definition Parameters” for detailed instructions. To customize alarm definitions, see the *HP OpenView Performance Agent User's Manual*, Chapter 7, “Performance Alarms.”

You must start OV Performance Agent prior to starting ARM-instrumented applications to make sure the transaction data you collect is valid.

To start OV Performance Agent from the command line:

- 1 Open a terminal window as a root user.
- 2 Enter:

```
mwa start
```



# Starting GlancePlus

Before you can run the Motif interface of GlancePlus, the `DISPLAY` variable must be set on your workstation. To do this, enter one of the following commands, depending on your system:

- Korn Shell: `export DISPLAY=<workstation_ID>:0.0`
- C-Shell: `setenv DISPLAY <workstation_ID>:0.0`
- Bourne Shell: `DISPLAY=<workstation_ID>:0.0`

where `<workstation_ID>` is your workstation's identifier. `xhost` must also be set for the display to be accessible. See the `xhost` man page for more information.

To start GlancePlus from the command line:

- 1 Log onto the system where GlancePlus is installed
- 2 To start GlancePlus in the:
  - Motif interface, type: **gpm**
  - character mode interface, type: **glance**





# Checking GlancePlus Pak Status

## Introduction

You can check all or some components of the GlancePlus Pak by running **perfstat**.

## Checking the Status of All Components

Enter the command: **perfstat**

```
*****  
** perfstat for <system_name> on <day:month:date:hh:mm:ss:timezone:yyyy>  
*****
```

list of performance tool processes:

```
-----  
  
Running midaemon      (measurement interface daemon) pid 21703  
  
MeasureWare scope status:  
Running scopeux      (MWA data collector) pid 25954  
  
MeasureWare background daemon status:  
Running ttd          (Transaction Tracker daemon) pid 19254
```

## Checking GlancePlus Pak Status

MeasureWare server status:

```
Running alarmgen      (alarm generator) pid 26282
Running agdbserver    (alarm database server) pid 26281
Running perflbd       (location broker) pid 25962
```

The following data sources have running repository servers:

```
                PID  DATA SOURCE
Running rep_server  26278  SCOPE
```

\*\*\*\*\* (end of perfstat -p output) \*\*\*\*\*

**Note that if ITO-SE or the OVO agent is still on your system, perfstat will report status on that agent.**

**The output appears as follows:**

```
*****
** perfstat for <system_name> on <day:month:date:hh:mm:ss:timezone:yyyy>
*****
list of performance tool processes:
-----
Running midaemon (measurement interface daemon) pid 19091
PerfView status:
  Running rpcd/dced (DCE Host daemon) pid 1024
  Running pvalarmd  (PerfView alarm manager daemon) pid 511
MeasureWare scope status:
  Running scopeux   (MWA data collector) pid 19093
MeasureWare background daemon status:
  Running ttd       (Transaction Tracker daemon) pid 19071
MeasureWare server status:
  Running alarmgen  (alarm generator) pid 18350
  Running agdbserver (alarm database server) pid 18349
  Running perflbd   (location broker) pid 18338
The following data sources have running repository servers:
                PID  DATA SOURCE
Running rep_server  18348  SCOPE
Lightweight Performance status:
  Running coda      (data collector) pid 9775

Operations Agent Status:
  Running opcctla   (Control Agent) pid 6457
  Running opcmsga   (Message Agent) pid 15163
Subagent 1:
  Running opcacta   (Action Agent) pid 15164
  Running opcle     (Logfile Encapsulator) pid 15165
  Running opcmona   (Monitor Agent) pid 15166
  Running opcmsgi   (Message Interceptor) pid 15167
***** (end of perfstat -p output) *****
```

# Documentation

## Introduction

In addition to printed manuals for its integrated products, GlancePlus Pak also includes:

- [Printable Files](#)
- [Release Notes](#)
- [Documentation on the Web](#)

## Printable Files

The printable files are in two different formats: Adobe Acrobat“ (\*.pdf) and ASCII text file. The printable files are installed in the following directories:

/opt/perf/paperdocs/gpak/C/ – for GlancePlus Pak

/opt/perf/paperdocs/mwa/C/ – for OpenView Performance Agent

/opt/perf/paperdocs/gp/C/ – for GlancePlus



The GlancePlus Pak Interoperability Guide (gpp-supplement.pdf) will no longer be produced beginning with this release. If you plan to continue using ITO-SE, and need this manual, you can access it as an archived version from the web. See [Documentation on the Web on page 32](#) for more information.

## Release Notes

Release Notes for GlancePlus Pak components are installed in the following directory:

```
/opt/perf/ReleaseNotes/
```

Refer to the product Release Notes as well as the *HP OpenView Performance Agent Installation & Configuration Guide* and the *GlancePlus Installation Guide* for more information about documentation.

## Documentation on the Web

You can view, download, and print the Adobe Acrobat format (\*.pdf) documents from the HP OpenView Manuals web site at:

[http://ovweb.external.hp.com/lpe/doc\\_serv/](http://ovweb.external.hp.com/lpe/doc_serv/)

Select glanceplus pak from the product list box, select the release version (which automatically selects the appropriate OS), and click [**Open**] to view the document online, or click [**Download**] to place the file on your computer.



# index

## A

alarmdef file, **24**

## D

directories

for printable files, **30**

disk space requirements, **14**

display requirements, **14**

DISPLAY variable

setting for GlancePlus, **25**

documentation

on the web, **32**

printablefiles, **30**

release notes, **31**

## F

files

alarmdef, **24**

automatic update of profile, **19**

executable, **19**

man pages, **19**

parm, **24**

printable, **30**

## G

GlancePlus

character mode interface, glance, **8**

motif mode interface, gpm, **8**

online help, **9**

overview, **8**

setting the DISPLAY variable, **25**

starting, **25**

GlancePlus Pak

removing GlancePlus Pak, **20**

removing ITO-SE from, **21**

## I

installation

checking results of, **19**

successful, **19**

ITO-SE

removing from GlancePlus Pak, **21**

## M

man pages, **19**

## O

online help for GlancePlus, **9**

OpenView Performance Agent

alarmdef file, **24**

overview, **10**

parm file, **24**

starting, **24**

operating system requirements, **15**

**P**

parm file, **24**

perfstat output, **27**

printable files, **30**

**R**

Release Notes, **31**

removing

GlancePlus Pak, **20**

ITO-SE from GlancePlus Pak, **21**

requirements

disk space, **14**

display, **14**

operating system, **15**

software, **15**

system, **14**

**S**

software requirements, **15**

starting

GlancePlus, **25**

OpenView Performance Agent, **24**

system requirements, **14**