

# HP QuickTest Professional

Software Version: 11.00

---

## Installation Guide

Document Release Date: October 2010

Software Release Date: October 2010



# Legal Notices

## Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

## Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

## Copyright Notices

© 1992 - 2010 Hewlett-Packard Development Company, L.P.

## Trademark Notices

Adobe® and Acrobat® are trademarks of Adobe Systems Incorporated.

Intel®, Pentium®, and Intel® Xeon™ are trademarks of Intel Corporation in the U.S. and other countries.

Java™ is a US trademark of Sun Microsystems, Inc.

Microsoft®, Windows®, Windows NT®, and Windows® XP are U.S registered trademarks of Microsoft Corporation.

Oracle® is a registered US trademark of Oracle Corporation, Redwood City, California.

Unix® is a registered trademark of The Open Group.

SlickEdit® is a registered trademark of SlickEdit Inc.

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates, or to verify that you are using the most recent edition of a document, go to:

**<http://h20230.www2.hp.com/selfsolve/manuals>**

This site requires that you register for an HP Passport and sign-in. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

Or click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

# Support

Visit the HP Software Support web site at:

**<http://www.hp.com/go/hpsoftwaresupport>**

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

To find more information about access levels, go to:

**[http://h20230.www2.hp.com/new\\_access\\_levels.jsp](http://h20230.www2.hp.com/new_access_levels.jsp)**

---

# Table of Contents

<b>Welcome to the HP QuickTest Professional</b>	
<b>Installation Guide</b> .....	<b>7</b>
HP QuickTest Professional Installation Guide Overview .....	7
Documentation Library Contents .....	8
Additional Online Resources .....	11
<b>Chapter 1: Before You Install</b> .....	<b>13</b>
Setting Required Access Permissions .....	14
Considerations When Upgrading from an Earlier Version of QuickTest .....	15
<b>Chapter 2: Setting Up QuickTest Professional</b> .....	<b>17</b>
Understanding the QuickTest Professional Setup for Different License Types .....	18
Considerations for Installing QuickTest Professional .....	21
Installing QuickTest Professional .....	22
Working with the Additional Installation Requirements Utility .....	35
QuickTest Professional Setup Window Options .....	45
Browsing the QuickTest Professional Program Folder .....	47
Setting Up a Silent Installation .....	48
QuickTest Professional User Interface Pack Installation .....	59
Troubleshooting and Limitations - Installing QuickTest.....	61
<b>Chapter 3: Working with QuickTest Professional Licenses</b> .....	<b>63</b>
Understanding QuickTest License Types .....	64
Requesting a Seat License Key .....	65
Installing a Seat License Key .....	68
Working with a Concurrent License .....	75
Modifying License Information .....	80
Working with Commuter Licenses .....	82
Validating QuickTest Licenses.....	95
Troubleshooting Concurrent Licensing Issues.....	100

**Chapter 4: Maintaining and Uninstalling QuickTest Professional ...107**

Installing and Uninstalling Specific QuickTest Professional

    Features .....108

Repairing Your QuickTest Professional Installation .....110

Uninstalling QuickTest Professional .....111

Saving and Restoring Your QuickTest Settings .....113

Troubleshooting and Limitations - Uninstalling QuickTest.....117

---

# Welcome to the HP QuickTest Professional Installation Guide

This chapter includes:

- "HP QuickTest Professional Installation Guide Overview" on page 7
- "Documentation Library Contents" on page 8
- "Additional Online Resources" on page 11

## HP QuickTest Professional Installation Guide Overview

Welcome to the *HP QuickTest Professional Installation Guide*.

This guide describes how to install and set up QuickTest Professional on a standalone computer.

### **Prerequisite Background**

This guide is intended for users who need to install and set up QuickTest Professional.

Readers of this guide should have some knowledge of system administration.

# Documentation Library Contents

This guide is part of the QuickTest Professional Documentation Library. The Documentation Library provides a single point of access for all QuickTest Professional documentation.

You can access the Documentation Library by using the following:

- Select **Help > QuickTest Professional Help**.
- In the Start menu, select **Program Files > HP QuickTest Professional > Documentation > HP QuickTest Professional Help**.
- Click in selected QuickTest windows and dialog boxes or press F1.
- View a description, syntax, and examples for a QuickTest test object, method, or property by placing the cursor on it and pressing F1.

The Documentation Library includes the following:

Type	Included Documentation
Getting Started Documentation	<ul style="list-style-type: none"><li>➤ <b>Readme</b> provides the latest news and information about QuickTest. Select <b>Start &gt; Programs &gt; HP QuickTest Professional &gt; Readme</b>.</li><li>➤ <b>HP QuickTest Professional Installation Guide</b> explains how to install and set up QuickTest. Select <b>Help &gt; QuickTest Professional Help</b> and click the link to the Installation Guide from the <b>Documentation Library Home</b> page.</li><li>➤ <b>HP QuickTest Professional Tutorial</b> teaches you basic QuickTest skills and shows you how to design tests for your applications. Select <b>Help &gt; QuickTest Professional Tutorial</b>.</li><li>➤ <b>Product Feature Movies</b> provide an overview and step-by-step instructions describing how to use selected QuickTest features. Select <b>Help &gt; Product Feature Movies</b>.</li><li>➤ <b>What's New</b> provides an overview of the features, enhancements and supported environments that are new in the current version of <i>QuickTest</i>. Choose <b>Help &gt; What's New</b>.</li></ul>

Type	Included Documentation
Feature Documentation	<p><b>QuickTest Professional Help</b> includes:</p> <ul style="list-style-type: none"> <li>➤ <b>Home</b> provides links to the Documentation Library guides in each available format (Help, PDF, and/or HTML).</li> <li>➤ <b>What's New in QuickTest Professional</b> describes the newest features, enhancements, and supported environments in the latest version of QuickTest.</li> <li>➤ <b>HP QuickTest Professional User Guide</b> describes how to use QuickTest to test your application.</li> <li>➤ <b>HP QuickTest Professional for Business Process Testing User Guide</b> provides step-by-step instructions for using QuickTest to create and manage assets for use with Business Process Testing.</li> <li>➤ <b>HP QuickTest Professional Add-ins Guide</b> describes how to work with supported environments using QuickTest add-ins, and provides environment-specific information for each add-in.</li> <li>➤ <b>HP QuickTest Professional Object Model Reference</b> describes QuickTest test objects, lists the methods and properties associated with each object, and provides syntax information and examples for each method and property.</li> </ul>

Type	Included Documentation
Reference Documentation	<ul style="list-style-type: none"><li>➤ <b>HP QuickTest Professional Advanced References</b> contains documentation for the following QuickTest COM and XML references:<ul style="list-style-type: none"><li>➤ <b>HP QuickTest Professional Automation Object Model</b> provides syntax, descriptive information, and examples for the automation objects, methods, and properties. It also contains a detailed overview to help you get started writing QuickTest automation scripts. The automation object model assists you in automating test management, by providing objects, methods and properties that enable you to control virtually every QuickTest feature and capability.</li><li>➤ <b>HP QuickTest Professional Run Results Schema</b> documents the run results XML schema, which provides the information you need to customize your run results.</li><li>➤ <b>HP QuickTest Professional Test Object Schema</b> documents the test object XML schema, which provides the information you need to extend test object support in different environments.</li><li>➤ <b>HP QuickTest Professional Object Repository Schema</b> documents the object repository XML schema, which provides the information you need to edit an object repository file that was exported to XML.</li><li>➤ <b>HP QuickTest Professional Object Repository Automation</b> documents the Object Repository automation object model, which provides the information you need to manipulate QuickTest object repositories and their contents from outside of QuickTest.</li></ul></li><li>➤ <b>VBScript Reference</b> contains Microsoft VBScript documentation, including VBScript, Script Runtime, and Windows Script Host.</li></ul>

## Additional Online Resources

**Sample applications.** The following sample applications are the basis for many examples in this guide:

- **Mercury Tours sample Web site.** The URL for this Web site is [newtours.demout.com](http://newtours.demout.com).
- **Mercury Flight application.** To access from the Start menu, select **Program Files > HP QuickTest Professional > Sample Applications > Flight**.

**Troubleshooting & Knowledge Base** accesses the Troubleshooting page on the HP Software Support Web site where you can search the Self-solve knowledge base. Choose **Help > Troubleshooting & Knowledge Base**. The URL for this Web site is <http://h20230.www2.hp.com/troubleshooting.jsp>.

**HP Software Support** accesses the HP Software Support Web site. This site enables you to browse the Self-solve knowledge base. You can also post to and search user discussion forums, submit support requests, download patches and updated documentation, and more. Choose **Help > HP Software Support**. The URL for this Web site is [www.hp.com/go/hpsupport](http://www.hp.com/go/hpsupport).

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract.

To find more information about access levels, go to:

[http://h20230.www2.hp.com/new\\_access\\_levels.jsp](http://h20230.www2.hp.com/new_access_levels.jsp)

To register for an HP Passport user ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

**HP Software Web site** accesses the HP Software Web site. This site provides you with the most up-to-date information on HP Software products. This includes new software releases, seminars and trade shows, customer support, and more. Choose **Help > HP Software Web site**. The URL for this Web site is [www.hp.com/go/software](http://www.hp.com/go/software).



# 1

---

## Before You Install

Welcome to HP QuickTest Professional, the advanced keyword-driven testing solution for functional test and regression test automation. QuickTest Professional is part of HP Quality Center. This guide describes everything you need to know to install QuickTest Professional on a standalone computer.

---

**Note:** Unless otherwise specified, references to **Quality Center** in this guide apply to all currently supported versions of Quality Center and HP ALM. Note that some features and options may not be supported in the specific edition of Quality Center or HP ALM that you are using.

For a list of the supported versions of Quality Center or HP ALM, see the *HP QuickTest Professional Product Availability Matrix*, available from the Documentation Library Home page or the root folder of the QuickTest Professional DVD.

For details on Quality Center or HP ALM editions, see the *HP Quality Center User Guide* or the *HP Application Lifecycle Management User Guide*.

---

Before you install QuickTest Professional, confirm that your computer meets all system requirements. For details, see the *HP QuickTest Professional Readme*. For the most updated listing of supported system configurations, visit [www.hp.com/go/QTP\\_SysReq](http://www.hp.com/go/QTP_SysReq).

You can upgrade to QuickTest Professional 11.00 only from QuickTest version 9.5 or later. If you are using a version earlier than QuickTest 9.5, you must first manually uninstall your current QuickTest version and the QuickTest Add-in for ALM/QC. For more information, see "Considerations When Upgrading from an Earlier Version of QuickTest" on page 15.

You must not run any other installation at the same time as you run the QuickTest Professional installation. In addition, you should ensure before you install QuickTest that your computer is not in a state that requires a restart. If this is the case, the installation will not run.

**This chapter includes:**

- Setting Required Access Permissions on page 14
- Considerations When Upgrading from an Earlier Version of QuickTest on page 15

## **Setting Required Access Permissions**

You must make sure the following access permissions are set to install and run QuickTest Professional.

### **Permissions Required to Install QuickTest Professional**

You must have administrator permissions on the computer on which you are installing QuickTest. You also need administrator rights for any other installation tasks, for example, uninstalling QuickTest, repairing or modifying the installation, or installing a patch.

In some circumstances, the installation may require a system restart. If a computer restart is required, your administrator permissions must include the part of the installation that occurs after the restart.

## Permissions Required to Run QuickTest Professional

You must have the following file system permissions:

- Full read and write permissions for all the files and folders under the folder in which QuickTest is installed
- Full read and write permissions to the Temp folder
- Read permissions to the Windows folder and to the System folder

You must have the following registry key permissions:

- Full read and write permissions to all the keys under **HKEY\_CURRENT\_USER\Software\Mercury Interactive**
- Read and Query Value permissions to all the **HKEY\_LOCAL\_MACHINE** and **HKEY\_CLASSES\_ROOT** keys

## Permissions Required When Working with Quality Center

You must have the following permissions to use QuickTest with Quality Center:

- Full read and write permissions to the Quality Center cache folder
- Full read and write permissions to the QuickTest Add-in for ALM/QC installation folder

## Considerations When Upgrading from an Earlier Version of QuickTest

- You can upgrade to QuickTest Professional 11.00 only from QuickTest version 9.5 or later. The previous version of QuickTest is automatically uninstalled.
- If you are upgrading to QuickTest Professional 11.00 from a version earlier than QuickTest 9.5, you must first manually uninstall your current QuickTest version and the QuickTest Add-in for ALM/QC. Otherwise, the installation process will not run. At the end of the uninstall process, restart your computer and install the new version and add-in.

---

**Note:** The Save and Restore Settings utility enables you to save existing customization settings and registry keys before you uninstall an old QuickTest version, and then restore them after you install the new version. For more information, see "Saving and Restoring Your QuickTest Settings" on page 113.

---

- QuickTest Professional supports the Sentinel RMS License Manager version 8.3.0 as its concurrent license server. If you are upgrading to QuickTest Professional with a concurrent license, you must also upgrade your concurrent license server. For details on setting up a concurrent license server, see the *HP Functional Testing Concurrent License Server Installation Guide*.
- License data is retained when upgrading from QuickTest Professional version 9.5 or later. However, if you have not installed a license before the upgrade, you must run the QuickTest Professional License Wizard as part of the installation. For more information, see step 11 on page 30.
- All add-ins that were installed in version 9.5 are identified during the upgrade and checked by default in the feature selection page of the installation. You can add or remove add-ins during the installation.
- The layout of the main QuickTest user interface, such as the size and position of various panes, is retained.
- All settings defined in **Tools > Options** are retained.
- Recent tests opened by QuickTest before the upgrade are displayed in the File menu.
- Connection settings to Quality Center are not retained by the upgrade process. If required, you must reconnect to Quality Center after the installation. To install the latest version of the ALM/QC Add-in, you must manually uninstall the previous version of the Add-in before installing the latest version.

# 2

---

## Setting Up QuickTest Professional

When you install QuickTest Professional, you must know which features and add-ins to you want to use. The installation process automatically installs QuickTest and the Web, Visual Basic, and ActiveX Add-ins, and also enables you to select which additional features and add-ins to install. For more information on add-ins, see the *HP QuickTest Professional Add-ins Guide*.

You must also know which type of license you want to install. A **Seat** license is a permanent license that is specific to the computer on which it is installed, and a **Concurrent** license is a per session license that is available only if your company has an HP Functional Testing Concurrent License Server. For more information, see "Understanding the QuickTest Professional Setup for Different License Types" on page 18.

Your QuickTest Professional license enables all QuickTest features, including the use of all QuickTest add-ins. You can use the latest released version of all QuickTest add-ins with QuickTest Professional. If upgrading from a previous version, only previously licensed add-ins will be available.

You can also set up QuickTest to install silently (in the background), and on remote computers.

---

**Note:** When you open QuickTest Professional, a silent check for updates to the application is performed in the background. You can check online for updates to all HP products installed on your computer at any time by choosing **Start > Programs > QuickTest Professional > HP Update**. You can then choose which updates you want to download and (optionally) install.

---

**This chapter includes:**

- Understanding the QuickTest Professional Setup for Different License Types on page 18
- Considerations for Installing QuickTest Professional on page 21
- Installing QuickTest Professional on page 22
- Working with the Additional Installation Requirements Utility on page 35
- QuickTest Professional Setup Window Options on page 45
- Browsing the QuickTest Professional Program Folder on page 47
- Setting Up a Silent Installation on page 48
- QuickTest Professional User Interface Pack Installation on page 59
- Troubleshooting and Limitations - Installing QuickTest on page 61

## **Understanding the QuickTest Professional Setup for Different License Types**

The general procedures for installing QuickTest Professional and activating a license differ for the various license types: **Seat**, and **Concurrent**. This section summarizes the procedures required for the different license types and directs you to the detailed information for each step.

### **Setting Up QuickTest Professional with a Seat License**

This section summarizes the procedure for setting up QuickTest Professional with a seat license. A seat license is a permanent license that is specific to the computer on which it is installed. The seat license includes a 30-day demo period, during which you may use all of the available QuickTest features, including Unified Functional Testing. Before the demo period ends, you must contact HP to obtain a permanent seat license key.

**Note:**

- If you want to run QuickTest using the demo license, do not run the License Installation wizard. The first time you open QuickTest, you are notified that the demo period started.
  - Seat licenses are not available for operating systems that have session capabilities, for example, Windows servers or Citrix.
- 

**To set up QuickTest Professional with a seat license:**

- 1** After you install QuickTest Professional, the Additional Installation Requirements screen opens. Make sure that **Run License Installation Wizard** is selected, and click **Run**.
- 2** When the License Installation wizard opens to the License Type screen, select **Seat**. For more information, see step 13 of “Installing QuickTest Professional” on page 31.
- 3** Run QuickTest Professional. Click **Install License** on the displayed warning message and request a seat license key from HP, as described in “Requesting a Seat License Key” on page 65.
- 4** After you receive the license key from HP, run the license installation wizard again to install your license key. For more information, see “Installing a Seat License Key” on page 68.

## Setting Up QuickTest Professional with a Concurrent License

This section summarizes the procedure for setting up QuickTest Professional with a concurrent license. A concurrent license is a per session license that is available only if your company has an HP Functional Testing Concurrent License Server, your computer has access to that server, and a free concurrent license is available for your use.

**To set up QuickTest Professional with a concurrent license:**

- 1** Install the HP Functional Testing Concurrent License Server on a network computer and activate the HP Functional Testing Concurrent License Server license. For more information, see the *HP Functional Testing Concurrent License Server Installation Guide*. This guide is installed on the computer where the HP Functional Testing Concurrent License Server is installed, and is called **MerLicSvr.pdf**.
- 2** Run the QuickTest Professional setup program on each client computer. In the License Type screen, select **Concurrent License**. For more information, see step 13 of “Installing QuickTest Professional” on page 31.
- 3** Begin using QuickTest Professional. When QuickTest Professional opens, it automatically searches for the specified license server and connects to it.

---

**Note:** If your computer cannot find and connect to the license server, you may need to set the LSHOST or LSFORCEHOST variable. For more information, see the *HP Functional Testing Concurrent License Server Installation Guide*.

---

## Considerations for Installing QuickTest Professional

- If you are upgrading to QuickTest Professional from QuickTest Professional version 9.2 or earlier, you need to first uninstall your current QuickTest version and the QuickTest Add-in for ALM/QC. Otherwise, the installation process will not run. At the end of the uninstall process, restart your computer and install the new version and add-in. The Save and Restore Settings utility enables you to save existing customization settings and registry keys before you uninstall an old QuickTest version, and then restore them after you install the new version. For more information, see "Saving and Restoring Your QuickTest Settings" on page 113.
- If you are upgrading to QuickTest Professional from version 9.5 or later, the installation wizard automatically upgrades your previous version of QuickTest and installs QuickTest Professional. The upgrade retains your existing configuration settings and preferences, such as your Options settings and window layout, as well as all your tests.
- QuickTest Professional supports the Sentinel RMS License Manager version 8.3.0 as its concurrent license server. If you are upgrading to QuickTest Professional with a concurrent license, you must also upgrade your concurrent license server. For details on setting up a concurrent license server, see the *HP Functional Testing Concurrent License Server Installation Guide*.
- If you have Astra QuickTest and/or Astra LoadTest installed, you must uninstall them before installing QuickTest Professional. After you install QuickTest Professional, you can then reinstall your other HP products.
- If the HP QuickTest Professional Files in Use dialog box is displayed during the installation process:
  - Close the applications listed in the dialog box and click **Try Again**.
  - If the HP QuickTest Professional Files in Use dialog box is displayed again, click the **Exit Installation** button and restart your computer. After the restart is complete, do not open any applications. Run the QuickTest Professional Setup program again.
  - If after restarting, the HP QuickTest Professional Files in Use dialog box lists Explorer as the open application, click **Continue**. If prompted, restart your computer at the end of the installation.

## Installing QuickTest Professional

Your QuickTest Professional DVD includes an installation program that guides you through the installation process.

### To install QuickTest Professional:

#### 1 Prerequisites:

- a** Make sure you are logged on with Administrator privileges.
- b** Select a local drive on which to install QuickTest Professional.  
(Do not install QuickTest Professional on a network drive.)
- c** Close any instances of QuickTest Professional. It is also recommended to close all other open applications.

#### 2 Insert the QuickTest Professional installation DVD into the DVD drive.

- If the DVD drive is on your local computer, and Autoplay is enabled, the QuickTest Professional Setup window opens. If Autoplay is disabled on your computer, right-click the DVD drive and select **Autoplay**.
- If you are installing from a network drive, double-click **setup.exe** in the root folder of the DVD.


The Setup window opens.



See "QuickTest Professional Setup Window Options" on page 45 for more information on the various options available in the QuickTest Professional setup window.

- 3 Click **QuickTest Professional Setup** to start the QuickTest Professional Setup program.

- 4 QuickTest requires specific software, for example, Microsoft Visual C++ Runtime components, to be installed before you install QuickTest. If Setup finds that the prerequisite software is not already installed on your computer, the following screen opens.



---

**Tip:** Select an item in the list to display a description of the program.

---

Click **OK** and follow the on-screen instructions to install the listed software before continuing with the QuickTest installation. If you click **Cancel**, Setup will stop because QuickTest cannot be installed without the prerequisite software.

In some situations, you may be prompted to restart your computer after installing the prerequisite software. To continue with the installation after restarting your computer, run the Setup program again.


**Note:** If you are upgrading from version 9.5 or later, a message is displayed informing you that a previous version of QuickTest exists on your computer and that the setup program will upgrade the previous version, saving all your settings and tests, before continuing with the installation. The upgrade process saves all your settings, including your QuickTest window layout and all your settings in the Options and Settings dialog boxes. In addition, it saves the files and settings that are listed in the section on Saved Files and Setting in "Saving and Restoring Your QuickTest Settings" on page 113. Click **OK** to continue.

- 5 The Welcome to the HP QuickTest Professional Setup Wizard opens. Click **Next** to proceed.
- 6 The License Agreement screen opens. Read the agreement.



To install QuickTest Professional, you must accept the terms of the license agreement by selecting **I Agree** and clicking **Next**.


- 7 In the Customer Information screen, type your name and the name of your organization.



The screenshot shows the 'Customer Information' window of the HP QuickTest Professional 11.00 installer. The window has a blue title bar with the text 'HP QuickTest Professional 11.00'. On the left side, there is a vertical navigation pane with the HP logo and the text 'QuickTest Professional Installation'. Below this, there is a list of steps: 'Welcome', 'Setup Type', 'Confirmation', 'Installation', and 'Finish'. The 'Welcome' step is currently selected and highlighted. The main area of the window is titled 'Customer Information' and contains the following text: 'Enter your name and company or organization in the box below. The installer will use this information for subsequent installations.' Below this text, there are two input fields: 'Name:' and 'Organization:'. The 'Name' field is currently empty, and the 'Organization' field is also empty. At the bottom right of the window, there are three buttons: '< Back', 'Next >', and 'Cancel'.

Click **Next** to proceed.

- 8 In the Custom Setup screen, select the QuickTest components and add-ins you want to install.



**Note:** Loading QuickTest add-ins enables QuickTest to work with the corresponding environments. You can install the add-ins you require when you install QuickTest Professional, or you can install them at a later time by running the installation again. When QuickTest opens, you can choose which of the installed add-ins you want to load using the QuickTest Professional Add-In Manager dialog box. For more information on the Add-in Manager, see the *HP QuickTest Professional Add-ins Guide*.

You can select an item in the list to see a description of the feature as well as the space requirement for the feature on your drive.

Click an icon to view a menu and select how that feature is installed on your computer. The following options are available, depending on the feature:



- **Will be installed on local hard drive.** Installs the selected feature on your local hard drive. Sub-features of the selected feature are not installed.



- **Entire feature will be installed on local hard drive.** Installs the entire selected feature and its sub-features on your local hard drive. For example, you can instruct QuickTest to install the .NET Add-in with its sub add-ins, Silverlight and Windows Presentation Foundation.



- **Entire feature will be unavailable.** Excludes the feature from the installation and it is not available in QuickTest.


---

**Note:** QuickTest Professional, its **Core Components**, and the **Run Results Viewer** option, cannot be deselected.

---

Click **Next**. If you are upgrading from version 9.5 or later, the upgrade installation automatically installs QuickTest Professional in the same folder in which the previous version of QuickTest was installed. Proceed to step 10.

- 9 In the Select Installation Folder screen, choose the location where you want to install QuickTest Professional.



- To select a different location, click **Browse**, choose a folder, and then click **OK**. You must specify a folder on a mapped drive (not a UNC path). If the destination folder does not exist, the setup program creates it.
- To view the required and available space on each of your mapped drives, click **Disk Cost**.


Ensure that you install QuickTest Professional on a drive with a sufficient amount of free disk space. For more information, see the system requirements, as described in the *HP QuickTest Professional Readme*.

Click **Next** to proceed.

- 10 The Confirm Installation screen opens. Click **Next** to proceed, and the installation process begins. The Installing HP QuickTest Professional screen displays the progress of the installation.

- 11 When the installation is complete, click **Finish**.

The Additional Installation Requirements screen opens.



---

**Note:** After the QuickTest installation is complete, the HP Run Results Viewer installation is performed in the background. Therefore, it may take some time before the Additional Installation Requirements screen opens.

---

In addition to options to configure Internet Explorer and DCOM settings, and to run the License Wizard, the Additional Installation Requirements screen displays any prerequisite software that must be installed or configured to work with QuickTest, according to the options selected during installation.


Select the required installation options. For more information on these options, see "Working with the Additional Installation Requirements Utility" on page 35.

---

**Tip:** Select an option name to display a description of the feature.

---

- 12** Click **Run** in the Additional Installation Requirements screen to install or configure your selections.
- 13** If you selected to run the **License Installation Wizard**, the QuickTest Professional License Installation - License Type screen opens.



Select a license type. (For information on the process required to set up various license types, see "Understanding the QuickTest Professional Setup for Different License Types" on page 18. For information on working with licenses, see "Working with QuickTest Professional Licenses" on page 63.)

► **Seat license.** Uses a license created for this computer.

A seat license is a permanent license that is specific to the computer on which it is installed. When you select this option, you also get a 30-day demo period during which you must request a permanent seat license key from the HP Webware License Key Delivery Service. After you receive the seat license key, you can activate it to work with QuickTest Professional permanently. For more information, see "Requesting a Seat License Key" on page 65.

If you select **Seat license**, proceed to step 14 on page 33.

► **Concurrent license.** Uses a network-based license.


A license server on the network regulates the number of concurrent QuickTest Professional users. You can work with a concurrent license only if a concurrent license server is installed on your local network, and that license server has at least one available license that is not currently in use.

Click **Next** to open the License Installation - Concurrent License Server dialog box and, if you know the name of the concurrent license server to which you want to connect, you can specify it in the text box. You can click **Check Connection** to verify that the license server is accessible from your network.

If you select this option but do not specify a concurrent license server, QuickTest will try to locate one for you when you open QuickTest.

For more information, see the *HP Functional Testing Concurrent License Server Installation Guide*.

- 14** If you chose to install QuickTest with a seat license, the QuickTest Professional License Installation - Welcome screen opens.




If you have a seat license key, proceed to step 3 on page 72 to install the seat license key.

If you do not have a license key, make a record of the displayed locking code for your computer. You will need it to request your license key. Click the link on the QuickTest Professional License Installation - Welcome screen for the **HP Webware License Key Delivery Service** to request your license key. Follow the instructions as described in "Requesting a License Key via the HP Webware License Key Delivery Service" on page 67 and then click **Cancel**. (You will be prompted to install the seat license when you open QuickTest.)

- 15** The installation continues with installing the options you selected in the Additional Installation Requirements screen. When these options are installed and configured on your computer, the screen reopens.

A checkmark is displayed next to the options that were successfully installed or configured.



---

**Tip:** You can run the Additional Installation Requirements utility at any time by choosing **Start > Programs > QuickTest Professional > Tools > Additional Installation Requirements**.

---

- 16** Click **Show Readme** if you want the *HP QuickTest Professional Readme* to open at the end of the installation.
- 17** Click **Close**. The Installation Complete screen opens.
- 18** Click **Finish**.

---

**Note:** In some situations, you may be prompted to restart your computer after you have installed QuickTest. It is recommended that you restart your computer as soon as possible if you are prompted to do so. Delaying the system restart may result in unexpected QuickTest behavior.

---

## Working with the Additional Installation Requirements Utility

Several prerequisites for working with QuickTest must be installed and configured after QuickTest is installed. In addition, to take advantage of QuickTest Professional debugging and remote access features, certain Internet Explorer and DCOM settings need to be configured.

The Additional Installation Requirements screen displays any prerequisite software that must be installed or configured to work with QuickTest, according to the options selected when QuickTest is installed or the installation is modified. For more information, see "Additional Installation Prerequisites" on page 36.

The Additional Installation Requirements utility enables you to configure the required settings automatically, and to run the License Installation Wizard and Microsoft Debugger installation during the QuickTest installation.

- Select an option name in the Additional Installation Requirements dialog box to display a description of the feature.
- Select the check box of one or more required options and click **Run**.

You can run the Additional Installation Requirements utility at any time by choosing **Start > Programs > HP QuickTest Professional > Tools > Additional Installation Requirements**. In addition to the options to configure Internet Explorer and DCOM settings, and to run the License Wizard, the dialog box displays any prerequisite software that is still required to be installed to work with QuickTest.

## Additional Installation Prerequisites

Additional installation requirements listed in the Additional Installation Requirements dialog box can include the following, according to the options selected when QuickTest is installed or the installation is modified:

- **Microsoft Visual C++ 2008 Redistributable.** Displayed only when the Stingray Add-in is installed.
- **Microsoft WSE 3.0 Runtime.** Provides a foundation for running applications based on published Web services specifications. This item is displayed only when not currently installed, and when the Web Services Add-in is installed.
- **Microsoft SOAP Toolkit 3.0.** Provides Web Services capabilities for COM components and applications. This item is displayed only when not currently installed, and when the Web Services Add-in is installed.
- **Microsoft Script Debugger.** Provides the debugging environment that QuickTest uses during test runs. This item is displayed only when not currently installed.
- **Terminal Emulator Wizard.** Provides a wizard that enables you to configure terminal emulator identifying settings. This item is displayed only when the Terminal Emulator (TE) Add-in is installed.
- **Stingray Wizard.** Provides a wizard that enables you configure QuickTest to work with your Stingray application. This item is displayed only when the Stingray Add-in is installed.

In addition, the Additional Installation Requirements utility enables you to perform the following:

- **Configure Internet Explorer settings.** Select this check box to automatically configure the Internet Explorer options that enable QuickTest to use the Microsoft Script Debugger application during test runs.

You can configure these options manually before running QuickTest. In Internet Explorer, select **Tools > Internet Options > Advanced**. Then select **Disable script debugging** and **Enable third-party browser extensions**.

- **Configure DCOM settings.** Select this check box to automatically change DCOM permissions and security settings and open a firewall port on your QuickTest computer.

These changes are only required if you want to run QuickTest tests remotely from Quality Center, and are running QuickTest on Windows XP Service Pack 2 or later, Windows 2003 Server, Windows Vista, or Windows 7.

For more information about the changes that QuickTest makes when you choose to set these options automatically, see the steps described in "Modifying DCOM Permissions Manually to Enable Remote QuickTest Execution" on page 38.

If you choose not to automatically set remote execution options during the QuickTest installation, you can, before attempting to remotely run QuickTest tests from Quality Center:

- Run the Additional Installation Requirements utility at a later time from **Start > Programs > HP QuickTest Professional > Tools > Additional Installation Requirements**.
- Make the required changes manually. For more information on making these changes manually, see "Modifying DCOM Permissions Manually to Enable Remote QuickTest Execution" on page 38.
- Make the required changes automatically, by running the Remote Agent <**QuickTest Professional installation**>\bin\AQTRmtAgent.exe at a later time.

---

**Note:** Contact Microsoft Support if you have questions regarding changes in DCOM securities on Windows XP Service Pack 2 or later, Windows 2003 Server, or Windows Vista.

---

- **Run License Installation Wizard.** Select this check box to run the QuickTest Professional License Wizard. If you want to run QuickTest using the Unified Functional Testing demo license for up to 30 days, do not select this check box.

---

**Note:** This option is not automatically selected when upgrading from QuickTest Professional version 9.5 or later because license data is retained. If you did not install a license before the upgrade, select this check box to run the QuickTest Professional License Wizard.

---

## **Modifying DCOM Permissions Manually to Enable Remote QuickTest Execution**

This section describes how to manually change DCOM permissions and open firewall ports to enable remote execution of QuickTest. These changes are only required if you are running QuickTest on Windows XP Service Pack 2, Windows 2003 Server Service Pack 1 or later, Windows Vista, or Windows 7.

If you chose to automatically make these changes during the QuickTest installation, you do not need to make these manual changes. If you do not intend to execute QuickTest tests remotely from Quality Center, you do not need to make these manual changes.

---

**Note:** The security changes described in this section should be performed by your System Administrator. Please contact Microsoft Support if you have questions regarding changes in DCOM securities on Windows XP Service Pack 2, Windows 2003 Server Service Pack 1 or later, or Windows Vista.

---

---

**Tip:** The HP Support Knowledge Base provides utilities to assist you in making these changes. For more information, see the HP Software Self-solve knowledge base (<http://h20230.www2.hp.com/selfsolve/document/KM196144>) and search for Problem ID 43245. The Knowledge Base area requires that you register as an HP Passport user and sign in.

---

To manually enable remote execution of QuickTest, perform the following procedures:

- Enable Windows to authenticate the remote user (described on page 39)
- Configure the Windows Firewall to enable port 135 for DCOM (described on page 39)
- Modify DCOM security properties (described on page 40)
- Configure security settings for the QuickTest Remote Agent DCOM applications (described on page 42)

In addition, before remotely running a test you must also make sure that the **Allow other HP products to run tests and components** option is selected in the Run tab of the QuickTest Options dialog box. For more information, see the *HP QuickTest Professional User Guide*.

**To enable Windows to authenticate the remote user:**

- 1** Add both computers to the same domain.
- 2** For domain users logged into both computers, add these domain users to the Local Administrators group on the QuickTest computer. This enables Windows to authenticate the remote user executing the tests against the DCOM objects.

**To configure the Windows Firewall to enable port 135 for DCOM:**

---

**Note:** If you disabled the firewall installed with Windows XP Service Pack 2, Windows 2003 Server, or Windows Vista, you do not need to open port 135 for DCOM, as described in this procedure.

---

- 1** On the QuickTest computer, select **Start > Settings > Control Panel > Windows Firewall**. The Windows Firewall dialog box opens.
- 2** Select the **Exceptions** tab.
- 3** Click **Add Program**. The Add a Program dialog box opens.

- 4 Select or browse to the Remote Agent (<**QuickTest Professional installation**>\bin\AQTRmtAgent.exe) and click **OK**.

---

**Note:** If you do not configure the Remote Agent as an exception as described above, a Windows Security Alert message will appear while running a test remotely. Click **Unblock** to solve this problem. The next time you remotely execute an automated test, the warning will not appear.

---

- 5 Click **OK** to close the Windows Firewall dialog box.

---

**Note:** For more information, a list of port assignments for commonly-used services can be found at: [http://www.microsoft.com/resources/documentation/Windows/2000/server/reskit/en-us/Default.asp?url=/resources/documentation/windows/2000/server/reskit/en-us/cnet/cnfc\\_por\\_SIMW.asp](http://www.microsoft.com/resources/documentation/Windows/2000/server/reskit/en-us/Default.asp?url=/resources/documentation/windows/2000/server/reskit/en-us/cnet/cnfc_por_SIMW.asp).

---

**To modify DCOM security properties:**

- 1 Select **Start > Run**, type **dcomcnfg**, and press **ENTER**. The Component Services window opens.
- 2 Navigate to **Console Root > Component Services > Computers > My Computer**.

---

**Note:** If a Windows Security Alert message opens, click **Ask me later** or **Unblock**.

---

- 3 Right-click **My Computer** and select **Properties**.

- 4** Select the **Default Properties** tab.
- 5** Make sure the **Default Impersonation Level** is **Identify** and click **Apply**.
- 6** Select the **COM Security** tab.
- 7** In the Access Permissions area, click **Edit Limits**. The Access Permission dialog box opens.
- 8** Click **Add**. The Select Users or Groups dialog box opens.
- 9** Click **Advanced**.
- 10** Click **Locations**. In the displayed dialog box, select your computer name and click **OK**.
- 11** Click **Find Now**.
- 12** Select the following users and groups from the local computer and click **OK**:
  - Administrator
  - Administrators
  - Authenticated Users
  - Anonymous Logon
  - Everyone
  - Interactive
  - Network
  - System
- 13** Add the following users from the domain and click **OK**:
  - <domain user logged into the QuickTest computer>
  - <domain user logged into the Quality Center computer that is performing the remote execution>
- 14** In the Access Permission dialog box, assign **Local Access** and **Remote Access** permissions to the groups and users in the list and click **OK**.
- 15** In the Launch and Activation Permissions area, click **Edit Limits**. The Launch Permission dialog box opens.

- 16** Repeat steps 8 to 13.
- 17** In the Access Permission dialog box, assign **Local Launch**, **Remote Launch**, **Local Activation**, and **Remote Activation** permissions to the groups and users in the list and click **OK**.

**To configure security settings for the QuickTest Remote Agent DCOM applications:**

- 1** In the Component Services window, navigate to **Console Root > Component Services > Computers > My Computer > DCOM Config**.
- 2** Right-click the **AQTRmtAgent** item and select **Properties**. The AQTRmtAgent Properties dialog box opens.
- 3** In the Identity tab, select **The interactive user**. This enables the DCOM application to authenticate the process against the logged-in Windows user and run the process in that security context.
- 4** Select the **Security** tab.
- 5** In the Launch and Activation Permissions area, select **Customize** and click **Edit**. The Launch Permission dialog box opens.
- 6** Click **Add**. The Select Users or Groups dialog box opens.
- 7** Click **Advanced**.
- 8** Click **Locations**. In the displayed dialog box, select your computer name and click **OK**.
- 9** Click **Find Now**.

- 10** Select the following users and groups from the local computer and click **OK**:
  - Administrator
  - Administrators
  - Authenticated Users
  - Anonymous Logon
  - Everyone
  - Interactive
  - Network
  - System
- 11** Add the following users from the domain and click **OK**:
  - <domain user logged into the QuickTest computer>
  - <domain user logged into the Quality Center computer that is performing the remote execution>
- 12** In the Launch Permission dialog box, for all the groups and users in the list, select **Allow** for all permissions and click **OK**.
- 13** In the Access Permissions area, select **Customize** and click **Edit**. The Access Permission dialog box opens.
- 14** Repeat steps 6 to 12.
- 15** Click **Apply** to save the changes and click **OK** to close the dialog box.
- 16** Close the Component Services window.
- 17** You can now remotely execute a QuickTest test from Quality Center.

---

**Note:** Before remotely running a test, you must also make sure that the **Allow other HP products to run tests and components** option is selected in the Run tab of the QuickTest Options dialog box. For more information, see the *HP QuickTest Professional User Guide*.

---

## **Modifying User Account Control Settings to Connect with Quality Center (Windows Vista, Windows 7, Windows Server 2008, and Windows Server 2008 R2)**

If you are running QuickTest on Windows Vista, Windows 7, Server 2008, or Server 2008 R2, you must disable User Account Control (UAC) before the first time you connect with Quality Center. After you have connected with Quality Center for the first time, you can enable User Account Control (UAC) again if required.

This change is required only if you are running QuickTest on one of the operating systems listed above. If you do not intend to execute QuickTest tests remotely from Quality Center, you do not need to make these changes.

---

**Note:** The security changes described in this section should be performed by your System Administrator. Please contact Microsoft Support if you have questions regarding changes in User Account Control (UAC) on any of these operating systems.

---

To temporarily turn off the UAC option, do the following:

### **For Microsoft Windows Vista and Windows Server 2008:**

- 1** Log in as an administrator.
- 2** From the Control Panel, select **User Accounts > Change Security Settings**, and clear the **Use User Account Control (UAC) to help protect your computer** check box.

### **For Microsoft Windows 7 and Windows Server 2008 R2:**

- 1** Log in as an administrator.
- 2** From the Control Panel, select **User Accounts > User Accounts > Change User Account Settings**.
- 3** In the User Account Control Settings window, move the slider to **Never notify**.

## QuickTest Professional Setup Window Options

The QuickTest Professional Setup window contains the following options:

Option	Description
<b>QuickTest Professional Setup</b>	Starts the QuickTest Professional Setup program.
<b>Installation Guide</b>	Opens a PDF copy of the <i>HP QuickTest Professional Installation Guide</i> , which is suitable for printing. To download Adobe, Reader click <b>Download Adobe Reader</b> .
<b>Readme</b>	Opens the Readme file.
<b>QuickTest Add-in for ALM/QC</b>	<p>Enables features in the Quality Center client installed on your computer.</p> <p>If you do not install the <b>QuickTest Add-in for ALM/QC</b>, you can perform only the following QuickTest operations in Quality Center:</p> <ul style="list-style-type: none"> <li>➤ Running tests remotely.</li> <li>➤ Configuring test execution parameters.</li> </ul> <p>To perform any other operations on QuickTest assets in Quality Center, you must install the <b>QuickTest Add-in for ALM/QC</b>. For example, the add-in enables you to:</p> <ul style="list-style-type: none"> <li>➤ View test and component scripts from Quality Center.</li> <li>➤ View run results in the Run Results window from Quality Center.</li> <li>➤ Create new tests and components from Quality Center.</li> <li>➤ Perform other operations in Quality Center that involve QuickTest user interface elements.</li> </ul> <p>For additional information on the QuickTest Add-in for ALM/QC, or to download the latest version of the add-in, see the QuickTest Professional Add-in screen in Quality Center (<b>Help &gt; Add-ins Page &gt; More HP Quality Center Add-ins &gt; QuickTest Professional Add-in</b>).</p> <p><b>Note:</b> QuickTest Professional 11.00 supports integration with Quality Center 9.0 or later. For Business Process Testing, QuickTest Professional 11.00 supports integration only with Quality Center 10.00 or later. You can install the Add-in for ALM/QC with all currently supported versions of Quality Center. For a list of supported versions, see the <i>HP QuickTest Professional Product Availability Matrix</i>, available from the Documentation Library Home page or the root folder of the QuickTest Professional DVD.</p>

Option	Description
<b>Add-in Extensibility and Web 2.0 Toolkits</b>	<p>Enables you to install the following:</p> <ul style="list-style-type: none"> <li>➤ QuickTest Professional Java Add-in Extensibility SDK</li> <li>➤ QuickTest Professional .NET Add-in Extensibility SDK</li> <li>➤ QuickTest Professional WPF and Silverlight Add-in Extensibility SDK</li> <li>➤ Extensibility Accelerator for Functional Testing (includes Web Add-in Extensibility SDK)</li> <li>➤ Web 2.0 Toolkit Support</li> </ul>
<b>Functional Testing License Server Setup</b>	<p>Enables you to install the HP Functional Testing Concurrent License Server or a concurrent license on the server. From the dialog box that opens you can also open a PDF copy of the <i>HP Functional Testing Concurrent License Server Installation Guide</i>.</p>
<b>Download Adobe Reader.</b>	<p>Downloads Adobe Reader.</p>
<b>Contact HP</b>	<p>Opens the contact information page on the HP Web site (<a href="http://welcome.hp.com/country/us/en/prodserv/software.html">http://welcome.hp.com/country/us/en/prodserv/software.html</a>). Click <b>Contact HP</b> in the upper left corner.</p>
<b>Support</b>	<p>Opens the HP Software Support Web site (<a href="http://www.hp.com/go/hpsoftwaresupport">http://www.hp.com/go/hpsoftwaresupport</a>).</p>
<b>Browse DVD</b>	<p>Enables you to view the contents of the QuickTest Professional DVD.</p>

## Included Utilities and Features

The utilities, features, and information that were available in the **QuickTest Plus Toolkit** in previous versions of QuickTest have been incorporated into the main QuickTest Professional application. These include:

- Code and SDK samples, which can now be installed by selecting **Samples** in the Select Features screen during the QuickTest custom installation. For more information, see step 8 on page 27.
- Object repository merge functionality, which is now available in the QuickTest Object Repository Merge Tool.

- External Action Call Modification utility, which is now handled by the QuickTest Missing Resources pane.
- The Register Browser Control utility.
- The License Validation utility.

For more information about these utilities and features, and answers to frequently asked questions, see the *HP QuickTest Professional User Guide* and the *HP Software Self-solve knowledge base* (<http://www.hp.com/go/hpsoftwaresupport>), available by clicking **Support** on the QuickTest Professional Setup window.

## Browsing the QuickTest Professional Program Folder

After the QuickTest Professional setup process is complete, a number of items are added to your QuickTest Professional program folder (**Start > Programs > QuickTest Professional**).

For a description of each of these items, see the *HP QuickTest Professional User Guide*.

---

**Note:** If you uninstalled a previous version of QuickTest Professional before installing this version, you may have additional (outdated) items in your QuickTest Professional program folder. In addition, if you have QuickTest Professional add-ins installed, you may have items in your program folder that relate specifically to these add-ins.

---

## Setting Up a Silent Installation

A *silent installation* (or *quiet installation*) is an installation that is performed in the background. You can install QuickTest Professional, QuickTest Add-ins, and the ALM/QC Add-in silently on your computer, without the need to navigate through setup screens or for user interaction. You can also install QuickTest Professional, QuickTest Add-ins, and the ALM/QC Add-in on remote computers.

For more information, see:

- "Before You Install QuickTest Silently" on page 48
- "Installing QuickTest Silently" on page 51
- "Installing the QuickTest Add-in for ALM/QC Silently" on page 55

### Before You Install QuickTest Silently

You must have administrator privileges to install QuickTest Professional and the ALM/QC Add-in. (You also need administrator rights for any other installation tasks, for example, uninstalling QuickTest, repairing or modifying the installation, or installing a patch.)

The following sections list the prerequisite software that must be installed on your computer before running a silent installation of QuickTest Professional and QuickTest Add-ins.

## Prerequisite Software for QuickTest Professional and the QuickTest Add-ins

The following prerequisite software is required to be installed on your computer before you install QuickTest Professional and QuickTest Add-ins. This software is available on the QuickTest installation DVD, and can be installed from the command line.

Prerequisite	Silent Command Line Syntax
Windows Installer 3.1	QuickTest\EN\prerequisites\msi31\WindowsInstaller-KB893803-v2-x86.exe /quiet
Microsoft Data Access Components 2.8 SP1	QuickTest\EN\prerequisites\mdac28\mdac28.exe /Q
Microsoft Windows Script 5.6 for Windows XP and Windows 2000	QuickTest\EN\prerequisites\wscript_56_win2k\wscript_56_win2k.exe /Q
Microsoft Visual C++ 2005 SP1 Run-time Components	QuickTest\EN\prerequisites\vc2005_sp1_redist /Q
Microsoft .NET Framework 3.5 Service Pack 1	QuickTest\Common\dotnet35_sp1\dotnetfx35_sp1.exe /quiet
Visual Studio Tools for Office redistributable	QuickTest\Common\vstor30\vstor30.exe /q

**Prerequisite Software for ALM/QC**

The following prerequisite software is required to be installed on your computer before you install the ALM/QC Add-in. This software is available on the QuickTest installation DVD, and can be installed from the command line.

Prerequisite	Command Line Syntax
Windows Installer 3.1	QuickTest\EN\prerequisites\msi31\WindowsInstaller-KB893803-v2-x86.exe /quiet
Microsoft Visual C++ 2005 SP1 Run-time Components	QuickTest\EN\prerequisites\vc2005_sp1_redist /Q
Microsoft .NET Framework 3.5 Service Pack 1	QuickTest\Common\dotnet35_sp1\dotnetfx35_sp1.exe /quiet
Visual Studio Tools for Office redistributable	QuickTest\Common\vstor30\vstor30.exe /q

---

**Caution:** The prerequisite software must be installed locally, even if the silent installation is performed remotely. You can begin the silent installation only after all the required prerequisite software is installed.

---

## Installing QuickTest Silently

This section describes how to install the following QuickTest features silently on your computer:

- QuickTest Professional
- QuickTest Add-ins
- Additional Installation Requirements

If you want to install the QuickTest Professional Add-in for ALM/QC, see "Installing the QuickTest Add-in for ALM/QC Silently" on page 55.

---

**Note:** You can use most standard MSI command line options when installing QuickTest from the command line. For more information about performing a silent, or quiet, MSI installation, see the relevant Microsoft documentation.

---

### Prerequisites

- 1** It is recommended to save any open files and close all open applications before running the silent installation.
- 2** Install the prerequisite software for QuickTest Professional. For the full list of prerequisite software, see "Before You Install QuickTest Silently" on page 48. You can begin the silent installation only after all the required prerequisite software is installed.

---

**Caution:** The prerequisite software must be installed locally, even if the silent installation is performed remotely. You can begin the silent installation only after all the required prerequisite software is installed.

---

### **Performing a standard installation of QuickTest, QuickTest Add-ins, and Additional Installation Requirements silently**

In the command line, run the **QTPSilentInstaller.bat** file, which performs **msiexec.exe** commands to install QuickTest, using the following format:

```
<QTP_DVD_PATH>\QTPSilentInstaller  
ConcurrentLicenseServer [MsiProperties] [MsiFlags]
```

---

**Note:** If you do not specify an installation folder, QuickTest is installed in the default installation folder.

---

For a description of the silent installation commands, see "Silent installation commands" on page 57.

### **Upgrading QuickTest, QuickTest Add-ins, and Additional Installation Requirements silently**

In the command line, run the **QTPSilentInstaller.bat** file with the **ALLOW\_UPGRADE** MSI property, using the following format:

```
<QTP_DVD_PATH>\QTPSilentInstaller  
ConcurrentLicenseServer "ALLOW_UPGRADE=1" [MsiProperties] [MsiFlags]
```

---

**Note:** When you upgrade from version 9.5 or later, the upgrade process saves all your settings, including your QuickTest window layout and all your settings in the Options and Settings dialog boxes. In addition, it saves the files and settings that are listed in the section on Saved Files and Setting in "Saving and Restoring Your QuickTest Settings" on page 113.

---

For a description of the silent installation commands, see "Silent installation commands" on page 57.

**Specifying which QuickTest features to install**

You can use the ADDLOCAL MSI property in the silent installation command line to specify the QuickTest features and add-ins that you want to install. If you want to install only the QuickTest core components, you do not need to use this option.

If you use this command, the following mandatory options must be included:

- **Core\_Components** (parent: QuickTest\_Professional)
- **Test\_Results\_Viewer** (parent: QuickTest\_Professional)
- **Web\_Add-in**

---

**Note:** When installing a feature using the ADDLOCAL property, its parent always gets installed as well.

---

In addition to the mandatory options, you can install the following QuickTest features and add-ins:

- .NET\_Add-in
- ActiveX\_Add-in
- Java\_Add-in
- Oracle\_Add-in
- PeopleSoft\_Add-in
- PowerBuilder\_Add-in
- SAP\_Solutions\_Add-in
- SAP\_eCATT\_integration (parent: SAP\_Solutions\_Add-in)
- Samples (parent: QuickTest\_Professional)
- Siebel\_Add-in
- Stingray\_Add-in
- TE\_Add-in

- VisualAge\_Add-in
- Visual\_Basic\_Add-in
- Web\_Services\_Add-in

### Examples of the QuickTest core silent installation

The following examples illustrate the different silent installation options, depending on whether upgrading or performing a complete installation.

#### Standard installation:

```
QTPSilentInstaller QtpLicServer "TARGETDIR=C:\Progra~1\QTP"  
/! *vx C:\Temp\QtpInstall.log
```

#### Upgrade:

```
QTPSilentInstaller QtpLicServer "ALLOW_UPGRADE=1"  
"TARGETDIR=<QTP_Folder>"
```

#### Standard installation with the Java Add-in:

```
QTPSilentInstaller QtpLicServer  
"ADDLOCAL=Core_Components,Test_Results_Viewer,Web_Add-in,Java_Add-in"  
"TARGETDIR=<QTP_Folder>"
```

### Additional installation requirements limitations

- The following additional installation prerequisites are not installed when using silent installation:

Prerequisite	Related Add-in
Terminal Emulator Wizard	Terminal Emulator
Stingray Wizard	Stingray
Microsoft WSE 3.0 Runtime	Web Services
SOAP Toolkit	Web Services

You must manually install these prerequisites using Additional Installation Requirements Utility. For details on installing additional requirements, "Working with the Additional Installation Requirements Utility" on page 35.

- The QuickTest Add-in for ALM/QC is installed using a separate silent installation. For details, see "Installing the QuickTest Add-in for ALM/QC Silently" on page 55.

## Installing the QuickTest Add-in for ALM/QC Silently

You can use the silent installation mechanism to install the QuickTest Add-in for ALM/QC. Unlike the QuickTest Professional core silent installation (described in "Installing QuickTest Silently" on page 51), you perform a silent installation of the ALM/QC Add-in by directly entering `msiexec.exe` commands in the command line.

### Installing the QuickTest Add-in for ALM/QC silently

- 1** It is recommended to save any open files and close all open applications before running the silent installation.
- 2** Run the appropriate Microsoft MSI installation from the command line, using one of the following formats:
  - **New installation** (any previous versions have already been uninstalled):
 

```
msiexec /i "<QTP_DVD_Path>\QCPlugin\MSI\<QC_Plugin_File>" /qn
```
  - **Upgrade** (from version 9.5 or later):
 

```
msiexec /qn /i "<QTP_DVD_Path>\QCPlugin\MSI\<QC_Plugin_File>"  
ALLOW_UPGRADE=1 TARGETDIR=<QT4QCAddin_Folder>
```

For a description of the silent installation commands, see "Silent installation commands" on page 57.

### Examples of the QuickTest Add-in for ALM/QC silent installation

The following examples illustrate the different silent installation options, depending on whether upgrading or performing a complete installation:

#### Standard installation:

```
msiexec /i "<QTP_DVD_Path\QCPlugin\MSI>  
\QuickTest_Add-in_for_ALM-QC.msi" /qn
```

Or:

```
msiexec /qn /i "<QTP_DVD_Path\QCPlugin\MSI>  
\QuickTest_Add-in_for_ALM-QC.msi"
```

#### Upgrade:

```
msiexec /i "<QTP_DVD_Path\QCPlugin\MSI>  
\QuickTest_Add-in_for_ALM-QC.msi" /qn ALLOW_UPGRADE=1  
TARGETDIR=<QT4QCaddin_Folder>
```

Or:

```
msiexec /qn /i "<QTP_DVD_Path\QCPlugin\MSI>  
\QuickTest_Add-in_for_ALM-QC.msi" ALLOW_UPGRADE=1  
TARGETDIR=<QT4QCaddin_Folder>
```

## Silent installation commands

The following table lists commands, arguments, and options used for silent installation (in alphabetical order):

Command / Argument	Description
<b>ADDLOCAL</b> (QuickTest core installation only)	Optional. Instructs the silent installation to install specific QuickTest features and add-ins. For more information and a list of available features, see "Specifying which QuickTest features to install" on page 53. <b>Note:</b> <ul style="list-style-type: none"><li>➤ If you do not use this argument, QuickTest is installed with the default add-ins.</li><li>➤ You must include <b>Test_Results_Viewer</b>, <b>Web_Add-in</b>, and <b>Core_Components</b> in the <b>ADDLOCAL</b> command.</li><li>➤ Values must be separated by commas and must not contain spaces.</li></ul>
<b>ALLOW_UPGRADE</b>	(Upgrade only) Mandatory. Instructs the silent installation to perform an upgrade instead of a complete installation.
<b>ConcurrentLicenseServer</b>	Mandatory. The name or IP address of the license server to specify when installing QuickTest licenses.
<b>MsiFlags</b>	Optional. Any MSI options, flags, and other instructions that are not included in the <b>MsiProperties</b> arguments, such as logging commands.
<b>MsiProperties</b>	Optional. Any MSI properties or parameters, such as TARGETDIR. Each MSI property and its definition must be contained in quotes (") and must not contain spaces.
<b>QC_Plugin_File</b> (QuickTest Add-in for ALM/QC installation only)	Mandatory. The name of the MSI installation file. <b>Note:</b> There is a different MSI file for each available language.

Command / Argument	Description
<b>QT4QC_Folder</b> (QuickTest Add-in for ALM/QC installation only)	(Upgrade only) Mandatory. The full path string (in quotes) of the folder in which the previous version of QuickTest Professional is currently installed.
<b>QTP_DVD_Path</b>	The path to the QuickTest Installation DVD or network location. The QuickTest Professional <b>.bat</b> file is located on the installation DVD in the root folder.
<b>QTP_Folder</b> (QuickTest core installation only)	(Upgrade only) Mandatory. The full path string (in quotes) of the folder in which the previous version of QuickTest Professional is currently installed.  <b>Caution:</b> If you specify a folder other than the folder in which QuickTest Professional 9.5 is installed, the silent installation will perform a complete uninstallation of the previous version and install QuickTest Professional 11.00. All your settings will not be saved.
<b>QTPSilentInstaller</b>	The name of the QuickTest silent installation <b>.bat</b> file.

For details on silent installation, see:

- "Installing QuickTest Silently" on page 51
- "Installing the QuickTest Add-in for ALM/QC Silently" on page 55

## QuickTest Professional User Interface Pack Installation

The QuickTest Professional User Interface Pack enables you to view the QuickTest, Run Results Viewer, and QuickTest Add-in for ALM/QC program user interface in your local language. You install the User Interface Pack from the <Language> **User Interface Pack** CD-ROM.

The User Interface Pack installation also enables you to install a localized version of the Functional Testing Concurrent License Server.

This section includes:

- "Prerequisites for the QuickTest Professional User Interface Pack Installation" on page 59
- "Installing the QuickTest Professional User Interface Pack" on page 60

### Prerequisites for the QuickTest Professional User Interface Pack Installation

- You must have QuickTest Professional installed before installing the User Interface Pack. For more information, see "Installing QuickTest Professional" on page 22.
- If you are installing the QuickTest Add-in for ALM/QC User Interface Pack, you must also have the QuickTest Add-in for ALM/QC installed. For installation information, see "QuickTest Professional Setup Window Options" on page 45.

---

**Note:** If you are installing the Functional Testing Concurrent License Server (<Language> Edition), you do not need to first install the English edition of the Functional Testing Concurrent License Server.

---

## Installing the QuickTest Professional User Interface Pack

The following describes how to install a User Interface Pack for QuickTest Professional, Run Results Viewer, and QuickTest Add-in for ALM/QC, and how to install the localized Functional Testing Concurrent License Server.

### To install the User Interface Pack:

- 1** Make sure that the prerequisites are met, as described in "Prerequisites for the QuickTest Professional User Interface Pack Installation" on page 59.
- 2** Insert the **<Language> User Interface Pack** CD into the CD-ROM drive. The **QuickTest Professional <Language> User Interface Pack Setup** window opens.

---

**Note:** If the CD-ROM drive is on a network computer, map the network drive, navigate to the root folder of the mapped network path, and double-click **setup.exe**.

---

- 3** In the main **QuickTest Professional <Language> User Interface Pack** setup window, do one or more of the following:

- Click the **QuickTest Professional User Interface Pack Setup** link and follow the on-screen instructions.

The **<Language> User Interface Pack** is installed in the **<QuickTest Professional installation>** folder.

- Click the **Run Results Viewer User Interface Pack Setup** link and follow the on-screen instructions.

The **<Language> User Interface Pack** is installed in the **<Run Results Viewer installation>** folder.

- Click the **QuickTest Add-in for ALM/QC User Interface Pack Setup** link and follow the on-screen instructions.

The **<Language> User Interface Pack** is installed in the **<QuickTest Add-in for ALM/QC installation>** folder.

- Click the **Functional Testing License Server Setup (<Language> Edition)** link and follow the on-screen instructions.

The **Functional Testing License Server (<Language> Edition)** is installed in **<Functional Testing License Server installation folder>**.

## Troubleshooting and Limitations - Installing QuickTest

This section describes troubleshooting and limitations for installing QuickTest.

The security settings in Windows Vista, Windows 7, Server 2008, or Server 2008 R2, may prevent you from performing a QuickTest Professional-related installation, such as a patch installation, or connecting to a Quality Center project (either directly or from QuickTest Professional). This can occur when the UAC (User Account Control) option is set to ON, and you have not yet connected to a Quality Center project (if relevant).

**Workaround:** Temporarily turn off the UAC option, as described in "Modifying User Account Control Settings to Connect with Quality Center (Windows Vista, Windows 7, Windows Server 2008, and Windows Server 2008 R2)" on page 44.



# 3

---

## Working with QuickTest Professional Licenses

You can install QuickTest Professional using a *seat* license (formerly known as a local or standalone license) or a *concurrent* license (formerly known as a floating license).

**This chapter includes:**

- Understanding QuickTest License Types on page 64
- Requesting a Seat License Key on page 65
- Installing a Seat License Key on page 68
- Working with a Concurrent License on page 75
- Modifying License Information on page 80
- Working with Commuter Licenses on page 82
- Validating QuickTest Licenses on page 95
- Troubleshooting Concurrent Licensing Issues on page 100

# Understanding QuickTest License Types

To use QuickTest Professional, you must have a valid license. There are two types of licenses: seat and concurrent. The table below summarizes the differences between the two license types.

Topic	Seat License	Concurrent License
General description	The license is specific to the computer on which it is installed.	Each license entitles the organization to one additional concurrent user.
Number of installations per license key	Each installation of QuickTest Professional requires a distinct license key.	There is no limit to the number of QuickTest Professional installations on the network, but a special concurrent license server regulates the number of computers that can run a copy of QuickTest Professional at any time.
Other issues	<p>The license key is based partially on the locking code, which is a code that identifies the computer on which QuickTest Professional is installed. The supplied license key works only for the computer on which the locking code was generated.</p> <p><b>Note:</b> A computer with multiple bootable partitions may generate a different locking code for each partition. If a different locking code is generated for a partition, you will need to request a unique license key for it.</p>	<p>Not supported for Unix networks.</p> <p>It is recommended that the concurrent license server has a fixed IP address.</p> <p>QuickTest Professional client computers must have TCP/IP installed.</p> <p>To use concurrent licenses across networks, UDP port 5093 must be open on the server.</p>

Topic	Seat License	Concurrent License
Entering license key	At the end of the installation procedure, QuickTest asks you to enter the license key. If you do not have a license key at that point, QuickTest asks you to enter the key the first time you open QuickTest.	Each time QuickTest opens, it automatically searches the same subnet for the concurrent license server. You do not need to enter a license key for your QuickTest client installation.

You can view and copy license information and license validation information, if needed. For example, you may want to retrieve license information for administrative or troubleshooting purposes. For more information, see "Validating QuickTest Licenses" on page 95.


## Requesting a Seat License Key

When you install QuickTest Professional with a seat license for the first time, it includes a 30-day demo license. To use QuickTest Professional beyond the 30-day period, you must request and activate a license key for your copy of QuickTest Professional.

### To request a seat license key:

- 1 Perform one of the following:
  - From the license warning message displayed when you start QuickTest Professional, click **Install License**.
  - From within QuickTest Professional, select **Help > About QuickTest Professional**. The About QuickTest Professional dialog box opens. Click **License**. The License Summary dialog box opens. Click **Modify License**.

The License Type screen opens. Select **Seat license** and click **Next**. Click **Yes** to install a new license key. The Welcome screen opens.



- 2 Make a record of the displayed locking code for your computer. You will need it to request your license key. Click the link on the QuickTest Professional License Installation - Welcome screen for the **HP Webware License Key Delivery Service** to request your license key. Follow the instructions as described in "Requesting a License Key via the HP Webware License Key Delivery Service" on page 67.

## Requesting a License Key via the HP Webware License Key Delivery Service

The HP Webware License Key Delivery Service assists you in requesting a license key. This procedure provides an overview of this process as it specifically relates to requesting QuickTest Professional license keys.

For details on the individual fields in the License Key Delivery Service form, download the ESD and Webware License Management Guide. (Click the **Webware User Guide** link in the **Support** section of the HP License Key Delivery Service Welcome page.)

### To request a license key:

- 1** Click the link on the QuickTest Professional License Installation - Welcome screen for the **HP Webware License Key Delivery Service**. The HP License Key Delivery Service Welcome page is displayed.
- 2** Click **Generate New Licenses**. The Generate license(s) page is displayed.
- 3** Enter the order number from the Software Entitlement Certificate you received in your LTU or ELTU package.
- 4** Click **Next**. The Product Selection page is displayed.
- 5** Select the check box next to the product for which you are requesting a license key.
- 6** Click **Next**. The Order Product Detail(s) page is displayed.
- 7** Enter the locking code for your computer. The locking code is found in the QuickTest Professional License Installation - Welcome screen.
- 8** Click **Next**. The Member sign-in page is displayed.
- 9** If you have used the Webware Licensing service before, enter your e-mail address and password. Otherwise, login as a new user.
- 10** Click **Sign-in**. The Address information page is displayed. If you are a returning user, Webware automatically populates the fields with your information. If you are a new user, fill in the information according to the on-screen instruction. For information on filling in the Address information page, see the ESD and Webware License Management Guide.

- 11** If you are a customer representative requesting a license key on behalf of a customer and do not want them to receive a copy of the transaction, deselect the **E-mail a copy of this license transaction to the license owner** check box.
- 12** If you are the end-user customer select the **I am the License owner** check box. The **License owner (End-user) information** section is disabled.
- 13** If you are a customer representative requesting a license key on behalf of a customer, deselect the **I am the License owner** check box. Complete the information requested in the **License owner (End-User) information** section.
- 14** Click **Next**. The License/Password page is displayed. Keep a record of your **Session ID** and click **Main Menu** to return to the Welcome page. A Permanent Password Certificate will be e-mailed to the address you provided, containing your license key.
- 15** Click **Cancel** and wait for your Permanent Password Certificate to arrive by e-mail. When it arrives, follow the instructions as described in "Installing a Seat License Key" on page 68.

## Installing a Seat License Key

In the License Key screen, you enter the license key you received from HP. The license key is included in the **.dat** file attached to the e-mail containing your Permanent Password Certificate.

---

### Caution:

- You must have Administrator privileges to install a license key.
  - After installing the seat license key, do not change your computer's date or time. This triggers a **Clock Tamper** lock on the license information, preventing you from using the license.
-

**To install a seat license key:**


- 1** Perform one of the following:
  - From the warning message displayed when you start QuickTest Professional, click **Install License**.
  - From within QuickTest Professional, select **Help > About QuickTest Professional**. In the About QuickTest Professional dialog box, click **License**. Then in the License Summary dialog box, click **Modify License**.

---


**Note:** You can also activate the seat license as part of the QuickTest installation. After you click **Finish** in the final installation screen, the QuickTest Professional License Installation - Welcome screen opens, as described below.

---

The License Type screen opens.



- 2 Select **Seat license** and click **Next**. In the confirmation box, click **Yes** to install a new license key. The Welcome screen opens.




---

**Tip:** Check that the locking code in the above screen matches the locking code you sent to HP when you requested a license key.

---

- 3 Click **Next** to begin installing the license. The License Key screen opens.



---

**Notes:**


- The license key is valid only for the computer with the locking code that you entered in the HP Software Support license request form.
  - A computer with multiple bootable partitions may generate a different locking code for each partition. If a different locking code is generated for a partition, you will need to request a unique license key for it.
- 

- 4 Open the **.dat** file attached to the email containing your Permanent Password Certificate using any text editor. The license key is also included in the Permanent Password Certificate.


- 5 Copy the license key (with or without the # character) from the **.dat** file to the clipboard.



- 6 Paste the key into the QuickTest Professional License Installation - License Key screen by clicking the **Paste From Clipboard** button.
- 7 Click **Next**. The Install Summary screen opens.



- 8 Verify that the information is correct and click **Next**. The Finish screen opens.



If you entered a valid license key, the Finish screen confirms that your license key was successfully installed.

If the license could not be installed successfully, a message is displayed describing why. For example, if a seat license was previously installed on your computer, and you try to install a seat license again using the same license key, the license installation will not succeed. If the license could not be installed, a **Send to Support** button is displayed. You can click **Send to Support** to create an e-mail with licensing information and send it to your nearest HP Software Support location. Make sure that you fill in the required information in the e-mail so that Software Support can assist you.

---

**Tip:** You can install another license by selecting the **Install another license** check box, clicking **Finish** and continuing with step 2 on page 71.

---

- 9 If you do not want to install another QuickTest license, click **Finish** to complete the license activation process and close the wizard.

## Working with a Concurrent License

If there is an accessible concurrent license server on your network with an available license, you can connect to it. This enables you to use a concurrent license instead of a seat license. For more information on working with concurrent license servers, and the supported versions, see the *HP Functional Testing Concurrent License Server Installation Guide*.

---


**Note:** You can also specify a concurrent license server during the QuickTest installation procedure. For more information, see "Installing QuickTest Professional" on page 22.

---


**To work with a concurrent license:**

- 1 Perform one of the following:
  - From the license warning message displayed when you start QuickTest Professional, click **Install License**.
  - From the Start menu, select **Start > Programs > HP QuickTest Professional > Tools > Additional Installation Requirements**, and select **Install License**.
  - From within QuickTest Professional, select **Help > About QuickTest Professional**. The About QuickTest Professional dialog box opens. Click **License**. The License Summary dialog box opens. Click **Modify License**.

The License Type screen opens.



- 2 Select **Concurrent license** and click **Next**. The Concurrent License Server screen opens.




- 3 In the edit box, either enter the name or IP address of the concurrent license server to which you want to connect, or leave the box blank to instruct QuickTest to search for an available server on your local network.

---

**Tip:** When you activate a concurrent license using the License Wizard and specify a single server name, the `LSFORCEHOST` user variable is automatically defined with the concurrent license server you specified. You can modify the concurrent license server either by running the License Wizard or by setting the `LSHOST` or `LSFORCEHOST` user variable. For more information, see the *HP Functional Testing Concurrent License Server Installation Guide*.

---

- 4 Click **Check Connection**. If QuickTest can connect to the concurrent license server, a success message is displayed.




---

**Note:** If the installation cannot connect to a concurrent license server, the Concurrent License Server screen informs you of this.

---

**Tip:** If you want to specify the name of a concurrent license server that is currently unavailable, but will be available later, you can enter the name of the concurrent license server in the edit box. Even though the Concurrent License Server screen informs you that the specified server is not available for connection, the next time you open QuickTest, QuickTest will try to locate the server you specified.

- 5 Click **Next**. The installation informs you that the concurrent license activation was successful.



- 6 Click **Finish** to close the wizard. If QuickTest Professional is open, you must close and restart it to use the concurrent license server.

## Modifying License Information

After you install QuickTest Professional, you can modify your license key and/or change your license type at any time. For more information on requesting a new license key, see "Requesting a Seat License Key" on page 65.


---

**Note:** You must be logged in with administrator privileges to change the license type used by your QuickTest installation from seat to concurrent or vice versa.


---

**To modify your license information:**

- 1 Open QuickTest Professional.
- 2 Click **Help > About QuickTest Professional**. The About QuickTest Professional dialog box opens.
- 3 Click **License**. The License Summary dialog box opens.



**4** Click **Modify License**. The License Type screen opens.



- To change your license type from concurrent to seat, select **Seat license** and click **Next**. A confirmation box opens.
- If you already have a valid seat license key installed, click **No** to save your selected license type.
- If you checked out a commuter license and want to use it now, click **No**.
- If you do not have a seat license key installed, click **Yes**.

The Welcome screen opens. Follow steps 4 to 9 in Installing a Seat License Key.

- To change your license type from seat to concurrent, select **Concurrent license** and click **Next**. Follow steps 2 to 6 in Working with a Concurrent License.

---

**Note:** To work with a concurrent license, a concurrent license server must be installed on and accessible from the network, and a concurrent license must be available. For information on installing a concurrent license server, see the *HP Functional Testing Concurrent License Server Installation Guide*.

---

- 5 Click **Close** to close the About QuickTest Professional dialog box.
- 6 Restart QuickTest Professional to apply your changes.

## Working with Commuter Licenses

If you use QuickTest with a concurrent license, but cannot connect your computer to your network (for example, during a business trip), you can install a commuter license. Commuter licenses are available in companies that have only concurrent licenses (not seat licenses).

For example, suppose you need to travel on business with your laptop computer and you want to use QuickTest while you are away. You can check out a QuickTest license from the concurrent license server to use for the duration of your trip, and then check the license back in upon your return. Commuter licenses are valid for up to 180 days, according to your requirements.

---

**Tip:** If you have a concurrent license and are located far from the concurrent license server, you can also use a commuter license if you encounter network traffic.

---

For more information, see "Checking Out a Commuter License" below, and "Checking In a Commuter License" on page 86.

---

**Note:** Installing a commuter license requires administrator permissions for the computer on which you want to use the license.

---

In addition, if you are unable to check out a license before you disconnect from the network (that is, leave for your trip), or if you checked out a license but it expired because your return was delayed, you can ask a local network user to check out a commuter license and send it to you remotely. For more information, see "Obtaining a Commuter License Remotely" on page 87.

---

**Note:** If you have upgraded to HP Functional Testing Concurrent License from a version earlier than 7.6, you need to request a new server license key to enable the commuter licensing functionality. For details, contact HP Software Support or your local representative.


---

## Checking Out a Commuter License

Before you check out a commuter license, ensure that the computer (for example, a laptop) on which you want to install the commuter license has QuickTest installed, is connected to the network, and has access to a concurrent license server with an available QuickTest license. After you have checked out the license, you can disconnect the computer from the network.

**To check out a commuter license:**

- 1 Run the **WCommute.exe** file located in **<QuickTest installation folder>\bin**. The WCommute dialog box opens.



- 2 To see commuter licenses available on all concurrent license servers located within your subnet, click **Search Subnet**. If you want to specify a particular concurrent license server, or if you want to select a concurrent license server outside of your subnet, click **Single Server**.
  - If you click **Search Subnet**, the WCommute utility searches the subnet for concurrent license servers that support commuter licensing and displays them in the WCommute dialog box. Note that this process may take several minutes.

- If you click **Single Server**, a dialog box opens enabling you to specify the concurrent license server you want to locate. Enter the concurrent license server computer's host name, IP address, or IPX address and click **OK**. The specified concurrent license server is located and displayed in the WCommute dialog box.

For each concurrent license server, a list of available commuter licenses is displayed. A red check mark next to a commuter license means that the license is already checked out to your computer. You cannot check out multiple licenses for the same application to the same computer. Click a license to view the license details in the right pane of the dialog box.

- 3 Select the license that you want to check out.
- 4 In the **Enter number of days until the commuter authorization expires** box, specify the maximum number of days to check out the license. The maximum number of days is 180.

---

**Note:**

- QuickTest Professional supports the Sentinel RMS License Manager version 8.3.0 as its concurrent license server. If you are upgrading to QuickTest Professional with a concurrent license, you must also upgrade your concurrent license server.
  - When you check out a license, it decreases the number of licenses available for use by others. Therefore, you should specify the absolute minimum number of days that you require.
- 

- 5 Click **Check Out**. The selected license is saved locally on your computer.
- 6 To use the new checked-out license, open QuickTest and change your license type from concurrent to seat. In the confirmation message that opens after you change the license type, click **No** to use the commuter license. For more information, see "Modifying License Information" on page 80.

## Checking In a Commuter License

When you finish using the commuter license, you should check it in from your computer to the concurrent license server from which you checked it out. This makes the license available to other users.


---

**Note:** If your license expires, you do not need to check it in. When a license expires, you can no longer use it. The license is automatically returned to the concurrent license server, even if your computer is not connected to the concurrent license server network.

---

**To check in a commuter license:**

- 1 Run the **WCommute.exe** file located in **<QuickTest installation folder>\bin**. The WCommute dialog box opens.



- 2 Locate the concurrent license server for the commuter license you want to check in, as described in step 2 of “Checking Out a Commuter License” on page 84. You must check in the license to the same concurrent license server from which you checked it out.

- 3 Select the license you previously checked out.

---

**Tip:** The checked-out license is indicated by a red check mark.

---

- 4 Click **Check In**. The license is returned to the concurrent license server, and is made available for use by others.

---

**Note:** Before you can use QuickTest again, you must change your license type from seat to concurrent. For more information, see "Modifying License Information" on page 80.

---

## Obtaining a Commuter License Remotely

A local network user can locally check out a QuickTest commuter license and send it to you for installation on a remote computer. This is useful in situations in which you are currently not connected to the concurrent license server network. For example, you may be out of the office on an extended business trip, but need to be able to use QuickTest.

### To obtain a commuter license remotely:

- 1 Run the WRCommute utility to generate a commuter locking code for your computer and send the commuter locking code to a local user who has access to the concurrent license server. For more information, see "Step 1: Generating a Remote Computer Locking Code" on page 88.
- 2 Ask the local user to run the WCommute utility (entering the commuter locking code you generated) to check out a remote commuter license, and send it to you. For more information, see "Step 2: Checking Out a Commuter License for a Remote Computer" on page 90.
- 3 Run the WRCommute utility to install the remote commuter license on your computer. For more information, see "Step 3: Installing a Commuter License on a Remote Computer" on page 93.

- 4 Open QuickTest and change your license type from concurrent to seat. In the confirmation message that opens after you change the license type, click **No** to use the commuter license. For more information, see "Modifying License Information" on page 80.

### Step 1: Generating a Remote Computer Locking Code

The first step in remotely obtaining a commuter license is to generate a locking code on your computer using the WRCommute utility, and transfer it (by e-mail) to a network user who has access to the concurrent license server.


---

**Note:** The remote computer locking code used to lock a commuter license is not the same as the locking code displayed by the ECHOID utility. You must use the WRCommute utility to obtain the commuter license locking code.

---

**To generate a locking code on a remote computer:**

- 1 Run the **WRCommute.exe** file located in <QuickTest installation folder>\bin. The WRCommute dialog box opens.



The **Locking code string for the current machine** box contains the locking code that you need to e-mail to a network user who has access to the concurrent license server containing the QuickTest licenses.

- 2** Send the locking code to the local network user in one of the following ways:



- Select the locking code string and click the **Copy to clipboard** button to copy the string to your Windows clipboard. Then open your e-mail program and paste the string into a new e-mail message and e-mail it to the local network user.



- Click the **Save lock code string to file** button to save the locking code in a file. Specify the name and location for the file, and then attach the file to a new e-mail message and e-mail it to the local network user.




- Click the **Display locking code string** button to display the entire locking code in another dialog box. You can then select the locking code string, right-click it and select **Copy** to copy it to your Windows clipboard. Then open your e-mail program and paste the string into a new e-mail message and e-mail it to the local network user.
- In the **E-mail address** box, enter the e-mail address of the local network user and click **Send**. Note that this option is supported only if Microsoft Outlook Express is set up as your e-mail client.

## Step 2: Checking Out a Commuter License for a Remote Computer

After a local network user receives the locking code, the user can check out the license and transfer it to you (by e-mail). To do this, the user must have QuickTest installed on his or her computer and also have access to the concurrent license server with an available QuickTest license.

To check out a commuter license for a remote computer:

- 1 Run the **WCommute.exe** file located in **<QuickTest installation folder>\bin**. The WCommute dialog box opens.



- 2 Locate the concurrent license server from which you want to check out a remote commuter license, as described in step 2 of “Checking Out a Commuter License” on page 84.

For each concurrent license server, a list of commuter licenses that you can check out is displayed.

- 3 Select the license that you want to check out.
- 4 Select the **Check out authorization for remote machine** check box.


- 5 In the **Enter the number of days until the authorization expires** box, specify the number of days to check out the license. The maximum number of days is 180.

---

**Note:**

- QuickTest Professional supports the Sentinel RMS License Manager version 8.3.0 as its concurrent license server. If you are upgrading to QuickTest Professional with a concurrent license, you must also upgrade your concurrent license server.
  - When you check out a license for a remote computer, it cannot be checked in and remains in use (unavailable to other users) for the entire number of days specified. Therefore, you should specify the absolute minimum number of days required.
- 

- 6 Click **Check Out**. The Locking Code for Remote Machine dialog box opens.



- 7 Enter the locking code that the remote user e-mailed you in one of the following ways:




- If the locking code was e-mailed to you in the body of an e-mail, copy it to your Windows clipboard. In the Locking Code for Remote Machine dialog box, select **Enter the locking code string for remote machine** and then click the **Paste from clipboard** button.



- If the locking code was e-mailed to you as an attached file, save the attachment and then select **Get locking code string for remote machine from file**. Click the **Load** button. Select the file that contains the locking code and click **Open**.

- 8 Click **OK**. The Remote Commuter Licensing dialog box opens.



- 9 Send the commuter license to the remote user in one of the following ways:




- Click the **Save** button to save the locking code in a file. Specify the name and location for the file, click **Save** and then click **OK**. Attach the file to a new e-mail message and e-mail it to the remote user.
- In the **E-mail address** box, enter the e-mail address of the remote user. Click **Send** and then click **OK**. Note that this option is supported only if Microsoft Outlook Express is set up as your e-mail client.

### Step 3: Installing a Commuter License on a Remote Computer

The final step in remotely obtaining a commuter license is to install the license that was sent to you by the network user on your computer.

To install a commuter license on a remote computer:

- 1 Ensure that you are logged in to your computer with administrator privileges.
- 2 Run the **WRCommute.exe** file located in <QuickTest installation folder>\bin. The WRCommute dialog box opens.
- 3 Click the **Install Remote Authorization Code** tab.



- 4 Enter the commuter license that the network user e-mailed you, as follows:



- If the commuter license was e-mailed to you in the body of an e-mail, copy it to your Windows clipboard. In the Install Remote Authorization Code tab of the WRCommute dialog box, select **Enter remote authorization code** and then click the **Paste from clipboard** button.



- If the commuter license was e-mailed to you as an attached file, save the attachment and then select **Get remote authorization code(s) from file**. Click the **Load** button. Select the file that contains the locking code and click the **Open** button.

- 5 Click **Install**. The new license code is installed on your computer.

#### Step 4: Modifying the License Type on the Remote Computer

Open QuickTest and change your license type from concurrent to seat. In the confirmation message that opens after you change the license type, click **No** to use the commuter license. For more information, see "Modifying License Information" on page 80.

---

**Note:** A remote commuter license cannot be checked in to the concurrent license server when you have finished using it—it simply expires on the remote computer. After you return to your office and are reconnected to the network, you should change your license type from seat to concurrent. For more information, see "Modifying License Information" on page 80.

---

## Validating QuickTest Licenses

The License Validation Utility decodes and validates QuickTest Professional license strings. This enables you to view and copy license information and license validation information for troubleshooting purposes.


The License Validation Utility performs the following operations:

- Decodes the license string and retrieves important information regarding the license. For more information, see "License Information" on page 98.
- Validates the license according to a predefined set of checks. For more information, see "Validation Checks" on page 99.

If required, you can copy the decoding and validation results to the clipboard. For more information, see "Copying your License Validation Result to the Clipboard" on page 99.

**To decode and validate a license:**

- 1 Select **Start > Programs > HP QuickTest Professional > Tools > License Validation Utility**.



- 2 In the **License Key** box, enter the license code you want to decode and validate. You can find the license code already installed on a QuickTest computer in the **lservrc** file. The location of this file is specified by the **lservrc** environment variable.

---

**Tips:**

- When you enter the license code, ensure that a # character is inserted at the end of the license code, or an error will be reported in the **License validation results** area. The # indicates the end of the license code, and any string after the # character is ignored by the License Validation Utility.
  - To find the path of the **lservrc** file in the environment variable, right-click **My Computer** and select **Properties**. In the System Properties dialog box, select the **Advanced** tab, and then click **Environment Variables**. The path is displayed in the **User variables for <user>** box of the Environment Variables window for the LSERVRC variable. For example, C:\Program Files\Common Files\HP\License Manager\lservrc.
- 

- 3** Click **Validate**. The license string is decoded.

License information is displayed in the **License information** area. For more information, see "License Information" on page 98.

The result of the validation is displayed in the **License validation results** area. For more information, see "Validation Checks" on page 99.

- 4** If required, click **Copy** to copy the information to the clipboard. The copied information includes the current computer locking code, the license string that was decoded, and the decoding and validation results. For more information, see "Copying your License Validation Result to the Clipboard" on page 99.
- 5** Click **Close** to close the utility.

## License Information

The result of the decoding operation includes the following information about the license.

---

**Note:** Some information provided by the operation is intended for HP Software Support only and is not described here.

---

- **Feature Name.** The QuickTest feature name specified when the license was created.
- **Feature Version.** The license version specified when the license was created. This is not the QuickTest Professional version number.
- **Seat/Concurrent.** The license type. This can be either a **Seat** license that is specific to the computer on which it is installed, or a **Concurrent** license, which references a current license server that can be used by multiple QuickTest users.
- **Trial/Normal.** The license type. It can be either a **Trial** license, which is a demo license that has a limited period of use, or a **Normal** license.
- **Trial Days Count.** Applicable only for trial licenses. Specifies the number of days until the trial period is over. The count is started from the date the QuickTest core components are installed.
- **Locking Code.** The locking code specified when the license was created. This code uniquely identifies the computer on which QuickTest is installed.
- **Clock Tamper.** Indicates whether a license can be issued, based on whether any date changes have been made to the computer on which QuickTest is installed.
- **Commuter License.** Indicates whether commuter licenses are supported. A commuter license enables you to work with QuickTest Professional when you are not connected to the QuickTest concurrent license server. Commuter licenses are available only with concurrent licenses. For more information, see "Working with Commuter Licenses" on page 82.

## Validation Checks

The validation checks performed by the License Validation Utility include the following:

- 1** Does the QuickTest feature name match one of the existing features?
- 2** Does the license version match one of the existing versions?
- 3** Does the locking code match the locking code of the computer on which QuickTest is installed?
- 4** Has the trial period specified in the license string ended?
- 5** If the license is a concurrent license, does it support commuter licenses?

## Copying your License Validation Result to the Clipboard

In some cases, you may need a copy of the information provided by this utility. For example, you may need to forward this information to HP Software Support.

When the validation operation is complete, click the **Copy** button to copy the information to the clipboard. Then paste the information as required.

## Troubleshooting Concurrent Licensing Issues

In certain circumstances, QuickTest Professional cannot connect to the license server, and a License Error message opens.

Check whether one or more of the following are causing the error:

- "There is no network connection between the server and client computers" on page 100
- "The license server is not running" on page 101
- "Licenses are not installed on the license server" on page 101
- "The license key file (lservrc) cannot be found on the server" on page 102
- "The license server is being used by the maximum number of users" on page 102
- "Two or more versions of the license server are running" on page 103
- "The client computer is configured to use a seat license" on page 103
- "The license key does not match the license server locking code" on page 103
- "The client computer cannot identify the license keys on the server computer" on page 104
- "The LSHOST or LSFORCEHOST variables are not set" on page 105
- "The LSERVRC system variable is set on the client computer" on page 105
- "The client computer connects through VPN software" on page 105

### **There is no network connection between the server and client computers**

You can check the network connection between the client and server machines by pinging the license server machine in a command prompt window.

For example: `c:\ ping <license server name>`

If there are no replies from the ping command, or if there are timeouts in the replies, there may be a network problem. If required, contact your Computer or Network Administrator.

## The license server is not running

You may need to start or restart the license server service.

**To start or restart the license server service:**

- 1** Open the Control Panel (**Start > Settings > Control Panel**).
- 2** Select **Services**.

---

**Note:** On some operating systems, such as Windows 2000, the Services utility is located in the Administrative Tools section (folder) of the Control Panel.

---

- 3** Select **SentinelRMS** service.
- 4** Click **Start the Service** (or **Restart the Service**), or right-click and select **Start** (or **Restart**).

## Licenses are not installed on the license server

Use the WlmAdmin utility to check that licenses are installed on the license server. For more information on the WlmAdmin utility, see the **Utilities** chapter in the *HP Functional Testing Concurrent License Server Installation Guide*.

**To check licenses on the license server:**

- 1** Run **SrvUtils.exe** in the **LicenseServer\utils** folder of the QuickTest Professional installation DVD.
- 2** Select **WlmAdmin**.
- 3** Enter the license server name as a defined server.
- 4** Try to expand the license server branch.

If no license key information is displayed, then the installed licenses are invalid, or the license key file (lservrc) cannot be found. If license key information is displayed, then the installed licenses are valid. You can check whether the licenses are all in use by selecting a license and checking the **Statistics** pane in the WlmAdmin utility.

### **The license key file (lservrc) cannot be found on the server**

The lservrc file should be located in the following directory:

**<drive>\Program Files\Common Files\SafeNet Sentinel\Sentinel RMS License Manager\WinNT**

If the file is not there, the license server will not be able to locate licenses. Search the license server computer for the file. If found, move the file to the correct directory and restart the SentinelLM service. If the file is not found, licenses are not installed.

### **The license server is being used by the maximum number of users**

- If all licenses are in use, the License Server Manager will not be able to issue another license until a license is released. You can use the WlmAdmin utility to determine which users are currently using the licenses. Run **SrvUtils.exe** in the **LicenseServer\utils** folder of the QuickTest Professional installation DVD, and select **WlmAdmin**.

For more information on the WlmAdmin utility, see the **Utilities** chapter in the *HP Functional Testing Concurrent License Server Installation Guide*.

- There may be cases where QuickTest closes unexpectedly and does not release the license automatically. If this happens, you can wait for the license to timeout, or you can restart the license server.

For more information, see the HP Software Self-solve knowledge base (<http://h20230.www2.hp.com/selfsolve/document>) (the Knowledge Base area requires that you register as an HP Passport user and sign in). In the knowledge base, search for:

**Document ID 18428.** "What happens if AQT/QTP crashes on a client machine while using a Floating license".

## Two or more versions of the license server are running

Only one version of the license server should be installed and running on the same computer. If there are more versions, use Add/Remove Programs to uninstall all of the license server instances. Then install the latest version of the license server software and reinstall the license code keys.

## The client computer is configured to use a seat license

For information on how to check and modify concurrent license or seat license configuration, see "Modifying License Information" on page 80.

## The license key does not match the license server locking code

Use the **lsdecode.exe** utility to check the locking code for a license key.

To check the license key locking code:

- 1** Copy the **lsdecode.exe** utility from the **LicenseServer\utils** folder of the QuickTest Professional installation DVD to the location of the **lservc** file (**<drive>\Program Files\Common Files\SafeNet Sentinel\Sentinel RMS License Manager\WinNT**).
- 2** Run the **lsdecode.exe** utility. A command prompt window will open with the decoded key information.

The locking code for the license key is displayed on the **Server locking code** line.

- 3** Run the **inst\_key.exe** utility from the **LicenseServer\KeyInstallation** folder of the QuickTest Professional installation DVD.

The license server computer's locking code will be displayed on the Welcome screen.

---

**Note:** This step must be done on the license server computer. Accessing the license server computer remotely can generate an invalid license code.

---

- 4 Compare the locking code for the license key and from the server computer.

If the locking codes do not match, you will need to determine why the locking code has changed. Reinstalling the operating system, renaming the computer, using a dynamic IP address, retrieving the locking code through a terminal session, or installing the license keys through a terminal session can cause the locking code to be changed and the license keys to become invalid.

After you have determined why the locking code has changed, you can submit a License Request to have a new license key generated.

### **The client computer cannot identify the license keys on the server computer**

Use the WlmAdmin utility to check the licenses on the client computer. For more information on the WlmAdmin utility, see the **Utilities** chapter in the *HP Functional Testing Concurrent License Server Installation Guide*.

#### **To check licenses on the client computer:**

- 1 Run **SrvUtils.exe** in the **LicenseServer\utils** folder of the QuickTest Professional installation DVD.
- 2 Select **WlmAdmin**.
- 3 Enter the license server name as a defined server.
- 4 Try to expand the license server branch.

If license keys are not identified, then either UDP Port 5093 is blocked between the client and server, or the IP address of the license server is using Network Address Translation (NAT), which is not supported. If required, contact your Computer or Network Administrator.

For more information, see the HP Software Self-solve knowledge base (<http://h20230.www2.hp.com/selfsolve/document>) (the Knowledge Base area requires that you register as an HP Passport user and sign in). In the knowledge base, search for:

- **Document ID 18402.** "What is port 5093 in the license mechanism used for?"
- **Document ID 41449.** "Does UDP port 5093 need to be bi-directional?"
- **Document ID 18424.** "How to set up the License Manager for machines running on different subnets."

### **The LSHOST or LSFORCEHOST variables are not set**

For information on how to set these variables, see the *HP Functional Testing Concurrent License Server Installation Guide*.

### **The LSERVRC system variable is set on the client computer**

The LSERVRC variable is used for seat licenses and may have been created for the demo license when QuickTest was installed. If this variable exists, it must be removed so it does not interfere with locating the license server.

**To remove The LSERVRC system variable:**

- 1** On your desktop, right-click **My Computer** and select **Properties**.
- 2** Select the **Advanced** tab and click **Environment Variables**.
- 3** Check the System Variables list for the LSERVRC variable. If it exists, click **Delete**.
- 4** Click **OK** to close the windows.
- 5** Reboot the client computer to implement the changes.

### **The client computer connects through VPN software**

If the client computer is connecting through VPN software, verify that VPN has **not** been configured to use **IPSec over UDP**. This configures the network to use Network Address Translation (NAT), which is not supported.



# 4

---

## Maintaining and Uninstalling QuickTest Professional

You can install and uninstall individual QuickTest Professional features, or uninstall all QuickTest Professional software and files (including add-ins). You can also repair a QuickTest Professional installation that has become corrupted.

---

**Note:** In some situations, you may be prompted to restart your computer after you have installed or made changes to the QuickTest installation. It is recommended that you restart your computer as soon as possible if you are prompted to do so. Delaying the system restart may result in unexpected QuickTest behavior.

---

### **This chapter includes:**

- Installing and Uninstalling Specific QuickTest Professional Features on page 108
- Repairing Your QuickTest Professional Installation on page 110
- Uninstalling QuickTest Professional on page 111
- Saving and Restoring Your QuickTest Settings on page 113
- Troubleshooting and Limitations - Uninstalling QuickTest on page 117

## Installing and Uninstalling Specific QuickTest Professional Features

Your QuickTest Professional DVD enables you to install or uninstall specific QuickTest Professional features. For example, you can install or uninstall an add-in or the sample applications provided with QuickTest Professional.

---

**Note:** You can also install or uninstall specific QuickTest Professional features by choosing **Start > Settings > Control Panel > Add or Remove Programs**, and then clicking the **Change** button for QuickTest Professional.

---

The procedure for installing or uninstalling features is similar to the procedure for performing a Custom installation. For more information on the specific screens mentioned in the procedure below, see "Installing QuickTest Professional" on page 22.

---

**Note:** Before uninstalling QuickTest Professional features, make sure that you have a minimum of 50 MB free disk space.

---

### To install or uninstall QuickTest Professional features:

- 1 Insert the QuickTest Professional DVD into the DVD drive. If the DVD drive is on your local computer, the QuickTest Professional Setup window opens.

If the DVD is in a network drive, double-click **setup.exe** in the root folder of the DVD. The QuickTest Professional Setup window opens.

---

**Note:** You must use the same QuickTest Professional version that you used for the original installation.

---

- 2 Click **QuickTest Professional Setup**. The Welcome to the HP QuickTest Professional Setup Wizard opens. Click **Next** to proceed.
- 3 The Maintenance Type screen opens. Select **Modify** and click **Next**.
- 4 In the Custom Setup screen, click an icon to view a menu and select how that feature is installed on your computer. The following options are available, depending on the feature:



- **Will be installed on local hard drive.** Installs the selected feature on your local hard drive.



- **Entire feature will be installed on local hard drive.** Installs the entire selected feature on your local hard drive.



- **Entire feature will be unavailable.** Excludes the feature from the installation and it is not available in QuickTest.

You can select an item in the list to see a description of the feature as well as the space requirement on your drive for the feature, or how much space will be freed up if the feature is uninstalled.

Click **Next** to proceed.

- 5 Click **Next** in the Confirm Installation screen. The Installing HP QuickTest Professional screen displays the progress of the application modification.
- 6 The Installation Complete screen opens. Click **Finish**.

---

**Note:** If you install a feature that has prerequisites for use with QuickTest, the Additional Installation Requirements dialog box will open after the feature is installed. For more information, see "Working with the Additional Installation Requirements Utility" on page 35.

---

## Repairing Your QuickTest Professional Installation

Your QuickTest Professional DVD enables you to repair an existing QuickTest Professional installation, by replacing any missing or damaged files from your previous QuickTest Professional installation.

---

**Note:** You can also repair an existing QuickTest Professional installation by choosing **Start > Settings > Control Panel > Add or Remove Programs**, and then clicking the **Change** button for QuickTest Professional.

---

### To repair your QuickTest Professional installation:

- 1** Insert the QuickTest Professional DVD into the DVD drive. If the DVD drive is on your local computer, the QuickTest Professional Setup window opens.

If the DVD is in a network drive, double-click **setup.exe** in the root folder of the DVD. The QuickTest Professional Setup window opens.

---

**Note:** You must use the same QuickTest Professional version that you used for the original installation.

---

- 2** Click **QuickTest Professional Setup**. The Welcome to the HP QuickTest Professional Setup Wizard opens.
- 3** Click **Next** to proceed. The Maintenance Type screen opens.
- 4** Select **Repair** and click **Next**. Then click **Next** on the Confirm Repair screen. The Setup Status screen displays the progress of the repair process.

**Note:** The repair process might take some time to start. During this time, the wizard might not respond. Afterwards, the Run Setup screens open and the repair process continues.

---

- 5 Click **Finish** in the Installation Complete screen.

## Uninstalling QuickTest Professional

You can uninstall QuickTest Professional using the **Add or Remove Programs** option in the Windows Control Panel or using the QuickTest Professional DVD.

You can save your existing customization settings and registry keys before you uninstall QuickTest Professional, and then if required, restore them after you install a new version. For more information, see "Saving and Restoring Your QuickTest Settings" on page 113.

Before uninstalling QuickTest, make sure that you have a minimum of 50 MB free disk space.

---

### Notes:

- You can uninstall specific QuickTest Professional features as described in "Installing and Uninstalling Specific QuickTest Professional Features" on page 108.
  - You can uninstall individual QuickTest Professional hotfixes (patches) using the **Add or Remove Programs** option in the Windows Control Panel.
-

**To uninstall QuickTest Professional using the Add or Remove Programs option in the Windows Control Panel:**

- 1** Select **Start > Settings > Control Panel > Add or Remove Programs**. The list of currently installed programs opens.
- 2** Select **QuickTest Professional** and click **Remove**. A message prompts you to confirm your decision to uninstall QuickTest Professional. Click **Yes** and follow the on-screen instructions to uninstall QuickTest Professional. Click **No** to keep QuickTest Professional installed on your computer.

The uninstall program removes all QuickTest Professional features from your computer (including any QuickTest Professional add-ins).

**To uninstall QuickTest Professional using the QuickTest Professional DVD:**

- 1** Insert the QuickTest Professional DVD into the DVD drive. If the DVD drive is on your local computer, the QuickTest Professional Setup window opens.

If the DVD is in a network drive, double-click **setup.exe** in the root folder of the DVD. The QuickTest Professional Setup window opens.

---

**Note:** You must use the same QuickTest Professional version that you used for the original installation.

---

- 2** Click **QuickTest Professional Setup**. The Welcome to HP QuickTest Professional Setup Wizard opens.
- 3** Click **Next**. The Maintenance Type screen opens.
- 4** Select **Remove** and click **Next**. Click **Next** in the Confirm Uninstall screen.

The uninstall program removes all QuickTest Professional features from your computer (including any QuickTest Professional add-ins).

- 5** Click **Finish** in the Removal Complete screen.

**Note:** Uninstalling QuickTest Professional does not uninstall any non-HP applications that you install as part of the QuickTest Professional installation, for example, the Microsoft Script Debugger or the Microsoft .NET Framework. You can uninstall these applications using the **Add or Remove Programs** dialog box in the **Control Panel**.

---

## **Saving and Restoring Your QuickTest Settings**

If you are upgrading from QuickTest Professional 9.2 or earlier, you need to first uninstall your previous version. The Save and Restore Settings utility enables you to save some existing customization settings and registry keys before you uninstall an old QuickTest version, and then restore them after you install the new version.

The Save and Restore Settings utility is particularly useful for saving the manual customizations made to Web event recording configuration **.xml** files.

For a list of the files and settings saved by the Save and Restore Settings utility, see "Saved Files And Settings" on page 115.

The Save and Restore Settings utility does not backup your tests folder. Although the uninstall process does not delete QuickTest tests, you may want to create a backup copy of your tests folder before uninstalling.

**To save existing settings:**


- 1 Before uninstalling your previous QuickTest version, run the **SaveRestoreSettings.exe** file located in the root of the QuickTest installation DVD.

---

**Note:** After installing QuickTest Professional, the Save and Restore Settings utility is also available from **Start > Programs > HP QuickTest Professional > Tools > Save and Restore Settings**.

---

The Save and Restore Settings dialog box opens.



- 2 Select the **Save settings to** radio button option and enter the location and **.zip** file name in which you want to save your existing QuickTest Professional customization settings, and registry keys.
- 3 Click **OK** to save your settings.

**To restore saved settings:**

- 1** After installing QuickTest Professional, select **Start > Programs > HP QuickTest Professional > Tools > Save and Restore Settings**. The Save and Restore Settings dialog box opens.
- 2** Select the **Restore settings from** radio button option and enter the location and **.zip** file name in which your QuickTest Professional customization settings, and registry keys are saved.
- 3** Click **OK** to restore your settings.

**Saved Files And Settings**

The Save and Restore Settings utility saves specific files from the **bin** and **dat** folders in the QuickTest Professional installation folder, and specific QuickTest registry keys.

**Bin Folder Files**

The following files in the <**QuickTest Professional installation**>\bin folder are saved by the Save and Restore Settings utility:

- **Mic.ini**
- **Qtreport.ini**

**Dat Folder Files**

The following files from the <**QuickTest Professional installation**>\dat folder are saved by the Save and Restore Settings utility, if they exist (depending on the installed add-ins):

Related Add-in	File Name
Siebel	SiebelConfiguration.xml*
Siebel	SiebelEventConfiguration.xml*
Siebel	SiebelExceptionConfig.xml*
Siebel	SiebelPatterns.xml*
Siebel	CASConfiguration.xml*
Siebel	CASEventConfiguration.xml*

Related Add-in	File Name
SAP	PropertyPatternConfigSAP.xml*
SAP	SAPConfiguration.xml*
SAP	SAPLearnFilter.xml*
SAP	SapEventConfiguration.xml*
PeopleSoft	PSConfiguration.xml*
PeopleSoft	PSEventConfiguration.xml*
PeopleSoft	PSLearnFilter.xml*
.NET	SwfConfig.xml
.NET	WebFormsConfiguration.xml*
.NET	WebFormsEventConfiguration.xml*
.NET	WebFormsLearnFilter.xml*

---

**Note:** Files marked with an asterisk are copied only if they were changed by the user, but are not copied if no changes were made.

---

### Registry Keys

The following registry key is saved by the Save and Restore Settings utility:

HKEY\_LOCAL\_MACHINE\SOFTWARE\Mercury Interactive\QuickTest Professional\MicTest\Packages\TEAPackage

## Troubleshooting and Limitations - Uninstalling QuickTest

This section describes troubleshooting and limitations for uninstalling QuickTest Professional.

- When a Quality Center client is installed on the same computer as QuickTest Professional, uninstalling QuickTest Professional may remove the association of movie (FBR) files. This may prevent you from viewing movies associated with defects in Quality Center using the HP Micro Player.

**Workaround:** Re-associate the movie files with the HP Micro Player, as follows:

- a** Select **Start > Programs > QuickTest Professional > Tools > HP Micro Player** to open the HP Micro Player.
- b** Select **File > Options** to open the HP Micro Player Options dialog box. Then select the **Associate FBR files with this Player** check box to associate the files directly with the HP Micro Player.

