

The EDM Client

Reference Guide

Legal Information

Trademarks

Enterprise Desktop Manager (EDM), EDM Administrator, EDM Agent, EDM Client, EDM Manager, EDM Stager, and EDM Packager are trademarks of Novadigm, Inc. Other brand names and product names are trademarks or registered trademarks of their respective companies. No investigation has been made of common-law trademark rights in any word. Unless otherwise noted, all names of companies, products, street addresses, and persons contained herein are part of completely fictitious scenarios, data, or other information, and are intended solely to document the use of Novadigm, Inc. software products. The Novadigm Enterprise Desktop Manager (EDM) enables you to manage and distribute software throughout your organization. It does not provide you with the right to make copies of software that you have obtained from third parties. You should make sure that you have obtained the right to make and use the number of copies of each software program which you distribute using EDM.

Confidentiality Statement

These materials contain the confidential, proprietary information of Novadigm, Inc., and are for the sole use of the party to which they are provided and solely for use with the Novadigm software with which they are provided, and as may be expressly agreed upon between that party and Novadigm, Inc. Any other dissemination, distribution, copying or use of the information disclosed hereunder is strictly prohibited.

Restricted Rights

The software and accompanying documentation are provided with "Restricted Rights." Use, duplication, or disclosure by the US Government is subject to restrictions as set forth in subparagraph (c) (1) (ii) of the Rights in Technical Data and Computer Software clause at DFAR §252.227-7013; in subparagraphs (c) (1) and (2) of FAR §52.227-19, Commercial Computer Software-Restricted Rights; or FAR §52.227.14, Rights in General Data, Alternative III, as applicable. Contractor/Manufacturer is Novadigm, Inc., One International Blvd., Suite 200, Mahwah, NJ, 07495.

Notices

The information contained in this document is subject to change without notice, and does not represent a commitment by NOVADIGM, INC. The software described herein is furnished under licensed agreement and/or nondisclosure agreement. NOVADIGM, INC. software can only be used, copied, or transmitted in accordance with the terms of the license agreement.

No part of this publication may be reproduced or transmitted in any form or by any means, electronic or mechanical, including but not limited to photocopying, scanning, or information storage and retrieval systems, for any purpose other than for the explicit use by the licensed organization and/or individual person, without the express written permission of NOVADIGM, INC.

Revised and reprinted with permission by Novadigm, Inc. 1998

Printed in the United States of America

Preface

The EDM Client Reference Guide provides you with a clear and concise overview of the components / modules that drive the different EDM processes.

Each module / component is defined by purpose, location, code specifics, and relationship(s) to other components. Also included in this guide are source and return code tables for each module.

Table of Contents

1 The Connect Process Module	9
List of Components.....	10
EDMSELRS_EXE	10
EDMACTRS_EXE.....	10
EDMASTER_EXE.....	10
EDMCON00_EXE	10
EDMCON10_EXE.....	11
EDMCON20_EXE.....	11
EDMCON25_EXE	11
EDMCON30_EXE.....	11
EDMSTGRQ_EXE.....	12
EDMGETRS_EXE.....	12
EDMCON40_EXE.....	12
EDMCON50_EXE.....	12
WINCON50_EXE.....	13
EDMCONS_EXE.....	13
EDMCONSW_EXE	13
EDMREXW_EXE	13
EDMCONSX_EXE	13
EDMFSCAN_EXE.....	14
EDMOBJT_EXE.....	14
EDMPNLGN_EXE.....	14
EDMPNLGR_EXE	14
EDMRMERG_EXE	15
EDMSBLD_EXE	15
EDMSPOST_EXE	15
EDMTIMER_EXE.....	15
EDMTMCP_EXE.....	15
EDMVER00_EXE.....	16
HWINFO_EXE	16
WINSELRS_EXE	16
WINACTRS_EXE.....	16
EDMMNT00.EXT.....	16
EDMMNTR_EXE.....	17
EDMMNT.EXT.....	17
Source and Return Codes Table	17
2 The Packager Module	21
List of Components.....	22

EDMCLNK_EXE.....	.22
EDMCWPS_EXE.....	.22
EDMCNTRG_EXE22
EDMDLNK_EXE22
EDMDNTRG_EXE.....	.22
EDMDPAK_EXE.....	.23
EDMDWPS_EXE.....	.23
EDMOBSPX_EXE.....	.23
EDMPGMAN_EXE23
EDMREG_EXE23
EDMREGCM_EXE24
PKMONITR_EXE24
Source and Return Codes Table24
3 The Administrator Module.....	.27
List of Components.....	.28
EDMGETF_EXE28
EDMOBJED_EXE.....	.28
EDMSNDF_EXE.....	.28
Source and Return Codes Table28
4 The Stager Module29
List of Components.....	.30
EDMSTGSV_EXE30
Source and Return Codes Table30
5 The Communication Module31
List of Components.....	.32
EDMAPEN2_EXE.....	.32
EDMAPMG2_EXE32
EDMAPMGR_EXE.....	.32
EDMDEMON_EXE.....	.32
EDMRUND_EXE32
EDMRUND2_EXE33
Source and Return Codes Table33
6 The Utilities Module35
List of Components.....	.36
CLIENTMT_EXE36
EDMBOX_EXE36
EDMCID_EXE.....	.36

EDMCIDMT_EXE.....	36
EDMCOPY_EXE	36
EDMDIFF_EXE	37
EDMEXCL_EXE	37
EDMFCMP_EXE.....	37
EDMFEXP_EXE	37
EDMTFYD_EXE	37
EDMSETVW_EXE	38
EDMSHELL_EXE	38
EDMSORT_EXE	38
EDMSORTM_EXE	38
EDMSTATE_EXE	38
EDMTRAP_EXE	39
EDMVER_EXE.....	39
Source and Return Codes Table	39
7 The Methods Module	41
List of Components.....	42
EDMBOOTO_EXE	42
EDMBOOTW_EXE	42
EDMCEXT_EXE	42
EDMCGRP_EXE	42
EDMCICON_EXE	42
EDMCMOD_EXE	43
EDMCPAK_EXE	43
EDMCREG_EXE	43
EDMCTIME_EXE	43
EDMDGRP_EXE	43
EDMDICON_EXE	44
EDMDMOD_EXE	44
EDMDREG_EXE	44
EDMDTIME_EXE	44
EDMEXEC_EXE	44
EDMEXECD_EXE	45
EDMINIT_EXE	45
EDMKILL_EXE	45
EDMLKM_EXE	45
EDMSETB_EXE.....	45
Source and Return Codes Table	46
8 The Install Module	47
List of Components.....	48
EDMADPRM_EXE.....	48
EDMINSTB_EXE	48
EDMIPRMS_EXE	48

INSTSPY_EXE	48
Source and Return Codes Table	49
Index	51

1 The Connect Process Module

The Connect Process is a step by step procedure where the EDM Manager configures the EDM Client. Through this process, the objects being managed on the EDM Client are verified, re-configured and inventoried.

The connection itself consists of an actual series of programs that execute on the EDM Client desktop to perform comprehensive configuration management.

The components in this module are:

EDMSELRS	EDMACTRS	EDMASTER
EDMCON00	EDMCON10	EDMCON20
EDMCON25	EDMCON30	EDMSTGRQ
EDMGETRS	EDMCON40	EDMCON50
WINCON50	EDMCONS	EDMCONSW
EDMREXW	EDMCONSX	EDMFSCAN
EDMOBJT	EDMPNLGN	EDMPNLGR
EDMRMERG	EDMSBLD	EDMSPOST
EDMTIMER	EDMTMCP	EDMVER00
HWINFO	WINSELRS	WINACTRS
EDMMNT00	EDMMNTR	EDMMNT

List of Components

EDMSELRS_EXE

Category RESOURCE
WIN NT 4/95

Detail This component determines which versioned resources should be activated. The specification of the version level to be activated is specified in the variable ZSERVICE.ZSVCVERS.

EDMACTRIS_EXE

Category RESOURCE
WIN NT 4/95

Detail This component controls the activation and de-activation of versioned resources. Resources to be activated are copied from the EDMDATA directory to their active client locations. If a resource is to be deactivated, its designated delete method is processed.

This component acts on the information provided by the EDMSELRS component.

EDMASTER_EXE

Category CLIENT VERIFY
WIN NT 4/95

Detail This component transfers the latest user and service information down to the EDM Client. It transfers the ZMASTER object to the Manager to identify the client. An updated ZMASTER is returned to the client for processing. It then transfers the ZSERVICE object to the client.

Any variables that are added or modified during the Manager resolution process are also updated.

EDMCON00_EXE

Category RESOURCE
WIN NT 4/95

Detail This component performs service object differencing, comparing the ZSERVICE object on the client to the current copy on the Manager. Differences from this compare are placed into the ZPROCESS object and resource differencing then takes

place. It is also used in comparing audit resource configurations between the Manager and the client and determines which services, if any, have changed. If there are no changes, resource differencing is not performed.

EDMCON10_EXE

Category CLIENT VERIFY
WIN NT 4/95

Detail This component presents the user with a list of optional services. Users who want to allow users to select which “New” services will be deployed during the Connect, use it on a limited basis.

The ZPROCESS object defines these variables.

EDMCON20_EXE

Category RESOURCE
WIN NT 4/95

Detail This component performs resource object differencing to determine what resource changes are necessary on the client desktop. If a resource has been added or updated, an instance is added to the ZRSCNEW object for further processing. If an existing resource is no longer needed, its specified delete method is run to remove it from the desktop.

EDMCON25_EXE

Category RESOURCE
MAC

Detail This component is a MAC platform executable. It is a MAC specific function that sorts objects on the EDM Manager.

EDMCON30_EXE

Category CLIENT VERIFY
WIN NT 4/95

Detail This component identifies the files that need to be transferred from the Manager. It interrogates the ZRSCNEW object and determines whether or not the resource needs any data transferred from the Manager. If data is indicated, the heap is placed in the ZTRANSRS object for further processing. It also ensures adequate disk space for mandatory resources.

EDMSTGRQ_EXE

Category RESOURCE
WIN NT 4/95

Detail This component retrieves needed resources from the EDM Stager. It uses the ZTRANSRS object as input. Only ZTRANSRS heaps with valid staging locations are processed. Before requesting resources directly from the Manager (EDMGETRS), this component will attempt to transfer the file from its staged location to the client location. It also stages resources brought down from the Manager that were not previously found on the EDM Stager.

EDMGETRS_EXE

Category RESOURCE
WIN NT 4/95

Detail This component retrieves needed resources from the EDM Manager, using the ZTRANSRS object to request these resources. It controls the data transfer and decompresses the resources if necessary. It then sets the resource status variable (ZRSCCSTA) accordingly.

The ZRSOURCE.ZINIT variable method can be employed to initialize a method or execute a command as soon as the file is sent down to the desktop.

EDMCON40_EXE

Category RESOURCE
WIN NT 4/95

Detail This component properly time stamps any non-versioned file resources downloaded during the connect process. It ensures the file was completely and successfully retrieved.

EDMCON50_EXE

Category RESOURCE
WIN NT 4/95

Detail This component launches the client create methods for the services that have changed and successfully deployed. Some of the common create methods used are: EDMICON/EDMCMOD/EDMCLNK (creates icons and links), and EDMCPAK (perform text file manipulation for line updates, such as .INI file pokes).

WINCON50_EXE

Category RESOURCE
WIN/OS2

Detail This component is the WIN/OS2 platform equivalent of EDMCON50.

EDMCONS_EXE

Category MAIN
WIN NT 4/95

Detail This component is a DOS platform executable that works as the driver that launches the extended batch programs. These various batch programs evaluate different functions, processes and codes.

EDMCONSW_EXE

Category MAIN
WIN NT 4/95, OS/2

Detail This component is the extended batch language interpreter. The Connect process is controlled in a extended batch script.

EDMREXW_EXE

Category MAIN
WIN NT 4/95

Detail This component is a REXX programming language interpreter, which contains extensions capable of interacting with EDM objects.

EDMCONSX_EXE

Category MAIN
UNIX

Detail This component is a Unix platform executable that works as the driver that launches the extended batch programs.

EDMFSCAN_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This component performs a desktop file scan based on supplied selection criteria. It is used during the software audit process, using the ZAUDITR object as input for processing. It collects the selected file statistics, which can optionally include version information for executables. This information is stored in an output object specified on the command line.

In the software audit process, the output object is ZAUDOUT.

EDMOBJT_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is used to transfer an EDM object to the Manager. This is a one way transfer of data. It can be optionally configured to transfer an object's related resources to the Manager as well. If an exception condition occurs during processing, the Manager is notified.

EDMPNLGN_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is the EDM screen painter. It displays a pre-configured GUI panel based on control information created in the specified EDM panel object. This panel object is created by the screen editor; an administrative tool that is provided. Any fields that are filled in on the panel are stored in EDM objects for possible further processing.

Typical usage includes "Sign-on" panels for both the Client and Administrator.

EDMPNLGR_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is the EDM screen painter (EDMPNKGN), with additional REXX programming capabilities. Once the panel is processed, a Rexx procedure can be scheduled for execution.

EDMRMERRG_EXE

Category CLIENT VERIFY
WIN NT 4/95

Detail This component runs in the local Connect process and performs local ZRSOURCE object differencing. It is an operational replacement for component EDMCON20 (see EDMCON20 for details).

EDMSBLD_EXE

Category CLIENT VERIFY
WIN NT 4/95

Detail This component is used to support local Connect processing. It runs as part of a Master Connect, where it prepares the ZSERVICE and ZRSOURCE objects that will be used during a Local Connect.

EDMSPOST_EXE

Category RESOURCE
WIN NT 4/95

Detail This component performs a second scan of Audit resources to determine if a file is new or updated. It then compares prior resources to current and sets a parameter definition in the ZAUDITR.ZSCANTYP variable that provides the results of the scan:

- “UPDATE” – file has been updated
- “NEW” – file is new

EDMTIMER_EXE

Category RESOURCE
WIN NT 4/95

Detail This component manages the desktop scheduled executions. It resides on the desktop and controls the execution of timed events via the ZTIMEQ object.

EDMTMCP_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This component compares two ASCII files and creates an object based on the differences.

EDMVER00_EXE

Category CLIENT VERIFY
WIN NT 4/95

Detail This component verifies the client's current resource configuration. It detects if a resource has been changed or deleted and needs to be re-deployed.

HWINFO_EXE

Category HARDWARE
WIN NT 4/95

Detail This component performs the hardware audit process. Out of this process, ZCONFIG, is typically sent to the Manager for reporting and configuration purposes.

WINSELRS_EXE

Category RESOURCE
WIN/OS2

Detail This component is a WIN/OS2 platform equivalent of EDMSELRS.

WINACTRS_EXE

Category RESOURCE
WIN/OS2

Detail This component is a WIN/OS2 platform equivalent of EDMACTRS.

*This component acts on the information provided by the WINSELRS component.

EDMMNT00.EXT

Category MAINTENANCE
WIN NT 4/95

Detail This component moves the EDM self-maintenance files from their inactive location (EDMDATA) to an active location (ZLOCCLNT). This component is launched by EDMMNT.EXT, which is controlled by EDMMNTR.

EDMMNTR_EXE

Category MAINTENANCE
WIN NT 4/95

Detail This component runs the EDM self-maintenance script. Its purpose is to enable maintenance to be deployed for the CONNECT.EXT batch file, EDMCONSW, and other programs in use during the connect process.

EDMMNT.EXT

Category MAINTENANCE
WIN NT 4/95

Detail This extended batch controls the EDM self maintenance process.

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	ZBRC Return Codes/Meaning
EDMSELRS WINSELRS	ZSERVICE ZRSOURCE	ZACTRES	0 – Task completed 4 – No resources selected for processing 8 – Internal memory / Object error
EDMACTRS WINACTRS	ZACTRES	None	0 – Task completed 8 – Program.exe dispatch error 8 – Internal memory / Object error.
EDMASTER	ZMASTER 0	ZMASTER	0 – Task completed 4 – No changes on Manager or Client 8 – Work object could not be loaded 16 – Communication error
EDMASTER	ZSERVICE	ZTMPSAVE	0 – Task completed 4 – No changes on Manager or Client 4 - Object not found in manager 8 – Internal memory / Object error 16 – Invalid object – No ZOBJDATE or ZOBJTIME 16 – Communication error
EDMCON00	ZSERVICE ZTMPSAVE	ZPROCESS	0 – Task completed 4 – No updates 8 – Invalid number of arguments 8 – Internal memory / Object error 16 – Invalid ZSERVICE object
EDMCON10	ZRSOURCE	ZRSOURCE	0 – Task completed 4 – No updates 8 – Objects could not be loaded 16 – Communication error

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	ZBRC Return Codes/Meaning
EDMCON20	ZRSOURCE	ZRSOURCE	0 – Task completed 4 – No updates 8 – Objects could not be loaded 16 – Communication error
EDMCON25	ZRSOURCE	ZRSOURCE	None
EDMCON30	ZRSCNEW	None	0 – Task completed 4 – No files to process 8 – No disk space required for optional resources 16 – Internal memory / Object error - Object sort failed
EDMSTGRQ	ZTRANSRS	None	0 – Task completed 8 – Unable to initialize request 8 – Load functions failed 8 – Required variables not found 8 – Internal memory / Object error 16 – Communication error
EDMGETRS	ZTRANSRS	ZCONFIRM	0 – Task completed 8 – Unexpected R/C during communication transfer 8 – Required object not found in memory 8 – Required field not found in object 16 – Communication error
EDMSTGRQ	ZTRANSRS	None	0 – Task completed 8 – Unable to initialize request 8 – Load functions failed 8 – Required Variables not found 8 – Internal memory / Object error 16 – Communication error
EDMCON40	ZTRANSRS	None	0 – Task completed 8 – Invalid ZSERVICE or ZRSOURCE object 8 – Internal memory / Object error
EDMCON50 WINCON50	ZRSCNEW	None	0 – Task completed 8 – Internal memory / Object error
EDMCONS			
EDMCONSW	The extended batch script (.EXT)	The extended batch script determination	0 – Task completed non 0 – Line number error in the batch script (.EXT)
EDMREXW	Rexx script (.REX / .CMD)	The script determines this	0 – Task completed 16 – REXX syntax error
EDMCONSX	Retains the existing date of the class	None	Optional
EDMFSCAN	Object then Object.Variable which holds the search template (i.e., *.*.*.*.) or multi-heap object for several different scan templates (Output Object)	The object containing all the files found on the desk-top that matches the search criteria	0 – Task completed 4 – No matches found 8 – Argument error 8 – Internal memory / Object error

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	ZBRC Return Codes/Meaning
EDMOBJT	<Any object>	None	0 – Task completed 4 – Object has no variables 8 – Work objects could not be loaded 16 – Communication error
EDMPNLGN	<Any panel object>	Creates ZPSELECT	There is no command defined to return a code. The only command that exists advising of an error is in the ZMASTER ZPSAVE object. It returns a "1" if the panel is accepted and a "0" if it is not. The only way to specifically diagnose the problem is to consult the log
EDMPNLGR	<Any panel object>	Creates ZPSELECT	There is no command defined to return a code. The only command that exists advising of an error is in the ZMASTER ZPSAVE Object. It returns a "1" if the panel is accepted and a "0" if it is not. The only way to specifically diagnose the problem is to consult the log. In order for this REXX panel script to run, a batch file must be launched that runs the ZMASTER ZPREEXEC script that launches REXX.
EDMRMERG	ZSERVICE.EDM ZAUDITR.EDM	ZRSCNEW.EDM / Can launch methods to try and recover problems	0 – Task completed 4 – No updates to process 4 – Start EDMCON40 to process deletes 5 – No more resources....Do not continue 8 – Internal memory / Object error 16 – Object error
EDMSBLD	ZSERVICE.EDM ZAUDITR.EDM	SSERVICE.EDM SRSOURCE.EDM	0 – Task completed 8 – Internal memory / Object error
EDMSPOST	AUDIT Object, SCAN Object	Method test	0 – Task completed 4 – Argument error 8 – Internal memory / Object error
EDMTIMER	ZTIMEQ.EDM	Whatever ZTIMEQ references	0 – Task completed 4 – Argument error 8 – Internal memory / Object error
EDMTMCP	Original file, Updated file	An object of the differences found in the ASCII files	0 – Task completed 4 – Argument error 8 – Internal memory / Object error (Refer to the EDMTMCP.LOG for the exact error)
EDMVER00	ZRSOURCE.EDM, ZSERVICE EDM	ZVER00.EDM, ZRSOURCE.ZRSCCSTA, ZSERVICE.ZSVCCSTA	0 – Task completed 8 – Internal memory / Object error 10 – ZSERVICE and ZRSOURCE are null or invalid 16 - Object error 20 – ZSERVICE and ZRSOURCE are null or invalid 36 - Files not found on disk
HWINFO	None	HWINFO.FIL	None
EDMMNT.EXT	None	None	None

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	ZBRC Return Codes/Meaning
EDMMNT00	ZRSOURCE.EDM, ZSERVICE.EDM	It moves inactive resources to active status	0 – Task completed 8 – Internal memory / Object error
EDMMNTR	None	None	None

2 The Packager Module

The Packager is an application that “packages” entire applications, or file updates, that will be deployed to hundreds or thousands of desktops.

The components in this module are:

EDMCLNK	EDMCWPS	EDMCNTRG
EDMDLNK	EDMDNTRG	EDMDPAK
EDMDWPS	EDMOBSPX	EDMPGMAN
EDMREG	EDMREGCM	PKMONITR

List of Components

EDMCLNK_EXE

Category RESOURCE
WIN NT 4/95

Detail This create method deploys shortcut links to the desktop.

EDMCWPS_EXE

Category RESOURCE
OS2

Detail This component is an OS2 platform executable. It creates icons and updates in the OS2.INI and OS2.SYS.INI files.

EDMCNTRG_EXE

Category RESOURCE
WIN NT 3.51/95

Detail This create method controls the deployment of registry keys and their associated values in the 32 bit Windows Operating Systems.

EDMDLNK_EXE

Category RESOURCE
WIN NT 4/95

Detail This delete method deletes desktop shortcut links deployed by EDMCLNK.

EDMDNTRG_EXE

Category RESOURCE
WIN NT 3.51/95

Detail This delete method reverses the actions taken by the create method, EDMCNTRG, in the 32 bit Windows Operating Systems.

EDMDPAK_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This delete method reverses the actions taken by the create method, EDMCPAK. It also affects both the section type (WIN.INI) and non-section type (AUTOEXEC.BAT) files.

EDMDWPS_EXE

Category RESOURCE
WIN/OS2

Detail This component is a WIN/OS2 platform executable. It deletes the icons and updates in the OS2.INI and OS2 SYS.INI files created by EDMCWPS.

EDMOBSPX_EXE

Category RESOURCE
OS2

Detail This component is an OS2 platform executable. It scans for new objects created during installation. It then works with components EDMCWPS and EDMDWPS when creating OS2 icons.

EDMPGMAN_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This component is a Windows 3.x.x and NT 3.5.1 platform executable. It is an icon-snapshot component. It scans the Program Manager and creates an object containing information about all program groups and icons found on the desktop.

EDMREG_EXE

Category RESOURCE
WIN 3.x.x

Detail This component is a Windows 3.1.1 platform executable. It provides a registry compare functionality by creating a back up for the EDMREGCM compare component.

EDMREGCM_EXE

Category RESOURCE
WIN 3.x.x

Detail This component is a Windows 3.1.1 platform executable. It utilizes a WIN 3.x.x registry compare functionality. The compare follows software installation.

PKMONITR_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This component provides a method to restart the EDM 4.0 Packager after a software install has completed. It adds an icon to the system tray during the software installation process. It is then launched after the installation is complete.

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMCLNK	ZDSPM00.EDM	It creates desktop links	0 - Task completed 4 - Internal memory / Object error 16 - Invalid Object - No ZONJDATE or ZOBJTIME
EDMCWPS	/S (Packager Session prefix) PACKINST.EDM, PACKDESK.EDM, PACKINI.EDM	It is an OS/2 desktop folder icon. Also, OS2.INI and OS2SYS.INI updates	0 - Task completed 8 - Internal memory / Object error
EDMCNTRG	ZDSPM00.EDM	It updates to the 32bit registry	0 - Task completed 4 - Argument error 4 - Object not found in manager 8 - Internal memory / Object error
EDMDLNK	ZDSPM00.EDM	It removes the desktop links created by EDMCLNK	0 - Task completed 4 - Argument error 8 - Internal memory / Object error
EDMDNTRG	ZDSPM00.EDM	It updates to the 32bit registry	0 - Task completed 4 - Argument error 4 - Internal memory / Object error 8 - Internal memory / Object error
EDMDWPS	/S (Packager Session prefix) PACKINST.EDM, PACKDESK.EDM, PACKINI.EDM	It is an OS/2 desktop folder icon. Also, OS2.INI and OS2SYS.INI updates	0 - Task completed 8 - Internal memory / Object error
EDMOBSPX	A Start or Stop (command line)	The object of new OS/2 desktop objects	0 - Task completed 99 - Internal memory / Object error

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMPGMAN	Output object name	All of the icons from the Program Manager	0 - Task completed 4 - Argument error 4 - Internal memory / Object error
EDMREGCM	Registry snap-shot	The difference between the snap-shot and the new registry database	0 - Task completed 4 - Argument error 4 - Internal memory / Object error
EDMREG	Output object name	Registry snap-shot	0 - Task completed 8 - Internal memory / Object error
PKMONITR	None	None	None

3 The Administrator Module

The Administrator provides various facilities that enable the user to configure and distribute multiple applications to the EDM Client desktops in the network.

The components in this module are:

EDMGETF	EDMOBJED	EDMSNDF
---------	----------	---------

List of Components

EDMGETF_EXE

Category RESOURCE
WIN NT 4/95

Detail This component retrieves a file from the EDM Manager.

EDMOBJED_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is an editing tool used to open and modify the contents of EDM objects on the EDM Client.

EDMSNDF_EXE

Category RESOURCE
WIN NT 4/95

Detail This component sends a file to the EDM Manager.

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMGETF	The file you need to "get"	The file itself from the Manager	0 - Task completed 4 - Transfer error 8 - Internal memory / Object error 16 - Communication error
EDMOBJED	Any EDM object	Any EDM object	None
EDMSNDF	There is a file to send	The file is sent to the Manager	0 - Task completed 4 - Transfer error 8 - Internal memory/ Object error 16 - Communication error

4 The Stager Module

The Stager is an intermediate object server that coordinates the management of the EDM Client desktops.

It provides a decentralized location for storing and retrieving applications and files, and staging their distributions to the EDM Clients through the EDM Client Connect Process.

The Stage has one component: EDMSTGSV.

List of Components

EDMSTGSV_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is the EDM Stager. It satisfies all retrieval and staging requests from the client component EDMSTGRQ.

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMSTGSV	The file is sent to the Stager	The files are actually staged	None

5 The Communication Module

The Communication module provides the user with the ability to communicate via the various protocols available.

The components in this module are:

EDMAPEN2	EDMAPMG2	EDMAPMGR
EDMDEMON	EDMRUND	EDMRUND2

List of Components

EDMAPEN2_EXE

Category RESOURCE
WIN NT 4/95

Detail This component ends the LU2 communication session with the EDM Manager.

EDMAPMG2_EXE

Category RESOURCE
WIN NT 4/95

Detail This component negotiates the LU2 communication session with the EDM Manager.

EDMAPMGR_EXE

Category RESOURCE
WIN NT 4/95

Detail This component negotiates the LU6.2 communication session with the EDM Manager.

EDMDEMON_EXE

Category RESOURCE
WIN NT 4/95

Detail This component controls the TCP/IP communication session with the EDM Manager.

EDMRUND_EXE

Category SESSION
WIN NT 4/95, WIN3.x, OS/2

Detail This component runs the LU2 dialog scripts necessary to initiate and terminate a session with the EDM Manager.

EDMRUND2_EXE

Category SESSION
WIN NT 4/95

Detail This component provides the EDM Manager logoff functionality on a session initiated by the EDMDEMON component.

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMAPEN2	None	None	None
EDMAPMG2	None	None	None
EDMAPMGR	ZMASTER.EDM	ZLOCAL.EDM	0 - Task completed 8 - Communication error
EDMDEMON	ZMASTER.EDM	ZLOCAL.EDM	0 - Task completed 4 - Transfer error 8 - Communication error 16 - Communication error 28 - Communication error
EDMRUND	ZMASTER.EDM	ZMASTER.EDM	0 - Task completed 8 - Communication error 8 - Internal memory / Object error 16 - Internal memory error
EDMRUND2	ZMASTER.EDM	ZMASTER.EDM	0 - Task completed 8 - Communication error 8 - Internal memory / Object error 16 - Internal memory error

6 The Utilities Module

The Utilities module is a stand-alone executable that provides additional support and functionality that enhances the EDM Process.

CLIENTMT	EDMBOX	EDMCID
EDMCIDMT	EDMCOPY	EDMDIFF
EDMEXCL	EDMF_CMP	EDMFEXP
EDMTFYD	EDMSETVW	EDMSHELL
EDMSORT	EDMSORTM	EDMSTATE
EDMTRAP	EDMVER	

List of Components

CLIENTMT_EXE

Category MAINTENANCE
WIN NT 4/95

Detail This component stores information about EDM component time, date and version in order to report back to EDM Tech Support.

EDMBOX_EXE

Category RESOURCE
WIN NT 4/95

Detail This component displays supplied text parameter and the “OK/Cancel” buttons message box on the desktop.

EDMCID_EXE

Category RESOURCE
WIN/OS2

Detail This component is a WIN/OS2 platform executable. It converts CID enabled applications to EDM managed applications.

EDMCIDMT_EXE

Category MAINTENANCE
WIN/OS2

Detail This component is a WIN/OS2 platform executable. It updates current CID enabled applications.

EDMCOPY_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This component copies one EDM object to another. It can also append a single heap to another object if a second parameter of heap information is supplied.

EDMDIFF_EXE

Category RESOURCE
WIN NT 4/95

Detail This component compares two objects and creates a third object with the differences. It verifies information via name, date, time and CRC codes.

EDMEXCL_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This component compares two objects and creates a third object with the differences found.

EDMFCMP_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is a stand-alone utility function that compresses a file using EDM's own proprietary compression formula.

EDMFEXP_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is a stand-alone utility function that decompresses a file using EDM's own proprietary compression formula.

EDMTFYD_EXE

Category RESOURCE
WIN '95/3.x.x

Detail This component is a Win '95/3.x.x platform executable. It is the notify demon component. It runs as a background process that waits for the notify commands sent from the EDM Manager.

EDMSETVW_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is a command line interface to manipulate EDM objects.

EDMSHELL_EXE

Category RESOURCE
WIN/OS2

Detail This component is a WIN/OS2 platform executable. It provides object shell space.

EDMSORT_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This component is a stand-alone utility that sorts an object using a variable in the object. It is a one key sort.

EDMSORTM_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is a stand-alone utility that sorts an object in ascending or descending order using a variable in the object. It is a multiple key sort.

EDMSTATE_EXE

Category RESOURCE
WIN NT 4/95

Detail This component creates a report of the current states of all EDM Managed resources and services on the client.

EDMTRAP_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is a SMNP utility which sends SMNP alerts to a SMNP console for processing.

EDMVER_EXE

Category RESOURCE
WIN NT 4/95

Detail This component produces an output of all programs in the EDM component itself. It is used by EDM Tech Support to determine the version being used.

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
CLIENTMT	None	None	None
EDMBOX	A message string, timeout value	An OK dialog	None
EDMCID	ZCID object	None	0 - Task Completed 8 - Communication error
EDMCIDMT	ZCID object	None	0 - Task Completed 8 - Communication error
EDMCOPY	An object to copy	A new object name	0 - Task completed 8 - Internal memory / Object error
EDMDIFF	Objects to difference	The object of the differences	0 - Task completed 8 - Internal memory / Object error
EDMEXCL	Objects to difference, Variable to difference on	The object of the differences	0 - Task completed 4 - Argument error 8 - Internal memory / Object error
EDMF_CMP	A file to compress	The compressed file	0 - Task completed 3 - Argument error 8 - Internal memory / Object error
EDMF_EXP	A file to de-compress	The de-compressed file	0 - Task completed 3 - Argument error 8 - Internal memory / Object error
EDMNTFYD	The number of seconds to wait	None	None

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMSETVW	{-DP} OBJECT HEAP_# VARIABLE VALUE -D =Delete Variable -P = Modify Protected Variable	None	0 - Task completed 8 - Object error 8 - Invalid parameters
EDMSHELL	PROGRAM PARMs WORK_ DIRECTORY WAIT_MODE	None	000 - (It always returns this code)
EDMSORT	OBJECT FIELD	A sorted object	0 - Task completed 8 - Invalid parameters 8 - Unable to open input file 8 - Unable to open work file 8 - Field found 8 - Error allocating memory for sort
EDMSORTM	[{-ad} OBJECT, field 1 {field k} {field n}]	A sorted object	0 - Task completed 16 - Error allocating memory for sort
EDMSTATE	{-dnoprtv?} {LibPath} {LogPath} {Extended_Batch}	EDMSTATE.LOG, ZSTATE.EDM, {ZSTATES.EDM, ZSTATER.EDM}	None
EDMTRAP	<host> <enterprise> <community> <specific-type> <device-description>[-a <agent-addr>]	None	None
EDMVER	A file name	The screen	None

7 The Methods Module

The Methods module is a program or procedure that can be packaged and exchanged as an object.

The components in this module are:

EDMBOOTO	EDMBOOTW	EDMCEXT
EDMCGRP	EDMCICON	EDMCMOD
EDMCPAK	EDMCREG	EDMCTIME
EDMDGRP	EDMDICON	EDMDMOD
EDMDREG	EDMDTIME	EDMEXEC
EDMEXECD	EDMINIT	EDMKILL
EDMLKM	EDMSETB	

List of Components

EDMBOOTO_EXE

Category RESOURCE
WIN/OS2

Detail This component is an OS/2 platform executable. It reboots an OS2 operating environment.

EDMBOOTW_EXE

Category RESOURCE
WIN NT 4/95

Detail This component reboots a Windows Operating environment.

EDMCEXT_EXE

Category RESOURCE
WIN 3.x.x

Detail This component is an operational equivalent of EDMCONSW. It is provided for the purpose of running an .EXT as a create method, while EDMCONSW is active. Certain platforms do not allow multiple instances of an executable to be run concurrently.

EDMCGRP_EXE

Category RESOURCE
WIN NT 4/95

Detail This component creates a group on WIN 3.x.x and size/placement can be designated.

EDMCICON_EXE

Category RESOURCE
WIN NT 4/95

Detail This create method deploys icons and program groups using the ZWINICON class.

* The create takes place when the variables from the ZWINICON class are connected to ZRSOURCE.

EDMCMOD_EXE

Category RESOURCE
WIN 3.51/3.x.x

Detail This create method deploys icons on the Program Manager operating systems.

EDMCPAK_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This create method performs text file manipulation for line updates, such as .INI file pokes. It affects both section type (WIN.INI) and non-section type (AUTOEXEC.BAT) files.

EDMCREG_EXE

Category RESOURCE
WIN 3.x.x

Detail This component creates REG.DAT keys and values in the 16 bit registry.

EDMCTIME_EXE

Category RESOURCE
WIN NT 4/95

Detail This create method creates an entry in the ZTIMEQ object used by EDMTIMER for scheduling events.

EDMDGRP_EXE

Category RESOURCE
WIN 3.x.x

Detail This component is a Win 3.x.x. program executable. It deletes a program group.

EDMDICON_EXE

Category RESOURCE
WIN NT 4/95

Detail This delete component deletes the icons and program groups created by the EDMCICON component.

EDMDMOD_EXE

Category RESOURCE
WIN 3.51/3.x.x

Detail This delete component removes program groups and icons created by EDMCMOD.

EDMDREG_EXE

Category RESOURCE
WIN 3.x.x

Detail This component deletes the keys and values in the 16 bit registry created by the EDMCREG component.

EDMDTIME_EXE

Category RESOURCE
WIN NT 4/95

Detail This delete method removes an entry in the ZTIMEQ placed there by EDMCTIME. It effectively cancels the timed event previously scheduled.

DMEXEC_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is used to control the availability and expiration of deployed EDM services.

EDMEXECD_EXE

Category RESOURCE
WIN NT/OS2

Detail This component is the notify daemon for Windows NT and OS/2. It runs as a background process that waits for the notify commands sent from the EDM Manager.

EDMINIT_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is the executable given control as a result of a communication protocol LU6.2 notify.

EDMKILL_EXE

Category RESOURCE
WIN NT 4/95

Detail This component is used to terminate a process running currently.

EDMLKM_EXE

Category RESOURCE
WIN NT 4/95

Detail This component controls the deployment of In-use resources. It utilizes the native operating system's capability to replace system components during system initialization.

EDMSETB_EXE

Category RESOURCE
WIN NT 4, 3.51/95, 3.x.x/OS/2

Detail This create method is used to resolve any EDM specific variables imbedded in an ASCII file during an EDM Packager session (i.e.; ZSERVICE.ZSRVDRV0, etc.).

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMBOOTO	None	None	None
EDMBOOTW	[DPW] [PROGRAM_NAME] D – Reboot to DOS P – Restart Windows and Run PROGRAM_NAME before restarting W – Restart Windows	None	None
EDMCEXT	EXTENDED_BATCH_FILENAME {Arg 1..Arg n}	None	None
EDMCICON	ZDSPM000.EDM	An icon	0 - Task completed 4 - Argument error 8 - Internal memory / Object error
EDMCMOD	ZDSPM000.EDM	An icon	0 - Task completed 8 - Internal memory / Object error
EDMCPAK	ZDSPM000.EDM (Command line arguments in separate document)	It provides ASCII file updates	0 - Task completed 8 - Internal memory / Object error
EDMCTIME	ZTIMEQ.EDM	None	0 - Task completed 4 - Argument error 8 - Internal memory / Object error
EDMDICON	ZDSPM000.EDM	Icon removal	0 - Task completed 4 - Argument error 8 - Internal memory / Object error
EDMDMOD	ZDSPM000.EDM	Icon removal	0 - Task completed 8 - Internal memory / Object error
EDMDTIME	ZTIMEQ.EDM	None	0 - Task completed 4 - Argument error 8 - Internal memory / Object error
EDMEXEC	ZSERVICE.EDM	ZSERVICE.EDM	0 - Task completed 4 - Service not active 8 - Internal memory / Object error
EDMEXECD	ZMASTER.EDM	The execution of the EDMDEMON	0 - Task completed 4 - Internal memory / Object error 16 - Communication error
EDMINIT	None	The start of the CONNECT process	None
EDMKILL	The executable is brought to a halt	None	None
EDMLKM	An executable that is currently locked up	Native methods are used for a rename of the executable upon system restart	0 - Task completed 8 - Internal memory / Object error
EDMSETB	A file used to convert variable information	The converted file	0 - Task completed 4 - Service not active 8 - Internal memory / Object error

8 The Install Module

The Install module is program or procedure where information is entered into a specific location via a text directive.

The components in this module are:

EDMADPRM	EDMINSTB	EDMIPRMS
INSTSPY		

List of Components

EDMADPRM_EXE

Category RESOURCE
WIN NT 4/95

Detail This component enters EDM Path information about the EDM Administrator directory into the system file. (i.e., WIN.INI, OS2.INI, EDMProf.Dat etc.)

EDMINSTB_EXE

Category RESOURCE
WIN NT 4/95

Detail This component substitutes EDM variables for their values in a text file that is specified in the input object.

EDMIPRMS_EXE

Category RESOURCE
WIN NT 4/95

Detail This component sets the EDMLIB, EDMSYS, EDMLOG path directives.

INSTSPY_EXE

Category RESOURCE
WIN/OS2

Detail This is a WIN/OS2 platform executable. OS/2 installs a .dll shell object space during packaging which can be turned on and off. When it is on, it watches everything that is happening and then proceeds to re-create the object on the desktop.

Source and Return Codes Table

Module Name	INPUT: EXE reads Object at desktop	OUTPUT: EXE reads Object at desktop	Return Codes
EDMADPRM	Provides PATH information into system files	System files updated	0 - Task completed 4 - Internal memory / Object error
EDMINSTB	An object containing a path to a file that needs to be updated	An updated file with variable substitutions resolved	8 - Required variable not found in object
EDMIPRMS	A Command line for EDM PATH information	It updates the EDM environment	None
INSTSPY	Blank = Install Spy U = Uninstall Spy	EDMOBSPY.DLL is installed in the OS/2 Workplace Shell	None

Index

C

CLIENT VERIFY

EDMASTER_EXE, 10
EDMCON10_EXE, 11
EDMCON30_EXE, 11
EDMRMERG_EXE, 15
EDMSBLD_EXE, 16
EDMVER00_EXE, 16

CLIENTMT_EXE

component details, 36
source and return codes, 39

E

EDMACTRS_EXE

component details, 10
source and return codes, 18

EDMAPEN2_EXE

component details, 32
source and return codes, 33

EDMAPMG2_EXE

component details, 32
source and return codes, 33

EDMAPMGR_EXE

component details, 32
source and return codes, 33

EDMASTER_EXE

component details, 10
source and return codes, 18

EDMBOOTO_EXE

component details, 42
source and return codes, 46

EDMBOOTW_EXE

component details, 42
source and return codes, 46

EDMBOX_EXE

component details, 36
source and return codes, 39

EDMCEXT_EXE

component details, 42
source and return codes, 46

EDMCGRP_EXE

component details, 42

EDMCICON_EXE

component details, 42
source and return codes, 46

EDMCID_EXE

component details, 36
source and return codes, 39

EDMCIDMT_EXE

component details, 36
source and return codes, 39

EDMCLNK_EXE

component details, 22
source and return codes, 24

EDMCMOD_EXE

component details, 43
source and return codes, 46

EDMCNTRG_EXE

component details, 22
source and return codes, 24

EDMCON00_EXE

component details, 10
source and return codes, 18

EDMCON10_EXE

component details, 11
source and return codes, 18

EDMCON20_EXE

component details, 11
source and return codes, 18

EDMCON25_EXE

component details, 11
source and return codes, 9, 18

EDMCON30_EXE

component details, 11
source and return codes, 19

EDMCON40_EXE

component details, 12
source and return codes, 19

EDMCON50_EXE

component details, 12
source and return codes, 19

EDMCONS_EXE component details, 23
source and return codes, 19

EDMCONSW_EXE component details, 13
source and return codes, 19

EDMCONSX_EXE component details, 13
source and return codes, 19

EDMCOPY_EXE component details, 36
source and return codes, 39

EDMCPAK_EXE component details, 43
source and return codes, 46

EDMCREG_EXE component details, 43
source and return codes, 46

EDMCWPS_EXE component details, 22
source and return codes, 24

EDMDEMON_EXE component details, 32
source and return codes, 33

EDMDGRP_EXE component details, 43

EDMDICON_EXE component details, 44
source and return codes, 46

EDMDIFF_EXE component details, 37
source and return codes, 39

EDMDLNK_EXE component details, 22
source and return codes, 24

EDMDMOD_EXE component details, 44
source and return codes, 46

EDMDNTRG_EXE component details, 22
source and return codes, 24

EDMDPAK_EXE component details, 18

EDMDREG_EXE component details, 44

EDMDTIME_EXE component details, 44
source and return codes, 46

EDMDWPS_EXE component details, 23
source and return codes, 24

EDMEXCL_EXE component details, 37
source and return codes, 39

EDMEXEC_EXE component details, 44
source and return codes, 46

EDMEXECD_EXE component details, 45
source and return codes, 46

EDMFCMP_EXE component details, 37
source and return codes, 39

EDMFEXP_EXE component details, 37
source and return codes, 39

EDMFSCAN_EXE component details, 14
source and return codes, 19

EDMGETF_EXE component details, 28
source and return codes, 28

EDMGETRS_EXE component details, 12
source and return codes, 19

EDMINIT_EXE component details, 45
source and return codes, 46

EDMKILL_EXE component details, 45
source and return codes, 46

EDMLKM_EXE component details, 45
source and return codes, 46

EDMMNT.EXT component details, 18

source and return codes, 20

EDMMNT00_EXE

- component details, 17
- source and return codes, 20

EDMMNTR_EXE

- component details, 17
- source and return codes, 20

EDMOBJED_EXE

- component details, 28
- source and return codes, 28

EDMOBJT_EXE

- component details, 14
- source and return codes, 19

EDMOBSPX_EXE

- component details, 23
- source and return codes, 24

EDMPGMAN_EXE

- component details, 23
- source and return codes, 25

EDMPNLGN_EXE

- component details, 14
- source and return codes, 20

EDMPNLGR_EXE

- component details, 14
- source and return codes, 20

EDMREG_EXE

- component details, 23
- source and return codes, 25

EDMREGCM_EXE

- component details, 24
- source and return codes, 25

EDMREXW_EXE

- component details, 13
- source and return codes, 19

EDMRMERG_EXE

- component details, 15
- source and return codes, 20

EDMRUND_EXE

- component details, 32
- source and return codes, 33

EDMRUND2_EXE

- component details, 33
- source and return codes, 33

EDMSBLD_EXE

- component details, 16
- source and return codes, 20

EDMSELRS_EXE

- component details, 10
- source and return codes, 9, 18

EDMSETB_EXE

- component details, 45
- source and return codes, 46

EDMSETVW_EXE

- component details, 38
- source and return codes, 40

EDMSHELL_EXE

- component details, 38
- source and return codes, 40

EDMSNDF_EXE

- component details, 28
- source and return codes, 28

EDMSORT_EXE

- component details, 38
- source and return codes, 40

EDMSORTM_EXE

- component details, 38
- source and return codes, 40

EDMSPOST_EXE

- component details, 16
- source and return codes, 20

EDMSTATE_EXE

- component details, 38
- source and return codes, 40

EDMSTGRQ_EXE

- component details, 12
- source and return codes, 19

EDMSTGSV_EXE

- component details, 30
- source and return codes, 30

EDMTFYD_EXE

- component details, 37
- source and return codes, 39

EDMTIMER_EXE

- component details, 16
- source and return codes, 20

EDMTMCP_EXE

- component details, 16
- source and return codes, 20

EDMTRAP_EXE	EDMCICON_EXE, 42
component details, 39	EDMCID_EXE, 36
source and return codes, 40	EDMCLNK_EXE, 22
EDMVER_EXE	EDMCMOD_EXE, 43
component details, 39	EDMCNTRG_EXE, 22
source and return codes, 40	EDMCON00_EXE, 10
EDMVER00_EXE	EDMCON25_EXE, 11
component details, 16	EDMCON40_EXE, 12
source and return codes, 20	EDMCON50_EXE, 12
H	EDMCOPY_EXE, 36
HARDWARE	EDMCPAK_EXE, 43
HWINFO_EXE, 17	EDMCREG_EXE, 43
HWINFO_EXE	EDMCTIME_EXE, 43
component details, 17	EDMCWPS_EXE, 22
source and return codes, 20	EDMDEMON_EXE, 32
M	EDMDGRP_EXE, 43
MAIN	EDMDICON_EXE, 44
EDMCONS_EXE, 13	EDMDIFF_EXE, 37
EDMCONSW_EXE, 13	EDMDLNK_EXE, 22
EDMCONSX_EXE, 13	EDMDMOD_EXE, 44
EDMREXW_EXE, 13	EDMDNTRG_EXE, 22
MAINTENANCE	EDMDPAK_EXE, 23
CLIENTMT_EXE, 36	EDMDREG_EXE, 44
EDMICDMT_EXE, 36	EDMDTIME_EXE, 44
EDMMNT.EXT, 18	EDMDWPS_EXE, 23
EDMMNT00.EXT, 17	EDMEXCL_EXE, 37
EDMMNTR_EXE, 17	EDMEXEC_EXE, 44
P	EDMEXECD_EXE, 45
PKMONITR_EXE	EDMF_CMP_EXE, 37
component details, 24	EDMFEXP_EXE, 37
source and return codes, 25	EDMFSCAN_EXE, 14
R	EDMGETF_EXE, 28
RESOURCE	EDMGETRS_EXE, 12
EDMACTRS_EXE, 10	EDMINIT_EXE, 45
EDMAPEN2_EXE, 32	EDMKILL_EXE, 45
EDMAPMG2_EXE, 32	EDMLKM_EXE, 45
EDMAPMGR_EXE, 32	EDMOBJED_EXE, 28
EDMBOOTO_EXE, 42	EDMOBJT_EXE, 14
EDMBOOTW_EXE, 42	EDMOBSPX_EXE, 23
EDMCEXT_EXE, 42	EDMPGMAN_EXE, 23
EDMCGRP_EXE, 42	EDMPNLGN_EXE, 14
	EDMPNLGR_EXE, 14
	EDMREG_EXE, 23
	EDMREGCM_EXE, 24
	EDMSELRS_EXE, 10
	EDMSETB_EXE, 45
	EDMSETVW_EXE, 38
	EDMSHELL_EXE, 38
	EDMSNDF_EXE, 28

EDMSORT_EXE, 38
EDMSORTM_EXE, 38
EDMSPOST_EXE, 16
EDMSTATE_EXE, 38
EDMSTGRQ_EXE, 12
EDMSTGSV_EXE, 30
EDMTFYD_EXE, 37
EDMTIMER_EXE, 16
EDMTMCP_EXE, 16
EDMTRAP_EXE, 39
EDMVER_EXE, 39
EMDCON20_EXE, 11
PKMONITR_EXE, 24
WINACTRS_EXE, 17
WINCON50_EXE, 13
WINSELRS_EXE, 17

S

SESSION
 EDMRUND_EXE, 32
 EDMRUND2_EXE, 33

W

WINACTRS_EXE
 component details, 17
 source and return codes, 18
WINCON50_EXE
 component details, 13
 source and return codes, 19
WINSELRS_EXE
 component details, 17
 source and return codes, 9, 18, 21, 31, 35, 41