

# HP OpenView Performance Insight

## Reference Guide

Software Version: 5.1

for the HP-UX, Linux, Solaris, and Windows operating systems



February 2005

© Copyright 2005 Hewlett-Packard Development Company, L.P.

## Legal Notices

### Warranty

*Hewlett-Packard makes no warranty of any kind with regard to this document, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. Hewlett-Packard shall not be held liable for errors contained herein or direct, indirect, special, incidental or consequential damages in connection with the furnishing, performance, or use of this material.*

A copy of the specific warranty terms applicable to your Hewlett-Packard product can be obtained from your local Sales and Service Office.

### Restricted Rights Legend

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause in DFARS 252.227-7013.

Hewlett-Packard Company  
United States of America

Rights for non-DOD U.S. Government Departments and Agencies are as set forth in FAR 52.227-19(c)(1,2).

### Copyright Notices

© Copyright 1992-2005 Hewlett-Packard Development Company, L.P.

No part of this document may be copied, reproduced, or translated into another language without the prior written consent of Hewlett-Packard Company. The information contained in this material is subject to change without notice.

### Trademark Notices

HP; Hewlett-Packard Company; and the HP logo are registered trademarks or trademarks of Hewlett-Packard Company. Microsoft®, Windows®, MS Windows®, and Windows NT® are U.S. registered trademarks of Microsoft Corporation. Oracle® is a registered US trademark of Oracle Corporation, Redwood City, California.

All other product names are the property of their respective trademark or service mark holders and are hereby acknowledged.

## Support

Please visit the HP OpenView web site at:

**<http://www.managementsoftware.hp.com/>**

This web site provides contact information and details about the products, services, and support that HP OpenView offers.

You can also go directly to the support web site at:

**<http://support.openview.hp.com/>**

HP OpenView online software support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valuable support customer, you can benefit by using the support site to:

- Search for knowledge documents of interest
- Submit and track progress on support cases
- Manage a support contract
- Look up HP support contacts
- Review information about available services
- Enter discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and log in. Many also require a support contract.

To find more information about access levels, go to the following URL:

**[http://support.openview.hp.com/access\\_level.jsp](http://support.openview.hp.com/access_level.jsp)**

To register for an HP Passport ID, go to:

**<https://passport.hp.com/hpp2/newuser.do>**



# contents

<b>Chapter 1</b>	<b>Introduction</b> .....	21
	Document Structure .....	22
	Document Conventions .....	23
	Command Line Syntax .....	24
	Functional List of Commands .....	25
	Node Management .....	26
	Collectors .....	27
	Process Control .....	28
	Table Maintenance Tools and Utilities .....	29
	Export and Import Tools .....	29
	Data Processes .....	31
	Utilities .....	32
	User Interface .....	33
	Reporting Tools .....	34
<b>Chapter 2</b>	<b>action</b> .....	37
	Requirements and Restrictions .....	37
	Syntax .....	38
	Options .....	38
	Usage Notes .....	39
	Installation Issues .....	40
	General Issues .....	40
	Collection Issues .....	40
	Settings .....	41
	Possible Failures Issues .....	42

Example	42
Messages	42
General	43
Status Messages	43
<b>Chapter 3 builder</b>	<b>45</b>
Requirements and Restrictions	45
Syntax	46
Options	46
Usage Notes	48
Examples	49
Error Messages	49
<b>Chapter 4 collection_manager</b>	<b>51</b>
Requirements or Restrictions	51
Syntax	52
Options	52
Naming Convention	56
Usage Notes	57
Modes of Operation	57
Import	57
Modify	57
Export	58
Remove	58
ASCII File	58
Using the collection_manager Command	62
Examples	63
Import Example	63
Modify Example	64
Modify_All Example	64
Export Examples	65
Remove_All Examples	65
Remove Example	66
Error Messages	66

<b>Chapter 5</b>	<b>datapipe_manager</b> .....	73
	Requirements and Restrictions .....	73
	Syntax .....	74
	Option Categories .....	75
	Options .....	76
	Usage Notes .....	82
	Examples .....	83
	Error Messages .....	83
	Command Line Option Errors .....	84
	Generic File I/O Errors .....	86
	Generic OVPI Errors .....	87
	Generic Database Errors .....	88
	Generic Database Connection Errors .....	88
<b>Chapter 6</b>	<b>db_delete_data</b> .....	89
	Requirements and Restrictions .....	89
	Syntax .....	90
	Options .....	90
	Usage Notes .....	93
	Examples .....	93
	Error Messages .....	94
<b>Chapter 7</b>	<b>deploytool</b> .....	97
	Requirements and Restrictions .....	97
	Syntax .....	98
	Options .....	98
	Usage Notes .....	101
	Using the deploytool Command .....	101
	Deploy Reports .....	101
	Undeploy Reports .....	102
	Examples .....	103
	Error Messages .....	104
<b>Chapter 8</b>	<b>dip_manager</b> .....	109
	Requirements or Restrictions .....	109
	Syntax .....	110

Options . . . . .	110
Naming Convention . . . . .	113
Usage Notes . . . . .	114
Modes of Operation . . . . .	114
Import . . . . .	114
Replace . . . . .	115
Export . . . . .	115
Remove . . . . .	115
ASCII File . . . . .	116
Using the dip_manager Command. . . . .	118
Examples . . . . .	120
Import Example. . . . .	120
Replace Example . . . . .	121
Export Examples . . . . .	121
Export_All Examples. . . . .	121
Remove Example . . . . .	122
Remove_All Examples. . . . .	122
Error Messages . . . . .	122
<b>Chapter 9 ee_collect . . . . .</b>	<b>127</b>
Requirements and Restrictions . . . . .	127
Syntax . . . . .	128
Format 1: . . . . .	128
Format 2: . . . . .	129
Options . . . . .	129
Usage Notes . . . . .	132
Interval Polling (CBC Mode). . . . .	133
Direct Polling (STF Mode). . . . .	133
Log File . . . . .	133
Using the ee_collect Command. . . . .	133
STF Mode . . . . .	134
CBC Mode . . . . .	135
Examples . . . . .	135
Direct Polling of a Datapipe (STF Mode) . . . . .	135
Interval Polling (CBC Mode). . . . .	136
Error Messages . . . . .	136



General Errors . . . . .	137
TEEL File Statement Errors . . . . .	139
Command Line Option Errors . . . . .	141
Generic File I/O Errors . . . . .	143
<b>Chapter 10 formdeploytool . . . . .</b>	<b>145</b>
Requirements and Restrictions . . . . .	145
Syntax . . . . .	146
Options . . . . .	146
Usage Notes . . . . .	148
Using the formdeploytool Command . . . . .	148
Deploy Forms . . . . .	149
Undeploy Forms . . . . .	150
Examples . . . . .	151
Error Messages . . . . .	152
<b>Chapter 11 generate . . . . .</b>	<b>155</b>
Syntax . . . . .	155
Options . . . . .	156
Usage Notes . . . . .	157
Examples . . . . .	158
<b>Chapter 12 groupctl . . . . .</b>	<b>159</b>
Requirements and Restrictions . . . . .	159
Syntax . . . . .	160
Options . . . . .	161
Usage Notes . . . . .	163
Modes of Operation . . . . .	164
Add . . . . .	164
Modify . . . . .	164
Delete . . . . .	164
Using the groupctl Command . . . . .	164
Add . . . . .	165
Modify . . . . .	166
Delete . . . . .	167
Examples . . . . .	167

	Error Messages . . . . .	169
<b>Chapter 13</b>	<b>groupimport</b> . . . . .	171
	Requirements or Restrictions . . . . .	171
	Syntax . . . . .	172
	Options . . . . .	172
	Usage Notes . . . . .	173
	Naming Conventions . . . . .	173
	File Format . . . . .	173
	Example . . . . .	178
<b>Chapter 14</b>	<b>group_manager</b> . . . . .	179
	Requirements or Restrictions . . . . .	179
	Syntax . . . . .	180
	Options . . . . .	181
	Naming Convention . . . . .	187
	Usage Notes . . . . .	188
	About Groups . . . . .	188
	Modes of Operation . . . . .	189
	Import . . . . .	189
	Export . . . . .	190
	Remove . . . . .	191
	Definition Files . . . . .	192
	Document Type Definition for Group Definitions . . . . .	192
	Document Type Definition for Polling Policies . . . . .	193
	Using the group_manager Command . . . . .	194
	Examples . . . . .	196
	Import Examples . . . . .	197
	Export Examples . . . . .	198
	Remove Examples . . . . .	198
	Remove_Policy Examples . . . . .	199
	Error Messages . . . . .	199
	Syntax Messages . . . . .	200
	Value Messages . . . . .	201

<b>Chapter 15</b>	<b>indexmaint</b>	203
	Requirements and Restrictions	203
	Syntax	204
	Options	204
	Usage Notes	207
	Table Indexes	207
	Sybase	207
	Oracle	210
	Processing Considerations	213
	Examples	214
<b>Chapter 16</b>	<b>install.pkg</b>	215
	Requirements and Restrictions	215
	Report Pack Directory Structure	216
	Install.pkg Processing	216
	Install.pkg Directives	217
	Install.pkg Syntax Rules	217
	Document Conventions for Directives	217
	Sample Layout for the File	249
<b>Chapter 17</b>	<b>log_backup</b>	251
	Syntax	251
	Options	252
	Naming Conventions	252
	Usage Notes	253
<b>Chapter 18</b>	<b>mw_collect</b>	255
	Requirements and Restrictions	255
	Syntax	255
	Option Categories	257
	Options	258
	Usage Notes	267
	Terms	268
	mw_collect Command	268
	Configuration File	269
	Syntax	270

Parameters . . . . .	271
By-Variables . . . . .	274
File Locks . . . . .	275
Local Storage of Data . . . . .	275
Interval Polling . . . . .	277
Distributed Polling . . . . .	277
Direct Polling . . . . .	278
Multiple Pollers . . . . .	278
Log File . . . . .	279
Directory Structure . . . . .	279
Examples . . . . .	280
Interval Polling . . . . .	280
Direct Polling . . . . .	281
<b>Chapter 19 node_manager . . . . .</b>	<b>283</b>
Requirements or Restrictions . . . . .	283
Syntax . . . . .	284
Options . . . . .	284
Usage Notes . . . . .	287
Modes of Operation . . . . .	287
Import . . . . .	287
Delete . . . . .	287
Remove . . . . .	287
Export . . . . .	288
ASCII File . . . . .	288
Using the node_manager Command . . . . .	291
Examples . . . . .	292
Import Examples . . . . .	292
Export Examples . . . . .	293
Remove Examples . . . . .	294
Delete Example . . . . .	294
Error Messages . . . . .	295
<b>Chapter 20 ovpi_bulk_copy . . . . .</b>	<b>299</b>
Requirements and Restrictions . . . . .	299
Syntax . . . . .	300

Options	300
Usage Notes	302
Using the <code>ovpi_bulk_copy</code> Command	303
Example	305
Error Messages	305
<b>Chapter 21 <code>ovpi_run_sql</code></b>	<b>307</b>
Requirements and Restrictions	307
Syntax	308
Options	308
Usage Notes	310
Using the <code>ovpi_run_sql</code> Command	310
Example	311
Error Messages	312
<b>Chapter 22 <code>pa_collect</code></b>	<b>313</b>
Syntax	313
Options	314
Usage Notes	316
<b>Chapter 23 <code>pa_discovery</code></b>	<b>317</b>
Requirements or Restrictions	317
Syntax	318
Options	318
Usage Notes	319
Processing Considerations	320
Configuration File Settings	320
<b>Chapter 24 <code>piadmin</code></b>	<b>323</b>
Syntax	323
Options	324
Usage Notes	325
Examples	326
<b>Chapter 25 <code>QGRconverter</code></b>	<b>327</b>
Syntax	327
Usage Notes	328

<b>Chapter 26</b>	<b>QSSconverter</b> .....	329
	Syntax .....	329
	Usage Notes .....	330
<b>Chapter 27</b>	<b>schedule</b> .....	331
	Requirements and Restrictions .....	331
	Syntax .....	332
	Options .....	333
	Usage Notes .....	339
	Modes of Operation .....	339
	Add .....	340
	List .....	340
	Remove .....	340
	Using the schedule Command .....	340
	List .....	341
	Remove .....	341
	Add .....	341
	Examples .....	343
	Error Messages .....	344
<b>Chapter 28</b>	<b>snmpv2dis</b> .....	347
	Syntax .....	347
	Options .....	348
	Usage Notes .....	349
<b>Chapter 29</b>	<b>tpmaint</b> .....	351
	Requirements or Restrictions .....	351
	Syntax .....	352
	Options .....	352
	Usage Notes .....	354
	Examples .....	355
<b>Chapter 30</b>	<b>trendcopy</b> .....	357
	Requirements or Restrictions .....	357
	Syntax .....	359
	Option Categories .....	360

Options . . . . .	360
Usage Notes . . . . .	365
Performance Notes . . . . .	366
Capabilities . . . . .	366
Keymap Tables . . . . .	367
Examples . . . . .	367
Using Various Options to Copy Database Tables . . . . .	367
Using the Row Filter Options To Copy Data by Date . . . . .	368
Using the Specific and Debug Options . . . . .	369
Error Messages . . . . .	371
General . . . . .	371
Server Name Error Messages . . . . .	371
Source Server . . . . .	372
Destination Server . . . . .	373
Table Name Error Messages . . . . .	373
View Error Messages . . . . .	375
By-variable Error Messages . . . . .	375
Foreign Key Error Messages . . . . .	376
Option Error Messages . . . . .	377
<b>Chapter 31 transform_maint . . . . .</b>	<b>379</b>
Requirements and Restrictions . . . . .	379
Syntax . . . . .	380
Options . . . . .	380
Usage Notes . . . . .	382
Using the transform_maint Command . . . . .	382
Examples . . . . .	384
Error Messages . . . . .	385
<b>Chapter 32 trend_discover . . . . .</b>	<b>387</b>
Requirements or Restrictions . . . . .	388
IP Discover Syntax . . . . .	389
IP Discover Options . . . . .	390
IP Discover Usage Notes . . . . .	393
How IP Discover Works . . . . .	393
IP Discover View Population . . . . .	394

Specifying Community Strings for an SNMP GET Request. . . . .	394
Community Strings Files. . . . .	395
Example . . . . .	395
SNMP Type Discover Syntax. . . . .	396
SNMP Type Discover Options . . . . .	396
Naming Convention . . . . .	398
Type Discover Usage Notes . . . . .	398
SNMP Type Discover View Population . . . . .	399
Type Definition Files. . . . .	399
Syntax. . . . .	399
SNMP Tests . . . . .	400
Type Definition File Examples . . . . .	402
<b>Chapter 33 trendexec</b> . . . . .	405
Requirements or Restrictions . . . . .	405
Syntax . . . . .	406
Options . . . . .	406
Example . . . . .	407
<b>Chapter 34 trend_export</b> . . . . .	409
Requirements or Restrictions . . . . .	409
Syntax . . . . .	410
Options . . . . .	410
Usage Notes . . . . .	412
Input Parameter File. . . . .	413
Input Parameter File Rules. . . . .	413
Input Parameter File Keyword Syntax. . . . .	413
Input Parameter File Keyword Descriptions . . . . .	415
Examples. . . . .	420
Command-line Examples . . . . .	420
Input Parameter File Examples. . . . .	421
<b>Chapter 35 trend_label</b> . . . . .	425
Syntax . . . . .	426
Options . . . . .	427
Usage Notes . . . . .	429



Populating the dsi_descr Column . . . . .	429
Locating the Target Row in the Source Data Table . . . . .	429
Ensuring Property Table/Data Table Compatibility . . . . .	430
Update Restrictions . . . . .	431
Extracting Substrings from Column Values . . . . .	431
Concatenating Column Values . . . . .	431
Examples . . . . .	432
<b>Chapter 36 trend_lock</b> . . . . .	435
Syntax . . . . .	435
Usage Notes . . . . .	435
Example . . . . .	436
Functionality in Commands . . . . .	437
Log Message . . . . .	437
<b>Chapter 37 trendpm</b> . . . . .	439
Syntax . . . . .	439
Options . . . . .	440
pe Option Parameters . . . . .	442
Procedure Application Type Values . . . . .	446
<b>Chapter 38 trend_proc</b> . . . . .	447
Requirements and Restrictions . . . . .	447
Syntax . . . . .	448
Options . . . . .	448
Usage Notes . . . . .	449
The trend_proc Input File . . . . .	450
Input File Definitions . . . . .	450
Input File Characteristics . . . . .	451
Processing the Input File . . . . .	452
Processing with Multiple trend_proc Files . . . . .	453
Creating a trend_proc File . . . . .	455
Scheduling a trend_proc File . . . . .	455
Examples . . . . .	455

<b>Chapter 39</b>	<b>trend_sum</b> .....	459
	Requirements or Restrictions .....	459
	Syntax .....	460
	Command-Line Options .....	460
	Input File Keywords .....	461
	Option Categories .....	462
	Keywords .....	462
	Options .....	469
	Naming Conventions .....	471
	Usage Notes .....	473
	Input Files .....	475
	By-Variables .....	475
	Determine the Last Processed Sample for Hysteresis .....	476
	Lag Time .....	477
	Reprocessing Data .....	478
	Rolling Baseline Table .....	478
	NULL Handling .....	479
	Troubleshooting .....	480
	Statistical Formulas and Variables .....	481
	Examples .....	484
<b>Chapter 40</b>	<b>trendtimer</b> .....	487
	Requirements and Restrictions .....	487
	Syntax .....	488
	Options .....	488
	Usage Notes .....	489
	The Schedule File .....	489
	Schedule File Syntax .....	489
	Schedule File Example .....	491
	Starting trendtimer .....	492
	UNIX Platforms .....	492
	Windows Platform .....	493
	Stopping trendtimer .....	493
	UNIX Platforms .....	493
	Windows Platform .....	494
	Example .....	494

<b>Chapter 41</b>	<b>TWQconverter</b> .....	495
	Syntax .....	495
	Options .....	496
	Usage Notes .....	496
<b>Chapter 42</b>	<b>userctl</b> .....	497
	Requirements and Restrictions .....	497
	Syntax .....	498
	Options .....	499
	Usage Notes .....	501
	Modes of Operation .....	502
	Add .....	502
	Modify .....	502
	Delete .....	502
	Using the userctl Command .....	502
	Add .....	503
	Modify .....	505
	Delete .....	506
	Examples .....	506
	Add .....	506
	Modify .....	508
	Delete .....	508
	Error Messages .....	509
<b>Chapter 43</b>	<b>userimport</b> .....	511
	Requirements or Restrictions .....	511
	Syntax .....	512
	Options .....	512
	Usage Notes .....	513
	Naming Conventions .....	513
	File Format .....	514
	Example .....	516
<b>Chapter 44</b>	<b>vantage_collect</b> .....	519
	Requirements and Restrictions .....	519
	Syntax .....	520

Options .....	521
Usage Notes .....	530
Example .....	531
<b>Chapter 45 viewctl</b> .....	<b>533</b>
Requirements and Restrictions .....	533
Syntax .....	534
Options .....	534
Usage Notes .....	536
Modes of Operation .....	537
Add .....	537
Modify .....	537
Delete .....	537
Using the viewctl Command .....	537
Add .....	538
Modify .....	538
Delete .....	539
Examples .....	539
Error Messages .....	540
<b>Chapter 46 viewer</b> .....	<b>541</b>
Requirements and Restrictions .....	541
Syntax .....	542
Options .....	542
Usage Notes .....	545
Examples .....	545
<b>Error Messages Index</b> .....	<b>547</b>
<b>Index</b> .....	<b>555</b>

# Introduction

The purpose of this guide is to assist HP OpenView Performance Insight (OVPI) users with data collection, aggregation, management, and reporting of data used for network management.

This reference guide describes the syntax and discusses the use of command-line interface commands. Each command has a separate chapter and appears in alphabetical order by command name. A functional list of the chapters appears at the end of this chapter; see [Functional List of Commands on page 25](#).

This reference guide also includes an index of the potential error messages in alphabetical order from the various chapters.

## Document Structure

Chapters containing command-line interface commands present the following types of information:

Overview	A brief description appears after the command name in the beginning of the chapter that describes its intended use.
Requirements or Restrictions	This section highlights special conditions or limitations that you may need to remember when you use the command.
Syntax	This section specifies the format for the command name and options that appear on the command line.
Option Categories	This section lists related options by class or groups.
Options	This section lists and describes the options for the command and identifies the valid values for the options.
Naming Conventions	This section defines unique file, directory, and extension naming patterns.
Usage Notes	This section provides detailed information concerning the application of the command.
Examples	This section furnishes practical illustrations of the use of the command.
Error Messages	This section lists potential error messages.

## Document Conventions

The following information describes the style and symbol conventions used in this guide.

**Helvetica Bold** The **Helvetica Bold** typeface identifies window titles, menu items, and other items displayed in the GUI. It is also used in procedural steps to indicate the same; for instance:

Select **File > Open** from the main menu.

**Courier Bold** The **Courier Bold** typeface indicates command line commands, command line options, and code listings used for input such as: **trend\_discover -t**.

*Italic* *Italic* text represents command line *variables* and *parameters* that are placeholders for values; for example:

**trendcopy -s source\_server**

This typeface also identifies *document titles* and defines *new terms* the first time they appear.

Courier The Courier typeface identifies output information from the system such as error messages and other screen messages. It also identifies file names.

Blue If you are viewing this document as a PDF file, blue text indicates a hypertext link.

## Command Line Syntax

The following information shows the conventions used for command-line interface commands.

Items listed but not contained in brackets ( [ ] ) are required.

**trendcopy -S** *target\_server*

Note that the **-S** option and the *target\_server* variable are both required.

[ ] Items that appear inside brackets ( [ ] ) are optional. For example:

**datapipe\_manager [-T** *table\_name* ]

Note that the **-T** option and the *table\_name* variable are not required; the brackets are not part of the syntax.

**Bold** **Bold** items represent commands, options, and keywords that, if used, must be entered as shown. For example:

**trend\_discover -t**

*Italics* Items that appear in *italics* are parameters that require an actual value. For example, enter an actual table name to replace the *table\_name* parameter.

**datapipe\_manager -T** *table\_name*

{ } When multiple keywords appear in braces ( { } ), one of the keywords must be entered on the command line along with the command and option. For example, enter **datapipe\_manager -p create** as a valid command from the following syntax.

**alter**  
**create**  
**delete**  
**remove**  
**verifyparms**



```
datapipe_manager -p {  
  alter  
  create  
  delete  
  remove  
  verifyparms  
}
```

## Functional List of Commands

This is a list of the HP OpenView Performance Insight (OVPI) commands grouped by function. For example, the commands that you can use to maintain database tables are in a section called Table Maintenance Tools and Utilities. The list for each section is in alphabetical order. This list contains the following functional groups:

- [Node Management on page 26](#)
- [Collectors on page 27](#)
- [Process Control on page 28](#)
- [Table Maintenance Tools and Utilities on page 29](#)
- [Export and Import Tools on page 29](#)
- [Data Processes on page 31](#)
- [Utilities on page 32](#)
- [User Interface on page 33](#)
- [Reporting Tools on page 34](#)

## Node Management

This section includes the commands that pertain to node management, which are the commands that allow you to manage the nodes on your OVPI system by discovering them automatically, or by adding, modifying, or deleting them.

**Table 1 Node Management Commands**

Module	Page	Description
<a href="#">node_manager</a>	283	The <b>node_manager</b> command is a stand-alone utility that allows you to manage nodes, types, and views. It also enables you to manage all relevant SNMP properties for nodes.
<a href="#">pa_discovery</a>	317	The <b>pa_discovery</b> command is a utility that allows you to discover an OpenView Performance Agent (OVPA) or an OpenView Operations Agent (OVOA) on an OVPI system.
<a href="#">snmpv2dis</a>	347	The SNMP V2 Discovery Utility ( <b>snmpv2dis</b> ) identifies devices that support the SNMP V2 protocol on an OVPI system.
<a href="#">trend_discover</a>	387	The <b>trend_discover</b> command is a utility that allows you to start an automated process to find the nodes on the system, ascertain whether or not each node is SNMP manageable, identify the type of device, and automatically update tables that control data collection.

## Collectors

This section includes the commands that pertain to collecting data on your OVPI system. These commands include setting parameters for specific types of devices, maintaining the polling policies for the collection process, or importing data from a flat file.

**Table 2 Collector Commands**

Module	Page	Description
<a href="#">action</a>	37	You can use the <b>action</b> command to monitor and report end-to-end network performance characteristics on an OVPI system.
<a href="#">collection_manager</a>	51	You can use the <b>collection_manager</b> command to add, modify, remove, and export polling policies on an OVPI system.
<a href="#">dip_manager</a>	109	You can use the <b>dip_manager</b> command to import, replace, remove, or export directed-instance polling groups on an OVPI system.
<a href="#">ee_collect</a>	127	You can use the <b>ee_collect</b> command to import data from a flat file into a datapipe on an OVPI system.
<a href="#">group_manager</a>	179	You can use the <b>group_manager</b> command to manage group definitions and polling policies.
<a href="#">mw_collect</a>	255	You can use the <b>mw_collect</b> command to collect SNMP data from nodes on an OVPI system.
<a href="#">pa_collect</a>	313	You can use the <b>pa_collect</b> command to collect data from an OpenView Performance Agent (OVPA) or an OpenView Operations Agent (OVOA) on an OVPI system.
<a href="#">vantage_collect</a>	519	You can use the <b>vantage_collect</b> command to collect SNMP data from two tables that have a control table and data table relationship on an OVPI system.

## Process Control

This section includes the commands that pertain to controlling the processing of the data on your OVPI system.

**Table 3 Process Control Commands**

Module	Page	Description
<a href="#">trendexec</a>	405	The <b>trendexec</b> program uses the <code>trend_sum</code> program to execute the <code>trend_sum</code> procedures listed in the database
<a href="#">trend_lock</a>	435	The <b>trend_lock</b> command is a utility that creates a lock to prevent running multiple instances of the same command with its corresponding options.
<a href="#">trend_proc</a>	447	The <b>trend_proc</b> command is a utility that allows you to group together multiple interrelated commands on an OVPI system.
<a href="#">trendtimer</a>	487	The <b>trendtimer</b> program is the OVPI scheduler that starts specific commands at scheduled times.

## Table Maintenance Tools and Utilities

This section includes the commands that pertain to maintaining the database tables on your OVPI system. These commands allow you to create, modify, and remove tables in your database and to maintain those tables by aging out old data or maintaining the indexes for the table.

**Table 4 Table Maintenance Commands**

Module	Page	Description
<a href="#">datapipe_manager</a>	73	The <b>datapipe_manager</b> command is a utility for creating data and property tables and views in an OVPI database.
<a href="#">db_delete_data</a>	89	The <b>db_delete_data</b> command is a utility used to age obsolete data out of the database.
<a href="#">indexmaint</a>	203	The <b>indexmaint</b> command is a utility used maintain indexes of existing OVPI tables in the database.

## Export and Import Tools

This section includes the commands that pertain to exporting and importing information such as data, nodes, groups, or polling policies on your OVPI system.

**Table 5 Export and Import Commands**

Module	Page	Description
<a href="#">collection_manager</a>	51	You can use the <b>collection_manager</b> command to export and import polling policies on an OVPI system.
<a href="#">dip_manager</a>	109	You can use the <b>dip_manager</b> command to import or export directed-instance polling groups on an OVPI system.

**Table 5    Export and Import Commands**

<b>Module</b>	<b>Page</b>	<b>Description</b>
<a href="#">ee_collect</a>	127	You can use the <b>ee_collect</b> command to import data from a flat file into a datapipe on an OVPI system.
<a href="#">groupimport</a>	171	You can use the <b>groupimport</b> command to import multiple user groups with an XML file from the command line on an OVPI system.
<a href="#">group_manager</a>	179	You can use the <b>group_manager</b> command to export and import group definitions and polling policies.
<a href="#">node_manager</a>	283	You can use the <b>node_manager</b> command to export and import nodes on an OVPI system.
<a href="#">ovpi_bulk_copy</a>	299	You can use the <b>ovpi_bulk_copy</b> command to bulk load or extract data on an OVPI system.
<a href="#">trend_export</a>	409	You can use the <b>trend_export</b> program to export data from the database into a text file on an OVPI system.
<a href="#">userimport</a>	511	You can use the <b>userimport</b> command to import multiple user accounts that access the Web Access Server with an XML file from the command line on an OVPI system.

## Data Processes

This section includes the commands that pertain to the processing of the data on your OVPI system, such as by copying the data, summarizing it, or managing the stored procedures that manipulate it.

**Table 6 Data Processing Commands**

Module	Page	Description
<code>transform_maint</code>	379	The <code>transform_maint</code> command is a utility that allows you to perform maintenance tasks related to transformations on an OVPI system.
<code>trendcopy</code>	357	The <code>trendcopy</code> command is a utility that allows you to copy data from one OVPI database to another.
<code>trend_label</code>	425	The <code>trend_label</code> command is a utility that populates one or more columns in a property table with data from its counterpart in the data table.
<code>trendpm</code>	439	The <code>trendpm</code> command is a utility that manages raw-to-delta and copy stored procedures on an OVPI system.
<code>trend_sum</code>	459	The <code>trend_sum</code> command is an application that manages summarization and aggregation stored procedures on an OVPI system.

## Utilities

This section includes the commands that pertain to miscellaneous utilities for the OVPI system.

**Table 7 Utility Commands**

Module	Page	Description
<code>groupctl</code>	159	You can use the <code>groupctl</code> command to add, delete, or modify a single user group from the command line on an OVPI system.
<code>groupimport</code>	171	You can use the <code>groupimport</code> command to add, delete, or modify multiple user groups with an XML file from the command line on an OVPI system.
<code>log_backup</code>	251	The <code>log_backup</code> command is a utility that allows you to move a specified file to a new file as a back up. The default backs up the <code>trend.log</code> file to a new file each day.
<code>ovpi_bulk_copy</code>	299	The <code>ovpi_bulk_copy</code> command is a utility that allows you to bulk load or extract data on an OVPI system.
<code>ovpi_run_sql</code>	307	The <code>ovpi_run_sql</code> command is a utility that allows you to run SQL scripts on an OVPI system.
<code>tpmaint</code>	351	The <code>tpmaint</code> command is a utility that populates time-period tables, which enable optimized searches of the database.
<code>trend_export</code>	409	You can use the <code>trend_export</code> program to export data from the database into a text file.
<code>userctl</code>	497	You can use the <code>userctl</code> command to add, delete, or modify a single user account for accessing the Web Access Server from the command line on an OVPI system.



**Table 7 Utility Commands**

<b>Module</b>	<b>Page</b>	<b>Description</b>
<a href="#">userimport</a>	<a href="#">511</a>	You can use the <b>userimport</b> command to add, delete, or modify multiple user accounts that access the Web Access Server with an XML file from the command line on an OVPI system.
<a href="#">viewctl</a>	<a href="#">533</a>	You can use the <b>viewctl</b> command to add, delete, or modify a catalog view from the command line on an OVPI system.

## User Interface

This section includes the commands that pertain to starting the graphical user interface (GUI) clients from the command line on an OVPI system.

**Table 8 User Interface Commands**

<b>Module</b>	<b>Page</b>	<b>Description</b>
<a href="#">builder</a>	<a href="#">45</a>	The <b>builder</b> command is the command that you enter to start the Report Builder client application.
<a href="#">piadmin</a>	<a href="#">323</a>	The <b>piadmin</b> command is the command that you enter to the start the Management Console from the command line.
<a href="#">viewer</a>	<a href="#">541</a>	The <b>viewer</b> command is the command that you enter to start the Report Viewer client application.

## Reporting Tools

This section includes the commands that pertain to the reporting functions on an OVPI system such as creating, generating, scheduling, deploying, and undeploying reports and forms.

**Table 9 Reporting Tools Commands**

Module	Page	Description
<a href="#">builder</a>	45	The <b>builder</b> command is the command that you enter to start the Report Builder client application.
<a href="#">deploytool</a>	97	The <b>deploytool</b> command is a stand-alone utility that allows you to deploy reports or a folder of reports to the Web Access Server so that you can view them from the Web Access Server. You can also use this command to undeploy reports or a folder of reports from the Web Access Server, which removes them from view on the Web Access Server.
<a href="#">formdeploytool</a>	145	The <b>formdeploytool</b> command is a stand-alone utility that allows you to deploy forms or a folder of forms to the OVPI Administration Server so that you can view them from the Object Manager. You can also use this command to undeploy forms or a folder of forms from the OVPI Administration Server, which removes them from view on the Object Manager.
<a href="#">generate</a>	155	The <b>generate</b> command is the command that you enter to generate the reports for a particular schedule.
<a href="#">install.pkg</a>	215	The <code>install.pkg</code> file provides Package Manager with the basic information needed to install a report pack.

**Table 9 Reporting Tools Commands**

<b>Module</b>	<b>Page</b>	<b>Description</b>
<a href="#">QGRconverter</a>	327	The <b>QGRconverter</b> command is a tool that allows you to convert a legacy TREND Graph Data Definition file (.qgr) to a report definition file (.rep) on an OVPI system.
<a href="#">QSSconverter</a>	329	The <b>QSSconverter</b> command is a tool that allows you to convert a legacy TREND Table Data Definition file (.qss) to a report definition file (.rep) on an OVPI system.
<a href="#">schedule</a>	331	The <b>schedule</b> command is a tool that allows you to configure schedules on an OVPI system.
<a href="#">TWQconverter</a>	495	The <b>TWQconverter</b> command is a tool that allows you to convert a legacy TRENDweb Query file (.twq) to a report definition file (.rep) on an OVPI system.
<a href="#">viewer</a>	541	The <b>viewer</b> command is the command that you enter to start the Report Viewer client application.



## action

You can use the HP OpenView Performance Insight (OVPI) **action** command, which is the Action poller, to monitor and report end-to-end network performance characteristics on an OVPI system. In this case, the Action poller performs two directed-instance polls, pre and post, around a central action, which is the collection of the Cisco Ping round trip data between the nodes of each pair.

### Requirements and Restrictions

- This command requires the installation of the Ping\_MIB report pack.
- To collect data with this command, the collector module for the data table must be **MW**.
- You can invoke the Action Poller from the command line or have **trendtimer** invoke it through an entry in the **trendtimer.sched** file.

## Syntax

The **action** command has the following syntax:

```
action  [-c child_processes]  
         [-d debug_level]  
         [-h]  
         -i polling_interval  
         [-p port]  
         [-r retries]  
         [-s round_factor]  
         [-t timeout]  
         [-v]
```

## Options

The **action** command has the following options:

- c** Use this option to specify the number of concurrent child action poller processes to run. The Action poller starts one child process for each node pair. The processing power of the host determines the value you specify for this option.  
The default is **20**.
- d** Use this option to specify the debug level. Valid values are **0**, **1**, **2**, or **3**. The higher the number, the more detailed the debug output.  
The default is **0**, which means no debug output. Debug output is written to the standard out. Use this option only with HP Technical Support for testing purposes because of the additional overhead it incurs.
- h** Use this option to display the command line options (help).

- i** Use this option to specify the polling interval. Each collection group that has the specified polling interval will be collected during this invocation of the Action poller.
- p** Use this option to specify the port number for SNMP sessions.  
The default is **161**.
- r** Use this option to specify the number of collection retries to attempt for each SNMP session.  
The default is **-1**, which means the default number of tries configured for SNMP.
- s** Use this option to specify the number of seconds for the round factor, which corresponds to the collection interval. The action poller will use this value to round off the collection time (ta\_period); for example, if the Action poller kicks off a collection at 3:07, and if you are using the default collection option of **300** seconds (5 minutes), the actual recorded ta\_period value for the collection will be 3:05.  
The default is **300**.
- t** Use this option to specify the collection timeout, in seconds, for SNMP sessions.  
The default is **-1**, which means the default timeout configured for SNMP.
- v** Use this option to display the version stamp for the **action** command.  
This option is in UPPERCASE.

## Usage Notes

This command is available only when the Ping\_MIB report pack exists on the system. Refer to the documentation with the report pack for more information about using this command.

## Installation Issues

When you use **Package Manager** to install the **Ping\_MIB** report pack, the system adds the following entry to the **trendtimer.sched** file:

```
15 - - {DPIPE_HOME}/bin/trend_proc -f {DPIPE_HOME}/scripts/
Ping_MIB_poll.pro
```

There is an entry in this file to execute the Action poller. When the system executes the command every 15 minutes, the entry is the following command:

```
action -i 15
```

To test the initial or new group collection manually, perform the following steps:

- 1 Comment out the Ping\_MIB entry in the **trendtimer.sched** file, if it is not already commented out.

```
#15 - - {DPIPE_HOME}/bin/trend_proc -f {DPIPE_HOME}/scripts/
Ping_MIB_poll.pro
```

- 2 Enter the following command (if the polling interval is **15**):

```
action -i 15
```

- 3 To restore automatic scheduling, remove the comment character from the Action poller entry in the **trendtimer.sched** file.

## General Issues

The file that the system uses to determine if a device is a Cisco Ping device is the `cisco_ping.dis` file. It contains a list of *oids*, which are object ids that identify the device.

If the Cisco Ping agent is running on the device, the poller reads the agent every second looking for completion. It polls for the following two oids:

```
ciscoPingReceivedPackets (1.3.6.1.4.1.9.9.16.1.1.1.10)
ciscoPingCompleted (1.3.6.1.4.1.9.9.16.1.1.1.14)
```

## Collection Issues

There is only one child collector, which is **action\_collect**, for **action**.

To collect data with this command, the collector module for the data table must be **MW**.



When there are received packets, the action poller will do an SNMP GET to retrieve various oid values such as the min, max, and average round trip times. The min, max, and average round trip times values are rate type data. The oid values follow:

```
ciscoPingPacketSize (1.3.6.1.4.1.9.9.16.1.1.1.5)
ciscoPingSentPackets (1.3.6.1.4.1.9.9.16.1.1.1.9)
ciscoPingReceivedPackets (1.3.6.1.4.1.9.9.16.1.1.1.10)
ciscoPingMinRtt (1.3.6.1.4.1.9.9.16.1.1.1.11)
ciscoPingAvgRtt (1.3.6.1.4.1.9.9.16.1.1.1.12)
ciscoPingMaxRtt (1.3.6.1.4.1.9.9.16.1.1.1.13)
```

## Settings

The following messages identify the settings for the Action poller, which are the Ping Sets. The configuration process sets the Ping Set parameters. See the `Ping_MIB` report pack documentation for more information about setting these parameters.

```
Setting ciscoPingEntryOwner (1.3.6.1.4.1.9.9.16.1.1.1.15) to
owner.
Setting ciscoPingEntryStatus (1.3.6.1.4.1.9.9.16.1.1.1.16) to 4.
Setting ciscoPingProtocol (1.3.6.1.4.1.9.9.16.1.1.1.2) to 1.
Setting ciscoPingAddress (1.3.6.1.4.1.9.9.16.1.1.1.3) to
address.
Setting ciscoPingPacketCount (1.3.6.1.4.1.9.9.16.1.1.1.4) to 5.
Setting ciscoPingPacketSize (1.3.6.1.4.1.9.9.16.1.1.1.5) to 100.
Setting ciscoPingPacketTimeout (1.3.6.1.4.1.9.9.16.1.1.1.6) to
2000.
Setting ciscoPingDelay (1.3.6.1.4.1.9.9.16.1.1.1.7) to 0.
```

where: *owner* is the administrator user name, which is usually trendadm.  
*address* is the destination node, which is the ip or name.

When the `ciscoPingEntryStatus` setting is 4, it means that the system will initiate the ping sequence.

When the `ciscoPingProtocol` setting is 1, it means that the address is an ip address.

The `ciscoPingPacketSize` value is in bytes.

The `ciscoPingPacketTimeout` and `ciscoPingDelay` values are in milliseconds.

When the `ciscoPingDelay` setting is 0, it means that the system should not wait.

All other values are the default values.

## Possible Failures Issues

Some of the usual causes of Ping Set failures include the following reasons.

- The source node is down.
- The source node is not a Cisco Ping Device.
- The Cisco Ping Agent is not running on the device.
- The write community string for Cisco Ping Device is incorrect.
- One or more of the destination nodes are down and ping sequence times out.

## Example

The following command invokes the Action poller to collect the collection table instances from the node pairs defined for all collection groups with a polling interval of **15**:

```
action -i 15
```

## Messages

This section describes some of the messages that can occur from **action**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.

## General

- ❑ The following message appears when the specified oid is missing from the file that determines if a device is a Cisco Ping device.

Not a Cisco Device.

If the device is a Cisco Ping device, verify that the oid for the device is in the `cisco_ping.dis` file.

- ❑ The following message appears when the agent is not running.

SNMP\_TIMEOUT.

Verify that the agent is running on the Cisco device.

## Status Messages

- ❑ The following message appears when the system polls the device, and the ping did not complete.

```
check ping results: ciscoPingCompleted = false
```

The system continues to poll the device while this statement is set to false.

- ❑ The following message appears when the system polls the device, and the ping did complete.

```
check ping results: ciscoPingCompleted = true, packets  
received = number
```

where: *number* is the number of packets received by the device.

This message will not appear if the timeout message appears.

*action*

# builder

You can use the **builder** command to start the Report Builder client application from the command line on an HP OpenView Performance Insight (OVPI) system.

## Requirements and Restrictions

- When you connect to a different server with the **-server** option, use the **Browse** option to view the files on the specified server.
- When you use the **-mode remote** option, you must include the **-file** option on the command line at the same time.
- When you use the **-file** option without the **-mode** option on the command line, the system will open the specified file on the local system.
- When you change a parameter with the **-params** option, remember that it is a global option and it applies to every report you open that has the parameter specified.

## Syntax

The **builder** command uses the following syntax:

```
builder [ -debug ddebug_value ]
          [ -file path_reportname ]
          [ -log logfile ]
          [ -mode location ]
          [ -p password ]
          [ -params parameter1=value1[,parameter2=value2, ... ] ]
          [ -port number ]
          [ -server servername ]
          [ -u username ]
```

## Options

The **builder** command has the following options:

- debug**      Use this option to enable diagnostic messages, which are an extra level of detail included in the log file.  
Valid values are:  
**true**            will enable diagnostic messages  
**false**          will not enable diagnostic messages  
The default is **false**.
- file**        Use this option to specify the name of the report you want to open automatically when you run **builder**. You can use the absolute or relative path with the name of the report file. For a remote file, you need to give the remote location in reference to its deployed location.

- log** Use this option to specify the name of the log file to open. Include the path for the name. The name should have a slash as the first character in the name because the system will add the prefix OVPI to the specified name.  
The default log file is `builder.log`.
- mode** Use this option to specify the location for the file you want to access. There are two values; they are:  
**local** when the file is on the local system.  
**remote** when the file is on the Web Access Server.  
The default is **local**.  
Use the **-file** option to specify the name and location of the file. You must use the **-file** option with this option to open a remote file automatically when you run **builder**.
- p** This option specifies the password for the login process.  
If you do not use this option with the **-u** option, the system will prompt for the username and password.
- params** Use this option to specify the report parameters to change report defaults at run time. A parameter has the following format: *parameter=value*. This is a global option; it applies to every report you open that has the parameter specified.  
When you specify more than one parameter, separate the parameters with a comma (,). When a parameter value contains a space, enclose all the parameters in one set of quotes. The following example shows multiple parameters with one parameter that has a space in the value.  
**-params "INTERFACE=92,CUSTOMER=All Telco"**  
When a parameter value contains a character that is special to the command interface (shell) such as a comma, precede the character with a backward slash (\), for example:  
**-params "INTERFACE=92,CUSTOMER=Telco\,North"**  
Refer to the *Performance Insight Guide to Building and Viewing Reports* for details about how to create and view the parameters associated with a report using Report Builder, and for details about how to view and modify the parameters associated with a report using the Web Access Server.

- port** Use this option to specify the port number of the Web Access Server that you want to access from the Report Builder client application.  
The default for this option is the port number supplied during the OVPI installation, which is port number **80**, in most cases.
- server** Use this option to specify the host name of the Web Access Server that you want to access from the Report Builder client application. If you want to access a system in a different domain, you will need to specify the full domain name for the host name.  
The default for this option is the server host name supplied during the OVPI installation.
- u** This option specifies the username for the login process.  
If you do not use this option with the **-p** option, the system will prompt for the username and password.

## Usage Notes

You can use Report Builder to build customized reports based on data from the OVPI database, modify existing reports, and deploy reports to the Web Access Server. Refer to the *Performance Insight Guide to Building and Viewing Reports* for more information about using the Report Builder client application.

If you want to browse the reports on a remote system when you run **builder**, you can use the **-server** option alone. However, if you want to open a specific report file automatically when you run **builder**, you can add the **-mode remote** option with the **-file** option.



## Examples

The following examples illustrate some uses of the **builder** command.

### Example 1

If you want to use the Report Builder client application to access reports on a different system such as **powder2**, and you want to bypass the **Login** dialog box, enter the following command.

```
builder -server powder2 -u trendadm -p trendadm -port 80
```

### Example 2

If you want to use the Report Builder client application to access reports on a different system such as **testsrvr1** with a different log file in the `OVPI/log` directory that has the name, **test\_build1.log**, enter the following command.

```
builder -server testsrvr1.abc.xyz.com -log /log/test_build1.log
```

## Error Messages

This section describes some of the messages that can occur from **builder**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
  - The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- ☐ If the following error message appears, the specified option is missing a value.

Error in arguments.

A value is required for argument *option* : *desc*.

Verify that the specified option has the correct value.

- ❑ If the following error message appears, the specified option is not a valid option.

Error in arguments *option* is not valid for this program.

Verify the spelling of the *option* on the command line. Check [Syntax on page 46](#) for the list of valid options.

- ❑ If the following error message appears, the system could not connect to the specified server.

Failed to connect to *server\_name*.

Verify the spelling of the *server\_name* on the command line. Note that you may need to use full domain name for the *server\_name*.

## collection\_manager

The **collection\_manager** command is a stand-alone utility that allows you to manage polling policies on an HP OpenView Performance Insight (OVPI) system. It allows you to add, modify, remove, and export polling policies.

You can also add, modify, and remove polling policies from the Management Console. Refer to the *Performance Insight Administration Guide* for more information.

### Requirements or Restrictions

- All required files must have the following parameters in the file: *policy\_name*, *table\_name*, and *group*.
- An error occurs if more than one of the following options appears on the command line at the same time: **-import**, **-export**, **-modify**, **-modify\_all**, **-remove**, or **-remove\_all**.
- An error occurs if the **-file** option does not appear with one of the following options on the command line at the same time: **-import**, **-modify\_all**, **-remove\_all**.

## Syntax

The **collection\_manager** command uses the following syntax:

```

collection_manager  [ -database db_name ]
                    [ -debug debug_level ]
                    [ -descr description ]
                    [ { -export
                      { -import
                      { -modify policy_name
                      { -modify_all
                      { -remove policy_name
                      { -remove_all
                    }
                    }
                    }
                    }
                    }
                    [ -file file_name ]
                    [ -group group_category.group_name ]
                    [ -help ]
                    [ -interval num_minutes ]
                    [ -pollfrom host_name ]
                    [ { -v
                      { -version
                    }
                    ]

```

## Options

The **collection\_manager** command has the following options:

**-database** This option identifies the database where the changes will occur. The database must appear in the list of available database servers. See the Web Access Server in the *Performance Insight Administration Guide* for more information about adding database servers to the list. The default is the database identified as the default in the database server list.

- debug** Use this option to set the debug output level. The higher the number, the more detailed the information. Debug output writes to standard output. Use this option only for testing in coordination with Technical Support due to the additional overhead it places on **collection\_manager**. The default is no debug output.
- descr** Use this option to modify a polling policy description directly from the command line. If you enter more than one word, you must enclose the description in double quotes (“). You must use the **-modify** option with this option. This option provides the same type of information as the *desc* parameter in the ASCII file.
- export** Use this option to generate a file containing the polling policies in the current collection catalog. Use the **-file** option to specify the output file name; otherwise, **collection\_manager** writes the data to standard output. If the specified output file already exists, the system will overwrite the file. See [ASCII File on page 58](#) for the format of the file. See [Export on page 58](#) for more information. This option cannot appear on the command line when the **-import**, **-modify**, **-modify\_all**, **-remove**, or **-remove\_all** option appears on the command line.
- file** This option identifies the file name, which is the text file that contains the information about the polling policies to import, modify, or remove. If the file is not in the current working directory, you must specify the fully qualified path to the file. See [ASCII File on page 58](#) for details on setting up this file. This is a required option when the **-import**, **-modify\_all**, or **-remove\_all** option appears on the command line.

- group** Use this option to modify the name of the group assigned to the polling policy from the command line. It must be in the form *group\_category.group\_name*. See [Naming Convention on page 56](#) for a more detailed description of this name. You must use the **-modify** option with this option. This option provides the same type of information as the *group* parameter in the ASCII file.
- help** This option is the help option, which displays the command-line syntax for the **collection\_manager** command.
- import** Use this option to import polling policies. It requires the **-file** option to identify the file that contains the list of polling policies to import. This option cannot appear on the command line when the **-export**, **-modify**, **-modify\_all**, **-remove**, or **-remove\_all** option appears on the command line.
- interval** Use this option to modify the polling interval directly from the command line. The polling interval is the number of minutes between polling requests. See the *poll\_interval* parameter in the ASCII file on [page 60](#) for a list of the valid values. You must use the **-modify** option with this option.
- modify** Use this option to modify an existing polling policy. You must specify the *policy\_name* on the command line following this option. This option must appear on the same line as one or more of the following options: **-descr**, **-group**, **-interval**, and **-pollfrom**. See [Modify on page 57](#) for more information. This option cannot appear on the command line when the **-export**, **-import**, **-modify\_all**, **-remove**, or **-remove\_all** option appears on the command line.

- modify\_all** Use this option to modify the polling policies specified with the **-file** option. See [ASCII File on page 58](#) for a description of the associated file. See [Modify on page 57](#) for more information.
- This option cannot appear on the command line when the **-export**, **-import**, **-modify**, **-remove**, or **-remove\_all** option appears on the command line.
- pollfrom** Use this option to change the name of the polling station for an existing polling policy directly from the command line. You must use the **-modify** option with this option.
- This option provides the same type of information as the *poll\_from* parameter in the ASCII file.
- remove** Use this option to remove a polling policy from the collection catalog. You must specify the *policy\_name* on the command line following this option. See [Remove on page 58](#) for more information.
- This option cannot appear on the command line when the **-export**, **-import**, **-modify**, **-modify\_all**, or **-remove\_all** option appears on the command line.
- remove\_all** Use this option to remove all the polling policies listed in the associated file from the collection catalog. It requires the **-file** option to identify the file that contains the list of polling policies to remove. See [Remove on page 58](#) for more information.
- This option cannot appear on the command line when the **-export**, **-import**, **-modify**, **-modify\_all**, or **-remove** option appears on the command line.
- v** Use this option to display the current version of the **collection\_manager** utility.
- This option is in UPPERCASE.
- version** Use this option to display the current version of the **collection\_manager** utility.

## Naming Convention

The **-group** option or the *group* parameter must use the following format, *group\_category.group\_name*.

The *group\_name* portion of this parameter is the name of the group that contains the list of objects to collect. It appears in the **Select Group to Poll From** pull-down list in the **Edit Polling Policy** or **Create Collection** dialog in **Polling Policy Manager**.

The *group\_category* portion of this parameter identifies the kind of group for the corresponding *group\_name*. If the group is a **type** list, then the *group\_category* is **type**. Similarly, if the group is a **view** list, then the *group\_category* is **view**. If the group is a single node group, then the *group\_category* is **node**. Otherwise, the *group\_category* is the same as the property table name.

The following table shows the typical association for the *group\_category* value to the corresponding kind of group in the **Collect Data From** field in the **Edit Polling Policy** or **Create Collection** dialog in **Polling Policy Manager**.

**Table 10 Typical Values for the Group Category Parameter**

Group Category Value	Value in Collect Data from Field
<b>type</b>	<b>All Nodes of the Same Type A Combination of Type and View</b>
<b>view</b>	<b>All Nodes in Same View</b>
<b>node</b>	<b>A Single Node</b>
<i>property_table_name</i>	<b>Specific Instances Custom Groups</b>

Refer to the *Performance Insight Administration Guide* for more information about **Polling Policy Manager**.



# Usage Notes

This section describes the available modes, the parameters for the associated ASCII file, and how to use the **collection\_manager** command.

Every group belongs to a group category. If the referenced group is not a **type**, **view**, or **node**, then the category will be the name of the property table that contains the objects defined in the group.

## Modes of Operation

The **collection\_manager** command has four modes of operation: import, modify, export, and remove.

### Import

The *import* mode provides the ability to define multiple polling policies. It requires a file that contains at least three parameters in each record to define each polling policy; they are *policy\_name*, *table\_name*, and *group*. See [ASCII File on page 58](#) for more information about the file.

### Modify

The *modify* mode provides the ability to change specific settings in existing polling policies. There are two options available; they are **-modify** and **-modify\_all**.

- The **-modify** option allows you to modify a single polling policy in the system by entering the parameters on the command line. You must include at least one of the following options in any combination on the command line at the same time: **-descr**, **-group**, **-interval**, and **-pollfrom**. When you use this option, **collection\_manager** changes only the specified settings in the polling policy.
- The **-modify\_all** option allows you to modify one or more polling policies in the system with the parameters from a file. You must include the **-file** option on the command line. You can change any combination of the following parameters in the file for each polling policy definition: *poll\_interval*, *poll\_from*, *group*, and *desc*; however, if you do not specify a modifiable parameter, **collection\_manager** will replace the missing

value with the default. Note, however, that each polling policy in the file must have the following three parameters: *policy\_name*, *table\_name*, and *group*; and a value or a placeholder for every parameter. See [ASCII File on page 58](#) for more information about the file.

You can use the **-database** option with either option to specify the server that contains the polling policies.

## Export

The *export* mode provides the ability to create a file containing the existing polling policies in the catalog.

## Remove

The *remove* mode provides the ability to remove polling policies from the catalog. There are two options available; they are **-remove** and **-remove\_all**.

- The **-remove** option allows you to remove a single polling policy from the system by using the command line.
- The **-remove\_all** option allows you to remove one or more polling policies from the system by using a file. You must include the **-file** option on the command line. In this mode, **collection\_manager** requires the *policy\_name*, *table\_name*, and *group* parameters in the associated file; however, it uses only the *policy\_name* parameter and ignores all the other parameters. Note that each polling policy in the file must have a value or a placeholder for every parameter. See [ASCII File on page 58](#) for more information about the file.

You can use the **-database** option with either option to specify the server that contains the polling policies.

## ASCII File

Three of the four modes of operation require an ASCII file. All of these modes require at least three parameters: *policy\_name*, *table\_name*, and *group*; but each record in the file must have a value or a placeholder for every parameter in the record. The ASCII file that contains the polling policies must be in the following format:

```
policy_name, table_name, poll_interval, datapipe_name, poll_from, user_name,
server_name, group, group_server, desc
```



If any of the required parameters contain invalid values for a particular option, an error message occurs and the process may terminate at that point. In some cases, the system skips the record and checks the rest of the file for additional errors. If an error occurs, verify that all records contain valid values before you resubmit the file. Verify that there are no blank lines; otherwise, an error message occurs and the process terminates at that point.

Use the comma delimiter as a placeholder for any parameter that is missing; otherwise, the system will skip the record, display an error message, and stop processing at that point.

The descriptions for the parameters in the file follow:

<i>policy_name</i>	<p>This parameter specifies the name of the polling policy. The length of the <i>policy_name</i> can be up to 30 characters.</p> <p>It appears in the <b>Policy Name</b> field in the polling policy.</p> <p>This is a required parameter for the <b>-import</b>, <b>-modify_all</b>, and <b>-remove_all</b> options.</p>
<i>table_name</i>	<p>This parameter specifies the SQL name of the table for the collected data. The table must already exist in the database. This parameter is the SQL name that corresponds to the Alias table name that appears in the <b>Data to Poll For</b> field in the polling policy. Use <b>Table Manager</b> to view the corresponding SQL names and the Alias names for tables. If you need to create a collectable table, see <a href="#">datapipe_manager on page 73</a> or refer to the <i>Performance Insight TEEL Reference Guide</i>.</p> <p>This is a required parameter for the <b>-import</b>, <b>-modify_all</b>, and <b>-remove_all</b> options.</p>

*poll\_interval* This parameter specifies the polling interval in minutes. The polling interval is the length of time between polling requests.

Valid values are:

<b>0</b>	off
<b>5</b>	5 minutes
<b>10</b>	10 minutes
<b>15</b>	15 minutes
<b>20</b>	20 minutes
<b>60</b>	1 hour
<b>1440</b>	1 day

The default value is **0**.

This parameter must contain a valid value when it is in the file; otherwise, an error message occurs. If you do not enter a value for this parameter, **collection\_manager** will use the default.

It appears in the **Poll Interval** field in the polling policy.

You can change this attribute in an existing polling policy with the **-modify** and **-interval** options on the command line.

*datapipe\_name* This parameter specifies the datapipe that contains the data. It must exist on the server specified in the *poll\_from* parameter.

The default value is **dpipe\_snmp**.

It appears in the **Use Datapipe** field in the polling policy.

*poll\_from* This parameter specifies the server that contains the data. The datapipe specified in the *datapipe\_name* parameter must exist on this server. If you do not enter a value for this parameter, **collection\_manager** will use the default.

The default value is the name of the local host server.

It appears in the **Polling Assigned to** field in the polling policy.

You can change this attribute in an existing polling policy with the **-modify** and **-pollfrom** options on the command line.

<i>user_name</i>	<p>This parameter specifies the owner of the polling policy. Currently, the value is always <b>trendadm</b>, which is the default value. The system ignores any other value at this time.</p> <p>It appears in the <b>User</b> field in the polling policy.</p>
<i>server_name</i>	<p>This parameter specifies the target server name, which is the database server that contains the collected data.</p> <p>The default value is the value flagged as the default in the OVPI connections file, unless this is overridden by the <b>-database</b> command line option.</p> <p>It appears in the <b>Server</b> field in the polling policy.</p>
<i>group</i>	<p>This parameter specifies the type of group, which is the <i>group_category</i>, along with the associated <i>group_name</i> for the polling policy. It must already exist in the group catalog. See <a href="#">Naming Convention on page 56</a> for a more detailed description of this name.</p> <p>It must be in the form <i>group_category.group_name</i>.</p> <p>This is a required parameter for the <b>-import</b>, <b>-modify_all</b>, and <b>-remove_all</b> options.</p> <p>You can change this attribute in an existing polling policy with the <b>-modify</b> and <b>-group</b> options on the command line.</p>
<i>group_server</i>	<p>Currently, this parameter is the same as the <i>server_name</i> parameter.</p>
<i>desc</i>	<p>This parameter provides a description for the polling policy. If you do not enter a value for this parameter, <b>collection_manager</b> will use the default.</p> <p>The default for this parameter is <b>NULL</b>.</p> <p>You can change this attribute in an existing polling policy with the <b>-modify</b> and <b>-desc</b> options on the command line.</p> <p>It appears in the <b>Description</b> field in the polling policy.</p>

## Using the collection\_manager Command

This section shows some formats of the command for the various modes.

- If you enter the **collection\_manager** command without any options, the system will display an error message followed by the help information.
- To display the syntax and options for this command, enter the following:

```
collection_manager -help
```

- To display the version information for this command, enter one of the following commands:

```
collection_manager -V or collection_manager -version
```

- To import one or more polling policies, enter the following command:

```
collection_manager -import -file file_name
```

where: *file\_name* is the name of the ASCII file that contains the list of nodes with their corresponding attributes to import.

- To modify a single polling policy, enter the following command:

```
collection_manager -modify policy_name -interval num_minutes  
-descr description -group group_category.group_name -pollfrom host_name
```

where: *policy\_name* is the name of the polling policy to modify.

*num\_minutes* is the number of minutes between polling requests.

*description* is the modified description of the polling policy.

*group\_category* is the kind of group for the corresponding *group\_name*.

*group\_name* is the name of the group that contains the list of nodes to poll.

*host\_name* is the name of the server that contains the data.

Note that you can use any combination of these options with the **-modify** option.

- To modify one or more polling policies, enter the following command:

```
collection_manager -modify_all -file file_name
```

where: *file\_name* is the name of the ASCII file that contains the list of polling policies with their corresponding settings to modify.

- To remove a single polling policy, enter the following command:  
**collection\_manager -remove *policy\_name***  
 where: *policy\_name* is the name of the polling policy to remove.
- To remove one or more polling policies, enter the following command:  
**collection\_manager -remove\_all -file *file\_name***  
 where: *file\_name* is the name of the ASCII file that contains the list of polling policy names to remove.
- To export a list of nodes to a file, enter the following command:  
**collection\_manager -export -file *file\_name***  
 where: *file\_name* is the name of the ASCII file that will contain the list of existing polling policies on the system.
- To export a list of nodes to the screen, enter the following command:  
**collection\_manager -export**

## Examples

This section has examples that show each mode of **collection\_manager**. They have the following characteristics.

- All examples refer to the sample file used in the import example.
- These examples do not contain any blank lines, and any spacing that appears between lines is for readability.
- Any information that appears about the **-file** option for one example also applies to other examples, such as the need for a qualified path.

### Import Example

To import a list of polling policies from a file named `policy_in.txt`, enter the following command:

```
collection_manager -import -file policy_in.txt
```

The following is an example of the contents for the input file `policy_in.txt`:

```
test_policy_1,test_data_tbl,20,test_dp,,trendadm,,
view.view_ex_lst,,Test polling policy 1.
test_policy_2,testtime_,0,testtime,,trendadm,,
type.type_ex_lst,,Test polling policy 2.
test_policy_3,test_data_1_tbl,15,dpipe_snmp,,trendadm,,
view.vw_lst2,,Test polling policy 3.
test_policy_4,test_data_1_tbl,1440,dpipe_snmp,,trendadm,,
type.type_ex_lst,,Test polling policy 4.
```

Note that the file does not contain any blank lines, the spacing here is for readability.

## Modify Example

To change a particular setting in an existing polling policy, use the **-modify** option with the corresponding option for the setting.

### Example 1

If you want to change the polling interval for **test\_policy\_3** from 15 minutes to an hour, enter the following command:

```
collection_manager -modify test_policy_3 -interval 60
```

### Example 2

If you want to change the group of nodes for **test\_policy\_2** from **type\_ex\_lst** to **tp\_lst1** and change the polling interval from `off` to 15 minutes, enter the following command:

```
collection_manager -modify test_policy_2 -group type.tp_lst1
-interval 15
```

## Modify\_All Example

Another way to make the changes described above at the same time is to use an ASCII file containing the polling policy definitions. The file should contain the following entries:

```
test_policy_2,testtime_,15,testtime,,trendadm,,type.tp_lst1,,
Test polling policy 2.
test_policy_3,test_data_1_tbl,60,dpipe_snmp,,trendadm,,
view.vw_lst2,,Test polling policy 3.
```



Note that every parameter must have a valid value or placeholder in the file. Furthermore, the following three parameters must be in the file with valid values: *policy\_name*, *table\_name*, and *group*. If you use a placeholder for a parameter, **collection\_manager** will use the default. In this example, the *poll\_from*, *server\_name*, and *group\_server* parameters will use the defaults. The name of the file in this example is **policy\_mod.txt**. To execute these changes, enter the following on the command line:

```
collection_manager -modify_all -file policy_mod.txt
```

## Export Examples

### Example 1

To generate a file containing all the polling policy definitions that are in the collection catalog, you can specify an ASCII file to store the definitions. For example, if you want to export the current list of polling policies to a file called **policy\_export.txt**, enter the following command:

```
collection_manager -export -file policy_export.txt
```

### Example 2

If you do not specify a file, **collection\_manager** exports the polling policy definitions to standard output. The polling policy definitions appear on the screen when you enter the following command:

```
collection_manager -export
```

### Example 3

If you want to export the polling policies from a different server named **bear** to a file named **policy\_out.txt**, enter the following command:

```
collection_manager -export -file policy_out.txt -database bear
```

## Remove\_All Examples

### Example 1

If you want to remove multiple polling policies, you can use an ASCII file to specify the list. To remove the policies in the file, **policy\_mod.txt**, enter the following:

```
collection_manager -remove_all -file policy_mod.txt
```

## Example 2

Note that you need to fully qualify the path for the file if it is in a different directory. For example, if the file were in the **lists** directory from the **D** drive on a Windows machine, you would enter the following command:

```
collection_manager -remove_all -file d:\lists\policy_mod.txt
```

## Remove Example

If you want to remove a single polling policy such as **test\_policy\_2**, enter the following command:

```
collection_manager -remove test_policy_2
```

## Error Messages

This section describes some of the messages that can occur from **collection\_manager**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.
- If the following error message appears, there is a command-line syntax error. This means that a required mode option is missing.

```
A mode of operation is required.  
Exiting program with code 1.
```

Verify that the command has only one of the following options on the command line at the same time: **-import**, **-export**, **-modify**, **-modify\_all**, **-remove**, or **-remove\_all**.

- If the following message appears, the value for the **-interval** option on the command line is not a numeric character.

```
Collection interval must be a number.  
Exiting program with code 1.
```

Verify that the value for the **-interval** option on the command line is an integer number and that it does not contain a letter or other characters such as a dot.

- If the following message appears, the specified *policy\_name* that is either with the **-modify** option or in the associated file does not exist.

Collection *policy\_name* does not exist.

Verify that the spelling of the policy name is correct or that the polling policy exists; you can use **Polling Policy Manager** to view the existing list of polling policies. The *policy\_name* may be in either of the following locations: with the **-modify** option on the command line or in the first position of each record in the associated file.

- If the following error message appears, the database specified with the **-database** option on the command line does not exist.

Connection URL not found.  
Exiting program with code 3.

Verify the spelling of the database name. If the spelling is correct, you can add the database using the Web Access Server.

- If the following message appears, the host name for the **-pollfrom** option on the command line does not appear in the list of **Datapipe Installations** for the specified datapipe in the policy.

Could not find installed datapipe for *host\_name*.

Verify the following items:

- The spelling of the host name is correct.
- The host name exists.
- The host name is in the list of **Datapipe Installations** for the specified datapipe.

You can use **Polling Policy Manager** to check the list of **Datapipe Installations**. From the **Edit** menu, select **Datapipe Installations**. The **Edit Datapipe Installations** window appears. Select the specified datapipe from the **Select Datapipe** field. Verify the host name appears in the **Hostname** column of the **Current Datapipe Installations** field. At this point you can add or modify the **Datapipe Installation**, if necessary.

- If the following message appears, the value for the *poll\_interval* parameter in the associated file is not a numeric character.

```
Could not convert string to integer on line n - interval
invalid.
Exiting program with code 4.
```

Verify that the value for the *poll\_interval* parameter in the associated file is an integer number and that it does not contain a letter or other characters such as a dot.

- If the following message appears, the datapipe name for the *datapipe\_name* parameter on the specified line in the associated file does not exist for the *table\_name* parameter on the same line.

```
Datapipe datapipe_name on line n does not exist for table
table_name.
```

Verify that the spelling of the datapipe name or the table's SQL name is correct, or that the datapipe exists. You can use **Polling Policy Manager** to check which datapipes exist for a selected table. From the **Edit Polling Policy** window, the alias name of the table appears in the **Data to Poll For** field and the datapipe name appears in the **Use Datapipe** field. Note that you must use the SQL name for the table in the ASCII file and not the alias name; you can use **Table Manager** to view the list of tables for the corresponding names.

- If the following message appears, the value for the **-debug** option on the command line is not a numeric character.

```
Debug level must be a number.
Exiting program with code 1.
```

Verify that the value for the **-debug** option on the command line is an integer number and that it does not contain a letter or other characters such as a dot.

- If the following message appears, the value for the **-debug** option on the command line is not valid.

```
Debug level must be between 0 and 3.
Exiting program with code 1.
```

Verify that the value for the **-debug** option on the command line is an integer number and is one of the following numbers: 0, 1, 2, or 3.

- If the following error message appears, the specified record in the file has a syntax error.

Exception: Wrong number of delimiters on line *n*.  
Exiting program with code 4.

Check the specified record in the file and fix the error. Verify that the record has either a value or a placeholder for all parameters or that the line is not blank.

- If the following error message appears, the file name specified on the command line in the **-file** *file\_name* option does not exist.

File *file\_name* does not exist.  
Exiting program with code 2.

Verify the spelling of the file name or that the file exists in the specified location. You may have to supply a fully qualified path name with the file name.

- If the following message appears, the value for the **-group** option on the command line does not exist.

Group *group\_name* does not exist.

Verify the following items:

- The spelling of the *group\_category* or the *group\_name* portion of the **-group** option value is correct.
- The *group\_name* portion of the **-group** option value exists for the type of group in the *group\_category* portion.
- The *group\_category* portion of the **-group** option value has the correct name.

You can use **Polling Policy Manager** to view the existing list of polling groups. From the **Edit** menu, select **Polling Groups**. The **Edit Polling Groups** window appears. The *group\_category* portion corresponds to the **Select Kind of Group** field. The *group\_name* portion corresponds to the **Select Group** field. You can also view the existing list of polling groups from the **Edit Polling Policy** window. See [Naming Convention on page 56](#) for more information.

- If the following message appears, the *group* parameter on the specified line in the associated file does not exist.

Group *group\_name* on line *n* does not exist.

Verify the following items:

- The spelling of the *group\_category* or the *group\_name* portion of the *group* parameter is correct.
- The *group\_name* portion of the *group* parameter exists for the type of group in the *group\_category* portion.
- The *group\_category* portion of the *group* parameter has the correct name.

You can use **Polling Policy Manager** to view the existing list of polling groups. From the **Edit** menu, select **Polling Groups**. The **Edit Polling Groups** window appears. The *group\_category* portion corresponds to the **Select Kind of Group** field. The *group\_name* portion corresponds to the **Select Group** field. You can also view the existing list of polling groups from the **Edit Polling Policy** window. See [Naming Convention on page 56](#) for more information.

- If the following message appears, the value for the **-interval** option on the command line is not a valid value for a polling interval.

```
Invalid collection interval.
Exiting program with code 1.
```

Verify that the value for the **-interval** option on the command line is a valid value for a polling interval. See the description of the *poll\_interval* parameter on [page 60](#) for the valid values.

- If the following message appears, the value for the *poll\_interval* parameter on the specified line in the associated file is not a valid value for a polling interval.

```
Invalid poll interval on line n.
Exiting program with code 4.
```

Verify that the value for the *poll\_interval* parameter on the specified line in the associated file is a valid value for a polling interval. See the description of the *poll\_interval* parameter on [page 60](#) for the valid values.

- If the following error message appears, the **-file** option is missing on the command line for an option that requires a file.

```
No file specified.
Exiting program with code 1.
```

Verify that the **-file** option is on the command line with one of the following options at the same time: **-import**, **-modify\_all**, **-remove\_all**.

- If the following error message appears, there is a command-line syntax error. This means that there are multiple mode options on the same command line.

Only one mode of operation is allowed.  
Exiting program with code 1.

Verify that the command has only one of the following options on the command line at the same time: **-import**, **-export**, **-modify**, **-modify\_all**, **-remove**, or **-remove\_all**.

- If the following message appears, the host name for the *poll\_from* parameter on the specified line in the associated file does not appear in the list of **Datapipe Installations** for the *datapipe\_name* parameter on the same line.

Poll from *host\_name* on line *n* not installed on datapipe *datapipe\_name*.

Verify the following items:

- The spelling of the host name is correct in the file.
- The host name exists.
- The host name is in the list of **Datapipe Installations** for the specified datapipe.

You can use **Polling Policy Manager** to check the list of **Datapipe Installations**. From the **Edit** menu, select **Datapipe Installations**. The **Edit Datapipe Installations** window appears. Select the specified datapipe from the **Select Datapipe** field. Verify the host name appears in the **Hostname** column of the **Current Datapipe Installations** field. At this point you can add or modify the **Datapipe Installation**, if necessary.

- If the following message appears, the table name for the *table\_name* parameter on the specified line in the associated file does not exist.

Table *table\_name* on line *n* does not exist.

Verify that the spelling of the table's SQL name is correct or that the table exists. You can use **Table Manager** to view the existing list of tables. Make sure that you use the table name from the **SQL Name** column in your ASCII file.

- If the following error message appears, the command is missing at least one setting to modify in the specified polling policy.

The `-modify` option requires at least one of the following:  
`-descr`, `-group`, `-pollfrom`, or `-interval`.  
Exiting program with code 1.

Verify that at least one of the following options is on the command line with the `-modify` option: **`-descr`**, **`-group`**, **`-interval`**, and **`-pollfrom`**.



## datapipe\_manager

You can use the **datapipe\_manager** command to create data and property tables and views in an HP OpenView Performance Insight (OVPI) database.

Refer to the *Performance Insight TEEL Reference Guide* for more information.

### Requirements and Restrictions

- You can create a data or property table using a TEEL file or a template.
- You can create a view using a TEEL file only.
- The **alter** mode of the **-p** option is only available from the command line.

# Syntax

A parameterless **datapipe\_manager** command displays the command syntax.

```

datapipe_manager [-a name ]
                  [-b ]

                  [-c { as-is
                        on
                        off } ]

                  [-C [n],sqlname,type,size,alias[,default=value
                    ,null={ yes
                             no } ,foreign_key(table.dsi_key_id)
                    ,desc=desc ] ]

                  [-d debug_level]
                  [-e ]
                  [-h ]
                  [-L alias_name ]
                  [-n hostname ]

                  [-p { alter
                        create
                        delete
                        remove
                        verifyparms } ]

                  [-P ]

                  [-r { copy
                       r2d } ]

                  [-s source_db_name ]
                  [-S target_db_name ]
                  [-t source_table_name ]
                  [-T target_table_name ]
                  [-v ]
                  [-x ]

```

# Option Categories

Table 11 shows the **datapipe\_manager** options that apply for the various modes of the **-p** option.

**Table 11** datapipe\_manager Option Categories

alter	create		delete	remove	verifyparms
	TEEL File	Template			
<b>-a</b>	<b>-a</b>	<b>-t</b>	<b>-S</b>	<b>-a</b>	<b>-a</b>
<b>-T</b>	<b>-c</b>	<b>-T</b>	<b>-b</b>	<b>-b</b>	
<b>-C</b>	<b>-n</b>	<b>-c</b>	<b>-T</b>	<b>-n</b>	
<b>-d</b>	<b>-S</b>	<b>-s</b>	<b>-x</b>	<b>-x</b>	
	<b>-r</b>	<b>-S</b>	<b>-d</b>	<b>-d</b>	
	<b>-P</b>	<b>-r</b>			
	<b>-e</b>	<b>-L</b>			
	<b>-d</b>	<b>-n</b>			
		<b>-P</b>			
		<b>-e</b>			
		<b>-d</b>			

## Options

The **datapipe\_manager** utility has the following options.

- a Specifies the TEEL file *name* in **create** mode, or the datapipe *name* in **remove** mode. The TEEL file must have the **.teel** extension. OVPI looks for the file in the current directory; otherwise, the file name must be fully qualified.  
You can use this option for **create**, **remove**, or **verifyparms** modes.
- b Indicates that **datapipe\_manager** will not automatically remove a property table when the last data table that references it is removed. This option overrides the default, which is to automatically remove the property table.
- c Sets the compatibility mode. The values are **as-is**, **on**, and **off**.  
The value **as-is** specifies that the table will be the same as the input. For template-based creation, the system uses an exact copy of the input table's columns. For TEEL-based creation, the system creates only those columns specified in the TEEL file.  
The value **on** specifies that compatibility mode is on, which creates the table with the legacy header/footer columns. Note that if there are column names with well-known names for the header/footer columns in the TEEL file, the system ignores those columns in this mode.  
The value **off** specifies that compatibility mode is off, which creates the table with a minimal set of management columns.  
The default is **on** for TEEL-based creation.  
The default is **as-is** for template-based creation.  
This option is only valid in **create** mode.
- c Describes column information. This option is only valid in **alter** mode.  
*n* This parameter can be a non-negative integer that specifies the column that contains the data in the data table, an OID, or a macro prefixed with a # character. For a raw-SNMP table, a valid OID string is required. A raw-SNMP table cannot have two columns specified with the same OID.

<i>sqlname</i>	Name of the column used to generate the dictionary entries within the OVPI database. The size of the name depends on the naming convention specified in the database engine, and is a maximum of 30 characters. This is a positional parameter.
<i>type</i>	Specifies the type of data in the column. This is a positional parameter. For more information, refer to the <i>Performance Insight TEEL Reference Guide</i> .
<i>size</i>	Corresponding length for the type of data specified in the <i>type</i> parameter. Only the <b>char_string</b> , <b>snmp_char_string</b> , <b>hex_string</b> , <b>snmp_hex_string</b> , and <b>numeric</b> types require a size. The size for the <b>numeric</b> type is a precision value. This is a positional parameter.
<i>alias</i>	Additional name for the column that may define the contents more clearly. The size for the name may be a maximum of 255 characters. When specifying an <i>alias</i> , all missing parameters in this statement require placeholders. This is a positional parameter. For more information, refer to the <i>Performance Insight TEEL Reference Guide</i> .
<b>default</b>	Specifies the default <i>value</i> for the data in the column.
<b>null</b>	Specifies that the column can be NULL. The values are <b>yes</b> and <b>no</b> . The default is <b>yes</b> , which allows NULL. If the <b>default</b> option is specified, then <b>null=no</b> .
<b>foreign_key</b>	Identifies a unique attribute from a pre-existing property table to include as an element in the datapipe. Specify the name of the parent <i>table</i> that contains the data with <b>dsi_key_id</b> as the column name.
<b>desc</b>	Use this parameter to add a description for the column. When you add the description, enclose it in double (“) quotes, and omit any spaces around the equal sign. If you omit this parameter, the value will be NULL.

This option is in UPPERCASE.

- d** Set a debug output level. Values of **1**, **2**, or **3** are valid. The higher the number, the more detailed the information. The default is no debug output. Debug output writes to standard out. Only use this option for testing in coordination with Technical Support due to the additional overhead it places on **datapipe\_manager**.
- e** Indicates that **datapipe\_manager** will create the table without datapipe registry entries. This option overrides the default behavior, which is to create the table with datapipe registry entries.
- h** Displays help information. This option overrides all other options on the command line.
- L** Specifies the alias name for the new table when using template-based creation.  
This option is in UPPERCASE.
- n** For **create** mode, specifies the name of the OVPI collector for datapipe registration. By default, this is the local host.  
For **remove** mode, specifies the name of the installed datapipe. If the *hostname* parameter is missing, the local hostname is the name of the installed datapipe.  
This option is only valid in **create** or **remove** mode.

- p Specifies the execution mode. The values are **alter**, **create**, **delete**, **remove**, and **verifyparms**. Note that **register** is a legacy parameter that is equivalent to **create**.

**alter**

Modifies a registered table that already exists in the OVPI dictionary by adding a column to it. Both data and property tables can have columns appended.

Use the **-C** option to specify the column information. The **datapipe\_manager** utility verifies that the column does not already exist, and then invokes the appropriate command to update the tables in the OVPI dictionary. Use the **-T** option to enter the table name from the command line. This mode is only available from the command line.

If you attempt to add non-nullable columns, **datapipe\_manager** will add those columns as nullable columns instead; it will not add by-variable columns.

**Note:** After you alter a collectible table, you will need to run the **mw\_collect** command with the **-b** option once to make the change across dependent objects. The modification to the table will not have any effect on the collection until this command is run.

- create** Creates any type of table in OVPI as long as the OVPI database knows the type. There are two methods to create a data or property table, with a TEEL file or an input table name as a template. The input table can exist on either a local or remote database. There is only one method to create a view, and that is with a TEEL file. The TEEL file method validates the TEEL file by checking for any syntax errors as in `verifyparms` mode, generates any settings not specified in the file, and adds the table to the OVPI dictionary. This method requires the use of the `-a` option. The input template table method uses the command line to specify the source template table name with the `-t` option and the target table name with the `-T` option. It then validates that the target table does not already exist, generates the new target table definition from the source template table, and adds the table to the OVPI dictionary. Note that if the table already exists, **datapipe\_manager** goes into **alter** mode. For example, if the existing table has eight columns and you specify a ten-column table, **datapipe\_manager** will add two columns to the existing table.
- delete** Deletes both data and property tables. **datapipe\_manager** attempts to clean up the dictionary entries associated with the specified table before dropping it from the database. A foreign key relationship may prevent certain tables from being dropped and/or removed from the system. Enter this mode from the command line with the `-T` option to specify the table name. If the table named with the `-T` option is a property table, **datapipe\_manager** verifies that the property table does not have any data tables mapped to it before dropping it.
- remove** Suspends the distribution of a datapipe on a collection station, but does not actually remove the table from the database. Use either the **delete** mode from this option or the **Drop Table(s)** command from **Table Manager** to remove the table from the database. This mode requires the use of the `-a` option.



**verifyparms** Checks the syntax for all the statements in the TEEL file. This mode requires the use of the **-a** option. This is the default mode when the **-p** parameter is missing.

- P** When you use this option, **datapipe\_manager** will create the property table in **as-is** mode. This means that **datapipe\_manager** will create the table using only the property columns in the TEEL file or from the existing property table in template mode, and it will not generate any columns automatically such as `dsi_target_name`, `dsi_table_key`, and `dsi_descr`. It will verify that the following columns exist in the input set with their corresponding attributes and at least one object or collection by-variable:

Column Name	Data Type	NULL Attribute	Default
<code>dsi_key_id</code>	numeric(10)	not NULL	
<code>dsi_status</code>	tinyint	not NULL	<b>2</b>
<code>dsi_status_time</code>	unix_time	not NULL	current time
<code>dsi_bv_state</code>			

This option is in UPPERCASE.

- r** Specifies which database objects to generate for a raw table. The values are **copy** and **r2d**.
  - copy** Generates the required database objects for processing, which are the rate table, two upload tables, and the **copy** stored procedure. The **copy** procedure copies data from the upload table to the rate table and filters the data so that there is no duplicate data.
  - r2d** Generates the required database objects for raw-to-delta processing, which are the rate table, two upload tables, a last keys table, and the **raw-to-delta** stored procedure.
- s** Specifies the source database name. This database can exist on either a local or remote system. The default for the database name is the name of the database specified as default in the `systems.xml` file. This option is only valid in **create** mode.

- s** Specifies the target database name. This database can exist on either a local or remote system. By default, the database is on the local system, and the database name is the name of the database specified as default in the `systems.xml` file.  
This option is in UPPERCASE.
- t** Specifies the source SQL or alias table name. This table can exist on either a local or remote database.
- T** Specifies the target SQL or alias table name. By default, the target table name is the same as the source table name.  
This option is in UPPERCASE.
- v** Displays version information for **datapipe\_manager**. This option is not valid with any other options.  
Note that this option is in UPPERCASE.
- x** Indicates that the system will not remove the table if a dependent collection policy exists. This option overrides the default behavior, which is that the system automatically removes any dependent collection policies when it deletes a data table.

## Usage Notes

The `datapipe_manager` program is a utility that creates tables based on input from a TEEL file or a template. A *template* is an existing table. It also creates views based on input from a TEEL file only. Refer to the *Performance Insight TEEL Reference Guide* for more information about TEEL file statements.

The **alter** mode of the **-p** option is only available from the command line. You can add one column at a time to a data or property table. The **alter** mode does not modify existing columns.

If you need to add multiple columns to a data or property table, you can use a TEEL file that specifies multiple column definitions for the table, and then use the **create** mode of the **-p** option to add the missing columns to the table. **datapipe\_manager** compares the specified table to the definition and adds the missing columns to the table.

## Examples

### Example 1

To have **datapipe\_manager** create and register a datapipe from a TEEL file named **test.teel** in compatibility mode, use the following command:

```
datapipe_manager -a test.teel -p create
```

### Example 2

To have **datapipe\_manager** create and register a datapipe from a TEEL file named **test.teel** in non-compatibility mode, use the following command:

```
datapipe_manager -a test.teel -p create -c off
```

### Example 3

To have **datapipe\_manager** use as-is mode to create a new raw table named **newtable** with the same definition as an existing table named **oldtable** and then set it up for raw-to-delta processing, use the following command:

```
datapipe_manager -p create -t oldtable -T newtable -r r2d
```

### Example 4

To have **datapipe\_manager** modify an existing property table named **oldtable** by adding a new text column that is 10 characters long and named **newcol**, use the following command:

```
datapipe_manager -p alter -T oldtable -C ,newcol,char_string,10
```

## Error Messages

This section describes some of the messages that can occur from **datapipe\_manager**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.

- A suggestion about the action to do so that the message will not appear again.

## Command Line Option Errors

- If the following error message appears, the specified option requires double quotes to enclose its corresponding values.

Arguments for option *option* must be enclosed in double quotes.

Verify that there is a double quote after the option and before the first value and another double quote after the last value for the specified option.

- If the following error message appears, the specified option has an incorrect value.

Argument *value* is invalid for option *option*.

Verify that the value is valid and is in the appropriate format for the specified option.

- If the following error message appears, the specified option has an incorrect value.

Argument *value* is not defined for the option *option*.

Verify that the value is valid and is in the appropriate format for the specified option.

- If the following error message appears, the specified value is no longer valid for the specified option. The value may have been valid in a previous version of the software.

Argument *value* is obsolete for option *option*.

Verify the valid values available for the specified option in the current release of the software.

- If the following error message appears, the specified file does not exist.

File *file\_name* referenced by option *option* does not exist.

Verify that the specified file name has the correct path on the command line. Remember to check the spelling of each member of the path and the file name.

- ❑ If the following error message appears, the specified command requires the specified option.  
Missing required option *option* for command *command\_name*.  
Verify that the **xxx** option is on the command line.
- ❑ If the following error message appears, the specified option does not require a value for the specified command.  
Option *option* does not take an argument for command *command\_name*.  
Verify that the specified option does not have a value after it on the command line.
- ❑ If the following error message appears, the specified option is not valid for the specified command.  
Option *option* is not defined for command *command\_name*.  
Verify that the specified option is not on the command line for the specified command.
- ❑ If the following error message appears, the specified option is no longer available for the **xxx** command.  
Option *option* is obsolete.  
Verify that the specified option is not on the command line.
- ❑ If the following error message appears, the specified option is missing the corresponding value for the specified command.  
Option *option* requires an argument for command *command\_name*.  
Verify that the specified option has its corresponding value and is in the appropriate format on the command line.
- ❑ If the following error message appears, the specified option requires a valid value.  
Option *option* requires valid argument.  
Verify that the specified option has its corresponding value and is in the appropriate format on the command line.
- ❑ If the following error message appears, the specified options are mutually exclusive.  
The option *option1* cannot be used with option *option2*.  
Verify that only one of the specified options is on the command line.

- ❑ If the following error message appears, the system is unable to create the specified file from the specified option.

Unable to create file *file\_name* referenced by option *option*.

Verify that the specified file has write permission and the correct path for the file on the command line. Remember to check the spelling of each member of the path and the file name.

## Generic File I/O Errors

- ❑ If the following error message appears, the file does not have the appropriate permissions to access the file.

File does not have read access *file\_name*.

Verify the following:

- The spelling of the file name is correct.
- The file exists in the specified location. You may have to supply a fully qualified path name with the file name.
- The file has the proper permissions to access it.

- ❑ If the following error message appears, the file name specified on the command line does not exist.

File *file\_name* does not exist.

Verify that the specified file name has the correct path and it is in the appropriate location. Remember to check the spelling of each member of the path and the file name.

- ❑ If the following error message appears, the system cannot read the specified file.

I/O error in reading file *file\_name*.

Verify that the specified file has read access and that the user has permission to read it.

- ❑ If the following error message appears, the system cannot write to the specified file.

I/O error in writing to file *file\_name*.

Verify that the specified file has write access and that the user has permission to write to it.

- If the following error message appears, the specified file has invalid statements in it.

Incorrect syntax in file *file\_name*.

Verify that the specified file has correct format and that the statements have the correct format.

## Generic OVPI Errors

- If the following error message appears, the specified database is not available.

Failed to connect with: *database\_name*.

Verify the following:

- The spelling of the database name is correct, as specified in the `systems.xml` file with the **<Name>** tag.
- The database exists, and is running.
- The database allows connections.

- If the following error message appears, the specified environment variable, which is required, is not set.

Required Environment variable not set: *env\_variable\_name*.

Verify that the specified environment variable is set correctly.

Some of the environment variables that OVPI uses are the following:

**COLLECT\_HOME** - is the directory where the OVPI collector modules store their working files, which includes the cache files. The default is `DPIPE_HOME/collect`.

**DPIPE\_HOME** - is the directory where OVPI resides.

**DPIPE\_TMP** - is the directory that contains the temporary files for OVPI. The default is `DPIPE_HOME/tmp`.

**TREND\_LOG** - is the directory that contains the log files for OVPI. The default is `DPIPE_HOME/log`.

- If the following error message appears, the system could not process the specified XML file.

Failed parsing XML. Input=*xml\_file\_name*.

Verify that the name of the XML file is correct and that statements have the correct format.

- ❑ If the following error message appears, the same command string is currently running.

The previous instance is already running. The process will not be executed : *command\_string*.

Verify that the specified command string is correct. If it is, verify that the same process is not running and then rerun it.

## Generic Database Errors

- ❑ If the following error message appears, the specified table is not in the database.

SQL table "*table\_name*" does not exist.

Verify the spelling of the SQL name for the table is correct or that the table exists in the database. You can use **Table Manager** to view the existing list of tables.

- ❑ If the following error message appears, the specified table is not in the database.

Alias table "*table\_name*" does not exist.

Verify the spelling of the Alias name for the table is correct or that the table exists in the database. You can use **Table Manager** to view the existing list of tables.

## Generic Database Connection Errors

- ❑ If the following error message appears, the system could not connect to the specified database. The message should provide additional information.

The connection to the database "*database\_name*" could not be established : *reason*.

Verify that the database name is correct and that it exists. If you need to add another database, use the Web Access Server.

- ❑ If the following error message appears, the system could not connect to the default database specified in the *systems.xml* file.

The connection to the default database could not be established.

Verify that the default database entry in the *systems.xml* file is correct.



## db\_delete\_data

The **db\_delete\_data** command is used to age obsolete data out of the database on an HP OpenView Performance Insight (OVPI) system.

### Requirements and Restrictions

- If you omit the **-f**, **-s**, and **-t** options, all data tables are aged, which is the default.
- The **-f**, **-s**, and **-t** options are mutually exclusive.
- If you use the **-u** option, you must include the **-U** option on the command line at the same time.

## Syntax

The **db\_delete\_data** command uses the following syntax:

```

db_delete_data    [ -c 1 ]
                   [ -d debug_level ]
                   [ -f table_category ]
                   [ -h ]
                   [ -i aging_days ]
                   [ -m ta_period ]
                   [ -q day_of_week ]
                   [ -s sqlname ]
                   [ -t alias_name ]
                   [ -u update_statistics ]
                   [ -U day_of_week ]
                   [ -v ]

```

## Options

The **db\_delete\_data** command has the following options:

- c** Use this option to set the number of deletions allowed to run concurrently.  
The default is **1**; that is, **db\_delete\_data** processes each table one at a time. At this time, if the value for this option is greater than **1**, **db\_delete\_data** will still process the tables one at a time.
- d** Use this option to set the debug output level. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information. Debug output is written to standard output.  
The default is **0**, which means no debug output.

- f Use this option to delete data only in tables whose source is the value of this option. Valid values for *table\_category* appear in the **Category** list under **Data Tables** in the **Table Manager** display.  
This option is mutually exclusive with the **-s** and **-t** options.  
If you omit the **-f**, **-s**, and **-t** options, tables from all sources are aged, which is the default.
- h Use this option to display the command format help.
- i Use this option to override the default aging value in the database each time it appears on the command line for **db\_delete\_data**. The *aging\_days* parameter for this option is the number of days that OVPI retains the data in a table. The **db\_delete\_data** program deletes data that has been in the table for one day more than the number specified.  
The default is to use the aging value set for the table in the database. Use **Table Manager** to view the default aging value for the table. Refer to the *Performance Insight Administration Guide* for details.
- m Use this option to perform key ID-based deletions depending on the value of this option. The only value currently available for this option is **ta\_period**, which deletes data by using the time period only.  
The default is **ta\_period**.
- q Use this option to specify the day of the week to rebuild the index.  
Valid values are:
 

<b>Su</b>	Sunday
<b>Mo</b>	Monday
<b>Tu</b>	Tuesday
<b>We</b>	Wednesday
<b>Th</b>	Thursday
<b>Fr</b>	Friday
<b>Sa</b>	Saturday
<b>All</b>	Every day

 This option invokes the **indexmaint** utility before running **db\_delete\_data**.

**-s** Use this option to age data only in the table specified. Enter the name of the table as shown in the **SQL Name** column of the **Table Manager** display. Refer to the *Performance Insight Administration Guide* for details.

This option is mutually exclusive with the **-t** and **-f** options.

If you omit the **-f**, **-s**, and **-t** options, all data tables are aged, which is the default.

**-t** Use this option to age data only in the table specified. Enter the name of the table as shown in the **Alias Name** column of the **Table Manager** display. Refer to the *Performance Insight Administration Guide* for details.

This option is mutually exclusive with the **-f** and **-s** options.

If you omit the **-f**, **-s**, and **-t** options, all data tables are aged, which is the default.

**-u** Invokes the **indexmaint** utility to update the index statistics page. Valid values are:

- 1 Before running **db\_delete\_data**.
- 2 After running **db\_delete\_data**.
- 3 Before and after running **db\_delete\_data**.

On Oracle databases, the default is **2**.

On Sybase databases, the default is **3**.

If you use this option, you must also use the **-U** option to specify which day to run the update.

**-U** Use this option to specify the day of the week to update the database statistics page. Valid values are:

- Su** Sunday
- Mo** Monday
- Tu** Tuesday
- We** Wednesday
- Th** Thursday
- Fr** Friday
- Sa** Saturday
- All** Every day

If you specify this option, you must also specify the **-u** option.

The default is **All**.

**-v** Use this option to display the version stamp for **db\_delete\_data**.

## Usage Notes

The **db\_delete\_data** utility deletes data from a table when that data has been stored longer than the retention period specified for the table in the database. You can find the data retention period for various tables in the **Table Manager** display. Refer to the *Performance Insight Administration Guide* for details.

It executes automatically according to the schedule specified in the **trendtimer.sched** file. You can also execute **db\_delete\_data** at any time from the command line.

## Examples

The following examples illustrate some uses of the **db\_delete\_data** command.

### Example 1

The following command deletes data from each OVPI database table one at a time according to the aging criteria specified for each table in the database.

```
db_delete_data
```

### Example 2

The following command runs update statistics on Sunday after **db\_delete\_data** completes.

```
db_delete_data -u 2 -U Su
```

### Example 3

The following command ages the data in the mib-II-ifEntry table, deleting data according to the aging value set for this table in the database.

```
db_delete_data -t mib-II-ifEntry
```

### Example 4

The following command invokes the **indexmaint** utility every Wednesday to rebuild the indexes for the tables, and then deletes the data from each OVPI database table.

```
db_delete_data -q We
```

## Error Messages

This section describes some of the messages that can occur from **db\_delete\_data**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.

- If the following error message appears, there was an error with the corresponding **indexmaint** command.

`indexmaint utility program returned non-zero exit status.`

Refer to the error messages associated with the corresponding **indexmaint** command.

- If the following error message appears, the specified program generated the specified error.

`Executing program program_name generated error: msg.`

Verify that the specified program has the appropriate information.

- If the following error message appears, the **-u** and **-U** options are not on the command line at the same time.

`Option -u must be used with option -U.`

Verify that the **-u** and **-U** options are on the command line at the same time.

- If the following error message appears, the specified SQL command generated an error in the middleware.

`Executing the SQL command "command" generated middleware error "msg".`

Refer to the following messages; otherwise, call Technical Support.

- If the following error message appears, there was a database I/O exception.

`db_delete_data: "msg".`

Refer to the message in quotes to determine the action to take.

- ❑ If the following error message appears, the system generated a database error.  
Received non-deadlock database error.  
Refer to the preceding messages to determine the actions to take.
- ❑ If the following error message appears, there was an error from the middleware while closing the database connection.  
Failure on closing database connection generated the middleware error "msg".  
Refer to the error messages associated with the corresponding middleware message.
- ❑ If the following error message appears, the specified table is missing the `ta_period` column.  
Column `ta_period` not found in table "`table_name`".  
Verify that the table name is correct and that it has a `ta_period` column.
- ❑ If the following error message appears, the name of the stored procedure is longer than 30 characters.  
Stored procedure "`proc_name`" is longer than 30 bytes.  
Verify that the name of the stored procedure is correct and that the length of the name is 30 characters or less.
- ❑ If the following error message appears, the stored procedure failed.  
One or more threads returned with failure.  
Refer to the preceding messages to determine the actions to take.
- ❑ If the following error message appears, the value for the specified option is incorrect.  
"`value`" is a bad argument for the option "`option`".  
Verify that the specified option has the correct value. See [Syntax on page 90](#) for the format of the option and [Options on page 90](#) for the details about the option.

- If the following error message appears, the value for the specified option is no longer supported.

The argument "*value*" of the option "*option*" is no longer supported.

Verify that the specified option has the current value. See [Syntax on page 90](#) for the format of the option and [Options on page 90](#) for the details about the option.

- If the following error message appears, the maximum number of threads exceeded the specified number.

Maximum number of threads can not exceed *number*.

Verify that the value for the **-c** option does not exceed the specified number.



# deploytool

The **deploytool** command is a stand-alone utility that allows you to deploy reports or a folder of reports to the Web Access Server so that you can view them from the Web Access Server on an HP OpenView Performance Insight (OVPI) system. You can also use this command to undeploy reports or a folder of reports from the Web Access Server, which removes them from view on the Web Access Server.

If you want to deploy or undeploy reports to the Web Access Server using the GUI tools, you can use the Deployment Wizard or the Web Access Server. Refer to the *Performance Insight Guide to Building and Viewing Reports* for more information.

## Requirements and Restrictions

- If you deploy or undeploy a report when your Web browser is open, you must click the **Refresh** button on the browser to see the result of the action.
- Either the **-d** option or the **-r** option is a required option on the command line; however, both of them cannot be on the command line at the same time.

## Syntax

The **deploytool** command uses the following syntax:

```
deploytool  -c { -deploy  
                -undeploy }  
              [ -d dir_path ]  
              [ -g group_name ]  
              -h hostname  
              [ -i rpt_desc ]  
              [ -l deploy_loc ]  
              [ -n rpt_display_name ]  
              -p port_num  
              -P password  
              [ -r rpt_name_path ]  
              -s  
              -t deploy_type  
              -U username
```

## Options

The **deploytool** command has the following options:

- c** This option specifies the task to perform.  
Valid values: **deploy**  
              **undeploy**  
This is a required option.

- d** This option specifies the directory that contains the reports to deploy or undeploy. When you use this option, the task applies to the contents of the directory. This means that when you deploy a directory, the system deploys the entire contents of the directory; or, when you undeploy a directory, the system undeploys the entire contents of the directory.

When you use this option, the **-r** option should not be on the same command line.
- g** This option specifies the name of the group of users to which you want to deploy the report.

For more information about how to create groups, see the **userimport** and **groupimport** utilities or refer to the *Performance Insight Administration Guide*.
- h** This option specifies the Web Access Server host name where you want to deploy or undeploy the report.

This is a required option.
- i** This option specifies the description for the report. Use double quotes to enclose the text for the description.

The description is optional; it appears in the **Description** field on the **Reports** page in the **Catalog** folder.
- l** This option specifies the deployment location that is relative to the **system** or **users** folder.

If you want to deploy reports to the top-level directory, use a forward slash (/) as the value for the deployment location.
- n** This option specifies the name for the report. Use double quotes to enclose the name if it contains spaces.

When you use the Web Access Server, this name appears as the report name in the list of deployed reports in the **Catalog** folder.
- p** This option specifies the port number for the Web Access Server specified with the **-h** option.

You must enter this option even though the default for this option is the port number supplied during the OVPI installation, which is port number **80**, in most cases.

This is a required option.

- P** This option specifies the corresponding password for the username that will access the Web Access Server.  
This option is in UPPERCASE.  
This is a required option.
- S** This option specifies that https will be used as the communications protocol. If this option is not specified, http is used.
- r** This option specifies the name of a single report you want to deploy or undeploy.  
In deploy mode, this value can contain the absolute or relative path that is the current location of the report. If this value does not include a path, then the report is in the current working directory.  
In undeploy mode, this value must be the name of the report only; this value should not include the path name. The system uses the path name specified in the **-l** option.  
When you use this option, the **-d** option should not be on the same command line.
- t** This option specifies the folder where the deployed reports will be.  
Valid values: **user**  
**system**  
**group**  
All users can view the reports in the system folder.  
The user folder will only show those reports and folders that the user can access. An administrative user can view all user reports.  
This is a required option.
- U** This option specifies the username of the user that will access the Web Access Server. The deployed reports will appear in the folder for this user name.  
This option is in UPPERCASE.  
This is a required option.

## Usage Notes

To view a report, you must first publish it by deploying it to a server for viewing. You can use this tool to deploy reports to the Web Access Server. There are two main folders that contain the deployed reports on the Web Access Server; they are the **System** and **Users** folders in the **Catalog**.

You must have Administrator privileges to deploy reports to the **System** folder; however, any user can deploy reports to their folder in the **Users** folder. For more information about deploying reports to the **System** folder, refer to the *Performance Insight Administration Guide*.

When you want to remove a report from the Web Access Server so that you can no longer view it, you undeploy it. You can use this tool to undeploy reports from the Web Access Server. You must have Administrator privileges to undeploy reports from the **System** folder and to undeploy Report Packs.

## Using the deploytool Command

This section shows some formats of the **deploytool** command.

- If you enter the **deploytool** command without any options, the system will display an error message followed by the help information.

### Deploy Reports

- To deploy a single report, enter the following command:

```
deploytool -U username -P password -h host_name -p port_num
-c deploy -r rpt_name -t deploy_type -l deploy_loc -i "rpt_desc"
-n "rpt_display_name"
```

where: *username* is the user that will access the Web Access Server.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*rpt\_name* is the name of the report with the absolute or relative path.

*deploy\_type* is the deployment type.

*deploy\_loc* is the deployment location.

*rpt\_desc* is the description of the report.

*rpt\_display\_name*  
is the name of the report that appears in the catalog.

- To deploy multiple reports in the same directory, enter the following command:

```
deploytool -U username -P password -h host_name -p port_num  
-c deploy -t deploy_type -l deploy_loc -d dir_path
```

where: *username* is the user that will access the Web Access Server.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*deploy\_type* is the deployment type.

*deploy\_loc* is the deployment location.

*dir\_path* is the directory that contains the reports.

If your configuration has two Web Access Server systems, you would first install the report packs on the Central Server using Package Manager and deploy the reports to one of your Web Access Server systems. You would then execute the **deploytool** command on the Central Server to deploy reports to your second Web Access Server.

The following example shows how the `trendadm` user deploys the entire directory of reports from the OVPI installation directory (C:\OVPI on a Windows system) to the `system` folder on the second Web Access Server system called `northeast`:

```
deploytool -U trendadm -P trendadm -h northeast -p 80  
-c deploy -l / -d .\reports
```

## Undeploy Reports

- To undeploy a single report, enter the following command:

```
deploytool -U username -P password -h host_name -p port_num  
-c undeploy -r rpt_name -t deploy_type -l deploy_loc
```

where: *username* is the user that has permission to undeploy the report.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*rpt\_name* is the name of the report with the absolute or relative path.

*deploy\_type* is the deployment type.

*deploy\_loc* is the deployment location.

- To undeploy an entire directory, which removes the directory and its contents, enter the following command:

```
deploytool -U username -P password -h host_name -p port_num  
-c undeploy -t deploy_type -d dir_path -l deploy_loc
```

where: *username* is the user that has permission to undeploy the reports.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*deploy\_type* is the deployment type.

*dir\_path* is the directory that contains the reports.

*deploy\_loc* is the deployment location.

## Examples

The following examples illustrate some uses of the **deploytool** command that an Administrator, such as the **trendadm** user, can enter.

### Example 1: Deploy a Report to the Web Access Server (UNIX)

To deploy a report with the name **execsum.rep** from the current working directory on the **cartman** host to the **testreports/Lan** directory in the **system** folder and then display it with a name of **Executive Summary** and a description, you can use the following command.

```
deploytool -h cartman -p 80 -U trendadm -P trendadm -c deploy  
-r execsum.rep -t system -l testreports/Lan/ -i "This report  
gives an overview of your lan." -n "Executive Summary"
```

### Example 2: Undeploy a Report from the Web Access Server (UNIX)

To undeploy a report with the name **execsum.rep** from the **testreports/Lan** directory in the **system** folder on the **cartman** host, you can use the following command.

```
deploytool -h cartman -p 80 -U trendadm -P trendadm -c undeploy
-r execsum.rep -t system -l testreports/Lan/
```

### Example 3: Deploy a Directory of Reports to a Different User

To deploy all the reports in the **d:\ovpi\reports\Interface\_Reporting\Admin** directory on the **powder2** host to the **user1\testreports** directory in the **user** folder, you can use the following command.

```
deploytool -h powder2 -p 80 -U user1 -P test1 -c deploy
-d d:\ovpi\reports\Interface_Reporting\Admin -t user
-l testreports
```

### Example 4: Deploy a Directory of Reports (UNIX)

To deploy all the reports in the **/user/reports/test** directory on the **cartman** host to the **trendadm/testreports** directory in the **user** folder, you can use the following command.

```
deploytool -h cartman -p 80 -U trendadm -P trendadm -c deploy
-d /user/reports/test -t user -l testreports
```

### Example 5: Undeploy a Directory of Reports

To undeploy all the reports in the **user/trendadm/testreports** directory on the **cartman** host, you can use the following command.

```
deploytool -h cartman -p 80 -U trendadm -P trendadm -c undeploy
-t user -d testreports -l /
```

## Error Messages

This section describes some of the messages that can occur from **deploytool**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.



- The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- If the following message appears, the user is unauthorized to deploy the specified directory.

Directory deployment failed: Unauthorized.

Verify the following:

- The user (**-U**) and password (**-P**) values are correct.
- The specified user has the appropriate privileges to deploy the directory.

- If the following message appears, the user is unauthorized to undeploy the specified directory.

Directory undeployment failed: Unauthorized.

Verify the following:

- The user (**-U**) and password (**-P**) values are correct.
- The specified user has the appropriate privileges to undeploy the directory.

- If the following error message appears, there is a command-line syntax error.

Error processing command line: A value is required for argument *option* : *description*.

Verify that every option on the command line has the appropriate value. The description specifies what information is missing.

- If the following error message appears, there is a command-line syntax error.

Error processing command line: *option* is not valid for this program.

Remove the invalid option from the command line. Check [Syntax on page 98](#) for the list of valid options.

- If the following error message appears, there is a command-line syntax error.

Error processing command line: Option *option* must be specified.

Verify that all required options are on the command line: **-c**, **-d** or **-r**, **-h**, **-p**, **-P**, **-t**, **-U**.

- ❑ If the following message appears, the type of task to perform is incorrect.  
Incorrect value for **-c** argument. Please specify "deploy" or "undeploy".  
Verify that the value for the **-c** option is **deploy** or **undeploy**.
- ❑ If the following message appears, the location for the deployed reports is incorrect.  
Invalid deployment type specified. Please specify "system" or "user".  
Verify that the value for the **-t** option is **system** or **user**.
- ❑ If the following message appears, the directory name is incorrect.  
Invalid directory specified: *directory\_name*.  
Verify that the directory name and path are correct for the **-d** option.
- ❑ If the following message appears, the report name is incorrect.  
Invalid report specified: *report\_name*.  
Verify that the name and the path of the report are correct for the **-r** option.
- ❑ If the following message appears, an input or output error occurred while reading the report or sending it to the Web Access Server.  
I/O error occurred.  
Verify that the file exists and that it is readable.
- ❑ If the following error message appears, there is a command-line syntax error.  
*option* option must be specified.  
Verify that required options for a specific task are on the command line, for example **-1** to deploy a report.
- ❑ If the following message appears, the user is unauthorized to deploy the specified report.  
Report deployment failed: Unauthorized.  
Verify the following:
  - The user (**-U**) and password (**-P**) values are correct.

- The specified user has the appropriate privileges to deploy the report.
- If the following message appears, the user is unauthorized to undeploy the specified report.

Report undeployment failed: Unauthorized.

Verify the following:

- The user (**-U**) and password (**-P**) values are correct.
- The specified user has the appropriate privileges to undeploy the report.
- If the following message appears, the report or directory name is missing on the command line.

Report or directory name must be specified.

Verify that the option for the report name (**-r**) or the directory name (**-d**) is on the command line. One of these options must appear on the command line.

- If the following message appears, there was an unusual error.

Unknown error occurred.

Verify that the values for all options are correct. Check the host name, especially if the following message also appears:

SEVERE: Unknown host. *host\_name*.



# dip\_manager

The **dip\_manager** command is a stand-alone utility that allows you to manage directed instance polling groups on an HP OpenView Performance Insight (OVPI) system. It allows you to import, replace, remove, or export directed instance polling groups.

## Requirements or Restrictions

- All required files must have the following statements in the file: **GroupCategory** before **GroupName**.
- An error occurs if more than one of the following options appears on the command line at the same time: **-import**, **-export**, **-export\_all**, **-remove**, **-remove\_all**, or **replace**.
- An error occurs if the **-file** option does not appear with one of the following options on the command line at the same time: **-export\_all**, **-import**, **-remove\_all**, or **replace**.

## Syntax

The **dip\_manager** command uses the following syntax:

```
dip_manager [ -database db_name ]
               [ -debug debug_level ]
               [ { -export grp_category.grp_name
                  -export_all
                  -import
                  -remove grp_category.grp_name
                  -remove_all
                  -replace
                } ]
               [ -file file_name ]
               [ -help ]
               [ { -v
                  -version
                } ]
```

## Options

The **dip\_manager** command has the following options:

**-database** This option identifies the database where the changes will occur. The database must appear in the list of available database servers. See the Web Access Server in the *Performance Insight Administration Guide* for more information about adding database servers to the list. The default is the database identified as the default in the database server list.

- debug** Use this option to set the debug output level. The higher the number, the more detailed the information. Debug output writes to standard output. Use this option only for testing in coordination with HP Technical Support due to the additional overhead it places on **dip\_manager**. The default is no debug output.
- export** Use this option to generate a file containing the directed instance polling group specified on the command line. The name of the group must be in the format of *grp\_category.grp\_name*; see [Naming Convention on page 113](#). Use the **-file** option to specify the output file name; otherwise, **dip\_manager** writes the data to standard output. See [Export on page 115](#) for more information.
- This option cannot appear on the command line when the **-export\_all**, **-import**, **-remove**, **-remove\_all**, or **-replace** option appears on the command line.
- export\_all** Use this option to generate a file containing all the directed instance polling group definitions. It requires the **-file** option to specify the output file name. See [Export on page 115](#) for more information.
- This option cannot appear on the command line when the **-export**, **-import**, **-remove**, **-remove\_all**, or **-replace** option appears on the command line.
- file** This option identifies the file name, which is the text file that contains the directed instance polling group definitions to import, export, remove, or replace. If the file is not in the current working directory, you must specify the fully qualified path to the file. See [ASCII File on page 116](#) for details on setting up this file.
- This is a required option when the **-import**, **-export\_all**, **-remove\_all**, or **-replace** option appears on the command line.
- help** This option is the help option, which displays the command-line options for the **dip\_manager** command.

- import** Use this option to import directed instance polling group definitions. It requires the **-file** option to identify the file that contains the list of directed instance polling groups to import. See [Import on page 114](#) for more information. This option cannot appear on the command line when the **-export**, **-export\_all**, **-remove**, **-remove\_all**, or **-replace** option appears on the command line.
- remove** Use this option to remove a directed instance polling group. You must specify the directed instance polling group on the command line following this option. The name of the group must be in the format of *grp\_category.grp\_name*; see [Naming Convention on page 113](#). See [Remove on page 115](#) for more information. This option cannot appear on the command line when the **-export**, **-export\_all**, **-import**, **-remove\_all**, or **-replace** option appears on the command line.
- remove\_all** Use this option to remove multiple directed instance polling groups. It requires the **-file** option to identify the file that contains the list of directed instance polling groups to remove. See [Remove on page 115](#) for more information. This option cannot appear on the command line when the **-export**, **-export\_all**, **-import**, **-remove**, or **-replace** option appears on the command line.
- replace** Use this option to replace the contents of specified directed instance polling groups. It requires the **-file** option to identify the ASCII file that contains the replacement directed instance polling groups. See [Replace on page 115](#) for more information. This option cannot appear on the command line when the **-export**, **-export\_all**, **-import**, **-remove**, or **-remove\_all** option appears on the command line.
- v**  
**-version** Use this option to display the current version of the **dip\_manager** utility. You can use either an uppercase **-V** or the lowercase, spelled-out form **-version**.



## Naming Convention

If you want to use the command line to specify a group to be removed or exported, use the following format to identify the group:

*grp\_category.grp\_name*.

The *grp\_name* portion of this parameter is the name of the group that contains the list of nodes or instances to poll. It appears in the Select Group to Poll From pull-down list in **Polling Policy Manager**. It also appears in the Select Group field in the Edit Polling Groups window for a specific category.

The *grp\_category* portion of this parameter identifies the kind of group for the corresponding *grp\_name*. If the group is a **type** list, then the *grp\_category* is **type**. Similarly, if the group is a **view** list, then the *grp\_category* is **view**. If the group is a single node group, then the *grp\_category* is **node**. Otherwise, the *grp\_category* is the same as the property table name.

The following table shows the typical association for the *grp\_category* value to the corresponding kind of group in the Collect Data From field in **Polling Policy Manager**.

**Table 12 Typical Values for the Group Category Parameter**

Group Category Value	Value in Collect Data From Field
<b>type</b>	All Nodes of the Same Type A Combination of Type and View
<b>view</b>	All Nodes in Same View
<b>node</b>	A Single Node
<i>property_table_name</i>	Specific Instances Custom Groups

Refer to the *Performance Insight Administration Guide* for more information about **Polling Policy Manager**.

## Usage Notes

The **dip\_manager** utility applies only to enumerated list groups. If you have a rule-based group, you can convert it to an enumerated list group and then use it with **dip\_manager**. To convert the group, use the Edit a Specific Instance Group window from **Polling Policy Manager** to select specific instances; make sure to click the **Save Selected Instances Only** box, and then click **OK**.

You can view the contents of the groups that you import or replace from **Polling Policy Manager**; refer to the “Managing Polling Groups” section in the *Performance Insight Administration Guide* for the instructions.

Every group belongs to a group category. If the referenced group is not a **type** or **view**, then the category will be the name of the property table that contains the objects defined in the group.

The rest of this section describes the available modes, the parameters for the associated ASCII file, and how to use the **dip\_manager** command.

## Modes of Operation

The **dip\_manager** command has four modes of operation: import, replace, export, and remove. All modes apply only to directed instance polling groups that are enumerated type groups. If you use a rule-based group, **dip\_manager** displays an error message.

### Import

The *import* mode enables you to add directed instance polling groups to the system. You must use the **-file** option to specify the name of the file that contains the group definitions to be imported. See [ASCII File on page 116](#) for more information about the file. If a group in the file already exists, **dip\_manager** adds the entries from the file to the existing group.

## Replace

The *replace* mode enables you to replace the members of existing directed instance polling groups. You must use the **-file** option to specify the name of the file that contains the existing groups with their new group member objects. See [ASCII File on page 116](#) for more information about the file.

In this mode, **dip\_manager** deletes the member objects from the specified group and then adds the objects from the corresponding file for that group. If the *grp\_category* parameter does not exist, **dip\_manager** will display an error message. If the *grp\_name* parameter does not exist, **dip\_manager** will create the group.

## Export

The *export* mode enables you to create a file containing directed instance polling group definitions from enumerated type groups. There are two ways to export directed instance polling group definitions:

- Create an export file containing just one directed instance polling group definition by entering the **-export** option followed by the group identifier on the command line. The group identifier must be in the format of *grp\_category.grp\_name*; see [Naming Convention on page 113](#) for an explanation of the group identifier.
- Create an export file containing all the directed instance polling groups from enumerated type groups on the system by entering the **-export\_all** option on the command line. You must also use the **-file** option and specify the output file name on the command line. Only the enumerated type groups appear in the file.

## Remove

The *remove* mode enables you to remove directed instance polling groups from the system that are enumerated type lists. There are two ways to remove directed instance polling group definitions:

- Remove groups one at a time by entering the **-remove** option followed by the group identifier on the command line. The group identifier must be in the format of *grp\_category.grp\_name*; see [Naming Convention on page 113](#) for an explanation of the group identifier.

- Remove multiple groups by using the **-remove\_all** option. You must include the **-file** option. With this option, **dip\_manager** uses only the *grp\_category* and *grp\_name* attributes in the associated file. See [ASCII File on page 116](#) for more information about the file.

## ASCII File

The ASCII file that contains the directed instance polling groups must be in the following format:

```
GroupCategory = grp_category  
GroupName = grp_name  
Object = object_by-variable1, object_by-variable 2, ...
```

The descriptions for the parameters in the ASCII file follow:

<i>grp_category</i>	This parameter specifies the directed instance polling group category. The values may be <b>type</b> , <b>view</b> , or the property table name. It is a required parameter for all input files.
<i>grp_name</i>	This parameter specifies the directed instance polling group name. The length of the <i>grp_name</i> can be up to 30 characters. This group must be an enumerated type group. It is a required parameter for all input files.

*object\_by-variable* This parameter specifies the contents of the directed instance polling group by identifying each object. It corresponds to the object by-variables associated with the property table. If the property table has three object by-variables, then each **Object** entry must have three values separated by commas. If the statement does not contain the proper number of object by-variables, **dip\_manager** displays an error message and skips the statement.

Many tables use the two default object by-variables, which are **dsi\_target\_name** and **dsi\_table\_key**.

For example, if the group consists of routers, each object is a router, and the object by-variables identify each router.

It is a required parameter when you use the **-import** or **-replace** option.

The following syntax rules apply to the file:

- The spelling of the statements GroupCategory, GroupName, and Object, must match exactly; they are case sensitive.
- There may be multiple group definitions in the file.
- The GroupCategory statement must appear before the GroupName statement in the file for each group.
- There may be multiple Object statements for each GroupCategory / GroupName pair.
- The number of object by-variables must match the number of by-variables for the corresponding property table.
- Commas separate the by-variables on the Object statement.
- The statements may contain spaces.
- The file may contain blank lines.



If any of the statements in the file contain syntax errors, an error message occurs and the process terminates at that point. The system does not check the rest of the file for additional errors.

If valid GroupCategory and GroupName statements appear in the file, **dip\_manager** will import or replace the group even if the corresponding Object statements are not valid. The group will not have any entries.

If there are invalid Object statements in the file for remove mode, **dip\_manager** ignores them and removes the groups; it will only stop processing if there is a syntax error.

## Using the dip\_manager Command

This section shows some formats of the command for the various modes.

- If you enter the **dip\_manager** command without any options, the system will display an error message followed by the help information.
- To display the syntax and options for this command, enter:

```
dip_manager -help
```

- To display the version information for this command, enter one of the following commands:

```
dip_manager -V
```

or

```
dip_manager -version
```

- To import directed instance polling group definitions, enter the following command:

```
dip_manager -import -file file_name
```

where: *file\_name* is the name of the ASCII file that contains the list of directed instance polling group definitions to import.

- To replace one or more directed instance polling group definitions, enter the following command:

```
dip_manager -replace -file file_name
```

where: *file\_name* is the name of the ASCII file that identifies the directed instance polling group definitions to change or add.

- To remove multiple directed instance polling group definitions, enter the following command:

```
dip_manager -remove_all -file file_name
```

where: *file\_name* is the name of the ASCII file that identifies the directed instance polling group definitions to remove.

- To remove a single directed instance polling group from the system, enter the following command:

```
dip_manager -remove grp_category.grp_name
```

where: *grp\_category* is the kind of group for the corresponding *grp\_name*.

*grp\_name* is the name of the group that contains the list of instances to poll.

- To export a single directed instance polling group definition to the screen, enter the following command:

```
dip_manager -export grp_category.grp_name
```

where: *grp\_category* is the kind of group for the corresponding *grp\_name*.

*grp\_name* is the name of the group that contains the list of instances to poll.

- To export a single directed instance polling group definition to a file, enter the following command:

```
dip_manager -export grp_category.grp_name -file file_name
```

*grp\_category*

is the kind of group for the corresponding *grp\_name*.

*grp\_name* is the name of the group that contains the list of instances to poll.

*file\_name* is the name of the ASCII file that will contain directed instance polling group definition.

- To export all directed instance polling group definitions to a file, enter the following command:

```
dip_manager -export_all -file file_name
```

where: *file\_name* is the name of the ASCII file that will contain the directed instance polling group definition.

## Examples

This section has examples that show each mode of **dip\_manager**. They have the following characteristics:

- All examples refer to the sample file used in the import example.
- Any information that appears about the **-file** option for one example also applies to other examples, such as the need for a qualified path.

### Import Example

To import a list of directed instance polling groups from a file named **dip\_grp\_in.txt**, enter the following command:

```
dip_manager -import -file dip_grp_in.txt
```

The following is an example of the contents for the input file, **dip\_grp\_in.txt**:

```
GroupCategory = test_prop_tbl
GroupName = test_dip_group_a
Object = test_node_1,abc
Object = test_node_2,xyz
Object = tst_a,20
Object = tst_b,25
```

```
GroupCategory = test_prop_tbl
GroupName = test_dip_group_b
Object = test_node_3,def
Object = test_node_4,ghi
Object = tst_c,20
Object = tst_d,25
```

You can see the results from this command by using the **Polling Groups** option from **Polling Policy Manager**; from the Edit Polling Groups window, do the following:

- Select **Specific Instances** from the Select Kind of Group field.
- Select the desired group name from the Select Group field.
- Click the **Edit** button. The Edit a Specific Instance Group window shows the group name, property table name, and the list of instances.



## Replace Example

To change the contents of existing directed instance polling groups, use the following command:

```
dip_manager -replace -file dip_grp_rep.txt
```

The following is an example of the contents for the input file, `dip_grp_rep.txt`:

```
GroupCategory = test_prop_tbl
GroupName = test_dip_group_c
Object = test_node_5,abc
Object = test_node_6,def
```

```
GroupCategory = test_prop_tbl
GroupName = test_dip_group_b
Object = test_node_7,abc
Object = test_node_8,xyz
```

In this example, **dip\_manager** will delete the current contents of **test\_dip\_group\_b** and replace it with the contents from this file; then it will add the group **test\_dip\_group\_c**, since it did not already exist.

## Export Examples

If you want to export the contents of a single directed instance polling group, such as **test\_dip\_group\_b**, to a file named `dip1.txt`, enter the following command:

```
dip_manager -export test_prop_tbl.test_dip_group_b  
-file dip1.txt
```

If you want to export the contents of a single directed instance polling group, such as **test\_dip\_group\_b**, to the screen, enter the following command:

```
dip_manager -export test_prop_tbl.test_dip_group_b
```

## Export\_All Examples

To generate a file containing all the directed instance polling group definitions that are in the catalog, you can specify an ASCII file to store the definitions. For example, if you want to export the current list of directed instance polling groups to a file called `dip_grp_out.txt`, enter the following command:

```
dip_manager -export_all -file dip_grp_out.txt
```

If you do not specify a file, **dip\_manager** exports the directed instance polling group definitions to standard output. The directed instance polling group definitions appear on the screen when you enter the following command:

```
dip_manager -export_all
```

If you want to export the directed instance polling groups from a different server named **bear** to a file named `dip_grp_bear.txt`, enter the following command:

```
dip_manager -export_all -file dip_grp_bear.txt -database bear
```

## Remove Example

If you want to remove a single directed instance polling group such as **test\_dip\_group\_c**, enter the following command:

```
dip_manager -remove test_prop_tbl.test_dip_group_c
```

## Remove\_All Examples

If you want to remove multiple directed instance polling groups, you can use an ASCII file to specify the list. To remove the directed instance polling groups in the file `dip_grp_rem.txt`, enter the following:

```
dip_manager -remove_all -file dip_grp_rem.txt
```

Note that you need to fully qualify the path for the file if it is in a different directory. For example, if the file were in the **lists** directory from the **D** drive on a Windows machine, you would enter the following command:

```
dip_manager -remove_all -file d:\lists\dip_grp_rem.txt
```

## Error Messages

This section describes some of the messages that can occur from **dip\_manager**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.

- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.
- If the following error message appears, there is a command-line syntax error. This means that a required mode option is missing.

A mode of operation is required.  
Exiting program with code 1.

Verify that the command has only one of the following options on the command line at the same time: **-import**, **-export**, **-export\_all**, **-remove**, **-remove\_all**, or **replace**.

- If the following error message appears, the database specified with the **-database** option on the command line does not exist.

Connection URL not found.  
Exiting program with code 3.

Verify the spelling of the database name. If the spelling is correct, you can add the database using the Web Access Server.

- If the following message appears, the value for the **-debug** option on the command line is not a numeric character.

Debug level must be a number.  
Exiting program with code 1.

Verify that the value for the **-debug** option on the command line is an integer number and that it does not contain a letter or other characters such as a dot.

- If the following message appears, the value for the **-debug** option on the command line is not valid.

Debug level must be between 0 and 3.  
Exiting program with code 1.

Verify that the value for the **-debug** option on the command line is an integer number and is one of the following numbers: 0, 1, 2, or 3.

- If the following error message appears, the file name specified on the command line in the **-file** *file\_name* option does not exist.

File *file\_name* does not exist.  
Exiting program with code 2.

Verify the spelling of the file name or that the file exists in the specified location. You may have to supply a fully qualified path name with the file name.

- If the following message appears, the *grp\_name* parameter on the command line with the **-remove** option is not an enumerated list. It could be a rule-based group.

Group *grp\_name* must be an enumerated list.

If the group is a rule-based group, you can convert it to an enumerated list. See [Usage Notes on page 114](#).

- If the following message appears, the *grp\_name* parameter on the command line with the **-export** option does not exist or is not an enumerated list.

Group *grp\_name* not found or not an enumerated instance group.  
Exiting program with code 7.

Verify the spelling of the group name or that the group exists for the corresponding *grp\_category*. If the group exists, it may be a rule-based group; if it is, you can convert it to an enumerated list. See [Usage Notes on page 114](#).

- If the following message appears, the entry for the **-export** or **-remove** option did not have the format *grp\_category.grp\_name* specified on the command line.

Group name must be specified category.group.  
Exiting program with code 1.

Verify the entry is in the format *grp\_category.grp\_name* and resubmit.

- If the following message appears, the `GroupCategory` statement on the specified line is missing in the associated file.

Missing category name - line *nl*.  
Exiting program with code 4.

Verify the `GroupCategory` statement is in the associated file. It must appear before the `GroupName` statement in the file for each group.

- If the following error message appears, the **-file** option is missing on the command line for an option that requires a file.

No file specified.  
Exiting program with code 1.

Verify that the **-file** option is on the command line with one of the following options at the same time: **-import**, **export\_all**, **-remove\_all**, or **replace**.

- If the following message appears, the number of entries on the specified line in the associated file does not match the number of object by-variables for the specified property table.

Object by-variable mismatch on line *n1* - *n2* expected.

Verify that each line in the associated file has the correct number of object by-variables on it separated by commas. If you need to verify the number of object by-variables for the property table, use **Table Manager** to view the columns in the property table. For more information about **Table Manager**, refer to the *Performance Insight Administration Guide*.

- If the following error message appears, there is a command-line syntax error. This means that there are multiple mode options on the same command line.

Only one mode of operation is allowed.  
Exiting program with code 1.

Verify that the command has only one of the following options on the command line at the same time: **-import**, **-export**, **-export\_all**, **-remove**, **-remove\_all**, or **replace**.

- If the following error message appears, there is a syntax error on the specified line in the file.

Syntax error - line *n*.  
Exiting program with code 4.

Verify the spelling of the statements in the file and that they have the correct format.

- If the following message appears, the specified *grp\_name* does not exist.

The group *grp\_name* does not exist.

The *grp\_name* may be in either of the following locations: with the **-remove** option on the command line or with the GroupName statement in the associated file. In some cases, the *grp\_category* name may be incorrect on the command line or in the GroupCategory statement in the associated file.

Verify the following items:

- The spelling of the *grp\_name* parameter is correct.
- The *grp\_name* exists for the type of group in the *grp\_category*.
- The spelling of the *grp\_category* parameter is correct and it has the appropriate designation.

You can use **Polling Policy Manager** to view the existing list of directed instance polling groups. From the Edit menu, select **Polling Groups**. The Edit Polling Groups window appears. The *grp\_category* corresponds to the Select Kind of Group field. The *grp\_name* corresponds to the Select Group field. You can also view the existing list of directed instance polling groups from the Edit Polling Policy window. See [Naming Convention on page 113](#) for more information.

- If the following message appears, the *grp\_category* portion of the GroupCategory statement in the associated file is not a valid category or property table name.

The group category *grp\_category* was not found.

Verify the spelling of the *grp\_category* name. If this name is a property table, verify the property table exists. For more information, refer to the *Performance Insight Administration Guide*.

- If the following error message appears, there is a value missing after the **-export** option.

Value after -export expected.  
Exiting program with code 1.

Enter a value after the **-export** command on the command line.

- If the following error message appears, there is a value missing after the **-remove** option.

Value after -remove expected.  
Exiting program with code 1.

Enter a value after the **-remove** command on the command line.

## ee\_collect

You can use the **ee\_collect** command to import data from a flat file into a datapipe on an HP OpenView Performance Insight (OVPI) system. It uses the instructions from a TEEL file associated with it to import the data. Refer to the *Performance Insight TEEL Reference Guide* for more information.

### Requirements and Restrictions

- The corresponding TEEL file must contain the import mapping and processing instructions.
- The TEEL file must contain the **DataPipe** statement, which specifies the registered datapipe.
- The TEEL file must contain the **TrendTableName** statement, the **PropertyTableName** statement, or both.
- The Single TEEL File (STF) mode requires the **-a** option.
- The Catalog-Based Collection (CBC) mode requires the **-i** option.
- The system ignores any of the following legacy options that appear on the command line: **-e**, **-p**, **-y**, **-z**, **-Z**.

# Syntax

A parameterless **ee\_collect** command displays the following command syntax.

## Format 1:

Format 1 executes by interval, which is Catalog-Based Collection Mode. In this format, **ee\_collect** obtains the instructions from the TEEL file identified in the associated polling policy.

```
ee_collect [-c max_process]  
            [-d debug_level ]  
            [-h ]  
            [-H alt_poller_name ]  
            -i interval  
            [-m { n }  
              { all } ]  
            [-mw option_list ]  
            [-n ]  
            [-N ]  
            [-v ]  
            [-w percentage ]
```



## Format 2:

Format 2 executes by TEEL file name for the datapipe, which is Single TEEL File Mode.

```

ee_collect  -a TEEL_file_name
               [-c max_process ]
               [-d debug_level ]
               [-h ]

               [-m { n
                       all } ]
               [-mw option_list ]
               [-N ]
               [-s source_data_file ]
               [-S source_directory ]
               [-u disposition[,target_directory,timestamp] ]
               [-v ]
               [-w percentage ]

```

## Options

The **ee\_collect** command has the following options:

- a**     Use this option to specify the name of the TEEL file that contains the instructions to process.  
This is a required option for Single TEEL File (STF) mode.

- c** Use this option to specify the maximum number of child-collection processes that **ee\_collect** spawns at the same time. When **ee\_collect** starts, it starts child processes that actually do the collection. It spawns a process for each specified file.

The valid values range from **1 - 25**.

The system default is **5**, which means that **ee\_collect** spawns up to 5 child-collection processes at the same time.
- d** Use this option to set the debug output level. The higher the number, the more detailed the information. Debug writes the output to standard output. Only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **ee\_collect**.

This option is for **ee\_collect** only; to turn on debugging for underlying processes, use the **-mw** option.

The valid values are **1, 2, or 3**.

The default is no debug output, which is **0**.
- h** This option is the help option, which displays the command-line syntax for the **ee\_collect** command. This option overrides all other options on the command line.
- H** Use this option to specify an alternate poller name. When you run **ee\_collect** in distributed mode, with the **-n** option, the poller compares the local hostname to the **Poll From** field in the polling policy. When you use the **-H** option, **ee\_collect** compares the **Poll From** field in the polling policy to the alternate poller name. See [Distributed Polling on page 277](#) for more information. You must include the **-n** option with this option on the command line to get the desired results.

This option is in UPPERCASE.

This option is available only in Catalog-Based Connection (CBC) mode.

- i** Use this option to specify the Collection ID that **ee\_collect** uses to execute entries in the polling policy, which have this value in their **Interval** field. Note that the configuration of **trendtimer** determines the frequency for running **ee\_collect**; however, for consistency, if a collection request has a collection ID of **5**, the system will run the command every 5 minutes.

This is a required option for Catalog-Based Connection (CBC) mode.
- m** Use this option to specify the maximum number of rows that **ee\_collect** will process for each file in the datapipe. This option overrides the **MaxRows** statement in the TEEL file.

The system default is **a11**.
- mw** Use this option to pass options to **mw\_collect**. Enclose the list of options in double quotes. Separate each option from the next option with a space.

The following **mw\_collect** options are invalid in this option:

**-a, -c, -f, -H, -i, -n, -t, -w**
- n** Use this option to enable distributed polling. If this option is used, **ee\_collect** only executes the collection request if the **Poll From** field in the polling policy for this collection request matches the hostname of the machine on which **ee\_collect** is running. If you omit this option, **ee\_collect** executes all polling requests whose interval matches the value of the **-i** option, regardless of the hostname specified to do the polling in the polling instructions.

This option is available only in Catalog-Based Connection (CBC) mode.
- N** Use this option to import data only for managed objects that already exist in the target database. When you use this option, **ee\_collect** will only import the managed objects that already exist in the associated property table, which are the existing keys.

This option is in UPPERCASE.
- s** Use this option to specify a single, source data file. This option overrides the **SourceFile** and/or **SourceDirectory** statements in the TEEL file. You must supply the complete path with the file name.

This option is available only in Single TEEL File (STF) mode.

- s** Use this option to specify the source data directory. This option overrides the **SourceFile** and/or **SourceDirectory** statements in the TEEL file. You must supply the complete path for the directory name. You can use wildcard characters with this option. The system processes all files in this specified directory.  
This option is available only in Single TEEL File (STF) mode.  
This option is in UPPERCASE.
- u** Use this option to specify the source file disposition. The values are **keep**, **copy**, **delete**, or **move**. The **copy** and **move** values require a path name for the directory location to store the source file; the filename remains the same. Note that there should not be a space after the comma (,) and before the directory path. This option overrides the **SourceDisposition** statement in the TEEL file.  
The system default is **keep**.  
This option is available only in Single TEEL File (STF) mode.
- v** Use this option to display the current version of the **ee\_collect** utility. This option overrides all other options on the command line, except the help option.  
This option is in UPPERCASE.
- w** Use this option to stop the collection of data when the database-used size reaches the specified percentage. The collection routine checks the dbstats tables to estimate the current state of the database-full size and determines if it should write to the database. The default is **90** for 90%.

## Usage Notes

If the table does not exist before **ee\_collect** tries to import the data, **ee\_collect** will create the table based on the instructions in the import TEEL file in non-compatibility mode, which has **-c off** on the **datapipe\_manager** command line.

## Interval Polling (CBC Mode)

When you invoke **ee\_collect** in the Catalog-Based Collection mode with the **-i** option, which is Format 1, it reads the polling control table in the database for the list of instructions whose intervals match the value of the **-i** option on the **ee\_collect** command line. Each entry in the list specifies which polled device group and datapipe to collect.

Use **Polling Policy Manager** to enter the polling policy information for the datapipe.

## Direct Polling (STF Mode)

When you invoke **ee\_collect** in the Single TEEL File mode with the **-a** option, which is Format 2, it imports the data for the datapipe specified in the TEEL file. The specified TEEL file is the value of the **-a** option, and it contains the instructions to import the data.

## Log File

The log entries from **ee\_collect** are in the file `$TREND_LOG/trend.log`.

## Using the ee\_collect Command

This section shows some formats of the command in the various modes. Note that some of the options override the corresponding statements in the associated TEEL file. Some of the options can be on the command line in either mode, so the formats with those options appear in each mode; you can combine those options in any combination that meets your needs.

- If you enter the **ee\_collect** command without any options, the system will display the help information.
- To display the syntax and options for this command, enter:  
**ee\_collect -h**
- To display the version information for this command, enter:  
**ee\_collect -v**

## STF Mode

- To specify a specific TEEL file, enter the following command:  
**ee\_collect -a *file\_name***  
 where: *file\_name* is the name of the TEEL file that contains the instructions to import the data into the datapipe.
- To copy the source files to another directory, enter the following command:  
**ee\_collect -a *file\_name* -u *directory\_name***  
 where: *file\_name* is the name of the TEEL file that contains the instructions to import the data into the datapipe.  
*directory\_name* is the location for the copies of the source files.
- To import the source files from a directory that is different than the directory or file specified in the TEEL file, enter the following command:  
**ee\_collect -a *file\_name* -S *directory\_name***  
 where: *file\_name* is the name of the TEEL file that contains the instructions to import the data into the datapipe.  
*directory\_name* is the name of the directory that contains the source files.
- To import a source file from a file that is different than the directory or file specified in the TEEL file, enter the following command:  
**ee\_collect -a *file\_name* -s *src\_file\_name***  
 where: *file\_name* is the name of the TEEL file that contains the instructions to import the data into the datapipe.  
*src\_file\_name* is the name of the source file to import with the complete path.
- To import data only for managed objects that already exist in the target database and process only some rows of data rather all the rows, enter the following command:  
**ee\_collect -a *file\_name* -N -m *number***  
 where: *file\_name* is the name of the TEEL file that contains the instructions to import the data into the datapipe.  
*number* is the number of rows to process.

## CBC Mode

- To specify an interval, enter the following command:

```
ee_collect -i interval
```

where: *interval* is the collection id that matches the interval in the polling policy.

- To enable distributed polling, enter the following command:

```
ee_collect -i interval -n
```

where: *interval* is the collection id that matches the interval in the polling policy.

- To import data from a specific poller, enter the following command:

```
ee_collect -i interval -n -H alt_poller_name
```

where: *interval* is the collection id that matches the interval in the polling policy.

*alt\_poller\_name* is the name of the poller in the **Poll From** field in the polling policy.

- To import data only for managed objects that already exist in the target database and process only some rows of data rather all the rows, enter the following command:

```
ee_collect -i interval -N -m number
```

where: *interval* is the collection id that matches the interval in the polling policy.

*number* is the number of rows to process.

## Examples

This section shows examples using the various modes of **ee\_collect**.

### Direct Polling of a Datapipe (STF Mode)

To have **ee\_collect** poll a node defined in a TEEL file named `test`, use the command:

```
ee_collect -a test
```

Note that **test.teel** is in the `$DPIPE_HOME/lib` directory.

## Interval Polling (CBC Mode)

### Example 1

To have **ee\_collect** execute all collection requests with a collection id of 10, which shows as a 10-minute interval in the polling policy, enter the following on the command line:

```
ee_collect -i 10
```

Note that the interval polling entries for **ee\_collect** are in the **trendtimer** schedule file `$DPIPE_HOME/lib/trendtimer.sched`. The system invokes **ee\_collect** according to that schedule.

### Example 2

To have **ee\_collect** execute all collection requests with a collection id of 10 for a particular hostname, which is the hostname where **ee\_collect** is running, enter the following on the command line:

```
ee_collect -i 10 -n
```

## Error Messages

This section describes some of the messages that can occur from **ee\_collect**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.



## General Errors

- ❑ If the following error message appears, the specified data table is not in the OVPI dictionary.

Data table "*table\_name*" not found in OVPI dictionary.

Verify that the data table exists in the OVPI dictionary. You can use **Table Manager** to view the current list of data tables in the system.

- ❑ If the following error message appears, **ee\_collect** was unable to convert the TEEL file for a property only import.

Failed to convert property only TEEL file "*file\_name*".

Note that ee\_collect converts TEEL files used for importing from the 4.6 version to the 5.0 version of TEEL. Refer to the messages that follow for additional information.

- ❑ If the following error message appears, **ee\_collect** was unable to convert the TEEL file for data import.

Failed to convert TEEL file "*file\_name*".

Note that ee\_collect converts TEEL files used for importing from the 4.6 version to the 5.0 version of TEEL. Refer to the messages that follow for additional information.

- ❑ If the following error message appears, the system failed to create the specified control file for **ee\_collect**. Typically, this message will appear with other messages that provide additional information.

Failed to create dpipe\_file control file : *file\_name*.

Refer to any messages that follow for additional information; otherwise, contact HP Technical Support.

- ❑ If the following error message appears, the system failed to create the specified **mw\_collect** configuration file. Typically, this message will appear with other messages that provide additional information.

Failed to create mw config file : *file\_name*.

Refer to any messages that follow for additional information; otherwise, contact HP Technical Support.

- ❑ If the following error message appears, the system failed to execute the **mw\_collect** command. Typically, this message will appear with other messages that provide additional information.

Failed to execute mw\_collect.

Verify that all variables are set and connections are in place.

- ❑ If the following error message appears, the corresponding **ee\_collect** command with the **-i** option failed. Typically, this message will appear with other messages that provide additional information.

Failed to get TEEL file from dictionary for datapipe : *datapipe\_name* and poll\_from : *server\_name*.

Verify the specified datapipe has a registration entry in the dictionary for the TEEL file on the specified server. The server name is from the *poll\_from* parameter in the corresponding collection policy. If the **-H** option is on the command line, then the server name is the alternate poller name specified with that option. Refer to any messages that follow for additional information.

- ❑ If the following error message appears, the corresponding **ee\_collect** command with the **-a** option failed. Typically, this message will appear with other messages that provide additional information.

Failed to perform TEEL base collection.

Verify that the file name is correct for the **-a** option and that all corresponding options with their appropriate values appear on the command line. Refer to any messages that follow for additional information.

- ❑ If the following error message appears, the system was unable to validate the rule file for a specific datapipe and host name.

Failed to validate rule file for a given datapipe and hostname.

Verify that the name of the rule file is correct, and that it is in the installed datapipe dictionary. Typically, this message will appear with other messages that provide additional information.

- ❑ If the following error message appears, there is no collection policy defined for this interval.

No collections defined for the interval : *value*.

Verify that a collection policy exists for the interval specified with the **-i** option, and that the table in the collection policy uses the *dsi\_ee* collector.

- ❑ If the following error message appears, the rule file, which is the TEEL file name specified in the **-a** option, is different than the rule file registered in the OVPI dictionary for a specific datapipe and host name.

Rule file mismatch for datapipe : *datapipe\_name* and host\_name : *host\_name*.

Verify the following:

- The TEEL file name specified in the **-a** option is correct for the specified datapipe and host name.
  - The corresponding rule file appears in the installed datapipe dictionary.
  - The specified datapipe does not have another TEEL (rule) file registered for it; if it does, use another TEEL file or datapipe name.
- If the following error message appears, the specification for the source directory name or source file name is missing either in the TEEL file or on the command line.

Source data files must be specified either in TEEL file or through command line option.

Verify that the SourceDirectory or the SourceFile statement is in the TEEL file, or that the **-s** or **-S** option is on the command line with the appropriate value.

## TEEL File Statement Errors

- If the following error message appears, the value for the CollectorModule statement is incorrect.

Collector module must be specified as "dsi\_ee" in TEEL file *file\_name*.

Verify that the value for the CollectorModule statement in the TEEL file is **dsi\_ee** when you use **ee\_collect** to import the data.

- If the following error message appears, the datapipe name in the collection policy is different than the datapipe name in the TEEL file.

DataPipe mismatch between TEEL file and collection policy : *datapipe\_name*.

Verify that the name of the datapipe is correct in the DataPipe statement in the TEEL file; otherwise, create a corresponding collection policy for the datapipe.

- If the following error message appears, the data table name in the collection policy is different than the data table name in the TEEL file.

Data table mismatch between TEEL file and collection policy :  
*table\_name* .

Verify that the name of the data table is correct in the TrendTableName statement in the TEEL file; otherwise, create a corresponding collection policy for the specified data table.

- If the following error message appears, the system failed to execute the PostProcessor statement in the TEEL file. Typically, this message will appear with other messages that provide additional information.

Failed to execute post-processor *post\_proc\_name* .

Verify that the command syntax for the PostProcessor statement in the TEEL file is correct, and that it includes all the parameters necessary to execute the command. Make sure that the command is the one you want to process after the system processes the TEEL file. Refer to any messages that follow for additional information.

- If the following error message appears, the system failed to execute the PreProcessor statement in the TEEL file. Typically, this message will appear with other messages that provide additional information.

Failed to execute pre-processor *pre\_proc\_name* .

Verify that the command syntax for the PreProcessor statement in the TEEL file is correct, and that it includes all the parameters necessary to execute the command. Make sure that the command is the one you want to process before the system processes the TEEL file. Refer to any messages that follow for additional information.

- If the following error message appears, there are new and legacy import statements in the TEEL file.

New and legacy import statements can not be used together.  
Replace legacy statements with new statements.

Verify that new and legacy import statements, such as ImportData and CoreColumn, do not appear in the TEEL file at the same time. The TEEL file should not contain any of the following statements:

CoreColumn.xxx statements

DataColumn statements with an offset

PropertyColumn statements with an offset

- If the following error message appears, the *pathname* specified in the SourceDirectory statement or the *filename* specified in the SourceFile statement in the TEEL file is incorrect.

Source file or directory *file\_name* not found.

Verify that the spelling of the file or directory name is correct, or that the file or directory name exists.

- If the following error message appears, a required statement is missing in the specified TEEL file.

Required directive *statement* is missing in TEEL file *file\_name*.

Verify that the following statements are in the TEEL file to import the data.

```
DataPipe
TrendTableName
PropertyTableName (for property table imports)
ImportData
```

## Command Line Option Errors

- If the following error message appears, the specified option requires double quotes to enclose its corresponding values.

Arguments for option *option* must be enclosed in double quotes.

Verify that there is a double quote after the option and before the first value and another double quote after the last value for the specified option.

- If the following error message appears, the specified option has an incorrect value.

Argument *value* is invalid for option *option*.

Verify that the value is valid and is in the appropriate format for the specified option.

- If the following error message appears, the command line has an option specified in the **-mw** option that **ee\_collect** already passes to **mw\_collect**.

Argument "*value*" is not allowed with "-mw" option.

Verify that the **-mw** option does not contain any of the following options to pass to **mw\_collect**.

```
-a, -c, -f, -H, -i, -n, -t, -w
```

- If the following error message appears, the specified option has an incorrect value.

Argument *value* is not defined for the option *option*.

Verify that the value is valid and is in the appropriate format for the specified option.

- ❑ If the following error message appears, the specified value is no longer valid for the specified option. The value may have been valid in a previous version of the software.

Argument *value* is obsolete for option *option*.

Verify the valid values available for the specified option in the current release of the software.

- ❑ If the following error message appears, the specified file does not exist.

File *file\_name* referenced by option *option* does not exist.

Verify that the specified file name has the correct path on the command line. Remember to check the spelling of each member of the path and the file name.

- ❑ If the following error message appears, the specified command requires the specified option.

Missing required option *option* for command *command\_name*.

Verify that the **xxx** option is on the command line.

- ❑ If the following error message appears, the specified option does not require a value for the specified command.

Option *option* does not take an argument for command *command\_name*.

Verify that the specified option does not have a value after it on the command line.

- ❑ If the following error message appears, the specified option is not valid for the specified command.

Option *option* is not defined for command *command\_name*.

Verify that the specified option is not on the command line for the specified command.

- ❑ If the following error message appears, the specified option is no longer available for the **xxx** command.

Option *option* is obsolete.

Verify that the specified option is not on the command line.

- ❑ If the following error message appears, the specified option is missing the corresponding value for the specified command.  
Option *option* requires an argument for command *command\_name*.  
Verify that the specified option has its corresponding value and is in the appropriate format on the command line.
- ❑ If the following error message appears, the specified option requires a valid value.  
Option *option* requires valid argument.  
Verify that the specified option has its corresponding value and is in the appropriate format on the command line.
- ❑ If the following error message appears, the specified options are mutually exclusive.  
The option *option1* can not be used with option *option2*.  
Verify that only one of the specified options is on the command line.
- ❑ If the following error message appears, the system is unable to create the specified file from the specified option.  
Unable to create file *file\_name* referenced by option *option*.  
Verify that the specified file has write permission and the correct path for the file on the command line. Remember to check the spelling of each member of the path and the file name.

## Generic File I/O Errors

- ❑ If the following error message appears, the file does not have the appropriate permissions to access the file.  
File does not have read access *file\_name*.  
Verify the following:
  - The spelling of the file name is correct.
  - The file exists in the specified location. You may have to supply a fully qualified path name with the file name.
  - The file has the proper permissions to access it.
- ❑ If the following error message appears, the file name specified on the command line does not exist.

File *file\_name* does not exist.

Verify that the specified file name has the correct path and it is in the appropriate location. Remember to check the spelling of each member of the path and the file name.

- ❑ If the following error message appears, the system cannot read the specified file.

I/O error in reading file *file\_name*.

Verify that the specified file has read access and that the user has permission to read it.

- ❑ If the following error message appears, the system cannot write to the specified file.

I/O error in writing to file *file\_name*.

Verify that the specified file has write access and that the user has permission to write to it.

- ❑ If the following error message appears, the specified file has invalid statements in it.

Incorrect syntax in file *file\_name*.

Verify that the specified file has correct format and that the statements have the correct format.

- ❑ If the following error message appears, **ee\_collect** was unable to locate the source files.

No source data file(s) found. ee\_collect Exiting.

Verify that the SourceDirectory (**-s**) or SourceFile (**-s**) statements have the correct path or file name specified in the TEEL file (or on the command line); otherwise, verify that the specified files exist in the specified location.

- ❑ If the following error message appears, **ee\_collect** was unable to locate the target directory name specified in the SourceDisposition statement in the TEEL file or the **-u** option on the command line.

Target archive directory "*directory\_name*" not found.

Verify that the SourceDisposition statement in the TEEL file or **-u** option on the command line have the correct path specified; otherwise, verify that the specified path exists.



# formdeploytool

The **formdeploytool** command is a stand-alone utility that allows you to deploy forms or a folder of forms to the OVPI Administration Server so that you can view them from the **Object Manager** on an HP OpenView Performance Insight (OVPI) system. You can also use this command to undeploy forms or a folder of forms from the OVPI Administration Server, which removes them from view on the **Object Manager**.

If you want to deploy or undeploy forms to the OVPI Administration Server using the GUI tools, you can use the Form Deployment Wizard or Package Manager. Refer to the *Performance Insight Guide to Building and Viewing Reports* or the *Performance Insight Administration Guide* for more information.

## Requirements and Restrictions

- If you deploy or undeploy a form when the management console is open, you must click the **Refresh** button and, in some cases, select the appropriate device to see the result of the action.
- Either the **-d** option or the **-r** option is a required option on the command line; however, both of them cannot be on the command line at the same time.

## Syntax

The **formdeploytool** command uses the following syntax:

```
formdeploytool  -c { -deploy  
                  -undeploy }  
                  [ -d dir_path ]  
                  -h hostname  
                  [ -i form_desc ]  
                  [ -l deploy_loc ]  
                  [ -n display_name ]  
                  -p port_num  
                  -P password  
                  [ -r form_name_path ]  
                  -U username
```

## Options

The **formdeploytool** command has the following options:

- c This option specifies the task to perform.  
Valid values: **deploy**  
**undeploy**  
This is a required option.

- d** This option specifies the directory that contains the forms to deploy or undeploy. When you use this option, the task applies to the contents of the directory. This means that when you deploy a directory, the system deploys the entire contents of the directory; or, when you undeploy a directory, the system undeploys the entire contents of the directory.

When you use this option, the **-r** option should not be on the same command line.
- h** This option specifies the host name where you want to deploy or undeploy the form.

This is a required option.
- i** This option specifies the description for the form. Use double quotes to enclose the text for the description.

The description is optional; it appears in the description field that shows when the list of tasks shows the Details view.
- l** This option specifies the deployment location that is relative to the Admin folder.

If you want to deploy forms to the top-level directory, use a forward slash (/) as the value for the deployment location.
- n** This option specifies the name for the form in deploy mode. Use double quotes to enclose the name if it contains spaces.

When you use the **Object Manager**, this name appears as the form name in the list of tasks.
- p** This option specifies the port number for the host name specified with the **-h** option.

You must enter this option even though the default for this option is the port number supplied during the OVPI installation, which is port number **80**, in most cases.

This is a required option.
- P** This option specifies the corresponding password for the username that has permission to deploy or undeploy the form.

This option is in UPPERCASE.

This is a required option.

- r** This option specifies the name of a single form you want to deploy or undeploy. Use the actual name as it appears in the directory.

In deploy mode, this value can contain the absolute or relative path that is the current location of the form. If this value does not include a path, then the form is in the current working directory.

In undeploy mode, this value must be the name of the form only; this value should not include the path name. In this case, the system uses the path name specified in the **-l** option.

When you use this option, the **-d** option should not be on the same command line.
- u** This option specifies the username of the user that has permission to deploy or undeploy the form.

This option is in UPPERCASE.

This is a required option.

## Usage Notes

To view a form, you must first publish it by deploying it to a server for viewing. You can use this tool to deploy forms to the OVPI Administration Server.

You must have Administrator privileges to deploy forms to the server. For more information about forms, refer to the *Performance Insight Guide to Building and Viewing Reports*.

When you want to remove a form from the **Object Manager** so that you can no longer view it, you undeploy it. You can use this tool to undeploy forms from the OVPI Administration Server. You must have Administrator privileges to undeploy forms from the server.

## Using the formdeploytool Command

This section shows some formats of the **formdeploytool** command.

If you enter the **formdeploytool** command without any options, the system will display an error message followed by the help information.

## Deploy Forms

- To deploy a single form, enter the following command.

```
formdeploytool -U username -P password -h host_name -p port_num
-c deploy -r form_name -l deploy_loc -i "form_desc" -n "display_name"
```

where: *username* is the user that has permission to deploy the form.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host where the action occurs.

*port\_num* is the port number of the host where the action occurs.

*form\_name* is the source name of the form with the absolute or relative path.

*deploy\_loc* is the target deployment location.

*form\_desc* is the description of the form.

*display\_name* is the name of the form that appears in the **Object Manager**.

- To deploy multiple forms in the same directory, enter the following command.

```
formdeploytool -U username -P password -h host_name -p port_num
-c deploy -l deploy_loc -d dir_path
```

where: *username* is the user that has permission to deploy the form.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host where the action occurs.

*port\_num* is the port number of the host where the action occurs.

*deploy\_loc* is the target deployment location.

*dir\_path* is the directory that contains the deployed forms.

## Undeploy Forms

- To undeploy a single form, enter the following command.

```
formdeploytool -U username -P password -h host_name -p port_num  
-c undeploy -r form_name -l deploy_loc
```

where: *username* is the user that has permission to undeploy the form.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host where the action occurs.

*port\_num* is the port number of the host where the action occurs.

*form\_name* is the actual name of the form in the deployed directory.

*deploy\_loc* is the source location that contains the deployed form.

- To undeploy an entire directory, which removes the directory and its contents, enter the following command:

```
formdeploytool -U username -P password -h host_name -p port_num  
-c undeploy -d dir_path
```

where: *username* is the user that has permission to undeploy the forms.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host where the action occurs.

*port\_num* is the port number of the host where the action occurs.

*dir\_path* is the directory that contains the deployed forms.

## Examples

The following examples illustrate some uses of the **formdeploytool** command that an Administrator, such as the **trendadm** user, can enter.

### Example 1: Deploy a Form to the Object Manager

To deploy a form with the name **update\_node.frep** from the current working directory on the **cartman** host to the **testforms/Lan** directory and then display it with a name of **Update Node** and a description, you can use the following command.

```
formdeploytool -h cartman -p 80 -U trendadm -P trendadm
-c deploy -r update_node.frep -l testforms/Lan/ -i "This form
allows you to update a node." -n "Update Node"
```

### Example 2: Undeploy a Form from the Web Access Server (UNIX)

To undeploy a form with the name **update\_node.frep** from the **testforms/Lan** directory on the **cartman** host, you can use the following command.

```
formdeploytool -h cartman -p 80 -U trendadm -P trendadm
-c undeploy -r update_node.frep -l testforms/Lan/
```

### Example 3: Deploy a Directory of Forms to a Different User

To deploy all the forms in the **d:\ovpi\forms\Interface\_Reporting\Admin** directory on the **powder2** host to the **user1\testforms** directory, you can use the following command.

```
formdeploytool -h powder2 -p 80 -U user1 -P test1 -c deploy
-d d:\ovpi\forms\Interface_Reporting\Admin -l testforms
```

### Example 4: Deploy a Directory of Forms (UNIX)

To deploy all the forms in the **/user/forms/test** directory on the **cartman** host to the **trendadm/testforms** directory, you can use the following command.

```
formdeploytool -h cartman -p 80 -U trendadm -P trendadm
-c deploy -d /user/forms/test -l testforms
```

### Example 5: Undeploy a Directory of Forms

To undeploy all the forms in the `user/trendadm/testforms` directory on the `cartman` host, you can use the following command.

```
formdeploytool -h cartman -p 80 -U trendadm -P trendadm  
-c undeploy -d testforms
```

## Error Messages

This section describes some of the messages that can occur from **formdeploytool**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.

- If the following message appears, the user is unauthorized to deploy the specified directory.

Directory deployment failed.

Verify the following:

- The user (**-U**) and password (**-P**) values are correct.
- The specified user has the appropriate privileges to deploy the directory.

- If the following message appears, the user is unauthorized to undeploy the specified directory.

Directory undeployment failed.

Verify the following:

- The user (**-U**) and password (**-P**) values are correct.
- The specified user has the appropriate privileges to undeploy the directory.



- ❑ If the following error message appears, there is a command-line syntax error.  
Error processing command line: A value is required for argument *option* : *description*.  
Verify that every option on the command line has the appropriate value. The description specifies what information is missing.
- ❑ If the following error message appears, there is a command-line syntax error.  
Error processing command line: *option* is not valid for this program.  
Remove the invalid option from the command line. Check [Syntax on page 146](#) for the list of valid options.
- ❑ If the following error message appears, there is a command-line syntax error.  
Error processing command line: Option *option* must be specified.  
Verify that all required options are on the command line: **-c**, **-d** or **-r**, **-h**, **-p**, **-P**, **-U**.
- ❑ If the following message appears, there is an error on the command line.  
Form deployment failed.  
Verify that the value for each option has the correct value, such as the values for the user (**-U**) and password (**-P**) options, or that the **-r** option has the appropriate type of file specified.
- ❑ If the following message appears, the form or directory name is missing on the command line.  
Form or directory name must be specified.  
Verify that the option for the form name (**-r**) or the directory name (**-d**) is on the command line. One of these options must appear on the command line.
- ❑ If the following message appears, there is an error on the command line.  
Form undeployment failed.  
Verify that the value for each option has the correct value, such as the value for the **-r** option is the actual name of the form as it appears in the directory and not the name specified for the **-n** option.

- ❑ If the following message appears, the type of task to perform is incorrect.  
Incorrect value for `-c` argument. Please specify "deploy" or "undeploy".  
Verify that the value for the `-c` option is **deploy** or **undeploy**.
- ❑ If the following message appears, the directory name is incorrect.  
Invalid directory specified: *directory\_name*.  
Verify that the directory name and path are correct for the `-d` option.
- ❑ If the following message appears, the form name is incorrect.  
Invalid form specified: *form\_name*.  
Verify that the name and the path of the form are correct for the `-r` option.
- ❑ If the following error message appears, there is a command-line syntax error.  
*option* option must be specified.  
Verify that required options for a specific task are on the command line, for example `-1` to deploy a form.
- ❑ If the following message appears, there was an incorrect host name.  
SEVERE: Unknown host. *host\_name*.  
Verify that the spelling of the host name is correct, and that it exists in the database.
- ❑ If the following message appears, the user is unauthorized to deploy or undeploy the specified form.  
Unauthorized.  
Verify the following:
  - The user (`-U`) and password (`-P`) values are correct.
  - The specified user has the appropriate privileges to deploy or undeploy the form.

# generate

You can use the **generate** command to generate the reports for a particular schedule on an HP OpenView Performance Insight (OVPI) system.

## Syntax

The **generate** command uses the following syntax:

```
generate [ -event uid_num ]  
          -host hostname  
          -log log_filename  
          -pass report_password  
          -port port_num  
          [ -schedule schedule_name ]  
          -user report_username
```

## Options

The **generate** command has the following options:

- event** Use this option to specify which report you want to run when it is from a schedule that includes multiple report entries. The value for this option must be the UID of the desired report. If you do not know the report's UID, see the discussion of the **-list** option in [schedule](#) on [page 334](#).
- host** Use this option to specify the name of the Web Access Server where the schedule resides to generate the reports. This is a required option.
- log** Use this option to specify the name of the log file with its full path. This file logs the schedule generation information when the system generates the reports. This is a required option.
- pass** Use this option to specify the corresponding password to the OVPI username required to access the Web Access Server. This is a required option.
- port** Use this option to specify the Web Access Server port where the schedule resides to generate the reports. The default value is **80**. This is a required option.
- schedule** Use this option to specify the name of the schedule you want to generate. If the schedule's name is longer than one word, enclose it in quotation marks, for example:  
**-schedule="Executive Summary"**.
- user** Use this option to specify the OVPI username required to access the Web Access Server. This is a required option.

## Usage Notes

You can use this command to generate reports on an as-needed basis. For example, if the scheduled reports did not run due to unexpected situations, such as a server was down, you could run the report from the Web Access Server or you could use the **generate** command to run the scheduled report from the command line.

When you execute the **generate** command, the system checks the schedule for reports that need to be run, based on their triggers. For more information about schedules and defining report triggers, see [schedule on page 331](#).

If you use the **-query** option with the **schedule** command, it is not necessary to use the **generate** command. The **-query** option causes the generator to automatically check the schedule to determine if any reports are due to be run. Similarly, if you schedule a report using the Web Access Server, you do not need to use the **generate** command.

### Using the generate Command

This section shows some formats of the **generate** command.

- If you enter the **generate** command without any options, the system will display the help information. Use the following format.

**generate**

- To generate a report, enter the following command:

```
generate -user username -pass password -host host_name
-port port_num -schedule sched_name -log log_name -event report_uid
```

where: *username* is the user name for the report.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*sched\_name* is the name of the schedule that will contain the added entry.

*log\_name* is the name of the log file with its full path.

*report\_uid* is the identification number of the event to run.

## Examples

The following examples illustrate some uses of the **generate** command.

### Example 1

To generate all the reports in the schedule named **system**, use the following command.

```
generate -user generation -pass generation -host rover -port 80
-schedule system -log /tmp/generate.log
```

The schedule generation information will be logged in the `generate.log` file, which has a path of `/tmp`.

### Example 2

To generate one report with the UID of `trendadm-1079052721695` in a schedule called **test\_sched\_1** that has multiple reports, use the following command.

```
generate -user trendadm -pass trendadm -host powder2 -port 80
-schedule test_sched_1 -log /tmp/test_gen_1.log
-event trendadm-1079052721695
```

Note that the schedule has three reports. You can use the **schedule** command with the **-list** option to locate the UID for the report to generate.

```
schedule -host powder2 -port 80 -user trendadm -pass trendadm
-schedule test_sched_1 -list
trendadm-1079052857539 | EventSummary.rep | Thresholds
trendadm-1079052818507 | RecentEvents.rep | Thresholds
trendadm-1079052721695 | System Performance | Admin
```

### Example 3

This example shows how one user can generate a schedule for another user. To generate a schedule called **schedule01** in the folder of **ncanfield**, use the following command.

```
generate -user generation -pass generation -host rover -port 80
-schedule ncanfield\schedule01 -log \tmp\generate.log
```

Note that you can do this only if the **-user** value has administrator permissions.

## groupctl

You can use the **groupctl** command to add, delete, or modify a single user group on an HP OpenView Performance Insight (OVPI) system. A *user group* is a collection or subset of user accounts that have access to the Web Access Server. You can use this command to perform the same function as the **groupimport** command ([page 171](#)), which is a bulk utility that performs the same actions as this utility except that it uses an XML formatted file for large numbers of user groups.

If you want to manage a user group from the Web Access Server with the GUI tools, refer to the *Performance Insight Administration Guide* for more information.

## Requirements and Restrictions

- You must be an administrative user to use this command.
- Each time you invoke this utility, you must enter the required options: **-group**, **-host**, **-mode**, **-port**, **-pwd**, and **-user**.
- Use the **-keepusers** option to keep existing users in the group, regardless of the type of change.

## Syntax

The **groupctl** command uses the following syntax:

```
groupctl [ -constraint column_name:operator:value ]  
          -group groupname  
          [ -help ]  
          -host hostname  
          [ -interactive ]  
          [ -keepusers ]  
          [ -member entry_name1 [ , entry_name2, ... , entry_nameN ] ]  
          -mode type  
          -port number  
          -pwd adm_pwd  
          -user adm_user  
          [ -verbose ]  
          [ -version ]
```



# Options

The **groupctl** command has the following options:

**-constraint** Use this option to specify the constraint, which is the filter for the user group, to add or remove. This constraint applies to every user in the group.

The format for the entry is *column\_name:operator:value*

where: *column\_name* is the name of the column to filter on in every query.

*operator* is the boolean operator to apply.

Valid operators are:

= equal  
 < less than  
 <= less than or equal  
 > greater than  
 >= greater than or equal  
 <> not equal

**like**

**not like**

**in**

**not in**

*value* is the value of the filter for the specified column. If the SQL type of the column is `CHAR` or `VARCHAR`, enclose the value in single quotes.

For example, if you want to only display the data for the records that have a customer id value of 10, use the following constraint.

**cust\_id::=10**

The **groupctl** command accepts multiple instances of this option. If there are multiple instances of this option, the system will join the filters together.

**-group** Use this option to specify the name of the user group to act upon.

This is a required option.

- help**            Use this option to display the syntax for the command.
- host**            Use this option to specify the Web Access Server hostname where the transaction occurs.  
This is a required option.
- interactive**   Use this option to display the login box. When you use this option, the system will display the login box if the entry for one or both of the **-user** or **-pwd** options is incorrect; otherwise, the system will display an error message.
- keepusers**     Use this option to keep the existing users in a user group when you add new users to the same group.  
By default, the system will remove existing users from a user group when you add new users to it.
- member**        Use this option to specify the username to add or remove from the user group. You can enter multiple members with a comma-separated list of usernames for this option. Do not use any spaces in the list.
- mode**            This option specifies the type of transaction to perform that affects the entire user group. For example, if you specify **delete** for this option, the system will remove the user group from the catalog. Valid entries are:

  - add**            Use this mode to add a new user group.
  - delete**        Use this mode to delete an entire user group.
  - modify**        Use this mode to modify an existing user group by adding members and filters.

This is a required option.
- port**            Use this option to specify the Web Access Server port number where the transaction occurs.  
You must enter this option even though the default for this option is the port number supplied during the OVPI installation, which is port number 80, in most cases.  
This is a required option.

- pwd** Use this option to specify the corresponding password for the username that has authorization to make the specified changes.  
This is a required option.
- user** Use this option to specify the username that has authorization to make the specified changes. This username must have administrative privileges.  
This is a required option.
- verbose** Use this option to turn on verbose messaging.
- version** Use this option to display the current version of **groupctl**.

## Usage Notes

The purpose of this command is to manage a single user group. You can control access to the Web Access Server by combining a set of user accounts that have a common interest into a user group. Note that a user group can contain other user groups.

For example, you can create a user group called *Thunderbolt* for all users in a company called Thunderbolt, Inc. This is useful if you are a service provider who wants to limit the data that certain companies can view.

In another case, you can create a group called *All*, which contains some user accounts and four groups called *North*, *East*, *South*, and *West*. The constraint placed on the users in the *North*, *East*, *South*, and *West* groups lets those users view only the data for their specific region. The users in the *All* group can view all the data that the users in the *North*, *East*, *South*, and *West* groups can view because the top-level group inherits the constraints of the groups below it in the hierarchy.

When you create groups, try to create effective constraints for the groups to limit the number of groups you might have in your system. For example, instead of using `interface` as a constraint and having 1000 or more groups for each interface, use `cust-id` as a constraint instead. A large number of groups can affect the efficiency and size of the query sent to the database.

## Modes of Operation

The **groupctl** command has three modes of operation: add, modify, and delete.

### Add

The *add* mode provides the ability to add a user or a filter to a user group that is on the Web Access Server.

### Modify

The *modify* mode provides the ability to change the members or the filter of the user group that is on the Web Access Server.

### Delete

The *delete* mode provides the ability to remove a user or a filter from a user group that is on the Web Access Server.

## Using the groupctl Command

This section shows some formats of the command for the various modes. There is a minimum of six required options for the **groupctl** command. Each mode will show the command with the required options along with the other options for the particular task; however, only the definitions for the new options will appear for each subsequent command. The definitions for the required options appear below.

- All **groupctl** commands must have all the following options for each task:

```
groupctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -group groupname -mode type
```

where: *host\_name* is the name of the host for the Web Access Server.  
*port\_num* is the port number for the Web Access Server.  
*adm\_user* is the administrative user name that has authorization to make the specified changes.

<i>adm_pwd</i>	is the corresponding password for the administrative user that has authorization to make the specified changes.
<i>groupname</i>	is the name of the user group to add, modify, or delete.
<i>type</i>	is the type of action to perform, such as add, modify, or delete.

- If you enter the **groupctl** command without any options, the system will display the help information. Use the following format.

```
groupctl
```

- If you want to display the version for the **groupctl** command, enter the following command.

```
groupctl -version
```

- If you want the login box to pop up if either of the required options, **-user** or **-pwd**, is incorrect, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -group groupname -mode type -interactive
```

## Add

The following formats show various options for adding user groups. Note that you can combine the additional options in any manner that meets your needs.

- To add a user group without any members in it, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -group groupname -mode add
```

- To add a user group with a member in it, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -group groupname -mode add -member entry_name
```

where: *entry\_name* is the user or group name to add to the group.

- To add a user group with a filter, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -group groupname -mode add  
-constraint column_name:operator:value
```

where: *column\_name* is the name of the column for the filter.

*operator* is the operation the system will perform for the filter.

*value* is the value for the filter.

## Modify

- To modify an existing user group that does not have a filter by adding a member to it, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -group groupname -mode modify -keepusers
-member entry_name
```

where: *entry\_name* is the user or user group name to add to the user group.

- To modify an existing user group by adding a filter to it or changing the filter for it, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -group groupname -mode modify -keepusers
-constraint column_name:operator:value
```

where: *column\_name* is the name of the column for the filter.

*operator* is the operation the system will perform for the filter.

*value* is the value for the filter.

- To modify an existing user group that does have a filter by adding a member to it, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -group groupname -mode modify -keepusers
-constraint column_name:operator:value -member entry_name
```

where: *entry\_name* is the user or user group name to add to the user group.

*column\_name* is the name of the column for the filter.

*operator* is the operation the system will perform for the filter.

*value* is the value for the filter.

- To remove a filter from an existing user group and keep the members of that group, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -group groupname -mode modify -keepusers
```

- To replace the members of an existing user group that does not have a filter, enter the following command.

```
groupctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -group groupname -mode modify -member entry_name1,
entry_name2, ... , entry_nameN
```

where: *entry\_name* is the user or user group name to add to the user group. In this case, you can enter any combination of user or group names.

Note that if you want to remove one or more members from a user group, you have to modify the group and supply the desired list of members with the **-member** option.

## Delete

- To delete a user group, enter the following command:

```
groupctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -group groupname -mode delete
```

## Examples

The following examples illustrate some uses of the **groupctl** command that an Administrator, such as the **trendadm** user, can enter.

### Example 1: Add a Group without Members

To add a group with the name **group1** on the **powder2** host without any members, you can use the following command.

```
groupctl -host powder2 -port 80 -user trendadm -pwd trendadm
-group group1 -mode add
```

### Example 2: Add a Group with Members

To add a group with the name `group2` on the `powder2` host with two members `user1` and `user2`, you can use the following command.

```
groupctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-group group2 -mode add -member user1,user2
```

### Example 3: Add a Filter to an Existing Group

To add a filter that requires the `cust_id` column to have the value `10` to an existing group that has the name `group1` on the `powder2` host without removing the existing members, you can use the following command.

```
groupctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-group group1 -mode modify -keepusers -constraint cust_id:=:10
```

### Example 4: Replace Members in an Existing Group

To replace members in an existing group that has the name `group1` on the `powder2` host with members such as `user1` and `user2`, you can use the following command.

```
groupctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-group group1 -mode modify -member user1,user3
```

### Example 5: Delete a Group

To delete a group with the name `group2` from the `powder2` host, you can use the following command.

```
groupctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-group group2 -mode delete
```



## Error Messages

This section describes some of the messages that can occur from **groupctl**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
  - The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- If the following message appears, the user is unauthorized to create, modify, or delete a user group.

Unauthorized.

Verify the following:

- The user (**-user**) and password (**-pwd**) values are correct.
- The specified user has administrator privileges.



## groupimport

You can use the **groupimport** command to add, modify, or delete Web Access Server groups on an HP OpenView Performance Insight (OVPI) system. This utility is an extension of the Web Access Server **Group Accounts** feature under the **Administration** link on the Management Console.

### Requirements or Restrictions

- There are five required command-line options that you must enter each time you invoke the utility.
- Any file to be imported must be in the Extensible Markup Language (XML) interchange format specified in this chapter.

## Syntax

The **groupimport** command uses the following syntax:

```
groupimport  -c communications_protocol
               -f group_XML_file_name
               -h application_server_name
               [ -help ]
               -p application_server_port_number
               -P administrator_password
               -U administrator_username
```

## Options

The **groupimport** commands have the following options:

- c The communications protocol that you want to use (http or https). If this option is not specified, http is used by default.
- f Name of the text file containing Web Access Server group information.
- h Name of the Web Access Server.
- help Display the command-line options for the **groupimport** command.
- p Port number of the Web Access Server.
- P Password of the OVPI administrator.  
This option is in UPPERCASE.
- U Username of the OVPI administrator.  
This option is in UPPERCASE.

# Usage Notes

This section describes the naming convention and file format for the text file that contains the XML tag sets when you use the **groupimport** command.

## Naming Conventions

The **groupimport** text file parameters must follow the naming conventions listed below:

- 1 The tag set parameter formats can be all alphabetic characters (upper and lower case), all numeric symbols, and all special characters except those cited in [Step 2](#).
- 2 DO NOT use any of the following characters in the **groupimport** text file:
  - single quotation mark ( ‘ )
  - double quotation mark ( “ )
  - ampersand ( & )
  - comma ( , )
  - space (blank)

## File Format

The **groupimport** text file uses XML tag sets to define the data to be imported into the Web Access Server. [Figure 1](#) shows all XML tag sets available for use in the **groupimport** text files. [Table 13](#) describes all XML tag sets available for use in the **groupimport** text files.

```
<?xml version="1.0" encoding="UTF-8"?>
<Groups>
  <Group>
    <Action>action</Action>
    <Name>group_name</Name>
    <ChildGroups>
      <Child>child_group_name</Child>
    </ChildGroups>
    <Users>
      <User>user_in_group_name</User>
    </Users>
    <FilterConstraints>
      <Constraint>
        <LeftHandSide>filter_on_column</LeftHandSide>
        <Operator>mathematic_operator</Operator>
        <RightHandSide>filter_value</RightHandSide>
      </Constraint>
    </FilterConstraints>
  </Group>
</Groups>
```

**Figure 1 groupimport Text File Format**



All the XML tag sets include the angle brackets (<>) as part of the tag.

Table 13 groupimport File - XML Tag Definitions

XML TAG SETS	DESCRIPTION
<code>&lt;?xml version="1.0" encoding="UTF-8"?&gt;</code>	Allows the parser to validate the XML format. It must appear as the first line in the file.
<code>&lt;Groups&gt;</code> <code>&lt;/Groups&gt;</code>	<code>&lt;Groups&gt;</code> is the opening tag for the <code>&lt;Groups&gt;&lt;/Groups&gt;</code> tag set. There can be multiple <code>&lt;Group&gt;&lt;/Group&gt;</code> tag sets inside the <code>&lt;Groups&gt;&lt;/Groups&gt;</code> tag set. All <code>&lt;Group&gt;&lt;/Group&gt;</code> tag sets are contained within the <code>&lt;Groups&gt;&lt;/Groups&gt;</code> tag set for each group being defined. This tag set is required.
<code>&lt;Action&gt;</code> <code>&lt;/Action&gt;</code>	Procedure tag set that defines the operation to perform. If a group exists and the <b>Add</b> action is specified, the request is ignored. Valid values = <b>Add, Modify, Delete</b> Default = <b>Add</b>
<code>&lt;Name&gt;</code> <code>&lt;/Name&gt;</code>	Defines group name. This tag set is required.
<code>&lt;ChildGroups&gt;</code> <code>&lt;/ChildGroups&gt;</code>	<code>&lt;ChildGroups&gt;</code> is the opening tag for the <code>&lt;ChildGroups&gt;&lt;/ChildGroups&gt;</code> tag set. There can be multiple <code>&lt;Child&gt;&lt;/Child&gt;</code> tag sets inside the <code>&lt;ChildGroups&gt;&lt;/ChildGroups&gt;</code> tag set. All <code>&lt;Child&gt;&lt;/Child&gt;</code> tag sets are contained within the <code>&lt;ChildGroups&gt;&lt;/ChildGroups&gt;</code> tag set for each sub-group being defined. This tag set is not required if there are no sub-groups.

**Table 13 groupimport File - XML Tag Definitions (cont'd)**

XML TAG SETS	DESCRIPTION
<p><b>&lt;Child&gt;</b> <b>&lt;/Child&gt;</b></p>	<p><b>&lt;Child&gt;</b> is the opening tag for the <b>&lt;Child&gt;</b> <b>&lt;/Child&gt;</b> tag set. This tag set specifies the sub-group name.</p> <p>There can be multiple <b>&lt;Child&gt;</b><b>&lt;/Child&gt;</b> tag sets inside the <b>&lt;ChildGroups&gt;</b> <b>&lt;/ChildGroups&gt;</b> tag set.</p> <p>All <b>&lt;Child&gt;</b><b>&lt;/Child&gt;</b> tag sets are contained within the <b>&lt;ChildGroups&gt;</b> <b>&lt;/ChildGroups&gt;</b> tag set for each sub-group being defined.</p> <p>This tag set is not required if there are no sub-groups.</p>
<p><b>&lt;Users&gt;</b> <b>&lt;/Users&gt;</b></p>	<p><b>&lt;Users&gt;</b> is the opening tag for the <b>&lt;Users&gt;</b> <b>&lt;/Users&gt;</b> tag set.</p> <p>There can be multiple <b>&lt;User&gt;</b><b>&lt;/User&gt;</b> tag sets inside the <b>&lt;Users&gt;</b><b>&lt;/Users&gt;</b> tag set.</p> <p>All <b>&lt;User&gt;</b><b>&lt;/User&gt;</b> tag sets are contained within the <b>&lt;Users&gt;</b><b>&lt;/Users&gt;</b> tag set for each user assigned to the group.</p> <p>This tag set is not required if there are no users assigned to the group being defined.</p>
<p><b>&lt;User&gt;</b> <b>&lt;/User&gt;</b></p>	<p><b>&lt;User&gt;</b> is the opening tag for the <b>&lt;User&gt;</b> <b>&lt;/User&gt;</b> tag set. This tag set specifies one user's name.</p> <p>There can be multiple <b>&lt;User&gt;</b><b>&lt;/User&gt;</b> tag sets inside the <b>&lt;Users&gt;</b><b>&lt;/Users&gt;</b> tag set.</p> <p>All <b>&lt;User&gt;</b><b>&lt;/User&gt;</b> tag sets are contained within the <b>&lt;Users&gt;</b><b>&lt;/Users&gt;</b> tag set for each user assigned to the group.</p> <p>This tag set is not required if there are no users assigned to the group being defined.</p>



Table 13 groupimport File - XML Tag Definitions (cont'd)

XML TAG SETS	DESCRIPTION
<p><b>&lt;FilterConstraints&gt;</b> <b>&lt;/FilterConstraints&gt;</b></p>	<p><b>&lt;FilterConstraints&gt;</b> is the opening tag for the <b>&lt;FilterConstraints&gt;</b> <b>&lt;/FilterConstraints&gt;</b> tag set.</p> <p>There can be multiple <b>&lt;Constraint&gt;</b> tag sets inside the <b>&lt;FilterConstraints&gt;</b> tag set.</p> <p>All <b>&lt;Constraint&gt;</b><b>&lt;/Constraint&gt;</b> tag sets are contained within the <b>&lt;FilterConstraints&gt;</b> tag set for each constraint being defined.</p> <p>This tag set is not required if there are no constraints.</p>
<p><b>&lt;Constraint&gt;</b> <b>&lt;/Constraint&gt;</b></p>	<p><b>&lt;Constraint&gt;</b> is the opening tag for the <b>&lt;Constraint&gt;</b><b>&lt;/Constraint&gt;</b> tag set. This tag set defines the filters for the group.</p> <p>Each <b>Constraint</b> tag contains three internal tags that define the filter.</p> <p><b>&lt;LeftHandSide&gt;</b> Defines the column to filter on.</p> <p><b>&lt;Operator&gt;</b> Defines the boolean operator to apply. The valid operators are: <b>=, &lt;, &lt;=, &gt;, &gt;=, &lt;&gt;, like, not like</b></p> <p><b>&lt;RightHandSide&gt;</b> Defines the value of the filter. If the SQL type of the column is a <b>CHAR</b> or <b>VARCHAR</b>, enclose the value in single quotes.</p> <p>If there are multiple <b>Constraint</b> tags for a single group, the filters will be joined together with <b>AND</b>.</p> <p>This tag set is not required if there are no filters.</p>

## Example

The sample **groupimport** file shown in [Figure 2](#), when called from the command line by the command listed below, will add one group:

```
groupimport -h app_server -p app_server_port -U admin_username  
-P admin_password -f full_path_and_filename
```

```
<?xml version="1.0" encoding="UTF-8"?>  
<Groups>  
  <Group>  
    <Action>Add</Action>  
    <Name>Technical Services</Name>  
    <Users>  
      <User>wbentley</User>  
      <User>jsmith</User>  
    </Users>  
  </Group>  
</Groups>
```

**Figure 2** Sample groupimport Text File

## group\_manager

The **group\_manager** utility is designed to manage group definitions and polling policies. Note that you can use both **collection\_manager** and **group\_manager** to define polling policies.

If you want more information about groups, see [About Groups on page 188](#).

### Requirements or Restrictions

- An error occurs if the **-infile** option does not appear with the **-import** option.
- An error occurs if more than one of the following options appears on the command line at the same time: **-import**, **-export**, **-export\_all**, **-export\_policy**, **-export\_policy\_all**, **-remove**, or **-remove\_policy**.
- The default database for all database options is the default database identified in the `systems.xml` file.

## Syntax

The **group\_manager** command uses the following syntax:

```

group_manager    [ -backup ]
                  [ -database db_name ]
                  [ -datadb datadb_server ]
                  [ -debug dbug_level ]

                  [ { -export category.group
                    { -export_all
                    { -export_policy policy_name
                    { -export_policy_all
                    { -import
                    { -remove category.group
                    { -remove_policy policy_name
                    }
                    }
                    }
                    }
                    }
                    }
                  ]

                  [ -force ]
                  [ -groupdb groupdb_server ]
                  [ -help ]
                  [ -infile file_name ]
                  [ -outfile file_name ]
                  [ -pollfrom host_name ]
                  [ -use_default ]
                  [ -user user_name ]

                  [ { -v
                    { -version
                    }
                  ]

```

## Options

The **group\_manager** command has the following options:

- backup** Use this option with the **-remove** or **-remove\_policy** option to back up a group definition or polling policy before OVPI removes it. If the group is a derived group, and you use the **-force** option, **group\_manager** backs up all dependent groups before removing them. OVPI writes the backup file for the group to the `$DPIPE_HOME/lib/groups` directory; the format of the file name is `TG_group_category.xml`. It writes the backup file for the polling policy to the `$DPIPE_HOME/lib/collection_defs` directory; the format of the file name is `PP_policy_name.xml`.
- database** This option identifies the database where the changes will occur. The database must appear in the list of available database servers. See the section on the Web Access Server in the *Performance Insight Administration Guide* for more information about adding database servers to the list. The default is the database identified as the default in the database server list.
- datadb** Use this option with the **-import** option to specify the database where OVPI will store collected data. This is the data database; see [data database on page 268](#) for the definition. The value associated with this option overrides the corresponding value, if any, in the input file that defines the polling policy. The corresponding value in **collection\_manager** is the `server_name` parameter in the ASCII file. The corresponding value in **Polling Policy Manager** is in the **Server** column on the database information page. You can use this option only when you are importing a polling policy. The `datadb_server` must exist in the list of OVPI databases before the import.

- debug**  
or  
**-d**
- Use this option to set the debug output level. The higher the number, the more detailed the information. Debug output writes to standard output. Use this option only for testing in coordination with Technical Support due to the additional overhead it places on **group\_manager**. The default is no debug output.
- export**
- Use this option to generate a file containing the group definition specified on the command line. You must specify the group in the format *category.group*; see [Naming Convention on page 187](#) for a description of these parameters. You can use the **-outfile** option to specify the output file name and storage location; otherwise, **group\_manager** writes the data to a self-generated file in the `$DPIPE_HOME/lib/groups` directory.
- You can use this option only when you are exporting group definitions; it does not include polling policies. This option cannot appear on the command line when the **-export\_all**, **-import**, **-remove**, or **-remove\_policy** option appears on the command line.
- export\_all**
- Use this option to generate files containing all the group definitions. You can use the **-outfile** option to specify the storage location; otherwise, **group\_manager** writes the data to self-generated files in the `$DPIPE_HOME/lib/groups` directory. It generates one file for each group, and it names each file in this form: `TG_group_category.xml`; see [Naming Convention on page 187](#) for a description of these parameters.
- You can use this option only when you are exporting group definitions; it does not include polling policies.
- This option cannot appear on the command line when the **-export**, **-import**, **-remove**, or **-remove\_policy** option appears on the command line.

- export\_policy** Use this option to generate a file containing the polling policy specified on the command line. You can use the **-outfile** option to specify the output file name and storage location; otherwise, **group\_manager** writes the data to a self-generated file in the `$DPIPE_HOME/lib/collection_defs` directory.
- You can use this option only when you are exporting polling policies; it does not include group definitions.
- This option cannot appear on the command line when the **-export**, **-export\_all**, **-export\_policy\_all**, **-import**, **-remove**, or **-remove\_policy** option appears on the command line.
- export\_policy\_all** Use this option to generate files containing all the polling policy definitions. You can use the **-outfile** option to specify the storage location; otherwise, **group\_manager** writes the data to self-generated files in the `$DPIPE_HOME/lib/collection_defs` directory. It generates one file for each group, and it names each file in this form: `PP_PollingPolicyName.xml`.
- You can use this option only when you are exporting polling policies; it does not include group definitions.
- This option cannot appear on the command line when the **-export**, **-export\_all**, **-export\_policy**, **-import**, **-remove**, or **-remove\_policy** option appears on the command line.
- force** Use this option with the **-remove** option to force the removal of all groups that depend on the group you are removing.

- groupdb** Use this option with the **-import** option to specify the database that contains the list of nodes to be polled. This is the topology database; see [topology database on page 268](#) for the definition. The value associated with this option overrides the corresponding value, if any, in the polling policy. The corresponding value in **collection\_manager** is the *group\_server* parameter in the ASCII file. You can use this option only when you are importing a polling policy. The *groupdb\_server* must exist in the list of OVPI databases before the import.
- help** This option is the help option, which displays the command-line options for the **group\_manager** command.
- import** Use this option to import one group or polling policy at a time. It requires the **-infile** option to identify the file that contains a group definition or polling policy to import. This option cannot appear on the command line when the **-export**, **-export\_all**, **-remove**, or **-remove\_policy** option appears on the command line.
- infile** This option identifies the XML file that contains the information about a polling policy or group to import. If the file is not in the current working directory, you must specify the fully qualified path to the file. See [Definition Files on page 192](#) for details on setting up this file. This is a required option when the **-import** option appears on the command line.



- outfile** This option identifies the name of the file or directory where OVPI will store the exported group definition. You should use the directory name with the **-export\_all** option.
- If this file already exists, **group\_manager** will overwrite it.
- You can use this option with the **-export** and **-export\_all** options.
- pollfrom** Use this option with the **-import** option to specify the server that contains the data for the polling policy. The value associated with this option overrides the corresponding value, if any, in the polling policy.
- The corresponding value in **collection\_manager** is the *poll\_from* parameter in the ASCII file or the **-pollfrom** option on the command line. The corresponding value in **Polling Policy Manager** is the **Polling Assigned to** field when you create or edit a polling policy.
- You can use this option only when you are importing a polling policy. The *host\_name* must exist before the import.
- remove** Use this option to remove a group definition. You must identify the group in the format *category.group* on the command line following this option; see [Naming Convention on page 187](#) for a description of these parameters.
- If you want to remove all groups that depend on this removed group, include the **-force** option on the command line.
- This option cannot appear on the command line when the **-export**, **-export\_all**, **-import**, or **-remove\_policy** option appears on the command line.

- remove\_policy** Use this option to remove a polling policy from the collection catalog.  
This option cannot appear on the command line when the **-export**, **-export\_all**, **-import**, or **-remove** option appears on the command line.
- use\_default** When you use this option to import polling policies, **group\_manager** will use the default values for the `<DataDb>`, `<TopDb>`, and `<PollFrom>` tags in the polling policy definition file. The default values for these tags are from the default database identified in the `systems.xml` file.  
In the `export_policy` modes, the definition files will not contain the `<DataDb>`, `<TopDb>`, and `<PollFrom>` values, when you use this option.
- user** Use this option to specify the owner of the imported group or polling policy. The value associated with this option overrides the corresponding value, if any, in the group definition or polling policy.  
The corresponding value in **collection\_manager** is the `user_name` parameter in the ASCII file. The corresponding value in **Polling Policy Manager** is in the **User** column on the database information page.  
The default is **trendadm**.
- V** Use this option to display the current version of the **group\_manager** utility.  
or  
**-version** You can use either an uppercase **-V** or the lowercase, spelled-out form (**-version**).

## Naming Convention

The **group\_manager** utility uses XML files for the import and export modes. The import files should have `.xml` as the suffix. The export files will have `.xml` as the suffix for each file unless you specify an existing file name that has a different suffix. The following rules apply for export mode.

- If you specify a file name with `.xml` as the suffix, **group\_manager** creates a file by that name.
- If you specify a file for output that already exists, **group\_manager** overwrites that file.
- If you do not use `.xml` as the suffix and the file does not already exist, **group\_manager** treats the entire name as a directory name. Within that directory, it creates one or more files that use the following naming convention: `TG_group_category.xml`. The descriptions of the *group* and *category* parameters follow.

The *group* portion of the name is the name of the group that contains the list of objects to collect. It may appear in the **Select Group to Poll From** pull-down list in **Polling Policy Manager**.

The *category* portion of the name identifies the kind of group for the corresponding *group*. If the group is a **type** list, then the *category* is **type**. Similarly, if the group is a **view** list, then the *category* is **view**. If the group is a single node group, then the *category* is **node**. Otherwise, the *category* is the same as the property table name.

The following table shows the typical association for the *category* value to the corresponding kind of group that may appear in the **Collect Data From** field in **Polling Policy Manager**.

**Table 14 Typical Values for the Group Category Parameter**

Category Value	Value in Collect Data From Field
<b>type</b>	All Nodes of the Same Type A Combination of Type and View
<b>view</b>	All Nodes in Same View
<b>node</b>	A Single Node
<i>property_table_name</i>	Specific Instances Custom Groups

These group and category definitions apply to the format of the group identity used with the **-export** or **-remove** option, which is *category.group*.

Refer to the *Performance Insight Administration Guide* for more information about **Polling Policy Manager**.

## Usage Notes

This section provides a brief description of groups in general and the available modes of operation. It also explains how to create an XML file to import a polling policy or a group and how to execute the **group\_manager** command.

### About Groups

An OVPI group represents a set of managed objects. A managed object can be a variety of things, such as a router, a customer, or a location. Each managed object is persisted in an OVPI database as a row in a property table. A property table is a set of managed objects that are similar to one another.

You can use **group\_manager** to define and manage three types of groups:

- |                        |  |
|------------------------|--|
| <b>Derived</b>         | A group that contains other, logically related groups. Currently, in OVPI a derived group can contain a maximum of two other groups.   |
| <b>Enumerated-list</b> | A group that contains a list of distinct objects.  |
| <b>Rule-based</b>      | A group whose membership is determined by a set of associated rules. The membership may change at various points in time with each evaluation of the rules. Currently, in OVPI a rule-based group can evaluate a maximum combination of two rules. |

Every group combines with a group category to create a unique identity for the group. A *group category* is a set of objects that corresponds to an existing property table. A group is a subset of the objects in the group category that could contain any number of objects in the set. The membership in the group depends on the type of group: derived, enumerated list, or rule-based.

Most group categories use the name of the property table for identification. However, there are three well-known group categories: type, view, and node. They pertain to the property table that contains the entire list of nodes. Any group associated with these group categories is an enumerated-list type of group.

## Modes of Operation

The **group\_manager** command has three modes of operation: import, export, and remove.

### Import

The *import* mode enables you to import a group definition or polling policy using an XML file. See [Definition Files on page 192](#) for more information about the file.

You must use the **-infile** option with the **-import** option. You may use the following options when you import a group definition or a polling policy.

- database** Specifies the server where OVPI will store the imported group definition or polling policy.
- user** Specifies the owner of the imported group or polling policy.

You may use these options only when you import a polling policy.

- datadb** Specifies the database where OVPI will store collected polling data.
- groupdb** Specifies the database that contains the list of nodes to be polled.
- pollfrom** Identifies the computer that will perform the polling specified in a polling policy.
- use\_default** Assigns the default values to the fields associated with the **-datadb**, **-groupdb**, and **-pollfrom** options from the default database identified in the `systems.xml` file.

## Export

The *export* mode provides the ability to create one or more files containing existing group definitions or polling policies. Four options are available:

**-export**, **-export\_all**, **-export\_policy**, and **-export\_policy\_all**.

You can use the following options to export group definitions:

- The **-export** option allows you to export a single group definition to a file by specifying the group on the command line.
- The **-export\_all** option allows you to export all existing group definitions to individual files in a directory that you can specify.

You can use the following options to export polling policies:

- The **-export\_policy** option allows you to export a single polling policy to a file by specifying the polling policy on the command line.
- The **-export\_policy\_all** option allows you to export all existing polling policies to individual files in a directory that you can specify.

You may use this option when you export a polling policy.

**-use\_default** Excludes the values from the fields associated with the **-datadb**, **-groupdb**, and **-pollfrom** options in the polling policy.

You may use the following option when you export a group definition or a polling policy.

**-database** Specifies the server that contains the group definitions or polling policies.

## Remove

The *remove* mode enables you to delete group definitions and polling policies. Two options are available: **-remove** and **-remove\_policy**.

- The **-remove** option allows you to remove a group definition from the system.
- The **-remove\_policy** option allows you to remove a polling policy from the system.

You may use any of the following options in remove mode.

**-backup** Backs up the group definition or polling policy before removing it from the system.

**-database** Specifies the server that has the group definition or polling policy that OVPI will remove.

You may only use the following option when you remove a group definition.

**-force** Removes all groups that depend on the group designated for removal. This option is for group definitions only.

## Definition Files

To import a group definition or polling policy with **group\_manager**, you create an XML file containing a Document Type Definition (DTD) that defines the group or polling policy. When **group\_manager** exports a group definition or polling policy, it exports the DTD to the output file. For guidance in programming in XML, refer to your XML documentation.

### Document Type Definition for Group Definitions

The following DTD is the set of rules that **group\_manager** uses to create groups.

```
<!?xml version='1.0'?>
<!-- DTD DEFINITION -->
<!DOCTYPE GROUP [
<!-- document type definition for group definitions -->
<!-- A group definition document contains element GROUP -->
<!-- that defines the group -->
<!ELEMENT GROUP ( GroupName, GroupCategory, description?,
GroupOwner?, GroupType )>
<!ELEMENT GroupName (#PCDATA)>
<!ELEMENT GroupCategory (#PCDATA)>
<!ELEMENT GroupOwner (#PCDATA)?>
<!ELEMENT description (#PCDATA)?>

<!-- groups can be any of the following types -->
<!ELEMENT GroupType (derived|enumerated|rule)>

<!-- Definition of various group types -->
<!-- Definition for the Derived type -->
<!-- Currently a derived group can have only 2 groups; -->
<!-- one of them must be based on ksi_managed_node -->
<!ELEMENT derived (MemberGroup, MemberGroup)>
<!ELEMENT <MemberGroup (GROUP) >
<!ATTLIST MemberGroup logop (enter|and|or|not) #REQUIRED>

<!--***** end of Derived definition ***** -->

<!-- Definition for the Enumerated List type -->
<!-- Note: For now, we assume that the data will not be loaded;
<!-- that is, the MBR tables will stay empty -->
<!ELEMENT enumerated EMPTY >

<!--***** end of Enumerated definition ***** -->

<!-- Definition for the Rule type -->
```



```

<!ELEMENT rule (column|(column, column))>
<!ELEMENT column EMPTY>
<!ATTLIST column name CDATA #REQUIRED>
<!ATTLIST column op (eq|lt|le|gt|ge|ne|like|not_like) #REQUIRED>
<!ATTLIST column logop (enter|and|or|not) #REQUIRED>
<!ATTLIST column value CDATA #REQUIRED>

]

<!-- END OF THE DTD -->

```

## Document Type Definition for Polling Policies

The following DTD is the set of rules that **group\_manager** uses to create polling policies.

```

<!?xml version='1.0'?>
<!-- DTD DEFINITION -->
<!DOCTYPE PollDefinition [
<!ELEMENT PollDefinition (Name, Interval, Table, PollForGroup,
PollFrom?, TopDB?, DataDB?, description?) >
<!ATTLIST PollDefinition datapipe CDATA #REQUIRED>
<!ELEMENT Name (#PCDATA)>
<!ELEMENT Interval (#PCDATA)>

<!-- Note: Table name must be SQL name, that is, real table -->
<!ELEMENT Table (#PCDATA)>

<!ELEMENT PollForGroup EMPTY>
<!ATTLIST PollForGroup groupName CDATA #REQUIRED>
<!ATTLIST PollForGroup groupCategory CDATA #REQUIRED>
<!ELEMENT PollFrom (#PCDATA)>
<!ELEMENT TopDb (#PCDATA)>
<!ELEMENT DataDb (#PCDATA)>
<!ELEMENT description (#PCDATA)>

]>

<!-- END OF THE DTD -->

```

## Using the group\_manager Command

This section shows some formats of the command for the various modes.

- If you enter the **group\_manager** command without any options, the system will display an error message followed by the help information.

- To display the syntax and options for this command, enter:

```
group_manager -help
```

- To display the version information for this command, enter:

```
group_manager -V
```

or

```
group_manager -version
```

- To import a group definition or a polling policy, enter the following command:

```
group_manager -import -infile file_name
```

where: *file\_name* is the name of the file that contains the group definition or polling policy to import. If you do not specify a path to the file, **group\_manager** expects to find the file in the current working directory.

- To export a group definition to a file with a system-generated name in the `$DPIPE_HOME/lib/groups` directory, enter the following command:

```
group_manager -export category.group
```

where: *category* identifies the kind of group to export for the corresponding *group* name. See [Naming Convention on page 187](#) for a description of this parameter.

*group* is the name of the group definition. See [Naming Convention on page 187](#) for a description of this parameter.

The format of the file name is `TG_group_category.xml`. See [Naming Convention on page 187](#) for more information.

- To export a group definition to a specified file or directory, enter the following command:

```
group_manager -export category.group -outfile file_name
```

where: *category* identifies the kind of group to export for the corresponding *group* name. See [Naming Convention on page 187](#) for a description of this parameter.

*group* is the name of the group definition. See [Naming Convention on page 187](#) for a description of this parameter.

*file\_name* is the name of the file or directory that will contain the exported group definition. If this is a file name, it must already exist. If this is a directory name, the format of the file name is `TG_group_category.xml`. See [Naming Convention on page 187](#) for more information.

- To export all group definitions to individual files in the `$DPIPE_HOME/lib/groups` directory, enter the following command:

```
group_manager -export_all
```

The format of each file name in the directory is `TG_group_category.xml`. See [Naming Convention on page 187](#) for more information.

- To export all group definitions to individual files in a specific directory, enter the following command:

```
group_manager -export_all -outfile dir_name
```

where: *dir\_name* is the name of the directory that will contain the exported group definitions. If this name already exists as a file, **group\_manager** will overwrite this file with each group definition and consequently end up with only the last group definition.

The format of each file name in the directory is `TG_group_category.xml`. See [Naming Convention on page 187](#) for more information.

- To export a polling policy to a file with a system-generated name in the `$DPIPE_HOME/lib/collection_defs` directory, enter the following command:

```
group_manager -export_policy policy_name
```

where: *policy\_name* identifies the polling policy to export.

The format of the file name is `PP_policy_name.xml`.

- To export all polling policies to individual files in the `$DPIPE_HOME/lib/collection_defs` directory, enter the following command:

```
group_manager -export_policy_all
```

The format of each file name in the directory is `PP_policy_name.xml`.

- To remove a group, enter the following command:

```
group_manager -remove category.group
```

where: *category* identifies the kind of group to remove from the system for the corresponding *group* name. See [Naming Convention on page 187](#) for a description of this parameter.

*group* is the name of the group definition. See [Naming Convention on page 187](#) for a description of this parameter.

- To remove a polling policy, enter the following command:

```
group_manager -remove_policy policy_name
```

where: *policy\_name* is the name of the polling policy that **group\_manager** will remove from the system.

- To back up a polling policy before removing it, enter the following command:

```
group_manager -remove_policy policy_name -backup
```

where: *policy\_name* is the name of the polling policy that **group\_manager** will remove from the system.

The backup file is in the `$DPIPE_HOME/lib/collection_defs` directory. The format of the file name is `PP_policy_name.xml`.

## Examples

This section has examples for each mode of **group\_manager**.



Whenever you enter a file name you must specify the complete path; otherwise, **group\_manager** refers to the current directory.

## Import Examples

### Example 1

To import group definition from a file named **groups\_in.xml**, enter the following command:

```
group_manager -import -infile groups_in.xml
```

The following is an example of the contents of **groups\_in.xml**.

```
<?xml version="1.0" ?>
<!-- Group Definition -->

<!-- this is enumerated group -->

GROUP>
  <GroupName> tp_lst1 </GroupName>
  <GroupCategory> type </GroupCategory>
  <GroupType>
    <enumerated/>
  </GroupType>
</GROUP>
```

### Example 2

To import a polling policy from a file named **policy\_in.xml**, enter the following command:

```
group_manager -import -infile policy_in.xml
```

The following is an example of the contents of **policy\_in.xml**.

```
<!-- Polling Policy Definition -->

<!-- this is PollingPolicy -->
<PollDefinition datapipe ="testtime">
  <Name> test_policy_gm </Name>
  <Interval> 20 </Interval>
  <Table> testtime_ </Table>
  <PollForGroup  groupName="tp_lst1" groupCategory="type"/>
  <PollFrom> powder2 </PollFrom>
  <TopDb> POWDER2 </TopDb>
  <DataDb> POWDER2 </DataDb>
  <description> This is a test policy. </description>
</PollDefinition>
```

## Export Examples

### Example 1

To generate a file named **export\_group\_1.xml**, containing a single group definition, **super.group1**, enter the following command:

```
group_manager -export super.group1 -outfile export_group_1.xml
```

If you do not specify a full directory path for the storage of the file, **group\_manager** saves the file in **\$DPIPE\_HOME/lib/groups** directory.

### Example 2

To generate one export file for each group in the system and place the files in a directory named **export\_groups**, enter the following command:

```
group_manager -export_all -outfile export_groups
```

The **group\_manager** utility assigns a unique name to each file, using this format: **TG\_group\_category.xml**. See [Naming Convention on page 187](#) for a description of the parameters in the name. For example, if a group with a **type** category has the name **Frame\_Relay\_Interfaces**, then the name for that exported file is **export\_groups/TG\_Frame\_Relay\_Interfaces\_type.xml**.

## Remove Examples

### Example 1

If you want to remove a group definition named **super.group2** from the system, enter the following command:

```
group_manager -remove super.group2
```

### Example 2

If **super.group2** is a member of a derived group, and you want to remove it and all its dependent groups, enter the following command:

```
group_manager -remove super.group2 -force
```

### Example 3

If you want to create backups of **super.group2** and its dependent groups before removing them from the system, enter the following command:

```
group_manager -remove super.group2 -force -backup
```

In this case, **group\_manager** creates one backup file for each group definition in the `$DPIPE_HOME/lib/groups` directory; each file name has the format `TG_group_category.xml`. See [Naming Convention on page 187](#) for a description of the parameters in the name.

## Remove\_Policy Examples

### Example 1

If you want to remove a single polling policy named **test\_policy\_2**, enter the following command:

```
group_manager -remove_policy test_policy_2
```

### Example 2

You can back up the polling policy before removing it with the following command:

```
group_manager -remove_policy test_policy_2 -backup
```

In this case, **group\_manager** creates a backup file for the polling policy in the `$DPIPE_HOME/lib/collection_defs` directory. The format of the backup file name is `PP_policy_name.xml`. In this example, the backup file name is `$DPIPE_HOME/lib/collection_defs/PP_test_policy_2.xml`.

## Error Messages

This section describes some of the messages that can occur from **group\_manager**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.

- A suggestion about the action to do so that the message will not appear again.

## Syntax Messages

- If the following error message appears, there is a command-line syntax error. This means that a required mode option is missing.

unknown operation 0

Verify that the command line has one of the following options after the **group\_manager** command: **-import**, **-export**, **-export\_all**, **-remove**, or **-remove\_policy**.

- If the following error message appears, the **-import** option is on the command line and the **-infile** option is missing.

Object definition file name must be specified.

Verify that the **-infile** option is on the command line with the **-import** option.

- If the following error message appears, there is an option with incorrect syntax.

command line error:[argument *value* is invalid].

Verify that the spelling and the syntax for each option on the command line is correct. For example, verify that you use **-infile** or **-outfile** instead of **-file** with the appropriate option.

- If the following error message appears, an option is missing its corresponding value.

command line error:[argument *option* missing value].

Verify that any of the following options on the command line has the appropriate corresponding value: **-database**, **-datadb**, **-export**, **-groupdb**, **-infile**, **-outfile**, **-pollfrom**, **-remove**, **-remove\_policy**, **-user**. See [Syntax on page 180](#).

- If the following error message appears, the input file name specified in **-infile** option does not exist.

input file *file\_name* is not a file.

Verify that the **-infile** option is on the command line with the **-import** option.



## Value Messages

- If the following error message appears, the file name specified on the command line in the **-infile** *file\_name* option does not exist.

Input file *file\_name* doesn't exist.

Verify the spelling of the file name or that the file exists in the specified location. You may have to supply a fully qualified path name with the file name.

- If the following error message appears, the specified value on the command line does not exist in the specified table in the database, and the error comes from the specified stored procedure.

*value* value in the table *table\_name* does not exist.  
(in stored procedure *stored\_procedure\_name*), ErrorCode: *number*

Verify that the option has the correct value on the command line. This message may also occur if the corresponding polling policy is in the table that contains the collection instructions, incorrectly.

- If the following error message appears, the database specified with the **-database** option on the command line does not exist.

Failed to connect to *database\_name* database.  
Connection URL not found.

Verify the spelling of the database name. If the spelling is correct, you can add the database using the Web Access Server.

- If the following error message appears, the specified group name is not in the database when you use the **-export** or **-remove** option.

Failed processing TREND object.  
[failed getting group definition from DB for group  
name=*group\_name* group category=*category*].  
The group *group\_name* does not exist.

Verify the spelling of the group name and the category name. This message may also occur if you enter an incorrect policy name in the format *xxx.yyy* for the **-remove\_policy** option.

- ❑ If the following error message appears, the policy name specified with the **-remove\_policy** option does not exist.

```
Failed processing TREND object.  
[failed exporting polling policy [policy_name]].  
The collection policy_name does not exist.
```

Verify the spelling of the policy name. You can verify that the polling policy exists by checking **Polling Policy Manager** or **collection\_manager**.

- ❑ If the following error message appears, a value on the command line is incorrect that prevented **group\_manager** from creating the polling policy.

```
Failed processing TREND object.  
[failed creating polling policy (trndbexp) pollPolicy:  
[policy_name] datapipe {datapipe_name} dataDB {datadb_value} topDB  
{groupdb_value} table {table_name} interval {interval_value} group  
{group: category=(category_name) name=(group_name)} pollFrom  
{pollfrom_value} user {user_value} ].
```

Verify the values for the options on the command line.

- ❑ If the following error message appears, the values in the XML file may be incorrect.

```
unable to create TrendObject.  
pollPolicy: [policy_name] datapipe {datapipe_name} dataDB  
{datadb_value} topDB {groupdb_value} table {table_name} interval  
{interval_value} group {group: category=(category_name)  
name=(group_name)} pollFrom {pollfrom_value} user {user_value}.  
specified group doesn't exist
```

Verify that the values in the XML file are correct. In particular, check the values for the group category and group name. One of these values may not exist or the combination of these values is incorrect.

# indexmaint

You can use the **indexmaint** command to maintain indexes of existing data tables on an HP OpenView Performance Insight (OVPI) system.

## Requirements and Restrictions

- When you use the **-g** option, you must include the **-t** option on the command line.
- An error occurs if the **-k** option appears on the command line with the **-t** option.
- An error occurs if the following option appear on the command line at the same time: **-c**, **-f**, and **-l**.

## Syntax

The **indexmaint** command uses the following syntax:

```

indexmaint [ -c ]
             [ -d debug_level ]
             [ -e index_name ]
             [ -f ]
             [ -g { -unique
                   -nonunique } , index_name , col1 [ , col2 , ... , colN ] ]
             [ -h ]
             [ -K ]
             [ -l ]
             [ -n ]
             [ -r ]
             [ -S database_server_name ]
             [ -t table_name ]
             [ -v ]

```

## Options

The **indexmaint** command has the following options:

- c** This option is available for an Oracle database only. Use this option to coalesce indexes instead of rebuilding them. An error occurs if this option is on the same command line as the **-f** and **-l** options.

- d** Use this option to specify the debug output level. Use the value **1** to see the debug output. Use this option only for testing in coordination with HP Technical Support due to the additional overhead it places on **indexmaint**.  
The default is no debug output.  
Debug output writes to standard output.
- e** Use this option to specify the name of the index to drop.
- f** On Sybase, use this option to unconditionally drop and recreate all non-primary indexes according to the guidelines in [Table 15](#). You can update the primary indexes by running the Sybase command **update statistics**.  
On Oracle, use this option to rebuild all indexes and their associated partitions if any of the following conditions exist:
- The index is not an index-organized table (IOT).
  - The index is an IOT and it is not a primary index.
- The system will analyze all of the indexes statistics according to the guidelines in [Table 16](#).  
An error occurs if this option is on the same command line as the **-c** option.
- g** Use this option to create an index for one or more columns. This option requires the following information:
- Specify the unique qualities of the index; valid values are **unique** or **nonunique**.
  - Enter the name of the index, which can be up to 30 characters.
  - Specify one or more columns where the system will create this index.
- h** Use this option to display all command line options (help).
- k** Use this option to maintain property and keymap tables only.  
An error occurs if this option is on the same command line as the **-t** option.  
This option is in UPPERCASE.

- l** Use this option to list existing indexes and write the results to the standard output.  
An error occurs if this option is on the same command line as the **-c** option.  
This option is lowercase “L.”
- n** Use this option to bypass the verification process for the required indexes and their associated index columns on each table.  
This option overrides the default, which is to verify.  
You should use this option only when you use the **-g** option on the same command line.
- r** This option is available for Sybase databases only.  
Use this option to prevent the creation of clustered indexes using the **sorted-data** option.  
This option overrides the default, which creates the clustered indexes using the **sorted-data** option.  
If the creation fails with a `data out of order` message, the default applies.  
When the clustered indexed columns contain sorted data, this option causes **indexmaint** to run faster.
- s** Use this option to specify the database server name.  
This option is in UPPERCASE.
- t** Use this option to maintain the index for the specified table only.  
An error occurs if this option is on the same command line as the **-k** option.
- v** Use this option to display the version number.  
This option is in UPPERCASE.

## Usage Notes

You can use the **indexmaint** command to rebuild and rename indexes of existing data tables in the table dictionary on an OVPI system to improve the efficiency of raw-to-delta and other processes. All actions appear in the `trend.log` file.

## Table Indexes

In order for an OVPI system to operate efficiently, all user data tables must have properly defined and maintained indexes. The **indexmaint** utility checks that the correct indexes exist on a table and then it creates the indexes, as needed. When you run **indexmaint** without any options, it checks all tables in the OVPI database, as follows. It locates the data tables, checks the type for each table, verifies the indexes, and then creates the appropriate indexes, if necessary.

## Sybase

If the appropriate index exists, **indexmaint** will run the Sybase command, **update statistics**, on the index. [Table 15](#) provides a list of the indexes for each OVPI table type.

**Table 15 Table Indexes — Sybase**

Table Type	Index Name	Index Type	Indexed columns (in order)	Notes
archive event raw	ind1	nonclustered	ta_period dsi_key_id_	
archive raw	ind2	nonclustered	dsi_key_id_ ta_period	
baseline forecast rank rate summary	cuind	unique, clustered	ta_period dsi_key_id_	

**Table 15 Table Indexes — Sybase (cont'd)**

<b>Table Type</b>	<b>Index Name</b>	<b>Index Type</b>	<b>Indexed columns (in order)</b>	<b>Notes</b>
baseline forecast rank rate summary	uind1	unique, nonclustered	dsi_key_id_ ta_period	
trendit	cuind	unique clustered	ta_period dsi_key_id_ dsi_agg_type	
trendit	uind1	unique, nonclustered	dsi_key_id_ ta_period dsi_agg_type	
property	pk_ prop_ tbl_name	unique, clustered	dsi_key_id	
property	uind1	unique, nonclustered	<i>object_by_var_list</i>	
property	uind2	unique, nonclustered	<i>object_by_var_list_ reverse</i>	
property	uind3	unique, nonclustered	<i>collection_by_ var_list</i> dsi_bv_state	This index will exist only if the collection by-variables are different from the object by-variables and if the dsi_bv_state column exists.



**Table 15 Table Indexes — Sybase (cont'd)**

<b>Table Type</b>	<b>Index Name</b>	<b>Index Type</b>	<b>Indexed columns (in order)</b>	<b>Notes</b>
property	uind4	unique, nonclustered	<i>collection_by_var_list_reverse</i> <i>dsi_bv_state</i>	This index will exist only if the collection by-variables are different from the object by-variables and if the <i>dsi_bv_state</i> column exists.
keymap	pk_ <i>keymap_</i> <i>tbl_name</i>	unique, clustered	<i>local_key_id</i> <i>foreign_server_id</i> <i>foreign_key_id</i>	
keymap	uind1	unique, nonclustered	<i>foreign_server_id</i> <i>local_key_id</i> <i>foreign_key_id</i>	
keymap	uind2	unique, nonclustered	<i>foreign_key_id</i> <i>foreign_server_id</i>	
lkeys	cuind	unique, clustered	<i>dsi_key_id_</i> <i>ta_period</i>	
lkeys	uind1	unique, nonclustered	<i>ta_period</i> <i>dsi_key_id_</i>	
lkeys	uind2	unique, nonclustered	<i>ta_period</i> <i>dsi_key_id_</i> <i>ta_period</i>	

where: *collection\_by\_var\_list*

is the list of collection by-variables in their original order.

*collection\_by\_var\_list\_reverse*

is the list of collection by-variables in reverse order.

*foreign\_key\_id*

is the *dsi\_key\_id\_* value on the remote server.

<i>foreign_server_id</i>	is the identification for the remote server.
<i>local_key_id</i>	is the <i>dsi_key_id_</i> value on the local server.
<i>object_by_var_list</i>	is the list of object by-variables in their original order.
<i>object_by_var_list_reverse</i>	is the list of object by-variables in reverse order.
<i>pk_keymap_tbl_name</i>	is the name of the keymap table with <i>pk_</i> as a prefix.
<i>pk_prop_tbl_name</i>	is the name of the keymap table with <i>pk_</i> as a prefix.

## Oracle

If the appropriate index exists, **indexmaint** will run the Oracle command, **Analyze Table**, on the index. [Table 16](#) provides a list of the indexes for each OVPI table type.

**Table 16 Table Indexes — Oracle**

<b>Table Type</b>	<b>Index Name</b>	<b>Index Type</b>	<b>Indexed columns (in order)</b>	<b>Notes</b>
archive event raw	<i>tbl_name_I1</i>	nonunique, normal	ta_period dsi_key_id_	
archive raw	<i>tbl_name_I2</i>	nonunique, normal	dsi_key_id_ ta_period	
baseline forecast rank rate summary	<i>pk_tbl_name</i>	IOT, unique, primary	ta_period dsi_key_id_	
baseline forecast rank rate summary	<i>tbl_name_I1</i>	unique, normal	dsi_key_id_ ta_period	

**Table 16 Table Indexes — Oracle**

<b>Table Type</b>	<b>Index Name</b>	<b>Index Type</b>	<b>Indexed columns (in order)</b>	<b>Notes</b>
trendit	<i>pk_tbl_name</i>	IOT, unique, primary	ta_period dsi_key_id_ dsi_agg_type	
trendit	<i>tbl_name_I1</i>	normal	dsi_key_id_ ta_period dsi_agg_type	
property	<i>pk_prop_ tbl_name</i>	IOT, unique, primary	dsi_key_id	
property	<i>prop_ tbl_name_I1</i>	unique, normal	<i>object_by_var_list</i>	
property	<i>prop_ tbl_name_I2</i>	unique, normal	<i>object_by_var_list_ reverse</i>	
property	<i>prop_ tbl_name_I3</i>	unique, normal	<i>collection_by_ var_list</i> dsi_bv_state	This index will exist only if the collection by-variables are different from the object by-variables and if the dsi_bv_state column exists.

**Table 16 Table Indexes — Oracle**

<b>Table Type</b>	<b>Index Name</b>	<b>Index Type</b>	<b>Indexed columns (in order)</b>	<b>Notes</b>
property	<i>prop_</i> <i>tbl_name_I4</i>	unique, normal	<i>collection_by_</i> <i>var_list_reverse</i> <i>dsi_bv_state</i>	This index will exist only if the collection by-variables are different from the object by-variables and if the <i>dsi_bv_state</i> column exists.
keymap	<i>pk_keymap_</i> <i>tbl_name</i>	unique, normal	<i>local_key_id</i> <i>foreign_server_id</i> <i>foreign_key_id</i>	
keymap	<i>keymap_</i> <i>tbl_name_I1</i>	unique, normal	<i>foreign_server_id</i> <i>local_key_id</i> <i>foreign_key_id</i>	
keymap	<i>keymap_</i> <i>tbl_name_I2</i>	unique, normal	<i>foreign_server_id</i> <i>foreign_key_id</i>	
lkeys	<i>pk_tbl_name</i>	IOT, unique, primary	<i>dsi_key_id_</i> <i>ta_period</i>	
lkeys	<i>tbl_name_I1</i>	unique, normal	<i>ta_period</i> <i>dsi_key_id_</i>	
lkeys	<i>tbl_name_I2</i>	unique, normal	<i>ta_period_old</i> <i>dsi_key_id_</i> <i>ta_period</i>	

where: *collection\_by\_var\_list*

is the list of collection by-variables in their original order.

*collection\_by\_var\_list\_reverse*

is the list of collection by-variables in reverse order.

<i>foreign_key_id</i>	is the <code>dsi_key_id</code> value on the remote server.
<i>foreign_server_id</i>	is the identification for the remote server.
<i>local_key_id</i>	is the <code>dsi_key_id</code> value on the local server.
<i>object_by_var_list</i>	is the list of object by-variables in their original order.
<i>object_by_var_list_reverse</i>	is the list of object by-variables in reverse order.
<i>keymap_tbl_name</i>	is the name of the keymap table.
<i>prop_tbl_name</i>	is the name of the property table.
<i>tbl_name</i>	is the name of the associated table.

## Processing Considerations

The **indexmaint** utility runs against either the entire system without command line options or against a single table with the `-t` option. For each table processed, it verifies that the correct indexes exist with the correct names. If an index is correct but does not have the correct name, the utility renames it according to the guidelines in [Table 15](#). If the utility finds an index by one of the names in [Table 15](#), but does not match the correct index profile, it drops the index and recreates it according to the guidelines. When you run the utility in default mode without options, it runs one of the following commands on each table:

- On a Sybase system, it runs the **update statistics** command.
- On an Oracle system, it runs the **Analyze Table** command.

The **indexmaint** utility may take a considerable amount of time to build these indexes on large tables. After you run the **indexmaint** utility for the entire system the first time, you may choose to place a once-a-day run entry in `trendtimer.sched` that executes **indexmaint** in default mode. This once-a-day entry handles any new tables introduced into the system that do not contain the proper indexes. You can add the entry shown below to the `trendtimer.sched` file to run **indexmaint** once a day in default mode.

```
23:00 - - ${DPIPE_HOME}/bin/indexmaint
```

Note that **indexmaint** only creates and drops indexes on data tables, if necessary. It does not create and drop indexes on property tables; it only updates the statistics on them.

## Examples

### Example 1

This command line entry checks all user data tables in the database for correct indexes and creates any missing indexes.

```
indexmaint
```

### Example 2

This entry rebuilds all the indexes for all of the user data tables in the OVPI system.

```
indexmaint -f
```

### Example 3

This command checks all user tables for the current index settings.

```
indexmaint -l
```

### Example 4

This command checks and possibly fixes only the user data table called *mytable*.

```
indexmaint -t mytable
```

### Example 5

This command displays the help information for the command. The output follows the command.

```
indexmaint -h
```

## install.pkg

The `install.pkg` file provides Package Manager with the basic information needed to install a report pack. For more information about using Package Manager to install report packs, refer to the *Performance Insight Administration Guide*.

This chapter explains the following:

- The report pack directory structure.
- How Package Manager processes the `install.pkg` file.
- The directives that the `install.pkg` file uses.


## Requirements and Restrictions

- The file name must be `install.pkg`.
- Do not use spaces between the directive and the value.
- The **version** directive must appear with the **report\_pack** directive.

## Report Pack Directory Structure

The HP OpenView Performance Insight (OVPI) installation program gives each report pack its own folder in the `$DPIPE_HOME/packages` directory. `$DPIPE_HOME` is the directory into which you installed OVPI. The **packages** directory contains a folder for each report pack and separate folders for the report pack's demo and upgrade versions. Each report pack's folder name must have the extension **.ap**. For example, the name of the folder for the DeviceResource report pack is **DeviceResource.ap**.

Figure 3 shows the directory structure for the **DeviceResource** report pack.



**Figure 3 Directory Structure of the DeviceResource Report Pack**

## Install.pkg Processing

When you use Package Manager to install selected report packs, Package Manager performs the following:

- Processes the `install.pkg` file
- Deploys the reports to the selected Web Access Server

After Package Manager has installed all of the selected reports, it will execute Type Discovery only if you had selected that option during the install wizard setup.



# Install.pkg Directives

The following sections describe the **install.pkg** directives and include examples of their use.

Package Manager processes the directives in the order they appear in the `install.pkg` file.

- The **report\_pack** and **version** directives should always be the first entries in the file.
- Any **dependency**, **software\_version**, and **db\_requirement** directives should follow the **report\_pack** and **version** directives.
- If directive B depends on directive A, remember to put directive A before directive B in the file.

## Install.pkg Syntax Rules

The following rules apply to all `install.pkg` files.

- The comment character is `#`. Any line of an `install.pkg` file with this character in the first position on the line is a comment.
- The `install.pkg` file does not ignore spaces on either side of the colon. Do not put any spaces between the directive and its value.
- All **install.pkg** directives use the following format:

*directive : value*

## Document Conventions for Directives

This section lists the conventions used in this chapter for defining each **install.pkg** directive.

- The description for each directive follows, with each directive starting on a new page in alphabetical order.
- Each directive has a syntax description that uses the following rules:
  - **Bold** items in Courier represent keywords that, if used, must be entered as shown.

- *Italic* items represent parameters for which the user assigns a value.
- If items appear in braces ({}), one of the items must be selected.
- Items that appear in brackets ([ ]) are optional.
- If an item is positional, it must appear in the order shown. If a positional item is missing, it must have a placeholder to mark its position. The placeholder is usually a comma (.). For example, if a directive has 3 positional parameters and the second parameter is missing, the format for the directive is the following:

**directive1=param1,,param3**

If directive has all of the parameters, the format for the directive is the following:

**directive1=param1,param2,param3**

## bin

This directive instructs Package Manager to copy the given file from the directory path that contains the `install.pkg` file to the `$DPIPE_HOME/bin` directory.

### Syntax

**bin:***file\_name*

where: *file\_name* is the name of the file to copy and register.

### Example

To copy a Perl script, **myperl.pl**, to the **bin** directory, add the following directive to the `install.pkg` file:

```
bin:myperl.pl
```

### Usage Notes

Package Manager registers the file as a component of the report pack with a type of **TREND module**.

When the report pack is uninstalled, Package Manager removes the file from the `$DPIPE_HOME/bin` directory.

The `install.pkg` file may have multiple **bin** directives in it.

## database\_procedure

This directive instructs Package Manager to register the specified procedure.

### Syntax

**database\_procedure:***procedure\_name*

where: *procedure\_name* is the SQL name of the procedure to register in the database.

### Example

If a procedure, **myproc**, is to be used by the report pack, add the following directive to the **install.pkg** file:

```
database_procedure:myproc
```

### Usage Notes

Package Manager registers the specified procedure as a **TREND database procedure**.

Note that this directive instructs Package Manager to make a registry entry only. The system actually creates the table when Package Manager executes the **run\_command** directive with the **datapipe\_manager** command. For more information, see [run\\_command on page 238](#).

When the report pack is uninstalled, Package Manager removes the procedure by executing **datapipe\_manager** in **delete** mode.

The `install.pkg` file may have multiple **database\_procedure** directives in it.

## database\_table

This directive instructs Package Manager to register the specified table.

### Syntax

**database\_table:***table\_name*

where: *table\_name* is the SQL name of the table to register in the database.

### Example

If a table, **mycollection**, is to be used by the report pack, add the following directive to the `install.pkg` file:

```
database_table:mycollection
```

### Usage Notes

Package Manager registers the specified table as a **TREND database table**.

Note that this directive instructs Package Manager to make a registry entry only. The system actually creates the table when Package Manager executes the **run\_command** directive with the **datapipe\_manager** command. For more information, see [run\\_command on page 238](#).

When the report pack is uninstalled, Package Manager removes the table by executing **datapipe\_manager** in **delete** mode.

The `install.pkg` file may have multiple **database\_table** directives in it.

## database\_view

This directive instructs Package Manager to register the specified view.

### Syntax

**database\_view:***view\_name*

where: *view\_name* is the SQL name of the view to register in the database.

### Example

If a view, **myview**, is to be used by the report pack, add the following directive to the `install.pkg` file:

```
database_view:myview
```

### Usage Notes

Package Manager registers the specified view as a **TREND database view**.

Note that this directive instructs Package Manager to make a registry entry only. The system actually creates the table when Package Manager executes the **run\_command** directive with the **datapipe\_manager** command. For more information, see [run\\_command on page 238](#).

When the report pack is uninstalled, Package Manager removes the table by executing **datapipe\_manager** in **delete** mode.

The `install.pkg` file may have multiple **database\_view** directives in it.

## db\_requirement

This directive specifies the type of database the report pack requires.

### Syntax

**db\_requirement**:*db\_type*

where: *db\_type* is **Sybase**, **Oracle**, or **All**.

### Example

If the report pack requires an Oracle database to run, add the following directive to the `install.pkg` file:

**db\_requirement:Oracle**

### Usage Notes

The **All** option indicates that the report pack can only run on an Oracle or Sybase database.

The **Oracle** option indicates that the report pack can only run on an Oracle database.

The **Sybase** option indicates that the report pack can only run on a Sybase database.

The check for the current database and the directive values occur in the Report Pack Selection Wizard window of the Package Manager application. If there is a discrepancy between the directive value of the report pack and the current database, Package Manager will not include that report pack in the selection list for possible installation.

## dependency

This directive specifies the name and version of a report pack that the current report pack depends on.

### Syntax

**dependency:***rptpack\_name*, *version*

where: *rptpack\_name* is the name of the report pack required for dependency.

*version* is the version of the report pack required for dependency. The format is either *major.minor* or *major* where *major* is an integer value that represents a major release and *minor* is an integer value that represents a minor release within a major release.

### Example

If the report pack defined in the `install.pkg` file is dependent upon another report pack, **Interface\_Reporting**, version **2.0**, add the following directive to the `install.pkg` file.

**dependency:Interface\_Reporting,2.0**

### Usage Notes

You can use an asterisk (\*) as the *major* or *minor* value for the *version* parameter. When used as a *major* value, its value is **1**. When used as a *minor* value, its value is **0**.

For example, the version for the following directive is 1.0.

**dependency:myReportPack,\*.\***

In this example, the current report pack will depend on a report pack named **myReportPack** that has a version of 1.0.

The report pack specified in this directive must be installed before you use the directive, so that Package Manager can install the current report pack, which is specified in the **report\_pack** directive. Package Manager will pre-select the dependencies and install them first, if they are not already installed.

Furthermore, when Package Manager installs the current report pack, it records the dependency in the report pack registry. See [report\\_pack on page 236](#) for more information about specifying the current report pack.



When you select a report pack to uninstall, Package Manager will pre-select any report pack that is dependent on the selected report pack.

The `install.pkg` file can have multiple **dependency** directives in it.

## Legacy Format

The system will still support the old format of this directive, which is as follows:

**dependency:***rptpack\_name*

where: *rptpack\_name* is the name of the report pack required for dependency.

When you use this format of the directive, a **version** directive must follow it. See the directive [version on page 248](#) for details. Do not include the **version** directive if you are using the other format for this directive.

For example, if the report pack defined in the `install.pkg` file is dependent upon another report pack, **myLanWan** at version 1.5, add the following directives to the `install.pkg` file.

**dependency:myLanWan**  
**version:1.5**



Note that the `install.pkg` file cannot include both formats of the directive, which is with (new) and without (old) the report pack version. Use only one format for all **dependency** directives in each `install.pkg` file.

## **dll**

This directive instructs Package Manager to copy the given file from the directory path that contains the `install.pkg` file to the `$DPIPE_HOME/dll` directory.

### **Syntax**

**dll:***file\_name*

where: *file\_name* is the name of the **dll** file to copy and register.

### **Example**

If the report pack requires a dll file, **new.dll**, add the following directive to the `install.pkg` file:

**dll:new.dll**

### **Usage Notes**

Package Manager registers the file as a component of the report pack with a type of **TREND dll**.

When the report pack is uninstalled, Package Manager removes the file from the `$DPIPE_HOME/dll` directory.

The `install.pkg` file may have multiple **dll** directives in it.

## docdir

This directive instructs Package Manager to copy the documents from the specified directory, which is in the `$DPIPE_HOME` directory, to a newly created directory for the report pack in the `$DPIPE_HOME/docs` directory.

### Syntax

**docdir:***doc\_path*

where: *doc\_path* is the location where the source documents are stored.

### Example

If you want to add the contents of a directory named `$DPIPE_HOME/current_files` that contains the user documents for the `Interface_Reporting` report pack to the `$DPIPE_HOME/docs` directory, add the following directives to the `install.pkg` file:

```
report_pack:Interface_Reporting
docdir:current_files
```

In this example, Package Manager creates the directory, `$DPIPE_HOME/docs/Interface_Reporting`, and then copies the contents of the directory `$DPIPE_HOME/current_files/*` to it.

### Usage Notes

Package Manager prepends `$DPIPE_HOME/` to the directory path specified in the **docdir** directive to locate the source documents. It then uses the value from the **report\_pack** directive and creates a new directory for it under the `$DPIPE_HOME/docs` directory. See [report\\_pack on page 236](#) for more information.

Package Manager registers the directory as a component of the report pack with a type of **TREND documentation directory**.

When a report pack is uninstalled, Package Manager removes the corresponding directory from the `$DPIPE_HOME/docs` directory.

The `install.pkg` file can have multiple **docdir** directives in it. Note, however, that if there are files in the source directories with the same name and path, the files in the last directive will overwrite the files from the previous directives.

## docs

This directive instructs Package Manager to copy the given file from the directory path that contains the `install.pkg` file to the `$DPIPE_HOME/docs` directory.

### Syntax

**docs:***doc\_name*

where: *doc\_name* is the name of the document file to copy and register.

### Example

If a user document, **User\_Guide.doc**, is part of the report pack, add the following directive to the `install.pkg` file:

**docs:User\_Guide.doc**

### Usage Notes

Package Manager registers the file as a component of the report pack with a type of **TREND documentation**.

When a report pack is uninstalled, Package Manager removes the corresponding files from the `$DPIPE_HOME/docs` directory.

The `install.pkg` file may have multiple **docs** directives in it.

## form

This directive instructs Package Manager to deploy the given file from the directory path that contains the `install.pkg` file to the Web Access Server located on the localhost system.

### Syntax

**form:***file\_name*

where: *file\_name* is the name of the form file to deploy and register.

### Example

If the package contains a form file, **myform.frep**, add the following directive to the `install.pkg` file:

**form:myform.frep**

### Usage Notes

This directive applies only when the user of the report pack selects the **Deploy Reports** option while installing the report pack with Package Manager.

Package Manager registers the file as a component of the report pack with a type of **TREND form**.

When the report pack is uninstalled, Package Manager will undeploy the file from the Web Access Server located on the localhost system. This occurs only when the user of the report pack selects the **Undeploy Reports** option while uninstalling the report pack with Package Manager.

The `install.pkg` file may have multiple **form** directives in it.

## formdir

This directive instructs Package Manager to deploy the forms from the specified directory to the Web Access Server located on the localhost system.

### Syntax

**formdir:***forms\_dir*

where: *forms\_dir* is the location where the source forms are stored and the name of the newly created directory in the \$DPIPE\_HOME/forms/deploy/admin directory.

### Example

If you want to add the `Interface_Reporting_Forms` directory that contains the forms to deploy to the `$DPIPE_HOME/forms/deploy/admin` directory, add the following directive to the `install.pkg` file:

```
formdir:Interface_Reporting_Forms
```

### Usage Notes

This directive applies only when the user of the report pack selects the **Deploy Reports** option while installing the report pack with Package Manager.

Package Manager registers the directory as a component of the report pack with a type of **TREND form directory**.

When the report pack is uninstalled, Package Manager will undeploy the directory from the Web Access Server located on the localhost system. This occurs only when the user of the report pack selects the **Undeploy Reports** option while uninstalling the report pack with Package Manager.

## lib

This directive instructs Package Manager to copy the given file from the directory path that contains the `install.pkg` file to the `$DPIPE_HOME/lib` directory.

### Syntax

**lib:***file\_name*

where: *file\_name* is the name of the library file to copy and register.

### Example

If the package contains a TEEL file, **my\_table.teel**, add the following directive to the `install.pkg` file:

```
lib:my_table.teel
```

### Usage Notes

Package Manager registers the file as a component of the report pack with a type of **TREND library file**.

When the report pack is uninstalled, Package Manager removes the file from the `$DPIPE_HOME/lib` directory.

The `install.pkg` file may have multiple **lib** directives in it.

## mibs

This directive instructs Package Manager to copy the given file from the directory path that contains the `install.pkg` file to the `$DPIPE_HOME/mibs` directory.

### Syntax

**mibs**:*MIB\_file\_name*

where: *MIB\_file\_name* is the name of the MIB file to copy and register.

### Example

If the report pack contains a MIB file, **myMib.mib**, add the following directive to the `install.pkg` file:

**mibs:myMib.mib**

### Usage Notes

Package Manager registers the file as a component of the report pack with a type of **TREND mibs**.

When the report pack is uninstalled, Package Manager removes the file from the `$DPIPE_HOME/mibs` directory.

The `install.pkg` file may have multiple **mib** directives in it.



## mw\_collection\_def

This directive instructs Package Manager to install a collection policy.

### Syntax

```
mw_collection_def:mib_path=table_category,poll_interval=frequency,table_name=collection_table,[collection_name=collection_name,]
read_comm=public,username=trendadm,device_type=type_list_name,
hostname=LOCAL
```

where: *table\_category* should match the category for the table being collected.

*frequency* is 5, 10, 15, 20, 60, or 1440.

*collection\_table* is the alias name of the table. Note that this table must already exist.

*collection\_name* is the name of the collection policy. This is an optional parameter; if you do not enter it, the default collection policy name is used.

*type\_list\_name* is the name of the enumerated group for the category of **type**.

### Example

If the package requires a collection definition for a table called **mycollection**, with a type list called **frame\_relay** at an interval of **15** minutes and a collection policy name of **theCollection**, add the following directive to the `install.pkg` file:

```
mw_collection_def:mib_path=Frame,poll_interval=15,table_name=mycollection,read_comm=public,username=trendadm,device_type=frame_relay,hostname=LOCAL,collection_name=theCollection
```

### Usage Notes

Package Manager registers the component to be of type **TREND collector definition**.

The default collection name contains a timestamp.

Note that when the package is uninstalled, no specific action is taken for this component.

## report\_dir

This directive instructs Package Manager to create a target directory for the reports and to copy those reports from the packages directory.

### Syntax

**report\_dir**:*rpt\_dir\_name*

where: *rpt\_dir\_name* is the name of the target reports directory to create.

### Example

The following example instructs Package Manager to create the directory, `$DPIPE_HOME/reports/my_reports`. It then copies the contents of the `my_reports` sub-directory in the directory path that contains the `install.pkg` file to the new directory, `$DPIPE_HOME/reports/my_reports`.

**report\_dir**:`my_reports`

### Usage Notes

This directive instructs Package Manager to create a directory under `$DPIPE_HOME/reports` with the specified report directory name. In addition, Package Manager copies the contents of that sub-directory in the directory path that contains the `install.pkg` file to the newly created directory.

Package Manager creates a registry entry for this directive.

When the report pack is uninstalled, Package Manager removes the subdirectory and its contents from `$DPIPE_HOME/reports`.

This directive has the same function as **reports** directive. See [reports on page 237](#).

## reportlink

This directive instructs Package Manager to deploy the given file from the directory path that contains the `install.pkg` file to the selected Web Access Server.

### Syntax

**reportlink:***file\_name*

where: *file\_name* is the name of the **tlg** file to copy and register.

### Example

If the report pack has links in it in a file named `my_link_grp.tlg`, add the following directive to the `install.pkg` file:

```
reportlink:my_link_grp.tlg
```

### Usage Notes

Package Manager registers the file as a component of the report pack with a type of **TREND report link**.

This directive applies only when the user of the report pack selects the **Deploy Reports** option while installing the report pack with Package Manager.

When the report pack is uninstalled, Package Manager will undeploy the file from the selected Web Access Server. This occurs only when the user of the report pack selects the **Undeploy Reports** option while uninstalling the report pack with Package Manager.

The `install.pkg` file may have multiple **reportlink** directives in it.

You can view links in this file from the Management Console, through Catalog Manager.

## report\_pack

This directive specifies the name of the report pack.

### Syntax

**report\_pack:***rptpack\_name*

where: *rptpack\_name* is the name of the report pack defined in the `install.pkg` file. This name can be up to 50 characters long.

### Example

The report pack will be in the `$DPIPE_HOME/packages/my_report_pack.ap` directory for the 2.1 version, add the following directives to the `install.pkg` file:

```
report_pack:my_report_pack  
version:2.1
```

### Usage Notes

This name must match the name of the directory containing the report pack contents (without the **.ap** extension). This name is the primary identification for the registered report pack.

A **version** directive must follow a **report\_pack** directive. See the directive [version on page 248](#) for details.

The `install.pkg` file may have only one **report\_pack** directive in it.

## reports

This directive instructs Package Manager to create a target directory for the reports and to copy those reports from the packages directory.

### Syntax

```
reports:rpt_dir_name
```

where: *rpt\_dir\_name* is the name of the target reports directory to create.

### Example

The following example instructs Package Manager to create the directory, `$DPIPE_HOME/reports/my_reports`. It then copies the contents of the `my_reports` sub-directory in the directory path that contains the `install.pkg` file to the new directory, `$DPIPE_HOME/reports/my_reports`.

```
reports:my_reports
```

### Usage Notes

This directive instructs Package Manager to create a directory under `$DPIPE_HOME/reports` with the specified report directory name. In addition, Package Manager copies the contents of that sub-directory in the directory path that contains the `install.pkg` file to the newly created directory.

Package Manager creates a registry entry for this directive.

When the report pack is uninstalled, Package Manager removes the subdirectory and its contents from `$DPIPE_HOME/reports`.

This directive has the same function as **report\_dir** directive. See [report\\_dir](#) on page 234.

## run\_command

This directive instructs Package Manager to execute the specified command during installation.

### Syntax

**run\_command:** *command*

where: *command* is the command to execute during installation.

### Example

Suppose a TEEL file, **mycollection.teel**, contained the table definition for the **mycollection** table. Add the following directive to create the table:

```
run_command:{DPIPE_HOME}/bin/datapipe_manager -p create  
-a {DPIPE_HOME}/packages/my_report_pack.ap/mycollection.teel
```

### Usage Notes

Specify the complete path for the *command* along with all required parameters for it.

There is no registry entry for the **run\_command** directive.

The `install.pkg` file may have multiple **run\_command** directives in it.

## run\_sql\_script

This directive instructs Package Manager to execute the specified SQL script during installation.

### Syntax

**run\_sql\_script**:*script\_name*

where: *script\_name* is the name of the SQL script to execute during installation.

### Example

Suppose the package requires an SQL script, **create\_custom\_proc.sql**, that contains a procedure definition. Add the following directive to the `install.pkg` file:

```
run_sql_script:create_custom_proc.sql
```

### Usage Notes

There is no registry entry for the **run\_sql\_script** directive.

The `install.pkg` file may have multiple **run\_sql\_script** directives in it.

## scripts

This directive instructs Package Manager to copy the given file from directory path that contains the `install.pkg` file to the `$DPIPE_HOME/scripts` directory.

### Syntax

**scripts:***file\_name*

where: *file\_name* is the name of the file to copy and register.

### Example

If the report pack uses a summary file, **utilization.sum**, add the following directive to the `install.pkg` file:

**scripts:utilization.sum**

### Usage Notes

Package Manager registers the file as a component of the report pack with one of the following types:

File Suffix	Component Type
.dis	<b>TRENDdiscover file</b>
.pro	<b>TRENDproc file</b>
.qss	<b>TREND qss file</b>
.rnk	<b>TRENDrank file</b>
.rot	<b>TRENDstep file</b>
.sql	<b>SQL script</b>
.sum	<b>TRENDsum file</b>
all others	<b>TREND Other</b>

When the report pack is uninstalled, Package Manager removes the component from the `$DPIPE_HOME/scripts` directory.

The `install.pkg` file may have multiple **scripts** directives in it.



## software\_version

This directive specifies the version string required for the corresponding OVPI software that supports the report pack.

### Syntax

**software\_version:***version\_string*

where: *version\_string* has the following format: *major.minor.point.patch*.

*major* is an integer that represents the major release value.

*minor* is an integer that represents the minor release value.

*point* is an integer that represents the point release value.

*patch* is an integer that represents the patch release value.

### Example

If the corresponding software required to use this report pack is at version **4.6**, add the following directive to the `install.pkg` file:

```
software_version:4.6.0.0
```

### Usage Notes

If the software version of the OVPI software is greater than or equal to the software version specified in this directive, then Package Manager will allow the installation of the report pack.

For example, if the OVPI software version is 4.5.0.3 and the value of the **software\_version** directive is 4.5.0.4, then Package Manager will not allow the installation of this report pack; however, if the OVPI software version is 4.6.0.0 and the value of the **software\_version** directive is 4.5.0.4, then Package Manager will allow the installation of this report pack.

Note that the **version.prp** file, which is located in the `DPIPE_HOME/data` directory, contains the software version of the OVPI software. OVPI compares the *version\_string* value to the software version listed in this file.

Package Manager registers the file as a component of the report pack with a type of **TREND software version**.

*install.pkg*

Note that you cannot use an asterisk (\*) in place of any value. You must enter an integer for each value.

## sql

This directive instructs Package Manager to copy the given file from the appropriate directory for the installed database in the package directory to the `$DPIPE_HOME/scripts/db` directory.

where: *db* is the database where OVPI is connected.

### Syntax

**sql**:*file\_name*

where: *file\_name* is the name of the file to copy and register.

### Example

If the report pack uses an SQL script file, **update.sql**, add the following directive to the `install.pkg` file:

```
sql:update.sql
```

### Usage Notes

The package directory contains a directory for each type of database that OVPI supports. These directories contain the appropriate SQL scripts for the specified databases. Package Manager will locate the specified file from the appropriate directory and copy it to the `$DPIPE_HOME/scripts/db` directory. For example, if OVPI is installed on an Oracle database and you are installing a package with the name ABC, Package Manager will locate the file in the `$DPIPE_HOME/packages/ABC/ABC.ap/Oracle` directory and copy it to the `$DPIPE_HOME/scripts/Oracle` directory. If the `install.pkg` has the **sql** directive as specified in the example section, Package Manager will copy the file `$DPIPE_HOME/packages/ABC/ABC.ap/Oracle/update.sql` as `$DPIPE_HOME/scripts/Oracle/update.sql`.

Package Manager registers the file as a component of the report pack with a type of **OVPI SQL file**.

The `install.pkg` file may have multiple **sql** directives in it.

## tmp

This directive instructs Package Manager to copy the given file from the directory path that contains the `install.pkg` file to the `$DPIPE_HOME/tmp` directory.

### Syntax

**tmp**:*file\_name*

where: *file\_name* is the name of the file to copy and register.

### Example

If the report pack uses the file, **mylog.txt**, add the following directive to the `install.pkg` file:

**tmp:mylog.txt**

### Usage Notes

Package Manager registers the file as a component of the report pack with a type of **TREND temporary file**.

When the package is uninstalled, Package Manager removes the file from the `$DPIPE_HOME/tmp` directory.

The `install.pkg` file may have multiple **tmp** directives in it.

## trend\_timer\_def

This directive contains the necessary information for Package Manager to insert an entry in the **trendtimer.sched** file.

### Syntax

```
trend_timer_def:time_control - - command
```

where: *time\_control* is when the corresponding *command* will run.

*command* is the command to run at the specified time.

See [trendtimer on page 487](#) for details on the allowed time control options.

### Example

The report pack requires that a procedure file, **myfile.pro**, run at 4:00 a.m. daily; add the following directive to the `install.pkg` file:

```
trend_timer_def:24:00+4:00 - - {DPIPE_HOME}/bin/trend_proc  
-f {DPIPE_HOME}/scripts/myfile.pro
```

### Usage Notes

Package Manager registers the entry as a component of type **TRENDtimer definition**.

Remember to fully qualify the command.

When the report pack is uninstalled, Package Manager removes the entry from the **trendtimer.sched** file.

The `install.pkg` file may have multiple **trend\_timer\_def** directives in it.

## uninstall\_cmd

This directive specifies a command that Package Manager runs only when it removes the report pack.

### Syntax

**uninstall\_cmd:***command*

where: *command* is the command to execute during the uninstall process.

### Example

If the report pack removes a directory upon uninstall, add the following directive to the `install.pkg` file:

```
uninstall_cmd:rmdir /tmp/junk
```

### Usage Notes

Package Manager registers this component to the report pack with a type of **TREND uninstall run command**.

The `install.pkg` file may have multiple **uninstall\_cmd** directives in it.

## uninstall\_sql

This directive specifies an SQL script that Package Manager runs only when it removes the report pack.

### Syntax

**uninstall\_sql**:*script\_name*

where: *script\_name* is the name of the SQL script to execute during the uninstall process.

### Example

If the report pack runs a script, **drop\_custom\_procs.sql**, that drops some custom procedures, add the following directive to the `install.pkg` file:

```
uninstall_sql:drop_custom_procs.sql
```

### Usage Notes

The SQL script to be run must exist in the `$DPIPE_HOME/scripts` directory.

Package Manager registers this component to the report pack with a type of **TREND uninstall run sql script**.

The `install.pkg` file may have multiple **uninstall\_sql** directives in it.

## version

This directive specifies the version string of a report pack.

### Syntax

**version:***version\_string*

where: *version\_string* is the version information for the corresponding report pack identified with this directive. The length of the string can be up to 20 characters.

### Example

If **my\_report\_pack** is at version 2.1 and is dependent upon the report pack **myLanWan** at version 1.5, add the following directives to the `install.pkg` file:

```
report_pack:my_report_pack  
version:2.1
```

```
dependency:myLanWan  
version:1.5
```

### Usage Notes

This directive provides the version information for the following reasons:

- To specify the version of the current report pack during installation.
- To specify the required version for a dependency report pack.

The **version** directive must follow the **report\_pack** directive or the **dependency** directive. The combination of the *version\_string* and the *rptpack\_name* in sequential directives uniquely identify the report pack.



## Sample Layout for the File

The following example is a sample layout for the `install.pkg` file. It just shows the possible order for the directives in the file. It does not use any existing file names. The comments appear for clarification.

```
## Datapipe Name and Version  ##
report_pack:xyz
version:1.0

## Datapipe Name Dependencies ##
software_version:1.0.0.0
dependency:abc_datapipe,1.0

## Reports to be installed in {DPIPE_HOME}/reports directory ##
report_dir:xyz

## Create db tables during install. These tables will be removed
during uninstall. ##
database_table:abc_view
database_table:xyz
database_table:Kxyz_property

## Files to install in DPIPE_HOME/lib directory ##
lib:abc_prop.teel

## Files to install in DPIPE_HOME/mibs directory ##
mibs:xyz_abc.mib

## Files to install in DPIPE_HOME/scripts directory ##
scripts:xyz_process.pro
scripts:xyz.sum
scripts:xyz.sql
lib:xyz.teel

## Install the Package ##
run_command:{DPIPE_HOME}/bin/trend_proc
-f {DPIPE_HOME}/packages/xyz/xyz.ap/install.pro

run_command:{DPIPE_HOME}/bin/datapipe_manager -p register
-a {DPIPE_HOME}/packages/xyz/xyz.ap/table_def.teel

## Clean up procedures for uninstall ##
uninstall_sql:xyz_remove_components.sql

## Data Collection Setup ##
```

```
mw_collection_def:mib_path=xyz,poll_interval=15,  
table_name=xyzcollect,read_comm=public,username=trendadm,  
device_type=abc_datapipe,hostname=LOCAL  
  
## Update trendtimer.sched file. ##  
trend_timer_def:1:00+20 - - {DPIPE_HOME}/bin/trend_proc  
-f {DPIPE_HOME}/scripts/abc.pro  
trend_timer_def:24:00+3:00 - - {DPIPE_HOME}/bin/trend_proc  
-f {DPIPE_HOME}/scripts/xyz.pro
```

# log\_backup

Backs up a specified file by moving the file to a new file.

## Syntax

The **log\_backup** command uses the following syntax:

```
log_backup [ -d debug_level ]  
            [ -f source_file_name ]  
            [ -n dir_name ]  
            [ -u ]  
            [ -v ]
```

## Options

The **log\_backup** command has the following options:

- d Set a debug output level. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information. The default is **0**, which means no debug output. Debug output is written to standard output.
- f Specify the complete path for the source file name.  
The default input file name is `$TREND_LOG/trend.log`; if that file does not exist, **log\_backup** looks for `$DPIPE_HOME/log/trend.log`.
- n Specify a new directory to store the file.  
The default directory name is `$TREND_LOG/backup`.
- u This option is the help option, which displays the command-line options for the **log\_backup** command.
- v Displays the version stamp for **log\_backup**.

## Naming Conventions

The default naming convention for the output files uses the complete spelling of the day of the week appended to the source file name with a dot. The default output file name has the following format.

`$TREND_LOG/backup/file_name.prev_day`

- where: *file\_name* is the name of the source file specified with **-f**.  
*prev\_day* is the name of the previous day of the week, such as `sunday` or `wednesday`.

## Back-Up Files Created

The seven default back-up files for the `trend.log` file created by this command are listed below.

```
$TREND_LOG/backup/trend.log.monday
$TREND_LOG/backup/trend.log.tuesday
$TREND_LOG/backup/trend.log.wednesday
$TREND_LOG/backup/trend.log.thursday
$TREND_LOG/backup/trend.log.friday
$TREND_LOG/backup/trend.log.saturday
$TREND_LOG/backup/trend.log.sunday
```

Similarly, **log\_backup** creates the following back-up files for specified files such as `audit.log` and `metrics.log`.

```
$TREND_LOG/backup/audit.log.monday
...
$TREND_LOG/backup/audit.log.sunday

$TREND_LOG/backup/metrics.log.monday
...
$TREND_LOG/backup/metrics.log.sunday
```

## Usage Notes

Entries to execute this utility are stored automatically in the `trendtimer.sched` file during the OVPI installation procedure.

This utility creates a backup file by moving the source file to another file that has the same name appended with a suffix for the previous day of the week. If you specify a new directory name, it will store the file in the same manner in the specified directory.



## mw\_collect

You can use the **mw\_collect** command to poll nodes for SNMP data on an HP OpenView Performance Insight (OVPI) system.

### Requirements and Restrictions

- To collect data with this command, the collector module for the data table must be **MW**.

### Syntax

The **mw\_collect** command uses the following syntax:

```
mw_collect [ -a ]  
             [ -A ]  
             [ -b ]
```

[ **-c** *max\_processes* ]  
[ **-C** *wait\_time* ]  
[ **-d** *debug\_level* ]  
[ **-D** *thread\_wait\_time* ]  
[ **-e** ]  
[ **-E** *clock\_error\_value* ]  
[ **-f** *config\_file* ]  
[ **-F** *min\_disk\_pct* ]  
[ **-g** ]  
[ **-G** *debug\_level\_pm* ]  
[ **-h** *hostname* ]  
[ **-H** *alternate\_poller\_name* ]  
**-i** *interval*  
[ **-I** *check\_index* ]  
[ **-k** ]  
[ **-K** *suppress\_spikes* ]  
[ **-L** ]  
[ **-M** *minimum\_filter* ]  
[ **-n** ]  
[ **-N** *retry\_interval* ]  
[ **-o** *timeout* ]  
[ **-p** *max\_entries\_per\_pdu* ]  
[ **-P** *snmp\_port* ]  
[ **-q** *log\_info\_level* ]  
[ **-Q** *name* ]  
[ **-r** *retries* ]  
[ **-R** *min\_rows* ]  
[ **-s** *round\_factor* ]  
[ **-S** *snmp\_version* ]  
[ **-t** *table\_name* ]  
[ **-u** ]



```

[ -V ]
[ -w high_water_mark ]
[ -W high_water_mark_log ]
[ -X ]
[ -Y ]
[ -Y delta_time ]
[ -z child_debug_level ]
[ -Z debug_log_bcpgateway ]

```



The following options are currently available in this version of OVPI for compatibility with previous versions of OVPI.

- j** To direct the poller to use the SNMP version as defined in the database. It uses the SNMP version associated with each node.
- T** To direct the poller to not perform fast time conversion.

## Option Categories

The following command line options are available for the parent poller.

**Table 17 mw\_collect Option Categories**

Category	Options
Typical	<b>-a, -b, -c, -C, -D, -e, -F, -g, -h, -H, -i, -k, -n, -o, -p, -P, -Q, -r, -R, -s, -S, -t</b>
Miscellaneous	<b>-d, -f, -L, -q, -u, -V, -w, -W, -Z, -y, -z</b>
Raw-to-Rate	<b>-A, -E, -G, -I, -K, -M, -N, -X, -Y</b>

## Options

The **mw\_collect** command has the following options:

- a** Directs the child collectors of **mw\_collect** to output the collected data in ASCII format. You may want to do this for debugging purposes.
- A** Enables archiving of raw data. The default is no archiving. When you use this option, it turns on archiving. The archive function stores the collected data in a raw data table. This option is in UPPERCASE. This option is equivalent to the **@bArchive=1** parameter in **trendpm**.
- b** Forces regeneration of definition files and worktable. The poller analyzes the structure of the table to be collected and creates definitions about how to load data into database for the **bcp\_gateway** process. This is a one-time process most of the time. However, when the poller realizes that the structures of the data table or related property tables have changed, it regenerates the **bcp\_gateway** process definitions and worktable. The **-b** option forces the regeneration of these definition files, and cleans up any internal database objects used during data loading. See the discussion for the **-g** option on [page 260](#) for more information. See the discussion for the **-k** option on [page 262](#) for more information.
- c** Specifies the number of collection processes to run concurrently. When **mw\_collect** starts, it starts child processes that actually do the collections. The default is **5**. You can reduce SNMP collection cycles by increasing this number.

- c** Specifies the number of minutes that each child process can run. The system kills the child process if it runs longer than the specified number of minutes.  
The default is **30** minutes.  
This option is in UPPERCASE.
- d** Sets the debug output level for the parent instance of **mw\_collect**. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is **0**, which means no debug output. Debug output is written to standard out. You should use this option only for testing in coordination with HP Technical Support due to the additional overhead it places on **mw\_collect**.  
The **-z** and **-Z** options set the debug level for the child processes of **mw\_collect**. The **-d**, **-z**, and **-Z** options can be used together to control the debug level of parent and child processes independently.
- D** This option specifies how many seconds the parent thread should wait for signals from the collector and bcp\_gateway threads.  
It is normal to get thread\_wait timeout messages in the log file when waiting for signals from the bcp\_gateway or **trendpm** thread due to potential long running jobs when writing to the database. The program exits when a thread\_timeout occurs, unless the thread\_timeout occurred when all collector jobs are finished and only bcp\_gateway or **trendpm** threads remained. In this case, the timeout only appears in the trend.log file.  
The default is the same value as the **-c** timeout value, which is **1800** seconds. For example, if the **-c** value is **2** (2 minutes), then the **-D** value defaults to **120** (120 seconds).  
This option is in UPPERCASE.
- e** Turns on **GETBULK** when using SNMP-V2.  
When the poller uses SNMP-V2, you can opt to use the GETBULK request instead of GETNEXT when getting SNMP data.

- E Sets the percentage level for valid data. The value is the percentage of difference between the delta values of two Received Timestamps and two System Uptimes. These statistics come from two consecutive raw data samples.

For example, if r1 and s1 are the Received Timestamp and System Uptime for the first sample, and r2 and s2 are the Received Timestamp and System Uptime for the second sample, then the calculation for the value is  $((r2 - r1) - (s2 - s1)) * 100 / (r2 - r1)$ . During processing, if the calculated value for the samples exceeds the value set by this option then the samples are rejected.

The default value is **10**.

This option is in UPPERCASE.

This option is equivalent to the **@zerror** parameter in **trendpm**.

- f Specifies the name of the configuration file that contains additional parameters. See [Configuration File on page 269](#) for descriptions of the parameters.

- F Specifies the minimum disk space (as percent of total disk space) that must exist on the disk where the \$COLLECT\_HOME directory resides. If less space exists on the directory, **mw\_collect** does not execute.

The default is **5**, which represents 5 percent.

This option is in UPPERCASE.

- g Use 3.5.x compatibility. That is, use the same method for inserting data into the table as version 3.5.x and earlier.

The **-g** option loads data into archive (raw) tables directly. The `bcp_gateway` definition file contains the setting for the **-g** option. This means that if you already invoked **mw\_collect** without the **-g** option and you need the **-g** option, then use the **-b** option to regenerate the definition file. Similarly, if you already invoked **mw\_collect** with the **-g** option and you do not need the **-g** option, then use the **-b** option to regenerate the definition file. Otherwise, **mw\_collect** uses the same setting for the **-g** option currently in effect when you originally generated the definition file.

- G** Sets the debug output level for the **trendpm** process of **mw\_collect**. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.

The default is **0**, which means no debug output.

Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **mw\_collect**.

This option is in UPPERCASE.

This option is equivalent to the **@debug\_level** parameter in **trendpm**.
- h** Names the host to be polled, which must be an SNMP-manageable device. This name will be saved in the database along with the data returned from the node, so in order to be consistent with other data, use the same node name format used when entering nodes in the database.
- H** Specifies an alternate poller name. When you run **mw\_collect** in distributed mode, with the **-n** option, the poller compares the local hostname to the **Poll From** field in the polling policy. When you use the **-H** option, **mw\_collect** compares the **Poll From** field in the polling policy to the alternate poller name.

This option is in UPPERCASE.

See [Distributed Polling on page 277](#) for more information.
- i** Is the Collection ID. **mw\_collect** executes the entries in the polling policy that have this value in their interval field. How frequently **mw\_collect** is actually run depends on the configuration of **trendtimer**, but the idea is to be consistent so that a collection request with a collection ID of **5** is run every 5 minutes. See [File Locks on page 275](#) for additional information.

This option is required.

- I** Specifies whether to use existing indices on the upload table or to drop existing indices and then recreate them. The value **1** means that the existing indices on the upload table are used. The value **0** means that the existing indices are dropped and then recreated. If the value is **1** and the proper indices are missing then the raw-to-delta process fails. The default is **0**.  
This option is in UPPERCASE.  
This option is equivalent to the **@bCheck\_index** parameter in **trendpm**.
- k** Populates the property tables (but not the data tables) for the devices you are polling.  
The **bcp\_gateway** definition file contains the setting for the **-k** option. This means that if you already invoked **mw\_collect** without the **-k** option and you need the **-k** option, then use the **-b** option to regenerate the definition file. Similarly, if you already invoked **mw\_collect** with the **-k** option and you do not need the **-k** option, then use the **-b** option to regenerate the definition file. Otherwise, **mw\_collect** uses the same setting for the **-k** option currently in effect when you originally generated the definition file.
- K** Specifies whether to reject samples if there are spikes. A spike is defined when a counter is manually reset, the difference of two consecutive samples from a counter exceeds the spike threshold, and the second sample is less than the first sample. The value of the spike threshold is  $2^{31}$  for 32-bit counters or  $2^{51}$  for 64-bit counters. Remember if the difference of the samples is negative; account for the rollover of the counter by adding  $2^{32}$  for 32-bit counters or  $2^{52}$  for 64-bit counters.  
Valid values for *suppress\_spikes* are:  
**1** Rejects samples if a spike occurs.  
**0** Does not reject samples. The default is **0**.  
This option is in UPPERCASE.  
This option is equivalent to the **@bSuppress\_spike** parameter in **trendpm**.
- L** Specifies that the collected data be stored locally instead of in the OVPI database. When you use this option, **mw\_collect** uses any previously saved collection definitions, and does not use the database.  
This option is in UPPERCASE.

- M** Sets the *minimum\_filter* value. The procedure rejects the sample if the delta value of a counter falls below this value.  
The default value is **-1**, which means to accept the entire sample.  
This option is in UPPERCASE.  
This option is equivalent to the **@line\_suppress\_value** parameter in **trendpm**.
- n** Enables distributed polling. If this option is used, **mw\_collect** executes the collection request only if the **Poll From** field in the polling policy for this collection request matches the hostname of the machine on which **mw\_collect** is running. If you omit this option, **mw\_collect** executes all polling requests whose interval matches the value of the **-i** option, regardless of the hostname specified to do the polling in the polling instructions.  
You can set an alternate hostname to poll with the **-H** option. See [Distributed Polling on page 277](#) for more information.
- N** Sets the *retry\_interval*, which is the number of seconds the procedure must wait in order to acquire a lock on an upload table.  
The default value is **10**, which is 10 seconds.  
This option is in UPPERCASE.  
This option is equivalent to the **@retry\_interval** parameter in **trendpm**.
- o** Number of seconds **mw\_collect** is to wait for a response after sending an SNMP request.  
The default is **1** second. (SNMP timeout.)
- p** The number of SNMP variables to include in the varbind list in the GETNEXT PDU (Protocol Data Unit) request. It is possible to generate a GETNEXT request that yields a response that is too long to transmit.  
The default value is **20**.
- P** This option allows the collection of SNMP data from the specified port rather than the default SNMP port of **161**.  
This option is in UPPERCASE.

- q** Sets the log information level for the parent instance of **mw\_collect**. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information. The default is **0**, which means no log information for the parent instance of **mw\_collect**.
- If the `$TREND_LOG` environment variable is set, then the log is written in the directory specified by the `$TREND_LOG` environment to a log file named `parent_collect_dbg.log`; the path and file name is `$TREND_LOG/parent_collect_dbg.log`.
- If the `$TREND_LOG` environment variable is not set, then the log is written to the same log file name in the `$DPIPE_HOME/log` directory; the path and file name is `$DPIPE_HOME/log/parent_collect_dbg.log`.
- You can modify the log file name using the **-Q** option.
- Q** Specifies the *name* for the ROOT of the trace log file. You can use this option to change the name of the log file, as follows:
- `pathname_pid_ppid_polltime_dbg.log`
- where: *path* is `$TREND_LOG` if the environment variable is set; otherwise, it is `$DPIPE_HOME/log`.
- name* is the name of the file that you supply.
- pid* is the process id number for this process.
- ppid* is the process id number of the parent process.
- polltime* is the number of seconds since 01/01/1970 00:00.
- When you use this option, set the **-q** option to a value greater than **0**. This option is in UPPERCASE.
- r** Specifies the *retries*, which is the number of times **mw\_collect** resends an SNMP request before assuming the target node is not going to respond. The default value is **5**. (SNMP retries)
- R** Sets the minimum number of rows to collect before starting the loading of data into database. The number of rows is an approximation, since there is an assumption that each row is 500 bytes.
- The default value is **1000** rows, which means that the loading of the file into the database starts when the size is 500,000 bytes (500 \* 1000). This option is in UPPERCASE.



- s** This option rounds off the collection time (`ta_period`). If the **mw\_collect** parent kicks off a collection at 3:07, and if you are using the default collection option of **300** seconds (5 minutes), the actual `ta_period` value for the collection will be recorded as 3:05.
- s** Specifies the SNMP version. This option is in UPPERCASE.  
Valid values: **1** for SNMP V1  
**2** for SNMP V2C.  
This option overrides the values read from the database.
- t** Specifies the *table\_name*, which is the name of the MIB table that you want to collect. The data table must already exist in the database.
- u** Displays the command line formats for **mw\_collect**.
- v** Displays the version stamp for **mw\_collect**.  
This option is in UPPERCASE.
- w** Specifies the *high\_water\_mark*. The high water mark stops collection of data when the database-used size reaches the specified percentage.  
Valid values are **1 - 100**.  
The default parameter is **90** for 90%.
- w** Specifies the *high\_water\_mark\_log*. The high water mark stops collection of data when the log-used size reaches the specified percentage. Valid values are **1 - 100**.  
The default parameter is **90** for 90%.  
This option is in UPPERCASE.
- x** This option turns off **trendpm** capability.  
This option is in UPPERCASE.
- y** This option disables the calculation of `total count` for `bcp_gateway` metrics.

- Y** Specifies which clock to use to calculate Delta Time.  
Valid values are:

  - 1** Directs the procedure to use System Uptime to calculate Delta Time.
  - 0** Directs the procedure to use the `received_ts` column for the calculation.

The default is **0**.  
This option is in UPPERCASE.  
This option is equivalent to the `@bDelta_time` parameter in **trendpm**.
  
- z** Sets the debug level for child collector processes.  
Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is **0**, which means no debug output.  
Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **mw\_collect**.
  
- z** This option specifies whether to turn on debugging or logging or both for the `bcp_gateway` process. When the logging option is turned on, the information is written to the log file. The name of the log file varies depending on which environment variable is set.  
If the `$TREND_LOG` environment variable is set, then the log is written in the directory specified by the `$TREND_LOG` environment to a log file named `bcp_gateway_dbg.log`; the path and file name is `$TREND_LOG/bcp_gateway_dbg.log`.  
If the `$TREND_LOG` environment variable is not set, then the log is written to the same log file name in the `$DPIPE_HOME/log` directory; the path and file name is `$DPIPE_HOME/log/bcp_gateway_dbg.log`.  
Valid values for this option are:

  - 1** Turn on logging.
  - 2** Turn on debugging.
  - 3** Turn on both logging and debugging.

This option is in UPPERCASE.



If any logging option is set to **on** and you are running `trendtimer.sched`, add an entry to `trendtimer.sched` to back up log files. To do that, add the following command to `trendtimer.sched`:

```
DPIPE_HOME}/bin/log_backup -f input_file_name
```

## Usage Notes

**mw\_collect** is the OVPI SNMP polling application for generic MIB tables. Its simplest use is to collect a specific table once from a single node, and store the information in the OVPI database. Fully utilized, **mw\_collect** follows user-defined instructions for the following:

- To poll a dynamic list of nodes anywhere on the network for data at regular intervals.
- To store the results on a local or remote system depending on who requests the information.
- Provide the ability to run without the database in cache mode.

The **mw\_collect** command invokes the **mw\_collect** parent poller. The **mw\_collect** parent poller, in turn, invokes multiple child pollers. Each child poller collects a single node/table combination. The **-c** option specifies the number of child pollers that run concurrently.

There are extra parameters that you can set in **mw\_collect** that supplement the command-line options for **mw\_collect**. The parameters are in a configuration file. You can specify the name of this file with the **-f** option on the command-line. See [Configuration File on page 269](#) for descriptions of the parameters and the file.

To collect data with this command, the setting for the **CollectorModule** statement in the TEEL definition file for the data table must be **MW**.

## Terms

This section defines the common terms that apply to **mw\_collect**.

<b>parent poller</b>	The main part of the SNMP poller. It is responsible for determining what to collect, starting child processes that perform collections and load data into database, and providing all the <i>how to rules</i> to these processes. See parent poller information on <a href="#">page 268</a> .
<b>child poller</b>	A child process that is spawned by the parent poller. It is responsible for the actual SNMP collection. A child poller deals with only one agent (node) and one table at a time. See child poller information on <a href="#">page 269</a> .
<b>bcp_gateway</b>	A child process that is spawned by the parent poller. It is responsible for loading collected data into the database. For more information on bcp_gateway see <a href="#">page 269</a> and <a href="#">page 276</a> .
<b>data database</b>	A database server where the poller will store collected data, and from where the poller will read table definitions.
<b>topology database</b>	A database server from which the poller will read all the node information; that is, views, types, and nodes.
<b>caching poller</b>	A feature that allows the poller to run without a database. See <a href="#">Directory Structure on page 279</a> .
<b>instance of poller or Collector ID</b>	A collection process for a given interval. The instance of the poller is identified by the interval. See <a href="#">File Locks on page 275</a> for more information.

## mw\_collect Command

- The **mw\_collect** command invokes the **mw\_collect** parent poller, which controls the collection process. The parent poller is responsible for the following:

- It determines what information to collect and from which device. It reads the *what to collect* information from the database and records this data in local files. If access to the database is not available the parent poller reads the local files instead.
- It has the ability to start multiple children.
- It starts and controls child processes that collect data and load it into the database.
- It supplies rules on how to process the data to child processes.
- It starts the raw-to-rate process on the collected data.

Each child poller collects a single node and table combination.

- A child poller does not have access to the database.
- A child poller is responsible for actual collection of data, but the parent must tell the child what methods to use.

When the child poller finishes, the data that is collected is appended to the latest existing holding file for loading into the OVPI database. The latest holding file is loaded into the database when the file is at least 500,000 bytes or every child poller has finished. See [Directory Structure on page 279](#) for a discussion of the directories in which these holding files are stored before they are loaded into the OVPI database.

**mw\_collect** calls the following procedures for each table and destination database pair:

- The `bcp_gateway` procedure updates property and data tables in the OVPI database.
- The **trendpm** procedure generates rate data in the OVPI database after **mw\_collect** collects all the data and stores it in the database for a particular table.

## Configuration File

The configuration file for **mw\_collect** contains additional parameters that you can set for **mw\_collect** to process. You only need to set these parameters in special circumstances such as at the direction of HP Technical Support. The `-f` option specifies the name of the file. See [Syntax on page 270](#) for the rules about the file and [Parameters on page 271](#) for the descriptions of the parameters in the file.

Note that the configuration file requires only the parameters that you want to set.

## Syntax

The following rules apply to the **mw\_collect** configuration file.

- The parameters can be in any case.
- The values may be case sensitive.
- The parameters can appear in any order.
- The format is *parameter = value*.

This list of parameters shows the syntax for them in alphabetical order. They appear in mixed case in this list for readability.

```
BatchSize = num_rows
CategoryName = name
CollectDefName = file_name
CollectHome = directory_name
DataDB = server_name
DontLock = 1
DSQUERY = value
DumpBcpG = 1
Element = name [, option ... ]
Feeder = value
GatewayWatchdog = num_seconds
GroupName = name
IgnoreSnmpDB = 1
KeepData = 1
max_tran_row_cnt = num_rows
Method = value
NoNewObjects = 1
PollTime = num_seconds
TopDB = server_name
```

**TrendpmRetryCount** = *num\_retries*

**TrendpmRetryInterval** = *num\_seconds*

## Parameters

This list of parameters provides the descriptions for them. You can use any case. They appear in this list in mixed case for readability.

**Table 18 mw\_collect Configuration File Parameters**

Parameter	Description
<b>BatchSize</b>	Specifies the size of the batch for bcp_gateway to process, which is the number of rows.
<b>CategoryName</b>	Specifies the category of the group to be polled. If you set this parameter, you must also set the <b>GroupName</b> parameter.
<b>CollectDefName</b>	Specifies the name of the CollectDef file that will contain the cached collection definitions.
<b>CollectHome</b>	Overrides the value in the \$COLLECT_HOME environment variable for this process. See <a href="#">Directory Structure on page 279</a> for more information.
<b>DataDB</b>	Specifies the server name for the Data database. See <a href="#">Terms on page 268</a> for more information.
<b>DontLock</b>	Specifies that <b>mw_collect</b> not lock the files in the \$COLLECT_HOME directory. See <a href="#">File Locks on page 275</a> for more information. The default is <b>0</b> , which is to lock the files. Use <b>1</b> to set, which is to not lock the files.
<b>DSQUERY</b>	Overrides the setting of the default database.

**Table 18 mw\_collect Configuration File Parameters**

<b>Parameter</b>	<b>Description</b>
<b>DumpBcpG</b>	<p>Specifies that <b>mw_collect</b> write the BCP rules to standard output without processing, which means that it will not load the data into the database.</p> <p>The default is <b>0</b>. Use <b>1</b> to set.</p>
<b>Element</b>	<p>Specifies an element that <b>mw_collect</b> passes to a child processor. The child processor determines the format for this statement; for example, you can use the following format to pass a host name to <b>dpipe_snmp</b>:</p> <p><i>element = name, community, version, retry, timeout</i></p> <p>The configuration file may have multiple <b>element</b> parameters in it.</p>
<b>Feeder</b>	<p>Specifies the name of the Feeder, which is the method that defines how the data is collected. Values are:</p> <p><b>EE ee_collect</b>  <b>HST vantage_collect</b>  <b>MW mw_collect</b>  <b>SR pa_collect</b></p>
<b>GatewayWatchdog</b>	<p>Specifies the timeout of the gateway watchdog in seconds. Use <b>0</b> for no timeout. This parameter applies only to Windows systems.</p> <p>The default is <b>900</b> seconds.</p>
<b>GroupName</b>	<p>Specifies the name of the group to be polled. If you set this parameter, you must also set the <b>CategoryName</b> parameter.</p>



Table 18 mw\_collect Configuration File Parameters

Parameter	Description
<b>IgnoreSnmpDB</b>	<p>Specifies that <b>mw_collect</b> ignore the SNMP version value from the database.</p> <p>You can use this parameter to turn off the default, which is equivalent to the <b>-j</b> option in earlier versions, when you set the value to <b>1</b>. The default is <b>0</b>. Use <b>1</b> to ignore.</p>
<b>KeepData</b>	<p>Specifies that <b>bcp_gateway</b> keep the input data files instead of deleting them by default. The default is <b>0</b>. Use <b>1</b> to keep the files.</p>
<b>max_tran_row_cnt</b>	<p>Passes this value, which is the <b>@max_tran_row_cnt</b> parameter, to <b>trendpm</b>. See <a href="#">@max_tran_row_cnt on page 444</a> for more information.</p> <p>HP strongly recommends that you use the default value. If this value is too low, it may affect performance; if this value is too high, it may affect concurrency.</p>
<b>Method</b>	<p>Relates to the <b>ByVarInfo</b> TEEL statement; it specifies how to process the data. Valid values are:</p> <p><b>MTD_HST</b> Specifies that the poller collects data from the intersection of the objects between the <i>property_table</i> value in the <b>ByVarInfo</b> statement and the collection group.</p> <p><b>MTD_HST2</b> Specifies that the poller collects data from the intersection of the objects between the <i>property_table</i> value in the <b>ByVarInfo</b> statement and the collection group along with the rest of the objects in the collection group.</p>

**Table 18 mw\_collect Configuration File Parameters**

<b>Parameter</b>	<b>Description</b>
<b>NoNewObjects</b>	Specifies that <b>mw_collect</b> only load the data, and not insert any new managed objects into the corresponding property table. The default is <b>0</b> . Use <b>1</b> to set.
<b>PollTime</b>	Passes the start time of the polling cycle value to a child process. This value is the number of seconds since midnight of January 1, 1970.
<b>TopDB</b>	Specifies the server name for the Topology database. See <a href="#">Terms on page 268</a> for more information.
<b>TrendpmRetryCount</b>	Passes this value, which is the <b>@retry_count</b> parameter, to <b>trendpm</b> . See <a href="#">@retry_count on page 445</a> for more information.
<b>TrendpmRetryInterval</b>	Passes this value, which is the <b>@retry_interval</b> parameter, to <b>trendpm</b> . The value for the <b>-N</b> option on the <b>mw_collect</b> command line overrides this setting during processing. For more information, see the <b>-N</b> option on <a href="#">page 263</a> or <a href="#">@retry_interval on page 445</a> .

## By-Variables

In the current OVPI release, the by-variable replaces the current unique key, which is the combination of the `target_name` and `table_key` columns. A combination of by-variable columns in the property table uniquely defines an object. For more information, refer to [By-Variables on page 475](#).

## File Locks

**mw\_collect** allows only one instance of collection for a particular Collection ID to run at the same time. Furthermore, only one `bcp_gateway` process runs at a time for a particular Collection ID, `table_name`, and data database combination.

When the parent poller **mw\_collect** starts, it attempts to place an exclusive lock on the running file in the `COLLECT_HOME/feeder/collection_id` directory. If the lock fails, the poller assumes that the previous instance of the poller is still running and exits. The parent poller releases the lock on the running file when every collector child finishes. Note that the lock releases before the poller finishes loading all the data into the database so that the polling continues even though the data loading portion is not finished.

Similarly, when **mw\_collect** starts a `bcp_gateway` process, it tries to place a lock on `COLLECT_HOME/feeder/collection_id/table_name_dbname.running`. If the lock fails, the parent poller assumes that the previous job is still running and does not attempt to start the `bcp_gateway` process. The data is stored locally.

## Local Storage of Data

**mw\_collect** provides the ability to perform collection without a database. It saves the collection definition locally.

After the poller connects to the database, it refreshes the database with the saved information. Note that the poller always uses information from the database when it is available, and does not then rely on locally saved information.

The following table summarizes this feature:

Process	Failure Point	Result Cache Features
Parent Poller	Failed to connect at startup.	Use cached information for collection. Store data locally.
Parent Poller	During initialization, lost connection.	Use cached information (in most cases). Store data locally.

<b>Process</b>	<b>Failure Point</b>	<b>Result Cache Features</b>
Parent Poller	Determined during initialization that database is full or transaction log is full.	Store data locally.
bcp_gateway	Failed to connect to a given database.	Returns code to calling parent thread. Parent will not attempt to load data into this database during this cycle. Data is stored locally.
bcp_gateway	Lost connection to database, database is full, or transaction log is full.	Removes successfully loaded data from the input file; deletes entire file when operating in ASCII mode (-a). Returns code to calling parent thread. (see above) Depending on when the database connection was lost or the database became full during the bcp_gateway process, the removal of successfully loaded data may not be accurate. This may cause insertion of duplicate data into raw data, which will fail (if there are indexes) and generate error messages in trend.log. bcp_gateway ignores this error message and continues loading new data.
bcp_gateway	Failed loading data for other reason than above.	Removes the entire input file.

## Interval Polling

**mw\_collect** is mainly used to poll for SNMP data at regular intervals. When invoked, **mw\_collect** reads the polling control table in the database for the list of instructions whose intervals match the value of the **-i** option on the **mw\_collect** command line. Each entry in the list specifies a MIB table to be collected and the device group, specific device, or specific instance from a device to be polled for the table.

This polling policy information is entered automatically when you install a report pack. You can also enter or modify polling policy information through the **Polling Policy Manager**. Refer to the *Performance Insight Administration Guide* for information about using Package Manager to install a report pack and for information about specifying your own polling policies.

**mw\_collect** queries the database for the list of fields in the table to be collected. Then, for each node to be polled, it obtains the node SNMP Read Community string from the database and polls the node for those fields. Once all target devices have been polled, the returned data is written to the database and **mw\_collect** exits.

## Distributed Polling

In order to distribute the polling load to the most efficient locations, you can install **mw\_collect** on any system in your network.

In the simplest case, all polling instructions, node information, and data tables are on a single system and all polling is done from that system. It is also possible to maintain polling instructions on one system; store target device names, their community strings, and polling View and Type lists on a second system; execute polling from a third system; store the returned data on a fourth system; and run reports against the returned data from a fifth system. This is the most extensive example of distributing the application. However, any combination from the simplest to the most extensive is possible and can be configured according to your requirements.

The **trendtimer** program invokes **mw\_collect**. By default, **mw\_collect** uses the default database entry in the `systems.xml` file to determine the database to be queried for polling instructions. Since any system can access a central database from anywhere on the network to get its list of polling instructions, you can define the polling policy for an entire network from one central location. As an alternative, you can define polling locally for each region within that region.

You can access information about the nodes to poll, including their community strings and their membership in polling View and Type lists, in **Polling Policy Manager**. Refer to the *Performance Insight Administration Guide* for more information.

The polling instructions include the name of the system that is intended to do the polling.

- When **mw\_collect** is run with the **-n** option, it checks this field to see if the hostname matches the name of the system on which it is running. If they do not match, **mw\_collect** does not execute the poll.
- The **-H** option is run with the **-n** option to specify an alternate poller name. When **-H** option is used, then **mw\_collect** compares the **Poll From** field in the polling policy to the *alternate\_poller\_name*.
- Without the **-n** option, **mw\_collect** ignores the hostname field and runs the poll regardless of any system name specified there.

The group to which the user who defined a polling request belongs also specifies the name of the database to which the collected data is to be written. Once the polls are completed, **mw\_collect** loads the collected data into that database.

## Direct Polling

You can use **mw\_collect** to immediately collect particular MIB table values from a particular node on demand by executing **mw\_collect** with the **-t** and **-h** options from the command line.

## Multiple Pollers

If you have multiple pollers, it is recommended that you edit the `trendtimer.sched` file and add the **-X** option to all **mw\_collect** commands; this prevents the pollers from running the raw to delta processing invoked by the **trendpm** command. If you do not do this, you could see performance issues.

You should edit the file for all of the pollers *except* one. For example, if you have a satellite system polling (that is, OVPI's Performance Manager component is installed on this system) with three remote pollers, edit the file for all of the pollers, leaving the satellite system's file as is. If the satellite system is not polling, then edit the file for two of the pollers leaving one as is.

To turn off raw to delta processing:

- 1 Edit the `trendtimer.sched` file.
- 2 Add the `-x` option to all of the `mw_collect` lines in the file.

For example, if the lines in your file read as follows:

```
5 -- {DPIPE_HOME}/bin/mw_collect -n -i 5 -K 1
10 -- {DPIPE_HOME}/bin/mw_collect -n -i 10 -K 1
15 -- {DPIPE_HOME}/bin/mw_collect -n -i 15 -K 1
20 -- {DPIPE_HOME}/bin/mw_collect -n -i 20 -K 1
60 -- {DPIPE_HOME}/bin/mw_collect -n -i 60 -K 1
24:00+1:00 -- {DPIPE_HOME}/bin/mw_collect -n -i 1440 -K 1
```

Edit the lines to look like the following:

```
5 -- {DPIPE_HOME}/bin/mw_collect -n -i 5 -K 1 -X
10 -- {DPIPE_HOME}/bin/mw_collect -n -i 10 -K 1 -X
15 -- {DPIPE_HOME}/bin/mw_collect -n -i 15 -K 1 -X
20 -- {DPIPE_HOME}/bin/mw_collect -n -i 20 -K 1 -X
60 -- {DPIPE_HOME}/bin/mw_collect -n -i 60 -K 1 -X
24:00+1:00 -- {DPIPE_HOME}/bin/mw_collect -n -i 1440 -K 1 -X
```

- 3 Save the file.

## Log File

**mw\_collect** makes log entries in the file `trend.log`. This file is in either the `$TREND_LOG` directory, if the `$TREND_LOG` environment variable is set, or the `$DPIPE_HOME/log` directory if the `$TREND_LOG` environment variable is not set.

## Directory Structure

Temporary files, data files, and cached polling policy files that **mw\_collect** uses are stored under the following directory:

**\$COLLECT\_HOME/feeder\_name/collection\_id**

where:

- \$COLLECT\_HOME** Is the directory that the `$COLLECT_HOME` environment variable points to (typically, `$DPIPE_HOME/collect`).
- feeder\_name* Always has the value **MW** for instances of **mw\_collect**.
- collection\_id* Identifies the collection ID, which is a number corresponding to the value of the **-i** option on the **mw\_collect** command.

One of the elements under this directory is the **BCP** directory, which is where data that is ready to be loaded into the database is stored. In this case, the format for this directory is as follows:

**\$COLLECT\_HOME/feeder\_name/collection\_id/BCP**

## Examples

The following examples show the format of the **mw\_collect** command that you can use for the different methods of polling.

### Interval Polling

#### Example 1

To have **mw\_collect** execute all collection requests with an interval id of **10**, invoke **mw\_collect** with the command line:

```
mw_collect -i 10
```

#### Example 2

To have **mw\_collect** execute all collection requests with an interval id of **5** on the machine on which **mw\_collect** is installed, putting a maximum of 20 MIB variables in each packet, trying to poll the node a maximum of 3 times, and waiting 2 seconds between polling attempts, invoke **mw\_collect** with the command line:

```
mw_collect -n -i 5 -p 20 -o 2 -r 3
```

Interval polling entries for **mw\_collect** are in the following file:



```
$DPIPE_HOME/lib/trendtimer.sched
```

## Direct Polling

To have **mw\_collect** poll a node called **foo.HP.com** for the MIB-II ifEntry table, use the command:

```
mw_collect -h foo.HP.com -t mib-II_ifEntry -i 59
```

In this example, **mw\_collect** uses the **-h** and **-t** options to collect the data, and uses the **-i** option, which is the Collection ID, for the file names; see [Directory Structure on page 279](#). In this case, **mw\_collect** will not read from the database polling policy that corresponds to interval **59**.



## node\_manager

The **node\_manager** command is a stand-alone utility that allows you to manage nodes, types, and views. It also enables you to manage all relevant SNMP properties for nodes.

There is another method to add nodes to an OVPI system; you can import nodes from a file or define nodes using **Polling Policy Manager**. Refer to the *Performance Insight Administration Guide* for more information.

### Requirements or Restrictions

- An error occurs if more than one of the following options appears on the command line at the same time: **-import**, **-export**, **-delete**, **-remove**.
- An error occurs if the **-file** option does not appear with one of the following options on the command line at the same time: **-import**, **-delete**, **-remove**.

## Syntax

The **node\_manager** command uses the following syntax:

```
node_manager [ -database db_name ]
             [ -debug dbug_level ]
             [ { -delete
                 -export
                 -import
                 -remove } ]
             [ -file file_name ]
             [ -help ]
             [ -insert_only ]
             [ { -v
                 -version } ]
```

## Options

The **node\_manager** command has the following options:

**-database** This option identifies the database where the changes will occur. The database must appear in the list of available database servers. See the Web Access Server in the *Performance Insight Administration Guide* for more information about adding database servers to the list. The default is the database identified as the default in the database server list.

- debug** Use this option to set the debug output level. Values of **1**, **2**, or **3** are valid. The higher the number, the more detailed the information. Debug output writes to standard output. Only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **node\_manager**.  
The default is no debug output.
- delete** Use this option to delete one or more nodes from the system. It requires the **-file** option to identify the file that contains the list of nodes to delete. This option ignores all other parameters in the file except the *node\_name*. See [Delete on page 287](#) for more information.  
This option cannot appear on the command line when the **-import**, **-export**, or **-remove** option appears on the command line.
- export** Use this option to generate a file containing the nodes in the current node catalog. The output file will also contain any type or view assignments for the nodes. Use the **-file** option to specify the output file name; otherwise, **node\_manager** writes the data to standard output. If the specified output file already exists, the system will overwrite the file. See [ASCII File on page 288](#) for the format of the file. See [Export on page 288](#) for more information.  
This option cannot appear on the command line when the **-import**, **-delete**, or **-remove** option appears on the command line.
- file** This option identifies the file name, which is the text file that contains the information about the nodes, types, and views to import, delete, or remove. If the file is not in the current working directory, you must specify the fully qualified path to the file. See [ASCII File on page 288](#) for details on setting up this file.  
This is a required option when the **-import**, **-delete**, or **-remove** option appears on the command line.

- help** This option is the help option, which displays the command-line options for the **node\_manager** command.
- import** Use this option to import nodes, assign the corresponding SNMP attributes, and populate any type or view lists. It requires the **-file** option to identify the file that contains the list of nodes to import. See [Import on page 287](#) for more information.

This option cannot appear on the command line when the **-export**, **-delete**, or **-remove** option appears on the command line.
- insert\_only** Use this option with the **-import** option to add nodes that do not already exist. If any of the nodes already exist, **node\_manager** will skip them and not update them.
- remove** Use this option to remove one or more nodes from one or more type or view lists. It requires the **-file** option to identify the file that contains the list of nodes with the corresponding type or view lists to remove. This option ignores all other parameters in the file except the *node\_name*, *type\_name*, and *view\_name*. See [Remove on page 287](#) for more information.

This option cannot appear on the command line when the **-import**, **-delete**, or **-export** option appears on the command line.
- v** Use this option to display the current version of **node\_manager**.

This option is in UPPERCASE.
- version** Use this option to display the current version of **node\_manager**.

# Usage Notes

This section provides a brief description of the different modes available, the parameters for the associated ASCII file, and using the **node\_manager** command.

## Modes of Operation

The **node\_manager** command has four modes of operation: import, delete, remove, and export.

### Import

The *import* mode provides the ability to add nodes to the system. It also provides the ability to assign the SNMP attributes to the node as well as add the node to specified type and view lists.

### Delete

The *delete* mode provides the ability to delete all the nodes in the associated file from the system. When **node\_manager** deletes a node from the system, it deletes the node from all enumerated group list memberships. It will not immediately delete any node that has dependencies; it marks those nodes for deletion at a later time. A node has a dependency when a property table has a record that references that node. When there are no more records that reference that node, **node\_manager** will delete that node the next time it runs in delete mode.

In this mode, **node\_manager** uses only the *node\_name* in the associated file and ignores all other attributes. Note, however, that each node in the file must have a value or a placeholder for every attribute associated with that node. See [ASCII File on page 288](#) for more information about the file.

### Remove

The *remove* mode provides the ability to remove the nodes in the associated file from the specified type and view lists. Since a node can be a member of multiple type and view lists, the node may appear multiple times in the file.

In this mode, **node\_manager** uses the *node\_name*, *type\_name*, and *view\_name* parameters in the associated file and ignores all other attributes. Note, however, that each node in the file must have a value or a placeholder for every attribute associated with that node. See [ASCII File on page 288](#) for more information about the file.

## Export

The *export* mode provides the ability to create a file of the existing nodes on the system.

## ASCII File

Three of the four modes of operation require an ASCII file. Some of the modes require only a subset of the parameters, but each record in the file must have a valid value or a placeholder for every parameter in the record. The ASCII file that contains a list of nodes must be in the following format:

*node\_name, read\_community, write\_community, type\_name, view\_name, snmp\_v1\_flag, snmp\_v2\_flag, node\_status, desc, snmp\_profile, port\_num, num\_retries, timeout\_sec, num\_oids, get\_bulk\_size*

Use the comma delimiter as placeholder for any parameter that is missing; otherwise, the system will skip the record. The descriptions for the parameters in the file follow:

*node\_name* This parameter specifies the name of the node or the IP address for the node.

This parameter must appear in the file for the **-import**, **-delete**, or **-remove** mode.

*read\_community* This parameter specifies the read community string for the node. If the profile for the read and write community string pair does not exist, the system will create it by concatenating the specified read and write community strings from this file. You can view the list of profiles from the Edit Community String Profiles window in **Polling Policy Manager**.

The default value is **public**.



- write\_community* This parameter specifies the write community string for the node. If the profile for the read and write community string pair does not exist, the system will create it by concatenating the specified read and write community strings from this file. You can view the list of profiles from the Edit Community String Profiles window in **Polling Policy Manager**. The default value is **private**.
- type\_name* This parameter specifies the name of the type list that contains the list of nodes to poll. If you specify this field in the file, you must specify the group name. In **-import** mode, if this name does not exist, **node\_manager** will create a type list with the specified name. This is the same name as the Group Name on the Edit Type Group window from **Polling Policy Manager**.  
If this parameter is blank, **node\_manager** will not assign this node to a type list group or remove this node from a type list group.
- view\_name* This parameter specifies the name of the view list that contains the list of nodes to poll. If you specify this field in the file, you must specify the group name. In **-import** mode, if this name does not exist, **node\_manager** will create a view list with the specified name. This is the same name as the Group Name on the Edit View Group window from **Polling Policy Manager**.  
If this parameter is blank, **node\_manager** will not assign this node to a view list group or remove this node from a view list group.
- snmp\_v1\_flag* This parameter specifies that the node supports the SNMP protocol when the value is **1**.  
The valid values are **0** and **1**.  
The default value is **1**.

<i>snmp_v2_flag</i>	<p>This parameter specifies that the node supports the SNMPv2 protocol when the value is <b>1</b>. The valid values are <b>0</b> and <b>1</b>. The default value is <b>0</b>.</p> <p><b>Note:</b> If are unsure if a node supports SNMPv2, leave this parameter blank.</p>
<i>node_status</i>	<p>This parameter indicates the status of the node upon import. The valid values are <b>0</b> for inactive and <b>1</b> for active. The default value is <b>1</b>.</p>
<i>desc</i>	<p>This parameter provides a description for the node. If this parameter is blank, the value is blank, which appears as a space in the export file. The length can be up to 255 characters.</p>
<i>snmp_profile</i>	<p>This parameter specifies the name of the SNMP profile assigned to the node. If this profile exists, <b>node_manager</b> will assign the profile to the node and ignore the following parameters; otherwise, <b>node_manager</b> will create the profile using the following parameters and then assign the profile to the node.</p> <p>When this parameter is blank, the value is <b>default</b>, and <b>node_manager</b> ignores the following parameters.</p>
<i>port_num</i>	<p>This parameter specifies the SNMP port number for the new SNMP profile. The default value is <b>161</b>.</p>
<i>num_retries</i>	<p>This parameter specifies the number of retries for the new SNMP profile. The default value is <b>5</b>.</p>
<i>timeout_sec</i>	<p>This parameter specifies the number of milliseconds allowed for timing out on an SNMP request. The default value is <b>1000</b>.</p>

<i>num_oids</i>	This parameter specifies the number of OIDs to include in a PDU for the new SNMP profile. The default value is <b>20</b> .
<i>get_bulk_size</i>	This parameter specifies the size to use for a get bulk SNMPv2 request. The default value is <b>50</b> .



If any of the parameters contain invalid values, an error message occurs and the process terminates at that point. The system does not check the rest of the file for additional errors. If an error occurs, verify that all records contain valid values before you resubmit the file; otherwise, an error will occur again. Verify that there are no blank lines; otherwise, an error message occurs.

## Using the `node_manager` Command

This section shows some formats of the command for the various modes.

- If you enter the **node\_manager** command without any options, the system will display an error message followed by the help information.
- To display the syntax and options for this command, enter:  
**node\_manager -help**
- To display the version information for this command, enter:  
**node\_manager -V** or **node\_manager -version**
- To import a list of nodes, enter the following command:  
**node\_manager -import -file *file\_name***  
where: *file\_name* is the name of the ASCII file that contains the list of nodes with their corresponding attributes to import.
- To import a list of nodes and only add those nodes that do not already exist, enter the following command:  
**node\_manager -import -insert\_only -file *file\_name***  
where: *file\_name* is the name of the ASCII file that contains the list of nodes with their corresponding attributes to import.

- To delete a list of nodes, enter the following command:

```
node_manager -delete -file file_name
```

where: *file\_name* is the name of the ASCII file that contains the list of nodes to delete.

- To remove a list of nodes from type and view lists, enter the following command:

```
node_manager -remove -file file_name
```

where: *file\_name* is the name of the ASCII file that contains the list of nodes with their corresponding type and view list names to remove.

- To export a list of nodes to the screen, enter the following command:

```
node_manager -export
```

- To export a list of nodes to a file, enter the following command:

```
node_manager -export -file file_name
```

where: *file\_name* is the name of the ASCII file that will contain the list of existing nodes on the system.

## Examples

This section has examples that show each mode of **node\_manager**. They have the following characteristics:

- All examples refer to the sample file used in the import example.
- Any information that appears about the **-file** option for one example also applies to other examples, such as the need for a qualified path.

### Import Examples

#### Example 1

To import a list of nodes from a file named `node_in.txt`, enter the following command:

```
node_manager -import -file node_in.txt
```

The following is an example of the contents for the input file, `node_in.txt`:

```
tst_a,,,,,,,,,,,,,
tst_b,,,tp_lst1,vw_lst2,,,,dsc2,,,,,
tst_c,public,private,,,1,0,1,dsc3,smp_1,161,10,500,20,50
tst_d,public,private,,,1,0,1, ,default,161,15,100,20,50
tst_e,public,private,tp_lst1,,1,0,1,dsc5,default,,,,,
tst_f,public,private,,vw_lst2,1,0,1, ,default,,,,,
tst_g,,,,,,,,,,,,,
```

### Example 2

To add nodes that do not already exist to the node list on the database named **powder2** from a list of nodes in a file named `n_in.txt` on the database named **bear**, which is on a different system, enter the following command:

```
node_manager -import -file n_in.txt -database bear -insert_only
```

## Export Examples

### Example 1

If you want to export a list of nodes to a file named `node_current.txt`, enter the following command:

```
node_manager -export -file node_current.txt
```

The following is an example of the contents of the output file, `node_current.txt`:

```
tst_b,public,private,tp_lst1,,1,0,1,dsc2,default,161,5,1000,20,50
tst_e,public,private,tp_lst1,,1,0,1,dsc5,default,161,5,1000,20,50
tst_b,public,private,,vw_lst2,1,0,1,dsc2,default,161,5,1000,20,50
tst_f,public,private,,vw_lst2,1,0,1, ,default,161,5,1000,20,50
tst_a,public,private,,,1,0,1, ,default,161,5,1000,20,50
tst_c,public,private,,,1,0,1,dsc3,smp_1,161,10,500,20,50
tst_d,public,private,,,1,0,1, ,default,161,5,1000,20,50
tst_g,public,private,,,1,0,1, ,default,161,5,1000,20,50
```

Note that the node **tst\_b** appears in the list twice because it has both type and view lists associated with it; and node **tst\_c** has different SNMP properties because it has a different SNMP profile, but **tst\_d** does not because it uses the default SNMP profile.

### Example 2

To export a list of nodes that are on the database named **bear** to a file named `node_bear.txt`, which will be on the system entering the command and has the database named **powder2**, enter the following command:

```
node_manager -export -file node_bear.txt -database bear
```

## Remove Examples

### Example 1

If you want to remove a list of nodes using a file named `node_rem.txt`, enter the following command:

```
node_manager -remove -file node_rem.txt
```

An example of the contents of the input file, `node_rem.txt`, are the following:

```
tst_e,public,private,tp_lst1,,1,0,1,,default,,,,,  
tst_f,public,private,,vw_lst2,1,0,1,,default,,,,,
```

### Example 2

Note that you need to fully qualify the path for the file if it is in a different directory. For example, if the file were in the **lists** directory from the **D** drive on a Windows machine, you would enter the following command:

```
node_manager -remove -file d:\lists\node_rem.txt
```

## Delete Example

To delete a list of nodes using a file named `node_out.txt`, enter the following command:

```
node_manager -delete -file node_out.txt
```

An example of the contents of the input file, `node_out.txt`, are the following:

```
tst_b,,,tp_lst1,vw_lst2,,,,dsc2,,,,,  
tst_c,public,private,,,1,0,1,dsc3,smp_1,161,10,500,20,50  
tst_d,public,private,,,1,0,1,,default,,,,,  
tst_g,,,,,,,,,,,,,
```

## Error Messages

This section describes some of the messages that can occur from **node\_manager**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
  - The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- If the following error message appears, there is a command-line syntax error. This means that required options are missing or there are multiple mode options on the same line.

```
A mode of operation is required.
Exiting program with code 1.
```

Verify that the command specifies the mode option or that the following mode options do not appear on the command line at the same time:

**-import, -export, -delete, -remove.**

- If the following error message appears, the database specified with the **-database** option on the command line does not exist.

```
Connection URL not found.
Exiting program with code 3.
```

Verify the spelling of the database name. If the spelling is correct, you can add the database using the Web Access Server.

- If the following error message appears, the specified record in the file has a syntax error.

```
Exception: Wrong number of delimiters on line n.
Exiting program with code 4.
```

Check the specified record in the file and fix the error. Verify that the record has either a value or a placeholder for all 15 parameters or that the line is not blank.

- ❑ If the following error message appears, the file name specified on the command line in the **-file** *file\_name* option does not exist.

File *file\_name* does not exist.  
Exiting program with code 2.

Verify the spelling of the file name or that the file exists in the specified location. You may have to supply a fully qualified path name with the file name.

- ❑ If the following informational message appears, the record for the specified *node\_name* in the file is missing a type or view group list name. The system is skipping the record.

Node *node\_name* does not have a type or view specified - skipping.

Check the specified record in the file and fix the error. Verify that the record has either an existing type or view group list name.

- ❑ If the following informational message appears, a record in the file is providing an incorrect type group list name. The system is skipping the record.

The type group *type\_name* does not exist - skipping.

Check the record in the file for the specified *type\_name*. Enter the correct type group list name for the record.

- ❑ If the following informational message appears, a record in the file is providing an incorrect view group list name. The system is skipping the record.

The view group *view\_name* does not exist - skipping.

Check the record in the file for the specified *view\_name*. Enter the correct view group list name for the record.







## ovpi\_bulk\_copy

You can use the **ovpi\_bulk\_copy** command to bulk load or extract data on an HP OpenView Performance Insight (OVPI) system.

### Requirements and Restrictions

- An error occurs if more than one of the following options appears on the command line at the same time: **-infile**, **-outfile**.
- An error occurs if the **-table** option does not appear on the command line.

## Syntax

The **ovpi\_bulk\_copy** command uses the following syntax:

```
ovpi_bulk_copy  [ -bcp "option_list" ]
                [ -database server_name ]
                [ -debug dbug_level ]
                [ -ftc "char" ]
                [ -help ]
                { -infile } file_name
                { -outfile }
                [ -logfile result_file ]
                [ -sqlldr "option_list" ]
                -table table_name
                [ -v ]
                [ -version ]
```

## Options

The **ovpi\_bulk\_copy** command has the following options:

- bcp** This option specifies the command line options for the Sybase **bcp** command. Refer to the Sybase documentation for the valid options.  
You must use double quotes to enclose the options.  
This option may appear on the command line with the **-sqlldr** option.
- database** This option specifies the name of the database server that will import or export data.  
The default for this option is the default database server.

- debug** Use this option to set the debug output level. The higher the number, the more detailed the information. Debug output writes to standard out. Use this option only for testing in coordination with HP Technical Support due to the additional overhead it places on **ovpi\_bulk\_copy**. The default is no debug output.
- ftc** This option specifies the field delimiter, which is the character that separates the fields, in the input or output file. This option allows you to identify the character in the file so that it will be the same on all database servers. You must use double quotes to enclose the character.
- help** This option is the help option, which displays the command-line syntax for the **ovpi\_bulk\_copy** command. This option overrides all other options on the command line.
- infile** This option specifies the name of the file that contains the data to be loaded into the specified table. This file name may contain a relative or fully qualified path name; it may also contain the substitution keyword, **{DEVENDOR}**. See [Usage Notes on page 302](#) for more information. This option or the **-outfile** option is a required option.
- logfile** This option specifies the name of the file that contains any output generated from the **bcp** or **sqldr** command. If this name is not a fully qualified path name, the file will be in the current working directory. If you do not specify a name, the results of the output will be in standard out.
- outfile** This option specifies the name of the file that will contain the data from the specified table. This file name may contain a relative or fully qualified path name; it may also contain the substitution keyword, **{DEVENDOR}**. See [Usage Notes on page 302](#) for more information. This option or the **-infile** option is a required option.

- sqlldr** This option specifies the command line options for the Oracle **sqlldr** command. Refer to the Oracle documentation for the valid options.  
You must use double quotes to enclose the options.  
This option may appear on the command line with the **-bcp** option.
- table** This option specifies the name of the table to import or export.
- v** Use this option to display the current version of the **ovpi\_bulk\_copy** utility. This option overrides all other options on the command line, except the help option.  
This option is in UPPERCASE.
- version** Use this option to display the current version of the **ovpi\_bulk\_copy** utility. This option overrides all other options on the command line, except the help option.

## Usage Notes

This command dynamically determines whether to execute the Sybase **bcp** command or the Oracle **sqlldr** command, depending on the database type.

You can use the substitution keyword, **{DBVENDOR}**, in a path name when the database type is part of the path. For example, if you want to import data from a file with the name **load\_data\_1** in the **system1/Sybase/load** directory on a Sybase database or in the **system1/Oracle/load** directory on an Oracle database, you can use the following path and file name with the **-infile** option:

```
-infile system1/{DBVENDOR}/load/load_data_1
```

## Using the ovpi\_bulk\_copy Command

This section shows some formats of the command for the various tasks.

- If you enter the **ovpi\_bulk\_copy** command without any options, the system will display the help information.
- To display the syntax and options for this command, enter the following command.

```
ovpi_bulk_copy -help
```

- To display the version information for this command, enter the following command.

```
ovpi_bulk_copy -V
```

- To import a specific data file on the default database into a specific table and send the output to standard out, enter the following command.

```
ovpi_bulk_copy -infile file_name -table table_name
```

where: *file\_name* is the path and file name of the data file to import.

*table\_name* is the name of the table that will contain the data.

- To import a specific data file on a specific database into a specific table and send the output to a specific file, enter the following command.

```
ovpi_bulk_copy -infile file_name -table table_name  
-database server_name -logfile result_file_name
```

where: *file\_name* is the path and file name of the data file to import.

*table\_name* is the name of the table that will contain the data.

*server\_name* is the name of database server where the table resides.

*result\_file\_name* is the name of the file that contains the output from the program that loads the data.

- To export data from a specific table on a specific database into a specific data file and send the output to a specific file, enter the following command.

```
ovpi_bulk_copy -outfile file name -table table_name  
-database server_name -logfile result_file_name
```

where: *file\_name* is the path and file name of the data file to export.  
*table\_name* is the name of the table that will contain the data.  
*server\_name* is the name of database server where the table resides.  
*result\_file\_name* is the name of the file that contains the output from the program that loads the data.

- To export data from a specific table using a specific set of options with the **sqlldr** command on an Oracle system and the **bcp** command on a Sybase system and send the output to standard out, enter the following command.

```
ovpi_bulk_copy -outfile file_name -table table_name
-sqlldr "option_list" -bcp "option_list"
```

where: *file\_name* is the path and file name of the data file to export.  
*table\_name* is the name of the table that will contain the data.  
*option\_list* is the list of options separated by spaces that the **sqlplus** or **isql** utility will use.

- To export data from a specific table using a specific set of options with the **sqlldr** command on an Oracle system and the **bcp** command on a Sybase system with both files using the same delimiter and send the output to standard out, enter the following command.

```
ovpi_bulk_copy -outfile file_name -table table_name
-sqlldr "option_list" -bcp "option_list" -ftc char
```

where: *file\_name* is the path and file name of the data file to export.  
*table\_name* is the name of the table that will contain the data.  
*option\_list* is the list of options separated by spaces that the **sqlplus** or **isql** utility will use.  
*char* is the character that separates the fields in the output file.



## Example

The following example illustrates a use of the **ovpi\_bulk\_copy** tool.

### Example: Copy Data to an Oracle Database Server

To copy the contents of the file `c:/tmp/Oracle/data` to a table called **dep** on an Oracle database server called **caspianc**, use the following command:

```
ovpi_bulk_copy -infile c/tmp/{DBVENDOR}/data -table dep
-database caspianc -ftc ","
```

## Error Messages

This section describes some of the messages that can occur from **ovpi\_bulk\_copy**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.

- If the following error message appears, the **-table** option is missing on the command line.

Missing the required '-table' option.

Verify the **-table** option with the name of the table is on the command line.

- If the following error message appears, the specified *server\_name* is missing in the `systems.xml` file.

The database server *server\_name* was not found in the `systems.xml` file.

Verify the spelling of the *server\_name* specified in the **-database** option on the command line. Check the System Manager on the Web Access Server to determine if the specified *server\_name* is in the `systems.xml` file. Refer to the *Performance Insight Administration Guide* for more information about System Manager.

- If the following error message appears, the default database server name is missing in the `systems.xml` file.

The default database server was not found in the `systems.xml` file.

Check the System Manager on the Web Access Server to determine if the default server name is in the `systems.xml` file. Refer to the *Performance Insight Administration Guide* for more information about System Manager.

## ovpi\_run\_sql

You can use the **ovpi\_run\_sql** command to run SQL scripts on an HP OpenView Performance Insight (OVPI) system.

### Requirements and Restrictions

- An error occurs if the **-sqlscript** option does not appear on the command line.

## Syntax

The **ovpi\_run\_sql** command uses the following syntax:

```

ovpi_run_sql      [ -database server_name ]
                   [ -debug dbug_level ]
                   [ -help ]
                   [ -isql "option_list" ]
                   [ -logfile result_file ]
                   [ -sqlplus "option_list" ]
                   -sqlscript sql_script_name
                   [ -v ]
                   [ -version ]

```

## Options

The **ovpi\_run\_sql** command has the following options:

- database**      This option specifies the name of the database server that will run the SQL script.  
The default for this option is the default database server.
- debug**          Use this option to set the debug output level. The higher the number, the more detailed the information. Debug output writes to standard out. Use this option only for testing in coordination with HP Technical Support due to the additional overhead it places on **ovpi\_run\_sql**.  
The default is no debug output.
- help**            This option is the help option, which displays the command-line syntax for the **ovpi\_run\_sql** command. This option overrides all other options on the command line.

- isql** This option specifies the command line options for the Sybase **isql** command. Refer to the Sybase documentation for the valid options.  
You must use double quotes to enclose the options.  
This option may appear on the command line with the **-sqlplus** option.
- logfile** This option specifies the name of the file that contains any output generated from the specified script. If this name is not a fully qualified path name, the file will be in the current working directory.  
If you do not specify a name, the results of the output will be in standard out.
- sqlplus** This option specifies the command line options for the Oracle **sqlplus** command. Refer to the Oracle documentation for the valid options.  
You must use double quotes to enclose the options.  
This option may appear on the command line with the **-isql** option.
- sqlscript** This option specifies the name of the SQL script to run. This name may contain a relative or fully qualified path name; it may also contain the substitution keyword, **{DBVENDOR}**. See [Usage Notes on page 310](#) for more information.  
This is a required option.
- v** Use this option to display the current version of the **ovpi\_run\_sql** utility. This option overrides all other options on the command line, except the **-help** option.  
This option is in UPPERCASE.
- version** Use this option to display the current version of the **ovpi\_run\_sql** utility. This option overrides all other options on the command line, except the **-help** option.

## Usage Notes

This command dynamically determines whether to execute the Sybase **isql** command or the Oracle **sqlplus** command depending on the installed database type.

You can use the substitution keyword, **{DBVENDOR}**, in a path name when the database type is part of the path. For example, if you want to run an SQL script with the name **sql\_script\_task\_1** in the **system1/Sybase/task** directory on a Sybase database or in the **system1/Oracle/task** directory on an Oracle database, you can use the following path and file name with the **-sqlscript** option:

```
-sqlscript system1/{DBVENDOR}/task/sql_script_task_1
```

## Using the ovpi\_run\_sql Command

This section shows some formats of the command for the various tasks.

- If you enter the **ovpi\_run\_sql** command without any options, the system will display the help information.
- To display the syntax and options for this command, enter the following command.

```
ovpi_run_sql -help
```

- To display the version information for this command, enter the following command.

```
ovpi_run_sql -v
```

- To run a script on the default database and send the output to standard out, enter the following command.

```
ovpi_run_sql -sqlscript sql_script_name
```

where: *sql\_script\_name* is the path and file name of the SQL script to run.

- To run a script on a specific database and send the output to a specific file, enter the following command.

```
ovpi_run_sql -sqlscript sql_script_name -database server_name  
-logfile result_file_name
```

where: *sql\_script\_name* is the path and file name of the SQL script to run.

*server\_name* is the name of database server where the script will run.

*result\_file\_name* is the name of the file that will contain the output from running the specified script.

- To run a script on a specific database while using a specific set of options with the **sqlplus** command on an Oracle database and send the output to a specific file, enter the following command.

```
ovpi_run_sql -sqlcscript sql_script_name -database server_name
-sqlplus "option_list" -logfile result_file_name
```

where: *sql\_script\_name* is the path and file name of the SQL script to run.

*server\_name* is the name of database server where the script will run.

*option\_list* is the list of options separated by spaces that the **sqlplus** utility will use.

*result\_file\_name* is the name of the file that will contain the output from running the specified script.

- To run a script using a specific set of options with the **sqlplus** command on an Oracle database and the **isql** command on a Sybase database and send the output to standard out, enter the following command.

```
ovpi_run_sql -sqlcscript sql_script_name -sqlplus "option_list" -isql
"option_list"
```

where: *sql\_script\_name* is the path and file name of the SQL script to run.

*option\_list* is the list of options separated by spaces that the **sqlplus** or **isql** utility will use.

## Example

To run a script with the name **sql\_script\_task\_1** in the **system1/Sybase/task** directory on a Sybase database and in the **system1/Oracle/task** directory on an Oracle database on the default database, enter the following command.

```
ovpi_run_sql -sqlcscript system1/{DBVENDOR}/task/sql_script_task_1
```

## Error Messages

This section describes some of the messages that can occur from **ovpi\_run\_sql**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
  - The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- If the following error message appears, the default database server name is missing in the `systems.xml` file.

The default database server was not found in the `systems.xml` file.

Check the System Manager on the Web Access Server to determine if the default server name is in the `systems.xml` file. Refer to the *Performance Insight Administration Guide* for more information about System Manager.

- If the following error message appears, the specified `server_name` is missing in the `systems.xml` file.

The database server `server_name` was not found in the `systems.xml` file.

Verify the spelling of the `server_name` specified in the **-database** option on the command line. Check the System Manager on the Web Access Server to determine if the specified `server_name` is in the `systems.xml` file. Refer to the *Performance Insight Administration Guide* for more information about System Manager.

- If the following error message appears, the **-sqlscript** option is missing on the command line.

Missing the required '-sqlscript' option.

Verify the **-sqlscript** option with the name of the SQL script is on the command line.



## pa\_collect

You can use the HP OpenView Performance Insight (OVPI) **pa\_collect** command to collect data from an OpenView Performance Agent (OVPA) or an OpenView Operations Agent (OVOA) on an OVPI system.

### Syntax

The **pa\_collect** command uses the following syntax:

```
pa_collect [ -d debug_level ]  
            [ -E sum_level ]  
            -i interval  
            [ -K end_date ]  
            [ -q log_info_level ]  
            [ -Q name ]  
            [ -u ]  
            [ -v ]
```

## Options

The **pa\_collect** command has the following options:

- d** Sets the debug output level for the parent instance of **pa\_collect**. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is **0**, which means no debug output. Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **pa\_collect**.
- E** Sets the summarization level for the data in minutes. Use this value to modify the granularity of the data rather than changing the polling interval. For example, if **i 60** sets the frequency of the polling to an hour and you want to gather the data at 15-minute intervals instead, you can add **-E 15** to the command line to modify the granularity, as follows:

```
pa_collect -i 60 -E 15
```

Note that when you increase the granularity for collecting the data, it does increase the collection time because you are collecting more data.

The valid values are the number of minutes and can be the following:

<b>0</b>	non-summarized data
<b>5</b>	5-minute summarized data
<b>15</b>	15-minute summarized data
<b>30</b>	30-minute summarized data
<b>60</b>	1-hour summarized data
<b>180</b>	3-hour summarized data
<b>360</b>	6-hour summarized data
<b>720</b>	12-hour summarized data
<b>1440</b>	1-day summarized data
<b>10080</b>	1-week summarized data

The default value is **60**.

This option is in UPPERCASE.

- i Is the Collection ID. **pa\_collect** executes the entries in the polling policy that have this value in their **Interval** field. How frequently **pa\_collect** is actually run depends on the configuration of **trendtimer**, but the idea is to be consistent so that a collection request with a collection ID of **5** is run every 5 minutes. See [File Locks on page 275](#) for additional information.  
This option is required.
  
- k Specifies the last date that the data resides in the OVPI database. The **dpipe\_pa** child collector uses this value as the start time for collecting data from the agent. The format of the date is *yyyymmdd*.  
where: *yyyy* is a 4-digit year  
*mm* is a 2-digit month  
*dd* is a 2-digit day  
This option is in UPPERCASE.
  
- q Sets the log information level for the parent instance of **pa\_collect**. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is **0**, which means no log information for the parent instance of **pa\_collect**.  
If the `$TREND_LOG` environment variable is set, then the log is written in the directory specified by the `$TREND_LOG` environment to a log file named `pa_collect_dbg.log`; so the path and file name is `$TREND_LOG/pa_collect_dbg.log`.  
If the `$TREND_LOG` environment variable is not set, then the log is written to the same log file name in the `$DPIPE_HOME/log` directory; so the path and file name is `$DPIPE_HOME/log/pa_collect_dbg.log`.  
You can modify the log file name using the **-Q** option.

- Q Specifies the *name* for the ROOT of the trace log file. You can use this option to change the name of the log file, as follows:  
*pathname\_dbg.log*  
where: *path* is \$TREND\_LOG if the environment variable is set; otherwise, it is \$DPIPE\_HOME\log.  
*name* is the name of the file that you supply.  
When you use this option, you must set the **-q** option to a value greater than 0.  
This option is in UPPERCASE.
- u Displays the command line formats for **pa\_collect**.
- v Displays the version stamp for **pa\_collect**.  
This option is in UPPERCASE.

## Usage Notes

The **pa\_collect** command is a wrapper around the **mw\_collect** command; this means that the **pa\_collect** command processes the options on its command line that are listed in this chapter first and then passes the results and any other **mw\_collect** options that appear on its command line to **mw\_collect** to complete the processing.

There is only one child collector, which is **dpipe\_pa**, for **pa\_collect**. This command works in conjunction with another utility, which is **pa\_discovery**; see [pa\\_discovery on page 317](#) for more information.

To collect data with this command, the collector module for the data table must be **SR**.

## pa\_discovery

The HP OpenView Performance Insight (OVPI) **pa\_discovery** command is a utility that allows you to discover an OpenView Performance Agent (OVPA) or an OpenView Operations Agent (OVOA) on an OVPI system. It does the following:

- Retrieves a list of managed nodes via the OVPI **node\_manager**.
- Determines if the agent exists.
- Gathers information from the existing agents.
- Creates a data file that **ee\_collect** will use to load the data into OVPI.

## Requirements or Restrictions

- Requires access to the OVPI **node\_manager**.
- An error occurs if the **-file** and the **-node** options appear on the command line at the same time.

## Syntax

The **pa\_discovery** command uses the following syntax:

```
pa_discovery  [ -d debug_level ]
               [ { -file file_name
                   -node node_name } ]
               [ -help ]
               [ -t trace_level ]
               [ { -v
                   -version } ]
```

## Options

The **pa\_discovery** command has the following options:

- d**            Use this option to set the debug output level. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
  
Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **pa\_discovery**.  
The default is **0**, which means no debug output.
- file**        This option identifies the name of an existing file that contains a list of nodes to discover. You must specify the fully qualified path to the file. See [node\\_manager on page 283](#) for a description of the format.  
  
This option may not appear on the command line with the **-node** option.
- help**        This option is the help option, which displays the command-line options for the **pa\_discovery** command.

- node** This option identifies the name of a single node to discover. The value may be the IP address or the hostname. This option may not appear on the command line with the **-file** option.
- t** Use this option to set the trace level, which is the level of detail to put in the status files generated at run time. Valid values are as follows:
- 0** Tracing level is off and no status files will be created.
  - 1** Error and Warning messages appear in the status file.
  - 2** Error, Warning, and Info messages appear in the status file.
  - 3** Error, Warning, Info, and Trace level 1 messages appear in the status file.
  - 4** Error, Warning, Info, and Trace level 1 and 2 messages appear in the status file.
- The default is **0**.
- v** Use this option to display the current version of **pa\_discovery**. This option is in UPPERCASE.
- version** Use this option to display the current version of **pa\_discovery**.

## Usage Notes

This utility is similar to any discovery utility that locates nodes in the system; however, it is different because it tests each node to determine if the node has a specific type of data to collect. It discovers nodes or agents that have historical data such as MeasureWare (MWA) agents.

Once it discovers that a node or agent has historical data, it adds the host name with the relevant information to a data file. This file has the name `pa_discovery.data` and is in the `DPIPE_HOME/data` directory. The report pack uses this file to populate the database with **ee\_collect**.

There is only one child collector, which is **dpipe\_pa**, for **pa\_discovery**. This utility works in conjunction with another command, which is **pa\_collect**; see [pa\\_collect on page 313](#) for more information.

## Processing Considerations

Typically, you can run the **pa\_discovery** utility without parameters, which means that it will check every node. If you want to check specific nodes, you can use an option.

- If you want to check a single node, use the **-node** option.
- If you want to check a specific list of nodes, use the **-file** option. When you use this option, you can omit nodes that would not contain the desired data, for example, routers and hubs.

## Configuration File Settings

The **pa\_discovery** program uses a configuration file to set various parameters. Some of these parameters override the defaults set by the OVPI **pa\_discovery** and **dpipe\_pa** programs. The configuration file has the name `pa_rpt.cnfg` and is in the `$DPIPE_HOME/data` directory.

You may need to fine-tune the system, depending on the installation environment and number of systems that you are discovering. You may have to modify the `ThreadCount` and `ThreadTimeout` parameters in the configuration file. The default settings for these parameters are as follows:

```
ThreadCount=35
ThreadTimeout=1
```

### ThreadCount

If your system is resource bound, you may need to make the `ThreadCount` smaller. If your system is time bound, you may need to make the `ThreadCount` larger.



## **ThreadTimeout**

If the processing does not complete in the time allowed, you may need to increase the value of the ThreadTimeout parameter in the configuration file. If you have a lot of nodes, you may need to increase the value of the ThreadTimeout parameter so that there is enough time to complete the processing.



# piadmin

You can use the **piadmin** command to open the HP OpenView Performance Insight (OVPI) Management Console. The Management Console lets you manage most features of your OVPI system.

You can start the management console from the **Start** menu or the command line. Refer to the *Performance Insight Administration Guide* for more information about using the Management Console.

This chapter describes the **piadmin** command, which is the command that you enter to start the Management Console from the command line.

## Syntax

The **piadmin** command uses the following syntax:

```
piadmin    [ -debug ]  
            [ -h ]  
            [ -help ]  
            [ -laf userinterface]
```

[ **-log** */logfile* ]  
[ **-p** *password* ]  
[ **-port** *number* ]  
[ **-server** *servername* ]  
[ **-u** *username* ]

## Options

The **piadmin** command has the following options:

- debug** This option enables diagnostic messages, which are messages with an extra level of detail that appear in the log file. The **-log** option specifies the name of the log file.
- h** Displays the syntax for the command.
- help** This option is only available on UNIX systems. You can use the abbreviated version, **-h**, or the spelled out version, **-help**.
- laf** This option specifies the look and feel for the application's user interface. The following options are available: Metal (Java), Motif (UNIX), and Windows.
- log** This option enables logging and specifies which log file to open. You can use this option to change the log file. If the file exists, the system will append the new messages to the end; otherwise, the system will create a new file with the specified name. If you include a directory with the name, it must exist in the DPIPE\_HOME directory. If you want the file to be in the log directory, you must include **/log/** with the name; otherwise, the file will be in the DPIPE\_HOME directory. Remember to include the preceding slash (or backslash) with every file name. The default log file is `console.log`, which is in the `DPIPE_HOME/log` directory.

- p** This option specifies the password for the login process. If you do not use this option with the **-u** option, the system will prompt for the username and password.
- port** This option specifies the Web Access Server port. The default for this option is the port number supplied during the OVPI installation, which is port number 80.
- server** This option specifies the Web Access Server host name. The default for this option is the server host name supplied during the OVPI installation.
- u** This option specifies the username for the login process. This username must have administrative privileges. If you do not use this option with the **-p** option, the system will prompt for the username and password.

## Usage Notes

If you enter the **piadmin** command without any options, the system will start the application and display the **Login** dialog box.

If you want to start the Management Console automatically so that it will not display the **Login** dialog box, enter the command with the username and password options.

To enter the command, do the following steps for the appropriate operating system.

### UNIX

From a shell window, enter the following command with the desired options, defined in [Options on page 324](#).

**piadmin**

### Windows

From a Command Prompt window, enter the following command with the desired options, defined in [Options on page 324](#).

**piadmin**

## Examples

The following examples illustrate some uses of the **piadmin** tool.

### Example 1

This example starts the application without displaying the Login dialog box from the user account, **user1**, which has the password **test1**. Note that user account must have administrative privileges.

```
piadmin -u user1 -p test1
```

### Example 2

This example starts the application on a different server, **ferrari1**, even though the default server host name is **powder2**.

```
piadmin -server ferrari1
```

## QGRconverter

You can use the **QGRconverter** command to convert a legacy TREND Graph Data Definition file (.qgr) to a report definition file (.rep) on an HP OpenView Performance Insight (OVPI) system.

### Syntax

The **QGRconverter** command uses the following syntax:

**QGRconverter** *qgr\_file* *report\_name*

where: *qgr\_file* is the name of the legacy TREND Graph Data Definition file, which has the .qgr extension.

*report\_name* is the name of the output report definition file, which has the .rep extension.

## Usage Notes

The TREND Graph Data Definition file is a graph definition file that has a `.qgr` file name extension and displays the data in a graphical format. The graph definition file is from the OVPI 4.5 version or earlier of TRENDgraph.



## QSSconverter

You can use the **qssconverter** command to convert a legacy TREND Table Data Definition file (.qss) to a report definition file (.rep) on an HP OpenView Performance Insight (OVPI) system.

### Syntax

The **QSSconverter** command uses the following syntax:

**QSSconverter** *qss\_file* *report\_name*

where: *qss\_file* is the name of the legacy TREND Table Data Definition file, which has the .qss extension.

*report\_name* is the name of the output report definition file, which has the .rep extension.

## Usage Notes

The TREND Table Data Definition file is a table definition file that has a .qss file name extension and displays the data in a tabular format. The table definition file is from the OVPI 4.6 version or earlier of TRENDsheet.

## schedule

The **schedule** command is a tool that allows you to configure schedules on an HP OpenView Performance Insight (OVPI) system. It allows you to add, remove, and list entries in the schedule.

You can also add, modify, and remove schedule entries from the Web Access Server. The Web Access Server is the graphical user interface (GUI) for OVPI. Refer to the *Performance Insight Guide to Building and Viewing Reports* for more information.

### Requirements and Restrictions

- An error occurs if more than one of the following options appears on the command line at the same time: **-list**, **-remove**, **-rn**.
- All modes require the following options with their corresponding values: **-host**, **-port**, **-pass**, **-user**, and **-schedule**.
- In add mode, the **-rn** option requires the following options with their corresponding values: **-format**, **-trigger**, and **-title**.

- In remove mode, the **-remove** option requires the **-uid** option to specify the report entry to remove from the schedule.
- If the command string is too long, you can use a continuation character to complete the entry.
  - For UNIX, use the backslash (\) as the last character on the line.
  - For Windows, use the character above the number 6 (^).

## Syntax

A parameterless **schedule** command displays the command syntax.

```

schedule    [ -behalf username ]
              [ -desc "rpt_desc" ]
              [ -drilldepth level ]
              [ -format type ]
              -host hostname
              {
                -list
                -remove
                -rn rpt_name
              }
              [ -p parameter=value [:parameter=value] ]
              -pass password
              -port port_num
              [ -query hh:mm ]
              [ -retain num_days ]
              -schedule sched_name ]
              [ -title "event_id" ]
              [ -trigger keyword=value [:keyword=value] ... ]
              [ -uid uid_num ]
              -user rpt_username

```

## Options

The **schedule** tool has the following options:

- behalf** This option allows an administrator to schedule a report on behalf of the named user. This means that the administrator runs a report for specific website login user and then puts the report results into a folder with the user's name and a sub-folder with the schedule file name.
- The user must have an existing schedule so that the administrator can add the report to it.
- If you are using the **-behalf** option and this is a new schedule name, precede this name with the username specified in the **-behalf** option and the appropriate slash for the operating system.
- Use this option only with the **-rn** option.
- desc** Describes the report. You must enclose the description in quotation marks.
- This appears in the **Description** field on the **Schedule Listing** page.
- Use this option only with the **-rn** option.
- drilldepth** Specifies the number of queries to the database, which is the resultant number of rows to show, when you link elements in a report. For more information about drill-down depth, see the *Performance Insight Guide to Building and Viewing Reports*.
- A value of **all** or **-1** will generate all possibilities, which may result in a very large file set. For this reason, you may want to avoid using this value.
- The default value is **5**.
- Use this option only with the **-rn** option.

**-format** Specifies the format type you want for the generated report. Valid values are:

**csv**  
**html**  
**pdf**  
**srep**

You may specify only one format type for a report.

This is a required option with the **-rn** option.

**-host** Specifies the host name of the Web Access Server where the schedule resides.

This is a required option.

**-list** Returns a list of report entries in a specified schedule. Each report entry includes its unique identification number (UID), the title of the report, and the description of the report.

This is the same list that appears on the **Schedule Listing** page.

The output from this option shows the following:

```
uid_num | event_id | rpt_desc
```

where: *uid\_num* is the UID for the report.

*event\_id* is the event identification from the **-title** option.

*rpt\_desc* is the description of the report from the **-desc** option. This field will show *None* if you did not include the **-desc** option in the schedule definition for the report.

This option should not be on the command line with either the **-remove** or **-rn** option; if it is, the system will show the list.

- p** Specifies the report parameters to change report defaults at run time. Uses the format *parameter=value*.  
When you specify more than one parameter, separate the parameters with a colon (:). When a parameter value contains a space, enclose all the parameters in one set of quotes. The following example shows multiple parameters with one parameter that has a space in the value.  
**-p "DEVICETYPE=WAN:REGION=NORTHEAST USA"**  
When a parameter value contains a character that is special to the command interface (shell) such as a comma, precede the character with a backward slash (\), for example:  
**-p DEVICETYPE=WAN:REGION=NORTH\,EAST**  
If the parameter has a colon (:) in its value, you will need to precede the colon with a backslash (\).  
Use this option only with the **-rn** option.
- pass** Specifies the corresponding password to the OVPI username required to access the Web Access Server and modify the schedule.  
This is a required option.
- port** Specifies the Web Access Server port where the schedule resides.  
The default value is **80**.  
This is a required option.

**-query** Specifies the time for the report generator to examine the schedule so that it can identify which reports to run. Use the 24-hour format for the time. For example, if you want the generator to examine the schedule at 3:34 p.m. every day, use the following option on the command string.

**-query 15:34**

If you want the generator to examine the schedule on an hourly basis, use the value, **-1**, as follows.

**-query -1**

This option is required if you want the reports to run automatically, according to the triggers you define. If you do not specify a query time, you must use the **generate** command to run the reports. See [generate on page 155](#) for more information.

This appears in the **Examination Time** field on the **Schedule Listing** page.

Use this option only with the **-rn** option.

**-remove** Removes a report entry from a schedule. Specify the entry using the **-uid** option, followed by the report's UID. For example, to remove the entry from the schedule with the UID equal to `trendadm-934786`, use the following option on the command string.

**-remove -uid trendadm-934786**

Do not use this option when the **-list** or **-rn** option is on the command line.

**-retain** Specifies the number of days to retain the generated report results in the Results folder. For example, if you want to delete the report results after 5 days, use the following option on the command string.

**-retain 5**

The default is to retain the results forever.

Note that you should enter a value for this option since the default consumes a large amount of disk space per report request.

Use this option only with the **-rn** option.



- rn** Specifies the path and name of the report to generate. Do not use this option when the **-list** or **-remove** option is on the command line.
- schedule** Specifies the name of the schedule for which you are adding an entry, removing an entry, or listing all existing entries. If the schedule's name is more than one word, enclose it in quotation marks. For example, if you want to create a schedule with the name, Executive Summary, use the following option on the command string.
- schedule "Executive Summary"**
- If you are using the **-behalf** option and this is a new schedule name, precede this name with the username specified in the **-behalf** option and the appropriate slash for the operating system.
- This name appears in the **Schedule File** field on the **Schedule Listing** page.
- This is a required option.
- title** Specifies the title identifier for the event you are scheduling. You must enclose the title in quotation marks.
- This is the name of the entry that appears in the specified schedule.
- This name appears in the **Title** field on the **Schedule *schedname* for user *username*** page, and it is the name that appears in the results folder for each format type.
- This is a required option with the **-rn** option.

**-trigger** Specifies the time to generate the report. You can choose to run the report on a specific day of every week, day of every month, date, or quarter. The keywords for this option are the following:

Keyword	Valid Values
<b>date=</b> <i>yyyy/mm/dd</i>	<p><i>yyyy</i> 4-digit year</p> <p><i>mm</i> 2-digit month, values are <b>01-12</b></p> <p><i>dd</i> 2-digit day, values <b>01-31</b> depending on the month</p>
<b>day=</b> <i>day</i>	<p>Specify the day of every week to generate the report. Valid values are:</p> <p><b>mon</b> <b>tues</b> <b>wed</b> <b>thurs</b> <b>fri</b> <b>sat</b> <b>sun</b></p>
<b>month=</b> <i>num_day</i>	<p>The value ranges from <b>1 - 31</b> to specify which day of every month to generate the report.</p>
<b>quarter=</b> <i>quarter</i>	<p>The value ranges from <b>1 - 4</b> to specify which quarter of the year to generate the report.</p>

You can use these keywords in combination by placing a colon (:) between them. For example, to run the report every Monday and on the 25th of every month, use the following option in the command string.

**-trigger day=mon:month=25**

This information appears on the **Triggers - path\_reportname.rep** page and you can modify it by clicking the **Edit Event** icon.

This is a required option with the **-rn** option.

- uid** Used to specify an entry to be removed from the schedule (with the **-remove** option). When you add a new entry to the schedule, the system assigns and displays its UID. The format is *user\_name-nnn*
- where: *user\_name* is the name of the user that will view the report, which is the user named in the **-behalf** option when it is used.
- nnn* is a unique identifier.
- Use this option only with the **-remove** option.
- user** Specifies the OVPI username required to access the Web Access Server and modify the schedule. This user must be an administrator user when the **-behalf** option is on the command line. This is a required option.

## Usage Notes

After you create a report, you can set up a time to generate the report on a regular basis. To do this, you add an event to the schedule that specifies when to run the report, which report template to use, what the format is for the report output, the title for the event, and when the system should check the schedule to generate the report.

You can use the **schedule** command to configure schedules when you want to automate the process or create a script.

As an administrator, you can create schedules that generate reports for other users to view.

## Modes of Operation

The **schedule** command has three modes of operation: add, list, and remove.

## Add

The *add* mode provides the ability to add an entry to the schedule. If the specified schedule does not exist, the Schedule tool creates it. When you add an entry to the schedule, the system returns a UID for that entry.

## List

The *list* mode provides the ability to view the current entries in the schedule.

## Remove

The *remove* mode provides the ability to remove an entry from the schedule.

## Using the schedule Command

This section shows some formats of the command for the various modes. There is a minimum of five required options for the schedule command. Each mode will show the command with the required options along with the other options for the particular task; however, only the definitions for the new options will appear for each subsequent command. The definitions for the required options appear below.

- All schedule commands must have all the following options for each task:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_name
```

where: *rpt\_username* is the user name for the report.

*password* is the password for the corresponding user name.

*host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*sched\_name* is the name of the schedule that will contain the added entry.

- If you enter the **schedule** command without any options, the system will display the help information. Use the following format.

```
schedule
```

## List

- To view the list of current entries in the schedule, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_name -list
```

## Remove

- To remove an entry from the schedule, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_name -remove -uid uid_num
```

where: *uid\_num* is the event identification number for the report.

## Add

The following formats show various options for adding an event to a schedule. Note that you can combine the additional options in any manner that meets your needs.

- To add an entry to the schedule using only the required options, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_name -rn rpt_name -title "event_id"
-format type -trigger key_value_set
```

where: *event\_id* is the title for the event in the schedule.

*rpt\_name* is the path and name of the report that the system will generate.

*type* is format of the output.

*key\_value\_set* is the set of keywords and values that specify the time to generate the report.

- To add an entry to the schedule for another user to view, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_name -rn path reportname
-title "event_id" -format type -trigger key_value_set
-behalf user_name
```

where: *user\_name* is the name of the user to access the report.

- To add an entry to the schedule that specifies the number of days to keep the generated report, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_namee -rn path_reportname
-title "event_id" -format type -trigger key_value_set
-retain num_days
```

where: *num\_days* is the number of days to keep the generated report.

- To add an entry to the schedule that specifies the time the generator will check the schedule to generate the reports, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_namee -rn path_reportname
-title "event_id" -format type -trigger key_value_set -query hh:mm
```

where: *hh:mm* is the time the generator will examine the schedule specified in a 24-hour time.

- To add an entry to the schedule that specifies the number of queries to the database for the linked elements in the report, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_namee -rn path_reportname
-title "event_id" -format type -trigger key_value_set
-drilldepth level
```

where: *level* is the number of queries to the database for the linked elements in the report.

- To add an entry to the schedule that adds a description for the event, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_namee -rn path_reportname
-title "event_id" -format type -trigger key_value_set -desc desc
```

where: *desc* is the description for the report.

- To add an entry to the schedule that changes the report defaults, enter the following command:

```
schedule -user rpt_username -pass password -host host_name
-port port_num -schedule sched_namee -rn path_reportname
-title "event_id" -format type -trigger key_value_set -p param_val_set
```

where: *param\_val\_set* is the set of parameters and values that change the report defaults.

## Examples

The following examples illustrate some uses of the **schedule** command.

### Example 1

To add an entry with the title **rpt1** to the schedule called **test1a** that will run every Thursday, use the following command.

```
schedule -user user1 -pass test1 -host powder2 -port 80
-rn d:\ovpi\reports\SystemResource\quickview.rep -trigger day=thu
-format csv -title "rpt1" -schedule test1a
```

This entry in schedule **test1a** will appear in the **user1** directory on the **powder2** host. It will have the **quickview** report from the **SystemResource** directory with a title of **rpt1**. The output will be a file in **csv** format, which means that it has comma-separated values. When you press **Enter** after typing this command, the system returns the UID number for this entry, which is **ID:user1-1064459800046** in this case.

### Example 2

To show all the entries in the schedule called **test1a** for user/password pair of **user1/test1** from host **powder2** and port **80**, use the **-list** option as in the following command.

```
schedule -user user1 -pass test1 -host powder2 -port 80 -schedule
test1a -list
```

The output shows the list of entries in the specified schedule. Each entry has three parts with each part separated by a bar (|). Each entry shows the UID, which is the user name followed by a dash and a unique number, the title of the report, which is from the **-title** option, and the description of the report from the **-desc** option.

The output for this example follows.

```
user1-1064459800046 | rpt1 |
user1-1064529136962 | rpt2 |
user1-1064526276978 | rpt3 |
user1-1064526237368 | rpt4 |
user1-1064526622837 | null | None
```

Note that when the **-title** option is missing from the command line during the add function, the title of the report is **null**.

### Example 3

To delete a report called **rpt1** from the schedule called **test1a** for user/password pair of **user1/test1** from host **powder2** and port **80**, use the **-remove** option with the **-uid** option as in the following command.

```
schedule -user user1 -pass test1 -host powder2 -port 80 -schedule
test1a -remove -uid user1-1064459800046
```

### Example 4

To add an entry called **CP** to the schedule named **john** that will run on the 15th of every month, use the following command.

```
schedule -user jmk -pass jmk -host rover -port 80 -schedule john
-rn \software\reports\deploy\system\Interface_Reporting\Interface\
Capacity_Planning.rep -trigger month=15 -format srep -retain 3
-title "CP" -p INTERFACE=92:CUSTOMER=Telco
```

The format of the report is srep, and the system keeps the report results for 3 days. When CP runs, the system will set the INTERFACE and CUSTOMER parameters to 92 and Telco, respectively.

When you press **Enter** after typing this command, the system displays the entry's UID. If you ever want to delete this entry from the schedule, you will need to use this UID.

## Error Messages

This section describes some of the messages that can occur from the **schedule** command. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.



- If the following error message appears, the value for the **-rn** option is missing.

A value is required for argument rn : Report file name to generate.

Verify that the **-rn** option has the name of the report to generate with a fully qualified path.

- If the following error message appears, the **-port** option is missing.

Option "-port" must be specified.

Verify that the command has the **-port** option with the number of the port.

- If the following error message appears, the schedule name specified with the **-schedule** *sched\_name* option with the **-user** *user\_name* option on the command line does not exist.

Schedule *user\_name* \ *sched\_name* not found.

Verify the spelling of the schedule name or that the schedule exists in the specified location.

- If the following error messages appear, the **-user** *user\_name* or the **-pass** *password* option is incorrect.

You are not authorized to view this website.  
Non-successful HTTP command received: 401

Verify the following items.

- The spelling of the *user\_name* or *password* is correct.
- The combination of the user name/password pair is correct.

- If the following error messages appear, the system cannot find the specified UID number for the specified schedule.

User *user\_name* is removing from schedule owned by *user\_name*.  
Looking for schedule *sched\_name*.  
Can't find schedule.  
Non-successful HTTP command received: 206

Verify the entry for **-uid** *uid\_num* option is on the command line with the **-remove** option and is correct.

- ❑ If the following error messages appear, the **-remove** option is not on the command line.

Report not found.

Non-successful HTTP command received: 206

Verify the **-remove** option is on the command line with the **-uid** option.

- ❑ If the following error message appears, there is an invalid option on the command line.

*-option* is not valid for this program.

Verify the spelling of the *option* on the command line.

- ❑ If the following error message appears, the value for the **-host** option is missing.

A value is required for argument host : Trend Application Server host.

Verify that the **-host** option has the name of the host that has the Web Access Server where the schedule resides.

- ❑ If the following error message appears, the **-host** option is missing.

Option "-host" must be specified.

Verify that the command has the **-host** option with the name of the host that has the Web Access Server where the schedule resides.

- ❑ If the following error message appears, the specified option is missing.

Option "*-option*" must be specified.

Verify that the command has the specified *option* with its corresponding value.

- ❑ If the following error message appears, the value for the specified option is missing.

A value is required for argument *option* : *value\_description*.

Verify that the specified option has the corresponding value with it. The *value\_description* describes the corresponding value.

## snmpv2dis

The SNMP V2 Discovery Utility (**snmpv2dis**) identifies devices that support the SNMP V2 protocol on an HP OpenView Performance Insight (OVPI) system.

### Syntax

The SNMP V2 Discovery Utility (**snmpv2dis**) has the following syntax.

```
snmpv2dis  [ -c category_name ]  
            [ -d debug_level ]  
            [ -E ]  
            [ -g group_name ]  
            [ -p num_nodes ]  
            [ -S server_name ]  
            [ -u ]  
            [ -v ]
```

## Options

The SNMP V2 Discovery Utility (**snmpv2dis**) has the following options:

- c** Specifies the category name.  
The default value is **ksi\_managed\_node**; however, if you specify a managed-object group name using the **-g** option, the default value is **view**.
- d** Specifies a debug output level. Values of **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is no debug output.  
Debug output writes to standard output.
- E** Echoes the progress of **snmpv2dis** to standard output, which is usually the screen.  
This option is in UPPERCASE.
- g** Specifies the name of the managed-object group to discover. This is equivalent to the view name defined using **Polling Policy Manager**.
- p** Specifies the number of nodes to test concurrently, which is the number of active sessions.  
The default is **10**.
- s** Specifies the name of the server that contains the list of SNMP devices to check. The default uses the server identified in the default database entry in the `systems.xml` file.  
This option is in UPPERCASE.
- u** Displays the list of command line options (help).
- v** Displays the version number of the product.  
This option is in UPPERCASE.

## Usage Notes

The SNMP V2 Discovery Utility (**snmpv2dis**) identifies devices that support the SNMP V2 protocol. Once this utility determines that a device supports the SNMP V2 protocol, it does not check that device again.

If you enter the **snmpv2dis** command without any options, it checks the SNMP devices on the database server identified in the default database entry in the `systems.xml` file. This means that the **snmpv2dis** utility checks all the nodes identified as SNMP devices in the `ksi_managed_node` property table that do not have SNMP V2 identification. In this case, there was no category name specified with the **-c** option and no managed-object group name specified with the **-g** option.

If you specify a managed-object group name with the **-g** option and do not specify the category name with the **-c** option, then the category name will be **view**. You can find managed-object group names from **Polling Policy Manager**. Refer to the *Performance Insight Administration Guide*.

If there are any errors, they will appear in `trend.log`.



## tpmaint

The Time Periods Maintenance Utility, **tpmaint**, is an HP OpenView Performance Insight (OVPI) utility that populates *time-period* tables. Each of these tables contains a list of time periods for a specified number of days, which is the retention value for the table. There are time-period tables for various time categories, such as day, hour, 5-minute, and 30-second. These tables enable optimized searches of the database.

### Requirements or Restrictions

- If you change the retention period for any data table to a retention period value longer than the default value for the corresponding time-period table by 1.5 or more times, it will negatively impact performance.

## Syntax

The **tpmaint** command uses the following syntax:

```
tpmaint    [ -d debug_level ]
           [ -e "end_date" ]
           [ -h ]
           [ -F ]
           [ -s "start_date" ]
           [ -S server_name ]
           [ -t time_period_table_name ]
           [ -u ]
           [ -v ]
```

## Options

The **tpmaint** command has the following options:

**-d** Specifies the type of debug output. The values are:

- 0** Provides no debug output.  
This is the default value.
- 1** Provides general debug output.

Debug output is in standard output. You should only use this option for testing in coordination with HP Technical Support.

**-e** This option specifies the end date. The format of the *end\_date* is *mm-dd-yyyy*.

where: *mm* is a 2-digit month  
*dd* is a 2-digit day  
*yyyy* is a 4-digit year

Enclose the date in quotes, since the format includes dashes.



- F** This option forces **tpmaint** to continue processing when there are more rows to process from the table than two times the default retention period for that table.  
This option is in UPPERCASE.
- h** Displays the syntax for this utility.
- s** This option specifies the start date. The format of the *start\_date* is *mm-dd-yyyy*.  
where: *mm* is a 2-digit month  
*dd* is a 2-digit day  
*yyyy* is a 4-digit year  
Enclose the date in quotes, since the format includes dashes.  
The default for this option sets the start date to today.
- S** This option specifies the database *server\_name*. It overrides the value of the default database entry in the `systems.xml` file for the current process.  
This option is in UPPERCASE.
- t** Used to specify the *time\_period\_table\_name* to be processed.  
The default for this option will cause all time period tables to be processed sequentially.
- u** Displays the syntax for this utility.
- v** Displays the version of this utility.  
This option is in UPPERCASE.

## Usage Notes

The **trendtimer** program should invoke the **tpmaint** utility on a daily basis. The utility verifies that each time-period table contains data for the specified number of retention days for the time category. For example, if the time-period table for the hour time category has a retention of 400 days, **tpmaint** will verify that there is data for at least 400 days in that table.

To improve performance, OVPI applications verify that the appropriate entries exist in the corresponding time-period table for a data table. They do this by comparing the begin and end dates of the source table to the begin and end dates of the corresponding time-period table. If the begin and end dates of the source table are within the range of the begin and end dates for the corresponding time-period table, the program continues processing; otherwise, it invokes **tpmaint** to update the corresponding time-period table. Note that if there are gaps in the time-period table for the range of dates from the source table, the program invokes **tpmaint** to cover that time frame.



You can change the retention period for any table in any time category; however, setting the retention period value longer than the default value of the time category (1.5 or more times) will negatively impact performance.

There are predefined limits for the number of rows to keep in time-period tables. Exceeding those numbers will result in performance problems. When **tpmaint** populates a time-period table and it tries to increase the number of rows to more than twice the recommended amount, it will generate the following messages in `trend.log`.

Adding the requested date range to the total of *number* days to table *table name* will exceed the total default of *retention* days by more than 2 times.

Reduce the date range specified or use `-F` to override.

If these error messages appear in `trend.log` while running **tpmaint**, you need to rerun **tpmaint** with the `-F` option to override the default and continue processing. Be aware that this will cause performance penalties.

Note that if you terminate **tpmaint** with **Ctrl+c**, you will need to terminate any associated stored procedures that are currently running on the server separately.

# Examples

## Example 1

The following command causes the **tpmaint** utility to populate the time-period tables with the date starting on September 14, 2003.

```
tpmaint -s "09-14-2003"
```



Note that a check is performed before adding a row to prevent inserting duplicate records.

## Example 2

The following command causes the table named **dsi\_local\_time\_period\_hour** to be processed.

```
tpmaint -t dsi_local_time_period_hour
```



# trendcopy

The **trendcopy** command allows the user to copy data from one HP OpenView Performance Insight (OVPI) database to another.

## Requirements or Restrictions

- This version of **trendcopy** copies data to or from databases in the following manner:

<b>From</b>	<b>To</b>
OVPI version 4.6, Sybase	OVPI version 5.0, Sybase or Oracle
OVPI version 5.0, Sybase	OVPI version 5.0, Sybase or Oracle OVPI version 4.6, Sybase
OVPI version 5.0, Oracle	OVPI version 5.0, Oracle

It does not copy data from databases with OVPI version 5.0 on Oracle to any OVPI database on Sybase.

- **trendcopy** only copies *new* data, which is data that is later than the latest **ta\_period** value in the destination table for a particular object (keyid).
- **trendcopy** can copy tables that have by-variables different from **target\_name** and **table\_key**. These tables can also have foreign keys.
- Data transported by **trendcopy** goes from data table to data table. Data copied in this way is accessible only by OVPI.
- **trendcopy** copies the property and data tables to another database only when the property table of the destination table has an identity column.
- **trendcopy** only copies the definitions of property and data tables to another database when the property table of the destination table is missing an identity column (such as a Report Package demo). In this case, use either the BCP or BCPfile utility to complete the transfer.
- **trendcopy** copies a source data table constructed as a view to an existing destination data table constructed as a view; otherwise, it creates the destination data table as a table.
- **trendcopy** copies a data table with a corresponding property table that is a view only when the view is a recognized view. The following table lists the recognized property table views.

**Table 19 Property Table Views Recognized by trendcopy**

Kmon_ethstatsdata_	Kmon2_alhostdata_	Kmone_ethstatsdata_
Kmon_histdata_	Kmon2_almatrixdata_	Kmone_histdata_
Kmon_histtrmdata_	Kmon2_nlhostdata_	Kmone_histtrmdata_
Kmon_histtrpdata_	Kmon2_nlmatrixdata_	Kmone_histtrpdata_
Kmon_hostdata_	Kmon2_statsdata_	Kmone_hostdata_
Kmon_matrixdata_		Kmone_matrixdata_
Kmon_trmstatsdata_		Kmone_trmstatsdata_
Kmon_trpstatsdata_		Kmone_trpstatsdata_
Kmon_trroutestatsdata_		Kmone_trroutestatsdata_
Kmon_trstationdata_		Kmone_trstationdata_

# Syntax

The format for **trendcopy** follows.

```
trendcopy  [ -d debug_level ]
            [ -D ]
            [ -e yyyymmdd [ : yyyymmdd ] ]
            [ -E seconds ]
            [ -f day_of_week [ : day_of_week ] ]
            [ -g hour [ : hour ] ]
            [ -h ]
            [ -I mode_value ]
            [ -K retries ]
            [ -M ]
            [ -N ]
            [ -P ]
            [ -q ]
            [ -Q ]
            [ -s source_server ]
-S destination_server
            [ -t source_table [ : destination_table ] ]
            [ -u ]
            [ -v ]
            [ -w high_water_mark ]
            [ -x level ]
            [ -Y ]
            [ -Z max_rows ]
```

## Option Categories

The following table lists the options in categories that you might use.

**Table 20 trendcopy Option Categories**

Category	Options
<b>Typical:</b>	<b>-t, -s, -S</b>
<b>Specific:</b>	<b>-D, -P, -M, -N, -Y</b>
<b>Row Filter:</b>	<b>-e, -f, -g</b>
<b>Limits:</b>	<b>-z, -w</b>
<b>Debug:</b>	<b>-d, -q, -x</b>
<b>Miscellaneous:</b>	<b>-h, -Q, -u, -v</b>

## Options

You can run the **trendcopy** command-line interface with the following options:

- d** Sets the debug output level.  
Valid values for *debug\_level* are 1, 2, and 3.  
The higher the number, the more detailed the information. Debug output is written to the standard output destination. Use this option only for testing in coordination with HP Technical Support.
- D** Copies the new rows into the data table for each specified data table only when there are entries in the corresponding keymap. It does not check, copy, or update the property table or the keymap. See [Using the Specific and Debug Options on page 369](#).  
This option is in UPPERCASE.



- e Provides filtering by date, which copies the data table rows that match the specified date. The format for the date is *yyyymmdd*, where:
  - yyyy* is the 4-digit year.
  - mm* is the 2-digit month.
  - dd* is the 2-digit day.

The **trendcopy** command accepts multiple instances of this option. See [Using the Row Filter Options To Copy Data by Date on page 368](#).

- E Specifies the number of seconds the system will wait before it tries to obtain a database lock on a table.

- f Provides filtering by day of week, which copies the data table rows that match the specified day of the week.

Valid *day\_of\_week* values may be upper or lower case and are the following:

<b>su</b>	Sunday
<b>mo</b>	Monday
<b>tu</b>	Tuesday
<b>we</b>	Wednesday
<b>th</b>	Thursday
<b>fr</b>	Friday
<b>sa</b>	Saturday

The *day\_of\_week* range is Sunday through Saturday, and does not wrap around to the following week. To specify a *day\_of\_week* range that wraps around to the following week, use two command-line options.

**trendcopy** accepts multiple instances of this option.

See [Using the Row Filter Options To Copy Data by Date on page 368](#).

- g** Provides filtering by hour of the day, which copies the data table rows that match the specified hour.  
Valid *hour* values are 0-23, where 13 means 1 p.m. and 0 (zero) means 12 midnight. This value does not wrap around to the following day. To specify an hour range that wraps around to the following day, use two command-line options.  
The value 9:14 selects the data table rows where *ta\_period* matches 9 a.m. to 2 p.m.  
**trendcopy** accepts multiple instances of this option.  
See [Using the Row Filter Options To Copy Data by Date on page 368](#).
- h** Displays a listing of all **trendcopy** options. This option is the same as the **-u** option.
- I** Use this option to specify the mode to run **indexmaint**, which maintains the indexes on the tables. Valid values are:

  - 0** Does not run **indexmaint**.
  - 1** To run **indexmaint** in maintenance mode.
  - 2** To run **indexmaint** in force mode.

The default is **0**.  
This option is in UPPERCASE.
- K** Specifies the number of retries the system will attempt to obtain a database lock on a table.
- M** Synchronizes the corresponding keymap for each data table specified. It updates the property table keymap by mapping only the keyids that are on both the source and destination servers. That is, the keymap contains the intersection of keyids on the servers. The updated keymap is on both servers. This option does not invoke the copy of the property table or the data table. See [Using the Specific and Debug Options on page 369](#).  
This option is in UPPERCASE.

- N** Transcribes the keymap, for the corresponding property table for each data table specified, from the destination server (**-s**) to the source server (**-s**) after processing all other tasks in the command. Note that this is an add-on option, which means that **trendcopy** will process this option after it processes all other options on the command line.  
This option is in UPPERCASE.
- P** Copies the new rows into the corresponding property table for each data table specified. It also updates the corresponding keymap. It does not copy the data table. See [Using the Specific and Debug Options on page 369](#).  
This option is in UPPERCASE.
- q** Checks and displays the list of tasks that **trendcopy** generates. Note that if the specified table does not exist on the destination server (**-s**), **trendcopy** will create the table and the corresponding property table without copying the data and then display the list of tasks. Use this option only for testing in coordination with HP Technical Support.
- Q** Specifies that **trendcopy** will not create the tables that do not exist on the destination server. See [Example 4 on page 368](#).  
This option is in UPPERCASE.
- s** Identifies the source server, which is the server (or database) that contains the data tables to copy. This name must be an entry in the `systems.xml` file with the tag `<Name>`.  
The default value for the `source_server` is default database entry in the `systems.xml` file.  
**trendcopy** uses the last instance of this option that appears in the command line.  
This option is not required, but when it is used, it readily identifies the location for the data.  
See [Using Various Options to Copy Database Tables on page 367](#).

- s** Identifies the destination (or target) server, which is the server (or database) to receive the copied data tables. There is no default for *destination\_server*. This name must be an entry in the *systems.xml* file with the tag **<Name>**.  
**trendcopy** uses the last instance of this option that appears in the command line.  
This is a required option.  
This option is in UPPERCASE.  
See [Using Various Options to Copy Database Tables on page 367](#).
- t** Identifies the tables to copy; the parameters are the following:  
*source\_table* contains the rows to copy  
*destination\_table* is the data table to receive the copied rows  
If the destination table name is missing, **trendcopy** will use the source table name (*source\_table\_name* => *destination\_table\_name*).  
Enter the name of the table as shown in the **SQL Name** column of the **Database Table Management** display from the management console. Note that, if the *destination\_table* name is from the **Alias Name** column, **trendcopy** will process the command as if the table name is an SQL name.  
Using this option, you can run multiple **trendcopy** instances simultaneously, improving throughput and reducing run times.  
If this option is missing, **trendcopy** will copy all data tables with the corresponding property tables serially, which may result in excessive run times.  
If the *destination\_table* does not exist on the destination server, **trendcopy** will create the table with the same property table assignment as the source data table. If the destination data table has a different property table than the source data table, then you need to create the destination tables with the appropriate property table assignment before running **trendcopy**.  
See [Using Various Options to Copy Database Tables on page 367](#).
- u** Displays a listing of all **trendcopy** options. This option is the same as the **-h** option.

- v** Displays the **trendcopy** version.  
This option is in UPPERCASE.
- w** **trendcopy** determines the current size of the database to be copied and does not run if the database-used size exceeds the percentage specified in this parameter. The default is 90 for 90%.
- x** Requests task timings to appear in the log. Enter any integer for the *level* value. The output will be in the **trendcopy\_dbg.log** file. Use this option only for testing in coordination with Technical Support.
- y** Requests that **trendcopy** not verify the keymap table. See [Example 6 on page 370](#).  
This option is in UPPERCASE.
- z** Specifies the number of maximum rows allowed for a BCP batch file; enter an integer for the *max\_rows* parameter. See [Example 2 on page 367](#) or [Using the Specific and Debug Options on page 369](#).  
The default is **1000** rows.  
This option is in UPPERCASE.

## Usage Notes

The basic function of **trendcopy** is to copy data tables from one OVPI database to another. For each table it copies, it copies the data that has a later timestamp than the latest timestamp in the corresponding destination table for each managed object. If there is a gap in the timestamps for the data, **trendcopy** will not copy the data to fill in the gap.

When **trendcopy** copies a data table, it verifies the keymap first and then copies the corresponding property table before copying the new data. If a data table does not exist, **trendcopy** will create the missing table. Some of the options allow you to modify the process. See [Options on page 360](#) for the descriptions of the options. See [Keymap Tables on page 367](#) for more information about keymaps.

Some applications for **trendcopy** follow.

- In an OVPI system that uses satellite servers to process data, use **trendcopy** to copy the processed data from an OVPI satellite server to the OVPI central server.
- In an OVPI system that includes an archive server, use **trendcopy** to copy data from the central server to the archive server.

## Performance Notes

- If property tables are static, this means that there are no new objects added to the property table, use the **-D** option.
- If you are satisfied with the integrity of the keymaps and you do not change them manually, use the **-Y** option.
- Before you copy a large data table, verify that the indexes of the table are in order by running **indexmaint** in force mode. See [indexmaint on page 203](#).
- By employing the **-t** processing option, you can run multiple **trendcopy** instances simultaneously, thus improving throughput and reducing run times. If you do not specify a specific table (with the **-t** option), **trendcopy** copies all the data tables with their corresponding property tables, that satisfy all the other processing options on the command line, serially. This may result in excessive run times.
- Consider the limits of your system when you run concurrent processes. Take into account which processes are already running or scheduled when you plan to run or schedule multiple **trendcopy** commands at the same time.

## Capabilities

**trendcopy** can:

- Copy all the rows in a table to a table in another OVPI database.
- Create a new data table in a database using information copied from a table in another database.
- Filter the data it copies by date or time of day.

## Keymap Tables

**trendcopy** copies tables using a keyid mapping scheme, which synchronizes just the new keyids to provide fast execution. In summary, this scheme maintains a keymap on the destination server, which maps all the keyids in a property table between source and destination servers.

For instance, suppose a keyid for a `Kib_ii_ifentry` table on server A has a value of 123 while that same object on destination server B has a keyid value of 234. Then, there would be a row in the server B keymap table for `Kib_ii_ifentry` having the values of server A, 123, and 234.

**trendcopy** insures the integrity of a keymap table. If the integrity check fails for a server, **trendcopy** assumes that all rows in the keymap table for that server are invalid and regenerates them.

## Examples

The following examples show various methods for copying OVPI database tables from one server to another.

### Using Various Options to Copy Database Tables

#### Example 1

This example shows the command to specify multiple tables on a single command line. If, for example, you want to copy three tables named `mib-II_ifEntry`, `mib-II_system`, and `rmon_history` from the `PRIMARY_DB` server to the `BACKUP_DB` server, use the following command.

```
trendcopy -t mib-II_ifEntry -t mib-II_system -t rmon_history
-s PRIMARY_DB -S BACKUP_DB
```

#### Example 2

This example shows the command to copy the data table `SDIRCustDevice` from the server `xyz_in` to a table named `test_tbl_b` on the server `XYZ_out`. It will copy 100 rows at a time in a batch file.

```
trendcopy -t SDIRCustDevice:test_tbl_b -s xyz_in -S XYZ_out -Z 100
```

### Example 3

This example shows the command to copy the data table **SDIRConfig** from the server **xyz\_in** to an existing table named **test\_tbl\_2** on the server **XYZ\_out**.

```
trendcopy -s xyz_in -S XYZ_out -t SDIRConfig:test_tbl_2
```

### Example 4

Note that this example will produce an error because the table named **test\_tbl\_2x** does not exist on the server **XYZ\_out**. The **-Q** option prevents **trendcopy** from creating the missing table on the destination server.

```
trendcopy -s xyz_in -S XYZ_out -t SDIRConfig:test_tbl_2x -Q
```

## Using the Row Filter Options To Copy Data by Date

You can use **trendcopy** to copy data filtered by date. The following examples explain the use of the **-e**, **-f**, and **-g** options for filtering by date, day of week, and hour of day. You can specify more than one filter; each filter can be a single value or a range of values.

All of the following examples copy the data from the source server named **xyz\_in** to the destination server named **XYZ\_out**. They use all the data tables to locate the data since the **-t** option is missing.

### Example 1

The following command copies any data for which the **ta\_period** is 1:00 p.m. (13) on either Monday (**mo**) or Friday (**fr**):

```
trendcopy -f mo -f fr -g 13 -s xyz_in -S XYZ_out
```

### Example 2

The following command copies data with **ta\_period** greater than or equal to Monday (**mo**) and less than or equal to Wednesday (**we**); and **ta\_period** greater than or equal to October 1, 2002 (20021001), and less than or equal to November 1, 2002 (20021101):

```
trendcopy -f mo:we -e 20021001:20021101 -s xyz_in -S XYZ_out
```



### Example 3

The following command copies data from a Wednesday (**we**) through the following Monday (**mo**). It specifies a day range that wraps around to the following week and uses two command-line options:

```
trendcopy -f we:sa -f su:mo -s xyz_in -S XYZ_out
```

### Example 4

The following command copies data with **ta\_period** greater than or equal to 1 a.m. (1) and less than or equal to 3 a.m. (3) and with a **ta\_period** greater than or equal to October 1, 2002 (20021001), and less than or equal to November 1, 2002 (20021101):

```
trendcopy -g 1:3 -e 20021001:20021101 -s xyz_in -S XYZ_out
```

### Example 5

The following command copies data from 8:00 p.m. (20) to 7:00 a.m. (7); it specifies an hour range that wraps around to the following day; that is, through midnight (0), with two command-line options.

```
trendcopy -g 20:23 -g 0:7 -s xyz_in -S XYZ_out
```

## Using the Specific and Debug Options

### Example 1

This example shows the command to copy only the new rows in the property table for the rate data table **Rasic\_interface\_info\_** from a satellite server to the central server. It will copy 10,000 rows at a time in a batch file.

```
trendcopy -t Rasic_interface_info_ -Z 10000 -P -s satellite_DB  
-S central_DB
```

### Example 2

This example shows the command to copy only the new rows in the rate data table **Rasic\_interface\_info\_** from a central server to the satellite server. It will copy all the data, 10,000 rows at a time.

```
trendcopy -t Rasic_interface_info_ -Z 10000 -D -s central_DB  
-S satellite_DB
```

### Example 3

This example shows the command to synchronize the keymaps on the servers `xyz_in` and `xyz_out` for `test_tbl_2`. It will update the keymaps to contain only the keys that are common on both servers.

```
trendcopy -t test_tbl_2 -s xyz_in -S XYZ_out -M
```

### Example 4

This example shows the command to copy only the new rows in the data table `test_tbl_2` from the server `xyz_in` to the server `xyz_out`. It will use the existing keymap on the destination server `xyz_out`. It will use the keymap created in [Example 3](#) if that was the last trendcopy command for this table and these servers.

```
trendcopy -t test_tbl_2 -s xyz_in -S XYZ_out -D
```

### Example 5

This example shows the command to copy only the new rows in the rate data table `Rasic_interface_info_` with the keymap from a central server, `xyz_in`, to the satellite server, `xyz_out`. It will copy only the keys that are common on both servers. Note that it is more efficient to use the `-M` option first and then the `-D` option as in the previous examples.

```
trendcopy -t Rasic_interface_info_ -D -M -s xyz_in -S XYZ_out
```

### Example 6

This example shows the command to skip the validation of the keymap and copy only the new rows in the data table `test_tbl_7` from the server `xyz_in` to the server `xyz_out`. In this example, **trendcopy** also copies the corresponding property table.

```
trendcopy -t test_tbl_7 -s xyz_in -S XYZ_out -Y
```

## Error Messages

This section describes some of the messages that can occur from **trendcopy**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
- The actual message that appears with parameters for any information that may be missing.
- A suggestion about the action to do so that the message will not appear again.

### General

- The following warning message appears when the same command is already running.

Trendcopy for table *table\_name* in db *server\_name* is already running.

If you want to run this command again, you will have to re-enter it when it is not already running. When this message appears, the system will not process or schedule the command.

- The following error message appears when the **trendcopy** command originates from an OVPI system that is not using the 4.6 version of it.

The TREND version on *server\_name* is unknown.

Verify that the database you originate the **trendcopy** command from is using OVPI version 4.6.

### Server Name Error Messages

- The following error message appears when the source and destination server names are the same and the **-M** option appears on the command line. The keymap table will not be copied.

Copy of keymap is not allowed when source db = destination db

Verify the entries and spelling of the source (**-s**) and destination (**-S**) servers.

- ❑ The following error message appears when the *host\_name* does not exist in the `DPIPE_HOME/data/systems.xml` file.

Error: failed to get ip information for host *host\_name*.

Verify the *host\_name* entry is in the `DPIPE_HOME/data/systems.xml` file.

- ❑ The following error message appears when the *src\_server\_name* and the *dest\_server\_name* entries in the `DPIPE_HOME/data/systems.xml` file have the same address.

Error: *src\_server\_name* and *dest\_server\_name* have the same network address of *address*.

Verify the entries and spelling of the source (**-s**) and destination (**-S**) server names. Verify the server entries in the `DPIPE_HOME/data/systems.xml` file.

- ❑ The following error message appears when the format of the name of the server on the command line does not match the format of the name in the `DPIPE_HOME/data/systems.xml` file.

Database '*db\_name*' was not found in `systems.xml` file.

Verify that the format and spelling of the source (**-s**) and destination (**-S**) servers is the same as the format of the server name entries in the `DPIPE_HOME/data/systems.xml` file. For example, if the *server\_name* for the **-s** or **-S** option is in lowercase, replace the *server\_name* in UPPERCASE. When this message appears, **trendcopy** will continue processing the command.

## Source Server

- ❑ The following error message appears when the source server is not available.

Unable to connect to source db (*server\_name*).

Verify the following:

- The source server specified in the **-s** option exists and has an entry in the `DPIPE_HOME/data/systems.xml` file.
- The spelling of the server name is correct.
- The server is running.

## Destination Server

- The following error message appears when the destination server name (**-s**) is missing.

A destination server needs to be specified.

Verify that the **-s** option is on the command line with a server name. Note that the **-s** option is in UPPERCASE.

- The following error message appears when the destination server is not available.

Unable to connect to destination db (*server\_name*).

Verify the following:

- The destination server specified in the **-s** option exists and has an entry in the `DPIPE_HOME/data/systems.xml` file. Note that the **-s** option is in UPPERCASE.
- The spelling of the server name is correct.
- The server is running.

## Table Name Error Messages

- The following error message appears when the source data table name does not exist in the OVPI dictionary and there is no property table for the data table.

No entry in *dictionary\_table* for *table\_name* on *server\_name*.

Verify that the source table specified in the **-t** option exists in the OVPI database on the specified server and the spelling of the table name is correct.

- The following error message appears when the property table name for the source data table does not exist.

No property table name for *table\_name* on *server\_name*.

When this message appears, **trendcopy** will not copy the data table. Call Technical Support.

- The following error message appears when the source property table is missing from the database dictionary table (sysobjects) and the data table exists.

Source property table *table\_name* does not exist on *server\_name*.

Verify that the property table for the specified data table in the **-t** option exists in the database. Determine if the name of the source property table changed.

- The following error message appears when the source data table is missing from the database dictionary table (sysobjects). In this case, there is a property table for the specified data table.

Source data table *table\_name* does not exist on *server\_name*.

Verify that the source data table specified in the **-t** option exists in the database and the spelling of the table name is correct. Determine if the name of the source data table changed.

- The following error message appears when the source and destination table names are the same and the source and destination server names are the same. The data table will not be copied.

Copy of *source\_table* to *destination\_table* is not allowed when source db = destination db.

Verify any of the following:

- The spelling of the source and destination table names specified in the **-t** option are correct.
- The names of the source and destination servers are correct.
- If the **-s** option for the source server is missing, check to see if the destination server is the same server identified in the default database entry in the `systems.xml` file.

- The following error message appears when the system cannot find any tables to copy.

No tables found in *dictionary\_table* on *server\_name*.

Verify the tables exist in the database on the specified server.

- The following error message appears when **trendcopy** needs to create a table but the **-Q** option is on the command line, which prevents **trendcopy** from creating the table by executing **datapipe\_manager**.

No table build by DPM for: *datapipe\_manager\_command*.

Verify that the table specified in the *datapipe\_manager\_command* exists in the database and the spelling of the table name is correct, or remove the **-Q** option from the command line so that **trendcopy** can create the missing table.

- The following error message appears when **trendcopy** copies many large property tables to an Oracle database system.

Reached maximum number of open cursors.

Run **trendcopy** again, and continue to run **trendcopy** until it copies all the tables and the message no longer appears.

## View Error Messages

- The following error message appears when the destination table is a view instead of a table or the destination property table is not a recognized view. The data table will not be copied.

*destination\_table* is a view; trendcopy does not copy into views.

See [Table 19 on page 358](#) for a list of recognized views.

Verify the table name specified in the **-t** option is data table name and not a view name. Note that if the box in the **Is View** column on the **Database Table Management** display has a check mark (4), then that table name is a view.

## By-variable Error Messages

- The following error message appears when the data type of the by-variable is not character or numeric.

Unacceptable data type of *data\_type* in BuildPropCols for *column\_name* in prop table *property\_table\_name* on *server\_name*.

Verify the spelling of the specified data table name, and that the corresponding property table has by-variables with character or numeric data types. If the by-variables have any other data types, **trendcopy** will not copy it or the data table.

- ❑ The following error message appears when the by-variables for a property table are missing.

Error: failed to find any by-variables in *property\_table\_name* on *server\_name*.

Verify the spelling of the specified data table name, and that the corresponding property table has at least one by-variable. If the property table does not have any by-variables, **trendcopy** will not copy it or the data table.

- ❑ The following error message appears when the number of by-variables for the source property table is different than the number of by-variables for the destination property table.

Error: *source\_property\_table* on *source\_server* has *num1* by-variables while *destination\_property\_table* on *destination\_server* has *num2*.

Verify the source and destination table names are correct, and that the corresponding property tables have the same number of by-variables; otherwise, **trendcopy** will not copy the property or data table.

- ❑ The following error message appears when the by-variables for the source property table are different from the by-variables for the destination property table.

Error: *source\_property\_table* on *source\_server* has *source\_byvar* as by-var *num* while *destination\_property\_table* on *destination\_server* has *destination\_byvar*.

Verify the source and destination table names are correct, and that the corresponding property tables have the same by-variables; otherwise, **trendcopy** will not copy the property or data table.

## Foreign Key Error Messages

- ❑ The following error message appears when the foreign key reference column is missing from the foreign key table.

foreign key reference column *fkey\_col\_name* for column *column\_name* in property table *property\_table\_name\_1* is not in foreign property table *fkey\_table\_name\_2*.

When this message appears, **trendcopy** will not copy the data table. Call Technical Support.



- The following error message appears when the foreign key reference column does not contain `dsi_key_id`.

Error: foreign-key reference column *fkey\_name* is not `dsi_key_id` for column *col\_name* in prop table *table\_name* on *server\_name*.

When this message appears, **trendcopy** will not copy the data table. Call Technical Support.

## Option Error Messages

- The following error message appears when the calendar date option (**-e**) contains a non-numeric value.

Invalid value for the `-e` option. The date must be in `yyyymmdd` format.

Verify the value specified for the **-e** option has a valid numeric value in the format `yyyymmdd`.

- The following error message appears when the day-of-week option (**-f**) contains an invalid value.

Invalid value for the `-f` option. The day of the week value must be one of the following: `MO`, `TU`, `WE`, `TH`, `FR`, `SA`, `SU`.

Verify the value specified for the **-f** option has one of the following values:

<b>MO</b>	for	Monday
<b>TU</b>	for	Tuesday
<b>WE</b>	for	Wednesday
<b>TH</b>	for	Thursday
<b>FR</b>	for	Friday
<b>SA</b>	for	Saturday
<b>SU</b>	for	Sunday

- The following error message appears when the hour-of-day option (**-g**) contains any value less than 0 and greater than 23.

Invalid value for the `-g` option. The time value must be between 0 and 23.

Verify the value specified for the **-g** option has a number greater than or equal to 0 (zero) and less than 24.

- The following error message appears when the **-P** option is on the same command line with either the **-D** or **-M** option.

Selection of both **-P** and *option\_letter* is unacceptable.

If you want to copy the property table only, then use the **-P** option without the **-D** or **-M** options. If you want to copy a data table with its corresponding property table, do not use the **-P**, **-D**, or **-M** options since that is the default behavior.

## transform\_maint

You can use the **transform\_maint** command to perform maintenance tasks related to transformations on an HP OpenView Performance Insight (OVPI) system. A *transformation* is a set of parameters with a corresponding procedure that changes the data from one form to another. In the case of summary transformations, a transformation is the set of parameters that **trend\_sum** will use to generate a procedure that will change the delta data in one table to the hourly data in another table.

### Requirements and Restrictions

- When you use the **-delete** option, you must include the **-name** option on the command line.
- One of the following options must appear on the command line: **-delete**, **-list**, **-refresh**, or **-remove**.

## Syntax

A parameterless **transform\_maint** command displays the following syntax:

```
transform_maint  [ -all ]  
                  [ -database server_name ]  
                  [ -d debug_level ]  
                  [ -debug debug_level ]  
                  [ -delete ]  
                  [ -h ]  
                  [ -help ]  
                  [ -l ]  
                  [ -list ]  
                  [ -name name ]  
                  [ -refresh ]  
                  [ -remove ]  
                  [ -v ]  
                  [ -version ]
```

## Options

The **transform\_maint** command has the following options:

- all**            Use this option to list the information for a transformation definition from the database. This information includes the transformation and procedure names, the source and destination table names, the first day of week and baseline days specifications, and the hysteresis and lag time settings. The format of the output has a tag enclosed in angle brackets followed by the value for the tag.
- This option must appear with the **-list** option on the command line.

- database** Use this option to specify the remote database name. The default for this option is the default database specified in the `systems.xml` file.
- d**  
**-debug** Use this option to set the debug output level. The higher the number, the more detailed the information. Debug output writes to standard out. Use this option only for testing in coordination with Technical Support due to the additional overhead it places on **transform\_maint**. The valid values are **0**, **1**, **2**, or **3**. The default is no debug output, which is **0**.
- delete** Use this option to remove a transformation definition. If the corresponding procedure is in use, the **transform\_maint** utility will not delete the transformation definition. You must use the **-name** option with this option.
- h**  
**-help** This option is the help option, which displays the command-line syntax for the **transform\_maint** command. This option overrides all other options on the command line.
- l**  
**-list** Use this option to list the names of the transformation definitions in the database. The output has the following format: `<name> 'transformation_definition_name'`.
- name** Use this option to specify the name of the transformation definition to remove or generate. You can use the **-list** option to get the name. This is a required option when the **-delete** option appears on the command line.
- refresh** Use this option to generate new procedures for the corresponding transformation definitions.
- remove** Use this option to remove the procedures that are no longer associated to any transformation definition. When you use this option, the **transform\_maint** utility will not remove any procedures that are running.
- v**  
**-version** Use this option to display the current version of the **transform\_maint** utility. This option overrides all other options on the command line, except the **-help** option. The **-v** option is in UPPERCASE.

## Usage Notes

The commands that create transformations use a set of specified parameters to generate a corresponding procedure that changes the data from one form to another. For example, **trend\_sum** creates summary transformations that change delta data in one table to hourly data in another table. It does this by using the settings from the `.sum` file and generating a procedure to aggregate the data. It also stores this information as a transformation in the database. When there are changes to the settings in the `.sum` file for a particular summary transformation, the system generates a new procedure for that transformation.

Currently, the **transform\_maint** utility will perform the following tasks related to summary transformation definitions.

- Force **trend\_sum** to create new summary procedures.
- Remove all the summary procedures that are no longer associated to any summary transformation definition.
- List the names of the summary transformation definitions with the record information from the database, which includes the following elements.
  - transformation and corresponding procedure name
  - source and destination table names
  - first day of week and baseline days designations
  - hysteresis and lag time settings
- Remove a specific summary definition and its associated procedure.

## Using the transform\_maint Command

This section shows some formats of the command for the various tasks.

- If you enter the **transform\_maint** command without any options, the system will display the help information.
- To display the syntax and options for this command, enter one of the following commands.

```
transform_maint -h or transform_maint -help
```

- To display the version information for this command, enter one of the following commands.

```
transform_maint -V OR transform_maint -version
```

- To generate new procedures for all transformation definitions available on the default database, enter the following command.

```
transform_maint -refresh
```

- To generate new procedures for all transformation definitions available on a specific database, enter the following command.

```
transform_maint -refresh -database server_name
```

where: *server\_name* is the name of the database that has the transformation definitions.

- To generate a new procedure for a specific transformation definition on a specific database, enter the following command.

```
transform_maint -refresh -name tname -database server_name
```

where: *tname* is the name of the specific transformation definition.

*server\_name* is the name of the database that has the transformation definitions.

- To display only the names of all transformation definitions on a specific database, enter the following command.

```
transform_maint -list -database server_name
```

where: *server\_name* is the name of the database that has the transformation definitions.

- To display the record information for a specific transformation definition on a specific database, enter the following command.

```
transform_maint -list -all -name tname -database server_name
```

where: *tname* is the name of the specific transformation definition.

*server\_name* is the name of the database that has the transformation definitions.

- To display the record information for all transformation definitions on a specific database, enter the following command.

```
transform_maint -list -all -database server_name
```

where: *server\_name* is the name of the database that has the transformation definitions.

- To remove a specific transformation definition on a specific database, enter the following command.

```
transform_maint -delete -name tname -database server_name
```

where: *tname* is the name of the specific transformation definition.

*server\_name* is the name of the database that has the transformation definitions.

- To remove all the procedures that are no longer associated to any transformation definition on a specific database, enter the following command.

```
transform_maint -remove -database server_name
```

where: *server\_name* is the name of the database that has the transformation definitions.

## Examples

The following examples illustrate some uses of the **transform\_maint** tool.

### Example 1

To list the name for each transformation definition on the **powder2** database, enter the following command.

```
transform_maint -list -database powder2
```

### Example 2

To list the record information for the transformation definition with the name **SDIRCust\_All\_SDIRDevPorts\_SDIRCust** on the **powder2** database, enter the following command.

```
transform_maint -list -name SDIRCust_All_SDIRDevPorts_SDIRCust  
-database powder2 -all
```



The output has the following tags with their corresponding values:

<name>, <source>, <target>, <first day of week>, <baseline days>, <hysteresis units>, <lagtime units>, and <procedure name>. The output follows:

```
<name> 'SDIRCust_All_SDIRDevPorts_SDIRCust' <source>
'SDIRDevPorts' <target> 'SDIRCust' <first day of week> 'Mon'
<baseline days> '0' <hysteresis units> '-1' <lagtime units> '-1'
<procedure name> 'null'
```

## Error Messages

This section describes some of the messages that can occur from **transform\_maint**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
  - The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- If the following error message appears, the specified command requires the specified option.

Missing required option *option* for command *command\_name*.

Verify that one of the following conditions occurs:

- At least one of the following options is on the command line: **-delete**, **-list**, **-refresh**, or **-remove**.
- The **-delete** and **-name** options are on the same command line.

- If the following error message appears, the specified *server\_name* may be missing in the `systems.xml` file.

The connection to the database *server\_name* could not be established : Connection URL not found.

Verify the spelling of the *server\_name* specified in the **-database** option on the command line. Check the **System Manager** on the Web Access Server to determine if the specified *server\_name* is in the `systems.xml` file. Refer to the *Performance Insight Administration Guide* for more information about **System Manager**.

- ❑ If the following error message appears, the default database server name may be missing in the `systems.xml` file.

The connection to the default database could not be established.

Check the **System Manager** on the Web Access Server to determine if the default server name is in the `systems.xml` file. Refer to the *Performance Insight Administration Guide* for more information about **System Manager**.

- ❑ If the following error message appears, the syntax for at least one of the options on the command line is incorrect.

The syntax of the command is incorrect.

Verify the format for each option on the command line. See [Syntax on page 380](#).

- ❑ If the following error message appears, a name enclosed in angle brackets (< >) appears on the command line.

The system cannot find the file specified.

Verify that each option on the command line has the correct format and that a value for an option does not have angle brackets (< >).

- ❑ If the following error message appears, the name for the transformation definition is not in the database.

Transformation definition *tname* not found in the OVPI system.

Verify the spelling of the name for the transformation definition. You can use the **-list** option to locate the name.

## trend\_discover

**trend\_discover** allows you to conduct a search that can:

- Find the nodes on your system.
- Ascertain whether or not each node is SNMP manageable.
- Determine the node type; for example, router, hub, switch.
- Automatically update the tables or views that control data collection.

As a result, **trend\_discover** gives you the option of using an automated process to define your network.



Note that the use of **trend\_discover** is optional. You can also populate and update your various node tables manually, if you choose.

## Requirements or Restrictions

- **trend\_discover** must run from a Performance Insight (OVPI) server.
- **trend\_discover** defaults to the **trendadm** user to run if the `USER` environment variable is not set.
- Type Discover is set to run automatically at least once a day from the OVPI scheduler.
- Type Discover requires `.dis` files to run. These files must exist in a specified directory or the `DPIPE_HOME/scripts` directory.
- The Management Console provides GUI access to both types of Discover. Use the **SNMP Discovery** option from the **Tools** menu for IP Discover. Use the **Type Discovery** option from the **Tools** menu for Type Discover. Refer to *Performance Insight Administration Guide* for more information about the GUI tools.

## IP Discover Syntax

IP Discover locates the nodes on your system and determines whether they are SNMP manageable.

```
trend_discover  [ -a delete_age ]  
                  [ -c community_string ]  
                  [ -C ping_packets ]  
                  [ -d debug_level ]  
                  [ -D ]  
                  [ -E ]  
                  [ -f community_names_file ]  
                  -h end_IP_range  
                  [ -H ]  
                  [ -k ]  
                  -l start_IP_range  
                  [ -m ]  
                  [ -o SNMP_timeout ]  
                  [ -O ping_timeout ]  
                  [ -p max_entries ]  
                  [ -P SNMP_port_number ]  
                  [ -q database_server ]  
                  [ -r SNMP_retries ]  
                  -s network_subnet  
                  [ -S ping_packet_size ]  
                  [ -u username ]  
                  [ -V ]  
                  [ -z ]
```

The minimum syntax required for the IP Discover command is shown below:

```
trend_discover -l start_IP_range -h end_IP_range -s network_subnet
```

## IP Discover Options

IP Discover has the following options:

- a** Specifies the *delete\_age*, which is the number of consecutive attempts to ping a node that must fail before automatically deleting the node from the *dsi\_nodes* and *dl\_type* views.  
The default is **10**.
- c** Specifies the single community string to use for all SNMP GETs.
- C** Specifies the *ping\_packets*, which is the number of packets that can be in a discover ping.  
The default is **1**.  
This option is in UPPERCASE.
- d** Specifies a debug output level. Values of **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is no debug output.  
Debug output writes to standard output.
- D** Suppresses domain names. This option truncates the translated host names starting from the first period in the host name.  
This option is in UPPERCASE.
- E** Echoes the progress of Discover to standard output, which is usually the screen.  
This option is in UPPERCASE.
- f** Specifies the *community\_names\_file*, which is a file containing community strings that Discover uses for SNMP GETs. Discover looks for the specified file in the `$DPIPE_HOME/scripts` directory unless you specify a path for the file.
- h** Defines the *end\_IP\_range*, which is the maximum value of the discover range. If the value is incomplete, Discover appends zeros to the end of that value. For example, if you input the value **134.70**, Discover assumes that input to be **134.70.0.0**.

- H** This is the help option, which displays a list of available Discover command line options to the screen.  
This option is in UPPERCASE.
- k** Disables the execution of the **snmpv2dis** utility.
- l** Defines the *start\_IP\_range*, which is the minimum value of the discover range. If the value is incomplete, Discover appends zeros to the end of that value. For example, if you input the value **134.70**, Discover assumes that input to be **134.70.0.0**.
- m** Disables the collection of a node's mac address (physical address) when Discover runs.  
For example, if a system has two IP addresses, Discover will use the mac address and treat this system as one node instead of two. If you specify the **-m** option, Discover will treat this system as two nodes with two different IP addresses.
- o** Sets the *SNMP\_timeout*, which determines how long Discover will wait before timing out an SNMP GET request.  
The default is **1** second.
- O** Sets the *ping\_timeout*, which specifies the time in milliseconds that must pass before Discover times out a ping when Discover is running from a Windows platform.  
The default is **750** milliseconds.  
This option is in UPPERCASE.
- p** Resets the maximum number of entries that can be in a Protocol Data Unit (pdu).  
The default is **20**.
- P** Defines the *SNMP\_port\_number*, which is the port number to use.  
The default is **161**.  
This option is in UPPERCASE.
- q** Specifies the name of the database in which the discovery information will be stored. If the **-q** option is not used, the default database is used. Use the database name not its hostname.

- r Defines the number of times Discover will retry its SNMP GET if there is no response.
- s Defines the *network\_subnet*, which is the Subnet Mask used in the Discover process. If the value is incomplete, Discover appends zeros to the end of that value. For example, if you input the value **134.70**, Discover assumes that input to be **134.70.0.0**.
- S Specifies the *ping\_packet\_size*, which is the packet size of a discover ping.  
The default is **1** byte.  
This option is in UPPERCASE.
- u Defines the OVPI username of the user conducting the discover. If you do not use this option, Discover attempts to get the *username* from the `USER` environment variable. If Discover cannot locate a `USER` environment variable, it uses **trendadm** for the *username*.
- v Displays the version number of the product.  
This option is in UPPERCASE.
- z Specifies that Discover will attempt to translate a discovered IP address to a host name.



Note that when the node translation (**-z**) option is on and a ping is successful, Discover performs a host name lookup. A previously discovered translated name can only be replaced by another translated name, not an IP address. In other words if the host name lookup fails to return translated name, Discover will not replace the current name with an IP address.



## IP Discover Usage Notes

IP Discover is a manually initiated process; you can initiate it either from the user interface or from the command line. The purpose of IP Discover is to find the devices on a network, and determine whether or not they are SNMP manageable.



Note that any OVPI user can initiate Discover, but only from an OVPI server. On OVPI clients, Discover is disabled.

### How IP Discover Works

You can initiate an IP Discover by defining a range of IP addresses, a Subnet mask, and one or more read community strings that the system will search. Discover then pings each IP address (except beginning subnet addresses [0] and broadcast addresses [255]) in that IP address range and one of the following occurs:

- If there is no device at the IP address, there is no response.
- If there is a device at that IP address that recognizes the ping, it responds to Discover. From this response, Discover knows that there is a device at that IP address. Discover then:
  - Sends an SNMP GET message to the responding device.
  - Attempts to discover the host name of the device (if you have specified host name translation).

If the device recognizes and responds to the GET, Discover identifies the device as SNMP manageable.

If your system has a protocol to translate IP addresses to host names, and it finds a host name, Discover associates it with the discovered device. If it does not find a host name, Discover lists the node by its IP address.

## IP Discover View Population

When Discover gets a response from an SNMP capable device, it inserts the host name (or IP address) of the device into the `dsi_nodes` view. Once the host name exists in `dsi_nodes`, OVPI can access the discovered device.



Note that **trend\_discover** only places primary IP addresses, or host names if using translation, into `dsi_nodes`.

## Specifying Community Strings for an SNMP GET Request

When Discover performs an SNMP GET request, the community strings it uses can be defined in the following ways:

- If you do not specify a community string, Discover will use the default, which is public.
- If you want to specify a single community string for all the SNMP GETs in a discover, you can use the **-c** *community\_string* option.
- Whatever character string you input with the **-c** option will be used as the identifying community string for the GET requests.
- If you want to specify multiple community strings for the SNMP GETs, you can use the **-f** option.

This option can be used in two ways:

- If you use the syntax **-f** *file\_name*, where *file\_name* is the name of a file, but does not include the file path, Discover will look for that file only in the **\$DPIPE\_HOME/scripts** directory.
- If you use the syntax **-f** *file\_path*, where *file\_path* is the name and path of a file (including either / or \), Discover will look for that file only in the specified path.

This file is a regular ASCII text file, with one read community string per line. Discover will try the community strings in this file until the first successful SNMP request is performed.

## Community Strings Files

Discover uses the entries in the Community Strings file in the order in which they appear. The sequence is as follows:

- 1 Discover polls the first node, using the strings identified in the Community Strings file.

Discover polls using the first string. If there is no response, Discover tries the second string, then the third, and so on.

When the node responds to a poll, Discover classifies that device as responding to that community string, and goes on to the next node.

- 2 Discover does the same for each node.

It is up to you to determine in which order the community strings appear in the Community Strings file.

► Note that in some cases, it is possible for devices on a network to respond to multiple community strings.

### Example

Some RMON vendors allow the use of public as the read community string for MIB-II tables, but require different community strings for RMON tables. This community string can also be used to GET MIB-II tables. In this case, the community strings file should list the RMON community string above the public community string.

► If a node is discovered with a community string other than the one it had when it was originally discovered, its community string will be updated only if the original community string was public.

When you create a Community Strings file, it is recommend that you list the more common community strings first; this can expedite the discover process. However, you should consider the possibility that your system may include devices that respond to multiple community strings, as described above.

## SNMP Type Discover Syntax

The only valid command line arguments for SNMP Type Discover are:

```
trend_discover  [ -d debug_level ]  
                  [ -E ]  
                  [ -F type_definition_file ]  
                  [ -H ]  
                  [ -k ]  
                  [ -o SNMP_timeout ]  
                  [ -p max_entries_pdu ]  
                  [ -P SNMP_port_number ]  
                  [ -r SNMP_retries ]  
                  [ -t ]  
                  [ -u username ]  
                  [ -v view_name ]  
                  [ -V ]
```

The minimum syntax required for the SNMP Type Discover command is shown below:

```
trend_discover -t
```

## SNMP Type Discover Options

SNMP Type Discover has the following options:

- d** Specifies a debug output level. Values of **1**, **2**, or **3** are valid. The higher the number, the more detailed the information. The default is no debug output. Debug output writes to standard output.
- E** Echoes the progress of Discover to standard output, which is usually the screen.  
This option is in UPPERCASE.

- F** Names the type definition file. Discover looks for the specified file in the `$DPIPE_HOME/scripts` directory unless you specify a path for the file.  
If this option is missing, Discover will look for **.dis** files in the directory, `DPIPE_HOME/scripts`. If the **.dis** files are missing, an error message appears.  
This option is in UPPERCASE.
- H** Displays the list of available Discover command line options (help).  
This option is in UPPERCASE.
- k** Disables the execution of the **snmpv2dis** utility.
- o** Sets the *SNMP\_timeout*, which determines how long Discover will wait before timing out an SNMP GET request.
- p** Resets the maximum number of entries that can be in a Protocol Data Unit (pdu).  
The default is **20**.
- P** Defines the *SNMP\_port\_number*, which is the port number to use.  
The default is **161**.  
This option is in UPPERCASE.
- r** Defines the number of times Discover will retry its SNMP GET if there is no response.
- t** Causes Discover to run an SNMP Type discover.
- u** Defines the OVPI user name of the user conducting the discover. If you do not use this option, Discover attempts to get the *username* from the `USER` environment variable. If Discover cannot locate a `USER` environment variable, it uses **trendadm** for the *username*.
- v** Specifies the name of the view to discover.
- V** Displays the version number of the product.  
This option is in UPPERCASE.

## Naming Convention

Type discover files must have the `.dis` extension and reside in the `DPIPE_HOME\scripts` directory.

## Type Discover Usage Notes

SNMP Type Discover typically runs automatically, once a day from the OVPI scheduler. You can initiate it in the following ways:

- Package Manager, when you use it to install a report pack
- From the command line
- From the Management Console, **Tools** menu

The purpose of SNMP Type Discover is to identify the nature of the devices in the `dsi_nodes` view.

In particular, SNMP Discover determines the Type of a discovered device. SNMP Type Discover interrogates nodes to determine what kind of device they are, and records the information in the OVPI database. This identification allows OVPI to target a specific type of device for data collection.

In SNMP Type Discover, the Discover function reads the `dsi_nodes` and `d1_type` views to identify the nodes that require type validation.

Discover uses special files, identified by the extension `.dis`, to determine whether or not a device is of a certain type. Each `.dis` file contains the necessary protocols to test a node for a single, specific type. See [Type Definition Files on page 399](#) for more information about `.dis` files.

## SNMP Type Discover View Population

There are two database views that are affected by SNMP Type Discover: `dsi_nodes` and `dl_type`.

<code>dsi_nodes</code>	The <code>dsi_nodes</code> view contains a row for each recognized IP node on your system. In addition, one column of <code>dsi_nodes</code> identifies whether a node is SNMP or RMON (default is SNMP). When SNMP Type Discover identifies an RMON-manageable device, it updates this column of <code>dsi_nodes</code> .
<code>dl_type</code>	For each node on your network, the <code>dl_type</code> view identifies the type of device it is. SNMP Type Discover populates this view by interrogating each new node in <code>dsi_nodes</code> , and adding an entry to <code>dl_type</code> .

## Type Definition Files

When you execute an SNMP Type Discover, the Discover function tries to assign different types to the nodes specified in `dsi_nodes`. Once a node is determined to be of a particular type, it is inserted into `dl_type`.

SNMP Type Discover is driven by information defined in Type Definition files. The path of a Type Definition file can be specified via the `-F` option. By default, **trend\_discover** searches for `*.dis` files in the `$DPIPE_HOME/scripts` directory. If `.dis` files are missing, an error message appears. Either install a report pack or create a custom report with a corresponding `.dis` file before running Type Discover again.



Note that once a node is determined to be of particular type, **trend\_discover** will not try to rediscover that node for the same type again.

## Syntax

The syntax rules for a Type Definition file follow.

- Every line in a Type Definition file must end with a semi-colon (`;`), except for comments.

- Comments begin with a slash and an asterisk (**/\***) and end with an asterisk and a slash (**\*/**), as shown in the following example:

```
/* this is a comment */
```

- Blanks are ignored in the input file, unless they are inside a string (between single quotes), as shown in the following example:

```
` this is a string `
```

- Each action begins with a keyword. The valid keywords for Type Definition files are **typename**, **collection**, and **nodetype**. Use of the **collection** and **nodetype** keywords is optional. The syntax for each keyword follows:

Syntax	Description
<b>typename</b> : <i>name_of_type</i> ;	Assigns a name to a type. Example: <b>typename</b> : <b>cisco_routers</b> ;
<b>collection</b> : <b>no</b> ; or <b>collection</b> : <b>yes</b> ; The default is <b>no</b> .	Specifies whether or not the polling policy controls Type Discover. If the value is <b>yes</b> , then <b>trend_discover</b> performs type discover only if there is a polling policy defined for this type (Group Name).
<b>nodetype</b> : <i>collect_type</i> ; where <i>collect_type</i> is <b>rmon</b> or <b>snmp</b> . The default is <b>snmp</b> .	Specifies whether this is an RMON or regular SNMP table.

## SNMP Tests

The actual definition of the type defines one or more SNMP Tests that a device must pass in order to be of the given type. If multiple SNMP Tests are defined for a given type, all of them must pass; for example, AND function is used. The following tests are available:



## Collection Table

This test checks that the device supports the Collection Table specified, to belong to the type.

Syntax: *collectiontable\_name*;  
 where *collectiontable\_name* is the alias name defined in *dsi\_tab\_alias*.

Example: **mib-II\_ifentry**;

## Simple Object Identifier (Oid)

This test checks that the device supports the OID. To pass this test, the device must support the OID.

Any value returned by the device for that OID indicates that the device supports the OID.

Syntax: *oid*;

Example: **1.3.6.1.2.1.1.1**;

## Simple NOT Object Identifier (Oid)

This test checks that the device does not support the OID. To pass this test, the device must NOT support the OID.

Syntax: *~oid*;

Example: **~1.3.6.1.2.1.1.1**;

## Value

To pass this test, the device must support the given OID and the return value must satisfy the defined expression. This test has 4 expressions:

- This first expression checks that the OID is equal to the specified string.
- This second expression checks that the OID is not equal to the specified string.

- This third expression checks that the OID is equal to the specified number.
- This fourth expression checks that the OID is not equal to the specified number.

If the *string\_value* contains wildcard characters, then the compare is not case-sensitive; otherwise, the compare is case-sensitive.

```
Syntax:  oid = 'string_value';
         or
         oid != 'string_value';
         or
         oid = numerical_value;
         or
         oid != numerical_value;
```

```
Example1: 1.3.6.1.2.1.1.1 = 'cisco router';
          /* this is regular string compare, case sensitive */
```

```
Example2: 1.3.6.1.2.1.1.1 = '*cisco*';
          /* this is wildcard character compare, when wildcard
          characters are used trend_discover will perform case
          insensitive compare */
```

```
Example3: 1.3.6.1.2.1.1.1 != 'bay router';
          /* this is a not equal test */
```

```
Example4: 1.3.6.1.2.1.1.1=453;
```

## Type Definition File Examples

### Example 1

```
/* this file defines 3com_device type */
/* the test is done on sysDescr oid */
typename:3com_devices;
collection:no;
1.3.6.1.2.1.1.1='*3com*';
```

## Example 2

```
/* this file defines 3com_routers */
/* the test is done on sysDescr oid and ipForwarding oid */
typename:3com_router;
collection:no;
1.3.6.1.2.1.1.1=`*3com*`;
1.3.6.1.2.1.4.1=1;
```

## Example 3

```
/* this file will define types that support mib-II_ifEntry */
/* collectiontable_name and have ipForwarding turned on */
typename:mibII;
collection:no;
mib-II_ifEntry;
1.3.6.1.2.1.4.1=1;
```

## Example 4

```
/* this file will define rmon1 ether stats type */
/* this type is limited to rmon1 devices that do not support */
/* rmon2 extensions */
typename:rmon1ethstats;
collection:no;
nodetype:rmon;
~1.3.6.1.2.1.16.1.4.1.1;
/* does not support rmon2 extension defined for rmon1 */
1.3.6.1.2.1.16.1.1.1.1; /* must support etherStatsIndex oid */
```



## trendexec

The **trendexec** program uses the **trend\_sum** program to execute the **trend\_sum** procedures listed in the database; it performs these functions when the time interval specified on the command line matches the time interval in the database. **trendtimer** contains entries for the **trendexec** program to run on an intermittent basis. You can launch the **trendexec** program to run at a different time from the command line.

### Requirements or Restrictions

- An OVPI database server must be available.

## Syntax

The **trendexec** command uses the following syntax:

```
trendexec  [ -b database_server ]  
            [ -d debug_level ]  
            [ -h ]  
            -i interval  
            [ -v ]
```

## Options

The **trendexec** command has the following options:

- b** Used to specify an alternate *database\_server*.
- d** Sets the debug output level in the **trend\_sum** program. Valid values for *debug\_level* are: **0**, **1**, **2**, **3**, **4**, and **5**. The default is **0**. The higher the number, the more detailed the information. Debug output is written to the standard output destination. Use this option only for testing in coordination with HP Technical Support.
- h** Displays the command line options.
- i** Used to specify the time interval in minutes. This option is required.
- v** Displays version information. This option is in UPPERCASE.

## Example

When executed, the command below locates and executes procedures to be run every 5 minutes.

```
trendexec -i 5
```





## trend\_export

The **trend\_export** program allows you to export data from the database into a text file.

### Requirements or Restrictions

- This command requires the **-o** option to specify a path and file name; there is no default.
- One of the following options must appear on the command line to provide a source for the data: **-t**, **-r**, **-i**.
- When the **-i** option is on the command line, the system ignores all other options.
- When the **max** keyword is in the input parameter file, the system ignores the following constraint keywords: **begindate**, **finishdate**, **begintime**, and **finishtime**; it also ignores any embedded **start** or **end** date constraints in the original **.rep** file.

## Syntax

The **trend\_export** command uses the following syntax:

```

trend_export [ -a { y } ]
                [ -d { y } ]
                [ -f delimiter ]
                [ -i file_name ]
                [ -m { y } ]
                [ -o export_file ]
                [ -p num_rows ]
                [ -quotes { y } ]
                [ -r report_name ]
                [ -s database_server ]
                [ -t table_name ]

```

## Options

The **trend\_export** command has the following options:

- a**        Use this option to specify if the text file includes column headers.  
Valid values:  
**y**        Specifies the text file will include column headers.  
**n**        Specifies the text file will not include column headers.  
The default value is **y** (yes).

- d** Use this option to set the debug mode.  
Valid values:  
**y** Specifies the program will run in debug mode.  
**n** Specifies the command will not produce any debug output.  
The default value is **n** (no).
- f** Use this option to specify the type of delimiter in the output text file that separates the data fields.  
Valid values:  
**tab** Use this value to generate a tab-separated text output file.  
**comma** Use this value to generate a comma-separated text output file  
The default value is **tab**.
- i** Use this option to specify the full path and file name of the input parameter file. See [Input Parameter File on page 413](#) for more information about the input parameter file. When you use this option, the system ignores all other options on the command line.
- m** Use this option to only include data with the most recent timestamp, which is the maximum `ta_period` value in the source data table.  
Valid values:  
**y** Only include data with the most recent timestamp.  
**n** Include all data regardless of the timestamp.  
The default value is **n** (no).
- o** Use this option to specify the name of the output file. This name must include the complete path and file name for the output file. If the path name is missing, the system will use the current working path.  
There is no default name.  
This is a required option except when the **-i** option is on the command line.

- p** Use this option to specify the maximum number of rows to export to the output file. This is the maximum number of rows that the output file will contain. If the source file has more rows, then the system will export this number of rows only; however, if there are fewer rows than this number, the system will export all the rows in the source file.

The default is **5000**.
- quotes** Use this option to specify that there are double quotes around string data.

Valid values:

  - y** There are double quotes around string data.
  - n** There are single quotes around string data.

The default value is **n** (no).
- r** Use this option to specify the name of the report that contains the data to export. This report is a `.rep` file that contains a single data element.
- s** Use this option to specify the name of the database server that contains the data to export.

This option is in UPPERCASE.
- t** Use this option to specify the name of the table that contains the data to export.

## Usage Notes

OVPI provides two methods for supplying information to **trend\_export**. One method is by using the command-line options. The other method is by using an input parameter file, which is the only method for generating multiple reports and multiple instances of those reports.

## Input Parameter File

You can use an input parameter file to export one or more text files from one or more reports and one or more instances of those reports. When you use the **-i** option to point the process to an input parameter file, the system ignores all other command-line options. This is the only method that you can use to generate multiple reports and multiple instances of those reports.

### Input Parameter File Rules

The guidelines for formatting the input parameter file follow.

- There is one parameter keyword entry per line.
- All entries of keywords with arguments use the format:  
*keyword = argument.*
- Each report to be run must be blocked off with a **start** and **end** parameter keyword.
- An asterisk (\*) in the first column indicates a comment.
- The system ignores any keywords not listed in the following tables.

### Input Parameter File Keyword Syntax

The following tables show the syntax of the keywords for the **trend\_export** input file with their equivalent command line options. The descriptions for the keywords are on [page 415](#) and are the same as for the corresponding command line options. [Table 21](#) shows the required keywords and [Table 22](#) shows the optional keywords for the input parameter file.

**Table 21 Required Keywords - trend\_export Input Parameter File**

Keyword	Corresponding Command-Line Option
<b>start</b>	
<b>report</b> = <i>rpt_name</i>	<b>-r</b>
<b>output</b> = <i>file_name</i>	<b>-o</b>
<b>end</b>	

**Table 22 Valid Keywords - trend\_export Input Parameter File**

<b>Keyword</b>	<b>Corresponding Command-Line Option</b>
<b>*</b>	
<b>begindate</b> = <i>mm/dd/yy</i>	
<b>begintime</b> = <i>hh:mm</i>	
<b>condense</b> = $\begin{Bmatrix} \mathbf{y} \\ \mathbf{n} \end{Bmatrix}$	<b>-c</b> (This option is no longer available.)
<b>dsquery</b> = <i>server_name</i>	<b>-S</b>
<b>exception</b> = $\begin{Bmatrix} \mathbf{y} \\ \mathbf{n} \end{Bmatrix}$	
<b>finishdate</b> = <i>mm/dd/yy</i>	
<b>finishtime</b> = <i>hh:mm</i>	
<b>format</b> = <i>delimiter</i>	<b>-f</b>
<b>frequency</b> = <i>value</i>	
<b>headers</b> $\begin{Bmatrix} \mathbf{y} \\ \mathbf{n} \end{Bmatrix}$	<b>-a</b>
<b>instances</b> = <i>value</i>	
<b>max</b> $\begin{Bmatrix} \mathbf{y} \\ \mathbf{n} \end{Bmatrix}$	<b>-m</b>
<b>maxlines</b> = <i>num_rows</i>	<b>-p</b>
<b>style</b> = <i>value</i>	

## Input Parameter File Keyword Descriptions

The format for the following keywords that have arguments is *keyword = argument*.

**begindate** Use this keyword to specify the beginning date of the data that you want to export from the source.

The format is *mm/dd/yy*.

where: *mm* is the 2-digit month.

*dd* is the 2-digit day.

*yy* is the 2-digit year.

**begintime** Use this keyword to specify the beginning time of the data that you want to export from the source.

The format is *hh:mm*.

where: *hh* is the 2-digit hour.

*mm* is the 2-digit minute.

The default is **00:00**.

**condense** Use this option to remove the trailing blanks from each column included in the SQL select statement.

The default is **n** (no).

**dsquery** Use this keyword to specify the name of the server that contains the data.

The default is the value in the DDSQUERY environment variable.

**end** Use this keyword to mark the end of the keywords for each report in the file. Each report to be run must be blocked off with a start and end statement. You can export data from multiple reports.

This is a required keyword.

**exception** Use this keyword to specify a report as an exception report and generate a list of instances that contains target\_name/table\_key pairs that match the exception criteria.

When you use this keyword, you can use the results from an exception report to drive drilldown reports.

**y** Generates the list of target\_name/table\_key pairs that match the exception criteria.

**n** Does not generate a list.

The default is **n** (no).

**finishdate** Use this keyword to specify the ending date of the data that you want to export from the source.

The format is *mm/dd/yy*.

where: *mm* is the 2-digit month.

*dd* is the 2-digit day.

*yy* is the 2-digit year.

**finishtime** Use this keyword to specify the ending time of the data that you want to export from the source.

The format is *hh:mm*.

where: *hh* is the 2-digit hour.

*mm* is the 2-digit minute.

The default is **23:59**.

**format** Use this keyword to specify the type of delimiter in the output text file that separates the data fields.

Valid values:

**tab** Use this value to generate a tab-separated text output file.

**comma** Use this value to generate a comma-separated text output file

The default is **tab**.



**frequency** Use this keyword to run the same report on a daily, weekly, or monthly basis. When you use it, you will not need to modify the control parameter file.

Valid values:

**daily** Use this value to query the previous day's data. For example, if the current date were 9/1/2004, then the report would query for data from 8/31/04 00:00 to 8/31/04 23:59.

**weekly** Use this value to query the previous week's data. For example, if today was Wednesday September 1, 2004, then the report would query for data from Monday August 30, 2004 00:00 to Sunday September 5, 2004 23:59.

**monthly** Use this value to query the previous month's data. For example, if today was September 1, 2004, then the report would query for data from August 1, 2004 00:00 to August 31, 2004 23:59.

Whenever you actually run the report, the system will query the data for the previous time period specified.

When you use this keyword, the system ignores any other data constraint in the same report specification block such as **max**, **begindate**, and **finishdate**.

**headers** Use this option to specify if the text file includes column headers.

Valid values:

**y** Specifies the text file will include column headers.

**n** Specifies the text file will not include column headers.

The default is **y** (yes).

**instances** Use this keyword to identify the `target_name` and `table_key` pairs that contain the data for the query. There are two formats; one format specifies one or more instance pairs, with each pair enclosed in parentheses, and the other format is the name of a file that contains the instance pairs.

### Format 1

**instances** = *pair1;pair2; ... pairN*

where: *pair* is (*target\_name,table\_key*)

*target\_name* is the name of the device that is the source of the data.

*table\_key* is the unique managed object within the target device.

### Format 2

**instances** = *file\_name*

where: *file\_name* is the complete path and file name of the file that contains the target name/table key instance pairs in the following form.

```
target-name1, table-key.1
target-name1, table-key.2
target-name2, table-key.1
```

Note that you can generate an instances file by specifying a report as an exception report. When a report specification block contains the **exception=y** keyword, the text output file generated is simply a list, which is the matching target name/table key pairs from the exception criteria. You can use the results from an exception report to drive drilldown reports. See [Example 4](#) on page 423.

You can have multiple **instances** parameters for each report.

- max** Use this keyword to only include data with the most recent timestamp, which is the maximum `ta_period` value in the source data table.
- Valid values:
- y** Only include data with the most recent timestamp.
  - n** Include all data regardless of the timestamp.
- The default is **n** (no).
- When the **max** keyword is in the input parameter file, the system ignores the following constraint keywords: **begindate**, **finishdate**, **begintime**, and **finishtime**; it also ignores any embedded **start** or **end** date constraints in the original **.rep** file.
- maxlines** Use this keyword to specify the maximum number of rows that the system will export into the output text file. The value is any positive integer.
- The default is **5000**.
- output** Use this keyword to identify the name of the output text file. The name must contain the complete path and file name for the output file. If you include the **exception=y** keyword in the list of parameters, the filename is the list of instance pairs.
- This is a required keyword.
- report** Use this keyword to specify the name of the report that contains the data to export. This report is a `.rep` file that contains a single data element. The name must contain the complete path and file name for the report.
- This is a required keyword.
- start** Use this keyword to mark the beginning of the keywords for each report in the file. Each report to be run must be blocked off with a start and end statement. You can export data from multiple reports.
- This is a required keyword.

**style** Use this keyword to specify the arrangement of the rows returned for multiple instances.

Valid values:

**individual** Use this value to write the rows into separate files, one for each target name/table key pair. In this case, each output file name will have *target\_name.table\_key* appended to its name.

**combine** Use this value to combine the rows into a single output file.

If there are no **instances** keywords in the parameter file, the system will ignore the **style** keyword.

The default is **individual**.

## Examples

There are two sets of examples in this section. The first set of examples show the options on the command line. The second set of examples show the keywords in the input parameter file.

### Command-line Examples

#### Example 1

You can use the following command to export data from the `KV_IRDevPorts` table to a text output file named `kvdata` in the `$DPIPE_HOME/tmp/export` directory. The text output file will have tab delimiters and 1000 rows of data from the specified table.

```
trend_export -o $DPIPE_HOME/tmp/export/kvdata.txt -f tab -p 1000
-t KV_IRDevPorts
```

#### Example 2

You can use the following command to export data from the `export` report in the `home/myuseraccount/reports` directory to a text output file named `kvdata` in the `$DPIPE_HOME/tmp/export` directory. The text output file will have comma delimiters and 5000 rows of data from the specified table.

```
trend_export -o $DPIPE_HOME/tmp/export/kvdata.txt -f comma
-r /home/myuseraccount/reports/export.rep
```

### Example 3

You can use the following command to export data from the Daily\_Lan\_Inventory report in the OVPI/reports directory to a text file named daily\_lan\_report.txt in the data directory. The output file will have comma delimiters.

```
trend_export -r /OVPI/reports/Daily_Lan_Inventory.rep
-o /data/daily_lan_report.txt -f comma
```

### Example 4

You can use the following command to export data using an input parameter file named export from the home/myuseraccount/batch directory to a text output file named kvdata in the \$DPIPE\_HOME/tmp/export directory.

```
trend_export -o $DPIPE_HOME/tmp/export/kvdata.txt
-i /home/myuseraccount/batch/export.batch
```

## Input Parameter File Examples

### Example 1

```
* this is a comment line
*
start
report = /apps/OVPI/reports/Mib-II/Daily_LAN_Interface_Inv.rep
output = /tmp/daily_lan_interface_inventory
headers = n
format = comma
dsquery = HARDWARE_SYBASE
condense = n
maxlines = 2000
style = individual
end
```

In this example, the source data comes from the report file named Daily\_LAN\_Interface\_Inventory.rep and the exported data is in the file named /tmp/daily\_lan\_interface\_inventory. The text file generated would have no column headers and would be in a condensed, comma delimited format. Lastly, the query would run against the SQL server HARDWARE\_SYBASE.

## Example 2

```

* this is a comment line*
start
report = /apps/OVPI/reports/Mib-II/Daily_LAN_Interface_Inv.rep
output = /tmp/daily_lan_interface_inventory
headers = n
format = comma
dsquery = HARDWARE_SYBASE
end

start
report = /apps/OVPI/reports/Mib-II/Serial_Interface_Usage.rep
output = /tmp/serial_interface_usageendstart
end

start
report = /myreports/lan_interface_load.rep
output = /myreports/lan_interface_load
max = y
instances = (mynode1,1); (mynode1,2); (mynode2,1); (mynode2,2)
instances = (mynode3,3); (mynode4,1)
end

start
report = /myreports/lan_interface_load.rep
output = /myreports/lan_interface_load
max = y
instances = (mynode1,1); (mynode1,2); (mynode2,1); (mynode2,2)
instances = (mynode3,3); (mynode4,1)
style = combine
format = comma
condense = y
end

```

In this example, **trend\_export** does the following tasks.

- 1 First, it would run the same report as in [Example 1](#).
- 2 The second report run would be `Serial_interface_Usage.rep`. Its output would be a tab-separated, uncondensed data saved in a file called `/tmp/serial_interface_usage`. Notice that `trend_export` uses all the default values for this second report.
- 3 The third report to be run, `lan_interface_load.rep` would produce six tab-separated, uncondensed text files because the keyword **style = individual** is used. The `.rep` report source file is the template to run the query for each of the listed instances. Note that the instances are on multiple lines. They could be on the same line. Also, note that the **max**

keyword indicates that the text files will only contain data for the most recent period available for each instance. The names of the output files will be the following:

```
lan_interface_load.mynode1.1
lan_interface_load.mynode1.2
```

```
lan_interface_load.mynode2.1
lan_interface_load.mynode2.2
```

```
lan_interface_load.mynode3.3
lan_interface_load.mynode4.1
```

- 4 The fourth report would produce the same data as the third report, but it would only produce a single output file called `lan_interface_load`. In addition, the output file would be comma delimited and condensed.

### Example 3

```
start
report = /myreports/lan_interface_load.rep
output = /myreports/lan_interface_load
max = n
begindate = 03/01/04
finishdate = 03/31/04
instances = (mynode1,1); (mynode1,2); (mynode2,1); (mynode2,2)
instances = (mynode3,3); (mynode4,1)
style = combine
format = comma
condense = y
end
```

In this example, **trend\_export** generates a set of reports, in a combined format; that is, it combines all the data from the listed instances into one output file, for only data whose `ta_period` lies between March 1st and March 31st.

### Example 4

```
start
report = /myreports/critical_interfaces.rep
output = /tmp/critical_interfaces_list
frequency = daily
exception = y
max = n
begindate = 03/01/04
finishdate = 03/31/04
format = comma
end
```

```
start
report = /myreports/lan_interface_performance_report.rep
output = /myreports/heavy_hitters
frequency = daily
max = n
instances = /tmp/critical_interfaces_list
format = comma
style = individual
end
```

[Example 4](#) demonstrates the use of the exception keyword. In the first report the **exception** keyword is in the parameter list; this causes the system to generate a target name/table key listing in the file named /tmp/critical\_interfaces\_list. The values in this list are the result of the criteria specified in the exception report. The output from this exception report becomes the instances input list for the next report. Note that the second report is set to **style = individual**, which means that for each target name/table key pair a separate output file will be generated. Also note that the **frequency = daily** keyword was used; this means that both the exception report and the drilldown report will only query for the previous day's data.



## trend\_label

You can use the **trend\_label** command to populate one or more columns in a property table with data from its counterpart data table.



Note that you cannot use **trend\_label** with summarized data tables. That is, columns from tables generated by **trend\_sum** will not populate columns in a property table.

Each data table in the HP OpenView Performance Insight (OVPI) database is associated with a property (key) table. By default, most of the columns in a data table are not present in its associated property table. However, you may find it useful to include some of these data columns in the property table. **trend\_label** allows you to do this.

You can run **trend\_label** from the command line, and schedule it to run regularly in **trendtimer.sched**.

## Syntax

The **trend\_label** command uses the following syntax:

```
trend_label [ -c [ alias= column ]  
              [ -d debug_level ]  
              [ -e column ]  
              [ -h ]  
              -k key_table  
              [ -n ]  
              [ -o hour ]  
              [ -r [ alias= column ]  
              -t source_data_table  
              [ -v ]
```

# Options

The **trend\_label** command has the following options:

- c Use this option to identify the column in the source data table that you want to use to populate the column in the property table. The *alias* parameter is the name assigned to the column in the property table and the *column* parameter is the name of the column in the source data table. When you use this option, **trend\_label** searches the property table for the column named by *alias*. If the column named *alias* exists, and if its value is null or blanks, **trend\_label** populates the column with data from the column named *column* in the source data table. If the column exists and its value is non-null or non-blank, the existing value in the target property table row is not changed.

If the column named *alias* does not exist in the property table, **trend\_label** creates it and then populates it in the manner described above.

You can repeat this option multiple times in the **trend\_label** statement to identify different property and data table columns or to concatenate column substrings or columns in the source data table to populate the property table column.

If you omit *alias=* from the command, the property table column is assigned the same name as the column in the source data table.

See [Usage Notes on page 429](#) and [Examples on page 432](#) for a complete description of this option with examples.

- d Sets the debug output level. Valid values are 1, 2, and 3. The higher the number, the more detailed the information. Debug output is written to the standard output destination. This option is for development purposes.
- e Identifies the column in the source data table that provides the data to populate the *dsi\_descr* column in the property table.
- h Displays the syntax of the **trend\_label** command.
- k Identifies the destination property table. Specify the SQL name of the table.

- n** Use this option to specify that the default target row in the source data table is the one where the maximum `ta_period` that is less than or equal to the current time (the minutes and seconds portions of the `ta_period` value are set to zeroes) minus 1 hour on today's date. If you omit both this option and the **-o** option, the default is the latest `ta_period`. This option cannot be on the same command line as the **-o** option. See [Locating the Target Row in the Source Data Table on page 429](#) for a detailed explanation of how the target row is located.
- o** Use this option to specify the hour of the previous day. Valid values are **0** (midnight) through **23**. The system uses this value to locate the row in the source data table associated with the `dsi_key_id` that it will use to populate the property table columns. If you omit both this option and the **-n** option, the default is the latest `ta_period`. This option cannot be on the same command line as the **-n** option. See [Locating the Target Row in the Source Data Table on page 429](#) for a detailed explanation of how the target row is located.
- r** Uses the same syntax and application as the **-c** option with the following exception: The target value from the source data table populates the associated column in the property table even if that column already exists and has a non-null or non-blank value.
- t** Identifies the SQL name of the source data table. The table is typically a rate table (but can be a raw table). Summary tables cannot be used as a source.
- v** Displays the current **trend\_label** command version. For example, a return value of 4.0 means version 4.0.

## Usage Notes

This section provides information on various aspects of the **trend\_label** command usage.

Note that omitting *alias=* from the command may produce an ambiguous error message such as "prog-name date/time - Ambiguous column name XXXX", which indicates a situation where the property table and data table both have a column called XXXX. The query uses both property and data tables in the *from* clause and uses only XXXX in the *select* clause; it does not specify the owner table name.

To resolve this situation, do the following:

- 1 Start an SQL session with user **dsi\_dpipes**.
- 2 Perform **sp\_help** on the property table to get the column-name listing.
- 3 Drop the improper column from the property table with the following syntax:

```
alter table tablename drop column_name
```

- 4 Exit the SQL session.
- 5 Correct the **trend\_label** syntax to use *alias=column*.

## Populating the dsi\_descr Column

When you generate a report, the report title appears above the graph and the legend appears below the graph. If the value of the *dsi\_descr* column in the property table that the report uses is null or blank, the legend simply displays the name of the node on which the report is based. However, if the *dsi\_descr* column is populated, the legend displays the description that appears in the column. This can make graphical reports easier to identify and read.

## Locating the Target Row in the Source Data Table

The source data table contains one row for each unique *dsi\_key\_id* for each collection period. Thus, if collections occur at 15 minute intervals, there are 96 rows for each unique *dsi\_key\_id*, which is four rows per hour \* 24 hours per day equals 96 rows.

If the **-o** option is used, the system compares the hour (0-23) specified in the option to the `ta_period` timestamp in the rows of the source data table as follows:

- 1 Get the timestamp for the current time minus 24 hours. Thus, if the current time is 11:22:35 on June 12, 2001, the resulting timestamp is 11:22:35 on June 11.
- 2 Make the hour portion of the timestamp equal to the value (0-23) specified in the **-o** option. Thus, if the **trend\_label** command line has the option **-o 4** on it, the timestamp is 04:22:35 on June 11.
- 3 Set the minutes and seconds portions of the timestamp to zeroes. In this example, 04:22:35 on June 11 becomes 04:00:00 on June 11. Thus, the target record in the source data table in this example is the one for the `dsi_key_id` where `ta_period` is Jun 11 2001 04:00:00.
- 4 If there is no row with the target time period, **trend\_label** decrements the hour by 1 until it finds a match. For example, if there is no row for the `dsi_key_id` where the `ta_period` time is 04:00:00, **trend\_label** looks for a time of 03:00:00, decrementing the hour by 1 in this manner until it finds a match.

If the **-n** option is used, the target row in the source table is the one for `dsi_key_id` where the maximum `ta_period` timestamp is less than or equal to the current time (with hours and minutes zeroed) minus 1 hour. For example, if the current time is 10:30 AM on June 12, 2001:

- 1 Get the `dsi_key_id` record in the source data table where the `ta_period` timestamp is Jun 12 2001 09:00:00 AM.
- 2 If no record exists for 09:00:00, **trend\_label** decrements the hour by 1 until it finds a match. For example, if there is no row for the `dsi_key_id` where the `ta_period` time is 09:00:00, **trend\_label** looks for a time of 08:00:00, decrementing the hour by 1 in this manner until it finds a match.

If neither the **-o** option nor the **-n** option is used, the default is the last `ta_period` timestamp in the rows of the source data table.

## Ensuring Property Table/Data Table Compatibility

You must ensure that the specified data table (**-t** option) uses the specified property table (**-k** option) in the OVPI database. The **trend\_label** command does not check for this.

## Update Restrictions

You cannot update the values in the property table columns `dsi_key_id`, `dsi_target_name`, or `dsi_table_key`.

## Extracting Substrings from Column Values

When you use the `-e`, `-c`, and `-r` options, you can specify a substring that **trend\_label** will extract from the source column and use to populate the destination property table column with the following syntax:

*column:offset,length*

where: *column* Is the column name in the source data table.

*offset* Is the starting character position of the substring in the column.

*length* Is the number of characters to include in the substring beginning with the offset column position.

For example, if you want to extract a substring that is 8 characters long and begins in position 13 of the `ta_period` value, use the following entry.

```
ta_period:13,8
```

This entry replaces the *column* parameter in the `-e`, `-c`, or `-r` option.

## Concatenating Column Values

You can populate a property table column with a value that is concatenated from the values of multiple columns and/or column substrings in the source data table by repeating the `-e`, `-c`, and `-r` options using the same *alias=* and different source column names or substrings. For example, if you want to create, if necessary, and populate a property table column named `dsi_eurodate` with the concatenated substrings from positions 5-7, 1-4, and 8-11 of the `ta_period` column in the source data table, you can use the following **trend\_label** command:

```
trend_label -k Ksi_dbstats_ -t Rsi_dbstats_  
-c dsi_eurodate=ta_period:5,3 -c dsi_eurodate=ta_period:1,4  
-c dsi_eurodate=ta_period:8,4
```

In this case, if the value of `ta_period` in the source data table is **Jul 29 2001 04:00:00:000AM**, then the value used to populate `dsi_eurodate` in the property table is **29 Jul 2001**.

## Examples

### Example 1

If you want to populate the `dsi_descr` column in the `Kib_ii_ifentry_` property table with the latest data contained in the `ifdescr010` column from the `mib_ii_ifentry_` source data table, use the following command.

```
trend_label -k Kib_ii_ifentry_ -t mib_ii_ifentry_ -e ifdescr010
```

### Example 2

If you want to populate three columns in the `Kib_ii_ifentry_` property table with the latest data contained from the `mib_ii_ifentry_` source data table, use the following command.

```
trend_label -k Kib_ii_ifentry_ -t mib_ii_ifentry_ -e ifdescr010  
-c speed=ifspeed013 -c type=ifttype011
```

In this example, `trend_label` populates the `dsi_descr` column in the `Kib_ii_ifentry_` property table with the latest data contained in the `ifdescr010` column from the `mib_ii_ifentry_` source data table. In addition, it creates the column (if it does not already exist) and populates the property table column named `speed` with the value for `ifspeed013` in the target source data table row and the property table column named `type` with the value for `ifttype011` in the target source data table row if the property table column values are null or blank. If the value in either column is non-null or non-blank, the current value remains the same.

### Example 3

If you want to populate the `dsi_descr` column in the `Ksi_dbstats` property table with a concatenation of the value for the `user_name` column and the first three characters of the `ta_period` value in the target source table row, you can use the following command.

```
trend_label -k Ksi_dbstats_ -t Rsi_dbstats_ -e user_name  
-e ta_period:1,3
```



In this example, if the `user_name` value is **Jones** and the first three characters of the `ta_period` value are **Nov**, then the value **JonesNov** is the value in the `dsi_descr` column in `Ksi_dbstats`, only if the existing value is null or blanks. If the existing `dsi_descr` value is non-null or non-blank, the value is not changed.

#### Example 4

If you want to populate the `dsi_descr` column in the `Ksi_dbstats` property table in the same way as described for [Example 3](#) with the exception that the existing value of `dsi_descr` is replaced by the concatenation even if that value is non-null or non-blank, you can use the following command.

```
trend_label -k Ksi_dbstats_ -t Rsi_dbstats_ -o 4
-r dsi_descr=user_name -r dsi_descr=ta_period:1,3
```

In this example, the `-r` option causes unconditional replacement of the value; whereas, the `-e` option, in [Example 3](#), replaces the value only if the existing value in the target property table record is null or blanks. Furthermore, the target record in the source data table is the `dsi_key_id` record where the `ta_period` value is 04:00:00AM on the previous day.

#### Example 5

If you want to do the following:

- use the data from the `Rsi_dbstats_data` table where `ta_period` for the `dsi_key_id` equals 04:00:00 AM on the previous day
- concatenate the `user_name` and the first three characters of the `ta_period` value in `Rsi_dbstats_data` table and place the result in the `dsi_descr` column in the `Ksi_dbstats_property` table
- create a column named **dsi\_eurodate** in the `Ksi_dbstats_property` table, if the column does not already exist, and unconditionally update that column with the result of concatenating positions 5-7, 1-4, and 8-11 from the `ta_period` value

You can use the following command:

```
trend_label -k Ksi_dbstats_ -t Rsi_dbstats_ -o 4 -e user_name
-e ta_period:1,3 -r dsi_eurodate=ta_period:5,3
-r dsi_eurodate=ta_period:1,4 -r dsi_eurodate=ta_period:8,4
```

### **Example 6**

If you want to populate the `dsi_descr` column in the `proptb11` property table with the data contained in the `ifdescr010` column from the `datatb12` source data table that has an earlier or equal timestamp to the current time, use the following command.

```
trend_label -k proptb11 -t datatb12 -e ifdescr010 -n
```

If the time when the **trend\_label** command executes is 11:45 AM, the `dsi_key_id` record with a `ta_period` value of today's date at 10:00:00 AM is used. If there is no record for 10:00:00 AM, **trend\_label** searches for a record for 09:00:00 AM and so on backward in 1-hour increments until a match is found, which is the maximum `ta_period` value that is equal to or less than the current hour minus 1 hour.

# trend\_lock

This utility creates a lock to prevent running multiple instances of the same command with its corresponding options.

## Syntax

**trend\_lock** *command\_string*

where: *command\_string* is any command with its corresponding options.

## Usage Notes

The **trend\_lock** utility is a wrapper around command strings to ensure that multiple instances of the same command string are not running at the same time. This situation can occur because **trendtimer** starts new processes at scheduled times regardless of the state of the system.

When you use **trend\_lock** with a command string, it will run the command if the same command string is not already running with **trend\_lock**; otherwise, it will not run the command and place a message in `trend.log`. When **trend\_lock** does not run the specified command string, it does not schedule the same command string for later. If you want to run the same command string later, you must enter it again. Note that if the specified command string automatically runs from **trendtimer**, **trend\_lock** will attempt to run the command string at the next invocation.

## Example

For example, if you want to run only one instance of the specific **db\_delete\_data** command:

```
db_delete_data -t test_tbl_1
```

Use **trend\_lock** in front of the command, as follows:

```
trend_lock db_delete_data -t test_tbl_1
```

If a previous instance of this specific **db\_delete\_data** command is already running, the following message will be in the `trend.log` file on a UNIX system.

```
The previous instance of db_delete_data -t test_tbl_1 is  
already running. The process will not be executed.  
SystemError 11. [Resource temporarily unavailable]
```

When this message appears, the system will cancel the new command. If you want to run the command later, you will need to enter the command again. However, if you run another instance of the **db\_delete\_data** command that is different, such as:

```
trend_lock db_delete_data -t test_tbl_abc
```

The system will run this command because the command string is not identical to the previous command string that is already running.

## Functionality in Commands

Note that this functionality already exists in various commands, such as:

```
indexmaint
mw_collect
tpmaint
trendcopy
trend_discover
trendexec
trend_label
trendpm
trend_proc
trend_sum
```

This means that you would not need to use **trend\_lock** in conjunction with these commands.

## Log Message

The format of the message that appears in `trend.log` follows:

```
The previous instance of command is already running. The
process will not be executed. SystemError sys_error_code.
[sys_error_msg]
```

The `sys_error_code` and `sys_error_msg` will be different depending on the type of operating system.

When you see this message in `trend.log` and it is the last occurrence of the specified command, you may need to run the command again.

*trend\_lock*

# trendpm

The **trendpm** command manages stored procedures used by HP OpenView Performance Insight (OVPI).

## Syntax

The **trendpm** command has the following syntax:

```
trendpm    [ -c code_gen_file ]  
            [ -cs "command_string" ]  
            [ -d ]  
            [ -db trace_level ]  
            [ -e ]  
            [ -f file_name ]  
            [ -g ]  
            [ -h ]  
            [ -ot target_table_name ]
```

```

[ -pe "parameter1=value [, parameter2=value] ..." ]
[ -pg "parameter1=value [, parameter2=value] ..." ]
[ -r ]
[ -s db_server_name ]
[ -t table_name, [proc_app_type], [proc_class], [proc_type] ]
[ -v ]

```

## Options

The **trendpm** command has the following options:

- c**        Specifies the name of the code generated file.
- cs**        This option contains command string options from another program such as **trend\_sum**.
- d**        Delete procedure.
- db**        Set trace parameters. Valid values for the trace level are **1 - 5** where **1** is the lowest verbosity and **5** is the highest verbosity.
- e**        Executes procedure synchronously.
- f**        Specifies the name for the legacy file associated with the procedure to be registered.  
The *file\_name* contains the full path with the file name.
- g**        Generates SQL procedure code.
- h**        List help options.
- ot**        Specifies target table name.



**-pe** Specifies the execution parameters for raw-to-delta procedures. The format for the valid parameters are:

**@bArchive**=*turn\_off\_archiving*  
**@bCheck\_index**=*check\_index*  
**@bDelta\_time**=*delta\_time*  
**@bSuppress\_spike**=*suppress\_spikes*  
**@bVerbose**=*verbose\_value*  
**@debug\_level**=*debug\_level\_pm*  
**@hwm\_data**=*high\_water\_mark*  
**@hwm\_log**=*high\_water\_mark\_log*  
**@line\_suppress\_value**=*min\_filter\_value*  
**@max\_tran\_row\_cnt**=*num\_rows*  
**@retry\_count**=*retry\_count*  
**@retry\_interval**=*retry\_interval*  
**@user\_proc\_name**=*'proc\_name'*  
**@zerror**=*clock\_error\_value*

Do not use any spaces in the parameter list; however, there is a space after the **pe** option. See [pe Option Parameters on page 442](#) for the descriptions of the parameters.

**-pg** Optional parameter values to replace default values in the generated output SQL procedure. The format for the valid parameters are:

**@column\_suppress**=*'column\_name'*  
**@column\_suppress\_value**=*suppress\_value*

The *column\_name* is the name of the column containing counter data to suppress. The *suppress\_value* is the value in the column to suppress.

Do not use any spaces in the parameter list; however, there is a space after the **pg** option. This option only applies for raw-to-delta procedures.

**-r** Registers procedure.

- s** Specifies database server name.
- t** Specifies table name, procedure application type, procedure class, and procedure type. Note that the procedure application type, procedure class, and procedure type values are optional and positional. When you use this option, you must enter at least the *table\_name* and the commas. See [Procedure Application Type Values on page 446](#) for the valid values.
- v** Displays version stamp for **trendpm**.



Note that the **-pe** and **-pg** options require double quotes (“) to enclose the parameters. Use single quotes (‘) to enter any character data from the parameters.

## pe Option Parameters

The descriptions for the **pe** option parameters follow.

- |                      |  |
|----------------------|--|
| <b>@bArchive</b>     | Enables archiving of raw data. The archive function stores the collected data in a raw data table. A value of <b>1</b> archives the raw data. A value of <b>0</b> does not archive the raw data.<br>The default is <b>1</b> .  |
| <b>@bCheck_index</b> | Specifies whether to use existing indices on the upload table or to drop existing indices and then recreate them. The value <b>1</b> means that the existing indices on the upload table are used. The value <b>0</b> means that the existing indices are dropped and then recreated. If the value is <b>1</b> and the proper indices are missing then the <b>trendpm</b> invocation fails.<br>The default is <b>0</b> . |

- @bDelta\_time** Specifies which clock to use to calculate Delta Time. The value of **1** directs the procedure to use System Uptime to calculate Delta Time. The value of **0** directs the procedure to use the Agent Clock Column, which is the `received_ts` column, for the calculation.  
The default is **0**.
- @bSuppress\_spike** Specifies whether to reject samples if there are spikes. A spike occurs when the value of any counter suddenly goes too high, which is when the difference of two consecutive samples from a counter exceeds the spike threshold. The value of the spike threshold is  $2^{31}$  for 32-bit counters or  $2^{51}$  for 64-bit counters. Remember if the difference of the values is negative, account for the rollover of the counter by adding  $2^{32}$  for 32-bit counters or  $2^{52}$  for 64-bit counters.  
Valid values are:
- 1** Rejects samples if a spike occurs.
  - 0** Does not reject samples.
- The default is **1**.
- @bVerbose** Sets the debug output level for the raw-to-delta procedures.  
Valid values are:
- 0** Suppress all messages
  - 1** Show row suppression messages
- The default is **1**.

<b>@debug_level</b>	<p>Sets the debug output level for the <b>trendpm</b> process of <b>mw_collect</b>. Values of <b>0</b>, <b>1</b>, <b>2</b>, or <b>3</b> are valid. The higher the number, the more detailed the information.</p> <p>The default is <b>0</b>, which means no debug output. Debug output is written to standard output. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on <b>mw_collect</b>.</p>
<b>@hwm_data</b>	<p>Specifies the <i>high_water_mark</i>. The high water mark denotes the level at which the database-used size reaches the specified percentage and data collection stops. Valid values are <b>1–100</b>.</p> <p>The default value is <b>90</b> for 90%, which means data aggregation stops when the database is 90% full.</p>
<b>@hwm_log</b>	<p>Specifies the <i>high_water_mark_log</i>, which is the high water mark for the log. Valid values are <b>1–100</b>.</p> <p>The default value is <b>90</b> for 90%, which means data aggregation stops when the log is 90% full.</p>
<b>@line_suppress_value</b>	<p>Sets the minimum filter value. The procedure rejects the sample if the delta value of a counter falls below this value.</p> <p>The default value is <b>-1</b>, which means to accept the entire sample.</p>
<b>@max_tran_row_cnt</b>	<p>Sets the size of the batch to commit, which is the number of rows to commit per transaction. The default value is <b>0</b>, which means the system calculates this value dynamically per table.</p> <p>HP strongly recommends that you use the default value. If this value is too low, it may affect performance; if this value is too high, it may affect concurrency.</p>

<b>@retry_count</b>	<p>Sets the number of times the procedure will try to acquire a lock on the specified object.</p> <p>The default value is <b>60</b>, which is 60 retries.</p>
<b>@retry_interval</b>	<p>Sets the number of seconds the procedure needs to wait in order to acquire a lock on the specified object.</p> <p>The default value is <b>60</b>, which is 60 seconds.</p>
<b>@user_proc_name</b>	<p>Specifies the name of the custom procedure to execute at the end. You can register it as a dependent procedure with the following command:</p> <pre><b>trendpm -r -t <i>input_table,C,D,R</i> -ot <i>output_table</i> -c <i>SQL_file</i>.</b></pre> <p>The <i>SQL_file</i> includes the custom procedure.</p> <p>The default value is <b>NULL</b>, which means that there is no custom procedure.</p>
<b>@zerror</b>	<p>Sets the percentage level for valid data. The value is the percentage of difference between the delta values of two Received Timestamps and two System Uptimes. These statistics come from two consecutive raw data samples.</p> <p>For example, if r1 and s1 are the Received Timestamp and System Uptime for the first sample, and r2 and s2 are the Received Timestamp and System Uptime for the second sample, then the calculation for the value is <math>((r2 - r1) - (s2 - s1)) * 100 / (r2 - r1)</math>. During processing, if the calculated value for the samples exceeds the value set by this option then the samples are rejected.</p> <p>This value is an integer that is less than 255.</p> <p>The default value is <b>10</b>.</p>

## Procedure Application Type Values

The following table provides a list of valid procedure application types and descriptions for the corresponding procedure types.

**Table 23 Valid Values for Procedure Application Type with Procedure Type**

Procedure Type	Valid Procedure Application Type	Procedure Application Type Description
C	C	Custom application type: Custom procedure of type, <b>custom</b> .
R	C	Custom application type: Normalization procedure
R	S	Asset management procedure
R	R	Raw-to-delta procedure
R	Z	Copy stored procedure
U	C	Custom application type: Summary procedure
U	N	Ranking procedure
U	T	Legacy <b>trendit</b> replacement procedure
U	G	General summary procedure
U	F	Forecast summary procedure
U	B	Baseline summary procedure

## trend\_proc

The **trend\_proc** command is a utility that allows you to group together multiple interrelated commands on an HP OpenView Performance Insight (OVPI) system.

### Requirements and Restrictions

- Limit nesting levels to avoid straining the resources.
- Avoid accessing the same database table at the same time.

## Syntax

The **trend\_proc** command uses the following syntax.

```
trend_proc [ -d debug_level ]  
             -f file_name  
             [ -h ]  
             [ -n ]  
             [ -v ]
```

## Options

The descriptions for the command line options of the **trend\_proc** command follows:

- d** Use this option to set the debug output level for **trend\_proc**. Values of **0**, **1**, **2**, **3**, or **4** are valid. The higher the number, the more detailed the information.  
The default is **0**, which means no debug output. Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **trend\_proc**.
- f** Use this option to specify the name of the text file that contains the instructions. If the file is not in the current working directory, you must specify the fully qualified path to the file.  
This is a required option.  
See [The trend\\_proc Input File on page 450](#) for a description of the contents for the file.
- h** Use this option to display the command-line syntax for the **trend\_proc** command.



- n** Use this option to skip the **trend\_lock** locking check. When you use this option, the system can run multiple instances of the same **trend\_proc** command at the same time.  
This option applies only to the command where it appears; it does not apply to the commands in the **trend\_proc** input file.  
See [trend\\_lock on page 435](#) for more information.
- v** Use this option to display the current version of **trend\_proc**.  
This option is in UPPERCASE.

## Usage Notes

The concept behind **trend\_proc** is relatively simple:

- 1 Take a sequence of processes and string them together in such a way that you can execute them with a single command.  
In **trend\_proc** terminology, this series of sequential commands makes up a block, which is the equivalent of a macro.
- 2 Next, make it possible to string blocks together like individual commands.
- 3 When one block finishes its assigned tasks, **trend\_proc** automatically launches the next block and continues this process until it launches all of the blocks.
- 4 Then, to make the process more powerful, make it possible to launch multiple blocks concurrently, so that they run in parallel.
- 5 Finally, make it possible to launch the entire process with a single entry in `trendtimer.sched`.

For example, users whose OVPI networks include satellite servers must export data to their central database every day. Typically, the export process occurs separately from the data roll-up process. If you want to export the data as soon as the system aggregates it, you can put both the roll-up and export processes in a single **trend\_proc** file. This way, as soon as the system aggregates the data, **trend\_proc** automatically exports the data to the proper database.

## The trend\_proc Input File

This section defines the elements of the input file and describes the characteristics of it. This section also describes how the system processes the input files.

### Input File Definitions

A **trend\_proc** file contains one or more blocks of commands. A block is a sequential list of commands to execute. For example, if there are six commands in a block, **trend\_proc** will execute the first command, and wait for that command to be completed. As soon as the first command is complete, **trend\_proc** initiates the second command. When the second command finishes, **trend\_proc** starts the third, and so on until it completes all of the commands in the block.

Most **trend\_proc** files contain multiple blocks, arranged in a linear progression. It is necessary for the blocks to be in the order of desired processing, because **trend\_proc** reads the blocks sequentially.

However, **trend\_proc** is able to execute commands from different blocks concurrently. This is so because **trend\_proc** recognizes two different kinds of blocks in a **trend\_proc** file: **wait** and **nowait**.

- A **wait** block is so called because it causes **trend\_proc** to wait until the block has completed its processing in full before moving on to another block.
- A **nowait** block permits **trend\_proc** to go to the next block in the sequence, and begin executing the commands in that block. The processing in a **nowait** block does not finish before **trend\_proc** starts processing the next block in the file.

The order of the blocks determines how **trend\_proc** will execute the commands from different blocks concurrently. For example, if the input file has three blocks with the first block as a **wait** block and the other blocks are **nowait** blocks, then the last two blocks will run concurrently. On the other hand, if the input file has three blocks with the first two blocks as **nowait** blocks and the third block is a **wait** block, then all three blocks will run concurrently. Note that the commands within the **wait** and **nowait** blocks run sequentially.

## Input File Characteristics

The **trend\_proc** command requires an input file with the following characteristics.

- It is a text file with the extension **.pro**.
- It must contain at least one block, and the blocks must adhere to a particular format, as follows.
  - A block begins with the **begin** statement; it has the following syntax.

```
begin: blockname [ { -wait  
                  -nowait } ]
```

where: *blockname* is a unique name for the block.

- If you do not specify **wait** or **nowait**, the default for the block is **wait**.
- A block can contain zero or more statements that **trend\_proc** will execute sequentially. These statements can be any executable commands, which may or may not be OVPI commands. You must provide the fully qualified path for the command.
- If a block does not contain a command, it is an empty block. This will not affect the performance of the **trend\_proc**, so long as the populated blocks have the correct format.
- A block ends with the **end** statement; it has the following format.

```
end: [ blockname ]
```

Putting the block name in the **end** statement is optional. It can, however, be useful for identification purposes, especially if you nest one **trend\_proc** inside of another. (Note that the brackets are not part of the syntax.)

- The words **begin** and **end** must be in lower case.
- There should not be a space between the statement, **begin** or **end**, and the colon.
- Comments within a block begin with the number character (#).

## Processing the Input File

This section describes how **trend\_proc** processes an input file. For example, a **trend\_proc** file contains five blocks of commands, two of which are **wait** blocks. Each block has a set of commands and appears in the following order in the input file.

Block 1: six commands (wait)

Block 2: seven commands (nowait)

Block 3: four commands (nowait)

Block 4: eleven commands (wait)

Block 5: eight commands (nowait)

Note that each block must have a unique name. The names used above are representative of a naming pattern. If you intend to create your own **trend\_proc** files, it is a good idea to establish a naming convention for your **trend\_proc** blocks.

The processing for this **trend\_proc** file requires four steps, as follows.

### Step 1

When the system launches **trend\_proc** from the appropriate **trend\_proc** entry in `trendtimer.sched`, for example, it executes the first command listed in Block 1. When the first command completes its processing, **trend\_proc** executes the second command in Block 1. Since this block is a **wait** block, **trend\_proc** must complete the entire sequence of six commands in Block 1 before beginning the sequence of commands contained in Block 2.

### Step 2

After **trend\_proc** executes the final command in Block 1, it begins immediately to execute the commands in Block 2. Again, **trend\_proc** will execute the commands in Block 2 in their proper sequence. However, since Block 2 is a **nowait** block, **trend\_proc** also begins to execute the sequence of commands in Block 3. Since Block 3 is also a **nowait** block, **trend\_proc** will also begin to execute the commands in Block 4. At this point, **trend\_proc** is executing commands from three different blocks at the same time.

### Step 3

Block 4 is a **wait** block; so once again, **trend\_proc** must complete the commands in Block 4 before beginning the processes in Block 5. However, it is possible that **trend\_proc** will execute all of the commands in Block 4 before

blocks 2 and 3 are completed. In this circumstance, **trend\_proc** does not have to wait for blocks 2 and 3, once Block 4 has completed its processing, **trend\_proc** will start with Block 5.

#### Step 4

When **trend\_proc** executes the commands in Block 5, the sequence is finished. The processing for the **trend\_proc** file is complete after all blocks finish processing.

Depending on how you format a **trend\_proc** file, you can execute commands from several blocks at once. In the example above, we see **trend\_proc** execute commands from three different blocks that could be running at the same time. This allows a large part of the individual **trend\_proc** file to be running in parallel.

## Processing with Multiple trend\_proc Files

A **trend\_proc** file can have one or more additional **trend\_proc** commands in it. In fact, multiple instances of the **trend\_proc** command can run concurrently, each running parallel processes.

This process of creating a **trend\_proc** file that contains one or more **trend\_proc** commands can be especially useful. Since it is possible for **trend\_proc** commands to conflict with each other, it is sometimes necessary to ensure that one **trend\_proc** command completes its processing before the system launches another. If, however, you create a **trend\_proc** file whose blocks are **trend\_proc** commands, you can launch an entire sequence of OVPI procedures with one entry in the `trendtimer.sched` file.



Note that while it is often a good idea to have a master **trend\_proc** controlling your **trend\_proc** files, you should limit this nesting to two levels. Otherwise, you increase the chance of creating a conflict between your various processes.

Note that **trend\_proc** has an automatic **trend\_lock** locking check that prevents the system from processing more than one instance of the same command string at the same time. This means that if you have a **trend\_proc** file and the initial **trend\_proc** command starts automatically and periodically from **trendtimer**, the system will not start the same command at the next time period if the previous command did not finish processing first.

You can override the **trend\_lock** locking check with the **-n** option. If you use the **-n** option on a **trend\_proc** command that has an input file with multiple **trend\_proc** commands in it, the option will only apply to the **trend\_proc** command where it appears. The effect of the option will not propagate down to any nested **trend\_proc** or executable commands.

### Processing Example with Multiple trend\_proc Files

You have a situation where you are obtaining data from various datapipes with **ee\_collect** on an hourly basis. The data is coming from multiple locations and you want to process that data on an hourly basis.

You can create different **trend\_proc** files to perform a particular function. For example, you can create a **trend\_proc** file that collects the data from the various locations. This file could have **ee\_collect** or **trendcopy** commands for each location. The name of the file could be CollectData. The next **trend\_proc** file would process the collected data; so, this file would have **trend\_sum** commands and any other commands necessary to process the data. The name of this file could be ProcessData. The third **trend\_proc** file would create the reports from the processed data; so, this file would have all the necessary commands to generate the reports. The name of this file could be ReportData. The last **trend\_proc** file would distribute the reports; so, this file would have all the necessary commands to distribute the reports to the various locations. The name of this file could be DistributeData.

You *could* create a separate entry in `trendtimer.sched` for each **trend\_proc** file, provided you spaced them out over time to ensure that each **trend\_proc** finished before the system launched the next one.

Rather than this, you create a fifth **trend\_proc** file, such as ProjectA, to contain the other four. Its blocks would be as follows:

Block A: CollectData (wait)

Block B: ProcessData (wait)

Block C: ReportData (wait)

Block D: DistributeData (wait)

You then put an entry into the `trendtimer.sched` file to run ProjectA for each hour of the day. You can add the **-n** option to the entry in the `trendtimer.sched` file so that the system can begin processing the same command at the next hour since the first internal **trend\_proc** command should be finished. Note that the **trend\_proc** commands inside ProjectA do not use the **-n** option so that the system will not start processing the command if the previous one has not finished; in this case, the system will skip the command if the previous one is still processing.

## Creating a trend\_proc File

Creating your own **trend\_proc** files is a four-step process. You must:

- 1 Define the commands you want to execute.
- 2 Determine the order to run the commands.
- 3 Create the **trend\_proc** file.

You need to make sure you define your blocks in the correct order using the **wait** and **nowait** options; otherwise, the processing may be different than you expect.

- 4 Schedule **trend\_proc** to launch.

## Scheduling a trend\_proc File

After you have created your **trend\_proc** file, you can run it from the command line or place an entry in the `trendtimer.sched` file to run it at the appropriate time. The syntax for this entry follows:

```
trend_proc -f filename
```

where: *filename*

is the name of your **trend\_proc** file.

If you do not use a fully qualified file name, the system will look for the file in the current working directory.

If you have a large or complicated **trend\_proc** file that **trendtimer** starts on a regular basis, you may want to use the **-n** option to prevent the **trend\_lock** locking check.

## Examples

The following examples show some possible applications of **trend\_proc**.

### Example 1

OVPI uses the **trend\_sum** application to maximize the efficiency of data aggregation. If you want to copy that data to the central server from a satellite server, you can use the **trendcopy** command to copy data once the **trend\_sum** command finishes its processing. Such a **trend\_proc** block might look like the one below:

```
begin: block1 wait
trend_sum -e SDifentry -f trendsum.sum
trendcopy -s src_db -S dest_db -t SDifentry
end: block1
```

In this example, the **trend\_sum** command accesses the table, **SDifentry**. It uses the instructions in the input file **trendsum.sum**, which is in the same directory where this **trend\_proc** file is running. After the **trend\_sum** processing is complete, the system invokes the **trendcopy** command to copy the same table from the satellite server, which is **src\_db**, to the central server, which is **dest\_db**.

### Example 2

In this example, the first block, **block0**, is a **wait** block; so the system will complete processing the **trend\_proc** command in this block before it starts processing the **trend\_sum** command in the next block, **block1**. Since **block1** is a **nowait** block, the system will also start processing the **trend\_sum** command in the next block, **block2**.

```
begin: block0 wait
{DPIPE_HOME}/bin/trend_proc -f {DPIPE_HOME}/scripts/abc_hr.pro
end: block0
begin: block1 nowait
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/
day_abc_loc.sum
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/
month_abc_loc.sum
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/
abc_loc_fore.sum
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/
abc_loc_DOW.sum
end: block1
begin: block2 nowait
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/
day_a2z_loc.sum
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/
month_a2z_loc.sum
end: block2
```



### Example 3

In this example, the first block, **block1**, is a **wait** block; so the system will complete processing the **trend\_sum** commands in this block before it starts processing the **trendcopy** commands in the next block, **block2**. Note that the input file for the **trend\_sum** command is in a different directory than the command; both the command and the input file have fully qualified path names since they may not be in the current working directory. After the **trend\_sum** processing is complete, the system invokes the **trendcopy** command to copy the same tables from the satellite server, which is **SAT\_DB**, to the central server, which is **CENTRAL\_DB**.

```
begin: block1 wait
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/Device1.sum
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/Device2.sum
{DPIPE_HOME}/bin/trend_sum -f {DPIPE_HOME}/scripts/Device3.sum
end:block1
```

```
begin: block2 wait
{DPIPE_HOME}/bin/trendcopy -t Device1 -s SAT_DB -S CENTRAL_DB
{DPIPE_HOME}/bin/trendcopy -t Device2 -s SAT_DB -S CENTRAL_DB
{DPIPE_HOME}/bin/trendcopy -t Device3 -s SAT_DB -S CENTRAL_DB
end: block2
```

### Example 4

In this example, the block is a **wait** block. This block has a **trend\_proc** command in it that must complete its processing before the system continues processing this block with the Perl program that follows. After the Perl program finishes, the system processes the **trend\_sum** commands that follow in the order that they appear in the block. When the processing for the last **trend\_sum** command is complete, the system processes the Perl program again. When the Perl program finishes, the processing for this block is complete.

```
begin: test1 wait

{DPIPE_HOME}/bin/trend_proc -f {DPIPE_HOME}/scripts/proc1.pro

{DPIPE_HOME}/bin/perl {DPIPE_HOME}/scripts/Perf1.pl
-p "Location_Summary" -t day -v start

{DPIPE_HOME}/bin/trend_sum -t SH_Loc -e SD_Loc -f {DPIPE_HOME}/
scripts/SD_Loc.sum
{DPIPE_HOME}/bin/trend_sum -t SD_Loc -e fore -y 42
-f {DPIPE_HOME}/scripts/SD_Loc_forecast.sum
{DPIPE_HOME}/bin/trend_sum -t SDCustLoc -e dow -y 42
-f {DPIPE_HOME}/scripts/SD_Loc_forecast_dow.sum
```

*trend\_proc*

```
{DPIPE_HOME}/bin/trend_sum -t SD_Loc -e SM_Loc -f {DPIPE_HOME}/  
scripts/SM_Loc.sum
```

```
{DPIPE_HOME}/bin/perl {DPIPE_HOME}/scripts/Perf1.pl  
-p "Location_Summary" -t day -v stop
```

```
end: test1
```

## trend\_sum

You can use **trend\_sum** to conduct a statistical analysis of source data on an HP OpenView Performance Insight (OVPI) system. It calculates various statistics such as averages, percentiles, and forecast values. It then uses these calculations to populate summary tables to monitor the behavior of the data for a particular window of time or to project the future behavior of that data.

### Requirements or Restrictions

- The **trend\_sum** command requires at least one option.
- The source table must be a rate table or a summary table.
- The column specification must be an *alias* if the column expression contains more than one source table column name. See the **column:** keyword on [page 464](#) for usage of the *alias* parameter.
- The maximum number of nested functions in an expression is ten.

- The required input file must contain at least one by-variable and column specification; see [Input Files on page 475](#).
- The command-line options may appear only once on the command line unless otherwise specified.

## Syntax

OVPI provides two methods for supplying information to **trend\_sum**. One method is by using the command-line options. The other method is by using an input file, which is the only method for entering by-variables and column specifications. See [Input File Keywords on page 461](#) for the syntax. Note that some options are only available by using the keywords in the input file while some other options are only available from the command line. See [Command-Line Options on page 460](#). For more information about processing considerations when using both the command-line options and the input file together, see [Input Files on page 475](#).

## Command-Line Options

**trend\_sum** uses the following command-line syntax:

```
trend_sum  [ -C num_rows ]  
            [ -d debug_level ]  
            [ -e dest_name ]  
            [ -f input_file ]  
            [ -F ]  
            [ -h ]  
            [ -H hysteresis_units ]  
            [ -L log_hwm_number ]  
            [ -P lag_time_minutes ]  
            [ -R ]  
            [ -S server_name ]  
            [ -t src_table_name ]
```

```

[ -U ]
[ -V ]
[ -W db_hwm_number ]
[ -x stored_proc_name ]
[ -y number_of_days ]
[ -z ]

```

## Input File Keywords

Table 24 shows the syntax of the keywords for the **trend\_sum** input file with their equivalent command line options. The descriptions for the keywords are the same as for the corresponding command line options. See [Options on page 469](#) for the descriptions and [Input Files on page 475](#) for more information about input files.

**Table 24 trend\_sum Input File Keywords**

Keyword	Command Line Option
<b>baseline_days:</b> <i>number_of_days</i>	<b>-y</b>
<b>by_variable:</b> <i>by_var_expr</i>	
<b>column:</b> <i>column_spec</i>	
<b>destination_table:</b> <i>dest_name</i>	<b>-e</b>
<b>first_day_of_week:</b> <i>day_of_week</i>	
<b>name:</b> <i>sum_def_name</i>	
<b>source_table:</b> <i>src_table_name</i>	<b>-t</b>
<b>syntax_version:</b> <i>version_num</i>	
<b>time_hysteresis:</b> <i>hysteresis_units</i>	<b>-H</b>
<b>time_lag:</b> <i>lag_time_minutes</i>	<b>-P</b>

## Option Categories

The following table lists the options in categories that you might use.

**Table 25 trend\_sum Option Categories**

Category	Options
Data	-e, -f, -H, -P, -S, -t, -y
Switches	-F, -R, -U
Process	-C, -x, -z
Maintenance	-L, -W
Miscellaneous	-d, -h, -V

## Keywords

The **trend\_sum** input file uses the following keywords:

**baseline\_days:** Specifies the number of days in the baseline period. See [Rolling Baseline Table on page 478](#) for more information about this keyword. The default is set during the procedure building.

**by\_variable:** The specification for the grouping by-variable which has the format:

[ *alias =* ] *column* or *bukeyword*

where: *column* is the name of a column in the source table.

*bukeyword* has one of the following values:

<b>keyid</b>	Group by the column named <b>dsi_key_id_</b>
<b>ta_period</b>	Group by ta_period
<b>hour</b>	Group by hour
<b>day</b>	Group by day
<b>week</b>	Group by week
<b>month</b>	Group by month
<b>quarter</b>	Group by quarter
<b>year</b>	Group by year
<b>day_of_week</b>	Group by day of week for baseline table
<b>day_of_week_by_hour</b>	Group by day of week, by hour for baseline table
<b>hour_of_day</b>	Group by hour of day for baseline table

The **trend\_sum** summary process requires the **by\_variable** keyword in the input file.

The input file may contain multiple by-variables. Each by-variable that appears in the input file must be unique. The time by-variable (if used) must appear last in the list.

For more information, see [Input Files on page 475](#) and [By-Variables on page 475](#).

**column:**

Use this keyword to generate a column in the destination table for each statistic that appears in the *column\_spec*.

The name of each column in the destination table has the following form: *prefix + alias\_name*  
or *prefix + column\_name*.

The *prefix* has three uppercase characters and appears as a column in [Table 27](#) with the corresponding statistic. See [Example 1 on page 484](#) for an example of derived column names.

See [Input Files on page 475](#) for more information about this keyword.

The *column\_spec* has one of the formats shown below.

**Single Statistic Format**

[*alias =*] *column\_expr:statistic* ]

or

[!][*alias =*] *column\_expr:statistic* ]

where: *alias* is another name for the column.

*column\_expr* is either a column name or an arithmetic expression. The arithmetic expression requires the *alias* parameter to provide a name for this column. See [Divide-By-Zero Error on page 480](#) to avoid a divide-by-zero error in an expression.

*statistic* is at least one of the statistics that appear in [Table 27 on page 482](#).

! (exclamation point) suppresses the *prefix*, derived from the statistics in [Table 27](#), from the derived column name.



## Multiple Statistics Format

```
[alias =]column_expr:statistic1[ ,statistic2
,statistic3, ... ,statisticN ]
```

or

```
[!][alias =] column_expr:statistic1
[!][alias =] column_expr:statistic2
[!][alias =] column_expr:statistic3
:
[!][alias =] column_expr:statisticN
```

When you use the exclamation point (!) to suppress the addition of the statistic prefix to the column name, you can only specify one statistic for that **column** argument. If you want to generate additional statistics from the same input when you suppress the prefix, you must specify the same expression in multiple **column** lines, as shown above, with an alias.

The **trend\_sum** summary process requires the **column** keyword in the input file.

The input file may contain multiple **column** specifications. Each **column** specification that appears in the input file must be unique.

**destination\_table:** This keyword has multiple formats; the format for a standard table is different than the format for a rolling baseline table.

### Standard Table

The *dest\_name* is the SQL name of the destination table for the **trend\_sum** output. This keyword is required for a non-baseline table.

### Rolling Baseline Table

The *dest\_name* is an optional suffix for the destination table with the **trend\_sum** baseline output.

For a baseline table, the full name of the destination table will contain the following parts in the specified order:

**SDnn** where *nn* is the number of days used for the value of the **-y** option or the **baseline\_days:** input file parameter.

*source\_table* name from the **-t** option or the **source\_table:** input file parameter.

*dest\_name* which is this suffix.

See [Rolling Baseline Table on page 478](#) for more information about this keyword.

**first\_day\_of\_week:** Use this keyword to specify the first day of the week. Valid values are: **Mon, Tue, Wed, Thu, Fri, Sat, or Sun**. Note that these values are not case-sensitive; however, this keyword is in lowercase and is case-sensitive.

The default is **Mon**.

**name:** Specifies the unique name of the summary definition. The length of this name can be up to 128 characters.

**source\_table:** Use this keyword to specify the name of the source table that is providing the input to **trend\_sum**. The **trend\_sum** summary process requires either the **-t** option on the command line or the **source\_table:** keyword in the input file.

**syntax\_version:** Use this keyword to specify the version of this input file.

**time\_hysteresis:** Specifies the amount of time to go back to reprocess data to insure that all samples were included. The value is the number of *hysteresis\_units* to reprocess. The destination table determines the *hysteresis\_units* to apply such as hours for an hourly table or days for a daily table.

For example, if the destination table is a daily table, this value will be the number of days, and OVPI will recalculate the data for the specified number of days.

If the destination table is a table with a long duration such as a year, the value should be 0; otherwise, OVPI will reprocess the data for the specified duration, which is the number of years. If the value is 0 (zero), OVPI will not reprocess any data; it will continue processing from the last processed sample. For more information, see [Determine the Last Processed Sample for Hysteresis on page 476](#).

This keyword identifies the beginning of the time range to process data from the source table. OVPI subtracts the number of corresponding *hysteresis\_units* from the last processed sample in source table and selects the samples that occur starting from that time. See the **-P** option for identifying the end of the time range.

The default is **-1**, which uses the default values for each type of table in the database.

You cannot use the **time\_hysteresis:** keyword with the **-U** option.

**time\_lag:**

Specifies the minimum lag time, which is the number of minutes to delay processing to insure most of the data has arrived before processing. The value is the minimum number of minutes earlier than the value of the calculated timestamp that a sample must be timestamped in order to be processed.

For example, if the value is 20 minutes and the calculated timestamp for the last sample was 10 minutes ago, OVPI will not process the data. However, if the calculated timestamp for the last sample was 30 minutes ago, OVPI will process the last sample.

This keyword identifies the ending of the time range to process data from the source table. OVPI subtracts the specified number of minutes from the calculated timestamp and selects the samples from the source table that occur before that time and that correspond to the destination table boundary. See the **time\_hysteresis:** keyword for identifying the beginning of the time range. For more information about lag time, see [Lag Time on page 477](#).

The default is **-1**, which uses the default values for each type of table in the database.

You cannot use the **time\_lag:** keyword with the **-U** option.

# Options

The **trend\_sum** command has the following options:

- c** Sets the size of the batch to commit, which is the number of rows to commit per transaction.  
The default value is **0**, which means the system calculates this value dynamically per table.  
HP strongly recommends that you use the default value. If this value is too low, it may affect performance; if this value is too high, it may affect concurrency.  
This option is in UPPERCASE.
- d** Specifies the type of debug output. The values are:
  - 0** Provides no debug output.  
This is the default value.
  - 1** Provides general debug output.
  - 2** Provides debug output for each record.  
This value only applies to the stored procedures.
  - 3** Provides debug outputDebug output is written to standard output.
- e** See the keyword, **destination\_table**: on [page 465](#), for the description of this option.
- f** Name of an input file containing the aggregation statements.
- F** If **trend\_sum** needs to run **tpmaint**, **trend\_sum** will pass the **-F** option to **tpmaint** so that it will continue processing when there are more rows to process from the source table than two times the default retention period for that table. See [tpmaint on page 351](#) for more information.  
This option is in UPPERCASE.
- h** Displays the syntax for this utility.

- H** See the keyword, **time\_hysteresis**: on [page 467](#), for the description of this option.  
You cannot use the **-H** option with the **-U** option.  
This option is in UPPERCASE.
- L** Specifies the high water mark for the log. The high water mark denotes the level for when the database-used log size reaches the specified percentage and data processing stops. Valid values are **1 - 100**.  
The default value is **90** for 90%, which means the data processing stops when the log is 90% full.  
This option is in UPPERCASE.
- P** See the keyword, **time\_lag**: on [page 468](#), for the description of this option.  
You cannot use the **-P** option with the **-U** option.  
This option is in UPPERCASE.
- R** Use this option to specify that **trend\_sum** replace the summary definition in the dictionary if the new definition is different than the old one.  
This option is in UPPERCASE.
- S** This option specifies the database server name. It overrides the value in the `system.xml` file for the current process.  
This option is in UPPERCASE.
- t** See the keyword, **source\_table**: on [page 466](#), for the description of this option.
- U** Specifies that **trend\_sum** ignore the time-period range restrictions and process all the data in the source table.  
You cannot use the **-U** option with the **-H** or **-P** option.  
This option is in UPPERCASE.
- V** Displays the version of this utility.  
This option is in UPPERCASE.

- W Specifies the *high\_water\_mark* for the segment where the table resides. The high water mark denotes the level for when the segment-used size of the database reaches the specified percentage and data processing stops. Valid values for the *high\_water\_mark* are **1 - 100**.  
The default value is **90** for **90%**, which means the data processing stops when the database is **90%** full.  
This option is in UPPERCASE.
- x Use this option to remove the named stored procedure.
- y See the keyword, **baseline\_days**: on [page 462](#), for the description of this option.
- z Use this option to remove and then regenerate the related stored procedure.

## Naming Conventions

- A **trend\_sum** input file generally has an extension of **.sum**, such as **ifexceptions.sum**; note that this is not a requirement.
- The source table name for **trend\_sum** input should start with an UPPERCASE **R** or **S**.
- The destination table **SQL** name for a **trend\_sum** baseline or forecast output table should have the following characteristics:
  - a** Start with the UPPERCASE letter **S**.
  - b** The second UPPERCASE letter designates the rollup interval such as **H** for hour, **D** for day, **W** for week, **M** for month, **Q** for quarter, or **Y** for year.
  - c** The number of baseline days follows the rollup interval.
  - d** An alphanumeric name follows the baseline days. This name is the *src\_table\_name* from the **-t** option followed by the *dest\_name* from the **-e** option.

- The destination table **Alias** name for a **trend\_sum** baseline or forecast output table should have the following characteristics:
  - a** Start with **hourofday\_**, **dayofweek\_**, or **dayofweekbyhour\_** for a baseline table or **sum\_** for a forecast table as a prefix.
  - b** The table category from the input table follows the prefix.
  - c** The SQL name of the output table is the last part.
- The destination table **SQL** name for a **trend\_sum** standard grouping output table should have the following characteristics:
  - a** Start with the UPPERCASE letter **S**.
  - b** The second UPPERCASE letter designates the rollup interval such as **H** for hour, **D** for day, **W** for week, **M** for month, **Q** for quarter, or **Y** for year.
  - c** An alphanumeric name follows the rollup interval. This name is the *dest\_name* from the **-e** option.
- The destination table **Alias** name for a **trend\_sum** standard grouping output table should have the following characteristics:
  - a** Start with **sum\_** as a prefix.
  - b** The table category from the input table follows the prefix.
  - c** The SQL name of the output table is the last part.
- The name of the summary definition that **trend\_sum** generates varies depending on the parameters, as follows.
  - If the **name** keyword is not in the input file and there are no options on the command line, **trend\_sum** generates the following name:

*FileName\_srcF\_destF*

where: *FileName* is the name of the input file.

*srcF* is the *src\_table\_name* from the **source\_table** keyword in the corresponding input file.

*destF* is the *dest\_name* from the **destination\_table** keyword in the corresponding input file.



- If the **name** keyword is not in the input file and there are options on the command line, **trend\_sum** generates the following name:

*FileName\_srcC\_destC*

where: *FileName* is the name of the input file.

*srcC* is the *src\_table\_name* from the **-t** option on the command line.

*destC* is the *dest\_name* from the **-e** option on the command line.

- If the **name** keyword is in the input file and there are no options on the command line, **trend\_sum** generates the following name:

*NameF*

where: *NameF* is the *src\_def\_name* from the **name** keyword in the input file.

- If the **name** keyword is in the input file and there are options on the command line, **trend\_sum** generates the following name:

*NameF\_srcC\_destC*

where: *NameF* is the *src\_def\_name* from the **name** keyword in the input file.

*srcC* is the *src\_table\_name* from the **-t** option on the command line.

*destC* is the *dest\_name* from the **-e** option on the command line.

## Usage Notes

You must use an input file to provide most parameters to **trend\_sum**. The combination of all the parameters from the input file, command-line options, and versions of the associated programs that **trend\_sum** invokes make up a *summary definition* that **trend\_sum** will store in the database with a unique name. Another name for the summary definition is *transformation*.

You can provide the name with the **name** keyword in the input file; otherwise, **trend\_sum** will generate a name depending on the parameters provided. See [Naming Conventions on page 471](#) for more information.

The associated programs that **trend\_sum** invokes are **datapipe\_manager** and **tpmaint**. See [datapipe\\_manager on page 73](#) and [tpmaint on page 351](#) for more information.

After **trend\_sum** registers the summary definition in the database, it generates a stored procedure, associates the procedure with the definition, and then executes the procedure.



Note that if you terminate **trend\_sum** with **Ctrl+c**, you will need to terminate any associated stored procedures that are currently running on the server separately.

There are two modes that **trend\_sum** uses to process its input files. If the **checkmode** value is **false**, which is the default, **trend\_sum** will determine the name of the summary definition and then check the database for it. If **trend\_sum** finds the definition in the database, it will execute the associated procedure without any sum file verification; otherwise, **trend\_sum** will create the procedure, store it, and execute it. If the **checkmode** value is **true**, **trend\_sum** will determine the name of the summary definition and then check the database for it. If **trend\_sum** finds the definition in the database, it will validate the existing definition by comparing it to the new definition. If the definitions are the same, **trend\_sum** will execute the procedure associated with the existing definition. If the definitions are not the same, and the **-R** option is on the command line, then **trend\_sum** will replace the existing definition with the new definition, regenerate the procedure, store it, and then execute it; otherwise, if the **-R** option is not on the command line, **trend\_sum** will display an error message and exit. The **trendsum\_checkmode** entry is in the `be_defaults.prp` file in the `DPIPE_HOME/data` directory.

To improve performance, **trend\_sum** uses time-period tables. It verifies that the appropriate entries exist in the corresponding time-period table. It does this by comparing the begin and end dates of the source table to the begin and end dates for the corresponding time-period table. If the begin and end dates of the source table are within the range of the begin and end dates for the corresponding time-period table, then **trend\_sum** will continue processing.

Otherwise, **trend\_sum** will invoke **tpmaint** to update the corresponding time-period table. Note that if there are gaps in the time-period table for the range of dates from the source table, then **trend\_sum** will invoke **tpmaint**.



Note that the **trend\_sum** and **tpmaint** programs require that the system have the correct date and time for the system date.

## Input Files

An input file includes statements with keywords that correspond to specific options on the command line. [Table 24 on page 461](#) lists the keywords and their equivalent command-line options.

The file name for the input file must contain the full path name in the specification of the **-f** option unless the file is present in the current directory or the `DPIPE_HOME/scripts` directory.

If you use a keyword in an input file and the corresponding command line option on the command line, **trend\_sum** executes the command line option, and ignores those keywords in the input file.

## By-Variables

A by-variable indicates a time period or a table element such as **dsi\_key\_id**. At least one by-variable is required to specify the aggregation level. If both a table element and a time by-variable are given, the time by-variable must be the last one specified. If a time by-variable is not specified, **trend\_sum** defaults to the **ta\_period** time by-variable.

When the source and destination data tables share a property table, **keyid** (or its equivalent) must be present as the only non-time by-variable. Similarly, when the data tables have separate property tables, **trend\_sum** will not allow **keyid** (or its equivalent) as the by-variable.

Each non-time by-variable must exist as a column in the source data or property table. Each non-time by-variable must also exist as a column in the destination property table. If the column name differs between the source and destination tables, use the **alias** feature. For example: **by\_variable: h\_key=frcircuitnumber**. In this example, the name of the column in the source table is **frcircuitnumber** and the name of the column in the destination property table is **h-key**.

If the only by-variable specified is a time by-variable then the value for the first non-time by-variable, which is **dsi\_target\_name**, defaults to the string “**All Devices**”; the second non-time by-variable, which is **table\_key**, defaults to the string “**0**”.

All *bvkeyword* values except **keyid** for the **by\_variable**: input file keyword are time by-variables. See [page 463](#) for the list of *bvkeyword* values.



Note that there are only three by-variables that you can use to populate a baseline table. They are **day\_of\_week**, **day\_of\_week\_by\_hour**, and **hour\_of\_day**. See [Rolling Baseline Table on page 478](#) for more information about baseline tables.

## Determine the Last Processed Sample for Hysteresis

To identify the beginning of the time period range for hysteresis, **trend\_sum** determines what the last processed sample timestamp is and then subtracts the hysteresis value from that timestamp.

To determine the last processed sample timestamp, **trend\_sum** uses the minimum timestamp from the following parameters:

- The last processed sample timestamp for the destination table.
- The last processed sample timestamp for a particular managed object for the destination table.
- The earliest not processed sample timestamp for a particular managed object that does not appear in the destination table.
- The earliest sample timestamp in the source table if the destination table is empty.
- The earliest sample timestamp in the source table if there are samples for more days in the source table than the number of retention days for the source table.

In the case of the last two parameters, **trend\_sum** does not need to subtract the hysteresis value since it will process the entire source table.

## Lag Time

OVPI uses a minimum lag time to establish the end point for processing data from the source table. The lag time is the amount of time to hold off performing the summarizing process until there is little chance that missing data will arrive. For example, if there are only 3 of the 4 samples for an hour in the source table and the interface is no longer available, the remaining sample will never show up. After the lag time hour has ended, OVPI summarizes the data that is in the table but did not occur during the lag time interval.

During the summarization process, **trend\_sum** will only include data for rollup periods. For example, **trend\_sum** will only process the data for the last hour available for an hourly table. Similarly, it will only process the data for the last day available for a daily table.

To establish the end point for processing the data, **trend\_sum** subtracts the lag time value from the current timestamp on the server. It then uses the calculated timestamp to process the data in the source table with timestamps that are earlier than the calculated timestamp.

By default, the minimum lag time value varies depending on the time type of table. The **-P** option (UPPERCASE) is available to provide a different minimum lag time value.

To calculate the end point for processing the data, do the following steps:

- 1 Use the current timestamp and subtract the minimum lag time value.
- 2 Round the difference in step 1 to the rollup interval such as hourly or daily.
- 3 If the value in step 2 is equal to the element's last **ta\_period**, nothing happens.
- 4 If the value in step 2 is greater than the element's last **ta\_period**, the processing includes the row.

For example, if **trend\_sum** is processing a daily summary from a rate table with a 60-minute lag time, the following results can occur. If **trend\_sum** runs at 07/03/01 00:30:00, the difference for step 1 is 07/02/01 23:30:00. The rollup interval is a day, so **trend\_sum** rounds the value in step 1 to 07/01/01 00:00:00, which is the last complete day. Since the value for step 2 is equal to the last **ta\_period**, which is 07/01/01 00:00:00, nothing happens.

However, if **trend\_sum** runs at 07/03/01 01:30:00 instead, the difference for step 1 is 07/03/01 00:30:00. The system rounds the value in step 1 to 07/02/01 00:00:00, which is the most recent day. Since the value for step 2 is greater than the last **ta\_period**, which is 07/01/01 00:00:00, then **trend\_sum** includes the row in the summarization process.

## Reprocessing Data

After **trend\_sum** determines the time range and identifies the samples from the source table, it then determines if it really needs to reprocess those samples. It will only reprocess those samples when there are more cumulative samples in the source table for a particular grouping than the number of cumulative samples recorded in the corresponding destination row for the same grouping.

## Rolling Baseline Table

Use the command line option **-y** or the input file keyword **baseline\_days:** to specify the number of days in the rolling baseline period. (When you specify the **-y** option, the **-e** option is not required. Likewise, if you use the input file parameter **baseline\_days:**, the input file parameter **destination\_table:** is not required.)

Once **trend\_sum** establishes a rolling baseline for a particular destination table, you cannot change the name of the source table used for the rolling baseline or the number of days in the baseline period.

Use of the **-y** option or the input file parameter **baseline\_days:** places restrictions on the destination table name. The destination table name always begins with SD42 (assuming a 42-day baseline). Normally, the remainder of the name is the source table name. For example, when the source table name is **SDifexceptions** the destination table name becomes **SD42SDifexceptions**.

You may use the **-e** option or the input file parameter **destination\_table:** to append the specified value to the name. For instance, the following option string yields **SD42SDifexceptionsfore** as the destination table name:

```
-y42 -t SDifexceptions -e fore
```

An input file that performs the same function would be as that shown below:

```
source_table: SDifexceptions
destination_table: fore
column: volume=(ifinoctets+ifoutoctets):tot
baseline_days: 42
by_variable: keyid
by_variable: hour_of_day
```

A rolling baseline is inherently a daily summary. Therefore, no time by-variable greater than **day** is accepted. However, you may specify a lower-level summarization level such as **hour\_of\_day** to get 24 summary rows of data per day. When summarizing into a baseline table, if you omit the time by-variable, **day** is the default.



When using the optional day-of-week or day-of-week-by-hour summarization level, it is strongly recommended that the number of days for the baseline period be evenly divisible by seven; otherwise, some summary rows will summarize a different number of days than others. For example, one summary row might be for seven Mondays while another row might be for six Tuesdays.

## NULL Handling

The database rules for NULL handling apply to **trend\_sum**.

In the event that NULL values exist in a column of data, **trend\_sum** will calculate most functions by ignoring the NULL values. For most functions, if a NULL value does appear as a result, it means that all the values in the column were NULL. For example, to calculate the **average** of two values, 1 and NULL, the result is 1 not 0.5.

There is one function that does not ignore NULL values in the column; it is **last**. This function may produce a NULL value as a result depending on the location of the NULL value. For example, if there are 20 values and the last value is NULL, then the result of the function **last** will be NULL. Resultant NULL values may indicate that the data is incorrect.

## Troubleshooting

If **trend\_sum** fails, always check the `trend.log` file for errors relating to **trend\_sum**, **tpmaint**, or **datapipe\_manager**. If **tpmaint** or **datapipe\_manager** fails then **trend\_sum** will fail.

### Date Range Error

There are predefined limits for the number of rows to keep in time-period tables. Exceeding those numbers will result in performance problems. When **tpmaint** populates a time-period table and it tries to increase the number of rows to more than twice the recommended amount, it will generate the following messages in `trend.log`.

Adding the requested date range to the total of *number* days to table *table name* will exceed the total default of *retention* days by more than 2 times.

Reduce the date range specified or use `-F` to override.

If these error messages appear in `trend.log` while running **trend\_sum** or **tpmaint**, you need to rerun **trend\_sum** with the `-F` option to override the default and continue processing. Be aware that this will cause performance penalties.

### Divide-By-Zero Error

It is possible to create a column definition that has an expression with a zero in the denominator. This will cause the database engine to generate a runtime error. You can avoid this error by using one of the following expressions:

- **NULLIF** (*D*, 0) where *D* is the denominator of an expression.  
This function produces a NULL value for the expression when the denominator is zero. The denominator, *D*, can be another expression. Remember that the maximum number of nested functions is ten.
- *D* + *V* where *D* is the denominator of an expression and *V* is a very small value.

The value, *V*, can be any small value with respect to the data so that the denominator will not be zero.



## Statistical Formulas and Variables

Table 26 defines the formula variables. Table 27 on page 482 shows the formulas for computing statistics. It also shows the corresponding prefix for the formula.



Note that in all formulas where it appears, **val** is the resolved value of the expression to which the function is applied. The **val** is considered to be *counter* data if more than one column appears in the expression or if a single-column expression is of counter data type. The **val** is considered to be *gauge* data only if the single-column expression is of gauge data type.

Table 26 lists the definitions for the variables that appear in Table 27.

**Table 26 trend\_sum Formula Variables**

Variable	Formula
<b>a</b>	$\text{ybar} - \text{b} * \text{xbar}$
<b>b</b>	$(\text{cnt} * \Sigma (\text{val} * \Delta\text{t}) - \text{tot} * \Sigma \Delta\text{t}) / \text{d}$
<b>cnt</b>	Number of samples being summarized.
<b>d</b>	$\text{cnt} * \Sigma (\Delta\text{t} * \Delta\text{t}) - \Sigma \Delta\text{t} * \Sigma \Delta\text{t}$
$\Delta\text{t}$	ta_period column value of this row minus the ta_period column value of the first row in the group.
$\Delta\text{tg}$	ta_period column value of the last row in the group minus the ta_period column value of the first row in the group.
<b>xbar</b>	$\Sigma \Delta\text{t} / \text{cnt}$
<b>ybar</b>	$\text{tot} / \text{cnt}$

Table 27 shows the formulas for computing statistics in **trend\_sum**. Note that a column statement may contain multiple statistics, and each statistic may appear only once on a column statement. If a column statement has a statistic repeated, then an error will occur.

**Table 27 trend\_sum Statistic Formulas and Prefixes**

Statistic	Prefix	Description and Formula
<b>avg</b>	AVG	Average <b>tot / cnt</b>
<b>cnt</b>	CNT	Count of samples in the group
<b>dt</b> [ <i>value</i> ]	DTT	Number of days until <i>value</i> is reached where <i>value</i> is the <b>threshold_value</b> the user specifies. <b>ceil(((threshold_value - a) / b - Δtg) / 86400)</b> <b>trend_sum</b> limits <b>dt</b> to ±1000.
<b>f30</b>	F30	Projected value in 30 days <b>a + b * (Δtg + 86400 * 30)</b>
<b>f60</b>	F60	Projected value in 60 days <b>a + b * (Δtg + 86400 * 60)</b>
<b>f90</b>	F90	Projected value in 90 days <b>a + b * (Δtg + 86400 * 90)</b>
<b>lst</b>	LST	Last value in the group
<b>mad</b>	MAD	Delta time when the maximum value occurred
<b>mat</b>	MAT	Time when the maximum value occurred in the source table
<b>max</b>	MAX	Maximum value

Table 27 trend\_sum Statistic Formulas and Prefixes (cont'd)

Statistic	Prefix	Description and Formula
<b>med</b>	MED	Median <b>vr[floor(.50 * (cnt))]</b> where <b>vr</b> is an array of <b>vals</b> sorted into ascending order. <ul style="list-style-type: none"> <li>The definition of this statistic has changed. It no longer subtracts <b>1</b> from <b>cnt</b>. The formula was <b>vr[floor(.50 * (cnt-1))]</b>.</li> </ul>
<b>mid</b>	MID	Delta time when the minimum value occurred
<b>min</b>	MIN	Minimum value
<b>mit</b>	MIT	Time when the minimum value occurred
<b>per90</b>	P90	90th percentile <b>vr[floor(.90 * (cnt))]</b> where <b>vr</b> is an array of <b>vals</b> sorted into ascending order. <ul style="list-style-type: none"> <li>The definition of this statistic has changed. It no longer subtracts <b>1</b> from <b>cnt</b>. The formula was <b>vr[floor(.90 * (cnt-1))]</b>.</li> </ul>
<b>per95</b>	P95	95th percentile <b>vr[floor(.95 * (cnt))]</b> where <b>vr</b> is an array of <b>vals</b> sorted into ascending order. <ul style="list-style-type: none"> <li>The definition of this statistic has changed. It no longer subtracts <b>1</b> from <b>cnt</b>. The formula was <b>vr[floor(.95 * (cnt-1))]</b>.</li> </ul>
<b>per98</b>	P98	98th percentile <b>vr[floor(.98 * (cnt))]</b> where <b>vr</b> is an array of <b>vals</b> sorted into ascending order. <ul style="list-style-type: none"> <li>The definition of this statistic has changed. It no longer subtracts <b>1</b> from <b>cnt</b>. The formula was <b>vr[floor(.98 * (cnt-1))]</b>.</li> </ul>

**Table 27 trend\_sum Statistic Formulas and Prefixes (cont'd)**

Statistic	Prefix	Description and Formula
<b>rct</b> [ <i>min - max</i> ]	RCT	Count of samples greater than or equal to the <i>min</i> value and less than the <i>max</i> value; that is, count of samples $\geq min$ and $< max$ .
<b>std</b>	STD	Standard deviation (the square root of the variance) $\sqrt{((cnt * \Sigma (val * val) - tot * tot) / (cnt * (cnt-1)))}$
<b>tct</b> [ <i>value</i> ]	TCT	Count of samples greater than or equal to <i>value</i> ; that is, count of samples $\geq value$ .
<b>tot</b>	TOT	Total $\Sigma val$ where <b>val</b> is the resolved value of the expression to which the <b>tot</b> function is being applied.
<b>vct</b> [ <i>value</i> ]	VCT	Count of samples equaling <i>value</i>
<b>wav</b>	WAV	Weighted Average $\Sigma (val * \Delta t) / (\Sigma \Delta t)$

## Examples

### Example 1

Execute the following command to invoke **trend\_sum** to read data from a rate table named **Rninterface\_base\_** and create a rolling baseline destination table named **SD42Rninterface\_base\_if** based on a 42-day rolling baseline period:

```
$DPIPE_HOME/bin/trend_sum -f $DPIPE_HOME/scripts/
if_baseline_hourofday_volume_interface.sum
```

The following file contains the column and by-variable specifications to be included in the **SD42Rninterface\_base\_if** destination table:

```
$DPIPE_HOME/scripts/if_baseline_hourofday_volume_
interface.sum
```

The contents of this input file are:

```
# trend_sum procedure to update hour_of_day baseline table for
# combined network volume
source_table: Rnterface_base_
destination_table: if
column: thru_put=(ifinooctets+ifoutooctets):per95,std,wav
column: volume=(ifinooctets+ifoutooctets):tot,avg
baseline_days: 42
by_variable: keyid
by_variable: hour_of_day
```

The **SD42Rnterface\_base\_if** destination table contains 24 rows, one row for each hour of the day, for each keyid present in the source table for each baseline period of 42 days.

The destination table created by the above process contains the following data columns:

- P95thru\_put
- STDthru\_put
- WAVthru\_put
- TOTvolume
- AVGVOLUME

## Example 2

Execute the following command to invoke **trend\_sum** to read a daily summary table named **SDifexceptions** and create a rolling baseline destination table named **SD42SDifexceptions** with a 42-day rolling baseline period:

```
$DPIPE_HOME/bin/trend_sum -f $DPIPE_HOME/scripts/if_forecast.sum
```

The input file `$DPIPE_HOME/scripts/if_forecast.sum` contains the column and by-variable specifications to be included in the **SD42SDifexceptions** destination table:

```
# trend_sum procedure to create days to threshold calculations
# from the daily summary table.
source_table: SDifexceptions
column: utilcurrent=P95utilization:per95
column: inutilcurrent=P95waninutil:per95
column: oututilcurrent=P95wanoututil:per95
```

```
column: errorcurrent=AVGerror_pct:avg
column: discardcurrent=AVGdiscard_pct:avg
column: utiltrend=P95utilization:dtc[40],f30,f60,f90
column: wanutiltrend=P95wanutil:dtc[40],f30,f60,f90
column: waninutiltrend=P95waninutil:dtc[40],f30,f60,f90
column: wanoututiltrend=P95wanoututil:dtc[40],f30,f60,f90
column: discardtrend=P95discard_pct:dtc[5],f30,f60,f90
column: errorstrend=P95error_pct:dtc[10],f30,f60,f90
baseline_days: 42
by_variable: keyid
```

The **SD42SDifexceptions** destination table contains one row for each keyid present in the source table for each baseline period of 42 days.

# trendtimer

The **trendtimer** program is the HP OpenView Performance Insight (OVPI) scheduler that invokes other OVPI processes at scheduled times. It runs as a service and you can change the scheduled processes by adding, modifying, or deleting entries in the `trendtimer.sched` file; see [The Schedule File on page 489](#) for more information.

## Requirements and Restrictions

- The `trendtimer.sched` file has a limit of 100 command entries that **trendtimer** will schedule.
- The interval and offset for each command in the `trendtimer.sched` file should be on a 5-minute boundary.
- Avoid using an interval of **24:00** without an offset for a command entry.
- The default location, and the only location on a Windows system, for the `trendtimer.sched` file is in the `$DPIPE_HOME/lib` directory.
- Note that you do not need to stop and restart the `ovpi_timer` UNIX process or the OVPI Timer Windows service for any changes to take effect.

## Syntax

The typical usage for **trendtimer** does not require using any options on the command line.

The **trendtimer** command uses the following syntax on a UNIX system:

```
trendtimer [ -h ]  
                [ -s schedule_file ]  
                [ -v ]
```

## Options

The **trendtimer** command has the following options:

- h**     This option is available on UNIX systems only.  
          Use this option to display the help information for the **trendtimer** command. This option is not valid with any other options.
- s**     This option is available on UNIX systems only.  
          Use this option to specify the path name of the schedule file.  
          The default is `$DPIPE_HOME/lib/trendtimer.sched`.
- v**     Use this option to display the version information for **trendtimer**.  
          This option is not valid with any other options.  
          This option is in UPPERCASE.



## Usage Notes

The **trendtimer** program invokes other OVPI applications that run at specific times or regular intervals. It runs on a 5-minute cycle. Every hour on the hour, and at 5-minute intervals in between, it examines the contents of its schedule file and determines which processes to run at the current time. It runs these processes one at a time, in the order in which they appear in the schedule file.

The contents of the default schedule file vary to enhance performance and manage resources. The default schedule file on a central server contains processes for various applications, such as the collection, log backup, maintenance, and package processes. The default schedule file on a remote poller contains only the collection and log backup processes.

## The Schedule File

When **trendtimer** starts, it determines what it is going to do by reading a schedule file. The name of the schedule file is `trendtimer.sched` and it is in the `$DPIPE_HOME/lib` directory. On a UNIX system, you can override this file with the `-s` command line option. There is no override option for this file on a Windows system.

## Schedule File Syntax

The schedule file has the following elements.

- It contains a maximum of 100 command entries in the following format:

*interval* - - *command\_line*

where: *interval* is how often the command on this line will be run.

*command\_line* is the entire command that **trendtimer** will run.

- The hyphens ( - ) in the syntax are placeholders for future arguments. They must be included.
- The time specification uses a 24-hour clock, and **trendtimer** runs the commands in the schedule file according to local time.
- Comment lines in the file begin with a #.

The *interval* has multiple formats. Typically, it specifies the hours or minutes when the command will run. However, it can contain an *offset* that specifies a time between hours or a specific time that the command will run. All intervals are counted in *interval* minutes or hours and minutes from **unix 0 time**, which is **midnight, Thursday, January 1, 1970**. The interval has the following formats.

<i>MM</i>	specifies the number of minutes the command will start during the day. For example, <b>20</b> means that the command will start every 20 minutes during the day.
<i>HH:00</i>	specifies the number of hours the command will start during the day. For example, <b>2:00</b> means that the command will start every 2 hours during the day. Do not use <b>24:00</b> since it produces unexpected results.
<i>HH:00+MM</i>	specifies the number of hours and minutes the command will start during the day. For example, <b>2:00+20</b> means that the command will start every 2 hours and 20 minutes during the day.
<b>24:00+HH:00</b>	specifies a specific hour of each day that the command will run. For example, <b>24:00+2:00</b> means that the command will start every day at 2:00 a.m.
<b>24:00+HH:00+MM</b>	specifies a specific hour and minutes of each day that the command will run. For example, <b>24:00+2:00+20</b> means that the command will start every day at 2:20 a.m.
<i>wkday+HH:00</i>	specifies a specific hour of the specified weekday that the command will run. Valid values for <i>wkday</i> are the first two letters of the day of the week in English, as follows: <b>SU</b> is Sunday, <b>MO</b> is Monday, <b>TU</b> is Tuesday, <b>WE</b> is Wednesday, <b>TH</b> is Thursday, <b>FR</b> is Friday, and <b>SA</b> is Saturday. For example, <b>MO+2:00</b> means that the command will start every Monday at 2:00 a.m. If you want to run a program at midnight for a specific day, note that midnight starts the day; so, if you want to run a program every Saturday night at midnight; that is, the midnight between Friday and Saturday, the entry is <b>SA+24:00</b> .
<b>MONTHx+HH:00</b>	specifies a specific day in the month and the hour of that day that the command will run. For example, <b>MONTH5+2:00</b> means that the command will start on the fifth day of every month at 2:00 a.m.

Intervals should divide evenly into 60 minutes to ensure that the process runs at a predictable time. For example, an interval of 5 minutes means the program invoked will run on the hour, and at 5, 10, 15, 20, and so on, minutes after every hour because these are 5-minute intervals since midnight, Thursday, January 1, 1970. A program to be run every 2 hours will have an interval of 2:00 and will run at midnight, 2 a.m., 4 a.m., and so on. You can specify interval values in minutes or in hours; for example, you can use 120 minutes or 2:00 hours since they have the same value. The weekday and month intervals can also have offsets in minutes in the interval.

Note that an offset of 0:00 is invalid; use 24:00 instead. To run exactly at midnight, use 24:00+24:00, since 24:00+0:00 is invalid.

The *command\_line* is the entire command that **trendtimer** will run. This is the rest of the line in the file. It does not need to be inside quotation marks. Environment variables can be used in the command line by placing them inside the braces, { }, and omitting the leading dollar sign (\$) in the UNIX variable name or the leading and trailing percent sign (%) in the Windows variable name.

Note that **trendtimer** will schedule only the first 100 command entries in the `trendtimer.sched` file.



Be careful that you do not overload your system. When you install a report pack, the installation process usually adds commands to the `trendtimer.sched` file. Note also that a single command can start multiple processes.

## Schedule File Example

A sample `trendtimer.sched` file is:

```
# trendtimer.sched
24:00+5:00 - - {DPIPE_HOME}/bin/trendexec -i 1440
MO+5:00 - - {DPIPE_HOME}/bin/trendexec -i 10080
MONTH2+5:00 - - {DPIPE_HOME}/bin/trendexec -i 44640

5 - - {DPIPE_HOME}/bin/mw_collect -i 5 -n -K 1
10 - - {DPIPE_HOME}/bin/mw_collect -i 10 -n -K 1
15 - - {DPIPE_HOME}/bin/mw_collect -i 15 -n -K 1
20 - - {DPIPE_HOME}/bin/mw_collect -i 20 -n -K 1
60 - - {DPIPE_HOME}/bin/mw_collect -i 60 -n -K 1

24:00+1:00 - - {DPIPE_HOME}/bin/tpmaint
24:00+1:00 - - {DPIPE_HOME}/bin/transform_maint -r
24:00+2:00 - - {DPIPE_HOME}/bin/trend_discover -t
24:00+24:00 - - {DPIPE_HOME}/bin/db_delete_data
# eof
```

In this example:

- The system starts **trendexec** every day at 5 a.m., every week on Monday morning at 5 a.m., and on the second day of every month at 5 a.m.
- The system starts **mw\_collect** every 5, 10, 15, 20, and 60 minutes for data collection.
- The system starts **tpmaint** and **transform\_maint** every day at 1:00 a.m.
- The system starts **trend\_discover** every day at 2:00 a.m.
- The system starts **db\_delete\_data** every day exactly at midnight.

Note that **trendtimer** runs the commands in the schedule file according to local time.

## Starting trendtimer

You can run **trendtimer** at any time, but you should invoke it at system startup. The OVPI installation adds a command to the system startup file to run the `ovpi_timer` script with the **start** action; this command invokes **trendtimer**. The **su** command in the startup file quotes the entire **trendtimer** command. This ensures that the **su** command runs the entire **trendtimer** command line rather than interpreting the **trendtimer** options as options to **su**.

## UNIX Platforms

If you need to start **trendtimer** manually, use the method described below. This method uses scripts for each platform that allow you to supply the action to perform, which is **start** in this case, as follows:

- 1 Open a new shell on the system where the application is installed.
- 2 Make sure that you are **root**.
- 3 Execute the command for your platform:
  - HP-UX:
 

```
/sbin/init.d/ovpi_timer start
```
  - Solaris:
 

```
/etc/init.d/ovpi_timer start
```

## Windows Platform

If you need to start **trendtimer** manually, use the procedure listed below to start it.

- 1 From the Windows Desktop, access the Services window via the **Control Panel**. This procedure varies depending on the type of Windows environment.
- 2 Locate the **OVPI Timer** entry and select it.
- 3 Click the **Start** button.

The Status field for OVPI Timer will show **Started**.

## Stopping trendtimer

After you stop **trendtimer**, remember that when you want to restart **trendtimer**, you need to restart it manually or reboot your system to restart it automatically.

## UNIX Platforms

Use the following procedure to stop **trendtimer**.

- 1 Shut down the OVPI application.
- 2 Open a new shell on the system where the application is installed.
- 3 Make sure that you are **root**.
- 4 Stop the server by entering:

— HP-UX:

```
/sbin/init.d/ovpi_timer stop
```

— Solaris:

```
/etc/init.d/ovpi_timer stop
```

## Windows Platform

Use the procedure listed below to stop **trendtimer**.

- 1 From the Windows Desktop, access the Services window via the **Control Panel**. This procedure varies depending on the type of Windows environment.
- 2 Locate the **OVPI Timer** entry and select it.
- 3 Click the **Stop** button.

The Status field for OVPI Timer will be blank.

- 4 Close the Services and Control Panel windows.

If you want to completely stop all OVPI processes, do the following steps.

- 1 Exit from the OVPI application if it is running.
- 2 Select the **Processes** tab from Task Manager to verify that no processes are running.

## Example

To start **trendtimer** using the schedule file `/tmp/mytimer.sched` on a UNIX system, user **trendadm** executes the command:

```
trendtimer -s /tmp/mytimer.sched
```

For an example of a `trendtimer.sched` file, see the [Schedule File Example on page 491](#).

# TWQconverter

You can use the **TWQconverter** command to convert a legacy TRENDweb Query file (.twq) to a report definition file (.rep) on an HP OpenView Performance Insight (OVPI) system.

## Syntax

The **TWQconverter** command uses the following syntax:

```
TWQconverter twq_file report_name -graph
```

or

```
TWQconverter twq_file report_name -table
```

where: *twq\_file* is the name of the legacy TRENDweb Query file, which has the .twq extension.

*report\_name* is the name of the output report definition file, which has the .rep extension.

## Options

The **TWQconverter** command has the following options:

- graph** Use this option to display the data in a graphical format.
- table** Use this option to display the data in a tabular format.

## Usage Notes

The TRENDweb Query file is a query file that has the `.twq` extension and is a data definition file from the 3.2 version of TRENDweb Builder.



## userctl

You can use the **userctl** command to add, modify, or delete a single user account that accesses the Web Access Server on an HP OpenView Performance Insight (OVPI) system. You can use this command instead of the **User Administration** page on the Web Access Server; refer to the *Performance Insight Administration Guide* for more information about using the GUI tools. If you want to add, modify, or delete a large number of users at the same time, you can use the **userimport** command that requires a file in XML format; see [userimport on page 511](#) for more information.

### Requirements and Restrictions

- If there are spaces in the value for any option, enclose the entire value in double quotes.
- If you specify a value for an option, it must be a minimum of one (1) character and a maximum of 255 characters, unless otherwise specified; in most cases, it may not contain any of the following characters: ‘, “, &, comma (,), or space.
- Each time you invoke this utility, you must enter the required options: **-host**, **-mode**, **-port**, **-pwd**, **-tuser**, and **-user**.

# Syntax

The **userctl** command uses the following syntax:

```
userctl    [ -database hostname ]  
            [ -debug ]  
            [ -dept name ]  
            [ -email email_address ]  
            [ -groups group1[,group2,...,groupN] ]  
            [ -help ]  
            -host hostname  
            [ -interactive ]  
            -mode action  
            [ -name firstname_lastname ]  
            -port number  
            [ -protocol protocol ]  
            -pwd adm_pwd  
            [ -role type ]  
            [ -tele phone_num ]  
            [ -tpwd password ]  
            -tuser username  
            -user adm_user  
            [ -verbose ]  
            [ -version ]  
            [ -view viewname ]
```

## Options

The **userctl** command has the following options:

- database** Use this option to specify the database the user will use for reporting. The specified database must exist in the Web Access Server.  
The default is the reporting database defined in the `systems.xml` file, which is the default database specified on the **Performance Insight Systems** page in the Web Access Server.
- debug** Use this option to run the command in debug mode. To use this option, set the value to **true**.  
By default, debug mode is not set.
- dept** Use this option to specify the company or department name for the user. If the name contains spaces, enclose it in double quotes.
- email** Use this option to specify the email address of the user.
- groups** Use this option to specify the Web Access Server groups of which the user is a member. Separate each group with a comma (,); if there are any spaces (such as between groups after the comma), enclose the entire value in double quotes. The specified groups must exist.  
Note that when you modify a user account, you must include this option if you want to keep the user as a member of the specified groups.
- help** Use this option to display the syntax for the **userctl** command.
- host** Use this option to specify the Web Access Server hostname where the transaction occurs.  
This is a required option.

- interactive** Use this option to display the login box. When you use this option, the system will display the login box if the entry for one or both of the **-user** or **-pwd** options is incorrect; otherwise, if you do not use this option, you will get an error message instead.
- mode** Use this option to specify the type of transaction to perform.  
Valid entries are:  
**add** Use this mode to add a new user.  
**delete** Use this mode to delete an existing user.  
**modify** Use this mode to modify an existing user by changing its properties.  
This is a required option.
- name** Use this option to specify the actual full name for the user. If you use spaces in the name, enclose the entire name in double quotes.
- port** Use this option to specify the Web Access Server port number where the transaction occurs.  
You must enter this option even though the default for this option is the port number supplied during the OVPI installation, which is port number **80**, in most cases.  
This is a required option.
- protocol** Use this option to specify the communication protocol.  
Valid values are **http** or **https**.
- pwd** Use this option to specify the corresponding password for the username that has authorization to make the specified changes.  
This is a required option.
- role** Use this option to specify the role of the user as an administrative user. To use this option, set the value to **admin**.  
The default value is **user**.

- tele** Use this option to specify the telephone number of the user. The format of the number is *aaa-ppp-nnnn*:  
where: *aaa* is the area code.  
*ppp* is the prefix.  
*nnnn* is the remainder of the telephone number.
- tpwd** Use this option to specify the corresponding password for the username to add, modify, or delete.  
This password parameter must be a minimum of four (4) characters and a maximum of ten (10) characters.  
This is a required option with the **-mode add** option.
- tuser** Use this option to specify the username to add, modify, or delete.  
This is a required option.
- user** Use this option to specify the username that has authorization to make the specified changes. This username must have administrative privileges.  
This is a required option.
- verbose** Use this option to turn on verbose messaging.
- version** Use this option to display the current version of **userctl**.
- view** Use this option to assign a single catalog view to the user. The specified view must exist.

## Usage Notes

The purpose of this command is to manage a single user account. All OVPI clients such as Report Builder, Report Viewer, Web Access Server, and the Management Console require users to log on.

By default, OVPI creates one user account when you install it. This is the `trendadm` account; ideally, you should create a user account for each person who will use the OVPI client applications.

## Modes of Operation

The **userctl** command has three modes of operation: add, modify, and delete.

### Add

The *add* mode provides the ability to add a user account to access the Web Access Server.

### Modify

The *modify* mode provides the ability to change the properties of an existing user account that is used for accessing the Web Access Server.

### Delete

The *delete* mode provides the ability to remove an existing user account that allows access to the Web Access Server.

## Using the userctl Command

This section shows some formats of the command for the various modes. There is a minimum of six required options for the **userctl** command. Each mode will show the command with the required options along with the other options for the particular task; however, only the definitions for the new options will appear for each subsequent command. The definitions for the required options appear below.

- All **userctl** commands must have all the following options for each task:

```
userctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -tuser username -mode action
```

where: *host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*adm\_user* is the administrative user name that has authorization to make the specified changes.

*adm\_pwd* is the corresponding password for the administrative user that has authorization to make the specified changes.

*username* is the name for the user account to add, modify, or delete.

*action* is the type of action to perform, such as add, modify, or delete.

- If you enter the **userctl** command without any options, the system will display the help information. Use the following format.

```
userctl
```

- If you want to display the version for the **userctl** command, enter the following command.

```
userctl -version
```

- If you want the login box to pop up if either of the required options, **-user** or **-pwd**, is incorrect, enter the following command.

```
userctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -tuser username -mode action -interactive
```

## Add

The following formats show various options for adding a user account to access the Web Access Server. Note that you can combine the additional options in any manner that meets your needs.

- To add a new user account without any user information, enter the following command:

```
userctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -tuser username -mode add -tpwd password
```

where: *password* is the password for the new user account.

- To add a new user account as an administrative user without any user information, enter the following command:

```
userctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -tuser username -mode add -tpwd password  
-role admin
```

where: *password* is the password for the new user account.

- To add a new user account with user information, enter the following command:

```
userctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -tuser username -mode add -tpwd password
-name "name_of_user" -tele phone_num -email email_address
-dept "name"
```

where: *password* is the password for the new user account.

*name\_of\_user* is the actual name of the user. Use quotes to enter the first and last names with a space.

*phone\_num* is the telephone number for the user.

*email\_address* is the email address for the user.

*name* is the company or department name for the user.

- To add a new user account without any user information and include it in two groups, enter the following command:

```
userctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -tuser username -mode add -tpwd password
-groups group1,group2
```

where: *password* is the password for the new user account.

*group1* is the name for the first group where the user will be a member.

*group2* is the name for the second group where the user will be a member.

- To add a new user account without any user information and specify another database for reporting, enter the following command:

```
userctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -tuser username -mode add -tpwd password
-database db_name
```

where: *password* is the password for the new user account.

*db\_name* is the name for the database that exists in the Web Access Server.



## Modify

- To add user information to an existing user account that is not a member of any group, enter the following command:

```
userctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -tuser username -mode modify -name "name_of_user"
-tele phone_num -email email_address -dept "name"
```

where: *name\_of\_user* is the actual name of the user. Use quotes to enter the first and last names with a space.

*phone\_num* is the telephone number for the user.

*email\_address* is the email address for the user.

*name* is the company or department name for the user.

- To change the group membership for the user to one group and assign a view to the user, enter the following command:

```
userctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -tuser username -mode modify -groups group1
-view viewname
```

where: *password* is the password for the new user account.

*group1* is the name of the group where the user will be a member.

*viewname* is the name of the view assigned to the user.

- To change the password for a user with group membership in two groups and add administrative privileges with a department name, enter the following command:

```
userctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -tuser username -mode modify -tpwd password
-groups group1,group2 -dept "name" -role admin
```

where: *password* is the password for the new user account.

*group1* is the name for the first group where the user is a member.

*group2* is the name for the second group where the user is a member.

*name* is the company or department name for the user.

## Delete

- To remove a user account, enter the following command:

```
userctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -tuser username -mode delete
```

## Examples

The following examples illustrate some uses of the **userctl** command that an Administrator, such as the **trendadm** user, can enter.

### Add

#### Example 1: Add a User Account without Additional Information

To add a user account with the name **user\_1** and a password **pass\_1** on the **powder2** host without additional information about the user, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_1 -mode add -tpwd pass_1
```

#### Example 2: Add a User Account with Administrative Privileges

To add a user account with the name **user\_2** and a password **pass\_2** on the **powder2** host with administrative privileges, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_2 -mode add -tpwd pass_2 -role admin
```

#### Example 3: Add a User Account with User Information

To add a user account with the name **user\_3** and a password **pass\_3** on the **powder2** host with information about the user such as the user's name, telephone number, email address, and department name, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_3 -mode add -tpwd pass_3 -name "User Three"  
-tele 310-555-1234 -email user3@xxx.com -dept Operations
```

### Example 4: Add a User Account as a Member of a Group

To add a user account with the name `user_4` and a password `pass_4` on the `powder2` host as a member of an existing group with the name `group1`, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_4 -mode add -tpwd pass_4 -groups group1
```

### Example 5: Add a User Account as a Member of Multiple Groups

To add a user account with the name `user_5` and a password `pass_5` on the `powder2` host as a member of two existing groups, `group1` and `group2`, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_5 -mode add -tpwd pass_5 -groups group3,group4
```

### Example 6: Add a User Account with a View

To add a user account with the name `user_6` and a password `pass_6` on the `powder2` host and associate it with an existing catalog view such as `view1`, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_6 -mode add -tpwd pass_6 -view view_1
```

### Example 7: Add a User Account to Access Another Database

To add a user account with the name `test_user_1` and a password `test_pass_1` on the `powder2` host and specify another database for reporting such as `test_system`, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser test_user1 -mode add -tpwd test_pass1  
-database test_system
```

Note that the database must exist in the Web Access Server.

## Modify

### Example 1: Change the Password of a User Account with a Group

To change the password of a user account with the name `user_4` and a current password `pass_4` to a password `pass_four` on the `powder2` host and adding administrative privileges and a department name of **Quality** while keeping the member in a group with the name `group1`, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_4 -mode modify -tpwd pass_four -dept Quality  
-groups group1 -role admin
```

### Example 2: Add a User Account with User Information

To modify an existing user account with the name `user_1` on the `powder2` host that does not have any group memberships by adding the name of the user, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_1 -mode modify -name "User One"
```

### Example 3: Add a User Account with User Information

To modify an existing user account with the name `user_5` on the `powder2` host that has membership in two groups to one group, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser user_5 -mode modify -groups group5
```

## Delete

To delete a user account with the name `test_user_1` on the `powder2` host, you can use the following command.

```
userctl -host powder2 -port 80 -user trendadm -pwd trendadm  
-tuser test_user1 -mode delete
```

## Error Messages

This section describes some of the messages that can occur from **userctl**. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
  - The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- ❑ If the following message appears, there is an incorrect value for the **-mode** option on the command line.

```
Error - Invalid application mode
```

Verify that the **-mode** option has the value **add**, **modify**, or **delete** on the command line.

- ❑ If the following message appears, there is an incorrect option on the command line.

```
Invalid Argument Supplied
```

Verify that all of the options are correct on the command line. See [Syntax on page 498](#) for the valid options.

- ❑ If the following message appears, the user is unauthorized to create, modify, or delete a user account.

```
Unauthorized.
```

Verify the following:

- The user (**-user**) and password (**-pwd**) values are correct.
- The specified user has administrator privileges.



# userimport

You can use the **userimport** command to add, modify, or delete Web Access Server users on an HP OpenView Performance Insight (OVPI) system. This utility is an extension of the Web Access Server **User Accounts** feature under the **Administration** link on the Management Console.

## Requirements or Restrictions

- There are five required command-line options that you must enter each time you invoke the utility.
- Any file to be imported must be in the Extensible Markup Language (XML) interchange format specified in this chapter.
- A group must already exist if you want to assign a user to it.

## Syntax

The **userimport** command uses the following syntax:

```
userimport  -c communications_protocol
              -f user_XML_file_name
              -h application_server_name
              [ -help ]
              -p application_server_port_number
              -P administrator_password
              -U administrator_username
              [ -v ]
```

## Options

The **userimport** commands have the following options:

- c**           The communications protocol that you want to use (http or https). If this option is not specified, http is used by default.
- f**           Name of the text file containing Web Access Server user information.
- h**           Name of the Web Access Server.
- help**       Display the command-line options for the **userimport** command.
- p**           Port number of the Web Access Server.
- P**           Password of the OVPI administrator.  
This option is in UPPERCASE.
- U**           Username of the OVPI administrator.  
This option is in UPPERCASE.



- v      Display version information for the **userimport** command.

## Usage Notes

When you want to assign a user to a group, the group must already exist. This implies that you must use the **groupctl** or **groupimport** commands from the command line or the **Add New Group** feature from the **Group Administration** page on the Web Access Server to create the group before you use this command to add a user to that group.

This rest of this section describes the naming convention and file format for the text file that contains the XML tag sets when you use the **userimport** command.

## Naming Conventions

The **userimport** text file parameters must follow the naming conventions listed below:

- 1 The tag set parameter formats are as follows:
  - a The parameters may contain alphabetic characters (upper and lower case), numeric symbols, and special characters except those cited in [Step 2](#).
  - b All parameters except *password* must be a minimum of one (1) character and a maximum of 255 characters.
  - c The *password* parameter must be a minimum of four (4) characters and a maximum of ten (10) characters.
  - d The *telephone* parameter can be in any format but cannot exceed 255 characters.
  - e The *e-mail* parameter can be in any format but cannot exceed 255 characters.
- 2 DO NOT use any of the following characters in the **userimport** text file:
  - a single quotation mark ( ' )
  - b double quotation mark ( " )

- c ampersand ( & )
- d comma ( , )
- e space (blank)

## File Format

The **userimport** text file uses XML tag sets to define the data to be imported into the Web Access Server. **Figure 4** shows all XML tag sets available for use in the **userimport** text files. **Table 28** describes all XML tag sets available for use in the **userimport** text files.

```
<?xml version="1.0" encoding="UTF-8"?>
<Users>
  <User>
    <Action>action</Action>
    <ID>user_logon_name</ID>
    <Password>user_password</Password>
    <RealName>user_name</RealName>
    <Department>user_department</Department>
    <Phone>user_telephone</Phone>
    <Email>user_e-mail</Email>
    <Groups>
      <Group>user_group_name</Group>
    </Groups>
    <Role>admin</Role>
  </User>
</Users>
```

**Figure 4 userimport Text File Format**



Note that all the XML tag sets include the angle brackets (< >) as part of the tag.

**Table 28 userimport File - XML Tag Definitions**

XML TAG SETS	DESCRIPTION
<code>&lt;?xml version="1.0" encoding="UTF-8"?&gt;</code>	Allows the parser to validate the XML format. It must appear as the first line in the file.
<code>&lt;Users&gt;</code> <code>&lt;/Users&gt;</code>	Opening tag for <code>&lt;Users&gt;&lt;/Users&gt;</code> tag set. Contains all <code>&lt;User&gt;&lt;/User&gt;</code> tag set information for all users defined in this file. Any number of users can be placed in this set using <code>&lt;User&gt;&lt;/User&gt;</code> tag sets inside the <code>&lt;Users&gt;&lt;/Users&gt;</code> tag set. This tag set is required.
<code>&lt;User&gt;</code> <code>&lt;/User&gt;</code>	Opening tag for the <code>&lt;User&gt;&lt;/User&gt;</code> tag set. Contains all tag sets; for example, <code>&lt;Action&gt;&lt;/Action&gt;</code> , <code>&lt;ID&gt;&lt;/ID&gt;</code> , and so on, that define a single user. This tag set is required.
<code>&lt;Action&gt;</code> <code>&lt;/Action&gt;</code>	Procedure tag set that defines the operation to perform. If a user exists and the <b>Add</b> action is specified, the request is ignored. Valid values are: <b>Add</b> , <b>Modify</b> , <b>Delete</b> . The default is <b>Add</b> .
<code>&lt;ID&gt;</code> <code>&lt;/ID&gt;</code>	Defines user's logon name. This tag set is required.
<code>&lt;Password&gt;</code> <code>&lt;/Password&gt;</code>	Defines user's password. This tag set is required only when the password is to be changed.
<code>&lt;RealName&gt;</code> <code>&lt;/RealName&gt;</code>	Defines actual name of the user.
<code>&lt;Department&gt;</code> <code>&lt;/Department&gt;</code>	Defines user's department or company name.
<code>&lt;Phone&gt;</code> <code>&lt;/Phone&gt;</code>	Defines user's telephone number.

**Table 28 userimport File - XML Tag Definitions (cont'd)**

XML TAG SETS	DESCRIPTION
<b>&lt;Email&gt; &lt;/Email&gt;</b>	Defines user's e-mail address.
<b>&lt;Groups&gt; &lt;/Groups&gt;</b>	<p><b>&lt;Groups&gt;</b> is the opening tag for the <b>&lt;Groups&gt; &lt;/Groups&gt;</b> tag set.</p> <p>There can be multiple <b>&lt;Group&gt;&lt;/Group&gt;</b> tag sets inside the <b>&lt;Groups&gt;&lt;/Groups&gt;</b> tag set.</p> <p>All <b>&lt;Group&gt;&lt;/Group&gt;</b> tag sets are contained within the <b>&lt;Groups&gt;&lt;/Groups&gt;</b> tag set for the user being defined.</p> <p>This tag set is not required if the user does not belong to a group or groups.</p>
<b>&lt;Group&gt; &lt;/Group&gt;</b>	<p><b>&lt;Group&gt;</b> is the opening tag for the <b>&lt;Group&gt; &lt;/Group&gt;</b> tag set. This tag set defines the group name that the user belongs to.</p> <p>There can be multiple <b>&lt;Group&gt;&lt;/Group&gt;</b> tag sets inside the <b>&lt;Groups&gt;&lt;/Groups&gt;</b> tag set.</p> <p>This tag set is not required if the user does not belong to a group or groups.</p>
<b>&lt;Role&gt; &lt;/Role&gt;</b>	<p>Defines the user as an administrator.</p> <p>Valid value = <b>admin</b></p> <p>This tag is required if the user will have administrative rights.</p>

## Example

The sample **userimport** file shown in [Figure 5](#), when called from the command line by the command listed below, will add two users: The first user is added to the **NE\_Reporting** group and has administrative rights to the Web Access Server. The second user is added to the **Technical Services** group.

```
userimport -h app_server -p app_server_port -U admin_username  
          -P admin_password -f full_path_and_filename
```

```
<?xml version="1.0" encoding="UTF-8"?>
<Users>
  <User>
    <Action>Add</Action>
    <ID>lsmiley</ID>
    <Password>4822</Password>
    <RealName>Leonard Smiley</RealName>
    <Department>NE_Reporting</Department>
    <Phone>310-732-2144</Phone>
    <Email>lsmiley@wnmb.com</Email>
    <Groups>
      <Group>NE_Reporting</Group>
    </Groups>
    <Role>admin</Role>
  </User>
  <User>
    <Action>Add</Action>
    <ID>wbentley</ID>
    <Password>0494</Password>
    <RealName>William Bentley</RealName>
    <Department>Technical Services</Department>
    <Phone>310-732-9844</Phone>
    <Email>wbentley@wnmb.com</Email>
    <Groups>
      <Group>Technical Services</Group>
    </Groups>
  </User>
</Users>
```

Figure 5 Sample userimport Text File

*userimport*

## vantage\_collect

You can use the **vantage\_collect** command to collect SNMP data from two linked tables that have a control table and data table relationship, for example, on an HP OpenView Performance Insight (OVPI) system.

### Requirements and Restrictions

- In general, the collection by-variables (other than `target_name`) in a property table define the instances the poller will poll for.
- The **MibIndexMap** statement in the TEEL definition file for the child table identifies the parent (source) table; this is the link between the two data tables for this command.
- To collect data with this command, the collector module for the data table must be **dsi\_hst**.

# Syntax

The **vantage\_collect** command uses the following syntax:

```
vantage_collect [ -a ]  
                  [ -A ]  
                  [ -b ]  
                  [ -c max_processes ]  
                  [ -C wait_time ]  
                  [ -d debug_level ]  
                  [ -D thread_wait_time ]  
                  [ -e ]  
                  [ -E clock_error_value ]  
                  [ -F min_disk_pct ]  
                  [ -g ]  
                  [ -G debug_level_pm ]  
                  [ -H alternate_poller_name ]  
                  -i interval  
                  [ -I check_index ]  
                  [ -k ]  
                  [ -K suppress_spikes ]  
                  [ -L ]  
                  [ -M minimum_filter ]  
                  [ -n ]  
                  [ -N retry_interval ]  
                  [ -o timeout ]  
                  [ -p max_entries_per_pdu ]  
                  [ -P snmp_port ]  
                  [ -q log_info_level ]  
                  [ -Q name ]  
                  [ -r retries ]
```



```

[ -R min_rows ]
[ -s round_factor ]
[ -S snmp_version ]
[ -u ]
[ -V ]
[ -w high_water_mark ]
[ -W high_water_mark_log ]
[ -X ]
[ -y ]
[ -Y delta_time ]
[ -z child_debug_level ]
[ -Z debug_log_bcpgateway ]

```

## Options

The **vantage\_collect** command has the following options:

- a** Directs the child collectors of **vantage\_collect** to output the collected data in ASCII format. You may want to do this for debugging purposes.
- A** Enables archiving of raw data. The default is no archiving. When you use this option, it turns on archiving. The archive function stores the collected data in a raw data table. This option is in UPPERCASE. This option is equivalent to the **@bArchive=1** parameter in **trendpm**.

- b** Forces regeneration of definition files and worktable.

The poller analyzes the structure of the table to be collected and creates definitions about how to load data into database for the `bcp_gateway` process. This is a one-time process most of the time. However, when the poller realizes that the structures of the data table or related property tables have changed, it regenerates the `bcp_gateway` process definitions and worktable.

The **-b** option forces the regeneration of these definition files, and cleans up any internal database objects used during data loading.

See the discussion for the **-g** option on [page 524](#) for more information.

See the discussion for the **-k** option on [page 525](#) for more information.
- c** Specifies the number of collection processes to run concurrently. When **vantage\_collect** starts, it starts child processes that actually do the collections.

The default is **5**.

You can reduce SNMP collection cycles by increasing this number.
- c** Specifies the number of minutes that each child process can run. The system kills the child process if it runs longer than the specified number of minutes.

The default is **30** minutes.

This option is in UPPERCASE.
- d** Sets the debug output level for the parent instance of **vantage\_collect**. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.

The default is **0**, which means no debug output. Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **vantage\_collect**.

The **-z** and **-z** options set the debug level for the child processes of **vantage\_collect**. The **-d**, **-z**, and **-z** options can be used together to control the debug level of parent and child processes independently.

- D** This option specifies how many seconds the parent thread should wait for signals from the collector and bcp\_gateway threads.

It is normal to get thread\_wait timeout messages in the log file when waiting for signals from the bcp\_gateway or **trendpm** thread due to potential long running jobs when writing to the database. The program exits when a thread\_timeout occurs, unless the thread\_timeout occurred when all collector jobs are finished and only bcp\_gateway or **trendpm** threads remained. In this case, the timeout only appears in the trend.log file.

The default is the same value as the **-C** timeout value, which is **1800** seconds. For example, if the **-C** value is **2** (2 minutes), then the **-D** value defaults to **120** (120 seconds).

This option is in UPPERCASE.
- e** Turns on **GETBULK** when using SNMP-V2.

When the poller uses SNMP-V2, you can opt to use the GETBULK request instead of GETNEXT when getting SNMP data.
- E** Sets the percentage level for valid data. The value is the percentage of difference between the delta values of two Received Timestamps and two System Uptimes. These statistics come from two consecutive raw data samples.

For example, if r1 and s1 are the Received Timestamp and System Uptime for the first sample, and r2 and s2 are the Received Timestamp and System Uptime for the second sample, then the calculation for the value is  $((r2 - r1) - (s2 - s1)) * 100 / (r2 - r1)$ . During processing, if the calculated value for the samples exceeds the value set by this option then the samples are rejected.

The default value is **10**.

This option is in UPPERCASE.

This option is equivalent to the **@zerror** parameter in **trendpm**.
- F** Specifies the minimum disk space (as percent of total disk space) that must exist on the disk where the \$COLLECT\_HOME directory resides. If less space exists on the directory, **vantage\_collect** does not execute.

The default is **5**, which represents 5 percent.

This option is in UPPERCASE.

- g** Use 3.5.x compatibility. That is, use the same method for inserting data into the table as version 3.5.x and earlier.

The **-g** option loads data into archive (raw) tables directly. The `bcp_gateway` definition file contains the setting for the **-g** option. This means that if you already invoked **vantage\_collect** without the **-g** option and you need the **-g** option, then use the **-b** option to regenerate the definition file. Similarly, if you already invoked **vantage\_collect** with the **-g** option and you do not need the **-g** option, then use the **-b** option to regenerate the definition file. Otherwise, **vantage\_collect** uses the same setting for the **-g** option currently in effect when you originally generated the definition file.
- G** Sets the debug output level for the **trendpm** process of **vantage\_collect**. Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.

The default is **0**, which means no debug output.

Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **vantage\_collect**.

This option is in UPPERCASE.

This option is equivalent to the `@debug_level1` parameter in **trendpm**.
- H** Specifies an alternate poller name. When you run **vantage\_collect** in distributed mode, with the **-n** option, the poller compares the local hostname to the **Poll From** field in the polling policy. When you use the **-H** option, **vantage\_collect** compares the **Poll From** field in the polling policy to the alternate poller name.

This option is in UPPERCASE.

See [Distributed Polling on page 277](#) for more information.
- i** Is the Collection ID. **vantage\_collect** executes the entries in the polling policy that have this value in their **Interval** field. How frequently **vantage\_collect** is actually run depends on the configuration of **trendtimer**, but the idea is to be consistent so that a collection request with a collection ID of **5** is run every 5 minutes. See [File Locks on page 275](#) for additional information.

This option is required.

- I** Specifies whether to use existing indices on the upload table or to drop existing indices and then recreate them. The value **1** means that the existing indices on the upload table are used. The value **0** means that the existing indices are dropped and then recreated. If the value is **1** and the proper indices are missing then the raw-to-delta process fails.

The default is **0**.

This option is in UPPERCASE.

This option is equivalent to the **@bCheck\_index** parameter in **trendpm**.
  - k** Populates the property tables (but not the data tables) for the devices you are polling.

The `bcp_gateway` definition file contains the setting for the **-k** option. This means that if you already invoked **vantage\_collect** without the **-k** option and you need the **-k** option, then use the **-b** option to regenerate the definition file. Similarly, if you already invoked **vantage\_collect** with the **-k** option and you do not need the **-k** option, then use the **-b** option to regenerate the definition file. Otherwise, **vantage\_collect** uses the same setting for the **-k** option currently in effect when you originally generated the definition file.
  - K** Specifies whether to reject samples if there are spikes. A spike is defined when a counter is manually reset, the difference of two consecutive samples from a counter exceeds the spike threshold, and the second sample is less than the first sample. The value of the spike threshold is  $2^{31}$  for 32-bit counters or  $2^{51}$  for 64-bit counters. Remember if the difference of the samples is negative; account for the rollover of the counter by adding  $2^{32}$  for 32-bit counters or  $2^{52}$  for 64-bit counters.

Valid values for *suppress\_spikes* are:

    - 1** Rejects samples if a spike occurs.
    - 0** Does not reject samples. The default is **0**.

This option is in UPPERCASE.

This option is equivalent to the **@bSuppress\_spike** parameter in **trendpm**.
-

- L** Specifies that the collected data be stored locally instead of in the OVPI database. When you use this option, **vantage\_collect** uses any previously saved collection definitions, and does not use the database.  
This option is in UPPERCASE.
- M** Sets the *minimum\_filter* value. The procedure rejects the sample if the delta value of a counter falls below this value.  
The default value is **-1**, which means to accept the entire sample.  
This option is in UPPERCASE.  
This option is equivalent to the **@line\_suppress\_value** parameter in **trendpm**.
- n** Enables distributed polling. If this option is used, **vantage\_collect** executes the collection request only if the **Poll From** field in the polling policy record for this collection request matches the hostname of the machine on which **vantage\_collect** is running. If you omit this option, **vantage\_collect** executes all polling requests whose interval matches the value of the **-i** option, regardless of the hostname specified to do the polling in the polling instructions.  
You can set an alternate hostname to poll with the **-H** option. See [Distributed Polling on page 277](#) for more information.
- N** Sets the *retry\_interval*, which is the number of seconds the procedure needs to wait in order to acquire a lock on an upload table.  
The default value is **10**, which is 10 seconds.  
This option is in UPPERCASE.  
This option is equivalent to the **@retry\_interval** parameter in **trendpm**.
- o** Number of seconds **vantage\_collect** is to wait for a response after sending an SNMP request.  
The default is **1** second. (SNMP timeout.)
- p** The number of SNMP variables to include in the varbind list in the GETNEXT PDU (Protocol Data Unit) request. It is possible to generate a GETNEXT request that yields a response that is too long to transmit.  
The default value is **20**.

- P This option allows the collection of SNMP data from the specified port rather than the default SNMP port of 161.  
This option is in UPPERCASE.
  
- q Sets the log information level for the parent instance of **vantage\_collect**.  
Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is **0**, which means no log information for the parent instance of **vantage\_collect**.  
If the \$TREND\_LOG environment variable is set, then the log is written in the directory specified by the \$TREND\_LOG environment to a log file named vantage\_collect\_dbg.log; the path and file name is \$TREND\_LOG/vantage\_collect\_dbg.log.  
If the \$TREND\_LOG environment variable is not set, then the log is written to the same log file name in the \$DPIPE\_HOME/log directory; the path and file name is \$DPIPE\_HOME/log/vantage\_collect\_dbg.log.  
You can modify the log file name using the **-Q** option.
  
- Q Specifies the *name* for the ROOT of the trace log file. You can use this option to change the name of the log file, as follows:  
*pathname\_pid\_ppid\_polltime\_dbg.log*  
where: *path* is \$TREND\_LOG if the environment variable is set; otherwise, it is \$DPIPE\_HOME/log.  
*name* is the name of the file that you supply.  
*pid* is the process id number for this process.  
*ppid* is the process id number of the parent process.  
*polltime* is the number of seconds since 01/01/1970 00:00.  
When you use this option, set the **-q** option to a value greater than **0**.  
This option is in UPPERCASE.
  
- r Specifies the *retries*, which is the number of times **vantage\_collect** resends an SNMP request before assuming the target node is not going to respond.  
The default value is **5**. (SNMP retries)

- R** Sets the minimum number of rows to collect before starting the loading of data into database. The number of rows is an approximation, since there is an assumption that each row is 500 bytes.  
The default value is **1000** rows, which means that the loading of the file into the database starts when the size is 500,000 bytes (500 \* 1000).  
This option is in UPPERCASE.
- s** This option rounds off the collection time (*ta\_period*). If the **vantage\_collect** parent kicks off a collection at 3:07, and if you are using the default collection option of **300** seconds (5 minutes), the actual *ta\_period* value for the collection will be recorded as 3:05.
- S** Specifies the SNMP version. This option is in UPPERCASE.  
Valid values:   **1** for SNMP V1  
                  **2** for SNMP V2C.  
This option overrides the values read from the database.
- u** Displays the command line formats for **vantage\_collect**.
- V** Displays the version stamp for **vantage\_collect**.  
This option is in UPPERCASE.
- w** Specifies the *high\_water\_mark*. The high water mark stops collection of data when the database-used size reaches the specified percentage.  
Valid values are **1 - 100**.  
The default parameter is **90** for 90%.
- W** Specifies the *high\_water\_mark\_log*. The high water mark stops collection of data when the log-used size reaches the specified percentage. Valid values are **1 - 100**.  
The default parameter is **90** for 90%.  
This option is in UPPERCASE.
- X** This option turns off **trendpm** capability.  
This option is in UPPERCASE.
- Y** This option disables the calculation of `total count` for `bcp_gateway` metrics.



- Y** Specifies which clock to use to calculate Delta Time.  
Valid values are:
- 1** Directs the procedure to use System Uptime to calculate Delta Time.
  - 0** Directs the procedure to use the `received_ts` column for the calculation.
- The default is **0**.  
This option is in UPPERCASE.  
This option is equivalent to the `@bDelta_time` parameter in **trendpm**.
- z** Sets the debug level for child collector processes.  
Values of **0**, **1**, **2**, or **3** are valid. The higher the number, the more detailed the information.  
The default is **0**, which means no debug output.  
Debug output is written to standard out. You should only use this option for testing in coordination with HP Technical Support due to the additional overhead it places on **vantage\_collect**.
- z** This option specifies whether to turn on debugging or logging or both for the `bcp_gateway` process. When the logging option is turned on, the information is written to the log file. The name of the log file varies depending on which environment variable is set.  
If the `$TREND_LOG` environment variable is set, then the log is written in the directory specified by the `$TREND_LOG` environment to a log file named `bcp_gateway_dbg.log`; the path and file name is `$TREND_LOG/bcp_gateway_dbg.log`.  
If the `$TREND_LOG` environment variable is not set, then the log is written to the same log file name in the `$DPIPE_HOME/log` directory; the path and file name is `$DPIPE_HOME/log/bcp_gateway_dbg.log`.  
Valid values for this option are:
- 1** Turn on logging.
  - 2** Turn on debugging.
  - 3** Turn on both logging and debugging.
- This option is in UPPERCASE.

## Usage Notes

You can use the **vantage\_collect** command to collect data from two data tables linked together with the **MibIndexMap** statement in the TEEL definition file for the child data table. Note that if there is no link to a second data table, **vantage\_collect** will collect data from the single data table. Sometimes, the reference to the second data table could be a parent table or a control table.

To collect data with this command, the setting for the **CollectorModule** statement in the TEEL definition file for the data table must be **dsi\_hst**.

The **vantage\_collect** command is a wrapper around the **mw\_collect** command; this means that the **vantage\_collect** command processes the options on its command line that are listed in this chapter first and then passes the results and any other **mw\_collect** options that appear on its command line to **mw\_collect** to complete the processing. See [mw\\_collect on page 255](#) for more information.

Typically, the **vantage\_collect** command generates two **mw\_collect** commands to collect the data. It generates an **mw\_collect** command for the parent or control data table to collect and process data for every device in the collection group; when it completes the processing of that command it generates the second **mw\_collect** command to collect the data from the child data table. Note that if some devices in the collection group are very slow, you may want to create a separate collection group and polling policy for those devices, because the second **mw\_collect** command will not start until the first one finishes its processing for each device in the group.

If the **MibIndex** statement in the TEEL definition file for the child data table has a time-related variable length, **vantage\_collect** will invoke a child process of **mw\_collect** with the **method** parameter set to **MTD\_HST**. Note that **mw\_collect** will execute the **method** parameter only if the **ByVarInfo** statement is set to **hst** in the TEEL definition file.

Refer to the *Performance Insight TEEL Reference Guide* for more information about the TEEL statements.

## Example

In this example, the system will locate the entries that have a collection ID of 15 for the hostname that matches the hostname where this command is running and then collect the data from the two tables identified in the policy. It will reject any sample that is a spike.

```
vantage_collect -n -i 15 -K 1
```



## viewctl

You can use the **viewctl** command to add, delete, or modify a single catalog view on an HP OpenView Performance Insight (OVPI) system. A *catalog view* is a list of deployed reports in the system folder that a user can access. This view applies to any database that the user may access.

You can use this command instead of the **Catalog Views** page on the Web Access Server; refer to the *Performance Insight Administration Guide* for more information about using the GUI tools.

## Requirements and Restrictions

- You must be an administrative user to use this command.
- Each time you invoke this utility, you must enter the required options: **-host**, **-mode**, **-port**, **-pwd**, and **-user**, and **-view**.

## Syntax

The **viewctl** command uses the following syntax:

```
viewctl    [ -add rpt_name ]  
            [ -del rpt_name ]  
            [ -desc desc_text ]  
            [ -help ]  
            -host host_name  
            [ -interactive ]  
            -mode type  
            [ -name viewname ]  
            -port port_num  
            [ -protocol protocol ]  
            -pwd adm_pwd  
            -user adm_user  
            [ -verbose ]  
            [ -version ]  
            -view viewname
```

## Options

The **viewctl** command has the following options:

- add**                    Use this option to specify the name of the report or folder to add to the view, relative to the system folder. You can add the reports or folders one at a time after you create the view.
- Use this option with **modify** mode only.

- del** Use this option to specify the name of the report or folder to remove from the view, relative to the system folder. Use this option with **modify** mode only.
- desc** Use this option to enter a description of the view. Enclose the text in double quotes if it contains any spaces.
- help** Use this option to display the syntax for the **viewctl** command.
- host** Use this option to specify the Web Access Server hostname where the transaction occurs. This is a required option.
- interactive** Use this option to display the login box. When you use this option, the system will display the login box if the entry for one or both of the **-user** or **-pwd** options is incorrect; otherwise, the system will display an error message.
- mode** This option specifies the type of transaction to perform that affects the entire view. For example, if you specify **delete** for this option, the system will remove the view from the catalog. Valid entries are:
- |               |  |
|---------------|--|
| <b>add</b>    | Use this mode to add a new view to the catalog.                                    |
| <b>delete</b> | Use this mode to delete the view from the catalog.                                 |
| <b>modify</b> | Use this mode to modify an existing view by adding or deleting reports or folders. |
- This is a required option.
- name** This option specifies the new name of the view. If the name contains spaces, enclose it in double quotes. Use this option with **modify** mode only.

- port** Use this option to specify the Web Access Server port number where the transaction occurs.  
You must enter this option even though the default for this option is the port number supplied during the OVPI installation, which is port number **80**, in most cases.  
This is a required option.
- protocol** Use this option to specify the communication protocol for the view.  
Valid values are **http** or **https**.
- pwd** Use this option to specify the corresponding password for the username that has authorization to make the specified changes.  
This is a required option.
- user** Use this option to specify the username that has authorization to make the specified changes. This username must have administrative privileges.  
This is a required option.
- verbose** Use this option to turn on verbose messaging.
- version** Use this option to display the current version of **viewctl**.
- view** Use this option to specify the name of the view to add, modify, or delete.  
This is a required option.

## Usage Notes

The purpose of this command is to manage a single OVPI catalog view. The process is to create the view and then add reports or folders to it one at a time using the **-add** option.

To remove a report or folder from the view, use the **-del** option. The **-mode delete** option removes the entire view.



## Modes of Operation

The **viewctl** command has three modes of operation: add, modify, and delete.

### Add

The *add* mode enables you to add a view to the OVPI catalog on the Web Access Server.

### Modify

The *modify* mode enables you to change the contents of an existing OVPI catalog view on the Web Access Server.

### Delete

The *delete* mode enables you to remove an existing view from the OVPI catalog on the Web Access Server.

## Using the viewctl Command

This section shows some formats of the command for the various modes. The **viewctl** command requires the six options shown and defined in the first bullet below. The following discussions of the various modes (for example, **add**) show the command with these basic options, along with the options that are specific to each task.

- All **viewctl** commands must have all the following options for each task:

```
viewctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -view viewname -mode action
```

where: *host\_name* is the name of the host for the Web Access Server.

*port\_num* is the port number for the Web Access Server.

*adm\_user* is the administrative user name that has authorization to make the specified changes.

*adm\_pwd* is the corresponding password for the administrative user that has authorization to make the specified changes.

*viewname* is the name for the OVPI catalog view to add, modify, or delete.

*action* is the type of action to perform, such as add, modify, or delete.

- If you enter the **viewctl** command without any options, the system will display the help information. Use the following format.

```
viewctl
```

- If you want to display the version for the **viewctl** command, enter the following command.

```
viewctl -version
```

- If you want the login box to pop up if either of the required options, **-user** or **-pwd**, is incorrect, enter the following command.

```
viewctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -view viewname -mode action -interactive
```

## Add

The following formats show various options for adding a view to the OVPI catalog on the Web Access Server. Note that you can combine the additional options in any manner that meets your needs.

- To add a view to the OVPI catalog on the Web Access Server, enter the following command:

```
viewctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -view viewname -mode add
```

- To add a view to the OVPI catalog on the Web Access Server with a description, enter the following command:

```
viewctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -view viewname -mode add -desc "text"
```

where: *text* is the description for the view.

## Modify

- To add a report or folder to an existing view in the OVPI catalog on the Web Access Server, enter the following command:

```
viewctl -host host_name -port port_num -user adm_user  
-pwd adm_pwd -view viewname -mode modify -add "rpt_name"
```

where: *rpt\_namet* is the name of the report or folder. Use quotes if there are any spaces in the name.

- To remove a report or folder from an existing view in the OVPI catalog on the Web Access Server, enter the following command:

```
viewctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -view viewname -mode modify -del "rpt_namet"
```

where: *rpt\_namet* is the name of the report or folder. Use quotes if there are any spaces in the name.

## Delete

- To remove a view from the OVPI catalog on the Web Access Server, enter the following command:

```
viewctl -host host_name -port port_num -user adm_user
-pwd adm_pwd -view viewname -mode delete
```

## Examples

The following examples illustrate some uses of the **viewctl** tool.

### Example 1: Add a View

To add a view with the name **view\_1** to the OVPI catalog on the **powder2** host, you can use the following command.

```
viewctl -host powder2 -port 80 -user trendadm -pwd trendadm -view
view_1 -mode add
```

### Example 2: Remove a Report from a View

To delete a report with the name **myrep.rep** from the view with the name **view\_1** from the OVPI catalog on the **powder2** host, you can use the following command.

```
viewctl -host powder2 -port 80 -user trendadm -pwd trendadm -view
view_1 -mode modify -del /system/dira/dirb/myrep.rep
```

### Example 3: Delete a View

To delete a view with the name `view_1` from the OVPI catalog on the `powder2` host, you can use the following command.

```
viewctl -host powder2 -port 80 -user trendadm -pwd trendadm -view
view_1 -mode -mode delete
```

## Error Messages

This section describes some of the messages that can occur from `viewctl`. Each message has the following format:

- A brief description about why the message appears. Each new message description starts with a check box.
  - The actual message that appears with parameters for any information that may be missing.
  - A suggestion about the action to do so that the message will not appear again.
- If the following message appears, the user is unauthorized to create, modify, or delete a user account.

Unauthorized.

Verify the following:

- The user (`-user`) and password (`-pwd`) values are correct.
- The specified user has administrator privileges.

- If the following message appears, there is an incorrect option on the command line.

Invalid Argument Supplied

Verify that all of the options are correct on the command line. See [Syntax on page 534](#) for the valid options.

- If the following message appears, there is an incorrect value for the `-mode` option on the command line.

Error - Invalid application mode

Verify that the `-mode` option has the value `add`, `modify`, or `delete` on the command line.

## viewer

You can use the **viewer** command to start the Report Viewer client application from the command line on an HP OpenView Performance Insight (OVPI) system.

### Requirements and Restrictions

- When you connect to a different server with the **-server** option, use the **Browse** option to view the files on the specified server.
- When you use the **-mode remote** option, you must include the **-file** option on the command line at the same time.
- When you use the **-file** option without the **-mode** option on the command line, the system will open the specified file on the local system.
- When you change a parameter with the **-params** option, remember that it is a global option and it applies to every report you open that has the parameter specified.

## Syntax

The **viewer** command uses the following syntax:

```
viewer [ -debug dbug_value ]  
        [ -file path_reportname ]  
        [ -log logfile ]  
        [ -mode location ]  
        [ -p password ]  
        [ -params parameter1=value1[,parameter2=value2, ... ] ]  
        [ -port number ]  
        [ -server servername ]  
        [ -u username ]
```

## Options

The **viewer** command has the following options:

- debug**      Use this option to enable diagnostic messages, which are an extra level of detail included in the log file.  
Valid values are:  
**true**            will enable diagnostic messages  
**false**          will not enable diagnostic messages  
The default is **false**.
- file**        Use this option to specify the name of the report you want to open automatically when you run **viewer**. You can use the absolute or relative path with the name of the report file. For a remote file, you need to give the remote location in reference to its deployed location.

- log** Use this option to specify the name of the log file to open. Include the path for the name. The name should have a slash as the first character in the name because the system will add the prefix OVPI to the specified name.  
The default log file is `viewer.log`.
- mode** Use this option to specify the location for the file you want to access. There are two values; they are:  
**local** when the file is on the local system.  
**remote** when the file is on the Web Access Server.  
The default is **local**.  
Use the **-file** option to specify the name and location of the file. You must use the **-file** option with this option to open a remote file automatically when you run **viewer**.
- p** This option specifies the password for the login process.  
If you do not use this option with the **-u** option, the system will prompt for the username and password.  
Use this option to specify the corresponding password for the username that has authorization to view the reports.

- params** Use this option to specify the report parameters to change report defaults at run time. A parameter has the following format: *parameter=value*. This is a global option; it applies to every report you open that has the parameter specified.
- When you specify more than one parameter, separate the parameters with a comma (,). When a parameter value contains a space, enclose all the parameters in one set of quotes. The following example shows multiple parameters with one parameter that has a space in the value.
- params "INTERFACE=92,CUSTOMER=All Telco"**
- When a parameter value contains a character that is special to the command interface (shell) such as a comma, precede the character with a backward slash (\), for example:
- params "INTERFACE=92,CUSTOMER=Telco\,North"**
- Refer to the *Performance Insight Guide to Building and Viewing Reports* for details about how to view or modify the parameters associated with a report using Report Viewer, and for details about how to view and modify the parameters associated with a report using the Web Access Server.
- port** Use this option to specify the port number of the Web Access Server that you want to access from the Report Viewer client application.
- The default for this option is the port number supplied during the OVPI installation, which is port number **80**, in most cases.
- server** Use this option to specify the host name of the Web Access Server that you want to access from the Report Viewer client application. If you want to access a system in a different domain, you will need to specify the full domain name for the host name.
- The default for this option is the server host name supplied during the OVPI installation.
- u** This option specifies the username for the login process. If you do not use this option with the **-p** option, the system will prompt for the username and password.



## Usage Notes

You can use Report Viewer to open and view reports located on your system and on the Web Access Server, modify existing reports to change how the data is displayed, and save and print reports. Refer to the *Performance Insight Guide to Building and Viewing Reports* for more information about using the Report Viewer client application.

If you want to browse the reports on a remote system when you run **viewer**, you can use the **-server** option alone. However, if you want to open a specific report file automatically when you run **viewer**, you can add the **-mode remote** option with the **-file** option.

## Examples

The following examples illustrate some uses of the **viewer** command.

### Example 1

You can use this example to log into the Report Viewer on a Windows operating system and display a report with the name, `Capacity_Planning.rep`, the **INTERFACE** parameter set to **92**, and the **CUSTOMER** parameter set to **Telco**.

```
viewer -file
D:\software\trend\reports\deploy\system\Interface_Reporting\
Interface\Capacity_Planning.rep -u katter -p dusquesne -params
INTERFACE=92,CUSTOMER=Telco
```

### Example 2

You can use this example to perform the same action as in the previous example, [Example 1](#), except that the report is on the Web Access Server.

```
viewer -file /system/Interface_Reporting/Interface/
Capacity_Planning.rep -u katter -p dusquesne -params
INTERFACE=92,CUSTOMER=Telco -mode remote
```

*viewer*

# A

## Error Messages Index

### Symbols

`"value"` is a bad argument for the option `"option"` . 95

### A

A destination server needs to be specified. 373

A mode of operation is required. 66, 123, 295

A value is required for argument `option : desc`. 49

A value is required for argument `rn` : Report file name to generate. 345, 346

Adding the requested date range to the total of `"number"` days to table `"table_name"` will exceed the total default of `"retention"` days by more than 2 times. 354

Adding the requested date range to the total of `number` days to table `table_name` will exceed the total default of `retention` days by more than 2 times. 480

Alias table `"table_name"` does not exist. 88

Argument `"value"` is not allowed with `"-mw"` option. 141

argument `option` missing value 200

argument `value` is invalid 200

Argument `value` is invalid for option `option`. 84, 141

Argument `value` is not defined for the option `option`. 84, 141

## Error Messages Index

Argument *value* is obsolete for option *option*. 84, 142

Arguments for option *option* must be enclosed in double quotes. 84, 141

### C

Can't find schedule. 345

Collection interval must be a number. 66

Collection *policy\_name* does not exist. 67

Collector module must be specified as "dsi\_ee" in TEEL file *file\_name*. 139

Column *ta\_period* not found in table "*table\_name*". 95

command line error: [argument *option* missing value] 200

command line error: [argument *value* is invalid] 200

Connection URL not found. 67, 123, 201, 295, 385

Copy of keymap is not allowed when source db = destination db 371

Copy of *source\_table* to *destination\_table* is not allowed when source db = destination db. 374

Could not convert string to integer on line *n* - interval invalid. 68

Could not find installed datapipe for *host\_name*. 67

### D

Data table "*table\_name*" not found in OVPI dictionary. 137

Data table mismatch between TEEL file and collection policy : *table\_name*. 140

Database "*db\_name*" was not found in systems.xml file. 372

Datapipe *datapipe\_name* on line *n* does not exist for table *table\_name*. 68

DataPipe mismatch between TEEL file and collection policy : *datapipe\_name* 139

*db\_delete\_data*

"msg". 94

Debug level must be a number. 68, 123

Debug level must be between 0 and 3. 68, 123

*destination\_table* is a view 375

Directory deployment failed. 152

Directory deployment failed: Unauthorized. 105

Directory undeployment failed. 152

Directory undeployment failed: Unauthorized. 105

### E

Error - Invalid application mode 509, 540

Error in arguments *option* is not valid for this program. 50

Error in arguments. 49

Error processing command line: A value is required for argument *option* :  
*description*. 105, 153

Error processing command line: Option *option* must be specified. 105, 153

Error: failed to find any by-variables in *property\_table\_name* on *server\_name*. 376

Error: failed to get ip information for host *host\_name*. 372

Error: foreign-key reference column *fkey\_name* is not *dsi\_key\_id* for column  
*col\_name* in prop table *table\_name* on *server\_name*. 377

Error: source\_property\_table on source\_server has num1 by-variables while  
destination\_property\_table on destination\_server has num2. 376

Error: source\_property\_table on source\_server has source\_byvar as by-var num  
while destination\_property\_table on destination\_server has  
destination\_byvar. 376

Error: *src\_server\_name* and *dest\_server\_name* have the same network address of *address*.  
372

ErrorCode:*number* 201

Exception: Wrong number of delimiters on line *n*. 69, 295

Executing program *program\_name* generated error: *msg*. 94

Executing the SQL command "*command*" generated middleware error "*msg*". 94

Exiting program with code 1. 66, 68, 70, 71, 72, 123, 124, 125, 126, 295

Exiting program with code 2. 69, 123, 296

Exiting program with code 3. 67, 123, 295

Exiting program with code 4. 68, 69, 70, 124, 125, 295

Exiting program with code 7. 124

## F

failed creating polling policy (trndbexp) pollPolicy: [*policy\_name*] datapipe  
{*datapipe\_name*} dataDB {*datadb\_value*} topDB {*groupdb\_value*} table  
{*table\_name*} interval {*interval\_value*} group {*group*:  
category=(*category\_name*) name=(*group\_name*)} pollFrom 202

failed exporting polling policy [*policy\_name*]. 202

failed getting group definition from DB for group name=*group\_name* group  
category=*category*. 201

Failed parsing XML. Input=*xml\_file\_name*. 87

Failed processing TREND object. 201, 202

Failed to connect to *database\_name* database. 201

## Error Messages Index

Failed to connect to *server\_name*. 50  
Failed to connect with  
    *database\_name*. 87  
Failed to convert property only TEEL file "*file\_name*". 137  
Failed to convert TEEL file "*file\_name*". 137  
Failed to create dpipe\_file control file : *file\_name*. 137  
Failed to create mw config file : *file\_name*. 137  
Failed to execute mw\_collect. 138  
Failed to execute post-processor *post\_proc\_name*. 140  
Failed to execute pre-processor *pre\_proc\_name*. 140  
Failed to get TEEL file from dictionary for datapipe : *datapipe\_name* and poll\_from  
    : *server\_name*. 138  
Failed to perform TEEL base collection. 138  
Failed to validate rule file for a given datapipe and hostname. 138  
Failure on closing database connection generated the middleware error "*msg*". 95  
File does not have read access *file\_name*. 86, 143  
File *file\_name* does not exist. 69, 86, 123, 144, 296  
File *file\_name* referenced by option *option* does not exist. 84, 142  
foreign key reference column *fkey\_col\_name* for column *column\_name* in property  
    table *property\_table\_name\_1* is not in foreign property table  
    *fkey\_table\_name\_2*. 376  
Form deployment failed. 153  
Form or directory name must be specified. 153  
Form undeployment failed. 153

## G

Group *group\_name* does not exist. 69  
Group *group\_name* on line *n* does not exist. 69  
Group *grp\_name* must be an enumerated list. 124  
Group *grp\_name* not found or not an enumerated instance group. 124  
Group name must be specified category.group. 124

## I

I/O error in reading file *file\_name*. 86, 144  
I/O error in writing to file *file\_name*. 86, 144  
I/O error occurred. 106

in stored procedure *stored\_procedure\_name* 201  
Incorrect syntax in file *file\_name*. 87, 144  
Incorrect value for -c argument. Please specify "deploy" or "undeploy". 106, 154  
indexmaint utility program returned non-zero exit status. 94  
Input file *file\_name* doesn't exist. 201  
input file *file\_name* is not a file. 200  
Invalid Argument Supplied 509, 540  
Invalid collection interval. 70  
Invalid deployment type specified. Please specify "system" or "user". 106  
Invalid directory specified: *directory\_name*. 106, 154  
Invalid form specified: *form\_name*. 154  
Invalid poll interval on line *n*. 70  
Invalid report specified: *report\_name*. 106  
Invalid value for the -e option. The date must be in yyyyymmdd format. 377  
Invalid value for the -f option. The day of the week value must be one of the following: MO, TU, WE, TH, FR, SA, SU. 377  
Invalid value for the -g option. The time value must be between 0 and 23. 377

## L

Looking for schedule *sched\_name*. 345

## M

Maximum number of threads can not exceed *number*. 96  
Missing category name - line *n1*. 124  
Missing required option *option* for command *command\_name*. 85, 142, 385  
Missing the required '-sqlscript' option. 312  
Missing the required '-table' option. 305

## N

New and legacy import statements can not be used together. Replace legacy statements with new statements. 140  
No collections defined for the interval : *value*. 138  
No entry in *dictionary\_table* for *table\_name* on *server\_name*. 373  
No file specified. 70, 124  
No property table name for *table\_name* on *server\_name*. 373  
No source data file(s) found. ee\_collect Exiting. 144

## Error Messages Index

No table build by DPM for: *datapipe\_manager\_command*. 375  
No tables found in the *dictionary\_table* on *server\_name*. 374  
Node *node\_name* does not have a type or view specified - skipping. 296  
Non-successful HTTP command received: 206 345, 346  
Non-successful HTTP command received: 401 345

## O

Object by-variable mismatch on line *n1* - *n2* expected. 125  
Object definition file name must be specified. 200  
One or more threads returned with failure. 95  
Only one mode of operation is allowed. 71, 125  
Option "-port" must be specified. 345, 346  
-*option* is not valid for this program. 346  
Option *option* does not take an argument for command *command\_name*. 85, 142  
Option *option* is not defined for command *command\_name*. 85, 142  
Option *option* is obsolete. 85, 142  
*option* option must be specified. 106, 154  
Option *option* requires an argument for command *command\_name*. 85, 143  
Option *option* requires valid argument. 85, 143  
Option **-u** must be used with option **-U**. 94

## P

Poll from *host\_name* on line *n* not installed on datapipe *datapipe\_name*. 71  
pollPolicy: [policy\_name] datapipe {datapipe\_name} dataDB {datadb\_value} topDB  
{groupdb\_value} table {table\_name} interval {interval\_value} group {group:  
category=(category\_name) name=(group\_name)} pollFrom {pollfrom\_value} user  
{user\_value}. 202  
prog-name date/time - Ambiguous column name *column\_name*. 429

## R

Reached maximum number of open cursors. 375  
Received non-deadlock database error. 95  
Reduce the date range specified or use -F to override. 354, 480  
Report deployment failed: Unauthorized. 106  
Report not found. 346  
Report or directory name must be specified. 107



Report undeployment failed: Unauthorized. 107  
 Required directive *statement* is missing in TEEL file *file\_name*. 141  
 Required Environment variable not set  
   *env\_variable\_name*. 87  
 Rule file mismatch for datapipe : *datapipe\_name* and host\_name : *host\_name*. 139

## S

Schedule *user\_name*\*sched\_name* not found. 345  
 Selection of both -P and *option\_letter* is unacceptable. 378  
 SEVERE: Unknown host. *host\_name*. 107, 154  
 Source data files must be specified either in TEEL file or through command line  
   option. 139  
 Source data table *table\_name* does not exist on *server\_name*. 374  
 Source file or directory *file\_name* not found. 140  
 Source property table *table\_name* does not exist on *server\_name*. 374  
 specified group doesn't exist 202  
 SQL table "*table\_name*" does not exist. 88  
 Stored procedure "*proc\_name*" is longer than 30 bytes. 95  
 Syntax error - line *n*. 125

## T

Table *table\_name* on line *n* does not exist. 71  
 Target archive directory "*directory\_name*" not found. 144  
 The argument "*value*" of the option "*option*" is no longer supported. 96  
 The collection *policy\_name* does not exist. 202  
 The connection to the database "*database\_name*" could not be established  
   *reason*. 88  
 The connection to the database *server\_name* could not be established  
   Connection URL not found. 385  
 The connection to the default database could not be established. 88, 386  
 The database server *server\_name* was not found in the systems.xml file. 305, 312  
 The default database server was not found in the systems.xml file. 306, 312  
 The group category *grp\_category* was not found. 126  
 The group *group\_name* does not exist. 201  
 The group *grp\_name* does not exist. 125  
 The -modify option requires at least one of the following: -descr, -group,

-pollfrom, or -interval. 72

The option *option1* can not be used with option *option2*. 85, 143

The previous instance is already running. The process will not be executed  
*command\_string*. 88

The previous instance of *command* is already running. The process will not be  
executed. SystemError *sys\_error\_code*. [*sys\_error\_msg*] 437

The syntax of the command is incorrect. 386

The system cannot find the file specified. 386

The TREND version on *server\_name* is unknown. 371

The type group *type\_name* does not exist - skipping. 296

The view group *view\_name* does not exist - skipping. 296

Transformation definition *tname* not found in the OVPI system. 386

trendcopy does not copy into views. 375

Trendcopy for table *table\_name* in db *server\_name* is already running. 371

## U

Unable to connect to destination db (*server\_name*). 373

Unable to connect to source db (*server\_name*). 372

Unable to create file *file\_name* referenced by option *option*. 86, 143

unable to create TrendObject. 202

Unacceptable data type of *data\_type* for column *column\_name* in prop table  
*property\_table\_name* on *server\_name*. 375

Unauthorized. 154, 169, 509, 540

Unknown error occurred. 107

unknown operation 0 200

User *user\_name* is removing from schedule owned by *user\_name*. 345

## V

Value after -export expected. 126

*value* value in the table *table\_name* does not exist. (in stored procedure  
*stored\_procedure\_name*) 201

## Y

You are not authorized to view this website. 345

## Numerics

- 32-bit counters, 262, 525
  - spike threshold, 443
- 3.5.x compatibility, 260, 524
- 64-bit counters, 262, 525
  - spike threshold, 443

## Symbols

- `$DPIPE_HOME`
  - /lib directory, 136
  - /scripts, 390, 394, 397, 399
- .teel extension, 76

## A

- accounts
  - See* user accounts
- action
  - error messages, 42
  - syntax, 38
- action\_collect child collector, 40
- Action tag, 175, 515
- aging
  - criteria, 93
  - data out of database, 89

- Alias Name column
  - Table Manager, 92
- alias parameter, 77
- alter
  - datapipe, 83
  - parameter, datapipe\_manager, 79
- Analyze Table command, 210, 213
- angle brackets, XML tags, 174, 514
- archive server, 366
- archiving raw data, 258, 442, 521
- ASCII file
  - format for collection\_manager, 58
  - format for dip\_manager, 116
  - format for node\_manager, 288
- as-is mode, 83
- automatic scheduling, 40

## B

- backing up log files, 267
- back-up files *See* log\_backup
- backup option, 181, 196
  - example, 199
- baseline, 462

- bcp\_gateway
    - defined, 268
    - definition file, 260, 262, 524, 525
    - procedure, 269
    - turn on debugging/logging, 266, 529
    - with local data storage, 276
  - BCP batch file, 365
  - bcp command, 300, 302, 304
  - begin statement, 451
  - bin directive, 219
  - block
    - definition, 450
    - empty, 451
    - naming convention, 452
    - series of sequential commands, 449
    - types, 450
    - unique name, 452
  - builder, 45
    - options, 46
    - syntax, 46
  - by-variable, 358, 460
    - error messages, 375
    - grouping, 463
    - trend\_sum, 475
  - ByVarInfo statement, 530
  - C**
  - caching poller, 268
  - calculate end point to process data, 477
  - catalog view, 533
  - category
    - group, 56, 57, 113, 114, 116, 187
    - defined, 189
    - type, 233
  - central server, 366
  - character data, entering, 442
  - check syntax of statements in TEEL file, 81
  - child collector
    - action\_collect, action, 40
  - ChildGroups tag, 175
  - child poller
    - defined, 268
    - responsibilities, 269
  - child process, 38
    - bcp\_gateway, 268
  - Child tag, 176
  - collection
    - See also* data collection
    - from OVP Agent or OVO Agent, 313
    - policy, install with Package Manager, 233
    - processes, 130
      - concurrent, 258, 522
    - request, 131, 136
    - retries, 39
    - routine, 132
    - stops, 444
    - store data locally, 262, 526
    - time, rounding, 265, 528
    - timeout, 39
    - without a database, 275
  - collection\_manager
    - ASCII file with, 58
    - description, 51
    - error messages, 49, 66
    - examples, 63
    - modes of operation, 57
    - options, 52
    - requirements, 51
    - syntax, 52
    - using, 62
  - collection\_name variable, 233
  - collection\_table variable, 233
-

Collection ID, 131, 261, 280, 524  
    pa\_collect, 315  
Collector ID, 268  
CollectorModule statement, 530  
column, generate in destination table, 464

commands

- builder, 45
- collection\_manager, 51
- datapipe\_manager, 73
- db\_delete\_data, 89
- deploytool, 97
- dip\_manager, 109
- formdeploytool, 145
- group\_manager, 179
- groupctl, 159
- groupimport, 171
- grouping related commands, 447
- indexmaint, 203
- install.pkg, 215
- log\_backup, 251
- mw\_collect, 255
- node\_manager, 283
- ovpi\_bulk\_copy, 299
- ovpi\_run\_sql, 307
- pa\_collect, 313
- pa\_discovery, 317
- piadmin, 323
- QGRconverter, 327
- QSSconverter, 329
- schedule, 331
- snmpv2dis, 347
- tpmaint, 351
- transform\_maint, 379
- trend\_discover, 387
- trend\_export, 409
- trend\_label, 425
- trend\_lock, 435
- trend\_proc, 447
- trend\_sum, 459
- trendcopy, 357
- trendexec, 405
- trendpm, 439
- trendtimer, 487
- TWQconverter, 495
- userctl, 497
- userimport, 511
- vantage\_collect, 519
- viewctl, 533
- viewer, 541
- comment character, install.pkg, 217
- community string
  - file, recommendation, 395
  - file containing, 390
  - multiple, 394
  - public, 395
  - RMON, 395
- compatibility mode, 83
- compatibility mode, setting, 76
- component type
  - list with file suffix, 240
  - OVPI SQL file, 243
  - SQL script, 240
  - TREND collector definition, 233
  - TREND database procedure, 220
  - TREND database view, 222
  - TRENDdiscover file, 240
  - TREND dll, 226
  - TREND documentation, 228
  - TREND documentation directory, 227
  - TREND form, 229
  - TREND form directory, 230
  - TREND library file, 231
  - TREND mibs, 232
  - TREND module, 219
  - TREND Other, 240
  - TRENDproc file, 240
  - TREND qss file, 240
  - TREND report link, 235
  - TREND software version, 241
  - TRENDstep file, 240
  - TRENDsum file, 240
  - TREND temporary file, 244
  - TRENDtimer definition, 245
  - TREND uninstall run command, 246
  - TREND uninstall run sql script, 247
- constraint, trend\_export
  - keywords, 409, 419

- Constraint tag, 177
  - convert legacy data definition file
    - qgr, 327
    - qss, 329
    - twq, 495
  - copy file to
    - \$DPIPE\_HOME/dll directory, 226
    - \$DPIPE\_HOME/docs directory, 228
    - \$DPIPE\_HOME/lib directory, 231
    - \$DPIPE\_HOME/mibs directory, 232
    - \$DPIPE\_HOME/scripts/db directory, 243
    - \$DPIPE\_HOME/scripts directory, 240
    - \$DPIPE\_HOME/tmp directory, 244
  - counter
    - 32-bit, 262, 525
      - spike threshold, 443
    - 64-bit, 262, 525
      - spike threshold, 443
  - counter data, suppressing, 441
  - create
    - datapipe, 82, 83
      - parameter, datapipe\_manager, 80
      - table, 364
  - csv report format, specifying, 334, 343
  - custom procedure, 445
- D**
- database
    - delete data from, 93
    - dictionary table, 374
    - engine, 77
    - objects, 81
    - size, 365
    - source, 81
    - statistics, 92
    - target, 82
    - type required by report pack, 223
  - database\_procedure directive, 220
  - database\_table directive, 221
  - database\_view directive, 222
  - database-full size, 132
  - database server
    - data database, 268
    - topology database, 268
  - Database Table Management
    - display, 364
  - database-used size, 132
  - data collection
    - See also* collection
    - granularity, 314
    - summarization level, 314
  - data database, defined, 268
  - datadb option, 181, 190
  - data definition file, converting, 495
  - datapipe
    - alter, 83
    - create, 83
  - datapipe\_manager, 73
    - error messages, 83
    - example, 83
    - option categories, 75
    - options, 76
    - syntax, 74
  - data processing stops, 470, 471
  - data storage, local, 275
  - data stored longer than retention period, 93
  - data table
    - associated with property table, 425
  - Date Range Error, 480
  - day range that wraps, 361, 369
  - days data retained in table, 91

- db\_delete\_data, 89
  - error messages, 94
  - examples, 93
  - options, 90
  - syntax, 90
- db\_requirement directive, 223
- dbstats tables, 132
- debug output, 38
- debug output level, 130
  - group\_manager, 182
  - transform\_maint, 381
- default
  - aging value, 91
  - data in column, 77
  - public, 394
- default parameter, 77
- delay processing, 468
- delete
  - data from database, 93
  - parameter, datapipe\_manager, 80
- delta time, 484
  - calculating, 266, 529
- Department tag, 515
- dependency directive, 224
  - legacy format, 225
  - version directive and, 248
- dependent procedure, 445
- deploytool, 97
  - deploying reports, 103
  - error messages, 104
  - options, 98
  - syntax, 98
  - undeploying reports, 104
- derived groups
  - defined, 189
  - removing with force option, 183, 198
- desc parameter, 77
- destination server
  - specifying, 364
- determine size of database, 365
- dictionary entries, 77
- dip\_manager, 109
  - ASCII file with, 116
    - syntax rules, 117
  - enumerated list groups, 114
  - error messages, 122
  - examples, 120
  - modes of operation, 114
  - options, 110
  - requirements, 109
  - syntax, 110
  - using, 118
- DIP groups
  - categories, 113, 114
  - enumerated list, 114
  - exporting, 111, 115, 119
    - examples, 121
  - group name, 113
  - importing, 112, 114, 118
    - example, 120
  - managing, 109
  - naming convention, 113
  - removing, 112, 115, 118, 119
    - examples, 122
  - replacing contents of, 112, 115, 118
    - example, 121
  - rule-based
    - converting to enumerated list, 114
  - viewing contents of, 114
- directed instance polling
  - See dip\_manager
  - See DIP groups



- directives
    - bin, 219
    - database\_procedure, 220
    - database\_table, 221
    - database\_view, 222
    - db\_requirement, 223
    - dependency, 224
    - dll, 226
    - docdir, 227
    - docs, 228
    - form, 229
    - formdir, 230
    - install.pkg, 217
    - lib, 231
    - mibs, 232
    - mw\_collection\_def, 233
    - report\_dir, 234
    - report\_pack, 236
    - reportlink, 235
    - reports, 237
    - run\_command, 238
    - run\_sql\_script, 239
    - scripts, 240
    - software\_version, 241
    - sql, 243
    - tmp, 244
    - trend\_timer\_def, 245
    - uninstall\_cmd, 246
    - uninstall\_sql, 247
    - version, 248
  - directory
    - \$DPIPE\_HOME/dll, 226
    - \$DPIPE\_HOME/docs, 227, 228
    - \$DPIPE\_HOME/lib, 136, 231
    - \$DPIPE\_HOME/mibs, 232
    - \$DPIPE\_HOME/reports, 234, 237
    - \$DPIPE\_HOME/scripts, 240, 247, 394, 399
    - \$DPIPE\_HOME/tmp, 244
    - create target for reports, 234, 237
  - discover
    - community strings
      - file, 395
      - for an SNMP GET request, 394
    - IP, 389
    - managed nodes, 317
    - OVP Agent or OVO Agent, 317
    - SNMP Type, 396
      - naming convention, 398
      - type definition files, 399
  - distributed polling, 131, 263, 277, 526
  - dl\_type table, 390, 398, 399
  - dll directive, 226
  - docdir directive, 227
  - docs directive, 228
  - double quotes, 442
  - DPIPE\_HOME
    - /dll directory, 226
    - /docs directory, 227, 228
    - /lib directory, 136, 231
    - /mibs directory, 232
    - /reports, 234, 237
    - /scripts directory, 240, 247
    - /tmp directory, 244
  - dpipe\_pa child collector, 315, 316, 320
  - dsi\_descr column, populating with trend\_label, 429
  - dsi\_nodes table, 390, 394, 398, 399
  - duplicate records, preventing, 355
- ## E
- ee\_collect
    - command line, 133
    - error messages, 136
    - how to use, 133
    - pa\_discovery and, 319
  - Email tag, 516

- empty block, 451
- end statement, 451
- enumerated list groups, 114
  - defined, 189
  - install.pkg, 233
- error messages
  - action, 42
  - by-variable, 375
  - collection\_manager, 49, 66
  - datapipe\_manager, 83
  - db\_delete\_data, 94
  - deploytool, 104
  - dip\_manager, 122
  - ee\_collect, 136
  - formdeploytool, 152
  - group\_manager, 199
  - groupctl, 169
  - node\_manager, 295
  - ovpi\_bulk\_copy, 305
  - ovpi\_run\_sql, 312
  - schedule, 344
  - transform\_maint, 385
  - trendcopy, 371
  - userctl, 509
  - viewctl, 540
- execution mode, 79
- exporting
  - DIP groups, 111, 115, 119
    - examples, 121
  - group definitions, 182, 190, 194, 195
    - examples, 198
  - nodes, 285, 288, 292
    - examples, 293
  - polling policies, 53, 63, 195, 196
    - examples, 65
  - polling policy definitions, 183
- Extensible Markup Language, 511
- extension .teel, 76

## F

- file
  - .dis, 398
  - converting legacy files, 327, 329
  - copy to \$DPIPE\_HOME/bin directory, 219
  - install.pkg, 215
  - log backup, naming conventions, 252
  - trendtimer.sched, 37, 40
  - type definition, 399
    - naming, 397
- file locks, 275
- filter, 368
  - by date, 361, 368
  - by day of week, 361
  - by hour of day, 362
  - defining, 177
  - minimum value, trendpm, 444
- FilterConstraints tag, 177
- force option, 183, 191
  - example, 198
- foreign\_key parameter, 77
- foreign key, 358
  - reference column, 376
- format
  - parameter file, 413
- formdeploytool, 145
  - error messages, 152
  - examples, 151
  - options, 146
  - syntax, 146
  - using, 148
- formdir directive, 230
- form directive, 229

forms  
   deploying, 145, 149  
   deployment examples, 151  
   undeploying  
     multiple, 150  
     single, 150  
   viewing, 148

formulas  
   computing statistics, 481

frequency  
   running ee\_collect, 131

frequency variable, 233

## G

generate  
   how to use, 157  
   options, 156  
   syntax, 155

GETBULK, turning on, 259, 523

GET message, 393

GETNEXT, 259, 263, 523, 526

group  
   *See also* DIP groups  
   backing up before removing, 181  
   category, 56, 57, 116, 187  
     defined, 189  
   defined, 188  
   definition (XML) file, 192  
   derived, 189  
     removing with force option, 183, 198  
   enumerated list, 114, 189  
     install.pkg, 233  
   exporting definitions, 182, 190, 194, 195  
     examples, 198  
   importing definitions, 184, 189, 194  
     example, 197  
   name, 516  
     conventions for, 56, 113, 187  
     specifying with snmpv2dis, 348, 349  
     XML tag, 175  
   remove definitions, 185, 191, 196  
     examples, 198  
   rule-based, 114, 189  
   specifying owner, 186  
   types, 189  
   user-access, defined, 159  
   Web Access Server, 171

group\_manager  
   description, 179  
   error messages, 199  
   examples, 196  
   forcing removal of dependent groups,  
     183, 191  
   how to use, 194  
   modes of operation, 189  
   options, 181  
   requirements, 179  
   syntax, 180

- groupctl, 159
  - error messages, 169
  - how to use, 164
  - modes of operation, 164
  - syntax, 160
- groupdb option, 184, 190
- groupimport, 171
  - example, 178
  - file format, 173
  - naming conventions, 173
  - options, 172
  - syntax, 172
- grouping by-variable, 463
- Groups tag, 175, 516
- Group tag, 516

## H

- help, 38
- help command
  - trend\_sum, 469
  - trendcopy, 364
- high water mark
  - database-used size, 444
  - log, trendpm, 444
  - setting
    - mw\_collect, 265
    - trend\_sum, 470, 471
    - trendpm, 444
    - vantage\_collect, 528
- holding file, 269
- host name, translated from IP address, 392
- hour range that wraps, 362
- html report format, specifying, 334
- hysteresis
  - beginning of time period range, 476
  - units to reprocess, 467

## I

- identity column, 358
- ID tag, 515
- ignore NULL values, 479
- ignore time-period range restrictions, 470
- importing
  - DIP groups, 112, 114, 118
    - example, 120
  - group definitions, 184, 189, 194
    - example, 197
  - nodes, 283, 286, 287, 291
    - examples, 292
  - polling policies, 54, 57, 62, 184, 189, 194
    - example, 63, 197
- index
  - maintaining, 203
  - statistics, 92
- indexmaint, 203
  - examples, 214
  - options, 204
  - Oracle, 210, 213
  - Sybase, 207, 213
  - syntax, 204
- indices on upload table, 262, 525
- infile option, 184
- install.pkg, 215
  - document conventions for directives, 217
  - format of directives, 217
  - processing of, 216
  - processing rules, 217
  - sample file layout, 249
  - syntax rules, 217
- installation
  - collection policy, 233
  - command to execute during, 238
  - SQL script to execute during, 239
- integrity checks, 367

- interval
  - ee\_collect executes by, 128
  - executes, 131
  - field, 131
  - list of instructions, 133
  - polling entries, 136
  - schedule file definition, 489
- interval polling, 277
- IP
  - address, translating to host name, 392
  - range, defining, 390
- isql command, 309, 310, 311
- K**
- key ID-based deletions, 91
- keyid mapping scheme, 367
- keymap, 363
  - integrity check, 367
- keyword, trend\_export
  - max, 409, 419
- L**
- lag time, 477
- last processed sample, 476
- legacy data definition file, converting, 327, 329, 495
- lib directive, 231
- list
  - trend\_sum options, 469
  - trendcopy options, 364
- local data storage, 275
- lock
  - preventing multiple command instances, 435
  - trend\_proc automatic locking check, 453
- log, 365
  - entries, ee\_collect, 133
  - information level, pa\_collect, 315
- log\_backup, 251
  - options, 252
  - output file naming conventions, 252
  - syntax, 251
  - trendtimer.sched file, 253
- log files
  - backing up, 267
- log information level, 264, 527
- M**
- macro, 449
- managed-object group name, 348, 349
- manual test, 40
- master trend\_proc, 453
- maximum
  - collection processes, 130
  - rows, 131, 365
- MaxRows statement, 131
- MeasureWare agents, 319

messages

- action, 42
- by-variable, 375
- collection\_manager, 49, 66
- datapipe\_manager, 83
- db\_delete\_data, 94
- deploytool, 104
- dip\_manager, 122
- ee\_collect, 136
- formdeploytool, 152
- GET, 393
- group\_manager, 199
- groupctl, 169
- node\_manager, 295
- ovpi\_bulk\_copy, 305
- ovpi\_run\_sql, 312
- schedule, 344
- transform\_maint, 385
- trendcopy, 371
- userctl, 509
- viewctl, 540

MIB-II tables, 395

MibIndexMap statement, 530

mibs directive, 232

MIB tables

- collecting values from a particular node, 278
- polling application for, 267
- specifying table to collect, 265

minimum filter value, 263, 526

minimum lag time, 468

mode

- as-is, 83
- compatibility, 76, 83
- execution, 79
- non-compatibility, 83

mw\_collect, 255

- configuration file, 269
  - parameters, 271
- directory structure, 279
- distributed polling, 277
- examples, 280
- file locks, 275
- interval polling, 277
- invoked by trendtimer, 277
- multiple pollers, 278
- polling instructions, 278

mw\_collection\_def directive, 233

**N**

name

- group, 516
- sub-group, 176

Name tag, 175

nesting trend\_proc files, 453

network subnet, 392

node\_manager, 283

- ASCII file with, 288
- error messages, 295
- examples, 292
- modes of operation, 287
- options, 284
- requirements, 283
- syntax, 284
- using, 291

- nodes
    - ASCII file list, 288
    - deleting, 285, 287, 292
      - example, 294
    - discovering, 317
    - exporting, 285, 288, 292
      - examples, 293
    - importing, 283, 286, 287, 291
      - examples, 292
    - locating, 317
    - managing, 283
    - removing from type and view lists, 286, 287, 292
      - examples, 294
    - SNMP
      - profile assigned to, 290
      - support of protocol, 289, 290
    - type list, removing from, 286, 287, 292
      - examples, 294
    - view list, removing from, 286, 287, 292
      - examples, 294
  - non-compatibility mode, 83
  - nowait block, 450
  - null
    - columns, 477
    - parameter, `datapipe_manager`, 77
  - NULL handling, 479
  - number of characters in substring, 431
- O**
- object by-variables, 117
  - Object Manager
    - deploying forms to be viewed, 145
    - form deploy example, 151
  - obsolete data, aging out of database, 89
  - OpenView Operations Agent, 317
  - OpenView Operations Agent, collecting data from, 313
  - OpenView Performance Agent, 317
  - OpenView Performance Agent, collecting data from, 313
  - option
    - mutually exclusive, 92
  - option categories, `trendcopy`, 360
  - Oracle
    - Analyze Table command, 210, 213
    - copying data across databases, 357
    - `db_requirement` option, 223
    - table indexes, 210
  - outfile option, 185
  - output file naming conventions, 252
  - override default, 480
  - override source statements, 131
  - `ovpi_bulk_copy`, 299
    - error messages, 305
    - examples, 305
    - options, 300
    - syntax, 300
    - using, 303
  - `ovpi_run_sql`, 307
    - error messages, 312
    - example, 311
    - options, 308
    - syntax, 308
    - using, 310
  - `ovpi_timer` UNIX process, 487, 492
  - OVPI database
    - dictionary entries, 77
  - OVPI SQL file, 243
  - OVPI Timer Windows service, 487, 493
  - OVPI version required for report pack, specifying, 241

## P

- pa\_collect, 313
  - dependence on trendtimer, 315
  - options, 314
  - syntax, 313
- pa\_discovery, 317
  - configuration file, 320
  - ee\_collect and, 319
  - options, 318
  - syntax, 318
- Package Manager
  - command to run when removing a report pack, 246
  - insert entry in trendtimer.sched file, 245
  - install.pkg file, 215
  - processing rules for install.pkg
    - directives, 217
  - removes entry from trendtimer.sched file, 245
  - running SNMP Type Discover, 398
  - script to run when removing a report pack, 247
- packets, ping, 390, 392
- parameter
  - e-mail, 513
  - max\_rows, 365
  - password, 513
  - telephone, 513
- parameterless command
  - ee\_collect, 128
  - transform\_maint, 380
- parent poller, 275
  - defined, 268
  - responsibilities, 268
- parser to validate the XML format, 175, 515
- password parameter, 513
- Password tag, 515
- pdf report format, specifying, 334
- pdu, 391, 397
- percentage level for valid data
  - mw\_collect, 260
  - trendpm, 445
  - vantage\_collect, 523
- performance penalties, 480
- performance problems
  - time-period tables, 354
- Phone tag, 515
- piadmin, 323
  - options, 324
  - syntax, 323
- ping packets
  - number of, 390
  - size, 392
- ping timeout, 391
- placeholders, required, 77
- poller
  - child, 268, 269
  - instance of, 268
  - parent, 268, 275
- poller, alternate name, 261, 524
- pollfrom computer, specifying, 55, 60, 185, 190
- polling
  - control table, 133
  - distributed, 131, 263, 277, 526
  - dynamic list of nodes, 267
  - entering policy information, 133
  - instructions, 131
    - mw\_collect, 278
  - interval, 131, 277
  - node, 135
  - requests, 131
  - station for a polling policy, 55
  - with multiple pollers, 278
- polling interval, 39



- polling policies
    - backing up before removing, 181, 196
    - definition (XML) file, 193
    - exporting, 53, 63, 195, 196
      - examples, 65
    - exporting definitions, 183
    - importing, 54, 57, 62, 184, 189, 194
      - example, 63, 197
    - install with Package Manager, 233
    - managing, 51
      - with group\_manager, 179
    - modifying, 54, 55, 57, 62
      - example, 64
    - removing, 55, 58, 63, 66, 186, 191, 196
      - examples, 65, 199
    - specifying owner, 186
  - polling policy
    - exporting definitions, 183
  - Polling Policy Manager
    - importing nodes, 283
  - populate property tables, 262, 525
  - port number, 39
  - procedures
    - application type, specifying, 442
    - application types, described, 446
    - class, specifying, 442
    - custom, 445
    - delete option, 440
    - dependent, 445
    - execution parameters, 441
    - managing, 439
    - registering, 220, 441
    - type, specifying, 442
    - types, list, 446
  - property table
    - associated with data table, 425
    - defined, 188
    - invalid name, 373
    - keyids mapped in, 367
    - populate, 262, 525
    - populating with data from data table, 425
    - views, 358
  - protocol data unit, 391, 397
- Q**
- QGRconverter, 327
    - syntax, 327
  - QSSconverter, 329
    - syntax, 329
  - quotation marks, 442
- R**
- r2d parameter usage, 83
  - raw-to-delta processing, 83
  - RealName tag, 515
  - rebuild index, 207
  - recognized view, 358
  - regenerate definition files, 258, 522
  - regenerate stored procedure, 471
  - registering
    - datapipe, 83
    - procedure, 220
    - table, 221
    - view, 222
  - rejecting samples, 262, 525

- remove
    - DIP groups, 112, 115, 118, 119
      - examples, 122
    - group definitions, 185, 191, 196
      - examples, 198
    - nodes, 286, 287, 292
      - examples, 294
    - parameter, `datapipe_manager`, 80
    - polling policies, 55, 58, 63, 186, 191, 196
      - examples, 65, 66, 199
  - rename index, 207
  - rep file, 495
  - replacing DIP groups, 112, 115, 118
    - example, 121
  - `report_dir` directive, 234
    - reports directive and, 237
  - `report_pack` directive, 236
    - dependency directive and, 224
    - version directive and, 248
  - report definition file, 495
  - report definition file, converting from legacy file, 327, 329
  - `reportlink` directive, 235
  - report pack
    - directory structure, 216
    - installing, 215
    - primary identification for, 236
    - specify dependent report pack, 224
    - specify name of, 236
    - specify version of, 248
  - reports
    - create target directory for, 234, 237
    - deploying directories of, 104
    - specifying desired format, 334
  - reports directive, 237
    - `report_dir` and, 234
  - retention period, 93
  - retries, number of, 264, 527
  - retry interval, 263, 526
  - RMON community string, 395
  - RMON-manageable device, 399
  - Role tag, 516
  - rolling baseline, 478
  - round collection time, 39
  - rule-based groups, 114
    - defined, 189
  - `run_command` directive, 220, 221, 222, 238
  - `run_sql_script` directive, 239
- ## S
- satellite server, 366
  - schedule, 331
    - error messages, 344
    - file, `trendtimer`, 489
      - example, 491
    - how to use, 340
    - modes of operation, 339
    - options, 333
    - OVPI processes, 487
    - syntax, 332
  - scheduling OVPI processes, 487
  - scripts directive, 240
  - server
    - archive, 366
    - central, 366
    - satellite, 366
    - source, 363
    - target, specifying, 364
  - services
    - starting, 492
    - stopping, 493
  - single quotes, 442

- size
    - database-full, 132
    - database-used, 132
  - size of batch to commit, 469
  - size parameter, 77
  - SNMP
    - See also* SNMP V2
    - collection cycles, 258, 522
    - GET, 392, 394, 397
    - GET message, 393
    - number of variables to include in
      - varbind list, 263, 526
    - polling application, 267
    - port, specifying, 263, 527
    - port number, defining, 391, 397
    - profile assigned to node, 290
    - protocol supported by node, 289, 290
    - Read Community string, 277
    - request retries, 264, 392, 397, 527
    - tests, 400
    - timeout, 263, 391, 397, 526
    - version, 257
    - version, specifying, 265, 528
  - SNMP V2
    - identifying devices that support protocol, 347
    - specifying version, 265, 528
  - snmpv2dis, 347
    - options, 348
    - specifying managed-object group name, 348, 349
    - syntax, 347
  - software\_version directive, 241
  - source
    - database, 81
    - data directory, 132
    - data file, single, 131
    - data table, 373
    - file disposition, 132
    - server, 363
    - table, 82
      - to copy, 364
  - SourceDirectory, 131
  - SourceDisposition, 132
  - SourceFile, 131
  - source statements, overriding, 131
  - spike, 262, 525
    - threshold, 443
  - SQL
    - generating procedure code, 440
    - Name column, 364
    - Table Manager, 92
  - sql directive, 243
  - sqlldr command, 302, 304
  - sqlname parameter, 77
  - sqlplus command, 309, 310, 311
  - SQL script
    - command that runs scripts on OVPI, 307
    - component type, 240
    - execute during installation, 239
    - report pack removal, 247
  - srep report format, specifying, 334, 344
  - start\_date format, 353
  - starting character position of substring, 431
-

- statement
  - begin, 451
  - end, 451
  - MaxRows, 131
  - SourceDirectory, 131
  - SourceDisposition, 132
  - SourceFile, 131
- statistics
  - update, 92, 93
- store data locally, 262, 526
- subnet mask, 392
- substring, number of characters in, 431
- summarization level, 314
- summary definition, defined, 473
- suppressing counter data, 441
- Sybase
  - copying data across databases, 357
  - db\_requirement option, 223
  - table indexes, 207
  - update statistics command, 207, 213
- synchronous execution (trendpm), 440
- syntax
  - check TEEL file statements, 81
  - ee\_collect command, 128
- sysobjects, 374

## T

- ta\_period, 265, 528

- table
  - element, 475
  - indexes
    - Oracle, 210
    - Sybase, 207
  - index maintenance, 203
  - registering, 221
  - retention period guideline, 354
  - source, 82, 364
  - target, 82
  - time-period, 351
  - upload, 442
- table\_category variable, 233
- table\_key, 358
- tag definitions, 175
- tag set parameter formats, 173
- target
  - database, 82
  - row in table, locating, 429
  - server, specifying, 364
  - table, 82
  - table name, 440
- target\_name, 358
- task
  - list of, trendcopy, 363
  - timings, 365
- TEEL
  - file
    - name, 129
  - TEEL file name
    - ee\_collect execution, 129
    - specifying, 76
- template for table creation, 82
- terminate associated stored procedures, 474
- test manually, 40
- ThreadCount parameter, 320
- ThreadTimeout parameter, 320, 321

- time control options, 245
  - timeout, ping, 391
  - time period, 475
    - tables, populating, 351
  - tmp directive, 244
  - topology database, defined, 268
  - tpmaint, 351
    - examples, 355
    - invoked by trendtimer, 354
    - options, 352
    - performance impact, 354
    - syntax, 352
    - trend.log message, 354
  - trace level, setting, 319
  - trace log file, 264, 316, 527
  - trace parameters, setting, 440
  - transcribe keymap for property table, 363
  - transform\_maint, 379
    - error messages, 385
    - how to use, 382
    - syntax, 380
  - transformation, defined, 473
  - trend.log file
    - indexmaint, 207
    - tpmaint, 354
    - trend\_lock, 436
      - message format, 437
  - trend\_discover, 387
    - syntax, 389
  - trend\_export, 409
    - options, 410
  - trend\_exportc
    - syntax, 410
  - trend\_label, 425
    - options, 427
    - property table, 425
    - syntax, 426
  - trend\_lock, 435
    - locking check for trend\_proc, 453
    - message format in trend.log, 437
    - syntax, 435
  - trend\_proc, 447
    - block, 449
      - definition, 450
      - format, 451
    - examples, 455
    - file
      - characteristics, 451
      - creating and applying, 455
      - description, 450
      - nesting limit, 453
      - processing, 452
      - scheduling, 455
      - syntax, 455
    - macro, 449
    - options, 448
    - processing multiple trend\_proc files, 453
    - scheduling, 455
    - syntax, 448
    - trend\_lock locking check, 453
    - trendtimer.sched file, 449
  - trend\_sum, 459
    - destination table
      - optional suffix name, 465
    - input file description, 475
    - naming conventions, 471
    - period-end threshold, 477
    - requirements, 459, 474
    - trendexec and, 405
    - trendlabel and, 425
    - trendpm and, 440
  - trend\_timer\_def directive, 245
  - trendadm, 392, 397
-

- trendadm user account, 501
  - TREND collector definition, 233
  - trendcopy, 357
    - error messages, 371
    - options, 360
    - syntax, 359
    - verify keymap table, 365
  - TREND database procedure, 220
  - TREND database table, 221
  - TREND database view, 222
  - TRENDdiscover file, 240
  - TREND dll, 226
  - TREND documentation, 228
  - TREND documentation directory, 227
  - trendexec, 405
    - example, 407
    - options, 406
    - syntax, 406
  - TREND form, 229
  - TREND form directory, 230
  - trendit
    - indexmaint and, 208, 211
  - TREND library file, 231
  - TREND mibs, 232
  - TREND module, 219
  - TREND Other, 240
  - trendpm, 439
    - options, 440
    - procedure, 269
    - syntax, 439
  - TRENDproc file, 240
  - TREND qss file, 240
  - TREND report link, 235
  - TREND software version, 241
  - TRENDstep file, 240
  - TRENDsum file, 240
  - TREND temporary file, 244
  - trendtimer, 37, 487
    - configuration, 131
    - mw\_collect and, 277
    - options, 488
    - sample command line, 494
    - schedule file, 136, 489
    - starting
      - at system startup, 492
      - manually
        - on UNIX, 492
        - on Windows, 493
    - stopping
      - on UNIX, 493
      - on Windows, 494
    - syntax, 488
    - tpmaint invocation, 354
    - trendexec and, 405
  - trendtimer.sched
    - db\_delete\_data execution, 93
    - description, 489
    - indexmaint execution, 213
    - insert entry in file, 245
    - log\_backup execution, 253
    - log file backup, 267
    - override, UNIX only, 489
    - remove entry from, 245
    - trend\_label execution, 425
    - trend\_proc and, 449, 453, 455
  - trendtimer.sched file, 40
  - TRENDtimer definition, 245
  - TREND uninstall run command, 246
  - TREND uninstall run sql script, 247
  - TRENDweb Builder, 496
  - TRENDweb Query file, 495, 496
-

TWQconverter, 495  
 options, 496  
 syntax, 495

twq file, 495

type  
 definition files, 399  
 naming, 397  
 parameter, 77  
 validation, 398

type\_list\_name variable, 233

## U

uninstall  
 command to execute during, 246  
 SQL script to execute during, 247

uninstall\_cmd directive, 246

uninstall\_sql directive, 247

unique key, 274

## UNIX

starting services, 492  
 stopping services, 493

unix 0 time, 490

update  
 keymap for property table, 362  
 statistics, 92, 93  
 time-period table, 475

update statistics command, 207, 213

upload table  
 use existing indices, 442

user  
 defining as administrator, 516  
 group\_manager option, 186

user-access group, defined, 159

user accounts  
 maintaining, 497  
 trendadm, 501

userctl, 497  
 error messages, 509  
 examples, 506  
 how to use, 502  
 modes of operation, 502  
 options, 499  
 syntax, 498

userimport, 511  
 example, 516  
 naming conventions, 513  
 options, 512  
 syntax, 512

users  
 add, modify, or delete, 511

Users tag, 176, 515

User tag, 176, 515

using input file and command line option,  
 475

## V

vantage\_collect, 519  
 example, 531  
 how to use, 530  
 options, 521  
 syntax, 520

verifyparms  
 parameter, datapipe\_manager, 81

version  
 minimum OVPI version required, 241  
 report pack string, 248  
 stamp, 39

version directive, 248  
 report\_pack directive and, 236

view  
 recognized, 358  
 registering, 222

- viewctl, 533
  - add mode, 538
  - delete mode, 539
  - error messages, 540
  - examples, 539
  - how to use, 537
  - modes of operation, 537
  - modify mode, 538
  - options, 534
  - required options, 537
  - syntax, 534
- viewer, 541
  - examples, 545
  - options, 542
  - syntax, 542

## W

- wait block, 450
- Web Access Server
  - deploy file to, 229
  - deploy forms to, 230
  - deploy reports to multiple systems, 102
  - form undeploy example, 151
  - groups, 171
  - maintaining user accounts, 497

## X

- XML
  - parser validates format, 175
  - required for imported files, 171, 511
  - tag definitions, 175
  - tag sets
    - groupimport, 173
    - userimport, 514
  - used in group definition files, 192
  - used in polling policy definition files, 193

## Z

- zero denominator, 480