HP Business Service Management

for the Windows and Linux operating systems

Software Version: 9.10

Modeling

Document Release Date: August 2011 Software Release Date: August 2011



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notices

© Copyright 2005 - 2011 Hewlett-Packard Development Company, L.P

Trademark Notices

Adobe® and Acrobat® are trademarks of Adobe Systems Incorporated.

AMD and the AMD Arrow symbol are trademarks of Advanced Micro Devices, Inc.

Google[™] and Google Maps[™] are trademarks of Google Inc.

Intel®, Itanium®, Pentium®, and Intel® Xeon® are trademarks of Intel Corporation in the U.S. and other countries.

iPod is a trademark of Apple Computer, Inc.

Java is a registered trademark of Oracle and/or its affiliates.

Microsoft®, Windows®, Windows NT®, Windows® XP, and Windows Vista® are U.S. registered trademarks of Microsoft Corporation.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

Acknowledgements

- This product includes software developed by Apache Software Foundation (http://www.apache.org/licenses).
- This product includes OpenLDAP code from OpenLDAP Foundation (http://www.openldap.org/foundation/).
- This product includes GNU code from Free Software Foundation, Inc. (http://www.fsf.org/).
- This product includes JiBX code from Dennis M. Sosnoski.
- This product includes the XPP3 XMLPull parser included in the distribution and used throughout JiBX, from Extreme! Lab, Indiana University.
- This product includes the Office Look and Feels License from Robert Futrell (http:// sourceforge.net/projects/officeInfs).
- This product includes JEP Java Expression Parser code from Netaphor Software, Inc. (http://www.netaphor.com/home.asp).

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates, or to verify that you are using the most recent edition of a document, go to:

http://h20230.www2.hp.com/selfsolve/manuals

This site requires that you register for an HP Passport and sign-in. To register for an HP Passport ID, go to:

http://h20229.www2.hp.com/passport-registration.html

Or click the New users - please register link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

Visit the HP Software Support web site at:

http://www.hp.com/go/hpsoftwaresupport

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

http://h20229.www2.hp.com/passport-registration.html

To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

Table of Contents

Welcome to This Guide	13
How This Guide Is Organized	13
Who Should Read This Guide	14
How Do I Find the Information That I Need?	14
Additional Online Resources	17
Documentation Updates	18

PART I: INTRODUCTION TO RTSM

Chapter 1: Topology Query Language	21
Topology Query Language (TQL) Overview	22
Creating TQL Queries in the RTSM Managers	23
Viewing TQL Query Results	24
Compound Relationship	
Join Relationship	26
Subgraph Definition	
The ALLOW_VOLATILITY Qualifier	
Define a TQL Query	
Add Query Nodes and Relationships to a TQL Query	32
Define a Compound Relationship – Scenario	33
Define a Join Relationship – Scenario	36
Create a Subgraph Definition – Scenario	
Shortcut Menu Options	40
Attribute Operator Definitions	45
TQL Logs	
Topology Query Language User Interface	
Troubleshooting and Limitations	

Chapter 2: Impact Modeling	109
Impact Modeling Overview	
Impact Layer	111
Impact Rules	
Propagation Reversal	113
Calculated Relationship Types	
Creating Views Based on the Impact Model	115
Chapter 3: Create a URL for a Direct Link	117
Generate a Direct Link – Overview	118
Generate a Direct Link – Scenario	120
Create a Direct Link to a Template with Parameter Values	120
Encrypt the Password of a Direct Link Using the JMX	
Console	
Generate a Direct Link User Interface	123
Chapter 4: Embedding RTSM Applets Using Direct Links	143
Using the Direct Link Functionality to Embed RTSM Applets	
RTSM Applet Tag – Overview	
Direct Link Operation Flow	
Chapter 5: Working with the CI Selector	155
CI Selector Overview	156
Display a View in Browse Mode	
Search for CIs in Search Mode	
Modify CI Selector Display Options	
CI Selector User Interface	
Troubleshooting and Limitations	174
Chapter 6: Working with Topology Map	175
Topology Map Overview	
Handling Large Views	177
Topology Map User Interface	178

PART II: MODELING

Chapter 7: Best Practices for Modeling	215
Using Modeling Studio	216
Models and Perspectives	216
Building Models	217
Model Dependencies on Other CIs in the RTSM	222
Modeling an Application with Running Software	223
Creating Views Using the Modeling Studio	

Chapter 8: IT Universe Manager	227
IT Universe Manager Overview	228
Working with Views in IT Universe Manager	
View Tree Structure	
Working with CIs	
Working with Relationships	
Create CIs and Relationships in the RTSM	
View Related CIs	
Check Status of Application Discovery (Rediscover a View)	
Retrieve Impact Analysis Results – Scenario	
Take a Snapshot of a View	257
Print and Save a Topology Map to File	258
IT Universe Manager User Interface	259
Chapter 9: Reports	303
Topology Reports Overview	304
Compare CIs	
Compare Snapshots	
Cron Expressions	
Reports User Interface	
L	
Chapter 10: Modeling Studio	335
Modeling Studio Overview	
View Formats	
Building a Business View	
Templates and Perspectives	
Predefined Folders and Views	
Creating Template Based Views	
Business CI Models	
Building a Perspective Based View Revealed CIs and Watchpoints	
Create a Pattern View	
Create a Template	
Create a Perspective	
Create a Template Based View	
Create Multiple Template Based Views	
Define Report Settings	
Build an Instance-based Model	
Build a Pattern-based Model	
Build a Perspective-based View Based on a Model	
Build a Perspective-based View Based on a Collection of CIs	
Build a Business CI Model – Scenario	
Modeling Studio User Interface	
modeling studio osci internece	

Chapter 11: Impact Analysis Manager	
Impact Analysis Manager Overview	
Define an Impact Rule – Workflow	
Impact Analysis Manager User Interface	
Chapter 12: CI Type Manager	475
CI Types Overview	
CI Type Attributes	
CI Type Relationships	
Deprecated CI Types	
System Type Manager	
Create a CI Type	
Create a Relationship Type	
Create a Calculated Relationship Type	
Create List and Enumeration Definitions	
Create an Enumeration Definition – Workflow	
View Descriptions for CI Types and Relationships	
CI Type Manager User Interface	
Chapter 13: Enrichment Manager	519
Enrichment Manager – Overview	
Define an Enrichment Rule – Scenario	
Add Enrichment Query Nodes and Relationships to an	
Enrichment TQL Query	
Enrichment Manager User Interface	

PART III: RTSM DATA MODEL

Chapter 14: RTSM Data Model Introduction	551
BTO Data Model (BDM) Overview	552
Data Model Documents	553
Upgrade Documents	554
Chapter 15: Exporting the RTSM Data Model to a UML Tool	557
Export to UML Tool – Overview	558
Export the Class Model	559
Convert XML of Selected Part of Class Model	560
Export Class Model to UML Wizard	562
Tool Plug-in Input	565

PART IV: REFERENCE INFORMATION

Chapter 16: Working with Tables	569
Columns User Interface	570

Chapter 17: Regular Expression Examples	575
Examples of Regular Expressions	576
Index	577

Table of Contents

Welcome to This Guide

This guide explains how to configure and work with an IT model that enables you to build a topology of your system. You populate the model with configuration items and their relationships, and then use the model to measure and manage critical business processes.

This chapter includes:

- ► How This Guide Is Organized on page 13
- ► Who Should Read This Guide on page 14
- ► How Do I Find the Information That I Need? on page 14
- ► Additional Online Resources on page 17
- ► Documentation Updates on page 18

How This Guide Is Organized

The guide contains the following chapters:

Part I Introduction to RTSM

Introduces the RTSM and provides general information about Topology Query Lanaguage, the CI Selector, and Topology Map.

Part II Modeling

Describes how to model your business environment by defining views and by building TQL queries that retrieve the required information from the RTSM; describes how to view and modify the definitions of configuration item types (CITs) defined in the RTSM and the relationships that define the connections between them.

Part III RTSM Data Model

Includes documents that explain and quantify the BTO Data Model (BDM) version 1.1.1 and the CMS data model.

Part IV Reference Information

Contains general reference information.

Who Should Read This Guide

This guide is intended for the following users:

- ► Business Service Management administrators
- ➤ Business Service Management platform administrators
- ► Business Service Management application administrators
- ► Business Service Management data collector administrators

Readers of this guide should be knowledgeable about enterprise system administration, have familiarity with ITIL concepts, and be knowledgeable about Business Service Management in general and the Operational Database technology specifically.

How Do I Find the Information That I Need?

This guide is part of the HP Business Service Management Documentation Library. This Documentation Library provides a single-point of access for all Business Service Management documentation.

You can access the Documentation Library by doing the following:

- ► In Business Service Management, select Help > Documentation Library.
- From a Business Service Management Gateway Server machine, select
 Start > Programs > HP Business Service Management > Documentation.

Topic Types

Within this guide, each subject area is organized into topics. A topic contains a distinct module of information for a subject. The topics are generally classified according to the type of information they contain.

This structure is designed to create easier access to specific information by dividing the documentation into the different types of information you may need at different times.

Three main topic types are in use: **Concepts**, **Tasks**, and **Reference**. The topic types are differentiated visually using icons.

Торіс Туре	Description	Usage
Concepts	Background, descriptive, or conceptual information.	Learn general information about what a feature does.

Торіс Туре	Description	Usage
Tasks	 Instructional Tasks. Step-by-step guidance to help you work with the application and accomplish your goals. Some task steps include examples, using sample data. Task steps can be with or without numbering: Numbered steps. Tasks that are performed by following each step in consecutive order. Non-numbered steps. A list of self-contained operations that you can perform in any order. 	 Learn about the overall workflow of a task. Follow the steps listed in a numbered task to complete a task. Perform independent operations by completing steps in a non-numbered task.
	Use-case Scenario Tasks. Examples of how to perform a task for a specific situation.	Learn how a task could be performed in a realistic scenario.

Торіс Туре	Description	Usage
Reference १	General Reference . Detailed lists and explanations of reference-oriented material.	Look up a specific piece of reference information relevant to a particular context.
	User Interface Reference. Specialized reference topics that describe a particular user interface in detail. Selecting Help on this page from the Help menu in the product generally open the user interface topics.	Look up specific information about what to enter or how to use one or more specific user interface elements, such as a window, dialog box, or wizard.
Troubleshooting and Limitations	Troubleshooting and Limitations. Specialized reference topics that describe commonly encountered problems and their solutions, and list limitations of a feature or product area.	Increase your awareness of important issues before working with a feature, or if you encounter usability problems in the software.

Additional Online Resources

Troubleshooting & Knowledge Base accesses the Troubleshooting page on the HP Software Support Web site where you can search the Self-solve knowledge base. Choose **Help** > **Troubleshooting & Knowledge Base**. The URL for this Web site is <u>http://h20230.www2.hp.com/troubleshooting.jsp.</u>

HP Software Support accesses the HP Software Support Web site. This site enables you to browse the Self-solve knowledge base. You can also post to and search user discussion forums, submit support requests, download patches and updated documentation, and more. Choose **Help** > **HP Software Support**. The URL for this Web site is <u>www.hp.com/go/hpsoftwaresupport</u>.

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

To register for an HP Passport user ID, go to:

http://h20229.www2.hp.com/passport-registration.html

HP Software Web site accesses the HP Software Web site. This site provides you with the most up-to-date information on HP Software products. This includes new software releases, seminars and trade shows, customer support, and more. Choose **Help** > **HP Software Web site**. The URL for this Web site is <u>www.hp.com/go/software</u>.

Documentation Updates

HP Software is continually updating its product documentation with new information.

To check for recent updates, or to verify that you are using the most recent edition of a document, go to the HP Software Product Manuals Web site (<u>http://h20230.www2.hp.com/selfsolve/manuals</u>).

Part I

Introduction to RTSM

1

Topology Query Language

This chapter includes:

Concepts

- ➤ Topology Query Language (TQL) Overview on page 22
- ➤ Creating TQL Queries in the RTSM Managers on page 23
- ➤ Viewing TQL Query Results on page 24
- ► Compound Relationship on page 26
- ► Join Relationship on page 26
- ► Subgraph Definition on page 28
- ➤ The ALLOW_VOLATILITY Qualifier on page 28

Tasks

- ► Define a TQL Query on page 30
- ► Add Query Nodes and Relationships to a TQL Query on page 32
- > Define a Compound Relationship Scenario on page 33
- > Define a Join Relationship Scenario on page 36
- ► Create a Subgraph Definition Scenario on page 38

Reference

- ► Shortcut Menu Options on page 40
- ► Attribute Operator Definitions on page 45
- ► TQL Logs on page 47
- ➤ Topology Query Language User Interface on page 53

Troubleshooting and Limitations on page 103

Concepts

🚴 Topology Query Language (TQL) Overview

Topology Query Language (TQL) is a language and tool for discovering, organizing, and managing IT infrastructure data. It enables you to create TQL queries that retrieve business service data from the RTSM. TQL queries also help you display the data in a visual representation that facilitates data monitoring and managing.

This section includes the following topics:

- ► "Topology Query Language" on page 22
- ► "The Roles of TQL" on page 23

Topology Query Language

TQL extends the standard SQL language by adding two important capabilities:

- ➤ TQL enables you to draw conceptual relationships between configuration items (CIs), which represent their actual interdependencies. Using predefined operators, the different types of interconnections (relationships) that exist between CIs can be established, and consequently the infrastructure design and performance are more accurately represented. This representation serves as a basis and a model for the discovery, arrangement, query, and management of complex infrastructures.
- TQL includes a graphical aspect, consisting of visual symbols and syntax, that represents the resources and their interconnections. This visualization of an IT infrastructure simplifies the understanding, monitoring, and managing of the IT business operations.

The Roles of TQL

TQL plays several roles:

- Builds a business service model that defines and delineates the interconnection between IT assets that function together as business services. The business service model guides the discovery and identification of these business services, from the ever-increasing number and complexity of infrastructure resources. After the resources that comprise the business services are discovered, the business service model structures the way they are organized and managed in the RTSM.
- Constantly searches the RTSM for changes that occur in the state of managed resources. When such changes are detected, the relevant subsystems are informed and updated.
- Creates queries that retrieve business service data from the RTSM, and displays the data in a visual representation that facilitates data monitoring and managing.

👶 Creating TQL Queries in the RTSM Managers

The following managers enable you to create TQL queries that retrieve specific data from the RTSM and to display that data:

- ➤ Impact Analysis Manager. An Impact rule simulates how infrastructure changes can impact your system and enables you to determine the true origin of a problem and its business impact. During rule creation, you define the base TQL query type, which can be a new query or an existing query. For details, see "Impact Analysis Manager" on page 449.
- Enrichment Manager. An Enrichment rule enables enlarging the RTSM, deleting CI instances from the RTSM, or updating the attributes of a CI that already exists in the RTSM. During rule creation, you define the base TQL query type, which can be a new query or an existing query. For details, see "Enrichment Manager" on page 519.

➤ Modeling Studio. You can build a new TQL query using the TQL Query Editor or you can build a new query while defining a new view, template, or perspective using the Pattern View Editor. You can also define the topology report settings for any view in the Pattern View Editor. For details, see "Modeling Studio" on page 335.

🚴 Viewing TQL Query Results

You view the resulting data in a visual representation in IT Universe Manager. The queries define the structure of the resulting topology map. The view displays only those CIs and relationships that meet the query definition. You can also view the results of a query by clicking the **Preview** button in the toolbar to open a preview display identical to IT Universe Manager. For more details about IT Universe Manager, see "IT Universe Manager" on page 227.

TQL Query Types and Priorities

When you define a TQL query, you define the type of the TQL query in the Type field of the Query Definition Properties dialog box. The following query types are available:

- ► View. TQL queries used as the basis for pattern views.
- ► Integration. TQL queries used for integrations.
- ► **Discovery.** TQL queries used as the basis for DFM patterns.
- **Template.** TQL queries used as the basis for templates.
- ► **Perspective.** TQL queries used as the basis for perspectives.
- Impact Analysis. TQL queries used as the basis for Impact rules. This is the default type for queries created in Impact Analysis Manager.
- ➤ Enrichment. TQL queries used as the basis for Enrichment rules. This is the default type for queries created in Enrichment Manager.

You cannot change the type of an existing TQL query if it has dependencies (such as views, templates, and so on).

Q

If a query imported though an integration is not assigned a type, it is considered a hidden query and does not appear in the query list in the Modeling Studio. To display hidden queries in the query list, change the setting for hidden queries under General in the User Preferences dialog box. For details, see "User Preferences Dialog Box" on page 102.

You can also set the priority level of a TQL query, which determines how often the query is rerun automatically to include updated information. The following priorities are available:

- ► Low. The TQL query is refreshed every 2 minutes.
- ► Medium. The TQL query is refreshed every 30 seconds.
- ► High. The TQL query is refreshed every 10 seconds.
- **Express.** The TQL query is refreshed continuously.
- ► Not Active. The TQL query is inactive.

Note: The above refresh times are average values.

If you set the priority of a TQL query to **Not Active**, the query becomes inactive and is not run automatically, however it can be used for manually building a view.

Base Queries

You can select a base query for a TQL query in the Query Definition Properties dialog box. In this case, the base query is first applied to the entire IT Universe, generating results. The new query is then applied to that subset of the universe, further refining the results. Selecting a base query enables you to filter the query results more finely and generate results more quickly in certain cases.

The base query you select must be both active and persistent for your new query to be active. If the base query is not active and persistent, the new query is automatically assigned a priority of **Not Active**.

\lambda Compound Relationship

A compound relationship represents a path in the topological graph. You use a compound relationship to define the allowed steps in the path between the source and the target CIs.

Each row represents one of the allowed steps in the path leading from the source CI to the target CI in the topology map.

Source	Relationship	Target
🖳 lpSubnet	Membership	Node
Node Node	Containment	IpAddress

For an example of a compound definition, see "Define a Compound Relationship – Scenario" on page 33. For details on defining compound relationships, see "Add/Edit Compound Relationship Dialog Box" on page 56.

👶 Join Relationship

A join relationship is a logical connection that represents the relationship between two CIs (and which appears only in the topology map containing the TQL query results). It does not exist in the RTSM. A join relationship is created by defining an attribute for each query node, whose values are used for comparison.

The TQL results retrieve all CIs whose attribute values meet the conditions defined in the join definition.

For example, you can create a join definition that links all **node** CIs connected to **IP Address** CIs whose **Created By** attribute values are equal (see the example below).

Node	Operator	lpAddress
Created By	Equal	Created By

Each join definition represents one condition defined for the join relationship.

Note: You can define multiple conditions.

For an example of a join definition, see "Define a Join Relationship – Scenario" on page 36. For details on defining join relationships, see "Add/Edit Join Relationship Dialog Box" on page 60.

🚴 Subgraph Definition

A subgraph definition enables you to create a graph that represents additional TQL query data related to a specific CI. The DFM job searches for the results from both the TQL query and the subgraph definitions. The query recursively retrieves all related CIs for a defined depth matching the definition of the subgraph. For details on defining subgraph definitions, see "Subgraph Definition Dialog Box" on page 100.

In the graph, you can define the relationship that is connected to a specific query node. For example, if one of the query nodes is of type node, you can specify different relationships for Windows, router, and IP Address. You can also define attribute conditions for query nodes. For details, see "Subgraph Condition Definition Dialog Box" on page 98.

DFM jobs retrieve data that meets the criteria defined in the subgraph.

For an example of a subgraph definition, see "Create a Subgraph Definition – Scenario" on page 38.

A The ALLOW_VOLATILITY Qualifier

This qualifier is used to mark attributes that enable minor deviations to their value. For example, there is probably no need to report a small disk size change (from 8.00008 to 8.00009 GB).

When updating an attribute that is marked with this qualifier, HP Business Service Management checks the new value against the old value. This check is performed on the server as part of the record update. If the difference between the two values is lower that the allowed deviation, an update is not performed (the action is considered a false update). This qualifier must contain one of the following data items that hold the allowed deviation:

- ALLOWED_DEVIATION_FIX. The type of deviation is the same as the attribute type for numeric attributes, and the integer type for date attributes. Deviation is measured by a fixed value, of the same unit as the attribute value. (For date attributes, the deviation is measured in seconds.)
- ➤ ALLOWED_DEVIATION_PERCENT. Deviation is measured by percentage. For date values, the percentage is checked against the millisecond date representation. This data item type is always integer, and the value range is 0 to 100.

To deactivate the qualifier:

Access the Infrastructure Settings Manager (Admin > Platform > Setup and Maintenance > Infrastructure Settings). Locate the Allow Volatility option. Change the value to False.

Tasks

P Define a TQL Query

This task describes how to create a TQL query in the Modeling Studio.

Note: You can also create a TQL query during the procedure for creating Impact rules, Enrichment rules, Views, Templates, and Perspectives.

This task includes the following steps:

- ► "Create a TQL Query" on page 30
- ► "Add Query Nodes and Relationships to the Query" on page 30
- ► "Set the Query Properties" on page 31

1 Create a TQL Query

In the Modeling Studio, select **New > Query** to open the TQL Query Editor. For details, see "TQL Query Editor" on page 440.

2 Add Query Nodes and Relationships to the Query

Add the TQL query nodes and relationships that define the query. The TQL query nodes represent the CITs, as defined in the CI Type Manager, and the relationships represent the connections between them. Relationships are defined one at a time for each pair of TQL query nodes in the query. For details, see "Add Query Nodes and Relationships to a TQL Query" on page 32.


Note: You can also define a self-relationship from a query node to itself.

3 Set the Query Properties

Click the **Query Definition Properties** button to open the Query Definition Properties dialog box. Set the query type, scope, priority, and other properties. For details, see "Query/View Definition Properties Dialog Box" on page 426.

Example of a TQL Query Definition:

The direction of the relationship indicates which query node is dependent on the other. The following example displays two nodes, an IP Service Endpoint, and a Client Port, which are linked to one another via a client/server connection. The TQL query results must comply with the direction of the arrows.



Note: A TQL query is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103.

P

膧 Add Query Nodes and Relationships to a TQL Query

This section explains how to add query nodes and relationships to a TQL query. It is relevant for Impact Analysis Manager, Enrichment Manager, and the Modeling Studio.

Note: For TQL queries to be valid, they must comply with certain restrictions. For details, see "Troubleshooting and Limitations" on page 103.

To add query nodes and relationships to a TQL query:

1 In Impact Analysis Manager or Enrichment manager, select the required query from the tree in the left pane or click the **New** button to create one.

In the Modeling Studio, select the Resources tab in the left pane, select Queries as the Resource type, and select the required query from the tree or click **New** > **Query** to create a new one.

- 2 In Impact Analysis Manager or Enrichment manager, click and drag one or more required TQL query nodes from the tree displayed in the CI Type Selector, onto the editing pane. In the Modeling Studio, select the CI Types tab in the left pane and drag the required TQL query nodes from the tree onto the editing pane. These are the TQL query nodes that are included in the query.
- **3** To add a relationship between two query nodes:
 - Select the required TQL query nodes by holding down CTRL and clicking the TQL query nodes, right-click and select Add Relationship. The Add Relationship dialog box opens. Select the required relationship. For details, see "Add/Edit Relationship Dialog Box" on page 63.

or

 Click the Create Relationship icon and draw a line between the required query nodes. The Select Relationship Type dialog box opens. Select the required relationship type. For details, see "Select Relationship Type Dialog Box" on page 97.

*

Î.

4 Click **OK**. The selected query nodes are linked by the relationship you have selected.

膧 Define a Compound Relationship – Scenario

This section describes how to define the allowed steps that form a compound relationship between a **IP Subnet** CI and an **IP Address** CI.

Note: To reach the required result, you must implement each one of the following steps.

To define a compound relationship between a IP Subnet CI and an IP Address CI:

- 1 Create a TQL query of type view and drag the following query nodes onto the editing pane:
 - ► IP Subnet
 - ► IP Address
- 2 Right-click the IP Subnet and IP Address query nodes and select Add Compound Relationship to open the Add Compound Relationship dialog box.
- ÷
- Click the Add button. In Enrichment Manager and Impact Analysis Manager, the Add Triplet dialog box opens. In the Modeling Studio, a row is added to the table. Make the following selections:
 - ► From the **Source** list, select **IP Subnet**.
 - ► From the **Target** list, select **Node**.
 - ► From the **Relationship** list, select **Membership**.
 - ► Select the required **Relationship** direction.

In Enrichment Manager and Impact Analysis Manager, click **OK** to save your changes.

Chapter 1 • Topology Query Language

+

- **4** Click the **Add** button again and make the following selections:
 - ► From the **Source** list, select **Node**.
 - ► From the Target list, select IP Address.
 - ► From the **Relationship** list, select **Containment**.
 - ► Select the required **Relationship** direction.


In Enrichment Manager and Impact Analysis Manager, click **OK** to save your changes.

The following shows an example of compound definitions following the changes:

Source	Relationship	Target
🖳 lpSubnet	Membership	Node 📄
Node Node	Containment	IpAddress


5 Click **OK** to save your changes.

The TQL query in the editing pane now looks like this:




6 Create a view based on your TQL query and save it.

7 Go to the required view in IT Universe Manager to view the results. If you did not select the Show full path between source and target CIs option, then the results display the names of the relationships that link the CIs as Virtual-Compound rather than the actual names of the relationships. See the illustration below:




You can double-click the **Virtual - Compound** relationship in IT Universe Manager to open the Link Map, which displays the CIs and relationships that comprise the allowed steps used to link the **IP Subnet** and **IP Address** CIs.



In the example above, the **192.168.168.0** (IP Subnet) CI is linked to the **192.168.0.1** (IP Address) CI through the **labm1ccm15** (Node) CI.

If you selected the **Show full path between source and target CIs** option, then the results in IT Universe Manager display the actual names of the relationships that link the CIs and the full path between the source and target CIs. See the illustration below:



膧 Define a Join Relationship – Scenario

This section explains how to define a join relationship that links **Node** CIs to **IP Address** CIs whose **Created by** attribute values are equal.

Note: To reach the required result, you must implement each one of the following steps.

To define a join relationship that links all IP Address and Node CIs whose Created by attribute values are equal:

- **1** Create a TQL query and drag the following query nodes from the CI Type Selector onto the editing pane:
 - ► Node
 - ► IP Address
- **2** Select the **Node** and **IP Address** query nodes and right-click to open the Add Join Relationship dialog box.
- **3** Click the **Add** button to add a row to the table and do the following:
 - ► In the Node Attribute box, select Created by.
 - ► In the **Operator** box, select **Equal**.
 - ► In the IP Address Attribute box, select Created by.


In Enrichment Manager and Impact Analysis Manager, you make these selections in the Join Relationship Condition dialog box.

The Join Definition area now looks like this.

Node	Operator	lpAddress
Created By	Equal	Created By

4 Click **OK** to save your changes.

The TQL query in the editing pane now looks like this:



膧 Create a Subgraph Definition – Scenario

This section describes how to create a subgraph definition. In this example, the TQL query results retrieve all CIs that are connected to a Business Service CI by a **Containment** relationship up to a depth of 3.

Note: To reach the required result, you must implement each one of the following steps.

To create this sample subgraph definition:

- **1** Create a TQL query and drag a query node of type **Business Service** onto the editing pane.
- **2** Right-click the Business Service query node and select **Subgraph Definition** to open the Subgraph Definition dialog box.

3 Click the **Add** button. In Enrichment Manager and Impact Analysis Manager, the Add Triplet dialog box opens. In the Modeling Studio, a row is added to the table. Make the following selections:

- ► From the **Source** drop-down list, select **Managed Object**.
- ► From the Target drop-down list, select Managed Object.
- ► From the **Relationship** drop-down list, select **Containment**.
- ► Set the direction of the relationship as left to right.

In Enrichment Manager and Impact Analysis Manager, click **OK** to save your changes.


The Subgraph Definition dialog box now looks like this.

Source	Relationship	Target	Relationship Direction
Managed Object	Containment	Managed Object	→

- **4** Set the **Depth** setting to **3**.
- **5** Click **OK** in the Subgraph Definition dialog box.

+

Go to the required view in IT Universe Manager to view the results.



The results show the Business Service CI **aaa** and all of the CIs linked to it in succession by Containment relationships down to three levels.

Reference

💐 Shortcut Menu Options

This section includes a list of TQL query shortcut menu options (listed alphabetically):

UI Element (A-Z)	Description
Add Calculated Relationship	 Enables you to create a calculated relationship. For details on how to create a calculated relationship, see "Triplets Page" on page 503. For details about Impact Modeling, see "Impact Modeling" on page 109.
Add Compound Relationship	Enables you to define the connection between two query nodes using a compound relationship. For details, see "Add/Edit Compound Relationship Dialog Box" on page 56.
Add Join Relationship	Enables you to define join relationships. You create them by defining an attribute for each query node. These query node values are used for comparison during federation. For details, see "Add/Edit Join Relationship Dialog Box" on page 60.
Add Related Query Node Wizard	Displays the Add Related Query Node Wizard which enables you to build a TQL query. For details, see "Add Related Query Node Wizard" on page 65.

UI Element (A-Z)	Description
Add Relationship	Enables you to create a relationship for your query nodes by selecting it from a predefined list. Displays the Add Relationship dialog box.
	For details, see "Add/Edit Relationship Dialog Box" on page 63.
	Note: In Enrichment Manager, this option adds an Enrichment relationship to the rule when working in Enrichment mode. Applicable for regular and Enrichment query nodes. For details, see "Enrichment Manager" on page 519. Added relationships are denoted by an added indicator.
Add to Hierarchy	Adds the selected query node to the hierarchy as a separate query node.
	Note: Only relevant for the Modeling Studio.
Add to Model Output	Designates the selected query node as output for the pattern-based model.
	Note: Only relevant for pattern-based models in the Modeling Studio.
Change Query Node/Relationship Type	Displays the Change Query Node Type dialog box. Enables you to change the CI type of the query node after you have created it. For details, see "Change Query Node/Relationship Type Dialog Box" on page 381.
	Note: Only relevant for the Modeling Studio.
Clear	Available by right-clicking a query node or relationship when working in Enrichment mode in the Enrichment Manager. Clears the query node/relationship's Enrichment rule definition. For details, see "Enrichment Manager" on page 519.
	Appears only if you have updated or deleted a query node/relationship using an Enrichment rule.
	Note: Only relevant for Enrichment Manager.

UI Element (A-Z)	Description
Copy/Paste	Copy/paste an existing TQL query node/relationship in the same query or into another TQL query.
	The copied TQL query node/relationship includes all TQL definitions.
	You can copy and paste relationships provided that the TQL query nodes to which the relationships are connected are also selected. A relationship on its own cannot be copied without its connecting TQL query nodes.
	You can select multiple TQL query nodes/relationships as well.
	Note: The Copy and Paste options are only available in the Modeling Studio. The Paste option is available only after using the Copy option to copy an existing TQL query node/relationship.
Define Impacted	Define which query node in the TQL query is the trigger Impact Analysis query node and which query nodes are impacted by the changes that occur in the system. For details, see "Impacted Query Nodes Dialog Box" on page 466.
	Note: Only relevant for Impact Analysis Manager.
Delete	Deletes the selected query node/relationship/CI.
	Note: This option is not available for calculated relationships.
Delete Relationship/Query	Available by right-clicking a query node or relationship when working in Enrichment mode.
Node	Creates a specific Enrichment rule that is designed to delete CIs/relationships from the RTSM. Applicable to regular query nodes and relationships only. You can use this option, for example, for removing unnecessary data from the RTSM. For details, see "Enrichment Manager" on page 519.
	Deleted query nodes and relationships are denoted by a removed - indicator.
	Note: Only relevant for Enrichment Manager.

UI Element (A-Z)	Description
Edit Relationship	Displays the Refine Relationship Type dialog box. For details, see "Refine Query Node Type Dialog Box" on page 96.
	Note: Not relevant in the Modeling Studio.
	Note: This option appears only when the selected relationship has descendants.
Query Node/Relationship Properties	Displays the Query Node/Relationship Properties dialog box, enabling you to define the attribute conditions for the selected TQL query node/relationship. For details, see "Query Node/Relationship Properties Dialog Box" on page 85.
	Note: This option is not available for calculated relationships.
Refine Query Node Type	Displays the Refine Query Node Type dialog box. Enables you to change the CI type of the query node after you have created it. For details, see "Refine Query Node Type Dialog Box" on page 96.
	Note : This option only appears if a child of the CI type exists. Only relevant for Impact Analysis Manager and Enrichment Manager.
Remove Subgraph	Only appears if you have defined a subgraph definition. For details, see "Subgraph Definition Dialog Box" on page 100.
Reset Impacted	Removes the Define Impacted definition applied to that query node. For details on the Define Impacted definition, see "Impacted Query Nodes Dialog Box" on page 466. Note: Only relevant for Impact Analysis Manager.
Reset Inner	Redraws a self-referential relationship in the Topology
Relationship	map as a square for ease of viewing.
	Note: Only relevant for self-referential relationships that are not square.

UI Element (A-Z)	Description
Set As Contact Query Node	Designates the selected query node as a contact query node for the perspective.
	Note: Only relevant for perspectives in the Modeling Studio.
Set Data Sources	Opens the Set Data Sources dialog box which enables you to select the required data sources for a TQL query node.
	Note: Only relevant for the Modeling Studio.
Set Element Invisible	When this option is selected, an invisible indicator papears to the right of the selected TQL query node in the editing pane.
	Any query results pertaining to that TQL query node are not displayed in the topology map. This can be useful when certain relationships or TQL query nodes are required to build the query but are not needed in the results. At least one query node must be visible for the view to be valid.
	Note: Only relevant for the Modeling Studio.
Set Element Visible	When this option is selected, the results pertaining to the TQL query node are displayed in the topology map.
	Note: Only relevant for the Modeling Studio.
Show Element instances	Displays the Element Instances dialog box which displays all the instances found for each query node in a table. For details, see "Element Instances Dialog Box" on page 77.
Show Node Parameters	Opens the Template Parameter Values dialog box, which enables you to set the values of the query node's parameters.
	Note: Only relevant for template-based views in the Modeling Studio.
Subgraph Definition	Displays the Subgraph Definition dialog box, where you can create a graph that represents additional TQL query data related to a specific query node. For details, see "Subgraph Definition Dialog Box" on page 100.

UI Element (A-Z)	Description
Update Relationship/Query Node	Use an Enrichment rule to update the value of CI attributes in the RTSM, or to add data to attributes that currently do not have values. Opens the Query Node Definition - Attributes dialog box. For details, see "Query Node/Relationship Definition Dialog Box" on page 544. This is applicable for both regular and Enrichment query nodes. Updated query nodes are denoted by an updated indicator. Note: Only relevant for Enrichment Manager.

💐 Attribute Operator Definitions

This section contains a list of operators used to define attribute conditions in various dialog boxes, such as the Subgraph Condition dialog box, Impact Rules Definition dialog box, or the Query Node/Relationship Properties dialog box.

Operator	Description
Changed during	(Displayed only when you select an attribute of type Date.) Displays only the instances that changed during the period specified in the Value box.
Equal	Checks whether the attribute value is equal to the value specified in the Value box.
Equal ignore case	Checks whether the attribute value is equal to the value specified in the Value box regardless of the case.
Greater	Checks whether the attribute value is greater than the value specified in the Value box.
Greater than or equal	Checks whether the attribute value is greater than or equal to the value specified in the Value box.

Operator	Description
In	Displays only the instances where this attribute value equals one of the selected values. For example, for CIs that have a Change state that equals Plan and New, select the operator In from the Operator list and select both Plan and New from the Value box.
Is null	Checks whether the attribute value is null.
Less	Checks whether the attribute value is less than the value specified in the Value box.
Less than or equal	Checks whether the attribute value is less than or equal to the value specified in the Value box.
Like	Uses a wildcard (%). Use Like when you are not sure of the complete name for which you are searching.
Like ignore case	Uses a wildcard (%). Use Like ignore case when you are not sure of the complete name for which you are searching. The case of the string is ignored.
Not equal	Checks whether the attribute value is not equal to the value specified in the Value box.
Unchanged during	(Displayed when you select a date type attribute.) Displays only the instances that did not change during the period specified in the Value box.

Note:

- For the Not equal operator, query results do not include data from the CI instances that are not assigned a value. For example, a system contains three nodes: Node1 is assigned the value A, Node2 is assigned the value B, and Node3 is not assigned a value. If you create a query to retrieve all nodes that are Not equal to A, the results of your query include Node2 only, because Node3 is not assigned a value.
- ➤ HP Business Service Management supports both Microsoft SQL Server and Oracle Server databases. Microsoft SQL Server is not case sensitive by default (unlike Oracle database which is case sensitive). Consequently, if you are using Microsoft SQL Server, the Equal operator retrieves the same query results as the Equal ignore case operator. For example, if you select the attribute City, the operator Equal, and type NEW YORK in the Value comparison box, case differences are ignored and query results include NEW YORK, New York and new york.

💐 TQL Logs

This section contains definitions for TQL parameter log files.

This section includes the following topics:

- ➤ "Pattern Log" on page 48
- ► "Pattern Statistics Log" on page 50
- ➤ "Audit Short/Detailed Log (TQL Perspective)" on page 50
- "Incremental Statistics Log" on page 51
- ► "Incremental Splitter Log" on page 52
- ► "Incremental Detailed Log" on page 53

Pattern Log

The log name is **cmdb.pattern.log**.

Log File	Description
Purpose	Information about the lifecycle of a TQL query that is handled and calculated in the RTSM.
	Only TQL queries stored in the RTSM are included. Information about ad hoc TQL queries is not included.
Information Level	Not available.
Error Level	Not available.
Debug Level	Possible actions performed on each TQL query include:
	 Status changes. Each TQL query has an internal state during its lifecycle. For example, all inactive queries are always in the INACTIVE state. Active queries begin in the NEW state. When they are first calculated, they move to the IN_CALC state. When a query is removed, it moves to the WAIT_FOR_DELETE state until it is removed completely. Model changes. Whenever a change occurs in the CMDB model, the TQL determines if it is relevant to its results. If so, it calculates the required change in the query results. The log displays the number of changes processed by this TQL. Query changes. When the TQL is modified, the log indicates that the query was modified and displayes its new priority.
Basic	Check if a TQL query has the same status for a long time:
Troubleshooting	► new – the query is in lazy loading
	► inactive
	 calculation – the calculation may have failed but the scheduler was not informed
	You can also view the number of notifications that a TQL query received.

Examples of typical log entries:

The TQL query named TQL1 is added and is in NEW state:

2011-01-25 07:44:48,763 DEBUG - TQL1 [NEW] State change NEW --> NEW

TQL1 is asked to be calculated and is moved to IN CALCULATION state:

2011-01-25 07:44:48,763 DEBUG - TQL1 [NEW] State change NEW --> IN_CALC

The calculation finishes and moves to IDLE state (waits for changes):

2011-01-25 07:44:48,778 DEBUG - TQL1 [IN_CALC] State change IN_CALC --> IDLE

Changes took place in the model (total of 5 changes):

2011-01-25 07:44:49,544 DEBUG - TQL1 [IDLE] Model Change Recieved 5 model changes.

Moving to a state that checks whether these change are relevant for this TQL query:

```
2011-01-25 07:44:49,544 DEBUG - TQL1 [IDLE] State change IDLE --> IN_IMMEDIATE_1
```

The pattern is changed. The new priority is medium:

2011-01-25 07:45:39,647 DEBUG - TQL1 [IDLE] Pattern change New priority MED_PRIORITY

Pattern Statistics Log

The log name is **cmdb.pattern.statistics.log**.

Log File	Description
Purpose	General calculation data for each TQL query, updated at predefined intervals.
Information Level	 The following information is given for each TQL query: name average, minimum, and maximum calculation times number of calculations last calculation time result size
Error Level	Not available.
Debug Level	Not available.
Basic Troubleshooting	 Verify that a specific TQL query was updated. Evaluate a TQL query's calculation time. Evaluate a TQL query's result size.

Audit Short/Detailed Log (TQL Perspective)

The log name is **cmdb.audit.short.log**.

Log File	Description
Purpose	RTSM state changes, CI Type changes, and TQL query results. You can use this log to follow the results of TQL queries.
Information Level	Not available.
Error Level	Not available.

Log File	Description
Debug Level	► Final calculation for TQL queries is logged.
	 If the final TQL query calculation is unchanged from the previous calculation, this is noted.
	➤ If the final TQL query calculation is changed from the previous calculation, results of the CIs and relationships are recorded in the detailed log. The number of CIs and relationships are recorded in the short log.
Basic Troubleshooting	 Use this log to verify which notifications are published by the TQL query subsystem.
	 Check the section at the end of each result. This section includes added, removed, and updated CIs and relationships.
	 Track the CIT changes and see if the query results also change. You can thus correlate the CIT changes to the results of the query calculations.

Incremental Statistics Log

The log name is **cmdb.incremental.statistics.log**.

Log File	Description
Purpose	Traces the calculation procedure, full or incremental, of every query.
Information Level	Not available.
Error Level	Not available.

Log File	Description
Debug Level	 Gives the date, time, query name, and whether an incremental statistic calculation was performed (yes/no). If an incremental statistic calculation was not performed, states the reason, the number of subcalculations (relevant for incremental calculations only), and the complete calculation time.
Basic Troubleshooting	 Monitors the calculation process. If a specific query calculation takes a long time, check if it is a full or incremental calculation: If full, check whether a full calculation is necessary.
	 If incremental, check how many subcalculations have been performed.

Incremental Splitter Log

The log name is **cmdb.incremental.splitter.log**.

Log File	Description
Purpose	Monitors the incremental splitter result made during an incremental calculation.
Information Level	Not available.
Error Level	Not available.
Debug Level	Gives the set of query node numbers of each query graph created by the incremental splitter.
Basic Troubleshooting	If the TQL result calculated by the incremental calculator is wrong, verify that the splitter result is correct.

Incremental Detailed Log

The log name is **cmdb.incremental.detailed.log**.

Log File	Description
Purpose	Monitors the incremental calculation process.
Information Level	Not available.
Error Level	Not available.
Debug Level	 Each incremental subcalculation entry includes the following: the trigger query node the number of elements classified to the trigger query node whether the subcalculation step is driven by new elements added to the model or by existing elements the calculated query graph
Basic Troubleshooting	Follows the basic steps of an incremental calculation.

💐 Topology Query Language User Interface

This section includes (in alphabetical order):

- ► Add/Edit Calculated Relationship Dialog Box on page 54
- ► Add/Edit Compound Relationship Dialog Box on page 56
- ► Add/Edit Join Relationship Dialog Box on page 60
- ► Add/Edit Relationship Dialog Box on page 63
- ► Add Related Query Node Wizard on page 65
- ► Add Triplet Dialog Box on page 73
- ► Element Instances Dialog Box on page 77
- ► Filter CI Instances Dialog Box on page 80
- ► Join Relationship Condition Dialog Box on page 82

- ► Layout Settings Dialog Box on page 84
- ► Query Node/Relationship Properties Dialog Box on page 85
- ► Refine Query Node Type Dialog Box on page 96
- ► Select Relationship Type Dialog Box on page 97
- ► Subgraph Condition Definition Dialog Box on page 98
- ► Subgraph Definition Dialog Box on page 100
- ► User Preferences Dialog Box on page 102

💐 Add/Edit Calculated Relationship Dialog Box

This dialog box enables you to define the connection between two query nodes using a calculated relationship from the CI Type model.

To access	To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio: Right-click the required query node in the editing pane in Enrichment Manager, Impact Analysis Manager, or the Modeling Studio and select Add Calculated Relationship.
	Note: If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Add Calculated Relationship option.
	 To access in Adapter Management in Data Flow Management (DFM): Select an adapter in the Resources pane.
	 In the Adapter Definition tab, click the Edit Input Query 2 button to the right of the Input Query box to open the Input Query Editor.
	3 Right-click the required query node and select Add Calculated Relationship .

Relevant tasks	➤ "Define an Impact Rule – Workflow" on page 452
	 "Define an Enrichment Rule – Scenario" on page 523
	➤ "Define a TQL Query" on page 30
	 "Implement a Discovery Adapter" in the RTSM Developer Reference Guide
	➤ "Create a Pattern View" on page 359
	➤ "Create a Template" on page 360
	 "Create a Perspective" on page 362
See also	 "Impact Modeling" on page 109 "CI Type Relationships" on page 478

UI Element (A-Z)	Description
1	Click Expand All to expand all the folders in the tree.
16	Click Collapse All to collapse all the folders in the tree.
Tree View	Click Tree View to select the display format of the calculated relationship tree. The following options are available:
	► Display label
	► Class name
	► Legacy class name
<calculated relationship tree></calculated 	Select the calculated relationship that defines the connection between two query nodes.
Relationship Direction	The direction of the relationship that indicates which query node is dependent on the other.
Relationship Name	The name of the calculated relationship.

UI Element (A-Z)	Description
Relationship Restrictions	Select an option to define how to handle relationships between identical query nodes or self relationships in the query results. A self relationship is a relationship that leads from a query node to itself.
	Note: This list appears only when you select one query node or two identical query nodes.
	➤ Allow All Relationships. All relationships appear in the query results.
	 Allow Self Relationships Only. Only self-relationships (a relationship that leads to itself) appear in the query results.
	 Allow Non Self Relationships Only. Self-relationships do not appear in the query results.

💐 Add/Edit Compound Relationship Dialog Box

This dialog box enables you to define the connection between two query nodes using a compound relationship.

To access	To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio:
	Right-click the required query nodes in the editing pane in Enrichment Manager, Impact Analysis Manager, or the Modeling Studio and select Add Compound Relationship .
	Note: If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Add Compound Relationship option.
	To access in Adapter Management in DFM:Select an adapter in the Resources pane.
	2 In the Adapter Definition tab, click the Edit Input Query 2 button to the right of the Input Query box to open the Input Query Editor.
	3 Right-click the required query node and select Add Compound Relationship .

Important information	You can create as many compound definitions as necessary.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362
See also	 "Compound Relationship" on page 26 "Define a Compound Relationship – Scenario" on page 33

User interface elements are described below:

UI Element (A-Z)	Description
*	Add a compound definition. In Impact Analysis Manager and Enrichment Manager, it opens the Add Triplet dialog box. In the Modeling Studio, it enters a default compound definition in the table. Click the Edit buttons to edit the definition components.
×	Delete the selected compound definition.
0	Edit the selected compound definition. In Impact Analysis Manager and Enrichment Manager, it opens the Add Triplet dialog box. In the Modeling Studio, it opens the Compound Relationship Condition Definition dialog box.
Max steps	The longest path allowed between the two CIs in the RTSM to be included in the discovery process. Default is: 5
Min steps	The shortest path allowed between the two CIs in the RTSM to be included in the discovery process. Default is: 1

UI Element (A-Z)	Description
Relationship	The relationship connecting the two query nodes.
Relationship Direction	The direction of the relationship that indicates which query node is dependent on the other.
Relationship Name	The name of the compound relationship.
Relationship Restrictions	Select an option to define how to handle relationships between identical query nodes or self relationships in the query results. A self relationship is a relationship that leads from a query node to itself.
	Note: This list appears only when you select one query node or two identical query nodes.
	➤ Allow All Relationships. All relationships appear in the query results.
	 Allow Self Relationships only. Only self-relationships (a relationship that leads to itself) appear in the query results.
	 Allow Non Self Relationships only. Self-relationships do not appear in the query results.
Show full path between source and target CIs	If you select this option, then the query results display the actual names of the relationships that link the CIs and the full path between the source and target CIs.
Source	The required source query node.

UI Element (A-Z)	Description
Stop at first compound level	Select this option if you want the system to stop looking for TQL query results once it reaches the first target in the path. In the following sample compound link definition, Depth is defined as 10 and Stop at first compound level is selected.
	Source Target 1 Target 4 Target 2 Target 3
	The TQL query results include the Target 1 , Target 3 , and Target 4 because they are all at level 1 (the first CI found in the path). Target 2 is not included in the TQL results because it is at level 2 (the second CI found in the path).
Target	The required target query node.
Visible	Select Visible to include query results relating to a join or compound relationship. By default, Visible is selected. When Visible is cleared, a box p appears to the left of the relationship's name in the editing pane, denoting that any query results pertaining to the relationship are not displayed in the topology map.

💐 Add/Edit Join Relationship Dialog Box

This dialog box enables you to define join relationships.

To access	To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio:
	Right-click the required query nodes in the editing pane in Enrichment Manager, Impact Analysis Manager, or the Modeling Studio and select Add Join Relationship .
	Note: If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Add Join Relationship option.
	To access in Adapter Management in DFM:1 Select an adapter in the Resources pane.
	 2 In the Adapter Definition tab, click the Edit Input Query 2 button to the right of the Input Query box to open the Input Query Editor. 3 Right-click the required query node and select Add Join Relationship.
Important information	When you access the dialog box from the Modeling Studio, you select the attributes and operator within the dialog box itself. When you access the dialog box from Impact Analysis Manager or Enrichment Manager, you select the attributes and operator from the Join Relationship Condition dialog box.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362
See also	 "Join Relationship" on page 26 "Define a Join Relationship – Scenario" on page 36

UI Element (A-Z)	Description
+	Define a join definition. In Impact Analysis Manager and Enrichment Manager, it opens the Join Relationship Condition dialog box. In the Modeling Studio, it adds the selected attributes and operator to the list.
×	Delete the selected join definition.
Ø	Edit the join definition. Opens the Join Relationship Condition dialog box.
	Note: This option is not relevant in the Modeling Studio.
<query node1<="" th=""><th>Select an attribute for the <end_1> query node.</end_1></th></query>	Select an attribute for the <end_1> query node.</end_1>
Attribute> box	Note: This option is only available in the Modeling Studio.
<query node2<="" th=""><th>Select an attribute for the <end_2> query node.</end_2></th></query>	Select an attribute for the <end_2> query node.</end_2>
Attribute> box	Note: This option is only available in the Modeling Studio.
<selected query<br="">node1> column</selected>	A selected query node. The first attribute applies to <end_1>.</end_1>
<selected query<br="">node2> column</selected>	A selected query node. The second attribute applies to <end_2>.</end_2>
And	All join definitions are linked by the And operator.
	Note: This is not relevant in the Modeling Studio.
Operator box	Select an operator. For details on the available operators, see "Join Relationship Condition Dialog Box" on page 82.
	Note: This option is only available in the Modeling Studio.
Operator column	The operator selected in the Join Relationship Condition dialog box. For details about operator definitions, see "Attribute Operator Definitions" on page 45.
Relationship Direction	The direction of the relationship that indicates which query node is dependent on the other.

UI Element (A-Z)	Description
Relationship Name	The name of the join relationship.
Relationship Restrictions	Select an option to define how to handle relationships between identical query nodes or self relationships in the query results. A self relationship is a relationship that leads from a query node to itself.
	Note: This list appears only when you select one query node or two identical query nodes.
	► Allow All Relationships. All relationships appear in the query results.
	 Allow Self Relationships only. Only self-relationships (a relationship that leads to itself) appear in the query results.
	 Allow Non Self Relationships only. Self-relationships do not appear in the query results.
Visible	Select Visible to include query results relating to a join or compound relationship. By default, Visible is selected. When Visible is cleared, an invisible box 🗊 appears to the left of the of the relationship's name in the editing pane. Any query results pertaining to the relationship are not displayed in the topology map.
	Virtual - Join

💐 Add/Edit Relationship Dialog Box

This dialog box enables you to define the connection between two query nodes in a TQL query.

To access	 To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio: ➤ Right-click the required query node in the editing pane in Enrichment Manager, Impact Analysis Manager, or the Modeling Studio and select Add Relationship. or ➤ Click the Create Relationship icon and draw a line between the required query nodes. The Select Relationship Type dialog box opens. Select Regular Relationship.
	Note : If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Add Relationship option.
	 To access in Adapter Management in DFM: 1 Select an adapter in the Resources pane. 2 In the Adapter Definition tab, click the Edit Input Query 2 button to the right of the Input Query box to
	open the Input Query Editor.3 Right-click the required query node and select Add Relationship.
Important information	This option does not appear when two selected query nodes (or a single selected query node) do not have a valid relationship between them.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Element (A-Z)	Description
階	Click Expand All to expand all the folders in the relationship tree.
B	Click Collapse All to collapse all the folders in the relationship tree.
Tree View	 Click Tree View to select the display format of the relationship tree. The following options are available: Display label Class name Legacy class name
<relationship tree=""></relationship>	Select the relationship that defines the connection between two query nodes.
Relationship Direction	The direction of the relationship that indicates which query node is dependent on the other.
Relationship Name	The name of the relationship.
Relationship Restrictions	Select an option to define how to handle relationships between identical query nodes or self relationships in the query results. A self relationship is a relationship that leads from a query node to itself.
	Note: This list appears only when you select one query node or two identical query nodes.
	➤ Allow All Relationships. All relationships appear in the query results.
	 Allow Self Relationships only. Only self-relationships (a relationship that leads to itself) appear in the query results.
	➤ Allow Non Self Relationships only. Self-relationships do not appear in the query results.

Add Related Query Node Wizard

This wizard enables you to build a TQL query.

To access	To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio: In the editing pane, right-click the required query node and select Add Related Query Node.
	Note : If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Add Related Query Node option.
	To access in Discovery Control Panel in DFM:1 Select a job in the Discovery Modules pane.
	2 Select a Trigger Query in the Properties tab. Click the Open the Query Editor <i>b</i> button to open the Trigger Query Editor.
	3 Right-click the required query node and select Add Related Query Node Wizard .
	To access in Adapter Management in DFM:1 Select an adapter in the Resources pane.
	2 In the Adapter Definition tab, click the Edit Input Query 2 button to the right of the Input Query box to open the Input Query Editor.
	Right-click the required query node and select Add Related Query Node Wizard.
Important information	If the TQL query is empty, drag the required TQL query nodes on to the editing pane from the tree displayed in the CI Type Selector or the CI Types tab of the left pane.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> Developer Reference Guide
	 "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

Wizard map	The Add Related Query Node Wizard contains:
	Related Query Node Type Page > Relationship Type Page > Related Query Node Properties Page > Related Query Node Instances Page
See also	"Topology Query Language (TQL) Overview" on page 22

🂐 Related Query Node Type Page

This wizard page enables you to add a query node to the TQL query.

Important information	If the TQL query is empty, drag the required TQL query node on to the editing pane from the tree displayed in the Configuration Item Types pane. For general information on the Add Related Query Node Wizard, see "Add Related Query Node Wizard" on page 65.
Wizard map	The Add Related Query Node Wizard contains: Related Query Node Type Page > Relationship Type Page > Related Query Node Properties Page > Related Query Node Instances Page

UI Element (A-Z)	Description
1	Click Expand All to expand all the folders in the tree.
16	Click Collapse All to collapse all the folders in the tree.
Tree View	Click Tree View to select the display format of the CI type tree. The following options are available:
	► Display label
	► Class name
	► Legacy class name
	Note: This feature is only available in the Modeling Studio.

UI Element (A-Z)	Description
<query node=""> is required</query>	Define the relationship cardinality. For details, see "Cardinality Tab" on page 89.
	 Select the <query node=""> is required check box for each query node to include a minimum of one instance of the query node at the other end of the relationship in the query results. Selecting the check box gives the relationship a cardinality value of 1*.</query> Clear the <query node=""> is required check box to give the relationship a cardinality value of 0*.</query>
<tql node<br="" query="">hierarchy tree></tql>	Select the required query node. The query node you select appears in the Element name box.
	This list only includes the query nodes of the CI type that have valid relationships to the selected (source) query node.
	To the right of each query node, the number of CI instances that exist in the RTSM for that CI type is displayed. The number of instances is only updated after you close the Add Related Query Node Wizard and open it again.
	Note : The first query node in the hierarchy tree is selected by default.
Element name	(Optional) Contains the name of the selected query node. By default, the CI type is assigned as the element's name.
	You can rename a TQL query node in the Element name box giving it a unique label. This can be helpful when there is more than one query node of the same CI type in the TQL query.
Show only CITs with instances	Select this check box to display only the CITs of which there are instances in the RTSM. If this box is not selected, the tree includes all CITs with a valid link to the source query node.
	Note : The Show only CITs with instances check box is selected by default.

💐 Relationship Type Page

This wizard page enables you to add a relationship to a TQL query.

Wizard map	The Add Related Query Node Wizard contains:
	Related Query Node Type Page > Relationship Type Page > Related Query Node Properties Page > Related Query Node Instances Page

Click Tree View to select the display format of the
 Relationship tree. The following options are available: Display label Class name Legacy class name Note: This feature is only available in the Modeling Studio.
Select the required relationship.
Select the required relationship direction. The direction indicates which query node is dependent on the other.
The name of the relationship. Note: This feature is only available in the Modeling Studio.
Select an option to define how to handle relationships between identical query nodes or self relationships in the query results. A self relationship is a relationship that leads from a query node to itself. Note: This feature is only available in the Modeling Studio.

UI Element (A-Z)	Description
Relationship Type	A valid relationship that defines the connection between the selected query nodes. The box displays the relationship you selected in the relationship hierarchy tree. Note: This feature is only available in Enrichment Manager and Impact Analysis Manager.
Show only relationships with instances	Display only the relationships of which there are instances in the RTSM. If this box is not selected, the tree includes all valid relationships between the selected query nodes.

💐 Related Query Node Properties Page

This wizard page enables you to create an expression that restricts the number of query nodes that appear in the query by adding an attribute condition to a query node or relationship.

Important information	When you access the wizard from the Modeling Studio, this wizard page has two tabs: Attribute and Qualifier . The Attribute tab includes the elements described below. For details on the Qualifier tab, see "Qualifier Tab" on page 92.
Wizard map	The Add Related Query Node Wizard contains: Related Query Node Type Page > Relationship Type Page > Related Query Node Properties Page > Related Query Node Instances Page

User interface elements are described below:

UI Element (A-Z)	Description
÷	Add an attribute condition.
×	Delete an attribute condition.
^	Move a selected row up.

UI Element (A-Z)	Description
U.	Move a selected row down.
Q	View the condition definition.
Advanced layout settings	Opens the Layout Settings dialog box which enables you to determine which attributes are used in the calculation of the TQL query when querying the RTSM using third- party or custom tools.
	Note: This option is only relevant when accessing the wizard from the Modeling Studio.
And/Or	Click inside the And/Or field and select either And or Or to link multiple conditions.
Attribute name	Choose an attribute from the list.
() Brackets	Click inside the Brackets box to display a list of brackets you can use to build more complex, logical statements.
Criteria	Contains the attribute condition definition as defined in the Element Instances Dialog Box.
Include subtypes	Display both the selected CI and its children in the topology map.
NOT	Select NOT if you want the condition statement to do the opposite of what is defined.
	Note : If you select NOT , query results do not include data from the CI instances that were not assigned a value. For example, your system contains three nodes: Node1 is assigned the value A, Node2 is assigned the value B and Node3 is not assigned a value. You create a query to retrieve all nodes that are equal to A and select NOT ; the results of your query only include Node2 because Node3 is not assigned a value.
Operator	Select the required operator. For details, see "Attribute Operator Definitions" on page 45.

UI Element (A-Z)	Description
Value	Enter or select the value of the attribute. The Value options vary according to the attribute type you select.
Visible	Select Visible to display the selected TQL query node in the editing pane. When Visible is cleared, an invisible box D appears to the right of the selected TQL query node in the editing pane.
	results. For example, Windows are connected to the network by defining specific IP Addresses, but in any query results you may want to view the IP Address elements only and not the Windows elements.

💐 Related Query Node Instances Page

This wizard page displays all the instances found for the selected TQL query node in a table.

Important information	The columns displayed in the report vary according to the CI type selected.
	By default, only columns corresponding to attributes that have been defined with the Asset Data , Change Monitored , and Comparable attribute qualifiers in the CI Type Manager are displayed as columns in the dialog box. For details, see "Attributes Page" on page 498.
	If required, you can click the Display Hidden Columns button to display the attributes that are defined as Visible but not Static. For details on Static attributes, see "Attributes Page" on page 498.
	Note: For information on the elements included in the Related Query Node Instances page, see "Element Instances Dialog Box" on page 77.
Wizard map	The Add Related Query Node Wizard contains: Related Query Node Type Page > Relationship Type Page > Related Query Node Properties Page > Related Query Node Instances Page

💐 Add Triplet Dialog Box

This dialog box enables you to define the allowed steps in a path in the topology graph leading from the source CI to the target CI when creating a subgraph definition, a compound relationship, or a calculated relationship.


To access	 In the Add Compound Relationship dialog box, click the Add button. For details, see "Add/Edit Compound Relationship Dialog Box" on page 56. In the Subgraph Definition dialog box, click Add. For details, see "Subgraph Definition Dialog Box" on page 100. In CI Type Manager, select Calculated Relationships from the drop-down list in the CI Types pane. In the editing pane, select the Triplets page and then click Add.
Important information	Select the query nodes and relationships to be included in the topology graph. Important: The Condition fields are displayed only when you access the Add Triplet dialog box from the Subgraph Definition dialog box.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362
See also	 "Compound Relationship" on page 26 "Define a Compound Relationship – Scenario" on page 33 "Subgraph Definition" on page 28

User interface elements ar	re described below:
----------------------------	---------------------

UI Element (A-Z)	Description
0	Define attribute conditions for the source and target query nodes you selected. When the Add Triplet dialog box is opened from the Subgraph Definition dialog box, it opens the Subgraph Condition Definition dialog box. When the Add Triplet dialog box is opened from the Add Compound Relationship dialog box, it opens the Compound Relationship Condition Definition dialog box.
	The Condition button is enabled only after you select a query node from the Source or Target lists.
	Note : You cannot define attribute conditions for the source and target query nodes in the CI Type Manager.
Relationship	Select an available relationship connecting the two query nodes. The list of available relationships appears only after defining both query nodes.
Relationship Direction	Select the required direction. Setting different relationship directions can achieve different query results. For an example, see "Setting Different Relationship Directions for Compound Definitions" on page 75. Note: The Relationship list remains empty until you have
Source	selected a source and target. Select the required source query node.
Target	Select the required target query node.

Setting Different Relationship Directions for Compound Definitions


You can achieve different TQL results by setting different relationship directions. For example, in your business world, as illustrated below, you want to create a compound relationship that connects between a query node of the CIT **a** and a query node of the CIT **b**. Depth is defined at **5** (for details, see "Depth" on page 101).




In the Add Triplet dialog box, you can create compound definitions to link query nodes **a** and **b** using different relationship directions.

Compound Definition	Source	Target	Relationship	Relationship Direction
#1	query node a	query node c	<relationship></relationship>	source> target
#2	query node c	query node b	<relationship></relationship>	source> target
#3	query node c	query node b	<relationship></relationship>	source < target


► Compound definitions 1 and 2 result in the following query:



► Compound definitions 1 and 3 result in the following query:



► Compound definitions 1, 2, and 3 result in the following query:



💐 Element Instances Dialog Box

This dialog box displays all of the CI instances found for the selected TQL query node in a table.

To access	To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio: In the editing pane, right-click the required query node and select Show Element Instances.
	Note: If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Show Element Instances option.
	To access in Adapter Management in DFM:1 Select an adapter in the Resources pane.
	2 In the Adapter Definition tab, click the Edit Input Query <i>⊘</i> button to the right of the Input Query box to open the Input Query Editor.
	3 Right-click the required query node and select Show Element's Instances .
	To access in Integration Studio:
	Create an integration point based on a discovery jython adapter. In the Trigger CI Instance menu, choose Select Existing CI .

Important information	The columns in the table display the attributes of the selected CI type. The attributes displayed vary according to the CI type selected.
	By default, only columns corresponding to attributes that have been defined with the Asset Data , Change Monitored , and Comparable attribute qualifiers in the CIT Manager are displayed as columns in the dialog box. For details, see "Attributes Page" on page 498.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362 "How to Work with Population Jobs" in <i>RTSM Data Flow Management Guide</i> "How to Work with Data Push Jobs" in <i>RTSM Data Flow Management Guide</i>

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
Show Cl instances of: Network	Specify the CIT you want displayed in the table. The table also includes the children of the selected CIT.
×	Click to delete the selected CI.
	Click Show CI Properties to open the Configuration Item Properties dialog box for the selected CI.
Ø	Click to refresh the list of CI instances.
7	Filters the CI instances you want to display for the selected query node. Opens the Filter CI Instances dialog box.
V	Clears the filter definitions you created in the Filter CI Instances dialog box.

UI Element (A-Z)	Description
	Enables you to select the columns to be displayed. For details, see "Select Columns Dialog Box" on page 570.
≜ ↑	Enables you to set the sort order of the CI instances. For details, see "Sort Column Content Dialog Box" on page 572.
Q	Click Find to display the Find toolbar.
	Click Send Mail to send the table data in an email.
8	Choose the export format for the table data. The available options are:
	 Excel. The table data is formatted as an .xls (Excel) file that can be displayed in a spreadsheet. PDF. The table data is exported in PDF format. Note: When exporting to PDF, select a reasonable number of columns to display to ensure that the report is legible. CSV. The table data is formatted as a comma-separated values (CSV) text file that can be displayed in a spreadsheet. Note: For the CSV formatted table data to display correctly, the comma (,) must be defined as the list separator. In Windows, to verify or modify the list separator value, open Regional Options from the Control Panel, and on the Numbers tab ensure that the comma is defined as the List Separator value.
	 XML. The table data is formatted as an XML file that can be opened in a text or XML editor. Tip: To extract HTML code from the report: Save the file as HTML Open the file in an HTML editor
	 Copy the relevant table into the target file
30 Rows per page	Select the number of rows to be displayed on each page. You can also manually enter value for the number of rows per page.

UI Element (A-Z)	Description
🕅 🔍 3 of 16528 🗅 🕅	Click to navigate through the results page by page or to jump to the first or last page.
<element instances=""></element>	The CI instances found for the selected TQL query node. You can double-click an instance to open the Configuration Item Properties dialog box for that CI.
<element instances<br="">shortcut menu></element>	For details, see "IT Universe Manager Shortcut Menu" on page 283.
Display Label	The name of the CI instance as it appears in the topology map.

💐 Filter CI Instances Dialog Box

This dialog box enables you to reduce the number of CI instances to be displayed in a list by selecting a condition and a value for a specific CI.

To access	Click the Filter 🝸 button in the Element Instances
	dialog box.

Important information	A description of the filter condition you defined appears above the table columns in the Element Instances dialog box. For example, the following illustration shows that a filter condition was created to display only CI instances whose CI type is Windows . Filter: CI Type[Equal nt]; Display Label CI Type VMXPUKR01 Windows
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Element (A-Z)	Description
Attribute	Displays all the attributes of the CI type to which the CI belongs.
Condition	Select the required operator. For details, see "Attribute Operator Definitions" on page 45.
NOT	Select to filter the results by the negation of a condition and value.
Value	Select or enter the required value.

💐 Join Relationship Condition Dialog Box

This dialog box enables you to define the connection between two query nodes using a join relationship.

To access	In Enrichment Manager or Impact Analysis Manager, click the Add ¹ button in the Add Join Relationship dialog box.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM Developer Reference Guide</i>.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<selected query<br="">node1></selected>	A selected query node. The first attribute applies to <end_1>.</end_1>

UI Element (A-Z)	Description
<selected query<br="">node2></selected>	A selected query node. The second attribute applies to <end_2>.</end_2>
Operator	Select one of the following operators:
	 Equal. The system checks whether two selected attributes are equal.
	 Not equal. The system checks whether two selected attributes are not equal.
	 Sub string. The system checks whether the value of the first attribute is a substring of the value of the second attribute.
	➤ Sub string ignore case. The system checks whether the value of the first attribute is a substring of the value of the second attribute regardless of the string's case.
	Important : When using the operator Not equal , ensure that both sides of the join relationship have a limited result size. It is recommended to define more specific conditions so as not to overload the system with large results.

💐 Layout Settings Dialog Box

This dialog box enables you to determine which attributes are used in the calculation of the TQL query when using the UCMDB API. For details, see "RTSM (HP Universal CMDB) Web Service API" in the *RTSM Developer Reference Guide*.

To access	Click Advanced layout settings in the Query Node/Relationship Properties dialog box.
Important information	Since this option is only relevant when querying the CMDB API, the query results in the user interface are not impacted by the attributes you select in this dialog box.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Element (A-Z)	Description
Attribute name	The name of the attribute.
Calculate	Select this check box to include the attribute in the query's calculation.

💐 Query Node/Relationship Properties Dialog Box

This dialog box enables you to define the attribute conditions for the selected TQL query node/relationship.

To access	To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio: In the editing pane, right-click the required query node and select Query Node/Relationship Properties.
	Note: If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Query Node Properties option.
	To access in DFM:
	1 To access from the Adapter Definition tab, select an adapter. Click the Edit Input Query <i>⊘</i> button to the right of the Input Query box to open the Input Query Editor.
	 Right-click the required query node/relationship and select Query Node Properties or Relationship Properties.
Relevant tasks	➤ "Define an Impact Rule – Workflow" on page 452
	► "Define an Enrichment Rule – Scenario" on page 523
	➤ "Define a TQL Query" on page 30
	► "Implement a Discovery Adapter" in the <i>RTSM</i>
	Developer Reference Guide
	 "Create a Pattern View" on page 359
	► "Create a Template" on page 360
	 "Create a Perspective" on page 362

UI Element (A-Z)	Description
Element name	(Optional) The Element name box contains the name of the selected query node/relationship. By default, the CI type is assigned as the element's name. You can rename a TQL query node in the Element name box giving it a unique label. This can be helpful when there is more than one query node of the same CI type in the TQL query.
Include subtypes	Select to display both the selected CI and its children in the topology map.
Query Result Count	Click Query Result Count to display a topology map of the TQL query showing the number of instances of each query node/relationship. Note: This feature is only available in the Modeling Studio.
Visible	Select Visible to display the selected TQL query node in the editing pane. When this option is cleared, an invisible box D appears to the right of the selected TQL query node in the editing pane. D D D D D D D D D D

Attribute Tab

This area enables you to create an expression defining conditions that restrict the number of query nodes that appear in the query. You can add an attribute condition to a query node or relationship and filter the query results.

To access	Click the Attribute tab in the Query Node/Relationship Properties dialog box.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Element (A-Z)	Description
+	Add the attribute condition you have defined.
×	Delete an attribute definition.
♠	Move a selected row up.
¥	Move a selected row down.
Q	Display the criteria in a popup dialog box.
Advanced layout settings	Opens the Layout Settings dialog box which enables you to determine which attributes are used in the calculation of the TQL query when querying the RTSM using third- party or custom tools.
And/Or	Click inside the And/Or field and select either And or Or to link multiple conditions.

Chapter 1 • Topology Query Language

UI Element (A-Z)	Description
Attribute name	Select an attribute from the drop-down list.
() Brackets	Click inside the Brackets box to display a list of brackets you can use to build more complex, logical statements.
Criteria	Contains the attribute condition definition as defined in the Element Instances dialog box.
Default Value	For parameterized attributes, enter a default value for the parameter.
Not	Select NOT if you want the condition statement to do the opposite of what is defined.
	Note : If you select NOT , query results do not include data from the CI instances that were not assigned a value. For example, your system contains three nodes: Node1 is assigned the value A, Node2 is assigned the value B and Node3 is not assigned a value. You create a query to retrieve all nodes that are equal to A and select NOT ; the results of your query only include Node2 because Node3 is not assigned a value.
Operator	Select the required operator. For details, see "Attribute Operator Definitions" on page 45.
Parameterized	Select Yes to define a parameterized value for the attribute. Select No to define a fixed value for the attribute.
	Note: This feature is only available in the Modeling Studio.
Parameter Name	If you are defining a parameterized value for the attribute, you must enter the parameter name.
	Note: This feature is only available in the Modeling Studio.
Value	Enter or select the value of the attribute. The Value options vary according to the attribute type you select.
	Note: You can paste a copied value into the window by pressing CTRL+V on the keyboard.

Cardinality Tab

In this area, you can define a relationship cardinality, which enables you to define how many CI instances you expect to have at the end of a relationship in your query result.

To access	Click the Cardinality tab in the Query Node Properties dialog box.
Important information	Select the required relationship to which the selected query node is attached. Then define the lower and upper limits for including the query node at the other end of the relationship in the query results.
	You can define relationship conditions that enable the relationship's connecting query node to be included in the TQL query results by creating an expression defining that condition. For an example, see "Example of a Relationship Condition" on page 91.
	Note: This tab only appears when a query node is selected.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362


UI Element (A-Z)	Description
÷	Add the cardinality definition you have defined.
×	Delete a cardinality definition from the Cardinality area.
♠	Move a selected row up.

UI Element (A-Z)	Description
V	Move a selected row down.
Q	Display the criteria in a popup dialog box.
1*	Inserts 1 in the Min box and * in the Max box. Note: Only relevant for the Modeling Studio.
0*	Inserts 0 in the Min box and * in the Max box. Note: Only relevant for the Modeling Studio.
And/Or	Click inside the And/Or field and select either And or Or to link multiple conditions.
() Brackets	Click inside the Brackets box to display a list of brackets you can use to build more complex, logical statements.
Criteria	Contains the cardinality condition definition as defined in the Element Instances Dialog Box.
Мах	Enter the value that defines the upper limits for including the query node at the other end of the relationship in the query results. Note: You can use an asterisk (*) in the Max box to represent an infinite value.
Min	Enter the value that defines the lower limits for including the query node at the other end of the relationship in the query results.
	For example, if <end_1> is lpAddress and <end_2> is Windows, entering 1 in the Min box and asterisk (*) in the Max box instructs the system to retrieve only those IP Addresses that are connected to at least one Windows operating system. (The asterisk indicates an infinite value.) Entering 3 in the Min box and asterisk (*) in the Max box instructs the system to retrieve only those Windows operating systems that are connected to at least three IP Addresses.</end_2></end_1>

UI Element (A-Z)	Description
Query Node	Select the required relationship to which the selected query node is attached. The list contains all the relationships that are linked to the selected query node.
Not	Select NOT if you want the condition statement to do the opposite of what is defined.
	Note : If you select NOT , query results do not include data from the CI instances that were not assigned a value. For example, your system contains three nodes: Node1 is assigned the value A, Node2 is assigned the value B and Node3 is not assigned a value. You create a query to retrieve all nodes that are equal to A and select NOT ; the results of your query only include Node2 because Node3 is not assigned a value.

Example of a Relationship Condition

The example of relationship conditions is based on the following TQL query:



In the Relationship Cardinality dialog box, the following relationship conditions are defined for the query:

- ► Containment Min: 2, Max: 4
- ► Membership Min: 1, Max: *

Using the OR operator, the definitions appear in the **Cardinality** section, as follows:

NOT	(Criteria)	And/Or
		Containment (Node, IpAddress) : 24		OR
		Membership (lpSubnet, Node) : 1*		

 [Containment (Node, IP Address)] OR [Membership (IP Subnet, Node)] means that the node must either have between two and four IP Addresses OR be a member of the IP Subnet.

Using the AND operator, the definitions appear in the **Cardinality** section, as follows:

NOT	(Criteria)	And/Or
		Containment (Node, lpAddress) : 24		AND
		Membership (IpSubnet, Node) : 1*		

[Containment (Node, IP Address)] AND [Membership (IP Subnet, Node)] means that the node must have between two and four IP Addresses AND also be a member of the IP Subnet.

Qualifier Tab

This area enables you to define qualifier conditions for the selected query node or relationship. For example, you can use a qualifier to define a CIT as abstract, meaning you cannot create instances from it.

To access	Click the Qualifier tab in the Query Node/Relationship
	Properties dialog box.

Important information	By default, multiple selection links the conditions with the OR operator.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Element (A-Z)	Description
ABSTRACT_CLASS	You cannot create instances of this CIT.
ALLOW_VOLATILITY	Used to mark attributes that enable minor deviations to their value. For example, there is probably no need to report a small disk size change (from 8.00008 to 8.00009 GB).
	By default, ALLOW_VOLATILITY is enabled for the following numeric or date attributes only:
	► CIT: Node
	► MemorySize
	► SwapMemorySize
	These attributes also include comparable and static qualifiers.
	► CIT: Host
	➤ HostLastBootTime
	► CIT: CPU
	► CpuClockSpeed
	► CIT: Filesystem
	► Disk_size
	For details of this qualifier's attributes and the procedure for activating and deactivating this feature, see "The ALLOW_VOLATILITY Qualifier" on page 28.

UI Element (A-Z)	Description
BDM_SCOPE	Indicates that the CI type is part of the BDM scope of the class model.
BLE_LINK_CLASS	A relationship that has been assigned this qualifier is loaded by an online BLE engine TQL and becomes part of the Dashboard status calculations.
CALCULATED_LINK	This qualifier is assigned to calculated relationships
CONTAINER	This qualifier is assigned to relationships that signify a containment relationship, such as Membership, Composition, Containment.
HIDDEN_CLASS	Instances of this CIT do not appear anywhere in the application.
ID_CLASS_NAME_OVER RIDE	Indicates that the class ID is calculated based on another class.
ITU_HIDDEN_CLASS	Instances of this CIT do not appear in the topology map application.
MAJOR_APP	CI types that are assigned this qualifier appear in the Application Breakdown overview report. For details, see "Application Breakdown Report" on page 416.
MODELING_ENABLED	Enables a CIT to act as a model in Modeling Studio. For details, see "Business CI Models" on page 346.
NETWORK_DEVICES	A qualifier common to all the CI types that represent a network device. It can be used for TQL queries related to network devices and serves as a replacement for CI types in a query.
Negate Qualifiers	If this check box is selected, then the element is included in the query results only if it has no qualifier in the list of selected qualifiers.
PM_SUSPECT	Used by Problem Isolation to determine which CIs are to be considered as suspects when isolating a problem. For details, see "Problem Isolation" in <i>Using Problem</i> <i>Isolation</i> .

UI Element (A-Z)	Description
RANDOM_GENERATED_ ID_CLASS	Indicates that the RTSM ID of the CIs is randomly generated rather than being based on the key attributes of the class.
READ_ONLY_CLASS	This CIT cannot be edited.
RECURSIVE_DELETE	Relevant for relationships. When the CI at one end of a relationship is deleted, the system checks the CI at the other end of the relationship. If it is not related to any other CIs, it is also deleted.
TRACK_LINK_CHANGES	Changes that occur in the specified relationship appear in Change reports.

Identity Tab

This area enables you to filter the TQL query results according to the element ID of the instances found for the selected TQL query node.

To access	Click the Identity tab in the Query Node Properties dialog box.
Important information	Move the required element from the Optional identities pane on the left to the Selected identities pane on the right to define what you want included in the TQL query results using the left and right arrows. Note: This tab only appears when a query node is
	selected.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

The following elements are included (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<toolbar></toolbar>	For descriptions of the toolbar buttons, see "Element Instances Dialog Box" on page 77.
Optional identities pane	Displays all the instances found for the selected TQL query node.
Selected identities pane	Displays the elements that are used to define what should be included in the TQL query results.

Refine Query Node Type Dialog Box

This dialog box enables you to change the CI type of a TQL query node after you have created a TQL query.

To access	In Impact Analysis Manager or Enrichment Manager, right- click the required query node and select Refine Query Node Type . Note: If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Refine Query Node Type option.
Important information	You can change the CI type to a type from one of the CI type's children, if one exists. If no such CI type exists, this option does not appear.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<list ci="" from<br="" of="" types="">which to choose></list>	Select the required CI type.

💐 Select Relationship Type Dialog Box

This dialog box enables you to select the type of TQL relationship to be created.

To access	In the editing pane of Impact Analysis Manager, Enrichment Manager, and the Modeling Studio, click the Create Relationship the button in the toolbar and draw a line between two query nodes. The Select Relationship Type dialog box opens automatically.
Important information	 Select one of the following relationship types: Regular Relationship. For details, see "Add/Edit Relationship Dialog Box" on page 63. Join Relationship. For details, see "Add/Edit Join Relationship Dialog Box" on page 60. Compound Relationship. For details, see "Add/Edit Compound Relationship Dialog Box" on page 56. Calculated Relationship. For details, see "Add/Edit Calculated Relationship Dialog Box" on page 54.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

💐 Subgraph Condition Definition Dialog Box

This dialog box enables you to create conditions that restrict the number of query nodes that appear in the query.

To access	In Impact Analysis Manager and Enrichment Manager, click Condition in the Add Triplet dialog box. In the Modeling Studio, click Condition in the Subgraph Definition dialog box.
Important information	 Contains the following tabs: Attribute. Enables you to define attribute conditions for query nodes and relationships. See a description of the elements in the Attribute tab in the table below. Qualifiers. Enables you to define qualifier conditions for the selected query node or relationship. For details, see "Qualifier Tab" on page 92.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Element (A-Z)	Description
+	Add the subgraph condition definition.
×	Delete the subgraph condition definition.
<u>^</u>	Move a selected row up.
₩	Move a selected row down.

UI Element (A-Z)	Description
Q	View the subgraph condition definition.
Advanced layout settings	Opens the Layout Settings dialog box which enables you to determine which attributes are used in the calculation when querying the RTSM using third-party or custom tools. Note: This option is only relevant when accessing the
	dialog box from the Modeling Studio.
And/Or	Click inside the And/Or field and select either And or Or to link multiple conditions.
Attribute name	Choose an attribute from the list.
() Brackets	Click inside the Brackets box to display a list of brackets you can use to build more complex, logical statements.
Criteria	Contains the attribute condition definition as defined in the Element Instances Dialog Box.
Element Name	Contains the CIT selected from the Source and Target lists.
Not	Select NOT if you want the condition statement to do the opposite of what is defined.
	Note : If you select NOT , query results do not include data from the CI instances that were not assigned a value. For example, let us assume that your system contains three nodes. Node1 is assigned the value A, Node2 is assigned the value B and Node3 is not assigned a value. If you create a query in which you want to retrieve all nodes that are equal to A and you select NOT , the results of your query only include Node2 because Node3 is not assigned a value.
Operator	Select the required operator. For details, see "Attribute Operator Definitions" on page 45.
Value	Enter or select the value of the attribute. The Value options vary according to the attribute type you select.

💐 Subgraph Definition Dialog Box

This dialog box enables you to create a graph that represents additional TQL query data related to a specific CI.

To access	To access in Enrichment Manager, Impact Analysis Manager, and the Modeling Studio: In the editing pane, right-click the required query node and select Subgraph Definition.
	Note: If you are using Enrichment Manager, select Query mode at the top of the editing pane to display the Subgraph Definition option.
	 To access in Adapter Management in DFM: 1 Select an adapter in the Resources pane. 2 In the Adapter Definition tab, click the Edit Input Query button to the right of the Input Query box to open the Input Query Editor. 3 Right-click the required query node and select Subgraph Definition.
Important information	The following icon is displayed next to the query node for which you define a subgraph:
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362
See also	 "Subgraph Definition" on page 28 "Create a Subgraph Definition – Scenario" on page 38

User interface elements are described belo	ow:
--	-----

UI Element (A-Z)	Description
+	Add a subgraph definition. In Enrichment Manager and Impact Analysis Manager, click to open the Add Triplet dialog box. In the Modeling Studio, click to add a row to the table.
×	Delete a subgraph definition.
Ø	Edit a subgraph definition. In Impact Analysis Manager and Enrichment Manager, click to open the Edit Triplet dialog box. In the Modeling Studio, click to open the Subgraph Condition Definition dialog box.
Depth	A number that represents the longest path (that is, the maximum connecting query nodes) allowed between two CIs in the RTSM that should be included in the DFM process. Default: 5
Element condition exists	A green asterisk appears next to either the source, relationship, or target in the subgraph definition if an attribute condition has been defined for one of them in the Subgraph Condition Definition dialog box. For details, see "Subgraph Condition Definition Dialog Box" on page 98.
Relationship	The relationship selected connecting the source to the target query node.
Relationship Direction	The direction of the relationship selected, indicating which query node is dependent on the other.
Source	The required source query node selected.
Target	The required target query node selected.

💐 User Preferences Dialog Box

This dialog box enables you to reset system preferences.

To access	Select Tools > User Preferences or click the Configure User Preferences 😭 button in the Status Bar.
Important information	All the preferences you select (such as whether to display certain wizard pages or warning message preferences) are stored in the system. This dialog box enables you to reset those preferences.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<left pane=""></left>	Select the preferences page to edit. The following options are available:
	➤ Wizard Preferences. Enables you to define whether to hide or display certain wizard pages.
	➤ Optional Messages Preferences. Enables you to define whether to hide or display certain messages.
	► Discovery Preferences. Enables you to define:
	 Whether to hide or display certain Discovery warning messages
	 The required default external editor (such as Notepad)
	► Whether to use Basic or Advanced Discovery mode
	 General. Enables you to define general application preferences.
<preferences list=""></preferences>	The list of warning messages and their user-selected preferences.
Filter by	Enter a search word to filter the list of options.
Reset All	Click to reset all the preferences to their default values.
Reset Page	Click to reset the selected preference to its default value.

Troubleshooting and Limitations

This section describes troubleshooting and limitations for Topology Query Language.

For TQL queries to be valid, they must comply with certain restrictions.


This section includes the following topics:

- ► "Understanding Validation Restrictions" on page 103
- ➤ "Impact Analysis TQL Query Validation" on page 105
- ➤ "Enrichment TQL Query Validation" on page 106


Understanding Validation Restrictions

For Impact Analysis, Discovery, and Enrichment TQL query types to be valid, they must comply with the following restrictions:


- > Unique Names. TQL query elements must have unique names.
- ➤ Self Relationships. A TQL query must not contain self relationships, that is, a relationship must not lead from a query node to itself, as the following example illustrates:



 Cyclic Graph. The TQL query structure cannot be a closed circle, as shown in the following example:




➤ Separate Query Nodes and Groups. All the TQL query nodes must be linked to one another, that is, the TQL query cannot contain separate query nodes or groups, as the following example illustrates:



Impact Analysis TQL Query Validation

Impact Analysis TQL queries must also comply with the following restrictions:

- Number of query nodes. An Impact Analysis TQL query must consist of at least two query nodes.
- ➤ Trigger and affected query nodes must be connected. There must be a path of relationships from the triggered query node to the affected query nodes.
- ➤ Selecting query nodes to function as Impact Analysis triggers. When selecting query nodes to function as Impact Analysis triggers, the query nodes must comply with the following restrictions:
 - You can select more than one query node as a trigger. However, you cannot define a query node both as affected and as a trigger.
 - ➤ If a query node has a relationship whose minimum limit is 0 (meaning that one of its ends does not necessarily have a query node linked to it), the query node that is linked to its other end cannot be a root cause query node (because it may or may not exist in the TQL query). For details about minimum limits, see "Cardinality Tab" on page 89. For example, Configuration Item cannot be either a root cause or affected query node because it is connected to the query node with a Min limit of 0.



Note: A query node that is not visible cannot be a root cause or an affected query node.


➤ The connection between trigger and affected query nodes. The trigger query node and affected query nodes you define must be connected by a path of relationships from the triggered query node to the affected query nodes.

Enrichment TQL Query Validation


Enrichment TQL queries must comply with the following restriction:

► **Required elements.** You cannot perform Enrichment on a non-required query node, that is, a query node that does not necessarily appear in the TQL query results.

Example 1. In this example, the TQL query results can be either **A** and **B** or **A** and **C**. Therefore, you cannot add an Enrichment query node to query nodes **B** or **C** because they are not required elements. You can add an Enrichment query node to query node **A** because it always appears in the TQL query results. For details on how to add Enrichment query nodes and relationships, see "Add Enrichment Query Nodes and Relationships to an Enrichment TQL Query" on page 528.



Example 2. In this example, both **A** and **B** are required elements that always appear in the TQL query results. Only **C** is not a required element because it has a cardinality of 0. Therefore, you cannot add an Enrichment query node to it.



Chapter 1 • Topology Query Language

2

Impact Modeling

This chapter includes:

Concepts

- ► Impact Modeling Overview on page 110
- ► Impact Layer on page 111
- ➤ Impact Rules on page 111
- ► Propagation Reversal on page 113
- ► Calculated Relationship Types on page 114
- ➤ Creating Views Based on the Impact Model on page 115

Concepts

🚴 Impact Modeling Overview

The impact model enables you to determine the direction of the propagation of the IT infrastructure CIs in your business world. The direction of the impact is not always the same direction as the physical relationships taken from the CI Type model.

The impact model uses the impact layer to change the propagation direction. The impact layer is used in the applications where propagation occurs. You change the direction of the impact using the impact layer, regardless of the direction of the physical relationships.

All KPI propagation is affected by the impact model. For details on KPI propagation in Service Health, see "Propagation Rules" in *Using Service Health*. For details on KPI propagation in Service Level Management, see "Propagation Rules" in *Using Service Level Management*.

🚴 Impact Layer

The impact layer changes the direction of the impact. The impact layer separates the impact direction from the CI Type model, creating an independent layer on top of the CI Type model. This means that components affected by the impact model are no longer relying on the physical relationships as defined in the CI Type model. As a result, the impact direction is no longer necessarily identical to the direction of the physical relationships in the CI Type model.

\lambda Impact Rules

The impact layer consists of impact rules. The impact rules are defined in the CI Type Manager. For details, see "Triplets Page" on page 503.

An impact rule is defined by one or more triplets. Each triplet is defined by the following components:

- ➤ One source CI type
- ➤ One target CI type
- ➤ A physical relationship type (for example, Containment) that links the two CI types
- ➤ The required impact direction. The direction of the impact can be identical to or opposite from the direction of the physical relationship between the source and target CIs.

HP Business Service Management implements the impact layer by creating calculated relationships that are defined by impact rules. Once one of the triplets fulfills the impact rule condition, HP Business Service Management automatically creates the calculated relationship based on the triplet definition.


Since calculated relationships are defined by physical relationships from within the class model, their lifetime is determined by the lifetime of the physical relationships defined in the impact rule. When the physical relationship in the class model is removed, the corresponding calculated relationship is removed from all view results as well. **Note:** If you create a new CI type or relationship in the CI Type Manager, you need to define the required triplets. For example, to enable the impact model to properly affect KPI propagation. If the triplets are not defined, the required KPIs are not included in the Dashboard views and SLA agreements.

You can use calculated relationships to create TQL queries just like any other relationship in the CI Type model. This enables you to base Enrichment rules, Impact rules, and views on calculated relationships. Calculated relationships affect the results of all TQLs that use that calculated relationships since calculated relationships are part of the class model.

Example of an Impact Rule Definition:

🗞 Propagation Reversal

The following example illustrates a scenario in which propagation is reversed.



Based on the impact rules defined in the CI Type Manager, the impact is propagating from the **Business2** CI to **Business1**, the same direction as the physical relationship that is connecting the **Running Software** CI to **Business2**.

According to the direction of the physical relationship between the **Running Software** CI and the **Node**, the **Running Software** CI should impact the **Node**.

But based on the following impact rule, a calculated relationship is automatically created and HP Business Service Management reverses the impact of the propagation.

Node	P Link	RunningSoftware	(
		Co runningoorware	

The impact is now propagated from the **Node** to the **Running Software**.

\lambda Calculated Relationship Types

There is one out-of-the-box calculated relationship called **Impacted By**. **Impacted By** contains two subtypes, each one representing a different type of dependency relationship (complete dependency vs. potential dependency.)

- ➤ Impacted by (Directly). Represents the fact that one CI that is linked to another CI using an Impacted By (Directly) relationship is part of that CI. You use an Impacted By (Directly) relationship for those CIs that you want to see in your model. The ownership of the two CIs may be the same, but this is not always the case.
- ➤ Impacted By (Potentially). Represents the fact that one CI consumes the products of another. CIs that are linked by an Impacted By (Potentially) relationship are not part of that model, but are listed as related CIs. For details, see "Model Editor" on page 396.

A Creating Views Based on the Impact Model

As a best practice, you should use Modeling Studio to create a view of calculated relationships based on a model. Modeling Studio enables you to create perspective based views that use calculated relationships instead of physical relationships. For details, see "Modeling Studio" on page 335.

For details on how to create and edit models, see "Model Editor" on page 396.

Note: For an in-depth description of the Impact Modeling Solution, see "Best Practices for Modeling" on page 215.

Chapter 2 • Impact Modeling

Create a URL for a Direct Link

This chapter includes:

Concepts

➤ Generate a Direct Link – Overview on page 118

Tasks

- ➤ Generate a Direct Link Scenario on page 120
- ➤ Create a Direct Link to a Template with Parameter Values on page 120
- Encrypt the Password of a Direct Link Using the JMX Console on page 122

Reference

► Generate a Direct Link User Interface on page 123

Concepts

🚴 Generate a Direct Link – Overview

Direct Links enables you to create a URL that guides another user to a specific target view or CI in HP Business Service Management.

You can create a URL that:

➤ Opens a specific HP Business Service Management view or CI directly in HP Business Service Management. This enables users to retrieve information from HP Business Service Management without being located in the HP Business Service Management context.

Note: To open a specific view or CI directly in HP Business Service Management, use the **Open in context links** option. For details, see "Select Command Page" on page 125.

- > Enables integration with HP Business Service Management:
 - If you create a URL using the Embedded links option, the URL takes you first to the HP Business Service Management login page. After you enter your login name and password, the target page opens in your browser.

Note: To open the target page in your browser, use the **Embedded links** option. For details, see "Select Command Page" on page 125.

When you create a URL, you can:

- ► Send the URL to an email recipient
- ► Copy the URL to the clipboard

➤ Test the URL to ensure that the target application page can be found

The user to whom you are sending the URL must have an account with sufficient privileges to open the target page. You must apply the appropriate viewing and editing permissions to the users and user groups that want to access the target view. You set permissions in Admin > Platform > Users and Permissions, select a user or a group and select Permissions. For details, see "How to Assign Permissions" in *Platform Administration*.

Note: You can use **Link to this Page** function to open a target HP Business Service Management page in your browser. While the **Link to this Page** function enables you to access another application page in HP Business Service Management, it does not enable you to access a specific CI or view. For details, see "Linking to a Specific Page" in *Platform Administration*.

Tasks

膧 Generate a Direct Link – Scenario

This scenario describes how to generate a direct link to email the URL of a specific CI to another person.

Jane Harrison is a senior engineer in the ABC Software company. She has encountered a problematic CI in a view she has created. She wants to inform Henry Jones, who is working with the same view through HP ServiceCenter, about the problematic CI. Since the view Jane has created contains many hundreds of CIs, she decides to email Henry the URL of the CI so that he does not have to spend a lot of time searching for that specific CI.

In IT Universe Manager, Jane selects **Generate Direct Link** from the **Edit** menu. In the Select Command page, she selects **Open in context links** and then the **Show view** option, and clicks **Next**.

In the **Direct Link Parameters** — **Show View** page, she selects the view she created, the problematic CI, and **View topology** as the mode in which Henry should open the CI. When the URL is created, she emails Henry the link to the problematic CI.

For details, see "Generate Direct Link Wizard" on page 124.

Create a Direct Link to a Template with Parameter Values

This task describes how to create a direct link to a template by including the parameter values in the URL.

This task includes the following steps:

- ➤ "Create a Direct Link to a Template" on page 121
- ► "Edit the URL" on page 121
- ▶ "Paste the URL into a Browser" on page 122

1 Create a Direct Link to a Template

In IT Universe Manager, select **Edit** > **Generate Direct Link** to run the Generate Direct Link wizard. On the Select Command page, select **Embedded links**. Select **Show view topology** from the list of options. On the Direct Link Parameters page, select the required template from the drop-down list.

2 Edit the URL

When the wizard finishes, click **Copy URL** and paste the URL into a text editor such as Notepad.

Append the following text to the end of the URL:

¶ms=[parameter1=value1,parameter2=value2]

where parameter1 and parameter2 are the parameter names for the selected template and value1 and value2 are the values you want to enter for the parameters.

Note: Any special characters must be entered using the URL encoding. In the above example, the URL encoding for the [character is %5B, the URL encoding for the] character is %5D, and the URL encoding for the comma is %2C. Thus, the actual text to enter is:

¶ms=%5Bparameter1=value1%2Cparameter2=value2%5D

3 Paste the URL into a Browser

Paste the URL into a browser. HP Business Service Management opens to the selected template with the parameters assigned the specified values.

P Encrypt the Password of a Direct Link Using the JMX Console

This task describes how to encrypt the password contained within a direct link using the JMX console.

To encrypt the password of a direct link using the JMX console:

- 1 Launch your Web browser and enter the following address: http://<server_name>:<port number>/jmx-console, where <server_name> is the name of the machine on which HP Universal CMDB is installed.
- 2 Under UCMDB-UI, locate UCMDB Integration.
- **3** Under **encryptString**, enter your password in the **Value** box.
- **4** Click **Invoke** to view the encrypted string.

Reference

💐 Generate a Direct Link User Interface

This section includes (in alphabetical order):

- ► Generate Direct Link Dialog Box on page 123
- ► Generate Direct Link Wizard on page 124

💐 Generate Direct Link Dialog Box

This dialog box enables you to create a URL to send to users so that they can access HP Business Service Management.

To access	From the Admin > RTSM Administration > Modeling main menu, select Edit > Generate Direct Link. After you configure the Direct Link parameters in the "Generate Direct Link Wizard" on page 124, click Finish in the Finish page.
	Alternatively, click the Generate Direct Link to View and button in the CI Selector toolbar in IT Universe Manager.
Relevant tasks	"Generate a Direct Link – Scenario" on page 120

UI Element (A-Z)	Description
Advanced	Enables you to build a direct link and choose specific elements such as views or CIs, for the end user to access. For details, see "Generate Direct Link Wizard" on page 124.
	Note: This feature is only relevant when accessing the Generate Direct Link dialog box from the CI Selector toolbar in IT Universe Manager.
Copy URL	Copies the URL to the clipboard.
Description	Describes the parameters that are included in the URL. For details on selecting the parameters, see "Select Command Page" on page 125.
Link URL	The created URL that accesses the specified HP Business Service Management function.
Mail URL	Opens an email containing the URL of the link.
Test URL	Checks the URL to ensure that the specified application page can be found.

User interface elements are described below:

💐 Generate Direct Link Wizard

This wizard enables you to create a URL that guides another user to a specific target view or CI in HP Business Service Management.

To access	From the Admin > RTSM Administration > Modeling main menu, select Edit > Generate Direct Link.
Important information	By default, this wizard is set to display a Welcome page. You can choose not to display the Welcome page by selecting the Do not show this page again check box.

Relevant tasks	"Generate a Direct Link – Scenario" on page 120
Wizard map	The Generate Direct Link wizard contains:
	Select Command Page (<open context="" in="" links="" options=""> and <embedded links="" options="">) > Finish Page</embedded></open>

💐 Select Command Page

This wizard page enables you to select the required parameters that must be added to the URL.

You can create two types of links:

- Open in context links. Creates a URL that opens a specific view or CI directly in HP Business Service Management without having to be in the HP Business Service Management context:
- ► Embedded links. Creates a URL that enables you to embed an RTSM applet into external applications.

Important information	By default, this wizard is set to display a Welcome page. You can choose not to display the Welcome page by selecting the Do not show this page again check box.
Wizard map	The Generate Direct Link wizard contains: Select Command Page (<open context="" in="" links="" options=""> and <embedded links="" options="">) > Finish Page</embedded></open>
See also	"Generate Direct Link Wizard" on page 124

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<left pane=""></left>	A graphic illustration of the selected command.
CII Grid	Creates a URL that displays all the CI instances found in the RTSM for a selected CI type and its children. For details, see "Direct Link Parameters – CII Grid Page" on page 131. Note: Available when you select the Embedded links option.
CI Selector	Creates a URL that embeds the CI Selector displaying the CIs of a selected view, into external applications. For details, see "Direct Link Parameters – CI Selector Page" on page 129.
	Note: Available when you select the Embedded links option.
Cl Type Selector	Creates a URL that embeds the CI type selector into external applications. For details, see "Direct Link Parameters – CI Type Selector Page" on page 129. Note: Available when you select the Embedded links
	option.
Description	A description of the selected command.
Impact Map	Creates a URL that embeds an impact map into an external application. For details, see "Direct Link Parameters – Impact Map Page" on page 132.
	Note: Available when you select the Embedded links option.
Model Editor	Creates a URL that embeds the Model Editor into an external application, highlighting the selected CIs in the CI Selector in the Model Editor. For details, see "Direct Link Parameters – Model Editor" on page 133. Note: Available when you select the Embedded links option.

UI Element (A-Z)	Description
Query Editor	Creates a URL that embeds the Model Editor into an external application, displaying the selected TQL query. For details, see "Direct Link Parameters – Query Editor" on page 134.
	Note: Available when you select the Embedded links option.
Related Cls	Creates a URL that opens a topology map displaying the selected CI and its immediate neighbors within the selected view. For details, see "Direct Link Parameters – Related CIs Page" on page 135.
	Note: Available when you select the Embedded links option.
Report Viewer	Creates a URL that opens a specific report. For details, see "Direct Link Parameters – Report Viewer Page" on page 136.
	Note: Available when you select the Embedded links option.
Report Viewer - Saved Report	Creates a URL that opens a saved topology or custom report. For details, see "Direct Link Parameters – Report Viewer – Saved Report Page" on page 136.
	Note: Available when you select the Embedded links option.
Show CI properties	Creates a URL that displays a CI's properties. For details, see "Direct Link Parameters – Show CI Properties Page" on page 137.
	Note: Available when you select the Embedded links option.
Show view	Creates a URL that displays the selected view and optionally preselects a query node in it. For details, see "Direct Link Parameters – Show View Page" on page 140.
	Note: Available when you select the Open in context links option.

UI Element (A-Z)	Description
Show view topology	Creates a URL that displays the topology map of the selected view and embeds it in an external application. For details, see "Direct Link Parameters – Show View Topology Page" on page 138.
	Note: Available when you select the Embedded links option.
Start in mode	Creates a URL that opens HP Business Service Management at the selected page. For details, see "Direct Link Parameters – Start in Mode Page" on page 141.
	Note: Available when you select the Open in context links option.
Steps	The current step in the procedure.
View Editor	Creates a URL that opens a specific view in the Pattern View Editor in Modeling Studio. For details, see "Direct Link Parameters – View Editor Page" on page 138.
	Note: Available when you select the Embedded links option.
Views Selector	Creates a URL that embeds the View Selector in an external application, enabling you to select and display a view in that application. For details, see "Direct Link Parameters – Views Selector Page" on page 139.
	Note: Available when you select the Embedded links option.

💐 Direct Link Parameters – CI Selector Page

This wizard page enables you to create a URL that embeds the CI Selector displaying the CIs of a selected view, into external applications.

Wizard map	Select Command Page (Embedded links > CI Selector) > Finish Page
Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.

User interface elements are described below:

UI Element (A-Z)	Description
Allow multi selection	Allow single or multiple selection of CIs.
Selected view	 Select the required view from which you want to select the required CIs. Click is to open the View Selector dialog box. Select the view you want to appear in the CI Selector. Click to delete the selected view.

💐 Direct Link Parameters – Cl Type Selector Page

This wizard page enables you to create a URL to a hierarchical tree or list of selected CI types, which can be embedded into an external application.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > CI Type selector) > Finish Page

UI Element (A-Z)	Description
CI type selector mode	View the selected CI types in either a hierarchical tree or list.
Invisible CITs (tree only)	 Select the CI types you do not want to appear in the tree. ➤ Click to open the CI Type Selector dialog box. Select the CI types you want to appear in the tree. ➤ Click to delete the selected CI types.
Root CI Type (tree only)	 Select the CI type you want to use as the root CI type in a hierarchical tree. Click local to open the CI Type Selector dialog box. Select the CI type you want to use as the root CI type in the tree. Click local to delete the selected CI type. The default is Configuration Item.
Selection mode	Allow single or multiple selection of CI types.
Unselectable CITs (tree only)	 Select the CI types which cannot be selected in the tree. ➤ Click log to open the CI Type Selector dialog box. Select the CI types which cannot be selected in the tree. ➤ Click to delete the selected CI types.
Visible CITs (list only)	 Select the CI types which you want to appear in the CI type list. ➤ Click to open the CI Type Selector dialog box. Select the CI types which you want to appear in the CI type list. ➤ Click to delete the selected CI types. Note: If you choose to view the CITs in a list, then you are required to select at least one CI type.

💐 Direct Link Parameters – CII Grid Page

This wizard page enables you to display all of the CI instances found in the RTSM for selected CI type, and its children.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > CII Grid) > Finish Page
See also	"Element Instances Dialog Box" on page 77

UI Element (A-Z)	Description
Class type	 Select the required CI type. Click to select the required CI type. Click X to clear the box.

🍳 Direct Link Parameters – Impact Map Page

This wizard page enables you to run an Impact Analysis rule defined in Impact Analysis Manager. The URL you create enables you to embed a topology map showing a simulation of all the CIs that are affected by the selected trigger CI for the selected severity and state. For details, see "Run Impact Analysis Dialog Box" on page 294.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Impact map) > Finish Page
See also	"IT Universe Manager" on page 227

UI Element (A-Z)	Description
Filter by CI types	 Select the CI types you do not want to appear in the impact analysis results. Click i to select the required CI types. Click X to delete the selected CI types.
Rule bundle	Enables you to define where you can run Impact Analysis rules.

UI Element (A-Z)	Description
Severity	Select the required severity from the drop-down list.
	Note : The severity list was defined for the state in the System Type Manager. For details, see "System Type Manager" on page 479.
	For example, you can create an Impact rule in the Impact Analysis Manager (see the "Impact Rules Definition Dialog Box" on page 467), that defines the severity of the trigger query node as other than No Change . If you select a severity other than No Change , for example, Plan , the condition is met and the simulated changes in the system are triggered.
	For details, see "Run Impact Analysis Dialog Box" on page 294.
Trigger Cls	 Click is to select the CIs that are used as the triggers in an impact map. These CIs represent the simulated changes to be made to the system. Opens the CI Selector dialog box. For details on how to use the CI Selector pane, see "CI Selector" on page 163. Click X to delete the selected CIs.

💐 Direct Link Parameters – Model Editor

This wizard page enables you to embed the Model Editor into an external application, highlighting the selected CIs in the CI Selector in the Model Editor.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Model Editor) > Finish Page
See also	"Business CI Models" on page 346

User interface elements are described below:

UI Element (A-Z)	Description
Model name	 Select the model you want to display in the Model Editor. Click i to open the Select Model dialog box. Select the model you want to appear in the Model Editor. Click to delete the selected model.
Selected CI in search	 Select the CIs you want to appear highlighted in the CI Selector in the Model Editor. ➤ Click i to open the CI Selector. ➤ Click 💥 to delete the selected CIs.

💐 Direct Link Parameters – Query Editor

This wizard page enables you to embed the Model Editor into an external application, displaying the selected TQL query.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Query Editor) > Finish Page
See also	"Business CI Models" on page 346

UI Element (A-Z)	Description
Query name	 Select the model you want to display in the Model Editor. Click i to open the Select Query dialog box. Select the query you want to appear in the Model Editor. Click to delete the selected query.

💐 Direct Link Parameters – Related Cls Page

This wizard page enables you to embed into an external application, a topology map that displays a specific CI, and all the CIs that are linked to it by a distance of no more than one relationship.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Related CIs) > Finish Page

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
Cls	 Select the CI type you want to appear in the topology map. Click is to select the required CI types. Opens the CI Selector dialog box. Click X to delete the value in the CIs box.
Filter by CI types	 Restrict the results of the topology map to related CIs of one or more CI types. Click i to select the required CI types. Click to delete the value in the Filter by CI types box.
Restrict to view	 Restrict the results of the topology map to related CIs from a specific view. Click is to select the required view. Opens the View Selector dialog box. Click to delete the selected view in the Restrict results to view box.

🍳 Direct Link Parameters – Report Viewer Page

This wizard page enables you to create a URL that opens a specific report.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Report Viewer) > Finish Page

User interface elements are described below:

UI Element (A-Z)	Description
Report type	Select the required report type. For information about the different report types, see "Reports" on page 303.

🂐 Direct Link Parameters – Report Viewer – Saved Report Page

This wizard page enables you to create a URL that opens a saved topology or custom report.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Report Viewer - Saved Report) > Finish Page

 UI Element (A-Z)
 Description

 Report
 Select the required saved report.

 > Click ...
 to open the Select Report dialog box. Select the required topology or custom report.

 > Click X
 to delete the selected report.

 For information about saved reports, see "Reports" on page 303.

User interface elements are described below:

💐 Direct Link Parameters – Show Cl Properties Page

This wizard page enables you to view basic information for an existing CI.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Show CI properties) > Finish Page
See also	"Configuration Item Properties Dialog Box" on page 266

UI Element (A-Z)	Description
Source CI object ID	 Select the required CI. Click to select the source CI and retrieve its object ID. Opens the Select Source CI dialog box. For details, see "CI Selector" on page 163. Click to delete the value in the Source CI object ID box.

💐 Direct Link Parameters – Show View Topology Page

This wizard page enables you to display the topology map of the selected view and embed it in an external application.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Show view topology) > Finish Page

User interface elements are described below:

UI Element (A-Z)	Description
Show topology of view	 Click to select the required view to be opened by the URL. Opens the View Selector dialog box. Click X to delete the selected view in the Show topology of view box.

🍳 Direct Link Parameters – View Editor Page

This wizard page enables you to create a URL that opens a specific view in the Pattern View Editor in Modeling Studio.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > View Editor) > Finish Page
See also	"Building a Business View" on page 339

User interface elements are described below:

UI Element (A-Z)	Description
View name	 Click is to select the required view to be opened by the URL. Opens the View Selector dialog box. Click to delete the selected view in the View name box.

💐 Direct Link Parameters – Views Selector Page

This wizard page enables you to embed into an external application, the View Selector, that enables you to select, and display a view in that application.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Embedded links > Views Selector) > Finish Page
See also	"Building a Business View" on page 339

💐 Direct Link Parameters – Show View Page

This wizard page enables you to create a URL to a specific view and optionally select a specific query node in that view. When the view opens, the CI you chose is selected in the view. The view opens in IT Universe Manager.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Open in context links > Show view) > Finish Page

UI Element (A-Z)	Description
<left pane=""></left>	A graphic illustration of the selected option.
Advanced pane (visibility)	Hide or display the Advanced pane in IT Universe Manager.
Select CI from view result	 (Optional) Click to select a CI and retrieve its object ID. When the view opens, the CI you chose is selected in the view. ➤ Click to choose the CI you want selected in the target view and retrieve its object ID. Opens the Select CI dialog box. For details, see "CI Selector" on page 163. ➤ Click to delete the object ID for the selected CI in the Select CI from view result box.

UI Element (A-Z)	Description
Selected View	 The target view to be opened by the URL. ➤ Click to select the target view to be opened by the URL. Opens the Select View dialog box. ➤ Click to delete the selected view in the Selected view box.
View mode	 The view options are: View Topology. Displays an entire layer within a view. Related in View. Displays the selected CI and its immediate neighbors within the current view. Related in CMDB. Displays the selected CI and its immediate neighbors in the RTSM.

💐 Direct Link Parameters – Start in Mode Page

This wizard page enables you to start the RTSM application at the selected page, for example, in the Modeling Studio page.

Important information	 For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124. Click Finish to close the wizard and create a URL. For details, see "Generate Direct Link Dialog Box" on page 123.
Wizard map	Select Command Page (Open in context links > Start in mode page) > Finish Page

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<left pane=""></left>	A graphic illustration of the selected mode.
Initial mode	Starts the RTSM application in the selected mode.

💐 Finish Page

This is the final page of the Generate Direct Link wizard. Click **Finish** to close the wizard and create a URL. Opens the Generate Direct Link dialog box.

Important information	For general information about the Generate Direct Link wizard, see "Generate Direct Link Wizard" on page 124.
Wizard map	Select Command Page (<open context="" in="" links="" options=""> and <embedded links="" options="">) > Finish Page</embedded></open>

Embedding RTSM Applets Using Direct Links

This chapter includes:

Concepts

- ► Using the Direct Link Functionality to Embed RTSM Applets on page 144
- ► RTSM Applet Tag Overview on page 145

Reference

► Direct Link Operation Flow on page 147

Note: This chapter is relevant to integration developers only.

Concepts

Using the Direct Link Functionality to Embed RTSM Applets

You can directly embed RTSM applets into external applications using a direct link. A direct link is a URL that you create using the Direct Links wizard. For details, see "Generate Direct Link Wizard" on page 124.

You can embed RTSM applets in the following ways:

➤ Using the URL itself to display RTSM content in an external application. For example, you can create a URL in the Direct Links wizard to display the properties of a certain CI. The login page opens if you are not already logged into HP Business Service Management or if Lightweight Single Sign-On Authentication Support (LW-SSO) is not enabled for HP Business Service Management.

Note: Using the URL to enable the integration requires opening the link in an IFrame or a new window. This does not allow you to manage the resulting RTSM applet using Javascript due to cross-site scripting issues. For example, if you use a URL that displays the properties of a specific CI using the object ID, you cannot use the same URL to display the properties of another CI.

➤ Using the RTSM applet tag to embed the RTSM applet in an external application. This enables integration developers to display a part of the HP Business Service Management user interface as part of their own application. In addition, this enables interaction with the embedded HP Business Service Management user interface using Javascript.

🗞 RTSM Applet Tag – Overview

The RTSM Applet tag creates the environment needed for the RTSM applet to run (HTML, Javascript, and server session parameters). The code behind the tag can log into the HP Business Service Management server in one of the following cases:

- ➤ The login parameters are specified and the user is not already logged in (or if Lightweight Single Sign-On Authentication Support (LW-SSO) is not enabled for HP Business Service Management).
- ► The clear session parameter is true.

Once a user session is established, the tag continues to write the required applet environment (HTML and Javascript code) to the result of the JSP processor. The resulting HTML page includes the required Javascript code to load the RTSM applet from the specified server. On error, the specified error string is printed to the page. This string can be customized using the **userErrorMessage** parameter and may include HTML elements and HTML wrapped Javascript code to initiate error handling scenarios.

Example of the Usage of an RTSM Applet Tag

```
<ucmdb:ucmdb_applet
serverConnectionString="http://labm3mam17.devlab.ad:8080"
serverType="UCMDB"
directLinkParameters="initViewName=NetworkTopology"
userName="user-name"
userPassword="password"
customerld="1"
encoded="false"
printDebugLogs="true"
userErrorMessage="This is your general error"
navigation="false"
clearSessionCookies="false"
command="ShowCISelector"/>
```

Caution: You retrieve the **directLinkParameters** from the URL created in the Direct Links wizard. Insert the values for each parameter in the tag as displayed. If the URL contains values for parameters not displayed above, copy them into the **directLinkParameters** line of the tag. For details on how to create a direct link, see "Generate Direct Link Wizard" on page 124.

The RTSM applet tag is located at <**HP Business Service Management>\odb\deploy\ucmdb-ui\WEB-INF\tags\ucmdb_applet.tag** on the Gateway Server machine.

You can copy the RTSM applet tag to an external application server. The RTSM applet tag requests the login data from the HP Business Service Management server provided that:

- ➤ The external application server can communicate with JSP tags.
- ➤ The HP Business Service Management server is accessible to the external application server and to the browser.

Reference

💐 Direct Link Operation Flow


This section describes different scenarios in which direct links are used to embed RTSM applets into external machines.

This section includes the flow descriptions:

- ► "Regular Login" on page 148
- ➤ "An Embedded RTSM Applet Using a Direct Link URL" on page 150
- ➤ "An Embedded RTSM Applet Using an RTSM Applet Tag" on page 152

Regular Login

This flow describes a regular login to the HP Business Service Management server. It serves as a base reference for the direct link flows.



- **1** The user enters the direct link URL (into the browser) to log into the HP Business Service Management server.
- **2** The browser sends the login request to the HP Business Service Management server.
- **3** The server checks the user credentials and creates a user session if required.
- **4** The server returns the requested first page of HP Business Service Management.


Note: This can be any page. For this flow, we assume that it is the **Admin** > **RTSM Administration** > **Modeling** page in which the RTSM applet is loaded.

- **5** The browser loads the Java virtual machine (JVM) with the code base location parameter (which instructs the JVM from where to load the RTSM applet files) as the HP Business Service Management server.
- **6** RTSM applet files (jars) and data are transferred between the HP Business Service Management server and the JVM loaded in the browser.

At this point, the RTSM applet is loaded and regards HP Business Service Management as the server with which it should communicate.

An Embedded RTSM Applet Using a Direct Link URL

This flow shows how to use the direct link to open an RTSM applet (opened to a specified context) in a new browser frame.




- **1** The external application has a page that needs to show the RTSM applet.
- **2** The returned page includes a directive to open the direct link in an IFrame or new browser window.
- **3** The browser opens a new frame (IFrame or new window) with the direct link as the frame URL.
- **4** The new frame sends the direct link to the HP Business Service Management server.

- **5** If the user is not already logged into HP Business Service Management, or if Lightweight Single Sign-On Authentication Support (LW-SSO) is not enabled for HP Business Service Management, HP Business Service Management displays the login page and waits for the user to enter credentials and click the login button.
- **6** The user session is created, if required.
- **7** The HP Business Service Management server returns a page that includes the directive to load the RTSM applet.
- **8** The browser processes the page. When the browser encounters the directive to load the RTSM applet, it starts the JVM. The browser then passes the needed parameters to the JVM, including the HP Business Service Management server location as "code base."
- **9** RTSM applet files (jars) and data are transferred between the HP Business Service Management server and the JVM loaded in the browser.

Caution: The HP Business Service Management server must be accessible from the browser machine.

An Embedded RTSM Applet Using an RTSM Applet Tag

This flow shows how to use the RTSM applet tag in conjunction with direct links to embed the RTSM applet (opened to a specified context) in an external application page.



- **1** The RTSM applet tag is included in the processed JSP in the external application.
- **2** The RTSM applet tag uses the parameters given to it to create an HTTP/ HTTPS connection to the HP Business Service Management server and requests the applet HTML snippet code.

- **3** If the user is not already logged in, the parameters from the RTSM applet tag are used (see the tag itself for reference information regarding this step). If login fails, the RTSM applet tag returns an error message, either the preset one or the one specified in the RTSM applet tag parameters.
- **4** The HP Business Service Management server returns the HTML snippet code (with embedded Javascript) that loads the RTSM applet. The external application can now incorporate this snippet code into the page, and send the page to the browser.
- **5** The external application sends the complete page that includes the HTML snippet code to the browser.
- **6** The browser processes the page. When the browser encounters the HTML snippet code that loads the RTSM applet, the JVM is started. The browser then passes the needed parameters to the JVM, including the HP Business Service Management server location as "code base".
- 7 RTSM applet files (jars) and data are transferred between the HP Business Service Management server and the JVM loaded in the browser.

Caution: The HP Business Service Management server must be accessible from the browser machine as well as the external application machine.

Chapter 4 • Embedding RTSM Applets Using Direct Links

5

Working with the CI Selector

This chapter includes:

Concepts

► CI Selector Overview on page 156

Tasks

- ➤ Display a View in Browse Mode on page 157
- ► Search for CIs in Search Mode on page 157
- ► Modify CI Selector Display Options on page 159

Reference

► CI Selector User Interface on page 161

Troubleshooting and Limitations on page 174

Concepts

🚴 CI Selector Overview

Note: The CI Selector was known as View Explorer in earlier versions of HP Business Service Management.

The CI Selector presents the elements of the IT universe model in HP Business Service Management through the medium of views. HP Business Service Management displays the CI Selector in the left pane of IT Universe Manager and the Modeling Studio.

When you select a view in the CI Selector, the configuration items (CIs) contained in the view are displayed in a hierarchical tree format according to the relationships defined between the CIs. A view may be empty if no CIs were found matching the TQL query. For details on views, see "View Formats" on page 338.

You can use the CI Selector to select views and to locate CIs. You can select a view and browse through the list of CIs, or you can search for a specific CI by name or by CI type. You can also save the search criteria for future use.

For information on the components of the CI Selector, see "CI Selector User Interface" on page 161.

Tasks

...

膧 Display a View in Browse Mode

When the CI Selector is set to **Browse** mode, you can display the contents of a selected view. For details on the CI Selector user interface in Browse mode, see "Browse Views Mode" on page 163.

1 Prerequisites

In the CI Selector pane, select Browse Views mode.

2 Select a View to Display

Click the ellipsis button to open the View Selector dialog box and select the view you want to display. The name of the selected view is shown in the **View** box. The CIs in the view appear in the CI tree in the lower part of the CI Selector pane. The view remains selected when you move to other applications in HP Business Service Management.

膧 Search for Cls in Search Mode

The CI Selector search tool enables you to locate a specific CI. The search is executed on the entire RTSM. For details on the CI Selector search tool user interface, see "Search CIs Mode" on page 167.

This task includes the following steps:

- ► "Prerequisites" on page 158
- ► "Search by CI Name" on page 158
- ➤ "Search by Configuration Item Type" on page 158
- ▶ "Run the Search and Sort the Results" on page 158
- ► "Run an Advanced Search" on page 159

Prerequisites

In the CI Selector pane, select **Search CIs** mode and select the **Simple** tab.

Search by CI Name

To search for CIs by name, enter a string in the **CI Name** box, representing the name of the CI, or part of the name. The search returns all CIs that contain the entered string somewhere in their names (within the boundaries of the other search criteria that you define).

Note: The search by CI name option is not case sensitive.

Search by Configuration Item Type

You can search for CIs using the **CI Type** box. This search returns CIs of the type specified in the **CI Type** box.

Click the ellipsis button and select the required CI type. You cannot manually enter a CIT in the **CI Type** box.

After defining a CI in the **CI Type** box, HP Business Service Management remembers your selection until you move to a different application, or until you define a different value.

Run the Search and Sort the Results

Run the search. The results appear in the lower part of the CI Selector pane, showing the CI name and type for each entry. You can sort the search results by clicking the appropriate heading.

When you select the required CI from the results list, the right pane displays details for the CI you selected, in the context in which you are working. To see a CI in the context of its view, right-click the CI and select **Locate CI in View**. The CI Selector reverts to Browse mode and displays the view that contains the CI, with the CI selected in the view tree.

When you select a CI in the search results, the CI appears in the topology map with its related CIs in the RTSM.

....

Optionally, save the search criteria by clicking the **Save** button and entering a name for the search. For details, see "Save Search Criteria Dialog Box" on page 173.

Run an Advanced Search

You can select the **Advanced** tab for other search options. For details on the CI Conditional search, see "CI Conditional Search Dialog Box" on page 161. For details on the Running Software search, see "Running Software Search Dialog Box" on page 172.

膧 Modify CI Selector Display Options

You can modify the display options for the CI Selector. These options are configured in the Infrastructure Settings Manager.

Caution: Modifying certain settings in the Infrastructure Settings Manager can adversely affect the performance of HP Business Service Management. Do not modify settings without first consulting HP Software Support or your HP Professional Services representative.

1 Prerequisites

Access the Infrastructure Settings Manager by selecting Admin > Platform > Setup and Maintenance > Infrastructure Settings.

2 Modify Selected Settings

The following settings under RTSM - General properties can be modified:

- Immediate Children Count. Number of children immediately displayed when expanding their parent's query node in the CI Selector.
- ► Maximal Children Count. Maximum number of children displayed under their parent's query node in the CI Selector.

- ► Maximal search results size. Maximum number of CMDB instances that can be returned in one search operation.
- Recently Used Views List size. Maximal number of recently used views to store per user.

Reference

💐 CI Selector User Interface

This section includes (in alphabetical order):

- ► CI Conditional Search Dialog Box on page 161
- ► CI Selector on page 163
- ► Organize Searches Dialog Box on page 171
- ► Running Software Search Dialog Box on page 172
- ► Save Search Criteria Dialog Box on page 173

🂐 CI Conditional Search Dialog Box

This dialog box enables you to search for CIs by attribute conditions, by related CIs, and by attribute conditions of related CIs.

To access	In the CI Selector, select the Advanced tab in Search
	mode and click the ellipsis button next to CI Conditional Search.
	Sedien:

User interface elements are described below:

UI Element (A-Z)	Description
+	Click to add an attribute condition.
×	Click to delete a selected row.
	Click to move a selected row up.
tt.	Click to move a selected row down.

UI Element (A-Z)	Description
	Click to display a preview of the attribute condition list.
Attribute name	Select an attribute from the drop-down list.
CI Name	Enter a CI name for which to search.
СІ Туре	Enter the CI type for which to search.
Operator	Select an operator from the drop-down list.
Related CI Name	Enter the name of a related CI for the search.
Related CI Type	Click the ellipsis button to select a CI type from the tree for a search by related CI.
Relationship Type	Click the ellipsis — button to select a relationship from the tree for a search by related CI.
Search by CI conditions	Select to run a search for CIs with the specified conditions.
Search by related CI conditions	Select to run a search for CIs related to CIs with the specified conditions.
Search by related CI criteria	Select to run a search for CIs related to the specified CIs or CI types.
Value	Enter a value for the attribute condition.

💐 CI Selector

To access	Appears in the left pane of the IT Universe Manager page and the Modeling Studio.
Important information	The CI Selector consists of two functional formats: Browse Views mode and Search CIs mode.
	➤ In Browse Views mode, you can search for and display a view, and browse through the view to locate a particular CI. You can also perform operations on the CI from a shortcut menu.
	➤ In Search CIs mode you can search for one or more CIs in the RTSM by name or by CI type.
	Note: Many of the features of the CI Selector are only relevant in the RTSM and not in other HP Business Service Management modules.
Relevant tasks	"Display a View in Browse Mode" on page 157
	"Search for CIs in Search Mode" on page 157

This feature enables you to select views and to locate CIs.

Browse Views Mode

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
	Click to refresh the data content of the hierarchical tree structure that may have been modified by other users.
	Click Show Template Parameters to open the Template Parameter Values dialog box, which enables you to edit the parameters of the selected template. Note: This button is only active when a template is selected.
	Click Add selected Cls to model/view to add the selected Cls to the current model or view. Note: This button only appears in the Modeling Studio.

UI Element (A-Z)	Description
(p	Click Add to model as related CIs to add the selected CI to the model as a related CI.
	Note: This button is only active in the Model Editor of the Modeling Studio.
69	Click Open selected model in a new tab to open the selected model in the Model Editor.
	Note: This button is only active when a model is selected in the Modeling Studio.
₿	Click Show models containing selected Cl to display a list of models containing the selected CI.
	Note: This button only appears in the Modeling Studio.
—	In IT Universe Manager, this represents Show View Definition , which takes you directly to the view definition in the Modeling Studio for the current view.
	In the Modeling Studio, this represents Open selected view , which opens the selected view in the Editor pane.
L	Click Show views containing selected Cl/model to display a list of views containing the selected CI or model.
	Note: This button only appears in the Modeling Studio.
1	Click Generate view for selected model to open the Creating New View dialog box which enables you to build a view based on the selected model.
	Note: This button is only active when a model is selected in the Modeling Studio.
	Click Show Discovery and Changes Summary to rediscover all the CIs in a selected view by manually starting the DFM jobs that originally discovered them. For details, see "Show Discovery Status and Changes Dialog Box" on page 298.
	Note: This button only appears in IT Universe Manager.

UI Element (A-Z)	Description
69	Click Generate Direct Link to View to create a direct link to the view using the Direct Links wizard.
	Note: This button only appears in IT Universe Manager.
8	Choose the export format for the browse results. The available options are:
	► Excel. The table data is formatted as an .xls (Excel) file that can be displayed in a spreadsheet.
	 PDF. The table data is exported in PDF format. Note: When exporting to PDF, select a reasonable number of columns to display to ensure that the report is legible.
	 RTF. The table data is exported in Rich Text Format. CSV. The table data is formatted as a commaseparated values (CSV) text file that can be displayed in a spreadsheet.
	Note: For the CSV formatted table data to display correctly, the comma (,) must be defined as the list separator. In Windows, to verify or modify the list separator value, open Regional Options from the Control Panel, and on the Numbers tab ensure that the comma is defined as the List Separator value.
	 XML. The table data is formatted as an XML file that can be opened in a text or XML editor. Tip: To extract HTML code from the report:
	 Save the file as HTML Open the file in an HTML editor Copy the relevant table into the target file

UI Element (A-Z)	Description
	Click the Snapshot button to work with snapshots. The following options are available:
	Save Snapshot. Select to open the Save Snapshot dialog box, which enables you to save a snapshot of the view. For details, see "Save Snapshot Dialog Box" on page 296.
	 Compare Snapshots. Select to run the Compare Snapshots Report. For details, see "Compare Snapshots Report" on page 318.
	 Schedule Snapshot. Select to open the Schedule Job dialog box. For details, see "Schedule Snapshot Dialog Box" on page 327.
	 Show Scheduled Snapshot Jobs. Select to open the Job List dialog box. For details, see "Job List Dialog Box" on page 325.
	Note: This button only appears in IT Universe Manager.
	Click View Based Report to display the topology report for the selected view.
	Note: This button only appears in IT Universe Manager.
	Click Asset Report to open the Asset report for the selected view. For details, see "Asset Report" on page 311.
	Note: This button only appears in IT Universe Manager.
•••	Click the ellipsis button to the right of the View box, to open the View Selector dialog box. You can browse through the folder tree to locate the view you want to display.
	Enables you to move to the next or previous result of the search for the string entered in the Find box.
<cls></cls>	The CIs contained in the currently selected view.
<tooltip></tooltip>	Hold the cursor over a CI to display a tooltip with the relevant CI type.

UI Element (A-Z)	Description
Find	Enter a CI name or a portion of a CI name in the Find box to locate a CI in the CI tree.
View	The View box displays the currently selected view. To select a view to display, click the down arrow on the right side of the View box; this displays an abridged list of views, containing the most recently accessed views. Click the arrow at the bottom of the list to scroll through the entire list. The recently accessed views appear at the top of the drop-down, above the dividing line. The complete list of views appears below the line. Alternatively, place the cursor in the list and begin typing the view name. HP Business Service Management completes the view name, if the first few letters that you type match an existing entry. If the names of several views begin with those letters, all matching views are displayed in the list.

Search Cls Mode

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
	Click Show Search Results in Table to open a separate pane with a table of the CIs in the search results. Note: This button only appears in IT Universe Manager.
>	Click Add selected Cls to model/view to add the selected Cls to the current model or view. Note: This button only appears in the Modeling Studio.
¢ĵ	Click Add to model as related CIs to add the selected CI to the model as a related CI. Note: This button is only active in the Model Editor of the Modeling Studio.

UI Element (A-Z)	Description
69	Click Open selected model in a new tab to open the selected model in the Model Editor.
	Note: This button is only active when a model is selected in the Modeling Studio.
	Click Show models containing selected Cl to display a list of the models containing the selected CI.
	Note: This button only appears in the Modeling Studio.
L.	Click Show views containing selected Cl/model to display a list of the views containing the selected CI or model.
	Note: This button only appears in the Modeling Studio.
	Click Generate view for selected model to open the Creating New View dialog box which enables you to build a view based on the selected model.
	Note: This button is only active when a model is selected in the Modeling Studio.

UI Element (A-Z)	Description
£	Choose the export format for the search results. The available options are:
	 Excel. The table data is formatted as an .xls (Excel) file that can be displayed in a spreadsheet. PDF. The table data is exported in PDF format. Note: When exporting to PDF, select a reasonable number of columns to display to ensure that the report is legible. RTF. The table data is exported in Rich Text Format. CSV. The table data is formatted as a commaseparated values (CSV) text file that can be displayed in a spreadsheet. Note: For the CSV formatted table data to display correctly, the comma (,) must be defined as the list separator value, open Regional Options from the Control Panel, and on the Numbers tab ensure that the comma is defined as the List Separator value. XML. The table data is formatted as an XML file that can be opened in a text or XML editor. Tip: To extract HTML code from the report: Save the file as HTML Open the file in an HTML editor Copy the relevant table into the target file
	Click to open the Organize Searches dialog box, where you can edit or delete searches from the list of saved
*	searches. Click to collapse or expand the search criteria area.
Q	Click to run the search. The search results are displayed in the lower part of the CI Selector pane.
	Click to save the current search criteria for future use.
	Enables you to move to the next or previous result of the search for the string entered in the Find field.

UI Element (A-Z)	Description
<search results=""></search>	After you run the search, the results are listed in the lower part of the CI Selector pane. The results are shown in two columns:
	► Name. Contains the name of the CI.
	► CI Type. Contains the CI type of the CI.
	If the CI or view name is abbreviated, hold the pointer over the entry to see the full name. You can sort the search results by clicking the appropriate heading.
Advanced tab	The following detailed search options are available:
	 Cl Conditional Search. Enables you to search for CIs by attribute conditions, by related CIs, and by attribute conditions of related CIs. Running Software Search. Enables you to search for hosts by the applications running on them and for
	applications by the host on which they are running.
	For each of the searches, click the ellipsis button to open the search dialog box. After running a search, click the Save button to save the search for future use.
CI Name	To search for a CI by name, enter the name of the CI for which to search.
СІ Туре	To search for CIs by CI type, click the ellipsis button to select a CI from the Select Configuration Item Type dialog box.
Find	Enter a CI name or a portion of a CI name in the Find box to locate a CI in the search results.
Searches	Select a search from the drop-down list of saved searches.
Search results count	The Search results count below the Find box displays the total number of CIs found in the search.
Simple tab	The Simple tab includes the standard search functionality. Click the Advanced tab for more detailed search options.

Shortcut Menu Options

Menu Item	Description
<it manager<br="" universe="">shortcut menu options></it>	The regular shortcut menu for the topology map in IT Universe Manager is also available from the CI Selector. For details on the menu options, see "IT Universe Manager Shortcut Menu" on page 283.
Add	Adds the selected CI to the current model or view. Note: This feature only appears in the Modeling Studio.
Add to model as related Cls	Adds the selected CI as a related CI to the current model. Note: This feature only appears in the Modeling Studio.
Generate view for selected model	Select to create a view based on the current model. The Creating New View dialog box opens which enables you to select a perspective to apply.
	Note: This feature only appears in the Modeling Studio.
Open selected model in a new tab	Opens the selected model in a new tab in the Model Editor.
	Note: This feature only appears in the Modeling Studio.
Show containing models	Select Show models containing selected CI to display a list of the models containing the selected CI.
	Note: This option only appears in the Modeling Studio.
Show containing views	Select Show views containing selected CI/model to display a list of the views containing the selected CI or model.
	Note: This option only appears in the Modeling Studio.

Q Organize Searches Dialog Box

This dialog box enables you to edit or delete searches from the list of saved searches.

To access	Click the Manage the list of saved searches 🚰 button
	in the CI Selector.

UI Element (A-Z)	Description
0	Click to edit the selected search. For simple searches, the CI Simple Search dialog box opens, which enables you to edit the name and type of the CI. For CI Conditional searches, the CI Conditional Search dialog box opens.
×	Click to delete the selected search.
**	Click to expand the search tree.
16	Click to collapse the search tree.
<searches tree=""></searches>	Displays all the saved searches in tree format.
Find	Enter a search name or a portion of a search name in the Find box to locate it in the list.
Find Next	Click to go to the next occurrence of the selected search phrase in the list.
Find Previous	Click to go to the previous occurrence of the selected search phrase in the list.

User interface elements are described below:

💐 Running Software Search Dialog Box

This dialog box enables you to search for hosts by the applications running on them and for applications by the host on which they are running.

In the CI Selector, select the Advanced tab in Search
mode and click the ellipsis button next to Running
Software Search.

User interface elements are described below:

UI Element (A-Z)	Description
Host name	Enter the name of the node for which you are searching.
Running Software	Select a running software CI from the drop-down list. Note: The drop-down list may not display an accurate list of available running software CI types (only the option Any appears). In this event, perform the Host name search only.
Search for	Select Running Software or Node . Note: To search for a running software CI running on a specific node, enter a node name, select the required running software CI and search for it.

💐 Save Search Criteria Dialog Box

This dialog box enables you to save the current search criteria for future use.

To access	Click the Save 🛗 button from Search mode in the CI
	Selector.

User interface elements are described below:

UI Element (A-Z)	Description
Existing Queries	Displays a list of existing searches in tree format.
Name	Enter a name for the current search.
Find	Enter a search name or a portion of a search name in the Find box to locate it in the list.
Find Next	Click to go to the next occurrence of the selected search phrase in the list.
Find Previous	Click to go to the previous occurrence of the selected search phrase in the list.

Troubleshooting and Limitations

This section describes troubleshooting and limitations for the CI Selector.

Unavailable Views and Cls

The View list in the CI Selector may not display all views in the RTSM, or it may not display the contents of a view, for any of the following reasons:

- ➤ The View list includes only the views for which you have the necessary permissions. Similarly, Search mode is only available if you have CI Search permission. To set permissions, select Admin > Platform > Users and Permissions, select a user or a group and select Permissions. For more information, see "How to Assign Permissions" in *Platform Administration*.
- ➤ Views that are currently inactive appear in red in the View list, but they cannot be selected. In IT Universe Manager, inactive views appear in faded text.
- ➤ Out-of-the-box views for which you do not have a license may appear in the View list, but these views do not contain CIs. For information on the out-of-the-box views, see "Predefined Folders and Views" on page 343.

Note: After deleting one or more query nodes from a TQL query, it can take time for changes to be updated to the view; meanwhile, the removed CIs appear in the view. If you select one of these CIs before it is updated, an error message is displayed. Click the **Refresh** button to update the view.

Working with Topology Map

This chapter includes:

Concepts

- ► Topology Map Overview on page 176
- ► Handling Large Views on page 177

Reference

► Topology Map User Interface on page 178

Concepts

🚴 Topology Map Overview

The Topology Map provides a graphical display of a view. All the CIs in a given layer of the view are represented by icons and the connecting lines represent relationships. You can select a CI in the Topology Map or in the CI Selector in the left pane. You can also drill down in the CI Selector to display different layers of the view in the Topology Map.

The label of a CI appears under the icon. You can set the maximum number of characters per line and the maximum number of lines in a CI label in the User Preferences dialog box under **General**. For details, see "User Preferences Dialog Box" on page 102.



If a CI icon appears with a downward arrow icon in the Topology Map, there is an additional CI layer beneath it, created by the hierarchy set for the view. You can click the arrow to display the CIs contained in the sublayer.

The topology map is automatically updated dynamically with changes in the IT Universe data, such as new CIs discovered by the Data Flow Management process.

The toolbar and Main Menu above the Topology Map enable you to zoom in, change the layout of the Topology Map, and print the Topology Map. Additional functionality is available from the shortcut menu by rightclicking a CI in the Topology Map or in the CI Selector.

🚴 Handling Large Views

The Topology Map cannot display a view with more than 900 CIs in a single layer. When you select a view which contains a layer with more than this number of CIs, the Topology Map appears empty. A layer with more than 900 CIs can be displayed in a table in Text mode.

To display large views in the Topology Map, use one of the following methods:

- ➤ Reduce the TQL query results by redefining the view in the Modeling Studio. For details, see "Change Query Node/Relationship Type Dialog Box" on page 381.
- Define a different hierarchy for the view to redistribute the CIs among the view's layers. For details on defining hierarchy, see "Setting the View Hierarchy" on page 340.
- Reset the maximum number of CIs allowed in the configuration parameters. Select the Max Object Count GUI for TS parameter under RTSM - Viewing Settings in the Infrastructure Settings Manager. However, be aware that increasing the maximum number of CIs per layer may significantly slow down the redrawing of the Topology Map.

To modify the setting, select Admin > Platform > Setup and Maintenance > Infrastructure Settings > Foundations > RTSM. Locate Max Object Count GUI for TS and change the value to the required number.

Reference

💐 Topology Map User Interface

This section includes (in alphabetical order):

- ► Export Map to Image Dialog Box on page 178
- ► Layout Properties Dialog Box on page 180
- ► Main Menu on page 197
- ► Print Dialog Box on page 198
- ► Print Preview Dialog Box on page 199
- ► Print Setup Dialog Box on page 199
- ► Toolbar Options on page 201
- ► Topology Map Sidebar on page 210

💐 Export Map to Image Dialog Box

This dialog box enables you to save a topology map to a file.

To access	From a topology map, select Operations > Export Map to Image.
Relevant tasks	"Print and Save a Topology Map to File" on page 258

UI Element (A-Z)	Description
Actual Size	Save the view so that the graph node sizes are at maximum.
Current Zoom Level	Save the view as you see it on the topology map. For example, if you have used the Interactive Zoom mode to decrease the view magnification, the graph nodes also appear smaller in the saved view. For details, see "Interactive Zoom" on page 204.
Custom	Specify the size of the view you want to save in the Width and Height boxes.
File Name	Specify the required file name and location (or click Browse to search for the file and location).
Fit in Canvas	Expand or shrink the view so that it fits in the pane.
Image Quality	The quality of the printed map. Select High , Medium , or Low .
Selected Objects Only	Saves only the graph nodes/CIs and their relationships that you selected in the map.
Туре	Select the required file format.
Visible Window Only	Saves only the part of the graph that appears in the pane.

User interface elements are described below:

💐 Layout Properties Dialog Box

This dialog box enables you to customize the layout of a specific layer in a view, to achieve the clearest presentation possible and to better understand and monitor the managed data.

To access	Select Layout > Layout Properties.
Important information	You define the layout of a view's layers by assigning logical positions for the graph's nodes and relationships that appear in a layer. You customize the layer layouts by modifying the default values.
	You set layout definitions for a specific layer only. The definitions cannot be saved for a different layer or a different view. Parameter values are in pixels.

Global Tab

This area enables you to define global layout parameters.

To access	Click the Global tab in the Layout Properties dialog box.
Important information	The Global tab enables you to define global settings for the layout.

User interface elements are described below:

UI Element (A-Z)	Description
Drawing Fitting	Select one of the following options for fitting the layout:
	Fit to Canvas. Fit the layout to the canvas on the screen.
	► Fit for Printing. Fit the layout to a page for printing.
	► No Fitting. Do not change the layout.

UI Element (A-Z)	Description
Labeling	Select Perform Labeling to ensure that the labels appear when the layout is redrawn. If this field is not selected, labels do not appear in the redrawn layout.
Style	Select Apply Style Deeply to apply the layout selected to all nested layers of the topology map.

All Styles Tab

To access	Click the All Styles tab in the Layout Properties dialog box.
Important information	The All Styles tab enables you to define general layout parameters for disconnected graph nodes and connected components.
	 A disconnected graph node is a node that is not connected to any other graph node.
	 A disconnected component is a component that is not connected to any other component. It contains a set of graph nodes that can be connected to each other.
	This illustrates a connected component with five graph nodes:
	This illustrates a connected component with two graph nodes:
	This illustrates four disconnected components, each made up of a single, disconnected graph node:

UI Element (A-Z)	Description
Components	The spacing between the components in a disconnected graph consists of both a constant value and a proportional value based on the sizes of the components.
	Select Detect Components to view the disconnected components. You can specify that all components be laid out together or individually, regardless of the other components. If the grouping for components is selected, each component is laid out, and the resulting components are packed together.
	When Detect Components is selected, enter values for the following settings:
	 Constant Spacing. Set constant spacing (horizontal and vertical) around each disconnected component. Default value: 20
	 Proportional Spacing. Set spacing (horizontal and vertical) that is proportional to the size of the component around each disconnected component. Default value: 0.05

UI Element (A-Z)	Description
Disconnected Graph Nodes	The spacing between the graph nodes in a disconnected graph consists of both a constant value and a proportional value based on the sizes of the graph nodes.
	Select Detect Disconnected Graph Nodes to view the disconnected graph nodes. You can specify that disconnected graph nodes be grouped into one component or laid out individually.
	When Detect Disconnected Graph Nodes is selected, enter values for the following settings:
	 Constant Spacing. Set constant spacing (horizontal and vertical) around each disconnected graph node. Default value: 20
	 Proportional Spacing. Set spacing (horizontal and vertical) that is proportional to the size of the component around each disconnected graph node. Default value: 0.05
Margin Spacing	Enter values for the right, left, top, and bottom margin spacing for the layout.

Circular Tab

To access	To access: Click the Circular tab in the Layout Properties dialog box.
Important information	The Circular tab enables you to group a graph's nodes into groups or clusters based on the grouping options you select. It is particularly suited for visualizing ring and star network topologies, and for link analysis.

UI Element (A-Z)	Description
Clustering	Set the values for the following settings:
	 Cluster Size Factor. Specifies the ratio between the average cluster size and the number of clusters. The size of a cluster is defined as the sum of the weights of all graph nodes in the cluster. You can assign a weight value to each graph node. Min Number of Clusters. The minimum number of clusters in a layer. Max Number of Clusters. The maximum number of clusters in a layer.
Cluster Layout Style	Displays clusters either in a symmetric or circular layout style.
	Select one of the following options:
	 Symmetric. Displays clusters in a symmetric layout style.
	► Circular. Displays clusters in a circular layout style.

UI Element (A-Z)	Description
Layout Quality	Adjusts the quality of the layout produced to fit your application's needs. The quality reflects the number of steps or the method used to produce the layout. For example, high quality is sharper but takes more time to set the layout.
	Select one of the following options:
	 Draft. Produces faster results (faster than Medium and Proof).
	Medium. Produces a result that is a combination of Draft and Proof, that is, it produces a more accurate graph layout than Draft, but not as accurate as Proof.
	 Proof. Produces a more refined result but takes more time.
	Note: The differences between the speed and resulting layout of each quality setting varies depending on the nature of the graph being laid out. You can try each option to determine which works best for you.

UI Element (A-Z)	Description
Spacing	Sets the spacing around each graph node within the same cluster and between clusters.
	Enter values for the following settings:
	Between Graph Nodes. Sets the spacing around each graph node within the same cluster. The larger the spacing, the more graph nodes there are on the cluster boundary.
	Default value: 50
	This illustration shows smaller graph node spacing.
	This illustration shows larger graph node spacing.
	► Between Clusters. Sets the spacing between clusters.
	Default value: 50
	This illustration shows smaller cluster spacing.
	This illustration shows larger cluster spacing.

To access	Click the Hierarchical tab in the Layout Properties dialog box.
Important information	The Hierarchical tab shows the precedence relationships that can represent organizational or information management system dependencies, as well as process models, software call graphs, and work flows. The hierarchical layout emphasizes dependencies by placing the graph nodes at different levels.

Hierarchical Tab

UI Element (A-Z)	Description
Backward Edges	Specifies how backward relationships are displayed in the hierarchical layout.
	Select one of the following options:
	 Minimize Backward Edges. Sets the number of backward relationships displayed in a layer to a minimum. Optimize for Feedback Flow. Sets the number of backward relationships displayed in a layer to a maximum. This mode is more appropriate for flow charts.
Horizontal Spacing	Enables you to set the minimum horizontal distance between two neighboring graph nodes at each level.
	Enter values for the following settings:
	 Between Graph Nodes. Sets a horizontal space around each graph node in the layer. Default value: 28
	 Between Edges. This setting is available only when you select Routing > Orthogonal. It sets a horizontal space between edges in the graph. Default value: 12

UI Element (A-Z)	Description
Layout Quality	Adjusts the quality of the layout produced to fit your application's needs. The quality reflects the number of steps or the method used to produce the layout. For example, high quality is sharper but takes more time to set the layout.
	Select one of the following options:
	► Draft . Produces faster results (faster than Medium and Proof).
	Draft
	 Medium. Produces a result that is a combination of Draft and Proof, that is, it produces a more accurate graph layout than Draft, but not as accurate as Proof. Proof. Produces a more refined result but takes more time.
	Note: The differences between the speed and resulting layout of each quality setting varies depending on the nature of the graph being laid out. You can try each option to determine which works best for you.

UI Element (A-Z)	Description
Level Alignment	Enables you to set the way graph nodes are vertically aligned.
	Select one of the following options:
	➤ Top. This illustration shows that the top of the graph nodes at the same level of the hierarchy are aligned.
	➤ Center. This illustration shows that the center of the graph nodes at the same level of the hierarchy are aligned.
	 Bottom. This illustration shows that the bottom of the graph nodes at the same level of the hierarchy are aligned.

UI Element (A-Z)	Description
Orientation	Enables you to set the orientation of the hierarchy. Select one of the following options:
	 Top to Bottom. The children are located above the parent. Left to Right. The children are located to the left of the parent. Bottom to Top. The children are located below the parent. Right to Left. The children are located to the right of the parent.
Orthogonal Routing - Fix Node Sizes	This setting is available only when you select Routing > Orthogonal . Maintain the size of a graph node. Clear this option if you want the layout to increase the size of a graph node, if it is necessary to maintain the specified relationship spacing, when more than one relationship is attached to the same side of the graph node.
Polyline Routing - Spacing Between Bends	This setting is available only when you select Routing > Polyline . Polyline routing routes edges (connecting lines) as one or more straight line segments with arbitrary angles. Path nodes are added automatically to prevent the edges (connecting lines) from overlapping. Default Value: 12
Routing	 Select the type of routing for the layout. The available options are: Orthogonal Polyline

UI Element (A-Z)	Description
Undirected Layout	Edge direction is not used to build the levels of the hierarchical drawing.
Variable Level Spacing	Variable level spacing adjusts the spacing between pairs of neighboring levels according to the density of edges between the levels.
	If the drawing's edges are orthogonally routed, this ensures the desired vertical spacing between horizontal edges (in a top-to-bottom or bottom-to-top layout) routed between levels.
	If the routing is polyline, variable level spacing makes it easier to distinguish among edges in very dense drawings.
Vertical Spacing	Enables you to set the minimum vertical distance between two neighboring graph nodes on different levels.
	Enter values for the following settings:
	 Between Graph Nodes. Sets a vertical space around each graph node in the level. Default value: 28
	 Between Edges. This setting is available only when you select Routing > Orthogonal. It sets a vertical space between edges in the graph. Default value: 12

Orthogonal Tab

To access	To access: Click the Orthogonal tab in the Layout Properties dialog box.
Important information	The Orthogonal tab enables you to set orthogonal layout route relationships horizontally and vertically. This results in relationships bending at 90-degree angles only.

UI Element (A-Z)	Description
Fix Node Sizes	Maintain the size of a graph node. Clear this option if you want the layout to increase the size of a graph node if it is necessary to maintain the specified relationship spacing when more than one relationship is attached to the same side of the graph node.
Horizontal Spacing	Enables you to set the minimum horizontal distance between graph nodes.
	Select one of the following options:
	 Between Graph Nodes. Set a horizontal space around each graph node in the layer. Default value: 20
	 Between Edges. Set a horizontal space between elements in the layer. Default value: 12
Layout Quality	Adjusts the quality of the layout produced to fit your application's needs. The quality reflects the number of steps or the method used to produce the layout. For example, high quality is sharper but takes more time to set the layout.
	Select one of the following options:
	► Draft. Set the layout to draft quality.
	► Medium. Set the layout to medium quality.
	► Proof. Set the layout to proof quality.
Vertical Spacing	Enables you to set the minimum vertical distance between graph nodes.
	Select one of the following options:
	 Between Graph Nodes. Set a vertical space around each graph node in the layer. Default value: 100
	 Between Edges. Set a vertical space between elements in the layer. Default value: 20

Symmetric Tab

To access	Click the Symmetric tab in the Layout Properties dialog box.
Important information	The Symmetric tab displays a clear representation of complex networks. The symmetric layout emphasizes the symmetries that may occur in a graph.

UI Element (A-Z)	Description
Layout Quality	Adjusts the quality of the layout produced to fit your application's needs. The quality reflects the number of steps or the method used to produce the layout. For example, high quality is sharper but takes more time to set the layout.
	Select one of the following options:
	➤ Draft. Produces faster results (faster than Medium and Proof).
	Medium. Produces a result that is a combination of Draft and Proof, that is, it produces a more accurate graph layout than Draft, but not as accurate as Proof.
	 Proof. Produces a more refined result but takes more time.
	Note: The differences between the speed and resulting layout of each quality setting varies depending on the nature of the graph being laid out. You can try each option to determine which works best for you.

UI Element (A-Z)	Description
Spacing	Allows you to set constant horizontal and vertical spacing around each graph node in the layer. The value you specify is a guideline for the layout, so that it is possible that the spacing for a particular pair of graph nodes might be different from the one you specified. The larger the graph node spacing, the farther apart the graph nodes are spaced in the final layout.
	Default value: 50
	The following figure illustrates smaller and larger spacing.
	node spacing=75 node spacing=150

To access	Click the Routing tab in the Layout Properties dialog box.
Important information	The Routing tab enables you to produce drawings that leave graph nodes essentially where they are, and reroute the lines orthogonally.

Routing Tab

UI Element (A-Z)	Description
Fix Node Positions	Maintain the position of all the graph nodes in the display. Clear this option for the layout to move the graph nodes if it is necessary to improve the layout. The movement is minimal, avoids overlaps, and minimizes bend points.
Fix Node Sizes	Maintain the size of a graph node. Clear this option if you want the layout to increase the size of a graph node if it is necessary to maintain the specified relationship spacing when more than one relationship is attached to the same side of the graph node.

UI Element (A-Z)	Description
Horizontal Spacing	Enables you to set the minimum horizontal distance between graph nodes.
	Select one of the following options:
	 Between Graph Nodes. Set a horizontal space around each graph node in the layer. Default value: 20
	 Between Edges. Set a horizontal space between elements in the layer. Default value: 12
Vertical Spacing	Enables you to set the minimum vertical distance between graph nodes.
	Select one of the following options:
	 Between Graph Nodes. Set a vertical space around each graph node in the layer. Default value: 20
	Between Edges. Set a vertical space between elements in the layer.
	Default value: 12

💐 Main Menu

To access	Located in the upper left portion of the screen.
Important information	The specific options contained within the Main Menu drop-downs are detailed in "Toolbar Options" on page 201.

This feature contains the options for working with the topology map.

UI Element (A-Z)	Description
Edit	Contains selection options for the topology map.
Editor Item	Contains the topology map shortcut menu options for the current manager.
	Note: This drop-down does not appear in CI Type Manager.
Layout	Contains options for changing the layout of the topology map.
Operations	Contains options for printing or exporting the topology map.
Resources	Contains the left pane shortcut menu options for the current manager.
	Note: This drop-down does not appear in IT Universe Manager, and in CI Type Manager it is called CI Types .
Tools	Contains the User Preferences, Log Configuration, and Screen Capture tools.
View	Enables you to hide or display the different panes of the module.

💐 Print Dialog Box

To access	Select Operations > Print .	
Important information	The results of printing a topology map is similar to a screen capture. Therefore, before printing, it is recommended to:	
	 Define your print settings and arrange the contents of the topology map according to your requirements. For details, see "Print Setup Dialog Box" on page 199. 	
	 Arrange the contents of the topology map for print. You can use the Layout option and Layout Properties. For details about the layout options, see "Layout" on page 205. For details about layout properties, see "Layout Properties Dialog Box" on page 180. 	
Relevant tasks	"Print and Save a Topology Map to File" on page 258	

This dialog box enables you to print the contents of the topology map.

UI Element (A-Z)	Description
Number of copies	Enter the number of copies you want to print.
Properties	Define document properties as required.

💐 Print Preview Dialog Box

This dialog box enables you to preview the content of the topology map before printing.

To access	Select Operations > Print Preview .
Relevant tasks	"Print and Save a Topology Map to File" on page 258

User interface elements are described below:

Menu Item	Description
	Print the map. For details, see "Print Dialog Box" on page 198.
•	Zoom out to view the map.
€	Zoom in to focus on specific details of the map.
2	Fit the complete view in the pane.

💐 Print Setup Dialog Box

This dialog box enables you to define the print settings for a topology map.

To access	Select Operations > Print Setup .
Relevant tasks	"Print and Save a Topology Map to File" on page 258

UI Element (A-Z)	Description
Actual Size	Print the view as it really is.
Color	Set the text color.
Font	Set the required font.

UI Element (A-Z)	Description
Page Setup	Set the printer settings.
Pages	Divide the map into rows and columns and print each section separately. Enter the number of columns and rows in the Page Columns and Page Rows boxes.
Position	Select the position of the caption from the Position list.
Print Background	Print the background behind the view.
Print Border	Print the map with a border. Click Color to select the required border color.
Print Caption	Enter the caption in the text area and click Font to select the required custom font.
Print Crop Marks	Print the crop marks.
Print Current Selection	Print the selected graph nodes and their relationships.
Print Current Window	Print the part of the view that appears in the pane.
Print Entire Drawing	Print the complete view.
Print Page Numbers	Print the page numbers.
Zoom Level	Print the view at the current zoom level.

💐 Toolbar Options

The following table contains a description of each Topology Map toolbar option, organized alphabetically.

Note: These toolbar options are relevant for RTSM applications.

Button	Option Name	Use This Option to
Acon	Additions Count	Calculate the number of instances that are created as a result of an Enrichment Rule. The number of TQL query node instances and relationships that are created appear next to the Enrichment query nodes/relationships, as seen in the figure below.
	Advanced Pane	Toggle between hiding and displaying the Advanced Pane at the bottom center of the screen. To access: Select View > Advanced Pane.
	Calculate Query Result Count	Calculate the number of instances found for each TQL query node/relationship.

Button	Option Name	Use This Option to
	Change Label Length/ Properties	Enter the maximum number of characters that the labels should contain. To access: In IT Universe Manager and the Modeling Studio, select Layout > Change Label Properties. In the other managers, select Layout > Change Label Length.
	CI Types Tree	Toggle between hiding and displaying the CI Type Selector at the right of the screen. To access: Select View > CI Types Tree . Note: In the Modeling Studio, this option is called CI Types.
Î.	Create Relationship	In most managers, create a relationship between two existing TQL query nodes. For details, see "Add Query Nodes and Relationships to a TQL Query" on page 32. In IT Universe Manager, create a relationship between existing CIs. For details, see "Attaching Existing CIs" on page 238.
×	Delete Selected Item(s)	Delete a CI from IT Universe Manager or a TQL query node from Impact Analysis Manager or Enrichment Manager.
	Drag Map	Drag the view. To access: Open the drop-down menu in the Mode box or select View > Drag Map . In IT Universe Manager and the Modeling Studio, select Layout > Dragging Mode .
F	Drill Down One Layer	Move down one level in the topology map. This option is enabled only if there is an additional CI layer below it, created by setting the hierarchy of the view. For details on setting the hierarchy, see "Setting the View Hierarchy" on page 340. Note: This option appears only in IT Universe Manager.
A60	Enable/ Disable Related CIs Retrieval	Toggle between disabling and enabling the redrawing of the topology map with related CIs when selecting a new CI in the CI Selector. Note: This option appears only in IT Universe Manager in the Related CIs tab.

Button	Option Name	Use This Option to
	Entities Tree	Toggle between hiding and displaying the manager specific entities tree at the left of the screen.
		To access: Select View > Entities Tree.
		Note: In the Modeling Studio, each of the tabs of the Left pane (Resources, CI Types, CI Selector) is listed as a separate option.
	Export Map to Image	Save the topology map to a file. For details, see "Export Map to Image Dialog Box" on page 178.
		To access: Select Operations > Export Map to Image.
8	Fit to	Fit the complete map in the pane.
22	Window	To access: Select Layout > Fit to Window.
	Generate	Generate a direct link to a view or CI.
	Direct Link	To access: Select Edit > Generate Direct Link.
<u>1</u>	Go Up One Layer	Move up one level in the topology map. This option is enabled only if there is an additional CI layer above it, created by setting the hierarchy of the view. For details on setting the hierarchy, see "Setting the View Hierarchy" on page 340.
		Note: This option appears only in IT Universe Manager.
	Hide All Inheritance	Toggle between showing and hiding Inheritance_f relationships and their connecting query nodes.
	From Map	To access: Select Layout > Hide All Inheritance From Map.
		Note: This option is only active in the toolbar in CI Type Manager.
	Hide All Query Node	Toggle between showing or hiding the CI/CIT/query node/pattern labels.
	Labels	To access: Select Layout > Hide All Query Node Labels.
		Note: This option is not available in IT Universe Manager and the Modeling Studio.
	Hide All	Toggle between showing or hiding the relationship labels.
	Relationship Labels	To access: Select Layout > Hide All Relationship Labels.
E		Note: This option is called Hide edges' labels in IT Universe Manager and the Modeling Studio.

Button	Option Name	Use This Option to
	Hide All Relationships	Toggle between showing and hiding the relationships in the displayed map.
		To access: Select Layout > Hide All Relationships.
		Note: This option is not available in IT Universe Manager and the Modeling Studio.
2a	Hide/Show	Toggle between hiding and displaying the Get Related CIs pane.
	Get Related Cls pane	Note: This option appears only in IT Universe Manager in the Related CIs tab.
	Hide/Show	Toggle between hiding and displaying the topology map legend.
Leg	Legend	Note: This option appears only in IT Universe Manager and the Modeling Studio.
	Interactive Zoom	 Decrease the view magnification by clicking and pushing the pointer upwards.
		 Magnify the view by clicking and pulling the pointer downwards.
		To access: Open the drop-down menu in the Mode box or select View > Interactive Zoom.
		Note: This option is not available in IT Universe Manager and the Modeling Studio.
	Layout Properties	Define the view's layer layout, by assigning positions for the query nodes and relationships of the view. For details, see "Layout Properties Dialog Box" on page 180.
		To access: Select Layout > Layout Properties.

Button	Option Name	Use This Option to
	Layout	Select the layout display from the list. The options are:
		► Hierarchical Layout. Enables you to display the precedence relations in the topology map.
		 Symmetric Layout. Enables you to display clear representations of complex networks.
		 Circular Layout. Groups a graph's nodes into groups or clusters.
		 Orthogonal Layout. Enables you to display views of outstanding clarity that are achieved by employing only horizontal and vertical edge routing.
		 Manual Layout. Enables you to display the changes you have made manually to the topology map.
		For further details about each of the options, see "Layout Properties Dialog Box" on page 180.
		Note: These layout options are only relevant for Enrichment Manager, CIT Manager, and Impact Analysis Manager.
	Log	Open the Log Configuration dialog box.
	Configuratio n	To access: Select Tools > Log Configuration.
	Map overview	Open a small box with a copy of the topology map. This is useful in large views when zooming in.
		To access: Select Layout > Map Overview. In IT Universe Manager and the Modeling Studio, select Layout > Show Map Overview.
	Maximize Workspace/ Restore Workspace	Toggle between the regular display and a full-screen display of the topology map.

Button	Option Name	Use This Option to
	Navigation	Take the pointer to the next connected CI/CIT/TQL query node in a clockwise direction.
		➤ Left-click to move in a clockwise direction.
		 Right-click to point to the next CI/CIT/query node/pattern in a clockwise direction.
		To access: Open the drop-down menu in the Mode box or select View > Navigation.
		Note:
		 You can use this option only on CI/CIT/query nodes/patterns that are connected by relationships. This option is not available in IT Universe Manager and the Modeling Studio.
€ *	New Cl	Define a new unrelated CI. For details, see "Working with CIs" on page 232.
		Note: This option appears in the toolbar in IT Universe Manager only.
a	New Related Cl	Define a new related CI. For details, see "Working with CIs" on page 232.
		Note: This option appears in the toolbar in IT Universe Manager only.
	Place in Center	Place the selected CI/CIT/query nodes/pattern in the center of the map.
		To access: Select Layout > Place in Center.
		Note: This option is not available in IT Universe Manager and the Modeling Studio.
	Print	Print the contents of the topology map. For details, see "Print Dialog Box" on page 198.
		To access: Select Operations > Print
	Print Preview	Preview the contents of the map before printing.
		To access: Select Operations > Print Preview.

Button	Option Name	Use This Option to
	Print Setup	Define print settings for printing the topology map. For details, see "Print Setup Dialog Box" on page 199.
		To access: Select Operations > Print Setup
<u>li/a</u> a	Remove Enrichment	Remove the instances created from an Enrichment rule from the RTSM.
	Results	Note : This option appears in the toolbar in Enrichment Manager only.
	Screen	Take a snapshot of the screen using the Screen Capture tool.
	Capture	To access: Select Tools > Screen Capture.
k	Select	Select a CI/CIT/TQL query node or multiple CIs/CITs/TQL query nodes.
		To access: Open the drop-down menu in the Mode box or select View > Select . In IT Universe Manager and the Modeling Studio, select Layout > Selection Mode .
	Select All	Select all the CIs and relationships in a selected layer.
		To access: Select Edit > Select All.
		Note: This option is not available in IT Universe Manager and the Modeling Studio.
	Select All	Select all the query nodes in a selected layer.
	Query Nodes	To access: Select Edit > Select All Query Nodes.
		Note: This option is not available in IT Universe Manager and the Modeling Studio.
	Select Columns	Enables you to select the columns to be displayed. For details, see "Select Columns Dialog Box" on page 570.
		Note: This option is displayed in Text mode of IT Universe Manager only.
0	Set Change Timeframe	Open the Change Timeframe dialog box, which enables you to set the period for the display of added or changed CI indicators.
		Note: This option appears in the toolbar in IT Universe Manager only.

Button	Option Name	Use This Option to
921-	Set scope of inter-layer	Select the scope of inter-layer relationships to display in the view. The available options are:
	relationships	► None. Hide all inter-layer relationships.
	displayed	 Inter-layer. Display regular inter-layer relationships, but not duplication metalinks.
		► Full. Display all inter-layer relationships.
÷Ū.	Show Candidates	Identify the CIs in the current view which are candidates for deletion with the following icon $\frac{1}{40}$.
f	for Deletion	Note: This option appears in the toolbar in IT Universe Manager only.
٩	Show Schedule Info	Display the scheduling information for the selected job. For details, see "Discovery Scheduler Dialog Box" in the <i>RTSM Data Flow Management Guide</i> .
		Note: This option appears in the toolbar in the Dependency Map tab of DFM. For details, see "Dependency Map Tab" in the <i>RTSM Data Flow Management Guide</i> .
≜ ↑	Sort Column Content	Enables you to set the order of the visible columns. For details, see "Sort Column Content Dialog Box" on page 572.
		Note: This option is displayed in Text mode of IT Universe Manager only.
	Straighten	Straightens any selected relationship between two query nodes that has angles.
		To access: Select Layout > Straighten.
		Note: This option is only available in Enrichment Manager and Impact Analysis Manager.
	User Preferences	Opens the User Preferences dialog box which enables you to reset warning message preferences. For details, see "User Preferences Dialog Box" on page 102.
		To access: Select Tools > User Preferences.

Button	Option Name	Use This Option to
	User Profile	Opens the User Profile dialog box which displays the user details for the user currently logged in.
		To access: Select Tools > User Profile
	Zoom In	Zoom in on a specific section of the topology map by clicking and drawing a selection rectangle around the part to magnify. The area you select is displayed at the highest percentage that fits in the topology map.
		To access: Open the drop-down menu in the Mode box or select View > Zoom In . In IT Universe Manager and the Modeling Studio, select Layout > Zoom in .

💐 Topology Map Sidebar

The following table contains a description of each Topology Map sidebar option. The Topology Map sidebar appears in IT Universe Manager and the Modeling Studio.

Button	Option Name	Use This Option to
*	Move Layout Toolbar to Right/Left	Move the sidebar to the right or left side of the screen.
@ 0	Zoom In/Out	Zoom in or out on the topology map.
k	Selection Mode	Enable selection mode in the topology map.
()	Dragging Mode	Enable dragging mode in the topology map.
	Refresh to get an optimal layout	Refresh the topology map to optimize the layout.
22	Fit to Window	Fit the complete map in the pane.
ž	Hide Edges' Labels	Hide the labels of all relationships.
	Change label properties	Open the Map Label Properties dialog box which enables you to set the maximum label length per line and maximum number of lines per label.
<u>P</u>	Show Map Overview	Open a small box with a copy of the topology map. This is useful in large views when zooming in.
8 85 85	Hierarchical Layout	Display the topology map in a layout displaying the precedence relations.

Button	Option Name	Use This Option to
68 g	Hierarchical Layout with Orthogonal Routing	Display the topology map in a layout displaying the precedence relations using only horizontal and vertical edge routing.
888	Circular Layout	Display the topology map in a layout that groups a graph's nodes into groups or clusters.
891 89 88	Orthogonal Layout	Display the topology map in a layout using only horizontal and vertical edge routing.
	Symmetric Layout	Display the topology map in a layout showing clear representations of complex networks.
	Print	Print the topology map.
a	Export Map to Image	Save the topology map to a file.

Chapter 6 • Working with Topology Map

Part II

Modeling

7

Best Practices for Modeling

This chapter includes:

Reference

- ► Using Modeling Studio on page 216
- ► Models and Perspectives on page 216
- ► Building Models on page 217
- ► Model Dependencies on Other CIs in the RTSM on page 222
- ► Modeling an Application with Running Software on page 223
- ➤ Creating Views Using the Modeling Studio on page 223

Reference

💐 Using Modeling Studio

The Modeling Studio is the RTSM module for building and modeling views for display in Service Health. This document details the required flow to create Service Health views using the Modeling Studio.

The motivation behind developing the Modeling Studio is to create a separation between the need to change the RTSM content by creating CIs and relationships and the need to consume (view) the RTSM content. In earlier versions, altering the RTSM content was part of the view creation workflow. Hence, users were unintentionally changing the RTSM and influencing other users' views. In the Modeling Studio, you build models and transform your content into views to be consumed by HP Business Service Management.

🂐 Models and Perspectives

A model is a CI collection that represents a managed business entity such as an application, business service, or line of business. A model is usually created by solution or application architects who are familiar with the content and hierarchy of the model. The model content can include system CIs (typically nodes), running software CIs (such as web servers, databases, and J2EE servers), end user monitoring components (Business Process Monitor or Real User Monitor applications), business processes, groups, and other existing models.

To generate a view from a model, a perspective needs to be applied. A perspective is a TQL-based tool that enriches the model content by adding additional CIs, thus creating a view. The default perspectives that are applied to create Service Health views add all descendent CIs that are related by impact links down to the level of monitor CIs. There are other perspectives provided out of the box that can be used to address additional use cases.

The resulting view shows the model content as it is monitored by HP Business Service Management.


💐 Building Models

The information required to define a model includes the CI content, the hierarchy, and the dependencies upon additional CIs.

HP Business Service Management is configured with a predefined list of CI types that represent your business entities. When creating a new model using the Modeling Studio, the following list of valid models appears:

Select CI Type
BusinessApplication
🐱 BusinessFunction
🖨 BusinessService
BusinessTransactionFlow
CiCollection
🗞 InfrastructureService
🔒 Organization

The model CI types can be arranged in hierarchies to reflect the organization's specific needs. Here is an example of a typical recommended model hierarchy:



A model can be nested in any logical hierarchy, but it is best to create a hierarchy that starts from high level business entities down to more specific model types.

It is strongly recommended to build models in a way that allows them to be reused as components of other models.

Building a model creates a **contains** link between the model and its CIs according to the defined hierarchy.

The creation of a CI which is a model CI results in the creation of an empty model by default. Therefore, if you want to create a model for a CI that does not yet exist, you create a new model and thus, a new CI. If you want to model an existing CI for the first time, select the CI in the CI Selector, drag it onto the canvas and select **Create a New Model**.

Preconfigured Models

HP Business Service Management creates out-of-the-box models for applications monitored by Business Process Monitor and Real User Monitor.

The Business Process Monitor model is of type business transaction flow and it contains business transaction CIs.

Banking* ×	4>
🏥 Map 🔲 Text 😭 🕸 ቩ 🐡 🐘 🛠 🐕	🖞 💫 🕶 🖓 🕶 🚰 🔹 🔍 🤤 Find
Name	СІ Туре
🖻 🕼 Banking	BusinessApplication
占 📳 Credit cards	BusinessTransactionFlow
– 🚇 trans_1	BusinessTransaction
─ Strans_2	BusinessTransaction
– 🚇 trans_3	BusinessTransaction
utrans_4	BusinessTransaction

The Real User Monitor model is of type application and contains the End User Management Application related group and business process step CIs. The Real User Monitor model is also impacted by the Real User Monitor Sessions monitor CIs, Real User Monitor Errors events CIs, and Real User Monitor Informational events CIs, which are visible in the Related CIs pane.

Text Mode	💌 🚰 🐵 🎕 🛄 🗶 📽 📽 🦄 🔸 🚳 🔹	🚰 🔹 🔍 Find		
	Name		СІ Туре	
B- 🎧	Saving Account	Application		
É (🐞 Business Processes	End User Management.	Application Related Group	
-	– 🔐 Show accounts list	Business Process Step		
-	– 🔐 Select account	Business Process Step		
-	- 🗊 update profile Business Process Step			
- 🔐 Search by dates Business Process Step				
	– 📖 request check book	Business Process Step	Business Process Step	
L	– 🔐 Account history	Business Process Step		
-	Related Cls Watchpoints unt (Application) < Show Al> >			
Direction	CI	CI type	Relation type	
-74	Rum Info Events	RUM Informational Events	Impacted By (Potentially)	
\$\$ >				
∰ >	Application Sessions	RUM Sessions monitor	Impacted By (Potentially)	

Building Model Content

Create a model of the desired type and assign it a name. The new model appears as the top CI in the content pane of the Model Editor. Drag and drop CIs from the CI Selector into the content pane to build the model content.

A model can contain system CIs, running software CIs, SiteScope groups, and other models (both existing models and new ones created during the modeling process).

The only CIs that cannot be part of a model containment tree are monitors. Monitor CIs are added to a model after you generate a view from the model using one of the monitor perspectives. You can include monitors in view by dragging them into the Related CIs pane when a model CI is selected in the upper pane of the Model Editor. If you try to drop a monitor CI into the upper pane, a message appears prompting you to add the monitor CI to the Related CIs pane.

The CI Selector pane offers two ways to search for a CI (both model CIs and non-model CIs):

► Browse Views

Use this option when you are familiar with a view that contains the CI you are looking for. The following out-of-the-box views can help you find commonly used CIs:

- End User Monitors view contains business process groups and their content.
- ➤ System Monitors view contains SiteScope groups hierarchy.
- System Software Monitoring view contains running software CIs and the servers on which they are deployed.

In the CI Selector, select **Browse Views** and begin entering the view name or use the view tree to look for a CI in a specific folder.

► Search Cls

If you know the CI type you are looking for, select the **Search CIs** mode and use the quick search dialog to locate the desired CI. Use the Advanced Search option for CIs that do not appear in the quick search mode. The search result appears in the left pane. After the list of CIs is refreshed, you can drag and drop CIs into the model content pane. It is possible to drag and drop multiple CIs in a single selection.

Models can be placed in a hierarchical mode. During the process of building the content you can insert new models and create groups.

Hierarchies between CI types which are not models is not supported.

Grouping

In some cases, there is a need to divide the model into logical groups according to ownerships, locations or any other custom representation.

In the following example the application contains two groups that represent data centers:

Bank One Data Centers* ×		
🔝 Map 🔲 Text 🚰 🚯 둶 😂 🖳 🗶 🗞 😪 📽 🖧	- 🙀 - 📴 - 🔍 Find	
Name	CI Type	
🖻 🊱 Bank One Data Centers	Business Service	
🖻 🖾 NY Data Center	CiCollection	
- 🗐 127.0.0.1 DefaultDomain	Node	
- 🕮 10-EN01-6	Windows	
🖻 🖾 LA Data Center	CiCollection	
— 🚎 ilogb89362eaf.devlab.ad	Windows	
— 📇 ilogb893734wa.devlab.ad	Windows	
- 📇 LABM1APP03	Windows	
LABM3AMINT06	Windows	

For details on creating groups in a model, see "CI Collection" on page 400.

🍳 Model Dependencies on Other Cls in the RTSM

Each model CI in the model can be dependent on other CIs that exist in the RTSM but are not part of the model itself. Examples of such CIs include shared resources such as database servers and storage devices.

The model structure may vary between organizations according to policies and responsibilities in the IT department. There are organizations where shared resources are considered to be part of the application and are monitored as part of it, while in other organizations they are considered external to the application. In the first case, shared resources are part of the model and appear in the content pane, whereas in the second case they appear as related CIs (in the lower pane of the Model Editor).

To create a dependency between a CI in the model and another CI in the RTSM, search for a CI in the left pane and drag it into the Related CIs tab. This operation creates a **usage** link in the RTSM.

In order to create a dependency relationship between two CIs, there must be a valid link in the RTSM between the two CI types. By default, all business CIs can be dependent on other business CIs.

The following example shows an application that depends on a web server and Oracle software elements:

🔀 Credit cards*×		
Text Mode 🔄 🚰 🐡 🕸 🐺 🙀 🗛	• 🖗 • 🚰 • 🔍 Find	
Name		СІ Туре
E- 🔓 Credit cards	Busine	ss Process Group
 — I ture debits 	Busine	ss Process Step
 — I select credit card 	Busine	ss Process Step
 — I Request data from Amex 	Busine	ss Process Step
 — 📰 Request new credit card 	Busine	ss Process Step
🗕 🎆 Last statement	Busine	ss Process Step
Properties Related Cls Wetchp Credit cards (Business Process Group)	oints	
Direction CI	Cityp	e Relation type
Microsoft IIS WebServer (16.59.57.14	5) IIS	Depends On
DB36 (labm2amdb11)	Oracle	Depends On

HP Business Service Management offers a revised out-of-the-box impact model. The impact model describes the impact relationships between CI types. For example, a running software CI is impacted by the node on which it is deployed. In the Modeling Studio, when you include a running software CI as part of a model, the node on which it is deployed appears in the Related CIs tab, since the running software is dependent on the server.

🂐 Modeling an Application with Running Software

Running software CIs are CIs that describe the implementation components of an application. Examples include web servers such as IIS or Apache, application servers such as Webshpere or Weblogic, and databases.

To build the implementation model of a three tier application using its running software CIs, create an application model.

You can use the Running Software search in the Advanced Search dialog or browse the System Software Monitoring view to locate running software CIs. The names of the running software CIs are formed by combining the running software CI type with the server name, for example, Microsoft IIS web server (Server1).

Drag the relevant running software CIs into the modeling pane. The server on which the running software was deployed as well as the monitor of the running software both appear automatically in the Related CIs pane. This change derives from the new SiteScope monitoring model. In previous versions, all monitors (of both hardware and software) were connected to the Server CI. The SiteScope model was enhanced and now hardware monitors are connected to the server CI, while software monitors are connected to the running software CIs.

🍳 Creating Views Using the Modeling Studio

There are two methods of creating perspective-based views using the Modeling Studio. The first option is to create a view based on a model (or on several models); the second one is to create a view out of CI collection that is not a model.

A view based on a model is updated automatically when the model content is updated. For example, a view was generated using a business process group model that initially contained five business process steps. The business process group was then updated to include additional business process steps. Those changes are automatically reflected in the view.

This option is the recommended one, since it creates a dynamic view.

In a view based both on models and individual CIs, the view content is updated according to changes in the models.

Generating a View from a Model

After building a model and saving the model definition, select the top model and select **Generate view for selected model**. In the dialog box that opens, select the desired perspective according to the desired view content.

The recommended perspective is the Impact Perspective. It creates a view with all the CIs in the model and for each CI, it adds all the child CIs including the monitor CIs. Additional perspectives that may be used for other purposes are described in "Predefined Perspectives" on page 344.

If the selected model includes dependent CIs (which appear in the Related CIs tab), they are also enriched by the perspective and become part of the view.

The Content Only perspective does not make any changes in the view, even for model CIs.

Hiding Irrelevant Cls from a View

The view result appears in the View Results pane. At this point, you may choose to hide CIs that appear in the view.

Hiding CIs from a view does not change the status calculation of CIs in the view (the status calculation is performed according to the RTSM hierarchy). For example, hiding two business process steps from a business process group with five steps does not affect the business process group status. If a hidden CI has a critical status and the remaining CIs are OK, the business process group shows a critical status.

For details on hiding CIs and restoring them to a view, see "Including and Excluding Child CIs" on page 352.

Chapter 7 • Best Practices for Modeling

IT Universe Manager

This chapter includes:

Concepts

- ► IT Universe Manager Overview on page 228
- ➤ Working with Views in IT Universe Manager on page 229
- ► View Tree Structure on page 231
- ► Working with CIs on page 232
- ► Working with Relationships on page 236

Tasks

- > Create CIs and Relationships in the RTSM on page 244
- ► View Related CIs on page 245
- > Check Status of Application Discovery (Rediscover a View) on page 247
- ► Retrieve Impact Analysis Results Scenario on page 250
- ► Take a Snapshot of a View on page 257
- > Print and Save a Topology Map to File on page 258

Reference

► IT Universe Manager User Interface on page 259

Concepts

🚴 IT Universe Manager Overview

IT Universe Manager enables you to manage the content of your IT Universe model. The following tasks represent the basic functionality of the application:

- Creating Cls without creating relationships. You can define new Cls that are added to the RTSM individually, so that no new relationships are created. For details, see "Creating a Non-Related Cl" on page 233.
- ➤ Creating Cls with relationships for them. You can define new Cls and attach them to existing Cls, so defining a new Cl and a new relationship in the RTSM. For details, see "Creating a Related Cl" on page 233.
- ➤ Adding existing CIs and creating relationships for them. You can attach CIs to an existing CI, so creating new relationships for existing CIs. For details, see "Attaching Existing CIs" on page 238.
- ► Deleting Cls. You can delete CIs from the RTSM. For details, see "Deleting CIs" on page 234.
- ➤ Getting Impact Analysis results. You can run the Impact rules you defined for a view to simulate how certain defined changes impact your system, and to discover the root causes of the changes. For more information about Impact rules, see "Impact Analysis Manager Overview" on page 450.

Populating the IT Universe Model

The IT Universe model in the RTSM contains the CIs and relationships produced by the CI-generating tools that operate within HP Business Service Management. Most CIs and relationships originate from one of the following sources:

➤ Data Flow Management (DFM). Automatically creates CIs and relationships based on the discovered IT resources and topology in your company's infrastructure. For details, see "Data Flow Management Overview" in the *RTSM Data Flow Management Guide*.

- ➤ IT Universe Manager. Enables you to manually create CIs and relationships that represent logical and physical elements of the business. For details, see "Working with CIs" on page 232.
- End User Management Administration and System Availability Management Administration. Enables you to manually create relationships between the CIs for monitor objects and CIs in the RTSM. For details, see "Integrating SiteScope Data with BSM's Configuration Items" in Using System Availability Management.
- ➤ Enrichment Manager. Enables you to add CIs and relationships to the RTSM by receiving data from the attributes of Enrichment query nodes as defined in the Enrichment TQL query. For details, see "Enrichment Manager" on page 519.

\lambda Working with Views in IT Universe Manager

In IT Universe Manager, you analyze data at the view level. Views are subsets of the IT Universe, containing only those CIs relating to a specific area of interest. All views are based on a pattern which determines the content of the view.

- ➤ Pattern views and template-based views are built from a TQL (Topology Query Language) query that defines the structure of the view. The view displays only those CIs and relationships that satisfy the query definition.
- Perspective-based views are built manually, by selecting a group of CIs and applying perspectives to them. A perspective is a pattern used to define which related CIs are included in the view.

You build all views in the Modeling Studio, using the appropriate editor for each view type. For information on the different view types and how they function, see "View Formats" on page 338.

Note: You must have **Change** permissions for a view to edit the view. If you do not have the necessary permissions, contact your HP Business Service Management Administrator.

CIs created by DFM are automatically added to each view where the CIs (and their relationships) fit the TQL definition for the view. When you open a view in the CI Selector, the TQL query for the view queries the RTSM for CIs that match the defined pattern. If there are no matches (for example, in the case of a view for a DFM process where the process has not yet run) then the view remains empty.

When you define a new CI while working in any view in IT Universe Manager, the CI (and any associated relationship) is created in the RTSM. The CI is added to your current view only if it meets the view's TQL specifications.

If the created CI and relationship do not meet the TQL requirements, then the CI and relationship are created in the RTSM but are not visible in the view. Similarly, if you attach an existing CI to a CI in the view, and the new pattern does not meet the TQL requirements, then the attached CIs do not appear in the view, but the relationship is still created.

Templates and Template-based Views

If you open a template in IT Universe Manager, it is displayed in the topology map like a pattern view. Click the **Show Template Parameters** button in the CI Selector toolbar to open the Template Parameter Values dialog box, where you can change the values of the template parameters and thereby affect the view results displayed in the topology map. You can try different parameter values and see the resulting topology map, but you cannot save changes to the template itself. To save the view results as a template-based view with the selected parameters, click the **Save As View** button in the Template Parameter Values dialog box.

You can also create a direct link to a template in IT Universe Manager and insert the parameter values directly into the URL. For details, see "Create a Direct Link to a Template with Parameter Values" on page 120.

View Lifecycle

If you do not access a view from the CI Selector for a specified period of time, the view is cleared out, to save memory in the system. It is not deleted from the RTSM; the view can be retrieved by clicking on it. The default time period for clearing out unused views is one hour.

0

Note: Views defined as persistent are not cleared out and always remain in the memory.

Hidden Views

You can designate a view as a hidden view that does not appear in IT Universe Manager by defining a bundle for hidden views and assigning the view to that bundle.

To designate a view as a hidden view:

- 1 In the Infrastructure Settings Manager, select Hidden Bundles Names in CI Selector.
- **2** Enter the name of the new bundle as the default value and save the setting.
- **3** In the Modeling Studio, open the relevant view and click the **View Definition Properties** button in the toolbar.
- **4** In the View Definition Properties dialog box, select the hidden views bundle and assign the view to it.

\lambda View Tree Structure

Views are organized in a hierarchical tree format in the left pane of IT Universe Manager, which is known as the CI Selector. The view name appears in the View box above the tree and acts as the containing folder for the CIs in the view.

The first level of the CI Selector tree consists of the query nodes for the root CIs. A root CI is the starting point for a view subtree. A view may contain any number of subtrees. Under the root CIs come the branch CIs, expanding down to the leaf CIs as the last query nodes at the ends of each branch.

The CIs at each level in a subtree are considered to be attached to the CI on the branch directly above. This attachment generally depicts a dependent relationship, so that the higher branch (closer to the root CI) represents a component of your business that depends on the CIs on the next branch down (closer to the leaf CIs) in the business process. For example, an application depends on the servers running the application.

The attachment between a higher and a lower query node is referred to as a parent-child relationship. The parent CI may have many attached child CIs, and the child CIs pass operational status to the parent. The status at each level is viewed in Service Health.



The tree topology is determined by the hierarchy defined for the view. In a pattern view, these are defined for the specific view. In a template-based or a perspective-based view, the hierarchy is defined as part of the template or perspective. For details on defining the hierarchy, see "Setting the View Hierarchy" on page 340.

\lambda Working with Cls

In IT Universe Manager, you can create related and non-related CIs, delete CIs, edit the CI properties, and remove out-of-date CIs using the aging mechanism.

This section includes the following topics:

- ➤ "Creating a Non-Related CI" on page 233
- ► "Creating a Related CI" on page 233

- ► "Deleting CIs" on page 234
- ► "CI Properties" on page 235
- ➤ "Removing Out of Date CIs Using the Aging Mechanism" on page 236

Creating a Non-Related Cl

You can define a new CI in IT Universe Manager by clicking the **New CI** button in the toolbar. The New CI dialog box opens, which enables you to define the properties for the new CI. The CI is created in the RTSM. For details, see "New CI/New Related CI Dialog Box" on page 289.

Note: The CI is added to the view only if it meets the specifications of the pattern, template, or perspective of the view.

A CI created in this way is added as an independent entity without any relationship to any other existing CI in the RTSM.

Creating a Related Cl

You can define a new CI to be added as a parent, child, or sibling of an existing CI.

To define a new related CI:

1 Select the CI in your view to which you want to attach the new CI.



<u>ک</u>

- **2** Click the **New Related CI** button in the toolbar.
- **3** In the New Related CI dialog box, define the properties and relationship for the CI. For details, see "New CI/New Related CI Dialog Box" on page 289.

The CI and relationship are created in the RTSM.

Note: The CI and relationship are added to the view only if they meet the specifications of the pattern of the view, template, or perspective.

Deleting Cls

You can delete a CI by selecting **Delete from CMDB** from the shortcut menu in IT Universe Manager. The CI is deleted from the RTSM and from all views. If the CI has children, they are not automatically deleted when you delete the parent CI. If you delete a CI without first deleting the relationship between the CI and any child CIs that appear with the parent CI in a view, the child CIs are removed from the view.

If the child CIs do not appear in any other view, they remain in the RTSM without appearing in a view. The child CIs might appear in the future in views where they meet the pattern requirements.

One exception to this rule is when the relationship between a child and parent CI is a **Composition** relationship; in that case, when the parent CI is deleted, the contained CI is also removed from the RTSM. For example, if a node CI is the container for a child CPU CI, then when the node CI is deleted, the CPU is also removed from the RTSM.

When you delete a CI that was created by the DFM process, the CI is restored the next time that DFM runs (if the CI is still valid), and it reappears in all relevant views.

CI Properties

In IT Universe Manager, you can edit the properties of a CI. The CI properties are divided into several categories which appear in the New CI dialog box:

- ➤ The general properties of a CI are common to all CIs. Some general properties are defined automatically during CI creation; others can only be defined manually in the New CI dialog box.
- ➤ CIT-specific properties are created as part of the CIT definition in the CI Type Manager. The values for the CIT-specific properties are taken from the CIs discovered during DFM. The values can also be entered manually, when you manually create CIs to represent entities in your infrastructure. For details, see "CI Type Manager" on page 475.
- ➤ Key properties can be general or CIT-specific properties, which must be assigned a value to create an instance of the CI type.

You can access the Configuration Item Properties dialog box to view the CI properties from IT Universe Manager by right-clicking the CI and selecting **Properties** or by clicking the Properties tab in the Advanced pane. You can also edit the CI properties if you have the necessary permissions for editing CIs. For details on CI properties, see "Configuration Item Properties Dialog Box" on page 266.

The CIT-specific properties are displayed in the **Specific Properties** section of the Configuration Item Properties dialog box when you sort the properties using the **Categorized** button. Some properties for the automatically created CIs can be edited, however, if the CI is configured to **Allow CI Update** (in the General Properties), then DFM may override your changes when it updates the CI. A description of the selected property can be found in the Description area at the bottom of the Configuration Item Properties dialog box.

Some of the CIT-specific properties for DFM CIs are set by default to be monitored for changes. When one of these properties has been modified, information on the change can be viewed in a CI change report, and in some cases, an icon is displayed in Service Health. For more information, see "CI Change Report" on page 426.

Removing Out of Date Cls Using the Aging Mechanism

If a CI or relationship is not updated or refreshed over a period of time (for example, a CI is not rediscovered by DFM and no manual update occurs), an aging mechanism deletes the CI from the RTSM. For details, see "CI Lifecycle and the Aging Mechanism" in the *RTSM Administration Guide*.

🚴 Working with Relationships

Many of the relationships between CIs in the RTSM are created automatically, for example, by DFM. In addition, you can create relationships manually in IT Universe Manager, Enrichment Manager, Impact Analysis Manager, or the Modeling Studio. You can also create relationships in System Availability Management and End User Management Administration.

This section includes the following topics:


- ➤ "Creating Relationships" on page 236
- ➤ "Creating Hierarchical Relationships" on page 237
- ➤ "Attaching Existing CIs" on page 238
- ➤ "Setting the View Hierarchy" on page 239
- ➤ "Viewing Related CIs" on page 240
- ► "Deleting Relationships" on page 240
- ► "Inter-Layer Relationships" on page 241

Creating Relationships

You can create relationships in IT Universe Manager by right-clicking a CI or multiple CIs in the CI Selector pane or the Topology Map and selecting **Relate to CI** from the shortcut menu. In the Topology Map, you can define a relationship between two CIs in the view by drawing a line between the two, using the **Create Relationship** button from the toolbar. Either of these actions opens the Insert Relationship dialog box. For details, see "Insert Relationship Dialog Box" on page 273.



You can create as many relationships as necessary between a CI in the RTSM and other CIs. Each new relationship exists as its own entity in the RTSM, and has its own properties that can be edited in IT Universe Manager (as described in "Configuration Item Properties Dialog Box" on page 266). You can also create more than one relationship between the same two CIs, when each relationship is based on a different relationship type. In the following example, host7 has both a **Backbone** and a **Talk** relationship with switch3.



Creating Hierarchical Relationships

By attaching one CI to another in IT Universe Manager or System Availability Management or End User Management Administration you create a hierarchical relationship (parent-child) between them, so that one CI is influenced by the other. Certain relationships defined in this way are restricted to the relationship type **usage** (if the relationship is between two non-monitoring CIs), or the relationship type **Monitored By** (if the child CI in the relationship is a monitor type CI); however, other relationship types are used between specific types of CIs. For example, if a relationship is defined between two node CIs, there are several possible relationship types.

Select Relationship
Source Cl: host06 (Node)
Target Cl(s): host07
Relationship:
Direction:
Define Relation Define Relation
Backbone

Note: When you attach a child CI to a parent CI, you are creating that relationship in the RTSM. The child therefore impacts on the parent CI in every view where the relationship exists, and is displayed in every view where the child and relationship match the TQL query.

When performing status calculations, the Business Logic Engine only recognizes calculated relationships. For details on calculated relationships, see "Impact Rules" on page 111.

Attaching Existing Cls

You can attach existing CIs using the Insert Relationship dialog box. The dialog box has two modes:

- > Selecting the CIs that you want to attach.
- > Defining the relationship between the original CI and the CIs to attach.

When selecting the CIs to attach, you can select multiple CIs from a view to attach to the original CI. However, all CIs that you want to attach in one operation must have the same relationship type. For example, you cannot attach a CI that uses the relationship **usage** in the same operation as a CI that uses the relationship **Monitored By**.

Note: SiteScope monitor CIs should not be attached to other CIs from within the RTSM. You should only create links to SiteScope monitor CIs from within SiteScope.

Setting the View Hierarchy

After setting the query node and relationship definitions of a view, you can set a hierarchy for the view. This enables you to define the organizational structure of CIs in the view by displaying selected CIs at different levels. When no hierarchy is defined, the Topology Map or table displays all CIs included in the query results on one level by default. For example, if the query results include nodes and IP Subnets, both CI types are displayed on the same level in the Topology Map or table.

Note: The maximum number of CIs that can be displayed in a single layer of the Topology Map is 900. If a view contains a layer with more than 900 CIs, the view is not displayed in the Topology Map until the hierarchy is changed. However, a layer with more than 900 CIs can be displayed in a table in Text mode.

For details on setting the hierarchy, see "Setting the View Hierarchy" on page 340.

Viewing Related Cls

You can view all the CIs related to a selected CI in the topology map. Select a CI in a view and then select the **Related CIs** tab. The Get Related CIs pane enables you to select the scope of the display. If you select **View**, the topology map displays only the selected CI and its related CIs in the view (no matter where it is in the view hierarchy). If you select **CMDB**, it displays the selected CI and all of its related CIs in the RTSM. You can also filter the results from the Get Related CIs pane by CI type and apply perspectives to a CI. For details, see "Get Related CIs Pane" on page 287.

You can also display Related CIs using the Get Related CIs from CMDB dialog box. For details, see "Get Related CIs From CMDB Dialog Box" on page 272.

Deleting Relationships

The Topology Map shows only the relationships for the CIs that are part of the current view; however, the same relationships may also be part of other views. When you delete a relationship in IT Universe Manager, it is deleted from the RTSM and from all views.

When a relationship is deleted, the CI on the other end of the relationship may remain in the view, if it still matches the pattern of the view. However, if the deleted relationship is a composition link, the target CI is deleted with it.

In a perspective-based view, you can remove the CI completely from the view (without deleting it from the RTSM), by hiding it from the view in the Perspective-based View Editor in the Modeling Studio.


When you delete a relationship that was created by the DFM process, the relationship is restored the next time that DFM runs (if the relationship is still valid), and it reappears in all relevant pattern views.

It can take a few minutes to delete subtrees, or multiple CIs and relationships, from a view.

Inter-Layer Relationships


In certain circumstances, IT Universe Manager displays a relationship between CIs in a layer of a view that does not reflect an actual relationship between the CIs in that layer, but rather a relationship between CIs on deeper layers of the view. Such a relationship is known as an **inter-layer relationship**.

For example, in the following view, two node CIs are related to each other with a dependency relationship. Each is also related to an IP Subnet by a membership relationship and the view hierarchy is defined such that the nodes are on the layer beneath the IP Subnet.



When you consume the view in IT Universe Manager, the relationship between the node CIs (which are under different IP Subnets) is displayed in the higher layer of the view as a relationship between the parent IP Subnets, even though the actual relationship only exists between the CIs in the lower layer of the view. You can double-click the relationship to display the full path between the IP Subnets. Another form of inter-layer relationship occurs when the same CI appears under more than one parent CI of the same type in the layer above it. In such a case, the child CI and its relationships are duplicated in the view display, due to the hierarchy definition. The relationships of such child CIs result in inter-layer relationships between the parent CIs. This type of interlayer relationship is known as a **duplication metalink**.

For example, in the following view, a single node CI appears under two IP Subnet CIs in the hierarchy. The node and its children thus appear twice in the view - once under each IP Subnet. Each node is effectively related to the child CIs of the node under the other IP Subnet, which generates an inter-layer relationship between the two IP Subnets.



Inter-layer relationships and duplication metalinks are displayed in gray in the topology map. IT Universe Manager provides the following options for viewing inter-layer relationships:

- ► None. Hide all inter-layer relationships.
- ➤ Inter Layer. Display inter-layer relationships of the first type, but not duplication metalinks.
- **Full.** Display all inter-layer relationships, including duplication metalinks.

A tooltip for the inter-layer relationship displays the inner relationships which it represents. If there is only one inner relationship, the relationship label displays that relationship type. If there are multiple inner relationships, the label becomes **Inter-layer** and the tooltip displays a list of all the inner relationships. If there are more than ten inner relationships, only the first ten are displayed, and a note indicates that there are more inner relationships.

Tasks

<u>ک</u>

9

P Create CIs and Relationships in the RTSM

This task describes how to create related and non-related CIs, as well as relationships between CIs, in the RTSM.

This task includes the following steps:

- ➤ "Define a New Non-related CI" on page 244
- ➤ "Define a New Related CI" on page 244
- ► "Attach Existing CIs" on page 244

Define a New Non-related CI

Click the **New CI** button in the toolbar. In the New CI dialog box, select a CI type from the tree and define the properties for the new CI. For details, see "New CI/New Related CI Dialog Box" on page 289.

Define a New Related Cl

Click the **New Related CI** button in the toolbar. In the **New Related CI** dialog box, select a CI type from the tree and define the properties for the new CI. On the Relationship page of the dialog box, select the type of relationship and define its properties. For details, see "New CI/New Related CI Dialog Box" on page 289.

Attach Existing Cls

Select a CI in a view. Right-click the CI and select **Relate to CI**. In the Insert Relationship dialog box, select a target CI. On the Relationship page of the dialog box, select the type of relationship and define its properties. For details, see "Insert Relationship Dialog Box" on page 273.

聄 View Related Cls

The following steps describe the options for viewing related CIs in IT Universe Manager.

- ► "Display Related CIs" on page 245
- ➤ "Select the Scope of the Display" on page 246
- ► "Filter the Related CIs" on page 246
- ➤ "Apply Perspectives to a CI" on page 246

Display Related Cls

In IT Universe Manager, select a CI in the Topology map or the CI Selector and select the **Related CIs** tab. Click the **Enable Related CIs Retrieval** button. The selected CI is displayed with its related CIs. Select a different CI or multiple CIs from the CI Selector, and the display changes accordingly.

Note: You can display the Related CIs content in map mode or in text mode.

For details on the Get Related CIs user interface, see "Get Related CIs Pane" on page 287.



Select the Scope of the Display

In the Get Related CIs pane, select the scope of the related CIs display. Click the **Show Related CIs** button. The display changes according to your selection.

Filter the Related Cls

In the Filter Related CIs by CI Type section, select the CI types to appear in the related CIs display. Click the **Filter Related CIs** button. The filtered results appear in the tab. The scope selected above still applies and the display is reduced according to your filter selection.

Apply Perspectives to a Cl

In the Apply Perspectives to CI section, select the perspectives to apply to your selected CI. Click the **Apply Perspectives** button. The results are displayed in the tab.

Note: This feature is only relevant when **CMDB** is selected as the scope.

Check Status of Application Discovery (Rediscover a View)

You, the application owner or administrator, need to be kept informed of any problems to your application. So, for example, you need to know that discovery is working correctly and that its current configuration can connect to the application database. This section explains how to run the rediscovery procedure that enables you to check the current status of the discovery of an application.

Note:

- Set up and configuration is performed by the HP Business Service Management administrator. For details, see "Prerequisites" on page 248.
- Rediscovery is performed by the application owner/administrator. For details, see "Access the View" on page 248.
- ► You do not need any knowledge of Data Flow Management (DFM) to run this procedure.
- ➤ By default, you can run the rediscovery procedure on views that include less than 10,000 CIs. For details on changing this number, see "Important information" on page 298.

This task includes the following steps:

- ► "Prerequisites" on page 248
- ► "Access the View" on page 248
- ► "View Results in the View" on page 249
- ► "Schedule the Rediscovery" on page 250

1 Prerequisites

Note: This step is performed by the HP Business Service Management administrator.

- **a** In DFM, create a module that contains the jobs that must discover the application. For details, see "How to Use Discovery Control Panel Advanced Mode Workflow" in the *RTSM Data Flow Management Guide*.
- **b** Activate the module and all the jobs. The jobs must remain activated.
- Verify that the module has run without errors. For details, see "Error Messages Overview" in the *RTSM Developer Reference Guide* and "Discovery Status Pane" in the *RTSM Data Flow Management Guide*.
- **d** Correct any errors in the application and confirm that DFM finds no errors during the next run.

Caution: The application owner cannot rediscover a view if DFM is reporting errors. You must set an error-free baseline.

- **e** In the Modeling Studio, define a view that includes the application CI or CIs to be rediscovered. These are the CIs that are created when you activate the jobs that discover the application. For details, see "Create a Pattern View" on page 359.
- **f** Notify the application owner of the name of the view.

2 Access the View

Note: This step is performed by the application owner/administrator.

In IT Universe Manager, access the view that includes the application CIs to be rediscovered. For details, see "Search for CIs in Search Mode" on page 157.

3 View Results in the View

a You need to check the complete application. You click the Show Discovery and Changes Summary button in the CI Selector toolbar. The Show Discovery Status and Changes of View dialog box is displayed. The dialog box displays information about which jobs and trigger CI discovered the CIs in the view, on the last occasion that DFM ran the discovery for the jobs. For details, see "Show Discovery Status and Changes Dialog Box" on page 298.

To run the discovery, click the **Rerun Discovery** button. To view information about the jobs and trigger CIs, use the links to drill down. For details, see "Error Messages Overview" in the *RTSM Developer Reference Guide*.

b You need to check specific components of your application. You select the component's CI in the Topology Map pane and display the Discovery tab in the Advanced pane. For details, see "Show Discovery Status and Changes Dialog Box" on page 298.

To rediscover several CIs, press CTRL, select the CIs and display the Discovery tab.

To run the discovery, click the **Rerun Discovery** button.

4 Schedule the Rediscovery

You can schedule how often the rediscovery procedure should run. In the Job Definition window, choose the **Rerun Discovery on View** action. For details, see "Job Definition Dialog Box" on page 88.

膧 Retrieve Impact Analysis Results – Scenario

Impact Analysis Manager enables you to create an Impact rule that allows you to simulate the impact certain infrastructure changes have on your system. The results of the Impact rule are displayed in IT Universe Manager. The Impact Analysis results in this task describe how a change in CPU operation impacts the node to which it is connected.

This task includes the following steps:

- ➤ "Define an Impact Analysis TQL Query" on page 250
- ► "Define an Impact Rule" on page 251
- ➤ "Create a View in the Modeling Studio" on page 253
- ➤ "Get Impact Analysis Results" on page 253


1 Define an Impact Analysis TQL Query

To define an Impact Analysis TQL query, you need to create an Impact rule and then add the TQL query nodes and relationships that define the query.

To create an Impact Analysis TQL query, select **Admin** > **RTSM Administration** > **Modeling** > **Impact Analysis Manager**. For details about how to add query nodes and relationships to a query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

Example of an Impact Analysis TQL Query:

In this Impact Analysis TQL query, a CPU and a node are linked by a Composition relationship.



2 Define an Impact Rule

When you define an Impact rule, you must specify the required causal relationship between the query nodes. Define one query node as the trigger, or the query node that represents the changes you want to make to the system, and another query node as the one that is impacted.

Right-click the query node you want to define as the trigger and select **Define Impacted** to open the Impacted Query Nodes dialog box. Select the query node that you want the trigger query node to impact and click **Next**. Then click the **Add** button to open the Impact Rules Definition dialog box to set conditions for defining impacted query nodes. For details about how to define an Impact rule, see "Impact Rules Definition Dialog Box" on page 467.

Note: The **change** state option in the Impact rule definition is no longer relevant for Impact Analysis. The only supported state is **operation**.


Example of an Impact Rule:

The Conditions area in the Impact Rules Definition dialog box defines the conditions under which the simulated change in the system is triggered. The Severity area defines the severity of the impact on the impacted query node.

The Impact rule in this example states that when the CPU operation is not in the normal state, the node is impacted. Since the severity is set to 100% of the trigger's severity, the severity of the node is the same as the severity of the CPU, which is determined when Impact Analysis is run.

🛓 Impact Rules De	finition ×	
Description:		
State:	operation	
Operator:	Not equal	
Value comparison:	I: Normal	
Scope Any All Range	% - 100 %	
O Fixed severity: Critical ▼		
Severity relative to trigger severity (%): 100		
	OK Cancel	

In the resulting TQL query, an upward arrow appears next to the query node defined as the trigger query node and a downward arrow appears next to the query node defined as the impacted query node.



3 Create a View in the Modeling Studio

Go to the Modeling Studio and create a view matching the TQL query of the Impact rule you defined. For details, see "Pattern View Editor" on page 413.

4 Get Impact Analysis Results

Select Admin > RTSM Administration > Modeling > IT Universe Manager and select the required view in the CI Selector. To get Impact Analysis results, you need to run the Impact rule on a CI instance in the topology map that is a trigger. Right-click a trigger CI and select **Run Impact Analysis** to open the Run Impact Analysis dialog box. For details on how to run an Impact rule, see "Run Impact Analysis Dialog Box" on page 294.

Example for Getting Impact Analysis Results:

An Impact Analysis TQL query is created containing a CPU and node connected by a Composition relationship. The CPU query node is defined as the trigger query node and the query node of type node is defined as the impacted query node.

The following Impact rule is defined for the query.


💪 Impact Rules De	finition	
Description:		
State:	operation 💌	
Operator:	Not equal	
Value comparison:	Normal	
Scope Any All Range	% - 100 %	
 ○ Fixed severity: Critical ▼ ● Severity relative to trigger severity (%): 100 		
	OK Cancel	

Right-click a CPU CI in the view, and select **Run Impact Analysis** to open the Run Impact Analysis dialog box. Set the trigger severity to a value other than **Normal**.

	ct Analysis							l .	
~	un Impact A lect the impact a	nalysis nalysis trigger an	d the set of imp	pact rules that v	ill be executed				
Trigger Se	verity								
Normal	Warning(1)	Warning(2)	Minor (3)	Minor (4)	Minor (5)	Minor (6)	0 Major (7)	Major (8)	Critical
Correlation	ı Rules								
-	act Rules npact rules locate	ed in specified bu	ndle						
Only im	npact rules locate	ed in specified bu	ndle						
-	npact rules locate	ed in specified bu	ndle						v
Only im	npact rules locate	ed in specified bu	ndie						v


To see results, click one of the following:

➤ Show in Views. This assigns a status to all the CIs in the view. Only the node CI connected to the CPU CI (whose severity was changed), becomes impacted. The trigger CI and the impacted CI turn orange because the trigger severity was set as Major (7) on the scale in the Run Impact Analysis dialog box, which is assigned an orange color.



➤ Show Map. A map appears in a separate window containing only the trigger CPU CI and the node CI it impacted. The relationship connecting the two CIs contains the name of the Impact rule defined in Impact Analysis Manager.

Note: Optionally, you can create a URL that enables you to embed the map. For details, see "Direct Link Parameters – Impact Map Page" on page 132.



➤ Generate Report. Generates an Impact Analysis report that displays a list of CIs that are impacted in the system as a result of the simulated changes. For details, see "Run Impact Analysis Dialog Box" on page 294.

🅆 Take a Snapshot of a View

You can take a snapshot of a view in IT Universe Manager, save it, and then compare snapshots of the same view taken at different times using the Compare Snapshots Report.

- ➤ For details on how to take a snapshot of a view, see "Save Snapshot Dialog Box" on page 296.
- ➤ For details on how to view actual differences in the compared views, see "Compare Snapshots Report" on page 318.

igearrow Print and Save a Topology Map to File

You can print the content of any topology map and then save it to file. Before printing, it is recommended to define your print settings and arrange the contents of the topology map according to your requirements.

- ➤ For details on how to define print settings, see "Print Setup Dialog Box" on page 199.
- ➤ For details on how to preview the content of the topology map before printing, see "Print Preview Dialog Box" on page 199.
- ➤ For details on how to print the content of a topology map, see "Print Dialog Box" on page 198.
- ➤ For details on how to save a topology map to file, see "Run Impact Analysis Dialog Box" on page 294.

Reference

💐 IT Universe Manager User Interface

This section includes (in alphabetical order):

- ► Add CIs to Model Dialog Box on page 259
- ► Add CIs to View Dialog Box on page 260
- ► Change Timeframe Dialog Box on page 261
- ► CI/Relationship History Dialog Box on page 262
- ➤ Configuration Item Properties Dialog Box on page 266
- ➤ Get Related CIs From CMDB Dialog Box on page 272
- ► Insert Relationship Dialog Box on page 273
- ► IT Universe Manager Page on page 278
- ➤ New CI/New Related CI Dialog Box on page 289
- ► Run Impact Analysis Dialog Box on page 294
- ► Save Snapshot Dialog Box on page 296
- > Show Discovery Status and Changes Dialog Box on page 298
- ► Show Impact Pane on page 300

💐 Add CIs to Model Dialog Box

This dialog box enables you to add selected CIs to a model.

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager. Right click a CI or multiple CIs in the CI Selector and select Add CIs to Model.
Important	This feature is only relevant for instance based models.
information	You cannot add selected CIs to a pattern based model.

UI Element (A-Z)	Description
<model tree=""></model>	When Existing Model is selected, select a model from the tree.
Define New CI Properties	When New Model is selected, define the name and properties of the model.
Existing Model	Select Existing Model to add the selected CIs to an existing model.
New Model	Select New Model to add the selected CIs to a new model.
Select Cl Type	When New Model is selected, select a CI type for the model.

User interface elements are described below:

🂐 Add Cls to View Dialog Box

This dialog box enables you to add selected CIs to a perspective based view.

To access	Select Admin > RTSM Administration > Modeling >
	IT Universe Manager. Right click a CI or multiple CIs in
	the CI Selector and select Add CIs to View.

UI Element (A-Z)	Description
<view tree=""></view>	When Existing View is selected, select a view from the tree.
Existing View	Select Existing View to add the selected CIs to an existing perspective based view.
New View	Select New View to add the selected CIs to a new perspective based view
View Name	When New View is selected, edit the name of the view.

Q Change Timeframe Dialog Box

This dialog box enables you to display changes in the topology map and set the time frame for the changes to display.

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager. Click the Set Change Timeframe button in the main toolbar or the IT Universe status bar.
Important information	When the change indicators are displayed in the topology map, a message appears in the IT Universe status bar Change Timeframe is Active .
	To hide the indicators, open the dialog box and select Do not display changes , or select the Reset Change Timeframe Dutton in the IT Universe status bar.

UI Element (A-Z)	Description
Display changes according to the selected timeframe	Select this option to display an indicator next to each CI that was added or changed within the selected period as follows:
	▶ 📩 Indicator for an added CI
	\blacktriangleright \triangle Indicator for a changed CI
	Select a time period from the drop-down list. If you select Custom , click the ellipsis button to select the Date From and Date Until fields. The changes to the CIs of the view within the selected period are displayed in the map.
	When the indicators are displayed, you can click the indicator to open the CI History dialog box, which displays the history for the CI over the selected period.
Do not display changes	Select this option to hide the change indicators.

💐 CI/Relationship History Dialog Box

This dialog box displays a list of CI or relationship attributes in which changes have occurred as well as the differences between two configuration files.

To access	 In IT Universe Manager, right-click the selected CI or relationship in the CI Selector or the Topology Map and select CI History. In Data Flow Management, in the Discovered by [Module or Job Name] CIs dialog box, right-click a CI and choose CI History. Note: CI and relationship history data is also available in the History tab of the Advanced pane in IT Universe Manager.
Important information	Only attributes marked with the Change Monitored or Comparable qualifiers are tracked in the CMDB History database. If you want an attribute to appear in the CI history, select the Change Monitored or the Comparable qualifier for it in the Attributes tab of the CI Type Manager. For CIs, some attributes are designated as Change Monitored by default. For relationships the attributes must be designated manually in the CI Type Manager. In addition, to track history for a relationship, you must select the TRACK_LINK_CHANGES qualifier for the relationship in the Qualifier tab of the CI Type Manager.

UI Element (A-Z)	Description
Ø	Click Refresh to refresh the data in the table.
٩	View the difference between two history entries for the content of a configuration file. This is relevant in the following situations:
	 Select two history entries for the Document Content attribute for CIs of the type Configuration Document to compare to each other.
	 Select one history entry for the Document Content attribute for CIs of the type Configuration Document to compare to the current content for that CI.
	Click the Show difference button to open the Visualdiff report, which displays a comparison of the two entries. Text added to the second entry appears highlighted in yellow. Text removed from the first entry appears highlighted in red. Differences between the entries appear highlighted in green.

UI Element (A-Z)	Description
8	Choose the export format for the table data. The available options are:
	 Excel. The table data is formatted as an .xls (Excel) file that can be displayed in a spreadsheet. PDF. The table data is exported in PDF format. Note: When exporting to PDF, select a reasonable number of columns to display to ensure that the report is legible. RTF. The table data is exported in Rich Text Format. CSV. The table data is formatted as a comma-separated values (CSV) text file that can be displayed in a spreadsheet. Note: For the CSV formatted table data to display correctly, the comma (,) must be defined as the list separator value, open Regional Options from the Control Panel, and on the Numbers tab ensure that the comma is defined as the List Separator value. XML. The table data is formatted as an XML file that can be opened in a text or XML editor. Tip: To extract HTML code from the report: Save the file as HTML Open the file in an HTML editor Copy the relevant table into the target file
Attribute	The name of the attribute.
Change Date	The date when the last change occurred.
Filter by	 Filter the data in the table by one or more of the following filters: Time Range. Select the time period for which the CI history is displayed. Change Type. Select the type of changes displayed in the table. Attribute. Select the attribute types displayed in the table.

UI Element (A-Z)	Description
Modified By	Indicates the cause of the change. For example, the field can contain the name of a user or a DFM job.
New Value	The new value of the attribute.
Old Value	The previous value of the attribute.

Representation Item Properties Dialog Box

This dialog box enables you to view and edit basic information for an existing CI or relationship.

To access	Select Admin > RTSM Administration > Modeling >
TO access	IT Universe Manager and use one of the following:
	➤ Select a CI in the topology map or the CI Selector. In the Advanced Pane, select the Properties tab and click Edit .
	 Right-click a CI in the CI Selector or the Topology map and select Properties.
Important information	The Configuration Item Properties dialog box contains two types of properties:
	 General properties, which include general information about the CI or relationship. These properties are common to all CITs and are documented below. CIT-specific properties, which include properties specific to that CI. These properties vary according to the type of CI or relationship and are not documented except in the case of TransactionVision Monitor CIs. For details about TV Monitor CIs, see "Transaction Configuration Page, Tracing Tab" in Using Transaction Management.
	When you sort the properties by category, the CIT-specific properties appear at the top of the list and the general properties appear at the bottom.
	You can view a description of the selected property in the Description Area at the bottom of the dialog box. Click the Show/Hide Description Area button to display the Description Area.
	When accessing the Configuration Item Properties dialog box from within certain applications, the fields are not editable.
	Mandatory fields are denoted by an asterisk.
	Note: HP Universal CMDB does not fully support surrogate pairs and combining characters.
See also	"CI Lifecycle and the Aging Mechanism" in the <i>RTSM</i> <i>Administration Guide</i>

UI Element (A-Z)	Description
	Click to display the properties by category.
51	Click to display the properties alphabetically.
i	Toggles between showing and hiding the description area at the bottom of the CI Properties dialog box.
*	Click Expand to expand the properties tree when the properties are displayed by category.
*	Click Collapse to collapse the properties tree when the properties are displayed by category.

UI Element (A-Z)	Description
🔁 Export 🕞	Choose the export format for the table data. The available options are:
	► Excel . The table data is formatted as an .xls (Excel) file that can be displayed in a spreadsheet.
	 PDF. The table data is exported in PDF format. Note: When exporting to PDF, select a reasonable number of columns to display to ensure that the report is legible.
	► RTF. The table data is exported in Rich Text Format.
	➤ CSV. The table data is formatted as a comma-separated values (CSV) text file that can be displayed in a spreadsheet.
	Note: For the CSV formatted table data to display correctly, the comma (,) must be defined as the list separator. In Windows, to verify or modify the list separator value, open Regional Options from the Control Panel, and on the Numbers tab ensure that the comma is defined as the List Separator value.
	► XML. The table data is formatted as an XML file that can be opened in a text or XML editor.
	Tip: To extract HTML code from the report:
	► Save the file as HTML
	► Open the file in an HTML editor
	► Copy the relevant table into the target file

UI Element (A-Z)	Description
<quick filter=""></quick>	Enter a string in the Quick filter box to filter the property names and values. Click the left end of the box to open the drop-down menu of filter options:
	Select All to search for the filter string in both property names and property values. Select Name to search for the filter string in property names only. Select Value to search for the filter string in property values only.
	 Select Case sensitive to search for the filter string exactly as entered. Select Case insensitive to ignore the case of the filter string.
	 Select Use wild cards to use the wildcard symbol * in the filter string.
	Select Match from start to search for the filter string at the beginning of a property name or value. Select Match exactly to search for the exact filter string. Select Match anywhere to search for the filter string anywhere in the properties.
Actual Deletion Period	The number of days after which the CI or relationship is deleted.
Allow CI Update	When selected, this option allows the DFM process to automatically update the CI or relationship properties with information that it discovers. If you change the value of a property supplied by the DFM process, the value is overridden by the discovered value.
	When this option is cleared, the CI or relationship properties are not overridden by the DFM process.
Apply	Click Apply to save the changes made to the CI or relationship properties.
СІ Туре	The type of the CI or relationship (read-only value). For information about CITs in HP Business Service Management, see "CI Type Manager" on page 475.
Created By	The user name of the administrator who manually created the CI or relationship, where applicable (read-only value).
Create Time	The date and time when the CI or relationship was created.

UI Element (A-Z)	Description
Deletion Candidate Period	The period after which the CI becomes a candidate for deletion when the aging mechanism is enabled.
Description	A brief description of the CI or relationship.
Display Label	The name of the CI or relationship as it appears in the CI Selector.
Edit	In the Properties tab of the Advanced pane, you can view a CI's properties but you cannot edit them. Click Edit to open the Configuration Item Properties dialog box where you can edit the properties.
Enable Aging	If a CI or relationship is not updated or refreshed over a period of time (for example, a CI is not rediscovered by DFM and no manual update occurs), an aging mechanism deletes the CI from the RTSM. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
	True : the aging mechanism is enabled for this CI or relationship.
	Default value: False. The default value for DFM CIs is True.
	Note:
	 If the aging mechanism is disabled, this field is ignored. This field is displayed for certain CIs only.
Global Id	The internal ID of the CI or relationship in the RTSM (read- only value).
Last Access Time	The time that the CI or relationship was last accessed, whether when being updated or being discovered by DFM. This field is only displayed for certain CIs or relationships.
	This parameter is used by the aging mechanism. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
Last Modified Time	The date and time when the CI or relationship properties were last updated.
Monitored By	Indicates whether the CI is monitored by a SiteScope monitor or an EMS Integration monitor.

UI Element (A-Z)	Description
Name	The name of the CI or relationship.
Note	Enables you to enter other information about the CI or relationship.
Origin	An ID for the source that automatically created the CI or relationship, or the application where the CI or relationship was created (read-only value).
Reset	Click the Reset button to restore the original property settings of the CI or relationship.
Updated by	The user name of the administrator who updated the CI or relationship properties.
User Label	Enables you to define a display label for the CI or relationship. If no value is entered, the CI name appears as the default label.

Shortcut Menu

Menu Item	Description
Copy Property Name and Value	Copies the name and value of the selected property to the memory.

💐 Get Related Cls From CMDB Dialog Box

This dialog box enables you to view the CIs related to a specified CI in the RTSM in map or table format.

To access	In IT Universe Manager, right-click the required CI and select Get Related CIs .
Important information	The Get Related CIs From CMDB dialog box is a standalone version of the Related CIs tab in IT Universe Manager. You can control the content of the display using the features in the Get Related CIs pane. For details, see "Get Related CIs Pane" on page 287.
	You cannot select the scope of the related CIs displayed in the Get Related CIs From CMDB dialog box. The scope is the entire CMDB.
	Note: The text mode format includes the icons found in the Element Instances dialog box. For details, see "Element Instances Dialog Box" on page 77.
Relevant tasks	"View Related CIs" on page 245

💐 Insert Relationship Dialog Box

This dialog box enables you to attach CIs to the CI you selected in the CI Selector.

To access	In IT Universe Manager, right-click a CI in the Topology Map or the CI Selector, and select Relate to CI .
Important information	To create a relationship between two CIs, select the source CI in the CI Selector or the Topology Map and then select Relate to CI from the shortcut menu. On the first page of the dialog box (the CI Selection page), you select the target CI(s). Then click Relationship , to select the relationship type on the second page of the dialog box.
	You can also create a relationship between two CIs graphically by clicking the Create Relationship the button in the toolbar and drawing a line between the two CIs. In this case, a smaller version of the Insert Relationship dialog box opens, which contains the following tabs:
	 Select Relationship. Displays a tree with the available relationship types. Select the required relationship. Note: You can double-click the relationship you select to save using the default properties.
	Relationship Properties. Displays the properties of the selected relationship. You can edit the properties as described in "Define Relationship Properties Pane" on page 275.
Relevant tasks	"Create CIs and Relationships in the RTSM" on page 244
See also	"CI Selector" on page 163

UI Element (A-Z)	Description
\$	Click to add the selected CIs in the left pane to the Target CIs pane.
¢	Click to remove selected CIs from the Target CIs pane (this does not delete the CIs from the RTSM).

UI Element (A-Z)	Description
Select target CIs	Select a view to display in the view tree and select CIs to move to the Target CIs pane. For details on the Select target CIs pane, see "CI Selector" on page 163.
Source Cl	The CI you selected as the source CI.
Target Cls	Displays the CIs you have selected as target CIs for the relationship.

💐 Relationship Page

This page enables you to define the relationship to be created between the original CI and the CIs selected in the CI Selection page of the dialog box.

To access	Click the Relationship button from the Insert Relationship dialog box.
Important information	When defining multiple relationships, you can define different descriptions and property values for each relationship. Skip the property definitions here and edit each relationship individually after it is created.

User interface elements are described below:

Select Relationship Pane

UI Element (A-Z)	Description
Direction	Select the direction of the relationship. For some relationship types (for example, Composition , or between a group CI and a monitor CI), only one direction is valid.
Relationship	Define the type of relationship created between the original CI and the CIs being attached. Select an option from the list.

UI Element (A-Z)	Description
Source Cl	Displays the name of the CI on the first end of the relationship. This is the CI that you selected in the view.
Target Cl	Displays the name of the CI on the second end of the relationship, that is attached to the original CI.

Define Relationship Properties Pane

UI Element (A-Z)	Description
Actual Deletion Period	The period after which the relationship is deleted when the aging mechanism is enabled.
Allow CI Update	When the value is set to true, the DFM process automatically updates the relationship.
Created By	The user name of the administrator who manually created the relationship, where applicable.
Create Time	The date and time when the relationship was created.
Deletion Candidate Period	The number of days after which the relationship becomes a candidate for deletion.
Description	A detailed description of the relationship.
Destination Network Address	Defined only for route links. Indicates the destination network address to which this route is configured.
Enable Aging	If a CI or relationship is not updated or refreshed over a period of time (for example, a CI is not rediscovered by DFM and no manual update occurs), an aging mechanism deletes the CI from the RTSM. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
	True : the aging mechanism is enabled for this CI or relationship.
	Default value: false. The default value for DFM CIs is true.
	Note:
	 If the aging mechanism is disabled, this field is ignored. This field is only displayed for certain CIs.

UI Element (A-Z)	Description
Last Access Time	The time that the relationship was last accessed, whether when being updated or being discovered by DFM. This field is displayed only for certain CIs.
	This parameter is used by the aging mechanism. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
Last Modified Time	The date and time when the relationship properties were last updated.
Must	When the value is set to true, the child CI is dominant when the percentage rule is used to calculate status for the parent CI. If the CI has low status, the parent must take the child CI status, if necessary overriding the percentage rule calculation. This is useful to give emphasis to an important CI. For example, you might want to define Must for a database CI, so that status is critical all the way up the subtree if the database falls, regardless of the status of the other CIs in the subtree.
	The must status defined for a relationship applies for that relationship only – it is not used in any other relationships of the child CI. For details, see "Understanding the Percentage Rule" in <i>Using Service Health</i> .
Name	A brief description of the relationship. If no value is entered, the relationship type is used in place of the name.
Note	Enables you to enter other information about the relationship.
Origin	An ID for the source that automatically created the relationship, or the application where the relationship was created.
Updated By	The user name of the administrator who updated the CI properties.

UI Element (A-Z)	Description
User Label	Enables you to define a display label for the relationship. If no value is entered, the relationship name appears as the default label.
Weight	When a weight value is entered, the child CI is given more weight in percentage calculations, when percentage rule is used to calculate status for the parent CI. For example, if a child CI is given a weight of 3, then it has three times more impact on the parent status calculation than its unweighted siblings.
	The weight defined for a relationship applies for that relationship only – it is not used in any other relationships the child CI may have. For more details, see "Understanding the Percentage Rule" in <i>Using Service Health</i> .

💐 IT Universe Manager Page

This page enables you to define and manage the CIs and relationships in your views.

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager.
Important information	The IT Universe Manager page contains the following panes:
	CI Selector. Displays the CIs of a selected view. You can select the view from a drop–down list or search for a specific CI. For details, see "CI Selector" on page 163.
	➤ Topology Map. Displays the CIs of a selected view in Map mode or Text mode.
	 Advanced Pane. Displays properties, history, and discovery for the selected CI or view.
	➤ Get Related Cls. This pane can be accessed from the Related Cls tab of the Topology Map. It controls the content of the display in the tab.
	In IT Universe Manager, you can create new CIs, modify existing CIs, or delete CIs. All of these actions have a direct effect on the entire IT Universe model. For example, if you delete a CI in your view, that CI is deleted from the IT Universe model and no longer appears in any view.

Тороlоду Мар

This area displays the CIs of the currently selected view in graphical or table format. By default, the CIs are displayed in graphical format.

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager.
Important information	When you select a CI in the CI Selector or the Topology Map, the Configuration Items drop-down in the Main Menu becomes active. The options available under that drop-down are the same as those available by right- clicking the CI.
	You can customize the Topology Map shortcut menu to include other commands (for example, ping, run a program, open a URL) from within CI Type Manager. For details, see "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496.
	Note: For grouped CIs and the relationships between them, not all of the shortcut menu options are active. Grouped CIs appear in parentheses in the CI Selector and in the Topology Map. You can double-click a link to a grouped CI to open the Link Map, which displays the individual CIs and relationships. Right-click a CI or relationship in the Link Map to display the regular shortcut menu. For details about grouping CIs, see "Query Node Grouping Dialog Box" on page 425.
See also	"Working with Topology Map" on page 175

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
Map Map mode	Click Map to display the selected layer of CIs in topology map format.
	Note: If the selected layer of the view is too large to display in topology map format, a message appears with a link to display the layer in text format.
Text mode	Click Text to display the attribute properties of the CIs in the selected layer in table format.
	For details on some of the toolbar icons in Text Mode, see "Element Instances Dialog Box" on page 77.
Show Clinstances of: Network	Specify the CIT you want displayed in the table. The table also includes the children of the selected CIT.
	Note: This option is displayed in Text mode only.
<breadcrumbs></breadcrumbs>	At the top of the topology map, the breadcrumbs indicate the relevant query nodes in each layer of the view for the path to the selected layer. The first item in the path is the Top Layer . When you select a CI from the layer below, the parent CI forms the next item in the breadcrumb path. You can click on any item in the path to display that layer in the topology map.
<ci attributes="" type=""></ci>	The columns appearing in Text mode represent the CIT attributes of the selected CIs.
<it status<br="" universe="">Bar></it>	The status bar below the topology map indicates the status of the following processes: ➤ if Impact Analysis is active or not
	➤ if Change Timeframe is active or not
	 if Candidates for Deletion are shown or not the time of the last update of the data
	r the time of the last update of the data

UI Element (A-Z)	Description
<legend></legend>	Indicates the icons displayed next to CIs with any of the following special statuses:
	► Added. When Change Timeframe is active, indicates that the CI was added.
	► Impacted. When Impact Analysis is active, indicates an impacted CI.
	 Impacted and Trigger. When Impact Analysis is active, indicates a trigger CI that is impacted.
	 Candidate for Deletion. Indicates that the CI is a candidate for deletion.
	➤ Changed. When Change Timeframe is active, indicates that the CI was changed.
	► Note. Indicates that a note was added for the CI.
	 Trigger. When Impact Analysis is active, indicates a trigger CI.
<main menu=""></main>	For details, see "Main Menu" on page 197.
<query node=""></query>	The query nodes in the topology map represent CIs.
	Hold the pointer over a query node to display its tooltip which describes the type of the CI.
<relationship></relationship>	The links in the topology map represent relationships.
	Hold the pointer over a relationship to display its tooltip, which describes the type of the relationship.
	Note: When you select a calculated relationship, the Delete \varkappa button in the toolbar is disabled.
<toolbar></toolbar>	For details, see "Toolbar Options" on page 201.
	Note: When accessing the Topology map via direct links, the toolbar includes options from the Related CIs Map. For details, see "Get Related CIs From CMDB Dialog Box" on page 272.
<topology map<br="">Sidebar></topology>	For details, see "Topology Map Sidebar" on page 210.

Chapter 8 • IT Universe Manager

UI Element (A-Z)	Description
Related CIs	Click the Related CIs tab to display the interdependencies of the selected CI within the view or the entire RTSM. You can control the scope of the display from the Get Related CIs pane.
View Results	Click the View Results tab to display an entire layer within a view.

IT Universe Manager Shortcut Menu

The IT Universe Manager page includes the following elements (listed alphabetically) available by right-clicking a CI or relationship in the CI Selector pane or the Topology Map:

Menu Item	Description
Actions	Select one of the following options:
	➤ Add Cl to Discovery Job. Displays the Add CI to Discovery Job dialog box, which enables you to manually invoke a DFM job for the selected CI. You can use this option to discover additional information about the CI through one of the available DFM jobs.
	Remove Cl from Discovery Job. Displays the Remove CI from Discovery Job dialog box, which enables you to manually remove a CI from the DFM job.
	➤ Show Discovery status. Opens the Discovery Status dialog box for the selected CI.
	➤ Open Cl Credentials. Displays the Protocol Parameter dialog box, which enables you to view the details of a previously-defined credential for that CI. You cannot make any changes. This option is only relevant for CIs that include a credentials property.
	For details, see "Protocol Parameter Dialog Box" in <i>RTSM Data Flow Management Guide</i> .
	 Edit Cl Credentials. Displays the Choose Credentials dialog box, which enables you to choose another credentials set or edit the existing credentials. This option is only relevant for CIs that include a credentials property. For details, see "Supported Protocols" in <i>RTSM Data Flow Management Guide</i>.
Add CIs to Model	Adds selected CIs to a new or existing model.
Add CIs to View	Adds selected CIs to a new or existing perspective based view.
CI/Relationship History	Displays the CI History dialog box. For details, see "CI/Relationship History Dialog Box" on page 262.

Menu Item	Description
Compare CIs Report	Run a Compare CIs Report for the selected CI. For details, see "Compare CIs Report" on page 432.
Delete from CMDB	Enables you to delete the selected CI or relationship from the view and from the RTSM.
	Note: When you delete a parent CI, the selected CI and its children are removed from the view, but only the selected CI is removed from the database.
Get Related Cls	Opens the Get Related CIs from CMDB dialog box. For details, see "Get Related CIs From CMDB Dialog Box" on page 272.
Label	Select one of the following options:
	► Edit Label. Opens the Edit Label dialog box which
	 enables you to edit the name of the CI. Restore Default Label. Resets the CI name to its default value from the RTSM.
Note	Select one of the following options:
	➤ Add Note. Opens an editing box where you can add a note to the CI.
	 Delete Note. Deletes all text saved in a note for the selected CI.
Properties	Displays the Properties page for the selected CI or relationship. For details, see "Configuration Item Properties Dialog Box" on page 266.
Relate to CI	Opens the Insert Relationship dialog box. For details, see "Insert Relationship Dialog Box" on page 273.
Run Impact Analysis	Enables you to run the Impact rule you defined in the Impact Analysis Manager. Displays the Run Impact Analysis dialog box. For details, see "Impact Analysis Manager" on page 449. Note: You can only see Impact Analysis results if you
	defined an Impact rule for that view in Impact Analysis Manager.

Menu Item	Description
Show Compound Path	Appears only for compound relationships. Displays the Link Map for the selected relationship, which shows the CIs involved in the compound relationship.

Menu Item	Description
Show Impact	Enables you to select a CI that is defined by an Impact rule as a root cause CI, and to display all the CIs that are impacted by it, and their statuses, in a separate window.
	This option appears only after the following has occurred:
	 You defined an Impact rule for the selected view in Impact Analysis Manager (for details, see "Impact Analysis Manager" on page 449).
	➤ You clicked Show in Views in the Run Impact Analysis dialog box.
	► Impact Analysis results appear in the Topology Map.
	For example, suppose an Impact rule is defined (for an IP Address CI) that specifies that the rule impacts nodes, ports, and client-servers linked to the IP Address.
	By using the Show Impact option, you can display all CIs that are impacted by the IP Address CI.
Show Root Cause	This option enables you to retrieve root cause information for CIs that are impacted by a chain of Impact rules. The output of Show Root Cause displays a logical map that describes a chain of trigger/impacted CITs that impact the CI.
	The root cause CI is displayed in a separate window. If only one Impact rule is defined for this CI, the Impact Analysis window is directly displayed.
	This option appears only after the following has occurred:
	 You defined an Impact rule for the selected view in the Impact Analysis Manager (for details see, "Impact Analysis Manager" on page 449).
	➤ You clicked Show in Views in the Run Impact Analysis dialog box.
	► Impact Analysis results appear in the Topology Map.
	A window is displayed containing the root cause CI and all the other CITs in the Impact rule chain.
	To view the information about specific CIs that are triggered or impacted by the Impact rule, double-click the relationship connecting the CIs. A map is displayed.

Advanced Pane

User interface elements are described below:

UI Element (A-Z)	Description
Discovery tab	Displays the DFM run status for the selected CIs. For details, see "Show Discovery Status and Changes Dialog Box" on page 298 and "Discovery Status Pane" in the <i>RTSM Data Flow Management Guide</i> .
History tab	Displays the history for the selected CI. For details, see "CI/Relationship History Dialog Box" on page 262.
Properties tab	Displays the selected CI's properties (the same properties that appear in the Configuration Item Properties dialog box). You can view the properties in the properties tab, but you must open the dialog box to edit the properties. For details, see "Configuration Item Properties Dialog Box" on page 266.

Get Related Cls Pane

This pane enables you to control the different options for viewing related CIs for a selected CI.

To access	Appears in the Related CIs tab of IT Universe Manager. If it is hidden, click the Show Get Related CIs pane A button in the toolbar to display it.
Important information	You can control the display in the Related CIs tab with the following controls:
	 Set the scope of the display Filter the related CIs by CI type Apply perspectives to the selected CI
	It is possible to display related CIs for several CIs at the same time. Use the CTRL key to select multiple CIs at the same time in the CI Selector or the topology map.
	Note: The Get Related CIs functionality is not available for federated CIs.
Relevant tasks	"View Related CIs" on page 245

UI Element (A-Z)	Description
4	Display the previous search results.
0	Display the next search results.
*	When the button is selected, the related CIs are added to the current results. When it is not selected, the current display content is cleared and only the new related CIs are displayed.
Apply perspectives to CI	Select perspectives from the list to apply to the selected CI. Only perspectives relevant to the selected CI appear in the list. The selected CI is used as content for the selected perspectives and the view results are displayed.
	Note: Application of perspectives is only relevant when CMDB is selected as the scope. The feature is inactive when View is selected as the scope.
Filter Related CIs by CI Type	Select the CI types from the list to display in the related CI results. Only the selected CI types appear in the displayed results.
Select scope	Select the scope of the related CIs displayed:
	 View. All related CIs in the selected view. CMDB. All related CIs in the RTSM.
	Note: This feature is not available in the Get Related CIs from CMDB dialog box opened from the shortcut menu.
Show Related CIs	Click to display the related CIs according to your selection.

💐 New Cl/New Related Cl Dialog Box

This dialog box enables you to define a new CI or a new related CI.

To access	In IT Universe Manager, click the New CI icon in the toolbar to create a non-related CI. Select a CI in the topology map and click the New Related CI icon to create a related CI.
Important information	To define a new CI, select the CI type from the tree at the top of the dialog box. The CI types in the tree that are available to be instantiated appear in black. The CI types in faded text cannot be instantiated.
	Edit the properties in the Define new CI properties area. The table below includes the properties which are common to all CIs. In addition, there are other properties specific to each CI.
	If you are creating a related CI, click the Relationship button to go to the relationship mode of the dialog box. Select a relationship and edit its properties.
Relevant tasks	"Create CIs and Relationships in the RTSM" on page 244
See also	 "CI Selector" on page 163 "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i>

UI Element (A-Z)	Description
Actual Deletion Period	The period after which the CI is deleted when the aging mechanism is enabled.
Allow CI Update	When the value is set to true, this option enables the DFM process to automatically update the CI properties with information that it discovers. If you change the value of a property supplied by the DFM process, the value is overridden by the discovered value. When the value is set to false, the CI properties are not overridden by the DFM process.

UI Element (A-Z)	Description
Created By	The user name of the administrator who manually created the CI, where applicable.
Create Time	The date and time when the CI was created.
Deletion Candidate Period	The period after which the CI becomes a candidate for deletion when the aging mechanism is enabled.
Description	A description of the CI.
Display Label	The label that appears for the CI in the topology map.
Enable Aging	If a CI or relationship is not updated or refreshed over a period of time (for example, a CI is not rediscovered by DFM and no manual update occurs), an aging mechanism deletes the CI from the RTSM. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
	True : the aging mechanism is enabled for this CI or relationship.
	Default value: false. The default value for DFM CIs is true.
	Note:
	► If the aging mechanism is disabled, this field is ignored.
	► This field is displayed for certain CIs only.
Is Candidate For Deletion	Indicates if the CI is a candidate for deletion.
Last Access Time	The time that the CI was last accessed, whether when being updated or being discovered by DFM. This field is displayed only for certain CIs.
	This parameter is used by the aging mechanism. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
Last Modified Time	The date and time when the CI properties were last updated.
Name	The name of the CI.
Note	Enables you to enter other information about the CI.

UI Element (A-Z)	Description
Origin	An ID for the source that automatically created the CI, or the application where the CI was created.
Relationship	For a related CI, click Relationship to go to the relationship mode of the dialog box.
Select CI Type	Enables you to select the CI type from the tree for the new CI. The CI types that are available for the selected CI or view appear active in the CI type tree. The other CI types appear in faded text and cannot be selected.
	To limit the CI type tree to CI types from the current view, select CI Types from the current view on the right. To display all CI types in the tree, select All CI Types .
Updated By	The user name of the administrator who updated the CI properties.
User Label	Enables you to define a display label for the CI. If no value is entered, the CI name appears as the default label.

💐 Relationship Dialog Box

This page enables you to define the relationship between the new CI and the CI selected in the view, as well as the properties of the relationship.

To access	Click the Relationship button from the New Related CI dialog box.
Important information	This page only appears for new related CIs.

UI Element (A-Z)	Description
Allow CI Update	When the value is set to true, the DFM process automatically updates the relationship.
CI Definition	Click CI Definition to return to the CI properties mode of the dialog box.

UI Element (A-Z)	Description
Created By	The user name of the administrator who manually created the relationship, where applicable.
Create Time	The date and time when the relationship was created.
Description	A description of the relationship.
Direction	Select the relationship direction from the drop-down box.
Enable Aging	If a CI or relationship is not updated or refreshed over a period of time (for example, a CI is not rediscovered by DFM and no manual update occurs), an aging mechanism deletes the CI from the RTSM. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
	True : the aging mechanism is enabled for this CI or relationship.
	Default value: false. The default value for DFM CIs is true.
	Note:
	 If the aging mechanism is disabled, this field is ignored. This field is displayed for certain CIs only.
Last Access Time	The time that the relationship was last accessed, whether when being updated or being discovered by DFM. This field is only displayed for certain relationships.
	This parameter is used by the aging mechanism. For details, see "CI Lifecycle and the Aging Mechanism" in the <i>RTSM Administration Guide</i> .
Must	When the value is set to true, the child CI is dominant when the percentage rule is used to calculate status for the parent CI. If the CI has low status, the parent must take the child CI status, overriding the percentage rule calculation if necessary. This is useful to give emphasis to an important CI. For example, you might want to define Must for a database CI, so that status is critical all the way up the subtree if the database falls, regardless of the status of the other CIs in the subtree.
	The Must status defined for a relationship applies to that relationship only – it is not used in any other relationships of the child CI.

UI Element (A-Z)	Description
Name	The name of the CI.
Network Address	Defined only for route links. Indicates the destination network address to which this route is configured.
Note	Enables you to enter other information about the CI.
Origin	An ID for the source that automatically created the relationship, or the application where the relationship was created.
Relationship	Enables you to define the type of relationship that is created between the two CIs.
Source CI	The name of the CI on the first side of the relationship. This is the CI that you selected in the view.
Target Cl	The name of the CI on the second side of the relationship. This is the new CI that you are creating.
Updated By	The user name of the administrator who updated the relationship properties.
Update Time	The date and time when the CI properties were last updated.
User Label	Enables you to define a display label for the relationship.
Weight	When a weight value is entered, the child CI is given more weight in percentage calculations, when the percentage rule is used to calculate status for the parent CI. For example, if a child CI is given a weight of 3, then it has three times more impact on the parent status calculation than its unweighted siblings. The weight defined for a relationship applies to that relationship only – it is not used in any other relationships of the child CI.

💐 Run Impact Analysis Dialog Box

This dialog box enables you to run the Impact rule you defined in Impact Analysis Manager for that view.

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager. Right-click a trigger query node in the Topology Map and select Run Impact Analysis or click the Run Impact Analysis Now > button in the IT Universe status bar.
Important information	 You can: Display in a new window all the CIs that are impacted by the trigger CI. The relationships in the map represent the Impact rules. The name of the relationship is the name of the Impact rule you defined in the Impact Analysis Manager. For details, see "Show Map" on page 296. Simulate how the statuses of the impacted CIs are impacted. For details, see "Show in Views" on page 295. Generate a report that displays a list of CIs that are impacted in the system as a result of the simulated changes. For details, see "Generate Report" on page 295. Note: This dialog only appears if an Impact rule is defined for that view. For details, see "Impact Analysis Manager" on page 449.
Relevant tasks	"Retrieve Impact Analysis Results – Scenario" on page 250

UI Element (A-Z)	Description
All Impact rules	Select to execute all impact rules in the impact analysis.
Impact rules bundle	Select the bundle containing the required impact rules for the impact analysis.

UI Element (A-Z)	Description
Generate Report	Generates an Impact Analysis report, which displays information that is divided as follows:
	➤ Grouping by CIT. All the impacted CIs (the CIs that are impacted in the system as a result of the simulated changes), sorted by CIT.
	 Affected Application. All the impacted CIs that belong to a specific business service.
	➤ Triggered Cls. The Cls that represent the changes you want to make to the system.
	For details on the Impact Analysis report, see "Impact Analysis Report" on page 323.
Only Impact rules located in specified bundle	Select to execute the impact rules from the specified bundle in the impact analysis.
Show in Views	Simulates how the statuses of the impacted CIs are impacted for the selected state. The Topology Map displays the statuses of the trigger CIs as well as all statuses of the CIs that are impacted by it.
	The Topology Map also displays the Impact Analysis indicators:
	 A trigger CI is marked by this (up arrow) indicator. A CI that is both an impacted and a trigger CI is marked by this (up and down arrow) indicator. An impacted CI is marked by this (down arrow) indicator.
	Note: The statuses that appear here and the colors that represent each status are defined in the severity list for that state in the System Type Manager. For details, see "Create/Update List/Enumeration Definition Dialog Box" on page 513.

UI Element (A-Z)	Description
Show Map	Enables you to select an Impact rule, and then display in a new window, a simulation of all the CIs that are impacted by the trigger CI for the selected state. If only one Impact rule is defined for this CI, the Impact Rules window is displayed directly. For more details, see "Show Impact Pane" on page 300.
	The relationships in the map represent the Impact rules and the name of the relationship is the name of the Impact rule you defined in the Impact Analysis Manager.
	Note: Show Map enables you to view the results of multiple triggers.
Trigger Severity	Select the required severity on the scale.
	Note : The severity scale was defined for the state in the System Type Manager. For details, see "System Type Manager" on page 479.
	For example, you can create an Impact rule in the Impact Analysis Manager that defines the severity of the trigger query node as other than Warning (1) . If you select a severity other than Warning (1) , for example, Minor (3) , the condition is met and the simulated changes in the system are triggered.
	For details, see the "Impact Rules Definition Dialog Box" on page 467.

💐 Save Snapshot Dialog Box

This dialog box enables you to take a snapshot of a view and save it.

To access	In IT Universe Manager, click the Snapshot ቬ button in the CI Selector and select Save Snapshot .
Important information	You can compare snapshots of the same view taken at different times using the Compare Snapshots Report. For details, see "Compare Snapshots Report" on page 318.
Relevant tasks	"Take a Snapshot of a View" on page 257

UI Element (A-Z)	Description					
Description	A description of the snapshot (optional).					
Note	A note about the snapshot (optional).					
View Name	The name of the view as it appears in the CI Selector. This field cannot be edited.					

💐 Show Discovery Status and Changes Dialog Box

This dialog box enables you to find recent changes, for example, to an application, by rediscovering the CIs and jobs in a view.

To access	In IT Universe Manager:				
	 To rediscover all CIs of a view, click the Show Discovery and Changes Summary button in the CI Selector toolbar. The Show Discovery Status and Changes dialog box is displayed. To rediscover one CI or several CIs in a view, select the CI and display the Discovery tab in the Advanced pane. 				
Important information	By default, you can run the rediscovery procedure on views that include less than 10,000 CIs.				
	 To increase the number of CIs that you can rediscover in a view: 1 Access the Infrastructure Settings Manager (Admin > Platform > Setup and Maintenance > Infrastructure Settings). 2 Select the Max CIs in view supported to rediscover setting in the infrastructure settings table. 3 Click the Value column and change the number. 4 Restart the server for the change to take effect. For details on working with the Infrastructure Settings Manager, see "Infrastructure Settings" in <i>Platform Administration</i>. 				
Relevant tasks	"Check Status of Application Discovery (Rediscover a View)" on page 247				
See also	"Discovery Status Pane" in <i>RTSM Data Flow Management</i> <i>Guide</i>				

UI Element (A-Z)	Description					
	Click to refresh the status of the selected CIs. This button is disabled when there is no data to be reloaded.					
	Click to rerun the discovery.					
Discovery Progress Status on View	For details, see "Discovery Status Pane" in the RTSM Da Flow Management Guide.					
History Changes on View	For details, see "CI/Relationship History Dialog Box" on page 262.					

💐 Show Impact Pane

This page opens a window that displays the statuses of the trigger CI as well as all statuses of the CIs that are impacted by it.

To access	In the Run Impact Analysis Dialog box, click Show Map . If Impact Analysis is already active, click on the Impact Analysis Is Active link in the IT Universe status bar.
Important information	 The following tabs are available: Impact Results. Displays a map of all CIs impacted by the selected CI. Trigger Cls. Displays a table of information on the selected trigger CIs.
	You can only see Impact Analysis results if you defined an Impact rule for that view in Impact Analysis Manager. For details, see "Impact Analysis Manager" on page 449.
	To view information about specific CIs that are triggered or impacted by the Impact rule, double-click the relationship connecting the CIs. A map is displayed.
	The relationships in the map represent the Impact rules. The name of the relationship is the name of the Impact rule you defined in the Impact Analysis Manager.
Relevant tasks	"Retrieve Impact Analysis Results – Scenario" on page 250

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description							
<legend></legend>	Indicates the icons displayed next to CIs with any of the following special statuses:							
	➤ Added. When Change Timeframe is active, indicates that the CI was added.							
	► Impacted. When Impact Analysis is active, indicates an impacted CI.							
	 Impacted and Trigger. When Impact Analysis is active, indicates a trigger CI that is impacted. 							
	 Candidate for Deletion. Indicates that the CI is a candidate for deletion. 							
	 Changed. When Change Timeframe is active, indicates that the CI was changed. 							
	► Note. Indicates that a note was added for the CI.							
	➤ Trigger. When Impact Analysis is active, indicates a trigger CI.							
<relationship></relationship>	The relationships represent the Impact rule you defined in the Impact Analysis Manager. For details, see "Impact Rules Definition Dialog Box" on page 467.							
<the and<br="" statuses="">the colors that represent each one></the>	The statuses that appear and the colors that represent each status are the ones that are defined in the severity list for that state in the System Type Manager. For details, see "Create/Update List/Enumeration Definition Dialog Box" on page 513.							
<toolbar></toolbar>	The Show Impact pane toolbar contains most of the buttons in the IT Universe Manager toolbar.							
<topology map<br="">Sidebar></topology>	For details, see "Topology Map Sidebar" on page 210.							

Chapter 8 • IT Universe Manager

9

Reports

This chapter includes:

Concepts

► Topology Reports Overview on page 304

Tasks

- ➤ Compare CIs on page 305
- ► Compare Snapshots on page 307

Reference

- ► Cron Expressions on page 309
- ► Reports User Interface on page 310

Concepts

🚴 Topology Reports Overview

Topology reports provide a method of displaying the data from views in a report format. Every view defined in the Modeling Studio has a corresponding topology report. The report settings are defined in the view definition in Report mode in the Pattern View Editor. For details, see "Pattern View Editor" on page 413.

For details on selecting the CIs to be displayed in a view, see "Working with the CI Selector" on page 155.

Templates and perspectives do not have topology reports. However, template-based views do have topology reports. The reports settings for such views are based on the settings defined in the base template or perspective.

Several additional reports are available in IT Universe Manager, including Asset Report, Compare CIs Report, Compare Snapshots Report, and Impact Analysis Report.

Tasks

聄 Compare Cls

This task explains how to compare the hierarchies of two compound CIs, view a CI's configuration file, and show the difference between two configuration files.


1 Select the Required Cls

In IT Universe Manager, select the two CIs you want to compare. The hierarchies of the two compound CIs are compared in the Compare CIs report (for details, see "Compare CIs Report" on page 313). You can choose to compare two CIs that appear in a selected view, or in the RTSM. For details, see "CI Selector" on page 163.

Example of Nonmatching Cls:

The following example displays the following:

- The No Matching Cl icon next to the CI LABM3QCRNDDB03 because it has no corresponding CI on the other side.
- The Show Different Attribute Values icon is displayed next to the MemorySize properties for the CIs LABM3QCRNDDB02 and LABM3ASTDB01 since they have different MemorySize values.



2 View a Cl's Configuration File

Select a CI of the CIT **Configuration File** and view the configuration file. For details, see "Compare CIs Report" on page 313.

3 Show the Difference Between Two Configuration Files

Select two CIs of the CIT **Configuration File** and view the difference between the two configuration files. For details, see "Compare CIs Report" on page 313.

膧 Compare Snapshots

This task describes how to take a snapshot of a view, and then compare two snapshots of a specific view taken at different times.

1 Take a Snapshot of a View

In IT Universe Manager, click the **Snapshot** button and select **Save Snapshot** to take a snapshot of a view and save it. For details, see the "Save Snapshot Dialog Box" on page 296.

2 Save Snapshots on a Periodic Basis

Optionally, you can schedule snapshots to be taken of a certain view at specific times by defining a task. For details, see "Schedule Snapshot Dialog Box" on page 327.

3 Compare Snapshots

Compare the snapshots of a view taken at different times. Click the **Snapshot** button and select **Compare snapshots**. For details, see "Compare Snapshots Report" on page 318.

Example of Snapshots of a View Taken at Different Times:

In the following example, the **Deleted Item** icon next to the **192.168.163.0** CI in the right pane, indicates that the CI has been deleted in the newer view.

6

Chapter 9 • Reports

Legend: 🛛 🔱 Contains An U	Jpdated Item 🔀	Deleted Item 🔺 New Item	n 🥃 Updated It
NetworkTopology		Wed Mar 10 11:16:18 IST	2010
Image: Constraint of the state of			
<u>F</u> ind:	\odot	<u>F</u> ind:	\bigcirc

Reference

💐 Cron Expressions

A Cron Expression is a string composed of six or seven fields separated by white space. Six of the fields are mandatory, and one is optional.

The following table contains the fields used in a Cron Expression.

Field Name	Allowed Values	Allowed Special Characters					
Seconds	0-59	, - * /					
Minutes	0-59	,-*/					
Hours	0-23	, - * /					
Day of month	1-31	, - * ? / L W C					
Month	1-12 or JAN-DEC	, - * /					
Day of week	1-7 or SUN-SAT	, - * ? / L C #					
Year (optional)	empty, 1970-2099	, - * /					

The following table contains examples of how to use Cron expressions.

Cron Expression	Meaning				
0 0 12 * * ?	The task runs every Wednesday at 12:00 PM.				
0 15 10 ? * *	The task runs at 10:15 AM every day.				
0 15 10 * * ? 2005	The task runs at 10:15 AM every day during the year 2005.				
0 0/5 14 * * ?	The task runs every 5 minutes starting at 2 PM and ending at 2:55 PM, every day.				
0 15 10 15 * ?	The task runs at 10:15 AM on the 15th day of every month.				

Cron Expression	Meaning				
0 15 10 ? * 6L	The task runs at 10:15 AM on the last Friday of every month.				
0 15 10 ? * 6#3	The task run at 10:15 AM on the third Friday of every month.				

For more details about Cron expressions, go to <u>http://confluence.zutubi.com/display/pulse0101/Project+Cron+Triggers</u>

💐 Reports User Interface

This section includes (in alphabetical order):

- ► Asset Report on page 311
- ► Compare CIs Report on page 313
- ► Compare Snapshots Report on page 318
- ► Impact Analysis Report on page 323
- ► Job List Dialog Box on page 325
- ► Schedule Snapshot Dialog Box on page 327
- ► Toolbar Options on page 329
- ► Topology Report on page 333

💐 Asset Report

This report displays a list of all the CIs in a specified view, their attribute values, as well as their child CIs in the RTSM. You use Asset reports to view and analyze the contents of the view and focus on the data that is of interest to you. For example, an Asset report can display a list of all the servers that are part of a specific application contained in the view.

View: SAN Topology Include information based on CMDB View									
Display Label						PrimaryDnsName			
⊡- 🕮 000E7FFD99F1						LABM3MAM11.devlab.ad			
🗕 🎩 16.59.56.213									

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager and click the Asset Report abutton.					
Important information	The report contains only the attributes whose Asset Data check box was selected in the Attributes tab in the CI Type Manager. For more details, see "Add/Edit Attribute Dialog Box" on page 489.					

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Elements (A-Z)	Description	
<toolbar></toolbar>	For details, see "Toolbar Options" on page 329.	
<shortcut menu=""></shortcut>	For details, see "IT Universe Manager Shortcut Menu" on page 283.	

UI Elements (A-Z)	Description			
Include information	Select one of the following:			
based on	 CMDB. Includes information from the selected view as well as information about the child CIs and their attribute values in the RTSM. 			
	By choosing this option, the report includes CIs that are connected by the Container qualifier to the CIs in selected view. For example, the report would include the CPU and memory of a server that is contained in the view.			
	➤ View. Includes only information about the CIs and their attributes that are contained in the selected view.			
View	Enables you to select a view by opening the View Selector. For details, see "CI Selector" on page 163.			
	Note: When you generate an Asset report from a specific view, the report retains the same hierarchical structure as the relevant view in the Topology Map.			

💐 Compare Cls Report

This report enables you to compare the hierarchies of two compound CIs. A compound CI is a CI that is linked to another CI by a relationship with CONTAINER qualifier. You can display the compared CIs and their child CIs that appear in a selected view, or in the RTSM.

Compared CI 000129F42269					
Compared CI 16.59.50.88 DefaultDomain	Compared CI 16.59.50.88 DefaultDomain				
Mutual View: unix_View_1					
Compare on: 🔘 View 🖲 CMDB					
Generate					
Legend: 🛛 Contains An Updated Item ≠ No N	Natching CI 😉 Updated Item				
000129F42269	16.59.50.88 DefaultDomain				
E -	E → 2 16.59.50.88 DefaultDomain				
<u>F</u> ind: 💿 🛇	<u>F</u> ind:				

To access	Select Admin > RTSM Administration > Modeling >	
	IT Universe Manager. Right-click a CI in the Topology	
	Map and select Compare Cls Report.	

Important information	 The Compare CIs page is divided into two panes. Each side displays a hierarchical tree structure of the CIs you selected. When you select a CI on one side, the corresponding CI on the other side is automatically selected, provided Synchronize Selection is pressed. You can compare only two CIs of the same CI type or one of the CI type's children in the hierarchy.
Relevant tasks	"Compare CIs" on page 305

UI Elements (A-Z)	Description
4	Finds the previous occurrence of an item marked as changed.
4	Finds the next occurrence of an item marked as changed.
	Show Configuration Files Differences. Shows the difference between the content of the two configuration files. Configuration files use the .xml, .txt or .ini extensions. Select a CI of the CIT Configuration File in both panes and slick the Show Differences button. A window opens
	and click the Show Differences button. A window opens displaying the differences (marked in blue) in the configuration files.
A.,	Show Only Different CIs in Tree. In the <properties panes="">, displays only the part of the tree structure containing CIs that do not match.</properties>
	Show Only Different Attribute Values. In the <properties panes="">, toggles between displaying all the comparable attribute values of the selected CI or only the attribute values that are different.</properties>

UI Elements (A-Z)	Description		
	Enables you to select a CI on one side and have its corresponding CI automatically selected on the other side.		
	The default state for the Synchronize Selection button is selected. Deselecting this button allows you to select different CIs from each of the two trees. This enables you to compare two different CIs and see their different properties.		
œ	Contains An Updated Item. Indicates that a CI's attribute value has changed. For example, a Contains an Updated Item icon is displayed next to the IpAddress CI in the figure below since the attribute of its child CI 10.168.100.2 icon has changed.		
*	No Matching Cl. Indicates that a CI in one pane does not match any corresponding CI in the other pane. The following example displays the No Matching Cl icon next to the Windows icon because it does not have a corresponding CI in the other pane.		
	□ • • • ■ 10.0.0.0 □ • • ● IpAddress □ • ● 10.0.0.2 □ • ● 10.168.100.2 □ • ● New Node □ • ● New Node • ● Windows		

UI Elements (A-Z)	Description			
G	Updated Item. Indicates that has changed.	t the attribute value of a CI		
	For example, the figure below shows that the CIs 10.0.0.2 and 16.59.124.1 display the Updated Item icon because they was updated with a new IP Network Mask value, as indicated by the Show Only Different Attribute Values icons (see the Name and Value columns in the bottom panes underneath the tree structure).			
	10.0.0.0	16.59.124.0		
		E→● 22 16.59.124.0 E→● ◎ lpAddress ◎ 16.59.124.1 ◎ New Node 		
	Eind: Image: Constraint of the second s			
	Name Value	Name Value		
	RoutingDomain DefaultDomain I IP Network Mask 255.255.0	RoutingDomain DefaultDomain P Network Mask 255.252.25		
	Enables you to move to the next or previous result of the search for the string entered in the Find field.			
<toolbar></toolbar>	For details, see "Toolbar Options" on page 329.			
<shortcut menu=""></shortcut>	For details, see "IT Universe Manager Shortcut Menu" on page 283.			

UI Elements (A-Z)	Description		
<properties pane=""></properties>	Displays the attributes of the selected CI. The Properties pane contains the following fields:		
	 Name. Displays the attribute name for the selected CI, which was marked as Comparable in the CI Type Manager. "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496 Value. Displays the attribute value for the currently selected CI. 		
<left and="" right<br="">panes></left>	Displays a tree of the compared CIs and their child CIs that appear in the selected view or in the RTSM, depending on whether you selected the View or the CMDB options.		
Compare in	 Select one of the following: CMDB. Includes the selected CIs and their child CIs that appear in the entire RTSM. View. Includes the selected CIs and their child CIs that appear only in a specific view. 		
Compared CI	Enables you to select the two CIs you want to compare. Click to open the CIs Selector dialog box. For details, see "CI Selector" on page 163. The CI you select in the top box is displayed in the left pane and the CI you select in the bottom box is displayed in the right pane.		
Find	Find. Enter a search name or a portion of a search name in the Find field to locate it in the list.		
Mutual View	If the CIs that you are comparing both exist within the same view, the name of that view is displayed in this field. Otherwise, the field displays the words No mutual view .		

💐 Compare Snapshots Report

This feature enables you to compare two snapshots of a specific view taken at different times. It enables you to visualize the differences between the views by comparing the statuses of the view at the times the snapshots were taken.

Compare Snapshots displays the status of a view in one snapshot by comparison with its status taken at a different time. You can compare a current snapshot to a previous snapshot or two snapshots both taken in the past.

Ompare Snapshots Report 1* X						
📴 Report Parameters 🛛 🗒 🐚 🖂 💾 😂 🔸 🎦 🔸 😫 🗛 📣 🖉 🗛 🍅						
View with snapshots	Netv	vorkTopology	/			-
Available Snapshots		Time	Descrip	Owner	Size	Note
		Current	Current		3,861	
		Mon Apr	snapshot2		3,861	
		Mon Apr	snapshot1		3,861	
Generate						
Legend: ♥ Contains An Updated Item ≭ Deleted Item ★ New Item ↔ Updated Item						
NetworkTopology Mon Apr 12 14:34:56 IDT						
⊕ - □□ 10.0.0.0 ⊕ - □□ 10.10.1.0 ⊕ - □□ 10.168.100.0 ⊕ - □□ 10.168.252.4 ⊕ - □□ 10.8.0.192			묘 10.0.0.0 묘 10.10.1.0 묘 10.168.10 묘 10.168.25			

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager. Click the Snapshot 🛗 button and select Compare snapshots.	
Important information	 You can compare a current snapshot to a previous snapshot or two snapshots both taken in the past. You can define a schedule that takes snapshots of a specific view on a periodic basis and saves them. For details, see "Schedule Snapshot Dialog Box" on page 327. Snapshots of views that are marked as Track Changes are created on a daily basis. 	
Relevant tasks	 "Compare Snapshots" on page 307 	
See also	 "Save Snapshot Dialog Box" on page 296 "Schedule Snapshot Dialog Box" on page 327 	

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Elements (A-Z)	Description	
8	Expands the entire hierarchical tree structure of the CIs you selected.	
85	Collapses the hierarchical tree structure of the CIs you selected.	
4	Finds the previous occurrence of an item marked as changed.	
4	Finds the next occurrence of an item marked as changed.	
Ø	Show Configuration Files Differences. Shows the difference between the content of the two configuration files. Configuration files use the .xml , .txt or .ini extensions.	
	Select a CI of the CIT Configuration File in both panes and click the Show Differences button. A window opens displaying the differences (marked in blue) in the configuration files.	

Chapter 9 • Reports

UI Elements (A-Z)	Description
160	Show Only Different CIs in Tree. In the <properties panes="">, displays only the part of the tree structure containing CIs that do not match.</properties>
	Show Only Different Attribute Values. In the <properties panes="">, toggles between displaying all the attribute values of the selected CI or only the attribute values that have changed.</properties>
100 100	Enables you to select a CI on one side and have its corresponding CI automatically selected on the other side.
	The default state for the Synchronize Selection button is selected. Deselecting this button allows you to select different CIs from each of the two trees. This enables you to compare two different CIs and see their different properties.
<u>,</u>	Contains An Updated Item. Indicates that a CI's attribute value has changed. For example, a Contains an Updated Item icon is displayed next to the 10.0.0.0 CI in the figure below since the attribute of its child CI 10.168.100.3 icon has changed.
	10.0.0.0 □ ↓ @ IpAddress □ 0.168.100.2 ↓ @ Windows Eind: ○ ○
	NameValueRoutingDomainDefaultDomP Network Mask255.0.0.0
×	Deleted Item . Indicates that a CI has been deleted from the view.

UI Elements (A-Z)	Description
*	New Item. Indicates that a new CI has been added to the view.
U	Updated Item. Indicates that the attribute value of a CI has changed. For example, the figure below shows that the CIs LABM3MAM16 displays the Updated Item icon because it was updated with a new Version value, as indicated by the Show Only Different Attribute Values icons (see the Name and Value columns in the bottom panes underneath the tree structure).
	sanity rep Sun Apr 11 10:55:08 IDT
	LABM3LTDB01 LABM3LTDB01 LABM3LTDB01 LABM3LTDB02 LABM3LTDB01 LABM3LTDB02 LABM3LTDDB01 LABM3LTDDB02 LABM3LTDDB02 LABM3LTDDB02 LABM3LTDDB02 LABM3LTDDB0 LABM3LTDB02 LABM
	Name Value Name Value
	DiscoveredProduc MSSQL DB DiscoveredProduc MSSQL DB Application Category Database Application Category Database Application Versio Application Versio Application Versio ProductName sql_server_datab ProductName sql_server_databa I Version I Version 2005
<left and="" right<br="">panes></left>	Displays a hierarchical tree structure of all the CIs in the view for that snapshot version. The left side always represents the newer of the two versions.

Chapter 9 • Reports

UI Elements (A-Z)	Description
<properties pane=""></properties>	Displays the attributes of the selected CI.
	The Properties pane contains the following fields:
	► Name. Displays the name of the selected CI as defined in the CI's label.
	► Value. Displays the attribute value for the currently selected CI.
<toolbar></toolbar>	For details, see "Toolbar Options" on page 329.
Available Snapshots	Displays the current status and previously saved snapshots of the view selected in the View with Snapshots field. Select the two snapshots you want to compare.
	Note: Visible when Show Report Parameters button is pressed.
View with snapshots	Displays the name of the view whose snapshots you want to compare. Only views for which snapshots have been taken are displayed.
	Note: Visible when Show Report Parameters button is pressed.

💐 Impact Analysis Report

This report displays a list of CIs that are impacted in the system as a result of simulated changes. For details, see "Run Impact Analysis Dialog Box" on page 294.

😭 Report Parameters	
riggered Cls: C2	Severity: Major(7) 💌 Rule Bundle: UCMDB
Generate	
	Triggered CIs Grouping by CIT Affected Application
Show CI instances of:	structure Element (3) 💌 💥 📑 😂 🔣 🚉 🍳
	Display Label
📇 labm2am11	
1112222	
📇 labm2am04	

To access	In IT Universe Manager, click Generate Report from the Run Impact Analysis dialog box.
See also	 "Impact Analysis Manager" on page 449 "Run Impact Analysis Dialog Box" on page 294

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Elements (A-Z)	Description
<toolbar></toolbar>	For details, see "Toolbar Options" on page 329.
Rule Bundle	Enables you to select the rule group with which the Impact Analysis rule works.
Severity	Sets the severity level that we want to simulate for the triggered CIs.
Triggered CIs	Select the CIs that represent the changes you want to make to the system. Opens the CI Selector.

Affected Application Tab

This tab displays all the CIs that belong to a specific business application, which were affected by the triggered CI severity change.

User interface elements are described below:

UI Elements (A-Z)	Description
Display Label	The name of the CI or relationship as it appears in the toplogy map.
Trigger Severity	The severity selected in the Severity box.

Grouping by CIT Tab

This tab displays all the CIs related to the triggered CIs that are impacted in the system as a result of the simulated changes, sorted by CI type.

User interface elements are described below:

UI Elements (A-Z)	Description
Display Label	The name of the CI or relationship as it appears in the toplogy map.
Trigger Severity	The severity selected in the Severity box.

Triggered Cls Tab

This tab displays all the CIs that represent the changes you want to make to the system. The CIs in this tab are the CIs selected in the **Triggered CIs** box.

UI Elements (A-Z)	Description
Display Label	The name of the CI or relationship as it appears in the toplogy map.

💐 Job List Dialog Box

This dialog box displays a list of the reports/snapshots that were scheduled to run in the "Schedule Snapshot Dialog Box" on page 327.

To access	Select Admin > RTSM Administration > Modeling >
	IT Universe Manager. Click the Snapshots ដ button,
	and select Show Scheduled Snapshot Jobs.

User interface elements are described below:

UI Elements (A-Z)	Description
*	Insert New Scheduled Report. Define a new job using the Schedule Job dialog box.
0	Edit Job. Edit the selected job using the Schedule Job dialog box.
Ð	Create Copy. Enables you to create a copy of the selected job. Opens a new job in the Schedule Job dialog box that uses the details of the selected job.
×	Remove Job. Deletes the selected job from the list of scheduled jobs.
	Run Job Immediate. Runs the selected job.
00	Pause Job. Pauses the selected job. Enabled only if the job has a Pending status.
()	Resume Job. Resumes the selected job.
	Note: The Resume button is enabled only for jobs that have a Paused status.
0	Refreshes the list of scheduled jobs.
¥	Clears the current filter.
	Change visible columns. Enables you to select the columns to be displayed.

Chapter 9 • Reports

UI Elements (A-Z)	Description
Current Status	The current status of each scheduled job:
	► Running. The job is currently executing.
	 Pending. The job is waiting for the scheduling requirements to be fulfilled.
	 Completed. The job has finished executing. Paused. The job has been paused.
	Note. If a job has a Completed status, and you want to resume running the job, you can either click Run Job Immediate or change the Next Execution Time to the current time. If you change it to a future time, the status changes to Pending .
Description	A description of the scheduled job as defined in the Schedule Job dialog box.
Execution Status	The job's current execution status:
	► Success. The job completed successfully.
	► Failure. The job failed to execute.
	► None. The job has not yet been executed.
Job Type	A scheduled job can either be Schedule Report or Schedule Snapshot .
Last Execution Time	The last time the report ran.
Name	The name of the scheduled job as defined in the Schedule Job dialog box.
Next Execution Time	The next time the report is scheduled to run.

💐 Schedule Snapshot Dialog Box

This dialog box enables you to define a schedule for taking snapshots of a specific view. You can see the list of reports/snapshots that have been scheduled to run in the "Job List Dialog Box" on page 325.

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager. Click the Snapshots 📸 button in the CI Selector, and select Schedule Snapshot.
Relevant tasks	 "Compare CIs" on page 305 "Compare Snapshots" on page 307

The following elements are included:

UI Elements (A-Z)	Description
Validate	Click to validate the Cron expression you entered in the Cron Expression box.
Cron Expression	Enter a Cron expression to schedule a job. For a description of the fields used in Cron expressions and examples of how to use them, see, "Cron Expressions" on page 309.
Description	A description of the scheduled job.
Ends	Select one of the following options:
	 Never. Do not specify an end date. Not relevant if you define a report to run only once. Until. Choose the date and time by which you want the action to stop running. Relevant only if you are using Cron expressions.
Locale	Select the language for the report.
Name	The name of the scheduled job.

Chapter 9 • Reports

UI Elements (A-Z)	Description
Repeat	Select one of the following actions:
	► Once. Activates a job only once.
	► Daily. Runs a job on a daily basis.
	➤ Weekly. Runs a job on a weekly basis. Select the day or days on which you want the action to run.
	➤ Monthly. Runs a job on a monthly basis. Select the month or months in which you want the job to run.
	► Yearly. Runs a job on a yearly basis.
	Cron. Use a Cron expression to schedule a job. For a description of the fields used in Cron expressions and examples of how to use them, see, "Cron Expressions" on page 309.
Repeat every	(Appears only when you select Daily , Weekly , Monthly or Yearly .) Select a value for the interval between successive runs.
	For example, if you select Weekly and then 2 , the job runs every second week.
Server Time	The exact server time according to the client's time zone.
Starts	Choose the time and date when you want the job to begin running.
Time Zone	Set the required time zone.

💐 Toolbar Options

This section describes the toolbar options for reports.

UI Elements (A-Z)	Description
Report Parameters	Displays the parameters that are defined for the report.
	Save Report. Saves the selected report.
٠	Schedule Report. Opens the Schedule Job dialog box, which enables you to define a job that:
	► Schedules the generation of a report
	 Specifies one or more formats in which to send the report, and the report's recipients Specifies the recurrence of the job
	For more information on the Schedule Job dialog box, see, "Schedule Snapshot Dialog Box" on page 327.
	Note: This option is available only before you generate a report or when you open a saved report.
	Send Mail. Opens the Send Mail dialog box. You can send an email containing the generated report in various formats, or as a direct link. For details on the various formats, see "Export Report." on page 330.
	Select one or more of the available formats for the generated report to be sent as attachments to an email recipient.
	Note: Required fields are marked with an asterisk.
9	Archive Report. Enables you to save the report results in the database. After the report is archive, a sicon appears next to the report name.
	Note: Enabled only for Topology reports.
ê	Generate Direct Link. Creates a direct link to the specific location on the server of the selected report, or to the data that you have exported as a specific format.

UI Elements (A-Z)	Description
F	Export Report.
	Enables you to select the export format for the report. The available options are:
	Excel. The report data is formatted as an .xls (Excel) file that can be displayed in a spreadsheet.
	► PDF. The report data is exported in PDF format.
	 CSV. The report data is formatted as a comma- separated values (CSV) text file that can be displayed in a spreadsheet.
	Note: For the CSV formatted table data to display correctly, the comma (,) must be defined as the list separator. In Windows, to verify or modify the list separator value, open Regional Options from the Control Panel, and on the Numbers tab ensure that the comma is defined as the List Separator value.
	➤ XML. The report data is formatted as an XML file that can be opened in a text or XML editor.
	Tip: To extract HTML code from the report:
	► Open the file in an HTML editor
	 Copy the relevant table into the target file
III Bar Chart	Bar Chart. Displays the generated report as a bar chart.
🌍 Pie Chart	Pie Chart. Displays the generated report as a pie chart.
III Table	Table. Displays the generated report in tabular format.
	Show Short Labels. Toggles between displaying the chart labels minimal/maximum information.
	Note: This option is available only for pie charts.
:=	Show Legend. Toggles between hiding and displaying the chart's legend.
	Note: This option is available only for pie charts.

UI Elements (A-Z)	Description
*	Slice chart. Toggles between displaying the pie chart with exploded and unexploded segments.
	Note: This option is available only for pie charts.
8	Expand All. Expands the tree structure.
85	Collapse All. Collapses the tree structure.
×	Delete from CMDB. Deletes the selected CI from the CMDB.
	Opens the Configuration Item Properties dialog box for the selected CI.
0	Refresh. Refreshes the report tree.
	Select Columns. Select the columns you want to display in the report.
≜ ↑	Sort Column Content. Enables you to set the sort order of the selected column's content.
Q	Find. Toggles between displaying and hiding the Find utility.
	Find the next occurrence of the phrase/Find the previous occurrence of the phrase. Enables you to move to the next or previous result of the search for the string entered in the Find field.
	Highlights all occurrences of the phrase. Highlights all occurrences in the CI tree of the string entered in the Find field.
Generate	Generate Report. Enables you to generate the selected report.
Generate	Note: This button appears disabled prior to defining the report parameters.

Chapter 9 • Reports

UI Elements (A-Z)	Description
<breadcrumbs></breadcrumbs>	Displays the levels through which you have navigated to get to the current level. Appears horizontally across the top of the chart. Note: Each level in the list of breadcrumbs is a clickable link.
<generated report=""></generated>	Displays the active generated report.
Find	Enter a search name or a portion of a search name in the Find field to locate it in the list.

💐 Topology Report

This report displays the topology of a view in report format.

To access	Select Admin > RTSM Administration > Modeling > IT Universe Manager and click the View Based Report button.
Important information	Every view in the RTSM can be displayed in report format. You define the settings for the report in the Report tab of the view in Modeling Studio.

User interface elements are described below:

UI Elements (A-Z)	Description
<bar graph="" pie<br="">chart></bar>	Each segment of the pie chart/column in a bar graph represents a CI on the selected level of the view.
	Click a slice/bar to drill down to the next level, if one exists. You can also display the information in table format.
	When you hold the mouse over the relevant segment/bar, a tooltip indicates the number of instances there are for that CIT, the percentage of the pie it represents (when viewing the information in pie chart format), and the CIT or CIT attribute the slice/bar represents.
<toolbar></toolbar>	For details, see "Toolbar Options" on page 329.

Chapter 9 • Reports

10

Modeling Studio

This chapter includes:

Concepts

- ► Modeling Studio Overview on page 337
- ► View Formats on page 338
- ► Building a Business View on page 339
- ➤ Templates and Perspectives on page 342
- ► Predefined Folders and Views on page 343
- ► Creating Template Based Views on page 345
- ► Business CI Models on page 346
- ► Building a Perspective Based View on page 349
- ► Revealed CIs and Watchpoints on page 354

Tasks

- ► Create a Pattern View on page 359
- ► Create a Template on page 360
- ► Create a Perspective on page 362
- ► Create a Template Based View on page 365
- ► Create Multiple Template Based Views on page 367
- ► Define Report Settings on page 369
- ► Build an Instance-based Model on page 370
- ► Build a Pattern-based Model on page 372
- ► Build a Perspective-based View Based on a Model on page 374

- ➤ Build a Perspective-based View Based on a Collection of CIs on page 374
- ► Build a Business CI Model Scenario on page 375

Reference

► Modeling Studio User Interface on page 378

Tip: For more information about using Modeling Studio in HP Business Service Management, see "Best Practices for Modeling" on page 215.

Concepts

🚴 Modeling Studio Overview

Modeling Studio is a tool for creating and managing views. You can create your own views, or work with the out-of-the-box (factory) views provided with your HP Business Service Management installation.

The IT Universe model in the configuration management database can be very large, holding thousands of configuration item (CI)s. A view enables you to build a subset of the overall IT universe model, containing only those CIs relating to a specific area of interest. You can define your own views to display only the information that is relevant to your organization's business needs.

The views are used to display performance status in Service Health, and for setting up SLAs in Service Level Management. HP Business Service Management supports three view formats: pattern views, template based views, and perspective based views, which are populated through different processes. For details, see "View Formats" on page 338.

👶 View Formats

HP Business Service Management supports three view formats, by which to populate your view:

- ➤ Pattern views are built from a Topology Query Language (TQL) query that defines the structure of the view. You can create a new TQL query as you build the view or base the view on an existing query. The view displays only those CIs and relationships that satisfy the query definition. When the view is displayed or refreshed, the Modeling Studio queries the RTSM for all elements that fit the query, and automatically updates the view with those elements.
- ➤ Template based views are based on a TQL query, to which a template is then applied. The template is a reusable view that includes parameters, which are saved as part of the template. This enables you to build multiple views with the same settings without having to re-enter the parameter information. The view displays only those CIs and relationships that satisfy the query definition and the conditions of the template. For details on templates, see "Templates and Perspectives" on page 342.
- ➤ Perspective based views are built by selecting a collection of individual CIs and applying a special type of template, known as a perspective, to it. Instance views, which no longer exist, are replaced by perspective based views. For details on perspectives, see "Templates and Perspectives" on page 342.

When you select a view for editing from the view tree in the left pane, it opens on the editing pane in the appropriate editor.

\lambda Building a Business View

In the Modeling Studio, you can define your own views to model your business environment.

This section includes the following topics:

- ► "The Structure of a View" on page 339
- ➤ "Setting the View Hierarchy" on page 340

The Structure of a View

The views you create should provide the business users with logical representations of your company's structure, processes, and goals. To meet these requirements, you generally build multiple views representing different aspects of your business; for example, you could build business views that revolve around any of the following:

- Company structure, so that data is organized by the geographical location of branches, or by data centers.
- Business processes, so that data is organized by line of business, or by applications.
- > Business goals, so that data is organized by sales, or by key customers.

The views depend on the particular demands of your organization and the actual hierarchical structure of the views should reflect those demands.

The usual hierarchical format of a view is as follows:

- ➤ Top level. The highest levels of the view, consisting of the root CI and the branches below it, are normally built from logical Business CI types such as Location, Line of Business, Customer, Application, and so on.
- ➤ Intermediate level. The intermediate branches of the view normally consist of System CI types, representing actual hardware and software and/or monitoring group CI types, representing groups containing monitors.

➤ Bottom level. The lowest level of the view, consisting of leaf CIs at the ends of the subtrees, is built from the Monitor CI types. These CIs receive the actual data from the data sources, used to determine KPI status all the way up the view subtrees, and so provide business context to the view.

Note: The bottom level is only relevant when a monitoring solution such as HP Business Service Management is connected and modeled in the RTSM.

Setting the View Hierarchy

The Pattern View Editor enables you to set the view hierarchy using the Hierarchy pane on the right side of the screen. There are two methods available for setting the hierarchy: **Manual** and **Rule-based**. The manual method is selected by default.

Manual Hierarchy Method

In the manual hierarchy method, the query nodes of the view are displayed in a tree format. You can create the hierarchy by manually dragging a selected query node under another query node or by using the toolbar buttons. The system only allows you to move a query node under another query node when the resulting hierarchy is valid. For details, see "Hierarchy Pane" on page 414.

It is possible to place a single query node from the view into the hierarchy multiple times. You can then adjust the hierarchy so that the query node appears in different layers, according to the required layout. The view results in such an instance would be the same as if you added another query node to the TQL query. Using the same query node twice in the hierarchy enables you to achieve the desired view results using a simpler TQL query.

Query Node Grouping

When setting the view hierarchy manually, you can create subgroups to group CIs by different criteria for the convenience of viewing the display. Click the **Add Group By** button and select one of the options. You can create a subgroup for CIs of the same type in the Topology Map using the **Add Group by CI Type** option. You can create a subgroup for a specific query node by selecting the **Add Group by Query Node** option. You can group CIs by a common attribute using the **Add Group by Attribute** button and entering a regular expression as described in "Query Node Grouping Dialog Box" on page 425. For details about regular expressions, see "Regular Expression Examples" on page 575.

You can also create nested groups (a query node group inside another query node group) to help fine-tune the TQL query results that are displayed in the Topology Map.

For example, after grouping query nodes of type node by their CIT, you can use their **operation state** attribute to create more focused groups.

Rule-Based Hierarchy Method

In the rule-based hierarchy method, you define hierarchy rules, using the Hierarchy Rules dialog box. You select a source CIT, target CIT, relationship type, and relationship direction, which define the conditions for a hierarchy rule. Any CIs in the view which satisfy the defined conditions are subject to the rule, that is, the target CI is placed on the layer below the source CI. For details on defining hierarchy rules, see "Hierarchy Rules Dialog Box" on page 388.

Templates and Perspectives

A template is a reusable pattern view with defined parameters. You use templates to build template-based views, setting the values of the parameters for each specific view. Any changes made to a template affect all existing views based on that template.

Template-based views can be opened in IT Universe Manager, like pattern views. You can also open the template itself in IT Universe Manager to view the results for various parameter values. If you want to save the results, you must save it as a template-based view. You define templates, template-based views, and pattern views in the Pattern View Editor.

Perspectives are a type of template designed to be applied to a specific collection of CIs, similar to the pattern in a pattern view. For example, a perspective could comprise a node containing an IP Address. In that case, the resulting perspective-based view would include all the CIs from among the CIs in the CI selection, along with the IP Addresses contained in the node CIs.

The most basic perspective is known as the Content Only perspective and consists of only the query node itself. If you apply the Content Only perspective to a CI collection, the resulting view contains only the selected CIs themselves.

Perspectives are also created and edited in the Pattern View Editor. You can have multiple views, templates, and perspectives open in the Pattern View Editor simultaneously, each with its own tab.

Perspectives do not appear in the list of views in IT Universe Manager, however perspective-based views can be opened in IT Universe Manager, like all other views. For details, see "Building a Perspective Based View" on page 349.

In summary, the Views tree in the Resources tab of the CI Selector in the Modeling Studio can include five distinct entities:

- ➤ pattern views
- ➤ templates
- ► template based views

- ➤ perspectives
- ► perspective based views

You can filter the tree to select the types of views or templates to display.

The following table summarizes the types of views and where they are created and viewed:

Type of View	Created in:	Can be opened in IT Universe Manager
Pattern View	Pattern View Editor	Yes
Template	Pattern View Editor	Yes, for the current session only
Template-based View	Pattern View Editor	Yes
Perspective	Pattern View Editor	No
Perspective-based View	Perspective-based View Editor	Yes

Predefined Folders and Views

The Views tree in the Resources tab of the CI Selector in the Modeling Studio includes predefined folders and views, as described in the following sections:

- ▶ "Predefined Folders" on page 343
- ► "Factory Views" on page 344
- ► "Predefined Perspectives" on page 344

Predefined Folders

The hierarchical file folder system in the CI Selector can help you organize your views. Predefined folders are provided for the out-of-the-box views; you can modify these folders, or add additional folders according to your organization's requirements.

Factory Views

Your HP Business Service Management installation includes out-of-the-box pattern views, templates, and perspectives. These views provide a quick start for working with the RTSM for setting up SLAs, and for viewing system performance information in Service Health.

The out-of-the-box views are initially empty. As soon as CIs are added to the RTSM by one of the CI generators, the TQL query built into each pattern view is able to identify the CIs that meet the pattern requirements, and add them to the view.

Views for CIs are created when a discovery process is run; the out-of-the-box views that are provided correspond to the relevant Data Flow Management (DFM) packages. For example, the Oracle view **(Root > Database > Oracle > Oracle)** is populated with CIs that are created when Data Flow Management activates the Database - Oracle module. For details on running DFM, see "How to Use Discovery Control Panel – Advanced Mode Workflow" in the *RTSM Data Flow Management Guide*.

For details on the cross-application processes for setting up the SAP views, see "Application Management for SAP Reports and Views" in *Solutions and Integrations*.

Some of the out-of-the-box views are set by default to display in specific HP Business Service Management applications. There are some out-of-the-box views that are hidden by default.

Some of the out-of-the-box views are considered basic to the system and cannot be deleted from the folders.

Predefined Perspectives

HP Business Service Management also provides out-of-the-box perspectives. One example is the Content Only perspective, which includes only the elements of the view content itself, without any additional CIs. The following out-of-the-box perspectives are intended to be used in Service Health:

- ➤ System Monitors only. This perspective enriches the model by adding child CIs down to the level of monitors. Use this perspective to create a Service Health view that includes System monitors only.
- ➤ End User Monitors. This perspective enriches the model by adding child CIs related to the end user experience of the application, such as Business Transaction and Business Transaction Flow. Use this perspective to create a Service Health view that includes monitoring statuses for End User Management only.
- ➤ Impact. This perspective enriches the model with all child CIs related by impact links. Use this perspective to configure additional monitors using the Monitor Deployment Wizard.
- Model and Dependency Hierarchy. This perspective enriches the model with all dependent CIs in the RTSM. Use this perspective to create a view with the full model hierarchy.
- ➤ APM Perspective. This perspective enriches the model with Business Transactions Flow and Business Transaction CIs. Use this perspective to add related infrastructure elements and SiteScope monitors to create a view that includes all APM information.

\lambda Creating Template Based Views

Template-based views based on the same template contain the same query nodes and relationships. They differ only in their parameter values. You create template-based views using the Template-based View wizard. The wizard enables you to create multiple views at one time based on the same template. When creating multiple views, you have the option of entering parameter values manually or importing them from a CSV file. The CSV file must be formatted correctly for the wizard to import the values. It must contain the name of at least one of the template parameters in the first row and it must contain at least one record. The records should be in separate rows and the parameter values for each record should be in the same row, separated by commas. The wizard also provides an Advanced Naming feature, which enables you to define an expression for the view names based on parameter values. For example, if your base template is called **Server_Template**, and one of the template parameters is **Serial Number**, you could define the view names to be **Server <Serial Number**>. In this way, the wizard automatically inserts the respective value of the parameter Serial Number into the name of each view.

An alternate way to assign names to the views when importing values from a CSV file is to include a column in the file called **template_based_view_name**. The file entries corresponding to this column are automatically entered by the wizard as the view names. Note that this naming method overrides the Advanced Naming feature; that is, view names are assigned the entries in the template_based_view_name column of the file, even when the Advanced Naming feature is selected.

For details on creating template-based views, see "Template-based View Wizard" on page 434.

You can also edit the parameters of a template-based view when the view is open in the Editor, from the Template Parameter Values dialog box. For details, see "Template Parameter Values Dialog Box" on page 440.

You cannot edit the report layout for a template-based view. To change the report layout, you need to make changes in the base template of the view.

\lambda Business CI Models

This section includes the following topics:

- ► "Instance-based Models" on page 347
- ▶ "Pattern-based Models" on page 348

The collection of CIs which compose the view content of perspective-based views can be selected in two ways. You can select CIs from the CI Selector and drag them onto the editing pane. In this case, you can build a view by applying a perspective to the collection and the collection cannot be reused in another view without repeating the selection process. The other way to select the CIs to appear in the view is by creating a model.

A model is a reusable collection of CI instances that define a business entity, such as a business service or line of business. By creating a model, you are building a CI collection that can be reused with other perspectives to create different views. Any changes you subsequently make to the model are reflected in all the views based on that model. There are two types of models: instance-based models and pattern-based models.

Instance-based Models

You build an instance-based model by first selecting a business CI to serve as its basis. The available business CIs include group, application, business service, business unit, and line of business. Then, you can add CIs to your model in the following ways:

- > Manually, by dragging CIs from the CI Selector into the Model Editor
- Revealing related CIs using a reveal path and selecting the ones to add to the model
- Defining a watchpoint for a selected CI and automatically adding CIs to the model

You can also begin building a model by dragging CIs onto the empty canvas and selecting **Create a new model**.

The model you create is a CI itself and the CIs in your model are related to the model by **Contains** relationships. You must save your model before applying a perspective to it to build a view.

Caution: The changes you make in a model affect the entire universe, not just the views based on that model. Thus, if you delete a CI from a model, you are deleting the relationship that existed between the CIs from the RTSM.

When working in IT Universe Manager, you can add selected CIs directly to a new model or an existing model. For details, see "Add CIs to Model Dialog Box" on page 259.

Pattern-based Models

Another type of model you can build is a pattern-based model. In a patternbased model, you define a TQL query to determine the CIs included, rather than selecting them manually. You can base your pattern-based model on an existing TQL query or create a new TQL query.

You must designate at least one query node in the model's TQL query as output for the model. The CIs of that type which match the pattern of the TQL query are the ones included in the model output.

The pattern-based model created is saved as a CI like an ordinary model, and can be used to form the content of a perspective-based view. The new TQL query created is saved as an ordinary query and can be used as the basis for a pattern view.

\lambda Building a Perspective Based View

A perspective based view is composed of perspectives applied to a model or a collection of CIs. The perspective is a special type of template which is designed to be applied to a subset of the IT Universe model.

The Content pane of the Perspective-based View Editor displays the models or CIs you have selected to serve as the basis of your view. The Perspective pane displays the selected perspectives. The Preview pane displays the resulting view based upon your content and perspective selections. When you make a change in the content or perspective selections, the view is updated accordingly in the Preview pane. For details, see "Perspective-based View Editor" on page 419.

This section includes the following topics:

- ► "Content" on page 349
- ► "Perspectives" on page 350
- ➤ "Views Based on Multiple Perspectives" on page 351
- ➤ "Including and Excluding Child CIs" on page 352

Content

The content in a perspective based view can be selected in two ways:

- ➤ You can add individual CIs to the view manually, using the CI Selector. The CIs in the collection are independent of each other. In this case, the collection of CIs is not defined as a model and cannot be reused in another view.
- ➤ You can add one or more models to the view, using the CI Selector. Alternatively, you can start by working with a model in the Model Editor and select Generate View for Selected Model to build a view based on that model. In this case, the identical content can be used to build another view by selecting the same models.

You can select both individual CIs and models to form the content of a perspective based view, however in that case, the models are treated as ordinary CIs. The models themselves are included in the view without their hierarchy of child CIs.


⊻.

When working in IT Universe Manager, you can add selected CIs directly to the content of a new or an existing perspective based view. For details, see "Add CIs to View Dialog Box" on page 260.

Perspectives

The perspectives you select for your view determine which CIs are included in the view. A perspective is a reusable pattern, similar to a template. The difference between a perspective and a regular template is that the perspective includes one or more query nodes designated as **contact query nodes**. A contact query node is a query node in the pattern which is used to apply the pattern to specific content and it is indicated by a small icon that appears next to the query node.

For example, in the following perspective, a query node of type Windows is designated as the contact query node and it has an IP Address related to it by a containment relationship.



When this perspective is applied to a CI collection, the resulting view contains all the CIs in the original collection as well as the IP Addresses connected to the Windows CIs in the collection (the CIs that were added by applying the perspective).

A perspective can have several contact query nodes, but every disconnected graph within a perspective must have at least one contact query node.

If you make a change to a perspective, all views based on that perspective are affected.

Views Based on Multiple Perspectives

You can select multiple perspectives to apply to the content of your view. There are two ways to select multiple perspectives:

- ➤ Perspective groups
- ► Perspective chains

In a **perspective group**, you select two or more perspectives to apply simultaneously to the same input content.

In a **perspective chain**, you select two or more perspectives at different levels of the view creation. The perspective in the first level is applied to the original view content to generate results in the form of a CI collection that serves as input content for the next level. The perspective in the second level is then applied to this content to generate the view results. You can build views based on multiple levels of perspectives, each one generating input content for the following level.

It is possible to apply both of the above methods at the same time, that is, by selecting multiple perspectives in each of the levels of a perspective selection.

For example, select a collection of **IP Subnet** CIs as your input content and select a perspective that adds the **node** CIs related to the IP Subnets as the first level perspective. The results of this stage consist of the original IP Subnets and their related nodes. Then add a second perspective level and select two perspectives for it: one that adds **CPU** CIs related to nodes and one that adds **File System** CIs related to nodes. The final results include the original IP Subnets, their related nodes, and the CPUs and File Systems related to those nodes.

These options help to simplify the process of creating a perspective-based view, by breaking down the functionality of a perspective into its component parts. Instead of building a separate large and complex perspective for each required view, you can construct a custom perspective combination to match the requirements of your specific case from smaller and more basic perspectives.

Including and Excluding Child Cls

When adding CIs that have children to a view, the CI and its children are only included in the view if the pattern of the perspective includes children for the selected CI type. In that case, children are included for all CIs of that type. After creating a view, you can hide specific CIs from the view by selecting the CI in the View Results pane and selecting **Hide CI from View** from the shortcut menu or clicking the **Hide CI from View** button in the toolbar. This option is only available for CIs that were added to the view via the perspective and were not part of the original content on which the view was based. Thus, if the view was based on a collection of CIs, the CIs in that collection cannot be hidden from the view. If the view was based on a model, the model itself cannot be hidden from the view, but the CIs contained in the model can be hidden.

When KPI status is calculated for a CI and displayed in Service Health, the status is based on all child CIs that exist in the RTSM for the parent CI. The Business Logic Engine calculates status from all child CIs attached to that parent CI, across all views. The calculation is based on all the relationships for the CI in the RTSM, without connection to the child CIs displayed in any particular view. To restrict the number of CIs displayed in the view, you can change the perspective to hide child CIs. This has no effect on KPI status – status is still calculated based on all child CIs, whether they are displayed in the view or hidden.

Whether or not all child CIs are displayed in the view does not influence the status calculations made for the parent CI and the status displayed in Service Health.

For example, the following pictures show status in Service Health for the same CI, Group1, in two views: In the first view, child CIs are included, and in the second, they are excluded. The same status result is shown for the CI in both views, regardless of the perspective in use.

p View Console Filters Geographical Map Custom Map Flow Map Reports			a* ⊫* ⊄
Hierarchy KPIs Business Impact	Alerts	Changes	& Incident
	Performance	Availability	Ack
0 ∰ <u>cnn2</u> ▼	<mark>©</mark> ↓ ₀	🛇 † ₀	
- · · · · · · · · · · · · · · · · · · ·	⊗ ↓ _o	Ø † ₀	8
acogle -	🔇 ¢ ₀	🔇 ¢ ₀	
google ▼	⊘ ¢ ₀	Ø ¢ ø	
p View Console Filters Geographical Map Custom Map Flow Map Reports			
PM_Profile1 -		•	a* 18* ⊄

When a CI has child CIs that are excluded from the view, the KPI tooltip in Service Health shows the number of hidden child CIs with KPIs attached, to indicate that the KPI status of the parent is based on CIs that are not in the view.

Details - Performance		
CI name:	fist_bpm_profile_1	
Status:	Critical	
Calculation Rule:	Worst Child Rule	
Held status since :	6/10/06 10:02:50 AM	
Hidden child CIs (with attached KPIs):	5	

You can use the **Find Visible and Hidden Child CIs** option to view information on hidden children. For details, see "How to Find Visible and Hidden Child CIs" in *Using Service Health*.

A Revealed CIs and Watchpoints

The Modeling Studio provides two advanced methods of adding CIs to an existing model: revealing related CIs and defining watchpoints.

This section includes the following topics:

- ► "Revealing CIs" on page 354
- ► "Watchpoints" on page 357

Revealing Cls

One approach to building a model is to add CIs related to the CIs in the model. The Modeling Studio provides a tool to help you reveal those CIs. The process of revealing related CIs involves constructing a reveal path, which is a chain of CI types that are related to each other. The first item in your reveal path is the CI type of the CI from which you started to reveal CIs. The Modeling Studio locates all of its related CIs and lists their CI types. By selecting one of those types, you build the next step of your path. All the related CIs of that type appear in the lower pane of the dialog box. You can select the ones you want to include in your model. The process is repeated to build the following step of the path.

For example:

1 If you begin to reveal CIs from a CI of type Windows, the Modeling Studio may reveal related CIs of types Interface, Network, and IP. If you select Network, the related CIs of type Network appear in the lower pane and can be added to the model by dragging them into the CIs Basket or clicking the CIs Basket icon:

veal Path: 📓 <u>Windows</u> 🖈				Save p
	СІ Туре	Conditions	CI coun	t
	Interface			-
	Network			
	T P			
(1) Drop CIs in order to add them to model	Eind:		Ci Type	
	·····································	Network	Citype	
			۵	
	Find:			

2 Click Next to build the next step of the path using Network as your selection. The Modeling Studio reveals related CIs of type Windows, Unix, and IP. Unix is selected and the Unix CIs appear in the lower pane and can be added to the model by dragging the selected ones into the CIs Basket pane:

eal Path:				Save
	СІ Туре	Conditions	Clc	ount
	S Windows			
	2 Unix			
	T IP			
I Drop CIs in order to add them to model	Name		CI Type	
	labm1hp4	Unix	Citype	
	labm1 np4	Unix		
	notredame	Unix		
	labm1sun05	Unix		
	labm1itg07	Unix		
	labm1itg10	Unix		
	labm1hp7	Unix		
	labm1itg02	Unix		

3 Click **Next** to build the next step of the path using Unix as your selection:

veal Path:	<u>Unix</u> ⇒			Save p
	CI Type	Conditions	CI count	
	🏶 SNMP			12
	OS User			122
	il Disk			12
	CPU			8
	Interface			23
	9년 Network			2
	SSH .			13
	Eind:	\bigcirc	\bigcirc	=
 Drop CIs in order to add them to model 	4			
	Name		CI Type	

In this case, a reveal path of **Windows > Network > Unix** was constructed. At each step, you have the option of adding any of the revealed related CIs to your model. For details on revealing CIs, see "Reveal CIs Dialog Box" on page 427.

It is also possible to construct a reveal path without revealing CIs. For details, see "Create/Edit/Save Reveal Path Dialog Box" on page 385.

Watchpoints

Another method of locating related CIs to add to the model is by defining a watchpoint for a selected CI in the model. A watchpoint is a mechanism which is triggered when a new related CI of a specified type is created. Every watchpoint is defined in connection with a reveal path. If a new related CI of any CI type included in the path is created, the watchpoint is triggered and an indicator appears next to the model. For details on defining a watchpoint, see "New Watchpoint Dialog Box" on page 409.

Note: You must save a new model before defining watchpoints for its CIs.

All the related CIs detected by the watchpoint are displayed in the Watchpoints Updates dialog box. The dialog box enables you to select the ones to add to your model and the ones to suppress, or exclude from your model. For details, see "Watchpoints Updates Dialog Box" on page 446.

You also have the option to include the detected CIs in your model automatically by selecting the check box in the New Watchpoint dialog box. In this case, all CIs detected by the watchpoint are added to the model.

A watchpoint can also be used to detect CIs included in the model which are no longer related to the model. If such CIs are found along the reveal path connected to the watchpoint, they also appear in the Watchpoints Updates dialog box. You can accept the suggestion to remove the CIs from your model, or you can suppress the suggestion, thereby keeping the CIs in your model.

Note: Although a watchpoint is defined for an individual CI, the watchpoint results display related CIs of the CI types included in the reveal path for all CIs in the model.

Tasks

🕆 Create a Pattern View

This task describes how to create a pattern view and define its TQL query.

This task includes the following steps:

- ➤ "Open a New View in the Pattern View Editor" on page 359
- ➤ "Add Query Nodes and Relationships to a TQL Query" on page 359
- ➤ "Set the View Hierarchy" on page 360
- ➤ "Define the Report Settings Optional" on page 360
- ► "Set Permissions" on page 360

1 Open a New View in the Pattern View Editor

Click the **New *** button and select **Pattern View**. In the New Pattern View dialog box, select the base TQL query on which your new view is based, or select **Create new query** to build a new TQL query. The Pattern View Editor opens. For details, see "New Pattern View/Template/Perspective Dialog Box" on page 407.

2 Add Query Nodes and Relationships to a TQL Query

Add the query nodes and relationships that define the query. For details on how to add query nodes and relationships to a TQL query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

Note: If you are starting with a blank view, you must add at least one query node in order to save your view.

3 Set the View Hierarchy

Set the hierarchy for the view by moving the required query nodes in the Hierarchy pane. For details, see "Setting the View Hierarchy" on page 340.

When you are finished, click **Save** 🛅 to save the view.

4 Define the Report Settings - Optional

Select the Report tab in the Pattern View Editor. Select the attributes you want to include in the report for each query node of the view. You can also set the order of the report columns, set the sort order of each column, and add a chart. For details, see "Define Report Settings" on page 369.

5 Set Permissions

Apply viewing and editing permissions to users and user groups for the new view. You set permissions in Admin > Platform > Users and Permissions, select a user or a group and select Permissions. For details, see "How to Assign Permissions" in *Platform Administration*.

隋 Create a Template

This task describes how to define a new template.

This task includes the following steps:

- ➤ "Open a New Template in the Pattern View Editor" on page 361
- ► "Add Query Nodes and Relationships to a TQL Query" on page 361
- ► "Set Parameter Values" on page 361
- ➤ "Set the Template Hierarchy" on page 361
- ➤ "Define the Report Settings Optional" on page 362
- ► "Set Permissions" on page 362

1 Open a New Template in the Pattern View Editor

Click the **New** button and select **Template**. In the New Template dialog box, select the base TQL query on which your new template is based, or select **Create new query** to build a new TQL query. For details, see "New Pattern View/Template/Perspective Dialog Box" on page 407.

2 Add Query Nodes and Relationships to a TQL Query

Add the query nodes and relationships that define the query. For details on how to add query nodes and relationships to a TQL query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

Note: If you are starting with a blank template, you must add at least one query node in order to save your template.

3 Set Parameter Values

Right-click a query node or relationship in the TQL query and select Query Node Properties. In the Attributes tab, add an attribute with a parameterized value. For details, see "Query Node/Relationship Properties Dialog Box" on page 85.

Note: If you do not set any parameters, when you try to save your template, you must save it as a pattern view.

4 Set the Template Hierarchy

Set the hierarchy for the template by moving the required query nodes in the Hierarchy pane. For details, see "Setting the View Hierarchy" on page 340.

When you are finished, click **Save** 🛅 to save the template.

5 Define the Report Settings - Optional

Select the Report tab in the Pattern View Editor. Select the attributes you want to include in the report for each query node of the view. You can also set the order of the report columns, set the sort order of each column, and add a chart. For details, see "Define Report Settings" on page 369.

6 Set Permissions

Apply viewing and editing permissions to users and user groups for the new template. You set permissions in Admin > Platform > Users and Permissions, select a user or a group and select Permissions. For details, see "How to Assign Permissions" in *Platform Administration*.

膧 Create a Perspective

This task describes how to define a new perspective.

This task includes the following steps:

- ➤ "Open a New Perspective in the Pattern View Editor" on page 363
- ➤ "Add Query Nodes and Relationships to a TQL Query" on page 363
- ➤ "Select a Contact Query Node" on page 363
- ► "Set the Perspective Hierarchy" on page 363
- ➤ "Define the Report Settings Optional" on page 364
- ► "Set Permissions" on page 364

1 Open a New Perspective in the Pattern View Editor

Click the **New *** button and select **Perspective**. In the New Perspective dialog box, select the base TQL query on which your new Perspective is based, or select **Create new query** to build a new TQL query. For details, see "New Pattern View/Template/Perspective Dialog Box" on page 407.

2 Add Query Nodes and Relationships to a TQL Query

Add the query nodes and relationships that define the query. For details on how to add query nodes and relationships to a TQL query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

3 Select a Contact Query Node

Select at least one query node in the TQL query to be a contact query node. Right-click the query node and select **Use As Contact Query Node**.

Note: If you do not select a contact query node, when you try to save your perspective, you must save it as a pattern view.

4 Set the Perspective Hierarchy

Set the hierarchy for the perspective by moving the required query nodes in the Hierarchy pane. For details, see "Setting the View Hierarchy" on page 340.

When you are finished, click **Save** 🛅 to save the perspective.

5 Define the Report Settings - Optional

Select the Report tab in the Pattern View Editor. Select the attributes you want to include in the report for each query node of the view. You can also set the order of the report columns, set the sort order of each column, and add a chart. For details, see "Define Report Settings" on page 369.

6 Set Permissions

Apply viewing and editing permissions to users and user groups for the new perspective. You set permissions in Admin > Platform > Users and Permissions, select a user or a group and select Permissions. For details, see "How to Assign Permissions" in *Platform Administration*.

膧 Create a Template Based View

This task describes how to define a single template based view.

This task includes the following steps:

- ► "Prerequisites" on page 365
- ► "Define a New Template Based View" on page 365
- ▶ "Select a Template" on page 365
- ➤ "Select the Method for Adding Parameter Values" on page 366
- ► "Set Parameters" on page 366
- ► "Set Permissions" on page 366

1 Prerequisites

If you want to base your view on a new template, create the template first. For details, see "Create a Template" on page 360.

2 Define a New Template Based View

You define a new template based view using the Template-based View wizard. Click the **New *** button and select **Template Based View**.

3 Select a Template

On the Select Template page of the wizard, select a template on which to base your view. For details, see "Select Template Page" on page 435.

4 Select the Method for Adding Parameter Values

On the Import Parameter Values page of the wizard, select the method for adding the parameter values. For details, see "Import Parameter Values Page" on page 436.

5 Set Parameters

On the Parameters page, enter the parameter values for the view. For details, see "Parameters Page" on page 437.

Note: You can also edit the parameters from within the Editor after creating the view, by selecting Show Parameters (P) from the toolbar or the shortcut menu.

When you are finished, click **Finish** to open the view in the Editor. Click **Save** to save the view.

6 Set Permissions

Apply viewing and editing permissions to users and user groups for that view. You set permissions in **Admin > Platform > Users and Permissions**, select a user or a group and select **Permissions**. For details, see "How to Assign Permissions" in *Platform Administration*.

膧 Create Multiple Template Based Views

This task describes how to define multiple template-based views.

This task includes the following steps:

- ► "Prerequisites" on page 367
- ➤ "Define New Template Based Views" on page 367
- ▶ "Select a Template" on page 367
- "Select the Methods for Adding Parameter Values and Naming Views" on page 368
- ► "Set Parameters" on page 368
- ➤ "Select the Location for Saving the Views" on page 368
- ► "Save the Views" on page 368
- ► "Set Permissions" on page 368

1 Prerequisites

If you want to base your views on a new template, create the template first. For details, see "Create a Template" on page 360.

2 Define New Template Based Views

You define new template based views using the Template-based View wizard. Click the **New *** button and select **Template Based View**.

3 Select a Template

On the Select Template page of the wizard, select a template on which to base your views. For details, see "Select Template Page" on page 435.

4 Select the Methods for Adding Parameter Values and Naming Views

On the Import Parameter Values page of the wizard, select the method for adding the parameter values. Also, if you want to use the Advanced Naming feature, select the check box on this page. For details, see "Import Parameter Values Page" on page 436.

5 Set Parameters

On the Parameters page, enter the parameter values for the view. If you selected to import the parameter values from a CSV file, they are automatically entered in the table. You can edit the view names and parameter values manually on this page. You can also add new views to the table or delete views from the table. For details, see "Parameters Page" on page 437.

6 Select the Location for Saving the Views

On the Select Location page, select the location in the view tree in which to save the new views. For details, see "Select Location for Views Page" on page 438.

7 Save the Views

On the Summary page, review the details of the views you created. If there are no further changes, click **Save** to save the views in the selected location.

8 Set Permissions

Apply viewing and editing permissions to users and user groups for each view created. You set permissions in Admin > Platform > Users and Permissions, select a user or a group and select Permissions. For details, see "How to Assign Permissions" in *Platform Administration*.

膧 Define Report Settings

This task describes how to define report settings for a view, template, or perspective.

This task includes the following steps:

- ► "Prerequisites" on page 369
- ➤ "Select Attributes to Appear as Report Columns" on page 369
- ➤ "Add Function Columns to the Report Optional" on page 370
- ➤ "Set the Sort Order of the Column Content" on page 370
- ➤ "Add a Chart to the Report Optional" on page 370

1 Prerequisites

After defining the content and hierarchy of a view, template, or perspective, you can define the report settings. Select the Report tab in the Pattern View Editor.

2 Select Attributes to Appear as Report Columns

For each query node in the view, select the query node in the Hierarchy pane and select the attributes to appear as columns in the report for that query node. You select attributes in the Query Node Definition pane by moving them from the Attributes list to the Report Layout list. Set the order of the columns using the arrow buttons in the Report Layout list. For details, see "Query Node Definition Pane" on page 416.

3 Add Function Columns to the Report - Optional

You have the option of adding a column for a selected query node consisting of data derived from a function performed on one of its child query nodes. Click the Add Function \int_{Φ} button to open the Add Function dialog box where you can select the relevant settings. For details, see "Add/Edit Function Dialog Box" on page 379.

4 Set the Sort Order of the Column Content

Click the Set Sort Order in button to open the Sort Column Content dialog box. Determine the columns by which to sort the report by moving columns from the Available Columns list to the Sorted Columns list. Use the arrow buttons to set the sort order of the columns. Use the Sort Ascending/Sort Descending buttons to set the sort direction for each column. For details, see "Sort Column Content Dialog Box" on page 433.

5 Add a Chart to the Report - Optional

You have the option of adding a chart to your report, in place of a table, for a selected layer of the view. When the necessary conditions for adding a chart are satisfied, the **Define Chart** link in the Chart Properties section of the Query Node Definition pane is active. Click the link and enter the chart settings. For details, see "Chart Properties" on page 418.

膧 Build an Instance-based Model

This task describes how to build an instance-based business CI model which can serve as the basis for a view.

This task includes the following steps:

- ► "Create the New Model" on page 371
- ➤ "Add CIs to the Model Manually" on page 371
- ► "Reveal CIs" on page 371
- ➤ "Define Watchpoints for CIs in the Model" on page 371

1 Create the New Model

In the Modeling Studio, click the **New** k button and select **Instance Based Model** to open the New Model dialog box. Select a CI type and enter the values for its properties. For details, see "New Model Dialog Box" on page 407.

2 Add CIs to the Model Manually

In the CI Selector, search for the CIs you want to include in your model. Select them and drag them into the model.

Tip: You can select more than one CI by holding the CTRL key while selecting CIs.

3 Reveal Cls

Select a CI in the model and reveal its related CIs along a reveal path. Add selected CIs from among the revealed CIs to your model. When you are done, save the model. For details, see "Reveal CIs Dialog Box" on page 427.

4 Define Watchpoints for CIs in the Model

Right-click a CI in the model and select **Watchpoint > New Watchpoint**. The New Watchpoint dialog box opens. Select a reveal path and click **OK**. A small icon appears next to the CI indicating that a watchpoint is defined for it. For details, see "New Watchpoint Dialog Box" on page 409.

🅆 Build a Pattern-based Model

This task describes how to build a pattern-based model which can serve as the basis for a perspective-based view.

This task includes the following steps:

- ► "Define the New Model" on page 372
- ► "Enter the Model Details" on page 372
- ► "Select a TQL Query" on page 372
- ➤ "Add Query Nodes and Relationships to a TQL Query" on page 372
- ➤ "Set Output Query Nodes" on page 373
- ► "Save the Model" on page 373

1 Define the New Model

You define a pattern-based model using the Pattern-based Model wizard. Click the **New *** button and select **Pattern Based Model**.

2 Enter the Model Details

On the first wizard page, select a CI type for the model and enter the properties. For details, see "Select CI Type Page" on page 411.

3 Select a TQL Query

On the next wizard page, select a TQL query for the model. You can create a new TQL query or select an existing query from the tree. The TQL Query Editor opens with the selected query. For details, see "Query Selection Page" on page 412.

4 Add Query Nodes and Relationships to a TQL Query

Add the query nodes and relationships that define the query. For details on how to add query nodes and relationships to a TQL query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

5 Set Output Query Nodes

Select one or more query nodes in the TQL query to serve as output for the model by right-clicking them and selecting **Add to Model Output**. The query node is indicated by a small icon next to it.

6 Save the Model

When you are finished, save the model with a unique name. If you created a new TQL query, the query is also saved independently of the model and can be re-used as a regular TQL query.

🅆 Build a Perspective-based View Based on a Model

This task describes how to build a view in the Modeling Studio based on a model and a perspective.

1 Open the Model

In the Modeling Studio, select **Models** as the Resource type in the left pane, select the relevant model, and click **Open Model** in the left pane toolbar.

2 Select a Perspective

In the Model Editor, right-click the model and select **Generate View for** selected model. The Creating New View dialog box opens. Select perspectives to apply to the model. For details, see "Creating New View Dialog Box" on page 386.

3 Save the View

The Perspective-based View Editor opens with your new view. Optionally, build a perspective chain by selecting perspectives for additional levels of the view creation. Rename the view and save it in the correct folder. For details, see "Perspective-based View Editor" on page 419.

Build a Perspective-based View Based on a Collection of Cls

This task describes how to build a view in the Modeling Studio based on a collection of CIs and a perspective.

This task includes the following steps:

- ► "Create the New View" on page 375
- ► "Add CIs to the View" on page 375
- ➤ "Select a Perspective and Save the View" on page 375

1 Create the New View

In the Modeling Studio, click the **New *** button and select **Perspective Based View** to open the Perspective-based View Editor. For details, see "Perspective-based View Editor" on page 419.

2 Add Cls to the View

In the CI Selector, search for the CIs you want to include in your view. Select them and drag them into the view. For details on the CI Selector, see "CI Selector" on page 163.

Tip: You can select more than one CI by holding the CTRL key while selecting CIs.

3 Select a Perspective and Save the View

In the Perspective pane, select perspectives to apply to your CI collection. Optionally, you can build a perspective chain by selecting perspectives for additional levels of the view creation. Rename the view and save it in the correct folder. For details, see "Perspective-based View Editor" on page 419.

聄 Build a Business CI Model – Scenario

This scenario describes how to build a business CI model for use in a human resources application.

This task includes the following steps:

- ► "Create a Model" on page 376
- ➤ "Create Application CI Models Within Your Model" on page 376
- ➤ "Add System CIs to Your Model" on page 376
- ➤ "Add CIs to Your Model as Related CIs" on page 377

1 Create a Model

To create a model, you need to select a CI type and enter its key properties.

Select Admin > RTSM Administration > Modeling > Modeling Studio to open the Modeling Studio. For details about how to create a model, see "New Model Dialog Box" on page 407.

Example of a Business CI Model:

In this example, a human resources application called Onboard Employee is to be created. Select **Business Process** as the CI type and enter **Onboard Employee** as the name under the key properties.

2 Create Application CI Models Within Your Model

You can create models within your model by clicking the New Model icon in the Model Editor. For details, see "Model Editor" on page 396.

Example of Application CI Models:

Within the Onboard Employee model, create a model of type **Application**. Enter HR Enterprise Resource Planning (ERP) as the name under the key properties. The application CI is created as a model within the Onboard Employee model. Repeat the process to create the following applications: Active Directory (AD) and Customer Relationship Management (CRM). The Onboard Employee model now includes three application models.

3 Add System Cls to Your Model

Add to your model the CIs for the servers or other software elements on which the applications are running.

Example of System CI Models:

Under the HR ERP application, drag the System CI **SAP System**. Under the AD application, drag the System CI **Node**. The System CIs are included in the model and their related CIs, such as Hosts and Monitors, are automatically added to the model as related CIs.

4 Add CIs to Your Model as Related CIs

Add the CIs that are to be related to the CIs in the model but are not included in the model. For details, see "Model Editor" on page 396.

Example of Related Cls:

Create an application CI of type Portal. Select the CRM application and click the Related CIs tab in the Information pane. Drag the Portal CI into the Information pane. The CI is added as a related CI to CRM.

Reference

🍳 Modeling Studio User Interface

This section includes (in alphabetical order):

- ► Add/Edit Function Dialog Box on page 379
- ► Change Query Node/Relationship Type Dialog Box on page 381
- ► Choose Operation for Selected Items Dialog Box on page 383
- ► Conditions of Related CIs Dialog Box on page 383
- ► Create/Edit/Save Reveal Path Dialog Box on page 385
- ► Creating New View Dialog Box on page 386
- ► Cycle Definition Dialog Box on page 387
- ► Hidden CIs Dialog Box on page 388
- ► Hierarchy Rules Dialog Box on page 388
- ► Left Pane on page 389
- ➤ Manage CI Watchpoints Dialog Box on page 395
- ► Model Editor on page 396
- ► Modeling Studio Page on page 404
- ➤ Models Containing Selected CI Dialog Box on page 406
- ► New Model Dialog Box on page 407
- ➤ New Pattern View/Template/Perspective Dialog Box on page 407
- ► New Watchpoint Dialog Box on page 409
- ➤ Open Reveal Path Dialog Box on page 410
- ► Pattern-based Model Wizard on page 411
- ► Pattern View Editor on page 413
- ► Perspective-based View Editor on page 419

- ➤ Query Node Grouping Dialog Box on page 425
- ➤ Query/View Definition Properties Dialog Box on page 426
- ► Reveal CIs Dialog Box on page 427
- ► Save Query Dialog Box on page 430
- ➤ Save View/Template/Perspective Dialog Box on page 431
- ► Select Data Sources Dialog Box on page 432
- ► Sort Column Content Dialog Box on page 433
- ➤ Template-based View Wizard on page 434
- ➤ Template Parameter Values Dialog Box on page 440
- ► TQL Query Editor on page 440
- ➤ Views Containing Selected CI Dialog Box on page 444
- ➤ Watchpoints Updates Dialog Box on page 446
- <Query/Template/Perspective Name> Dependencies Dialog Box on page 447

💐 Add/Edit Function Dialog Box

This dialog box enables you to define which of the query node's functions and parameters you want to include in the report.

Important information	When defining the report columns for a selected query node in a view, template, or perspective, you can define a column consisting of data deriving from a function defined for one of its child query nodes. Select the relevant child query node, attribute, and function that you want to define.
	First, select the required query node and function. The attribute list adjusts to display the relevant attribute for the selected combination. Select the required attribute.
Relevant tasks	"Define Report Settings" on page 369

User interface elements are described below:

UI Element (A-Z)	Description
Attribute	Select an attribute from the list.
Function	From the Function list, select the function you want to use to calculate the results on these columns.
	The following are the available options:
	➤ Average. The average value of the selected attribute for all the CI instances of the selected query node.
	 Concatenated List. Lists the values of the selected attribute for all the CI instances of the selected query node.
	 Count. Calculates the number of CI instances of the selected query node.
	 Distinct List. Lists the unique values of the selected attribute for all the CI instances of the selected query node.
	➤ Max. The maximum value of the selected attribute for all the CI instances of the selected query node.
	Min. The minimum value of the selected attribute for all the CI instances of the selected query node.
	Sum. The sum of the selected attribute values for all the CI instances of the selected query node.

UI Element (A-Z)	Description
Related Query Node	The child query node on which you want to perform the function.
Title	The name of the function attribute displayed in the report.

💐 Change Query Node/Relationship Type Dialog Box

This dialog box enables you to change the CI type of a TQL query node or relationship after you have created a TQL query.

To access	In the TQL Query Editor or Pattern View Editor, right- click the required query node and select Change Query Node Type . For relationships, right-click the required relationship and select Change Relationship Type .
Important information	You can change the CI type of the selected query node to any other valid type based on the existing relationships and conditions of the selected query node.
Relevant tasks	 "Define a TQL Query" on page 30 "Implement a Discovery Adapter" in the <i>RTSM</i> <i>Developer Reference Guide</i> "Create a Pattern View" on page 359

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
1	Click Expand All to expand all the folders in the tree.
1	Click Collapse All to collapse all the folders in the tree.

UI Element (A-Z)	Description
Tree View	Click Tree View to select the display format of the CI type/Relationship tree. The following options are available:
	► Display label
	Class name
	► Legacy class name
<ci type/Relationship tree></ci 	Select the required CI type or relationship.
Relationship	Select the direction of the relationship.
Direction	Note: Only relevant for relationships.
Relationship Name	The name of the relationship.
	Note: Only relevant for relationships.
Relationship Restrictions	Select an option to define how to handle relationships between identical query nodes or self relationships in the query results. A self relationship is a relationship that leads from a query node to itself.
	➤ Allow All Relationships. All relationships appear in the query results.
	 Allow Self Relationships only. Only self-relationships (a relationship that leads to itself) appear in the query results.
	► Allow Non Self Relationships only. Self-relationships
	do not appear in the query results.
	Note: Only relevant for relationships.

💐 Choose Operation for Selected Items Dialog Box

To access	In the Modeling Studio, drag CIs from the CI Selector onto the empty canvas.
Important information	You can drag individual or multiple CIs onto the canvas. You can select ordinary CIs and/or models to drag onto the canvas. Use the CTRL key while selecting CIs to select multiple CIs.
See also	"Best Practices for Modeling" on page 215

This dialog box enables you to create models and views from selected CIs.

User interface elements are described below:

UI Element (A-Z)	Description
Create a new model	Select to build a model comprising the CIs in your selection. If the CIs you dragged onto the canvas include at least one CI that has no valid links to any of the model CI types, this option is disabled.
Create a new view	Select to build a view based on the CI collection formed by your selection.
Edit the model of the selected CI	Select to edit the selected model in the Model Editor. Note: This option only appears when a single model is dragged onto the canvas.

💐 Conditions of Related Cls Dialog Box

This dialog box enables you to define conditions for the CI types in a reveal path.

To access	Click the Add Condition or Edit Condition buttons from the Conditions column of the Reveal CIs dialog box.
See also	"Best Practices for Modeling" on page 215

User interface elements are described below:

UI Element (A-Z)	Description
÷	Add the attribute condition you have defined.
×	Delete an attribute condition.
1	Move a selected row up.
U.	Move a selected row down.
Q	View the condition definition.
And/Or	Click inside the And/Or field and select either And or Or to link multiple conditions.
Attribute name	Select an attribute from the list.
Brackets	Click inside the Brackets box to display a list of brackets you can use to build more complex, logical statements.
Criteria	Contains the attribute condition definition as defined in the Element Instances dialog box.
Not	Select NOT if you want the condition statement to do the opposite of what is defined.
	Note : If you select NOT , query results do not include data from the CI instances that were not assigned a value. For example, your system contains three node CIs: Node1 is assigned the value A, Node2 is assigned the value B and Node3 is not assigned a value. You create a query to retrieve all nodes that are equal to A and select NOT ; the results of your query only include Node2 because Node3 is not assigned a value.
Operator	Select the required operator. For details, see "Attribute Operator Definitions" on page 45.
Value	Enter or select the value of the attribute. The Value options vary according to the attribute type you select.

💐 Create/Edit/Save Reveal Path Dialog Box

This dialog box enables you to define a new reveal path or edit an existing path.

To access	To define a new reveal path, click the Reveal how button from the Model Editor, and select Create Reveal Path . To edit an existing reveal path, select a path from the Open Reveal Path dialog box and click Edit . To save a reveal path, click Save Path from the Reveal CIs dialog box.
See also	"Best Practices for Modeling" on page 215

User interface elements are described below:

UI Element (A-Z)	Description
Description	Enter a description of the path.
Name	Enter the name of the path.
Preview	Opens the Reveal CIs dialog box displaying the related CIs in the path. Note: This button does not appear in the Save Reveal Path dialog box.
Reveal Path	Build the path by clicking the 💠 icon to open a dialog box with a CI type tree. Select the CI type for the next item in the path.
	When you hold the pointer over a reveal path item, the following options are available:
	 Delete Selected Item(s). Deletes the selected item from the reveal path.
	 Add condition. Opens the Conditions of Related CIs dialog box, which enables you to set conditions for the reveal path item.
	► Refine Query Node Type. Opens a CI type tree, which enables you to change the CI type of the reveal path item.

💐 Creating New View Dialog Box

This dialog box enables you to select a perspective to create a view from a model.

To access	In the Modeling Studio, right-click a model in the Model Editor, Perspective-based View Editor, or CI Selector and select Generate view for selected Model or click the Generate view for selected model icon I from the Model Editor.
Important information	You select perspectives in the left pane and move them to the right pane using the arrow buttons.
Relevant tasks	"Build a Perspective-based View Based on a Model" on page 374
See also	"Best Practices for Modeling" on page 215

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
Available Perspectives	A list of the available perspectives to apply to your model.
Selected Perspectives	The perspectives you selected to apply to your model.

A Cycle Definition Dialog Box

To access	In the Modeling Studio, right-click a query node in the Hierarchy pane of the Pattern View Editor and select Define Cycles .
Important information	You can extend the TQL query definition of a view by defining a cycle in the view hierarchy. Select a query node in the Hierarchy pane to be the source query node. The Cycle Definition dialog box displays the valid target query nodes for that source. The target query node in the cycle, along with its hierarchy, is treated as a child or sibling of the source query node (depending on your folding rule selection).
See also	"Best Practices for Modeling" on page 215

This dialog box enables you to define a cyclical hierarchy in a view.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
Folding Rule	Select one of the following options:
	➤ Folded cycle under source. The target query node becomes a child of the source query node.
	 Flattened cycle under parent. The target query node becomes a sibling of the source query node.
Target	Displays the valid target query nodes for the selected source query node. A query node is defined as a valid target query node if all of the following conditions are true:
	➤ it is related to the source query node
	 it is an ancestor of the source query node (or the source query node itself)
	► it is a query based node (not a grouping node)

💐 Hidden Cls Dialog Box

This dialog box enables you to restore hidden CIs to a view.

To access	From the Perspective-based View Editor, click the Show Hidden CIs icon from the toolbar of the View Results pane.
See also	"Best Practices for Modeling" on page 215

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<check box=""></check>	Select the check boxes for the CIs you want to restore.
СІ Туре	The CI type of the excluded CI.
Name	The name of the excluded CI.
Restore	Click Restore to include the selected CIs in the view.
Select All	Click Select All to select all the CIs in the list for inclusion in the view.
Unselect All	Click Unselect All to clear the check boxes of all the CIs in the list.

🂐 Hierarchy Rules Dialog Box

This dialog box enables you to set the hierarchy of a view by defining hierarchy rules.

To access	From the Hierarchy pane of the Pattern View Editor, when Rule Based is selected as the hierarchy method, click the Add Hierarchy Rule 💠 button from the toolbar.
Important information	For each hierarchy rule you define, select a source CI type, target CI type, relationship, and direction.
See also	"Best Practices for Modeling" on page 215

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
÷	Click to add a hierarchy rule.
×	Click to delete the selected hierarchy rule.
Relationship	Select a relationship from the drop-down list to edit the selected hierarchy rule.
Relationship Direction	Select a direction from the drop-down list to edit the selected hierarchy rule.
Source	Select a CI type for the source CI type from the drop- down tree to edit the selected hierarchy rule.
Target	Select a CI type for the target CI type from the drop- down tree to edit the selected hierarchy rule.

💐 Left Pane

This area enables you to browse views and TQL queries, search for CIs or models to open in the Editor pane, and select CI types to use in the TQL Query Editor or Pattern View Editor.

To access	Located to the left of the Editor pane in Modeling Studio.
Important information	 The following tabs are available: Cl Selector. See "CI Selector" on page 163. Resources. Enables you to select a model, view, or TQL query to open in the Editor pane. Cl Types. Enables you to select CI types from the tree to add as a query node to your TQL query.
See also	"Best Practices for Modeling" on page 215

Resources Tab

Important	When Views or Queries is selected as the resource type,
information	you can drag and drop views, queries, or folders to move
	them from one folder to another.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
	Click New Folder to create a new folder in the resource tree.
	Note: This button only appears when Queries or Views are selected as the resource type.
×	Click Delete to delete the selected resource from the RTSM.
0	Click Refresh to refresh the resource tree.
8	Click Expand All to expand all the folders in the resource tree.
	Note: This button only appears when Queries or Views are selected as the resource type.
5	Click Collapse All to collapse all the folders in the resource tree.
	Note: This button only appears when Queries or Views are selected as the resource type.
E 3	When Queries or Views are selected as the resource type, click Hide Empty Folders to display only folders containing views or TQL queries.
	When Models is selected as the resource type, click Show only models with content to display only models containing CIs.

UI Element (A-Z)	Description
Y	When Views is selected as the resource type, click Filter Tree to filter the types of views and templates that appear in the tree.
	When Queries is selected as the resource type, it enables you to filter the TQL queries that appear in the tree by query type.
	When Models is selected as the resource type, click Filter Table to filter the models in the table by CI type.
B	Click Open Query to open the selected TQL query in a new tab.
	Note: This button only appears when Queries is selected as the resource type.
—	Click Open View to open the selected view in a new tab.
	Note: This button only appears when Views is selected as the resource type.
F	Click Cl Properties to view the properties of the selected model.
	Note: This button only appears when Models is selected as the resource type.
L a	Click Show views containing selected CI/model to display a list of views including the selected CI or model.
	Note: This button only appears when Models is selected as the resource type.
\$	Click Open Model to open the selected model in the Model Editor.
	Note: This button only appears when Models is selected as the resource type.
IXHL.	Click Import From XML to import XML files that contain saved views or queries to the Modeling Studio.
	Note: This button only appears when Queries or Views are selected as the resource type.

UI Element (A-Z)	Description
E State	Click Export To XML to export the view or query as an XML script. This option can be used to move a view or query from one workstation to another.
	Note: This button only appears when Queries or Views are selected as the resource type.
<resources></resources>	 When Views or Queries is selected as the resource type, the available views or TQL queries are displayed under their respective folders in tree format. When Models is selected as the resource type, the available models are displayed in a table. For views, the following view types are included: Denotes a pattern view. Denotes a template. Denotes a template-based view. Denotes a perspective. Denotes a perspective-based view.
Resource Type	Select the resource type to display in the pane. The available options are Models, Views, and Queries.

Resources Tab Shortcut Menu

The Resources tab includes the following elements (listed alphabetically) available by right-clicking a resource:

Menu Item	Description
Create a new View/Template/Pers	Create a new view, template, or perspective based on the selected view, template, or perspective.
pective	Note: This option is only active for queries when a query of type view, template, or perspective is selected.
Delete	Delete the selected resource from the RTSM.
Export To XML	Export the view or query as an XML script. This option can be used to move a view or query from one workstation to another.
New Folder	Create a new folder in the resource tree.

Menu Item	Description
New Template Based View	Edit the parameters of the selected template to define a new template-based view.
	Note: This option is only active when a template is selected in the view tree.
Open Query/View/Model	Open the selected view, TQL query, or model in a new tab.
Properties	Opens the CI Properties dialog box for the selected model.
	Note: This option is only relevant for models.
Refresh	Refresh the resource tree.
Remove	Remove the selected model.
	Note: This option is only relevant for models.
Rename Folder	Rename the selected folder.
Save As	Save the selected TQL query with a new name.
Show containing views	Opens the Views containing selected CI dialog box for the selected model.
	Note: This option is only relevant for models.

CI Types Tab

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
駘	Click Expand All to expand all the folders in the CI Type tree.
5	Click Collapse All to collapse all the folders in the CI Type tree.

UI Element (A-Z)	Description
Tree View	Click Tree View to select the display format of the CI type tree. The following options are available:
	► Display label
	► Class name
	► Legacy class name
\$	Click to add the selected CI type to the TQL query which is open in the Editor pane.
	Note: This button is only active when a view or TQL query is open in the Editor pane.
0	Click Refresh to refresh the CI Type tree.
<ci tree="" type=""></ci>	The available CI types are displayed in tree format.

CI Types Tab Shortcut Menu

The CI Types tab includes the following elements (listed alphabetically) available by right-clicking a CI type:

Menu Item	Description
Add Selected CITs to Query	Select to add the selected CI type to the TQL query open in the Editor pane.
Go to Cl Type Definition	Takes you directly to the selected CI type in CIT Manager.
Show Element Instances	Opens the CI Instances window, which displays all instances of the selected CIT. For details, see "Element Instances Dialog Box" on page 77.

🎕 Manage CI Watchpoints Dialog Box

This dialog box enables you to add or remove watchpoints for a CI in a model.

To access	From within a model in the Model Editor, click the
	Watchpoint 🚳 button and select Manage CI
	Watchpoints or right-click a CI in the model and select
	Watchpoint > Manage CI Watchpoints.

User interface elements are described below:

UI Element (A-Z)	Description
Add	Click to open the New Watchpoint dialog box which enables you to add a new watchpoint.
× Remove	Click to delete the selected watchpoint.
Automated	A check mark indicates that the new CIs found by the watchpoint are to be added to the view automatically.
Source CI	Displays the CI forming the beginning of the reveal path.
Watchpoint Name	The name of the reveal path associated with the watchpoint.
Watchpoint Path	Displays the reveal path for the watchpoint.

💐 Model Editor

To access	In the Modeling Studio, click the New subtrom and select Instance Based Model to create a new model or select Models as the Resource type and open an existing model.
Important information	 The Model Editor contains the following panes: Content pane. Lists the CIs and models contained in the model. Information pane. Displays the properties, related CIs and watchpoints for the selected CI or model. You can drag CIs from the CI Selector into the Content pane of an existing model to add them to the model. However, you cannot drag in a CI that is already included in the model. You can drag CIs from the CI Selector into the Related CIs tab of the Information pane provided that the selected source and target CI can be related by a usage relationship.
See also	"Best Practices for Modeling" on page 215

This feature enables you to create and edit models.

Content Pane

User interface elements are described below:

UI Element (A-Z)	Description
jea Map	Select Map Mode to display the CIs as icons in a diagram.
I Text	Select Text Mode to display the CIs in a list.
	Click Cl Properties to open the Configuration Item Properties dialog box for the selected CI.
	Click Show models containing selected CI to display a list of the models containing the selected CI.

UI Element (A-Z)	Description
	Click Show views containing selected CI/model to display a list of the views containing the selected CI or model.
60	Click Open selected model in a new tab to open the selected model in a separate Model Editor tab.
	Click Generate view for selected model to create a view based on the current model. The Creating New View dialog box opens, which enables you to select a perspective to apply.
×	Click to remove a selected CI from the model (it remains in the RTSM).
R	Click Insert new model to open the New Model dialog box which enables you to define a new model within the existing model.
8	Click Expand All to expand the model hierarchy.
**	Click Collapse All to collapse the model hierarchy.
Ra	 Click Reveal for the following options: Start Revealing. Opens the Reveal CIs dialog box. For details, see Reveal CIs dialog box. Create Reveal Path. Opens the Create Reveal Path dialog box. For details, see Create Reveal Path dialog box. Open Reveal Path. Opens the Open Reveal Path dialog box. For details, see Open Reveal Path dialog box.

UI Element (A-Z)	Description
<u></u>	 Click Watchpoint for the following options: Watchpoints Updates. Display the watchpoint results and select CIs to add to the model. For details, see Watchpoints Updates dialog box. New Watchpoint. Define a new watchpoint for the selected CI. For details, see New Watchpoint dialog box. Manage CI Watchpoints. Add new watchpoints to the CI or remove existing ones. For details, see Manage CI Watchpoints dialog box.
	 Click Cl Collection to group CIs in a collection under a model. Select one of the following options: Insert New Cl Collection. Create a new empty CI Collection. After creating the collection, you can drag CIs into it from the CI Selector, the related CIs tab, or from the model itself. Join to Cl Collection. Select a CI or several CIs in the model and join them to an existing CI collection or form a new collection. Decompose Cl Collection. Select a CI collection and decompose it. Its CIs remain directly under the main model.
	Click Find to toggle between displaying and hiding the Find box and arrow controls. Note: This button only appears in Text mode.
	Click to refresh the map and optimize the map layout. Note: This button only appears in Map mode.
	Click Fit to Window to resize the map to fit the size of the pane. Note: This button only appears in Map mode.

UI Element (A-Z)	Description
▶ Select ▼	 Select the functionality of the cursor from the Mode drop-down. The following options are available: Select Drag Map Zoom In Note: This feature only appears in Map mode.
Print	Click the Print button to select Print, Print Preview or Print Setup.
0	Select a CI and click Show External Relationships to display the related CIs for that CI. Note: This button only appears in Map mode.
2	Click Hide External Relationships to hide the related CIs. Note: This button only appears in Map mode.
0	Indicates that watchpoints are defined for the current CI.
0	Indicates that the watchpoints have detected new CIs related to the current model. Click it to open the Watchpoints Updates dialog box.
CI Type column	Displays the type of each CI in the model.
Find	Enter a CI name or a portion of a CI name in the Find box to locate a CI in the model.
Find Next	Click to go to the next occurrence of the selected search phrase in the model.
Find Previous	Click to go to the previous occurrence of the selected search phrase in the model.
Highlight	Click to highlight all occurrences of the search phrase in the model.
Name column	Displays the name of each CI in the model.

Shortcut Menu Options

Menu Item	Description
CI Collection	Click Cl Collection to group CIs in a collection under a model. Select one of the following options:
	Insert New Cl Collection. Create a new empty collection. After creating the collection, you can drag CIs into it from the CI Selector, the related CIs tab, or from the model itself.
	Join to Cl Collection. Select a CI or several CIs in the model and join them to an existing CI collection or form a new group.
	 Decompose Cl Collection. Select a CI collection and decompose it. Its CIs remain directly under the main model.
Fit to Window	Resizes the map to fit the size of the pane.
	Note: This option only appears in Map mode.
Generate view for selected model	Select to create a view based on the current model. The Creating New View dialog box opens which enables you to select a perspective to apply.
Hide External	Hides the related CIs from the map.
Relationships	Note: This option only appears in Map mode.
Insert New Model	Opens the New Model dialog box which enables you to create a new model within the existing model.
Open selected model in a new tab	Opens the selected model in a separate Model Editor tab.
Print	Select one of the following options:
	► Print
	> Print Preview
	► Print Setup
Properties	Opens the Configuration Item Properties dialog box for the selected CI.
Refresh Layout	Refreshes the map and optimizes the map layout.
	Note: This option only appears in Map mode.

Menu Item	Description
Reveal	The following options are available:
	 Start Revealing. Opens the Reveal CIs dialog box. For details, see Reveal CIs dialog box. Open Reveal Path. Opens the Open Reveal Path dialog box. For details, see Open Reveal Path dialog
	box.
Remove Selected CI(s) from the Model	Deletes the selected CIs from the model (it remains in the RTSM).
Select	 Select the functionality of the cursor. The following options are available: Select Drap Map Zoom In
	Note: This option only appears in Map mode.
Show Containing Models	Click to display a list of the models containing the selected CI.
Show Containing Views	Click to display a list of the views containing the selected CI or model.
Show External	Displays the related CIs for the selected CI.
Relationships	Note: This option only appears in Map mode.
Watchpoint	The following options are available:
	 Watchpoints Updates. Display the watchpoint results and select CIs to add to the model. For details, see Watchpoints Updates dialog box. New Watchpoint. Define a new watchpoint for the selected CI. For details, see New Watchpoint dialog box. Manage CI Watchpoints. Add new watchpoints to the
	CI or remove existing ones. For details, see Manage CI Watchpoints dialog box.
Zoom	Select the size of the map from the list of percents.
	Note: This option only appears in Map mode.

Information Pane - Properties Tab

This area displays the properties of the selected CI.

Important	This pane is identical to the Properties tab of the
information	Information pane in IT Universe Manager. For details, see
	"Configuration Item Properties Dialog Box" on page 266.

Information Pane - Related Cls Tab

This area displays the CIs related to the model by one of the triplets that includes an Impacted By (Potentially) relationship.

UI Element (A-Z)	Description
×	Click to delete the relationship to the selected CI.
\$	Click Invert Direction to switch the direction of the relationship for the selected CI.
	Note: This option is only active for CIs related by a usage relationship.
<ci list=""></ci>	Lists the name and CI type of the CIs related to the model by usage relationships, as well as the direction of the relationship.
Filter by	Select a field by which to filter the results and enter the value in the by box.

Information Pane - Watchpoints Tab

This area displays the watchpoints defined for the selected CI.

UI Element (A-Z)	Description
Ø	Click to open the Manage CI Watchpoints dialog box, which enables you to edit the watchpoint.
Automated	Indicates whether the new CIs found by the watchpoint are automatically added to the view.
Source CI	Displays the CI forming the beginning of the reveal path.
Watchpoint Name	The name of the reveal path associated with the watchpoint.
Watchpoint Path	Displays the reveal path of the watchpoint.

💐 Modeling Studio Page

This page enables you to create and edit models and views.

Tip: For more information about using Modeling Studio in HP Business Service Management, see "Best Practices for Modeling" on page 215.

To access	Select Admin > RTSM Administration > Modeling > Modeling Studio.
Important	The Modeling Studio page contains the following panes:
information	Left pane. Enables you to search for CIs or select a view, model, or TQL query to open. For details, see "Left Pane" on page 389.
	 Editor pane. Displays the topology map of a selected view, model, or TQL query.
	The Editor pane is a blank canvas before any views or models are opened. When you open a view, model, or TQL query, the relevant editor appears there. Multiple views, models, and queries can be open at the same time in the Editor pane, each within a separate tab.
See also	"Model Editor" on page 396, "Perspective-based View Editor" on page 419, "Pattern View Editor" on page 413, and "TQL Query Editor" on page 440.

UI Element (A-Z)	Description
* New	Click the click the New button to select one of the following options:
	 Instance Based Model. To create a new instance based model.
	➤ Pattern Based Model. To create a new pattern based model.
	► Pattern View. To create a new pattern view.
	➤ Template Based View. To create a new template-based view.
	 Perspective Based View. To create a new perspective- based view.
	► Template . To create a new template.
	► Perspective. To create a new perspective.
	► Query. To create a new TQL query.
H	Click Save to save the changes to your view, model, or query.
	For views, a dialog box opens which enables you to rename your view and save it in the appropriate folder.
P.	Click Save As to save your view, model, or TQL query under a new name.
5	Click Undo to reverse the last change you made.
2	Click Redo to repeat the last action you took.
	Click Maximize Workspace to toggle between the regular display and a full-screen display of the editor.
<menu></menu>	For details, see "Main Menu" on page 197.

💐 Models Containing Selected CI Dialog Box

This dialog box enables you to display a list of the models containing the selected CI.

To access	Click the Show models containing selected CI (a) button in the Model Editor or select Show containing models from the shortcut menu.
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
F	Click Cl Properties to open the Configuration Item Properties dialog box for the selected model.
F a	Click Show views containing selected Cl/model to display a list of views containing the selected model.
×	Click Remove model to delete the selected model.
СІ Туре	Displays the CI types of the models containing the selected CI.
Find	Enter a model name or a portion of a model name in the Find box to locate it in the list.
Find Next	Click to go to the next occurrence of the selected search phrase in the list.
Find Previous	Click to go to the previous occurrence of the selected search phrase in the list.
Name	Displays the names of the models containing the selected CI.
	Note: The name of the current model appears in faded text.

💐 New Model Dialog Box

This dialog box enables you to define a reusable model containing a collection of CIs.

To access	Click the New * button and select Instance Based Model or drag a CI from the tree in the CI Selector onto the editing pane and select Create a new model .
Relevant tasks	"Build an Instance-based Model" on page 370
See also	"Best Practices for Modeling" on page 215

User interface elements are described below:

UI Element (A-Z)	Description
Define new Cl Properties	Enter the values for the CI properties. You must enter values for key properties and required properties. The key properties are marked with a key symbol \Im and the required properties are marked with an asterisk.
Select CI Type	Select a CI type from the list to serve as the basis for your model.

💐 New Pattern View/Template/Perspective Dialog Box

This dialog box enables you to define a new pattern view, template, or perspective using the Pattern View Editor.

To access	In the Modeling Studio, click the New * button and select Pattern View, Template, or Perspective from the drop-down menu.
Important information	After making your selection and clicking OK, you go directly to the Pattern View Editor to begin building your view. For details, see "Pattern View Editor" on page 413.

Relevant tasks	 "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
\bigcirc	Click to go to the next occurrence of the selected search phrase in the list of TQL queries.
	Click to go to the previous occurrence of the selected search phrase in the list of TQL queries.
	Click to highlight all occurrences of the search phrase in the list of TQL queries.
<tql query="" tree=""></tql>	Displays the existing TQL queries in tree format.
Choose base query	If you want to base your new view on an existing TQL query, select this option and select a TQL query from the tree. The Pattern View Editor opens with the selected TQL query on the canvas.
Create new query	If you want to base your new view on a new TQL query, select this option. The Pattern View Editor opens with a blank canvas.
Find	Enter a TQL query name or a portion of a query name in the Find box to locate a TQL query in the list.

💐 New Watchpoint Dialog Box

To access	From within a model in the Model Editor, click the Watchpoint we button and select New Watchpoint or right-click a CI in the model and select Watchpoint > New Watchpoint .
Important information	If no reveal paths are found for the selected CI, no watchpoints can be defined.
	You cannot define watchpoints for CIs in a new model until you save the model.
Relevant tasks	"Build an Instance-based Model" on page 370

This dialog box enables you to define a watchpoint for a CI in a model.

UI Element (A-Z)	Description
Automatically update model	Select to automatically add all revealed CIs from the selected path to the model.
Control updates manually	Select to manually add revealed CIs from the selected path to the model.
Select Watchpoint reveal path	Select a reveal path from the drop-down list.
Show reveal paths for CI type	Select a CI type from the drop-down list. All reveal paths beginning with that CI type appear in the list in the lower drop-down box.

💐 Open Reveal Path Dialog Box

This dialog box enables you to open an existing path.

To access	From within a model in the Model Editor, click the Reveal a button and select Open Reveal Path or right- click a CI in the model and select Reveal > Open Reveal Path .
Important information	After selecting the reveal path you want to use, click Execute . If CIs are found on the selected path, the Reveal CIs dialog box opens for that path. If no CIs are found, a message appears stating that no CIs were found on the path.

UI Element (A-Z)	Description
Description column	Displays the descriptions of the existing paths.
Edit	Opens the Edit Reveal Path dialog box which enables you to edit the selected path.
Execute	Opens the Reveal CIs dialog box for the selected reveal path.
Find	Enter a path name or a portion of a path name in the Find box to locate a path in the list.
Find Next	Click to go to the next occurrence of the selected search phrase in the list of paths.
Find Previous	Click to go to the previous occurrence of the selected search phrase in the list of paths.
Highlight	Click to highlight all occurrences of the search phrase in the list of paths.
Name column	Displays the names of the existing paths.
Remove	Deletes the selected path.
Show reveal paths for CI type	Select a CI type from the drop-down list. All paths beginning with the selected CI appear in the table below.

🍳 Pattern-based Model Wizard

To access	In the Modeling Studio, click the New * button and select Pattern Based Model from the drop-down menu.
Important information	When you create a pattern-based model, the model is saved as a CI, as with an ordinary model. If you based your model on a new TQL query, the query is also saved and appears in the TQL query tree.
Relevant tasks	"Build a Pattern-based Model" on page 372
Wizard map	The Pattern-based Model Wizard contains: Select CI Type Page > Query Selection Page
See also	"Pattern-based Models" on page 348

This wizard enables you to build a pattern-based model.

💐 Select Cl Type Page

This wizard page enables you to select a CI type for the model and define its details.

Wizard map	The Pattern-based Model Wizard contains:
	Select CI Type Page > Query Selection Page

UI Element (A-Z)	Description
Define new Cl Properties	Enter the values for the CI properties. You must enter values for key properties and required properties. The key properties are marked with a key symbol \Im and the required properties are marked with an asterisk.
Select Cl Type	Select a CI type from the list to serve as the basis for your model.

Query Selection Page

This wizard page enables you to select a TQL query upon which the model is based.

Wizard map	The Pattern-based Model Wizard contains:
	Select CI Type Page > Query Selection Page

UI Element (A-Z)	Description
\bigcirc	Click to go to the next occurrence of the selected search phrase in the list of TQL queries.
	Click to go to the previous occurrence of the selected search phrase in the list of TQL queries.
	Click to highlight all occurrences of the search phrase in the list of TQL queries.
<tql query="" tree=""></tql>	Displays the existing TQL queries in tree format.
Choose base query	If you want to base your model on an existing TQL query, select this option and select a query from the tree. The TQL Query Editor opens with the selected query on the canvas.
Create new query	If you want to base your model on a new TQL query, select this option. The TQL Query Editor opens with a blank canvas.
Find	Enter a TQL query name or a portion of a query name in the Find box to locate a query in the list.

💐 Pattern View Editor

This feature enables you to build and edit pattern views, templates, and perspectives.

To access	To open a new view in the Pattern View Editor, go to the Modeling Studio, click the New button and select the required type of view. To open an existing view in the Pattern View Editor, go to the Resources tab of the left pane in the Modeling Studio and select Views as the Resource type. Right click a view in the tree and select Open View or double click a view or drag a view onto the Editor pane. The topology map of the view opens in the Editor pane.
Important information	You can access the Editor in View mode or in Report mode. ► In View mode, the following panes are included:
	 Query Definition pane. For details, see "TQL Query Editor" on page 440.
	 Advanced pane. For details, see "Advanced Pane" on page 442.
	 Hierarchy pane. Enables you to set the hierarchy of the view. (Located in the right portion of the Editor page.)
	➤ In Report mode, the following panes are included:
	 Hierarchy pane. Enables you to set the hierarchy of the view. (Located in the left portion of the Editor page.)
	 Query Node Definition. Enables you to select the attributes to be included in the report and to set their order.
	Note: To save your view, template, or perspective, use the Save button in the Modeling Studio main toolbar.
Relevant tasks	 "Create a Pattern View" on page 359
	➤ "Create a Template" on page 360
	 "Create a Perspective" on page 362
See also	"Best Practices for Modeling" on page 215

Hierarchy Pane

UI Element (A-Z)	Description
6	Click Add Group By to create a subgroup in the hierarchy. The following options are available:
	Add Group By Attribute. Opens the Query Node Grouping dialog box, which enables you to select an attribute for a subgroup in the hierarchy.
	Add Group By CI Type. Create a subgroup in the hierarchy for the CI type of the selected query node.
	Add Group by Query Node. Create a subgroup in the hierarchy for the selected query node only.
0	Click Edit Group By Attribute to open the Query Node Grouping dialog box, which enables you to edit the attribute for a subgroup in the hierarchy.
R	Click Rename to rename the selected query node.
×	Click Delete Query Node to delete the selected query node from the hierarchy tree.
¢	Click Move Query Node Layer Up to place the selected query node one layer higher in the hierarchy.
\$	Click Move Query Node Layer Down to place the selected query node under the query node above it in the hierarchy.
	Note: If the selected query node is located at the top of the hierarchy tree, clicking Move Query Node Layer Down places it under the query node beneath it in the hierarchy.
1	Click Move Query Node Up to move the selected query node up in the hierarchy tree. The query node order in the hierarchy determines the query node order in the report generated for the view in Reports.

UI Element (A-Z)	Description
₩	Click Move Query Node Down to move the selected query node down in the hierarchy tree. The query node order in the hierarchy determines the query node order in the report generated for the view in Reports.
Q	Click Preview to display a preview of the topology report. Note: This option only appears in the Hierarchy pane when Report mode is selected.
<hierarchy tree=""></hierarchy>	The query nodes of the TQL query are arranged in a hierarchical tree reflecting the hierarchy defined for the view.
	You can click and drag query nodes to change the hierarchy. When you click a query node and begin to drag it, the query nodes under which it is possible to place your query node are highlighted in green.
Hierarchy Method	 Select the method of setting the hierarchy: Manual. Set the hierarchy manually, by dragging query nodes and using the toolbar buttons. Rule Based. Open the Hierarchy Rules dialog box which enables you to set rules for the hierarchy.

Shortcut Menu

The Hierarchy pane includes the following elements (listed alphabetically) available by right-clicking a query node in the hierarchy tree:

Menu Item	Description
Add Group By Attribute	Select Add Group By Attribute to open the Query Node Grouping dialog box, which enables you to select an attribute for a subgroup in the hierarchy.
Add Group By Cl Type	Select Add Group By CI Type to create a subgroup in the hierarchy for the CI type of the selected query node.
Add Group By Query Node	Select Add Group By Query Node to create a subgroup in the hierarchy for the selected query node only.

Menu Item	Description
Define Cycles	Select Define Cycles to define a cyclical hierarchy. For details, see "Cycle Definition Dialog Box" on page 387.
Delete Query Node	Select to delete the selected query node from the hierarchy tree.
Move Query Node Down	Select to move the selected query node down in the hierarchy tree.
Move Query Node Layer Down	Select Move Query Node Layer Down to place the selected query node under the query node above it in the hierarchy.
	Note: If the selected query node is located at the top of the hierarchy tree, selecting Move Query Node Layer Down places it under the query node beneath it in the hierarchy
Move Query Node Layer Up	Select Move Query Node Layer Up to place the selected query node one layer higher in the hierarchy.
Move Query Node Up	Select to move the selected query node up in the hierarchy tree.
Rename	Select to rename the selected query node.
Subgraph Hierarchy	Enables you to define whether the subgraph defined for the selected query node is displayed as flat or as folded under the query node. Note: This option is only relevant for query nodes that have a defined subgraph.

Query Node Definition Pane

Important information	The Query Node Definition pane is disabled for template based views. To make changes to the report layout, edit
	the based template of the view. When you open a template based view in the Editor and select the Report tab, a warning message appears containing a link to the base template of the view.

UI Element (A-Z)	Description
1	Click Up to move a selected attribute up in the report layout order.
Ų	Click Down to move a selected attribute down in the report layout order.
Ø	Click Edit to edit the function for the selected attribute.
×	Click Delete to delete a selected attribute from the report layout.
⇒	Click to move the selected attributes to the Report Layout list.
Add Function	Click Add Function to open the Add Function dialog box, which enables you to define the functions to include in the report for the selected query node. Each function that you add is treated as an attribute and becomes a column in the report.
	Note: This button is only active if there is a query node below the selected query node in the view hierarchy.
Attributes	The list of available attributes for the selected query node.
Define Chart	Click Define Chart to display the data for the current layer of the view in a graphical chart format. The Chart Properties fields are displayed.
	The Define Chart option is only active for a query node or a grouping node that:
	► has a layer below it in the view hierarchy
	► is the only query node on its layer of the view
	➤ has at least one numeric attribute selected for the report layout

UI Element (A-Z)	Description
Report Layout	Displays the list of attributes selected to appear in the report. Use the toolbar buttons to change the order of the attributes in the report and to add functions.
Set Sort Order	Click to open the Set Column Sort Order dialog box which enables you to set the order of the report columns.

Chart Properties

The Chart Properties portion of the pane includes the following elements (listed alphabetically):

UI Element (A-Z)	Description
×	Click Remove Chart to remove the chart from the report. The report is generated in table format.
Breakdown by	The chart is broken down by the CI or grouping node display label. This is fixed for all reports.
Chart Type	Select Pie to create a pie chart or Bar to create a bar chart.
Value	Select a value from the drop-down list.

Rerspective-based View Editor

To access	In the Modeling Studio, click the New * button and select Perspective Based View to create a new view or drag CIs from the CI Selector onto the blank canvas and select Create a new view .
	To open an existing view in the Editor, select Views as the resource type in the Resources pane, select the required perspective-based view from the tree, and click Open View in or double-click the view.
Important information	The Perspective-based View Editor contains the following panes:
	 Content pane. Drag CIs and/or models onto this pane to include them in your view.
	 Perspective pane. Select perspectives to apply to the content to build a view.
	➤ View Results pane. Displays a topology map with a preview of the current view. This pane includes most of the IT Universe Manager functionality.
Relevant tasks	 "Build a Perspective-based View Based on a Model" on page 374 "Build a Perspective-based View Based on a Collection of CIs" on page 374
See also	"Best Practices for Modeling" on page 215

This feature enables you to create and edit perspective-based views.

Content Pane

UI Element (A-Z)	Description
•	Go directly to IT Universe Manager for the current view.
P	Click Properties to open the Configuration Item Properties dialog box for the selected CI.

UI Element (A-Z)	Description
₿	Click Show models containing selected CI to display a list of the models containing the selected CI.
	Click Show views containing selected Cl/model to display a list of the views containing the selected CI or model.
60	Click Open selected model in a new tab to open the selected model in a separate Model Editor tab.
F \$	Click Generate view for selected model to create a view based on the selected model. The Creating New View dialog box opens which enables you to select a perspective to apply.
×	Click to remove a selected CI from the view content.
*	Click View Definition Properties to open the View Definition Properties dialog box which enables you to set properties for the view.
Q	Click Find to toggle between displaying and hiding the Find box and arrow controls.
CI Type column	Displays the type of each CI in the view.
Find	Enter a CI name or a portion of a CI name in the Find box to locate a CI in the view
Find Next	Click to go to the next occurrence of the selected search phrase in the view.
Find Previous	Click to go to the previous occurrence of the selected search phrase in the view.
Highlight	Click to highlight all occurrences of the search phrase in the view.
Name column	Displays the name of each CI in the view.

Shortcut Menu Options

Menu Item	Description
Generate view for selected model	Select to create a view based on the selected model. The Creating New View dialog box opens which enables you to select a perspective to apply.
Open selected model in a new tab	Opens the selected model in a separate Model Editor tab.
Properties	Opens the Configuration Item Properties dialog box for the selected CI.
Remove Base Cls	Deletes the selected CI or model from the view content.
Show Containing Models	Click to display a list of the models containing the selected CI.
Show Containing Views	Click to display a list of the views containing the selected CI or model.

Perspective Pane

UI Element (A-Z)	Description
×	Delete the selected level of the perspective selection.
1	Shift the perspective selection from the current level to the previous one.
U.	Shift the perspective selection from the current level to the following one.
+	Add a new level to the perspective selection. The results of the previous perspective level serve as the input content for the new level.
	Open a dialog box with the available perspectives. Move the required perspectives from the available column to the selected column using the arrow buttons.

UI Element (A-Z)	Description
Apply Over Model Hierarchy	For views based on models, select the Apply Over Model Hierarchy check box to include the model hierarchy in the view and apply the perspectives to the CIs included in the model as well as to the model itself. Clear the check box to exclude the model hierarchy from the view and apply the perspectives to the model itself only. In this case, the model is treated as an ordinary CI. Note: This option is disabled for a view based on a collection of CIs or on a model and a collection of CIs.
Perspectives	Lists the selected perspectives. A default perspective appears in the window before any selection is made. You can set the value of the default perspective using the Selected perspectives for new perspective based views infrastructure setting.

View Results Pane

UI Element (A-Z)	Description
Мар	Click to display the view results in Map mode.
Text	Click to display the view results in Text mode.
Î۴.	Create a relationship between two CIs in the view.
	Toggle between hiding and displaying the topology map legend.
٢	Move up one level in the topology map.
£	Move down one level in the topology map.
×	Delete the selected CI from the view.
P	Click Show Cl Properties to open the Configuration Item Properties dialog box for the selected CI.

UI Element (A-Z)	Description
Ø	Click Refresh to refresh the view results.
Ū	Click Hide Cl from View to hide the selected CI from the view. This option is only relevant for CIs that were added to the view via the perspective. You cannot hide CIs from the original view content from the view.
	Note: Hidden CIs can be restored from the Hidden CIs dialog box.
<u>تة</u>	Click Show Hidden CIs to open the Hidden CIs dialog box which enables you to restore CIs that were hidden from the view manually.
1	Click Create view based on selected CI /s to create a new view based on the CIs selected from the View Results pane.
	Click Expand preview display to display the preview in a separate pane.
<breadcrumbs></breadcrumbs>	At the top of the topology map, the breadcrumbs indicate the relevant query nodes in each layer of the view for the path to the selected layer. The first item in the path is the Top Layer . When you select a CI from the layer below, the parent CI forms the next item in the breadcrumb path. You can click on any item in the path to display that layer in the topology map.

UI Element (A-Z)	Description
<legend></legend>	Indicates the icons displayed next to CIs with any of the following special statuses:
	► Added. When Change Timeframe is active, indicates that the CI was added.
	➤ Candidate for Deletion. Indicates that the CI is a candidate for deletion.
	➤ Changed. When Change Timeframe is active, indicates that the CI was changed.
	► Impacted. When Impact Analysis is active, indicates an impacted CI.
	► Impacted and Trigger. When Impact Analysis is active, indicates a trigger CI that is impacted.
	► Note. Indicates that a note was added for the CI.
	► Trigger. When Impact Analysis is active, indicates a trigger CI.
<topology map=""></topology>	The topology map in the View Results pane follows the layout of the topology map in IT Universe Manager. For details, see "Topology Map" on page 279.
<topology map<br="">Sidebar></topology>	For details, see "Topology Map Sidebar" on page 210.

Shortcut Menu Options

Menu Item	Description
<it shortcut<br="" universe="">Menu options></it>	The IT Universe Manager shortcut menu options are available. For details, see "IT Universe Manager Shortcut Menu" on page 283.
Create view based on selected CI/s	Select Create view based on selected Cl/s to create a new view based on the CIs selected from the View Results pane.

Menu Item	Description
Hide CI from View	Click to hide the selected CI from the view. This option is only relevant for CIs that were added to the view via the perspective. You cannot hide CIs from the original view content from the view. In the case of a view based on a model, the model cannot be hidden but its CIs can.
Show Hidden Cls	Restore hidden CIs to the view.

Query Node Grouping Dialog Box

This dialog box enables you to define a new grouping of CIs or to edit an existing grouping.

To access	Click the Add Group by 🚰 button in the Hierarchy pane
	of the Pattern View Editor and select Add Group by
	Attribute or right click the required query node and
	select Add Group by Attribute from the shortcut menu.

UI Element (A-Z)	Description
Expression capture group index	Enter the number of the relevant portion of the regular expression. Enter 0 if the entire expression is relevant.
Group by	Select an attribute from the drop-down list.
Mask to group by	Enter a regular expression pattern representing the structure of the selected attribute. For details, see "Query Node Grouping" on page 341.

Query/View Definition Properties Dialog Box

This dialog box enables you to configure the properties of a TQL query or view.

To access	In the Modeling Studio, click the Query/View Definition Properties for button in the TQL Query Editor or Pattern View Editor.
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
Base Query	Select an existing TQL query on which to base your new query.
	Note:
	This field is only relevant for TQL queries.This field is optional.
Bundles	A method of grouping TQL queries or views by category. Select the bundles associated with the current query or view or create a new bundle for it.
	Note: This field is optional.
Description	A description of the TQL query or view.
Inter-Layer Links	Set the scope of inter-layer relationships displayed in the topology results.
	Note: This field is only relevant for views.
Persistent	Select to define the TQL query as persistent. A persistent query remains in the memory permanently.
	Note: This field is only relevant for TQL queries.

UI Element (A-Z)	Description
Priority	Select a priority level for the TQL query or view from the drop-down list (Low, Medium, High, Express, Not Active). This setting determines how often the query should be rerun automatically by the system to include updated information from the RTSM.
	Note: When you change the priority of a view, the priority of the TQL query on which the view is based is also changed.
Scope	Select the scope of the TQL query from the drop-down list. Note: This field is only relevant for Integration TQL queries.
Туре	Select the type of the TQL query from the drop-down list. Note: This field is only relevant for TQL queries.

💐 Reveal CIs Dialog Box

This dialog box enables you to search for CIs related to the CIs in a model and add them to the model.

In the Model Editor of the Modeling Studio, select a CI,
click the Reveal 💫 button, and select Start Revealing or
right-click a CI in the model and select Reveal > Start
Revealing.

Important information	The upper pane displays the CI types of the CIs related to the selected CI. The lower pane displays the CIs of the type selected in the upper pane.
	The first step in the reveal path is the CI type of the CI you began with. When you select a CI type from the list in the upper pane, that CI type becomes the second step in the path. Click Next to display the CI types available for the next step of the path.
	The number at the top of the box in parentheses indicates the length of the constructed path thus far.
Relevant tasks	"Build an Instance-based Model" on page 370

UI Element (A-Z)	Description
×	Click to delete a selected item from the CIs basket.
1	Click to add a selected CI from the lower pane to the CIs basket.
\bigcirc	Click to go to the next occurrence of the selected search phrase in the list of CIs.
\bigcirc	Click to go to the previous occurrence of the selected search phrase in the list of CIs.
<lower pane=""></lower>	Displays a list of related CIs of the type selected in the upper pane.
CI count	Indicates how many related CIs of each type were found.
CIs Basket	Displays the related CIs you selected to include in the model.
СІ Туре	Displays a list of CI types of the CIs related to the selected CI.

UI Element (A-Z)	Description
Conditions	A check mark indicates that conditions were defined for the selected CI type. Click the Conditions column for the CI type you want to select and click the Add Condition or Edit Condition button to open the Conditions of Related CIs dialog box. This enables you to define and edit conditions for the CI type.
Find	Enter a CI name or a portion of a CI name in the Find box to locate a CI in the list of CIs.
Finish	Click Finish when you have finished adding CIs to the CI basket.
Next	Click Next to display the CI types available for the next step of the path.
Reveal path	Displays the reveal path being constructed.
	Clicking the blue arrows in the path \Rightarrow displays a drop- down list of the CI types available for the next step of the path.
	Clicking the CI types in the path displays the following options:
	► Jump to page. Refreshes the table with the available CI types for the selected step of the path.
	➤ Edit Condition. Opens the Conditions of Related CIs dialog box.
	 Delete Selected Item(s). Deletes the selected CI type from the reveal path (the path ends at the previous CI type).
Save Path	Opens the Save Reveal Path dialog box which enables you to save the path. This option is only active when a unique reveal path has been constructed.

💐 Save Query Dialog Box

This dialog box enables you to save a new TQL query.

To access	In the Modeling Studio, click the Save button when defining a new TQL query.
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
	Click New Folder to create a new folder in the resource tree.
×	Click Delete to delete the selected resource from the RTSM.
0	Click Refresh to refresh the resource tree.
1	Click Expand All to expand all the folders in the resource tree.
5	Click Collapse All to collapse all the folders in the resource tree.
\bigcirc	Click to go to the next occurrence of the selected search phrase in the tree.
\bigcirc	Click to go to the previous occurrence of the selected search phrase in the tree.
	Click to highlight all occurrences of the search phrase in the tree.
<resource tree=""></resource>	Select a folder in the tree in which to save the query.
Find	Enter a folder name or a portion of a name in the Find box to locate a folder in the list.
Query Name	Enter the name of the new TQL query.

💐 Save View/Template/Perspective Dialog Box

This dialog box enables you to save a new pattern view, template-based view, perspective-based view, template, or perspective.

To access	In the Modeling Studio, click the Save button when defining a new pattern view, template-based view, perspective-based view, template, or perspective.
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
	Click New Folder to create a new folder in the resource tree.
×	Click Delete to delete the selected resource from the RTSM.
Ø	Click Refresh to refresh the resource tree.
聪	Click Expand All to expand all the folders in the resource tree.
16	Click Collapse All to collapse all the folders in the resource tree.
\odot	Click to go to the next occurrence of the selected search phrase in the tree.
\bigcirc	Click to go to the previous occurrence of the selected search phrase in the tree.
	Click to highlight all occurrences of the search phrase in the tree.
<resource tree=""></resource>	Select a folder in the tree in which to save the view, template, or perspective.
Find	Enter a folder name or a portion of a name in the Find box to locate a folder in the list.

UI Element (A-Z)	Description
New query	Select New query if the view is based on a new TQL query.
	Note: This field is not relevant for template-based views and perspective-based views.
View Name	Enter the name of the new view, template, or perspective.

💐 Select Data Sources Dialog Box

This dialog box enables you to select the required data sources for a TQL query node.

To access	In the Modeling Studio, right-click a TQL query node and select Set Data Sources .
Important information	You can select the data sources from which the TQL query generates the results for each query node. For details on data sources, see "Integration Studio Overview" in the <i>RTSM Data Flow Management Guide</i> .
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
<data list="" source=""></data>	A list of available data sources.
All Data Sources	Select to include CIs from all RTSM and external sources for the selected query node in the TQL query results.
Local Data Source	Select to include CIs from the RTSM only for the selected query node in the TQL query results.
Select Data Sources	Select to include CIs from the selected sources only for the selected query node in the TQL query results.

💐 Sort Column Content Dialog Box

This dialog box enables you to set the order of the column content in a report.

To access	In the Modeling Studio, click Set Sort Order in the Query Node Definition pane of the Pattern View Editor (in Report mode).
Important information	The report is sorted by columns following the order of the attributes in the Sorted Columns pane. Each selected column is sorted in ascending or descending order according to your selection.
Relevant tasks	"Define Report Settings" on page 369
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
⇒	Click Move to Sorted Columns to move the selected attribute to the Sorted Columns pane.
¢	Click Move to Available Columns to move the selected attribute to the Available Columns pane.
***	Click to move all the attributes to the Sorted Columns pane.
5	Click to move all the attributes to the Available Columns pane.
¥	Click to move the selected attribute down in the Sorted Columns list.
1	Click to move the selected attribute up in the Sorted Columns list.
L ↑	Click Sort Ascending to sort the selected column in ascending order.
F ↓	Click Sort Descending to sort the selected column in descending order.

UI Element (A-Z)	Description
Available Columns	The attributes selected to appear as columns in the report.
Sorted Columns	The columns selected to be sorted.

🂐 Template-based View Wizard

This wizard enables you to define template-based views manually or by importing parameter data from a CSV file.

To access	Click the New * button and select Template Based View .
Important information	The wizard enables you to create multiple template-based views based on the same template. When creating multiple views, the wizard includes the Save Views page as the final page. When creating a single template-based view, the wizard finishes with the Parameters page and opens the new view in the Editor. You can save the new view from within the Editor.
Relevant tasks	 "Create a Template Based View" on page 365 "Create Multiple Template Based Views" on page 367
Wizard map	The Template-based View Wizard contains: Select Template Page > Import Parameter Values Page > Parameters Page > Select Location for Views Page > Summary Page > Save Views Page
See also	"Creating Template Based Views" on page 345

💐 Select Template Page

This wizard page enables you to select a template on which to base your view.

Important information	If you don't want to use any of the templates in the tree, you can create a new template first and then build a view based on it. For details on creating a template, see "Create a Template" on page 360.
Wizard map	The Template-based View Wizard contains: Select Template Page > Import Parameter Values Page > Parameters Page > Select Location for Views Page > Summary Page > Save Views Page

UI Element (A-Z)	Description
0	Click Refresh to refresh the template tree.
影	Click Expand All to expand all the folders in the template tree.
16	Click Collapse All to collapse all the folders in the template tree.
\bigcirc	Click to go to the next occurrence of the selected search phrase in the tree.
\bigcirc	Click to go to the previous occurrence of the selected search phrase in the tree.
	Click to highlight all occurrences of the search phrase in the tree.
<template tree=""></template>	Displays the existing templates in tree format.
Find	Enter a template name or a portion of a name in the Find box to locate a template in the list.

💐 Import Parameter Values Page

This wizard page enables you to import parameter values from a CSV file.

Important information	If you are creating a large number of views based on the same template, you can save the parameter values in a CSV file and import them directly into the wizard.
Wizard map	The Template-based View Wizard contains: Select Template Page > Import Parameter Values Page > Parameters Page > Select Location for Views Page > Summary Page > Save Views Page

UI Element (A-Z)	Description
Add parameter values manually	Select this option to enter the parameter values manually, whether for a single view or for multiple views.
Import parameter values from a CSV file	Select this option to import the parameter values from a CSV file. Click the ellipsis button to browse your files for the required file.
Use Advanced Naming	Select the Use Advanced Naming option to automatically name the created views based on parameter values. In the box, enter an expression containing at least one parameter name in angle brackets. The views are named based on the values of the selected parameter.

💐 Parameters Page

This wizard page enables you to set the values of the template's parameters for each new view created.

Important information	If you are creating multiple views, click Next after you set the parameter values to proceed to the Save Views page. If you are creating a single view, click Finish after you set the parameter values to open the new view in the Editor.
Wizard map	The Template-based View Wizard contains: Select Template Page > Import Parameter Values Page > Parameters Page > Select Location for Views Page > Summary Page > Save Views Page

UI Element (A-Z)	Description
÷	Click to add a new view instance.
×	Click to delete the selected view instance.
<parameter columns></parameter 	In each parameter column, enter or select the required parameter value for each view.
Reset	Click to reset the selected parameter to its original value.
Use Advanced Naming	Select the Use Advanced Naming option to automatically name the created views based on parameter values. In the box, enter an expression containing at least one parameter name in angle brackets. The views are named based on the values of the selected parameter. Note: All view names must be unique.
View Name	Enter names for each of the new views, or use the default names assigned.

💐 Select Location for Views Page

This wizard page enables you to select the location in which to save the created views.

Important information	All created views must be saved in the same location
Wizard map	The Template-based View Wizard contains: Select Template Page > Import Parameter Values Page > Parameters Page > Select Location for Views Page > Summary Page > Save Views Page

UI Element (A-Z)	Description
	Click New Folder to create a new folder in the view tree.
0	Click Refresh to refresh the view tree.
	Click Expand All to expand all the folders in the view tree.
86	Click Collapse All to collapse all the folders in the view tree.
0	Click to go to the next occurrence of the selected search phrase in the tree.
\bigcirc	Click to go to the previous occurrence of the selected search phrase in the tree.
	Click to highlight all occurrences of the search phrase in the tree.
<view tree=""></view>	Select a folder (or the root) from the view tree.
Find	Enter a template name or a portion of a name in the Find box to locate a template in the tree.

💐 Summary Page

This wizard page displays the details of the created views before saving.

Wizard map	The Template-based View Wizard contains:
	Select Template Page > Import Parameter Values Page > Parameters Page > Select Location for Views Page >
	Summary Page > Save Views Page

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
Save view summary	A summary of the views created including the name of the base template, the number of views created, and the location selected for saving the views.

💐 Save Views Page

This wizard page enables you to save the new views you created.

Important information	This wizard page is only relevant when you are creating multiple template-based views.
Wizard map	The Template-based View Wizard contains:
	Select Template Page > Import Parameter Values Page > Parameters Page > Select Location for Views Page > Summary Page > Save Views Page

UI Element (A-Z)	Description
Save Results	A table displays the names of the new views and a message indicating whether each view was saved successfully or not.

🂐 Template Parameter Values Dialog Box

This dialog box enables you to edit the parameters of a template-based view.

To access	From within a template-based view in the Modeling Studio, right-click a query node with parameters defined and select Show Node Parameters , or click the Show Parameters (P) button in the toolbar.
Important information	When you open the dialog box from the shortcut menu by right-clicking a query node with parameters defined, the dialog box only displays the parameters for the selected query node. When you open the dialog box from the toolbar, it displays all the parameters defined for any of the query nodes in the view.
See also	"Best Practices for Modeling" on page 215

User interface elements are described below:

UI Element (A-Z)	Description
<parameters></parameters>	Edit the values of the parameters.

A TQL Query Editor

This feature enables you to build and edit TQL queries.

To access	To open a new TQL query in the TQL Query Editor, go to the Modeling Studio, click the New button and select Query .
	To open an existing TQL query in the TQL Query Editor, go to the Resources tab of the left pane in the Modeling Studio and select Queries as the Resource type. Right click a TQL query in the tree and select Open Query or double click a TQL query or drag a TQL query onto the empty canvas. The TQL query opens in a new tab.
Important information	To save your TQL query, use the Save button in the Modeling Studio main toolbar.

440

Relevant tasks	"Define a TQL Query" on page 30
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
٢	Click Show View Results in IT Universe to go directly to the selected view in IT Universe Manager.
	Note: This button only appears for views, templates, or perspectives.
Î.	Click Create Relationship to draw a relationship from one query node to another.
	Click Hide/Show Legend to toggle between hiding and displaying the topology map legend.
	Click Calculate Query Result Count to calculate the number of instances found for each TQL query node or relationship.
Q	Click Preview to display a preview of the TQL query results as they would appear in IT Universe Manager.
×	Click Delete to delete the selected query node or relationship from the query.
	For queries, opens the Query Definition Properties dialog box which enables you to edit the type, scope, and priority of the TQL query.
	For views, opens the View Definition Properties dialog box.
	Opens the Template Parameter Values dialog box which enables you to edit the parameters of a query node in a template-based view.
	Note: This button only appears for template-based views.

UI Element (A-Z)	Description
<legend></legend>	Indicates the icons displayed next to CIs with any of the following special designations:
	➤ It is defined as a contact query node in a perspective
	 It is defined as the output query node of a pattern- based model
	► It has attributes defined
	 It has selected identities defined
	 It is set as an invisible element
	► It has a subgraph defined
<main menu=""></main>	For details, see "Main Menu" on page 197.
<shortcut menu<br="">options></shortcut>	For details, see "Shortcut Menu Options" on page 40.
<topology map<br="">Sidebar></topology>	For details, see "Topology Map Sidebar" on page 210.

Advanced Pane

This area displays the properties, conditions, and cardinality for the selected query node and relationship.

Important	The Advanced pane appears in the lower part of the window in the following managers and user interfaces: Modeling Studio, Impact Analysis Manager, Enrichment Manager, the Input Query Editor and Trigger Query Editor in DFM.
information	A small green indicator * appears next to the tabs that contain data.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Elements (A-Z)	Description
	If the window is not wide enough to display all the tabs, use the left and right arrows to move to the required tab.
•	Click Show List to display a list of the available tabs for the current module. You can select a tab from the list.
Attributes	Displays the attribute conditions defined for the query node or the relationship. For details, see "Attribute Tab" on page 87.
Cardinality	Cardinality defines how many query nodes you expect to have at the other end of a relationship. For example, in a relationship between a node and an IP Address, if the cardinality is 1:3, the TQL query retrieves only those nodes that are connected to between one and three IP Addresses. For details, see "Cardinality Tab" on page 89.
Data Sources	Displays the data sources set for the selected query node.
	Note: This tab appears only in the Modeling Studio.
Details	 Displays the following information: Cl Type. The CIT of the selected query node/relationship. Visible. A green check indicates that the selected query node/relationship is visible in the topology map. A red mark indicates that it is not visible. Include subtypes. A green check indicates that both the selected CI and its children are displayed in the topology map. A red mark indicates that only the selected CI appears.
Edit	Click Edit to open the relevant dialog box for the selected tab.

UI Elements (A-Z)	Description
Enrichment Rules	Displays the Enrichment rule defined for the selected query node or relationship. If the Enrichment rule is used to update the attributes of a CI, click Edit to open the Query Node/Relationship Definition dialog box and edit the rule if required. For details, see "Query Node/Relationship Definition Dialog Box" on page 544. Note: This tab appears only in Enrichment Manager.
Impacted Query Nodes	Indicates which query node is affected by the changes that occur in the selected trigger query node. If required, you can click Edit to open and modify the Affected Query Nodes dialog box. For details, see "Impacted Query Nodes Dialog Box" on page 466. Note: This tab appears only in Impact Analysis Manager.
Qualifiers	Displays the qualifier conditions defined for the query node or the relationship. For details, see "Qualifier Tab" on page 92.
Selected Identities	Displays the element instances that are used to define what should be included in the TQL query results. For details, see "Identity Tab" on page 95.

💐 Views Containing Selected CI Dialog Box

This dialog box enables you to display a list of the views containing the selected CI.

To access	Click the Show views containing selected Cl/model button in the Model Editor or select Show containing views from the shortcut menu.
See also	"Best Practices for Modeling" on page 215

UI Element (A-Z)	Description
•	Click Show View Results in IT Universe to go directly to the selected view in IT Universe Manager.
×	Click Delete Selected Item(s) to delete the selected view.
Z	Click Disconnect view from perspective to disconnect the selected view from its perspective. The view becomes a pattern view.
Find	Enter a view name or a portion of a view name in the Find box to locate it in the list.
Find Next	Click to go to the next occurrence of the selected search phrase in the list.
Find Previous	Click to go to the previous occurrence of the selected search phrase in the list.
Highlight	Click to highlight all occurrences of the search phrase in the list.
View Name	Displays the list of views dependent on the selected template or perspective.
	Note: The name of the current view appears in faded text.

% Watchpoints Updates Dialog Box

This dialog box displays the changes found in related CIs by a watchpoint defined for a model.

To access	From within a model in the Model Editor, click the Watchpoint Button and select Watchpoints Updates or right-click a CI in the model and select Watchpoint > Watchpoints Updates .
Important information	The Watchpoints Updates dialog box indicates any changes found involving the CIs related to the model via the associated reveal path. If a new related CI is found which is not included in the model, the suggested update is an added CI. If a CI in the model is found to no longer be related via the path, the suggested update is a removed CI. This option is only enabled when watchpoints are defined for the model and CIs have been found.

UI Element (A-Z)	Description
Accept	Select the check boxes for the CIs you want to add to your model or remove from your model.
Accept All	Click Accept All to apply all the suggested changes to your model.
СІ	The names of the CIs found by the watchpoint.
СІ Туре	The types of the CIs found by the watchpoint.
Clear All	Click Clear All to clear the check boxes for all the found CIs.
Restore	Select the check boxes for the CIs in the Suppressed CIs pane that you want to consider for inclusion in your model.
Show/Hide Suppressions	Toggle between hiding and displaying the Suppressed CIs pane of the dialog box.

UI Element (A-Z)	Description
Suggested Update	Indicates whether the suggested change is an added CI or a removed CI.
Suppress	Select the check boxes for the CIs you want to exclude from your model or leave in your model.
Suppress All	Click Suppress All to decline all the suggested changes to your model.

% <Query/Template/Perspective Name> Dependencies Dialog Box

This dialog box enables you to clarify the status of dependent views when saving changes to a query, template, or perspective.

To access	In the Modeling Studio, make a change to a query, template, or perspective with dependent views. When you click Save , the dialog box opens.
Important information	Any change made to a resource affects the views based on that resource. Before the changes are saved, you need to specify the desired result on the dependent views. For each dependent view, select one of the available options: Delete, Re-Apply, or Detach.

UI Element (A-Z)	Description
Delete	Select this option to delete the selected dependent view.
Detach	Select this option to detach the selected dependent view from the template or perspective. The view becomes a pattern view. Note: This option is not relevant for queries.

Chapter 10 • Modeling Studio

UI Element (A-Z)	Description
Re-Apply	Select this option to apply the revised query, template, or perspective to the selected dependent view. The view type remains the same as it was previously (pattern view, template-based view, or perspective-based view).
Resource	The dependent views are displayed in a tree format.

11

Impact Analysis Manager

This chapter includes:

Concepts

► Impact Analysis Manager Overview on page 450

Tasks

► Define an Impact Rule – Workflow on page 452

Reference

► Impact Analysis Manager User Interface on page 456

Concepts

\lambda Impact Analysis Manager Overview

Impact Analysis Manager enables you to define the interdependencies between components in your IT infrastructure to simulate how infrastructure changes (for example, a new software installation or upgrade) can impact your system.

By creating Impact rules based on TQL queries, you can determine the true origin of a problem and its business impact. Each Impact rule you define is attached to a specific Impact Analysis TQL query. For more information about TQL queries, see "Topology Query Language" on page 21.

You define Impact rules to specify a causal relationship between two or more Impact Analysis query nodes. Define one query node as the trigger, or the query node that represents the changes you want to make to the system, and another query node as the one that is impacted. After the causal relationship is established, Impact Analysis Manager enables you to determine the effect of the changes occurring in root cause query nodes.

You then run the Impact rules in IT Universe Manager to simulate how the changes impact your system and discover the root causes of the changes (for details, see "Run Impact Analysis Dialog Box" on page 294). This enables you to evaluate and handle accordingly, the possible implications of any action, update, new deployment, or a failure of the service delivery.

A simulated change in an impacted CI can alter the CI's map status, which is manifested through an addition of a status icon to the CI's symbol. The Topology Map displays the statuses of the trigger CIs as well as all statuses of the CIs that are impacted by it. Each color represents a different status.

For details about the status icons and the colors that represent them, see "Show Impact Pane" on page 300.

You can then generate a report displaying the following:

- ► CIs in the system that are impacted by the changes.
- ➤ Trigger CIs (the CIs that represent the changes you want to make to the system).
- ► CIs that belong to a specific business service.

Tasks

膧 Define an Impact Rule – Workflow

This section describes how to define an Impact rule whereby a change in CPU operation impacts the node to which it is connected.

This task includes the following steps:

- ➤ "Create an Impact Analysis TQL Query" on page 452
- ► "Define an Impact Rule" on page 453


1 Create an Impact Analysis TQL Query

To create an Impact Analysis TQL query, you need to create an Impact Analysis TQL and then add the TQL query nodes and relationships that define the query.

Select Admin > RTSM Administration > Modeling > Impact Analysis Manager to open the Impact Analysis Manager. For details about how to create an Impact Analysis TQL query, see "New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard" on page 469. For details about how to add query nodes and relationships to a query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

Example of an Impact Analysis TQL Query:

In this Impact Analysis TQL query, a CPU and a node are linked by a Composition relationship. The TQL query results must comply with the direction of the arrows.



Note: An Impact Analysis TQL query is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103.

2 Define an Impact Rule

When you define an Impact rule, you must specify the required causal relationship between the query nodes. Define one query node as the trigger, or the query node that represents the changes you want to make to the system, and another query node as the one that is impacted.

Right-click the query node you want to define as the trigger query node and select **Define Impacted** to open the Impacted Query Nodes dialog box. Select the query node you want the trigger query node to impact. Then click the **Add** button to open the Impact Rules Definition dialog box to set conditions for defining impacted query nodes. For details about how to define an Impact rule, see "Impact Rules Definition Dialog Box" on page 467. **Note:** The **change** state option in the Impact rule definition is no longer relevant for Impact Analysis. The only supported state is **operation**.


Example of an Impact Rule:

The Conditions area in the Impact Rules Definition dialog box defines the conditions under which the simulated change in the system is triggered. The Severity area defines the severity of the impact on the impacted query node.

The Impact rule in this example states that when the CPU operation is not in the normal state, the node is impacted. Since the severity is set to 100% of the trigger's severity, the severity of the node is the same as the severity of the CPU, which is determined when Impact Analysis is run.

🛓 Impact Rules De	finition
Description:	
State:	operation
Operator:	Not equal
Value comparison:	Normal
Scope Any All Range	% - 100 %
 Fixed severity: Severity relative t 	Critical 💌
	OK Cancel

In the resulting TQL query, an upward arrow appears next to the query node defined as the trigger query node and a downward arrow appears next to the query node defined as the impacted query node.



Note: To retrieve the Impact Analysis results, you must run the Impact rule in IT Universe Manager. For details, see "Retrieve Impact Analysis Results – Scenario" on page 250.

Reference

💐 Impact Analysis Manager User Interface

This section includes (in alphabetical order):

- ► Details Dialog Box on page 457
- ► Impact Analysis Manager Page on page 458
- ► Impacted Query Nodes Dialog Box on page 466
- ► Impact Rules Definition Dialog Box on page 467
- New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard on page 469

💐 Details Dialog Box

This dialog box displays the new Impact rule you created in the Impact Rules Definition dialog box.

To access	In the Impact Analysis Manager, click Next in the Impacted Query Nodes dialog box.
Relevant tasks	"Define an Impact Rule – Workflow" on page 452

UI Element (A-Z)	Description
Description	The description of the new Impact rule.
State	The category you chose from the State list in the Impact Rules Definition dialog box.

🂐 Impact Analysis Manager Page

To access	Select Admin > RTSM Administration > Modeling > Impact Analysis Manager.
Important information	When selecting query nodes to function as Impact Analysis triggers, they must comply with certain restrictions. For details, see "Troubleshooting and Limitations" on page 103.
Relevant tasks	"Define an Impact Rule – Workflow" on page 452
See also	"Impact Analysis Manager Overview" on page 450

This page enables you to define Impact rules.

Impact Rules Pane

This area displays a hierarchical tree structure of predefined folders and Impact rules. Each Impact rule is associated with a TQL query.

Important information	You can create your own Impact rules, or work with the default rules provided with your HP Business Service Management installation.
	The predefined folders are provided for the default Impact rules; you can modify these folders, or add additional folders according to your organization's requirements.
	You can drag and drop Impact rules or folders to move them from one folder to another.

UI Element (A-Z)	Description
	Create a new folder.
*	Creates an Impact rule. Opens the New Impact Rule Wizard.
×	Deletes the selected folder or Impact rule.

UI Element (A-Z)	Description
0	Refreshes the data content of the hierarchical tree structure that may have been modified by other users.
8	(Enabled only when a new Impact rule is created or when changes are made to an existing one.) Saves the Impact rule to the RTSM.
F	Opens the Impact Rule Properties Wizard. Enables you to change the description of the rule.
Q	Generates a preview of the results of the selected Impact rule.
E	Represents a folder.
Q	Represents an Impact rule.
<impact rules="" tree=""></impact>	Displays the existing Impact rules in tree format.
	Note: Only Impact Analysis rules appear in the tree. TQL queries of type Impact Analysis (created in the Modeling Studio) do not appear.

The following elements are available by right-clicking a folder or Impact rule:

UI Element (A-Z)	Description
Delete	Delete the selected folder or Impact rule.
Export To XML	Displays a standard Save As dialog box, enabling you to save the Impact rule as an XML script. This option can be used to move an Impact rule from one workstation to another, provided the related TQL query is also relocated.
Import From XML	Imports XML files that contain saved Impact rules to Impact Analysis Manager.
New	Creates an Impact rule. Opens the New Impact Rule Wizard.
New Folder	Creates a new folder.

UI Element (A-Z)	Description
Preview	Generates a preview of the results of the selected Impact rule.
Properties	Opens the Impact Rule Properties Wizard. Enables you to change the description of the rule.
Rename Folder	Rename the folder.
Save	(Enabled only when a new Impact rule is created or when changes are made to an existing one.) Saves the Impact rule to the RTSM.
Save As	Displays the Save As Impact Rule Wizard, enabling you to create new Impact rules based on an existing query.

Editing Pane

This area displays the selected Impact rule, which consists of query nodes that are defined in the TQL query and the relationships between them.

Important information	 When you select a folder in the Impact Rules pane, the editing pane is empty. When you select an Impact rule in the Impact Rules pane, the editing pane displays the selected rule, which consists of TQL query nodes that are defined in the TQL query and the relationships between them.
Relevant tasks	"Add Query Nodes and Relationships to a TQL Query" on page 32
See also	When selecting query nodes to function as Impact Analysis triggers, they must comply with certain restrictions. For details, see "Troubleshooting and Limitations" on page 103.

UI Element (A-Z)	Description
+	Indicates a trigger query node. Located to the right of the trigger query node's icon.
+	Indicates an impacted query node. Located to the right of the impacted query node's icon.
1	Indicates query nodes that are both impacted and trigger query nodes.
<main menu=""></main>	For details, see "Main Menu" on page 197.
<query node=""></query>	A component from which TQL queries are built.
<relationship></relationship>	The entity that defines the relationship between two query nodes.
<shortcut menu<br="">options></shortcut>	For details, see "Shortcut Menu Options" on page 40.
<toolbar></toolbar>	For details, see "Toolbar Options" on page 201.
<tooltip></tooltip>	Hold the cursor over a query node or relationship to view its tooltip.
	The tooltips contain the following information:
	► Element name. The name of the query node.
	 Cl Type. The CIT of the query node as defined in the CI Type Manager. For details, see "CI Type Manager" on page 475.
	 Definitions of the selected query nodes and relationships. The attribute conditions, as described in "Query Node/Relationship Properties Dialog Box" on page 85.
	Names of the trigger and the impacted query nodes. This is only relevant if the query node over which the cursor is hovering is the trigger query node.

CI Type Selector

This area displays a hierarchical tree structure of the CI Types found in the ODB.

Important information	The CI Type Selector is part of Enrichment Manager, Impact Analysis Manager, and Trigger TQL Editor.
	To create or modify a TQL query, click and drag query nodes to the Editing pane and define the relationship between them. Your changes are saved to the ODB. For details, see "Add Query Nodes and Relationships to a TQL Query" on page 32.
	Note : The number of instances of each CIT in the ODB is displayed to the right of each CIT.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Create a Pattern View" on page 359

UI Elements (A-Z)	Description
¢	Click Add CI Type to Map to move the selected CI type to the Editing pane.
Ø	Click Refresh to refresh the CI type tree.
Q	Click Search to search for the CI type entered.
1	Click Expand All to expand all subtrees within the CI type tree.
	Click Collapse All to collapse the subtrees within the CI type tree.
<search window=""></search>	Enter the name or part of a name of a CI type for which to search.

Shortcut Menu Options

The CI Type Selector includes the following elements (listed alphabetically) available by right-clicking a CI Type:

Menu Item	Description
Add CI Type to Map	Select to add the selected CI type to the Editing pane.
Go to Cl Type Definition	Takes you directly to the selected CI type in CIT Manager.
Show CIT Instances	Opens the CIT Instances window, which displays all instances of the selected CIT. For details, see "Element Instances Dialog Box" on page 77.

Advanced Pane

This area displays the properties, conditions, and cardinality for the selected query node and relationship.

Important	The Advanced pane appears in the lower part of the window in the following managers and user interfaces: Modeling Studio, Impact Analysis Manager, Enrichment Manager, the Input Query Editor and Trigger Query Editor in DFM.
information	A small green indicator ** appears next to the tabs that contain data.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Elements (A-Z)	Description
	If the window is not wide enough to display all the tabs, use the left and right arrows to move to the required tab.
v	Click Show List to display a list of the available tabs for the current module. You can select a tab from the list.
Attributes	Displays the attribute conditions defined for the query node or the relationship. For details, see "Attribute Tab" on page 87.
Cardinality	Cardinality defines how many query nodes you expect to have at the other end of a relationship. For example, in a relationship between a node and an IP Address, if the cardinality is 1:3, the TQL query retrieves only those nodes that are connected to between one and three IP Addresses. For details, see "Cardinality Tab" on page 89.
Data Sources	Displays the data sources set for the selected query node. Note: This tab appears only in the Modeling Studio.
Details	 Displays the following information: Cl Type. The CIT of the selected query node/relationship. Visible. A green check indicates that the selected query node/relationship is visible in the topology map. A red mark indicates that it is not visible. Include subtypes. A green check indicates that both the selected CI and its children are displayed in the topology map. A red mark indicates that only the selected CI appears.
Edit	Click Edit to open the relevant dialog box for the selected tab.

UI Elements (A-Z)	Description
Enrichment Rules	Displays the Enrichment rule defined for the selected query node or relationship. If the Enrichment rule is used to update the attributes of a CI, click Edit to open the Query Node/Relationship Definition dialog box and edit the rule if required. For details, see "Query Node/Relationship Definition Dialog Box" on page 544. Note: This tab appears only in Enrichment Manager.
Impacted Query Nodes	Indicates which query node is affected by the changes that occur in the selected trigger query node. If required, you can click Edit to open and modify the Affected Query Nodes dialog box. For details, see "Impacted Query Nodes Dialog Box" on page 466. Note: This tab appears only in Impact Analysis Manager.
Qualifiers	Displays the qualifier conditions defined for the query node or the relationship. For details, see "Qualifier Tab" on page 92.
Selected Identities	Displays the element instances that are used to define what should be included in the TQL query results. For details, see "Identity Tab" on page 95.

💐 Impacted Query Nodes Dialog Box

This dialog box enables you to define which query node in the TQL query is the trigger Impact Analysis query node and which query nodes are impacted by the changes that occurred in the system.

To access	Right-click the query node or relationship that functions as a trigger and select Define Impacted . The Impacted Query Nodes dialog box opens to display the query nodes in the TQL query.
Important information	Before creating the TQL query, you must know which query node in the query is the trigger Impact Analysis query node and which are impacted by the changes beforehand. The definition is performed here.
Relevant tasks	"Define an Impact Rule – Workflow" on page 452.

UI Element (A-Z)	Description
Impacted Query Nodes pane	Contains a list of the Impact Analysis query nodes in the Impact rule. Select the query nodes to be impacted by the trigger query node.

💐 Impact Rules Definition Dialog Box

This dialog box enables you to set conditions for defining impacted query nodes, define the scope of the trigger conditions, and define the severity of the impact.

To access	In the Impact Analysis Manager, click Add in the Details dialog box.
Important information	 In the Conditions area, set conditions for defining impacted query nodes. When this condition is met, the simulated change in the system is triggered. For example, you can define an Impact Analysis condition that states that the operational state of the query node is other than Normal. When the operational state of the query node instance changes and is no longer Normal, the condition is met and the simulated changes in the system are triggered.
	 In the Scope area, define how many instances of the trigger query node should fulfill the conditions for triggering the changes in the system. You can apply the trigger conditions to a single instance of a trigger query node, to a certain percentage of the trigger instances, or to all of them. For example, you can define that impact is calculated when at least 10% of the system's nodes are down. In the Severity area, define the severity of the Impact Analysis impact.
Relevant tasks	"Define an Impact Rule – Workflow" on page 452

UI Element (A-Z)	Description
All	All instances should fulfill the conditions.
Any	One instance or more should fulfill the conditions.
Description	A description of the Impact rule you are defining.

UI Element (A-Z)	Description
Fixed severity	Define a fixed severity level for every system change generated. Then, select the required severity level from the list.
Function	Select Function (displayed when you selected the All and Range options in the Scope area) to define a severity level for the system changes, as a function of the severity levels of all the trigger query node instances that are included in the range. From the list, select either Average or Max .
	For example, if you select Average , the severity level of the system changes is the average severity of all the trigger instances.
Operator	Select the required operator. For a list of the operators you can use for defining an attribute condition, see "Attribute Operator Definitions" on page 45.
Range	A certain percentage of all instances should fulfill the conditions. For example, if you enter a range of 50% to 100%, the changes are triggered when 50% or more of the instances meet the conditions.
Severity relative to trigger severity (%)	Select Severity relative to trigger severity (%) (displayed when you selected the Any option in the Scope area) to define a severity level for each system change that is relative (as a percentage) to the severity of the trigger event. Enter the percentage in the box provided.
State	Choose the required state. The states that appear in the
	list are the states that are defined in the State Manager. For details, see "State Manager" in the <i>RTSM</i> <i>Administration Guide</i> .
Value comparison	Select the required attribute.

New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard

To access	 To create an Impact rule, right-click anywhere in the Impact Rules pane and click New or click the New button. To modify an Impact rule, right-click an Impact rule in the Impact Rules pane and select Properties. To create a new Impact rule based on an existing query, right-click an Impact rule in the Impact Rules pane and select Save As. 	
Important information		
Relevant tasks	"Define an Impact Rule – Workflow" on page 452	
Wizard map	The New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard contains: Impact Rule General Attributes Page > Impact Rule Base Query Page > Impact Rule Groups Page	

This wizard enables you to create or modify an Impact rule.

🂐 Impact Rule General Attributes Page

This wizard page enables you to enter a unique name and description for the Impact rule.

Important information	 The Impact Analysis TQL query that serves as the basis of the Impact rule, is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103. If the TQL query is not valid, it cannot be used for the creation of an Impact rule. For important information on the effects of making changes to the TQL query after creating it, see "New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard" on page 469. By default, this wizard is set to display a Welcome page. You can choose not to display the Welcome page 			
	by changing the user preferences. For details, see "User Preferences Dialog Box" on page 102.			
Wizard map	The New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard contains:			
	Impact Rule General Attributes Page > Impact Rule Base Query Page > Impact Rule Groups Page			
See also	"IT Universe Manager" on page 227			

User interface elements are described below:

UI Element (A-Z)	Description	
Rule Description	(Optional) Enter a description of the Impact rule.	
Rule Name	Enter a unique name for the Impact rule. The rule name cannot contain any of the following characters: \/ : " < > % ? Note : If the Impact rule name is either empty, contains a name used by another Impact rule, or uses invalid characters, the Next and Finish buttons are disabled.	

💐 Impact Rule Base Query Page

This wizard page enables you to define the properties of the TQL query on which the Impact rule is based. You can use an existing query or create a new query.

Important information	 The Impact Analysis TQL query that serves as the basis of the Impact rule is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103. If the TQL query is not valid, it cannot be used for the creation of an Impact rule. For important information on the effects of making changes to the TQL query after creating it, see "New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard" on page 469. 	
Wizard map	The New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard contains: Impact Rule General Attributes Page > Impact Rule Base Query Page > Impact Rule Groups Page	
See also	"IT Universe Manager" on page 227	

User interface elements are described below:

UI Element (A-Z)	Description	
Base the Impact rule on a new query	Select this check box if you want to base the Impact rule on a new TQL query. The query results are based on the attributes defined for the new TQL query.	
Base the Impact rule on an existing query	Select this check box if you want to base the Impact rule on an existing TQL query. Select the required Impact Analysis TQL query from the drop-down list.	
Base Query Description	(Optional) Enter a description of the TQL query.	

UI Element (A-Z)	Description	
Base Query Name	Enter a unique name for the Impact Analysis TQL query. If you selected the Base the Impact rule on an existing TQL option, select the Impact Analysis TQL query on which you want to base the rule.	
Base Query Priority	There is no need to make a selection here since all TQL queries of the type Impact Analysis are automatically set to inactive.	
Save a new query based on the current definition	Select to save a new TQL query based on your Impact rule definition. Note: This field only appears in the Save As Impact Rule wizard.	

💐 Impact Rule Groups Page

This wizard page enables you to define where you can run Impact rules.

Important information	➤ The Impact Analysis TQL query that serves as the basis of the Impact rule, is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103. If the TQL query is not valid, it cannot be used for the creation of an Impact rule.
	➤ For important information on the effects of making changes to the TQL query after creating it, see "New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard" on page 469.
	By default, this wizard is set to display a Completion page after clicking Next in this page. You can choose not to display the Completion page by changing the user preferences. For details, see "User Preferences Dialog Box" on page 102.

Wizard map	The New Impact Rule/Impact Rule Properties/Save As Impact Rule Wizard contains: Impact Rule General Attributes Page > Impact Rule Base Query Page > Impact Rule Groups Page	
See also	"IT Universe Manager" on page 227	

User interface elements are described below:

UI Element (A-Z)	Description	
UCMDB	Enables you to run an Impact rule in IT Universe Manager. For details, see "IT Universe Manager Overview" on page 228.	

Chapter 11 • Impact Analysis Manager

12

CI Type Manager

This chapter includes:

Concepts

- ► CI Types Overview on page 476
- ► CI Type Attributes on page 477
- ► CI Type Relationships on page 478
- ► Deprecated CI Types on page 478
- ► System Type Manager on page 479

Tasks

- ► Create a CI Type on page 481
- ➤ Create a Relationship Type on page 483
- > Create a Calculated Relationship Type on page 484
- ► Create List and Enumeration Definitions on page 485
- ➤ Create an Enumeration Definition Workflow on page 486

Reference

- ➤ View Descriptions for CI Types and Relationships on page 488
- ➤ CI Type Manager User Interface on page 488

Note to HP Software-as-a-Service customers: The data in CI Type Manager can be viewed but not edited.

Concepts

🚴 CI Types Overview

A configuration item (CI) can represent hardware, software, services, business processes, or any component of your IT infrastructure. CIs with similar properties are grouped under a CI type (CIT). Each CIT provides a template for creating a CI and its associated properties.

Every CI must belong to a CI type. The following are the main categories of CITs:

- ➤ Business Element. CITs that correspond to the logical elements of your business, such as processes and organizational groups.
- ➤ IT Process Record. CITs that correspond to changes that occur in your IT infrastructure.
- Monitor. CITs that handle incoming metrics collected from your business universe.
- ➤ Location. CITs that correspond to the location of devices and business organizations or people supporting a function.
- Party. CITs that correspond to an active entity such as a person or organization.
- ► CI Collection. A logical collection of CIs.
- ► Infrastructure Element. CITs that correspond to the physical elements (hardware and software) installed in your business environment.

The CITs are arranged in a tree structure under these categories in the CI Types pane. You can browse the CI Type model by expanding the tree in the CI Types pane. The CIT selected in the left pane is displayed in the topology map along with all the potential valid relationships to other CITs.

You can also define new CITs to match your business needs. For details on defining new CITs, see "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496.

\lambda CI Type Attributes

Every CI type has attributes which define it such as name, description, and default value. The CITs grouped under other CITs in the CI Type tree inherit attributes from the higher-level CITs.

When you define a new CI type, you first select a Base Configuration Item Type from a list of existing CITs. Your new CIT inherits the attributes of the existing CIT. You can then set the attributes for the new CIT. You edit the attributes of an existing CIT by selecting a CIT from the tree in the CI Types pane and selecting the Attributes tab of the topology map. For details on CIT attributes, see "Attributes Page" on page 498.

You can designate one or more of the CIT's attributes as key attributes. A key attribute is an attribute that is used as an identifier of the CIT. When you define an instance of a CIT, the CIT's key attributes are mandatory fields for CIs of that type. You can assign as many key attributes as you want to a given CIT. If you do not assign a key attribute when defining a new CIT, you must select one of the following qualifiers on the Qualifier page of the wizard:

- ➤ ABSTRACT_CLASS. The CIT is created, but it remains abstract, that is, you are unable to create instances of it.
- RANDOM_GENERATED_ID_CLASS. You can create instances of the CIT, but their ID is not based on a key attribute (it is generated randomly).

You can remove the key attributes of an existing CIT as long as at least one key attribute remains. You cannot remove all the key attributes of an existing CIT unless it has one of the above qualifiers.

Entity names in HP Business Service Management for RTSM-based applications follow the conventions described below:

- ➤ CIT attributes values. All primitive types are supported: long, double, float, string, and so on.
- ► CIT attributes values-type string. All special characters are supported. The maximum length is 4000 characters.

- ➤ CIT names and attributes names. The following are permitted: a-z, A-Z, and underscore (_). The length is limited to 200 characters. The CIT name must be in English. The number 0-9 are also permitted, but they must not be the first character in the CIT name.
- ➤ CIT attribute length. The total length of all the attribute values in one CIT cannot exceed 8K bytes due to a Microsoft SQL Server limitation.

🚴 CI Type Relationships

A relationship defines the link between two CIs. Relationships represent the dependencies and connections between the entities in your IT environment. When you select relationships or calculated relationships in the drop-down box in the CI Types pane, the topology map displays all the valid instances of CITs linked by the selected relationship. For details about calculated relationships, see "Impact Modeling" on page 109.

The same attributes defined for CITs are also defined for relationships. You can also assign key attributes for relationships but it is not required. For details on defining new relationship types, see "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496.

🚴 Deprecated CI Types

CITs and relationships that are scheduled to be removed in a subsequent product version are known as deprecated CITs. Such CITs appear in the user interface in strikethrough font. You can hold the pointer over a deprecated CIT to display a tooltip with information about it, including which CIT replaces it.

Note: The strikethrough font is only visible when a font size of 14 points or higher is selected for the topology map.

Deprecated CITs appear in the CIT tree in Modeling Studio, however it is not recommended to use them in building new TQL queries and views. In place of a deprecated CIT, use the CIT indicated in the tooltip as its replacement. Deprecated CITs do not appear in out-of-the-box queries and views.

CIT attributes which are scheduled to be removed are deprecated attributes. They also appear in strikethrough font in the user interface.

The following image displays a TQL query containing a deprecated CIT:

<u> </u>	ontainme	nt	
IpAddre:	ss Compos	ition). Fill	÷

👶 System Type Manager

System Type Manager enables you to create a predefined list whose values define an attribute type. For more details on System Type Manager, see "System Type Manager Dialog Box" on page 516.

You can create the following attribute types:

- ➤ List. Enables you to create a predefined list of values, for example, Location.
- ► Enumeration. Enables you to create a predefined list of values, as well as assign each value a color. Enumerations are designed to be used as severity value lists by states. For details, see "State Manager" in the *RTSM Administration Guide*.

Severity lists are used for:

- ➤ Retrieving Impact Analysis results in IT Universe Manager. For details, see "IT Universe Manager" on page 227.
- Creating an Impact rule. For details, see "Impact Analysis Manager" on page 449.

You can use both List and Enumeration values for:

- ► Editing the attributes of a CIT. For details, see "Create a CI Type" on page 481.
- Defining an attribute condition for a TQL query node or relationship. For details, see "Query Node/Relationship Properties Dialog Box" on page 85.

Tasks

聄 Create a Cl Type

This task describes the process you follow to create a CIT using the Create CI Type wizard.

This task includes the following steps:

- ► "Prerequisites" on page 481
- ► "Define the CI Type" on page 481
- ➤ "Set the CI Type Attributes" on page 481
- ► "Assign Qualifiers to the CI Type" on page 482
- ➤ "Assign an Icon to the CI Type" on page 482
- ► "Customize the CI Type Menu" on page 482
- ➤ "Define the CI Type Default Label" on page 482
- ➤ "Define the Matching Rules" on page 482

1 Prerequisites

*

From the CI Type Manager, select **CI Types** from the list box in the CI Types pane. Then select **New** to start the Create CI Type Wizard.

2 Define the CI Type

Enter the name, description and base configuration item type for the new CI type. For details, see "Details Page" on page 497.

3 Set the CI Type Attributes

Edit the attributes of the new CI type and define key attributes for it. For details, see "Attributes Page" on page 498.

Note: List and Enumeration definitions are created in the System Type Manager. If required, you can create additional List and Enumeration definitions. For details, see "Create List and Enumeration Definitions" on page 485.

4 Assign Qualifiers to the CI Type

Assign qualifiers to the definition of the new CI type. For details, see "Qualifiers Page" on page 502.

5 Assign an Icon to the CI Type

Select an icon to assign to the new CI type. For details, see "Icon Page" on page 505.

6 Customize the CI Type Menu

Select the menu items and commands to appear in the shortcut menu for the new CI type. For details, see "Attached Menu Page" on page 506.

7 Define the CI Type Default Label

Define the attributes to appear in the CI type label. For details, see "Default Label Page" on page 510.

8 Define the Matching Rules

If necessary, define the matching rules for the new CI type. For details, see "Matching Rules Page" on page 512.

Note: This step is only relevant for customers running HP Universal CMDB Configuration Manager.

膧 Create a Relationship Type

This task describes the process you follow to create a relationship type using the Create Relationship wizard.

This task includes the following steps:

- ► "Prerequisites" on page 483
- ▶ "Define the Relationship" on page 483
- ➤ "Set the Relationship Attributes" on page 483
- ➤ "Assign Qualifiers to the Relationship" on page 484
- ➤ "Customize the Relationship Menu" on page 484
- ➤ "Define the Relationship Default Label" on page 484

1 Prerequisites

*

From the CI Type Manager, select **Relationships** from the list box in the CI Types pane. Then select **New** to start the Create Relationship Wizard.

2 Define the Relationship

Enter the name, description and base CI type for the new relationship. For details, see "Details Page" on page 497.

3 Set the Relationship Attributes

Edit the attributes of the new relationship and define key attributes for it. For details, see "Attributes Page" on page 498.

Note: List and Enumeration definitions are created in the System Type Manager. If required, you can create additional List and Enumeration definitions. For details, see "Create List and Enumeration Definitions" on page 485.

4 Assign Qualifiers to the Relationship

Assign qualifiers to the definition of the new relationship. For details, see "Qualifiers Page" on page 502.

5 Customize the Relationship Menu

Select the menu items and commands to appear in the shortcut menu for the new relationship. For details, see "Attached Menu Page" on page 506.

6 Define the Relationship Default Label

Define the attributes to appear in the relationship label. For details, see "Default Label Page" on page 510.

膧 Create a Calculated Relationship Type

This task describes the process you follow to create a calculated relationship type using the Create Calculated Relationship wizard.

This task includes the following steps:

- ► "Prerequisites" on page 484
- ➤ "Define the Calculated Relationship" on page 484
- ➤ "Assign Qualifiers to the Relationship" on page 485
- ➤ "Add Required Triplets" on page 485

1 Prerequisites

From the CI Type Manager, select **Calculated Relationships** from the list box in the CI Types pane. Then select **New** to start the Create Calculated Relationship Wizard.

2 Define the Calculated Relationship

Enter the name, description and base CI type for the new calculated relationship. For details, see "Details Page" on page 497.

*

3 Assign Qualifiers to the Relationship

Assign qualifiers to the definition of the new relationship. For details, see "Qualifiers Page" on page 502.

4 Add Required Triplets

Add the required triplets. For details, see "Triplets Page" on page 503.

膧 Create List and Enumeration Definitions

This section describes the tasks for creating List and Enumeration definitions.

This task includes the following steps:

- ► "Create a List Definition" on page 485
- ► "Create an Enumeration Definition" on page 485

1 Create a List Definition

You can create a **List** definition of predefined values. For example, a List definition called Location might contain:

- ► New York
- ► Boston
- ► Baltimore

For details, see "Create/Update List/Enumeration Definition Dialog Box" on page 513.

2 Create an Enumeration Definition

You can create an **Enumeration** definition, which enables you to assign a color for each value on the list. For details, see "Create/Update List/Enumeration Definition Dialog Box" on page 513. For an example of an Enumeration definition, see "Create an Enumeration Definition – Workflow" on page 486.

+

🅆 Create an Enumeration Definition – Workflow

The following steps describe how to create an Enumeration definition.

Note: To retrieve the required results, you must follow each step in this task.

To create an Enumeration definition:

- 1 Select Admin > RTSM Administration > Modeling > CI Type Manager.
- 2 From the Main Menu, select Cl Types > System Type Manager to open the System Type Manager dialog box.
- **3** Click the **Add** button to open the Create List Definition dialog box.

Note: Alternatively, you can select **Admin > RTSM Administration > Administration > State Manager** and then click the **New Enumeration** button to open the Create Enumeration Definition dialog box.

4 Select **Enumeration**.

- **5** In the **Name** box, enter the required name.
- **6** (Optional) In the **Display Name** box, enter the required display name.

This example describes how to create the following severity list:

Кеу	Value	Severity Represented
0	Green	Normal
1	Orange	Major
2	Red	Critical

- **7** Click the **Add** button to create a new row.
 - 8 In the Value box, enter Normal, in the Key box, enter 0, and in the Color section, select Green.
- **9** Click the **Add** button to create another row.
 - **10** In the Value box, enter Major, in the Key box, enter 1, and in the Color section, select Orange.
- **11** Click the **Add** button to create another row.
 - **12** In the Value box, enter Critical, in the Key box, enter 2, and in the Color section, select Red.

The following image shows the Enumeration Definition section after the changes:

Name:	Oper_States	
Display Name:		
🔾 List	۲	Enumeration
-Enumeration [Definition	
+		
Normal		Value: Critical
🗙 Major		Key: 2
Critical		Ney. 2
		Color
		🔘 🗹 Green
		🔵 🔁 Light Olive
		🔿 📙 Yellow
		🔿 🗄 Orange
		Red
		🔘 🗖 Gray

13 Click **OK** to save your changes.

Reference

💐 View Descriptions for CI Types and Relationships

You can view a complete list of available CI types in tree format in the left pane of CI Type Manager. You can search incrementally for a specific CI type as described in "CI Type Manager" on page 492. To see a description for a particular CI type, select it from the tree and hold the pointer over the icon which corresponds to it in the Topology Map. A tooltip containing a description of the CI type is displayed.

For relationships, select **Relationships** in the left pane and search incrementally by the first letter of the relationship. Select the relationship you want and hold the pointer over its icon in the Topology Map to display a tooltip containing a description of the relationship.

For detailed information on CI types and relationships, refer to the HP Software BTO Data Model Reference file, hp-software-core-dm-1.1-final.html, in the <BSM root directory>\AppServer\webapps\site.war\ amdocs\eng\pdfs folder.

💐 CI Type Manager User Interface

This section includes (in alphabetical order):

- ► Add/Edit Attribute Dialog Box on page 489
- ► Add/Remove Relationship Dialog Box on page 492
- ► CI Type Manager on page 492
- Create Configuration Item Type/Relationship/Calculated Relationship Wizard on page 496
- ► Create/Update List/Enumeration Definition Dialog Box on page 513
- ➤ System Type Manager Dialog Box on page 516

Add/Edit Attribute Dialog Box

This dialog box enables you to define a new attribute to add to a CIT or to edit an existing attribute of a CIT.

To access	In the CI Type Manager, select the Attributes tab, then click the Add + button, or select an attribute and click the Edit button or double-click the attribute.
Important information	In Edit mode, fields that cannot be changed are disabled.

Details Tab

User interface elements are described below:

UI Element (A-Z)	Description
Attribute Name	Enter a unique name for the new attribute. The name can contain all characters except the following: " \ / []: <> + = ; , ? *
	Note: The attribute name is not case sensitive.
Attribute Type	Select one of the following options:
	Primitive. Choose from one of the following field types: boolean, bytes, date, double, float, integer, integer_list, long, string, string_list, xml.
	➤ Enumeration/List. Contains a list of Enumerations and Lists defined in the System Type Manager. For details, see "System Type Manager" on page 479.
	This option enables you to define an attribute with a predefined value. For example, a location attribute might be defined by a location list containing the following values: Singapore, Paris, New York.
Default Value	Enter or select a default value for the attribute. The options for the Default Value field vary depending on the attribute type you selected.
	Note: If you select the integer_list or string_list Primitive attribute type, you can enter multiple values.

UI Element (A-Z)	Description
Description	Enter a description for the new attribute. Note: This field is optional.
Display Name	Enter a name for the new attribute to identify it in HP Business Service Management. Note: This field is optional.
Scope	Select the scope of the new attribute (the class model to which it belongs).
Value Size	Enter a value for the maximum physical size of the new attribute. (Enabled for bytes and string only).

Advanced Tab

User interface elements are described below:

UI Element (A-Z)	Description
Asset Data	Select to display the attribute value in the Asset Report.
Change Monitored	Select to define attributes whose values are being marked as Change Monitored in CI Type Manager. The changes in the values of such attributes are saved in the CMDB History database.
	Note:
	 When this qualifier is selected for a given attribute, the attribute appears as a visible column in the Element Instances dialog box. For details, see "Element Instances Dialog Box" on page 77. Change Monitored is not relevant for attributes of the type list of integers or list of strings.
Comparable	Select to enable this attribute to be used for comparing compound CIs.
Editable	Select to enable future editing of the attribute. Only attributes that are marked as Editable (or ones that have values) are displayed in the Properties tab in IT Universe Manager.

UI Element (A-Z)	Description
Enable Auto Truncate by DFM	If selected, when attributes of type STRING exceed the size limit, Discovery truncates the value. For details, see "Data Validation on the Data Flow Probe" in <i>RTSM Data Flow</i> <i>Management Guide</i> .
Index	Select to accelerate the attribute retrieval performance. This option is recommended for attributes that are used frequently in search conditions. For example, IP address is usually an index attribute of a node.
Lower Case	When this option is selected, the attribute value appears in lower case.
Password	When this option is selected, the attribute value appears as asterisks (a hidden value).
Required	Select to define this attribute as a required one, if its value is required for the creation of the CIT.
Static	Select to define this attribute as static.
Unique	When this option is selected, different instances of this CI type must have unique values.
Upper Case	When this option is selected, the attribute value appears in upper case.
Use Update Value Policy	Select this option to add the ALLOW_VOLATILITY qualifier. For details on this qualifier, see "The ALLOW_VOLATILITY Qualifier" on page 28.
Visible	Select to display this attribute in the Properties tab in IT Universe Manager.

💐 Add/Remove Relationship Dialog Box

This dialog box enables you to add or remove default or new relationships between CITs, which define their physical or logical connections.

To access	In the CI Type Manager, right-click a CIT or two CITs and select Add/Remove Relationship .
Important information	When adding a relationship between two CITs, select the two CITs to be linked by holding down CTRL and clicking the CIT names. Then right-click one of them and select Add/Remove Relationship .

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
<query node1="" to<br="">query node2></query>	Select the relationships to add in the direction of the first query node to the second.
<query node2="" to<br="">query node1></query>	Select the relationships to add in the direction of the second query node to the first.
Relationship Name	A list of the possible relationships.

💐 CI Type Manager

This page enables you to view the information in the CI Type model, which contains the definitions of all configuration item types (CITs) defined in the system and the relationships that define the connections between them. Each CIT has its own attributes, as well as the attributes inherited from its parent CIT.

To access	Select Admin > RTSM Administration > Modeling > CI Type
	Manager.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
*	Click the New button to open the Create Configuration Item Type Wizard which enables you to define a new CI type. For details, see "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496.
×	Click Delete to delete the selected CI type or relationship.
Ø	Click to refresh the data content of the hierarchical tree structure that may have been modified by other users.
	Click the Save button to save changes made to a CI type.
THE L	Enables you to import CITs from an external file.
E	Enables you to export a CIT as an XML file. Use this option to move CITs from one server to another.
₩	Enables you to export a CIT as a PDF.
<ci Type/Relationship Box></ci 	 Select one of the following options: ➤ Cl Types. Display the CI types in the CIT model. ➤ Relationships. Display the relationships in the CIT model. ➤ Calculated Relationships. Display the calculated relationships in the CIT model.

UI Element (A-Z)	Description
<editing pane=""></editing>	The following tabs are available:
	 Dependencies. Displays the CI Type model in a topology map, including the CITs and the relationships between them. The name of the selected CI type or relationship appears in the border at the top of the pane. When you point to a CIT, a tooltip displays the display name of the CIT and its description. Details. Enables you to edit the basic information about
	the CI type selected in the left pane. For details, see "Details Page" on page 497.
	 Attributes. Enables you to edit the attributes of the selected CIT. For details, see "Attributes Page" on page 498.
	 Qualifiers. Enables you to assign qualifiers to the selected CIT. For details, see "Qualifiers Page" on page 502.
	➤ Triplets. Enables you to create a calculated relationship. For details, see "Triplets Page" on page 503. This tab appears only for calculated relationships.
	➤ Icon. Enables you to assign an icon to the selected CIT. For details, see "Icon Page" on page 505. This tab does not appear for relationships.
	➤ Attached Menu. Enables you to customize the shortcut menu of a CI by adding menu items and commands (for example, ping, run a program, open a URL). The customized menu is displayed when you right-click a CI instance in IT Universe Manager. For details, see "Attached Menu Page" on page 506.
	➤ Default Label. Enables you to define attributes that appear in the CIT label. You can include more than one attribute by using the function buttons. For details, see "Default Label Page" on page 510.
	➤ Matching Rules. Enables you to define matching rules for use in HP Universal CMDB Configuration Manager. For details, consult the Configuration Manager documentation. This tab does not appear for relationships and only appears when UCMDB is running with Configuration Manager.

UI Element (A-Z)	Description
<main menu=""></main>	For details, see "Main Menu" on page 197.
<toolbar></toolbar>	For details, see "Toolbar Options" on page 201.
CI Types Pane	A hierarchical tree structure of the CI Type model containing the inheritance relationships among CITs, and displaying the number of instances of each CIT in the RTSM.
	All CITs included in the CI Type model are classified as either a CIT or a relationship.
	You can drill down and view the relationships and neighbors of the selected CIT in the topology map. You can search in the list of CITs or relationships using the Incremental Search by entering the first letter of the CIT or relationship repeatedly until you reach the required selection. You can also search for a CIT or relationship by entering its full name.

Shortcut Menu

CI Type Manager includes the following options available by right clicking a CI type in the CI Types pane or the Dependencies map:

UI Element (A-Z)	Description
Add/Remove Relationship	Opens the Add/Remove Relationship dialog box, which enables you to add or remove relationships from CITs. For details, see "Add/Remove Relationship Dialog Box" on page 492.
Delete Selected Item	Deletes the selected CI type. This option is only available for CI types that have no children and no instances.
Export To XML	Enables you to export a CIT as an XML file. Use this option to move CITs from one server to another.

UI Element (A-Z)	Description
New	Opens the Create Configuration Item Type Wizard which enables you to define a new CI type. For details, see "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496.
Show CIT Instances	Opens the Show All Instances dialog box, which displays all instances of the selected CIT. For details, see "Element Instances Dialog Box" on page 77.

A Create Configuration Item Type/Relationship/Calculated Relationship Wizard

This wizard enables you to define a new configuration item type or relationship.

To access	Click a CI type or relationship in the topology map or CI Types pane of the CI Type Manager and select New or click the New * button in the CI types pane.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains:
	Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

The Create Configuration Item Type wizard includes the following pages:

- ► "Details Page" on page 497
- ► "Attributes Page" on page 498
- ► "Qualifiers Page" on page 502
- ► "Triplets Page" on page 503
- ► "Icon Page" on page 505
- ► "Attached Menu Page" on page 506

- ► "Default Label Page" on page 510
- ► "Matching Rules Page" on page 512

💐 Details Page

This wizard page enables you to enter basic information about the new CI type you are defining.

Important information	For general information about the Create Configuration Item Type Wizard, see "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains:
	Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

User interface elements are described below:

UI Element (A-Z)	Description
Base CI Type	Select a base CIT for the CIT you are creating. The new CIT inherits the base CIT's attributes.
	Note: This field only appears in the Create CI Type Wizard. It is not relevant when editing an existing CIT in the Details tab of CI Type Manager.
Created By	The user who created the new CIT.
	Note: This field is optional.
Description	A description for the new CIT.
	Note: This field is optional.
Display Name	The name of the CIT as it appears in the HP Business Service Management interface.
	Note: This field is optional.

UI Element (A-Z)	Description
Identification	Displays the key attributes or reconciliation rule by which the CIT is identified.
	Note: This field only appears when editing an existing CIT in the Details tab of CI Type Manager. It is not relevant in the Create CI Type Wizard.
Name	The unique name of the new CIT. The name must be in English. The name can contain all characters except the following: " \ / []: <> + = ; , ? *
	Note: The name field is case sensitive, but you cannot use the same name with different cases for two different CITs.
Scope	Select the scope of the new CIT (the class model to which it belongs).

💐 Attributes Page

This wizard page enables you to edit the attributes of the CI type.

Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains:
	Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
Ŷ	To define an attribute as a key attribute, click in the Key column beside the attribute name. A key icon appears in the cell. A key attribute is an attribute that must be defined for CIs of that CI type.
	To remove the key attribute definition, click in the Key column again. The key icon disappears.
	For more information on key attributes, see "CI Type Attributes" on page 477.
Sec.	Denotes a static attribute. A static attribute takes the same value for all the CIs of that type. If it is changed, all the CIs of that type are affected and automatically display the new value. A static attribute cannot be defined as a key attribute.
	Note: You cannot define an attribute as static from within the CIT Manager. It is done by deploying the relevant package. Static attributes are for internal use only.
+	Click the Add button to define a new attribute. For details, see "Add/Edit Attribute Dialog Box" on page 489.
Ø	Select a row and click the Edit button to open the Edit Attribute dialog box. For details, see "Add/Edit Attribute Dialog Box" on page 489.
	Note: If you modify an attribute belonging to a CIT's parent, the text turns light blue. If you modify an attribute belonging to the CIT itself, the text remains dark blue.
×	Click the Delete button to delete a selected attribute. This option is only active for newly defined attributes.
Ø	Click the Reset button to reset the attribute settings after editing a pre-existing attribute.
	Click Select Columns to select the columns to appear using the Select Columns dialog box. For details, see "Select Columns Dialog Box" on page 570.

UI Element (A-Z)	Description
<attributes></attributes>	Displays all attributes associated with the new CIT. Attributes appearing in black are ones that the new CIT inherits from the base CIT. Attributes appearing in dark blue are ones that are private to this CIT and its descendants. Attributes appearing in light blue are inherited ones that have been modified for the new CIT.
Asset Data	Indicates whether the attribute value is displayed in the Asset Report. For details see "Asset Report" on page 419.
	Note: When this qualifier is selected for a given attribute, the attribute appears as a visible column in the Element Instances dialog box. For details, see "Element Instances Dialog Box" on page 77.
BDM Scope	Indicates whether the attribute is included in the BDM class model.
Change Monitored	Select to define attributes whose values are being marked as Change Monitored in CI Type Manager. The changes in the values of such attributes are saved in the CMDB History database.
	Note : When this qualifier is selected for a given attribute, the attribute appears as a visible column in the Element Instances dialog box. For details, see "Element Instances Dialog Box" on page 77.
Comparable	Indicates whether this attribute is to be used for comparing compound CIs. For details, see "Compare CIs Report" on page 432. The changes in the value of such an attribute are saved in the CMDB History database.
	Note: When this qualifier is selected for a given attribute, the attribute appears as a visible column in the Element Instances dialog box. For details, see "Element Instances Dialog Box" on page 77.
Default Value	The default value for the attribute. This value appears when the new CIT is defined and there is no runtime value for the attribute.
Description	A description of the attribute.

UI Element (A-Z)	Description
Display Name	The attribute name that appears in the HP Business Service Management interface.
Editable	Indicates whether the attribute can be edited.
	Only attributes that are marked as Editable (or ones that have values) are displayed in the Properties tab in IT Universe Manager.
Enable Auto Truncate by DFM	Indicates whether the auto-truncate feature for attributes of type STRING is enabled.
Index	Indicates whether the attribute has been defined as an index attribute, which enables you to accelerate the attribute retrieval performance.
	This option is recommended for attributes that are used frequently in search conditions. For example, IP address is usually an index attribute of a node.
Кеу	When the key icon \Im appears in this column, it indicates that the attribute is defined as a key attribute.
	When the static attribute icon \Re appears in this column, it indicates that the attribute cannot be defined as a key attribute.
Lower Case	Indicates whether to keep the attribute value in lower case.
Name	The actual name of the attribute (compare to Display Name). The name must be in English.
Required	Indicates whether this attribute is defined as a required one, whose value is required for the creation of the CIT.
Static	Indicates whether this attribute is defined as static.
Туре	The type of the attribute.
Unique	Indicates whether this attribute is defined as unique, for which different instances of this CI type must have unique values
Upper Case	Indicates whether to keep the attribute value in upper case.
Visible	Indicates whether this attribute is displayed in the Properties tab in IT Universe Manager.

Qualifiers Page

This wizard page enables you to assign qualifiers to a CI type definition.

Important information	Qualifiers enable you to define added attribute definitions to the CIT. In the Qualifiers list, select the required qualifiers using the Add buttons to move your selections to the Configuration Item Type Qualifiers list. You can make multiple selections by holding down the CTRL key.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains: Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
**	Click this button to move all qualifiers to the Configuration Item Type Qualifiers list.
\$	Select the qualifier and click this button to add the qualifier to the Configuration Item Type Qualifiers list. Select multiple qualifiers by holding down the CTRL key.
¢	To remove a qualifier from the CIT definition, select the qualifier from the Configuration Item Type Qualifiers list and click this button.
#	Click this button to remove all qualifiers from the Configuration Item Type Qualifiers list.
Insert	To define a new, custom qualifier, enter the qualifier name in the text box and click Insert . The qualifier appears in the Configuration Item Type Qualifiers list.

UI Element (A-Z)	Description
<configuration Item Type Qualifiers></configuration 	The list of qualifiers that define attributes of the new CIT. For example, you can use a qualifier to define a CIT as abstract, which means that you cannot create instances from it.
<qualifiers></qualifiers>	For a list of the available qualifier options, see "Qualifier Tab" on page 92.

💐 Triplets Page

This wizard page enables you to create a calculated relationship. Each row on the Triplets page represents one of the allowed steps in the path leading from the source CI to the target CI in the topology map.

Note: This step of the wizard is only relevant for calculated relationships.

Important information	 This page is displayed if you select Calculated Relationships in the drop-down box in the CI Types pane. For details about calculated relationships, see "Impact Modeling" on page 109. For general information about the Create Configuration Item Type Wizard, see "Create Configuration Item Type/Relationship/Calculated Relationship Wizard" on page 496.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains: Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page
See also	"Impact Modeling" on page 109

UI Element (A-Z)	Description
\$	Click to define the allowed steps in a path in the topology graph leading from the source CI to the target CI in the calculated relationship. Opens the Add Triplet dialog box. For details, see "Add Triplet Dialog Box" on page 73.
0	Select a row and click the Edit button to edit the triplet. Opens the Edit Triplet dialog box. For details, see "Add Triplet Dialog Box" on page 73.
×	Click the Delete button to delete a selected triplet.
Relationship	The required relationship connecting the two query nodes.
Relationship Direction	 The source and target of a relationship. ➤ ➡ The direction is from source to target. ➤ ➡ The direction is from target to source.
Source	The required source query node.
Target	The required target query node.

💐 Icon Page

This wizard page enables you to select an icon to assign to the new CI Type.

Note: This step of the wizard is not relevant for relationships.

Important information	Each CIT is displayed with a default icon. However, you can attach different icons to the same CIT when certain conditions apply. For example, you can associate different icons with the same CIT when one of its attribute values changes.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains: Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

UI Element (A-Z)	Description
+	Click to add a row. Note: Only active if Change the Configuration Item Type icon according to its attribute value is selected.
×	Click to remove a row. Note: Only active if Change the Configuration Item Type icon according to its attribute value is selected.
Attributes	Select an attribute to determine the icon assigned to the CIT.

UI Element (A-Z)	Description
Change the Configuration Item Type icon according to its attribute value	Enables you to assign an icon for each attribute value. For example, you could define two values for the City attribute: if City=London, one icon is displayed. If City=Beijing, another icon is displayed. Note: If you change the icon of a CIT that appears in an existing view, the CIT's icon is not updated in the view.
Configuration Item Type Main Icon	Select the group to which the CIT belongs.
lcon	Select an icon to associate with the value you entered in the Value column.
Value	Enter a value corresponding to the attribute you selected. You can add a new line for each value you enter.

💐 Attached Menu Page

This wizard page enables you to customize the shortcut menu of a CI by adding menu items and commands (for example, ping, run a program, open a URL). The customized menu is displayed when you right-click a CI instance in IT Universe Manager.

Important information	If a CIT does not have a method defined specifically for it, the CIT inherits all the menus from its parent CIT or the nearest ancestor that does have a method defined for it. If you create or modify a menu, the change occurs only in the specific CIT that is being edited.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains: Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

UI Element (A-Z)	Description
+	Select a menu item from the tree and click the button. A new entry appears under the selected item.
×	Click to remove a menu item.
Ŷ	Click to move a selected menu item up in the menu.
4	Click to move a selected menu item down in the menu.
<tree></tree>	Hierarchical tree containing the default menu items.
	Caution: It is not recommended to edit the definitions of the default menu items.
Command	To connect to a specific location on the World Wide Web, select URL, and enter the exact Internet address, for example, http://www.hp.com/go/software. (Available only if you select the URL command type option.)
	Note: If you use a variable in the Command field, use the format command name %1 and define the CIT attributes as described in Parameters. The parameter values replace %1 according to their order in the list. For example, %1 is replaced by the first parameter in the list, %2 is replaced by the second parameter in the list, and so on.
Description	Enter a description for the method. (This is for internal use only and does not appear in the menu.)
Existing Method	Select to choose a command from a list of defined methods inherited from the IT Universe CIT and all its ancestors.
lcon	Select the icon to appear next to the menu option in the shortcut menu. Note: This field is optional.
Menu Item Name	Enter a name for the new menu item as it should appear in the menu.

UI Element (A-Z)	Description
Method	Enables you to add a command to the menu.
	Note: To create a method and not override the existing method, it is recommended to create a new menu item and place the new method there.
Method Name	Enter a name for the command.
New Method	Select to add an action (for example, ping) to the menu item.
Parameters	To add attributes to the command or URL, click the Add Parameter button and select the attribute from the list.
	To delete an existing entry, select it and click the Remove Parameter button.
	Note: Parameters are not relevant when Inner Process is selected.
Require user confirmation	Select the check box for users to confirm access to a menu item before the item is displayed.
Separator	To place a separator between two menu items:
	Click OK to place a separator underneath the selected menu option.
Shortcut	Press any key combination to create a shortcut for the menu item, for example, CTRL+H.
	Note: This field is optional.

UI Element (A-Z)	Description
Sub-Menu	Select to create a sub-menu under the selected menu option.
	I History Note Add Note Sub-menu New Related CI Actions
Туре	 Choose a command type: URL. Opens a web page to the specified URL. Enter the URL of a Web page for the command to open in the URL box. Inner Process. Triggers an internal HP Business Service Management action. Select an action from the drop-down list of actions.
	 Execute. Triggers an executable action. Enter an executable command in the Executable box. Note: In the Executable box, enter only the name of the executable file (for example, notepad.exe). Do not enter a path to the executable file. A path cannot execute a program.

💐 Default Label Page

This wizard page enables you to define attributes that appear in the CI type label. You can include more than one attribute by using the function buttons. This is the final step of the Create Configuration Item Type Wizard.

Important information	You build a label by selecting attributes in the CI Type Attributes pane and adding them to the Format pane, using the operators in the Format pane to connect them.
	The label appears as the title under a CI of the new CI Type. The label definition can be customized to include different attribute values. For example, if the function label of the node CIT is composed of hostname and network, the displayed label is: server1 10.0.65.0. Labels can also be created using regular expressions.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains:
	Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

UI Element (A-Z)	Description
+	Click to add the selected attribute to the Format pane.
0	Adds parentheses to the formatted text (use in conjunction with the other functions).
&	Places an AND operator between two attributes in the formatted text. For example, network_netaddr&network_domain displays the network address and the domain of a query node.
0	Places an OR operator between two attributes in the formatted text.

UI Element (A-Z)	Description
5	Adds a regular expression (using regular expression syntax) to the label definition. The structure of the entry is (v1, v2, v3) , where v1 represents the selected attribute, v2 represents the regular expression itself (which divides the value into groups), and v3 represents the number of the selected group.
	For example, if the selected attribute is a name, consisting of a first name, a space, and a surname, the regular expression would be (name, $(S^*)(S^*), 3$), which indicates that the surname can be used for the name attribute in the default label.
	For examples of how to use regular expression syntax, see "Regular Expression Examples" on page 575.
5	Click to undo the last change in the Format pane.
4	Click to clear the Format pane.
CI Type Attributes	Displays the available options of attributes to be included in the CIT label.
CI Type Label Definition Format	Displays the attributes that you select to appear in the CIT label.
	For example, to label a node by its host name and operating system, choose the host_hostname and host_os attributes. The CIT label is host1 UNIX .
	You can define conditions using AND and OR combinations.
	Note: To delete an attribute from the Format pane, highlight it and press the DELETE key.

💐 Matching Rules Page

This wizard page enables you to define matching rules for comparable attributes for use in HP Universal CMDB Configuration Manager.

Important information	This page is only relevant when Configuration Manager is installed. For details on matching rules, refer to the Configuration Manager documentation.
	Note: You can activate the Matching Rules page manually by setting the Enable Configuration Manager Matching Rules setting to true in the Infrastructure Settings Manager.
Wizard map	The Create Configuration Item Type/Relationship/Calculated Relationship Wizard contains:
	Details Page > Attributes Page > Qualifiers Page > Triplets Page > Icon Page > Attached Menu Page > Default Label Page > Matching Rules Page

UI Element (A-Z)	Description
\$	Click to move the selected comparable attributes to the Matching Rules pane. Select multiple attributes by holding down the CTRL key.
¢	Click to remove an attribute from the Matching Rules pane.
*	Click to move all attributes to the Matching Rules pane.
5	Click this button to remove all attributes from the Matching Rules pane.
	Set the order of the matching rules using the up and down buttons.
Comparable Attributes	A list of all the attributes of the selected CI type with the comparable qualifier selected.
Matching Rules	The attributes selected to determine matching rules for Configuration Manager.

💐 Create/Update List/Enumeration Definition Dialog Box

This dialog box enables you to define a new List or Enumeration definition. The List or Enumeration definition you have created appears in the System Type Manager dialog box, where you can edit it if required (for details, see "System Type Manager Dialog Box" on page 516).

To access	Click the Add button in the System Type Manager dialog box.
Important information	You can access the Create/Update Enumeration Definition dialog box from the State Manager as well. For details, see "State Manager" in the <i>RTSM Administration Guide</i> .
Relevant tasks	"Create List and Enumeration Definitions" on page 485

UI Element (A-Z)	Description
Display Name	Enter the name you want to appear in the list of System Type Definitions. If you leave this field empty, the entry in the Name field is used.
Enumeration	Enables you to create a predefined list of values, as well as assign each value a color. For details, see "Enumeration Definition Area" on page 515.
List	Enables you to create a predefined list of values. For details, see "List Definition Area" on page 514.
Name	Enter a unique name for the definition.

List Definition Area

This area enables you to create a predefined list of values.

To access	Select List in the Create List/Enumeration Definition dialog box.
Important information	 For example, a Location attribute might be defined by a location list containing the following values: New York Boston Baltimore

The following elements are included (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
+	Add a List definition. Double-click inside the row and either select a date from the calendar that appears (if you chose the type Date) or type the required value.
×	Delete a List definition.
Туре	Choose one of following field types:
	► Date
	► Double
	► Integer
	► Long
	► String

Enumeration Definition Area

This area enables you to create a list from a predefined list of values (similar to **List**), with capabilities such as assigning a color for every value.

To access	Select Enumeration in the Create List/Enumeration Definition dialog box.
Important information	Enumerations are designed to be used as severity value lists by states. You can use Enumerations for lists that require key values.
See also	"Create an Enumeration Definition – Workflow" on page 486

UI Element (A-Z)	Description
4	Add an Enumeration definition.
×	Remove an Enumeration definition.
Color	Select a color that indicates the severity level. Note: Gray is only enabled when you create an Enumeration of the type Admin.

UI Element (A-Z)	Description
Кеу	Type a number to create an enumeration that describes a severity list for a category.
	Assign key values according to the following rules:
	 The list of key values must always begin with zero (0). (Zero represents the Normal state.) Otherwise, it does not appear in the State Manager (for details, see "State Manager" in the <i>RTSM Administration Guide</i>). The list must always be numbered consecutively. For an example of an Enumeration definition, see "Create an Enumeration Definition – Workflow" on page 486.
Value	Type a value, either a string or a number, for example, Red or my value. The value appears in the tooltip for the CI in IT Universe Manager.

💐 System Type Manager Dialog Box

This dialog box enables you to display the attribute types you defined in the Create List/Enumeration Definition dialog box.

To access	From the CI Type Manager, select CI Types > System Type Manager .
Relevant tasks	"Create List and Enumeration Definitions" on page 485
See also	"Create an Enumeration Definition – Workflow" on page 486

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
4	Create a predefined list whose values define an attribute type. You can create a definition for the following attribute types:
	► List definition.
	► Enumeration definition.
	For a description of these attribute types, see "Create/Update List/Enumeration Definition Dialog Box" on page 513.
0	Enables you to edit an existing definition. For details, see "Create/Update List/Enumeration Definition Dialog Box" on page 513.
×	Delete an existing definition. Select the system type definition you want to delete and click the Delete button.
<system type<br="">Definitions></system>	The list of Enumeration and List definitions created in the System Type Manager.

Chapter 12 • CI Type Manager

Enrichment Manager

This chapter includes:

Concepts

► Enrichment Manager – Overview on page 520

Tasks

- ► Define an Enrichment Rule Scenario on page 523
- Add Enrichment Query Nodes and Relationships to an Enrichment TQL Query on page 528

Reference

► Enrichment Manager User Interface on page 530

Concepts

🚴 Enrichment Manager – Overview


Enrichment rules can be used for several purposes:

- ► Adding new CIs and relationships to the RTSM.
- ➤ Deleting specific CI instances from the RTSM.
- ► Updating the attribute values of specific CI instances in the RTSM.

Enrichment query nodes and relationships differ from other query nodes and relationships in that they are conceptual deductions that represent real relationships and CIs that cannot be discovered automatically by the discovery process.

Enrichment query nodes and relationships are created as part of a TQL query, whose other TQL query nodes are regular ones, meaning TQL query nodes that already exist in the RTSM. For more information about TQL queries, see "Topology Query Language" on page 21.

The following example displays a regular query node of type **Node** linked to a **Websphere AS** Enrichment query node by an Enrichment **Composition** relationship.




By placing an Enrichment query node within a TQL query context, the query receives data from its attributes, and uses it to insert new information into the RTSM.

When you create Enrichment rules, the following results can occur:

➤ The RTSM is enlarged. Add Enrichment query nodes and relationships that are currently not included in the RTSM.

The following Enrichment rule example displays a regular **Windows** query node (that already exists in the RTSM) connected to a **Log File** Enrichment query node by an Enrichment **Composition** relationship.



This Enrichment rule states that for every **Windows** CI instance that is found in the RTSM, a new **Log File** CI instance is created, and linked to the **Windows** CI with a **Composition** relationship.

- ➤ Specific Cl instances are deleted from the RTSM. For an example, see "Define an Enrichment Rule – Scenario" on page 523.
- ► The values of CI attributes are updated. Use an Enrichment rule to update the attributes of a CI that already exists in the RTSM.

The following Enrichment rule example illustrates that a regular **Windows** query node (that already exists in the RTSM) has been updated with an Enrichment rule.



This Enrichment rule states that every **Windows** CI found in the RTSM is updated with the attribute value defined in the Enrichment rule.

Tasks

膧 Define an Enrichment Rule – Scenario

This task describes how to create the following Enrichment rule:

An **IP Address** CI is connected to two identical **Node** CIs: one **Node** CI is identified by its IP address and the other is identified by its lowest MAC address. For every such instance, delete the **Node** CI that is identified by its IP address from the RTSM.

Note: To reach the required result, you must implement each one of the following steps.

This task includes the following steps:

- ➤ "Create an Enrichment TQL Query" on page 524
- "Define the Query Node of Type Node that Is Identified by its Lowest MAC Address" on page 526
- "Define the Query Node of Type Node that is Identified by its IP Address" on page 526
- ▶ "Define the Enrichment Rule" on page 527

1 Create an Enrichment TQL Query

To create an Enrichment TQL query, you need to define an Enrichment rule and then add the regular TQL query nodes and relationships that define the query.

Note: You can add Enrichment query nodes and relationships only after at least one regular query node has been added to the query.


Select Admin > RTSM Administration > Modeling > Enrichment Manager. For details about how to create an Enrichment TQL query, see "New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard" on page 539. For details about how to add query nodes and relationships to a query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

Example of an Enrichment TQL Query:


A new Enrichment TQL query called doubleHosts1 (located under the **Network** folder) is created in Enrichment Manager.

Rule Name:	doubleHosts1
Rule Description:	
Pale Description.	Delete incomplete host
Rule is Active	

The **doubleHosts1** Enrichment rule is displayed in the Enrichment Rules pane.



In this Enrichment TQL query, an **IP Address** query node is linked to two query nodes of type **Node** by a **Containment** relationship. The TQL results must comply with the direction of the arrows.



Note: A TQL query is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103.

2 Define the Query Node of Type Node that Is Identified by its Lowest MAC Address

At the top of the Enrichment Manager page, select **Query** mode. In the editing pane, right-click the required query node of type **Node**, select **Query Node Properties** to open the Query Node Properties dialog box. Then define an attribute condition in the Attribute tab. For details on how to define an attribute condition, see "Attribute Tab" on page 87.

Example of an Attribute Condition Definition that Identifies the Node by its Lowest Mac Address:

In the Attribute tab, this attribute condition definition identifies the required Node by its lowest MAC address.

- ► Attribute name Node is Complete
- ► Operator Equal
- ► Value True

3 Define the Query Node of Type Node that is Identified by its IP Address

At the top of the Enrichment Manager page, select **Query** mode. In the editing pane, right-click the required query node of type **Node**, and select **Query Node Properties** to open the Query Node Properties dialog box. Then define two attribute conditions in the Attribute tab. For details on how to define an attribute condition, see "Attribute Tab" on page 87.

Example of an Attribute Condition that Enables a Node to Be Identified by its IP Address:

This attribute condition is the first attribute condition you need to define in the Attribute tab to enable the query node of type node to be identified by its IP Address.

Attribute name — Node is Complete

Operator — Equal

Value — False

This is the second attribute condition you need to define in the Attribute tab to enable the query node of type node to be identified by its IP address.

Attribute name — Node is Complete

Operator — Is null


Value — Value cannot be changed

4 Define the Enrichment Rule

Define the Enrichment rule that deletes all instances of the query node of type **Node** that are identified by their IP addresses. From the toolbar, select **Enrichment** mode. In the Enrichment Rules pane, select the **doubleHosts1** Enrichment rule. Then right-click the query node of type **Node** that is identified by its IP address and select **Delete Relationship/Query Node Item**.

Example of a Query Node of Type Node Containing a Removed Indicator:

The query node of type **Node** now has a removed indicator to denote that all node instances that have identical attribute and cardinality settings are removed from the RTSM. The Enrichment query now looks like this.




Add Enrichment Query Nodes and Relationships to an Enrichment TQL Query

This section describes how to add Enrichment query nodes and relationships to an Enrichment TQL query in Enrichment Manager.

To add Enrichment query nodes and relationships to a TQL query:

- 1 From the tree in the Enrichment Rules pane, select the Enrichment rule to which you want to add Enrichment query nodes and relationships or create a new one. For details, see "New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard" on page 539.
- **2** From the **Query/Enrichment** drop-down at the top of the page, select **Enrichment Mode**.



3 From the tree displayed in the CI Type Selector, click and drag the query nodes you want to function as an Enrichment query node on to the editing pane. These are the TQL query nodes that are included in the query. Added Enrichment query nodes are displayed by an added indicator.

Note: You can add more than one Enrichment query node to a rule.

4 Link the Enrichment query node to an existing TQL query node or query nodes, to provide the Enrichment query node with the needed context for its operation.

Following are the Enrichment rule validations:

- You must link the new Enrichment query node to at least one of the existing TQL query nodes in the rule.
- Enrichment query nodes can only be linked to one another with an Enrichment relationship.

+

- ➤ If the new Enrichment query node must be contained (according to its CIT definition) in another query node, you must use the Composition relationship to connect this Enrichment query node to an existing TQL query node.
- You cannot link an Enrichment query node to a TQL query node that is not visible.
- **5** To add a relationship between two query nodes:
 - Select the required query nodes by holding down CTRL and clicking the TQL query nodes, right-click and select Add Relationship.

or

 Click the Create Relationship icon and draw a line between the required query nodes.

Added Enrichment relationships are displayed by an added indicator.

The Add Relationship dialog box opens. For details, see "Add/Edit Relationship Dialog Box" on page 63.

6 Click **OK**. The selected query nodes are linked by the relationship you have selected.

Î⊾ +

Reference

💐 Enrichment Manager User Interface

This section includes (in alphabetical order):

- ► Enrichment Manager Page on page 530
- ➤ New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard on page 539
- ➤ Query Node/Relationship Definition Dialog Box on page 544
- ➤ Query Node Definition Advanced Attribute Dialog Box on page 546

🂐 Enrichment Manager Page

This page enables you to define Enrichment rules. These rules, which are based on a specific TQL query, can be used for several purposes, including:

- ► Adding new CIs and relationships to the RTSM.
- ➤ Deleting specific CI instances from the RTSM.
- ➤ Updating the attribute values of specific CI instances in the RTSM.

To access	Select Admin > RTSM Administration > Modeling > Enrichment Manager.
Important information	Enrichment Manager has two modes in which you can work. Always check the Enrichment/Query mode list in the toolbar to verify the currently selected mode.
Relevant tasks	"Define an Enrichment Rule – Scenario" on page 523

Enrichment Rules Pane

This area displays a hierarchical tree structure of predefined folders and Enrichment rules. Each Enrichment rule is associated with a TQL query.

Important information	You can create your own Enrichment rule, or work with the out-of-the-box (factory) Enrichment rules provided with your HP Business Service Management installation.
	The default folders are provided for the out-of-the-box queries. You can modify these folders, or add additional folders according to your organization's requirements.
	You can drag and drop Enrichment rules or folders to move them from one folder to another.

UI Element (A-Z)	Description
-	Creates a new folder.
*	Creates an Enrichment rule. Opens the New Enrichment Rule/Properties wizard.
×	Deletes the selected folder or Enrichment rule.
Ø	Refreshes the data content of the hierarchical tree structure that may have been modified by other users.
	(Enabled only when an Enrichment rule is created or when changes are made to an existing one.) Saves the Enrichment rule to the RTSM.
£	Opens the New Enrichment Rule/Properties wizard. Enables you to change the description and the activation state of the Enrichment rule.
Q	Generates a preview of the results of the selected Enrichment rule.
	Represents a folder.

UI Element (A-Z)	Description
.0	Represents an Enrichment rule.
<enrichment rule<br="">tree></enrichment>	Displays the existing Enrichment rules in tree format. Note: Only Enrichment rules appear in the tree. TQL queries of type Enrichment (created in the Modeling Studio) do not appear in the tree.

The following elements are available by right-clicking a folder or Enrichment rule:

UI Element (A-Z)	Description
Delete	Deletes the selected folder or Enrichment rule.
Export To XML	Displays a standard Save As dialog box, enabling you to save the Enrichment rule as an XML script. This option can be used to move an Enrichment rule from one workstation to another, provided the related TQL query is also relocated.
Import From XML	Imports XML files that contain saved Enrichment queries to the Enrichment Manager.
New	Creates an Enrichment rule. Opens the New Enrichment Rule wizard.
New Folder	Creates a new folder.
Preview	Generates a preview of the results of the selected Enrichment rule.
Properties	Opens the New Enrichment Rule/Properties wizard. Enables you to change the description and the activation state of the rule.
Rename Folder	Renames the folder.

UI Element (A-Z)	Description
Save	(Enabled only when a new Enrichment query is created or when changes are made to an existing one.) Saves the Enrichment rule to the RTSM.
Save As	Displays the Save As Enrichment Rule wizard, enabling you to define a new name and description for a query. This option can be used for creating a new Enrichment rule based on an existing one.

Editing Pane

This area enables you to create and define Enrichment query nodes and relationships.

Important information	 When you select a folder in the Enrichment Rules pane, the editing pane is empty. When you select an Enrichment rule in the Enrichment Rules pane, the editing pane displays the selected rule, which consists of TQL query nodes that are defined in the TQL query and the relationships between them, and the Enrichment query nodes and relationships that are created and added to the rule. The Enrichment Manager has two modes in which you can work: Enrichment mode and Query mode. The mode in which you are working determines the options that appear in the shortcut menu. For details, see the editing pane description below.
	You can calculate the number of instances that were created as a result of an Enrichment rule and remove the instances created from an Enrichment rule from the RTSM. For details, see "Additions Count" on page 201 and "Remove Enrichment Results" on page 207.
Relevant tasks	"Define an Enrichment Rule – Scenario" on page 523
See also	For details on how to create a TQL query, see "Add Query Nodes and Relationships to a TQL Query" on page 32.

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Element (A-Z)	Description
+	Indicates an added Enrichment query node or relationship.
Ξ	Indicates a query node or relationship that has been deleted from the RTSM.
κ	Indicates an updated query node or relationship.
Enrichment Mode 💌 Query Mode Enrichment Mode	The Enrichment Manager has two modes in which you can work: Enrichment mode and Query mode.
Query and Enrichment	Working in:
Query and Enrichment mode	Query mode enables you to define regular (non-Enrichment) relationships and query nodes and add them to the TQL query you defined.
	► Enrichment mode enables you to define Enrichment relationships and query nodes and add them to the TQL query you defined.
<main menu=""></main>	For details, see "Main Menu" on page 197.
<query node=""></query>	A component from which TQL queries are built.
<relationship></relationship>	The entity that defines the relationship between two query nodes.
<shortcut menu=""> options</shortcut>	For details, see "Shortcut Menu Options" on page 40.

UI Element (A-Z)	Description
<toolbar></toolbar>	For details, see "Toolbar Options" on page 201.
<tooltips></tooltips>	Hold the cursor over a query node or relationship to view its tooltip.
	The tooltips contain the following information:
	► Element name. The name of the query node.
	 Cl Type. The CIT of the query node as defined in the CI Type Manager. For details, see "CI Type Manager" on page 475.
	 Definitions of the selected query nodes and relationships. The attribute conditions, as described in "Query Node/Relationship Properties Dialog Box" on page 85.

CI Type Selector

This area displays a hierarchical tree structure of the CI Types found in the ODB.

Important information	The CI Type Selector is part of Enrichment Manager, Impact Analysis Manager, and Trigger TQL Editor.
	To create or modify a TQL query, click and drag query nodes to the Editing pane and define the relationship between them. Your changes are saved to the ODB. For details, see "Add Query Nodes and Relationships to a TQL Query" on page 32. Note: The number of instances of each CIT in the ODB is displayed to the right of each CIT.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Create a Pattern View" on page 359

User interface elements are described below (unlabeled elements are shown in angle brackets):

UI Elements (A-Z)	Description
<	Click Add CI Type to Map to move the selected CI type to the Editing pane.
Ø	Click Refresh to refresh the CI type tree.
Q	Click Search to search for the CI type entered.
8	Click Expand All to expand all subtrees within the CI type tree.
1	Click Collapse All to collapse the subtrees within the CI type tree.
<search window=""></search>	Enter the name or part of a name of a CI type for which to search.

Shortcut Menu Options

The CI Type Selector includes the following elements (listed alphabetically) available by right-clicking a CI Type:

Menu Item	Description
Add CI Type to Map	Select to add the selected CI type to the Editing pane.
Go to Cl Type Definition	Takes you directly to the selected CI type in CIT Manager.
Show CIT Instances	Opens the CIT Instances window, which displays all instances of the selected CIT. For details, see "Element Instances Dialog Box" on page 77.

Advanced Pane

This area displays the properties, conditions, and cardinality for the selected query node and relationship.

Important information	The Advanced pane appears in the lower part of the window in the following managers and user interfaces: Modeling Studio, Impact Analysis Manager, Enrichment Manager, the Input Query Editor and Trigger Query Editor in DFM. A small green indicator ** appears next to the tabs that contain data.
Relevant tasks	 "Define an Impact Rule – Workflow" on page 452 "Define an Enrichment Rule – Scenario" on page 523 "Define a TQL Query" on page 30 "Create a Pattern View" on page 359 "Create a Template" on page 360 "Create a Perspective" on page 362

UI Elements (A-Z)	Description
	If the window is not wide enough to display all the tabs, use the left and right arrows to move to the required tab.
T	Click Show List to display a list of the available tabs for the current module. You can select a tab from the list.
Attributes	Displays the attribute conditions defined for the query node or the relationship. For details, see "Attribute Tab" on page 87.
Cardinality	Cardinality defines how many query nodes you expect to have at the other end of a relationship. For example, in a relationship between a node and an IP Address, if the cardinality is 1:3, the TQL query retrieves only those nodes that are connected to between one and three IP Addresses. For details, see "Cardinality Tab" on page 89.

UI Elements (A-Z)	Description
Data Sources	Displays the data sources set for the selected query node.
	Note: This tab appears only in the Modeling Studio.
Details	Displays the following information:
	 Cl Type. The CIT of the selected query node/relationship. Visible. A green check indicates that the selected query node/relationship is visible in the topology map. A red mark indicates that it is not visible.
	➤ Include subtypes. A green check indicates that both the selected CI and its children are displayed in the topology map. A red mark indicates that only the selected CI appears.
Edit	Click Edit to open the relevant dialog box for the selected tab.
Enrichment Rules	Displays the Enrichment rule defined for the selected query node or relationship. If the Enrichment rule is used to update the attributes of a CI, click Edit to open the Query Node/Relationship Definition dialog box and edit the rule if required. For details, see "Query Node/Relationship Definition Dialog Box" on page 544.
	Note: This tab appears only in Enrichment Manager.
Impacted Query Nodes	Indicates which query node is affected by the changes that occur in the selected trigger query node. If required, you can click Edit to open and modify the Affected Query Nodes dialog box. For details, see "Impacted Query Nodes Dialog Box" on page 466.
	Note: This tab appears only in Impact Analysis Manager.
Qualifiers	Displays the qualifier conditions defined for the query node or the relationship. For details, see "Qualifier Tab" on page 92.
Selected Identities	Displays the element instances that are used to define what should be included in the TQL query results. For details, see "Identity Tab" on page 95.

New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard

To access	 To create a new Enrichment rule, right-click anywhere in the Enrichment Rules pane and click New or click the New * button. To modify an existing Enrichment rule, right-click an Enrichment rule in the Enrichment Rules pane and select Properties.
	 To create a new Enrichment rule based on an existing query, right-click an Enrichment rule in the Enrichment Rules pane and select Save As.
Important information	 When creating a new Enrichment rule, bear in mind that the application does not allow you to make any changes in the TQL query that are necessary for the rule. These changes include the following: Deleting, from the Enrichment TQL query, the query nodes or relationships connected to the Enrichment query node, causing a query node to become unattached to any relationship. You cannot change the cardinality definition to 0 (not required) of a query node or relationship that is used in an Enrichment rule. For details on relationship cardinality, see "Query Node/Relationship Properties Dialog Box" on page 85. An Enrichment TQL query that serves as the basis for Enrichment rules, is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103. If the TQL query is not valid, you cannot save it.
Relevant tasks	► "Define an Enrichment Rule – Scenario" on page 523
Wizard map	The New Enrichment Rule /Enrichment Rule Properties/Save As Enrichment Rule wizard contains: Rule General Attributes Page > Rule Base Query Page
See also	"Topology Query Language" on page 21

This wizard enables you to create or modify an Enrichment rule.

💐 Rule General Attributes Page

This wizard page enables you to enter a unique name and description for the Enrichment rule.

Important information	 An Enrichment TQL query that serves as the basis for Enrichment rules is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103. If the TQL query is not valid, you cannot save it. For important information on the effects of making changes to the TQL query after creating it, see "New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard" on page 539. By default, this wizard is set to display a Welcome page. You can choose not to display this page by changing the user preferences. For details, see "User Preferences Dialog Box" on page 102.
Wizard map	The New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard contains: Rule General Attributes Page > Rule Base Query Page
See also	"Topology Query Language" on page 21

UI Element (A-Z)	Description
Rule Description	(Optional) Enter a description of the rule.
Rule is Active	(Optional) Select this option to activate the rule in the system as soon as it is saved.
	Default: Not selected.
	Note:
	 If an active Enrichment rule is deactivated (by clearing the Rule is Active check box), all changes that occur in the RTSM relating to the rule are deleted from the system. When you deactivate an Enrichment rule, a red X appears next to the Enrichment rule in the Enrichment Rules pane. To reactivate the rule, right-click the rule in the Enrichment Rules pane and select Properties. In the General Attributes page, select Rule is Active.
Rule Name	Enter a unique name for the Enrichment rule.
	The rule name cannot contain any of the following characters: \/:" < > % ?
	Note: If the rule name is either empty, contains a name used by another Enrichment rule, or uses invalid characters, the Next and Finish buttons are disabled.

💐 Rule Base Query Page

This wizard page enables you to define the properties of the TQL query on which the Enrichment rule is based.

Important information	 An Enrichment TQL query that serves as the basis for Enrichment rules, is subject to certain validation restrictions. For details, see "Troubleshooting and Limitations" on page 103. If the TQL query is not valid, you cannot save it. For important information on the effects of making
	 For important information on the creets of making changes to the TQL query after creating it, see "New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard" on page 539. By default, this wizard is set to display a Completion page after clicking Next in this page. You can choose not to display the Completion page by changing the user preferences. For details, see "User Preferences Dialog Box" on page 102.
Wizard map	The New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule Wizard contains: Rule General Attributes Page > Rule Base Query Page
See also	"Topology Query Language" on page 21

UI Element (A-Z)	Description
Base the Enrichment rule on a new query	Select this check box if you want to base the Enrichment rule on a new TQL query. The TQL results are based on the attributes defined for the new TQL query.
Base the Enrichment rule on an existing query	Select this check box if you want to base the Enrichment rule on an existing TQL query. Select the required Enrichment TQL query from the drop-down list.
Base Query Description	(Optional) Enter a description of the TQL query.

UI Element (A-Z)	Description
Base Query Name	Enter a unique name for the Enrichment TQL query. If you selected the Base the Enrichment rule on an existing TQL option, select the Enrichment TQL query on
Base Query Priority	which you want to base the rule. Select a priority level for the new TQL query (Low, Medium, High, or Express). This setting determines how often the query is rerun automatically by the system to include updated information from the RTSM.
Save a new query based on the current definition	Select to save a new TQL query based on your Enrichment rule definition. Note: This field only appears in the Save As Enrichment Rule wizard.

Query Node/Relationship Definition Dialog Box

This dialog box displays the attributes of the selected query node/relationship. The key attributes and the required attributes of the selected query node appear in bold.

To access	Right-click a query node or relationship when in Enrichment mode (select Enrichment from the Query/Enrichment drop-down at the top of the Enrichment Manager page) and select Update Relationship/Query Node .
Important information	Use an Enrichment rule to update the value of CI attributes in the RTSM, or to add data to attributes that currently do not have values. You can use this option, for example, for simultaneously adding a note to all CI instances.
	You must fill in the value of the key attributes and the required attributes of the Enrichment query node. The method you use to define these values determines the number of instances created.
	If you enter a dynamic value, you can create numerous instances. For example, entering the dynamic value of a host_key for the CIT Node or an IP address attribute for the CIT IpAddress .
Relevant tasks	"Define an Enrichment Rule – Scenario" on page 523

Attributes Area

User interface elements are described below:

UI Element (A-Z)	Description
Name	The attribute name.
Туре	The field type of the selected attribute.
Value	The value as defined in one of the following:
	➤ The Value box in the Set Attributes area.
	 The combination of the values in the By Attribute boxes in the Set Attributes area.
	The Value column if you selected Simple in the Type column in the Query Node Definition - Advanced Attribute dialog box.
	The combination of the values in the Value column and the column to the right of the Value column if you selected By Attribute in the Type column in the Query Node Definition - Advanced Attribute dialog box.

Set Attributes Area

UI Element (A-Z)	Description
	(Appears only if you selected an attribute of the field type string .) Opens the Query Node Definition - Advanced Attribute dialog box.
	Define query node and relationship attributes of the type string using simple or complex expressions. You can also create complex expressions using regular expression format.
Advanced	(Appears only if you selected an attribute of the field type string .) Displays the attribute value you defined in the Query Node Definition - Advanced Attribute dialog box.

UI Element (A-Z)	Description
By Attribute	Define an attribute using attributes from other query nodes in the TQL query.
	 In the box to the left, select the required query node. In the box to the right, select the query node's required attribute. The attribute definition appears in the Value column in
	the Attributes area.
RegExp Group	(Appears only when you select an attribute of the field type string .) Enter the group number only if you are adding a regular expression using regular expression syntax. This is the part of the regular expression pattern to focus on when creating the attribute. A set of parentheses () constitutes a group.
Regular Expression	(Appears only when you select an attribute of the field type string .) Add a regular expression using regular expression syntax. Enter the regular expression pattern.
Value (in the Set Attributes area)	Define a constant value. Enter the required value in the Value box or select a value from the Value list.
	Note : The value definition appears in the Value column in the Attributes area.

💐 Query Node Definition – Advanced Attribute Dialog Box

This dialog box enables you to define query node and relationship attributes of the type **String** using simple or complex expressions. You can also create complex expressions using regular expression format.

To access	Select an attribute of the type string in the Query Node Definition dialog box. Select Advanced and then click the Advanced button.
Relevant tasks	"Define an Enrichment Rule – Scenario" on page 523

UI Element (A-Z) Description Define an attribute value using simple or complex + expressions. Creates a new entry in the **Type** column. Click the new entry and select either **Simple** or **By** Attribute. For details, see the description for the **Type** column below. Delete an attribute value. × Move a selected row up. Move a selected row down. \downarrow Advanced Value (This list is only available if you select **By Attribute** in the **Type** column.) Click the entry inside the box and select the required attribute. Concatenate Use all the attribute values listed in this dialog box. RegExp Group (This list is available only if you select **By Attribute** in the Type column.) Click inside the **RegExp Group** column, click the **button**, and enter the group number in the Value for RegExp Group dialog box that opens. This is the part of the regular expression pattern to focus on when creating the attribute. A set of parentheses () constitutes a group. **Regular Expression** (This list is only available if you select **By Attribute** in the Type column.) Click inside the Regular Expression column, click the **button**, and enter the regular expression pattern in the Value for Regular Expression dialog box that opens.

UI Element (A-Z)	Description
Туре	Click the entry inside the Type column and select one of the following options:
	 Simple. Define a constant value using a simple expression.
	► By Attribute . Define an attribute using attributes from other query nodes in the TQL.
	Default is: Simple
Use first attribute with value	Use the first attribute value listed in this dialog box that is not empty.
Value	 If you select Simple in the Type column, click inside the Value column, click the button, and enter the required value in the Value for Simple dialog box. If you select By Attribute in the Type column, click inside the Value column and select the required value from the list.

Part III

RTSM Data Model

RTSM Data Model Introduction

This chapter includes:

Concepts

► BTO Data Model (BDM) Overview on page 552

Reference

- ► Data Model Documents on page 553
- ► Upgrade Documents on page 554

Concepts

🚴 BTO Data Model (BDM) Overview

The BTO Data Model (BDM) enables you to manage the business functions, services, processes, and activities of your IT Universe model.

The BDM documents are located in the following folder:

\\<Business Service Management root directory>\AppServer\
webapps\site.war\amdocs\eng\pdfs

Reference

💐 Data Model Documents

BDM – Conceptual Data Model

The conceptual model presents a high level picture of the BTO Data Model (BDM) organized in structured layers. This document is a map of the concepts being modeled, as well as the scope of the model. This conceptual data model provides a starting point for understanding the semantics of the domain modeled.

Note: As this is an abstract representation of the model, the document does not include every entity or relationship.

BDM – Data Model UMLs

This document represents the data model in a visually appealing set of UML diagrams. Rather than a single, large, complex UML diagram of the entire model, small diagrams with specific points of view are presented. The purpose of the UML diagrams is to provide a pictorial representation of the model entities and their relationships to each other.

Note: To make the UML diagrams easier to understand, some relationships and entities may have been excluded.

BDM – Data Model HTML

This document includes all the BDM class information in HTML format.

BDM – Business Model and Best Practices

This document covers the business part of the RTSM data model, as well as some best practices and guidelines on how to model your business.

CMS Data Model 9.03 Documentation

This document covers all BDM classes and a subset of the CMS classes. It includes the following information:

- class descriptions
- ► attribute information
- ► object scoping (BDM/CMS)
- ► qualifier information
- ► hierarchy information

Note: This document can be automatically generated from the RTSM user interface.

💐 Upgrade Documents

RTSM Class Mapping Summary

This mapping document presents a high level view of the class mappings between versions 8.0x and 9.03, including the hierarchy changes.

RTSM Class Model Comparison

This document covers the differences between the 8.0x class model and the 9.03 data model in greater detail. The document includes the following information:

- class and attribute mapping
- ► new classes and attributes

- ► qualifier changes
- ► deprecation information
- ► removed classes
- ► key attribute changes
- ► hierarchy changes

Chapter 14 • RTSM Data Model Introduction

15

Exporting the RTSM Data Model to a UML Tool

This chapter includes:

Concepts

► Export to UML Tool – Overview on page 558

Tasks

- ► Export the Class Model on page 559
- ➤ Convert XML of Selected Part of Class Model on page 560

Reference

- ► Export Class Model to UML Wizard on page 562
- ► Tool Plug-in Input on page 565

Note: Currently, Altova UModel versions 2008 and 2009 are supported.

Concepts

🚴 Export to UML Tool – Overview

The Export to UML tool enables you to export selected sections of the RTSM class model to a format compatible with UML tools, and to view the model as a UML diagram.

The input for the tool is the RTSM class model XML file retrieved by the JMX service UCMDB:service=Class Model Services/ exportClassModelToXml().

Note: To access the JMX console, enter the following address in your browser: **http:**//<**server_name>:21212/jmx-console**, where <**server_name>** is the name of the machine on which HP Business Service Management is installed.

Tasks

膧 Export the Class Model

This task describes how to use the Export Class Model to UML tool wizard.

This task includes the following steps:

- ► "Prerequisites" on page 559
- ► "Run the UML Tool" on page 559
- ➤ "View the Exported File in Altova" on page 559

1 Prerequisites

Set up the tool by extracting the following zip file to any location:

<HP BSM root directory>:\odb\tools\ExportClassModel.zip

2 Run the UML Tool

You use the Export Class Model to UML wizard to choose the CIT and its attributes to be exported to the UML tool.

For details on working with the Export to UML wizard, see "Export Class Model to UML Wizard" on page 562.

3 View the Exported File in Altova

- **a** In Altova, select **File > Import From XMI File**.
- **b** Select the XMI file. The class model entry appears in the Model Tree pane.
- **c** Right-click the entry and select **Show in new diagram > Content**. Click **OK**.

P Convert XML of Selected Part of Class Model

This task describes how to use the custom plug-in to convert the XML of a selected part of the class model to the UML tool format.

The plug-in can be either a Java class or an XSLT text file. If you use a Java class, it must implement the **ITransformToUML(ExportToUML.jar)** interface; the **transformToUML()** method receives an XML string as a parameter and returns a byte array that is written to the output file.

For details on the custom plug-in input, see "Tool Plug-in Input" on page 565.

This task includes the following steps:

- ► "Activate the Plug-in Using a Java Class" on page 560
- ➤ "Activate the Plug-in Using an XSLT Text File" on page 561

Activate the Plug-in Using a Java Class

Add the display name and fully-qualified class name to the **config.xml** file in the ExportToUML directory, as follows:

<ConverterToUML> <Name><display name></Name> <Class><fully qualified class name></Class> </ConverterToUML>

Continue with the procedure for exporting the class model. For details, see "Export the Class Model" on page 559.

Activate the Plug-in Using an XSLT Text File

In this case, XSLT from the specified file is applied to the class model XML and is written to the output file.

Add the display name and full path of the XSLT file to the **config.xml** file in the ExportToUML directory, as follows:

```
<ConverterToUML>
<Name><display name></Name>
<XsltFile><Full_path_of_the_XSLT_file></XsltFile>
</ConverterToUML>
```

Continue with the procedure for exporting the class model. For details, see "Export the Class Model" on page 559.

Reference

💐 Export Class Model to UML Wizard

This wizard enables you to choose the CIT and its attributes to be exported to the UML tool.

To access	Browse to the location where you extracted the tool. Right-click ExportClassModel.jar in the ExportClassModel directory. Select Open With > Java 2 Platform SE binary .
Important information	By default the tool opens the ClassModel.xml file in the ExportClassModel directory. You open other files through the File > Open Class Model File menu.
Relevant tasks	"Export the Class Model" on page 559
Wizard map	The Export Class Model to UML wizard contains: Export Class Model to UML Wizard > Select Valid Links > Export Selected Items
See also	"Tool Plug-in Input" on page 565

UI Element (A-Z)	Description
File	Displays a list of XML files. Open the file that contains the class model.

UI Element (A-Z)	Description	
Select Attributes Pane	 Select the attributes to be displayed in the UML tool. The attributes of the selected CIT are displayed in this pane. The attributes are colored as follows: Attributes inherited from the parent CIT are black. Attributes specific to this CIT are dark blue. 	
Select CI Types Pane	The CITs displayed here are retrieved from the ClassModel.xml file. Select the CIT and its sub nodes to be exported to the UML tool. Use the buttons to select or clear all subindex.	

💐 Select Valid Links

This wizard page enables you to select links that can be used between two CITs.

Important information	General information about the wizard is available in "Export Class Model to UML Wizard" on page 562.	
Wizard map	The Export Class Model to UML wizard contains:	
	Export Class Model to UML Wizard > Select Valid Link > Export Selected Items	

UI Element (A-Z)	Description	
٩	Click to remove the filter from the list of CITs.	
Filter by	Enables you to filter the list of valid links. You can filter the list of CITs and you can sort the list by CIT or relationship.	

💐 Export Selected Items

This wizard page enables you to export the selected CITs and their attributes to the UML tool.

Important information	General information about the wizard is available in "Export Class Model to UML Wizard" on page 562.	
Wizard map	The Export Class Model to UML wizard contains:	
	Export Class Model to UML Wizard > Select Valid Links > Export Selected Items	

UI Element (A-Z)	Description	
Export	Click to browse to the UML file, in XMI format, to which you want to add the UCMDB CITs and their attributes. If there are no valid links for a pair of CITs, a no valid links message is displayed in the Select Valid Links page.	

💐 Tool Plug-in Input

The input for the plug-in is an XML string (selected classes/attributes/valid links) in the following form:

```
<?xml version="1.0" encoding="ISO-8859-1"?>
   <Class-Model>
   <Class class-name="hostresource" display-name="Host Resource"
visibility="public">
      <Attribute name="isvirtual" display-name="Is Virtual" visibility="public"/>
    <Attribute name="city" display-name="City" visibility="public"/>
   </Class>
   <Class class-name="host_node" display-name="Computer" visibility="public">
     <Derived-From class-name="host"/>
   </Class>
   <Class class-name="vax" display-name="VAX" visibility="public">
     <Attribute name="root actualdeletionperiod" display-name="Actual Deletion
Period" visibility="public"/>
     <Attribute name="data allow auto discovery" display-name="Allow CI Update"
visibility="public"/>
    <Derived-From class-name="host node"/>
   </Class>
   <Class class-name="host" display-name="Host" visibility="public">
     <Attribute name="host iscomplete" display-name="Host Is Complete"
visibility="public"/>
     <Attribute name="host isroute" display-name="Host Is Route" visibility="public"/>
     <Attribute name="host hostname" display-name="Host Name" visibility="public"/>
     <Attribute name="host os" display-name="Host Operating System"
visibility="public"/>
   </Class>
   <Class class-name="unix" display-name="Unix" visibility="public">
     <Derived-From class-name="host node"/>
   </Class>
   <Valid-Link ID="host member host" display-name="Member" visibility="public">
     <End1 class-name="host"/>
    <End2 class-name="host"/>
   </Valid-Link>
   <Valid-Link ID="host container f hostresource" display-name="Container link"
visibility="public">
    <End1 class-name="host"/>
     <End2 class-name="hostresource"/>
   </Valid-Link>
   </Class-Model>
```

Chapter 15 • Exporting the RTSM Data Model to a UML Tool

Part IV

Reference Information

16

Working with Tables

This chapter includes:

Reference

► Columns User Interface on page 570

Reference

💐 Columns User Interface

This section includes (in alphabetical order):

- ► Select Columns Dialog Box on page 570
- ► Sort Column Content Dialog Box on page 572

💐 Select Columns Dialog Box

This dialog box enables you to choose the information you are interested in displaying. You can hide a column or display a hidden column.

Description	Click the Select Columns we button. This button appears above every table in a report.	
Important information	The order of the columns in the list in the Visible Columns pane determines the order of the columns displayed in the table. To change the order of table columns, move them to the required position using the up and down arrow buttons or by dragging a column to a new location.	

The following elements are included:

UI Element (A-Z)	Description	
⇒	Displays a column. Moves the selected column from the Available Columns pane to the Visible Columns pane.	
¢	Hides a selected column. Moves the selected column from the Visible Columns pane to the Available Columns pane.	
	Displays all hidden columns. Moves all the columns from the Available Columns pane to the Visible Columns pane	

UI Element (A-Z)	Description	
5	Hides all columns. Moves all the columns from the Visible Columns pane to the Available Columns pane.	
1	Nove a selected column up in the list in the Visible Columns pane.	
U.	Move a selected column down in the list in the Visible Columns pane.	
Available Columns	The columns in this pane do not appear in the table.	
Visible Columns	The columns in this pane are visible in the table.	

💐 Sort Column Content Dialog Box

This dialog box enables you to set or change the sort order for the entries displayed in a table.

Description	Click the 📑 Sort Column Content button.	
Important information	To sort a table by one column: Move the column name from the Available Columns to the Sorted Columns list. Select the name and decide whether to sort in ascending (upward triangle) or descending (downward triangle) order by clicking the relevant button.	
	To sort a table by more than one column: Move the column names from the Available Columns to the Sorted Columns list. For each column, decide whether to sort in ascending or descending order.	
	To change the order in which columns are sorted: In the Sorted Columns list, select an entry, and click the Up or Down arrow to change the order. (Entries higher in the list are sorted before entries lower in the list.) A number is displayed in the table's column headers.	
	Note: Only columns that are displayed can be sorted. For details on how to define which columns are displayed in the table and in which order, see "Select Columns Dialog Box" on page 570.	

The following elements are included:

UI Element (A–Z)	Description	
>	Moves the selected column from the Available Columns pane to the Sorted Columns pane. You can double-click the selection to perform the same procedure.	
¢	Moves the selected column from the Sorted Columns pane to the Available Columns pane.	
	Moves all the columns from the Available Columns pane to the Sorted Columns pane.	

UI Element (A–Z)	Description	
5	Moves all the columns from the Sorted Columns pane to the Available Columns pane.	
₩ ♠	Moves the selected column up or down in the list to increase or decrease its priority in establishing the sort order.	
lat ≓↓	Enables you to sort the column content in ascending or descending order.	
	In the Sorted Columns pane, select a column name and click the ascending or descending button.	
Available Columns	The columns whose content is not sorted.	
	Note: You can select multiple columns.	
Sorted Columns	The columns whose content is sorted in either ascending or descending order.	

Chapter 16 • Working with Tables

17

Regular Expression Examples

This chapter includes:

Reference

► Examples of Regular Expressions on page 576

Reference

examples of Regular Expressions

Enter a regular expression to define an IP address (aa.yy.zz.mm):

То:	In the First Field Enter:	In the Second Field Enter:
Create label by aa	(.*)([.].*[.].*[.].*)	1
Create label by yy	(.*[.])(.*)([.].*[.].*)	2
Create label by zz	(.*[.].*[.])(.*)([.].*)	2
Create label by mm	(.*[.].*[.])(.*)	2

Enter a regular expression to create the label by the first or last letters of the selected attribute:

То:	In the First Field Enter:	In the Second Field Enter:
Create label by the first letter	(.)(.*)	1
Create label by the last letter	(.*)(.)	2
Create label by the first two letters	()(.*)	1
Create label by the last two letters	(.*)()	2

Index

A

Add Calculated Relationship dialog box 54 Add Compound Relationship dialog box 56 Add Function dialog box Modeling Studio 379 Add Join Relationship dialog box 60 Add Related Query Node wizard 65 Related Query Node Instances page 72 Related Query Node Properties page 69 Related Query Node Type page 66 Relationship Type page 68 Add Triplet dialog box 73 Add/Edit Attribute dialog box 489 Add/Edit Relationship dialog box 63 Add/Remove Relationship dialog box 492 adding Enrichment nodes and relationships to a TQL query 528 query nodes and relationships to a TQL query 32 aging mechanism for CIs 236 All Styles tab Layout Properties dialog box 181 ALLOW VOLATILITY qualifier 28 Asset report 311 attribute operator definitions 45

В

browse mode displaying a view 157 business CI models 346 building 370, 375 business view building 339

C

calculated relationship types impact modeling 114 calculated relationships creating 484 Change Query Node Type dialog box 381 Change Relationship Type dialog box 381 Change Timeframe dialog box 261 child CIs hidden 353 Choose Operation for Selected Item dialog box 383 CI Conditional Search dialog box 161 CI Properties dialog box 266 CI Selector 163 Browse mode 163 configuration 159 displaying a view 157 limitations and troubleshooting 174 overview 156 Search mode 167 unavailable views 174 using the search tool 157 CI Type Manager 475, 492 Attached Menu tab 506 Attributes tab 498 context menu 495 Default Label tab 510 Details tab 497 Icon tab 505 Qualifiers tab 502 Triplets tab 503 CI Types assigning a calculated relationship 485 assigning icons 482 assigning qualifiers 482, 484, 485

Index

attributes 477 creating 481 customizing the menu 482, 484 defining 481, 483, 484 defining default labels 482, 484 overview 476 relationships 478 setting attributes 481, 483 view descriptions 488 CI/Relationship History dialog box 262 Circular tab Layout Properties dialog box 183 CIS adding to Data Flow Management job 283 attaching existing 238 automatic deletion with aging mechanism 236 comparing 305 creating 244 creating new in view 232 creating non-related CIs 233 creating related CIs 233 deleting 234, 284 hidden in Dashboard 353 hiding from view 224 properties 235 removing from Data Flow Management job 283 class model converting selected part 560 introduction 551 columns user interface 570 Compare CIs report 313 Compare Snapshots report 318 comparing CIs 305 comparing snapshots 307 compound relationships 26 defining 33 Conditions of Related CIs dialog box 383 Create Calculated Relationship wizard 496 Create Configuration Item Type wizard 496 Attached Menu page 506 Attributes page 498 Default Label page 510 Details page 497

Icon page 505 Qualifiers page 502 Create Enumeration Definition dialog box 513 Enumeration definition area 515 Create List Definition dialog box 513 list definition area 514 Create New Enrichment Rule wizard Rule Base Query page 542 Rule General Attributes page 540 Create New Impact Rule/Impact Rule Properties/Save As Impact Rule wizard Impact Rule General Attributes page 470 Impact Rule Groups page 472 Rule Base Query page 471 Create Relationship wizard 496 Create Reveal Path dialog box 385 create views based on impact modeling impact modeling 115 Creating New View dialog box 386 Cron expressions 309 Custom Reports Pane 329 Cycle Definition dialog box 387

D

Data Flow Management job adding to a CI 283 removing from CIs 283 data model introduction 551 defining compound relationships 33 join relationships 36 map printing settings 199 subgraph definitions 38 defining report settings 369 Dependencies dialog box 447 Details dialog box Impact Analysis Manager 457 direct link embedded applets overview 144 direct link operation flow 147 Direct Link Parameters – CI Selector page Generate Direct Link wizard 129

Direct Link Parameters – CI Type Selector page Generate Direct Link wizard 129 Direct Link Parameters - Model Editor page Generate Direct Link wizard 133 Direct Link Parameters – Query Editor page Generate Direct Link wizard 134 Direct Link Parameters – Report Viewer page Generate Direct Link wizard 136 Direct Link Parameters - Report Viewer -Saved Report page Generate Direct Link wizard 136 Direct Link Parameters - Show CI Neighborhood page Generate Direct Link wizard 135 Direct Link Parameters – Show CI Properties page Generate Direct Link wizard 137 Direct Link Parameters – Show Impact Map page Generate Direct Link wizard 132 Direct Link Parameters - Show Instances Grid page Generate Direct Link wizard 131 Direct Link Parameters – Start in Mode page Generate Direct Link wizard 141 Direct Link Parameters page - Show View Generate Direct Link wizard 140 Direct Link Parameters page – Show View Topology Generate Direct Link wizard 138 Direct Link Parameters page – View Editor Generate Direct Link wizard 138 Direct Link Parameters page - Views Selector Generate Direct Link wizard 139 Discovery Status tab in Modeling 298 documentation updates 18

Е

Edit Reveal Path dialog box 385 Element Instances dialog box 77 embedding applets using direct links 143 Enrichment Manager Node/Relationship Definition dialog box 544 overview 520 Enrichment Manager page 530 Enrichment Manager user interface 530 Enrichment nodes and relationships adding to a TQL query 528 Enrichment rules define 523 validations 528 enumeration definitions 517 creating 485 workflow 486 Export Class Model to UML tool 557, 558 plugin input 565 Export Class Model to UML wizard 562 Export Selected Items 564 Export to Class Model tool 559

F

Filter CI Instances dialog box 80 Finish page Generate Direct Link wizard 142 folders predefined 343

G

Generate Direct Link dialog box 123 overview 118 scenario 120 wizard 124 Generate Direct Link wizard Direct Link Parameters – CI Selector page 129 Direct Link Parameters - CI Type Selector page 129 Direct Link Parameters - Model Editor page 133 Direct Link Parameters – Query Editor page 134 Direct Link Parameters – Report Viewer - Saved Report page 136

Direct Link Parameters – Report Viewer page 136 Direct Link Parameters – Show CI Neighborhood page 135 Direct Link Parameters – Show CI Properties page 137 Direct Link Parameters - Show Impact Map page 132 Direct Link Parameters - Show Instances Grid page 131 Direct Link Parameters - Start in Mode page 141 Direct Link Parameters page – Show View page 140 Direct Link Parameters page – Show View Topology page 138 Direct Link Parameters page - View Editor page 138, 139 Finish page 142 Select Command page 125 group by nested groups 341

Н

hidden child CIs 353 Hidden CIs dialog box 388 Hierarchical tab Layout Properties dialog box 187 Hierarchy Rules dialog box 388 HP Software Support Web site 17 HP Software Web site 18

I

Impact Analysis Manager Details dialog box 457 Impact Rules Definition dialog box 467 Impacted Nodes dialog box 466 overview 450 Impact Analysis Manager page 458 Impact Analysis Manager user interface 456 Impact Analysis results retrieving 250 impact layer 111

impact modeling calculated relationship types 114 create views based on impact modeling 115 impact rules 111 propagation reversal 113 Impact modeling overview 110 Impact Rule Base Query page Create New Impact Rule/Impact Rule Properties/Save As Impact Rule wizard 471 Impact Rule General Attributes page Create New Impact Rule/Impact Rule Properties/Save As Impact Rule wizard 470 Impact Rule Groups page Create New Impact Rule/ Impact Rule Properties/ Save As Impact Rule wizard 472 Impact rules create 452 validation of TQL queries 105 impact rules impact modeling 111 Impact Rules Definition dialog box Impact Analysis Manager 467 Impacted Nodes dialog box Impact Analysis Manager 466 Import Parameter Values page Template-based View wizard 436 Insert Relationship dialog box 273 Relationship page 274 instance views. See perspective based views invisible child CIs 353 IT Universe large views 177 relationships 236 views 229, 231 IT Universe Manager CI Properties dialog box 266 overview 228 Topology Map 279 IT Universe Manager page 278 IT Universe model populating 228

J

Job List dialog box 325 join relationship 26 Join Relationship Condition dialog box 82 join relationships defining 36

K

Knowledge Base 17

L

large views 177 Layout Properties dialog box 180 All Styles tab 181 Circular tab 183 Hierarchical tab 187 Orthogonal tab 191 Routing tab 195 Symmetric tab 193 Layout Settings dialog box 84 list definitions 517 creating 485

Μ

Manage CI Watchpoints dialog box 395 map printing settings defining 199 Model Editor 396 Modeling Discovery Status tab 298 modeling an application 223 Modeling Studio Add Function dialog box 379 overview 337 Modeling Studio Left pane 389 Modeling Studio page 404 models building 217 dependencies on other CIs 222 grouping in 221 preconfigured 219

models and perspectives 216 Models Containing Selected CI dialog box 406

Ν

New CI dialog box 289 New Enrichment Rule/Enrichment Rule Properties/Save As Enrichment Rule wizard 539 New Impact Rule /Impact Rule Properties/Save As Impact Rule wizard 469 New Model dialog box 407 New Pattern View/Template/Perspective dialog box 407 New Watchpoint dialog box 409 Node/Relationship Definition dialog box Enrichment Manager 544

0

ODB applet tag overview 145 online resources 17 Open Saved Reveal Path dialog box 410 Organize Searches dialog box 171 Orthogonal tab Layout Properties dialog box 191 overview CI Selector 156 Topology Query Language 22

Р

Parameters page Template-based View wizard 437 Pattern View Editor 413 pattern views creating 359 Pattern-based Model wizard 411 Query Selection page 412 Select CI Type page 411 pattern-based models building 372

Index

perspective based views building 349 including and excluding child CIs 352 Perspective-based View Editor 419 perspectives creating 362 predefined 344 previewing topology map before printing 199 printing topology map contents 198 propagation reversal impact modeling 113

Q

Query Node Grouping dialog box 425 Query Node/Relationship Properties dialog box 85 query nodes and relationships adding to a TQL query 32 Query Selection page Pattern-based Model wizard 412 Query/Template/Perspective Name 447 Query/View Definition Properties dialog box 426

R

Refine Query Node Type dialog box 96 regular expressions adding to default label 511 examples 575 Related CIs dialog box 272 Related Query Node Instances page Add Related Query Node wizard 72 Related Query Node Properties page Add Related Query Node wizard 69 Related Query Node Type page Add Related Query Node wizard 66 Relationship Type page Add Related Query Node wizard 68 relationships about 236 creating 236, 244, 483 deleting 240

hierarchical 237 view descriptions 488 visible, in TQL queries 59, 62 reports defining settings 369 Schedule Report dialog box 327 Reveal CIs dialog box 427 revealing CIs 354 root causes 450 Routing tab Layout Properties dialog box 195 Rule Base Query page Create New Enrichment Rule wizard 542 Rule General Attributes page Create New Enrichment Rule wizard 540 Run Impact Analysis dialog box 294 Running Software Search dialog box 172

S

Save Query dialog box 430 Save Reveal Path dialog box 385 Save Search Criteria dialog box 173 Save Snapshot dialog box 296 Save View dialog box 431 Save Views page Template-based View wizard 439 saving to file Topology Map 178 Schedule Report dialog box reports 327 search tool using 157 Select CI Type page Pattern-based Model wizard 411 Select Columns dialog box 570 Select Command page Generate Direct Link wizard 125 Select Location page Template-based View wizard 438 Select Relationship Type dialog box 97 Select Template page Template-based View wizard 435 Select Valid Links 563

Set Data Sources dialog box 432 shortcut menu options **TQL 40** Show Impact pane 300 snapshots comparing 307 taking of view 257 Sort Column Content dialog box 433, 572 Subgraph Condition Definition dialog box 98 subgraph definition 28 Subgraph Definition dialog box 100 subgraph definitions defining 38 Summary page Template-based View wizard 439 Symmetric tab Layout Properties dialog box 193 System Type Manager 479 System Type Manager dialog box 516

Т

template based views creating a single view 365 creating multiple views 367 Template Parameter Values dialog box 440 Template-based View wizard 434 Import Parameter Values page 436 Parameters page 437 Save Views page 439 Select Location page 438 Select Template page 435 Summary page 439 Template-based views creating 345 templates creating 360 Topology Map 175, 279 Main menu 197 overview 176 previewing before printing 199 printing and saving 258 saving to file 178 toolbar options 201

topology map contents printing 198 Topology Map sidebar 210 Topology Query Language 22 overview 22 Topology Query Language (TQL) user interface 53 **Topology Report 333** Topology reports overview 304 **Topology Reports Pane 329** TQL audit short/detailed log 50 circular queries 104 incremental detailed logs 53 incremental splitter logs 52 incremental statistics log 51 logs 47 pattern log 48 pattern statistics log 50 queries, circular 104 queries, validation restrictions 103 queries, visible relationships 59, 62 queries, visible TQL nodes 71, 86 self relationships 56, 62, 64, 68, 103, 382 shortcut menu options 40 TQL nodes visible, in TQL queries 71, 86 TQL queries creating 23 TQL query define 30 TQL Query Editor 440 trigger node 450 Troubleshooting and Knowledge Base 17 troubleshooting and limitations CI Selector 174

U

UML tool export to 559 Update Enumeration Definition dialog box 513 enumeration definition area 515 Index

Update List Definition dialog box 513 list definition area 514 updates, documentation 18 User Preferences dialog box 102 Using Modeling Studio 216

V

validation restrictions TQL queries 103 view formats 338 view-based discovery 247 viewing related CIs 245 views based on a CI collection 374 based on a model 374 creating new CIs 232 creating non-related CIs 233 creating related CIs 233 displaying 157 factory 344 in IT Universe 229 large 177 lifecycle 230 predefined 343 rediscovering 247 relationships in 236 tree structure 231 unavailable views 174 Views Containing Selected CI dialog box 444 visible node 71 visible relationship 59, 62

W

watchpoints 354 Watchpoints Updates dialog box 446 working with Topology Map 175