

HP Cloud Service Automation

Software Version: 4.20
Windows® operating systems

Configuration Guide

Document Release Date: December 2014
Software Release Date: December 2014



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notice

© Copyright 2010-2014 Hewlett-Packard Development Company, L.P.

Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

The OpenStack® Word Mark and the Square O Design, together or apart, are trademarks or registered trademarks marks of OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission.

Oracle and Java are registered trademarks of Oracle and/or its affiliates.

RED HAT READY™ Logo and RED HAT CERTIFIED PARTNER™ Logo are trademarks of Red Hat, Inc.

This product includes an interface of the 'zlib' general purpose compression library, which is Copyright © 1995-2002 Jean-loup Gailly and Mark Adler.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to: <http://h20230.www2.hp.com/selfsolve/manuals>

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to: <http://h20229.www2.hp.com/passport-registration.html>

Or click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

Visit the HP Software Support Online web site at: <http://www.hp.com/go/hpsupport>

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

HP Software Solutions Now accesses the HPSW Solution and Integration Portal Web site. This site enables you to explore HP Product Solutions to meet your business needs, includes a full list of Integrations between HP Products, as well as a listing of ITIL Processes. The URL for this Web site is <http://h20230.www2.hp.com/sc/solutions/index.jsp>

Contents

- Chapter 1: Overview 12
- Chapter 2: Getting Started 14
 - Prepare LDAP for HP CSA 14
 - Configure the HP CSA Truststore Properties 15
 - Location of the HP CSA Truststore 16
 - Request Software Licenses 17
 - Request a Software License 17
 - Request a Software License for a Clustered Environment 18
 - Request a Software License for a System with an Updated IP Address 18
 - Enable TLS on Your Web Browser 19
 - Update the HP Cloud Service Automation Service Startup Type 20
 - Location of the JRE Installed with HP CSA 21
- Chapter 3: Secure Connections 22
 - Configure Secure Connections for Client Browsers 22
 - Configure HP CSA to Use a Trusted Certificate Authority-Signed or Subordinate Certificate Authority-Signed Certificate 23
 - Step 1: Create a Keystore and Self-Signed Certificate 24
 - Step 2: Create a Certificate Signing Request 24
 - Step 3: Submit the Certificate Signing Request to a Certificate Authority 25
 - Step 4: Import the Certificate Authority's Root Certificate 25
 - Step 5: Import the Certificate Authority-Signed Certificate 26
 - Step 6: Configure the Marketplace Portal 26
 - Step 7: Configure the Web Server 27
 - Step 8: Configure Client Browsers 28
 - Step 9: Test Secure Connections 28
 - Configure HP CSA to Use an Internal Certificate Authority-Signed Certificate 28
 - Step 1: Import the Certificate Authority's Root Certificate 29
 - Step 2: Import the Internal Certificate Authority-Signed Certificate 30
 - Step 3: Configure the Marketplace Portal 30
 - Step 4: Configure the Web Server 31
 - Step 5: Configure Client Browsers 32
 - Step 6: Test Secure Connections 32
 - Configure HP CSA to Use a Self-Signed Certificate 32

- Step 1: Create a Keystore and Self-Signed Certificate33
- Step 2: Export the Self-Signed Certificate34
- Step 3: Import the Self-Signed Certificate as a Trusted Certificate34
- Step 4: Configure the Marketplace Portal35
- Step 5: Configure the Web Server36
- Step 6: Configure Client Browsers (Optional)37
- Step 7: Test Secure Connections37
- Configure Secure Connections for LDAP38
- Configure Secure Connections for SMTP38
- Configure Secure Connections for an Oracle Database39
- Configure Secure Connections for Microsoft SQL Server42
- Configure Secure Connections for HP Operations Orchestration Load Balancer43
- Chapter 4: HP Operations Orchestration46**
 - Configure HP Operations Orchestration for Topology Designs46
 - Configure an Internal User47
 - Deploy Content Packs48
 - Configure HP Single Sign-On Between HP CSA and HP Operations Orchestration48
 - Configure and Enable HP Single Sign-On49
 - Configure LDAP Users for Single Sign-On49
 - Configure HP Operations Orchestration Properties in the `csa.properties` File50
 - Configure a Secure Connection Between HP CSA and HP Operations Orchestration50
 - Run the Component Tool50
 - Configure HP Operations Orchestration for Sequential Designs54
 - Configure HP Operations Orchestration Version 10.2054
 - Add a JRE to the System Path55
 - Install the HP CSA Content Pack56
 - Configure Internal Users56
 - Deploy Content Packs Required by HP CSA57
 - Set Up System Accounts for the HP CSA Content Pack58
 - Set Up System Properties for the HP CSA Content Pack59
 - Configure HP Single Sign-On Between HP CSA and HP Operations Orchestration59
 - Configure and Enable HP Single Sign-On60
 - Configure LDAP Users for Single Sign-On60
 - Configure a Secure Connection Between HP Cloud Service Automation and HP Operations Orchestration61
 - Import HP Operations Orchestration Flows61
 - Configure HP Operations Orchestration Version 9.0761

Add a JRE to the System Path	62
Install HP CSA Flows	62
Set Remote Action Services	63
Configure System Accounts Settings	63
Configure System Properties Settings	64
Configure General System Configuration Settings in HP Operations Orchestration Central	64
Configure a Secure Connection Between HP Cloud Service Automation and HP Operations Orchestration	65
Check RAS Timeout Settings (Optional)	66
Change HP Operations Orchestration REST API Timeout (Optional)	66
Import HP Operations Orchestration Flows	67
Step 1: Install HP Cloud Service Automation flows in the HP Operations Orchestration Flow Library	68
Step 2: Create a Database Properties File	68
Step 3: Create an HP Operations Orchestration Input File	74
Step 4: Run the Process Definition Tool	82
Examples of Folder Attributes Used to Import Flows	84
Examples of HPOOInfoInput.xml Content	85
Chapter 5: The Cloud Service Management Console	89
Configure the Provider Organization	89
Add a Software License	90
Proxy Configuration for Resource Providers Outside the Internal Network	90
Customize the Cloud Service Management Console Dashboard	92
Using the Predefined Custom Tile	93
Enabling the HP IT Executive Scorecard Tiles	94
Enabling Other Predefined Dashboard Tiles	94
Creating a Dashboard Tile	94
Adding a Secondary Dashboard	98
Modifying a Dashboard Tile	101
Disabling a Dashboard Tile	102
Dashboard Configuration File Syntax	102
Customize the Cloud Service Management Console Font	104
Customize the Cloud Service Management Console Title	104
Delete the Sample Consumer Organization	105
Chapter 6: Common HP CSA Tasks	106
Launch the Cloud Service Management Console	106

Launch the Marketplace Portal	106
Start HP CSA	109
Restart HP CSA	109
Stop HP CSA	110
Encrypt a Password	110
Clear the Web Browser Cache	111
Uninstall HP CSA	112
Chapter 7: The Marketplace Portal	114
Encrypt a Marketplace Portal Password	114
Chapter 8: User Administration	115
Allow Non-Administrator Users to Start and Stop the HP CSA or Marketplace Portal Service	115
To allow non-administrator users to start and stop the HP CSA or Marketplace Portal service	115
Allow the HP CSA and Marketplace Portal Services to be Run as a Non-Administrator User	117
Create Non-Administrator Users	118
Configure the HP CSA and Marketplace Portal Services	118
Configure File System Permissions For the Non-Administrator Users	119
Change HP CSA Out-of-the-Box User Accounts	121
Cloud Service Management Console User Accounts	122
Marketplace Portal User Account	132
Chapter 9: Configure IPv6	134
Chapter 10: Common Access Card	136
Stop HP CSA	136
Update JBoss Configuration to Set Up Client Authentication	137
Configure the Cloud Service Management Console	138
Configure the Marketplace Portal	139
Configure Certificate Revocation	142
Configure HP CSA to Use a Certificate Revocation List	142
Configure HP CSA to Use a Certificate Revocation List Distribution Point	143
Configure HP CSA to Use the Online Certificate Status Protocol	143
Start HP CSA	143
Chapter 11: Single Sign-On	144

Integrate with HP Single Sign-On	144
Enable HP Single Sign-On	144
Configure the Domain	145
Set the HP SSO Property	145
Configure the Identity Management Component	146
Restart HP CSA	147
Disable HP Single Sign-On	147
Integrate HP CSA with a Single Sign-On Solution	148
Verify the HP CSA Provider Organization's LDAP Server Configuration	148
Verify the HP CSA Consumer Organization's LDAP Server Configuration	149
Configure the Custom SSO Server to Work with HP CSA	149
Stop HP CSA	150
Configure the Cloud Service Management Console	150
Configure the Marketplace Portal	150
Configure Proxy Mapping	150
Start HP CSA	151
Verify the SSO Integration	151
Integrate HP CSA with CA SiteMinder	152
Configure the HP CSA Provider Organization's LDAP Server	153
Configure the HP CSA Consumer Organization's LDAP Server	153
Configure the SiteMinder Policy Server for HP CSA Integration	154
Configure HP CSA for SiteMinder Integration	155
Stop HP CSA	156
Configure the Cloud Service Management Console	156
Configure the Marketplace Portal	158
Start HP CSA	161
Launch the Marketplace Portal	161
Customize the Marketplace Portal Landing Page (Optional)	162
Customize the Logout Page (Optional)	162
Configure the Marketplace Portal to Use the Fully-Qualified Domain Name of the SiteMinder Web Agent (Optional)	163
Request Flow	164
 Chapter 12: FIPS 140-2 Compliance	 167
Prerequisites	167
Examples Used in this Section	168
Configuration Overview	170
Stop HP CSA	171

Update applicationContext.xml to be FIPS 140-2 Compliant	171
Configure Properties in the Java Security File	172
Create an HP CSA Encryption Keystore	173
Generate an Encrypted Symmetric Key	174
When to Regenerate the HP CSA Encryption Keystore or Encrypted Symmetric Key	175
Create a New Keystore and Truststore for Secure Communication	177
Step 1: Create an HP CSA Server Keystore that Supports PKCS #12	178
Step 2: Create HP CSA's Certificate, Create a Truststore that Supports PKCS #12, and Import Certificate(s)	178
Step 3: Configure the Web Server	180
Step 4: Import the HP Operations Orchestration Certificate as a Trusted Certificate	183
Step 5: Import the Provider's Certificate as a Trusted Certificate	184
Step 6: Import the Certificates for other Applications as Trusted Certificates	184
Step 7: Configure Client Browsers (Optional)	185
Re-Encrypt HP CSA Passwords	185
Configure HP CSA Properties	188
Configure the Marketplace Portal	192
Password Encryption	192
Keyfile, Encryption, and Decryption Workflow	193
Create a Keyfile	193
Encrypt	193
Decrypt	193
Encrypt a Password	193
Configure Settings for Keyfile, Session ID Cookie Secret, IdM Transport User Password, and SSL Keyfile or Truststore Passphrase	194
Configure TLS	195
Configure the Identity Management Component	196
Update the applicationContext.xml File	196
Re-Encrypt Passwords	197
Update the idm-security.properties File	200
Start HP CSA	200
Test Secure Connections	201
Chapter 13: Database Administration	202
Restart the Database	202
Configure the CSA Reporting Database User	203
Update the HP CSA Database System	205

Update the HP CSA Database User or Password	206
Import Large Archives	208
Import Large Archives Using the HP CSA Content Archive Tool	208
Import Large Archives from the Cloud Service Management Console or through the REST API	209
Purge Service Subscriptions and Audit Data	210
About Service Subscriptions	210
About Audit Data	211
Deleting Service Subscriptions and Audit Data	212
Install the HP CSA Database Schema	221
Upgrading or Installing the Database Schema	222
Configure HP CSA to Mitigate Frequently Dropped Database Connections	227
Appendix A: Cloud Service Management Console Properties	230
Appendix B: Marketplace Portal Attributes	261
Appendix C: HP Operations Orchestration Settings	269
Appendix D: Identity Management Configuration	272
External Configuration	272
Configure Seeded Authentication	273
Configure the Java Relying Party Library	274
IdentityServiceConfig	274
IdentityAuthenticationProvider	274
HeaderAuthenticationProvider	275
Internal Configuration	275
InfinispanTokenStore	275
JwtTokenFactory	276
ConvergedLdapAuthConfig	277
ConvergedActiveDirectoryAuthenticationProvider and ConvergedLdapAuthenticationProvider	278
SeededAuthenticationProvider	278
IdentityAuthenticationProvider	279
MultiTenantAuthenticationProvider	279
IdentityServiceImpl	280
IdentityController	281
KeystoneAuthenticationProvider	281
KeystoneConfig	281

RestTemplateFactoryImpl	283
Send Documentation Feedback	284

Chapter 1: Overview

This document provides information on how to set up the Cloud Service Management Console and HP CSA in order to enable users to log in and use the Cloud Service Management Console and Marketplace Portal. Some tasks must be completed before you can start using HP CSA.

The user who sets up HP CSA should have knowledge of or work with someone who has knowledge of LDAP, TLS, HP Operations Orchestration, and the resource providers that will be integrated with HP CSA.

The following information is provided in this document:

Getting Started. Before setting up the Cloud Service Management Console, you may need to complete some initial configuration such as preparing LDAP, configuring HP CSA truststore properties, and requesting a software license.

Secure Connections. Many of the components that interact with HP CSA may require communication over a secure connection. You may want to replace the HP CSA self-signed certificate or configure a secure connection for LDAP, SMTP, the Oracle Database, the Microsoft SQL Server, or the HP Operations Orchestration Load Balancer.

HP Operations Orchestration. A process engine whose flows are executed by HP CSA, HP Operations Orchestration must be integrated with HP CSA and sample flows must be imported before the flows can be executed.

The Cloud Service Management Console. To set up the Cloud Service Management Console so that users can log in, you must configure the provider organization. In order to start using the Cloud Service Management Console, you must add a software license. You may wish to import the sample service designs provided with HP CSA, configure a proxy, or enable or customize tiles in the Cloud Service Management Console.

Common HP CSA Tasks. Common tasks include launching the Cloud Service Management Console and Marketplace Portal, starting, stopping, or restarting HP CSA and the Marketplace Portal, encrypting an HP CSA password, and uninstalling HP CSA.

The Marketplace Portal. The Marketplace Portal's password utility is different from the one used by HP CSA. This section explains how to encrypt passwords used by the Marketplace Portal. Configuring the Marketplace Portal is completed using the Cloud Service Management Console. Refer to the *HP Cloud Service Management Console Help* for information about configuring the Marketplace Portal.

User Administration. User administration includes tasks such as allowing non-administrator users to start and stop HP CSA services and changing the out-of-the-box users.

IPv6 Configuration. Configure HP CSA to support IPv6 (both dual-stack and IPv6-only).

Common Access Card. Common access cards are used for user authentication and allow users to log in to HP CSA using a Personal Identity Verification card.

Single Sign-On. Enable or disable HP Single Sign-On that is included with HP CSA. Single sign-on can also be configured for the Cloud Service Management Console and Marketplace Portal with almost any single sign-on solution and a specific solution for CA SiteMinder is provided.

FIPS 140-2 Compliance. FIPS 140-2 is a standard for security requirements for cryptographic modules defined by the National Institute of Standards and Technology (NIST). HP CSA can be configured for FIPS 140-2 compliance.

Database Administration. Database administration includes any task that might involve the database, such as configuring the HP CSA reporting database user if you did not configure it during installation, updating HP CSA database system or users and passwords, importing large archives, purging service subscriptions, installing the HP CSA database schema, and configuring HP CSA to mitigate frequently dropped database connections.

Cloud Service Management Console Properties. This is a reference to the Cloud Service Management Console configurable properties.

Marketplace Portal Attributes. This is a reference to the Marketplace Portal configurable attributes.

HP Operations Orchestration Settings. This is a reference to the HP Operations Orchestration configurable settings applicable to HP CSA.

Identity Management Configuration. This is a reference to the Identity Management component configurable settings applicable to HP CSA.

Refer to the following guides for more information about:

- HP CSA: *HP Cloud Service Automation Concepts Guide*
- Supported components and versions: *HP Cloud Service Automation System and Software Support Matrix*
- Installation: *HP Cloud Service Automation Installation Guide*
- Cloud Service Management Console: *HP Cloud Service Management Console Help*
- Automated, on-demand cloud services creation: *HP Cloud Service Automation Service Design Guide*
- Sample service designs and resource offerings: *HP Cloud Service Automation Integration Pack*

These guides are available from the HP Software Support Web site at <http://h20230.www2.hp.com/selfsolve/manuals/> (this site requires that you register with HP Passport).

Chapter 2: Getting Started

This chapter provides information for common setup tasks that need to be completed for HP CSA.

Caution: If you are configuring HP CSA to be compliant with FIPS 140-2, proceed to ["FIPS 140-2 Compliance" on page 167](#) to start configuring HP CSA. Do NOT configure any other feature of HP CSA and do not use any of the HP CSA tools until you have configured HP CSA to be compliant with FIPS 140-2.

Tasks include:

- ["Prepare LDAP for HP CSA" below](#) (required)
- ["Configure the HP CSA Truststore Properties" on the next page](#) (required)
- ["Request Software Licenses" on page 17](#) (required)
- ["Enable TLS on Your Web Browser" on page 19](#) (required)
- ["Update the HP Cloud Service Automation Service Startup Type" on page 20](#) (optional)

Prepare LDAP for HP CSA

HP CSA supports limited authentication out-of-the-box and has a fixed set of user names (and associated passwords) that can be used to log in. This basic form of authentication can be used for initial setup and experimentation with the product, but in a production environment, authentication should be configured to occur against a directory service.

HP CSA can be configured to authenticate against a Lightweight Directory Access Protocol (LDAP) server. Users can then log in with a pre-existing user name (such as an enterprise email address) and password combination. LDAP authenticates the login credentials by verifying that the user name and password match an existing user in the LDAP directory.

In HP CSA, LDAP is used to:

- Authenticate a user's login to the Cloud Service Management Console and Marketplace Portal
- Authenticate a user's access to information
- Authorize a user's access to information
- Retrieve information about a user's manager for approvals
- Retrieve information about a user's group membership for approvals

These functions are configured when you configure LDAP and access control for an organization.

Before you configure LDAP for the Cloud Service Management Console or Marketplace Portal, you should be familiar with your enterprise LDAP server and LDAP configuration tasks.

Note: The user object configured in LDAP that is used to log in to HP Cloud Service Automation and by which users can be identified should be configured to contain the following attribute types:

- **User Email - Required.** This attribute type designates the email address of the user to which to send email notifications. Common LDAP attribute names for email include **mail**, **email**, and **userPrincipalName**. If the value for this attribute in the user object in LDAP is empty or not valid, the user for whom the value is empty or not valid does not receive email notifications.
- **Manager Identifier - Required.** This attribute type identifies the manager of the user. A common LDAP attribute name for a user's manager is **manager**. If the value for this attribute in the user object in LDAP is empty or not valid, approval policies that use the User Context Template will fail.
- **Manager Identifier Value - Required.** This attribute type describes the value of the manager identifier. A common value for the manager identifier in LDAP is the **dn** (distinguished name) of the manager's user object. If the manager's user object cannot be located based on the values for manager identifier and manager identifier value, approval policies that use the User Context Template will fail.

The group object configured in LDAP must contain the following attribute type:

- **Group Membership - Required.** This attribute type identifies a user as belonging to the group. Common LDAP attribute names that convey group membership include **member** and **uniqueMember**.

The attribute names configured in your LDAP directory for these attribute types are used when configuring an organization's LDAP in the Cloud Service Management Console.

Note: Do not create users in your LDAP directory that match the out-of-the-box users provided by HP Cloud Service Automation (the out-of-the-box users are `admin`, `cdaInboundUser`, `csaCatalogAggregationTransportUser`, `csaReportingUser`, `csaTransportUser`, `idmTransportUser`, and `ooInboundUser`). Creating the same users in LDAP may allow the out-of-the-box users unintended access to the Cloud Service Management Console or give the LDAP users unintended privileges.

Configure the HP CSA Truststore Properties

You must configure information about the HP CSA's keystore. Do the following:

1. Open the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file in a text editor.

2. Enter values for the `csaTruststore` and `csaTruststorePassword` properties.

Property	Description
<code>csaTruststore</code>	Required. The HP Cloud Service Automation keystore that stores trusted Certificate Authority certificates. Note: Use only forward slashes (/) as your path separators.
<code>csaTruststorePassword</code>	Required. The encrypted password of the HP Cloud Service Automation keystore (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.

For more information about these properties, refer to ["Cloud Service Management Console Properties" on page 230](#).

3. Save and exit the file.
4. Restart HP CSA.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

Location of the HP CSA Truststore

The location of the HP CSA truststore depends on the JRE you are using with HP CSA and where the JRE has been installed.

The following are examples of where the HP CSA truststore may be located.

- If you are using the JRE that is installed with HP CSA (OpenJDK JRE), the truststore is located in the following location:

```
%CSA_HOME%\openjre\lib\security\cacerts
```

For example: `C:\Program Files\Hewlett-Packard\CSA\openjre\lib\security\cacerts`

- If you are using an Oracle JRE, the truststore may be found in the following location:

```
<JRE_HOME>\lib\security\cacerts
```

For example: `C:\Program Files\Java\jre7\lib\security\cacerts`

Request Software Licenses

HP CSA version 4.20 requires a software license. HP CSA licensing is based on the number of operating system instances (OSIs) being used in current, active subscriptions.

After initial installation of HP CSA version 4.20, when you log in to the Cloud Service Management Console, a temporary 90-day trial license is activated. Once the trial license expires, you are limited to 25 OSIs. If you created more than 25 OSIs during the trial period, you cannot create any additional OSIs. You can add more licenses at any time to increase your OSI capacity.

After upgrade to HP CSA version 4.20, when you log in to the Cloud Service Management Console, all HP CSA version 4.x licenses are valid and are automatically added.

Note: HP CSA version 4.20 licenses are not compatible with HP CSA versions 4.01 or 4.10. That is, you cannot add HP CSA version 4.20 licenses to HP CSA versions 4.01 or 4.10.

The following topics are covered in this section:

- Request a software license
- Request a software license for a clustered environment
- Request a software license for a system with an updated IP address
- Request an emergency key

For information on how to view, add, or delete a license, refer to the *HP Cloud Service Management Console Help*.

Request a Software License

If you received an Electronic Delivery Receipt, use the link to the licensing portal located in the receipt and follow the online instructions to request a software license. Otherwise, to access the licensing portal, go to <http://www.hp.com/software/licensing>, enter your Entitlement Order Number, and follow the online instructions to request a software license.

Refer to the [Software License Activation Quick Start Guide](#) for more information about requesting a software license.

IP Address Limitations

When you request a software license, you must supply the IP address (IPv4 or Ipv6) of the system on which HP CSA is installed.

Do NOT use the following IP addresses when requesting a software license:

- Loopback address - 127.0.0.1 (IPv4) or ::1 (IPv6)

Request a Software License for a Clustered Environment

If you are configuring HP CSA in a clustered environment, use the IP address of the load balancer (in the examples given in the *Configuring an HP CSA Cluster for High Availability Using an Apache Web Server*, this is the APACHE_IP_ADDR; in the examples given in the *Configuring an HP CSA Cluster for High Availability Using a Load Balancer*, this is the LOAD_BALANCER_IP_ADDR). The license should be installed on only one node in the clustered environment.

Request a Software License for a System with an Updated IP Address

If you change the IP address of the system on which HP CSA is running, you must request a new software license.

If you immediately add the new license without restarting HP CSA, the license will not be accepted. You must restart HP CSA before adding the new license. To restart CSA, see ["Restart HP CSA" on page 109](#). For more information about managing software licenses, refer to the *HP Cloud Service Management Console Help*.

Enable TLS on Your Web Browser

The Cloud Service Management Console is configured to require https (http over a secure connection) for client browsers. Specifically, the Cloud Service Management Console is configured to use the TLS protocol. You must enable TLS 1.0 as the required minimum protocol for the browser, and, if applicable, disable the SSL protocols.

Enable your Web browser to use the TLS protocol:

Chrome

1. Exit or kill all Chrome sessions.
2. If you added a shortcut to launch Chrome from the Taskbar, remove it: right-click the shortcut on the Taskbar and select **Unpin this program from taskbar**.
3. For every shortcut you use to launch Chrome, do the following:
 - a. Right-click on the shortcut and select **Properties**.
 - b. Select the **Shortcut** tab.
 - c. At the end of the Target field, enter the following after the last quotation mark (and include a space after the last quotation mark but before the following content):

--ssl-version-min=tls1
 - d. Click **OK**.
 - e. If asked for administrator privileges, click **Continue**.
4. If you deleted the shortcut from the Taskbar, right-click on any updated shortcut and select **Pin to Taskbar**.
5. If Chrome is your default browser, edit the registry:
 - a. Click on the **Start** icon, enter **regedit** in the Search programs and files box, and press **Enter**.
 - b. From the Registry Editor, select **HKEY_CLASSES_ROOT > http > shell > open > command**.
 - c. Double-click (**Default**).
 - d. Adding the following at the end of the Value data field (and include a space before the following content):

--ssl-version-min=tls1

- e. Click **OK**.
- f. Close the Registry Editor dialog.

Caution: Depending on how you launch Chrome, your browser session still may allow SSLv3 connections.

Microsoft Internet Explorer

1. Open the **Tools** menu (click on the tools icon or type Alt - x) and select **Internet options**.
2. Select the **Advanced** tab.
3. Scroll down to the bottom of the **Settings** section.
4. If TLS is not enabled, select the checkboxes next to **Use TLS 1.0**, **Use TLS 1.1**, and **Use TLS 1.2**.
5. Disable SSL 2.0 and SSL 3.0, if enabled (recommended). Unselect the checkbox next to **Use SSL 2.0** and/or **Use SSL 3.0**.
6. Click **OK**.

Firefox

1. Launch the Firefox browser.
2. In the Location Bar (address bar), enter **about:config** and press **Enter**.
3. In the Search box, enter **security.tls** and press **Enter**.
4. Double-click **security.tls.version.min**.
5. Set the value to **1** and click **OK**.

Update the HP Cloud Service Automation Service Startup Type

If you have services or applications installed on the same system as HP CSA that HP CSA requires to be available when HP CSA is started (such as the database), update the HP Cloud Service Automation service startup to be delayed. This allows those services time to start before HP CSA starts if the system is rebooted.

Note: If you have configured HP CSA to be FIPS 140-2 compliant, you will need to create an HP CSA encryption keystore password file and restart HP CSA after the system has been rebooted. Refer to "[Restart HP CSA](#)" on page 109 for more information.

To delay the start of the HP CSA on system reboot, do the following:

1. On the server that hosts HP Cloud Service Automation, navigate to **Start > Administrative Tools > Services**.
2. In the Service dialog, right-click on the HP Cloud Service Automation service and select **Properties**.
3. In the Properties dialog, locate the **Startup type** field and change the value to **Automatic (Delayed Start)**.
4. Click **OK**.

Location of the JRE Installed with HP CSA

The location of the JRE installed with HP CSA (OpenJDK JRE) is located in the following location:

`%CSA_HOME%\openjre`

For example: `C:\Program Files\Hewlett-Packard\CSA\openjre`

Note: An additional JRE is installed with HP CSA in the `%CSA_HOME%\IA-openjre` directory. This JRE is used exclusively by the HP CSA installer. This JRE should NOT be used for any other purposes.

Chapter 3: Secure Connections

This chapter provides information about configuring secure connections between HP CSA and some commonly used components of HP CSA.

Note: HP CSA only accepts secure connections using the TLSv1 protocol. If you are integrating with an application and are using secure connections, you must configure the application to use the TLSv1 protocol with HP CSA.

Information includes:

- ["Configure Secure Connections for Client Browsers" below](#) (required when the HP CSA self-signed certificate expires)
- ["Configure Secure Connections for LDAP" on page 38](#) (required if the LDAP server requires a secure connection)
- ["Configure Secure Connections for SMTP" on page 38](#) (required if the SMTP server requires a secure connection)
- ["Configure Secure Connections for an Oracle Database" on page 39](#) (required if the Oracle database requires a secure connection)
- ["Configure Secure Connections for Microsoft SQL Server" on page 42](#) (required if Microsoft SQL Server requires a secure connection)
- ["Configure Secure Connections for HP Operations Orchestration Load Balancer" on page 43](#) (required if you are running the HP OO LB server and it requires a secure connection)

Configure Secure Connections for Client Browsers

The Cloud Service Management Console is configured to require https (http over a secure connection) for client browsers. For a secure connection to be established, a certificate must first be installed on the HP Cloud Service Automation (HP CSA) server.

A self-signed certificate is created and configured when HP CSA is installed and is configured with the fully-qualified domain name that was entered during the installation. This self-signed certificate is used when https browser requests are issued for the Cloud Service Management Console and expires 120 days after HP CSA is installed.

When client browsers connect to the Cloud Service Management Console in this default configuration, the client browser will usually issue warnings that the certificate was not issued by a trusted authority. The end user can choose to continue to the Web site or close the browser.

Although the self-signed certificate can be used in production, HP recommends that you replace this certificate by configuring a trusted third-party Certificate Authority-signed or subordinate Certificate

Authority-signed certificate (see ["Configure HP CSA to Use a Trusted Certificate Authority-Signed or Subordinate Certificate Authority-Signed Certificate" below](#)) or by configuring an internal Certificate Authority-signed certificate (see ["Configure HP CSA to Use an Internal Certificate Authority-Signed Certificate" on page 28](#)). Or, you can replace this certificate by [configuring a self-signed certificate](#) (see ["Configure HP CSA to Use a Self-Signed Certificate" on page 32](#)).

Note: If you have configured HP CSA to be compliant with FIPS 140-2, you must substitute the HP CSA server truststore (for example, `csa_server_truststore.p12`) for the Java truststore (`cacerts`) and substitute the HP CSA server truststore password for the Java truststore password (`changeit`) in the examples. See ["Create a New Keystore and Truststore for Secure Communication" on page 177](#) for more information about the HP CSA server truststore and password.

Configure HP CSA to Use a Trusted Certificate Authority-Signed or Subordinate Certificate Authority-Signed Certificate

This section describes the process you should follow to obtain, install, and configure a trusted third-party Certificate Authority-signed or subordinate Certificate Authority-signed certificate for use by HP CSA. The process by which you acquire a certificate depends on your organization. If you are obtaining a certificate from a trusted third-party Certificate Authority, such as Verisign, perform the following general steps, which are described in detail below. If you are generating and/or obtaining a certificate from an internal Certificate Authority, such as a corporate Certificate Authority, you should perform the general steps in ["Configure HP CSA to Use an Internal Certificate Authority-Signed Certificate" on page 28](#).

1. Create a keystore and a self-signed certificate
2. Create a certificate signing request
3. Submit the certificate signing request to a Certificate Authority
4. Import the Certificate Authority's root certificate
5. Import the Certificate Authority-signed certificate
6. Configure the Marketplace Portal
7. Configure the Web server
8. Configure client browsers
9. Test the secure connection

Note: In the following instructions, `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed (for example, `C:\Program Files\Hewlett-Packard\CSA`) and the

keytool utility is included with the JRE.

Also, the following instructions are applicable for subordinate Certificate Authorities. Wherever the Certificate Authority is mentioned, the subordinate Certificate Authority is implied. For example, if the content states to submit the certificate to a Certificate Authority, you may also submit the certificate to a subordinate Certificate Authority.

Step 1: Create a Keystore and Self-Signed Certificate

Create a self-signed certificate to send with your request to a Certificate Authority by doing the following:

1. Open a command prompt and change directories to %CSA_HOME%.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -genkeypair -alias csa_ca_signed  
-validity 365 -keyalg rsa -keysize 2048 -keystore  
.\jboss-as\standalone\configuration\keystore_ca_signed
```

where *<csa_jre>* is the directory in which the JRE that is used by HP CSA is installed.

You can use different values for *-alias*, *-validity*, *-keysize* and *-keystore*. These instructions assume that you will use the *-alias* and *-keystore* values recommended here; you will have to adjust the commands accordingly if you use different values.

3. Enter a keystore password.

This password is used to control access to the keystore. This password must be the same as the password you enter for the key later in this procedure.

4. When you are prompted for your first and last name, enter the fully qualified domain name of the HP CSA server.
5. Follow the prompts to enter the remaining organization and location values.
6. Enter the keystore password you supplied earlier to use as the key password.

Although *keytool* allows you to enter different passwords for the keystore and the key, the two passwords must be the same to work with HP CSA.

Step 2: Create a Certificate Signing Request

To enable a Certificate Authority to sign the self-signed certificate, you will need to create a Certificate Signing Request using the following procedure:

1. Open a command prompt and change directories to %CSA_HOME%.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -certreq -alias csa_ca_signed  
-file C:\csacsr.txt -keystore .\jboss-as\standalone\configuration\keystore_ca_  
signed
```

where *<csa_jre>* is the directory in which the JRE that is used by HP CSA is installed.

3. When you are prompted for a password, enter the password you supplied for the keystore and key when you created the keystore and self-signed certificate in step 1.

Step 3: Submit the Certificate Signing Request to a Certificate Authority

Submit the Certificate Signing Request to the Certified Authority following the procedure used by your organization or the third-party provider. After the submission has been processed, you will receive a Certificate Authority-signed certificate and a root certificate for the Certificate Authority.

In our example, we will assume the Certificate Authority's root certificate is named *csaca.crt*, the Certificate Authority-signed certificate is named *csa_ca_signed.crt*, and that both are located in C:\.

Step 4: Import the Certificate Authority's Root Certificate

This step configures the JRE so it trusts the Certificate Authority that has signed your certificate. The JRE ships with a list of common, trusted Certificate Authority certificates that are stored in a keystore named *cacerts*. If the Certificate Authority used to sign your certificate is well known, it is likely that this root certificate is already present in the *cacerts* keystore. It is recommended that you perform the following steps even if you suspect that the certificate is already installed. The *keytool* command will detect if the certificate is already present, and you can exit the import process if the certificate exists.

1. Open a command prompt.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias csaca -file C:\csaca.crt -  
trustcacerts -keystore "<csa_jre>\lib\security\cacerts"
```

where *<csa_jre>* is the directory in which the JRE that is used by HP CSA is installed.

3. When prompted for the keystore password, enter *changeit*.
4. Enter *yes* when prompted to trust the certificate.

Step 5: Import the Certificate Authority-Signed Certificate

1. Open a command prompt and change directories to %CSA_HOME%.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias csa_ca_signed  
-file C:\csa_ca_signed.crt -trustcacerts -keystore  
.\jboss-as\standalone\configuration\keystore_ca_signed
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

Use this alias and keystore name when you configure the Web server.

3. When prompted, enter the password for the key and keystore.

Use this password when you configure the Web server.

Step 6: Configure the Marketplace Portal

This step converts the HP CSA keystore to a PKCS#12 archive and configures the Marketplace Portal to use the Certificate Authority-signed certificate.

1. Open a command prompt and navigate to %CSA_HOME%.
2. Convert the HP CSA keystore to a PKCS#12 archive. Run the following command:

```
"<csa_jre>\bin\keytool" -importkeystore -srckeystore  
.\jboss-as\standalone\configuration\keystore_ca_signed -deststoretype PKCS12 -  
destkeystore .\portal\conf\mppkeystore_ca_signed
```

3. When prompted, enter the password for the PKCS#12 archive. You will need this password when you configure the passphrase attribute later in this section.
4. When prompted, enter the password for the HP CSA keystore (changeit).
5. Open the %CSA_HOME%\portal\conf\mpp.json file in a text editor.
6. Update the ca attribute value for the provider. Enter the path to the certificate file that you imported in step 2. For example, C:\csa_ca_signed.crt.
7. Update the ca attribute value for the idmProvider. Enter the path to the certificate file that you imported in step 2. For example, C:\csa_ca_signed.crt.
8. Update the pfx attribute value. Enter the name of the PKS#12 archive you created earlier. For example, ..\conf\mppkeystore_ca_signed.
9. Update the passphrase attribute value. Enter the encrypted password used to access the

.mppkeystore_ca_signed archive (see "Encrypt a Marketplace Portal Password" on page 114 for instructions on encrypting Marketplace Portal passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.

10. Save and exit the file.

Step 7: Configure the Web Server

1. Open %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml in a text editor.
2. Locate the following entry:

```
<ssl name="ssl" key-alias="CSA" certificate-key-file=
"%CSA_HOME%\jboss-as\standalone\configuration\
.keystore" verify-client="false"/>
```

3. Add a new attribute named password with a value that corresponds to the password you selected for the keystore, change the name of the key-alias to the alias you used in step 5, and change the name of the certificate-key-file to the keystore you used in step 5.

```
<ssl name="ssl" key-alias="csa_ca_signed" certificate-key-file=
"%CSA_HOME%\jboss-as\standalone\configuration\
.keystore_ca_signed" password="keystorePassword"
verify-client="false"/>
```

Note: This example stores the password in clear text. If you want to use an encrypted password, follow the instructions at <https://community.jboss.org/wiki/JBossAS7SecuringPasswords> to create a password vault for JBoss.

Note: If you are using the vault scripts, verify that the %JAVA_HOME% environment variable has been defined, verify that %JAVA_HOME% has been set to the directory in which the JRE that is used by HP CSA is installed, and, if the directory path name includes a space, that the value has been enclosed in quotations marks. For example, to set %JAVA_HOME% to a directory path name that includes a space, from a command prompt, type

```
set JAVA_HOME="C:\Program Files\Hewlett-Packard\CSA\jre"
```

To verify that %JAVA_HOME% has been defined, from a command prompt, type

```
echo %JAVA_HOME%.
```

The following is an example of an encrypted password attribute using the JBoss password vault:

```
password="{VAULT::<vault_block_example>:password::N2NhZDzOMtES0ZGE4MmEtX0}"
```

4. Restart the HP Cloud Service Automation service.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

5. After the service has started, review the log files in `%CSA_HOME%\jboss-as\standalone\log\` and verify that no TLS or keystore errors are present.

Step 8: Configure Client Browsers

The client browser must be configured to trust certificates that are signed by the Certificate Authority. In most situations, this step will already have occurred. Client browsers are likely to already trust well-known third-party Certificate Authorities, or will have previously accessed and trusted Web sites that use internal Certificate Authority root certificates.

To test whether or not the browser on a client system is configured to trust certificates signed by your Certificate Authority, open a supported Web browser and navigate to `https://<csahostname>:8444/csa`. If you do not see a certificate warning, then the browser is configured properly.

If client browsers need to be configured to trust certificates signed by your Certificate Authority, then you will need to make the root certificate available to clients so it can be installed in the browser. The process of installing the root certificate will vary based on the browser.

- **Microsoft Internet Explorer** and **Chrome**: From Windows Explorer, double-click on the `.crt` file to begin the import process. Install the certificate in the Trusted Root Certification Authorities store. For information on how to import the certificate, refer to the browser's online documentation.
- **Firefox**: To begin the import process, select **Tools > Options**, select **Advanced**, select the **Encryption** tab, and click **View Certificates**. Import the root certificate into the Authorities tab. For information on how to import the certificate, refer to the browser's online documentation.

Step 9: Test Secure Connections

To test the connection to the Cloud Service Management Console, on a client system, open a supported Web browser and navigate to `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system that was used when the certificate was created. If the client browser is configured to accept the Certificate Authority's root certificate and the Web application opens without a certificate warning, then you have successfully configured HP Cloud Service Automation to use a Certificate Authority-signed certificate. If a certificate warning is displayed, review steps 1-8 to be sure they were followed as documented.

Configure HP CSA to Use an Internal Certificate Authority-Signed Certificate

This section describes the process you should follow to install and configure an internal root and internal Certificate Authority-signed certificate for use by HP CSA. An internal certificate is one that is generated by an internal Certificate Authority, such as a corporate or government Certificate Authority.

For an internal Certificate Authority, you do not have to generate a self-signed certificate nor create a certificate signing request. The internal Certificate Authority should provide you with a root certificate and signed certificate.

Perform the following general steps, which are described in detail below:

1. Import the internal Certificate Authority's root certificate
2. Import the internal Certificate Authority-signed certificate
3. Configure the Marketplace Portal
4. Configure the Web server
5. Configure client browsers
6. Test the secure connection

Note: In the following instructions, %CSA_HOME% is the directory in which HP Cloud Service Automation is installed (for example, C:\Program Files\Hewlett-Packard\CSA) and the keytool utility is included with the JRE.

In this example, we will assume you are given an internal Certificate Authority-signed certificate (referred to as `csa_internalca_signed.crt`), an internal Certificate Authority's root certificate (referred to as `csainternalca.crt`), and both certificates are located in C:\.

Step 1: Import the Certificate Authority's Root Certificate

This step configures the JRE so it trusts the internal Certificate Authority that has signed your certificate by importing the internal Certificate Authority into a keystore named `cacerts` that is shipped with the JRE.

1. Open a command prompt.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias csainternalca -file  
C:\csainternalca.crt -trustcacerts -keystore "<csa_jre>\lib\security\cacerts"
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

3. When prompted for the keystore password, enter `changeit`.
4. Enter `yes` when prompted to trust the certificate.

Step 2: Import the Internal Certificate Authority-Signed Certificate

1. Open a command prompt and change directories to %CSA_HOME%.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias csa_internalca_signed  
-file C:\csa_internalca_signed.crt -trustcacerts -keystore  
.\jboss-as\standalone\configuration\keystore_internalca_signed
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

Use this alias and keystore name when you configure the Web server.

3. When prompted, enter the password for the key and keystore.

Use this password when you configure the Web server.

Step 3: Configure the Marketplace Portal

This step converts the HP CSA keystore to a PKCS#12 archive and configures the Marketplace Portal to use the internal Certificate Authority root certificate.

1. Open a command prompt and navigate to %CSA_HOME%.
2. Convert the HP CSA keystore to a PKCS#12 archive. Run the following command:

```
"<csa_jre>\bin\keytool" -importkeystore -srckeystore  
.\jboss-as\standalone\configuration\keystore_internalca_signed -deststoretype  
PKCS12 -destkeystore .\portal\conf\mppkeystore_internalca_signed
```

3. When prompted, enter the password for the PKCS#12 archive. You will need this password when you configure the passphrase attribute later in this section.
4. When prompted, enter the password for the HP CSA keystore (changeit).
5. Open the %CSA_HOME%\portal\conf\mpp.json file in a text editor.
6. Update the ca attribute value for the provider. Enter the path to the certificate file that you imported in step 2. For example, C:\csa_internalca_signed.crt.
7. Update the ca attribute value for the idmProvider. Enter the path to the certificate file that you imported in step 2. For example, C:\csa_internalca_signed.crt.
8. Update the pfx attribute value. Enter the name of the PKS#12 archive you created earlier. For example, ..\conf\mppkeystore_internalca_signed.
9. Update the passphrase attribute value. Enter the encrypted password used to access the

.mppkeystore_internalca_signed archive (see "[Encrypt a Marketplace Portal Password](#)" on [page 114](#) for instructions on encrypting Marketplace Portal passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.

10. Save and exit the file.

Step 4: Configure the Web Server

1. Open %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml in a text editor.
2. Locate the following entry:

```
<ssl name="ssl" key-alias="CSA" certificate-key-file=
"%CSA_HOME%\jboss-as\standalone\configuration\
.keystore" verify-client="false"/>
```

3. Add a new attribute named password with a value that corresponds to the password you selected for the keystore, change the name of the key-alias to the alias you used in step 2, and change the name of the certificate-key-file to the keystore you used in step 2.

```
<ssl name="ssl" key-alias="csa_internalca_signed" certificate-key-file=
"%CSA_HOME%\jboss-as\standalone\configuration\
.keystore_internalca_signed" password="keystorePassword"
verify-client="false"/>
```

Note: This example stores the password in clear text. If you want to use an encrypted password, follow the instructions at <https://community.jboss.org/wiki/JBossAS7SecuringPasswords> to create a password vault for JBoss.

Note: If you are using the vault scripts, verify that the %JAVA_HOME% environment variable has been defined, verify that %JAVA_HOME% has been set to the directory in which the JRE that is used by HP CSA is installed, and, if the directory path name includes a space, that the value has been enclosed in quotations marks. For example, to set %JAVA_HOME% to a directory path name that includes a space, from a command prompt, type

```
set JAVA_HOME="C:\Program Files\Hewlett-Packard\CSA\jre"
```

To verify that %JAVA_HOME% has been defined, from a command prompt, type

```
echo %JAVA_HOME%.
```

The following is an example of an encrypted password attribute using the JBoss password vault:

```
password=":${VAULT::<vault_block_example>::password::N2NhZDzOMtES0ZGE4MmEtX0}"
```

4. Restart the HP Cloud Service Automation service.

See "[Restart HP CSA](#)" on page 109 for detailed information on how to restart HP CSA.

5. After the service has started, review the log files in %CSA_HOME%\jboss-as\standalone\log\ and verify that no TLS or keystore errors are present.

Step 5: Configure Client Browsers

The client browser must be configured to trust certificates that are signed by the Certificate Authority. In most situations, this step will already have occurred. Client browsers are likely to already trust well-known third-party Certificate Authorities, or will have previously accessed and trusted Web sites that use internal Certificate Authority root certificates.

To test whether or not the browser on a client system is configured to trust certificates signed by your Certificate Authority, open a supported Web browser and navigate to `https://<csahostname>:8444/csa`. If you do not see a certificate warning, then the browser is configured properly.

If client browsers need to be configured to trust certificates signed by your Certificate Authority, then you will need to make the root certificate available to clients so it can be installed in the browser. The process of installing the root certificate will vary based on the browser.

- **Microsoft Internet Explorer** and **Chrome**: From Windows Explorer, double-click on the .crt file to begin the import process. Install the certificate in the Trusted Root Certification Authorities store. For information on how to import the certificate, refer to the browser's online documentation.
- **Firefox**: To begin the import process, select **Tools > Options**, select **Advanced**, select the **Encryption** tab, and click **View Certificates**. Import the root certificate into the Authorities tab. For information on how to import the certificate, refer to the browser's online documentation.

Step 6: Test Secure Connections

To test the connection to the Cloud Service Management Console, on a client system, open a supported Web browser and navigate to `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system that was used when the certificate was created. If the client browser is configured to accept the Certificate Authority's root certificate and the Web application opens without a certificate warning, then you have successfully configured HP Cloud Service Automation to use a Certificate Authority-signed certificate. If a certificate warning is displayed, review steps 1-5 to be sure they were followed as documented.

Configure HP CSA to Use a Self-Signed Certificate

This section describes the process you should follow to obtain, install, and configure a self-signed certificate for use by HP CSA.

In general, HP recommends that you replace HP CSA's self-signed certificate with a Certificate Authority-signed certificate. However, you may consider replacing HP CSA's self-signed with a self-signed certificate you create in the following situations:

- HP CSA's self-signed certificate has expired and you do not want to configure a Certificate Authority-signed certificate at this time.
- The hostname that you entered when you installed HP CSA has changed (the hostname you entered during installation is used to configure HP CSA's self-signed certificate).
- You entered an IP address instead of the fully-qualified domain name when HP CSA was installed.
- Obtaining a Certificate Authority-signed certificate is not an option in your environment.

You should perform the following general steps, which are described in detail below:

1. Create a keystore and a self-signed certificate
2. Export the self-signed certificate
3. Import the self-signed certificate as a trusted certificate
4. Configure the Marketplace Portal
5. Configure the Web server
6. Configure client browsers (optional)
7. Test the secure connection

Note: In the following instructions, %CSA_HOME% is the directory in which HP Cloud Service Automation is installed (for example, C:\Program Files\Hewlett-Packard\CSA) and the keytool utility is included with the JRE.

Step 1: Create a Keystore and Self-Signed Certificate

Create a self-signed certificate by doing the following:

1. Open a command prompt and change directories to %CSA_HOME%.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -genkeypair -alias csa_self_signed  
-validity 365 -keyalg rsa -keysize 2048  
-keystore .\jboss-as\standalone\configuration\  
.keystore_self_signed [-ext san=ip:<ip_address>]
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed and `-ext san=ip:<ip_address>` is the option to specify the IP address of the system on which HP CSA is installed. This option is required if you specified an IP address instead of the fully-qualified domain name when you installed HP CSA. If you specified the fully-qualified domain name during installation, you may omit this option.

You can use different values for `-alias`, `-validity`, `-keysize` and `-keystore`. These instructions assume that you will use the `-alias` and `-keystore` values recommended here; you will have to adjust the commands accordingly if you use different values.

3. Enter a keystore password.

This password is used to control access to the keystore. This password must be the same as the password you enter for the key later in this procedure.

4. When you are prompted for your first and last name, enter the fully qualified domain name of the HP CSA server.
5. Follow the prompts to enter the remaining organization and location values.
6. Enter the keystore password you supplied earlier to use as the key password.

Although `keytool` allows you to enter different passwords for the keystore and the key, the two passwords must be the same to work with HP CSA.

Step 2: Export the Self-Signed Certificate

Export the self-signed certificate using the following procedure:

1. Open a command prompt and change directories to `%CSA_HOME%`.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -export -alias csa_self_signed  
-file C:\csa_self_signed.crt  
-keystore .\jboss-as\standalone\configuration\  
.keystore_self_signed
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

3. When you are prompted for a password, enter the keystore password used in step 1.

Step 3: Import the Self-Signed Certificate as a Trusted Certificate

This step configures the JRE so it trusts the self-signed certificate.

1. Open a command prompt.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias csa_self_signed  
-file C:\csa_self_signed.crt -trustcacerts  
-keystore "<csa_jre>\lib\security\cacerts"
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

3. When prompted for the keystore password, enter `changeit`.
4. Enter `yes` when prompted to trust the certificate.

Step 4: Configure the Marketplace Portal

This step converts the HP CSA keystore to a PKCS#12 archive and configures the Marketplace Portal to use the self-signed certificate.

1. Open a command prompt and navigate to `%CSA_HOME%`.
2. Convert the HP CSA keystore to a PKCS#12 archive. Run the following command:

```
"<csa_jre>\bin\keytool" -importkeystore -srckeystore  
.\jboss-as\standalone\configuration\keystore_self_signed -deststoretype PKCS12  
-destkeystore .\portal\conf\mppkeystore_self_signed
```

3. When prompted, enter the password for the PKCS#12 archive. You will need this password when you configure the `passphrase` attribute later in this section.
4. When prompted, enter the password for the HP CSA keystore (`changeit`).
5. Open the `%CSA_HOME%\portal\conf\mpp.json` file in a text editor.
6. Update the `ca` attribute value for the provider. Enter the path to the certificate file that you imported in step 2. For example, `C:\csa_self_signed.crt`.
7. Update the `ca` attribute value for the `idmProvider`. Enter the path to the certificate file that you imported in step 2. For example, `C:\csa_self_signed.crt`.
8. Update the `pfx` attribute value. Enter the name of the PKCS#12 archive you created earlier. For example, `..\conf\mppkeystore_self_signed`.
9. Update the `passphrase` attribute value. Enter the encrypted password used to access the `.mppkeystore_self_signed` archive (see ["Encrypt a Marketplace Portal Password" on page 114](#) for instructions on encrypting Marketplace Portal passwords). An encrypted password is preceded by `ENC` without any separating spaces and is enclosed in parentheses.
10. Save and exit the file.

Step 5: Configure the Web Server

1. Open %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml in a text editor.
2. Locate the following entry:

```
<ssl name="ssl" key-alias="CSA" certificate-key-file=
"%CSA_HOME%\jboss-as\standalone\configuration\
.keystore" verify-client="false"/>
```

3. Add a new attribute named password with a value that corresponds to the password you selected for the keystore, change the name of the key-alias to the alias you used in step 2, and change the name of the certificate-key-file to the keystore you used in step 2.

```
<ssl name="ssl" key-alias="csa_self_signed"
certificate-key-file="%CSA_HOME%\jboss-as\standalone\
configuration\.keystore_self_signed" password="keystorePassword" verify-
client="false"/>
```

Note: This example stores the password in clear text. If you want to use an encrypted password, follow the instructions at <https://community.jboss.org/wiki/JBossAS7SecuringPasswords> to create a password vault for JBoss.

Note: If you are using the vault scripts, verify that the %JAVA_HOME% environment variable has been defined, verify that %JAVA_HOME% has been set to the directory in which the JRE that is used by HP CSA is installed, and, if the directory path name includes a space, that the value has been enclosed in quotations marks. For example, to set %JAVA_HOME% to a directory path name that includes a space, from a command prompt, type
set JAVA_HOME="C:\Program Files\Hewlett-Packard\CSA\jre"

To verify that %JAVA_HOME% has been defined, from a command prompt, type
echo %JAVA_HOME%.

The following is an example of an encrypted password attribute using the JBoss password vault:

```
password="${VAULT::<vault_block_example>::password::N2NhZDzOMtES0ZGE4MmEtX0}"
```

4. Restart the HP Cloud Service Automation service.

To restart HP CSA:

- a. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for

the `keystorePasswordFile` property in the
`%CSA_HOME%\jboss-as\standalone\deployments\csa.war\
WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

- b. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
 - c. Right-click on the HP Cloud Service Automation service and select **Restart**.
 - d. Right-click on the HP Marketplace Portal service and select **Restart**.
5. After the service has started, review the log files in
`%CSA_HOME%\jboss-as\standalone\log\` and verify that no TLS or keystore errors are present.

Step 6: Configure Client Browsers (Optional)

Because the self-signed certificate is not signed by a Certificate Authority, when accessing the Cloud Service Management Console, warning messages are displayed in the browser (these messages do not affect normal operations of HP CSA). To avoid these warning messages, import the `csa_self_signed.crt` file or add an exception.

- **Microsoft Internet Explorer and Chrome:** From Windows Explorer, double-click on the `csa_self_signed.crt` file to begin the import process. Install the certificate in the Trusted Root Certification Authorities store. For information on how to import the certificate, refer to the browser's online documentation.
- **Firefox:** Add an exception by opening the browser and navigating to `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which HP CSA is running. When the **This Connection is Untrusted** page opens, select **I Understand the Risks**, click the **Add Exception** button, verify the Server Location, and click **Confirm Security Exception**. For information on how to import the certificate, refer to the browser's online documentation.

Step 7: Test Secure Connections

To test the connection to the Cloud Service Management Console, on a client system, open a supported Web browser and navigate to `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system that was used when the certificate was created. If the client browser is configured to accept the self-signed certificate (that is, you have completed step 6) and the Web application opens without a certificate warning, then you have successfully configured HP CSA to use a self-signed certificate. If you did not complete step 6, verify that the only certificate

warning relates to the certificate not being issued by a trusted authority. If any other certificate warning is displayed, review steps 1-6 to be sure they were followed as documented.

Configure Secure Connections for LDAP

If the LDAP server requires a secure connection, follow these steps to import the LDAP server Certificate Authority's root certificate into the Java truststore of HP CSA. If necessary, contact your LDAP administrator to obtain the LDAP server certificate.

If the LDAP server does not require a secure connection, you can omit this task.

Note: If you have configured HP CSA to be compliant with FIPS 140-2, you must substitute the HP CSA server truststore (for example, `csa_server_truststore.p12`) for the Java truststore (`cacerts`) and substitute the HP CSA server truststore password for the Java truststore password (`changeit`) in the examples. See ["Create a New Keystore and Truststore for Secure Communication" on page 177](#) for more information about the HP CSA server truststore and password.

1. Open a command prompt and run the `keytool` utility with the following options to create a local trusted certificate entry for the LDAP server.

```
"<csa_jre>\bin\keytool" -importcert -trustcacerts -alias ldap  
-keystore "<csa_jre>\lib\security\cacerts"  
-file <c:\certfile_name.crt> -storepass changeit
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed and `<c:\certfile_name.crt>` is the path and name of the Certificate Authority's root certificate for the LDAP server. The file extension may be `.cer` rather than `.crt`. You can also use a different value for `-alias`.

2. At the prompt to import the certificate, type **Yes**.
3. Press **Enter**.
4. Restart HP CSA.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

Configure Secure Connections for SMTP

For each organization, if its SMTP server requires a secure connection, follow these steps to import the SMTP server Certificate Authority's root certificate into the Java truststore of HP CSA. If necessary, contact your SMTP server administrator to obtain the SMTP server certificate.

If the SMTP server does not require a secure connection, you can omit this task.

Note: If you have configured HP CSA to be compliant with FIPS 140-2, you must substitute the HP CSA server truststore (for example, `csa_server_truststore.p12`) for the Java truststore (`cacerts`) and substitute the HP CSA server truststore password for the Java truststore password (`changeit`) in the examples. See ["Create a New Keystore and Truststore for Secure Communication" on page 177](#) for more information about the HP CSA server truststore and password.

1. Open a command prompt and run the `keytool` utility with the following options to create a local trusted certificate entry for the SMTP server.

```
"<csa_jre>\bin\keytool" -importcert -trustcacerts -alias smtp  
-keystore "<csa_jre>\lib\security\cacerts"  
-file <c:\certfile_name.crt> -storepass changeit
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed and `<c:\certfile_name.crt>` is the path and name of the Certificate Authority's root certificate for the SMTP server. The file extension may be `.cer` rather than `.crt`. You can also use a different value for `-alias`.

2. At the prompt to import the certificate, type **Yes**.
3. Press **Enter**.
4. Restart HP CSA.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

Configure Secure Connections for an Oracle Database

If the Oracle database server requires a secure connection, complete the following steps (if the Oracle database does not require a secure connection, you can omit these steps):

Note: If you have configured HP CSA to be compliant with FIPS 140-2, you cannot configure a secure connection for the Oracle database. If you configure a secure connection for the Oracle database, you cannot configure HP CSA to be compliant with FIPS 140-2.

1. Complete one of the following tasks:
 - If you do not want to configure HP CSA to check the database DN, do the following:
 - i. Open `%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` in a text editor.
 - ii. Add the following to the Oracle datasource:

```
<connection-url>jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS_LIST=(ADDRESS=(PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521)))(CONNECT_DATA =(SERVICE_NAME = ORCL)))</connection-url>
```

where <host> is the name of the system on which the Oracle database server is installed.

- iii. Save and close the file.
- iv. Import the Oracle database server Certificate Authority's root certificate into the Java truststore of HP CSA.
 - A. Copy the Oracle database server Certificate Authority's root certificate to the HP CSA system. If necessary, contact your database administrator to obtain the Oracle database server certificate.
 - B. On the HP CSA system, open a command prompt and run the `keytool` utility with the following options to create a local trusted certificate entry for the Oracle database server.

```
"<csa_jre>\bin\keytool" -importcert -trustcacerts  
-alias oracledb  
-keystore "<csa_jre>\lib\security\cacerts"  
-file <c:\certfile_name.crt> -storepass changeit
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed and <c:\certfile_name.crt> is the path and name of the Certificate Authority's root certificate for the Oracle database server. The file extension may be .cer rather than .crt. You can also use a different value for -alias.

- C. At the prompt to import the certificate, type **Yes**.
- D. Press **Enter**.
- E. Restart HP CSA.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

- If you want to configure HP CSA to check the database DN, do the following:
 - i. Open %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml in a text editor.
 - ii. Add the following to the Oracle datasource:

```
<connection-url>jdbc:oracle:thin:@(DESCRIPTION =(ADDRESS_LIST = (ADDRESS = (PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521)))(CONNECT_DATA =
```



```
(SERVICE_NAME = ORCL))(SECURITY=(SSL_SERVER_CERT_
DN="CN=abc,OU=dbserver,O=xyz,L=Sunnyvale,ST=CA,C=US"))</connection-url>
```

where <host> is the name of the system on which the Oracle database server is installed and the values for SSL_SERVER_CERT_DN are for the DN of the Oracle database server.

- iii. Add the following to the system-properties element:

```
<property name="oracle.net.ssl_server_dn_match" value="true" />
```

- iv. Save and close the file.

- v. Import the Oracle database server Certificate Authority's root certificate into the Java truststore of HP CSA.

- A. Copy the Oracle database server Certificate Authority's root certificate to the HP CSA system. If necessary, contact your database administrator to obtain the Oracle database server certificate.
- B. On the HP CSA system, open a command prompt and run the `keytool` utility with the following options to create a local trusted certificate entry for the Oracle database server.

```
"<csa_jre>\bin\keytool" -importcert -trustcacerts
-alias oracledb
-keystore "<csa_jre>\lib\security\cacerts"
-file <c:\certfile_name.crt> -storepass changeit
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed and <c:\certfile_name.crt> is the path and name of the Certificate Authority's root certificate for the Oracle database server. The file extension may be .cer rather than .crt. You can also use a different value for -alias.

- C. At the prompt to import the certificate, type **Yes**.
- D. Press **Enter**.
- E. Restart HP CSA.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

2. If client authentication is enabled on the Oracle database server, do the following:

- a. Open %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml in a text editor.
- b. Add the following to the system-properties element:

```
<property name="javax.net.ssl.keyStore" value="<certificate_key_file>" />
<property name="javax.net.ssl.keyStorePassword" value="<certificate_key_
file_password>" />
<property name="javax.net.ssl.keyStoreType" value="<certificate_key_file_
type>" />
```

where <certificate_key_file> is the same keystore file defined by the certificate-key-file attribute in the ssl element (for example, %CSA_HOME%\jboss-as\standalone\configuration\ .keystore), <certificate_key_file_password> is the password to the keystore file (for example, changeit), and <certificate_key_file_type> is the keystore type (for example, JKS or PKCS12).

- c. Save and close the file.
- d. Use Oracle's wallet manager to import HP CSA's certificate into the Oracle database server's wallet as a trusted certificate.

Configure Secure Connections for Microsoft SQL Server

If Microsoft SQL Server requires a secure connection, complete the following steps (if Microsoft SQL Server does not require a secure connection, you can omit these steps):

1. Open %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml in a text editor.
2. Locate the connection-url entry for the Microsoft SQL Server datasource and change ssl=request to ssl=authenticate.

For example:

```
<connection-url>
  jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=requestauthenticate
</connection-url>
```

3. Save and close the file.
4. Import the Microsoft SQL Server Certificate Authority's root certificate into the Java truststore of HP CSA.
 - a. Copy the Microsoft SQL Server Certificate Authority's root certificate to the HP CSA system. If necessary, contact your database administrator to obtain the Microsoft SQL Server certificate.
 - b. On the HP CSA system, open a command prompt and run the keytool utility with the following options to create a local trusted certificate entry for the Microsoft SQL Server.

```
"<csa_jre>\bin\keytool" -importcert -trustcacerts  
-alias mssqldb -keystore "<csa_jre>\lib\security\cacerts"  
-file <c:\certfile_name.crt> -storepass changeit
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed and `<c:\certfile_name.crt>` is the path and name of the Certificate Authority's root certificate for the Microsoft SQL Server. The file extension may be `.cer` rather than `.crt`. You can also use a different value for `-alias`.

- c. At the prompt to import the certificate, type **Yes**.
- d. Press **Enter**.
- e. Restart HP CSA.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

Configure Secure Connections for HP Operations Orchestration Load Balancer

If the HP Operations Orchestration Load Balancer (HP OO LB) server requires a secure connection, follow these steps to import the HP OO LB server Certificate Authority's root certificate into the Java truststore of HP Cloud Service Automation. If necessary, contact your HP OO LB administrator to obtain the HP OO LB server certificate.

Note: If you have configured HP CSA to be compliant with FIPS 140-2, you must substitute the HP CSA server truststore (for example, `csa_server_truststore.p12`) for the Java truststore (`cacerts`) and substitute the HP CSA server truststore password for the Java truststore password (`changeit`) in the examples. See ["Create a New Keystore and Truststore for Secure Communication" on page 177](#) for more information about the HP CSA server truststore and password.

For each system running HP CSA, import the root certificate of HP OO LB's Certificate Authority into HP Cloud Service Automation (you must first export HP OO LB's certificate from HP OO LB's truststore and then import it into HP CSA's truststore).

1. Open HP OO LB in a Web browser (using `https`).
2. Export the certificate from the Web browser.

If you are using a Chrome Web browser, do the following:

- a. In the address bar, click the lock icon with the red X over it and select **certificate information**.

- b. In the Certificate dialog, do the following:
 - i. Select the **Details** tab.
 - ii. Click **Copy to File**.
 - iii. In the Certificate Export Wizard, do the following:
 - A. Click **Next**.
 - B. Select **Base-64 encoded X.509 (.CER)** and click **Next**.
 - C. Click **Browse** and select a directory in which to save the certificate.
 - If you are running HP OO LB on the same system as HP CSA, select the `<csa_jre>\lib\security` directory (where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed), enter **paslb.cer** as the file name, and click **Save**.
 - If you are running HP OO LB on a system that is not running HP CSA, select a directory in which to store the certificate file, enter **paslb.cer** as the file name, and click **Save**.
 - D. Click **Next**.
 - E. Click **Finish**.
 - F. Click **OK**.
 - iv. Click **OK**.

If you are using a Firefox Web browser, do the following:

- a. Click **Add Exception**.
- b. In the Add Security Exception dialog, click **View**.
- c. In the Certificate Viewer, do the following:
 - i. Select the **Details** tab.
 - ii. Click **Export**.
 - iii. Select a directory in which to save the certificate.
 - If you are running HP OO LB on the same system as HP CSA, select the `<csa_jre>\lib\security` directory (where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed), enter **paslb.cer** as the file name, select **X.509 Certificate (PEM)** as the Type, and click **Save**.
 - If you are running HP OO LB on a system that is not running HP CSA, select a directory in which to store the certificate file, enter **paslb.cer** as the file name, select **X.509 Certificate (PEM)** as the Type, and click **Save**.
 - iv. Click **Close**.

- d. Click **Cancel**.

If you are using a Windows IE Web browser, do the following:

- a. In the address bar, click **Certificate Error** and select **View certificates**.
- b. In the Certificate Export Wizard, do the following:
 - i. Select the **Details** tab.
 - ii. Click **Copy to File**.
 - iii. In the Certificate Export Wizard, do the following:
 - A. Click **Next**.
 - B. Select **Base-64 encoded X.509 (.CER)** and click **Next**.
 - C. Click **Browse** and select a directory in which to save the certificate.
 - If you are running HP OO LB on the same system as HP CSA, select the `<csa_jre>\lib\security` directory (where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed), enter **paslb.cer** as the file name, and click **Save**.
 - If you are running HP OO LB on a system that is not running HP CSA, select a directory in which to store the certificate file, enter **paslb.cer** as the file name, and click **Save**.
 - D. Click **Next**.
 - E. Click **Finish**.
 - F. Click **OK**.
 - iv. Click **OK**.
3. If you are running HP OO LB on a system that is not running HP CSA, copy the `paslb.cer` file to the `<csa_jre>\lib\security` directory on the system running HP CSA (where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed).
4. On the system running HP CSA, open a command prompt and run the following commands:

```
cd "<csa_jre>\lib\security"  
  
..\..\bin\keytool -importcert -alias paslb -file paslb.cer  
-keystore cacerts -storepass changeit
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.
5. When prompted to trust the certificate, enter `yes`.

Chapter 4: HP Operations Orchestration

The HP CSA solution includes a number of HP Operations Orchestration flows that perform HP CSA operations.

Note: If you followed the instructions in the *HP Cloud Service Automation Installation Guide* or *HP Cloud Service Automation Upgrade Guide* to configure HP Operations Orchestration, you should have already completed the tasks in this section to configure HP Operations Orchestration.

In this release, you can install HP Operations Orchestration with HP CSA using the HP CSA installer or you can install HP Operations Orchestration externally. Only one instance of HP Operations Orchestration is required for both topology and sequential designs. If you have upgraded from an earlier version of HP CSA, you may have configured multiple instances of HP Operations Orchestration for sequential designs. If you have upgraded from an earlier version of HP CSA that uses multiple instances of HP Operations Orchestration for sequential designs, you can continue to use the multiple instances of HP Operations Orchestration for sequential designs. If you have upgraded from an earlier version of HP CSA that uses only a single instance of HP Operations Orchestration or are installing HP CSA for the first time, only one configured instance of HP Operations Orchestration is supported.

This chapter describes the following tasks:

- ["Configure HP Operations Orchestration for Topology Designs" below](#)
- ["Configure HP Operations Orchestration for Sequential Designs" on page 54](#)

Configure HP Operations Orchestration for Topology Designs

The following tasks are to configure HP Operations Orchestration for topology designs. Configure only one instance of HP Operations Orchestration for topology designs.

Note: If you followed the instructions in the *HP Cloud Service Automation Installation Guide* or *HP Cloud Service Automation Upgrade Guide* to configure HP Operations Orchestration, you should have already completed the tasks in this section to configure HP Operations Orchestration.

Complete the following tasks to configure HP Operations Orchestration to integrate with HP CSA:

- Configure an internal user
- Deploy content packs required by HP CSA
- Configure HP Single Sign-On

- Configure properties in HP CSA
- Configure a secure connection between HP CSA and HP Operations Orchestration
- Run the component tool

Note: In the following instructions, %CSA_HOME% is the directory in which HP Cloud Service Automation is installed and %ICONCLUDE_HOME% or \$ICONCLUDE_HOME is where you installed HP Operations Orchestration.

Be sure all the latest patches for HP Operations Orchestration have been installed. See the *HP Cloud Service Automation System and Software Support Matrix* for more information, available on the HP Software Support Web site at <http://h20230.www2.hp.com/selfsolve/manuals/> (this site requires that you register with HP Passport).

Configure an Internal User

Internal users can be used to configure HP Operations Orchestration for HP CSA.

This user is used for provisioning topology designs.

1. Log in to HP Operations Orchestration Central.
2. Click the **System Configuration** button.
3. Select **Security > Internal Users**.
4. Click the **Add** button.
5. Enter the following information:

Field	Recommended Value
User Name	admin
Password	cloud
Roles	ADMINISTRATOR, SYSTEM_ADMIN

The admin user is used with HP Single Sign-On (HP SSO). When HP Operations Orchestration is launched from the Cloud Service Management Console, this user allows access to HP Operations Orchestration without having to log in. If you are using topology designs, the admin user can also be used for provisioning topology designs.

6. Click **Save**.

7. Enable authentication by selecting the **Enable Authentication** check box.
8. Select **OK** in the confirmation dialog.

Deploy Content Packs

1. From HP Operations Orchestration Central, click the **Content Management** button.
2. Click the **Content Packs** tab.
3. Click the **Deploy New Content** icon.
4. In the Deploy New Content dialog, click the **Add files for deployment** icon.
5. Click the **Deploy New Content** icon.
6. Click the **Add files for deployment** icon.
7. Navigate to the %CSA_HOME%\Tools\ComponentTool\contentpacks\ directory, select all the content packs, and click **Open**.
8. Click **Deploy**.

The deployment may take a few minutes and the dialog will show a progress bar.

9. When the deployment succeeds, click **Close** to close the dialog.

Configure HP Single Sign-On Between HP CSA and HP Operations Orchestration

If HP Single Sign-On (HP SSO) was enabled during installation of HP CSA, HP SSO can be configured between HP CSA and HP Operations Orchestration. Configuring HP SSO allows you to launch HP Operations Orchestration from the Cloud Service Management Console without having to log in to HP Operations Orchestration.

HP CSA provides an out-of-the-box user (admin) and password (cloud) and, earlier in this guide, you configured an internal user for HP Operations Orchestration with the same username and password. When HP Single Sign-On is configured between HP CSA and HP Operations Orchestration, this user can be used for single sign-on. That is, if you are logged in to HP CSA as the admin user, you can launch HP Operations Orchestration from the Cloud Service Management Console and not have to log in to HP Operations Orchestration.

You can also configure LDAP users for single sign-on. In order to enable single sign-on for LDAP users, you must either configure HP CSA and the embedded HP Operations Orchestration to use the same LDAP source or, if HP CSA and the embedded HP Operations Orchestration use different LDAP sources, configure the same users in both sources. In either case, the HP CSA user must be assigned

to the CSA Administrator or Service Operations Manager role and the embedded HP Operations Orchestration user must be assigned any role that allows flows to be viewed.

Note: In order to use HP SSO between HP CSA and HP Operations Orchestration, the systems on which HP CSA and HP Operations Orchestration are installed must be in the same domain.

Configure and Enable HP Single Sign-On

To configure and enable HP SSO on HP Operations Orchestration, do the following:

1. Log in to HP Operations Orchestration Central.
2. Click the **System Configuration** button.
3. Select **Security > SSO**.
4. Select the **Enable** checkbox.
5. Enter the **InitString**. This is the value to which the `crypto InitString` attribute is set in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\hpssoConfiguration.xml` file. For example, if the entry in the file is `crypto InitString="10JisF9S1bf79hmLsd"`, copy `10JisF9S1bf79hmLsd` to this field. This string is used to encrypt and decrypt the `LWSSO_COOKIE_KEY` cookie that is used to authenticate the user for single sign-on.
6. Enter the **Domain**. This is the domain name of the network of the servers on which HP CSA and HP Operations Orchestration are installed.
7. Click **Save**.

Configure LDAP Users for Single Sign-On

In order to enable single sign-on for LDAP users, you must either configure HP CSA and HP Operations Orchestration to use the same LDAP source or, if HP CSA and HP Operations Orchestration use different LDAP sources, configure the same users in both sources. In either case, the HP CSA user must be assigned to the CSA Administrator or Service Operations Manager role and the HP Operations Orchestration user must be assigned any role that allows flows to be viewed.

To configure LDAP for HP Operations Orchestration, do the following:

1. Log in to HP Operations Orchestration Central.
2. Click the **System Configuration** button.
3. Select **Security > LDAP**.
4. Enter the information to configure LDAP.
5. Click **Save**.

Configure HP Operations Orchestration Properties in the csa.properties File

If you integrated with HP Operations Orchestration using the installer (during the installation or upgrade process), you do not need to configure these properties (they are already configured). These properties are used to integrate with HP Operations Orchestration. In the subscription event overview section of the **Operations** area in the Cloud Service Management Console, selecting the Process ID opens HP Operations Orchestration to the detailed page of the selected process when these properties are configured.

Edit the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties file and configure the following properties:

Property	Description
OOS_URL	<p>The URL used to access HP Operations Orchestration Central. This is the HP Operations Orchestration used for provisioning topology designs (HP Operations Orchestration version 10.20).</p> <p>Set this URL to the system on which HP Operations Orchestration version 10.20 is installed. For example, <code>https://<hostname>:8443</code>.</p>
OOS_USERNAME	<p>The username used to log in to HP Operations Orchestration Central.</p> <p>Set this username to admin.</p>
OOS_PASSWORD	<p>The encrypted password used by the user defined in OOS_USERNAME to log in to HP Operations Orchestration Central.</p> <p>Set this property to the encrypted value of the user defined in OOS_USERNAME (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p>

Configure a Secure Connection Between HP CSA and HP Operations Orchestration

If you integrated with HP Operations Orchestration using the installer (during the installation or upgrade process), you do not need to configure a secure connection (it has already been configured).

Run the Component Tool

The component tool imports the HP Operations Orchestration flows from the content packs installed with HP CSA (used only with HP Operations Orchestration version 10.20). To run the component tool, do the following:

1. Open a command prompt and change the directory to %CSA_HOME%\Tools\ComponentTool.
2. Generate the sample database properties files. Run the following command:

```
"<csa_jre>\bin\java" -jar component-tool.jar -g
```

3. Make a copy of the appropriate sample database properties file, rename it to config.properties, and update the content, as needed.

Property Name	Description
jdbc.driverClassName	<p>The JDBC driver class.</p> <p>Example</p> <p>Oracle: jdbc.driverClassName=oracle.jdbc.driver.OracleDriver MS SQL: jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver PostgreSQL: jdbc.driverClassName=org.postgresql.Driver</p>
jdbc.dialect	<p>The classname that allows JDBC to generate optimized SQL for a particular database.</p> <p>Example</p> <p>Oracle: jdbc.dialect=org.hibernate.dialect.OracleDialect MS SQL: jdbc.dialect=org.hibernate.dialect.SQLServerDialect PostgreSQL: jdbc.dialect=org.hibernate.dialect.PostgreSQLDialect</p>

Property Name	Description
jdbc. database Url	<p>The JDBC URL. When specifying an IPv6 address, it must be enclosed in square brackets (see example below).</p> <p>Example</p> <p>Oracle, TLS not enabled <code>jdbc.databaseUrl=jdbc:oracle:thin:@127.0.0.1:1521:XE</code></p> <p>Oracle, TLS not enabled, using an IPv6 address <code>jdbc.databaseUrl=jdbc:oracle:thin:@[f000:253c::9c10:b4b4]:1521:XE</code></p> <p>Oracle, TLS enabled, HP CSA does not check the database DN <code>jdbc.databaseUrl=jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS_LIST=(ADDRESS=(PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA =(SERVICE_NAME = ORCL)))</code> where <host> is the name of the system on which the Oracle database server is installed.</p> <p>Oracle, TLS enabled, HP CSA checks the database DN <code>jdbc.databaseUrl=jdbc:oracle:thin:@(DESCRIPTION =(ADDRESS_LIST = (ADDRESS = (PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA = (SERVICE_NAME = ORCL))(SECURITY=(SSL_SERVER_CERT_DN="CN=abc,OU=dbserver,O=xyz,L=Sunnyvale,ST=CA,C=US")))</code> where <host> is the name of the system on which the Oracle database server is installed and the values for SSL_SERVER_CERT_DN are for the DN of the Oracle database server.</p> <p>MS SQL, TLS not enabled <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request</code></p> <p>MS SQL, TLS not enabled, using an IPv6 address <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://[::1]:1433/example;ssl=request</code></p> <p>MS SQL, TLS enabled <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate</code></p> <p>MS SQL, FIPS 140-2 compliant <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate</code></p>

Property Name	Description
	PostgreSQL <code>jdbc.databaseUrl=jdbc:postgresql://127.0.0.1:5432/csadb</code>
<code>jdbc.username</code>	The user name of the database user you configured for HP CSA after installing the database.
<code>jdbc.password</code>	The password for the database user. The password should be encrypted (see the <i>HP Cloud Service Automation Configuration Guide</i> for instructions on encrypting passwords). If you have configured HP CSA to be FIPS 140-2 compliant, encrypt this password after you have configured CSA to be FIPS 140-2 compliant (that is, you should use the updated encryption tools to encrypt the password). Example <code>jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)</code>

Example config.properties content

Oracle, TLS not enabled

```
jdbc.driverClassName=oracle.jdbc.driver.OracleDriver
jdbc.dialect=org.hibernate.dialect.OracleDialect
jdbc.databaseUrl=jdbc:oracle:thin:@127.0.0.1:1521:XE
jdbc.username=csa
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

MS SQL, TLS not enabled

```
jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver
jdbc.dialect=org.hibernate.dialect.SQLServerDialect
jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request
jdbc.username=csa
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

MS SQL, TLS enabled

```
jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver
jdbc.dialect=org.hibernate.dialect.SQLServerDialect
jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate
jdbc.username=csa
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

MS SQL (FIPS 140-2 compliant)

```
jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver
jdbc.dialect=org.hibernate.dialect.SQLServerDialect
jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/
```

```
example;ssl=authenticate  
jdbc.username=csa  
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

PostgreSQL

```
jdbc.driverClassName=org.postgresql.Driver  
jdbc.dialect=org.hibernate.dialect.PostgreSQLDialect  
jdbc.databaseUrl=jdbc:postgresql://127.0.0.1:5432/csadb  
jdbc.username=csadbuser  
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

4. Run the component tool:

Oracle

```
"<csa_jre>\bin\java" -jar component-tool.jar -c config.properties  
-cp contentpacks -m mappingFiles -me metainfo.txt -j <jdbc_driver_  
directory>\ojdbc.jar
```

MS SQL and PostgreSQL

```
"<csa_jre>\bin\java" -jar component-tool.jar -c config.properties  
-cp contentpacks -m mappingFiles -me metainfo.txt
```

Note: Do not edit the `metainfo.txt` file or the `contentpacks` and `mappingFiles` directories.

Configure HP Operations Orchestration for Sequential Designs

The following tasks are to configure HP Operations Orchestration for sequential designs. If you are installing HP CSA for the first time, configure only one instance of HP Operations Orchestration. If you have upgraded from an earlier version of HP CSA that has multiple instances of HP Operations Orchestration configured for sequential designs, you can continue to use multiple instances of HP Operations Orchestration, including HP Operations Orchestration 9.07.

Note: If you followed the instructions in the *HP Cloud Service Automation Installation Guide* or *HP Cloud Service Automation Upgrade Guide* to configure HP Operations Orchestration, you should have already completed the tasks in this section to configure HP Operations Orchestration.

Configure HP Operations Orchestration Version 10.20

Complete the following tasks to configure HP Operations Orchestration to integrate with HP CSA:

- Add a JRE to the system path
- Install the HP CSA content pack
- Configure internal users
- Deploy content packs required by HP CSA
- Set up system accounts for the HP CSA content pack
- Set up system properties
- Configure HP Single Sign-On
- Configure a secure connection between HP Cloud Service Automation and HP Operations Orchestration
- Import HP Operations Orchestration flows

Note: In the following instructions, %CSA_HOME% is the directory in which HP Cloud Service Automation is installed and %ICONCLUDE_HOME% or \$ICONCLUDE_HOME is where you installed HP Operations Orchestration.

Be sure all the latest patches for HP Operations Orchestration have been installed. See the *HP Cloud Service Automation System and Software Support Matrix* for more information, available on the HP Software Support Web site at <http://h20230.www2.hp.com/selfsolve/manuals/> (this site requires that you register with HP Passport).

Add a JRE to the System Path

The HP CSA flows that are imported require that a JRE be included in the system path on the system running HP CSA.

1. Open the **Environment Variables** dialog:
 - a. Right-click **Computer** and select **Properties**.
 - b. Select **Advanced System Settings**.
 - c. Click **Environment Variables**.
2. Select the **Path** system variable.
3. Click **Edit**.
4. At the end of the value for **Variable value**, add a semicolon (;) and the following path:

If HP Operations Orchestration and HP CSA are installed on the same system:

```
%ICONCLUDE_HOME%\java\bin
```

or

If HP Operations Orchestration and HP CSA are installed on different systems:

```
<csa_jre>\bin
```

5. Click **OK** and close all windows.

Note: By setting the system path, all applications (that require a JRE) use the JRE that is installed with HP Operations Orchestration or HP CSA (depending on the path you configured and if it is the only path or the first path set to a JRE in the system path). If you need to run another JRE with an application, you must type in the relative path to that JRE in order to run it (for example, when you configure TLS).

Install the HP CSA Content Pack

- Copy the %CSA_HOME%\CSAKit-4.2\00 Flow Content\10X\oo10-csa-cp-4.20.000-uuids.txt file to:

Windows

```
%ICONCLUDE_HOME%\central\cmu\exclusions
```

Linux

```
$ICONCLUDE_HOME/central/cmu/exclusions
```

- If HP CSA and HP Operations Orchestration are running on different systems, copy the %CSA_HOME%\CSAKit-4.2\00 Flow Content\10X\oo10-csa-cp-4.20.000.jar file from the HP Cloud Service Automation system to the HP Operations Orchestration system (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed).

Configure Internal Users

Internal users can be used to configure HP Operations Orchestration for HP CSA.

1. Log in to HP Operations Orchestration Central.
2. Click the **System Configuration** button.
3. Select **Security > Internal Users**.
4. Click the **Add** button.
5. Enter the following information:

Field	Recommended Value
User Name	csaouser
Password	cloud
Roles	ADMINISTRATOR, SYSTEM_ADMIN

The csaouser user is used to import the HP Operations Orchestration flows. When importing flows, this user is configured in the HP Operations Orchestration input file used by the process definition tool.

6. Click **Save**.
7. Enable authentication by selecting the **Enable Authentication** check box.
8. Select **OK** in the confirmation dialog.
9. Click the **Add** button.
10. Enter the following information:

Field	Recommended Value
User Name	admin
Password	cloud
Roles	ADMINISTRATOR, SYSTEM_ADMIN

The admin user is used with HP Single Sign-On (HP SSO). When HP Operations Orchestration is launched from the Cloud Service Management Console, this user allows access to HP Operations Orchestration without having to log in. If you are using topology designs, the admin user can also be used for provisioning topology designs.

11. Click **Save**.
12. Enable authentication by selecting the **Enable Authentication** check box.
13. Select **OK** in the confirmation dialog.
14. Log out of HP Operations Orchestration Central and log back in as the csaouser.

Deploy Content Packs Required by HP CSA

1. From HP Operations Orchestration Central, click the **Content Management** button.
2. Click the **Content Packs** tab.
3. Click the **Deploy New Content** icon.

4. In the Deploy New Content dialog, click the **Add files for deployment** icon.
5. Click the **Deploy New Content** icon.
6. Click the **Add files for deployment** icon.
7. Navigate to the %CSA_HOME%\CSAKit-4.2\OO Flow Content\10X directory, select the oo10-csa-cp-4.20.0000 content pack, and click **Open**.
8. Click **Deploy**.

The deployment may take a few minutes and the dialog will show a progress bar.

9. When the deployment succeeds, click **Close** to close the dialog.

Set Up System Accounts for the HP CSA Content Pack

Set up system accounts for the HP CSA content pack:

1. Log in to HP Operations Orchestration Central.
2. Click the **Content Management** button.
3. Select **Configuration Items > System Accounts**.
4. Click the **Add** icon.
5. Enter the following information if it is not already configured:

Field	Recommended Value
System Account Name	CSA_REST_CREDENTIALS
User Name	oolnboundUser
Password	cloud

Note: The **User Name** configured for the CSA_REST_CREDENTIALS System Account setting must match the **Property Value** (HP Operations Orchestration version 9.07) or **Override Value** (HP Operations Orchestration version 10.20) configured for the CSA_OO_USER System Property setting.

6. Click **Save**.
7. Click the **Add** icon.

8. Enter the following information if it is not already configured:

Field	Recommended Value
System Account Name	CSA_SERVICEMANAGER_CREDENTIALS
User Name	falcon
Password	<leave_blank>

9. Click **Save**.

Set Up System Properties for the HP CSA Content Pack

Set up the following system properties for the HP CSA content pack:

1. Log in to HP Operations Orchestration Central.
2. Click the **Content Management** button.
3. Select **Configuration Items > System Properties**.
4. Click the **Add** icon.
5. Enter the following information if it is not already configured:

Field	Recommended Value
Name	CSA_REST_URI
Override Value	https://<csa_hostname>:8444/csa/rest

6. Click **Save**.

Configure HP Single Sign-On Between HP CSA and HP Operations Orchestration

If HP Single Sign-On (HP SSO) was enabled during installation of HP CSA, HP SSO can be configured between HP CSA and HP Operations Orchestration. Configuring HP SSO allows you to launch HP Operations Orchestration from the Cloud Service Management Console without having to log in to HP Operations Orchestration.

HP CSA provides an out-of-the-box user (admin) and password (cloud) and, earlier in this guide, you configured an internal user for HP Operations Orchestration with the same username and password. When HP Single Sign-On is configured between HP CSA and HP Operations Orchestration, this user can be used for single sign-on. That is, if you are logged in to HP CSA as the admin user, you can launch HP Operations Orchestration from the Cloud Service Management Console and not have to log in to HP Operations Orchestration.

You can also configure LDAP users for single sign-on. In order to enable single sign-on for LDAP users, you must either configure HP CSA and the embedded HP Operations Orchestration to use the same LDAP source or, if HP CSA and the embedded HP Operations Orchestration use different LDAP sources, configure the same users in both sources. In either case, the HP CSA user must be assigned to the CSA Administrator or Service Operations Manager role and the embedded HP Operations Orchestration user must be assigned any role that allows flows to be viewed.

Note: In order to use HP SSO between HP CSA and HP Operations Orchestration, the systems on which HP CSA and HP Operations Orchestration are installed must be in the same domain.

Configure and Enable HP Single Sign-On

To configure and enable HP SSO on HP Operations Orchestration, do the following:

1. Log in to HP Operations Orchestration Central.
2. Click the **System Configuration** button.
3. Select **Security > SSO**.
4. Select the **Enable** checkbox.
5. Enter the **InitString**. This is the value to which the `crypto InitString` attribute is set in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\hpssoConfiguration.xml` file. For example, if the entry in the file is `crypto InitString="10JisF9S1bf79hmLsd"`, copy `10JisF9S1bf79hmLsd` to this field. This string is used to encrypt and decrypt the `LWSSO_COOKIE_KEY` cookie that is used to authenticate the user for single sign-on.
6. Enter the **Domain**. This is the domain name of the network of the servers on which HP CSA and HP Operations Orchestration are installed.
7. Click **Save**.

Configure LDAP Users for Single Sign-On

In order to enable single sign-on for LDAP users, you must either configure HP CSA and HP Operations Orchestration to use the same LDAP source or, if HP CSA and HP Operations Orchestration use different LDAP sources, configure the same users in both sources. In either case, the HP CSA user must be assigned to the CSA Administrator or Service Operations Manager role and the HP Operations Orchestration user must be assigned any role that allows flows to be viewed.

To configure LDAP for HP Operations Orchestration, do the following:

1. Log in to HP Operations Orchestration Central.
2. Click the **System Configuration** button.

3. Select **Security > LDAP**.
4. Enter the information to configure LDAP.
5. Click **Save**.

Configure a Secure Connection Between HP Cloud Service Automation and HP Operations Orchestration

If you integrated with HP Operations Orchestration using the installer (during the installation or upgrade process), you do not need to configure a secure connection (it has already been configured).

Import HP Operations Orchestration Flows

See "[Import HP Operations Orchestration Flows](#)" on page 67 for more information.

Configure HP Operations Orchestration Version 9.07

Only if you have upgraded from an earlier version of HP CSA that uses HP Operations Orchestration 9.07 for sequential designs, you can continue to use HP Operations Orchestration 9.07. For a new installation of HP CSA, HP Operations Orchestration 9.07 is not supported.

Complete the following tasks to configure HP Operations Orchestration to integrate with HP CSA:

- Add a JRE to the system path
- Install HP CSA flows
- Set remote action services
- Configure system accounts settings
- Configure system properties settings
- Configure general system configuration settings in HP Operations Orchestration Central
- Configure a secure connection between HP CSA and HP Operations Orchestration
- Check RAS timeout settings (optional)
- Change HP Operations Orchestration REST API timeout (optional)
- Import HP Operations Orchestration flows

Note: In the following instructions, `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed and `%ICONCLUDE_HOME%` or `$ICONCLUDE_HOME` is where you installed HP

Operations Orchestration.

Be sure all the latest patches for HP Operations Orchestration have been installed. See the *HP Cloud Service Automation System and Software Support Matrix* for more information, available on the HP Software Support Web site at <http://h20230.www2.hp.com/selfsolve/manuals/> (this site requires that you register with HP Passport).

Add a JRE to the System Path

The HP CSA flows that are imported require that a JRE be included in the system path on the system running HP CSA.

1. Open the **Environment Variables** dialog:
 - a. Right-click **Computer** and select **Properties**.
 - b. Select **Advanced System Settings**.
 - c. Click **Environment Variables**.
2. Select the **Path** system variable.
3. Click **Edit**.
4. At the end of the value for **Variable value**, add a semicolon (;) and the following path:

If HP Operations Orchestration and HP CSA are installed on the same system:

```
%INCLUDE_HOME%\jre1.6\bin
```

or

If HP Operations Orchestration and HP CSA are installed on different systems:

```
<csa_jre>\bin
```

5. Click **OK** and close all windows.

Note: By setting the system path, all applications (that require a JRE) use the JRE that is installed with HP Operations Orchestration or HP CSA (depending on the path you configured and if it is the only path or the first path set to a JRE in the system path). If you need to run another JRE with an application, you must type in the relative path to that JRE in order to run it (for example, when you configure TLS).

Install HP CSA Flows

The flows for HP Cloud Service Automation must be installed in the HP Operations Orchestration Flow Library.

To install HP Cloud Service Automation flows:

1. If HP Cloud Service Automation and HP Operations Orchestration are running on different systems, copy the %CSA_HOME%\CSAKit-4.2\OO Flow Content\9X\CSA-4_20-ContentInstaller.jar file from the HP Cloud Service Automation system to the HP Operations Orchestration system (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed).
2. On the system running HP Operations Orchestration, open a command prompt (Windows) or shell (Linux) and change to the directory where the CSA-4_20-ContentInstaller.jar is located.
3. Run the following command:

Windows

```
"%INCLUDE_HOME%\jre1.6\bin\java" -jar CSA-4_20-ContentInstaller.jar  
-centralPassword <OOAdminPassword>
```

Linux

```
$INCLUDE_HOME/jre1.6/bin/java -jar CSA-4_20-ContentInstaller.jar  
-centralPassword <OOAdminPassword>
```

Set Remote Action Services

1. Log in to HP Operations Orchestration Studio.
2. Open the **Configuration > Remote Action Services** folder.
3. Double-click **RAS_Operator_Path**.
4. Set the **URL** to:

```
https://<FQDN>:9004/RAS/services/RCAgentService
```

where <FQDN> is the fully qualified domain name or IP address of the HP Operations Orchestration host. Do not use localhost in the URL. Using localhost does not work correctly even though it appears to work when you run HP Operations Orchestration Studio on the same machine as the RAS.

RAS must be run on the same system as HP Operations Orchestration Studio. Running HP Operations Orchestration Studio on another machine produces errors and turns flows red with a cryptic error message about result assignments to result variables that do not exist.

Configure System Accounts Settings

1. Log in to HP Operations Orchestration Studio.
2. Open the **Configuration > System Accounts** folder.
3. Double-click **CSA_REST_CREDENTIALS**.

4. Verify the Credentials are set to the following values:

- **User Name:** oolInboundUser
- **Password:** cloud

where **CSA_REST_CREDENTIALS** are the credentials for HP CSA REST authentication.

Note: The **User Name** configured for the CSA_REST_CREDENTIALS System Account setting must match the **Property Value** (HP Operations Orchestration version 9.07) or **Override Value** (HP Operations Orchestration version 10.20) configured for the CSA_OO_USER System Property setting.

Configure System Properties Settings

1. Log in to HP Operations Orchestration Studio.
2. Open the **Configuration > System Properties** folder.
3. Double-click **CSA_REST_URI**.
4. Set the **Property Value** to:

`https://<csa_hostname>:8444/csa/rest`

5. Double-click **CSA_OO_USER**.
6. Verify the **Property Value** is set to:

oolInboundUser

Note: The **Property Value** (HP Operations Orchestration version 9.07) or **Override Value** (HP Operations Orchestration version 10.20) configured for the CSA_OO_USER System Property setting must match the **User Name** configured for the CSA_REST_CREDENTIALS System Account setting.

The other settings can be optionally configured. For information about the settings, refer to the *HP Cloud Service Automation Configuration Guide*.

Configure General System Configuration Settings in HP Operations Orchestration Central

1. Log in to HP Operations Orchestration Central.
2. Open the **Administration > System Configuration > General** tab.

3. Set the **Save history base on flags** property to true.

Configure a Secure Connection Between HP Cloud Service Automation and HP Operations Orchestration

For each system running HP CSA, import the root certificate of each HP Operations Orchestration's Certificate Authority.

Import HP Operations Orchestration's certificate into HP CSA

Import the root certificate of HP Operations Orchestration's Certificate Authority into HP Cloud Service Automation (you must first export HP Operations Orchestration's certificate from HP Operations Orchestration's truststore and then import it into HP CSA's truststore).

1. On the system running HP Operations Orchestration, open a command prompt and change the directory to %ICONCLUDE_HOME% (Windows) or \$ICONCLUDE_HOME (Linux).
2. Run the following command:

Windows

```
.\jre1.6\bin\keytool -exportcert -alias pas -file C:\oo.crt -  
keystore .\Central\conf\rc_keystore -storepass bran507025
```

Linux

```
./jre1.6/bin/keytool -exportcert -alias pas -file /tmp/oo.crt -  
keystore ./Central/conf/rc_keystore -storepass bran507025
```

where C:\oo.crt and /tmp/oo.crt are examples of filenames and locations used to store the exported root certificate (you can choose a different filename and location).

3. If HP Operations Orchestration is not running on the same system as HP Cloud Service Automation, copy oo.crt from the HP Operations Orchestration system to the system running HP Cloud Service Automation (in this example, the file is copied to C:\).
4. On the system running HP Cloud Service Automation, run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias pas -file C:\oo.crt -keystore <csa_  
jre>\lib\security\cacerts -storepass changeit
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

5. When prompted to trust the certificate, enter yes.
6. Restart the HP CSA services.

To restart HP CSA:

- a. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for

the `keystorePasswordFile` property in the
`%CSA_HOME%\jboss-as\standalone\deployments\csa.war\
WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA
encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore
password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

- b. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
- c. Right-click on the HP Cloud Service Automation service and select **Restart**.
- d. Right-click on the HP Marketplace Portal service and select **Restart**.

Check RAS Timeout Settings (Optional)

Remote Access Server (RAS) operations are subject to a default timeout limit of 20 minutes on HP Operations Orchestration Central. You can change the time-out setting to support operations that are likely to take more than 20 minutes to complete.

If you expect to run large deployments, change the time-out setting according to **Changing the timeout limit for RAS operations** in the *HP Operations Orchestration Software Administrator's Guide*. You may also refer to *HP Operations Orchestration User's Guide* sections **Adding a RAS override** and **Best practices for runtime environment overrides**. Both documents are available on the HP Software Support Web site at <http://h20230.www2.hp.com/selfsolve/manuals/> (this site requires that you register with HP Passport).

Change HP Operations Orchestration REST API Timeout (Optional)

The calls HP CSA makes to the HP Operations Orchestration REST APIs are synchronous, and HP Operations Orchestration will time-out the connection after one hour by default. To extend this time-out, do the following:

1. Open the following file in a text editor:

Windows

```
%INCLUDE_HOME%\Central\conf\Central.properties
```

Linux

```
$INCLUDE_HOME/Central/conf/Central.properties
```

2. Add the following lines:

```
# the maximum flow timeout value in milliseconds, this is equivalent to 2 hrs  
dharma.headless2.continuation.timeout=7200000
```

3. Open the following file in a text editor:

Windows

```
%ICONCLUDE_HOME%\Central\WEB-INF\applicationContext.xml
```

Linux

```
$ICONCLUDE_HOME/Central/WEB-INF/applicationContext.xml
```

4. Add the following property to the dharma.RCDefaults section:

```
<bean id="dharma.RCDefaults"  
class="com.iconclude.dharma.util.spring.RCDefaultsSpringFactory" lazy-  
init="false" singleton="true">  
  
.....  
  
<prop  
key="dharma.headless2.continuation.timeout">${dharma.headless2.continuation.tim  
eout}</prop>
```

5. Restart the HP Operations Orchestration Central service.

Import HP Operations Orchestration Flows

HP Operations Orchestration flows can be executed by HP Cloud Service Automation (HP CSA) lifecycle actions or used to submit delegated approvals. Before executing flows through HP CSA, they must be imported into HP CSA by running the process definition tool. The process definition tool creates an HP CSA process definition for every imported HP Operations Orchestration flow. The process definitions are associated with a process engine and that process engine corresponds to the HP Operations Orchestration system containing the imported flows.

To import flows, perform the following general steps, which are described in detail below:

- Install HP Cloud Service Automation flows in the HP Operations Orchestration Flow Library
- Create a database properties file
- Create an HP Operations Orchestration input file that defines the flows to be imported
- Run the process definition tool

Note: HP recommends that you generate sample database properties files and input file by doing the following:

1. Navigate to the %CSA_HOME%\Tools\ProcessDefinitionTool directory.
2. Run the following command:

```
"<csa_jre>\bin\java" -jar process-defn-tool.jar -g
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

Note: In this section, %CSA_HOME% is the directory in which HP Cloud Service Automation is installed.

Step 1: Install HP Cloud Service Automation flows in the HP Operations Orchestration Flow Library

Install HP Cloud Service Automation flows in the HP Operations Orchestration Flow Library (if you have not already done so when HP CSA was installed).

Step 2: Create a Database Properties File

To create a database properties file, do the following:

1. Navigate to the %CSA_HOME%\Tools\ProcessDefinitionTool directory.
2. In the working directory, if you generated the sample database properties files as recommended in the note, make a copy of the appropriate sample database properties file, rename it to db.properties, and update the content (described below) as needed. Otherwise, create a file named db.properties with the following content:

Property Name	Description
db.type	The database used by HP Cloud Service Automation. Examples Oracle: db.type=oracle MS SQL: db.type=mssql

Property Name	Description
db.url	<p>The JDBC URL. When specifying an IPv6 address, it must be enclosed in square brackets (see examples below).</p> <p>Examples</p> <p>Oracle (TLS not enabled): db.url=jdbc:oracle:thin:@127.0.0.1:1521:XE</p> <p>Oracle (TLS not enabled, using an IPv6 address): db.url=jdbc:oracle:thin:@[f000:253c::9c10:b4b4]:1521:XE</p> <p>Oracle (TLS enabled, HP CSA does not check the database DN): db.url=jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS_LIST=(ADDRESS=(PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA =(SERVICE_NAME = ORCL))) where <host> is the name of the system on which the Oracle database server is installed.</p> <p>Oracle (TLS enabled, HP CSA checks the database DN): db.url=jdbc:oracle:thin:@(DESCRIPTION =(ADDRESS_LIST = (ADDRESS = (PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA = (SERVICE_NAME = ORCL))(SECURITY=(SSL_SERVER_CERT_DN="CN=abc,OU=dbserver,O=xyz,L=Sunnyvale,ST=CA,C=US"))) where <host> is the name of the system on which the Oracle database server is installed and the values for SSL_SERVER_CERT_DN are for the DN of the Oracle database server.</p> <p>MS SQL (TLS not enabled): db.url=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request</p> <p>MS SQL (TLS not enabled, using an IPv6 address): db.url=jdbc:jtds:sqlserver://[::1]:1433/example;ssl=request</p> <p>MS SQL (TLS enabled): db.url=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate</p> <p>MS SQL (FIPS 140-2 compliant): db.url=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate</p>

Property Name	Description
db.user	The user name of the database user you configured for HP Cloud Service Automation after installing the database.
db.password	<p>The encrypted password for the database user (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>While you may enter a password in clear text, after you run the tool, the clear text password is automatically replaced by an encrypted password.</p> <p>If you have configured HP CSA to be compliant with FIPS 140-2, encrypt this password after you have configured CSA to be compliant with FIPS 140-2 (that is, you should use the updated encryption tools to encrypt the password).</p> <p>Example</p> <pre>db.password=ENC(fc5e38d38a5703285441e7fe7010b0)</pre>

Property Name	Description
<p>csaTruststore</p>	<p>Required if certificates are imported into a truststore that is not the standard JVM truststore (<code>cacerts</code>) or if FIPS 140-2 compliance mode is enabled and the database requires a secure connection. The truststore that stores trusted Certificate Authority certificates, in which the root certificate of the database's Certificate Authority has been imported.</p> <p>Example (if certificates are imported into a truststore that is not the standard JVM truststore)</p> <pre>truststore="<csa_jre>/lib/security/<truststore>"</pre> <p>where <code><csa_jre></code> is the directory in which the JRE that is used by HP CSA is installed.</p> <p>If you have configured HP CSA to be compliant with FIPS 140-2 and the database requires a secure connection, use the name of the HP CSA server truststore.</p> <p>Example (this example uses the same example name from the <i>Create an HP CSA Encryption Keystore</i> section):</p> <pre>%CSA_HOME%\jboss-as\standalone\configuration\csa_server_truststore.p12</pre>
<p>csaTruststorePassword</p>	<p>Required if certificates are imported into a truststore that is not the standard JVM truststore (<code>cacerts</code>) or if FIPS 140-2 compliance mode is enabled and the database requires a secure connection. The encrypted password of the truststore (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses.</p> <p>Example</p> <pre>truststorePassword=ENC(1fABFLAdgy2kAvSaDq9MSI9s=)</pre> <p>If you have configured HP CSA to be compliant with FIPS 140-2 and the database requires a secure connection, encrypt this password after you have configured CSA to be compliant with FIPS 140-2 (that is, you should use the updated encryption tools to encrypt the password). This is referred to as the <i><HP CSA server truststore password></i> in the <i>Create an HP CSA Encryption Keystore</i> section.</p>

Example db.properties content

Oracle (TLS not enabled)

```
db.type=oracle  
db.url=jdbc:oracle:thin:@127.0.0.1:1521:XE  
db.user=csa  
db.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

MS SQL (TLS not enabled)

```
db.type=mssql  
db.url=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request  
db.user=csa  
db.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

MS SQL (TLS enabled)

```
db.type=mssql  
db.url=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate  
db.user=csa  
db.password=ENC(fc5e38d38a5703285441e7fe7010b0)
```

If you have configured HP CSA to be compliant with FIPS 140-2, add the following content to `db.properties`:

Property Name	Description
<code>useExternalProvider</code>	<p>Required if enabling FIPS 140-2 compliance mode. To enable, set this property to true. To disable, set this property to false or comment it out.</p> <p>When enabled, HP CSA uses the RSA BSAFE libraries to encrypt and decrypt passwords. If a password was encrypted using different libraries (for example, if the password was encrypted before this property is enabled), the resulting decrypted password will not be valid.</p> <p>If you cannot connect to the database after you have configured HP CSA for FIPS 140-2 compliance, try re-encrypting the database password in the database properties file.</p>
<code>securityProviderName</code>	<p>Required if FIPS 140-2 compliance mode is enabled. The name of the FIPS 140-2 compliant provider. By default, HP CSA uses the RSA BSAFE provider and this property should be set to <code>JsafeJCE</code>.</p>

Property Name	Description
keystore	<p>Required if FIPS 140-2 compliance mode is enabled. The absolute path to and file name of the HP CSA encryption keystore. This is the keystore that supports PKCS #12 and stores the key used by HP CSA to encrypt and decrypt data in HP CSA.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/csa_encryption_keystore.p12</pre>
keyAlias	<p>Required if FIPS 140-2 compliance mode is enabled. The alias used to identify the HP CSA encryption key in the HP CSA encryption keystore.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>csa_encryption_key</pre>
keystorePasswordFile	<p>Required if FIPS 140-2 compliance mode is enabled. The absolute path to and file name of the HP CSA encryption keystore password. This is a temporary file that stores the HP CSA encryption keystore password in clear text. This file is required to start the HP CSA service and is automatically deleted when the service is started.</p> <p>The password file must contain only the following content:</p> <pre>keystorePassword=<HP CSA encryption keystore password></pre> <p>where <HP CSA encryption keystore password> is the HP CSA encryption keystore password in clear text.</p>
encryptedKeyFile	<p>Required if FIPS 140-2 compliance mode is enabled. The location of the HP CSA encrypted symmetric key.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/key.dat</pre>

Property Name	Description
keySize	<p>Optional. The key size used for HP CSA encryption. By default, the key size is 128. If you manually enter a different key size when encrypting a password, uncomment this property and configure the value to the key size used to encrypt the passwords.</p> <div style="border: 1px solid gray; padding: 5px; background-color: #f0f0f0;"> <p>Note: All passwords must be encrypted using the same key size.</p> <p>By default, the password encryption utility encrypts all passwords using a key size of 128 (even if you do not specify a key size when running the utility).</p> </div>

Example db.properties content (when HP CSA is configured to be compliant with FIPS 140-2)

```
db.type=mssql
db.url=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate
db.user=csa
db.password=ENC(fc5e38d38a5703285441e7fe7010b0)
csaTruststore="%CSA_HOME%\jboss-as\standalone\
    configuration\csa_server_truststore.p12"
csaTruststorePassword=ENC(1fABFLAdgy2kAvSaDq9MSI9s=)
useExternalProvider=true
securityProviderName=JsafeJCE
keystore=%CSA_HOME%\jboss-as\standalone\configuration\
    csa_encryption_keystore.p12
keyAlias=csa_encryption_key
keystorePasswordFile=C:\password.txt
encryptedKeyFile=%CSA_HOME%\jboss-as\standalone\
    configuration\key.dat
```

Step 3: Create an HP Operations Orchestration Input File

To create an HP Operations Orchestration input file, do the following:

In the working directory (%CSA_HOME%\Tools\ProcessDefinitionTool), if you generated the sample HP Operations Orchestration input file, make a copy of the HPO0InputSample.xml file, rename it to HPO0InfoInput.xml, and update the attributes and values, described below, as needed. The HPO0InfoInput.xml file is formatted as follows (attributes and values are described below):

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<ooengines>
  <ooengine name="<CSA_process_engine>"
    uri="https://<OO_server>:8443/PAS/services/WSCentralService"
    username="<OO_user>" password="<encrypted_password>"
```

```

truststore="<location_of_truststore>"
truststorePassword="<truststore_encrypted_password>"
[accessPointType="URL" | "EXTERNAL_APPROVAL" |
"RESOURCE_POOL_SYNC"]
[update="true" | "false"] [delete="true" | "false"] >
  <folder path="<path_name>" [flow="true" | "false"]
    [recursive="true" | "false"] [regex="<regular_expression>"]
    [update="true" | "false"] />
</oengine>
</ooengines>
    
```

where attributes define the flows that are imported and are described below:

Attributes of oengine

Attribute	Description
name	<p>Required. The name given to the HP CSA process engine that contains or will contain the imported flows. If the name does not exist, the process engine with the specified name is created in HP CSA. If the name exists, the contents of the existing process engine are updated based on the value of the folder's update attribute.</p> <p>Example name="oo-instance-1"</p>
uri	<p>Required. The URI of the HP Operations Orchestration Central server. In the URI, the <OO_server> can be localhost or the fully-qualified domain name if localhost or the fully-qualified domain name is configured as the cn in the HP Operations Orchestration server's certificate. The <oo_server> can also be the IP address if the Subject Alt Name attribute has been configured as the IP address in the HP Operations Orchestration server's certificate.</p> <p>The default port is 8443.</p> <div style="background-color: #f0f0f0; padding: 5px; margin: 10px 0;"> <p>Note: Use only forward slashes (/) as your path separators.</p> </div> <p>Examples</p> <pre> uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService" uri="https://localhost:8443/PAS/services/WSCentralService" uri="https://127.0.0.1:8443/PAS/services/WSCentralService" </pre>
username	<p>Required. The name of a user who has access to the HP Operations Orchestration flows to be imported</p> <p>Example username="csaouser"</p>

Attributes of ooengine, continued

Attribute	Description
password	<p>Required. The encrypted password of the HP Operations Orchestration user (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>While you may enter a password in clear text, after you run the tool, the clear text password is automatically replaced by an encrypted password.</p> <p>Example</p> <pre>password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"</pre> <p>If you have configured HP CSA to be FIPS 140-2 compliant, encrypt this password after you have configured CSA to be FIPS 140-2 compliant (that is, you should use the updated encryption tools to encrypt the password).</p>
truststore	<p>Required. The truststore that stores trusted Certificate Authority certificates, in which the root certificate of HP Operations Orchestration's Certificate Authority has been imported. The example shows the location of HP CSA's truststore (in which the root certificate of HP Operations Orchestration's Certificate Authority should have already been imported).</p> <p>Example</p> <pre>truststore="<csa_jre>/lib/security/cacerts"</pre> <p>where <code><csa_jre></code> is the directory in which the JRE that is used by HP CSA is installed.</p> <p>If you have configured HP CSA to be compliant with FIPS 140-2, use the name of the HP CSA server truststore.</p> <p>Example (this example uses the same example name from the <i>Create an HP CSA Encryption Keystore</i> section):</p> <pre>%CSA_HOME%/jboss-as/standalone/configuration/csa_server_truststore.p12</pre> <p>Note: Use only forward slashes (/) as your path separators.</p>

Attributes of ooengine, continued

Attribute	Description
truststorePassword	<p>Required. The encrypted password of the truststore (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>Example</p> <pre>truststorePassword="ENC(1fABFLXBEAdgy2kAvSaDq9M1Pd3/aSI9s=)"</pre> <p>If you have configured HP CSA to be FIPS 140-2 compliant, encrypt this password after you have configured CSA to be FIPS 140-2 compliant (that is, you should use the updated encryption tools to encrypt the password). This is referred to as the <i><HP CSA server truststore password></i> in the <i>Create an HP CSA Encryption Keystore</i> section.</p>

Attributes of ooengine, continued

Attribute	Description
accessPointType	<p>Optional. By default (if not specified), this value is URL. Defines the flows that are contained in the process engine. Valid values include URL, EXTERNAL_APPROVAL, or RESOURCE_POOL_SYNC.</p> <p>The accessPointType cannot be changed after a process engine is created.</p> <p>URL</p> <p>When set to URL, this process engine contains flows that will be selectable in the Cloud Service Management Console when creating lifecycle actions for a resource offering or service design.</p> <p>Required flow inputs: none</p> <p>EXTERNAL_APPROVAL</p> <p>When set to EXTERNAL_APPROVAL, this process engine contains flows that will be selectable when configuring a delegating approval policy for a service catalog in the Cloud Service Management Console.</p> <p>Required flow inputs:</p> <ul style="list-style-type: none"> • APPROVAL_CONTEXT_ID - The ID of the service request for which the approval is being processed. • APPROVAL_PROCESS_ID - The ID of the approval process being processed by the external approval system. • CATALOG_ID - The ID of the catalog from which the subscription was ordered. • ORGANIZATION_ID - The organization ID of the subscriber's organization. • USER_CONTEXT_ID - The ID of the subscriber who submitted the service request. <p>RESOURCE_POOL_SYNC</p> <p>When set to RESOURCE_POOL_SYNC, this process engine contains flows that will be selectable when configuring a resource synchronization action on a resource pool in the Cloud Service Management Console.</p> <p>Required flow inputs:</p> <ul style="list-style-type: none"> • CSA_CONTEXT_ID - The ID of the resource pool on which resource synchronization is being requested. • CSA_PROCESS_ID - The process instance ID used by the flow to notify

Attributes of ooengine, continued

Attribute	Description
	<p>HP CSA of the completion status of the action (success or fail).</p> <p>Example</p> <pre>accessPointType="EXTERNAL_APPROVAL"</pre>
update	<p>Optional. By default (if not specified), this value is false. When set to true, the HP CSA process engine's uri, username, or password are updated. That is, this information can be updated for a process engine if, for example, the imported flows have been moved to a different HP Operations Orchestration instance or the username and password of the HP Operations Orchestration instance have been changed.</p> <p>Example</p> <pre>update="true"</pre>
delete	<p>Optional. By default (if not specified), this value is false. When set to true, the HP CSA process engine and all associated process definitions are deleted. However, if any associated process definition is used in a resource offering or service design, the process engine (and all associated process definitions) cannot be and are not deleted.</p> <p>Any process engine that contains a process definition that is referenced by a retired service instance cannot be deleted. Even if the resource offerings and service designs in that process definition (referenced by a retired service instance) are deleted, the process engine and its associated process definitions cannot be deleted.</p> <p>Example</p> <pre>delete="true"</pre>

Attributes of folder

Attribute	Description
<p>path</p>	<p>Required. The absolute path to a folder containing flows or the absolute path to a single flow on the system running HP Operations Orchestration.</p> <p>Note: Use only forward slashes (/) as your path separators.</p> <p>Example</p> <p>path="/Library/ITIL/Change Management/stop_request"</p> <p>Note: The absolute path and name of a flow among one or more HP Operations Orchestration instances must be unique in order to import it into HP Cloud Service Automation. If the flow is not unique, it is not imported.</p> <p>Once you import a flow, you cannot import it into a different HP Cloud Service Automation process engine (using the same absolute path and name).</p> <p>If you want to import flows with the same names from different HP Operations Orchestration instances, the flows on each HP Operations Orchestration instance must be stored in different folders (the absolute path names must be different).</p> <p>If two HP Operations Orchestration instances have the same flows stored in the same folders (same absolute path) and you customize one of the flows on one of the instances, you should rename the customized flow to a unique name in order to import it (or you could rename the unchanged flow). The flow path and name between the customized and uncustomized flow must be unique.</p>
<p>flow</p>	<p>Optional. By default (if not specified), this value is false. When set to true, the name specified in the path attribute is the absolute path and filename of a single HP Operations Orchestration flow to import.</p> <p>Valid values: true, false</p> <p>Example</p> <p>flow="true"</p>
<p>recursive</p>	<p>Optional. By default (if not specified), this value is false. When set to true, flows are imported from the specified path and its subdirectories. When set to false, only flows located directly in the specified path are imported.</p> <p>Valid values: true, false</p> <p>Example</p> <p>recursive="true"</p>

Attributes of folder, continued

Attribute	Description
regex	<p>Optional. Specify a regular expression, used to find HP Operations Orchestration flows to import. If the regular expression matches the filename or a string in the filename, the flow is imported.</p> <p>Example</p> <p>Find all flows with "lifecycle" in their names:</p> <pre>regex="lifecycle"</pre>
update	<p>Optional. By default (if not specified), this value is false. When set to false, if the specified flow has already been imported, it is not imported again.</p> <p>When set to true, if the specified flow has already been imported but the flow has been updated (on the HP Operations Orchestration system), the updated flow is imported to HP Cloud Service Automation (the process definition on the HP Cloud Service Automation system is updated).</p> <p>When set to true, if a specified flow that has already been imported no longer exists on the HP Operations Orchestration system, it is removed from HP Cloud Service Automation. However, if the flow in HP Cloud Service Automation is linked to an action, it is not removed.</p> <p>When set to true and the <code>regex</code> attribute is used, only specified flows are updated. If a specified flow that has already been imported no longer exists on the HP Operations Orchestration system, it is removed from HP Cloud Service Automation. However, if the flow in HP Cloud Service Automation is linked to an action, it is not removed.</p> <p>Valid values: true, false</p> <p>Example</p> <pre>update="true"</pre>
delete	<p>Optional. By default (if not specified), this value is false. When set to true, the flows in the specified HP Operations Orchestration folder that are not associated with an HP CSA process definition are deleted. If a flow in the HP Operations Orchestration folder is associated with an HP CSA process definition, that flow is not deleted.</p> <p>Valid values: true, false</p> <p>Example</p> <pre>delete="true"</pre>

Examples of folder attributes and `HP00InfoInput.xml` content are located at the end of the section.

Step 4: Run the Process Definition Tool

To run the process definition tool, in the working directory (%CSA_HOME%\Tools\ProcessDefinitionTool), run the following command:

```
"<csa_jre>\bin\java" -jar process-defn-tool.jar -d db.properties  
-i HPOOInfoInput.xml
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

If a secure connection is enabled between HP CSA and the Oracle database, additional command line options must be specified based on your configuration:

```
"<csa_jre>\bin\java" [-Doracle.net.ssl_server_dn_match=true]  
[-Djavax.net.ssl.keyStore="<certificate_key_file>"  
-Djavax.net.ssl.keyStorePassword=<certificate_key_file_password>  
-Djavax.net.ssl.keyStoreType=<certificate_key_file_type>]  
-jar process-defn-tool.jar -d db.properties  
-i HPOOInfoInput.xml
```

The -Doracle.net.ssl_server_dn_match=true option is specified if a secure connection is enabled for the Oracle database server and HP CSA has been configured to check the database DN.

The -Djavax.net.ssl.keyStore="<certificate_key_file>", -Djavax.net.ssl.keyStorePassword=<certificate_key_file_password>, and -Djavax.net.ssl.keyStoreType=<certificate_key_file_type> options are specified if a secure connection and client authentication are enabled for the Oracle database server where <certificate_key_file> is the same keystore file defined by the certificate-key-file attribute in the ssl element of the %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml file (for example, %CSA_HOME%\jboss-as\standalone\configuration\keystore), <certificate_key_file_password> is the password to the keystore file (for example, changeit), and <certificate_key_file_type> is the keystore type (for example, JKS or PKCS12).

After the process definition tool is run, the total number of imported flows is displayed (depending on the number of flows imported, this may take some time to complete). If more than one HP Operations Orchestration system is specified in the HPOOInfoInput.xml file, flows are imported sequentially by system (that is, the flows from the first HP Operations Orchestration system listed are imported; once these flows have been imported/updated in HP Cloud Service Automation, the flows from the next HP Operations Orchestration system are imported).

Review the log file, process-defn-tool.log, for any error messages.

The following options are available in the process definition tool:

Option	Description
-d <filename>	Required. The name and location of the database properties file. Example -d db.properties
-i <filename>	Required. The name and location of the HP Operations Orchestration input file. Example -i HPO0InfoInput.xml
-g	Optional. Generate example files: MsSqlInputSample.properties, OracleInputSample.properties, PostgreSQLInputSample.properties, ProcessEngineInputSample.xml, and HPO0InputSample.xml. The sample HPO0InputSample.xml file can be used to import all the flows whose associated process definitions are referenced in the out-of-the-box resource offerings and service designs provided with HP Cloud Service Automation.
-h	Optional. List the options available in this tool.
-l	Optional. The location of the JDBC driver(s) to be used by this tool. By default, the tool looks for the JDBC driver(s) in the working directory. If you are not running the tool from %CSA_HOME%\Tools\ProcessDefinitionTool, specify the name and location of the JDBC driver(s) to be used. For a list of supported JDBC driver versions, refer to the <i>HP Cloud Service Automation System and Software Support Matrix</i> , available on the HP Software Support Web site at http://h20230.www2.hp.com/selfsolve/manuals/ (this site requires that you register with HP Passport). Multiple drivers may be listed and should be delimited by a space. The absolute path name or relative path name (from the working directory) should be specified. If the path name contains a space, the path and file name should be enclosed in quotation marks. For example: -l "C:\Program Files\jdbc\ojdbc6.jar"
-v <filename>	Optional. Validate the HP Operations Orchestration input file. Example -v HPO0InfoInput.xml

After you have imported HP Cloud Service Automation flows into HP CSA, you can import the sample service designs provided with HP CSA (some of these imported flows are used by the sample service designs). For more information about the sample service designs provided with HP CSA, refer to the *HP Cloud Service Automation Service Design Guide*.

Examples of Folder Attributes Used to Import Flows

The following examples show how to set folder attributes to import flows from your HP Operations Orchestration instance.

Import a specific flow

Format

```
<folder path="<directory_name>" flow="true" />
```

Example

Import the flow named stop_request from the Library/ITIL/Change Management directory

```
<folder path="/Library/ITIL/Change Management/stop_request" flow="true" />
```

Import a specific flow, re-import it if it has been updated, or delete it if it no longer exists

Format

```
<folder path="<directory_name>" flow="true" update="true" />
```

Example

Import the flow named stop_request from the Library/ITIL/Change Management directory

```
<folder path="/Library/ITIL/Change Management/stop_request" flow="true" update="true" />
```

Import all flows in the specified directory

Format

```
<folder path="<directory_name> /">
```

Example

Import all flows in the directory Library/ITIL/Change Management

```
<folder path="/Library/ITIL/Change Management" />
```

Import all flows in the specified directory and all subdirectories

Format

```
<folder path="<directory_name> recursive="true" /">
```

Example

Import all flows at and below the directory Library/ITIL/Change Management

```
<folder path="/Library/ITIL/Change Management" recursive="true" />
```

Import all flows whose name matches a regular expression and are in the specified directory

Format

```
<folder path="<directory_name>" regex="regular_expression" />
```

Example

Import all flows with "lifecycle" in their names in the directory Library/ITIL/Change Management

```
<folder path="/Library/ITIL/Change Management" regex="lifecycle" />
```

Import all flows whose name matches a regular expression and are in the specified directory and all subdirectories

Format

```
<folder path="<directory_name>" regex="regular_expression"  
recursive="true" />
```

Example

Import all flows with "lifecycle" in their names at and below the directory Library/ITIL/Change Management

```
<folder path="/Library/ITIL/Change Management" regex="lifecycle"  
recursive="true" />
```

Examples of HPOOInfoInput.xml Content

In the following examples, an HP Operations Orchestration instance contains the following flows:

- Flows invoked by lifecycle actions: start_job, stop_job, cancel_job, start_request, stop_request, and cancel_request located in /Library/ITIL/Change Management
- Flows used to submit delegated approvals: job_needs_approval and request_needs_approval located in /Library/ITIL/Change Management/Delegated Approvals
- Flows used for resource synchronization: sync_resources located in /Library/ITIL/Change Management/Resource Pool Sync

Import the flow named stop_request

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<ooengines>
  <ooengine name="oo-instance-1"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)" >
    <folder path="/Library/ITIL/Change Management/stop_request"
      flow="true" />
  </ooengine>
</ooengines>
```

Import the flows named stop_request and start_job

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<ooengines>
  <ooengine name="oo-instance-1"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)">
    <folder path="/Library/ITIL/Change Management/stop_request"
      flow="true" />
    <folder path="/Library/ITIL/Change Management/start_job"
      flow="true" />
  </ooengine>
</ooengines>
```

Import the flows named `stop_request` and `request_needs_approval`

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<ooengines>
  <ooengine name="oo-instance-1"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)">
    <folder path="/Library/ITIL/Change Management/stop_request"
      flow="true" />
  </ooengine>
  <ooengine name="oo-instance-2"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)"
    accessPointType="EXTERNAL_APPROVAL" >
    <folder path="/Library/ITIL/Change Management/
    Delegated Approvals/request_needs_approval" flow="true" />
  </ooengine>
</ooengines>
```

Import all flows (invoked by lifecycle actions) with "st" in their name

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<ooengines>
  <ooengine name="oo-instance-1"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)">
    <folder path="/Library/ITIL/Change Management" regex="st" />
  </ooengine>
</ooengines>
```

In this example, the following flows are imported: `start_job`, `stop_job`, `start_request`, `stop_request`, and `cancel_request`).

Import all flows

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<ooengines>
  <ooengine name="oo-instance-1"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)">
    <folder path="/Library/ITIL/Change Management" />
  </ooengine>
  <ooengine name="oo-instance-2"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)"
    accessPointType="EXTERNAL_APPROVAL" >
    <folder path="/Library/ITIL/Change Management/
    Delegated Approvals" />
  </ooengine>
  <ooengine name="oo-instance-3"
    uri="https://oo_server.xyz.com:8443/PAS/services/WSCentralService"
    username="admin" password="ENC(a3pGFPJQFwwXwtBBdpYktg==)"
    truststore="C:/Program Files/Hewlett-Packard/CSA/jre/lib/
    security/cacerts"
    truststorePassword="ENC(sh582cWF1HCfA1DB6JGgRKukv7HR3Wpd)"
    accessPointType="RESOURCE_POOL_SYNC" >
    <folder path="/Library/ITIL/Change Management/
    Resource Pool Sync" />
  </ooengine>
</ooengines>
```


Chapter 5: The Cloud Service Management Console

This chapter provides information for tasks needed to prepare and set up the Cloud Service Management Console in order to start using HP CSA. You must complete the required tasks before you can start to use the Cloud Service Management Console.

Tasks include:

- ["Configure the Provider Organization" below](#) (required)
- ["Add a Software License" on the next page](#) (required)
- ["Proxy Configuration for Resource Providers Outside the Internal Network" on the next page](#) (optional)
- ["Customize the Cloud Service Management Console Dashboard" on page 92](#) (optional)
- ["Customize the Cloud Service Management Console Title" on page 104](#) (optional)
- ["Delete the Sample Consumer Organization" on page 105](#) (optional)

Configure the Provider Organization

1. Launch the Cloud Service Management Console by typing the following URL in a supported Web browser: `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which the Cloud Service Management Console resides.
2. Log in to the Cloud Service Management Console as a CSA Administrator (refer to the *HP Cloud Service Automation Concepts Guide* and HP Cloud Service Management Console Help for more information about the CSA Administrator role).
3. Click the **Organizations** tile.

In the left-navigation frame, the provider organization icon () appears to the right of the

provider organization that is automatically set up (CSA-Provider). You may modify the provider organization, as needed. However, you cannot delete it. There can be only one provider organization.

4. In the left-navigation frame, select the provider organization.
5. Configure the provider organization by selecting and entering information into each section of the organization's navigation frame (General Information, LDAP, Access Control, Email Notifications,

and Catalogs). Refer to the *HP Cloud Service Management Console Help*, which is available in a printable PDF format, for more information about the fields in each section. This document is available on the HP Software Support Web site at <http://h20230.www2.hp.com/selfsolve/manuals/> (this site requires that you register with HP Passport).

Add a Software License

HP CSA version 4.20 requires a software license. HP CSA licensing is based on the number of operating system instances (OSIs) being used in current, active subscriptions.

After initial installation of HP CSA version 4.20, when you log in to the Cloud Service Management Console, a temporary 90-day trial license is activated. Once the trial license expires, you are limited to 25 OSIs. If you created more than 25 OSIs during the trial period, you cannot create any additional OSIs. You can add more licenses at any time to increase your OSI capacity.

After upgrade to HP CSA version 4.20, when you log in to the Cloud Service Management Console, all HP CSA version 4.x licenses are valid and are automatically added.

Note: HP CSA version 4.20 licenses are not compatible with HP CSA versions 4.01 or 4.10. That is, you cannot add HP CSA version 4.20 licenses to HP CSA versions 4.01 or 4.10.

Before you can add a software license, you must request a license using the licensing portal. See "[Request Software Licenses](#)" on page 17 for more information.

To add a software license, log in to the Cloud Service Management Console as the CSA Administrator. From the **Options** menu, select **Licensing**. For more detailed information about adding a license, refer to the *HP Cloud Service Management Console Help*.

For information on how to view or delete a license, refer to the *HP Cloud Service Management Console Help*.

Proxy Configuration for Resource Providers Outside the Internal Network

If you are using a network proxy server to communicate with a resource provider outside of the internal network (the resource provider's service access point is located outside of the internal network), configure HP CSA and HP Operations Orchestration to use this proxy server.

If you are using a network proxy server to communicate with a resource provider outside of the internal network, proxy configuration is required in the following situations:

- HP CSA - Validating the accessibility of a resource provider's URL. When a resource provider is created or modified, accessibility of the provider URL is validated with an HTTP or HTTPS GET call.

- HP Operations Orchestration - Contacting a resource provider. When an HP Operations Orchestration workflow provisioning step is executed, HP Operations Orchestration attempts to contact the resource provider.

If you do not configure the proxy server, you may see a Provider Validation Failed message when creating or updating a resource provider whose service access point is located outside of the internal network. Or, provisioning of a design fails when HP Operations Orchestration is unable to communicate with a resource provider that is located outside of the internal network.

To configure the proxy server for HP CSA and HP Operations Orchestration, do the following:

1. On the system running HP CSA, open the %CSA_HOME%\jboss-as\bin\standalone.conf.bat file in a text editor.
2. After the last uncommented line that sets the JAVA_OPTS property, add the following lines:

```
rem # HTTP Proxy Settings
set "JAVA_OPTS=%JAVA_OPTS% -Dhttp.proxyHost=<proxy.company.com>
-Dhttp.proxyPort=<proxy_port>"

rem # HTTPS Proxy Settings
set "JAVA_OPTS=%JAVA_OPTS% -Dhttps.proxyHost=<proxy.company.com>
-Dhttps.proxyPort=<proxy_port>"

rem # HTTP/HTTPS hosts not handled by the proxy
set "JAVA_OPTS=%JAVA_OPTS% -
Dhttp.nonProxyHosts=mycsaserver^^^|localhost^^^|127.*^^^|10.* "
```

where <proxy.company.com> is the fully-qualified domain name of the proxy server, <proxy_port> is the port used to communicate with the proxy server, and ^^| is the separator used when defining more than one non-proxy host.

3. Save and exit the file.
4. Restart HP CSA.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.
5. If you have integrated with HP Operations Orchestration version 9.07, do the following:
 - a. Log in to HP Operations Orchestration Studio.
 - b. Open the **Configuration** folder.
 - c. Right-click the **System Properties** folder and select **New**.
 - d. In the dialog, enter **CSA_Proxy_Host** and click **OK**.
 - e. Set the **Property Value** to the fully-qualified domain name of the proxy server and click **OK**.

- f. Right-click the **System Properties** folder and select **New**.
 - g. In the dialog, enter **CSA_Proxy_Port** and click **OK**.
 - h. Set the **Property Value** to the port used to communicate with the proxy server and click **OK**.
6. If you have integrated with HP Operations Orchestration version 10.20, do the following:
- a. Log in to HP Operations Orchestration Central.
 - b. Click the **Content Management** button.
 - c. Select **Configuration Items > System Properties**.
 - d. Click the **Add** icon.
 - e. Enter the following information if it is not already configured:

Field	Description
Name	CSA_Proxy_Host
Override Value	The fully-qualified domain name of the proxy server.
Name	CSA_Proxy_Port
Override Value	The port used to communicate with the proxy server.

- f. Click **Save**.

Customize the Cloud Service Management Console Dashboard

The Cloud Service Management Console dashboard is made up of predefined tiles that launch predefined pages. You can customize the dashboard by using the predefined custom tile, creating new tiles, modifying existing tiles, adding secondary dashboards, or disabling existing tiles.

Topics in this section include:

- ["Using the Predefined Custom Tile" on the next page](#)
- ["Enabling the HP IT Executive Scorecard Tiles" on page 94](#)
- ["Creating a Dashboard Tile" on page 94](#)
- ["Adding a Secondary Dashboard" on page 98](#)

- ["Modifying a Dashboard Tile" on page 101](#)
- ["Disabling a Dashboard Tile" on page 102](#)

The Cloud Service Management Console dashboard can be customized by a user who has access to the system on which HP CSA is running and permissions to modify and save files in the HP CSA installation directory.

A disabled predefined custom tile definition, disabled sample tile definitions, and a disabled sample secondary dashboard definition are provided in HP CSA as examples of how to create a tile and secondary dashboard. Examples of how to use the sample tile definitions and secondary dashboard definition are provided in this section.

Using the Predefined Custom Tile

By default, HP CSA contains sample predefined tiles that are disabled. One predefined tile, whose `id` attribute is set to `custom`, is a predefined tile that can be used when you are upgrading from a previous version of HP CSA.

The predefined custom tile allows for an easy migration of customized content from a previous version of HP CSA that contained a customized tile (for information on how to upgrade a Cloud Service Management Console custom tile, refer to the *HP Cloud Service Automation Upgrade Guide*).

If you are not upgrading from an older version of HP CSA, this tile can be used to create a custom tile. Information on how to create a custom tile by modifying the predefined custom tile is included in this section.

To use the predefined custom tile to create a new custom tile, on the system running HP CSA, do the following:

1. Create a folder called `custom-content` in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war` directory (where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed). Match the spelling and capitalization of the `custom-content` folder name exactly.
2. Create a Java server page named `index.jsp` in the `custom-content` directory. The `index.jsp` file contains the content that is displayed in an embedded page launched by the custom tile.
3. Make a backup of the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json` dashboard configuration file (where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed).
4. Edit the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json` file:
 - a. Locate the tile definition whose `id` and `name` are set to `custom`.
 - b. Set the `enabled` attribute to **true**.

- c. Save and exit the file.
5. Log in to the Cloud Service Management Console to view the tile. If you are already logged in, log out and log back in. Click the custom tile to launch the `index.jsp` page.

By default, the name of the tile is "Custom" and the description that appears in the tile is "Custom integration content." To modify this content, refer to ["Creating a Dashboard Tile" below](#) for more information.

Enabling the HP IT Executive Scorecard Tiles

HP CSA provides predefined HP IT Executive Scorecard tiles (accessed from the Cloud Analytics tile in the Cloud Service Management Console dashboard). When the HP IT Executive Scorecard tiles are enabled, they will launch predefined HP IT Executive Scorecard reports. Refer to the *HP Cloud Service Management Console Help* for more information about the requirements to enable the HP IT Executive Scorecard tiles.

Enabling Other Predefined Dashboard Tiles

HP CSA provides several predefined but disabled dashboard tiles. You can enable these tiles by doing the following:

1. Make a backup of the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json` dashboard configuration file (where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed).
2. Edit the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json` file:
 - a. Locate the tile definition to enable.
 - b. Set the `enabled` attribute to **true**.
 - c. Save and exit the file.
3. Log in to the Cloud Service Management Console to view the tile. If you are already logged in, log out and log back in.

To modify the tile, refer to ["Creating a Dashboard Tile" below](#) for more information.

Creating a Dashboard Tile

The Cloud Service Management Console dashboard is made up of predefined tiles that launch predefined pages. You can customize the dashboard by creating tiles in the dashboard that launch custom pages.

Tiles are defined in a configuration file and the tile definitions determine what is displayed in the Cloud Service Management Console dashboard. The default dashboard configuration file defines a primary dashboard that consists of enabled tiles and disabled tiles, a secondary dashboard (launched from the Designs tile), and a disabled sample secondary dashboard. Information about tile attributes and values defined in the configuration file is included in the steps below. See ["Adding a Secondary Dashboard" on page 98](#) for more information about how to add a secondary dashboard.

To create a Cloud Service Management Console dashboard tile, do the following:

1. Make a backup of the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json dashboard configuration file (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed).
2. Edit the config.json dashboard configuration file.

In the configuration file, the tiles defined for a dashboard are configured sequentially. That is, the first tile definition configured in a dashboard definition is the first tile displayed in the dashboard. The second tile definition is the second tile displayed. For example, in the default dashboard configuration file, the first tile definition configured in the primary dashboard is the Organizations tile. The Organizations tile is the first tile displayed in the Cloud Service Management Console dashboard. The second tile definition is the Resources tile and it is the second tile displayed in the Cloud Service Management Console dashboard.

Determine where you want the tile to appear in the dashboard and find the location in the configuration file. For example, if you want a tile to appear between the Organizations and Resources tiles in the dashboard, find the location between the Organizations and Resources tile definitions. If you want the tile to appear as the last tile, find the end of the last enabled tile definition.

- a. Copy the sample tile definition, whose id attribute is set to blanktile, and place it in the selected location. The following is an example tile definition (multiple tile definitions are separated by a comma):

```
{
  "id": "<tile_id>",
  "name": "<tile_name>",
  "description": "<tile_description>",
  "enabled": <true_or_false>,
  "style": "<tile_style>",
  "target": "<tile_target>",
  "data": "<tile_data>",
  "helptopic": "<tile_helptopic>",
  "roles": ["<role_1>", "<role_2>", ... , "<role_n>"]
}
```

- b. Update the attribute values in the tile definition as described in the table.

Attribute	Description
id	A unique identifier of the tile in this dashboard among all tiles defined for this dashboard.
name	<p>The name of the attribute in the <code>messages.properties</code> or <code>messages_<locale>.properties</code> file that defines the name of the tile that is displayed on the dashboard (where <code><locale></code> identifies the language to which the title has been translated, for example, <code>en</code> for English or <code>ja</code> for Japanese).</p> <p>The file may appear in the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\custom</code> or <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\messages\common</code> directory. If the file exists in both directories, the value defined in <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\custom</code> takes precedence.</p>
description	<p>The name of the attribute in the <code>messages.properties</code> or <code>messages_<locale>.properties</code> file that defines the description of the tile that is displayed on the dashboard (where <code><locale></code> identifies the language to which the title has been translated, for example, <code>en</code> for English or <code>ja</code> for Japanese).</p> <p>The file may appear in the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\custom</code> or <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\messages\common</code> directory. If the file exists in both directories, the value defined in <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\custom</code> takes precedence.</p>
enabled	Enable or disable the tile in the dashboard. If set to true , the tile is displayed in the dashboard. If set to false , the tile is not displayed in the dashboard.
style	<p>The name of the attribute in the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\css\base.css</code> file that defines the color of the tile's header that is displayed on the dashboard.</p> <p>If you are creating an assistance tile (that is, you set <code>target</code> to assistance), you must set this attribute to a pre-defined style named assistance.</p>

Attribute	Description
target	<p>The type of page launched when the tile is selected. Values include:</p> <ul style="list-style-type: none"> ○ iframe - An iframe or page is launched within the same dashboard or page. ○ page - A new page is launched outside of the dashboard or page. ○ dashboard - A sub-dashboard is launched within the same dashboard or page. ○ assistance - If the data attribute is defined, a new page is launched outside of the dashboard or page. If the data attribute is not defined, no page is launched and the tile simply contains content defined by the description attribute. The style attribute must be set to assistance.
data	<p>What is launched, based on the type of target.</p> <p>If iframe or page is the type of target selected, enter a URL or relative path (relative to the location of this file, %CSA_HOME%\jboss-as\standalone\deployments\) and filename of a Java server page to display. For example, enter http://www.hp.com or /csa/administration/index.jsp.</p> <p>If dashboard is the type of target selected, enter the unique dashboard id attribute of the dashboard to display. For example, the Designs tile of the main dashboard launches a sub- or secondary dashboard. The id of the secondary dashboard is designs therefore you would set the value of this attribute to designs.</p> <p>If assistance is the type of target selected and if you enter a value for this attribute, a Learn More link is displayed in the assistance tile. Clicking the Learn More link launches a page with the content defined by this attribute. Enter a URL or relative path (relative to the location of this file, %CSA_HOME%\jboss-as\standalone\deployments\) and filename of a Java server page to display. For example, enter http://www.hp.com or /csa/administration/index.jsp.</p>
helptopic	<p>If the type of target selected is iframe, this is the name of the help topic that is displayed when the Assistance icon on the page is selected. If the type of target selected is page, or dashboard, or assistance, this attribute is ignored.</p>

Attribute	Description
roles	<p>The role required by the user in order for the tile to display in the dashboard. One or more roles may be entered. However, only one role must match the user role in order for the user to see the tile. Roles must be enclosed in quotation marks and, if more than one role is entered, separated by a comma (for example, "CSA_ADMIN", "RESOURCE_SUPPLY_MANAGER"). If no roles are specified, the tile can be seen by all users.</p> <p>Values include:</p> <ul style="list-style-type: none"> ○ CONSUMER_SERVICE_ADMINISTRATOR - The Consumer Service Administrator configures and manages consumer organizations. ○ CSA_ADMIN - The Administrator has access to all functionality in the Cloud Service Management Console. ○ RESOURCE_SUPPLY_MANAGER - The Resource Supply Manager creates and manages cloud resources, such as providers and resource offerings. ○ SERVICE_BUSINESS_MANAGER - The Service Business Manager creates and manages the service offerings and service catalogs. ○ SERVICE_DESIGNER - The Service Designer designs, implements, and maintains service designs (also referred to as blueprints), component palettes, component types, component templates, and resource offerings. ○ SERVICE_OPERATIONS_MANAGER - The Service Operations Manager views and manages subscriptions and service instances. <p>See the "Role Descriptions" help topic in the Cloud Service Management Console for more information about these roles (navigate to Organizations > Access Control > Role Descriptions in the online help).</p>

- c. Save and exit the file.
3. Log in to the Cloud Service Management Console to view the tile. If you are already logged in, log out and log back in.

Adding a Secondary Dashboard

Tiles in the Cloud Service Management Console dashboard can be configured to launch a secondary dashboard. For example, in the default configuration of the Cloud Service Management Console dashboard, the Designs tile launches another dashboard from which you can select a designer to use. The Designs tile is configured with the `target` attribute set to **dashboard** and the `data` attribute set to the `id` of the secondary dashboard (**designs**). A sample secondary dashboard, whose `id` attribute is set to `providerpanel`, is provided.

After a tile in the main dashboard is configured to launch a secondary dashboard, a secondary dashboard definition must be added to the dashboard configuration file. For example, in the default configuration of the Cloud Service Management Console dashboard, a secondary dashboard with an **id** of **designs** is defined. Information about dashboard attributes and values defined in the configuration file is included in the steps below.

To add a secondary dashboard, do the following:

1. Make a backup of the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json dashboard configuration file (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed).
2. Edit the config.json file.
 - a. Determine where you want the secondary dashboard tile (the tile that launches the secondary dashboard) to appear in the dashboard and find the location in the configuration file. For example, if you want the secondary dashboard tile to appear between the Organizations and Resources tiles in the dashboard, find the location between the Organizations and Resources tile definitions. If you want the tile to appear as the last tile, find the end of the last enabled tile definition.

Copy the sample secondary dashboard tile definition, whose `id` attribute is set to `providerpanel` and `target` attribute is set to `dashboard`, and place it in the selected location.

Update the content of the secondary dashboard tile (see ["Creating a Dashboard Tile" on page 94](#) for more information about updating the content).

- b. In the configuration file, secondary dashboards are defined after the main dashboard. Locate where the main or any secondary dashboard definition ends, and add a secondary dashboard definition within the global dashboard definition. For example, in the default dashboard configuration file, you could add another secondary dashboard after the predefined **designs** secondary dashboard.

Copy the sample secondary dashboard definition, whose `id` attribute is set to `providerpanel` and `type` attribute is set to `secondary`, and place it in the selected location. The following is an example secondary dashboard definition (multiple dashboard definitions are separated by a comma):

```
{
  "id": "<dashboard_id>",
  "name": "<dashboard_name>",
  "style": "<dashboard_style>",
  "type": "<dashboard_type>",
  "helptopic": "<dashboard_helptopic>",
  "roles": ["<role_1>", "<role_2>", ... , "<role_n>"],
  "tiles": [ { ... } ]
}
```

- c. Update the attribute values in the dashboard definition as described in the table. See ["Creating a Dashboard Tile" on page 94](#) for more information about tile attributes.

Attribute	Description
id	A unique identifier of the dashboard among all defined dashboards.
name	The name of the attribute in the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\messages\common\messages.properties file that defines the name displayed in the dashboard. If this is the primary dashboard, the name is displayed above the tiles. If this is a secondary dashboard, the name is the label that is displayed next to the left-facing arrow icon or back button in the header.
style	The name of the attribute in the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\css\base.css file that defines the color of the secondary dashboard's back button. For the primary dashboard, leave this value empty.
type	<p>The type of dashboard. Values include:</p> <ul style="list-style-type: none"> ◦ primary - The dashboard that is displayed after launching HP CSA and successfully logging into the Cloud Service Management Console. This dashboard does not contain a back button. Only one primary dashboard can be defined. ◦ secondary - A sub-dashboard that is launched from a dashboard tile and contains a back button. Zero, one, or multiple secondary dashboards can be defined.
helptopic	The name of the help topic that is displayed when the Assistance icon on the page is selected.

Attribute	Description
roles	<p>The role required by the user in order for the dashboard to display. One or more roles may be entered. However, only one role must match the user role in order for the user to see the tile. Roles must be enclosed in quotation marks and, if more than one role is entered, separated by a comma (for example, "CSA_ADMIN", "RESOURCE_SUPPLY_MANAGER"). If no roles are specified, the tile can be seen by all users.</p> <p>Values include:</p> <ul style="list-style-type: none"> ○ CONSUMER_SERVICE_ADMINISTRATOR - The Consumer Service Administrator configures and manages consumer organizations. ○ CSA_ADMIN - The Administrator has access to all functionality in the Cloud Service Management Console. ○ RESOURCE_SUPPLY_MANAGER - The Resource Supply Manager creates and manages cloud resources, such as providers and resource offerings. ○ SERVICE_BUSINESS_MANAGER - The Service Business Manager creates and manages the service offerings and service catalogs. ○ SERVICE_DESIGNER - The Service Designer designs, implements, and maintains service designs (also referred to as blueprints), component palettes, component types, component templates, and resource offerings. ○ SERVICE_OPERATIONS_MANAGER - The Service Operations Manager views and manages subscriptions and service instances. <p>See the "Role Descriptions" help topic in the Cloud Service Management Console for more information about these roles (navigate to Organizations > Access Control > Role Descriptions in the online help).</p>
tiles	<p>Tile definition. At least one tile must be configured. See "Creating a Dashboard Tile" on page 94 for more information about tile attributes.</p>

- d. Save and exit the file.
3. Log in to the Cloud Service Management Console to view the dashboard. If you are already logged in, log out and log back in.

Modifying a Dashboard Tile

To modify an existing dashboard tile, edit the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json file (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed):

1. Locate the tile definition that you want to modify.
2. Update one or more attributes. For a description of the attributes, refer to "[Creating a Dashboard Tile](#)" on page 94.
3. Save and exit the file.

Disabling a Dashboard Tile

To disable a dashboard tile, edit the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\dashboard\config.json file (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed):

1. Locate the tile definition that you want to disable.
2. Set the enabled attribute to **false**.
3. Save and exit the file.

Dashboard Configuration File Syntax

The following is an example of a dashboard configuration file configured with only one secondary dashboard that has one generic tile and an assistance tile defined.

```
{
  "dashboards": [
    {
      "id": "<primary_id>",
      "name": "<primary_name>",
      "style": "",
      "type": "primary",
      "helptopic": "<primary_helptopic>",
      "roles": ["CONSUMER_SERVICE_ADMINISTRATOR", "SERVICE_BUSINESS_MANAGER",
"SERVICE_DESIGNER", "CSA_ADMIN", "RESOURCE_SUPPLY_MANAGER", "SERVICE_OPERATIONS_
MANAGER"],
      "tiles": [
        {
          "id": "<tile_id_1>",
          "name": "<tile_name>",
          "description": "<tile_description>",
          "enabled": <true_or_false>,
          "style": "<tile_style>",
          "target": "<tile_target>",
          "data": "<tile_data>",
          "helptopic": "<tile_helptopic>",
          "roles": ["<role_1>", "<role_2>", ... , "<role_n>"]
        },
        .
      ]
    }
  ]
}
```

```
.  
.  {  
    "id": "<tile_id_n>",  
    "name": "<tile_name>",  
    "description": "<tile_description>",  
    "enabled": <true_or_false>,  
    "style": "<tile_style>",  
    "target": "<tile_target>",  
    "data": "<tile_data>",  
    "helptopic": "<tile_helptopic>",  
    "roles": ["<role_1>", "<role_2>", ... , "<role_n>"]  
  }  
]  
, {  
  "id": "<secondary_id>",  
  "name": "<secondary_name>",  
  "style": "<secondary_style>",  
  "type": "secondary",  
  "helptopic": "<secondary_helptopic>",  
  "roles": ["<role_1>", "<role_2>", ... , "<role_n>"],  
  "tiles": [  
    {  
      "id": "<tile_id>",  
      "name": "<tile_name>",  
      "description": "<tile_description>",  
      "enabled": <true_or_false>,  
      "style": "<tile_style>",  
      "target": "<tile_target>",  
      "data": "<tile_data>",  
      "helptopic": "<tile_helptopic>",  
      "roles": ["<role_1>", "<role_2>", ... , "<role_n>"]  
    }, {  
      "id": "<assistance_tile_id>",  
      "name": "<assistance_tile_name>",  
      "description": "<assistance_tile_description>",  
      "enabled": <true_or_false>,  
      "style": "assistance",  
      "target": "assistance",  
      "data": "<optional_Learn_More_Link>",  
      "helptopic": "<value_is_ignored>",  
      "roles": ["<role_1>", "<role_2>", ... , "<role_n>"]  
    }  
  ]  
}  
]  
}
```

Customize the Cloud Service Management Console Font

The font used by the Cloud Service Management Console can be customized. You can change the font if you are a user who has access to the system on which HP CSA is running. To change the font, on the system running HP CSA, do the following:

1. Open the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\custom\custom.css` file in a text editor (where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed).
2. At the end of the file, add the following:

```
html, body {  
font-family: <font_name>;  
}
```

where `<font_name>` is the font used by the Cloud Service Management Console.

For example, to change the font to Arial, add the following to the file:

```
html, body {  
font-family: Arial;  
}
```

3. Save and exit the file.
4. Restart the Cloud Service Management Console.

Customize the Cloud Service Management Console Title

The Cloud Service Management Console title appears at the top of the Cloud Service Management Console next to the HP logo. By default, the title is "HP Cloud Service Automation."

You can change the title if you are a user who has access to the system on which HP CSA is running. To change the title, on the system running HP CSA, do the following:

1. Open the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\custom\messages.properties` file in a text editor (where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed).
2. Add the following attribute and value:


```
csa_title=<title>
```

where *<title>* is the title that displays at the top of the Cloud Service Management Console.

For example, to change the title to "HP CloudSystem," add the following to the file:

```
csa_title=HP CloudSystem
```

Note: You cannot change the HP logo.

If you are translating the title, create a file named `messages_<Locale>.properties` instead (where *<locale>* identifies the language to which the title has been translated, for example, `en` for English or `ja` for Japanese).

3. Save and exit the file.

Delete the Sample Consumer Organization

The sample consumer organization can be used by the sample `consumer` user to experiment with the Marketplace Portal. Delete this sample consumer organization (and disable the sample `consumer` user) if you no longer are using it or if you are moving the application to production.

To delete the sample consumer organization and disable the sample `consumer` user:

1. Log in to the Cloud Service Management Console and delete the sample consumer organization in the **General Information** page of the **Organizations** area.

Note: In order to delete an organization, it must not have any active catalogs.

2. Edit the `%CSA_HOME%\portal\conf\mpp.json` file. Update the `defaultOrganizationName` attribute's value if it is set to `CSA_CONSUMER`. Set the value to an existing consumer organization's Organization Identifier where the Organization Identifier is the unique name that HP Cloud Service Automation assigns to the organization, based on the organization display name (the organization identifier can be found in the General Information section of the **Organizations** tile of the Cloud Service Management Console). The `defaultOrganizationName` attribute defines the organization that is accessed by the Marketplace Portal when the Marketplace Portal is launched from a URL that does not specify the organization.
3. Edit the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-consumer-users.properties` file. Update the `Consumer` property to disable this user account. For example, set `Consumer` to the following encrypted value: `cloud,SERVICE_CONSUMER,ROLE_REST,disabled`

See ["Encrypt a Password" on page 110](#) for instructions on how to encrypt this value.

Chapter 6: Common HP CSA Tasks

This chapter provides information on how to perform common HP CSA tasks.

Tasks include:

- "Launch the Cloud Service Management Console" below
- "Launch the Marketplace Portal" below
- "Start HP CSA" on page 109
- "Stop HP CSA" on page 110
- "Restart HP CSA" on page 109
- "Encrypt a Password" on page 110
- "Clear the Web Browser Cache" on page 111
- "Uninstall HP CSA" on page 112

Launch the Cloud Service Management Console

Launch the Cloud Service Management Console by typing the following URL in a supported Web browser: `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which the Cloud Service Management Console resides.

Launch the Marketplace Portal

Launch the default Marketplace Portal

Launch the default Marketplace Portal by typing one of the following URLs in a supported Web browser:

- `https://<csahostname>:8444/mpp`
- `https://<csahostname>:8089`

where `<csahostname>` is the fully-qualified domain name of the system on which the Marketplace Portal instance resides and that was used when HP CSA was installed.

For example: `https://csa_system.abc.com:8444/mpp`

The organization associated with the default Marketplace Portal is defined in the `%CSA_HOME%\portal\conf\mpp.json` file. By default, this is the sample organization that is installed with

HP CSA (CSA_CONSUMER). To modify the organization associated with the default Marketplace Portal, modify the `defaultOrganizationName` property value by setting it to the `<organization_identifier>` of the desired organization, where `<organization_identifier>` is the unique name that HP Cloud Service Automation assigns to the organization, based on the organization display name (the organization identifier can be found in the General Information section of the **Organizations** tile of the Cloud Service Management Console).

Launch an organization-specific Marketplace Portal

Launch an organization's Marketplace Portal by typing the following URL in a supported Web browser:

```
https://<csahostname>:8089/org/<organization_identifier>
```

where:

- `<csahostname>` is the fully-qualified domain name of the system on which the Marketplace Portal instance resides and that was used when HP CSA was installed.
- `<organization_identifier>` is the unique name that HP Cloud Service Automation assigns to the organization, based on the organization display name (the organization identifier can be found in the General Information section of the **Organizations** tile of the Cloud Service Management Console)

Example:

```
https://csa_system.xyz.com:8089/org/ORGANIZATIONA
```

Caution: Do not launch more than one organization-specific Marketplace Portal from the same browser session. For example, if you launch ORGANIZATION_A's Marketplace Portal in a browser, do not open a tab or another window from that browser and launch ORGANIZATION_B's Marketplace Portal. Otherwise, the user who has logged in to the Marketplace Portal launched for ORGANIZATION_A will start to see data for ORGANIZATION_B.

Instead, start a new browser session to launch another organization's Marketplace Portal.

Launch the default remote instance of a Marketplace Portal

Launch the default remote instance of the Marketplace Portal by typing one of the following URLs in a supported Web browser:

- `https://<csahostname>:8444/mpp`
- `https://<mpphostname>:8089`

where:

- `<csahostname>` is the fully-qualified domain name of the system on which HP CSA is installed and the URL in the `%CSA_HOME%\jboss-as\standalone\deployments\mpp.war\index.html` file (on

the system on which HP CSA is installed) has been updated to `https://<mpphostname>:8089`.

- `<mpphostname>` is the fully-qualified domain name of the system on which the Marketplace Portal instance resides.

Examples:

- `https://csa_system.abc.com:8444/mpp`
- `https://mpp_system.abc.com:8089`

The organization associated with the default Marketplace Portal is defined in the `%CSA_HOME%\portal\conf\mpp.json` file (on the system on which the Marketplace Portal instance resides). By default, this is the sample organization that is installed with HP CSA (`CSA_CONSUMER`). To modify the organization associated with the default Marketplace Portal, modify the `defaultOrganizationName` property value by setting it to the `<organization_identifier>` of the desired organization, where `<organization_identifier>` is the unique name that HP Cloud Service Automation assigns to the organization, based on the organization display name (the organization identifier can be found in the General Information section of the **Organizations** tile of the Cloud Service Management Console).

Launch an organization-specific remote instance of a Marketplace Portal

Launch an organization's remote instance of the Marketplace Portal by typing the following URL in a supported Web browser:

`https://<mpphostname>:8089/org/<organization_identifier>`

where:

- `<mpphostname>` is the fully-qualified domain name of the system on which the Marketplace Portal instance resides.
- `<organization_identifier>` is the unique name that HP Cloud Service Automation assigns to the organization, based on the organization display name (the organization identifier can be found in the General Information section of the **Organizations** tile of the Cloud Service Management Console)

Example:

`https://mpp_system.xyz.com:8089/org/ORGANIZATION_A`

Caution: Do not launch more than one organization-specific Marketplace Portal from the same browser session. For example, if you launch ORGANIZATION_A's Marketplace Portal in a browser, do not open a tab or another window from that browser and launch ORGANIZATION_B's Marketplace Portal. Otherwise, the user who has logged in to the Marketplace Portal launched for ORGANIZATION_A will start to see data for ORGANIZATION_B.

Instead, start a new browser session to launch another organization's Marketplace Portal.

Start HP CSA

To start HP CSA:

1. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for the `keystorePasswordField` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

2. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
3. Right-click on the HP Cloud Service Automation service and select **Start**.
4. Right-click on the HP Marketplace Portal service and select **Start**.
5. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Start**.

Restart HP CSA

To restart HP CSA:

1. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for the `keystorePasswordField` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

2. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
3. Right-click on the HP Cloud Service Automation service and select **Restart**.
4. Right-click on the HP Marketplace Portal service and select **Restart**.

Stop HP CSA

To stop HP CSA:

1. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Cloud Service Automation service and select **Stop**.
3. Right-click on the HP Marketplace Portal service and select **Stop**.
4. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.

Encrypt a Password

To encrypt a password (for use with HP CSA configuration only; see ["Encrypt a Marketplace Portal Password" on page 114](#) for information on how to encrypt a Marketplace Portal password):

1. Open a command prompt and change to the %CSA_HOME%\Tools\PasswordUtil directory. For example:

```
C:\Program Files\Hewlett-Packard\CSA\Tools\PasswordUtil
```

2. Run the following command:

```
"<csa_jre>\bin\java" -jar passwordUtil-standalone.jar encrypt <myPassword>
```

If you have configured HP CSA to be FIPS 140-2 compliant, run the following command (this example uses the same example names from the *Create an HP CSA Encryption Keystore* section):

```
"<csa_jre>\bin\java" -jar passwordUtil-standalone.jar encrypt <password>  
JsafeJCE ../../jboss-as/standalone/configuration/csa_encryption_keystore.p12  
<HP CSA encryption keystore password> csa_encryption_key  
../../jboss-as/standalone/configuration/key.dat
```

Note: The path separators used in the passwordUtil-standalone.jar script options are forward slashes (/). You can also use double backward slashes (\\) as your path separators.

If you used different names for the keystore, alias, or encrypted symmetric key file, here is an example of the command without using the example names:

```
"<csa_jre>\bin\java" -jar "%CSA_HOME%\Tools\PasswordUtil\passwordUtil-standalone.jar" encrypt <password> JsafeJCE <HP CSA encryption keystore>  
<HP CSA encryption keystore password>  
<HP CSA encryption keystore alias>  
<Location and name of the encrypted symmetric key>
```

Note: If you use path separators in the `passwordUtil-standalone.jar` script options, use either a single forward slash (/) or double backward slashes (\\) as your path separator.

Clear the Web Browser Cache

It may be necessary to clear your Web browser cache on systems that previously accessed the Cloud Service Management Console after upgrading HP CSA. To clear your Web browser cache:

- If you are using a Chrome Web browser:
 - a. Open the browser.
 - b. Select **<Ctrl>+<Shift>+<Delete>**.
 - c. For **Obliterate the following items from**, select **the beginning of time**.
 - d. Select only **Empty the cache**. Unselect all other items.
 - e. Click **Clear browsing data**.
- If you are using a Firefox Web browser:
 - a. Open the browser.
 - b. Select **<Ctrl>+<Shift>+<Delete>**.
 - c. For **Time range to clear**, select **Everything**.
 - d. Expand **Details**.
 - e. Select only **Cache**. Unselect all other items.
 - f. Click **Clear Now**.
- If you are using a Windows IE Web browser:

- a. Open the browser.
- b. Select **<Ctrl>+<Shift>+<Delete>**.
- c. Select only **Temporary Internet Files**. Unselect all other items.
- d. Click **Delete**.

Uninstall HP CSA

Uninstalling HP CSA removes the %CSA_HOME% directory and all of its contents (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed). If all the contents in %CSA_HOME% are not deleted, you must manually delete them and the %CSA_HOME% directory.

If you installed an embedded HP Operations Orchestration instance with HP CSA (you installed HP Operations Orchestration with HP CSA using the HP CSA installer), the embedded HP Operations Orchestration instance is removed. If you are using HP CSA with an external HP Operations Orchestration instance (you installed HP Operations Orchestration separately from HP CSA), the external HP Operations Orchestration instance is not removed.

Note: The HP CSA database is NOT updated or uninstalled.

To uninstall HP CSA:

1. Stop the HP CSA and Marketplace Portal services.

To stop HP CSA:

- a. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
- b. Right-click on the HP Cloud Service Automation service and select **Stop**.
- c. Right-click on the HP Marketplace Portal service and select **Stop**.
- d. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.

2. Verify that the services were stopped.

If the HP CSA service is still running, open a command prompt, navigate to %CSA_HOME%\jboss-as\bin, and run the following command:

```
jboss-cli.bat --connect --command=:shutdown
```

3. Close all instances of Windows Explorer, close all command prompts, and exit all programs that are running on the system.

4. Navigate to **Control Panel > Uninstall a program**.
5. Right-click on **HP Cloud Service Automation** and select **Uninstall/Change**.
6. Click **Uninstall**.
7. Delete the %CSA_HOME% directory and any remaining contents, if they exist.
8. If they exist, delete all HP CSA entries from the following file:

C:\Program Files\Zero G Registry\.com.zerog.registry.xml

Chapter 7: The Marketplace Portal

This chapter provides information on how to encrypt a password used by the Marketplace Portal.

For information about the attributes in the `mpp.json` file, refer to "[Marketplace Portal Attributes](#)" on [page 261](#).

Refer to the *HP Cloud Service Management Console Help* for information about configuring the Marketplace Portal.

Encrypt a Marketplace Portal Password

To encrypt a password used by the Marketplace Portal:

1. Open a command prompt and change to the `%CSA_HOME%\portal\bin` directory. For example:

```
C:\Program Files\Hewlett-Packard\CSA\portal\bin
```

2. Run the following command:

```
..\..\node.js\node passwordUtil --keyfilePath <keyfile> --password <myPassword>
```

where `<keyfile>` is the path to (absolute or relative to the bin directory) and name of the file that contains the Marketplace Portal's encrypted symmetric key (if the file does not exist, it will create the file) and `<myPassword>` is the password to be encrypted.

Chapter 8: User Administration

This chapter provides information for additional administration and configuration tasks.

Tasks include:

- ["Allow Non-Administrator Users to Start and Stop the HP CSA or Marketplace Portal Service" below](#) (optional)
- ["Allow the HP CSA and Marketplace Portal Services to be Run as a Non-Administrator User" on page 117](#) (optional)
- ["Change HP CSA Out-of-the-Box User Accounts" on page 121](#) (optional)

Allow Non-Administrator Users to Start and Stop the HP CSA or Marketplace Portal Service

By default, only users with administrator privileges can start or stop the HP CSA and Marketplace Portal services. This procedure explains how to grant permissions to non-administrator users to start and stop these services. This process involves the following tasks:

- Create a non-administrator user account, if one does not exist.
- Determine the security identifier (SID) of the non-administrator user.
- Set the security descriptor for the services to allow the non-administrator user to start and stop them.
- Add necessary permissions to the HP CSA installation directory for the non-administrator user.

To allow non-administrator users to start and stop the HP CSA or Marketplace Portal service

1. Start the Control Panel on the HP CSA system and click **Add or remove user accounts** that is under **User Accounts**.
2. Click **Create a new account** in the Manage Accounts window that appears.
3. Enter a name for the user, select the **Standard user** radio button if it is not selected, and then click the **Create Account** button to create the user account.

In this procedure we will use the user account name "CSAUser."

4. Open a command prompt window and run the following command, as is applicable, to display the security descriptor for the HP CSA or Marketplace Portal service:

For the HP CSA service - sc sdshow csa

For the Marketplace Portal service - sc sdshow hpmarketplaceportal.exe

The command returns a security descriptor in Security Descriptor Definition Language (SDDL), like the following example for the HP CSA service:

```
D: (A;;CCLCSWRPWPDTLOCRRC;;;SY) (A;;CCDCLCSWRPWPDTLOCRSDRCWDWO;;;BA)
(A;;CCLCSWLOCRRC;;;IU) (A;;CCLCSWLOCRRC;;;SU)S:
(AU;FA;CCDCLCSWRPWPDTLOCRSDRCWDWO;;;WD)
```

5. Copy the security descriptor that was returned by the above command to a text editor such as Notepad.
6. Run the following command to display the names and SIDs for all existing user accounts:

```
wmic useraccount get name,sid
```

7. From the command output, copy the SID for the non-administrator user to the text editor.

The SID is usually in a format like S-1-5-21-3637136161-1358011849-3560387905-1014.

8. Add (A;;RPWPCR;;;<SID of non-admin user>) before the S: (AU;... portion of the security descriptor that you copied to a text editor earlier in this procedure.

Using the security descriptor and SID from our example, the result would be as follows, with the added text shown against a gray background:

```
D: (A;;CCLCSWRPWPDTLOCRRC;;;SY) (A;;CCDCLCSWRPWPDTLOCRSDRCWDWO;;;BA)
(A;;CCLCSWLOCRRC;;;IU) (A;;CCLCSWLOCRRC;;;SU) (A;;RPWPCR;;;S-1-5-21-3637136161-
1358011849-3560387905-1014)S: (AU;FA;CCDCLCSWRPWPDTLOCRSDRCWDWO;;;WD)
```

9. Run the following command, as is applicable, to set the security descriptor for the HP CSA or Marketplace Portal service to the new value:

For the HP CSA service - sc sdset csa "<new security descriptor>"

For the Marketplace Portal service - sc sdset hpmarketplaceportal.exe "<new security descriptor>"

The message [SC] SetServiceObjectSecurity SUCCESS is returned if the command completes successfully.

Note: Repeat steps 4 through 9 as necessary so that the security descriptor is changed for both services.

The non-administrator user now has the permissions necessary to start and stop the HP CSA and Marketplace Portal services. As a test, you can log in using the non-administrator user account and start and stop the HP CSA and Marketplace Portal services.

The final steps below will add necessary permissions to the HP CSA directory for the non-administrator user.

1. Log into the HP CSA machine as administrator.
2. In Windows Explorer, navigate to the HP CSA installation directory (for example, C:\Program Files\Hewlett-Packard\CSA), right-click on the folder, and select **Properties** in the menu that appears to open the CSA Properties dialog box.
3. Click the **Security** tab in the CSA Properties dialog box.
4. Check if the user is listed in the Group or user names list in the dialog box, and if it is not listed, continue with the next step. If it is listed, go to Step 7 to continue.
5. Click the **Edit...** button, click the **Add...** button in the dialog box that appears, enter the non-administrator user name in the Enter the object names to select field, and then click the **Check Names** button.
6. Select the name, and then click **OK** to add the user to the Group or user names list.
7. Select the user name, select the **Allow** checkbox for the following permissions, and then click **OK**.
 - Read & execute
 - List folder contents
 - Read
 - Write

Allow the HP CSA and Marketplace Portal Services to be Run as a Non-Administrator User

By default, the HP CSA and Marketplace Portal services are run as the service user. This section explains how to configure HP CSA so that the HP CSA and Marketplace Portal services can be run by non-administrator users. This process involves the following tasks:

- Create non-administrator users
- Configure the services
- Configure file system permissions

Caution: If the HP CSA and Marketplace Portal services are run as non-administrator users, you will not be able to do the following:

- Upgrade HP CSA
- Deploy hotfixes
- Install patches
- Use external tools such as the component tool, content archive tool, database purge tool, process definition tool, provider tool, schema installation tool, and support tool.
- Modify Autopass license data

Note: Certificates must be replaced and regenerated as the Administrator user.

Create Non-Administrator Users

The following example shows how to create two non-administrator user accounts, one for the HP CSA service to run as and the other for the Marketplace Portal service to run as. Alternatively, but not documented, you may also create a single non-administrator user to run as for both services.

1. Log in as the Administrator.
2. Start the Control Panel on the HP CSA system and click **Add or remove user accounts** that is under **User Accounts**.
3. Click **Create a new account** in the Manage Accounts window that appears.
4. Enter a name for the user, select the **Standard user** radio button if it is not selected, and then click the **Create Account** button to create the user account.

Create two user accounts: one for "CSAUser" and one for "MPPUser."

Configure the HP CSA and Marketplace Portal Services

1. Log in as the Administrator.
2. Stop HP CSA.

To stop HP CSA:

- a. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.

- b. Right-click on the HP Cloud Service Automation service and select **Stop**.
 - c. Right-click on the HP Marketplace Portal service and select **Stop**.
 - d. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.
3. Back up and then delete the log files in the %CSA_HOME%\jboss-as\standalone\log\ directory.
4. Delete all files in the %CSA_HOME%\jboss-as\standalone\tmp\ directory.
5. Configure the HP Cloud Service Automation service to be run as CSAUser:
 - a. Navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service and select **Properties**.
 - c. Select the **Log On** tab.
 - d. Select **This account**.
 - e. In the first field, enter **CSAUser**.
 - f. Enter the password for CSAUser, confirm the password, and click **OK**.
6. Configure the Marketplace Portal service to be run as MPPUser:
 - a. Navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the Marketplace Portal service and select **Properties**.
 - c. Select the **Log On** tab.
 - d. Select **This account**.
 - e. In the first field, enter **MPPUser**.
 - f. Enter the password for MPPUser, confirm the password, and click **OK**.

Configure File System Permissions For the Non-Administrator Users

Assign permissions to each user for the specified directories in the HP CSA file system.

1. Log in as the Administrator.
2. Open the File Explorer.

3. For each of the directories listed in the following table, do the following (where C:\Program Files\Hewlett-Packard\CSA is the directory in which HP CSA has been installed):
 - a. Right-click on the directory and select **Properties**.
 - b. Click the **Security** tab.
 - c. Click **Edit**.
 - d. Select a user (CSAUser or MPPUser) and select the permissions listed in the table.
 - e. Click **OK** to exit the Permissions dialog.
 - f. Click **OK** to exit the Properties dialog.

Directory	User(s)	Allowed Permission(s)
C:\	CSAUser MPPUser	Full Control Modify Read & execute List folder contents Read Write
C:\Program Files\Hewlett-Packard	CSAUser MPPUser	Full Control Modify Read & execute List folder contents Read Write
C:\Program Files\Hewlett-Packard\CSA	CSAUser MPPUser	Full Control Modify Read & execute List folder contents Read Write
C:\Program Files\Hewlett-Packard\CSA\Autopass	CSAUser MPPUser	Full Control Read
C:\Program Files\Hewlett-Packard\CSA\jboss-as	CSAUser	Read
C:\Program Files\Hewlett-Packard\CSA\jboss-as\bin	CSAUser	Write
C:\Program Files\Hewlett-Packard\CSA\CONTENT_IMPORT_LOGS	CSAUser	Write

Directory	User(s)	Allowed Permission(s)
C:\Program Files\Hewlett-Packard\CSA\jboss-as\standalone	CSAUser	Write
C:\Program Files\Hewlett-Packard\CSA\jboss-as\standalone\deployments	CSAUser MPPUser	Modify Read & execute List folder contents Read Write
C:\Program Files\Hewlett-Packard\CSA\jboss-as\standalone\configuration	CSAUser MPPUser	Modify Read & execute List folder contents Read Write
C:\Program Files\Hewlett-Packard\CSA\node.js	MPPUser	Read
C:\Program Files\Hewlett-Packard\CSA\openjre* *This is the JRE used by HP CSA. If you are using a different JRE, set the permissions to that JRE's directory.	CSAUser MPPUser	Read & execute List folder contents Read Write
C:\Program Files\Hewlett-Packard\CSA\portal	MPPUser	Read
C:\Program Files\Hewlett-Packard\CSA\portal\bin\daemon	MPPUser	Write
C:\Program Files\Hewlett-Packard\CSA\portal\logs	MPPUser	Write
C:\Program Files\Hewlett-Packard\CSA\scripts	CSAUser	Read
C:\Program Files\Hewlett-Packard\CSA\security	CSAUser MPPUser	Read
C:\Program Files\Hewlett-Packard\CSA\Tools	CSAUser	Read

4. Start HP CSA.
5. Examine the %CSA_HOME%\jboss-as\standalone\log\server.log file and verify the changes deployed correctly.

Change HP CSA Out-of-the-Box User Accounts

HP CSA ships with built-in user accounts. The user accounts are used to authenticate REST API calls and for initial setup and experimentation with the product. For security reasons, you may want to disable or change the passwords associated with these accounts (do not change the usernames).

Note: Do not create users in your LDAP directory that match the out-of-the-box users provided by HP Cloud Service Automation (the out-of-the-box users are admin, cdaInboundUser, csaCatalogAggregationTransportUser, csaReportingUser, csaTransportUser, idmTransportUser, and ooInboundUser). Creating the same users in LDAP may allow the out-of-the-box users unintended access to the Cloud Service Management Console or give the LDAP users unintended privileges.

Cloud Service Management Console User Accounts

The following users ship out-of-the-box and are used with the Cloud Service Management Console:

admin User: Cloud Service Management Console

Username	admin
Default Password	cloud
Default Role	ROLE_REST
Usage	This account is used to initially log in to the Cloud Service Management Console to configure the provider organization.
To Disable	<p>Edit the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-provider-users.properties file. Update the admin property to disable this user account. For example, set admin to the following value (this value should be encrypted):</p> <pre>cloud,ROLE_REST,disabled</pre> <p>Note: This property not only determines if the account is enabled, it also contains the password and the roles that control access to HP CSA.</p> <p>By default, the unencrypted value of this property is:</p> <pre>cloud,ROLE_REST,enabled</pre> <p>See "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by ENC without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p>

admin User: Cloud Service Management Console, continued

To Change Password	<p>If you change the password to this account, you must update the value of the password in the <code>csa-provider-users.properties</code> file and the <code>securityAdminPassword</code> property in the <code>csa.properties</code> file (you must use the same password). You must also update and use the same password for every REST API call that uses the password.</p> <p>Updating the admin property in <code>csa-provider-users.properties</code></p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-provider-users.properties</code> file. Update the password portion of the <code>admin</code> value and encrypt the entire value, including the roles and account status (see "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p> <div style="background-color: #f0f0f0; padding: 10px; margin: 10px 0;"> <p>Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.</p> <p>By default, the unencrypted value of this property is: <code>ccloud,ROLE_REST,enabled</code></p> </div> <p>Updating the <code>securityAdminPassword</code> property in <code>csa.properties</code></p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties</code> file (where <code>%CSA_HOME%</code> is the directory in which HP Cloud Service Automation is installed) and update the value of the <code>securityAdminPassword</code> property. Use the same encrypted password that you entered for the <code>admin</code> property in the <code>csa-provider-users.properties</code> file.</p> <p>After modifying the <code>csa.properties</code> file, restart HP CSA. See "Restart HP CSA" on page 109 for detailed information on how to restart HP CSA.</p>
---------------------------	---

consumerAdmin User: Marketplace Portal

Username	consumerAdmin
Default Password	cloud
Default Role	CONSUMER_ORGANIZATION_ADMINISTRATOR
Usage	This account is used to initially log in to the Cloud Service Management Console to configure and manage the sample CSA Consumer organization.

consumerAdmin User: Marketplace Portal, continued

<p>To Disable</p>	<p>Edit the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-consumer-users.properties file. Update the consumerAdmin property to disable this user account. For example, set consumerAdmin to the following value (this value should be encrypted):</p> <pre>c1oud,CONSUMER_ORGANIZATION_ADMINISTRATOR,disabled</pre> <p>Note: This property not only determines if the account is enabled, it also contains the password and the roles that control access to HP CSA.</p> <p>By default, the unencrypted value of this property is:</p> <pre>c1oud,CONSUMER_ORGANIZATION_ADMINISTRATOR,enabled</pre> <p>See "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by ENC without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p>
<p>To Change Password</p>	<p>Edit the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-consumer-users.properties file. Update the password portion of the consumerAdmin value and encrypt the entire value, including the roles and account status (see "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by ENC without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p> <p>Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.</p> <p>By default, the unencrypted value of this property is:</p> <pre>c1oud,CONSUMER_ORGANIZATION_ADMINISTRATOR,enabled</pre>

csaCatalogAggregationTransportUser User: Cloud Service Management Console

<p>Username</p>	<p>csaCatalogAggregationTransportUser</p>
<p>Default Password</p>	<p>cloud</p>
<p>Usage</p>	<p>This account is used to authenticate REST API calls.</p>
<p>To Disable</p>	<p>Do not disable this account.</p>

csaCatalogAggregationTransportUser User: Cloud Service Management Console, continued

To Change Password	<p>If you change the password to this account, you must update the value of the securityCatalogAggregationTransportUserPassword property in csa.properties. You must also update the password using the catalog aggregation registration REST APIs.</p> <p>Edit the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties file (where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed) and update the value of the securityCatalogAggregationTransportUserPassword property. Determine a suitable new password (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p> <p>After modifying the csa.properties file, restart HP CSA. See "Restart HP CSA" on page 109 for detailed information on how to restart HP CSA.</p>
---------------------------	--

csaReportingUser User: Cloud Service Management Console

Username	csaReportingUser
Default Password	cloud
Default Roles	ROLE_REST, ROLE_DYNAMIC
Usage	This account is used when a subscription is ordered or modified and a field for the subscription includes a dynamically generated list. The dynamically generated list is a subscriber option property configured to use a dynamic query. The dynamic query uses this account to access HP Cloud Service Automation to determine the values that will appear in the list. This account has read-only access to HP Cloud Service Automation.
To Disable	Do not disable this account.

csaReportingUser User: Cloud Service Management Console, continued

To Change Password	<p>If you change the password to this account, you must update the value of the password in the <code>csa-provider-users.properties</code> file and the <code>securityCsaReportingUserPassword</code> property in the <code>csa.properties</code> file (you must use the same password). You must also update and use the same password for every REST API call that uses the password.</p> <p>Updating the <code>csaReportingUser</code> property in <code>csa-provider-users.properties</code></p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-provider-users.properties</code> file. Update the password portion of the <code>csaReportingUser</code> value and encrypt the entire value, including the roles and account status (see "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p> <div style="background-color: #f0f0f0; padding: 10px; margin: 10px 0;"> <p>Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.</p> <p>By default, the unencrypted value of this property is: <code>ccloud,ROLE_REST,ROLE_DYNAMIC,enabled</code></p> </div> <p>Updating the <code>securityCsaReportingUserPassword</code> property in <code>csa.properties</code></p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties</code> file (where <code>%CSA_HOME%</code> is the directory in which HP Cloud Service Automation is installed) and update the value of the <code>securityCsaReportingUserPassword</code> property. Use the same encrypted password that you entered for the <code>csaReportingUser</code> property in the <code>csa-provider-users.properties</code> file.</p> <p>After modifying the <code>csa.properties</code> file, restart HP CSA. See "Restart HP CSA" on page 109 for detailed information on how to restart HP CSA.</p>
---------------------------	---

csaTransportUser User: Cloud Service Management Console

Username	<code>csaTransportUser</code>
Default Password	<code>csaTransportUser</code>
Usage	This account is used to authenticate REST API calls.
To Disable	Do not disable this account.

csaTransportUser User: Cloud Service Management Console, continued

To Change Password	<p>If you change the password to this account, you must update the value of the <code>securityTransportPassword</code> property in the <code>csa.properties</code> file and the <code>idm.csa.password</code> property in the <code>applicationContext.properties</code> file (you must use the same password). You must also update and use the same password for every REST API call that uses the password.</p> <p>Updating the <code>securityTransportPassword</code> property in <code>csa.properties</code></p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties</code> file (where <code>%CSA_HOME%</code> is the directory in which HP Cloud Service Automation is installed) and update the value of the <code>securityTransportPassword</code> property. Determine a suitable new password (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p> <p>Updating the <code>idm.csa.password</code> property in <code>applicationContext.properties</code></p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties</code> file and update the value of the <code>idm.csa.password</code> property. Use the same encrypted password that you entered for the <code>securityTransportPassword</code> property in the <code>csa.properties</code> file.</p> <p>After modifying and saving the changes to the files, restart HP CSA. See "Restart HP CSA" on page 109 for detailed information on how to restart HP CSA.</p>
---------------------------	---

idmTransportUser User: Cloud Service Management Console

Username	idmTransportUser
Default Password	idmTransportUser
Default Roles	ROLE_AMIN, PERM_IMPERSONATE
Usage	This account is used to authenticate REST API calls.
To Disable	Do not disable this account.

idmTransportUser User: Cloud Service Management Console, continued

To Change Password

If you change the password to this account, you must update the value of the `securityIdmTransportUserPassword` property in the `csa.properties` file, the `idmTransportUser` property in the `integrationusers.properties` file, and the `password` attribute in the `idmProvider` section of the `mpp.json` file (you must use the same password). You must also update and use the same password for every REST API call that uses the password.

Updating the `securityIdmTransportUserPassword` property in `csa.properties`

Edit the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file (where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed) and update the value of the `securityIdmTransportUserPassword` property. Determine a suitable new password (see ["Encrypt a Password" on page 110](#) for instructions on encrypting passwords). An encrypted password is preceded by `ENC` without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.

Updating the `idmTransportUser` property in `integrationusers.properties`

Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.

By default, the unencrypted value of this property is:
`idmTransportUser,ROLE_ADMIN,PERM_IMPERSONATE,enabled`

Edit the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\integrationusers.properties` file and update the value of the `idmTransportUser` property. Use the same password that you used for the `securityIdmTransportUserPassword` property in the `csa.properties` file and encrypt the entire value of the `idmTransportUser` property, including the roles and account status (see ["Encrypt a Password" on page 110](#) for instructions on how to encrypt this value). The encrypted value is preceded by `ENC` without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.

Updating the password attribute in `mpp.json`

Edit the `%CSA_HOME%\portal\conf\mpp.json` file (where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed) and update the value of the `password` attribute in the `idmProvider` section and the `keyfile` attribute. Use the same password that you used for the `securityIdmTransportUserPassword` property in the `csa.properties` file and encrypt this password using the password utility that is provided by the Marketplace Portal:

1. Open a command prompt and navigate to the `%CSA_HOME%\portal\bin` directory. For example:

```
C:\Program Files\Hewlett-Packard\CSA\portal\bin
```


idmTransportUser User: Cloud Service Management Console, continued

	<p>2. Run the following command:</p> <pre>..\..\node.js\node passwordUtil</pre> <p>When prompted, enter the name and location of the keyfile to generate (for example, ../conf/keyfile) and the password to encrypt.</p> <p>3. An encrypted password is displayed. Copy the encrypted password to the password attribute value in the idmProvider section. An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value. For example ENC (3oKr7eAo25bEn3Zn2t9wIA==)</p> <p>4. Copy the keyfile name and location to the keyfile attribute.</p> <p>After modifying and saving the changes to the files, restart HP CSA and clear the JBoss server cache. See "Restart HP CSA" on page 109 for detailed information on how to restart HP CSA and the Marketplace Portal.</p> <p>To clear the JBoss server cache, remove the contents from the %CSA_HOME%\jboss-as\standalone\tmp directory.</p>
--	--

oolnboundUser User: Cloud Service Management Console

Username	oolnboundUser
Default Password	cloud
Default Role	ROLE_REST
Usage	This account is used by HP Operations Orchestration to authenticate REST API calls with HP Cloud Service Automation.
To Disable	Do not disable this account.

oolInboundUser User: Cloud Service Management Console, continued

<p>To Change Password</p>	<p>If you change the password to this account, you must update the value of the password in the <code>csa-provider-users.properties</code> file and the <code>securityOoInboundUserPassword</code> property in the <code>csa.properties</code> file (you must use the same password). You must also update and use the same password for every REST API call that uses the password.</p> <p>Updating the oolInboundUser property in csa-provider-users.properties</p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-provider-users.properties</code> file. Update the password portion of the <code>ooInboundUser</code> value and encrypt the entire value, including the roles and account status (see "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p> <div style="background-color: #f0f0f0; padding: 10px; margin: 10px 0;"> <p>Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.</p> <p>By default, the unencrypted value of this property is: <code>ccloud,ROLE_REST,enabled</code></p> </div> <p>You must also update and use the same password for the <code>CSA_REST_CREDENTIALS</code> system account in HP Operations Orchestration (located in the Configuration folder of the Public Repository).</p> <p>Updating the securityOoInboundUserPassword property in csa.properties</p> <p>If you change the password to this account, you must update the value of the <code>securityOoInboundUserPassword</code> property in <code>csa.properties</code>. You must also update and use the same password for the <code>CSA_REST_CREDENTIALS</code> system account in HP Operations Orchestration (located in the Configuration folder of the Public Repository).</p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties</code> file (where <code>%CSA_HOME%</code> is the directory in which HP Cloud Service Automation is installed) and update the value of the <code>securityOoInboundUserPassword</code> property. Use the same encrypted password that you entered for the <code>ooInboundUser</code> property in the <code>csa-provider-users.properties</code> file.</p> <p>After modifying the <code>csa.properties</code> file, restart HP CSA. See "Restart HP CSA" on page 109 for detailed information on how to restart HP CSA.</p>
----------------------------------	--

cdalInboundUser User: Cloud Service Management Console

<p>Username</p>	<p><code>cdalInboundUser</code></p>
------------------------	-------------------------------------

cdainboundUser User: Cloud Service Management Console, continued

Default Password	CDA2CSAIntegration!
Default Role	ROLE_REST
Usage	This account is used by HP Continuous Delivery Automation (HP CDA) to authenticate REST API calls with HP Cloud Service Automation.
To Disable	Do not disable this account.
To Change Password	<p>If you change the password to this account, you must update the value of the password in the <code>csa-provider-users.properties</code> file and the <code>securityCdaInboundUserPassword</code> property in the <code>csa.properties</code> file (you must use the same password). You must also update and use the same password for every REST API call that uses the password.</p> <p>Updating the <code>cdainboundUser</code> property in <code>csa-provider-users.properties</code></p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-provider-users.properties</code> file. Update the password portion of the <code>cdainboundUser</code> value and encrypt the entire value, including the roles and account status (see "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p> <div style="background-color: #f0f0f0; padding: 10px; margin: 10px 0;"> <p>Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.</p> <p>By default, the unencrypted value of this property is: <code>CDA2CSAIntegration!,ROLE_REST,enabled</code></p> </div> <p>Updating the <code>securityCdaInboundUserPassword</code> property in <code>csa.properties</code></p> <p>If you change the password to this account, you must update the value of the <code>securityCdaInboundUserPassword</code> property in <code>csa.properties</code>. You must also update and use the same password in HP CDA.</p> <p>Edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties</code> file (where <code>%CSA_HOME%</code> is the directory in which HP Cloud Service Automation is installed) and update the value of the <code>securityCdaInboundUserPassword</code> property. Use the same encrypted password that you entered for the <code>cdainboundUser</code> property in the <code>csa-provider-users.properties</code> file.</p> <p>After modifying the <code>csa.properties</code> file, restart HP CSA. See "Restart HP CSA" on page 109 for detailed information on how to restart HP CSA.</p>

Marketplace Portal User Account

The following is a sample user that ships with HP CSA and is used to access the Marketplace Portal:

consumer User: Marketplace Portal

Username	consumer
Default Password	cloud
Default Roles	SERVICE_CONSUMER, ROLE_REST
Usage	This account is used to initially log in to and experiment with the Marketplace Portal (LDAP does not have to be configured). This user belongs to the "CSA consumer internal group" and is a member of the "CSA Consumer" organization (both the group and organization are provided as samples).
To Disable	<p>Edit the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-consumer-users.properties file. Update the consumer property to disable this user account. For example, set consumer to the following value (this value should be encrypted):</p> <pre>cloud,SERVICE_CONSUMER,ROLE_REST,disabled</pre> <p>Note: This property not only determines if the account is enabled, it also contains the password and the roles that control access to HP CSA.</p> <p>By default, the unencrypted value of this property is:</p> <pre>cloud,SERVICE_CONSUMER,ROLE_REST,enabled</pre> <p>See "Encrypt a Password" on page 110 for instructions on how to encrypt this value). The encrypted value is preceded by ENC without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.</p>

consumer User: Marketplace Portal, continued

**To
Change
Password**

Edit the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-consumer-users.properties file. Update the password portion of the consumer value and encrypt the entire value, including the roles and account status (see ["Encrypt a Password" on page 110](#) for instructions on how to encrypt this value). The encrypted value is preceded by ENC without any separating spaces and is enclosed in parentheses. Ensure there is no blank space at the end of the value.

Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.

By default, the unencrypted value of this property is:
c1oud,SERVICE_CONSUMER,ROLE_REST,enabled

Chapter 9: Configure IPv6

This chapter explains how to configure HP CSA to support IPv6 (both dual-stack and IPv6-only). Make sure that IPv6 has been implemented on the system on which HP CSA is running (including configuring the network and DNS) and that your Web browser, such as Firefox or Chrome, have been enabled for IPv6 support.

To configure HP CSA to support IPv6, open %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml in a text editor and make the following changes:

1. Locate and comment out the following line:

```
<property name="java.net.preferIPv4Stack" value="true" />
```

2. Add the following two lines below the commented out line:

```
<property name="java.net.preferIPv4Stack" value="false" />  
<property name="java.net.preferIPv6Addresses" value="true" />
```

3. Locate and comment out the following line:

```
<wsdl-host>${jboss.bind.address:127.0.0.1}</wsdl-host>
```

4. Add the following line below the commented out line:

```
<wsdl-host>${jboss.bind.address:[::1]}</wsdl-host>
```

5. Locate and comment out the following line:

```
<inet-address value="${jboss.bind.address.management:127.0.0.1}" />
```

6. Add the following line below the commented out line:

```
<inet-address value="${jboss.bind.address.management:[::1]}" />
```

7. Locate and comment out the following line:

```
<inet-address value="${jboss.bind.address:0.0.0.0}" />
```

8. Add the following line below the commented out line:

```
<inet-address value="${jboss.bind.address:[::]}" />
```

To configure the Marketplace Portal to support IPv6, do the following:

- Open the `%CSA_HOME%\portal\conf\mpp.json` file in a text editor.
- In the general attribute section (for example, after the `uid` attribute), add a `bindIP` attribute and set the value to the IPv6 address to which the Marketplace Portal binds.
- Save and close the file.

To configure HP CSA tools (such as the process definition tool, purge tool, schema installation tool, provider tool, or content archive tool) to support IPv6, when configuring the `db.url`, `dbUrl`, or `jdbc.databaseUrl` attribute in the database file used by the tool (for example, `config.properties`, `jdbc.properties`, or `db.properties`), enclose the IPv6 address in square brackets (for example, `[f000:253c::9c10:b4b4]` or `[::1]`).

Chapter 10: Common Access Card

This chapter provides information about the integration between a Common Access Card (CAC) and HP CSA, where CAC is used as the user authentication mechanism. By configuring CAC, you are able to log into HP CSA using a Personal Identity Verification (PIV) card.

Caution: If you configuring HP CSA to be compliant with FIPS 140-2, do NOT configure CAC before configuring HP CSA to be compliant with FIPS 140-2. If you have configured any feature before configuring HP CSA to be compliant with FIPS 140-2, you must re-install HP CSA.

After integrating HP CSA with CAC, you can log in to the Cloud Service Management Console and the Marketplace Portal using a PIV card with a valid certificate, log in to the Cloud Service Management Console and the Marketplace Portal using an HP CSA out-of-the-box user account without a PIV card, and cannot log in to the Cloud Service Management Console and the Marketplace Portal as a valid LDAP user without a PIV card.

Caution: For the Cloud Service Management Console and for the Marketplace Portal, single sign-on (SSO) cannot be enabled at the same time as CAC.

Caution: For the Cloud Service Management Console, in a standard environment (not a FIPS 140-2 compliant environment), only the JKS keystore type is supported for CAC. In a FIPS 140-2 compliant environment, only the PKCS #12 keystore type is supported for CAC.

Complete the following steps to integrate HP CSA with CAC:

- [Stop HP CSA](#)
- [Update JBoss configuration to set up client authentication](#)
- [Configure the Cloud Service Management Console](#)
- [Configure the Marketplace Portal](#)
- [Configure certificate revocation](#)
- [Start HP CSA](#)

Stop HP CSA

To stop HP CSA:

1. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Cloud Service Automation service and select **Stop**.
3. Right-click on the HP Marketplace Portal service and select **Stop**.
4. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.

Update JBoss Configuration to Set Up Client Authentication

To update the JBoss configuration, do the following:

1. Download the CA certificate for the digital certificate from the PIV card.
2. Import the CA certificate into a new truststore. The truststore type is determined by the HP CSA environment. That is, if HP CSA is running in a standard environment, the truststore type must be JKS. If HP CSA is running in a FIPS 140-2 compliant environment, the truststore type must be PKCS #12. For example, in a standard environment, if you named the CA certificate from step 1 CACcert.cer, saved it in C:\, and want to create a truststore named %CSA_HOME%\jboss-as\standalone\configuration\.piv_keystore, run the following command:

```
"<csa_jre>\bin\keytool" -importcert -file C:\CACcert.cer -alias caccert -keystore %CSA_HOME%\jboss-as\standalone\configuration\.piv_keystore -storepass changeit
```

3. In the %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml file, add the `ca-certificate-file=<Location of truststore>` and `ca-certificate-password=<truststore password>` attributes to the `<ssl>` element and update the `verify-client` parameter in the `<ssl>` element to `want`. For example, change the following from:

```
<ssl name="ssl" key-alias="CSA" certificate-key-file="%CSA_HOME%\jboss-as\standalone\configuration\.keystore" verify-client="false"/>
```

to

```
<ssl name="ssl" key-alias="CSA" certificate-key-file="%CSA_HOME%\jboss-as\standalone\configuration\.keystore" ca-certificate-file="%CSA_HOME%\jboss-as\standalone\configuration\.piv_keystore" ca-certificate-password="TruststorePassword" verify-client="falsewant" />
```

Note: This example stores the password in clear text. If you want to use an encrypted password, follow the instructions at <https://community.jboss.org/wiki/JBossAS7SecuringPasswords> to create a password vault for JBoss.

If you are configuring CAC in a FIPS 140-2 compliant environment, you must encrypt the password.

Note: If you are using the vault scripts, verify that the %JAVA_HOME% environment variable has been defined, verify that %JAVA_HOME% has been set to the directory in which the JRE that is used by HP CSA is installed, and, if the directory path name includes a space, that the value has been enclosed in quotations marks. For example, to set %JAVA_HOME% to a directory path name that includes a space, from a command prompt, type
set JAVA_HOME="C:\Program Files\Hewlett-Packard\CSA\jre"

To verify that %JAVA_HOME% has been defined, from a command prompt, type
echo %JAVA_HOME%.

The following is an example of an encrypted password attribute using the JBoss password vault:

```
password="{VAULT::<vault_block_example>::password::N2NhZDzOMtES0ZGE4MmEtX0}"
```

Configure the Cloud Service Management Console

Complete the following steps to integrate the Cloud Service Management Console with CAC:

1. Open the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties file in a text editor and uncomment the following line:

```
enableCAC=true
```

2. Update the Spring Security configuration. Open the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml file in a text editor and make the following changes:
 - a. Locate the x509 and custom filter config for CAC comment and uncomment the following line:

```
<x509 subject-principal-regex="CN=(.*?)," user-service-ref="cacUserDetailsService" />
```

Note: The <x509 subject-principal-regex="CN=(.*?)," user-service-

```
ref="cacUserDetailsService" /> line uses a regular expression to let Spring know that it should extract the CN (Common Name) from the certificate and use it as the username of the user to load the user details. If the username is not stored as the CN in the certificate, you can change the regex to pick it up from the relevant field.
```

- b. Locate and uncomment the following line:

```
<custom-filter position="LAST" ref="cacFilter" />
```

Note: The `<custom-filter position="LAST" ref="cacFilter" />` line defines the custom filter to be used and specifies that it will need to be set as the LAST filter in the chain of filters.

- c. Locate the `Below is logout filter definition` comment.

Verify that `<beans:constructor-arg value="/logout.jsp"/>` is commented out. If it is not, comment it out.

Uncomment the following content:

```
<beans:constructor-arg value="http://www.hp.com"/>
```

Update the value to point to a URL of your choice (outside of the HP CSA application URLs).

Note: The URL must start with `http://` and cannot start with just `www`.

- d. Locate the `Bean definitions for CAC` comment and uncomment the content that follows it:

```
<beans:bean id="cacUserDetailsService"  
  class="com.hp.csa.authn.impl.CACUserDetailsServiceImpl">  
  <beans:property name="restRole" value="ROLE_REST" />  
</beans:bean>  
<beans:bean id="cacFilter" class="com.hp.csa.authn.impl.CACFilter" />
```

Configure the Marketplace Portal

Complete the following steps to integrate the Marketplace Portal with CAC:

1. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext-security.xml` file in a text editor.
2. Uncomment the `START Certificate Authentication Configuration` section so that it

appears as follows:

```
<!-- START Certificate Authentication Configuration -->
<security:http pattern="/idm/v0/login" use-expressions="true" auto-
config="false">
    <security:http-basic />
    <security:custom-filter ref="requestTokenCompositeFilter"
position="FIRST"/>
    <security:x509 subject-principal-regex="CN=(.*?)," user-service-
ref="cacUserDetailsService" />
    <security:custom-filter position="LAST" ref="cacFilter" />
</security:http>

<bean id="cacFilter"
    class="com.hp.ccue.identity.filter.certificate.CertificateFilter">
    <property name="generateTokenUtil" ref="generateTokenUtil" />
    <property name="loginRedirectionHandler" ref="loginRedirectionHandler"/>
    <property name="tokenFactory" ref="tokenFactory"/>
    <property name="authenticationProvider" ref="cacLdapAuthProvider"/>
</bean>
<!-- END Certificate Authentication Configuration -->
```

Note: The `<security:x509 subject-principal-regex="CN=(.*?)," user-service-ref="cacUserDetailsService" />` line uses a regular expression to let Spring know that it should extract the CN (Common Name) from the certificate and use it as the username of the user to load the user details. If the username is not stored as the CN in the certificate, you can change the regex to pick it up from the relevant field. The `<security:custom-filter position="LAST" ref="cacFilter" />` line defines the custom filter to be used and specifies that it will need to be set as the LAST filter in the chain of filters.

3. Uncomment the `START Simplified Logout Configuration` section so that it appears as follows:

```
<!-- START Simplified Logout Configuration -->
<security:http pattern="/idm/v0/logout" use-expressions="true" auto-
config="false">
    <security:custom-filter ref="simpleLogoutRedirect" position="FIRST"/>
    <security:http-basic />
</security:http>

<bean id="simpleLogoutRedirect"
class="com.hp.ccue.identity.filter.RedirectFilter">
    <property name="url" value="/idm/v0/logout/close"/>
</bean>
<!-- END Simplified Logout Configuration -->
```

4. Uncomment the START Certificate Authentication / SiteMinder SSO / HP SSO Configuration section so that it appears as follows:

```
<!-- START Certificate Authentication / SiteMinder SSO / HP SSO Configuration -  
-->  
  <bean id="loginRedirectionHandler"  
class="com.hp.ccue.identity.filter.LoginRedirectionHandler">  
    <property name="tokenService" ref="tokenService"/>  
  </bean>  
  
<bean name="generateTokenUtil"  
    class="com.hp.ccue.identity.util.GenerateResponseTokenUtil" />  
<!-- END Certificate Authentication / SiteMinder SSO / HP SSO Configuration -->
```

5. Open the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.xml file in a text editor.
6. Uncomment the Certificate Authentication Configuration section so that it appears as follows:

```
<!-- START Certificate Authentication Configuration -->  
<bean id="cacLdapAuthProvider"  
class="com.hp.ccue.identity.filter.certificate.CertificateLdapAuthenticationPro  
vider">  
    <property name="config" ref="csaAuthConfig"/>  
    <property name="templateFactory" ref="csaTemplateFactory"/>  
</bean>  
<bean id="cacUserDetailsService">  
    <property name="restRole" value="ROLE_ADMIN" />  
</bean>  
<!-- END Certificate Configuration -->
```

7. Comment out activeDirectoryAuthProvider and ldapAuthProvider so that they appear as follows:

```
<bean id="multiTenantAuthProvider"  
class="com.hp.ccue.identity.authn.MultiTenantAuthenticationProvider">  
    <property name="providers">  
        <list>  
            <!-- <ref bean="activeDirectoryAuthProvider"/>  
            <!-- <ref bean="ldapAuthProvider"/> -->  
            <ref bean="seededAuthProvider"/>  
        </list>  
    </property>  
    .....  
</bean>  
</bean>
```

Configure Certificate Revocation

You will need to revoke a certificate if it has been compromised in any way or if an employee leaves your organization.

The following are the methods to revoke a certificate:

- Configure HP CSA to use a Certificate Revocation List (CRL)
- Configure HP CSA to Use a Certificate Revocation List Distribution Point (CRL DP)
- Configure HP CSA to Use the Online Certificate Status Protocol (OCSP)

Configure HP CSA to Use a Certificate Revocation List

The following is an example of how to revoke a certificate that was generated by the certificate authority and publish a Certificate Revocation List (CRL) that contains this certificate ID in the list. The CRL must already exist. You will download and save it in a folder on the system where HP CSA is installed and point to its location using the `ca-revocation-url` parameters.

1. Copy the CRL file to the system where HP CSA is installed (for example, copy it to the `<crl_file_directory>` directory).
2. In the `%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` file, add the `ca-revocation-url="<crl_file_directory>"` attribute to the `<ssl>` element. For example, change the following from:

```
<ssl name="ssl" key-alias="CSA" certificate-key-file="%CSA_HOME%\
jboss-as\standalone\configuration\.keystore"
ca-certificate-file="<csa_jre>\lib\security\cacerts"
verify-client="want"/>
```

to

```
<ssl name="ssl" key-alias="CSA" certificate-key-file="%CSA_HOME%\
jboss-as\standalone\configuration\.keystore"
ca-certificate-file="<csa_jre>\lib\security\cacerts"
verify-client="want" ca-revocation-url="<crl_file_directory>" />
```

3. Log in to the Cloud Service Management Console or the Marketplace Portal using a revoked certificate. The Secure Connection Failed message should display in the browser.

After restarting HP CSA (described below), you should log in to the Cloud Service Management Console or the Marketplace Portal using a revoked certificate. The Secure Connection Failed message should display in the browser.

Configure HP CSA to Use a Certificate Revocation List Distribution Point

To enable a Certificate Revocation List Distribution Point (CRL DP), edit the `%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` file and enable revocation and CRL DP by adding the following lines under `<system-properties>`:

```
<property name="com.sun.net.ssl.checkRevocation" value="true"/>
<property name="com.sun.security.enableCRLDP" value="true"/>
```

Configure HP CSA to Use the Online Certificate Status Protocol

To enable the Online Certificate Status Protocol (OCSP), do the following:

1. Edit the `%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` file and enable revocation by adding the following line under `<system-properties>`:

```
<property name="com.sun.net.ssl.checkRevocation" value="true"/>
```

2. Edit the `<csa_jre>\lib\security\java.security` file and uncomment the following line (where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed):

```
ocsp.enable=true
```

Start HP CSA

See "[Start HP CSA](#)" on page 109 for detailed information on how to start HP CSA.

Chapter 11: Single Sign-On

This chapter provides information about integrating HP CSA with a single sign-on solution.

Tasks include:

- ["Integrate with HP Single Sign-On" below](#)
- ["Integrate HP CSA with a Single Sign-On Solution" on page 148](#)
- ["Integrate HP CSA with CA SiteMinder" on page 152](#)

Integrate with HP Single Sign-On

HP Single Sign-On (HP SSO) is included with HP CSA and can be used only from the Cloud Service Management Console when launching an application from the Cloud Service Management Console. HP SSO must be installed and configured on the application before single sign-on can be integrated between it and HP CSA.

Details on how to integrate HP SSO between HP CSA and HP Operations Orchestration or HP IT Executive Scorecard are included in the documentation for HP CSA. Information regarding HP Operations Orchestration can be found in this guide (the tasks are located in ["HP Operations Orchestration" on page 46](#)). Information regarding HP IT Executive Scorecard can be found in the *HP Cloud Service Management Console Help*.

If you want to integrate HP SSO between HP CSA and another application (the application must be launched from the Cloud Service Management Console), you must use HP CSA's `cryptoInitString` attribute value. This value can be found in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\hpsssoConfiguration.xml` file. Information on how to integrate HP SSO between HP CSA and other applications is not provided in this guide.

The following sections describe how to enable HP SSO if it was not enabled during installation and how to disable HP SSO.

Enable HP Single Sign-On

HP CSA installs HP SSO during installation which may have been enabled or disabled . If HP SSO was not enabled during installation and you want to start using HP SSO, complete the following tasks:

Note: If you enabled HP SSO during the installation of HP CSA, you do not need to complete these tasks.

Caution: If HP SSO and CA SiteMinder are both configured for HP CSA, and if only HP SSO is

enabled for another application, a user logging out from the other application will not be logged out from HP CSA. For example, if HP SSO is enabled between HP CSA and HP Operations Orchestration, when a user logs out from HP Operations Orchestration Central, the user will not be logged out from the Cloud Service Management Console.

1. Configure the domain
2. Set the HP SSO property
3. Configure the Identity Management component
4. Restart HP CSA

Configure the Domain

Complete the following steps to configure the domain name of the network of the server on which HP CSA is installed. Applications launched from the Cloud Service Management Console with which you want to use HP SSO must be installed on systems that belong to this domain.

1. Navigate to the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF` directory where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed. For example:

```
C:\Program Files\Hewlett-Packard\CSA\jboss-as\standalone\deployments\  
csa.war\WEB-INF
```

2. Make a backup copy of the `hpssoConfiguration.xml` file.
3. Open the `hpssoConfiguration.xml` file in a text editor.
4. Locate the following content:

```
<creationDomains>  
  <domain>sso.domain</domain>  
</creationDomains>
```

5. Change `sso.domain` to domain name of the network of the server on which HP CSA is installed. Applications launched from the Cloud Service Management Console with which you want to use HP SSO must be installed on systems that belong to this domain.

For example, if your system hostname is `csa_system.xyz.com`, enter `xyz.com` as the domain name.

6. Save and exit the file.

Set the HP SSO Property

Complete the following steps to set the HP SSO property.

1. Navigate to the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes directory.
2. Make a backup copy of the csa.properties file.
3. Open the csa.properties file in a text editor.
4. Locate the following content:

```
#enableHPSSO=true
```

5. Uncomment this line.
6. Save and exit the file.

Configure the Identity Management Component

Complete the following steps to configure the Identity Management component.

1. Navigate to the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF directory.
2. Open the web.xml file in a text editor.
3. Locate the following comment (near the end of the file):

```
<!-- START HP SSO Configuration -->
```

4. Uncomment the following content after this comment:

```
<listener>  
  <listener-class>com.hp.hpsso.HpSsoContextListener</listener-class>  
</listener>  
  
<context-param>  
  <param-name>com.hp.sw.bto.ast.security.lwssso.conf.fileLocation</param-name>  
  <param-value>C:\Program Files\Hewlett-Packard\CSA\jboss-as-7.1.1.Final\  
standalone\deployments\idm-service.war\WEB-INF\hpssoConfig.xml</param-value>  
</context-param>
```

5. Update the directory path name in <param-value> from "jboss-as-7.1.1.Final" to "jboss-as." For example, change

```
<param-value>C:\Program Files\Hewlett-Packard\CSA\jboss-as-7.1.1.Final\  
standalone\deployments\idm-service.war\WEB-INF\hpssoConfig.xml</param-value>
```

to

```
<param-value>C:\Program Files\Hewlett-Packard\CSA\jboss-as\standalone\
deployments\idm-service.war\WEB-INF\hpssoConfig.xml</param-value>
```

6. Save and exit the file.

Restart HP CSA

Restart HP CSA:

1. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Cloud Service Automation service and select **Restart**.
3. Right-click on the HP Marketplace Portal service and select **Restart**.

Disable HP Single Sign-On

If you no longer want to use HP SSO, you can disable it. Do the following:

1. Navigate to the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes directory.
2. Make a backup copy of the csa.properties file.
3. Open the csa.properties file in a text editor.
4. Locate the following content:

```
enableHPSSO=true
```
5. Change **true** to **false**.
6. Save and exit the file.
7. Restart HP CSA:
 - a. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service and select **Restart**.
 - c. Right-click on the HP Marketplace Portal service and select **Restart**.

Integrate HP CSA with a Single Sign-On Solution

While HP CSA provides an SSO solution using CA SiteMinder, there are a variety of scenarios where you may need to perform the integration with HP CSA using another SSO solution. For example, you may be using:

- an implementation where you need to authenticate with an SSO vendor other than CA SiteMinder.
- a different deployment architecture than what is provided by HP CSA.
- a different version of CA SiteMinder than what is supported by HP CSA.
- an entirely different architecture than that which is supported.

In such cases it makes sense to create a custom SSO solution so that you can extend the HP-provided implementation to your own.

For the Cloud Service Management Console and for the Marketplace Portal, SSO cannot be enabled at the same time as CAC.

Verify the HP CSA Provider Organization's LDAP Server Configuration

You should verify that an LDAP user can log into the Cloud Service Management Console and the Marketplace Portal, which should already be configured. By performing this verification, you can be confident that any login issues that occur after integration have nothing to do with this particular configuration.

If there are any login issues, then update or configure the LDAP server for both the provider organization and the consumer organization from the Cloud Service Management Console, which is the interface from which you perform all administration tasks for *both* the Cloud Service Management Console and the Marketplace Portal.

Note: You must configure the HP CSA Provider organization to use the same LDAP server used by the custom SSO Server. If you do not configure this access point, no one will be able to access the Cloud Service Management Console.

To configure or update the provider organization's LDAP server:

1. Launch the Cloud Service Management Console by typing the following URL in a supported Web browser: `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which the Cloud Service Management Console resides.
2. Log in to the Cloud Service Management Console as a CSA Administrator.

3. Click the **Organizations** tile.
4. In the left-navigation frame, select the provider organization.
5. From the provider organization's navigation frame, select **LDAP**.
6. Update the LDAP server information.
7. Click **Save**.

Verify the HP CSA Consumer Organization's LDAP Server Configuration

Note: The same LDAP server must be used by the HP CSA Provider organization, HP CSA consumer organization and custom SSO Server.

To configure or update the consumer organization's LDAP server:

1. Launch the Cloud Service Management Console by typing the following URL in a supported Web browser: `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which the Cloud Service Management Console resides.
2. Log in to the Cloud Service Management Console as the CSA Administrator.
3. Click the **Organizations** tile.
4. In the left-navigation frame, select a consumer organization.
5. From the consumer organization's navigation frame, select **LDAP**.
6. Update the LDAP server information.
7. Click **Save**.
8. Repeat these steps for every consumer organization configured in HP CSA.

Only the `/csa` and `/mpp` contexts are supported (this is required by the SSO proxy setup).

Configure the Custom SSO Server to Work with HP CSA

To configure your custom SSO server to work with HP CSA, follow the instructions provided with your SSO application.

Stop HP CSA

To stop HP CSA:

1. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Cloud Service Automation service and select **Stop**.
3. Right-click on the HP Marketplace Portal service and select **Stop**.
4. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.

Configure the Cloud Service Management Console

To configure the Cloud Service Management Console:

1. Update the `applicationContext-security.xml` file as appropriate for your custom SSO solution (based on the Spring Security Framework documentation).
2. Update the `csa.properties` file by uncommenting the string `enableSSO=true` and setting the value of `csa.subscriber.portal.url` to `{<protocol>}://{<host>}/mpp/org/{<orgName>}`.

Configure the Marketplace Portal

To configure the Marketplace Portal:

1. Change `proxy` in the `mpp.json` file to the IP address of the proxy to be used by SSO. See the *Configure Proxy Mapping* section for details.
2. Update the `applicationContext-security.xml` file as appropriate for your custom SSO solution (based on the Spring Security Framework documentation).
3. Update the `applicationContext.xml` file as appropriate for your custom SSO solution (based on the Spring Security Framework documentation).

Configure Proxy Mapping

To configure proxy mapping:

1. Map the `/csa` proxy to the HP CSA deployment.

Caution: Use only `/csa` as the alias. Using another alias may cause HP CSA to fail.

For example, when configuring the alias in an Apache proxy server, set the following:

```
ProxyPass /csa https://<csahostname>:8444/csa/  
ProxyPassReverse /csa https://<csahostname>:8444/csa/
```

2. Map the `/idm-service` proxy to the identity management (IdM) deployment.
3. Map the `/mpp` proxy to the Marketplace Portal deployment.

Start HP CSA

To start HP CSA:

1. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for the `keystorePasswordFile` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

2. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
3. Right-click on the HP Cloud Service Automation service and select **Start**.
4. Right-click on the HP Marketplace Portal service and select **Start**.
5. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Start**.

Verify the SSO Integration


You should verify that the SSO integration works by logging into both the Cloud Service Management Console and the Marketplace Portal using the newly-integrated SSO solution.

Integrate HP CSA with CA SiteMinder

HP CSA, as well as SiteMinder with a reverse proxy solution, must already be installed and configured before you can integrate them. The LDAP server shared by HP CSA and SiteMinder must be configured for the HP CSA provider and consumer organization (from the Cloud Service Management Console) before integration between HP CSA and SiteMinder is started.

SiteMinder is made up of several components that work with HP CSA and your LDAP server to provide secure access. The information provided in this section configures HP CSA to work with a reverse proxy solution, as shown in the following diagram.

Supported SiteMinder Deployment Architecture



For more information about how to install and configure CA SiteMinder for a reverse proxy solution, refer to the *Configure Reverse Proxy Servers* section in the *Web Agent Configuration Guide* (a Web Agent guide), which is located at the following URL:

https://supportcontent.ca.com/cadocs/0/CA%20SiteMinder%20r12%20SP2-ENU/Bookshelf_Files/HTML/index.htm?toc.htm?1004185.html

Complete the following steps to integrate HP CSA and SiteMinder:

- Configure the HP CSA Provider and Consumer Organization's LDAP Server
- Configure the SiteMinder Policy Server for HP CSA integration
- Configure HP CSA for SiteMinder integration

Configure the HP CSA Provider Organization's LDAP Server

You must configure the HP CSA provider organization to use the same LDAP server used by the SiteMinder Policy Server. If you do not configure this access point before integrating HP CSA and SiteMinder, you will not be able to access HP CSA after integration.

Caution: LDAP must be configured for the HP CSA provider organization before you begin the integration between HP CSA and SiteMinder. After integrating HP CSA and SiteMinder, you can only log in to the Cloud Service Management Console via SiteMinder using a valid user from this LDAP directory. The out-of-the-box HP CSA users can no longer be used to log in to HP CSA.

When using the REST API, the out-of-the-box HP CSA users are still valid after integration.

To configure the provider organization's LDAP server, do the following:

1. Launch the Cloud Service Management Console by typing the following URL in a supported Web browser: `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which the Cloud Service Management Console resides.
2. Log in to the Cloud Service Management Console as a CSA Administrator.
3. Click the **Organizations** tile.
4. In the left-navigation frame, select the provider organization.
5. From the provider organization's navigation frame, select **LDAP**.
6. Update the LDAP server information.
7. Click **Save**.

Configure the HP CSA Consumer Organization's LDAP Server

You must configure each HP CSA consumer organization to use the same LDAP server used by the SiteMinder Policy Server. If you do not configure this access point, no one will be able to access the Marketplace Portal.

To configure a consumer organization's LDAP server, do the following:

1. Launch the Cloud Service Management Console by typing the following URL in a supported Web browser: `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which the Cloud Service Management Console resides.
2. Log in to the Cloud Service Management Console as the CSA Administrator.
3. Click the **Organizations** tile.
4. In the left-navigation frame, select a consumer organization.
5. From the consumer organization's navigation frame, select **LDAP**.
6. Update the LDAP server information.
7. Click **Save**.
8. Repeat these steps for every consumer organization configured in HP CSA.

Configure the SiteMinder Policy Server for HP CSA Integration

Complete the following steps to configure the SiteMinder Policy Server for HP CSA integration.

1. Navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Marketplace Portal service and select **Stop**.
3. Configure the SiteMinder Policy Server to use the LDAP server that will be shared between HP CSA and SiteMinder.
4. Configure the SiteMinder Policy Server idle timeout, the Cloud Service Management Console session timeout, and the Marketplace Portal session timeout to be the same amount of time, regardless of the units (minutes or seconds) used by the parameters in the respective configuration files. By default, the session timeout value for the Cloud Service Management Console is 60 minutes, and for the Marketplace Portal, it is 1800 seconds.

The session timeout for the Cloud Service Management Console is configured using the `session-timeout` parameter in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\web.xml` file:

```
...  
<session-config>  
...  
  <session-timeout>60</session-timeout>  
...
```

The session timeout for the Marketplace Portal is configured using the `timeoutDuration` parameter in the `%CSA_HOME%\portal\conf\mpp.json` file:

```
...  
"session": {  
...  
  "timeoutDuration": 1800,  
...  
}
```

The timeout should match that of the `timeoutDuration` parameter in the `%CSA_HOME%\portal\conf\mpp.json` file:

5. Configure the SiteMinder Policy Server cleanup interval for the Marketplace Portal. By default, the cleanup interval is 3600 seconds.

The cleanup interval for the Marketplace Portal is configured using the `cleanupInterval` parameter in the `%CSA_HOME%\portal\conf\mpp.json` file:

```
...  
"session": {  
...  
  "cleanupInterval": 3600  
...  
}
```

The `cleanupInterval` parameter is not directly related to the `timeoutDuration` parameter, but it should be twice that of the `timeoutDuration` parameter.

6. To process image file names that contain spaces, from the SiteMinder Policy Server, either comment out the `BadUrlChars` parameter or modify the SiteMinder Policy Server to allow image file names that contain spaces.
7. Navigate to **Control Panel > Administrative Tools > Services**.
8. Right-click on the HP Marketplace Portal service and select **Start**.

Configure HP CSA for SiteMinder Integration

To configure HP CSA for SiteMinder integration, you must:

- Stop HP CSA
- Configure the Cloud Service Management Console
- Configure the Marketplace Portal
- Start HP CSA

Stop HP CSA

To stop HP CSA:

1. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Cloud Service Automation service and select **Stop**.
3. Right-click on the HP Marketplace Portal service and select **Stop**.
4. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.

Configure the Cloud Service Management Console

Complete the following steps to configure the Cloud Service Management Console for a SiteMinder reverse proxy solution. Update the `applicationContext-security.xml` file:

1. Navigate to the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF` directory where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed. For example:

```
C:\Program Files\Hewlett-Packard\CSA\jboss-as\standalone\deployments\csa.war\WEB-INF
```

2. Make a backup copy of the `applicationContext-security.xml` file.
3. Open the `applicationContext-security.xml` file in a text editor.
4. Locate the `SSO Authentication Provider` comment and uncomment the following content that appears after this comment:

```
<security:authentication-provider ref='ssoAuthenticationProvider' />
```

5. Locate the `custom filter config for SSO` comment and uncomment the following content that appears after this comment:

```
<custom-filter position="PRE_AUTH_FILTER" ref="ssoSiteminderFilter" />
```

6. Locate the `Below is logout filter definition` comment and uncomment the following content that appears after this comment:

```
<beans:constructor-arg value="/ssologout.jsp"/>
```

7. In the same section of the file, comment out the following content:

```
<beans:constructor-arg value="/logout.jsp"/>
```

8. Locate the Bean definitions for SSO comment and uncomment the following content that appears after this comment:

```
<beans:bean id="ssoSiteminderFilter"
  class="com.hp.csa.authn.impl.SSOHeaderAutheticationFilter">
  <beans:property name="principalRequestHeader" value="SM_USER" />
  <beans:property name="authenticationManager"
    ref="authenticationManager" />
  <beans:property name="exceptionIfHeaderMissing" value="true" />
  <beans:property name="ignoreURLContaining">
    <beans:list>
      <beans:value>/csa/rest/</beans:value>
      <beans:value>/csa/api/blobstore</beans:value>
    </beans:list>
  </beans:property>
</beans:bean>

<beans:bean id="ssoAuthenticationProvider"
  class="org.springframework.security.web.authentication.preauth.
  PreAuthenticatedAuthenticationProvider">
  <beans:property name="preAuthenticatedUserDetailsService">
    <beans:bean id="userDetailsServiceWrapper"
      class="org.springframework.security.core.userdetails.
      UserDetailsByNameServiceWrapper">
      <beans:property name="userDetailsService"
        ref="ssoPreAuthenticatedUserDetailsService" />
    </beans:bean>
  </beans:property>
</beans:bean>
<beans:bean id="ssoPreAuthenticatedUserDetailsService"
  class="com.hp.csa.authn.impl.SSOUserDetailsService">
  <beans:property name="restRole" value="ROLE_REST" />
</beans:bean>
```

9. Save and exit the file.
10. Navigate to the classes subdirectory (%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes).
11. Open the csa.properties file in a text editor.
12. Edit the following line to configure the URL to display for the organization in the Cloud Service Management Console:

```
csa.subscriber.portal.url={protocol}://{host}:8089/org/{orgName}
```

You can define a hard-coded URL or a URL that is replaced by information as known by the client-side browser. The following tokens are supported: protocol (http or https), host (the host in the browser URL used to access the Cloud Service Management Console), and orgName (the organization name of the selected organization in the browser). For example, if the client URL is

`https://csa-server.company.com:8444/csa`, for a selected organization named `devteam`, then after the token replacement, the client displays a URL of `https://csa-server.company.com:8089/#/login/devteam`. No port is defined, and the `mpp` context is added to the URL. The context should be the same as is defined for the Marketplace Portal in the `mpp.json` file.

13. Locate the `Needed for SSO` comment and uncomment the following content:

```
enableSSO=true
```

14. Save and exit the file.

Configure the Marketplace Portal

Complete the following steps to configure the Marketplace Portal for a SiteMinder reverse proxy solution.

1. Open the `%CSA_HOME%\portal\conf\mpp.json` file in a text editor.
2. In the `idmProvider` section, for `returnUrl`, change `proxy` to the IP address of the proxy to be used by SSO, and add `redirectUrl` as follows with the proxy IP address as well:

```
"idmProvider": {  
    .....  
    "returnUrl": "https://{proxy}/mpp",  
    "redirectUrl": "https://{proxy}",  
    .....  
}
```

For example:

```
"idmProvider": {  
    .....  
    "returnUrl": "https://101.32.24.101/mpp",  
    "redirectUrl": "https://101.32.24.101",  
    .....  
}
```

To enable SSO for the Marketplace Portal, you must also set up a proxy for the Marketplace Portal and for the IdM service. The mapping for the Marketplace Portal should use the same context name (`mpp`) and proxy port as defined in the `%CSA_HOME%\portal\conf\mpp.json` file.

3. Enable the proxy element to be used by SSO by setting `enabled` to `true` as follows:

```
"proxy": {  
  "enabled": true,  
  "port": 8090,  
  "contextPath": "/mpp"  
}
```

You can also customize the value for the port, but you also must make the corresponding change in the SSO configuration for the Marketplace Portal. Do not modify the `contextPath` setting (it must remain set to `/mpp`). See the *Configure Proxy Mapping* section for details.

4. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext-security.xml` file in a text editor.
5. Uncomment the `START SiteMinder SSO Configuration` section so that it appears as follows:

```
<!-- START SiteMinder SSO Configuration -->  
  
<security:http pattern="/idm/v0/login" use-expressions="true" auto-  
config="false">  
  <security:http-basic />  
  <security:custom-filter ref="requestTokenCompositeFilter"  
position="FIRST"/>  
  <security:custom-filter position="PRE_AUTH_FILTER"  
ref="ssoSiteminderFilter" />  
  <security:custom-filter position="LAST" ref="ssoFilter" />  
  
</security:http>  
  
<security:authentication-manager id="ssoAuthManager">  
  <security:authentication-provider ref="ssoAuthenticationProvider"/>  
</security:authentication-manager>  
  
<bean id="ssoSiteminderFilter"  
class="org.springframework.security.web.authentication.preauth.RequestHeaderAut  
henticationFilter">  
  <property name="principalRequestHeader" value="SM_USER"/>  
  <property name="authenticationManager" ref="ssoAuthManager" />  
  <property name="exceptionIfHeaderMissing" value="true" />  
</bean>  
  
<bean id="ssoFilter" class="com.hp.ccue.identity.filter.sso.SSOFilter">  
  <property name="generateTokenUtil" ref="generateTokenUtil" />  
  <property name="tokenFactory" ref="tokenFactory"/>  
  <property name="loginRedirectionHandler" ref="loginRedirectionHandler"/>  
</bean>  
  
<!-- END SiteMinder SSO Configuration -->
```

6. Uncomment the START Simplified Logout Configuration section so that it appears as follows:

```
<!-- START Simplified Logout Configuration -->
<security:http pattern="/idm/v0/logout" use-expressions="true" auto-
config="false">
  <security:custom-filter ref="simpleLogoutRedirect" position="FIRST"/>
  <security:http-basic />
</security:http>

<bean id="simpleLogoutRedirect"
class="com.hp.ccue.identity.filter.RedirectFilter">
  <property name="url" value="/idm/v0/logout/close"/>
</bean>
<!-- END Simplified Logout Configuration -->
```

7. Uncomment the START Certificate Authentication / SiteMinder SSO / HP SSO Configuration section so that it appears as follows:

```
<!-- START Certificate Authentication / SiteMinder SSO / HP SSO Configuration -
->

  <bean id="loginRedirectionHandler"
class="com.hp.ccue.identity.filter.LoginRedirectionHandler">
  <property name="tokenService" ref="tokenService"/>
</bean>

<bean name="generateTokenUtil"
class="com.hp.ccue.identity.util.GenerateResponseTokenUtil" />

  <!-- END Certificate Authentication / SiteMinder SSO / HP SSO Configuration --
  >
```

8. Open the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\applicationContext.xml file in a text editor.

9. Uncomment the START SiteMinder SSO Configuration section so that it appears as follows:

```
<!-- START SiteMinder SSO Configuration -->

<bean id="ssoAuthenticationProvider"
class="org.springframework.security.web.authentication.preauth.PreAuthenticated
AuthenticationProvider">
  <property name="preAuthenticatedUserDetailsService">
    <bean id="userDetailsServiceWrapper"
class="org.springframework.security.core.userdetails.UserDetailsServiceWr
apper">
      <property name="userDetailsService"
ref="ssoPreAuthenticatedUserDetailsService" />
    </bean>
```



```
    </property>
</bean>

<bean id="ssoPreAuthenticatedUserDetailsService"
class="com.hp.ccue.identity.filter.sso.SSOUserDetailsServiceImpl">
    <property name="restRole" value="ROLE_REST" />
</bean>

<!-- END SiteMinder SSO Configuration -->
```

Start HP CSA

To start HP CSA:

1. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for the `keystorePasswordFile` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

2. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
3. Right-click on the HP Cloud Service Automation service and select **Start**.
4. Right-click on the HP Marketplace Portal service and select **Start**.
5. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Start**.

Launch the Marketplace Portal

After completing the Marketplace Portal changes and restarting HP CSA, launch the Marketplace Portal using the URL: `https://<proxy_server_ip>/mpp/`. Depending on the Web agent configuration being used, a proxy server port *may* be required.

Note: If the single sign-on prompt appears multiple times when accessing the Marketplace Portal, you may need to [configure the Marketplace Portal to use the fully-qualified domain name of the SiteMinder Web Agent](#).

Customize the Marketplace Portal Landing Page (Optional)

When accessing the Marketplace Portal during a single sign-on session, the user lands on the landing page displaying a button to be clicked to get to the Marketplace Portal dashboard. By default, the button is labeled "Log In." This might cause confusion as the authentication has already been completed using a single sign-on login prompt. In order to avoid this confusion, the label of the button can be modified:

1. Edit the `%CSA_HOME%\portal\node_modules\mpp-ui\dist\locales\<Locale>\rb.json` file. The location of the file depends on the locale being used. For example, for English, the file is `%CSA_HOME%\portal\node_modules\mpp-ui\dist\locales\en\rb.json`:

Modify the label of the login button. For example, to change the label to "Click to continue," make the following modification:

```
"login": {  
  .....  
  "login": "Click to continue",  
  .....  
}
```

2. Restart the Marketplace Portal service:
 - a. Navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the Marketplace Portal service.
 - c. Select **Restart**.

Customize the Logout Page (Optional)

After clicking the Log out link from the Cloud Service Management Console or the Marketplace Portal, the user is directed to a logout page. This page is customizable.

The following is the name and location of the logout file. There is one file for the Cloud Service Management Console and another file for the Marketplace Portal.

- Cloud Service Management Console:

```
%CSA_HOME%\jboss-as\standalone\deployments\  
csa.war\ssologout.jsp
```

where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed. For example:

```
C:\Program Files\Hewlett-Packard\CSA\jboss-as\  
standalone\deployments\csa.war\ssologout.jsp
```

- Marketplace Portal:

```
%CSA_HOME%\portal\node_modules\mpp-ui\dist\locales\en\rb.json
```

where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed. For example:

```
C:\Program Files\Hewlett-Packard\CSA\portal\node_modules\mpp-  
ui\dist\locales\en\rb.json
```

In the above example, the rb.json file is for the English locale (language) and is therefore in the en folder.

You customize the logout message for your locale by modifying the youAreOut text. For example, for English locales, you can modify the text as follows:

```
"logout":{  
  ...  
  "youAreOut": "Please close your browser window. This prevents the  
possibility of someone pressing the ''Back'' button on your browser and possibly  
viewing confidential information.",  
  ...  
},
```

For other locales, modify the corresponding rb.json files.

Note: By default, after logging out, the user must close the Web browser in order to completely clear the SiteMinder session.

The logout page can be customized to point to a SiteMinder logout page if one is available.

Configure the Marketplace Portal to Use the Fully-Qualified Domain Name of the SiteMinder Web Agent (Optional)

The single sign-on prompt might appear multiple times when trying to access the Marketplace Portal when the domain name generated in the SiteMinder cookie (SMSESSION) does not match the address that is used to access the Marketplace Portal. If this problem occurs, do the following:

1. If the system (from which the browser that accesses the Marketplace Portal is launched) is unable to recognize the fully-qualified domain name of the SiteMinder Web Agent, update the system configuration to define an alias for the fully-qualified domain name to the IP address of the SiteMinder Web Agent. For example, define an alias in the host file.
2. On the system on which the Marketplace Portal is installed, do the following:
 - a. Update the following properties in the %CSA_HOME%\portal\conf\mpp.json file:


```
"idmProvider": {  
  .....
```

```
"returnUrl": "https://<FQDN_OF_SITEMINDER_WEB_AGENT>/mpp",  
"redirectUrl": "https://<FQDN_OF_SITEMINDER_WEB_AGENT>",  
.....  
}
```

- b. Update the system configuration to define an alias for the fully-qualified domain name to the IP address of the SiteMinder Web Agent. For example, define an alias in the host file.
 - c. Restart the system. Verify that the Marketplace Portal service has restarted.
3. On the system on which HP CSA is installed, do the following:
- a. Verify that the Organization URL (the URL used to access the Marketplace Portal) displayed in the Cloud Service Management Console uses the fully-qualified domain name of the SiteMinder Web Agent. To view the Organization URL, from the Cloud Service Management Console dashboard, select the Organizations tile. In the left navigation frame, select the organization. In the organization's navigation frame, select **General Information**.
 - b. If the Organization URL does not use the fully-qualified domain name of the SiteMinder Web Agent, update the `csa.subscriber.portal.url` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.
 - c. If you updated the `csa.subscriber.portal.url` property, restart the HP Cloud Service Automation service (navigate to **Control Panel > Administrative Tools > Services**, right-click on the HP Cloud Service Automation service, and select **Restart**).

Request Flow

The following diagram shows how a request is processed when HP CSA and SiteMinder are integrated.



1. A user sends a request to launch the Marketplace Portal.
2. The request is intercepted by the SiteMinder Web Agent.
3. The SiteMinder Web Agent queries the SiteMinder Policy Server to determine if it is a protected URL.
4. The SiteMinder Policy Server verifies that the URL is protected.
5. The user is redirected by the SiteMinder Web Agent to a login page where the user's credentials are collected.
6. The SiteMinder Web Agent sends the user's credentials to the SiteMinder Policy Server for authentication.
7. The SiteMinder Policy Server authenticates the user's credentials using the LDAP server (SiteMinder Policy Store).
8. The verification of the authenticated user is returned to the SiteMinder Web Agent.

9. The SiteMinder Web Agent redirects the user's request to launch the Marketplace Portal, which uses Identity Management (IdM) to generate the necessary token.
10. The Marketplace Portal uses LDAP to perform the authorization.

Additional requests from the user using the same SiteMinder session are automatically directed by the SiteMinder Web Agent to HP CSA.

Chapter 12: FIPS 140-2 Compliance

This chapter explains how to configure HP CSA to be compliant with Federal Information Processing Standards (FIPS) 140-2.

Caution: Do NOT configure any other feature of HP CSA and do not use any of the HP CSA tools before configuring HP CSA to be compliant with FIPS 140-2. If you have configured any feature or used one of the tools, you must re-install HP CSA before you can configure HP CSA to be compliant with FIPS 140-2.

Note: HP CSA that is compliant with FIPS 140-2 supports the Microsoft SQL database and Oracle JRE only. For more information about application and version requirements, refer to the *HP Cloud Service Automation System and Software Support Matrix*.

FIPS 140-2 is a standard for security requirements for cryptographic modules defined by the National Institute of Standards and Technology (NIST). To view the publication for this standard, go to:

csrc.nist.gov/publications/fips/fips140-2/fips1402.pdf

After you have configured HP CSA for FIPS 140-2 compliance, HP CSA uses or complies with the following:

- RSA BSAFE Crypto software
- Keystore and truststore: PKCS #12
- Asymmetric algorithm: RSA
- Symmetric-key algorithm: AES
- Random number generation algorithm: HMAC DRBG (128-bit)
- Hashing algorithm: SHA-256

Prerequisites

Before configuring HP CSA to be compliant with FIPS 140-2, do the following:

1. Verify that you are configuring a new or fresh installation of HP CSA version 4.20 to be compliant with FIPS 140-2. You cannot configure an upgraded installation of HP CSA version 4.20 or an installation of HP CSA version 4.20 that is in use.

2. Back up the following directories:
 - %CSA_HOME%\jboss-as\standalone\deployments\csa.war\
 - %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\
 - %CSA_HOME%\jboss-as\standalone\configuration\
 - %CSA_HOME%\portal\conf\
 - %CSA_HOME%\node.js\
 - <csa_jre>\lib\security
(where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed)
 - 3. Download and install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy Files from the following site:

<http://www.oracle.com/technetwork/java/javase/downloads/jce-7-download-432124.html>

Refer to the `Readme.txt` file from the downloaded content for information on how to deploy the files and upgrade the JRE used by HP CSA.

4. Download and install the Microsoft Visual C++ 2010 Redistributable Package (x86) from the following site:

<http://www.microsoft.com/en-us/download/details.aspx?id=5555>

5. Install the RSA BSAFE Crypto software files. On the system on which HP CSA is installed, unzip `\rsa\CSAFIPS.zip` to `<csa_jre>\lib\ext\` (where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed).
6. Install the recompiled version NodeJS needed for FIPS compliance. On the system on which HP CSA is installed, unzip `\fips\nodejs-fips-windows.zip` file to the `%CSA_HOME%\node.js\` directory.

Note: Once you have configured HP CSA to be compliant with FIPS 140-2, you cannot revert back to the standard configuration unless you uninstall and re-install HP CSA.

Examples Used in this Section

The following table is a quick reference to the items and values used in the FIPS 140-2 examples. Also included are the names used in this document to reference the items. If you choose to use different values for these items, you must substitute the different value in all of the FIPS 140-2 examples in this document.

Item	Referenced as	Description	Value Used in Examples
Directory where HP CSA is installed	%CSA_HOME%	The directory in which the HP CSA product is installed.	C:\Program Files\ Hewlett-Packard\CSA
Directory where the JRE used by HP CSA is installed	<csa_jre>	The directory in which the JRE used by the HP CSA product is installed. For example, C:\Program Files\ Java\CSA\jre\jre.	<csa_jre>
Keystore for encryption	HP CSA encryption keystore	The keystore that stores the keypair that is used to encrypt and decrypt HP CSA's symmetric key (also known as the secret key). HP CSA's symmetric key is used to encrypt and decrypt HP CSA's data.	%CSA_HOME%\ jboss-as\ standalone\configuration\ csa_encryption_ keystore.p12
Keystore alias for encryption	HP CSA encryption keystore alias	The alias is a name assigned to identify a keypair in the HP CSA encryption keystore. This keypair is used by HP CSA to encrypt and decrypt HP CSA's symmetric key.	csa_encryption_key
Key for encryption	HP CSA encryption keystore file or encrypted symmetric key	This is the file containing HP CSA's encrypted symmetric key and used by HP CSA to encrypt and decrypt data in HP CSA.	%CSA_HOME%\ jboss-as\ standalone\configuration\ key.dat
Keystore password for encryption	HP CSA encryption keystore password	This is the password used to access the HP CSA encryption keystore.	<HP CSA encryption keystore password>
Keystore for secure communication	HP CSA server keystore	This is a file that stores the keypair used for secure communication and is the identity of the HP CSA server.	%CSA_HOME%\ jboss-as\ standalone\configuration\ keystore_csaID.p12

Item	Referenced as	Description	Value Used in Examples
Keystore alias for secure communication	HP CSA server keystore alias	The alias is a name assigned to identify the HP CSA TLS keypair. When used with keytool's <code>-export</code> option, the alias is the name used by the HP CSA server keystore to identify the certificate.	<code>csa_fips</code>
Keystore password for secure communication	HP CSA server keystore password	This is the password used to access the HP CSA server keystore.	<i><HP CSA server keystore password></i>
Certificate for HP CSA	HP CSA's certificate	This is the certificate for HP CSA that must be imported into an application's truststore if HP CSA communicates with this application using TLS.	<code>C:\csa_fips.crt</code>
Truststore for secure communication	HP CSA server truststore	This is the truststore that holds all certificates for trusted applications that communicate with HP CSA using TLS.	<code>%CSA_HOME%\jboss-as\standalone\configuration\csa_server_truststore.p12</code>
Truststore alias for secure communication	HP CSA server truststore alias	When used with keytool's <code>-import</code> option, the alias is a name assigned to identify the certificate imported into the HP CSA truststore. Typically the truststore alias is identical to the keystore alias used to generate the certificate.	<code>csa_fips</code> (alias for HP CSA's certificate) <code>pas</code> (alias for the root certificate of HP Operations Orchestration's Certificate Authority)
Truststore password for secure communication	HP CSA server truststore password	This is the password used to access the HP CSA server truststore.	<i><HP CSA server truststore password></i>

Configuration Overview

Complete the following steps to configure HP CSA to be compliant with FIPS 140-2:

- ["Stop HP CSA" below](#)
- ["Update applicationContext.xml to be FIPS 140-2 Compliant" below](#)
- ["Configure Properties in the Java Security File" on the next page](#)
- ["Create an HP CSA Encryption Keystore" on page 173](#)
- ["Create a New Keystore and Truststore for Secure Communication" on page 177](#)
- ["Re-Encrypt HP CSA Passwords" on page 185](#)
- ["Configure HP CSA Properties" on page 188](#)
- ["Configure the Marketplace Portal" on page 192](#)
- ["Configure the Identity Management Component" on page 196](#)
- ["Start HP CSA" on page 200](#)
- ["Test Secure Connections" on page 201](#)

Stop HP CSA

To stop HP CSA:

1. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Cloud Service Automation service and select **Stop**.
3. Right-click on the HP Marketplace Portal service and select **Stop**.
4. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.

Update applicationContext.xml to be FIPS 140-2 Compliant

1. Open the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext.xml file in a text editor. For example, edit the following file:

```
C:\Program Files\Hewlett-Packard\CSA\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext.xml
```

2. Locate the START Standard Mode Configuration comment and comment out the following content that appears between the START Standard Mode Configuration and END Standard Mode Configuration comments:

```
<bean id="simpleEncryptionConfiguration"  
class="com.hp.csa.security.CSASimplePBCEConfig" init-method="init">  
</bean>
```

```
<bean id="configurationEncryptor"  
class="org.jasypt.encryption.pbe.StandardPBEStrategyEncryptor">  
  <property name="config" ref="simpleEncryptionConfiguration" />  
</bean>
```

```
<bean id="propertyConfigurer" class="org.jasypt.spring.properties.  
EncryptablePropertyPlaceholderConfigurer">  
  <constructor-arg ref="configurationEncryptor" />  
  <property name="locations">  
    <list>  
      <value>classpath:csa.properties</value>  
    </list>  
  </property>  
</bean>
```

3. Locate the START FIPS Mode Configuration comment and uncomment the following content that appears between the START FIPS Mode Configuration and END FIPS Mode Configuration comments:

```
<bean id="configurationEncryptor"  
class="com.hp.csa.security.util.CSAHelper" />
```

```
<bean id="propertyConfigurer" class=  
"com.hp.csa.security.CSAEncryptablePropertyPlaceholderConfigurer">  
  <constructor-arg ref="configurationEncryptor" />  
  <property name="locations">  
    <list>  
      <value>classpath:csa.properties</value>  
    </list>  
  </property>  
</bean>
```

4. Save and close the file.

Configure Properties in the Java Security File

Edit the Java security file for the JRE to add additional security providers and configure properties for FIPS 140-2 compliance. Open the `<csa_jre>\lib\security\java.security` file in an editor (where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed) and do the following:

1. For every provider listed (in the format `security.provider.<nn>=<provider_name>`), increment the preference order number (<nn>) by one. For example, change a provider entry from `security.provider.1=sun.security.provider.Sun` to `security.provider.2=sun.security.provider.Sun`.

2. Add a new default provider (RSA JCE). Add the following provider to the top of the provider list:

```
security.provider.1=com.rsa.jsafe.provider.JsafeJCE
```

3. Update the SunJSSE provider to use packages that are compliant with FIPS 140-2.

For example, change the following entry from:

```
security.provider.<nn>=com.sun.net.ssl.internal.ssl.Provider
```

to

```
security.provider.<nn>=com.sun.net.ssl.internal.ssl.Provider JsafeJCE
```

4. Set the default keystore type to PKCS #12. Edit or add the following entry:

```
keystore.type=PKCS12
```

5. Add the following entry to ensure RSA BSAFE is used in FIPS 140-2 compliant mode:

```
com.rsa.cryptoj.fips140initialmode=FIPS140_SSL_MODE
```

6. Set the default random number generation algorithm to HMAC DRBG with 128-bit security strength:

```
com.rsa.crypto.default.random = HMACDRBG128
```

7. Exit and save the `java.security` file.

Create an HP CSA Encryption Keystore

This section describes an example of how to create a keystore, referred to in this document as the HP CSA encryption keystore, that is used by HP CSA to encrypt and decrypt a key. This key is used to encrypt and decrypt the data in HP CSA. The validity period assigned to the HP CSA encryption keystore is not used by HP CSA.

The examples used in this document saves the keystore in the `%CSA_HOME%\jboss-as\standalone\configuration\` directory. You may choose to store the keystore in any location; however, you must remember to use that location in any other subsequent example.

Note: In the following examples, `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed (for example, `C:\Program Files\Hewlett-Packard\CSA`), the `keytool`

utility is included with the JRE, and a JRE has been installed for HP CSA in `<csa_jre>`.

The following is an example of how to create the HP CSA encryption keystore:

1. Open a command prompt and change directories to `%CSA_HOME%`.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -genkey -alias csa_encryption_key  
-validity 365 -keyalg rsa -keysize 2048 -storetype PKCS12  
-keystore .\jboss-as\standalone\configuration\  
csa_encryption_keystore.p12
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

You can use different values for `-alias`, `-validity`, `-keysize` and `-keystore`. These instructions assume that you will use the `-alias` and `-keystore` values recommended here; you will have to adjust the commands accordingly if you use different values.

Because the HP CSA encryption keystore is used by HP CSA to only encrypt and decrypt a key and not to generate certificates, you can enter any value for `-validity`. The validity period assigned to the HP CSA encryption keystore is not used by HP CSA.

3. Enter a keystore password (referred to in this document as the HP CSA encryption keystore password).

This password is used to control access to the keystore. This password must be the same as the password you enter for the key in step 5 of this task.

Note: You must create a password file with this password whenever HP CSA is started. See ["Start HP CSA" on page 109](#) for more information.

4. Follow the prompts to enter your first and last name, organization, and location values.
5. Enter the keystore password you supplied earlier to use as the key password.

Although `keytool` allows you to enter different passwords for the keystore and the key, the two passwords must be the same to work with HP CSA.

Generate an Encrypted Symmetric Key

This section describes an example of how to generate an encrypted symmetric key that is used by HP CSA to encrypt and decrypt data. This key is also used to encrypt the passwords for the Cloud Service Management Console.

Caution: Do NOT generate the key more than one time.

The following is an example of how to generate an encrypted symmetric key:

1. Open a command prompt and change to the %CSA_HOME%\Tools\PasswordUtil directory. For example:

```
C:\Program Files\Hewlett-Packard\CSA\Tools\PasswordUtil
```

2. Run the following command (this example uses the same example names from ["Create an HP CSA Encryption Keystore" on page 173](#)):

```
"<csa_jre>\bin\java" -jar passwordUtil-standalone.jar genAndEncKey JsafeJCE  
../../jboss-as/standalone/configuration/csa_encryption_keystore.p12 <HP CSA  
encryption keystore password>  
csa_encryption_key  
../../jboss-as/standalone/configuration/key.dat
```

Note: The path separators used in the passwordUtil-standalone.jar script options are forward slashes (/). You can also use double backward slashes (\\) as your path separators.

In this example, the encrypted symmetric key is saved to:

```
%CSA_HOME%\jboss-as\standalone\configuration\key.dat
```

Note: You will use this file name and location when encrypting HP CSA passwords for the Cloud Service Management Console.

If you used different names for the keystore, alias, or encrypted symmetric key file, here is an example of the command without using the example names:

```
"<csa_jre>\bin\java" -jar "%CSA_HOME%\Tools\PasswordUtil\passwordUtil-  
standalone.jar" genAndEncKey JsafeJCE <HP CSA encryption keystore>  
<HP CSA encryption keystore password>  
<HP CSA encryption keystore alias>  
<location and name of the encrypted symmetric key>
```

Note: If you use path separators in the passwordUtil-standalone.jar script options, use either a single forward slash (/) or double backward slashes (\\) as your path separator.

When to Regenerate the HP CSA Encryption Keystore or Encrypted Symmetric Key

You should not regenerate the HP CSA encryption keystore or encrypted symmetric key unless one of the following occurs:

- The HP CSA encryption keystore or encrypted symmetric key was deleted and is not recoverable.
- The HP CSA encryption keystore or encrypted symmetric key was regenerated and the original file is not recoverable.
- The HP CSA encryption keystore password is not retained.

Locate your situation in the table below and perform the tasks starting at the listed step.

Situation	Start at:
Lost HP CSA encryption keystore	Step 1
Lost encrypted symmetric key	Step 2
Regenerated HP CSA encryption keystore	Step 1
Regenerated encrypted symmetric key	Step 3
Forgotten HP CSA encryption keystore password	Step 1

Tasks to perform:

1. Regenerate the HP CSA encryption keystore (see "[Create an HP CSA Encryption Keystore](#)").
2. Regenerate the encrypted symmetric key (see "[Generate an Encrypted Symmetric Key](#)").
3. Encrypt HP CSA passwords (see "[Re-Encrypt HP CSA Passwords](#)" on page 185).
4. Configure HP CSA properties (see "[Configure HP CSA Properties](#)" on page 188). As applicable, update the keystore, keyAlias, encryptedKeyFile, and csaTruststorePassword property values.
5. Reset the password for every organization's LDAP access point:

Update the passwords for the following users in the CSA_ACCESS_POINT table in the database.

- a. Open an SQL client to your database.
- b. Run the following: `update CSA_ACCESS_POINT set password=null;`
- c. Launch the Cloud Service Management Console by typing the following URL in a supported Web browser: `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which the Cloud Service Management Console resides.
- d. Log in to the Cloud Service Management Console as the CSA Administrator.
- e. Click the **Organizations** tile.

- f. In the left-navigation frame, select an organization.
 - g. From the organization's navigation frame, select **LDAP**.
 - h. Enter the password in the **Password** and **Retype Password** fields.
 - i. Click **Save Changes**.
 - j. Repeat steps f - i for every organization.
6. Restart HP CSA.

See "[Restart HP CSA](#)" on page 109 for detailed information on how to restart HP CSA.

Create a New Keystore and Truststore for Secure Communication

To comply with FIPS 140-2, the keystore and truststore (that store the keys and certificates used for secure communication between HP CSA and other applications) must support PKCS #12: Personal Information Exchange Syntax Standard (PKCS #12). You must create a new keystore and truststore for HP CSA for PKCS #12.

This section describes the process you should follow to obtain, install, and configure a certificate that supports PKCS #12 for use by HP CSA.

Perform the following tasks (described in more detail in the sections that follow the list below):

1. Create the HP CSA server keystore that supports PKCS #12
2. Create HP CSA's certificate, create a truststore that supports PKCS #12, and import certificate(s)
3. Configure the Web server
4. Import the HP Operations Orchestration certificate as a trusted certificate
5. Import the VMware vCenter certificate as a trusted certificate
6. Import the certificates for other applications as trusted certificates
7. Configure client browsers (optional)

Note: In the following examples, %CSA_HOME% is the directory in which HP Cloud Service Automation is installed (for example, C:\Program Files\Hewlett-Packard\CSA), the keytool utility is included with the JRE (you may choose to use a different utility), and a JRE has been installed for HP CSA in <csa_jre>.

Step 1: Create an HP CSA Server Keystore that Supports PKCS #12

Create the HP CSA server keystore. For example, do the following:

1. Open a command prompt and change directories to %CSA_HOME%.
2. Run the following command:

```
"<csa_jre>\bin\keytool" -genkey -alias csa_fips -validity 365  
-keyalg rsa -keysize 2048 -storetype PKCS12 -keystore  
.\jboss-as\standalone\configuration\keystore_csaID.p12
```

You can use different values for `-alias`, `-validity`, `-keysize` and `-keystore`. These instructions assume that you will use the `-alias` and `-keystore` values recommended here; you will have to adjust the commands accordingly if you use different values.

3. Enter a keystore password (referred to in this document as the HP CSA server keystore password).

This password is used to control access to the keystore. This password must be the same as the password you enter for the key in task 6 of this step.

4. When you are prompted for your first and last name, enter the fully qualified domain name of the HP CSA server.
5. Follow the prompts to enter the remaining organization and location values.
6. Enter the keystore password you supplied earlier to use as the key password.

Although `keytool` allows you to enter different passwords for the keystore and the key, the two passwords must be the same to work with HP CSA.

Step 2: Create HP CSA's Certificate, Create a Truststore that Supports PKCS #12, and Import Certificate(s)

This section shows examples on how to export a self-signed certificate, create a Certificate Authority-signed certificate (optional), create the HP CSA server truststore that supports PKCS #12, and import the certificates into the truststore and keystore.

Select the type of certificate you will be using (self-signed or Certificate Authority-signed) and complete one of the applicable sections below.

Using a Self-Signed Certificate

Export a self-signed certificate, create the HP CSA server truststore that supports PKCS #12, and import the self-signed certificate into the HP CSA server truststore. For example:

1. Open a command prompt and change directories to %CSA_HOME%.
2. Export a self-signed certificate by exporting HP CSA's certificate:
 - a. Run the following command:

```
"<csa_jre>\bin\keytool" -export -alias csa_fips  
-file C:\csa_fips.crt -storetype PKCS12 -keystore  
.\jboss-as\standalone\configuration\keystore_csaID.p12
```
 - b. When you are prompted for a password, enter the HP CSA server keystore password used in step 1 (where you created the HP CSA server keystore that supports PKCS #12).
3. Create a truststore that supports PKCS #12 and import the self-signed certificate:
 - a. Run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias csa_fips  
-file C:\csa_fips.crt -trustcacerts -keystore  
.\jboss-as\standalone\configuration\csa_server_truststore.p12
```
 - b. When prompted, enter a truststore password (referred to in this document as the HP CSA server truststore password). You will need this password when you import the HP Operations Orchestration and other certificates.
 - c. Enter yes when prompted to trust the certificate.

Using a Certificate Authority-Signed Certificate

Create a self-signed certificate, create a Certificate Authority-signed certificate, import the Certificate Authority-signed certificate into the HP CSA server keystore, create the HP CSA server truststore that supports PKCS #12, and import the root certificate into the HP CSA server truststore. For example:

1. Open a command prompt and change directories to %CSA_HOME%.
2. To create a Certificate Authority-signed certificate, you must create a certificate signing request and submit the certificate signing request to a Certificate Authority:
 - a. From the command prompt, run the following command:

```
"<csa_jre>\bin\keytool" -certreq -alias csa_fips  
-file C:\csacsrfips.csr -keystore  
.\jboss-as\standalone\configuration\keystore_csaID.p12
```
 - b. When you are prompted for a password, enter the HP CSA server keystore password used in step 1 (where you created the HP CSA server keystore that supports PKCS #12).
 - c. Submit the Certificate Signing Request (C:\csacsrfips.csr) to the Certified Authority following the procedure used by your organization or a third-party provider. After the submission has been processed, you will receive a Certificate Authority-signed certificate

(referred to as `C:\ca_signed.crt` in the example below) and a root certificate (referred to as `C:\ca_root.crt` in the example below) for the Certificate Authority.

3. Import the Certificate Authority-signed certificate into the HP CSA server keystore:

a. Open a command prompt and change directories to `%CSA_HOME%`.

b. From the command prompt, run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias ca_signed  
-file C:\ca_signed.crt -keystore  
.\jboss-as\standalone\configuration\keystore_csaID.p12
```

c. When you are prompted for a password, enter the HP CSA server keystore password used in step 1 (where you created the HP CSA server keystore that supports PKCS #12).

4. Create a truststore that supports PKCS #12 and import the root certificate:

a. From the command prompt, run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias ca_root  
-file C:\ca_root.crt -trustcacerts -keystore  
.\jboss-as\standalone\configuration\csa_server_truststore.p12
```

b. When prompted, enter a truststore password (referred to in this document as the HP CSA server truststore password). You will need this password when you import the HP Operations Orchestration and other certificates.

c. Enter yes when prompted to trust the certificate.

Step 3: Configure the Web Server

1. Encrypt the HP CSA server keystore password and datasource (database) password using the vault scripts. Follow the instructions at <https://community.jboss.org/wiki/JBossAS7SecuringPasswords> to create a password vault for JBoss. You will use the encrypted passwords in the following tasks of this step.

Note: If you are using the vault scripts, verify that the `%JAVA_HOME%` environment variable has been defined, verify that `%JAVA_HOME%` has been set to the directory in which the JRE that is used by HP CSA is installed, and, if the directory path name includes a space, that the value has been enclosed in quotations marks. For example, to set `%JAVA_HOME%` to a directory path name that includes a space, from a command prompt, type `set JAVA_HOME="C:\Program Files\Hewlett-Packard\CSA\jre"`

To verify that `%JAVA_HOME%` has been defined, from a command prompt, type `echo %JAVA_HOME%`.

The following is an example of an encrypted password attribute using the JBoss password vault:

```
password="${VAULT::<vault_block_example>::password::N2NhZDzOMtES0ZGE4MmEtX0}"
```

2. Open `%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` in a text editor.
3. Locate the following entry for the HP CSA server keystore password (this entry may have been modified):

```
<ssl name="ssl" key-alias="CSA" certificate-key-file=
"%CSA_HOME%\jboss-as\standalone\configuration\
.keystore" verify-client="false"/>
```

4. Update the entry by:
 - Removing the name and key-alias attributes and values
 - Changing the value of certificate-key-file to the keystore you created in step 1 (`%CSA_HOME%\jboss-as\standalone\configuration\keystore_csaID.p12`)
 - Adding or changing the value of password to the encrypted value of the HP CSA server keystore password you generated in task 1 of this step
 - Adding the attribute keystore-type and setting its value to PKCS12

For example:

```
<ssl name="ssl" key-alias="CSA"
certificate-key-file="%CSA_HOME%\jboss-as\
standalone\configuration\keystore_csaID.p12"
password="${VAULT::<vault_block_ssl>::password::BdBDkaoLEhJodLsaOI0x0}"
keystore-type="PKCS12"
verify-client="false"/>
```

5. Locate the following entry for the datasource password (this entry may have been modified):

Microsoft SQL Server

```
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="mssqlDS">
  <connection-url>jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request
  </connection-url>
  <driver>mssqlDriver</driver>
  <pool>
    <min-pool-size>10;</min-pool-size>
    <max-pool-size>200;</max-pool-size>
    <prefill>>true;</prefill>
  </pool>
  <security>
```

```
        <security-domain>csa-encryption-sec;</security-domain>  
    </security>  
</datasource>
```

6. Replace the security-domain entry with the datasource username and password, setting the password value to the encrypted value of the datasource password you generated in task 1 of this step. For Microsoft SQL Server, also update the connection-url ssl attribute value from request to authenticate (if it has not already been updated).

For example:

Microsoft SQL Server

```
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="mssqlDS">  
    <connection-url>  
        jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=requestauthenticate  
    </connection-url>  
    <driver>mssqlDriver</driver>  
    <pool>  
        <min-pool-size>10;</min-pool-size>  
        <max-pool-size>200;</max-pool-size>  
        <prefill>>true;</prefill>  
    </pool>  
    <security>  
        <del>security-domain>csa-encryption-sec;</del></security-domain>  
        <user-name>datasource_username</user-name>  
        <password>  
            ${VAULT::<vault_block_datasource>::password::AjkhlDF0blGeMmEtX0}  
        </password>  
    </security>  
</datasource>
```

7. Locate and delete the following entry for the datasource password (this entry may have been modified):

Microsoft SQL Server

```
<security-domain name="csa-encryption-sec" cache-type="default">  
    <authentication>  
        <login-module  
code="org.picketbox.datasource.security.SecureIdentityLoginModule"  
flag="required">  
            <module-option name="username" value="<old_user_name>"/>  
            <module-option name="password" value="<old_encoded_password>"/>  
            <module-option name="managedConnectionFactoryName"  
value="jboss.jca:service=LocalTxCM,name=mssqlDS"/>  
        </login-module>  
    </authentication>  
</security-domain>
```

8. Add the following vault properties to `<server xmlns="urn:jboss:domain:1.3">`. Set the values as applicable to your system setup.

```
<vault>
  <vault-option name="KEYSTORE_URL" value="C:\vault\vault.keystore"/>
  <vault-option name="KEYSTORE_PASSWORD" value="MASK-2PtpNyQsI1E7t"/>
  <vault-option name="KEYSTORE_ALIAS" value="vault"/>
  <vault-option name="SALT" value="12345678"/>
  <vault-option name="ITERATION_COUNT" value="50"/>
  <vault-option name="ENC_FILE_DIR" value="C:\vault\"/>
</vault>
```

Step 4: Import the HP Operations Orchestration Certificate as a Trusted Certificate

Because the integration of HP CSA and HP Operations Orchestration requires a secure connection, you must import the HP Operations Orchestration certificate.

For each system running HP CSA, import the root certificate of each HP Operations Orchestration's Certificate Authority (you must first export HP Operations Orchestration's certificate from HP Operations Orchestration's truststore and then import it into the HP CSA server truststore).

The following is an example of how to export the HP Operations Orchestration certificate and import it into the HP CSA server truststore.

1. On the system running HP Operations Orchestration, open a command prompt and change the directory to `%ICONCLUDE_HOME%` (Windows) or `$ICONCLUDE_HOME` (Linux).
2. Run the following command:

HP Operations Orchestration 10.x, Windows

```
.\java\bin\keytool -exportcert -alias tomcat -file C:\oo.crt
-keystore .\Central\var\security\key.store -storepass changeit
```

HP Operations Orchestration 9.x, Windows

```
.\jre1.6\bin\keytool -exportcert -alias pas -file C:\oo.crt
-keystore .\Central\conf\rc_keystore -storepass bran507025
```

HP Operations Orchestration 10.x, Linux

```
./java/bin/keytool -exportcert -alias tomcat -file /tmp/oo.crt
-keystore ./Central/var/security/key.store -storepass changeit
```

HP Operations Orchestration 9.x, Linux

```
./jre1.6/bin/keytool -exportcert -alias pas -file /tmp/oo.crt
-keystore ./Central/conf/rc_keystore -storepass bran507025
```

where `C:\oo.crt` and `/tmp/oo.crt` are examples of filenames and locations used to store the exported root certificate (you can choose a different filename and location).

3. If HP Operations Orchestration is not running on the same system as HP Cloud Service Automation, copy `oo.crt` from the HP Operations Orchestration system to the system running HP Cloud Service Automation (in this example, the file is copied to `C:\`).
4. On the system running HP CSA, change the directory to `%CSA_HOME%` and run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias pas -file C:\oo.crt -keystore  
. \jboss-as\standalone\configuration\csa_server_truststore.p12  
-storepass <HP CSA server truststore password>
```

5. When prompted to trust the certificate, enter `yes`.

Step 5: Import the Provider's Certificate as a Trusted Certificate

If you configure the access point to HP Matrix Operating Environment, HP Server Automation, VMware vCenter, or any provider in the Cloud Service Management Console to use a secure connection, you must import the provider's certificate into the truststore.

For each system running HP CSA, import the root certificate of the provider's Certificate Authority into the truststore (you must first export the provider's certificate from the provider's truststore and then import it into the HP CSA server truststore).

The following is an example of how to import the VMware vCenter certificate into the HP CSA server truststore.

1. Obtain the root certificate of VMware vCenter's Certificate Authority and copy it to the system running HP Cloud Service Automation (in this example, the file is copied to `C:\vcenter.crt`).
2. On the system running HP CSA, change the directory to `%CSA_HOME%` and run the following command:

```
"<csa_jre>\bin\keytool" -importcert -alias vcenter -file C:\vcenter.crt -  
keystore  
. \jboss-as\standalone\configuration\csa_server_truststore.p12  
-storepass <HP CSA server truststore password>
```

3. When prompted to trust the certificate, enter `yes`.

Step 6: Import the Certificates for other Applications as Trusted Certificates

If other applications, such as the database, LDAP, SMTP, HP Operations Orchestration Load Balancer, or HP Continuous Delivery Automation require a secure connection, you must import the other applications' certificates into the HP CSA server truststore.

The following is an example of how to import another application's certificate into the HP CSA server truststore.

1. Export the certificate for the application and copy the certificate file to the system running HP CSA.
2. Import this certificate into the HP CSA server truststore.

For example, run the following command on the system running HP CSA:

```
"<csa_jre>\bin\keytool" -importcert -alias <alias>  
-file <filename.crt> -trustcacerts  
-keystore "%CSA_HOME%\jboss-as\standalone\  
configuration\csa_server_truststore.p12"  
-storepass <HP CSA server truststore password>
```

Step 7: Configure Client Browsers (Optional)

If HP CSA's certificate is not signed by a Certificate Authority, when accessing the Cloud Service Management Console, warning messages are displayed in the browser (these messages do not affect normal operations of HP CSA). To avoid these warning messages, import the `csa_fips.crt` file or add an exception.

- **Microsoft Internet Explorer and Chrome:** From Windows Explorer, double-click on the `csa_fips.crt` file to begin the import process. Install the certificate in the Trusted Root Certification Authorities store. For information on how to import the certificate, refer to the browser's online documentation.
- **Firefox:** Add an exception by opening the browser and navigating to `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system on which HP CSA is running. When the **This Connection is Untrusted** page opens, select **I Understand the Risks**, click the **Add Exception** button, verify the Server Location, and click **Confirm Security Exception**. For information on how to import the certificate, refer to the browser's online documentation.

Re-Encrypt HP CSA Passwords

This section describes how to generate and replace the passwords used by HP CSA. You will be generating new passwords using FIPS 140-2 compliant utilities.

Note: In the following instructions, `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed (for example, `C:\Program Files\Hewlett-Packard\CSA`) and a JRE has been installed for HP CSA in `<csa_jre>`.

Generate and replace the passwords for the following HP CSA properties (default passwords appear in parentheses):

- csaTruststorePassword
- securityAdminPassword (cloud)
- securityCsaReportingUserPassword (cloud)
- securityTransportPassword (csaTransportUser)
- securityOolInboundUserPassword (oolInboundUser)
- securityCdaInboundUserPassword (CDA2CSAIntegration!)
- securityIdmTransportUserPassword (idmTransportUser)
- securityCatalogAggregationTransportUserPassword (cloud)
- securityEncryptedSigningKey (cloud)

Generate and replace the passwords for the following tools:

- Content archive tool
- Purge tool
- Process definition tool
- Provider tool
- Schema installation tool

To generate and replace existing passwords used by HP CSA, do the following:

1. Open a command prompt and change to the %CSA_HOME%\Tools\PasswordUtil directory. For example:

```
C:\Program Files\Hewlett-Packard\CSA\Tools\PasswordUtil
```

2. Generate a password by running the following command (this example uses the same example names from ["Create an HP CSA Encryption Keystore" on page 173](#)):

```
"<csa_jre>\bin\java" -jar passwordUtil-standalone.jar encrypt <password>  
JsafeJCE ../../jboss-as/standalone/configuration/csa_encryption_keystore.p12  
<HP CSA encryption keystore password> csa_encryption_key  
../../jboss-as/standalone/configuration/key.dat
```

Note: The path separators used in the passwordUtil-standalone.jar script options are forward slashes (/). You can also use double backward slashes (\\) as your path separators.

The encrypted value of the password is displayed.

If you used different names for the keystore, alias, or encrypted symmetric key file, here is an example of the command without using the example names:

```
"<csa_jre>\bin\java" -jar "%CSA_HOME%\Tools\PasswordUtil\passwordUtil-standalone.jar" encrypt <password> JsafeJCE <HP CSA encryption keystore>  
<HP CSA encryption keystore password>  
<HP CSA encryption keystore alias>  
<Location and name of the encrypted symmetric key>
```

Note: If you use path separators in the `passwordUtil-standalone.jar` script options, use either a single forward slash (/) or double backward slashes (\\) as your path separator.

- To update HP CSA properties used by the Cloud Service Management Console, edit the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file. Update the password for the following properties:
 - `csaTruststorePassword`
 - `securityAdminPassword`
 - `securityCsaReportingUserPassword`
 - `securityTransportPassword` (use the same password for the Identity Management component)
 - `securityOoInboundUserPassword`
 - `securityCdaInboundUserPassword`
 - `securityIdmTransportUserPassword` (use the same password for the Identity Management component and Marketplace Portal)
 - `securityCatalogAggregationTransportUserPassword`
 - `securityEncryptedSigningKey` (use the same password for the Identity Management component)

See ["Configure the Identity Management Component" on page 196](#) for more information about configuring password for the Identity Management component.

Note: In the properties file, the encrypted password value must be preceded by `ENC` without any separating spaces and is enclosed in parentheses.

For more information about these properties, refer to the *HP Cloud Service Automation Configuration Guide*.

4. Update the password property value defined in the database property file for the following tools:
 - Content archive tool
 - Purge tool
 - Process definition tool
 - Provider tool
 - Schema installation tool

Configure HP CSA Properties

To configure HP CSA properties for FIPS 140-2 compliance:

1. Open a command prompt and change to the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes` directory. For example:

```
C:\Program Files\Hewlett-Packard\CSA\jboss-as\
standalone\deployments\csa.war\WEB-INF\classes
```

2. Open the `csa.properties` file in an editor.
 - a. Verify that the `enableHPSSO` property is either set to `false` or is commented out.
 - b. Configure the following properties:

Property	Description
useExternalProvider	<p>Required if enabling FIPS 140-2 compliance mode. To enable, set this property to true. To disable, set this property to false or comment it out.</p> <p>When enabled, HP CSA uses the RSA BSAFE libraries to encrypt and decrypt passwords. If a password was encrypted using different libraries (for example, if the password was encrypted before this property is enabled), the resulting decrypted password will not be valid.</p> <p>If you cannot connect to the database after you have configured HP CSA for FIPS 140-2 compliance, try re-encrypting the database password in the database properties file.</p> <p>Default: commented out/disabled</p>
securityProviderName	<p>Required if FIPS 140-2 compliance mode is enabled. The name of the FIPS 140-2 compliant provider. By default, HP CSA uses the RSA BSAFE provider and this property should be set to JsafeJCE.</p>
keySize	<p>Optional. The key size used for HP CSA encryption. By default, the key size is 128. If you manually enter a different key size when encrypting a password, uncomment this property and configure the value to the key size used to encrypt the passwords.</p> <div data-bbox="646 1199 1369 1444" style="background-color: #f0f0f0; padding: 10px;"> <p>Note: All passwords must be encrypted using the same key size.</p> <p>By default, the password encryption utility encrypts all passwords using a key size of 128 (even if you do not specify a key size when running the utility).</p> </div>

Property	Description
keystore	<p>Required if FIPS 140-2 compliance mode is enabled. The absolute path to and file name of the HP CSA encryption keystore. This is the keystore that supports PKCS #12 and stores the key used by HP CSA to encrypt and decrypt data in HP CSA.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/csa_encryption_keystore.p12</pre> <p>Note: Use only forward slashes (/) as your path separators.</p>
keyAlias	<p>Required if FIPS 140-2 compliance mode is enabled. The alias used to identify the HP CSA encryption key in the HP CSA encryption keystore.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>csa_encryption_key</pre>
keystorePasswordFile	<p>Required if FIPS 140-2 compliance mode is enabled. The absolute path to and file name of the HP CSA encryption keystore password. This is a temporary file that stores the HP CSA encryption keystore password in clear text. This file is required to start the HP CSA service and is automatically deleted when the service is started.</p> <p>The password file must contain only the following content:</p> <pre>keystorePassword=<HP CSA encryption keystore password></pre> <p>where <HP CSA encryption keystore password> is the HP CSA encryption keystore password in clear text.</p> <p>Note: Use only forward slashes (/) as your path separators.</p>

Property	Description
encryptedKeyFile	<p>Required if FIPS 140-2 compliance mode is enabled. The location of the HP CSA encrypted symmetric key.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/key.dat</pre> <p>Note: Use only forward slashes (/) as your path separators.</p>
csaTruststore	<p>Required. The HP Cloud Service Automation keystore that stores trusted Certificate Authority certificates.</p> <p>Note: This property is located in another section of the <code>csa.properties</code> file. Its description is repeated here as its value should be updated when HP CSA has been configured to be compliant with FIPS 140-2.</p> <p>Example (this example uses the same example name of the HP CSA server truststore from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/csa_server_truststore.p12</pre> <p>Note: Use only forward slashes (/) as your path separators.</p>

Property	Description
csaTruststorePassword	<p>Required. The encrypted password of the HP Cloud Service Automation keystore (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>Default: No default specified</p> <p>Example</p> <pre>ENC(9eC7TTnB0uG0GK5U648UITcEV5AuV5T)</pre> <p>Note: This property is located in another section of the <code>csa.properties</code> file. Its description is repeated here as its value should be updated when HP CSA has been configured to be compliant with FIPS 140-2.</p> <p>This is the <code><HP CSA server truststore password></code> from "Create an HP CSA Encryption Keystore" on page 173.</p>

- Copy the property values from step 2b to the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\idm-service.properties` file. The property values must be the same in both files.

Configure the Marketplace Portal

This section describes how to configure the Marketplace Portal to comply with FIPS 140-2.

Password Encryption

The Marketplace Portal implements password encryption via PBES2 using the NodeJS crypto library. The key is hard coded in the JavaScript (JS), but it is not directly used. Instead, the key is used to decrypt a randomly-generated key that is encrypted and saved in a keyfile, which will be protected by the file system.

Note: Make sure the file system in which the Marketplace Portal exists is protected by the operating system, so that no one without permission can read or edit files or folders.

Keyfile, Encryption, and Decryption Workflow

Create a Keyfile

1. Generate password (the real password use to encrypt any message).
2. Generate the salt.
3. Use the master password (hard coded) to generate a derived key (PBKDF2).
4. Use the derived key to encrypt a password using 3DES (PBES2).
5. Save the salt and the encrypted password to a keyfile.

Encrypt

1. If the keyfile does not exist, create one; otherwise, read the keyfile to obtain the salt and the encrypted password.
2. Decrypt the encrypted password with a master password to get the derived key.
3. Encrypt plain text (UTF-8) with a derived key (Base64) and salt (Base64) to get the encrypted message.

Decrypt

1. Read the keyfile to obtain the salt and the encrypted password .
2. Decrypt the encrypted password with the master password to get the derived key.
3. Decrypt the encrypted message with the derived key and salt to get the plaintext message.

Encrypt a Password

The Marketplace Portal provides a password utility (`passwordUtil.js`), which you use to encrypt a password and generate a keyfile.

Following is the password utility syntax.

```
cd %CSA_HOME%\portal\bin
..\..\node.js\node passwordUtil.js --help
..\..\node.js\node passwordUtil.js --password <password to encrypt>
```

Following is an example.

```
..\..\node.js\node passwordUtil.js
Please enter password to encrypt -password hidden-
Encrypted password is ENC(TPhdYjB72z+v+pHdscGskQ==)
```

Note: If the keyfile needs to be regenerated, delete the existing keyfile, as defined in the `mpp.json` file (see next section for the exact location) and run the password utility script (it will generate a keyfile if it does not exist).

Configure Settings for Keyfile, Session ID Cookie Secret, IdM Transport User Password, and SSL Keyfile or Truststore Passphrase

1. Edit the `%CSA_HOME%\portal\conf\mpp.json` file:

```
{
  "uid": "ccue_mpp",
  "port": 8089,
  "defaultOrganizationName": "CSA_CONSUMER",
  "keyfile": "conf/keyfile",
  "session": {
    "cookieSecret": "enc(dqmtAEFpkRd4DYpx4pDMzQ==)",
    "timeoutDuration": 1800,
    "cleanupInterval": 3600
  },
  "provider": {
    "url": "https://localhost:8444",
    "contextPath": "/csa/api/mpp"
  },
  "idmProvider": {
    "url": "https://localhost:8444",
    "contextPath": "/idm-service",
    "username": "idmTransportUser",
    "password": "enc(2JQmsT2352L4XdiIVldKnoZn8p09Pdn+)"
  },
  "https": {
    "enabled": true,
    "options": {
      "pfx": "../conf/.mpp_keystore"
      "passphrase": "enc(2b+Uxofd5ionF7mPsasARvg==)"
    }
  },
  "ha": {
    "enabled": false,
    "numWorkers": 2,
    "redis": {
      "options": {
        "host": "localhost",
        "port": 6379
      }
    }
  }
}
```

```
    }  
  }  
}
```

2. Set the following parameters:

- `keyfile` is the location of the key file generated by the Marketplace Portal password utility (`passwordUtil.js`).
- `session.cookieSecret` is the secret passphrase to encrypt the session ID cookie on the browser. This is an encryptable field, so make sure you enclose it with `enc()`.
- `idmProvider.password` is the transport user used to connect to Identity Management (IdM). This is an encryptable field, so make sure you enclose it with `enc()`.
- `https.options.passphrase` is the passphrase of the SSL keyfile or truststore. This is an encryptable field, so make sure you enclose it with `enc()`.

Note: Do not copy the encrypted password from this example, because the encryption key and salt are generated and stored in the keyfile. However, you can reuse the keyfile for multiple systems, and the encrypted password in the `mpp.json` file will be the same.

Configure TLS

The Marketplace Portal uses the NodeJS HTTPS module to enable TLS. OpenSSL is used to perform the encryption and decryption.

FIPS 140-2 supports only TLS. You must configure the Marketplace Portal to use a FIPS-compliant cipher as follows.

1. Edit the `%CSA_HOME%\portal\conf\mpp.json` file:

```
"https": {  
  "enabled": true,  
  "options": {  
    "passphrase": "ENC(pEYj2aVNBVUyH85PDnVjZg==)"  
    "key": "../conf/.mpp_privateKey.pem",  
    "cert": "../conf/.mpp_publicKey.pem",  
    "secureProtocol": "TLSv1_method",  
    "ciphers": "TLS_RSA_WITH_3DES_EDE_CBC_SHA:HIGH:!MD5:!aNULL:!EDH",  
    "honorCipherOrder": true  
  }  
},
```

2. The key and cert files should be generated from the pfx file (`../conf/.mpp_keystore`).

3. Set the `secureProtocol` parameter to `TLSv1_method`.
4. Set the `ciphers` parameter to `TLS_RSA_WITH_3DES_EDE_CBC_SHA:HIGH:!MD5:!aNULL:!EDH`.
5. Set the `honorCipherOrder` parameter to `true`.

Configure the Identity Management Component

If you are using the Identity Management component, to configure the Identity Management component for FIPS 140-2 compliance, do the following:

1. Update the `applicationContext.xml` file.
2. Re-encrypt passwords.
3. Update the `idm-security.properties` file.

Note: The examples in this section explain how to configure the Identity Management component that is installed on the same instance as HP CSA, where HP CSA is configured in a standalone environment. If your environment is different, files may be located in a different directory.

In the following instructions, `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed (for example, `C:\Program Files\Hewlett-Packard\CSA`) and `<csa_jre>` is the directory in which the JRE used by HP CSA has been installed.

Update the applicationContext.xml File

The `applicationContext.xml` file for the Cloud Service Management Console must be updated to be FIPS 140-2 compliant. Do the following:

1. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.xml` file in a text editor.
2. Locate the `START Standard Mode Configuration` comment and comment out the following content that appears between the `START Standard Mode Configuration` and `END Standard Mode Configuration` comments:

```
<bean id="simpleEncryptionConfiguration"  
class="com.hp.csa.security.CSASimplePBCEConfig" init-method="init">  
</bean>  
  
<bean id="configurationEncryptor"  
class="org.jasypt.encryption.pbe.StandardPBEStrngEncryptor">  
  <property name="config" ref="simpleEncryptionConfiguration" />  
</bean>
```

```
<bean id="propertyConfigurer" class="org.jasypt.spring.properties.
EncryptablePropertyPlaceholderConfigurer">
  <constructor-arg ref="configurationEncryptor" />
  <property name="locations">
    <list>
      <value>classpath:csa.properties</value>
      <value>classpath:swagger.properties</value>
    </list>
  </property>
</bean>
```

3. Locate the `START FIPS Mode Configuration` comment that appears immediately after the `Standard Mode Configuration` section and uncomment the following content that appears between the `START FIPS Mode Configuration` and `END FIPS Mode Configuration` comments:

```
<bean id="configurationEncryptor"
class="com.hp.csa.security.util.CSA SecurityHelper" />

<bean id="propertyConfigurer" class=
"com.hp.csa.security.CSAEncryptablePropertyPlaceholderConfigurer">
  <constructor-arg ref="configurationEncryptor" />
  <property name="locations">
    <list>
      <value>/WEB-INF/spring/applicationContext.properties</value>
    </list>
  </property>
</bean>
```

4. Locate the `START FIPS Mode Configuration` comment for the `csaTemplateFactory` bean and uncomment the following content that appears between the `START FIPS Mode Configuration` and `END FIPS Mode Configuration` comments:

```
<property name="fipsEnabled" value="true" />
```

5. Locate the `START FIPS Mode Configuration` comment for the `keystoneTemplateFactory` bean and uncomment the following content that appears between the `START FIPS Mode Configuration` and `END FIPS Mode Configuration` comments:

```
<property name="fipsEnabled" value="true" />
```

6. Save and close the file.

Re-Encrypt Passwords

This section describes how to generate and replace the passwords used by the Identity Management component. You will be generating new passwords using FIPS 140-2 compliant utilities.

Generate and replace the passwords for the following Identity Management component properties:

- idm.csa.password
- idm.encryptedSigningKey
- idm.keystone.transportPassword
- consumer
- idmTransportUser

Note: The default password values for these properties are provided in the steps below (they will appear in parentheses after the property name).

To generate and replace existing passwords used by the Identity Management component, do the following:

1. Open a command prompt and change to the %CSA_HOME%\Tools\PasswordUtil directory. For example:

```
C:\Program Files\Hewlett-Packard\CSA\Tools\PasswordUtil
```

2. Generate a password by running the following command (this example uses the same example names from ["Create an HP CSA Encryption Keystore" on page 173](#)):

```
"<csa_jre>\bin\java" -jar passwordUtil-standalone.jar encrypt <password>  
JsafeJCE ../../jboss-as/standalone/configuration/csa_encryption_keystore.p12  
<HP CSA encryption keystore password> csa_encryption_key  
../../jboss-as/standalone/configuration/key.dat
```

Note: The path separators used in the passwordUtil-standalone.jar script options are forward slashes (/). You can also use double backward slashes (\\) as your path separators.

The encrypted value of the password is displayed.

If you used different names for the keystore, alias, or encrypted symmetric key file, here is an example of the command without using the example names:

```
"<csa_jre>\bin\java" -jar "%CSA_HOME%\Tools\PasswordUtil\passwordUtil-  
standalone.jar" encrypt <password> JsafeJCE <HP CSA encryption keystore>  
<HP CSA encryption keystore password>  
<HP CSA encryption keystore alias>  
<Location and name of the encrypted symmetric key>
```

Note: If you use path separators in the passwordUtil-standalone.jar script options, use either a single forward slash (/) or double backward slashes (\\) as your path separator.

3. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties` file in a text editor and do the following:
 - a. Update the `idm.csa.password` (`csaTransportUser`) property. `idm.csa.password` must be the same password you configured for the `securityTransportPassword` property (which is configured in the `csa.properties` file). See ["Re-Encrypt HP CSA Passwords" on page 185](#) for more information about encrypting the `securityTransportPassword` password property.
 - b. Update the `idm.encryptedSigningKey` (`cloud`) property. `idm.encryptedSigningKey` must be the same password you configured for the `securityEncryptedSigningKey` property (which is configured in the `csa.properties` file). See ["Re-Encrypt HP CSA Passwords" on page 185](#) for more information about encrypting the `securityEncryptedSigningKey` password property.
 - c. If you are using Keystone, update the `idm.keystone.transportPassword` property. `idm.keystone.transportPassword` must be the password you configured for the user defined by the `idm.keystone.transportUsername` property and is located above the `idm.keystone.transportPassword` property.
 - d. Save and close the file.
4. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-consumer-users.properties` file in a text editor and do the following:
 - a. Update the `consumer` (`cloud,SERVICE_CONSUMER,ROLE_REST,enabled`) and `consumerAdmin` (`cloud,SERVICE_CONSUMER,ROLE_REST,ROLE_ADMIN,enabled`) properties.

Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.

This entire value must be encrypted.

- b. Save and close the file.
5. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\csa-provider-users.properties` file in a text editor and do the following:
 - a. Update the `admin` (`cloud,ROLE_REST,enabled`), `csaReportingUser` (`cloud,ROLE_REST,ROLE_DYNAMIC,enabled`), `cdaInboundUser` (`CDA2CSAIntegration!,ROLE_REST,enabled`), and `ooInboundUser` (`cloud,,ROLE_REST,enabled`) properties.

Note: This property not only contains the password, but also the roles that control access

to HP CSA and if the account is enabled.

This entire value must be encrypted.

- b. Save and close the file.
6. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\integrationusers.properties` file in a text editor and do the following:
 - a. Update the `idmTransportUser` (`idmTransportUser,ROLE_ADMIN,PERM_IMPERSONATE,enabled`) property.

Note: This property not only contains the password, but also the roles that control access to HP CSA and if the account is enabled.

This entire value must be encrypted.

The password in the `idmTransportUser` value must be the same password you configured for both the `securityIdmTransportUserPassword` property (configured in the `csa.properties` file) and the `password` attribute (configured in the `idmProvider` section of the `mpp.json` file). See ["Re-Encrypt HP CSA Passwords" on page 185](#) for more information about encrypting the `securityIdmTransportUserPassword` password property. See ["Encrypt a Marketplace Portal Password" on page 114](#) for more information about encrypting the `password` attribute.

- b. Save and close the file.

Update the `idm-security.properties` File

Enable the FIPS 140-2 security settings in the `idm-security.properties` file. Do the following:

1. Open the `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\idm-service.properties` file in a text editor.
2. Verify that the FIPS 140-2 property values in this file are the same values that are configured in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file. You should have already copied these values (see ["Configure HP CSA Properties" on page 188](#) for more information about these properties).
3. Save and close the file.

Start HP CSA

To start HP CSA:

1. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for the `keystorePasswordFile` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

2. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
3. Right-click on the HP Cloud Service Automation service and select **Start**.
4. Right-click on the HP Marketplace Portal service and select **Start**.
5. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Start**.

After the service has started, review the log files in `%CSA_HOME%\jboss-as\standalone\log\` and verify that no TLS or keystore errors are present.

Test Secure Connections

To test the connection to the Cloud Service Management Console, on a client system, open a supported Web browser and navigate to `https://<csahostname>:8444/csa` where `<csahostname>` is the fully-qualified domain name of the system that was used when the certificate was created. If the client browser is configured to accept HP CSA's certificate and the Web application opens without a certificate warning, then you have successfully configured HP CSA to use HP CSA's certificate. If you did not configure the client browser to accept HP CSA's certificate, verify that the only certificate warning relates to the certificate not being issued by a trusted authority. If any other certificate warning is displayed, review all steps in "[Create a New Keystore and Truststore for Secure Communication](#)" on [page 177](#) to be sure they were followed as documented.

Chapter 13: Database Administration

This chapter provides miscellaneous information about maintaining the database.

Tasks include:

- ["Restart the Database" below](#)
- ["Configure the CSA Reporting Database User" on the next page](#)
- ["Update the HP CSA Database User or Password" on page 206](#) (required if you change the database user or password)
- ["Import Large Archives" on page 208](#)
- ["Purge Service Subscriptions and Audit Data" on page 210](#)
- ["Install the HP CSA Database Schema" on page 221](#)
- ["Configure HP CSA to Mitigate Frequently Dropped Database Connections" on page 227](#)

Restart the Database

If you restart the database, you must restart the HP Cloud Service Automation service. If you do not restart the service, you may not be able to log in to the Cloud Service Management Console or Marketplace Portal.

Note: You only need to restart the HP Cloud Service Automation service. You do not need to restart the Marketplace Portal service.

To restart the service, do the following:

Note: If you have configured HP CSA to be FIPS 140-2 compliant, additional steps are required. Refer to ["Restart HP CSA" on page 109](#) for more information.

1. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
2. Right-click on the HP Cloud Service Automation service and select **Restart**.

Configure the CSA Reporting Database User

This section explains how to configure the CSA reporting database user and role and run the schema installation script to define a read-only user required to use the reporting capabilities of HP CSA.

If you already configured the CSA reporting database user and role and defined the CSA reporting database user when running the installer or upgrade installer, you do not need to repeat these steps (the CSA reporting database user is already configured).

If you installed or upgraded HP CSA but did not configure the CSA reporting database user during the installation or upgrade and want to use the reporting capabilities of HP CSA, complete the tasks in this section.

To configure the CSA reporting database user, do the following:

1. Create a read-only user.

Caution: The username cannot contain more than one dollar sign symbol (\$). For example, c\$adb is a valid name but c\$\$adb and c\$ad\$b are not valid names.

For example, do one of the following, based on the database you are using with HP CSA:

Oracle

Run the following commands to create the CSAReportingDBRole role and CSAReportingDBUser user:

```
Create user CSAReportingDBUser identified by CSAReportingDBUser;  
Create role CSAReportingDBRole;  
Grant CREATE SESSION to CSAReportingDBUser;  
Grant CSAReportingDBRole to CSAReportingDBUser;  
Alter user CSAReportingDBUser default role CSAReportingDBRole;
```

You will also need to add the CREATE ANY SYNONYM privilege to the HP CSA database user. This allows the HP CSA database user to create synonyms for the HP CSA reporting (read-only) database user.

For example, if the HP CSA database user is named CSADBUser, run the following command:

```
Grant CREATE ANY SYNONYM to CSADBUser
```

Microsoft SQL

Add a reporting database user (CSAReportingDBUser) to the HP CSA database with no roles:

```
CREATE LOGIN CSAReportingDBUser WITH PASSWORD = '<csareportingdbuser_
password>';
CREATE USER CSAReportingDBUser FOR LOGIN CSAReportingDBUser WITH DEFAULT_SCHEMA
= csa;
```

PostgreSQL

From the psql prompt, enter the following:

```
CREATE ROLE CSAReportingDBUser LOGIN PASSWORD '<csareportingdbuser_password>'
NOSUPERUSER NOCREATEDB NOCREATEROLE INHERIT;
GRANT CONNECT ON DATABASE csadb to CSAReportingDBUser;
```

2. Run the following script:

Oracle

```
%CSA_HOME%\scripts\reporting\oracle\grant-reporting-user.sql
```

Microsoft SQL

```
%CSA_HOME%\scripts\reporting\mssql\grant-reporting-user.sql
```

PostgreSQL

```
%CSA_HOME%\scripts\reporting\postgresql\grant-reporting-user.sql
```

3. Restart HP CSA.

To restart HP CSA:

- a. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for the `keystorePasswordFile` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

- b. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.

- c. Right-click on the HP Cloud Service Automation service and select **Restart**.
 - d. Right-click on the HP Marketplace Portal service and select **Restart**.
4. The CSA reporting database user can access the data using the following view:

RPT_RSC_CAPACITY_V

Update the HP CSA Database System

If you changed the hostname, domain, IP address, or port of the system on which the database used by HP Cloud Service Automation is installed, you must update the HP Cloud Service Automation configuration files that store this information.

1. Stop the HP Cloud Service Automation service.

To stop HP CSA:

- a. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service and select **Stop**.
 - c. Right-click on the HP Marketplace Portal service and select **Stop**.
 - d. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.
2. On the system running HP Cloud Service Automation, open a command prompt and change to the %CSA_HOME%\jboss-as\standalone\configuration directory where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed.
 3. In a text editor, open the standalone.xml file.
 4. In the file, locate the <datasource> element of the HP Cloud Service Automation database and the system information to be updated. For example:

Microsoft SQL Server

```
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="mssqlDS">
  <connection-
url>jdbc:jtds:sqlserver://127.0.0.1:1433/csadb;ssl=request</connection-url>
  <driver>mssqlDriver</driver>
  .
  .
  .
</datasource>
```

Oracle

```
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="OracleDS">  
  <connection-url>jdbc:oracle:thin://127.0.0.1:1521/csadb</connection-url>  
  <driver>oracleDriver</driver>  
  .  
  .  
  .  
</datasource>
```

5. The highlighted text should contain the old fully-qualified domain name, IP address, and/or port that must be updated. Replace this highlighted text with the new fully-qualified domain name, IP address, and/or port.
6. Save the `standalone.xml` file.
7. Restart HP Cloud Service Automation service.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

8. If you are using a tool (such as the content archive tool, process definition tool, provider tool, purge tool, or schema installation tool) that uses a database or configuration properties file (for example, `db.properties` or `config.properties`), update the appropriate property or properties in the file. By default, the file is located in the `%CSA_HOME%\Tools\<Tool_Name>` directory.

Update the HP CSA Database User or Password

If you changed the user or password of the database used by HP Cloud Service Automation, you must update the JBoss DataSource and other files that store this information.

1. On the system running HP Cloud Service Automation, open a command prompt and change to the directory `%CSA_HOME%\jboss-as` where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed.
2. Run the following command to generate an encoded version of the new database password:

```
"<csa_jre>\bin\java" -cp "modules\org\jboss\logging\main\  
jboss-logging-3.1.2.GA.jar;modules\org\picketbox\main\  
picketbox-4.0.13.Final.jar"  
org.picketbox.datasource.security.SecureIdentityLoginModule <password>
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

Copy the encoded password value that is returned (do not include spaces).

3. Stop the HP Cloud Service Automation service.

To stop HP CSA:

- a. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service and select **Stop**.
 - c. Right-click on the HP Marketplace Portal service and select **Stop**.
 - d. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.
4. In a text editor, open the %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml file.
 5. In the file, locate the following content:

Microsoft SQL Server

```
<security-domain name="csa-encryption-sec" cache-type="default">
  <authentication>
    <login-module
code="org.picketbox.datasource.security.SecureIdentityLoginModule"
flag="required">
      <module-option name="username" value="<old_user_name>"/>
      <module-option name="password" value="<old_encoded_password>"/>
      <module-option name="managedConnectionFactoryName"
value="jboss.jca:service=LocalTxCM,name=mssqlDS"/>
    </login-module>
  </authentication>
</security-domain>
```

Oracle

```
<security-domain name="csa-encryption-sec" cache-type="default">
  <authentication>
    <login-module
code="org.picketbox.datasource.security.SecureIdentityLoginModule"
flag="required">
      <module-option name="username" value="<old_user_name>"/>
      <module-option name="password" value="<old_encoded_password>"/>
      <module-option name="managedConnectionFactoryName"
value="jboss.jca:service=LocalTxCM,name=OracleDS"/>
    </login-module>
  </authentication>
</security-domain>
```

6. Replace `<old_encoded_password>` with the new encoded password you copied in step 2 and `<old_user_name>` with the new user name.
7. Save the standalone.xml file.

8. Restart HP Cloud Service Automation service.

See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

9. If you are using a tool (such as the content archive tool, process definition tool, provider tool, purge tool, or schema installation tool) that uses a database or configuration properties file (for example, `db.properties` or `config.properties`), update the appropriate property or properties in the file. By default, the file is located in the `%CSA_HOME%\Tools\<Tool_Name>` directory.

The password property value should be *encrypted* (see ["Encrypt a Password" on page 110](#) for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.

Import Large Archives

Archives exported from HP CSA can be imported to install artifacts or update existing artifacts in HP CSA. Archives can be imported using the HP CSA Content Archive Tool, the Cloud Service Management Console, or the REST API.

The default configuration for importing archives supports an archive up to 1.5 MB in size. When an archive larger than 1.5 MB is imported (typically, a catalog), the import operation may hang or take a very long time to complete. If an archive is larger than 1.5 MB, HP recommends using the Content Archive Tool and increasing the JVM heap size to greater than 1 GB (the default JVM heap size).

Import Large Archives Using the HP CSA Content Archive Tool

If you want to import an archive larger than 1.5 MB, HP recommends using the Content Archive Tool because the tool uses its own JVM heap (it does not share the JVM heap used by HP CSA). When you reconfigure the JVM heap size for the tool, you do not need to restart HP CSA and HP CSA performance is not affected by the import.

To increase the JVM heap size when running the Content Archive Tool, add the `-Xms<heap_size>M -Xmx<heap_size>M` options to the command line. For example, to increase the JVM heap size to 2 GB, type:

```
"<csa_jre>\bin\java -Xms2048M -Xmx2048M -jar content-archive-tool.jar -i -z catalog_archive.zip
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

Note: By default, the JVM heap size used by the Content Archive Tool is 1 GB. If you want to use a larger JVM heap size, you must always specify the two options listed above when running the Content Archive Tool.

For more information about the Content Archive Tool, refer to the *HP Cloud Service Automation Content Archive Tool* guide.

Import Large Archives from the Cloud Service Management Console or through the REST API

If you want to import an archive larger than 1.5 MB, HP recommends using the Content Archive Tool. If you must use the Cloud Service Management Console or REST API to import a large archive, you must update the JVM heap size for HP CSA which requires HP CSA to be restarted. Also, importing a large archive from the Cloud Service Management Console or through the REST API may slow the performance of HP CSA.

To increase the JVM heap size before importing a large archive from the Cloud Service Management Console or through the REST API, do the following:

1. Stop HP CSA.

To stop HP CSA:

- a. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
- b. Right-click on the HP Cloud Service Automation service and select **Stop**.
- c. Right-click on the HP Marketplace Portal service and select **Stop**.
- d. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.

2. Increase the JVM heap size for HP CSA.

- a. Open the `%CSA_HOME%\jboss-as\bin\standalone.conf.bat` file in a text editor.
- b. Locate the following line:

```
set "JAVA_OPTS=%JAVA_OPTS% -Xms1024M -Xmx1024M -XX:PermSize=256M  
-XX:MaxPermSize=256M"
```

- c. Increase the JVM heap size (by default, the JVM heap size is 1 GB). For example, to change the JVM heap size to 2 GB, change the line to:

```
set "JAVA_OPTS=%JAVA_OPTS% -Xms2048M -Xmx2048M -XX:PermSize=256M  
-XX:MaxPermSize=256M"
```

- d. Save and close the file.

3. Start HP CSA.

To start HP CSA:

- a. If you have configured HP CSA to be FIPS 140-2 compliant, create an HP CSA encryption keystore password file. The name and location of this file must match the value configured for the `keystorePasswordFile` property in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties` file.

The password file must contain only the following content: `keystorePassword=<HP CSA encryption keystore password>`

where `<HP CSA encryption keystore password>` is the HP CSA encryption keystore password in clear text.

This file is automatically deleted when the HP Cloud Service Automation service is started.

- b. On the server that hosts HP CSA, navigate to **Control Panel > Administrative Tools > Services**.
- c. Right-click on the HP Cloud Service Automation service and select **Start**.
- d. Right-click on the HP Marketplace Portal service and select **Start**.
- e. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Start**.

For more information about importing archives from the Cloud Service Management Console, refer to the HP Cloud Service Management Console Help. For more information about importing archives through the REST API, refer to the *HP CSA API Reference* guide.

Purge Service Subscriptions and Audit Data

The purge tool can be used to delete service subscriptions and audit data.

About Service Subscriptions

Canceled, expired, failed, and retired service subscriptions store information in the database that, over time, is no longer needed. The purge tool can be used to delete canceled, expired, failed, and retired subscriptions along with specific associated or referenced artifacts and entities. Canceled, expired, and failed subscriptions must have a service instance status of failed, canceled, cancellation failed, or expiration failed in order to be deleted. Canceled, expired, and failed subscriptions that are not in one of these states will not be deleted. All retired subscriptions are deleted.

By default, when the purge tool is run, canceled, expired, failed, and retired subscriptions that are older than 400 days (subscriptions that have been in a canceled, expired, failed, or retired state longer than 400 days) and certain referenced artifacts and entities are deleted from the database. The age of deleted subscriptions can be increased or decreased by modifying the `age.in.days.to.purge.subscription` property in the configuration properties file used by the purge tool.

When a subscription is deleted, the following artifacts and entities are deleted from the database:

Deleted Artifact	Referenced by (Reference Fields)	Referenced Artifacts and Entities that are Deleted
ServiceSubscription		action associatedRequest basePrice catalogItem initiatingServiceRequest pricingModel property serviceInstance totalPrice
ServiceRequest	ServiceSubscription (associatedRequest or initiatingServiceRequest)	action basePrice pricingModel property totalPrice
ServiceInstance	ServiceSubscription (serviceInstance)	componentRoot
ServiceComponent	ServiceInstance (componentRoot)	action property resourceBinding
ResourceBinding	ServiceComponent (resourceBinding)	action catalogItem lifecycleProperties property resourceInstance
ResourceSubscription	ResourceBinding (resourceInstance)	action catalogItem lifecycleProperties property
ProcessInstance		

About Audit Data

HP CSA creates audit event records in the database for events that occur during the lifetime of a running instance of HP CSA.

By default, when the purge tool is run, audit data that is older than 400 days is deleted from the database. The age of deleted audit data can be increased or decreased by modifying the `age.in.days.to.purge.audit` property in the configuration properties file used by the purge tool.

For more information about auditing data, refer to the *Reporting and Auditing* whitepaper.

Deleting Service Subscriptions and Audit Data

To delete canceled, expired, failed, and retired subscriptions or audit data from the database, do the following:

Caution: Deleted subscriptions and audit data cannot be restored unless you have backed up the database.

1. Change to the `%CSA_HOME%\Tools\db-purge-tool\` directory where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed.
2. Generate the sample configuration files by running the following command (a sample configuration file is generated for each type of database supported by HP CSA):

Oracle

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -g -j ojdbc6.jar
```

where `ojdbc6.jar` is the name of the Oracle JDBC driver installed in `%CSA_HOME%\Tools\db-purge-tool\`.

Note: Additional command line options are required if a secure connection is enabled between the Oracle database and HP CSA. See step 4 below for more information.

MS SQL and PostgreSQL

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -g
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

3. In the current directory, copy the sample configuration file that corresponds to the type of database you are using to a file named `config.properties`. For example, if you are using an Oracle database, make a copy of the `config.properties.oracle` file and rename it to `config.properties`. Update the content of `config.properties` as needed, as described in the table:

Property Name	Description
jdbc.driverClassName	<p>The JDBC driver class.</p> <p>Examples</p> <p>Oracle: jdbc.driverClassName=oracle.jdbc.driver.OracleDriver MS SQL: jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver PostgreSQL: jdbc.driverClassName=org.postgresql.Driver</p>
jdbc.dialect	<p>The classname that allows JDBC to generate optimized SQL for a particular database.</p> <p>Examples</p> <p>Oracle: jdbc.dialect=org.hibernate.dialect.OracleDialect MS SQL: jdbc.dialect=org.hibernate.dialect.SQLServerDialect PostgreSQL: jdbc.dialect=org.hibernate.dialect.PostgreSQLDialect</p>

Property Name	Description
jdbc. databaseUrl	<p>The JDBC URL. When specifying an IPv6 address, it must be enclosed in square brackets (see examples below).</p> <p>Examples</p> <p>Oracle (TLS not enabled): <code>jdbc.databaseUrl=jdbc:oracle:thin:@127.0.0.1:1521:XE</code></p> <p>Oracle (TLS not enabled, using an IPv6 address): <code>jdbc.databaseUrl=jdbc:oracle:thin:@[f000:253c::9c10:b4b4]:1521:XE</code></p> <p>Oracle (TLS enabled, HP CSA does not check the database DN): <code>jdbc.databaseUrl=jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS_LIST=(ADDRESS=(PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA =(SERVICE_NAME = ORCL)))</code> where <host> is the name of the system on which the Oracle database server is installed.</p> <p>Oracle (TLS enabled, HP CSA checks the database DN): <code>jdbc.databaseUrl=jdbc:oracle:thin:@(DESCRIPTION = (ADDRESS_LIST = (ADDRESS = (PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA = (SERVICE_NAME = ORCL))(SECURITY=(SSL_SERVER_CERT_DN="CN=abc,OU=dbserver,O=xyz,L=Sunnyvale,ST=CA,C=US"))</code> where <host> is the name of the system on which the Oracle database server is installed and the values for SSL_SERVER_CERT_DN are for the DN of the Oracle database server.</p> <p>MS SQL (TLS not enabled): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request</code></p> <p>MS SQL (TLS not enabled, using an IPv6 address): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://[::1]:1433/example;ssl=request</code></p> <p>MS SQL (TLS enabled): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate</code></p> <p>MS SQL (FIPS 140-2 compliant): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/</code></p>

Property Name	Description
	example;ssl=authenticate
jdbc. username	The user name of the database user you configured for HP Cloud Service Automation after installing the database.
jdbc. password	<p>The password for the database user. The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>If you have configured HP CSA to be FIPS 140-2 compliant, encrypt this password after you have configured CSA to be FIPS 140-2 compliant (that is, you should use the updated encryption tools to encrypt the password).</p> <p>Example</p> <pre>jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)</pre>
idmConfig.Url	<p>The system on which HP CSA is installed.</p> <p>Default: https://127.0.0.1:8444</p>
securityTransport. UserName	<p>The user used to authenticate legacy REST API calls.</p> <p>Default: csaTransportUser</p>
securityTransport. password	<p>The password for the user used to authenticate legacy REST API calls. The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>If you have configured HP CSA to be FIPS 140-2 compliant, encrypt this password after you have configured CSA to be FIPS 140-2 compliant (that is, you should use the updated encryption tools to encrypt the password).</p> <p>Example</p> <pre>securityTransport.password= ENC(r1bE8430uFSD1jert85441e7fe701jkY)</pre>

Property Name	Description
securityIdmTransport.UserName	The user used to authenticate consumer REST API calls. Default: idmTransportUser
securityIdmTransport.password	The password for the user used to authenticate consumer REST API calls. The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses. If you have configured HP CSA to be FIPS 140-2 compliant, encrypt this password after you have configured CSA to be FIPS 140-2 compliant (that is, you should use the updated encryption tools to encrypt the password). Example securityIdmTransport.password=ENC (1Ddh98Kfe76op81hjE0E1897k1RCB5321sb)
age.in.days.to.purge.audit	The age of audit data, in days, that the audit data must be equal to or older than to be deleted by this tool. Default: 400
age.in.days.to.purge.subscription	The amount of time, in days, a subscription has been in a canceled, expired, failed, or retired state before it is deleted by this tool. Default: 400

Example config.properties content

Oracle (TLS not enabled)

```

jdbc.driverClassName=oracle.jdbc.driver.OracleDriver
jdbc.databaseUrl=jdbc:oracle:thin:@127.0.0.1:1521:XE
jdbc.username=csa
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
jdbc.dialect=org.hibernate.dialect.OracleDialect
idmConfig.Url=https://127.0.0.1:8444
securityTransportUserName=csaTransportUser
securityTransport.password=ENC(rlbE8430uFSDljert85441e7fe701jkY)
securityIdmTransportUserName=idmTransportUser
securityIdmTransport.password=ENC(1Ddh98Kfe76op81hjE0E1897k1RCB5321sb)
age.in.days.to.purge.audit=400
age.in.days.to.purge.subscription=400
  
```


MS SQL (TLS not enabled)

```
jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver
jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request
jdbc.username=csa
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
jdbc.dialect=org.hibernate.dialect.SQLServerDialect
idmConfig.Url=https://127.0.0.1:8444
securityTransportUserName=csaTransportUser
securityTransport.password=ENC(rlbE8430uFSDljert85441e7fe701jkY)
securityIdmTransportUserName=idmTransportUser
securityIdmTransport.password=ENC(1Ddh98Kfe76op8lhjE0E1897k1RCB5321sb)
age.in.days.to.purge.audit=400
age.in.days.to.purge.subscription=400
```

MS SQL (TLS enabled)

```
jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver
jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/
example;ssl=authenticate
jdbc.username=csa
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
jdbc.dialect=org.hibernate.dialect.SQLServerDialect
```

MS SQL (FIPS 140-2 compliant)

```
jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver
jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/
example;ssl=authenticate
jdbc.username=csa
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
jdbc.dialect=org.hibernate.dialect.SQLServerDialect
idmConfig.Url=https://127.0.0.1:8444
securityTransportUserName=csaTransportUser
securityTransport.password=ENC(rlbE8430uFSDljert85441e7fe701jkY)
securityIdmTransportUserName=idmTransportUser
securityIdmTransport.password=ENC(1Ddh98Kfe76op8lhjE0E1897k1RCB5321sb)
age.in.days.to.purge.audit=400
age.in.days.to.purge.subscription=400
```

PostgreSQL

```
jdbc.driverClassName=org.postgresql.Driver
jdbc.databaseUrl=jdbc:postgresql://127.0.0.1:5432/csadb
jdbc.username=csadbuser
jdbc.password=ENC(fc5e38d38a5703285441e7fe7010b0)
jdbc.dialect=org.hibernate.dialect.PostgreSQLDialect
idmConfig.Url=https://127.0.0.1:8444
securityTransportUserName=csaTransportUser
securityTransport.password=ENC(rlbE8430uFSDljert85441e7fe701jkY)
securityIdmTransportUserName=idmTransportUser
securityIdmTransport.password=ENC(1Ddh98Kfe76op8lhjE0E1897k1RCB5321sb)
```

```
age.in.days.to.purge.audit=400  
age.in.days.to.purge.subscription=400
```

4. Run the following command to delete subscriptions and audit data (you can specify options to delete only subscriptions or only audit data):

Caution: THE PURGE TOOL RUNS WITHOUT PROMPTING FOR A CONFIRMATION.

Deleted subscriptions and audit data cannot be restored unless you have backed up the database.

Verify that you have entered the correct information into the `config.properties` file before running this tool.

Note: When running the tool to delete subscriptions or audit data, you will be prompted for a username and password. This user **MUST** be assigned to the CSA Administrator role. Users who are not assigned to this role cannot delete subscriptions nor audit data.

Oracle (TLS not enabled)

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -j ojdbc6.jar
```

where `ojdbc6.jar` is the name of the Oracle JDBC driver installed in `%CSA_HOME%\Tools\db-purge-tool` and `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

Oracle (TLS enabled, HP CSA does not check the database DN, client authentication is enabled on the Oracle database server)

```
"<csa_jre>\bin\java"  
-Djavax.net.ssl.keyStore="<certificate_key_file>"  
-Djavax.net.ssl.keyStorePassword=<certificate_key_file_password>  
-Djavax.net.ssl.keyStoreType=<certificate_key_file_type>  
-jar db-purge-tool.jar -j ojdbc6.jar
```

where `ojdbc6.jar` is the name of the Oracle JDBC driver installed in `%CSA_HOME%\Tools\db-purge-tool`, `certificate_key_file` is the same keystore file defined by the `certificate-key-file` attribute in the `ssl` element of the

```
%CSA_HOME%\jboss-as\standalone\configuration\  
standalone.xml file (for example, %CSA_HOME%\jboss-as\  
standalone\configuration\keystore), certificate_key_file_password is the password to the keystore file (for example, changeit), certificate_key_file_type is the keystore type (for example, JKS or PKCS12), and <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.
```

Oracle (TLS enabled, HP CSA does not check the database DN, client authentication is NOT enabled on the Oracle database server)

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -j ojdbc6.jar
```

where `ojdbc6.jar` is the name of the Oracle JDBC driver installed in `%CSA_HOME%\Tools\db-purge-tool` and `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

Oracle (TLS enabled, HP CSA checks the database DN, client authentication is enabled on the Oracle database server)

```
"<csa_jre>\bin\java"  
-Doracle.net.ssl_server_dn_match=true  
-Djavax.net.ssl.keyStore="<certificate_key_file>"  
-Djavax.net.ssl.keyStorePassword=<certificate_key_file_password>  
-Djavax.net.ssl.keyStoreType=<certificate_key_file_type>  
-jar db-purge-tool.jar -j ojdbc6.jar
```

where `ojdbc6.jar` is the name of the Oracle JDBC driver installed in `%CSA_HOME%\Tools\db-purge-tool`, `certificate_key_file` is the same keystore file defined by the `certificate-key-file` attribute in the `ssl` element of the

`%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` file (for example, `%CSA_HOME%\jboss-as\standalone\configuration\keystore`), `certificate_key_file_password` is the password to the keystore file (for example, `changeit`), `certificate_key_file_type` is the keystore type (for example, `JKS` or `PKCS12`), and `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

Oracle (TLS enabled, HP CSA checks the database DN, client authentication is NOT enabled on the Oracle database server)

```
"<csa_jre>\bin\java"  
-Doracle.net.ssl_server_dn_match=true -jar db-purge-tool.jar -j ojdbc6.jar
```

where `ojdbc6.jar` is the name of the Oracle JDBC driver installed in `%CSA_HOME%\Tools\db-purge-tool` and `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

MS SQL and PostgreSQL

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

The following options are available in the purge tool

Option	Description
<code>-jar db-purge-tool.jar</code>	Required. The name of the tool to run.

Option	Description
-a, --audit	<p>Optional. Purge audit data. If neither -a nor -s are specified, the tool purges both audit data and subscriptions.</p> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>Note: When running the tool to delete subscriptions or audit data, you will be prompted for a username and password. This user MUST be assigned to the CSA Administrator role. Users who are not assigned to this role cannot delete subscriptions nor audit data.</p> </div>
-c <config_properties>, --config <config_properties>	<p>Optional. The name and location of the configuration properties file. By default, the tool looks for the configuration properties file in the working directory (the directory from which the tool is run). If this option is not specified, the tool looks for the config.properties in the working directory. The examples in this document assume the file is located in the working directory and is named config.properties.</p>
-g, --generate	<p>Optional. Generate example configuration properties files for supported databases.</p>
-h, --help	<p>Optional. List the options available in this tool.</p>
-j <jdbc_drivers>, --jars <jdbc_drivers>	<p>Optional. The name and location of the JDBC driver(s) to be used by this tool. If more than one driver needs to be specified, separate each driver by a space. By default, the tool looks for the JDBC driver(s) in the working directory (the directory from which the tool is run). If you are not running the tool from %CSA_HOME%\Tools\db-purge-tool, specify the name and location of the JDBC driver(s) to be used. If the path name contains a space, the path and file name should be enclosed in quotation marks. For example:</p> <pre style="margin-left: 20px;">-j "C:\Program Files\jdbc\ojdbc6.jar"</pre> <p>For a list of supported JDBC driver versions, refer to the <i>HP Cloud Service Automation System and Software Support Matrix</i>, available on the HP Software Support Web site at http://h20230.www2.hp.com/selfsolve/manuals/ (this site requires that you register with HP Passport).</p>
-s, --subscription	<p>Optional. Purge subscription data. If neither -s nor -a are specified, the tool purges both subscriptions and audit data.</p> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>Note: When running the tool to delete subscriptions or audit data, you will be prompted for a username and password. This user MUST be assigned to the CSA Administrator role. Users who are not assigned to this role cannot delete subscriptions nor audit data.</p> </div>

Examples for Oracle (TLS is not Enabled)

Display the purge tool help:

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -h -j ojdbc6.jar
```

Generate sample configuration properties files:

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -g -j ojdbc6.jar
```

Purge subscriptions and associated entities:

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -s -j ojdbc6.jar
```

Purge audit data: "<csa_jre>\bin\java" -jar db-purge-tool.jar -a -j ojdbc6.jar

Purge subscriptions and associated entities and audit data:

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -j ojdbc6.jar
```

Examples for MS SQL and PostgreSQL

Display the purge tool help: "<csa_jre>\bin\java" -jar db-purge-tool.jar -h

Generate sample configuration properties files:

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -g
```

Purge subscriptions and associated entities:

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar -s
```

Purge audit data: "<csa_jre>\bin\java" -jar db-purge-tool.jar -a

Purge subscriptions and associated entities and audit data:

```
"<csa_jre>\bin\java" -jar db-purge-tool.jar
```

Install the HP CSA Database Schema

The schema installation tool is used to upgrade the existing HP CSA database schema or install a fresh database schema without re-installing HP CSA. Use this tool if you did not install HP CSA database components onto the database during installation, did not upgrade the database schema during an upgrade, or if you want to drop the existing schema and install a fresh HP CSA database schema. You can also use this tool to complete an upgrade if the upgrade failed, the database schema was not updated, the failure was not due to a database problem, and the problem can be fixed without rerunning the upgrade installer. For example, if the upgrade failed but can be completed successfully by manual configuration but the database schema was not updated, you can simply make the manual changes to complete the upgrade and run the schema installation tool instead of reverting HP CSA back to the previous version and running the upgrade installer again.

Note: Do not run this tool if you installed the database components during the installation of HP CSA or if you upgraded the database schema when you upgraded HP CSA.

If you run this tool on an existing schema (where HP CSA has been upgraded but the database schema was not upgraded), the schema is upgraded and no data in the database is lost. However, if you drop the existing schema and run this tool, all data in the database associated with the dropped schema is lost. Once you run the tool, a fresh schema is installed and you cannot revert back to the dropped schema.

Caution: Once you drop an existing schema and run the database schema installation tool, you cannot revert back to the dropped schema.

Upgrading or Installing the Database Schema

To upgrade or install a fresh HP CSA database schema, do the following:

1. If HP CSA is running, stop HP CSA.

To stop HP CSA:

- a. On the server that hosts HP Cloud Service Automation, navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service and select **Stop**.
 - c. Right-click on the HP Marketplace Portal service and select **Stop**.
 - d. If you installed an embedded HP Operations Orchestration instance, right-click on the HP Operations Orchestration Central service and select **Stop**.
2. Change to the %CSA_HOME%\Tools\SchemaInstallationTool\ directory where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed.
 3. During upgrade or installation of HP CSA, a file named db.properties was generated in %CSA_HOME%\Tools\SchemaInstallationTool\. Verify the property values in this file. If you changed any database property values in the %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml file after installation, the values in db.properties may not be up-to-date.

If you have dropped the existing database schema and are installing a fresh database schema after upgrading to HP CSA4.20, you must update the driverFiles property value. The properties defined in db.properties are described in the table.

Property Name	Description
dbUrl	<p>The JDBC URL. When specifying an IPv6 address, it must be enclosed in square brackets (see examples below).</p> <p>Examples</p> <p>Oracle (TLS not enabled): <code>jdbc.databaseUrl=jdbc:oracle:thin:@127.0.0.1:1521:XE</code></p> <p>Oracle (TLS not enabled, using an IPv6 address): <code>jdbc.databaseUrl=jdbc:oracle:thin:@[f000:253c::9c10:b4b4]:1521:XE</code></p> <p>Oracle (TLS enabled, HP CSA does not check the database DN): <code>jdbc.databaseUrl=jdbc:oracle:thin:@(DESCRIPTION=(ADDRESS_LIST=(ADDRESS=(PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA =(SERVICE_NAME = ORCL)))</code> where <host> is the name of the system on which the Oracle database server is installed.</p> <p>Oracle (TLS enabled, HP CSA checks the database DN): <code>jdbc.databaseUrl=jdbc:oracle:thin:@(DESCRIPTION = (ADDRESS_LIST = (ADDRESS = (PROTOCOL = TCPS)(HOST = <host>)(PORT = 1521))) (CONNECT_DATA = (SERVICE_NAME = ORCL))(SECURITY=(SSL_SERVER_CERT_DN="CN=abc,OU=dbserver,O=xyz,L=Sunnyvale,ST=CA,C=US"))</code> where <host> is the name of the system on which the Oracle database server is installed and the values for SSL_SERVER_CERT_DN are for the DN of the Oracle database server.</p> <p>MS SQL (TLS not enabled): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=request</code></p> <p>MS SQL (TLS not enabled, using an IPv6 address): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://[::1]:1433/example;ssl=request</code></p> <p>MS SQL (TLS enabled): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate</code></p> <p>MS SQL (FIPS 140-2 compliant): <code>jdbc.databaseUrl=jdbc:jtds:sqlserver://127.0.0.1:1433/example;ssl=authenticate</code></p>

Property Name	Description
dbUserName	The user name of the database user you configured for HP Cloud Service Automation after installing the database.
dbPassword	<p>The password for the database user. The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>While you may enter a password in clear text, after you run the tool, the clear text password is automatically replaced by an encrypted password.</p> <p>If you have configured HP CSA to be FIPS 140-2 compliant, encrypt this password after you have configured CSA to be FIPS 140-2 compliant (that is, you should use the updated encryption tools to encrypt the password).</p> <p>Example</p> <pre>dbPassword=ENC(fc5e38d38a5703285441e7fe7010b0)</pre>

Property Name	Description
driverFiles	<p>The database driver files used by this tool. If you are running a fresh installation of HP CSA 4.20 (you did not upgrade to HP CSA 4.20), you do not need to change these values.</p> <p>If you have upgraded to HP CSA 4.20 and want to upgrade the existing schema, you do not need to change these values.</p> <p>If you have upgraded to HP CSA 4.20, have dropped the existing database schema, and are installing a fresh database schema, you must update this value to the following:</p> <p>Oracle (upgrade and dropped schema only) <code>driverFiles=%CSA_HOME%\scripts\schemainstallforupg\ create-oracle-schema.sql, %CSA_HOME%\scripts\schemainstallforupg\ create-oracle-topology-schema.sql, %CSA_HOME%\scripts\schemainstallforupg\oracle\ seed_data_driver.sql, %CSA_HOME%\scripts\reporting\oracle\ install_views_driver.sql, %CSA_HOME%\scripts\reporting\oracle\ grant-reporting-user.sql</code></p> <p>PostgreSQL (upgrade and dropped schema only) <code>driverFiles=%CSA_HOME%\scripts\schemainstallforupg\ create-postgres-schema.sql, %CSA_HOME%\scripts\schemainstallforupg\ create-postgres-topology-schema.sql, %CSA_HOME%\scripts\schemainstallforupg\postgres\ seed_data_driver.sql, %CSA_HOME%\scripts\reporting\postgres\ install_views_driver.sql, %CSA_HOME%\scripts\reporting\postgres\ grant-reporting-user.sql</code></p> <p>Microsoft SQL (upgrade and dropped schema only) <code>driverFiles=%CSA_HOME%/scripts/schemainstallforupg/ alterdb.sql, %CSA_HOME%\scripts\schemainstallforupg\ create-mssql-schema.sql, %CSA_HOME%\scripts\schemainstallforupg\ create-mssql-topology-schema.sql, %CSA_HOME%\scripts\schemainstallforupg\ mssql\seed_data_driver.sql,</code></p>

Property Name	Description
	<p>Note: Add the grant-reporting-user.sql file only if you have created the reporting database user for HP CSA.</p>
jdbcDriverClassName	<p>The JDBC driver class. Do not change this value.</p> <p>Examples</p> <p>Oracle: jdbc.driverClassName=oracle.jdbc.driver.OracleDriver</p> <p>MS SQL: jdbc.driverClassName=net.sourceforge.jtds.jdbc.Driver</p> <p>PostgreSQL: jdbc.driverClassName=org.postgresql.Driver</p>
jdbcDriverDir	<p>The location of the JDBC driver(s) used by this tool. Do not change this value.</p>

4. Run the following command:

Oracle (TLS not enabled), MS SQL, and PostgreSQL

```
"<csa_jre>\bin\java" -jar schema-installation-tool.jar
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

Oracle (TLS enabled, HP CSA does not check the database DN, client authentication is enabled on the Oracle database server)

```
"<csa_jre>\bin\java" -Djavax.net.ssl.keyStore="<certificate_key_file>"
-Djavax.net.ssl.keyStorePassword=<certificate_key_file_password>
-Djavax.net.ssl.keyStoreType=<certificate_key_file_type>
-jar schema-installation-tool.jar
```

where certificate_key_file is the same keystore file defined by the certificate-key-file attribute in the ssl element of the %CSA_HOME%\jboss-as\standalone\configuration\standalone.xml file (for example, %CSA_HOME%\jboss-as\standalone\configuration\keystore), certificate_key_file_password is the password to the keystore file (for example, changeit), certificate_key_file_type is the keystore type (for example, JKS or PKCS12) and <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

Oracle (TLS enabled, HP CSA does not check the database DN, client authentication is NOT enabled on the Oracle database server)

```
"<csa_jre>\bin\java" -jar schema-installation-tool.jar
```

where <csa_jre> is the directory in which the JRE that is used by HP CSA is installed.

Oracle (TLS enabled, HP CSA checks the database DN, client authentication is enabled on the Oracle database server)

```
"<csa_jre>\bin\java" -Doracle.net.ssl_server_dn_match=true  
-Djavax.net.ssl.keyStore="<certificate_key_file>"  
-Djavax.net.ssl.keyStorePassword=<certificate_key_file_password>  
-Djavax.net.ssl.keyStoreType=<certificate_key_file_type>  
-jar schema-installation-tool.jar
```

where `certificate_key_file` is the same keystore file defined by the `certificate-key-file` attribute in the `ssl` element of the `%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` file (for example, `%CSA_HOME%\jboss-as\standalone\configuration\keystore`), `certificate_key_file_password` is the password to the keystore file (for example, `changeit`), `certificate_key_file_type` is the keystore type (for example, `JKS` or `PKCS12`), and `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

Oracle (TLS enabled, HP CSA checks the database DN, client authentication is NOT enabled on the Oracle database server)

```
"<csa_jre>\bin\java" -Doracle.net.ssl_server_dn_match=true  
-jar schema-installation-tool.jar
```

where `<csa_jre>` is the directory in which the JRE that is used by HP CSA is installed.

Configure HP CSA to Mitigate Frequently Dropped Database Connections

If you are experiencing frequently dropped database connections, configure the JBoss data source connections to mitigate the problem.

In a standalone environment, do the following:

1. Stop the HP Cloud Service Automation service:
 - a. Navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service.
 - c. Select **Stop**.
2. Edit the `%CSA_HOME%\jboss-as\standalone\configuration\standalone.xml` file:
 - a. Find the `dataSource` tag which is used for HP CSA database configuration.
 - b. Add the following after the line that ends with `</security>`:

Oracle

```
<validation>  
<check-valid-connection-sql>select 1 from DUAL</check-valid-connection-sql>  
<validate-on-match>>false</validate-on-match>  
</validation>
```

MS SQL or PostgreSQL

```
<validation>  
<check-valid-connection-sql>select 1</check-valid-connection-sql>  
<validate-on-match>>false</validate-on-match>  
</validation>
```

3. Start the HP Cloud Service Automation service:
 - a. Navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service.
 - c. Select **Start**.

In a clustered environment, do the following:

1. Stop the HP Cloud Service Automation service:
 - a. Navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service.
 - c. Select **Stop**.
2. Edit the %CSA_HOME%\jboss-as\domain\configuration\domain.xml file:
 - a. Find the dataSource tag which is used for HP CSA database configuration.
 - b. Add the following after the line that ends with </security>:

Oracle

```
<validation>  
<check-valid-connection-sql>select 1 from DUAL</check-valid-connection-sql>  
<validate-on-match>>false</validate-on-match>  
</validation>
```

MS SQL or PostgreSQL

```
<validation>  
<check-valid-connection-sql>select 1</check-valid-connection-sql>
```

```
<validate-on-match>false</validate-on-match>  
</validation>
```

3. Start the HP Cloud Service Automation service:
 - a. Navigate to **Control Panel > Administrative Tools > Services**.
 - b. Right-click on the HP Cloud Service Automation service.
 - c. Select **Start**.

Appendix A: Cloud Service Management Console Properties

This section lists and describes the properties that can be configured for the Cloud Service Management Console, which are located in one of the following files:

- %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties
- %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\web.xml

where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed.

The following areas contain properties that can be configured (for many properties, default values are provided):

- [Authentication](#)
- [Security Banner](#)
- [Marketplace Portal URL](#)
- [Security](#)
- [HP Cloud Service Automation keystore](#)
- [Service request processor scheduler](#)
- [Auditing](#)
- [Process execution manager](#)
- [Lifecycle engine](#)
- [Approval engine scheduler](#)
- [LDAP cache scheduler](#)
- [Clustering](#)
- [Dynamic property](#)
- [HP CDA integration](#)
- [Marketplace Portal](#)

- [FIPS 140-2](#)
- [Common access card](#)
- [Single sign-on](#)
- [HP Single Sign-On](#)
- [Process executor delegate](#)
- [Miscellaneous](#)
- [HP Operations Orchestration](#)
- [HP CSA 3.x API authentication](#)
- [Topology designer](#)
- [Session timeout](#)

After modifying the `csa.properties` file, restart HP CSA. See "[Restart HP CSA](#)" on page 109 for detailed information on how to restart HP CSA.

Authentication

These properties are used for authentication.

These properties are configured in `csa.properties`.









Property	Description
<code>csa.provider.hostname</code>	<p>Required. The fully-qualified domain name of the system on which HP Cloud Service Automation is running.</p> <p>If you change this hostname, you must update the value of the <code>idm.csa.hostname</code> property in the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties</code> file.</p>
<code>csa.provider.port</code>	<p>Required. The port used to connect to the system on which HP Cloud Service Automation is running.</p> <p>If you change this port, you must update the value of the <code>idm.csa.port</code> property in the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties</code> file.</p>
<code>csa.provider.rest.protocol</code>	<p>Required. The protocol used by the REST API to connect to the system on which HP Cloud Service Automation is running.</p> <p>This attribute must be set to https.</p> <p>If you change this protocol, you must update the value of the <code>idm.csa.protocol</code> property in the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties</code> file.</p>
<code>csa.orgName.identifier</code>	<p>Required. The provider organization identifier assigned to the organization who is providing this instance of the Cloud Service Management Console.</p> <p>This attribute must be set to CSA-Provider.</p>

Security Banner Attributes

The attributes in the following table are used by the Cloud Service Management Console to enable or disable the display of a disclaimer upon logging in to the Cloud Service Management Console and a color-coded banner that appears at the top and bottom of the Cloud Service Management Console.

These properties are configured in `csa.properties`.

Attribute	Description
csa.provider.agency	<p>By default, this attribute is commented out. When this attribute is commented out or does not contain a valid value, the login disclaimer and color-coded banners are not displayed for the Cloud Service Management Console.</p> <p>If you want to enable the login disclaimer and color-coded banners, uncomment this attribute and set the value to GOVERNMENT. If set to any other value, the login disclaimer and color-coded banners are not displayed.</p> <p>To edit the disclaimer page, edit the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\static\template\disclaimerNote.jsp file.</p> <p>To edit the disclaimer content, edit the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\msgs\messages_en.properties file.</p>

Attribute	Description
<p>csa.provider.contentType</p>	<p>By default, this attribute is commented out. This attribute defines the color and content that displays in the security banner. The security banners appear at the top and bottom of the Cloud Service Management Console.</p> <p>The following values are provided out-of-the-box:</p> <ul style="list-style-type: none"> <p>UNCLASSIFIED. The banner is light green and contains no content. An example is shown below.</p>  <p>UNCLASSIFIED_FOUO. For official use only. The banner is light green and displays the text "FOUO." An example is shown below.</p>  <p>UNCLASSIFIED_NOFORN. Not releasable to foreign nationals. The banner is light green and displays the text "NOFORN." An example is shown below.</p>  <p>CONFIDENTIAL. The banner is light blue and displays the text "CONFIDENTIAL." An example is shown below.</p>  <p>CONFIDENTIAL_FOUO. The banner is light blue and displays the text "CONFIDENTIAL-FOUO." An example is shown below.</p>  <p>CONFIDENTIAL_NOFORN. The banner is light blue and displays the text "CONFIDENTIAL-NOFORN." An example is shown below.</p>  <p>SECRET. The banner is red and displays the text "SECRET." An example is shown below.</p>  <p>TOPSECRET. The banner is orange and displays the text "TOPSECRET." An example is shown below.</p>  <p>To edit the banner content, edit the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\msgs\messages_en.properties</code> file.</p>

Marketplace Portal URL

This property is used to define the URL of the Marketplace Portal for an organization and is displayed in the Cloud Service Management Console.

This property is configured in `csa.properties`.

Property	Description
<p><code>csa.subscriber.portal.url</code></p>	<p>The URL used to access the Marketplace Portal of an organization and is displayed in the Organization URL field in the General Information section of an organization's page in the Cloud Service Management Console.</p> <p>You can use specific values or one or more of the following variables:</p> <ul style="list-style-type: none"> • <code>{protocol}</code> - The protocol used to connect to the Marketplace Portal. This is either <code>http</code> or <code>https</code>. The variable value is the same protocol used to access the Cloud Service Management Console. • <code>{host}</code> - The fully-qualified domain name or IP address of the system on which the Marketplace Portal is installed. The variable value is the same host on which the Cloud Service Management Console is installed. • <code>{orgName}</code> - The organization's name. The variable value is the Organization Identifier displayed in the General Information section of an organization's page. The Organization Identifier is based on the value entered in the Organization Display Name field. <p>The port configured for the Marketplace Portal in this property should match the <code>port</code> attribute value configured in the <code>%CSA_HOME%\portal\conf\mpp.json</code> file.</p> <p>If a variable's value is incorrect, you can enter a specific value in place of the variable. For example, <code>https://{host}:8089/org/{orgName}</code> or <code>{protocol}://csa_system.xyz.com:8089/#/login/marketing</code></p> <p>Default: <code>{protocol}://{host}:8089/org/{orgName}</code></p>

Security

These properties are used to configure encrypted passwords (see ["Encrypt a Password" on page 110](#) for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.

These properties are configured in `csa.properties`.

Property	Description
<p>securityAdminPassword</p>	<p>Required. The encrypted password used by the out-of-the-box admin user (defined in the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml file). The admin user account is used for initial login to the Cloud Service Management Console and can also be used to authenticate REST API calls.</p> <p>The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>If you change this password, you must also update the password of any REST API calls that use this password. For more information about the REST APIs, refer to the <i>HP Cloud Service Automation Integration Guide</i>.</p>
<p>securityCsaReportingUserPassword</p>	<p>Required. The encrypted password used by the out-of-the-box csaReportingUser user (defined in the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml file). The csaReportingUser user account is used when a subscription is ordered or modified and a field for the subscription includes a dynamically generated list. The dynamically generated list is a subscriber option property configured to use a dynamic query. The dynamic query uses this account to access HP Cloud Service Automation to determine the values that will appear in the list. This account has read-only access to HP Cloud Service Automation.</p> <p>The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>If you change this password, you must also update the password of any REST API calls that use this password. For more information about the REST APIs, refer to the <i>HP Cloud Service Automation Integration Guide</i>.</p>

Property	Description
<p>securityTransport UserName</p>	<p>Required. The out-of-the-box user used to authenticate REST API calls between the Marketplace Portal and Cloud Service Management Console (it should not be used to log in to the Cloud Service Management Console).</p> <p>If you change this username, you must update the value of the <code>idm.csa.username</code> property in the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties</code> file.</p> <p>For more information about the integration user account, see "Change HP CSA Out-of-the-Box User Accounts" on page 121. For more information about the REST APIs, refer to the <i>HP Cloud Service Automation Integration Guide</i>.</p>
<p>securityTransportPassword</p>	<p>Required. The encrypted password used by the out-of-the-box <code>csaTransportUser</code> user (defined in the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml</code> file). The <code>csaTransportUser</code> user account is used to authenticate REST API calls between the Marketplace Portal and Cloud Service Management Console (it should not be used to log in to the Cloud Service Management Console).</p> <p>The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses.</p> <p>If you change this password, you must update the value of the <code>idm.csa.password</code> property in the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties</code> file.</p> <p>For more information about the integration user account, see "Change HP CSA Out-of-the-Box User Accounts" on page 121. For more information about the REST APIs, refer to the <i>HP Cloud Service Automation Integration Guide</i>.</p>

Property	Description
<p>securityOoInbound UserPassword</p>	<p>Required. The encrypted password used by the out-of-the-box ooInboundUser user (defined in the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml file). The ooInboundUser user account is used by HP Operations Orchestration to authenticate REST API calls with HP Cloud Service Automation (it should not be used to log in to the Cloud Service Management Console).</p> <p>The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>If you change this password, you must also update and use the same password for the CSA_REST_CREDENTIALS system account in HP Operations Orchestration (see "HP Operations Orchestration Settings" on page 269 and the <i>HP Cloud Service Automation Installation Guide</i>).</p>
<p>securityCdaInbound UserPassword</p>	<p>Required. The encrypted password used by the out-of-the-box cdaInboundUser user (defined in the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml file). The cdaInboundUser user account is used by HP CDA to authenticate REST API calls with HP Cloud Service Automation (it should not be used to log in to the Cloud Service Management Console).</p> <p>The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>If you change this password, you must also update and use the same password in HP CDA. For more information about this user account, see "Change HP CSA Out-of-the-Box User Accounts" on page 121.</p>

Property	Description
securityIdmTransportUserPassword	<p>Required. The encrypted password used by the out-of-the-box <code>idmTransportUser</code> user (defined in the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml</code> file). The <code>idmTransportUser</code> user account is used to authenticate REST API calls (it should not be used to log in to the Cloud Service Management Console).</p> <p>The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses.</p> <p>If you change this password, you must also update the following passwords (you must use the same password):</p> <ul style="list-style-type: none">• the <code>idmTransportUser</code> property in the <code>%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\classes\integrationusers.properties</code> file.• the <code>password</code> attribute in the <code>idmProvider</code> section of the <code>%CSA_HOME%\portal\conf\mpp.json</code> file (this password uses a different password encryption utility; see "Encrypt a Marketplace Portal Password" on page 114 for more information about encrypting the password attribute).• the password of any REST API calls that use this password. <p>For more information about this user account, see "Change HP CSA Out-of-the-Box User Accounts" on page 121.</p>

Property	Description
<p>securityCatalog AggregationTransport UserPassword</p>	<p>Required. The encrypted password used by the out-of-the-box csaCatalogAggregationTransportUser user (defined in the %CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml file). The csaCatalogAggregationTransportUser user account is used to authenticate catalog aggregation REST API calls with HP Cloud Service Automation (it should not be used to log in to the Cloud Service Management Console).</p> <p>The password should be encrypted (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>If you change this password, you must also update the password using the catalog aggregation registration REST APIs. For more information about this user account, see "Change HP CSA Out-of-the-Box User Accounts" on page 121.</p>
<p>securityEncrypted SigningKey</p>	<p>HP CSA's encrypted signing key used to encrypt and decrypt authentication data passed between HP CSA and the HP Identity Management component.</p> <p>If you change this key, you must also update the idm.encryptedSigningKey property in the %CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\applicationContext.properties file.</p> <p>The key should be encrypted (see "Encrypt a Password" on page 110 for instructions on how to encrypt this key). The encrypted key is preceded by ENC without any separating spaces and is enclosed in parentheses.</p>
<p>com.hp.ccue.consumption disallowedExtensions</p>	<p>A comma-delimited list of the file extensions that designate the types of documents or files that cannot be uploaded to the Cloud Service Management Console.</p> <p>Default: exe,bat,com,cmd</p>

Property	Description
<p>csa.additionalSupportedExtensionsForImport</p>	<p>A comma-delimited list of the file extensions that designate the types of documents or files that can be uploaded to the Cloud Service Management Console. The file extensions listed can be the sole extension of the file (for example, <code>mydocument.txt</code>, where <code>txt</code> is one of the listed file extensions) or the start of the file extension (for example, <code>mydocument.txt_3491767613</code>).</p> <p>Files can be uploaded using the Cloud Service Management Console, the content archive tool, or the import API. Refer to the HP Cloud Service Management Console Help, <i>HP Cloud Service Automation API Reference Guide</i>, or <i>HP Cloud Service Automation Content Archive Tool</i> for more information about using these features.</p> <p>The following extensions are automatically supported (and do not need to be defined by this property): <code>jpg</code>, <code>jpeg</code>, <code>jpe</code>, <code>jfif</code>, <code>svg</code>, <code>tif</code>, <code>tiff</code>, <code>ras</code>, <code>cmx</code>, <code>ico</code>, <code>pnm</code>, <code>pbm</code>, <code>pgm</code>, <code>ppm</code>, <code>rgb</code>, <code>xbm</code>, <code>xpm</code>, <code>xwd</code>, <code>png</code>, <code>gif</code>, <code>bmp</code>, <code>cod</code>, <code>ief</code>, <code>json</code>, <code>xml</code>, <code>jsp</code>, <code>jspx</code>.</p> <p>Default: (no default defined)</p> <p>Example: <code>txt,log</code></p>
<p>csa.maxFileUploadSize</p>	<p>The maximum size of a file, in megabytes (MB), that can be uploaded to the HP CSA system using the Cloud Service Management Console. If this property is not listed or is not set in the <code>csa.properties</code> file, the default maximum size of 50 MB is used.</p> <p>Default: 50 (MB)</p>

HP Cloud Service Automation Keystore

These properties are used to configure information about HP Cloud Service Automation's keystore.

These properties are configured in `csa.properties`.

Property	Description
<code>csaTruststore</code>	<p>Required. The HP Cloud Service Automation keystore that stores trusted Certificate Authority certificates.</p> <p>Default: No default specified</p> <p>Example</p> <p><code>C:/Program Files/Hewlett-Packard/CSA/openjre/lib/security/cacerts</code></p> <p>Note: Use only forward slashes (/) as your path separators.</p>
<code>csaTruststorePassword</code>	<p>Required. The encrypted password of the HP Cloud Service Automation keystore (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by <code>ENC</code> without any separating spaces and is enclosed in parentheses.</p> <p>Default: No default specified</p> <p>Example</p> <p><code>ENC(9eC7TTnB0uG0GK5U648UITcEV5AuV5T)</code></p>

Service Request Processor Scheduler

These properties are used to configure the service request processor scheduler. The service request processor scheduler validates a consumer's requests, initiates the approval process, if configured, and maintains a request's status.

These properties are configured in `csa.properties`.

Property	Description
<code>serviceRequestProcessorScheduler.maxInstancesToProcess</code>	Optional. The maximum number of service requests the service request processor can process when it checks the start and end dates of submitted subscriptions. Default: 100
<code>serviceRequestProcessorScheduler.period</code>	Optional. How often, in milliseconds, the service request processor checks the start and end dates of submitted subscriptions. Default: 5000 (5 seconds)

Auditing

These properties are used to configure auditing.

These properties are configured in `csa.properties`.

Property	Description
<code>csaAuditEnabled</code>	Optional. Enable or disable auditing, which tracks user activities and system-generated events. Messages are logged to the <code>CSA_AUDIT_EVENT</code> table in the database. Default: true (enabled)
<code>jboss.shutdown.log.location</code>	Required. This property is set during installation and <i>must not be changed</i> . The location of the JBoss log file that records when the HP CSA service was stopped. Used for auditing purposes. Default: <code>%CSA_HOME%/jboss-as/bin/shutdown.log</code> Note: Use only forward slashes (/) as your path separators.

Process Execution Manager

These properties are used to configure the process execution manager. The process execution manager starts internal actions and HP Operations Orchestration flow actions, checks the status of process instances, and performs callback once the actions are completed.

These properties are configured in `csa.properties`.

Property	Description
<code>com.hp.csa.ProcessExecutor.THREAD_WAKEUP_TIME</code>	Optional. How often, in milliseconds, the process execution manager starts new process instances (which start HP Operations Orchestration flows) and checks the status of process instances. Default: 5000 (5 seconds)
<code>com.hp.csa.ProcessExecutor.THREAD_POOL_CORE_SIZE</code>	Optional. The maximum number of threads used to run process instances. Default: 2
<code>com.hp.csa.PEM.PARAM_PROCESS_INSTANCE_ID</code>	Optional. The token that stores the process instance ID and is used when HP Cloud Service Automation starts an HP Operations Orchestration flow. Default: <code>CSA_PROCESS_ID</code>
<code>com.hp.csa.PEM.PARAM_CONTEXT_ID</code>	Optional. The token that stores the artifact ID of the artifact that owns the action that executes the HP Operations Orchestration flow. Default: <code>CSA_CONTEXT_ID</code>

Lifecycle Engine

These properties are used to configure the lifecycle engine. The lifecycle engine processes service instances and executes lifecycle actions.

These properties are configured in `csa.properties`.

Property	Description
<code>com.hp.csa.LifecycleExecutor.THREAD_WAKEUP_TIME</code>	Optional. How often, in milliseconds, the lifecycle engine checks for service components that it needs to transition. Default: 5000 (5 seconds)
<code>com.hp.csa.LifecycleExecutor.THREAD_POOL_SIZE</code>	Optional. The maximum number of threads used to transition service components. Default: 2

Approval Engine Scheduler

This property is used to configure the approval engine scheduler. The approval engine scheduler checks each approver's response to a pending approval process to see if the process can be marked as completed and updates the decision and status of an approval process, as needed.

This property is configured in `csa.properties`.

Property	Description
<code>com.hp.csa.ApprovalDecisionMaker.THREAD_WAKEUP_TIME</code>	Optional. How often, in minutes, the approval engine scheduler checks for completion of an approval process to determine if an approval process should be approved or denied. Default: 1

LDAP Cache Scheduler

These properties are used to configure the LDAP cache scheduler. The LDAP cache scheduler checks the age of the user group cache and deletes it if it has expired.

For users who can log in to the Cloud Service Management Console or Marketplace Portal, certain actions require authorization (verification if the user belongs to a group). When authorization is requested for a user, HP CSA checks for group membership by using the cache. If the cache does not exist, LDAP is queried for the user's user groups which are temporarily cached to the database. After a configured expiration time, the cache is deleted. During a single session, the cache may be deleted and refreshed as needed.

These properties are configured in `csa.properties`.

Property	Description
<code>com.hp.csa.UserGroupExecutor.THREAD_WAKEUP_TIME</code>	Optional. How often, in minutes, the LDAP cache scheduler checks for user group caches that have expired. This number should be less than the value configured for <code>com.hp.csa.UserGroupExecutor.CACHE_EXPIRATION_TIME</code> . Default: 20
<code>com.hp.csa.UserGroupExecutor.CACHE_EXPIRATION_TIME</code>	Optional. How long, in minutes, LDAP user groups for a user are temporarily cached in the database before they are deleted. This time should be greater than the value configured for <code>com.hp.csa.UserGroupExecutor.THREAD_WAKEUP_TIME</code> . Default: 30
<code>com.hp.csa.UserGroupExecutor.UserGroupDeletionBatchSize</code>	Optional. The maximum number of user IDs that are deleted in a single batch from the cache. This number cannot be larger than 1,000. Default: 250

Clustering

This property is used to configure clustering.

This property is configured in `csa.properties`.

Property	Description
deploymentMode	<p>Required. The mode in which HP CSA is running (single or clustered). When set to <code>single</code>, HP CSA runs in standalone mode (on a single instance) and all HP CSA services are run on this instance. When set to <code>clustered</code>, HP CSA runs in domain mode (in a clustered environment) and all HP CSA services are run on the master node.</p> <p>If you are using Microsoft SQL Server as your database, this property must be set to <code>single</code>.</p> <p>Default: <code>single</code></p>

Dynamic Property

These configuration properties are used to limit the amount of time to retrieve data and the amount of data retrieved when using a dynamic property. A dynamic property is a Dynamic Query value entry method for a subscriber option property that defines what information is retrieved. A dynamic property allows the Service Designer to list a dynamic set of values that change based on the user context (for example, the organization to which the user belongs).

These properties are configured in `csa.properties`.

Property	Description
DynamicPropertyFetch.READ_TIMEOUT	<p>Optional. How long, in milliseconds, HP Cloud Service Automation attempts to fetch or retrieve data for dynamic properties.</p> <p>Default: 3000 (3 seconds)</p>
DynamicPropertyFetch.RESPONSE_SIZE	<p>Optional. The maximum amount of data, in bytes, that can be retrieved for dynamic properties.</p> <p>Default: 50000</p>

Group Approval

This configuration property is used when configuring a group approval template.

This property is configured in `csa.properties`.

Property	Description
<code>csa.group.numberOfApprovers</code>	Optional. The maximum number of members in an LDAP group used for approvals. For reasonable performance, do not specify more than ten (10) members. Default: 10

HP CDA Integration

This configuration property is used when integrating with HP Continuous Delivery Automation (HP CDA).

This property is configured in `csa.properties`.

Property	Description
<code>defaultDaysToExtendExpirationDate</code>	Optional. How long, in days, HP Cloud Service Automation automatically extends an expired subscription if the subscription is based on HP CDA designs and other services depend on this subscription. If a subscription is based on HP CDA designs and other services depend on the HP Cloud Service Automation service subscription, this subscription cannot be canceled. Default: 1

Marketplace Portal

These properties are the default values displayed in the Cloud Service Management Console that are used to configure the Marketplace Portal for an organization. The values configured in the Cloud Service Management Console take precedence over the values set in this properties file.

These properties are configured in `csa.properties`.

Property	Description
csa.consumer.featuredCategory	<p>Optional. The default value of the Featured Category field displayed in the Cloud Service Management Console of a selected organization. This value may be overwritten in the Cloud Service Management Console. The value configured in the Cloud Service Management Console takes precedence over this value.</p> <p>This is the category that is used when displaying service offerings in the Marketplace Portal.</p> <p>The value entered for this attribute is the name of a category configured in the Cloud Service Management Console but is in all capitalized letters and replaces any spaces with an underscore (_). For example, if you configure a category named e-mail Servers and want to feature this category, you would set this attribute to E-MAIL_SERVERS.</p> <ul style="list-style-type: none"> • ACCESSORY • APPLICATION_SERVERS - Default. • APPLICATION_SERVICES • BACKUP_SERVICES • CRM • DATABASE_SERVERS • FILE_SERVERS • HARDWARE • MAIL_SERVICES • NETWORK_SERVICES • PLATFORM_SERVICES • SIMPLE_SYSTEM • SOFTWARE • WEB_HOSTING_SERVICES <p>For more information about the featured services, refer to the <i>Marketplace Portal Help</i>. For more information about configuring categories for a catalog, refer to the <i>HP Cloud Service Management Console Help</i>. Online help content is available in a printable PDF format on the HP Software Support Web site at http://h20230.www2.hp.com/selfsolve/manuals/ (this site requires that you register with HP Passport).</p>

Property	Description
	Default: APPLICATION_SERVERS
csa.consumer.endDatePeriod	<p>Optional. The default value of the Subscription End Date field displayed in the Cloud Service Management Console of a selected organization. This value may be overwritten in the Cloud Service Management Console. The value configured in the Cloud Service Management Console takes precedence over this value.</p> <p>This is the maximum length of a subscription, in months, if a requested end date is specified. When a subscriber selects a requested start date and requests an end date, the length of the subscription cannot be longer than the value of this property. The maximum allowed value is 12 months. For example, if the subscriber selects a requested start date of June 15, 2012, based on the default value of this property, the requested end date cannot be later than June 14, 2013. If no end date is selected, this value is ignored.</p> <p>Default: 12 (months)</p>
csa.consumer.legalNoticeUrl	<p>Optional. The default value of the Privacy Statement Link field displayed in the Cloud Service Management Console of a selected organization. This value may be overwritten in the Cloud Service Management Console. The value configured in the Cloud Service Management Console takes precedence over this value.</p> <p>This is a link to an organization's privacy statement and, when enabled in the Cloud Service Management Console, appears on the login page below the copyright statement.</p> <p>Default: HP's online privacy statement</p>
csa.consumer.termsOfUseUrl	<p>Optional. The default value of the Terms and Conditions Link field displayed in the Cloud Service Management Console of a selected organization. This value may be overwritten in the Cloud Service Management Console. The value configured in the Cloud Service Management Console takes precedence over this value.</p> <p>This is a link to an organization's terms and conditions statement and, when enabled in the Cloud Service Management Console, appears when a subscriber is ordering a service.</p> <p>Default: HP's terms of use statement</p>

FIPS 140-2 Configuration

These configuration properties are used to configure HP CSA to be compliant with FIPS 140-2.

Note: The `csaTruststore` and `csaTruststorePassword` properties are repeated here because you may need to update them for FIPS 140-2 configuration. These properties are configured in a different section of the `csa.properties` file.

These properties are configured in `csa.properties`.

Property	Description
useExternalProvider	<p>Required if enabling FIPS 140-2 compliance mode. To enable, set this property to true. To disable, set this property to false or comment it out.</p> <p>When enabled, HP CSA uses the RSA BSAFE libraries to encrypt and decrypt passwords. If a password was encrypted using different libraries (for example, if the password was encrypted before this property is enabled), the resulting decrypted password will not be valid.</p> <p>If you cannot connect to the database after you have configured HP CSA for FIPS 140-2 compliance, try re-encrypting the database password in the database properties file.</p> <p>Default: commented out/disabled</p>
securityProviderName	<p>Required if FIPS 140-2 compliance mode is enabled. The name of the FIPS 140-2 compliant provider. By default, HP CSA uses the RSA BSAFE provider and this property should be set to <code>JsafeJCE</code>.</p>
keySize	<p>Optional. The key size used for HP CSA encryption. By default, the key size is 128. If you manually enter a different key size when encrypting a password, uncomment this property and configure the value to the key size used to encrypt the passwords.</p> <div style="background-color: #f0f0f0; padding: 5px; margin-top: 10px;"> <p>Note: All passwords must be encrypted using the same key size.</p> <p>By default, the password encryption utility encrypts all passwords using a key size of 128 (even if you do not specify a key size when running the utility).</p> </div>

Property	Description
keystore	<p>Required if FIPS 140-2 compliance mode is enabled. The absolute path to and file name of the HP CSA encryption keystore. This is the keystore that supports PKCS #12 and stores the key used by HP CSA to encrypt and decrypt data in HP CSA.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/csa_encryption_keystore.p12</pre> <p>Note: Use only forward slashes (/) as your path separators.</p>
keyAlias	<p>Required if FIPS 140-2 compliance mode is enabled. The alias used to identify the HP CSA encryption key in the HP CSA encryption keystore.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>csa_encryption_key</pre>
keystorePasswordFile	<p>Required if FIPS 140-2 compliance mode is enabled. The absolute path to and file name of the HP CSA encryption keystore password. This is a temporary file that stores the HP CSA encryption keystore password in clear text. This file is required to start the HP CSA service and is automatically deleted when the service is started.</p> <p>The password file must contain only the following content:</p> <pre>keystorePassword=<HP CSA encryption keystore password></pre> <p>where <HP CSA encryption keystore password> is the HP CSA encryption keystore password in clear text.</p> <p>Note: Use only forward slashes (/) as your path separators.</p>
encryptedKeyFile	<p>Required if FIPS 140-2 compliance mode is enabled. The location of the HP CSA encrypted symmetric key.</p> <p>Example (this example uses the same example name from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/key.dat</pre> <p>Note: Use only forward slashes (/) as your path separators.</p>

Property	Description
<p>csaTruststore</p>	<p>Required. The HP Cloud Service Automation keystore that stores trusted Certificate Authority certificates.</p> <div data-bbox="542 380 1370 558" style="background-color: #f0f0f0; padding: 5px;"> <p>Note: This property is located in another section of the <code>csa.properties</code> file. Its description is repeated here as its value should be updated when HP CSA has been configured to be compliant with FIPS 140-2.</p> </div> <p>Example (this example uses the same example name of the HP CSA server truststore from "Create an HP CSA Encryption Keystore" on page 173):</p> <pre>%CSA_HOME%/jboss-as/standalone/ configuration/csa_server_truststore.p12</pre> <div data-bbox="542 789 1370 865" style="background-color: #f0f0f0; padding: 5px;"> <p>Note: Use only forward slashes (/) as your path separators.</p> </div>
<p>csaTruststorePassword</p>	<p>Required. The encrypted password of the HP Cloud Service Automation keystore (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p> <p>Default: No default specified</p> <p>Example</p> <pre>ENC(9eC7TTnB0uG0GK5U648UITcEV5AuV5T)</pre> <div data-bbox="542 1209 1370 1388" style="background-color: #f0f0f0; padding: 5px;"> <p>Note: This property is located in another section of the <code>csa.properties</code> file. Its description is repeated here as its value should be updated when HP CSA has been configured to be compliant with FIPS 140-2.</p> </div> <p>This is the <i><HP CSA server truststore password></i> from "Create an HP CSA Encryption Keystore" on page 173.</p>

Common Access Card

This property is used to enable integration between Common Access Card (CAC) and HP CSA.

This property is configured in `csa.properties`.

Property	Description
enableCAC	Optional. Enable integration between CAC and HP CSA, where the CAC is used as an approval mechanism. To enable, this property must be uncommented and set to true. To disable, either comment out the property or set it to false. Default: (disabled)

Single Sign-On

This property is used to enable integration between CA SiteMinder and HP CSA.

This property is configured in `csa.properties`.

Property	Description
enableSSO	Optional. Enable integration between CA SiteMinder and HP CSA, where the SiteMinder is used for single sign-on. To enable, this property must be uncommented and set to true. To disable, either comment out the property or set it to false. Default: (disabled)

HP Single Sign-On

This property is used to enable integration between HP Single Sign-On (HP SSO) and the Cloud Service Management Console. HP SSO can be used when launching an application, such as HP IT Executive Scorecard, from the Cloud Service Management Console.

This property is configured in `csa.properties`.

Property	Description
enableHPSSO	Optional. Enable integration between HP SSO and the Cloud Service Management Console. To enable, this property must be uncommented and set to true. To disable, either comment out the property or set it to false. In a FIPS 140-2 compliant environment, this property must be set to false or must be commented out. This property is automatically set during installation.

Process Executor Delegate

These properties are used to configure the process executor delegate. The process executor delegate handles processing of the process instances. It discovers the ready instances, submits them to different thread pools for processing based on process definition and model type (sequenced or topology).

These properties are configured in `csa.properties`.

Property	Description
com.hp.csa.service.process.ProcessExecutorDelegate.INTERNAL_POOL_SIZE	Optional. The maximum number of threads used for processing internal executors (for example, clone patterns). Default: 2
com.hp.csa.service.process.ProcessExecutorDelegate.EXTERNAL_POOL_SIZE	Optional. The maximum number of threads used for processing external executors (for example, HP Operations Orchestration). Default: 2
com.hp.csa.service.process.ProcessExecutorDelegate.CALLBACK_POOL_SIZE	Optional. The maximum number of threads used by the callback pool. Default: 2
com.hp.csa.service.process.ProcessExecutorDelegate.MONITOR_POOL_SIZE	Optional. The maximum number of threads used by the monitor pool. Default: 2

Miscellaneous

The following is a miscellaneous property that does not fall under any specific category.

This property is configured in `csa.properties`.

Property	Description
com.hp.csa.TimeoutChecker.THREAD_WAKEUP_TIME	Optional. How often, in milliseconds, the background thread monitors for processes that have timed out. Default: 300000

HP Operations Orchestration

These properties are used to integrate with HP Operations Orchestration.

These properties are configured in `csa.properties`.

The following properties configure the interaction between the Cloud Service Management Console and HP Operations Orchestration. In the subscription event overview section of the **Operations** area in the

Cloud Service Management Console, selecting the Process ID opens HP Operations Orchestration to the detailed page of the selected process when these properties are configured.

Property	Description
OOS_URL	The URL used to access HP Operations Orchestration Central. This is the HP Operations Orchestration used for provisioning topology designs (HP Operations Orchestration version 10.20). Set this URL to the system on which HP Operations Orchestration version 10.20 is installed. For example, <code>https://<hostname>:8443</code> .
OOS_USERNAME	The username used to log in to HP Operations Orchestration Central. Set this username to admin.
OOS_PASSWORD	The encrypted password used by the user defined in OOS_USERNAME to log in to HP Operations Orchestration Central. Set this property to the encrypted value of the user defined in OOS_USERNAME (see "Encrypt a Password" on page 110 for instructions on encrypting passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.

The following properties configure background services to monitor HP Operations Orchestration.

Property	Description
com.hp.csa.oo.OOClient.SOCKET_TIMEOUT	Optional. How long, in milliseconds, HP CSA keeps a socket open for SOAP-based communication with HP Operations Orchestration. Default: 60000
com.hp.csa.OosMonitor.THREAD_WAKEUP_TIME	Optional. How often, in milliseconds, the background thread monitors HP Operations Orchestration processes. Default: 60000
com.hp.csa.service.process.OosMonitorDelegate.MONITOR_POOL_SIZE	Optional. The maximum number of threads used by the monitor pool. Default: 2

HP CSA 3.x API Authentication

These properties are used to configure authentication for the HP CSA 3.x API.

These properties are configured in `csa.properties`.

Property	Description
xAuthToken	<p>Optional. An optional token in the Authorization header used for HTTP basic authentication by the HP CSA 3.x API. If the token is sent, it is used to authenticate the <code>userIdentifier</code> parameter in the REST API. For more information about the HP CSA API, refer to the <i>HP Cloud Service Automation API Quick Start Guide</i>.</p> <p>Default: X-Auth-Token</p>
integrationAccountUserList	<p>Required. A comma-delimited list of users who are authorized to exercise the HP CSA 3.x API. The username in the Authorization header used for HTTP basic authentication must match one of the users in this list.</p> <p>By default, the following HP CSA out-of-the-box users are configured: <code>admin</code>, <code>csaCatalogAggregationTransportUser</code>, <code>csaReportingUser</code>, <code>csaTransportUser</code>, <code>oolInboundUser</code>, and <code>cdalInboundUser</code>. You can also add LDAP users (identified by the User ID) to this list. For example, if you use email addresses for the User ID, you could add <code>user1@xyz.com</code> to the list.</p> <p>For more information about the HP CSA API, refer to the <i>HP Cloud Service Automation API Quick Start Guide</i>.</p> <p>Default: <code>admin,csaReportingUser,oolInboundUser,cdalInboundUser,csaTransportUser,csaCatalogAggregationTransportUser</code></p>

Topology Designer

These properties are used to configure the features of topology designs. Topology designs are built using components supported by various resource provider types and each component is bound to a specific provider type.

These properties are configured in `csa.properties`.

Property	Description
TopologyDesignProvisioning.TIMEOUT	<p>Optional. The amount of time, in seconds, HP CSA attempts to provision or de-provision a topology design (topology design provisioning and de-provisioning is orchestrated by interacting with resource providers corresponding to the components used in the design).</p> <p>If the time is exceeded, in the Operations area of the Cloud Service Management Console, the subscription (to a service offering that is created from a topology design) will show a Subscription Status of <code>Failed</code> and a Service Instance Status of <code>Failed</code>. If you select the Events tab of the subscription, the event will show a Status of <code>Timeout</code>. If you select the Topology tab of the subscription, the topology view will show the status of the components in the service instance as their respective status just before the timeout occurred.</p> <p>HP recommends that this value is set to the same value as the HP Operations Orchestration flow timeout value.</p> <p>Default: 7200 (2 hours)</p>
OrchestratedTopologyDesignProvisioning.ProviderSelection.Enabled	<p>Optional. Enable or disable the resource provider selection option (displaying or not displaying this option to a subscriber) for topology designs.</p> <p>Default: true (enabled)</p>
csa.topology.expressDesignEnabled	<p>Optional. Enable or disable express designs in the topology designer. Express designs simplify the process of creating basic HP Helion OpenStack® topology designs.</p> <p>Default: false</p>

Property	Description
csa.topology.calloutsEnabled	Optional. Enable or disable the Pre-create Callout and Post-create Callout properties of the Server Group Type component in the topology designer. Refer to the <i>HP Cloud Service Management Console Help</i> for more information about these properties. Default: false
csa.topology.CloudOsSpecEnabled	Optional. Enable or disable the HP Helion OpenStack tab in the Create new design dialog in the topology designer. The tab allows the designer to select an HP Helion OpenStack provider when creating a topology design. Default: false

Session Timeout

This property is used to configure the Cloud Service Management Console session.

This property is configured in `web.xml`.

Property	Description
session-timeout	Optional. The amount of inactivity, in minutes, that causes the Cloud Service Management Console session to time out. Default: 60

Restart the HP Cloud Service Automation Service

After modifying the `csa.properties` file, restart HP CSA. See ["Restart HP CSA" on page 109](#) for detailed information on how to restart HP CSA.

Appendix B: Marketplace Portal Attributes

This section lists and describes the attributes that can be configured for the Marketplace Portal. Recommended modifications to the values can be found in the related feature's section in this guide or other documentation (for example, refer to the Identity Management component section in this guide for more information about the Identity Management component-related attributes).

The attributes are located in the following file:

`%CSA_HOME%\portal\conf\mpp.json`

where `%CSA_HOME%` is the directory in which HP Cloud Service Automation is installed.

The following areas contain attributes that can be configured (for many attributes, default values are provided):

- [General Marketplace Portal attributes](#)
- [Provider attributes](#)
- [Identity Management component attributes](#)
- [Secure connection attributes](#)
- [High availability attributes](#)
- [Logging attributes](#)
- [Proxy server attributes](#)

General Marketplace Portal Attributes

These attributes are general purpose attributes that can be configured for the Marketplace Portal.

Attribute	Description
uid	A unique identifier of the Marketplace Portal process used only on Linux systems. Default: ccue_mpp

Attribute	Description
port	<p>The port used to connect to the system on which the Marketplace Portal is running.</p> <p>The port configured for the Marketplace Portal in this attribute should match the port value configured for the <code>csa.subscriber.portal.url</code> property in the <code>%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\classes\csa.properties</code> file.</p> <p>Default: 8089</p>
defaultOrganizationName	<p>The organization identifier of the organization that is accessed by the Marketplace Portal when the Marketplace Portal is launched from a URL that does not specify the organization. The organization identifier is the unique name that HP Cloud Service Automation assigns to the organization, based on the organization display name (the organization identifier can be found in the General Information section of the Organizations tile of the Cloud Service Management Console).</p> <p>Default: CSA_CONSUMER</p>
defaultHelpLocale	<p>The language in which the online help is presented. Available languages can be found in the <code>%CSA_HOME%\portal\node_modules\mpp-ui\dist\ccue-marketplaceportal-help\help\<defaultHelpLocale></code> directory.</p> <p>Default: en_US (English)</p>
defaultHelpPage	<p>The name of the help file that is launched if there is no context-sensitive help available for a topic.</p> <p>The page is relative to <code>%CSA_HOME%\portal\node_modules\mpp-ui\dist\ccue-marketplaceportal-help\help\<defaultHelpLocale></code> and uses the <code>defaultHelpLocale</code> to determine which language to use.</p> <p>Default: MarketplacePortal_Help_CSA.htm</p>
keyfile	<p>The file that contains the Marketplace Portal's encrypted symmetric key and is used by the Marketplace Portal to encrypt and decrypt data in the Marketplace Portal. The path to the file can be absolute or relative to the <code>%CSA_HOME%\portal\bin</code> directory.</p> <p>If this file does not exist, it can be generated using the <code>%CSA_HOME%\portal\bin\passwordUtil</code> utility (see "Encrypt a Marketplace Portal Password" on page 114 for more information).</p> <p>Default: ../conf/keyfile</p>

Attribute	Description
rejectUnauthorized	<p>Allows the Marketplace Portal to accept or reject requests based on the type of certificate passed. If enabled (set to true), the Marketplace Portal will only accept requests that use a Certificate Authority-signed or subordinate Certificate Authority-signed certificate and it will reject requests that use a self-signed certificate.</p> <p>If disabled (set to false), the Marketplace Portal will accept requests that use a Certificate Authority-signed, subordinate Certificate Authority-signed certificate, or a self-signed certificate.</p> <p>Default: false</p>
session: cookieSecret	<p>The authentication cookie used to verify if a user is logged in and to encrypt the user's identification.</p> <p>The cookie/password should be encrypted (see "Encrypt a Marketplace Portal Password" on page 114 for instructions on encrypting Marketplace Portal passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p>
session: timeoutDuration	<p>The amount of inactivity, in seconds, that causes the Marketplace Portal session to time out.</p> <p>Default: 1800 (30 minutes)</p>
session: cleanupInterval	<p>How often, in seconds, a background process is run to clean up expired sessions.</p> <p>Default: 3600 (1 hour)</p>

Provider Attributes

These attributes are used to configure how the Marketplace Portal interacts with HP CSA.

Attribute	Description
url	<p>The URL to access HP CSA.</p> <p>Default: https://localhost:8444</p>
contextPath	<p>The context path to access HP CSA.</p> <p>Default: /csa/api/mpp</p>

Attribute	Description
strictSSL	<p>When enabled, the Marketplace Portal verifies the validity of the hostname and expiration date of the certificate used to access the Cloud Service Management Console (the certificate of the host that is being connected to by the Marketplace Portal).</p> <p>When enabled, if the hostname configured for the certificate is not valid, access is denied to the Marketplace Portal. To check if this is causing access problems to the Marketplace Portal, look for the following error message in the %CSA_HOME%\portal\logs\mpp.log file:</p> <pre>ERROR GetPost : java.security.cert.CertificateException: No name matching <csa.provider.hostname> found</pre> <p>Default: true (enabled)</p>
secureProtocol	<p>Used for FIPS 140-2 compliance. Determines the connection method used and understood by the server.</p> <p>Default: TLSv1_method</p>
ca	<p>Used only when strictSSL is enabled. The path to and name of the file that is an actual certificate or contains a comma-delimited list of certificates for HP CSA, which may include Certificate Authority-signed and self-signed certificates. If you are using a self-signed certificate, it must be listed in this file. The path to the file can be absolute or relative to the %CSA_HOME%\portal\bin directory.</p> <p>The certificates must be in a PEM or DER format.</p> <p>To use the self-signed certificate generated during the installation of HP CSA, set this attribute's value to %CSA_HOME%\jboss-as\standalone\configuration\jboss.crt where %CSA_HOME% is the directory in which HP Cloud Service Automation is installed.</p>

Identity Management component Attributes

These attributes are used to configure how the Marketplace Portal interacts with the Identity Management component.

Attribute	Description
url	<p>The URL to access the Identity Management component.</p> <p>Default: https://localhost:8444</p>
returnUrl	<p>If proxy configuration is enabled, this is the URL to which the Identity Management component is redirected after authentication has succeeded.</p> <p>Default: https://localhost:8089</p>

Attribute	Description
contextPath	<p>The context path to access the Identity Management component.</p> <p>Default: /idm-service</p>
username	<p>The name of the account used by HP CSA to authenticate REST API calls.</p> <p>Default: idmTransportUser</p>
password	<p>The encrypted password for the <code>username</code> (see "Encrypt a Marketplace Portal Password" on page 114 for instructions on encrypting Marketplace Portal passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses. See "Change HP CSA Out-of-the-Box User Accounts" on page 121 for more information about this account.</p>
strictSSL	<p>When enabled, the Marketplace Portal verifies the validity of the hostname and expiration date of the certificate used to access the Identity Management component (the certificate of the host that is being connected to by the Marketplace Portal).</p> <p>When enabled, if the hostname configured for the certificate is not valid, access is denied to the Marketplace Portal. To check if this is causing access problems to the Marketplace Portal, look for the following error message in the <code>%CSA_HOME%\portal\logs\mpp.log</code> file:</p> <pre>ERROR GetPost : java.security.cert.CertificateException: No name matching <csa.provider.hostname> found</pre> <p>Default: true (enabled)</p>
secureProtocol	<p>Used for FIPS 140-2 compliance. Determines the connection method used and understood by the server.</p> <p>Default: TLSv1_method</p>
ca	<p>Used only when <code>strictSSL</code> is enabled. The path to and name of the file that is an actual certificate or contains a comma-delimited list of certificates for the Identity Management component, which may include Certificate Authority-signed and self-signed certificates. If you are using a self-signed certificate, it must be listed in this file. The path to the file can be absolute or relative to the <code>%CSA_HOME%\portal\bin</code> directory.</p> <p>The certificates must be in a PEM or DER format.</p> <p>To use the self-signed certificate generated during the installation of HP CSA, set this attribute's value to <code>%CSA_HOME%\jboss-as\standalone\configuration\jboss.crt</code> where <code>%CSA_HOME%</code> is the directory in which HP Cloud Service Automation is installed.</p>

Secure Connection Attributes

These attributes are used to configure a secure connection for the Marketplace Portal.

Attribute	Description
enabled	<p>Determines the protocol used by the Marketplace Portal. If enabled (set to true), the Marketplace Portal uses the HTTPS protocol. If disabled (set to false), the Marketplace Portal uses the HTTP protocol.</p> <p>The options listed below are used only when this attribute is enabled. Additional options may be specified and are defined at http://nodejs.org/api/tls.html#tls_tls_createserver_options_secureconnectionlistener.</p> <p>Default: true</p>
options: pfx	<p>The file that contains the Marketplace Portal's private key, self-signed certificate, and Certificate Authority-signed certificates (also known as a PKCS #12 archive). The path to the file can be absolute or relative to the %CSA_HOME%\portal\bin directory.</p> <p>Default: ../conf/.mpp_keystore</p>
options: passphrase	<p>The encrypted password used to access the pfx (see "Encrypt a Marketplace Portal Password" on page 114 for instructions on encrypting Marketplace Portal passwords). An encrypted password is preceded by ENC without any separating spaces and is enclosed in parentheses.</p>
options: secureProtocol	<p>Used for FIPS 140-2 compliance. Determines the connection method used and understood by the server.</p> <p>Default: TLSv1_method</p>

High Availability Attributes

These attributes are used to configure the Marketplace Portal in a clustered environment. For more information on how to configure HP CSA in a clustered environment, refer to *Configuring an HP CSA Cluster for High Availability Using an Apache Web Server*.

Attribute	Description
enabled	<p>Determines the environment in which HP CSA is running. If enabled (set to true), the Marketplace Portal is running in a clustered environment. If disabled (set to false), the Marketplace Portal is running in a standalone environment.</p> <p>Default: false</p>
numWorkers	<p>The number of workers on which to deploy the Marketplace Portal. Each worker is deployed on each CPU and is therefore bound by the number of CPUs on the host.</p> <p>Default: 2</p>
redis: options: host	<p>The hostname of the system on which the Redis data structure server is running.</p> <p>Default: localhost</p>

Attribute	Description
redis: options: port	The port to connect to the Redis data structure server. Default: 6379

Logging Attributes

These attributes are used to configure logging.

Attribute	Description
console: enabled	Determines if messages are written to the console. If enabled (set to true), messages are displayed in the console. If disabled (set to false), messages are not displayed in the console. Default: false
console: level	The level of logging. For example, error, warn, info, debug, or trace. Default: info
file: enabled	Determines if messages are written to a log file. If enabled (set to true), messages are logged to a file (%CSA_HOME%\portal\logs\mpp.log). If disabled (set to false), messages are not logged to a file. Default: true
file: level	The level of logging. For example, error, warn, info, debug, or trace. Default: info
file: maxSizeMB	The maximum size to which the log file can grow, in megabytes, before it is archived. Default: 10
file: maxFile	The maximum number of archived log files. Default: 10
cef: enabled	If the Marketplace Portal logging has been integrated with ArcSight Logger, determines if log events are sent and stored in ArcSight Logger. If enabled (set to true), log events are sent and stored in ArcSight Logger. If disabled (set to false), log events are not sent and stored in ArcSight Logger. For information on HP CSA and ArcSight Logger integration, see the <i>Integration with ArcSight Logger</i> technical white paper. Default: false
cef: address	The hostname of the system on which the ArcSight Logger is installed. Default: localhost

Attribute	Description
cef: port	The port used to connect to the system on which the ArcSight Logger is installed. Default: 9876
cef: level	The level of logging. For example, error, warn, info, or debug. Default: warn

Proxy Attributes

These attributes are used to configure proxy settings for the Marketplace Portal.

Attribute	Description
enabled	Determines if a proxy (an alternate URL using a different port and context path) is used to access the Marketplace Portal (for example, you may need to use a proxy, such as <code>http://localhost:8090/mpp</code> instead of <code>http://localhost:8089</code> , when the Marketplace Portal is integrated with a single sign-on solution). If enabled (set to true), the Marketplace Portal uses a proxy. If enabled, you must update the <code>returnUrl</code> attribute to use the proxy for the Identity Management component (this attribute is also located in the <code>mpp.json</code> file). If disabled (set to false), the Marketplace Portal does not use a proxy. Default: false
port	The port used for proxying. Default: 8090
contextPath	The mount path to which the Marketplace Portal is forwarded. Default: /mpp

Appendix C: HP Operations Orchestration Settings

This section is provided as a reference only. The listed HP Operations Orchestration settings are configured in HP Operations Orchestration Studio and are used to integrate HP Operations Orchestration and HP CSA. These settings should have been configured as part of installing HP CSA. Information on how to configure these settings can be found in the *HP Cloud Service Automation Installation Guide*.

The following areas contain settings that can be configured from HP Operations Orchestration Studio:

- [Remote Action Services](#)
- [System Accounts](#)
- [System Properties](#)

Remote Action Services

Setting	Description
RAS_ Operator_ Path	<p>Required. The name and URL that accesses the RAS used by HP Operations Orchestration Central.</p> <p>HP recommends the following value:</p> <pre>https://<FQDN>:9004/RAS/services/RCAgentService</pre> <p>where <FQDN> is the fully qualified domain name or IP address of the HP Operations Orchestration host. Do not use localhost in the URL. Using localhost does not work correctly even though it appears to work when you run HP Operations Orchestration Studio on the same machine as the RAS.</p> <p>RAS must be run on the same system as HP Operations Orchestration Studio. Running HP Operations Orchestration Studio on another machine produces errors and turns flows red with a cryptic error message about result assignments to result variables that do not exist.</p>

System Accounts

Setting	Description
CSA_REST_CREDENTIALS	<p>Required. Credentials for HP CSA REST authentication.</p> <p>HP recommends the Credentials are set to the following values:</p> <ul style="list-style-type: none"> • User Name: oolnboundUser • Password: cloud <p>Note: The User Name configured for the CSA_REST_CREDENTIALS System Account setting must match the Property Value (HP Operations Orchestration version 9.07) or Override Value (HP Operations Orchestration version 10.20) configured for the CSA_OO_USER System Property setting.</p>

System Properties

Setting	Description
CSA_DMA_WorkflowTimeout	<p>Required. The amount of time, in seconds, to wait for a DMA workflow to complete.</p> <p>Default Property Value: 3600</p>
CSA_NA_CreateVlanScript	<p>Required. The name of the HP Network Automation command script to create a VLAN that was imported when you integrated HP Network Automation with HP CSA.</p> <p>Default Property Value: HPN Create Vlan</p>
CSA_NA_DeleteVlanScript	<p>Required. The name of the HP Network Automation command script to delete a VLAN that was imported when you integrated HP Network Automation with HP CSA.</p> <p>Default Property Value: HPN Delete Vlan</p>

System Properties, continued

Setting	Description
CSA_OO_USER	<p>Required. The user that communicates with HP CSA using the REST API.</p> <p>Default Property Value: oolInboundUser</p> <div style="background-color: #e0e0e0; padding: 5px; border: 1px solid #ccc;"> <p>Note: The Property Value (HP Operations Orchestration version 9.07) or Override Value (HP Operations Orchestration version 10.20) configured for the CSA_OO_USER System Property setting must match the User Name configured for the CSA_REST_CREDENTIALS System Account setting.</p> </div>
CSA_REST_URI	<p>Required. The URI used to communicate with HP Cloud Service Automation using the REST API.</p> <p>HP recommends the following Property Value: <code>https://<csa_hostname>:8444/csa/rest</code></p>
CSA_SiteScope_MonitoringLockId	<p>Required. HP SiteScope monitoring lock ID.</p> <p>Default Property Value: SiteScope Lock for Deploying Monitors</p>
CSA_SiteScope_RootMonitorGroup	<p>Required. The default name of the HP SiteScope root monitor group path.</p> <p>Default Property Value: CSA Monitors</p>
CSA_SiteScope_MonitoringSleepTime	<p>Required. The amount of time, in seconds, to wait before acquiring the HP SiteScope monitoring lock. This time may be increased if there are a large number of subscription requests.</p> <p>Default Property Value: 30</p>
CSA_vCenterPropertyCollectionTimeout	<p>Required. How often, in seconds, properties are collected about a deployed virtual machine.</p> <p>Default Property Value: 1800</p>

Appendix D: Identity Management Configuration

If you are using the Identity Management component, the identity service and its components require configuration. Because it is a Spring Framework application, most of its configuration is defined in the `applicationContext.xml` file, although key attributes are externalized to the `applicationContext.properties` file. Both files are in `%CSA_HOME%\jboss-as\standalone\deployments\idm-service.war\WEB-INF\spring\`.

You should make most common configuration changes to the `applicationContext.properties` file. To avoid service disruptions, only advanced users who understand the Spring Framework should change the `applicationContext.xml` file.

You must also configure the Java Relying Party Library.

Note: You should always make a copy of a configuration file before editing it.

External Configuration

Selected settings are pulled from the `applicationContext.properties` file, which you can override by an external properties file set as a JVM argument: `-Didm.properties=<external_properties_filename>`. You can add this JVM argument to the `JAVA_OPTS` environment variable or by editing the `standaloneconf.bat` file in `%CSA_HOME%\jboss-as\bin\` to add it to `JAVA_OPTS` for the HP CSA JBoss container.

The table below describes the properties that are set in the properties file. These properties are required (although if you set the `idm.keystone.enabled` property to `false`, all other `idm.keystone*` properties in this table are ignored).

If you are integrating with Keystone, the `idm.keystone*` properties must match the Keystone network location, transport user credentials, and so on. All `idm.csa*` properties and all `ConvergedLdapAuthConfig` properties (which are listed in the *ConvergedLdapAuthConfig* section below) must match the HP CSA network location and transport user credentials.

Property Name	Description
<code>idm.ssl.requireValidCertificate</code>	Flag indicating whether valid certificates are required: true or false
<code>idm.csa.protocol</code>	The protocol used to access the HP CSA instance: http or https
<code>idm.csa.hostname</code>	The hostname or IP address of the HP CSA server
<code>idm.csa.port</code>	The port number used by the HP CSA server
<code>idm.csa.username</code>	The username for the HP CSA integration account

Property Name	Description
<code>idm.csa.password</code>	The password for the HP CSA integration account. For improved security, this value should be encrypted.
<code>idm.encryptedSigningKey</code>	The shared signing key for all token factory objects. For improved security, this value should be encrypted.
<code>idm.keystone.enabled</code>	Flag indicating whether secondary authentication through Keystone is enabled: <code>true</code> or <code>false</code>
<code>idm.keystone.required</code>	Flag indicating whether successful secondary authentication through Keystone is required for authentication to succeed: <code>true</code> or <code>false</code>
<code>idm.keystone.protocol</code>	The protocol used to access the Keystone instance: <code>http</code> or <code>https</code>
<code>idm.keystone.hostname</code>	The hostname or IP address of the Keystone server
<code>idm.keystone.port</code>	The port number used by the Keystone server. Typically 5000.
<code>idm.keystone.servicePath</code>	The service path where the Keystone service listens. The typical value is <code>v3</code> .
<code>idm.keystone.domainName</code>	The OpenStack domain name to use for all authentication on the Keystone server. The typical value is <code>Default</code> .
<code>idm.keystone.transportUsername</code>	The username for the integration account used to communicate with Keystone and perform OpenStack operations.
<code>idm.keystone.transportPassword</code>	The password for the integration account used to communicate with Keystone and perform OpenStack operations. For improved security, this value should be encrypted.
<code>idm.keystone.transportProject</code>	The Keystone project name for the integration account. All Keystone users must belong to a project whose name exactly matches the HP CSA organization ID used to log in — including case (for example, a Keystone project name of <code>project_name</code> will not match an HP CSA organization ID of <code>PROJECT_NAME</code>).

Configure Seeded Authentication

The top-level configuration file for seeded authentication is specified by the `configFile` property of the `SeededAuthenticationProvider` bean defined in the `applicationContext.xml` configuration file. In the default configuration, this file is `seededorgs.properties`, but it can be changed. Each line in this

file contains a key-value pair. The key is an HP CSA organization ID, and the value is the name of another properties file that contains the users for that organization. By default, the following organizations are configured to use the specified files.

Organization	User File
CSA_CONSUMER	csa-consumer-users.properties

You can define additional organizations or change the user file associated with any organization. Each line in each user file contains a key-value pair. The key is the username, and the value is a comma-separated list of the password, granted authorities, and an optional flag indicating whether the account is enabled. For improved security, the *entire* value should be encrypted. Following is an example of a line from a user file that defines a user named `consumer` with the password `cloud` and granted the `SERVICE_CONSUMER` and `ROLE_REST` authorities.

```
consumer=cloud,SERVICE_CONSUMER,ROLE_REST,enabled
```

Configure the Java Relying Party Library

The Java Relying Party Library is a set of classes provided by the identity service that abstract and simplify invoking the service from Java applications, such as HP CSA. You modify the properties listed in this section in the `%CSA_HOME%\jboss-as\standalone\deployments\csa.war\WEB-INF\applicationContext-security.xml` file. The `tokenFactory` property value should be the same for all `AuthenticationProvider` beans (listed in the *Internal Configuration* section below) in the identity service and in the Java Relying Party library.

IdentityServiceConfig

Configures the connection to the identity service.

Class: `com.hp.ccue.identity.rp.IdentityServiceConfig`

Property Name	Description
<code>protocol</code>	The protocol (<code>http</code> or <code>https</code>) to use to connect to the identity service
<code>hostname</code>	The hostname or IP address of the server running the identity service
<code>port</code>	The port number where the identity service is running, typically <code>8444</code>
<code>servicePath</code>	The path on the server to the identity service, typically <code>idm-service</code>

IdentityAuthenticationProvider

Abstracts the invocation of the identity service to perform authentication.

Class: `com.hp.ccue.identity.rp.IdentityAuthenticationProvider`

Property Name	Description
templateFactory	Creates the RestTemplate object that facilitates performing REST calls
configuration	Network configuration of the identity service to connect to perform authentication: an IdentityServiceConfig object
tokenFactory	The token factory to validate returned tokens
tenantHeaderName	The name of the HTTP header where the tenant name is passed. The default is HP-Tenant-Name

HeaderAuthenticationProvider

Performs authentication based on a token passed in an HTTP header.

Class: com.hp.ccue.identity.rp.HeaderAuthenticationProvider

Property Name	Description
headerName	The name of the HTTP header where the token is transferred
tokenValidator	The TokenValidator object to use to validate tokens

Internal Configuration

The applicationContext.xml file defines the configuration of the classes in the identity service. The tokenFactory property value should be the same for all AuthenticationProvider beans (listed in the sections below) in the identity service and in the Java Relying Party library.

Note: Modify this file only if you cannot express the necessary configuration change in the applicationContext.properties file. The applicationContext.xml file must follow the syntax rules specified by the Spring Framework. In the following tables, the default values are used if no values are provided in the configuration file. You can configure items marked as externalized in the applicationContext.properties file.

InfinispanTokenStore

Defines the persistence mechanism for request tokens. Most attributes of this object define how the identity service behaves in high availability (HA) or clustered deployments.

Class: com.hp.ccue.identity.ha.InfinispanTokenStore

Property Name	Description
lifetimeSeconds lifetimeMinutes lifetimeHours	<p>Required. Time (in seconds, minutes, or hours) that an entry is permitted to remain in the token store. These properties determine the amount of time that the login page is valid. The lifetime as installed is 60 minutes. More permissive organizations should use a larger value; more restrictive organizations should use a smaller value.</p> <p>Default value: (None)</p> <p>Externalized: No</p>
clusterEnabled	<p>Required in a clustered environment. A flag indicating whether clustering should be enabled: true or false</p> <p>Default value: false</p> <p>Externalized: No</p>
clusterConfigFile	<p>Required in a clustered environment. The filename of the jgroups.xml configuration file that defines the cluster. Setting this property forces the clusterEnabled property to true.</p> <p>Default value: (None)</p> <p>Externalized: No</p>
configFile	<p>Required in a clustered environment. The filename of the Infinispan XML configuration file. The settings in this configuration file override the values in the clusterEnabled and clusterConfigFile properties.</p> <p>Default value: (None)</p> <p>Externalized: No</p>

JwtTokenFactory

Defines how tokens are created.

Class: com.hp.ccue.identity.domain.JwtTokenFactory

Property Name	Description
lifetimeMinutes	<p>Required. The lifetime of the token, in minutes. The lifetime as installed is 30 minutes. Reducing this value will render tokens invalid faster and thus requires a more-frequent token refresh, which might reduce performance. Increasing this value allows tokens to last longer, which might allow someone who has intercepted a valid token to access the system for a period of time.</p> <p>Default value: (None)</p> <p>Externalized: No</p>

Property Name	Description
defaultTypeName	Optional. Default type of JWT token to create: PLAINTEXT, SIGNED, or ENCRYPTED Default value: PLAINTEXT Externalized: No
signingKey	Required if defaultTypeName is set to SIGNED. This is a Base64-encoded byte array representing the key used to sign signed tokens. If defaultTypeName is set to SIGNED, this value must be the same for all components that validate tokens. For improved security, this item should be encrypted. Default value: (None) Externalized: idm.encryptedSigningKey
refreshEnabled	Optional. Boolean value indicating whether token refresh is enabled: true or false. The recommended value is true. Default value: true Externalized: No

ConvergedLdapAuthConfig

Defines the configuration for connecting to an HP CSA server to get LDAP configuration information. The `idm.csa*` external properties (which are listed in the *External Configuration* section above) and all `ConvergedLdapAuthConfig` properties must match the HP CSA network location and transport user credentials.

Class: `com.hp.ccue.identity.ldap.ConvergedLdapAuthConfig`

Property Name	Description
providerProtocol	Required if using ActiveDirectory or LDAP. <code>http</code> or <code>https</code> , depending on the protocol used by the HP CSA instance Default value: (None) Externalized: <code>idm.csa.protocol</code>
providerHostname	Required if using ActiveDirectory or LDAP. Hostname or IP address of the HP CSA server Default value: (None) Externalized: <code>idm.csa.hostname</code>

Property Name	Description
providerPort	Required if using ActiveDirectory or LDAP. Port number used by the HP CSA server Default value: (None) Externalized: idm.csa.port
securityTransportUsername	Required if using ActiveDirectory or LDAP. Username for the HP CSA integration account Default value: (None) Externalized: idm.csa.username
securityTransportPassword	Required if using ActiveDirectory or LDAP. Password for the HP CSA integration account Default value: (None) Externalized: idm.csa.password

ConvergedActiveDirectoryAuthenticationProvider and ConvergedLdapAuthenticationProvider

Performs authentication with Active Directory and LDAP authentication mechanisms.

Class: com.hp.ccue.identity.ldap.ConvergedActiveDirectoryAuthenticationProvider, com.hp.ccue.identity.ldap.ConvergedLdapAuthenticationProvider

Property Name	Description
config	Required if using ActiveDirectory or LDAP. The ConvergedLdapAuthConfig that represents the HP CSA server to use to get the LDAP configuration for each organization Default value: (None) Externalized: No
tokenFactory	Required if using ActiveDirectory or LDAP. The token factory for creating identity tokens in response to successful authentications Default value: (None) Externalized: No

SeededAuthenticationProvider

Performs seeded authentication.

Class: com.hp.ccue.identity.seeded.SeededAuthenticationProvider

Property Name	Description
configFile	Required if using seeded authentication. Typically seededorgs.properties, which is the file that defines the seeded organizations Default value: (None) Externalized: No
tokenFactory	Required if using seeded authentication. The token factory for creating identity tokens in response to successful authentications Default value: (None) Externalized: No

IdentityAuthenticationProvider

Performs integration account authentication.

Class: com.hp.ccue.identity.seeded.IntegrationAuthenticationProvider

Property Name	Description
configFile	Required. Typically integrationusers.properties, which is the file that defines the seeded organizations Default value: (None) Externalized: No
tokenFactory	Required. The token factory for creating identity tokens in response to successful authentications Default value: (None) Externalized: No

MultiTenantAuthenticationProvider

Connects to mechanism-specific authentication providers.

Class: com.hp.ccue.identity.authn.MultiTenantAuthenticationProvider

Property Name	Description
providers	Required. List of AuthenticationProvider objects that provide mechanism-specific authentication Default value: (None) Externalized: No
secondaryEnabled	Required if using Keystone. Flag that indicates whether the secondary authentication path (Keystone) is enabled Default value: false Externalized: idm.keystone.enabled
secondaryProvider	Required if using Keystone. Reference to Authentication provider bean to use for secondary authentication path. The Keystone authentication provider is the only one that supports this type of usage. Default value: (None) Externalized: No
secondaryRequired	Required if using Keystone. Flag that indicates whether secondary (Keystone) authentication must succeed in order for authentication to be considered a success. Default value: false Externalized: idm.keystone.required

IdentityServiceImpl

The identity service implementation object.

Class: com.hp.ccue.identity.service.IdentityServiceImpl

Property Name	Description
provider	Required. Reference to the AuthenticationProvider bean to use to perform authentication. This is the MultiTenantAuthenticationProvider Default value: (None) Externalized: No
tokenFactory	Required. The token factory for creating identity tokens in response to successful authentications Default value: (None) Externalized: No

IdentityController

The controller object that provides the REST API for the identity service.

Class: `com.hp.ccue.identity.service.IdentityController`

Property Name	Description
<code>identityService</code>	Required. The <code>IdentityService</code> object that implements the identity service. You must set the value of this to the <code>IdentityServiceImpl</code> instance. Default value: (None) Externalized: No

KeystoneAuthenticationProvider

Uses Keystone (if used) to perform authentication.

Class: `com.hp.ccue.identity.keystone.KeystoneAuthenticationProvider`

Property Name	Description
<code>templateFactory</code>	Required. Creates the <code>RestTemplate</code> object that facilitates performing REST calls Default value: (None) Externalized: No
<code>configuration</code>	Required. Network configuration of the Keystone service to connect to in order to perform authentication: a <code>KeystoneConfig</code> object Default value: (None) Externalized: No
<code>tokenFactory</code>	Required. The token factory to validate returned tokens Default value: (None) Externalized: No

KeystoneConfig

Identifies the Keystone endpoint for authentication.

Property Name	Description
protocol	Optional if the default value is not acceptable. The protocol to access Keystone Default value: http Externalized: <code>idm.keystone.protocol</code>
hostname	Required. Optional if the default value is not acceptable. The hostname or IP address of the Keystone server Default value: (None) Externalized: <code>idm.keystone.hostname</code>
port	Optional if the default value is not acceptable. The port number for Keystone on hostname Default value: 5000 Externalized: <code>idm.keystone.port</code>
servicePath	Optional if the default value is not acceptable. The service path to the Keystone API on the Keystone server Default value: v3 Externalized: <code>idm.keystone.servicePath</code>
domainName	Optional if the default value is not acceptable. The Keystone domain name under which all operations are performed Default value: Default Externalized: <code>idm.keystone.domainName</code>
transportUsername	Required. The username for the Keystone transport user Default value: (None) Externalized: <code>idm.keystone.transportUsername</code>
transportPassword	Required. The password for the Keystone transport user Default value: (None) Externalized: <code>idm.keystone.transportPassword</code>
transportProject	Required. The project for the Keystone transport user Default value: (None) Externalized: <code>idm.keystone.transportProject</code>

RestTemplateFactoryImpl

Configures how REST services are invoked.

Class: com.hp.ccue.identity.rest.RestTemplateFactoryImpl

Property Name	Description
fipsEnabled	<p>A flag that indicates whether the template factory should ignore settings that interfere with FIPS 140-2 compliance</p> <p>Default value: false</p> <p>Externalized: No</p>
wrapEnabled	<p>A flag that indicates whether the template factory should wrap JSON output in its specified root value or assume that incoming JSON is wrapped in the root value. This setting depends on the REST service being invoked. For template factories used to invoke HP CSA REST APIs, it should be set to false; for template factories used to invoke Keystone REST APIs, it should be set to true.</p> <p>Default value: true</p> <p>Externalized: No</p>
requireValidCertificate	<p>A flag that indicates whether the template factory should perform certificate validation and hostname verification (true) or ignore them (false). If this value is set to true, then the corresponding server host names for all beans that use that template factory must be given in a way that matches the certificate for that server (a fully-qualified domain name is generally required).</p> <p>Default value: true</p> <p>Externalized: idm.ssl.requireValidCertificate</p>

Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this system, click the link above and an email window opens with the following information in the subject line:

Feedback on Configuration Guide (Cloud Service Automation 4.20)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to CSAdocs@hp.com.

We appreciate your feedback!

