Peregrine AssetCenter



Physical Data Models



Part No. DAC-440-EN11

© Copyright 2004 Peregrine Systems, Inc.

All Rights Reserved.

Information contained in this document is proprietary to Peregrine Systems, Incorporated, and may be used or disclosed only with written permission from Peregrine Systems, Inc. This manual, or any part thereof, may not be reproduced without the prior written permission of Peregrine Systems, Inc. This document refers to numerous products by their trade names. In most, if not all, cases these designations are claimed as Trademarks or Registered Trademarks by their respective companies.

Peregrine Systems ®andAssetCenter ® are trademarks of Peregrine Systems, Inc. or its subsidiaries.

This document and the related software described in this manual are supplied under license or nondisclosure agreement and may be used or copied only in accordance with the terms of the agreement. The information in this document is subject to change without notice and does not represent a commitment on the part of Peregrine Systems, Inc. Contact Peregrine Systems, Inc., Customer Support to verify the date of the latest version of this document.

The names of companies and individuals used in the sample database and in examples in the manuals are fictitious and are intended to illustrate the use of the software. Any resemblance to actual companies or individuals, whether past or present, is purely coincidental.

If you need technical support for this product, or would like to request documentation for a product for which you are licensed, contact Peregrine Systems, Inc. Customer Support by email at support@peregrine.com.

If you have comments or suggestions about this documentation, contact Peregrine Systems, Inc. Technical Publications by email at doc_comments@peregrine.com.

This edition applies to version 4.4 of the licensed program

AssetCenter

Peregrine Systems, Inc. 3611 Valley Centre Drive San Diego, CA 92130 858.481.5000 Fax 858.481.1751 www.peregrine.com

Table of Contents

PEREGRINE

Preface	5
Tables	5 6
Chapter 1. Portfolio	9
Models . <td>10 11 12 13 14 15 16</td>	10 11 12 13 14 15 16
Chapter 2. Procurement cycle	17
Procurement cycle .	18 19 20 21 22 23
Chapter 3. Contracts	25
Contracts	26

Chapter 4. Financials	27
Budget and expenses	28 29 30
Chapter 5. Cable and Circuit	31
Cables and cable devices	32
Color codes	33
	34
Pair/conductor types	35
Cable duties	36 37
	38
Topology groups	39
Termination-field configurations	40
Cable links	41
Chapter 6. Administration	43
Access to the database	44

Preface

PEREGRINE

This guide presents diagrams that correspond to the physical data models in AssetCenter.

Each of these diagrams contains one or more tables used by the modules in AssetCenter.

Tables

Each of the tables represented in this guide is identified by its SQL name. Examples:

- The Portfolio items table uses the SQL name **amPortfolio**.
- The Assets table uses the SQL name amAsset.
- The Locations table uses the SQL name amLocation.
- The Departments and Employees table uses the SQL name **amEmplDept**.

The most important tables in each diagram are shown as the largest. Examples:

- The Assets table (amAsset) in the Assets [page 12] diagram.
- The Cables table (amCable) in the Cables and cable devices [page 32] diagram.
- The Taxes table (amTax) in the Taxes [page 30] diagram.

Links

There are three types of links between tables:

- 1-1 links.
- 1-n and n-1 links.
- n-n links.

Type of link	Graphical representation of link
1-1	
1-n (reverse link of of n-1)	← and ≻
n-n	→ → → →

Each of the links represented in this guide is identified by its SQL name.

Examples:

- The link going from the Portfolio items table (amPortfolio) to the Departments and Employees table (amEmplDept) has the SQL name User.
- The link going from the Departments and Employees table (amEmplDept) to the Portfolio items table (amPortfolio) has the SQL name ItemsUsed.

ጆ Note:

The SQL name of a link assumes that one of the linked tables is the source table and the other is the destination table. Thus, the **User** link between the source table (**amPortfolio**) indicates that the link points to the user record of the destination table (**amEmplDept**). It's reverse link, though, is called **ItemsUsed**. This link points to the records of the assets used by a given user. In this case, the source table is that of departments and employees and the destination table is that of portfolio items.

In an effort not to overload our diagrams, reverse links are not represented. The choice of a link and its reverse link is arbitrary. If you want to find out what the SQL name of a reverse link is:

- 1 Launch AssetCenter Database Administrator.
- 2 Open your database description.
- 3 Select the table of your choice.
- 4 Click [№].
- 5 Select a link.

6 The SQL name of its reverse link is indicated in the **Reverse link** field.

1-1 links

This kind of link means that:

One record in the source table is linked to one record in the destination table.
Example: The Asset link between the Computers table (amComputer) and the Assets table (amAsset) in the Computers [page 14] diagram. This link indicates that only one computer record can be linked to only one asset record.

1-n and n-1 inks

A 1-n link means that:

- One record from the source table can be linked to several records in the destination table.
- Several records in the destination table can be linked to one record in the source table.

Example: The **Rents** link between the Contracts table (**amContracts**) and the Contract rents (**amCntrRent**) table in the Contracts [page 26] diagram. This link indicates that one contract record can be linked to several contract rent records.

A n-1 link means that:

- Several records in the source table can be linked to one record in the destination table.
- One record in the destination table can be linked to several records in the source table.

Example: The **Model** link between the Assets table (**amAsset**) and the Models table (**amModel**) in the Models [page 10] diagram. This link indicates that several asset records can correspond to the same model record.

n-n links

This type of link means that:

 Several records in the source table can be linked to several records in the destination table.

Example: The **FuncRights** link between the User profiles table (**amProfile**) and the Functional rights table (**amFuncRight**) in the Access to the database [page 44]


diagram. This link indicates that an asset record can be linked to several functional right records and that a functional right record can be linked to several user profile records.




This chapter presents diagrams of the following physical data models:

- Models [page 10]
- Portfolio items [page 11]
- Assets [page 12]
- Assets linked to the procurement cycle [page 13]
- Computers [page 14]
- Telephones [page 15]
- Ports and connections [page 16]

Models




Portfolio items




AssetCenter 4.4 - Physical Data Models | 11


Assets




Assets linked to the procurement cycle




Computers



Telephones



Ports and connections







This chapter presents diagrams of the following physical data models:

- Procurement cycle [page 18]
- Purchase requests [page 19]
- Orders [page 20]
- Receptions [page 21]
- Invoices [page 22]
- Assets to be returned [page 23]


Procurement cycle




Purchase requests




Orders




Receptions



Invoices



Assets to be returned








This chapter presents the diagram of the following physical data model:

Contracts [page 26]

Contracts









This chapter presents diagrams of the following physical data models:

- Budget and expenses [page 28]
- Chargebacks [page 29]
- Taxes [page 30]


Budget and expenses



Chargebacks



Taxes







This chapter presents diagrams of the following physical data models:

- Cables and cable devices [page 32]
- Color codes [page 33]
- Label rules [page 34]
- Pair/conductor types [page 35]
- Cable duties [page 36]
- Slots [page 37]
- Topologies [page 38]
- Topology groups [page 39]
- Termination-field configurations [page 40]
- Cables and cable devices [page 32]


Cables and cable devices




Color codes




Label rules




Pair/conductor types




Cable duties




Slots



Topologies




Topology groups




AssetCenter 4.4 - Physical Data Models | 39

Termination-field configurations



40 | AssetCenter 4.4 - Physical Data Models

Cable links







This chapter presents the diagram of the following physical data model:

Access to the database [page 44]

Access to the database

