

HP OpenView Service Oriented Architecture Manager

OVIS Integration Instructions

Version: 2.1

Windows, UNIX, Linux



June 2006

© Copyright 2004-2006 Hewlett-Packard Development Company, L.P.

Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notices

© Copyright 2004-2006 Hewlett-Packard Development Company, L.P.

Trademark Notices

Java™ is a U.S. trademark of Sun Microsystems, Inc.

Linux is a U.S. registered trademark of Linus Torvalds

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation

UNIX® is a registered trademark of The Open Group

Support

You can visit the HP OpenView web site at:

<http://www.hp.com/managementsoftware/support>

This web site provides contact information and details about the products, services, and support that HP OpenView offers.

HP OpenView online software support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support site to:

- Search for knowledge documents of interest
- Submit enhancement requests online
- Download software patches
- Submit and track progress on support cases
- Manage a support contract
- Look up HP support contacts
- Review information about available services
- Enter discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and log in. Many also require a support contract.

To find more information about access levels, go to:

http://www.hp.com/managementsoftware/access_level

To register for an HP Passport ID, go to:

<http://www.managementsoftware.hp.com/passport-registration.html>

Contents

- Overview 7**
- Installing the SOA Manager Probe 7**
- Configure the Probe 8**
 - Create a Service Group..... 8
 - Create a Service Target 8
 - Configure SLOs and Alarms..... 9
 - Create a Probe Location 10

The HP OpenView Internet Services (OVIS) Integration Instructions are intended for users who want to take advantage of the HP OpenView Service Oriented Architecture (SOA) Manager integration with OVIS. Users should be familiar with SOA Manager and OVIS before completing these instructions.

Overview

OVIS provides a single integrated view of your Internet and related services. It is designed to help IT staff efficiently predict, isolate, diagnose and troubleshoot problems, anticipate capacity shortfalls, and manage and report on service level agreements.

The SOA Manager OVIS probe imports business service performance data into OVIS, measuring availability, response time, and other performance metrics. This integration provides greater visibility of the overall health of your business services by leveraging the advanced Service Level Objectives (SLO) monitoring, SLA conformance, trend analysis and reporting provided by OVIS.

This document assumes that you are familiar with creating OVIS service configurations. For more information read the OVIS User's Reference Guide.

Installing the SOA Manager Probe

The SOA Manager probe can only be installed on a Windows system, and requires the .Net framework 1.1. It is expected that the probe will only ever be installed on the same server as the Internet Services Configuration Manager, as the probe location is basically irrelevant.

The Internet Services Configuration Manager on the Management Server needs to be updated with the SOA Manager's probe definition, which is specified in an SRP file. The SRP file is located on the SOA Manager CD in the `Addons/OVIS/6.0` directory.

To load the file:

- 1 On the Management Server, open a command prompt.
- 2 Run the following command:

```
repload -load repload_C_SOAM_PROBE.SRP
```
- 3 After the new SRP file is loaded, run the following command:

```
ovc -restart ovtomcatA
```
- 4 Exit the current Dashboard session and restart.

- 5 On the system where the Internet Services Configuration Manager is installed, copy the probe binary probeSoam.exe into the <OVIS_install_dir>/probes folder. For more information on installing custom probes see the *OVIS Custom Probes API Guide*.


Configure the Probe

The following sections are used to configure the SOA Manager probe:

- Create a Service Group
- Create a Service Target
- Configure SLOs and Alarms
- Create a Probe Location

Create a Service Group

In the OVIS Configuration Manager, create a new service group of the type SOAM Probe. Although not a requirement, it is recommended that you create a single service group for each business service to be monitored in OVIS, using the same name for both. This is because in OVIS a service group is the level at which SLO metrics are defined. The Create Service Group dialog box is shown below:



Create a Service Target

Each business service monitored in OVIS has a corresponding service target in the OVIS Configuration Manager. This target is the address of the business service's service performance Web service interface (see the *SOA Manager Integrator Guide* for documentation about this API). The SOAM Probe Information dialog box is shown below:

Complete the fields as follows:

- **Target Host** – host of the SOA Manager Network Services Server.
- **Port** – Port of the SOA Manager Network Services Server.
- **urlfile** – The relative soap address of the ServicePerformanceSnapshotSoapHttpBinding Port Type for the associated business service. This address is specified in the business services WSDL, which is listed under Deployed WSMF Services found at `http://<SOA_Manager_host>:<SOA_Manager_port>/wsmf/servlet/AxisServlet`. A sample WSDL extract containing the address is shown below.


```
<wsdl:port binding="tns:ServicePerformanceSnapshotSoapHttpBinding"
  name="BusinessServiceServicePerformanceSnapshotPort">
  <soap:address location="http://inspector.ovrtest.adapps.hp.com:
    5002/wsmf/services/Runtime$service=
    WsmfBusinessService$name=Finance" />
</wsdl:port>
```

For the above WSDL, the UriFile field would be

```
/wsmf/services/Runtime$service=WsmfBusinessService$name=Finance
```

Note : There should be no ?wsdl at the end of this value. Use the name of your business service in the place of 'Finance' in the given example.
- **Label** – An identity that will be used to refer to the business service in the OVIS dashboard.

Configure SLOs and Alarms

SLOs and alarms can be setup for the following metrics:

- **AVAILABILITY** – Availability of the business service is either 0 or 100% for a specific time interval.
- **RESPONSE_TIME** – The average response time in seconds for all requests to the business service during the last time period.
- **MAX** – The maximum response time in seconds during the last time period.
- **MIN** - The minimum response time in seconds during the last time period.

- **SEC_VIOLATIONS** – The total number of authentication or authorization failures.
- **SUCSESSES** – The number of successful requests.
- **SUCCESS_MILLIS** – The cumulative response time of all successful requests in milliseconds.
- **FAILURES** – The number of requests that failed.
- **FAILURE_MILLIS** – The cumulative response time of failed messages in milliseconds.
- **POLL_DURATION** – The duration in milliseconds of the time interval over which the above metrics are summarized.

Create a Probe Location

Before the SOAM Probe can start to gather business service performance, a probe location needs to be configured. This specifies where and when the probe should start to gather data. The Probe Location Info dialog box is shown below:

Probe Location Info

Probe Location: Local System

OK

Cancel

Help

Probe Request Information

Measurement Interval: 60 seconds

Request Timeout: 20 seconds

Probe Delay Information

Use Probe Delay

Delay at Start

Execution Delay: 0 seconds

Network Connection

Default

New Connection

Edit Connection

Delete Connection

Target Priority

Web Proxy Information

This is the proxy used by the probe to access the service targets.
For HTTP, HTTPS, HTTP_TRANS & STREAMING_MEDIA only

HTTP Proxy Address: <none> Port:

HTTPS Proxy Address: <none> Port:

Internal Internet Services Proxy Information

This is the proxy used by the probe to access the Internet Services server.

Proxy address: <none> Port:

IP Performance Server Ports

Enable Ports

TCP Port: 5002

UDP Port: 5002

Complete the fields as follows:

- **Probe Location** – The probe should be configured to run on the local system.
- **Measurement Interval** – The metrics that the SOA Manager probe loads are a snapshot of the previous minute's performance. Therefore, it is important that the measurement interval be set to 60 seconds.

