

HP Client Automation Enterprise

Proxy Server

for the AIX, HP-UX, Linux, Solaris, and Windows® operating systems

Software Version: 7.20

Migration Guide

Document Release Date: August 2008

Software Release Date: July 2008



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notices

© Copyright 2006-2008 Hewlett-Packard Development Company, L.P.

Trademark Notices

Linux is a registered trademark of Linus Torvalds.

Microsoft®, Windows®, and Windows® XP are U.S. registered trademarks of Microsoft Corporation.

OpenLDAP is a registered trademark of the OpenLDAP Foundation.

PREBOOT EXECUTION ENVIRONMENT (PXE) SERVER

Copyright © 1996-1999 Intel Corporation.

TFTP SERVER

Copyright © 1983, 1993

The Regents of the University of California.

OpenLDAP

Copyright 1999-2001 The OpenLDAP Foundation, Redwood City, California, USA.

Portions Copyright © 1992-1996 Regents of the University of Michigan.

OpenSSL License

Copyright © 1998-2001 The OpenSSLProject.

Original SSLeay License

Copyright © 1995-1998 Eric Young (eay@cryptsoft.com)

DHTML Calendar

Copyright Mihai Bazon, 2002, 2003

Support

You can visit the HP Software support web site at:

www.hp.com/go/hpsoftwaresupport

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online software support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require an active support contract. To find more information about support access levels, go to the following URL:

http://h20230.www2.hp.com/new_access_levels.jsp

To register for an HP Passport ID, go to the following URL:

<http://h20229.www2.hp.com/passport-registration.html>

Contents

1	Upgrading the Proxy Server	5
	Terminology	5
	Proxy Server Upgrade Instructions.....	6

1 Upgrading the Proxy Server

This guide is for Client Automation system administrators who want to upgrade Radia or HP Configuration Management *Integration Server-based* Proxy Servers to an *Integration Server-based* Proxy Server Version 7.20.



This guide does not cover migrating *Integration Server-based* Proxy Servers for Windows to the Enterprise Proxy Server (an *Apache-based* server); this migration path is *not supported*. Only new installations of the Enterprise Proxy Server for Windows are supported.

This guide contains information for both Windows and UNIX platforms; it should be used by systems administrators who want to:

- Upgrade Proxy Servers on Windows platforms from Version 2.x (Radia 4.x media) or 5.xx (CM 5.00 or 5.1x) to Version 7.20.
- Upgrade Proxy Servers on UNIX platforms from version 2.x (from Radia 4.x media) or 5.00 (CM 5.00 or 5.10 media) to Version 7.20.

You should be familiar with Client Automation products, such as the Configuration Server, Configuration Server Database (CSDB), the Admin CSDB Editor, and the Portal.

Terminology

Table 1 Terminology

Term	Definition
co-located Proxy Server	A Proxy Server installed on the same machine as the Configuration Server (CS) so that resources can be downloaded from the CS database using HTTP. Configured with a <code>-static-type</code> of server and with its <code>-static-root</code> pointing to the CS database. Requires no preloading.
edmprof file	The Configuration Server Settings file. This manual uses this non-platform specific, generic reference. <ul style="list-style-type: none">• On UNIX operating systems, it is .edmprof, located on the home directory of the UNIX user ID that installs, starts, stops, and maintains the Configuration Server.• On Windows operating systems, it is edmprof.dat, located in the bin folder of the Configuration Server directory.


Term	Definition
base installation directory	<p>The location where your Proxy Server is installed. The default for the base directory changed as of Version 5.00. By default, the Proxy Server is installed into the following directory:</p> <p>On a Windows machine, it is: <SystemDrive>\Program Files\Hewlett-Packard\CM\IntegrationServer</p> <p>On a UNIX machine, it is: /opt/HP/CM/IntegrationServer</p> <p>Note: If a previously installed service has not been removed, the installation will target the existing base installation directory. If the service has been removed, the new default directory location will be targeted for installation.</p>

Proxy Server Upgrade Instructions

Use these procedures to upgrade an existing *Integration Server-based* Proxy Server from version 2.x or 5.xx to Version 7.20. The procedure applies to both Windows and UNIX environments. The Version 7.20 components include the following:

- An NVDKIT using Tcl Version 8.4 (versions prior to 5.10 used Tcl Version 8.2).
- Provision of the latest `tls.tkd` component, which is required to configure secured communications using HTTPS. Refer to the *HP Client Automation Enterprise SSL Implementation Guide* for more information.
- Updated `rps.tkd`, `rps.cfg` and other Proxy Server-related modules.

Note that as of version 5.00, the default installation location changed to `C:\Program Files\Hewlett-Packard\CM\IntegrationServer` on Windows and `/opt/HP/CM/IntegrationServer` on UNIX. To upgrade to the new location, the existing service must be stopped and removed. If the previous version of the Integration Server service exists when you use the 7.20 installation, the new installation will target the existing directory where the Integration Server is installed. If the previous service is removed, then the install will show the new default installation directory.

 A Proxy Server co-located with the Configuration Server points to the resources of the Configuration Server DB. HP recommends installing a co-located Proxy Server into the new default location.

To use the Portal Version 7.20 to upgrade your Proxy Servers to 7.20

If you have installed the Portal, Version 7.20, you can use the **Install Proxy Server** task to remotely upgrade the existing Proxy Servers in your enterprise to Proxy Server version 7.20.

For requirements and procedures related to performing the **Install Proxy Server** task from the Management Portal, see the topics in the *HP Client Automation Portal Installation and Configuration Guide for Windows*, as well as the *HP Client Automation Proxy Server Installation and Configuration Guide*.

To upgrade from 4.x or 5.x to 7.20 using SETUP.EXE

The upgrade procedure directs you to rename the `rps.cfg` file prior to running the install so that the new `rps.cfg` file is unpacked. After installation, you can merge your earlier customizations with the new `rps.cfg` file. For additional configuration information, see the *HP Client Automation Proxy Server Installation and Configuration Guide*.

- 1 Create a backup of the entire Proxy Server directory.
- 2 Rename the `rps.cfg` file in the existing Integration Server's `etc` directory to `rps32.bak`. This step forces the install of the new `rps.cfg` file.

► You only need to perform steps 3 through 5 if you want to install Proxy Server 7.20 to its new default directory.

- 3 Open a command prompt, and navigate to the current installation directory for your Proxy Server. The default installation directory for previous versions was `C:\Novadigm\IntegrationServer`.
- 4 For Windows, type `sc stop httpd` to stop the service. Then type `sc delete httpd` to remove the service.
- 5 For UNIX, stop the `httpd` service for the existing Proxy Server. For details, refer to the *Proxy Server Installation and Configuration Guide*.
- 6 Run the Proxy Server installation program from the computer where the existing Proxy Server is installed. The install program is located on the `\infrastructure\extended_infrastructure\proxy_server\<platform>` directory of the installation media.

► For Windows, the components for Proxy Server 7.20 will be installed to the same location as your existing Proxy Server if the previously installed service was not been removed. If the service has been removed, the new default directory location will be targeted for installation.

For UNIX, the new default directory will display as the target installation path: `/opt/HP/CM/IntegrationServer`. If desired, modify this path to target a different installation directory.

For details on running the install program, see the Installation chapter of the *Proxy Server Installation and Configuration Guide*.

- 7 After installation, compare the contents of the new `rps.cfg` file that was installed to the Integration Server's `etc` directory with the `rps32.bak` file. Port any customizations you had in the `rps32.bak` file to the new `rps.cfg` file.
- 8 Place the merged `rps.cfg` file back in the Integration Server's `etc` directory.
- 9 The path to your Configuration Server may have changed for this Version. Review the `rps.cfg` file for any configuration parameters pointing to a Configuration Server location. If necessary, modify the paths to represent the current location of your Configuration Server. For Version 7.20, the default path is:

Windows:

`C:\Program Files\Hewlett-Packard\CM\ConfigurationServer`

UNIX:

`/opt/HP/CM/ConfigurationServer`

- 10 Start the HP Client Automation Integration Server (`httpd`) to start the Proxy Server.

If you installed the Proxy Server into the new path, the Windows service name is **HP Client Automation IntegrationServer (httpd)**.

To start the Proxy Server for UNIX

- 1 Change your current directory to where you installed the Proxy Server. (If you removed the existing service, the new default is: **/opt/HP/CM/IntegrationServer/**).
- 2 Type:
`./nvdkit httpd.tkd`
- 3 Press **Enter**.
- 4 The Proxy Server is started on your computer.