

# HP Client Automation Enterprise Messaging Server

For the Windows® operating system

Software Version: 8.10

---

## Reference Guide

Document Release Date: February 2012

Software Release Date: February 2012



## Legal Notices

### Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

### Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

### Copyright Notice

© Copyright 1993 - 2011 Hewlett-Packard Development Company, L.P.

### Trademark Notices

Microsoft®, Windows®, Windows® XP, and Windows Vista® are U.S. registered trademarks of Microsoft Corporation.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

### Acknowledgements

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

This product includes cryptographic software written by Eric Young ([eay@cryptsoft.com](mailto:eay@cryptsoft.com)).

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

This product includes software written by Tim Hudson ([tjh@cryptsoft.com](mailto:tjh@cryptsoft.com)).

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

**<http://h20230.www2.hp.com/selfsolve/manuals>**

This site requires that you register for an HP Passport and log on. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

Or click the **New users - please register** link on the HP Passport log on page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

## Support

Visit the HP Software Support Online web site at:

**<http://www.hp.com/go/hpsoftwaresupport>**

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

To find more information about access levels, go to:

**[http://h20230.www2.hp.com/new\\_access\\_levels.jsp](http://h20230.www2.hp.com/new_access_levels.jsp)**

---

## Contents

Reference Guide.....	1
Contents.....	5
Introduction.....	7
About the Messaging Server.....	7
Features and Benefits.....	7
Messaging Server Processing on the Configuration Server.....	8
About the Data Delivery Agents.....	10
About Routing Inventory Data.....	11
About the SQL Database Tables and Scripts for Inventory.....	11
Creating SQL Tables for the Inventory Database.....	11
About Using Store and Forward.....	11
About this Guide.....	12
Abbreviations and Variables.....	13
Summary.....	13
Configuring and Tuning the Messaging Server.....	15
Understanding the Configuration Server Modules that Support the Messaging Server.....	15
Getting Agent information to the Messaging Server.....	15
About the Patch Method for Collection.....	15
About the ZTASKEND REXX method.....	16
ZTASKEND calls to QMSG.....	16
Processing Phase-Dependent Objects.....	16
Processing CORE Objects by Phase.....	17
Adding Items to a Critical Object List.....	19
Processing Always Objects.....	19
Adding Custom Objects to the BuildAlways Object List.....	19
QMSG Method Syntax.....	19
How Priority Establishes Messaging Server Processing Order.....	21
Configuring the Messaging Server.....	21

Editing the Configuration Files for the Messaging Server and Data Delivery Agents.....	21
About the Sections in the RMS.CFG File.....	30
Additional Sections in the RMS.CFG File.....	30
About the Sections in the CORE.DDA.CFG File.....	31
ODBC Settings for CORE, INVENTORY and WBEM Objects.....	32
About the Sections in the PATCH.DDA.CFG File.....	33
ODBC Settings for PATCH Objects.....	34
Additional Tuning Topics.....	34
Configuring the Poll Interval and Post Quantity.....	34
Configuring for Retry Attempts.....	35
Configuring for Failover.....	35
Configuring the Log Level, Log Size and Number.....	36
Changing the Logging Level.....	36
Changing the Size and Number of Log Files.....	36
Configuring the Messaging Server to Discard or Drain Messages.....	37
Example: Discarding messages for the Portal.....	37
Example: Draining a Message Queue.....	37
Configuring the Messaging Server to Route Portal Messages.....	37
About the Portal Data Queue (mpq) in CORE.DDA.CFG.....	37
Restoring Routing for Portal Messages.....	38
Enhancing Messaging Server Performance.....	39
Disabling Processing of Messages in a Queue.....	39
Modifying the Priority in which Messages are Processed.....	41
<b>Troubleshooting the Messaging Server.....</b>	<b>43</b>
<b>We appreciate your feedback!.....</b>	<b>45</b>

## Introduction

### About the Messaging Server

The HP Client Automation Messaging Server (Messaging Server) is a robust messaging service that provides a means to forward data from one piece of the HPCA infrastructure to another. It can be used as a point to aggregate different types of data as well as to segregate data accumulated from various HPCA servers by type. Its job is to monitor predefined data queues and dynamically route data objects to one or more external destinations. The Messaging Server provides retry, rerouting, and failover capabilities to ensure all data is transferred efficiently and reliably.

On the HPCA Configuration Server (Configuration Server), the Messaging Server operates hand-in-hand with the executable, `QMSG`, to handle the transfer of data reported from HPCA agents to the appropriate ODBC reporting database or external HPCA Server.

### Features and Benefits

The Messaging Server provides an efficient and flexible messaging system that can be used by HPCA infrastructure modules. For example, it can:

- Route a single message to multiple destinations.
- Automatically retry a message delivery.
- Re-route messages to a new host after an unsuccessful delivery attempt (failover capability).
- Route data from one Messaging Server to another one (store and forward capability).
- Maintain multiple data queues on Store and Forward Messaging Servers.

The Messaging Server provides the following benefits:

- Multiple, specialized queues that enable separate workers to operate on each queue, and therefore allows for parallel processing of object messages.
- Additional workers can be configured to drain a queue more quickly.
- Independent data delivery agents allow for modular upgrades.
- Eliminates bottlenecks on the Configuration Server.
- Reliability of processing Inventory and Patch data is maintained, due to:
  - Built-in retry capability.
  - Ability to reroute messages remaining in a queue to a failover location.
  - Retry, holding, and re-routing features eliminate potential loss of data caused by network failures.
- Improved memory control related to creating the Inventory Manager SQL tables and loading the SQL commands upon startup. As a result, these SQL tasks are always performed upon Messaging Server and Data Delivery Agent startup, and support for the previous `STARTUPLOAD` parameter has been removed.
- Improved queue control and throttling capability for posting HPCA Portal data.
- New support for customized message routing to multiple DSNs using ODBC.

## Messaging Server Processing on the Configuration Server

The Messaging Server acts as a delivery service between the Configuration Server and external ODBC databases or HPCA services. It is a separate component from the Configuration Server.

When a customer has multiple Configuration Servers, each one will have a co-located Messaging Server and the ability to route object data to the appropriate target location.


The figure "[Messaging Server Processing](#)" (on page 8) provides an overview of Messaging Server Processing.

The HPCA agent connects to the Configuration Server to resolve its desired state. At the end of each agent connection, the agent passes objects back to the Configuration Server. Different agent objects are passed according to each specific phase of the agent connect process.

The Messaging Server refers to CORE objects as the standard HPCA agent objects that are exchanged between the agent and the Configuration Server. Examples of CORE objects are ZMASTER, PREFACE, and SESSION. Other types of objects that can be exchanged are multi-heap WBEM reporting objects, FILEPOST objects created by an inventory agent audit process (called INVENTORY objects) and the DEERROR, BUSTATUS, DESTATUS, and PASTATUS agent objects collected for HPCA Patch Manager processing.

Messaging Server Processing
-----------------------------





Legend

1. ZTASKEND is called
2. QMSG.EXE assembles object data
3. Messaging Server Data Delivery Agents poll the queues and transfer data

1. ZTASKEND is Called

On the Configuration Server, the ZTASKEND rexx method is called at the end of the agent connect process. ZTASKEND creates the commands to invoke the QMSG executable. The commands to QMSG contain parameters that define the appropriate objects to send as well as the designated queues in which to place the objects. ZTASKEND is responsible for naming all objects forwarded to QMSG—with the exception of objects needed for Patch reporting. For Patch objects, five methods in the PRIMARY.SYSTEM.ZMETHOD class of the Configuration Server Database call QMSG for the PATCH objects.

2. QMSG.EXE Assemble Object Data

QMSG assembles object data into XML files and creates header files with the appropriate metadata “address” needed to deliver the message by the Messaging Server. When the two

message files (XML and meta data files) are created, QMSG places these files in one or more predefined data queues on the Configuration Server.

**Note:** QMSG places objects in separate queues, based on the parameters specified in ZTASKEND and in the five PATCH\_\* methods (DEERROR, BUSTATUS, DESTATUS, and PASTATUS). The Messaging Server is configured to use individual Data Delivery Agents (DDAs) to process messages from these queues. The table "[Data Queues and Data Delivery Agents](#)" lists the Data Delivery Agents that operate on each data queue location.

3. Messaging Server Data Delivery Agents poll the queues and transfer data  
The Messaging Server DDA's poll the message queues and automatically pick up and transfer data files to the appropriate external locations using the routing type and locations defined in the specific data delivery agent's configuration file.

### Data Queues and Data Delivery Agents

Data Queue	Data Delivery Agent
..\Data\MessagingServer\core	core.dda
..\Data\MessagingServer\patch	patch.dda
..\Data\MessagingServer\usage	usage.dda

The Messaging Server runs on all Windows platforms supported by the Configuration Server.

## About the Data Delivery Agents

The Data Delivery Agents are function-specific modules created to transfer certain types of message data. There are Data Deliver Agents available for CORE, PATCH, and USAGE message data.

- The CORE message data refer to agent objects typically exchanged during a standard agent connect process. The CORE message data also includes the FILEPOST objects created during the agent audit process and the WBEM reporting object data. Examples of CORE type message objects include ZMASTER, SESSION, and ZCONFIG. CORE objects support reports for Vulnerability Management, Windows CE Thin Clients and Application Management Profiles, among others.
- The PATCH message data is comprised of DESTATUS, BUSTATUS, DEERROR and PASTATUS agent object data.

The Data Delivery Agents (DDAs) have the ability to post messages using ODBC into a SQL database that can be used for reporting. For processing efficiency, each DDA works independently on its own queue.

The Messaging Server loads these independent data delivery agents, whose configurations define how and where the messages for CORE, INVENTORY, WBEM, and PATCH data objects will be delivered.

**Note:** The CORE data delivery agent is configured to post CORE object data to an Inventory Manager database, as well as CORE object data to a Portal directory.

The data delivery agent modules are located in the `\MessagingServer\modules` folder. The modules are loaded using “`dda.module load`” statements in the Messaging Server configuration file (`rms.cfg`).

Each data delivery agent is configured from its own configuration file (`*.dda.cfg`). These configuration files are located in the `\MessagingServer\etc` folder.

## About Routing Inventory Data

This Messaging Server supports direct ODBC posting of Inventory Manager data to a back-end SQL Inventory Database. The CORE.DDA has the ability to route CORE, INVENTORY and WBEM data messages to a back-end SQL database using ODBC. This is the HP recommended routing option for best performance.

## About the SQL Database Tables and Scripts for Inventory

The CORE Data Delivery Agent posts the message data into the SQL table, for which the default definitions and associated SQL queries are found in the following Messaging Server directories:

```
/etc/<module name>/hp
```

Customized scripts can be placed in the directories:

```
/etc/<module name>/
```

The script necessary to map the CORE object data to the related SQL table column is `taskend.tcl`. The script necessary to map the INVENTORY object data (FILEPOST object) is called `filepost.tcl`. Both of these scripts are found in the `/etc/<module name>/lib` directory of the Messaging Server.

All inventory and the application deployment related tables have a foreign key constraint with the table `DeviceConfig`. This foreign key constraint ensures that when a device is deleted, all the records corresponding to that device are deleted from all the other tables.

## Creating SQL Tables for the Inventory Database

The SQL tasks to create the tables for the Inventory Database and load the SQL commands into memory are performed when the Messaging Server service and the Data Delivery Agents are initially started.

**Note:** All SQL tasks are performed at service startup and any STARTUPLOAD value found in a configuration file is ignored.


## About Using Store and Forward

The Messaging Server includes store and forward capabilities that allow you to forward messages to another Messaging Server using HTTP or HTTPS. In addition, if the Messaging Server is not located close to the SQL database, it is a good practice to forward the messages to one that is located as close to the SQL database as possible.

The Messaging Server supports forwarding and receiving messages using multiple queues.

The figure ["Store and Forward Messaging Server"](#) illustrates a typical configuration that forwards messages to another Messaging Server, prior to posting data to the Inventory database using ODBC.

## Store and Forward Messaging Server



1. The Messaging Server on the Configuration Server is configured to have the CORE data delivery agent forward the data to another Messaging Server using HTTP or HTTPS. This configuration makes use of the *coreforward*, *inventoryforward*, and *wbemforward* sections that are provided in the data delivery agent configuration files.
2. The Store and Forward Messaging Server is located close to the Inventory Manager SQL database. It receives the CORE, INVENTORY, and WBEM objects.
3. The attending CORE data delivery agent on the receiving Messaging Server posts the data objects to the Inventory Manager database using ODBC.

## About this Guide

In addition to this chapter, this book contains the following information:

- **Configuring and Tuning the Messaging Server**

This chapter describes how the Configuration Server ZTASKEND REXX and the QMSG executable work hand-in-hand with the Messaging Server. It also discusses how to configure the Messaging Server configuration file, which loads the Data Delivery Agents. In addition, this chapter also describes how to configure the DDA modules to route CORE, INVENTORY, WBEM, and PATCH message data to the Inventory, Portal, and Patch Manager databases or directories. Additional tuning options are included.

- **Troubleshooting**

This chapter reviews how to resolve common error messages in the `rms.log` files and identifies solutions for typical posting problems.

- **Additional Messaging Server Configuring Options**

This chapter describes alternate configurations, including how to install and configure for Store and Forward, and other customized configurations.

## Abbreviations and Variables

### Abbreviations Used in this Guide

Abbreviation	Definition
HPCA	HP Client Automation
Core and Satellite	HPCA Enterprise environment consisting of one Core server and one or more Satellite servers. All features are installed as part of the Core or Satellite server installation.
CSDB	Configuration Server Database
Portal	HPCA Portal

### Variables Used in this Guide

Variable	Description	Default Values
<i>InstallDir</i>	Location where the HPCA server is installed	For a 32-bit OS: C:\Program Files\Hewlett-Packard\HPCA  For a 64-bit OS: C:\Program Files (x86)\Hewlett-Packard\HPCA
<i>SystemDrive</i>	Drive label for the drive where the HPCA server is installed	C:

## Summary

- The Messaging Server routes the object data collected from Client Automation Agents and placed into queues into the appropriate Client Automation server or SQL database. Messages can also be forwarded to another Messaging Server.
- Messages processed include agent objects collected for core, inventory, wbem and patch data.
- Configuration settings in the `rms.cfg` file allow you to load the Data Delivery Agents needed to process the queues on that server. There are separate Data Delivery Agents for core, inventory (filepost), wbem and patch data objects.
- Configuration settings in the `*.dda.cfg` files for the specific data delivery agents specify how and where to route the data processed by that data delivery agent.
- Additional tuning options address load balancing when processing high-volumes of data as well as large-sized objects.



## Configuring and Tuning the Messaging Server

**Note:** To configure the Usage Data Delivery Agent, see the *HP Client Automation Enterprise Application Usage Manager Reference Guide*.

### Understanding the Configuration Server Modules that Support the Messaging Server

This topic explains how the methods on the Configuration Server work hand-in-hand with the Messaging Server to collect, queue, and then deliver data to the appropriate external location.

#### Getting Agent information to the Messaging Server

Agent objects exchanged with or created on the Configuration Server during an agent connect session are formatted into messages for the Messaging Server via the Configuration Server binary executable QMSG. The QMSG executable is part of the HPCA release. This executable is invoked during agent taskend processing by the rexx method ZTASKEND or a connection to the Patch Manager methods. The calls to QMSG can include parameters specifying what queue to place the messages in, the priority in which the message is to be processed, the objects that are to be included in the messages, and the “destination address” or routing identifier for the file.

The QMSG executable formats the object data into an XML file. Each XML file can be made up of multiple objects, such as when processing the CORE objects (for example, ZMASTER, SESSION and ZCONFIG) or it can be a single multi-heap object such as a wbem or filepost object. Each call to QMSG will produce two files, the XML file created from the object data and a file which contains the metadata. Metadata are attributes describing the XML file, how big it is, when it was created and the routing identifier. The actual file names are created with a timestamp format. This enables the Messaging Server to process the oldest messages first. The Messaging Server always processes in a “First In First Out” mode when the messages have the same processing priority.

When queue designations are specified when invoking QMSG, messages are placed in a directory with the specified queue name. When no queue identifier is used, messages are placed in a directory named default. Each data delivery agent uses its own unique queue for its particular messages. This segregation of messages according to type allows for the simultaneous processing of all queues and leads to more efficient operation.

#### In Summary:

- For agent information needed by the Patch Manager, QMSG is executed as a result of the `SYSTEM.ZMETHOD.PATCH*` instances: `PATCH_DEERROR`, `PATCH_BUSTATUS`, `PATCH_DESTSTATUS`, and `PATCH_PASTATUS`.  
For more information on creating the method connection needed for Patch message processing, see the *HPCA Patch Manager Reference Guide (Patch Manager Guide)*.
- For information needed by the Inventory Manager, Portal, and Application Management Profiles, the Configuration Server REXX method, ZTASKEND, is used to trigger the call to QMSG. The format of the QMSG call is included in the discussion of ZTASKEND which follows.

#### About the Patch Method for Collection

Five methods call the QMSG executable with the parameters in the ZMTHPRMS attribute of the method. The default value of this attribute looks like this:

```
ZMTHPRMS      -to PATCH5 -queue patch <<object-name>>
```

The `-to PATCH5` parameter specifies that the messages will be placed in a queue called `../data/patch` relative to the location of where QMSG is executed. This is the default location specified in the install of the `patch.dda`.

The `<<object-name>>` parameters (`DEERROR`, `BUSTATUS`, `DESTATUS`, and `PASTATUS`) specify the objects that will be included in the message files created by QMSG.

## About the ZTASKEND REXX method

The ZTASKEND REXX method on the Configuration Server is called at the end of each agent connect, while objects associated with the present session are still available in storage on the Configuration Server. ZTASKEND invokes QMSG when agent data needs to be collected for another service, such as Inventory Manager, Application Management Profiles, or the Portal. QMSG collects the data and places the messages in specified queues for pickup and processing by the Messaging Server and its data delivery agents.

**Note:** Different object types (core, inventory and wbem objects) are placed in separate queues whenever the Data Delivery Agents have been installed for those data objects.

An important job of ZTASKEND is to ensure unique agent data is collected at the appropriate agent connect phase. For efficiency, ZTASKEND also groups identical messages, having the exact same object content, to minimize the number of calls made to QMSG.

This topic explains:

- How ZTASKEND determines when to call QMSG for the various agent connect phases and which objects are collected.
- The basic syntax of calls to QMSG.
- How the QMSG `-to` parameter establishes one or more destinations for message processing.
- How the QMSG `-priority` parameter establishes Messaging Server processing order.

## ZTASKEND calls to QMSG

This topic reflects the ZTASKEND method.

## Processing Phase-Dependent Objects

Each time an HPCA agent connects to the Configuration Server, the agent declares its connection intent or phase. An important role of the ZTASKEND REXX code is to minimize the collection of duplicate information. With that goal in mind, the ZTASKEND method invokes QMSG depending on the agent connection phase and the objects present. ZTASKEND restricts message posting to five specific connection phases. The phases of interest are:

- `BOOTSTRAP` (Client Operations Profiles or COP)
- `AGENT SELF MAINTENANCE`
- `CATALOG RESOLUTION`
- `SERVICE RESOLUTION`
- `AGENT REPORTING`



## Processing CORE Objects by Phase

There are "critical objects" collected for each of the core targets for Inventory Manager (RIM) and Portal (RMP). The potential critical objects are:

For RIM: APPEVENT MSIEVENT SYNOPSIS RNPEVENT

For RMP: SYNOPSIS IDENTITY

In addition to the above critical objects, the table "[Critical Objects collected by phase](#)" identifies critical objects collected for each phase.

### Critical Objects collected by phase

Phase	Critical Objects
BOOTSTRAP (COP)	SESSION PREFACE ZSTATUS SMINFO
AGENT SELFMAINTENANCE	SESSION PREFACE ZSTATUS SMINFO
CATALOG RESOLUTION	SESSION PREFACE ZSTATUS ZCONFIG ZMASTER SMINFO
SERVICE RESOLUTION	SESSION PREFACE ZSTATUS SMINFO
AGENT_REPORTING	SESSION PREFACE ZSTATUS SAPSTATS ZRSTATE SMINFO

With this in mind, ZTASKEND uses the following logic:

1. Whenever a critical object is presented, the critical object and the additional objects are processed by QMSG and deposited into queues for processing by Messaging Server (RMS).
2. If a critical object is not present, then the code invokes QMSG when an agent connects during the phases CATALOG\_RESO and AGENT\_REPORTING.
3. If a critical object is not found, then code does not invoke QMSG for the following agent phases: BOOTSTRAP (COP), SERVICE RESOLUTION and AGENT\_SELF MAINTAINANCE.
4. Finally, ZTASKEND does not invoke QMSG to obtain error message objects (ZERRORM & ZERROR).

The table "[ZTASKEND calls to QMSG for CORE Data for RIM and RMP](#)" summarizes the Agent Connect phases and the objects collected during the ZTASKEND calls to QMSG, for CORE data going to Inventory Manager or the Portal.

### ZTASKEND calls to QMSG for CORE Data for RIM and RMP

Agent Connect Phase	QMSG call if not critical object?	QMSG call if critical object
<b>Bootstrap - COP Resolution:</b> for Client Operations Profile.	No	Collects these objects for CORE.RIM and CORE.RMP destinations:  APPEVENT   MSIEVENT   SYNOPSIS   RNPEVENT SESSION

Agent Connect Phase	QMSG call if not critical object?	QMSG call if critical object
		PREFACE ZSTATUS SMINFO
<b>Agent Maintenance:</b>	No	Collects these objects for CORE.RIM and CORE.RMP destinations:  APPEVENT   MSIEVENT   SYNOPSIS   RNPEVENT SESSION PREFACE ZSTATUS SMINFO
<b>Catalog Resolution:</b> Agent connects to the Configuration Server to obtain service resolution list.	<b>Always.</b> Collects these objects for CORE.RIM and CORE.RMP destinations: SESSION PREFACE ZCONFIG ZMASTER ZSTATUS SMINFO	See previous column, but also collects APPEVENT   MSIEVENT   SYNOPSIS   RNPEVENT.
<b>Single Service Resolution:</b> For each service to be resolved, agent makes another connection to the Configuration Server.	No	Collects the following objects for CORE.RIM and CORE.RMP destinations:  APPEVENT   MSIEVENT   SYNOPSIS   RNPEVENT SESSION PREFACE ZSTATUS SMINFO
<b>Agent Reporting:</b> At the end of service resolution. Agent data is reported back to the Configuration Server.	<b>Always.</b> Collects these objects for CORE.RIM destination: SESSION PREFACE ZSTATUS SAPSTATS ZRSTATE SMINFO	See previous column, but also collects APPEVENT   MSIEVENT   SYNOPSIS   RNPEVENT

## Adding Items to a Critical Object List

The ZTASKEND rexx code can be configured to add object names to the critical and additional object lists. The rexx variables `CriticalRIMObjects` and `CriticalRMPObjets` contain the object names for each of these targets. The rexx function call to `BuildObjectList` is used to build the object list for each phase.

```
Call BuildObjectList ....
:
:
:
:
CriticalRIMObjects = "APPEVENT MSIEVENT SYNOPSIS RNPEVENT"
CriticalRMPObjets = "SYNOPSIS"
```

The ZTASKEND rexx code contains additional information on how to alter these items.

## Processing Always Objects

There is a section of the ZTASKEND rexx code to define objects that will always be processed, independent of the phase being processed. The larger Inventory Manager objects, FILEPOST, WBEMAUDT and CLISTATS are processed this way. If these objects exist, then they are sent to the specified target. In addition to the larger Inventory Manager objects, the job objects: JOBSTAT, JOBPARM, and JOBTASK are also processed this way.

## Adding Custom Objects to the BuildAlways Object List

This part of the rexx code can also be configured to add "custom" objects that are always delivered to the specified target. The rexx function `BuildAlways` is used to configure the target, queue and objects to process. The rexx code contains additional information on how to alter these items.

```
Call BuildAlways "inventory", InventoryQueue, "FILEPOST"
```

## QMSG Method Syntax

The QMSG command/method is used to post Configuration Server objects for Inventory Manager, Portal and Application Management Profiles. QMSG reads the specified object and converts it to XML and then writes it to the specified queue.

The syntax of the QMSG method is given below:

```
qmsg -to <destination(s)> -queue <queue> -priority <priority> object1
object2 ... objectn
```

### **-to <destination(s)>**

must be explicitly coded with one or more destinations, or targets. Messages going to multiple destinations have comma-separated entries. For example:

```
-to CORE.RIM,CORE.RMP
```

The Messaging Server destination values used by the delivered QMSG include:

```
-to CORE.ODBC
```

```
-to CORE.RMP
```

```
-to INVENTORY.ODBC

-to WBEM.ODBC
```

Each message destination requires an equivalent ROUTE defined for it in the msg::register router section of the appropriate Data Delivery Agent's \*.dda.cfg file. The table "[QMSG Destinations and DDA Configuration Locations](#)" gives the destination values of QMSG and the configuration file and section used to define its ROUTE.

**QMSG Destinations and DDA Configuration Locations**

QMSG -to destination	Configuration File in MessagingServer\etc folder	Required ROUTE section
-to CORE.ODBC	core.dda.cfg	msg::register corerouter
-to CORE.RMP	core.dda.cfg	msg::register corerouter
-to INVENTORY.ODBC	core.dda.cfg	msg::register inventoryrouter
-to WBEM.ODBC	core.dda.cfg	msg::register wbemrouter

**-queue <queue>**

The queue is a directory relative to where QMSG.EXE exists. QMSG is located in the \bin directory of the Configuration Server. For example, if QMSG resides at

```
C:\Program Files\Hewlett-Packard\HPCA\ConfigurationServer\bin\qmsg.exe
```

Then the queues would reside at:

```
C:\Program Files\Hewlett-Packard\HPCA\ConfigurationServer\data\blue

C:\Program Files\Hewlett-Packard\HPCA\ConfigurationServer\data\default

C:\Program Files\Hewlett-Packard\HPCA\ConfigurationServer\data\green

C:\Program Files\Hewlett-Packard\HPCA\ConfigurationServer\data\red
```

The parent directory of all queues is "data". For illustrative purposes, this example shows the existence of the (fictitious) blue, green and red queues. Note that the queue named "default" is the default queue.

**Note:** Queue locations are defined near the top of ZTASKEND. For Patch routing, the queue location is named in the parameters passed to QMSG from the five SYSTEM.ZMETHOD.PATCH\_\* instances. The instances are named DEERROR, BUSTATUS, DESTATUS, and PASTATUS. For example:

```
Method = qmsg
Parameter = -to PATCH5 -queue patch <<object>>
To modify the parameters to pass, edit the value of the ZMTHPRMS attribute in the PATCH_* instance.
```

**-priority**

The priority is available to establish Messaging Server processing priority. If omitted, a default priority of 10 is given to the message. Valid values are 00 (highest priority) to 99 (lowest priority). For more information on Messaging Server processing priority, see the topic "[How Priority Establishes Messaging Server Processing Order](#)" (on page 21).

**object1 [objectn]**

The rest of the command line includes the names of the objects to queue, object1 object2... objectn. The objects are processed in the order specified; thus, depending on the destination, there might be a dependent order.

## How Priority Establishes Messaging Server Processing Order

When ZTASKEND calls QMSG, the optional **-priority** parameter in the call assigns a processing priority to the message. Priority values can range from 00 to 99, with 00 reserved for critical processing and 99 being the lowest priority.

For messages waiting to be processed in the same queue, the Messaging Server processes all messages assigned to a higher priority (such as 10) *before* processing any messages assigned to a lower priority (such as 20). Within a given priority, messages are processed using first in, first out (FIFO) order.

**Note:** The message priority remains the same for the life of the message. For example, if a message is forwarded from one Messaging Server to another, the message priority remains the same.

- Priority 10 is the default if a priority is not specified.
- Previously, ZTASKEND called QMSG with parameters to assign a lower priority of 20 to the larger objects collected for Inventory Manager Reports: these include file audits, wbem reporting data, and agent statistics (CLISTATS).
- This is no longer necessary because of the segregation of queues by object type.

If the Messaging Server is not able to process the messages as fast as they are delivered from QMSG, the lower priority messages will accumulate at the bottom of a queue location, even though newer messages with higher priorities are still being processed.

## Configuring the Messaging Server

Use these topics to reconfigure or tune the Messaging Server after installation, or reconfigure or tune the data delivery agents for core or patch data.

## Editing the Configuration Files for the Messaging Server and Data Delivery Agents

The Messaging Server and Data Delivery Agents standard installation allows configuration of several of the configuration parameters contained in the respective configuration files. You will need to edit the configuration file with a text editor to achieve a more customized environment.

All of the configuration files for the Messaging Server and Data Delivery Agents are found in the `\etc` directory of where the Messaging Server was installed.

All the configuration files for the Messaging Server and the associated Data Delivery Agents have similar configuration sections. Understanding these sections and the syntax used to configure them will aid in customizing your environment.

The structure for the RMS configuration file sections is given below:

```
msg::register <unique identifier> {  
  TYPE           <RMS registered TYPE>  
  <Configurable Variable for the registered TYPE>      <Value for that
```

```

Variable>
  <Configurable Variable for the registered TYPE>      <Value for that
Variable> ...
}

```

Each configuration section starts with the command `msg::register`. This signals the start of a configuration parameter for the Messaging Server and its modules.

A unique identifier follows the `msg::register` command. Within an instance of the Messaging Server, which includes the configuration files for the Messaging Server and all of the DDA modules, this unique identifier label can only be used once. The unique identifier is followed by a curly brace "`{`". The configuration section for this TYPE must be ended by a closing curly brace for the entire configuration to work.

All configuration file sections have a TYPE identifier, which indicate the kind of work to be done by this section. These are the current acceptable TYPE designations:

- QUEUE
- ROUTER
- HTTP
- HTTPS
- HTTPD
- FILTER
- SQLBALANCER (only configurable in `core.dda.cfg`)

The table "[Glossary of Section TYPEs and Configurable Parameters](#)" describes the different section TYPES and their configurable parameters. The sections are listed in the general order in which they appear in the configuration files.

### Glossary of Section TYPEs and Configurable Parameters

Section TYPE	Configurable Parameters
<p><b>QUEUE</b> Defines the directory where messages are placed for processing.</p>	<p><b>DIR</b> The directory name of the queue.</p> <p><b>USE</b> Specify the name of the unique identifier that will signify how to dispatch the message. Usually this is a ROUTER type.</p> <p><b>POLL</b> By default, the Messaging Server is configured to poll the queue location every 10 seconds and post up to 100 objects at a time. To change the poll interval, modify the POLL parameter.</p> <p><b>COUNT</b> Maximum number of objects to post at a time (during the polling interval defined by POLL). Default is 100 objects.</p> <p><b>ATTEMPTS</b></p>

Section TYPE	Configurable Parameters
	<p>Maximum number of attempts to retry a failed message delivery before discarding the message. Default is 200 attempts. (By default, the Messaging Server and Data Delivery Agents are configured to retry any failed posts every hour, and make up to 200 attempts.)</p> <p><b>DELAY</b> Number of seconds to wait between attempts to retry a failed message delivery. Default is 3600 seconds, or one hour.</p> <p><b>Note:</b> To calculate the maximum time that a message could stay in the queue before being discarded, take the DELAY time and multiply it by the ATTEMPTS value. Using the default settings, this is a DELAY of 3600 seconds x 200 ATTEMPTS, or approximately eight days.</p>
<p><b>ROUTER</b> Defines where the messages are going to sent.</p>	<p><b>ROUTE</b> Delimit each Route by curly braces</p> <p><b>TO</b> This is the address of the message. It is contained in the meta data file of each message when the message is created.</p> <p><b>USE</b> Specify the unique name of a Messaging Server TYPE that will be used to dispatch the message, such as HTTP or HTTPS. (In a DDA file, the USE entries may also be COREODBC, WBEMODBC and PATCHDDAODBC).</p>
<p><b>HTTP</b> This is a way to post the message to another server location using http protocol. The target server can be another Messaging Server where the message can be re-queued or it can be another part of the infrastructure, such as the Portal.</p>	<p><b>ADDRESS</b> Delimit each address using curly braces. Multiple URL destinations can be specified within each HTTP TYPE as long as each has its own ADDRESS label and a different priority.</p> <p><b>PRI</b> Denotes the priority in which to sent messages to the companion URL. The default priority is 10. The priority setting only matters if multiple ADDRESS entries are configured. If multiple ADDRESS entries are configured the lowest priority is tried first and if that fails the next priority URL is tried. This allows failover capability if there are network problems.</p> <p><b>URL</b> Specifies the URL to use to send the message.</p>
<p><b>HTTPS</b></p>	<p><b>ADDRESS</b> Same as TYPE of HTTP.</p>

Section TYPE	Configurable Parameters
<p>This is a way to post the message using a secure socket. The HTTPS parameters are configured the same as the HTTP parameters—with the exception of the URL specification. The URL uses the <code>https://</code> convention.</p>	<p><b>PRI</b> Same as TYPE of HTTP.</p> <p><b>URL</b> Specifies the URL using the <code>https://</code> convention.</p> <p>For detailed information, see the <i>HP Client Automation SSL Implementation Guide</i>.</p>
<p><b>HTTPD</b> Defines the parameters the Messaging Server will use to receive incoming messages.</p>	<p><b>PORT</b> Defines the Port used to “listen” for messages. Only one port specification can be used for a given Messaging Server.</p> <p><b>URLHANDLER</b> Delimit with curly braces. If the incoming messages are to be deposited into different queues, depending upon the URL, the URLHANDLER must be used to delimit the USE and URL parameters.</p> <p><b>USE</b> Specify the name of the QUEUE type that will receive the incoming messages.</p> <p><b>URL</b> Specify the URL prefix that that will be accepted by the Messaging Server. When messages are received with the designated URL they are deposited in the associated queue. The QUEUE type must be defined when messages are received. All URL’s specified must start with <code>/proc/</code>.</p>
<p><b>FILTER</b> A means to route PATCH data into multiple SQL tables.</p>	<p><b>USE</b> Specify the name of the unique identifier that will signify how to dispatch the message.</p> <p><b>TO</b> This is the address of the message. It is contained in the meta data file of each message when the message is created.</p> <p><b>FILTER</b> Used for PATCH object processing into multiple tables</p>
<p><b>COREODBC</b> Used to post CORE messages into a SQL database.</p>	<p><b>DSN</b> Data Source Name</p> <p><b>USER</b> User ID for the DSN</p> <p><b>PASS</b> Password for the DSN</p>



Section TYPE	Configurable Parameters
	<p><b>DSN_ATTEMPTS</b> Number of attempts to connect to the DSN. Default is 1.</p> <p><b>DSN_DELAY</b> Delay in seconds between attempts to connect to the DSN. Default is 5 seconds.</p> <p><b>DSN_PING</b> Delay in seconds between pinging the database connection to verify the DSN is available. Default is 300 seconds.</p> <p><b>STARTUPLoad</b> No longer supported; any existing value is ignored.</p> <p><b>Note:</b> The SQL tasks to create the tables and load the scripts for the Inventory Database are always performed upon Messaging Server and Data Delivery Agent startup.</p>
<p><b>PATCHDDAODBC</b> Used to post PATCH data messages into a SQL or Oracle database.</p> <p>Only configurable in <code>patch.dda.cfg</code></p>	<p><b>DSN</b> Data Source Name</p> <p><b>USER</b> User ID for the DSN</p> <p><b>PASS</b> Password for the DSN</p> <p><b>DBTYPE</b> Database type of MSSQL (for Microsoft SQL Database) or ORACLE (for an Oracle Database).</p>
<p><b>SQL</b> The SQL database connection that handles all operational and inventory related data flows.</p>	<p><b>DSN</b> Data Source Name</p> <p><b>SERVER</b> The name of the SQL server</p> <p><b>USER</b> User ID for the DSN</p> <p><b>PASS</b> Password for the DSN</p> <p><b>AUTOCOMMIT</b> The transaction management mode for the SQL server that decides whether to commit or roll back the data.</p> <p><b>DSN_DELAY</b></p>

Section TYPE	Configurable Parameters
	<p>Delay in seconds between attempts to connect to the DSN. Default is 5 seconds.</p> <p><b>DSN_PING</b></p> <p>Delay in seconds between pinging the database connection to verify the DSN is available. Default is 300 seconds.</p> <p><b>TRUNCATE</b></p> <p>Truncates the data if it exceeds the column size. If disabled, the Messaging Server throws an error message.</p> <p><b>DISABLE_TABLE_UPDATES</b></p> <p>The Messaging Server disables the provision to update the specified tables in the database. You can specify the tables for which you want to disable the updates. For example, to disable the tables <code>HDeviceConfig</code> and <code>HAppEvent</code> from being updated, add the following entry in the <code>*.cfg</code> file:</p> <pre>DISABLE_TABLE_UPDATES {HDeviceConfig HAppEvent}</pre> <p><b>ENABLE-CORE</b></p> <p>Flag to enable the routing of CORE data objects placed in the queue locations for the core objects.</p> <p><b>ENABLE-INVENTORY</b></p> <p>Flag to enable routing of INVENTORY data objects placed in the queue locations for filepost (file audit inventory).</p> <p><b>ENABLE-WBEM</b></p> <p>Flag to enable routing of WBEM data objects placed in <code>\data\wbem</code> queue location.</p> <p><b>ENABLE-VM</b></p> <p><b>AUTOCREATE</b></p> <p>A switch to enable the creation of a new SQL file and table in the Inventory ODBC database when a new object class is received. Default is 0.</p> <p>0 – Does not create a SQL file or table entry for a new object class.</p> <p>1 – Creates a new SQL file and table entry for a new object class.</p>

Section TYPE	Configurable Parameters
	<p><b>AUTOLOAD</b> Enables autoloading of schemas</p> <p><b>SQLPATH</b> The path where the schemas are stored.</p> <p><b>MAPPATH</b> The path where the mappings (*.tcl files) are stored.</p> <p><b>WBEM-PKEYS</b> Enables creation of WBEM tables on demand with primary keys instead of unique indexes.</p> <p><b>ARCHIVE</b> Enables archiving of messages. If enabled, the messages are moved to the Archive location.</p> <p><b>REJECTS</b> Moves the messages to the REJECTS handler. The messages that fail to get processed, after maximum number of attempts have been tried to deliver this message, are moved to the REJECTS handler.  Maximum number of attempts to retry a failed message</p> <p><b>VALIDATE-NLS_PARAMS</b> National Language Support (NLS) connection settings that can be set for Oracle.</p>
<p><b>SQLBALANCER</b> Routes all messages for a given device to a single sub-queue based on the host name, with a single worker process processing the data in the queue.</p>	<p><b>QUEUE_DIR</b> The directory where the queue is stored. For example, <code>&lt;InstallDir&gt;\\Data\MessagingServer\core.</code></p> <p><b>QUEUE_POLL</b> By default, the Messaging Server is configured to poll the queue location every 1 second and post up to 100 objects at a time. To change the poll interval, modify the POLL parameter.</p> <p><b>QUEUE_COUNT</b> Maximum number of objects to post at a time (during the polling interval defined by POLL). Default is 5000 objects.</p> <p><b>QUEUE_DELAY</b> Number of seconds to wait between attempts to retry a failed message delivery. Default is 3600 seconds.</p>

Section TYPE	Configurable Parameters
	<p><b>QUEUE_ATTEMPTS</b></p> <p>Maximum number of attempts to retry a failed message delivery before discarding the message. Default is 200 attempts. (By default, the Messaging Server and Data Delivery Agents are configured to retry any failed posts every hour, and make up to 200 attempts.)</p> <p><b>QUEUE_REJECTS</b></p> <p>Moves the messages to the REJECTS handler. The messages that fail to get processed are moved to the REJECTS handler.</p> <p><b>SQL_DSN</b></p> <p>Data Source Name</p> <p><b>SQL_SERVER</b></p> <p><b>SQL_USER</b></p> <p>User ID for the DSN</p> <p><b>SQL_PASS</b></p> <p>Password for the DSN</p> <p><b>SQL_AUTOCOMMIT</b></p> <p>The transaction management mode for the SQL server that decides whether to commit or roll back the data.</p> <p><b>SQL_DSN_DELAY</b></p> <p>Delay in seconds between attempts to connect to the DSN. Default is 5 seconds.</p> <p><b>SQL_DSN_PING</b></p> <p>Delay in seconds between pinging the database connection to verify the DSN is available. Default is 300 seconds.</p> <p><b>SQL_ENABLE-CORE</b></p> <p>Flag to enable the routing of CORE data objects placed in the queue locations for the core objects.</p> <p><b>SQL_ENABLE-WBEM</b></p> <p>Flag to enable routing of WBEM data objects placed in \data\wbem queue location.</p> <p><b>SQL_ENABLE-INVENTORY</b></p> <p>Flag to enable routing of INVENTORY data objects</p>

Section TYPE	Configurable Parameters
	placed in the queue locations for filepost (file audit inventory).
	<p><b>SQL_ENABLE-VM</b></p> <p><b>SQL_AUTOCREATE</b></p> <p>A switch to enable the creation of a new SQL file and table in the Inventory ODBC database when a new object class is received. Default is 0.</p> <p>0 – Does not create a SQL file or table entry for a new object class.</p> <p>1 – Creates a new SQL file and table entry for a new object class.</p> <p><b>SQL_AUTOLOAD</b></p> <p>Enables autoload of schemas</p>

You can adjust default values and routing options by editing the \*.cfg files, located in the \etc directory of where the Messaging Server was installed.

The base Messaging Server configuration file (rms.cfg) loads the individual Data Directory Agent (DDA) modules for posting the following object types: core, inventory, wbem, and patch. Each DDA has its own configuration file (\*.dda.cfg) that defines where and how the objects are routed.

See the following topics for more information on how to configure or modify each configuration file.

- ["About the Sections in the RMS.CFG File" \(on page 30\)](#)
- ["About the Sections in the CORE.DDA.CFG File" \(on page 31\)](#)
- ["About the Sections in the PATCH.DDA.CFG File" \(on page 33\)](#)
- ["Additional Tuning Topics" \(on page 34\)](#)

**Note:** To configure the USAGE.DDA.CFG file, see Configuring Aggregation in *the HP Client Automation Enterprise Application Usage Manager Reference Guide*.

To edit a Messaging Server or Data Delivery Agent \*.cfg file:

1. Stop the Messaging Server before editing the rms.cfg file.
2. Edit the appropriate \*.cfg file using any text editor. By default, the \*.cfg files are located at: `<InstallDir>\MessagingServer\etc`.
3. Modify the sections using the information given in the following topics.  
**Note:** All path entries in the configuration files must be specified using forward slashes.
4. Save your changes and restart the Messaging Server.

To encrypt a password entry for a database DSN in a configuration file:

1. The PASS value in all the .cfg files where specification of DSN parameters is necessary has to be encrypted. When the value is entered during the install process, the installation program

takes care of encryption using AES, by default. If you need to modify the password, you can use the `nvdkit` utility to create an encrypted password using the AES or DES encryption method, and specify this encrypted value within the appropriate section of the configuration file. Enclose the encrypted value in quotation marks.

2. Open a command prompt and go to the directory where the Messaging Server is installed.
3. Enter the following command: `nvdkit`
4. At the `%` prompt, type the following command for AES encryption (the installation default):  
`nvdkit encrypt <password_value> aes`

Alternatively, type the following command for DES encryption:

```
nvdkit encrypt <password_value>
```

The utility will return an encrypted password value.

5. Cut and paste this encrypted password value into the `configuration` file as the `PASS` value. Enclose the value in quotation marks.

## About the Sections in the RMS.CFG File

The Messaging Server Configuration file, `rms.cfg`, has the following main sections after the header. The configuration file loads separate modules for data delivery agents (DDAs), whose job is to post the objects to the configured locations.

There are separate data delivery agents for core data (Inventory Manager and Portal objects) and patch data (for Patch Manager)

Optional entries in the `rms.cfg` file can include SSL support, a “`msg:register httpd`” section if this Messaging Server is receiving forwarded messages from another Messaging Server, and a “`msg:register default`” section if this Messaging Server is posting messages from a single queue location of `\data\default`.

## Additional Sections in the RMS.CFG File

- **Required packages**

Do not remove the following lines at the top of the `rms.cfg` file

```
package require nvd.msg
```

```
package require nvd.httpd
```

- **SSL Configuration Parameters**

If the Messaging Server is SSL enabled, this Overrides Config { } section in the `rms.cfg` is used to define the necessary certificates and parameters for SSL support. It also includes the command `module load tls`, which loads the code necessary to support SSL. For more information, refer to the *HP Client Automation SSL Implementation Guide*.

- **log::init**

Logging configuration. These settings apply to all Messaging Server logging. For details on changing the logging configurations, see ["Configuring the Log Level, Log Size and Number" \(on page 36\)](#). The log files are located in the Logs directory of where the Messaging Server was installed.

- **loglevel 3**

Default logging level for entries written to the log files. Default is 3. Normally, this is not changed.

- **loglines 200000**  
The default number of lines contained in a log before the log is rolled over.
- **loglimit 7**  
The default number of rolled logs to keep.
- **Load Data Delivery Agents for posting objects**  
Include the following lines at the end of `rms.cfg` to load the data delivery agents needed to post each type of object.
  - **dda.module load core**  
Posts CORE message data to a SQL or Oracle database and, optionally, CORE message data to the Portal directory. See "[About the Sections in the CORE.DDA.CFG File](#)" (on page 31) for more information on how to configure the posting of core objects.
  - **dda.module load patch**  
Post PATCH message data to a SQL or Oracle database. See "[About the Sections in the PATCH.DDA.CFG File](#)" (on page 33) for information on how to configure the posting of patch objects.
- **(Optional) msg::register default, msg::register router, and msg::register <rim|rmp|other>**  
These sections, if they exist, define how the Messaging Server handles the messages placed by QMSG in an existing `/data/default` location (or `/data/default queue`).
- **(Optional) Configure the maximum log size and number of logs.**  
Note that these options apply for each Worker assigned to process the `\data\default queue`. For more information, see "[Configuring the Log Level, Log Size and Number](#)" (on page 36).

## About the Sections in the CORE.DDA.CFG File

The `core.dda.cfg` file defines where and how to route objects placed in queue locations for core objects. As mentioned previously, the core objects are objects created on the agent, available during the agent connect process and used in reports. Examples of core objects are ZMASTER, ZCONFIG, and SESSION.

- To activate the `core.dda` module, the command `dda.module load core` must be included at the end of the `rms.cfg` file.
- For a Messaging Server co-located with a Configuration Server, the queue locations are folders where the QMSG executable places messages:  
Queue folder for core messages: `<InstallDir>\data\core`
- For a Messaging Server receiving messages forwarded from another Messaging Server `core.dda` module, URLs define the locations on which to listen for messages:  
URL for core messages: `http://localhost:3461/proc/core`

Several configurations are possible.

- Core object data can be routed using ODBC directly to the back-end SQL database. This option is best used when the database is close to the current location.
- Core data can be forwarded to another Messaging Server. This option is used to place the objects as close as possible to the SQL database, before ODBC posting, in order to avoid slow network response.

- Core messages for the Portal can be routed using HTTP to a Portal Zone, or discarded using the built-in `/dev/null` location.

The `core.dda.cfg` file has the following main sections:

- **msg::register core**

This is the SQLBALANCER type for the `core.dda` configuration. Routes all messages for a given device to a single sub-queue based on the host name, with a single worker process processing the data in the queue.

The parameters are summarized below:

- DIR defines the full path of the `/data/core` location. This is set at installation time.
- USE defines where the routing information for each TO label is located.
- POLL and COUNT establish the polling interval and post quantity for the Messaging Server, which determines how often and how many messages are posted at a time. To adjust this, see the topic "[Configuring the Poll Interval and Post Quantity](#)" (on page 34).
- Retry Attempts (DELAY and ATTEMPTS), after maximum retry attempts, a message is automatically discarded

- **msg::register core.odbc**

This is the SQL type. Routes messages to sub-queues based on the hostname. Defines a DSN, User, and Password to post core data directly to an ODBC database. For details on the entries, see the topic "[ODBC Settings for CORE, INVENTORY and WBEM Objects](#)" (on page 32).

- **(Optional) Configure the maximum log size and number of logs**

Note that these options apply for each Worker assigned to process the specific queue. For more details, see "[Configuring the Log Level, Log Size and Number](#)" (on page 36).

## ODBC Settings for CORE, INVENTORY and WBEM Objects

The following settings are configured in the `msg::register core.odbc` section of `core.dda.cfg`:

DSN	Specify the Data Source Name (DSN) for the Inventory ODBC database. Enclose the entry in quotes.
USER	Specify the user name for the Inventory ODBC database identified in the DSN parameter.
PASS	Specify the password for the user of the Inventory ODBC database. When modifying a password entry, obtain an encrypted entry using the procedure <a href="#">To encrypt a password entry for a database DSN in a configuration file</a> . Both AES (the installation default) and DES password encryption methods are supported.
DSN_ ATTEMPTS	Number of attempts to connect to the Inventory Manager database DSN. Default is 1.
DSN_ DELAY	Delay in seconds between attempts to connect to the Inventory Manager database DSN. Default is 5 seconds.
DSN_ PING	Delay in seconds between pings to the database connection to verify the DSN is available. Default is 300 seconds.
AUTOCREATE	A switch to enable the creation of a new SQL file and table in the Inventory



	ODBC database when a new object class is received. Default is 0. 0 – Does not create a SQL file or table entry for a new object class. 1 – Creates a new SQL file and table entry for a new object class.
STARTUPLoad	No longer supported; any coded value is ignored. <b>Note:</b> The SQL tasks to create the tables and load the scripts for the Inventory Database are always performed upon Messaging Server and Data Delivery Agent startup.
SQLPATH	The path where the schemas are stored.
MAPPATH	The path where the mappings (*.tcl files) are stored.
WBEM-PKEYS	If true, enables creation of WBEM tables on demand with primary keys instead of unique indexes.
ARCHIVE	Enables archiving of messages. If enabled, the messages are moved to the Archive location.
REJECTS	Moves the messages to the REJECTS handler. The messages that fail to get processed, after maximum number of attempts have been tried to deliver this message, are moved to the REJECTS handler.
VALIDATE_NLS_PARAMS	The NLS connection setting that can be set for Oracle.

## About the Sections in the PATCH.DDA.CFG File

The `patch.dda.cfg` file defines where and how to route the objects placed in the `\data\patch` queue location. Most of the configuration is done automatically during the installation of the Messaging Server.

The `patch.dda.cfg` file has the following main sections after the header and required lines:

```
# DO NOT REMOVE FOLLOWING LINE
package require nvd.msg.patchodbc
package require nvd.msg
```

- **msg::register patchq**

This is the QUEUE type for the `patch.dda.cfg`. Defines how the Messaging Server handles the messages placed by QMSG in the `/data/patch` location (or `/data/patch` queue). The parameters are summarized below:

- TYPE of QUEUE defines a Messaging Server location and polling values for picking up messages.
- DIR defines the full path of the `/data/patch` message location. This is set at installation time.
- USE defines where the routing information for the TO PATCH objects are located.

- POLL and COUNT establish the polling interval and post quantity for the Messaging Server, which determines how often and how many messages are posted at a time. To adjust this, see the topic "[Configuring the Poll Interval and Post Quantity](#)" (on page 34).
- Retry Attempts (DELAY and ATTEMPTS), after maximum retry attempts, a message is automatically discarded
- **msg::register patchrouter**  
This is the ROUTER type for the `patch.dda.cfg`. Configures routing assignments for each –To patch type of message. At least one route is specified for each –To type:  
-To PATCH  
  
-To PATCH5
- **msg::register patchddasummarize**  
Translates any ZOBJSTAT patch reporting objects from pre-5.0 agents into the PATCH reporting objects used in Version 5.0 or higher patch reporting. Not configurable.
- **msg::register patchddaodbc**  
Defines a DSN, User, Password and DBTYPE to post patch data directly to an ODBC database. For details on the entries, see "[ODBC Settings for PATCH Objects](#)" (on page 34).  
**Note:** This section may be pre-configured during the install.
- **(Optional) Configure the maximum log size and number of logs.**  
Note that these options apply for each Worker assigned to process the specific queue. For more information, see "[Configuring the Log Level, Log Size and Number](#)" (on page 36).

## ODBC Settings for PATCH Objects

The following settings are configured in the **msg::register patchddaodbc** section of `patch.dda.cfg`:

DSN	Specify the Data Source Name (DSN) for the Patch Manager ODBC database. Enclose the entry in quotes.
USER	Specify the user name for the Patch Manager ODBC database identified in the DSN parameter. Enclose the entry in quotes. Default value is {sa}.
PASS	Specify the password for the user of the Patch Manager ODBC database. Enclose the entry in quotes.
DBTYPE	Specify <code>SMSSQL</code> for a Microsoft SQL Server, or <code>ORACLE</code> for an Oracle SQL Database. Enclose the entry in quotes. Default is <code>MSSQL</code> .

## Additional Tuning Topics

### Configuring the Poll Interval and Post Quantity

By default, the Messaging Server is configured to poll the queue location every 10 seconds and post up to 100 objects at a time. To change the poll interval, modify the POLL parameter in the appropriate configuration file and `msg::register` section with a TYPE of QUEUE.

To change the maximum number of objects to be posted at a time, modify the COUNT parameter in the same section.

If the objects being posted are very large, HP recommends increasing the POLL interval to give sufficient time to complete the posting.

## Configuring for Retry Attempts

The Messaging Server and the Data Delivery Agents are configured to retry any message that fails to post. By default, the Messaging Server will retry posting the message every hour, and make up to 200 attempts. These values are defined by the DELAY and ATTEMPTS entries in the sections of the configuration files that have a TYPE of QUEUE. See the table "[Configuration File and Section Used to Modify Queue Processing](#)" for a list of msg::register sections used to modify QUEUE processing.

**Note:** After the last attempt, the message is automatically discarded from the queue without being posted.

To calculate the maximum time that a message could stay in the `/data/default` queue, take the DELAY time and multiply it by the ATTEMPTS value. Using the default settings, this is a DELAY of 3600 seconds x 200 ATTEMPTS, or approximately eight days.

You can adjust the DELAY and ATTEMPTS values in configuration files to establish a different maximum time that a message could stay in the `/data/default` queue. Specify the DELAY in seconds.

## Configuring for Failover

You can configure the Messaging Server with one or more servers defined for failover support when defining HTTP types. When defining failover servers, each one is assigned a PRI value. If the Messaging Server fails to connect with the first server (that is, the server with the lowest PRI value) it will try the next server on the list (or, the next higher PRI value).

**Note:** This PRI value is separate from the `-priority` value assigned by QMSG for processing priority. The PRI value and the QMSG `-priority` value are not related.

To set failover in a `*.dda.cfg` file:

Failover support is added by inserting additional ADDRESS entries to the appropriate section of an HTTP type in a DDA `cfg` file.

The URL entries will be tried in order of PRI (priority) starting with the *lowest* PRI value.

The code sample below shows sample modifications to the `msg::register rim` section of `core.dda.cfg` for failover. The code in **bold** was added to define a failover server for Inventory Manager processing.

```
msg::register rim {
    TYPE          HTTP
    ADDRESS       {
        PRI       10
        URL       http://rim1:3466/proc/rim/default
    }
    ADDRESS {
        PRI 20
        URL http://rim2:3466/proc/rim/default
    }
}
```

## Configuring the Log Level, Log Size and Number

The log files for the Messaging Server (`rms.log`) reside in the Logs folder of the `MessagingServer` directory,

```
<InstallDir>\ConfigurationServer\MessagingServer\logs.
```

### Changing the Logging Level

The `log::init` section at the beginning of the configuration file establishes the logging level for all Messaging Server logging. The default logging level is 3. Valid levels are 0 (no logging) to 10 (maximum logging level). Normally, the log level is not changed unless requested by a customer support person for troubleshooting purposes. The following lines show the log level increased to 4:

```
log::init {  
    -loglevel 4  
}
```

### Changing the Size and Number of Log Files

The Messaging Server writes entries to a set of log files for each WORKER. There is generally one WORKER attending each queue location. Queue locations include:

```
\data\core  
\data\inventory  
\data\patch  
\data\wbem
```

or

```
\data\default
```

By default, the Messaging Server creates and retains seven log files per worker, each file having a maximum of 5000 lines. The log files are located in the Messaging Server `\logs` directory.

The following line in the `rms.cfg` file establishes the default logging:

```
-loglines 200000
```

To control the size and number of logs created for each worker, add or modify the following entries below the `log::init` section of the `rms.cfg` file:

```
-loglines maximum_lines  
-loglimit maximum number of logs
```

where *maximum\_lines* is the maximum number of lines for a given log file. After the maximum is reached, another log file is created, until the *maximum number of logs* specified in the `log.configure` `-size` entry is reached. After the maximum number of logs is reached, the oldest log files are deleted.

The next code sample illustrates an `RMS.CFG` file containing entries to limit each log file to 1000 lines, and allow up to 10 log files to be retained.

```
log::init {  
    -loglevel 3  
    -loglines 1000  
    -loglimit 10  
}
```

## Configuring the Messaging Server to Discard or Drain Messages

The location of `/dev/null` is built into the Messaging Server for discarding messages. When the `USE` parameter is set to `/dev/null` in any of the `ROUTER` type sections of the Messaging Server or Data Delivery Agent configuration files, the messages being processed will be successfully discarded without an error.

### Example: Discarding messages for the Portal

For example, to discard all RMP messages placed in the `\data\core` queue (these messages have a `TO` label of `CORE.RMP`), specify the following `ROUTE` in the `msg::register corerouter` section of `core.dda.cfg`:

```
msg::register corerouter {
    TYPE      ROUTER
    . . .
    ROUTE     {
                TO      CORE.RMP
                USE      /dev/null
            }
}
```

### Example: Draining a Message Queue

As another example, to quickly drain an entire queue, temporarily replace `USE router` in the `msg::register` section for the queue with `USE /dev/null`. See the table ["Configuration File and Section Used to Modify Queue Processing"](#) for a list of the configuration files and sections that control each queue type. After draining the queue, reset it back to `USE router`.

## Configuring the Messaging Server to Route Portal Messages

### About the Portal Data Queue (rmpq) in CORE.DDA.CFG

The default `core.dda.cfg` configuration re-queues `CORE` messages that are to be posted to the Portal directory into its own queue, named `rmpq`. This allows for separate throttling of the `CORE` messages being posted via `HTTP` to the Portal directory, as opposed to the `CORE` messages being posted using `ODBC` to another database.

The following code shows the sections from `core.dda.cfg` used for this purpose.

```
# Requeue and process just RMP data to throttle the data flow
msg::register rmpq {

    TYPE      QUEUE

    DIR      ../ConfigurationServer/data/rmp
    USE      rmpqrouter

    POLL     10
    COUNT    30
    DELAY    3600
    ATTEMPTS 200
}

msg::register rmpqrouter {
```

```

TYPE          ROUTER

ROUTE        {
TO           CORE.RMP
USE          rmpqhttp
}
}

msg::register rmpqhttp {
TYPE         HTTP

ADDRESS      {
PRI          10
URL          http://localhost:3471/proc/xml/obj
}
}

```

## Restoring Routing for Portal Messages

If you initially installed the Messaging Server to discard Portal messages, use the steps below to begin routing Portal data to a Portal Server and Port.

To modify `core.dda.cfg` for posting Portal data:

1. Use a text editor to edit the `core.dda.cfg` file, located in the `etc` folder of the Messaging Server directory.
2. Look for the section starting with `msg:register corerouter`, and then find the entry for the ROUTE defining `CORE.RMP` messages. The Portal data that is being discarded will show the following entry with a USE value set to `/dev/null`:

```

ROUTE        {
TO           CORE.RMP
USE          /dev/null
}

```

3. Change the USE value from `/dev/null` to `rmpq`, as shown below:

```

TO           CORE.RMP
USE          rmpq

```

4. Next, locate the `msg::register rmpqhttp` section near the end of the `core.dda.cfg` file, and find the default URL entry, shown below:

```

msg::register rmpqhttp {
TYPE         HTTP

ADDRESS      {
PRI          10
URL          http://localhost:3466/proc/xml/obj
}
}

```

5. Edit the URL value of `localhost:3466` to indicate the host and port of your Portal server. For example, a Portal with a hostname of `PORTALSVR` on port 3471 is defined with the following URL entry:

```

URL          http://PORTALSVR:3471/proc/xml/obj

```

Host names can be specified using an IP address or a DNS name.

6. Save your changes and restart the Messaging Server.

## Enhancing Messaging Server Performance

If the Messaging Server posts large amount of objects to the ODBC and the Portal, the Portal throughput for Messaging Server object degrades. To improve Messaging Server performance for posting objects to the Portal, apply the following configurations in the `rmp.cfg` file. The modified configuration decouples the Messaging Server object posting to the Portal from Messaging Server's main ODBC path. The Messaging Server stores the Portal outbound objects to the disk. The Portal then invokes a separate thread dedicated for processing these messages at its own pace.

The Messaging Server posts the messages into the Portal queue; the Portal then initiates a thread that reads from this folder and updates the destination (Database, OpenLDAP, or Configuration Server database).

These configuration should be applied only to the core Messaging Server.

To improve the Messaging Server performance for posting objects to the Portal, complete the following steps:

1. Stop the HPCA Portal service.
2. Add the following parameters in the `<InstallDir>/ManagementPortal/etc/rmp.cfg` file in the `rmp::init { }` block:

```
ENABLE_RMSQUEUE 1
RMSQUEUE_PATH
RMSQUEUE_REJECTS_PATH
```

where,

`RMSQUEUE_PATH` is the path to the Messaging Server folder where the Portal objects are stored.

`RMSQUEUE_REJECTS_PATH` is the path to the rejects folder

For example:

```
ENABLE_RMSQUEUE 1
RMSQUEUE_PATH {<InstallDir>/Data/MessagingServer/rmp}
RMSQUEUE_REJECTS_PATH {<InstallDir>/Data/MessagingServer/rejects}
```

3. Add the following line of code in the `<InstallDir>/HPCA/ManagementPortal/etc/HPCA-RMP.rc` file in the Overrides Config `{ }` block:

```
RMS_STORE_SUBSCRIBERS 0
```
4. Restart the HPCA Portal Service.
5. Ensure that `ATTEMPTS` is set to the desired value in the `<InstallDir>/HPCA/ManagementPortal/etc/rms.cfg` in the `msg::register rmp { }` block.

## Disabling Processing of Messages in a Queue

The objects in a disabled queue are not polled or posted. You may want to disable processing during peak agent connect periods if resources are in contention, or if you know a target server is down.

You can re-enable the processing at night or during slower periods to allow the Messaging Server to transfer the messages.

To disable queue processing using `WORKERS -1` (minus 1) value:

To disable a queue from being polled and its contents posted, set a WORKERS value of -1 (minus one) at the end of the appropriate msg::register section for that queue.

### Configuration File and Section Used to Modify Queue Processing

Queue	Configuration File in MessagingServer\etc folder	msg::register section
\data\core	core.dda.cfg	msg::register coreq
\data\inventory	core.dda.cfg	msg::register inventoryq
\data\patch	patch.dda.cfg	msg::register patchq
\data\wbem	wbem.dda.cfg	msg::register wbemq
\data\default (in earlier Versions)	rms.cfg	msg::register default

To add a WORKERS value to create multiple processes (WORKERS):

1. Use a text editor to open the appropriate \*.cfg file for the Messaging Server or Data Delivery Agent processing the queue to be disabled. The table "[Configuration File and Section Used to Modify Queue Processing](#)" identifies the configuration file to use for each queue type.
2. Locate the 'msg::register' section named in the table "[Configuration File and Section Used to Modify Queue Processing](#)"; it will be defined with { TYPE QUEUE }.
3. Add or modify a line for WORKERS with a value of -1 (minus 1) to the end of the section. A sample entry for disabling a wbem queue is shown below with a WORKERS value of -1.

```
msg::register wbemq {
  TYPE    QUEUE

  DIR     C:/Progra~/Hewlet~/CM/ConfigurationServer/data/wbemq
  USE     router

  POLL    10
  COUNT   100
  DELAY   3600
  ATTEMPTS 200
  WORKERS -1
}
```

4. Save your changes and exit the editor.

To enable a disabled queue:

To enable a previously disabled queue, change the WORKERS value in the msg::register section of appropriate configuration file from -1 to 1. The number of WORKERS indicates the number of independent and lightweight processes to be started for this queue. The default configuration uses 1, which is the HP-recommended value for a Messaging Server that is processing multiple queues with Data Delivery Agents.



## Modifying the Priority in which Messages are Processed

**Note:** With the adoption of specific queues for each object type, the priority feature is no longer applicable. However, the code for processing messages in increasing priority order has not been disabled.

To modify the priority in which messages are processed, see the earlier topic "[How Priority Establishes Messaging Server Processing Order](#)" (on page 21).



## Troubleshooting the Messaging Server

**Caution:** If your environment uses Core and Satellite servers, first read the *HP Client Automation Enterprise Edition Getting Started and Concepts Guide* as the installation, configuration, and troubleshooting information in that guide may override the information in this guide.

The Messaging Server log file is located in the Logs directory of the root `MessagingServer` installation directory.

Review the common error messages and solutions given in this section to troubleshoot Messaging Server problems.

Failed posts can be the result of the line `sql::init` being commented out in one or more files in the `/etc/sql` folder of your Messaging Server's installation directory.

### Problem 1: Log indicates no route defined or failed delivery

Your Messaging Server log includes WARNING and ERROR messages indicating 'no route defined for default' and 'failed to deliver to default', as shown below.

```
Warning: router1: To: default, From: <CM-CS>@<CM-CS_hostname>,
subject: - no route defined for default
Error: MSG/QUEUE: q2: To: default, From: <CM-CS>@<CM-CS_hostname>,
subject: - failed to deliver to default
```

#### Solution:

These messages indicate that one or more QMSG calls in ZTASKEND are missing a `-to` parameter and or value. When this happens, the word 'default' becomes the `-to` value for that message. Since the Messaging Server does not have a route defined for messages labeled with a `-to` value of default, it cannot route the message and writes these warning and error messages to the log.

The solution is to review the QMSG calls in ZTASKEND and add any missing `-to` parameters or missing values. As delivered, QMSG `-to` values include: `-to core.rim`, `-to core.rmp`, `-to inventory`, and `-to inventory.wbem`, although there may be others. For details, see the ["QMSG Method Syntax" \(on page 19\)](#).

### Problem 2: Log indicates DB connect failed with a Unix DataDirect driver – check ODBCINI

#### Solution:

When using a Unix (HP-UX or Solaris) DataDirect driver, your Messaging Server log includes the following ERROR message:

```
Error: MSG/SQL<coreodbc> DB: connect failed: IM002 0
{[DataDirect][ODBC lib]
System information file not found. Please check the ODBCINI
environment
variable.
```

This error is returned from a lower level, third party API.

The ODBCINI environment variable for your Unix Data Direct ODBC driver is not set properly. The error is likely caused by one of the following reasons:

1. `ODBCINI` is not set in the environment.  
Test this by running: `cat $ODBCINI`  
If the `ODBCINI` file is not written to the terminal then either the value does not exist or it is pointing to the wrong location.
2. `ODBCINI` is not exported.  
If you are unsure, re-export with the following command:  
`export ODBCINI`
3. `ODBCINI` is set and exported but the DSN given does not exist in the `ODBCINI` file.  
This could be caused by improperly quoted strings. (Single quotes are not allowed.) Either use double quotes (") or braces {} to delimit the DSN if it contains spaces. DSN delimiters are not needed if the DSN does not contain spaces.

After correcting the `ODBCINI`-related error, restart the service for the Messaging Server.

**Problem 3: You receive Error 404 (page not found) or error 500 (server internal error) for all attempted posts to a the Messaging Server**

**Solution:**

Review the `*.sql` files located in the `/etc/sql` folder of your Messaging Server. Check the bottom of your `sql` files to see if there is a commented out section that looks like:

```
#sql::url . . .
```

The solution for Error 404 or Error 500 is to remove the # (pound sign) to un-comment this line.

- If you do not have any customizations, you can move all of the `*.sql` files out of the `/etc/sql` directory (place them in an outside location), and then stop and start the Messaging Server. This unpacks the new `.sql` files, which should fix the error.
- If you have more than one customization, use the following steps to correct the problem and still keep your customizations:
  - a. Locate any `*.sql` files that you have customized in the `/etc/sql` folder.  
**Note:** The HP-delivered default `.sql` files will be located in the `/etc/sql/hp` directory.  
The data delivery agents will load the customized files from the `/etc/sql` directory first, if a file is not found in the `/etc/sql` directory, it loads it from the `/etc/sql/hp` directory. Therefore the customized files will always take precedence over the default files.
  - b. Delete the remaining `*.sql` files from the `/etc/sql/hp` folder.
  - c. Restart the Messaging Server to unpack a new set of `*.sql` files into the default location of `/etc/sql/hp`.
  - d. Go to where you placed the customized `*.sql` files, and un-comment the `sql::url` line at the bottom of each file.
  - e. Restart the HPCA Messaging Server service.

## **We appreciate your feedback!**

If an email client is configured on this system, by default an email window opens when you click [here](#).

If no email client is available, copy the information below to a new message in a web mail client, and then send this message to [docfeedback@hp.com](mailto:docfeedback@hp.com).

**Product name and version:** HP Client Automation Enterprise Messaging Server, 8.10

**Document title:** Reference Guide

**Feedback:**

**Reference Guide**

We appreciate your feedback!

---