

WinRunner®  
*TSL Reference Guide*  
Version 6.0



## **TSL Reference Guide, Version 6.0**

**© Copyright 1994 - 1999 by Mercury Interactive Corporation**

All rights reserved. All text and figures included in this publication are the exclusive property of Mercury Interactive Corporation, and may not be copied, reproduced, or used in any way without the express permission in writing of Mercury Interactive. Information in this document is subject to change without notice and does not represent a commitment on the part of Mercury Interactive.

Mercury Interactive may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents except as expressly provided in any written license agreement from Mercury Interactive.

WinRunner, XRunner, LoadRunner, TestDirector, TestSuite, and WebTest are registered trademarks of Mercury Interactive Corporation in the United States and/or other countries. Astra, Astra SiteManager, Astra SiteTest, RapidTest, QuickTest, Visual Testing, Action Tracker, Link Doctor, Change Viewer, Dynamic Scan, Fast Scan, and Visual Web Display are trademarks of Mercury Interactive Corporation in the United States and/or other countries.

This document also contains registered trademarks, trademarks and service marks that are owned by their respective companies or organizations. Mercury Interactive Corporation disclaims any responsibility for specifying which marks are owned by which companies or organizations.

If you have any comments or suggestions regarding this document, please send them via e-mail to documentation@mercury.co.il.

**Mercury Interactive Corporation  
1325 Borregas Avenue  
Sunnyvale, CA 94089 USA**

---

# Table of Contents

Welcome to TSL.....	v
Using this Guide.....	v
WinRunner Documentation Set.....	vi
Online Resources.....	vi
Typographical Conventions.....	viii
Chapter 1: Introduction .....	1
Function Types .....	2
Analog Functions.....	3
Context Sensitive Functions .....	3
Customization Functions.....	5
Standard Functions.....	5
Chapter 2: Language.....	7
Variables and Constants .....	7
Operators and Expressions .....	12
Statements .....	17
Control Flow.....	18
Arrays.....	22
Input-Output .....	28
Comments .....	29
Built-in Functions.....	29
User-Defined Functions.....	30
External Function Declarations.....	32
Chapter 3: Reserved Words .....	35
Chapter 4: Functions by Category .....	39
Analog Functions.....	40
Context Sensitive Functions .....	42
Customization Functions.....	77
Standard Functions.....	80

<b>Chapter 5: Return Values .....</b>	<b>97</b>
General Return Values.....	98
Return Values for Database Functions .....	102
Return Values for PowerBuilder and Table Functions .....	103
Return Values for Terminal Emulator Functions.....	104
<b>Chapter 6: Alphabetical Reference .....</b>	<b>105</b>
<b>Index.....</b>	<b>469</b>

---

# Welcome to TSL

Welcome to TSL, Mercury Interactive's Test Script Language (TSL).

## Using this Guide

This book is a comprehensive guide to Mercury Interactive's Test Script Language (TSL). It provides a detailed description of TSL and how to use it in your test scripts. It lists all TSL functions alphabetically and by category, and describes the parameters, return values, and availability for each function. This book assumes that you are already familiar with WinRunner. For information on using WinRunner, see the *WinRunner User's Guide*.

This book contains the following sections:

### **Introduction**

Provides an overview of TSL and the different types of TSL functions. Read this section to learn which groups of TSL functions are relevant for your product.

### **Language**

Describes the basic elements of the TSL programming language, such as: constants and variables, operators and expressions, statements, control-flow, arrays, input/output.


### **Functions by Category**

Provides a list of TSL functions grouped according to the type of tasks they perform. Functions are arranged alphabetically within each category, and a brief description of each function is included.

### **Alphabetical Reference**

Lists all TSL functions alphabetically. The name of each function is listed along with the type and the category to which it belongs. A description and complete syntax are provided. The definition of the function's parameters and its return values and availability are also described.

## WinRunner Documentation Set



In addition to this guide, WinRunner comes with a complete set of documentation:

**WinRunner Installation Guide** describes how to install WinRunner on a single computer or a network.

**WinRunner Tutorial** teaches you basic WinRunner skills and shows you how to start testing your application.

**WinRunner User's Guide** explains how to use WinRunner to meet the special testing requirements of your application.

**WinRunner Customization Guide** explains how to customize WinRunner to meet the special testing requirements of your application.

**WebTest User's Guide** teaches you how to use the WebTest add-in to test your Web site.

## Online Resources

WinRunner includes the following online resources:

**Read Me First** provides last-minute news and information about WinRunner.

**What's New in WinRunner** describes the newest features in the latest versions of WinRunner.

**Books Online** displays the complete documentation set in PDF format. Online books can be read and printed using Adobe Acrobat Reader 4.0, which is included in the installation package. Check Mercury Interactive's Customer Support web site for updates to WinRunner online books.

**WinRunner Context-Sensitive Help** provides immediate answers to questions that arise as you work with WinRunner. It describes menu commands and dialog boxes, and shows you how to perform WinRunner tasks. Check Mercury Interactive's Customer Support Web site for updates to WinRunner help files.

**TSL Online Reference** provides additional information on each function and examples of usage. You can open the *TSL Online Reference* from the WinRunner group in the Start menu or from WinRunner's Help menu. To open the online reference to a specific function, click the context-sensitive Help button and then click a TSL statement in your test script, or place your cursor on a TSL statement in your test script and then press the F1 key. Check Mercury Interactive's Customer Support Web site for updates to the *TSL Online Reference*.

**WinRunner Sample Tests** includes utilities and sample tests with accompanying explanations. Check Mercury Interactive's Customer Support Web site for updates to WinRunner help files.

**Technical Support Online** uses your default Web browser to open Mercury Interactive's Customer Support Web site.

**Support Information** presents Mercury Interactive's Customer Support Web site and home page, the e-mail address for requesting information, the name of the relevant news group, the location of Mercury Interactive's public FTP site, and a list of Mercury Interactive's offices around the world.

**Mercury Interactive on the Web** uses your default Web browser to open Mercury Interactive's home page. This site provides the most up-to-date information on Mercury Interactive and its products. This includes new software releases, seminars and trade shows, customer support, educational services, and more.

## Typographical Conventions

This book uses the following typographical conventions:

<b>Bold</b>	<b>Bold</b> text indicates function names and the elements of the functions that are to be typed in literally.
<i>Italics</i>	<i>Italic</i> text indicates variable and parameter names.
Helvetica	The Helvetica font is used for examples and statements that are to be typed in literally.
[ ]	Square brackets enclose optional parameters.
{ }	Curly brackets indicate that one of the enclosed values must be assigned to the current parameter.
...	In a line of syntax, three dots indicate that more items of the same format may be included. In a program example, three dots are used to indicate lines of a program that have been intentionally omitted.
	A vertical bar indicates that either of the two options separated by the bar should be selected.

# 1

---

## Introduction

The scripts you create with Mercury Interactive systems are written in Test Script Language (TSL). TSL is an enhanced, C-like programming language designed for testing. At the heart of Mercury Interactive's integrated testing environment, TSL is high-level and easy to use. It combines the power and flexibility of conventional programming languages with functions specifically developed for use with Mercury Interactive's products. This enables you to modify recorded material or to program sophisticated test suites.

This reference manual is intended to help you read, edit, and write TSL scripts. It contains a description of the programming language capabilities of TSL and a list of TSL functions.

This chapter provides overviews about:

- Function Types
- Analog Functions
- Context Sensitive Functions
- Customization Functions
- Customization Functions

## Function Types

There are four types of TSL functions. Each type of function addresses a different requirement.

Function Type	Requirement
Analog	perform mouse and keyboard input
Context Sensitive	perform operations on GUI objects
Standard	perform basic programming-language operations
Customization	configure the testing tool according to your requirements

The functions that are available depend on which testing product you are using.

**WinRunner:** If you work with WinRunner, you can use functions from all of the categories. Some functions are supported only when working with applications developed in a specific environment such as PowerBuilder or Visual Basic. To check the availability of a specific function, click the Availability button at the top of the Help screen for that function.

**LoadRunner GUI Vusers on PC platforms:** This type of GUI Vuser uses WinRunner to create system load. For this reason, you can use functions from any of the categories. You can also use the LoadRunner functions described in the “GUI Vuser Scripts” section of the *LoadRunner Creating Virtual User Scripts User's Guide for Windows and UNIX Platforms*.

**LoadRunner Scenarios:** In LoadRunner scenario scripts (UNIX only), you can use standard functions in addition to the LoadRunner functions described in the *LoadRunner Controller User's Guide*.

## Analog Functions

*Analog functions* record and execute operations at specified screen coordinates. When you record in Analog mode, these functions are used to depict mouse clicks, keyboard input, and the exact coordinates traveled by the mouse. When you run a test, Analog functions retrace the mouse tracks and exactly resubmit the input you recorded. Analog functions also support different test operations such as synchronization, verification, and text manipulation.

Analog functions are available for:

- WinRunner
- LoadRunner GUI Vusers on PC Platforms

### Coordinate and Numbering Conventions

Many of the Analog functions refer to screen coordinates. In the system of coordinates used by Mercury Interactive's products, the origin (0,0 coordinate) is located in the upper left corner of the screen. The maximum value of x is the width of the screen, in pixels, minus one. The maximum value of y is the height of the screen, in pixels, minus one.

## Context Sensitive Functions

*Context Sensitive functions* depict actions on the application under test in terms of GUI objects (such as windows, lists, and buttons), ignoring the physical location of an object on the screen. In Context Sensitive mode, each time you record an operation on the application under test (AUT), a TSL statement is generated in the test script which describes the object selected and the action performed.

Context Sensitive functions are available for:

- WinRunner
- LoadRunner GUI Vusers on PC Platforms

## Context Sensitive Object Naming Conventions

Most Context Sensitive functions include parameters which refer to an object's logical name.

Note that you can replace the logical name of the object with the physical description. During recording, the logical name is automatically used by the system. However, the function will also work with the physical description of the object.

For example, the syntax of **button\_press** function is:

```
button_press ( button [, mouse_button ] );
```

The *button* parameter may be the logical name of the button—for example:

```
button_press("OK");
```

But it can also be the physical description—for instance:

```
button_press("{class:push_button, label:\"OK\"}");
```

## Numbering Conventions

Numbering for most Context Sensitive functions starts from 0. For example, the function **list\_get\_item** returns 0 for the first item of the given list.

Position coordinates for the "edit" Context Sensitive functions, such as **edit\_get\_info**, are denoted by row and column. The first row is numbered "0." Columns are denoted by insertion position, not by character index. In other words, the position before the first character in any line is "0", the position between the first and second characters is "1", and so on.

## Customization Functions

*Customization functions* allow you to enhance your testing tool so that it better supports your specific needs. For example, you can add functions to the Function Generator, or create custom GUI checkpoints.

Customization functions are available for WinRunner.

## Standard Functions

*Standard functions* include the general elements of a programming language, such as basic input and output, control-flow, mathematical, and array functions. By combining these elements with Analog and Context Sensitive functions, you can transform a simple test into an advanced testing program.

Standard functions are available for all Mercury Interactive products.



# 2

---

## Language

This appendix describes the basic elements of the TSL programming language, including:

- Variables and Constants
- Operators and Expressions
- Statements
- Control Flow
- Arrays
- Input-Output
- Comments
- Built-in Functions
- User-Defined Functions
- External Function Declarations

### Variables and Constants

Variables and constants may be either strings or numbers. Declaration is optional; if variables are not declared, their type is determined at run time according to their context.

Variable names can include English-language letters (a-z and A-Z), digits, and underscores (\_). The first character must be a letter or an underscore. TSL is case-sensitive; *y* and *Y* are therefore two different characters. Note that names of built-in functions and keywords (such as *if*, *while*, *switch*) cannot be used as variable names.

## Types of Variables and Constants

TSL supports two types of constants and variables: *numbers* and *strings*.

Numbers may be either integer or floating point, and exponential notation is also acceptable. For example, -17, .05, -3e2, and 3E-2 are all legal values.

Strings consist of a sequence of zero or more characters enclosed within double quotes. When a backslash (\) or double-quote ("') character appears within a string, it must be preceded by a backslash. Special characters can be incorporated in a string using the appropriate representation:

backspace	\b	vertical tab	\v
carriage return	\r	newline	\n
formfeed	\f	octal number	\ooo
horizontal	\t		

In the case of octal numbers, the zeroes represent the ASCII code of a character. For example, "\126" is equivalent to the letter "v."

For example, to represent the string "The values are: 12 14 16", type:

```
"\"The values are:\t12\t14\t16\""
```

At a given moment, the value of a constant or variable can be either a string or a number. The TSL interpreter determines the type according to the operation performed. For example:

```
x = 123;  
s = x & "Hello";  
y = x + 1;
```

Variable *x* is assigned the value *123*. In the second statement, because the operation is concatenation (&), *x* is treated as a string. The interpreted value of *s* is therefore *123Hello*. In the third line, because the operation is addition, *x* is treated as a number. Variable *y* is therefore assigned the value *124*.

In the case of an expression where a mathematical operation is performed on a string, such as

```
"6RED87" + 0
```

the numeric value of the string is the first part of the string that can be evaluated to a number. Here, the numeric value of the expression is 6.

Since relational operators are valid for both strings and numbers, a numeric comparison is always performed if both operands can be evaluated to a number. For instance, in the relational expression below,

```
"0.01" == "1e-2"
```

although both constants are written like strings (enclosed within quotation marks), both expressions are also valid numbers so a numeric comparison is performed. But in the next expression,

```
"0.01" == "1f-2"
```

the second expression is not a number, so a string comparison is performed.

### Undeclared Variables

If a variable is not declared, it is created implicitly when it is assigned or used in an expression. If a variable is not initialized, it is given the string value "" (null) at run time.

All undeclared variables are global, unless they are on the formal Parameter List of a called test. For more information on parameters, see the *WinRunner User's Guide*.

### Variable Declarations

Note that while constant and variable declarations are optional in tests, they are required in user-defined functions. Variable declarations have the following syntax:

```
class variable [= init_expression];
```

The *init\_expression* assigned to a declared variable can be any valid expression. If an *init\_expression* is not set, the variable is assigned an empty string. The variable *class* can be any one of the following:

**auto:** An auto variable can only be declared within a function and is local to that function. It exists only while the function is running. A new copy of the variable is created each time the function is called.

**static:** A static variable is local to the function, test, or compiled module in which it is declared. The variable retains its value until the test is terminated by a Stop command.

**public:** A public variable can only be declared within a test or module, and is available for all functions, tests, and compiled modules.

**extern:** An extern declaration indicates a reference to a public variable declared outside of the current test or module.

With the exception of the auto variable, all variables continue to exist until the Stop command is executed. For example, the statement

```
static a=175, b=get_time( ), c = 2.235;
```

defines three variables (a, b, and c), and assigns each an initial value. This value is retained between invocations of the test. The following script segment demonstrates how a static variable can be used so that a message is printed only the first time that the test, T\_2, is called.

```
static first = 1;  
pause ("first = " & first);  
if (first == 1) {  
    first = 0;  
    report_msg ("Test T_2 was called.");  
}
```

The following table summarizes the scope, lifetime, and location of the variable declarations for each class:

Declaration	Scope	Lifetime	Declare the variable in...
auto	local	end of function	function
static	local	until stop	function, test, or module
public	global	until stop	test or module
extern	global	until stop	function, test, or module

## Constant Declarations

The **const** specifier indicates that the declared value cannot be modified. The syntax of this declaration is:

[ *class* ] **const** *name* [ = *expression* ];

The *class* of a constant may be either public or static. (If no class is explicitly declared, the constant is assigned the default class public.) Once a constant is defined, it remains in existence until the Stop command is executed.

For example, defining the constant TMP\_DIR using the declaration:

```
const TMP_DIR = "/tmp";
```

means that the assigned value /tmp cannot be modified. (This value can be changed only by explicitly making a new constant declaration for TMP\_DIR.)

## Operators and Expressions

TSL supports six types of operators: arithmetical, concatenation, relational, logical, conditional, and assignment. Operators are used to create expressions by combining basic elements. In TSL, expressions can consist of constants, variables, function calls, and other expressions.

### Arithmetical Operators

TSL supports the following arithmetical operators:

+	addition
-	subtraction (unary)
-	subtraction (binary)
*	multiplication
/	division
%	modulus
^ or **	exponent
++	increment (adds 1 to its operand - unary operator)
--	decrement (subtracts 1 from its operand - unary operator)

The result of the modulus operation is assigned the sign of the dividend. For example:

```
7 % -4 = 3  
-4.5 % 4 = -0.5
```

The increment and decrement operators may be placed before the variable (`++n`), or after (`n++`). As a result, the variable is incremented either before or after the value is used. For example:

```
i = 5;  
j = i++;  
k = ++i;  
print(i & j & k);
```

prints the values 7, 5, 7. Note that the increment and decrement operators may be applied only to variables, and not to expressions, such as  $(a + b)$ .

### Concatenation Operator

The ampersand (&) character is used to concatenate strings. For example, the statement

```
x = "ab" & "cd";
```

assigns the string value *abcd* to variable *x*.

### Relational Operators

The relational operators used in TSL are:

>	greater than
>=	greater than or equal to
<	less than
<=	less than or equal to
==	equal to
!=	not equal to

Relational expressions are evaluated to the value 1 if true, and 0 if false. When the value of an expression is null or zero, it is considered false. All other values are considered true.

Strings are compared character by character according to their ASCII value. Letter strings are evaluated in terms of alphabetical order; the string which comes first alphabetically is considered smaller. For instance, “galactic” < “galaxy”.

## Logical Operators

Logical operators are used to create logical expressions by combining two or more basic expressions. TSL supports the following logical operators:

&&	and
	or
!	not (unary)

Logical expressions are assigned the value 1 if true, and 0 if false. When the value of an expression is null or zero, it is considered false. All other values are considered true. Logical expressions are evaluated from left to right, and as soon as the value of an expression is determined, interpretation stops. For example, in the expression

`(g != 0) && (d/g > 17)`

if the first expression is false, then the second expression is not evaluated.

## Conditional Operator

The conditional operator is the ? (question mark) character. Conditional expressions have the format:

`expression1 ? expression2 : expression3`

`expression1` is evaluated first; if it is true, `expression2` is evaluated and becomes the value of the expression. If `expression1` is false (zero or null), then `expression3` is executed and becomes the value of the expression. In the following statement,

`(g != 0) ? 17 : 18;`

if the first expression is true (`g` is not equal to zero), then the value of the conditional expression is 17. If the first expression is false, then the value of the conditional expression is 18.

For more information, see “Control Flow” on page 18.

## Assignment Operators

Assignment operators are used to assign values to variables and arrays. All of the binary arithmetical operators have corresponding assignment operators:

Operator	Example	Meaning
=	a = b	assign the value of <i>b</i> to <i>a</i>
+ =	a += b	assign the value of <i>a</i> plus <i>b</i> to <i>a</i>
- =	a -= b	assign the value of <i>a</i> minus <i>b</i> to <i>a</i>
* =	a *= b	assign the value of <i>a</i> times <i>b</i> to <i>a</i>
/ =	a /= b	assign the value of <i>a</i> divided by <i>b</i> to <i>a</i>
% =	a %= b	assign the value of <i>a</i> modulo <i>b</i> to <i>a</i>
$\wedge=$ or $**=$	a $\wedge$ = b	assign the value of <i>a</i> to the power of <i>b</i> to <i>a</i>

For example, in the following segment of a test script,

```
for (i=0; i<200; i+=20)
    move_locator_abs(i,i);
```

the value of *i* is incremented by 20 after each repetition of the loop. The mouse pointer is then moved to the new position defined by *i*. For more information about for loops see “Control Flow” on page 18.

## Precedence and Associativity of Operators

The rules of precedence and associativity determine the order in which operations are performed when more than one operator appears in an expression. Operators with higher precedence are interpreted before operators with lower precedence. For example, multiplication is performed before addition.

When more than one operator of the same level of precedence appears in an expression, the associativity indicates the order in which they are interpreted. For example, in

`x / 2 + i - q`

division is performed first. Addition is performed before subtraction because the associativity of these operators, which have the same level of precedence, is left to right.

The following table lists the precedence, in descending order, and the associativity of operators:

### Operator (in order of precedence) Associativity

( ) (parentheses)	none
<code>++ --</code>	none
<code>^ **</code>	right to left
<code>! - + (unary)</code>	none
<code>* / %</code>	left to right
<code>+ - (binary)</code>	left to right
<code>&amp;</code>	left to right
<code>&lt; &lt;= &gt; &gt;= == !=</code>	none
<code>in (array operator)</code>	none

&&	left to right
	left to right
?	right to left
=    +=    -=    *=    /=    %=    ^=    **=	right to left

## Statements

Any expression followed by a semicolon is a statement. A statement can continue beyond one line.

In a control-flow structure, a single statement can be replaced by a group of statements, or block. Statements are grouped by enclosing them within curly brackets { }. Each individual statement within brackets is followed by a semicolon, but the brackets themselves are not. This is illustrated below:

```
for (i = 0; i < 10; i++) {
    st = "Iteration number " & i;
    type (st);
}
```

## Control Flow

TSL control-flow statements include:

- *if/else* and *switch* for decision-making
- *while*, *for*, and *do* for looping
- *break* and *continue* for loop modification

### If/Else Statement

TSL provides an *if/else* statement for decision-making. The *else* clause is optional. The syntax of this statement is:

```
if ( expression )
    statement1
[ else
    statement2 ]
```

The *expression* is evaluated; if the value of the *expression* is true (nonzero or non-null), *statement1* is executed; if the value is false (zero or null), and the [*else statement2*] clause is included, *statement2* is executed.

When if statements are nested, the TSL interpreter associates each *else* with the *if* that appears closest to it. For example, a statement such as:

```
if (b1) if (b2) s1; else s2;
```

is interpreted as follows:

```
if (b1) {
    if (b2)
        s1;
    else
        s2;
}
```

## Switch Statement

The *switch* statement provides the mechanism for a multi-way decision. The syntax of this structure is:

```
switch ( expression )
{
    case case_expr1:
        statement(s)
    case case_expr2:
        statement(s)
    case case_exprn:
        statement(s)
    [default: statement(s) ]
}
```

The *switch* statement consecutively evaluates each of the enumerated case expressions (*case\_expr1*, *case\_expr2*,..., *case\_exprn*), until one is found that equals the initial *expression*. If no case expression is equal to the specified *expression*, then the optional default statements are executed.

Note that the first time a case expression is found to be equal to the specified initial *expression*, no further case expressions are evaluated. However, all subsequent statements enumerated by these cases are executed, unless you use a *break* statement within a case to end the loop. For example:

```
switch (a) {
    case "xyz":
        b = a & "tw";
        break;
    case "uv":
        pause ("hello");
        x = a;
        break;
    default:
        x = a;
}
```

Note that while the initial expression can be any regular expression, case expressions can only be constants or variables.

## Looping Statements

TSL provides several statements that enable looping.

```
while ( expression )
    statement
```

While the *expression* is true, the *statement* is repeatedly executed. At the start of each repetition of the loop, the *expression* is evaluated; if it is true (nonzero or non-null), the *statement* is executed, and the *expression* is re-evaluated. The loop ends when the value of the *expression* is false. For example,

```
i = 1;
while (i < 21)
    type (i++);
```

types the value of *i* 20 times.

```
for ( [ expression1 ]; [ expression2 ]; [ expression3 ]; )
    statement
```

First, *expression1* is implemented as the starting condition. While *expression2* is true, the *statement* is executed, and *expression3* is evaluated. The loop repeats until *expression2* is found to be false. This statement is equivalent to:

```
expression1          # state initial condition
while (expression2) {
    statement        # while this is true
    expression3      # perform this statement and
                    # evaluate this expression
}
```

For example, the *for* loop below performs the same function as the *while* loop above.

```
for (i=1; i<21; i++)
    type (i);
```

Note that if *expression2* is missing, it is always considered true, so that

```
for (i=1;i++)
```

```
type (i);
```

is an infinite loop.

```
do
    statement
while ( expression );
```

The *statement* is executed and then the *expression* is evaluated. If the *expression* is true, then the cycle is repeated. This statement differs from the *while* and *for* statements in that the *expression* is evaluated at the end. Therefore, the loop is always executed at least once. For example, in the following statement,

```
i = 20;
do
    type (i++);
while (i < 17);
```

the structure of the loop ensures that the value of *i* is typed at least once.

## Loop Modification

The following statements can be used to exit a loop or to jump to the next iteration.

### **break;**

The *break* statement causes an exit from within a loop. If loops are nested, *break* affects the innermost *for*, *while*, or *do* loop that encloses it.

For example, a *for* loop where *expression2* is undefined can be terminated using *break*:

```
for (i = 1; i++) {
    type (i);
    if (i > 29)
        break;
}
continue;
```

The *continue* statement causes the next cycle of the loop to begin. In a *do/while* loop, execution resumes with the test expression. In a *for* loop, execution resumes with *expression3*. For example:

```
for (i = 1; i<=300; i++) {  
    if (i % 3 != 0) {  
        continue; # to next number  
    }  
    ...          # long processing  
    type(i & "<kReturn>");  
}
```

Here, a certain process should only be performed on every third number. Therefore, if *i* cannot be divided equally by three, execution continues with the next iteration of the loop.

## Arrays

TSL supports associative arrays. Arrays in TSL are unique in that:

- Array declaration and initialization are optional.
- Each element has a user-defined string subscript.

Rather than arrays of fixed length with numeric subscripts, TSL arrays contain an undefined number of elements, each with a user-defined string subscript. For example, the statement

```
capitals["Ohio"] = "Columbus";
```

assigns the value "Columbus" to the element with subscript "Ohio" in the array *capitals*. If array elements are not declared, they are created the first time they are mentioned and the order of the elements in the array is not defined. Any uninitialized array element has the numeric value zero and the string value null ("").

Arrays can be used to store both numbers and strings. In the following test script, an array is used to store a series of dates and times:

```
for (i=0; i<5; i++) {
    date = time_str();
    date_array[i] = date;
    wait(5);
}
```

Here, each array element includes the date and time of the call to the **time\_str** function. The subscript of the array element is the value of *i*.

### Array Declaration

Array declaration is optional within a test but required within user-defined functions (initialization is optional). Using the following syntax, you can define the class and/or the initial expression of an array. Array size need not be defined in TSL.

```
class array_name [ ] [ =init_expression ]
```

The array *class* may be any of the classes listed under Variable Declarations. The *init* expression can take one of two formats: C language syntax, or a string subscript for each element.

An array can be initialized using the C language syntax. For example:

```
public hosts [ ] = {"lithium", "silver", "bronze"};
```

This statement creates an array with the following elements:

```
hosts[0]="lithium"
hosts[1]="silver"
hosts[2]="bronze"
```

Note that, as in C, arrays with the class *auto* cannot be initialized.

In addition, an array can be initialized using a string subscript for each element. The string subscript may be any legal TSL expression. Its value is evaluated during interpretation or compilation. For example:

```
static gui_item [ ]={  
    "class"="push_button",  
    "label"="OK",  
    "X_class"="XmPushButtonGadget",  
    "X"=10,  
    "Y"=60  
};
```

creates the following array elements:

```
gui_item ["class"]="push_button"  
gui_item ["label"]="OK"  
gui_item ["X_class"]="XmPushButtonGadget"  
gui_item ["X"]=10  
gui_item ["Y"]=60
```

## Array Initialization

Arrays are initialized once during a test run. The TSL interpreter maintains the original initialization values throughout the test run. If you edit an array's initialization values, the new values will not be reflected during test execution. To reset the array with new initialization values, perform one of the following:

- stop/abort the test run
- define the array elements explicitly

When you stop the test run, all of the script's variables are destroyed. The next time you execute the script, the array is initialized with the new values.

Alternatively, you can explicitly define an array's elements. When you assign a value to each array element, you ensure that the array is updated

with the new values for each test run. In the following example, the regular array initialization is replaced with explicit definitions:

Regular Initialization	Explicit Definitions
public array[] = {1,2,3};	array[0] = 1; array[1] = 2; array[2] = 3;

## Multidimensional Arrays

TSL supports multidimensional arrays such as `a[i,j,k]`. Multidimensional arrays can be used like records or structures in other languages. For example, the following script uses a multidimensional array to store the date and time:

```
for (i = 0;i < 10; i++) {
    date=time_str();
    split(date,array," ");
    multi_array[i, "day"] = array[1];
    multi_array[i, "time"] = array[4];
    wait(5);
}
```

TSL simulates multidimensional arrays using one-dimensional arrays. The element `multi_array[i1, i2,...,in]` is stored in the one-dimensional array called `multi_array`, in the element `[i1 & SUBSEP & i2 & SUBSEP... & in]`. (The variable `SUBSEP` has the initial value “\034,” but this value may be changed.)

Multidimensional arrays can also be declared and initialized, as described above. For example, a multidimensional array could be initialized as follows:

```
static rectangles [ ] = {
    {153, 212, 214, 437},
    {72, 112, 88, 126},
    {351, 312, 399, 356}
}
```

## The *in* Operator

The *in* operator is used to determine if a subscript exists in an array.

*subscript in array;*

returns the value 1 if the subscript exists, and 0 if it does not. It can be used in a conditional statement, like the one below which checks whether the element with the subscript *new* exists in the array *menu\_array*:

```
if ("new" in menu_array)
```

The operator *in* should be used rather than the following statement:

```
if (menu_array["new"] != "")...
```

because this statement causes the element to be created, if it does not already exist. (Recall that array elements are created the first time they are mentioned.)

The *in* operator can also be used for multidimensional arrays. The subscript of the element is enclosed in parentheses, as in the following statement:

```
if (("new.doc", 12) in multi_array)...  
for ( element in array ) statement
```

causes the *element* to be set to the subscript of each element in the *array*. The statement is executed once for each element of the array, and the loop is terminated when all elements have been considered. The order in which the subscripts are read is undefined. The sample script below reads an array for which each element is a date and time string. A *for* loop is used to print to the screen each of the elements of the array.

```
for (i in date_array)  
print ("the date was " & date_array[i]);
```

## Specifying a Starting Subscript

TSL allows you to assign values to array elements starting from a specific subscript number. You specify the starting subscript in the array initialization. Remember that the array subscripts are zero-based—the first subscript number is 0.

```
abc[ ] = {starting subscript = value1, value2, value3... }
```

For example, if the array size is ten, you can assign values to the last five elements of the array:

```
public abc[ ] = {5 = 100,101,102,103,104}
```

As a result, the abc array receives the following values:

```
abc[5]=100  
abc[6]=101  
abc[7]=102  
abc[8]=103  
abc[9]=104
```

## Array Functions

TSL provides two array functions: **delete** and **split**. The **delete** function removes an element from an array; **split** splits a string into fields and stores the fields in an array. Note that since TSL arrays are associative, deleting one element does not affect any other element. For instance, if you delete the element a[2] from an array with three elements, a[1] and a[3] will not be affected. For details, see the alphabetical reference.

## Input-Output

TSL provides a number of built-in functions that allow you to read and write to files or to the screen.

For XRunner and other UNIX products, the **print** and **printf** functions are used to write to the screen or to a file. The **print** function prints simple expressions, while the **printf** function generates formatted output. Output can be printed to the screen or written to a file using the appropriate redirection operator. The **close** function closes a file that was opened in response to a **print** or **printf** statement. The **getline** function is used to read a line from a file to a variable. The **sprintf** function returns a formatted string to a variable.

For WinRunner and other PC products, use the **file\_open** function to open a file for reading and writing. The **file\_printf** function writes to a file, and **file\_getline** reads from a file. The **file\_close** function closes a file that you opened with **file\_open**.

There are two functions that generate output within the testing environment. The **report\_msg** function prints a user-defined string expression to the test execution report. The **pause** function stops test execution and displays a string expression in a message box on the screen.

For more information on any of the TSL built-in functions, refer to the *TSL Online Reference*.

## Comments

A number sign (#) indicates that all text from this point to the end of the line is a comment. Comments can appear within statements that extend beyond one line, or can stand alone on a line of test script. The TSL interpreter does not process comments. For example,

```
# Type the date
i=1
while (i<=31)# number of days in month
    type ("The date is January " & i++ & ", 1994");
```

Note that a number sign (#) that appears within a string constant is not considered a comment; for instance, a="#3".

## Built-in Functions

TSL provides numerous built-in functions that perform a range of tasks. To call a built-in function from within a test script, use the following syntax:

```
function ( [ parameters ] );
```

Most built-in functions return a value. This value can be assigned to a variable. For example,

```
x = int(12.42);
```

The **int** function returns the integer portion of a positive, real number. Here, x is equal to 12.

The return value of a built-in function can also become part of an expression. When a function returns the value 0, the value of the expression is considered false. When it returns any other value, it is considered true. For example,

```
while (getline address < "clients.doc")
    type (address "<kReturn>");
```

The **getline** function returns the value 1 if it succeeds, and 0 at the end of the file. Therefore, the *while* loop above continues until the end of the file is reached (the function returns the value 0).

For detailed information on each of the TSL functions, refer to the *TSL Online Reference*.

## User-Defined Functions

In addition to the built-in functions it offers, TSL allows you to design and implement your own functions in test scripts. A user-defined function has the following structure:

```
[class] function name ( [mode] parameter... )  
{  
    declarations;  
    statements;  
}
```

### Class

The class of a function may be either public or static. If no class is explicitly declared, the function is assigned the default class public. A public function is available to all tests; a static function is available only to the test or compiled module within which the function was defined.

### Parameters

Function parameters can be of mode *in*, *out*, or *inout*. For all non-array parameters, the default mode is *in*. The significance of each parameter type is as follows:

**in:** A parameter which is assigned a value from outside the function.

**out:** A parameter which passes a value from inside the function.

**inout:** A parameter which can be assigned a value from outside the function as well as pass on a value to the outside.

A parameter designated as *out* or *inout* must be a variable name, not an expression. Only a variable can be assigned a value in a function call, not an expression. For example, consider a function defined in the following manner:

```
function my_func (out p) {... }
```

Proper usage of the function call is: `my_func (var_1)`; Illegal usage of the function call is: `my_func (arr[i])`; `my_func (a+b)`; because `arr[i]` and `a+b` are expressions.

Array parameters are designated by square brackets. For example, the following parameter list indicates that parameter *a* is an array:

```
function my_func (a[], b, c){  
...  
}
```

Array parameters can be either *out* or *inout*. If no class is specified, the default *inout* is assumed.

While variables used within a function must be explicitly declared, this is not the case for parameters.

## Declarations

Variables used by a function must be declared. The declaration for such a variable can be within the function itself, or anywhere else within the test or module. For syntax, “Variable Declarations”, on page9 in this chapter.

## Return Statement

Any valid statement used within a TSL test script can be used within a function. In addition, the *return* statement is used exclusively in functions.

```
return [ expression ];
```

This statement halts execution of the called function and passes control back to the calling function or test. It also returns the value of the evaluated expression to the calling function or test. (If no expression is attached to

the return statement, an empty string is returned.) For additional information on functions, refer to the *TSL Online Reference*.

## External Function Declarations

The **extern** function declaration is used to declare functions that are not part of TSL, but reside in external C libraries. For more information on using C functions stored in external dlls, refer to your *User's Guide*.

The **extern** declaration must appear before the function can be called. The syntax of the **extern** function declaration is:

```
extern type function_name (param1, param2,...);
```

The *type* refers to the return value of the function. Type can be one of the following:

- *char* (signed and unsigned)*float*
- *short* (signed and unsigned)*double*
- *int* (signed and unsigned)*string* (equivalent to C *char*\*)
- *long* (signed and unsigned)

Each parameter must include the following information:

[*mode*] *type* [*name*] [< *size* >]

*mode*                   The *mode* can be *in*, *out*, or *inout*. The default is *in*. Note that these values must appear in lower case.

*type*                   The *type* can be any of the values listed above.

*name*                   An optional *name* can be assigned to the parameter to improve readability.

*size*                   This information is required only for an *out* or *inout* parameter of type *string*. (See below.)

For example, to declare a function named *set\_clock* that sets the time in a clock application, you write the following:

```
extern int set_clock ( string name, int time );
```

The `set_clock` function accepts two parameters. Since they are both input parameters, no mode is specified. The first parameter, a string, is the name of the clock window. The second parameter specifies the time to be set on the clock. The function returns an integer that indicates whether the operation was successful.

Once the `extern` declaration is interpreted, you can call the `set_clock` function the same way you call a TSL built-in function:

```
result = set_clock ( "clock v. 3.0", 3 );
```

If an `extern` declaration includes an `out` or `inout` parameter of type *string*, you must budget the maximum possible string size by specifying an integer *size* after the parameter *type* or (optional) *name*. For example, the statement below declares the function `get_clock_string`. It returns the time displayed in a clock application as a string value in the format “The time is...”

```
extern int get_clock_string ( string clock, out string time <20> );
```

The *size* should be large enough to avoid an overflow. If no value is specified for *size*, the default is 127. There is no maximum size.

TSL identifies the function in your C code by its name only. You must pass the correct parameter information from TSL to the C function. TSL does not check parameters: if the information is incorrect, the operation fails.

In addition, your C function must adhere to the following conventions:

- Any parameter designated as a *string* in TSL must be associated with a parameter of type *char\** in C.
- Any parameter of mode *out* or *inout* in TSL must be associated with a pointer in C. For instance, a parameter *out int* in TSL must be associated with a parameter *int\** in the C function.
- For WinRunner the external function must observe the standard Pascal calling convention *export far Pascal*.

For example, the following declaration in TSL:

```
extern int set_clock (string name, inout int time);
```

must appear as follows in C:

```
int _far _pascal _export [_loads] set_clock (
    char* name,
    int* time
)
```

# 3

---

## Reserved Words

WinRunner contains reserved words. In addition to the words listed below, all TSL functions and statements are reserved words in WinRunner.

Note that you can change the color and appearance of reserved words in WinRunner's script editor. For more information, refer to the "Customizing the Test Script Editor" chapter in the *WinRunner User's Guide*.

auto	button_check_enabled
button_get_value	case
char	check_file
check_wid	const
continue	default
display_date_result	display_euro_result
double	edit_check_content
edit_check_format	else
endif	exception_on_print
exit	extern
float	function
get_lang	get_obj_record_method
get_runner_str	getline
grab	gsub
GUI_buf_get_data	GUI_buf_get_data_attr

GUI_buf_set_data_attr	GUI_data_get_attr
GUI_data_set_attr	GUI_list_data_attrs
GUI_mark	GUI_point_to
GUI_replay_wizard	if
in	inout
input_to_description_int	list_check_multi_selection
list_check_row_num	list_check_selection
list_get_items_count	list_get_multi_selected
long	menu_get_items_count
menu_verify	move_mouse_abs
move_mouse_rel	move_window
next	obj_check_attr
obj_check_enabled	obj_check_focused
obj_check_label	obj_check_pos
obj_check_size	obj_check_style
obj_set_focus	obj_verify
out	pause_test
printf	process_return_value
prvars	public
quad_click	report_event
report_param_msg	reset_filter
reset_internals	return
save_report_info	scroll_get_value
set_filter	set_obj_record_method
short	signed

static	string
sub	tab_get_page
tab_get_selected_page	tab_select_page
tbl_get_cell_coords	tbl_synchronize
tech	tl_get_status
tl_set_status	tl_setvar
toolbar_get_info	toolbar_wait_info
treturn	trpl_click
tsl_set_module_mark	tsl_test_is_module
ungrab	unsigned
vendor	vuser_status_message
wait_stable_window	win_check_attr
win_check_label	win_check_pos
win_check_size	win_press_cancel
win_press_ok	win_press_return
win_set_focus	win_verify



# 4

---

## Functions by Category

This section lists all TSL functions according to the type of tasks they perform. Functions are arranged alphabetically within each category, and a very brief description of each function is included. Where appropriate, functions appear in more than one category.

There are four types of functions:

- Analog
- Context Sensitive
- Customization
- Standard

## Analog Functions

Analog functions record and run operations at specified screen coordinates.

When you record in Analog mode, these functions are used to depict mouse clicks, keyboard input, and the exact coordinates traveled by the mouse.

When you run a test, Analog functions retrace the mouse tracks and exactly resubmit the input you recorded. Analog functions also support test operations such as synchronization, verification, and text manipulation.

Analog functions are divided into the following categories:

- bitmap checkpoint
- input device
- synchronization
- text checkpoint
- table

### Bitmap Checkpoint Function

Function	Description	See Page
<b>check_window</b>	compares a bitmap of an AUT window to an expected bitmap	127

## Input Device Functions

Function	Description	See Page
<b>click</b>	clicks a mouse button	128
<b>click_on_text</b>	clicks a mouse button on a string	129
<b>dbl_click</b>	double-clicks a mouse button	143
<b>get_x</b>	returns the current x-coordinate of the mouse pointer	206
<b>get_y</b>	returns the current y-coordinate of the mouse pointer	206
<b>move_locator_abs</b>	moves the mouse to a new absolute position	257
<b>move_locator_rel</b>	moves the mouse to a new relative position	257
<b>move_locator_text</b>	moves the mouse to a string	258
<b>move_locator_track</b>	moves the mouse along a prerecorded track	258
<b>mtype</b>	clicks one or more mouse buttons	259
<b>type</b>	specifies keyboard input	406

## Synchronization Function

Function	Description	See Page
<b>wait_window</b>	waits for a window bitmap to appear in order to synchronize test execution	411

## Table Functions

Function	Description	See Page
<b>tbl_click_cell</b>	clicks in a cell in a JFC JTable object	330
<b>tbl_dbl_click_cell</b>	double-clicks in a cell in a JFC JTable object	332
<b>tbl_drag</b>	drags a cell to a different location within a JFC JTable object	336

## Text Checkpoint Functions

Function	Description	See Page
<b>click_on_text</b>	clicks on a string	129
<b>find_text</b>	searches for a string	197
<b>get_text</b>	reads text from the screen	205
<b>move_locator_text</b>	moves the mouse to a string	258

## Context Sensitive Functions

Context Sensitive functions depict actions on the application under test in terms of GUI objects, ignoring the physical location of an object on the screen. When you record in Context Sensitive mode, a TSL statement, which describes the object selected and the action performed, is generated in the test script.

Context Sensitive functions are divided into the following categories:

- ActiveBar
- ActiveX/Visual Basic
- bitmap checkpoint
- button object
- calendar
- database
- data-driven tests
- Delphi
- edit object
- EURO
- GUI checkpoint
- GUI map configuration

- GUI map editor
- icon object
- Java
- list object
- menu object
- object
- Oracle
- PowerBuilder
- scroll object
- Siebel
- spin object
- static text object
- statusbar
- synchronization
- tab object
- table
- Terminal Emulator
- text checkpoint
- toolbar object
- Web
- window object
- Year 2000

## ActiveBar Functions

Function	Description	See Page
<b>ActiveBar_combo_select_item</b>	Selects an item in a ComboBox tool.	106
<b>ActiveBar_dump</b>	Stores information about ActiveBar bands and tools. This information includes captions, names, types and IDs.	107
<b>ActiveBar_select_menu</b>	Selects a menu item in a toolbar.	108
<b>ActiveBar_select_tool</b>	Selects a tool in the toolbar.	109

## ActiveX/Visual Basic Functions

Function	Description	See Page
<b>ActiveX_activate_method</b>	invokes an ActiveX method of an ActiveX control	110
<b>ActiveX_get_info</b>	returns the value of an ActiveX/Visual Basic control property	110
<b>ActiveX_set_info</b>	sets the value of a property in an ActiveX/Visual Basic control	111

## Bitmap Checkpoint Functions

Function	Description	See Page
<b>obj_check_bitmap</b>	compares a current object bitmap to an expected bitmap	260
<b>win_check_bitmap</b>	compares a current window bitmap to an expected bitmap	433

## Button Object Functions

Function	Description	See Page
<b>button_check_info</b>	checks the value of a button property	116
<b>button_check_state</b>	checks the state of a radio or check button	116
<b>button_get_info</b>	returns the value of a button property	117
<b>button_get_state</b>	returns the state of a radio or check button	117
<b>button_press</b>	clicks a push button	118
<b>button_set</b>	sets the state of a radio or check button	118
<b>button_wait_info</b>	waits for the value of a button property	119

## Calendar Functions

The following functions are available for calendars included in Visual Studio Version 6 and higher and in Internet Explorer Active Desktop Version 4 and higher.

Function	Description	See Page
<b>calendar_activate_date</b>	double clicks the specified date in the calendar	119
<b>calendar_get_selected</b>	retrieves and counts the selected dates in a calendar	120
<b>calendar_get_status</b>	returns the status validity of the date	120
<b>calendar_get_valid_range</b>	returns the date range	121
<b>calendar_select_date</b>	clicks the specified date in a calendar	122
<b>calendar_select_range</b>	clicks the specified date in a calendar	122
<b>calendar_select_time</b>	selects a time in the HH:MM:SS format	123
<b>calendar_set_status</b>	sets the selection status to valid or invalid	124

## Database Functions

Function	Description	See Page
<b>db_check</b>	compares current database data to expected database data	136
<b>db_connect</b>	creates a new database session and establishes a connection to an ODBC database	137
<b>db_disconnect</b>	disconnects from the database and ends the database session	138
<b>db_execute_query</b>	executes the query based on the SQL statement and creates a record se	139
<b>db_get_field_value</b>	returns the value of a single field in the database	140
<b>db_get_headers</b>	returns the number of column headers in a query and the content of the column headers, concatenated and delimited by tabs	140
<b>db_get_last_error</b>	returns the last error message of the last ODBC or Data Junction operation	141
<b>db_get_row</b>	returns the content of the row, concatenated and delimited by tabs	142
<b>db_write_records</b>	writes the record set into a text file delimited by tabs	142

## Database Function for Working with Data Junction

Function	Description	See Page
<b>db_dj_convert</b>	runs a Data Junction export file (.djs file)	138

## Data-Driven Test Functions

Function	Description	See Page
<b>ddt_close</b>	closes a data table file	144
<b>ddt_export</b>	exports the information of one table file into a different table file	144
<b>ddt_get_current_row</b>	retrieves the active row in a data table	145
<b>ddt_get_parameters</b>	returns a list of all the parameters in a data table	145
<b>ddt_get_row_count</b>	retrieves the number of rows in a data table	146
<b>ddt_is_parameter</b>	returns whether a parameter in a data table is valid	146
<b>ddt_next_row</b>	changes the active row in a data table to the next row	147
<b>ddt_open</b>	creates or opens a data table file so that WinRunner can access it	147
<b>ddt_report_row</b>	reports the active row in a data table to the test results	148
<b>ddt_save</b>	saves the information in a data table	148
<b>ddt_set_row</b>	sets the active row in a data table	149
<b>ddt_set_val</b>	sets a value in the current row of the data table	150
<b>ddt_set_val_by_row</b>	sets a value in the specified row of the data table	151
<b>ddt_show</b>	shows or hides the table editor of a specified data table	152
<b>ddt_update_from_db</b>	imports data from a database into a data table	152

Function	Description	See Page
<b>ddt_val</b>	returns the value of a parameter in the active row in a data table	153
<b>ddt_val_by_row</b>	returns the value of a parameter in the specified row in a data table	154

## Delphi Functions

Function	Description	See Page
<b>add_dlph_obj</b>	adds a Delphi object	113
<b>dlph_edit_set</b>	replaces the entire content of a Delphi edit object	160
<b>dlph_list_select_item</b>	selects a Delphi list item	160
<b>dlph_obj_get_info</b>	retrieves the value of a Delphi object	161
<b>dlph_obj_set_info</b>	sets the value of a Delphi object	161
<b>dlph_panel_button_press</b>	clicks a button within a Delphi panel	162

## Edit Object Functions

Function	Description	See Page
<b>edit_check_info</b>	checks the value of an edit object property	163
<b>edit_check_selection</b>	checks that a string is selected	164
<b>edit_check_text</b>	checks the contents of an edit object	164
<b>edit_delete</b>	deletes the contents of an edit object	165
<b>edit_delete_block</b>	deletes a text block from an edit object	166
<b>edit_get_block</b>	returns a block of text from an edit object	166
<b>edit_get_info</b>	returns the value of an edit object property	167
<b>edit_get_row_length</b>	returns the length of a row in an edit object	168
<b>edit_get_rows_count</b>	returns the number of rows written in an edit object	168
<b>edit_get_selection</b>	returns the selected string in an edit object	169
<b>edit_get_selection_pos</b>	returns the position at which the selected block starts and ends	170
<b>edit_get_text</b>	returns the text in an edit object	170
<b>edit_insert</b>	inserts text in an edit object	171
<b>edit_insert_block</b>	inserts text in a multi-line edit object	172
<b>edit_replace</b>	replaces part of the contents of an edit object	172
<b>edit_replace_block</b>	replaces a block of text in a multi-line edit object	173
<b>edit_set</b>	replaces the entire contents of an edit object	173
<b>edit_set_insert_pos</b>	places the cursor at the specified point in an edit object	174

Function	Description	See Page
<b>edit_set_selection</b>	selects text in an edit object	175
<b>edit_type</b>	types a string in an edit object	175
<b>edit_wait_info</b>	waits for the value of an edit object property	176

## EURO Functions

The following functions are available for WinRunner EURO users only:

Function	Description	See Page
<b>EURO_check_currency</b>	captures and compares the currencies in a window	177
<b>EURO_compare_columns</b>	compares two currency columns (dual display) and returns the number of mismatches	178
<b>EURO_compare_fields</b>	compares two fields while converting	178
<b>EURO_compare_numbers</b>	compares two numbers while converting	180
<b>EURO_convert_currency</b>	returns the converted currency value between two currencies	181
<b>EURO_override_field</b>	overrides the original currency in a field to a new currency	182
<b>EURO_set_auto_currency_verify</b>	activates/deactivates automatic EURO verification	183
<b>EURO_set_capture_mode</b>	determines how WinRunner EURO captures currency in terminal emulator applications	184

Function	Description	See Page
<b>EURO_set_conversion_mode</b>	sets the EURO conversion run mode in the test script	184
<b>EURO_set_conversion_rate</b>	sets the conversion rate between the EURO currency and a national currency	185
<b>EURO_set_cross_rate</b>	sets the cross rate method between two currencies	186
<b>EURO_set_currency_threshold</b>	sets the minimum value of an integer which will be considered a currency	187
<b>EURO_set_decimals_precision</b>	sets the number of decimals in the conversion results	187
<b>EURO_set_original_new_currencies</b>	sets the original and new currencies of the application	188
<b>EURO_setRegional_symbols</b>	sets the character used as decimal separator and the character used to separate groups of digits to the left of the decimal	189
<b>EURO_set_triangulation_decimals</b>	sets the default decimals precision for the EURO triangulation	189
<b>EURO_type_mode</b>	disables/enables overriding of automatic currency recognition for all integer objects in a GUI application	190

## GUI Checkpoint Functions

Function	Description	See Page
<b>obj_check_gui</b>	compares current GUI data to expected GUI data for any class of object	260
<b>win_check_gui</b>	compares current GUI data to expected GUI data for a window	434

## GUI Map Configuration Functions

Function	Description	See Page
<b>get_class_map</b>	returns the standard class associated with a custom class	201
<b>get_record_attr</b>	returns the properties recorded for an object class	203
<b>get_record_method</b>	returns the recording method used for an object class	204
<b>set_class_map</b>	associates a custom class with a standard class	291
<b>set_record_attr</b>	sets the properties to learn for an object class	292
<b>set_record_method</b>	sets the operations to learn for a custom object class	292
<b>unset_class_map</b>	unbinds a custom class from a standard class	409

## GUI Map Editor Functions

Function	Description	See Page
<b>GUI_add</b>	adds an object to a GUI map file	208
<b>GUI_buf_get_desc</b>	returns the physical description of an object in a GUI map file	208
<b>GUI_buf_get_desc_attr</b>	returns the value of an object property in a GUI map file	209

Function	Description	See Page
<b>GUI_buf_get_logical_name</b>	returns the logical name of an object in a GUI map file	210
<b>GUI_buf_new</b>	creates a new GUI map file	210
<b>GUI_buf_set_desc_attr</b>	sets the value of a property in a GUI map file	211
<b>GUI_close</b>	closes a GUI map file	211
<b>GUI_close_all</b>	closes all GUI map files	212
<b>GUI_delete</b>	deletes an object from a GUI map file	212
<b>GUI_desc_compare</b>	compares two physical descriptions	213
<b>GUI_desc_get_attr</b>	gets the value of a property from a physical description	213
<b>GUI_desc_set_attr</b>	sets the value of a property	214
<b>GUI_get_name</b>	returns the type of GUI for the application under test	214
<b>GUI_get_window</b>	returns the active window in the GUI map	215
<b>GUI_list_buf_windows</b>	lists all windows in a GUI map file	216
<b>GUI_list_buffers</b>	lists all open GUI map files	216
<b>GUI_list_desc_attrs</b>	returns a list of all property values for an object	217
<b>GUI_list_map_buffers</b>	lists all loaded GUI map files	218
<b>GUI_list_win_objects</b>	lists all objects in a window	218
<b>GUI_load</b>	loads a GUI map file	219
<b>GUI_map_get_desc</b>	returns the description of an object in the GUI map	220
<b>GUI_map_get_logical_name</b>	returns the logical name of an object in the GUI map	220

Function	Description	See Page
<b>GUI_open</b>	opens a GUI map file	221
<b>GUI_save</b>	saves a GUI map file	221
<b>GUI_save_as</b>	saves a GUI map file under a new name	222
<b>GUI_set_window</b>	sets the scope for identifying objects in the GUI map	222
<b>GUI_unload</b>	unloads a GUI map file	223
<b>GUI_unload_all</b>	unloads all loaded GUI map files	223

### Icon Object Functions

Function	Description	See Page
<b>icon_move</b>	moves an icon to a new location	226
<b>icon_select</b>	clicks an icon	227

### Java Function

Function	Description	See Page
<b>java_activate_method</b>	invokes the requested Java method for the given object	230

## List Object Functions

Function	Description	See Page
<b>list_activate_item</b>	activates an item	231
<b>list_check_info</b>	checks the value of a list property	232
<b>list_check_item</b>	checks the content of an item in a list	232
<b>list_check_selected</b>	checks that the specified item is selected	233
<b>listCollapse_item</b>	hides items in a tree view object	233
<b>list_deselect_item</b>	deselects an item	234
<b>list_deselect_range</b>	deselects all items between two specified items	234
<b>list_drag_item</b>	drags an item from a source list	235
<b>list_drop_on_item</b>	drops an object onto a target list item	236
<b>list_expand_item</b>	displays hidden items in a tree view object	236
<b>list_extend_item</b>	adds an item to the items already selected	237
<b>list_extend_multi_items</b>	adds multiple items to the items already selected	238
<b>list_extend_range</b>	selects a range of items and adds them to the items currently selected	238
<b>list_get_checked_items</b>	returns the value of items marked as checked	239
<b>list_get_column_header</b>	returns the value of a ListView column header	240
<b>list_get_info</b>	returns the value of a list property	240
<b>list_get_item</b>	returns the contents of an item	241
<b>list_get_item_info</b>	returns the state of a list item	242
<b>list_get_item_num</b>	returns the position of an item	242

Function	Description	See Page
<b>list_get_selected</b>	returns the currently selected item	243
<b>list_get_subitem</b>	returns the value of the ListView subitem	244
<b>list_rename_item</b>	activates an item's edit mode in order to rename it	244
<b>list_select_item</b>	selects an item in a list	245
<b>list_select_multi_items</b>	selects items in a multiple-selection container object	246
<b>list_select_range</b>	selects all items between two specified items	246
<b>list_set_item_state</b>	sets the state of an icon of the specified ListView or TreeView	247
<b>list_wait_info</b>	waits for the value of a list property	248

## Menu Object Functions

Function	Description	See Page
<b>menu_get_desc</b>	returns the physical description of a menu	253
<b>menu_get_info</b>	returns the value of a menu property	254
<b>menu_get_item</b>	returns the contents of an item	254
<b>menu_get_item_num</b>	returns the position of an item	255
<b>menu_select_item</b>	selects an item	256
<b>menu_wait_info</b>	waits for the value of a menu property	256

## Object Functions

Function	Description	See Page
<b>obj_check_bitmap</b>	compares a current object bitmap to an expected bitmap	260
<b>obj_check_gui</b>	compares current GUI data to expected GUI data	260
<b>obj_check_info</b>	checks the value of an object property	261
<b>obj_click_on_text</b>	clicks on text in an object	262
<b>obj_drag</b>	begins dragging an object	263
<b>obj_drop</b>	ends dragging an object	264
<b>obj_exists</b>	checks if an object is displayed	264
<b>obj_find_text</b>	returns the location of a string within an object	265
<b>obj_get_desc</b>	returns an object's physical description	266
<b>obj_get_info</b>	returns the value of an object property	266
<b>obj_get_text</b>	reads text from an object	267
<b>obj_highlight</b>	highlights an object	268
<b>obj_mouse_click</b>	clicks on an object	268
<b>obj_mouse_dbl_click</b>	double-clicks on an object	270
<b>obj_mouse_drag</b>	drags the mouse within an object	271
<b>obj_mouse_move</b>	moves the mouse within an object	272
<b>obj_move_locator_text</b>	moves the mouse to a string in an object	272
<b>obj_set_info</b>	sets the value of an object property	274
<b>obj_type</b>	sends keyboard input to an object	274
<b>obj_wait_bitmap</b>	waits for an object bitmap	275
<b>obj_wait_info</b>	waits for the value of an object property	276

## Oracle Functions

Function	Description	See Page
<b>edit_activate</b>	double-clicks an object in an Oracle application	163
<b>edit_set_focus</b>	focuses on an object in an Oracle application	174
<b>lov_get_item</b>	retrieves an item from a list of values in an Oracle application	251
<b>lov_select_item</b>	selects an item from a list of values in an Oracle application	251

## PowerBuilder Functions

Function	Description	See Page
<b>datawindow_get_info</b>	retrieves the value of a DataWindow object property	135
<b>datawindow_text_click</b>	clicks a DataWindow text object	135
<b>datawindow_text dbl_click</b>	double-clicks a DataWindow text object	136

## Scroll Object Functions

Function	Description	See Page
<b>scroll_check_info</b>	checks the value of a scroll property	283
<b>scroll_check_pos</b>	checks the current position of a scroll	283
<b>scroll_drag</b>	drags a scroll to the specified location	284
<b>scroll_drag_from_min</b>	scrolls the specified distance from the minimum position	284
<b>scroll_get_info</b>	returns the value of a scroll property	285
<b>scroll_get_max</b>	returns the value of a scroll at its maximum (end) position	285
<b>scroll_get_min</b>	returns the value of the scroll at its minimum (start) position	286
<b>scroll_get_pos</b>	returns the current scroll position	286
<b>scroll_get_selected</b>	returns the minimum and maximum values of the selected range on a slider	287
<b>scroll_line</b>	scrolls the specified number of lines	288
<b>scroll_max</b>	sets a scroll to the maximum (end) position	288
<b>scroll_min</b>	sets a scroll to the minimum (start) position	289
<b>scroll_page</b>	moves a scroll the specified number of pages	289
<b>scroll_wait_info</b>	waits for the value of a scroll property	290

## Siebel Functions

Function	Description	See Page
<b>siebel_click_history</b>	clicks the history button	295
<b>siebel_connect_repository</b>	connects to the Siebel repository database	296
<b>siebel_get_active_applet</b>	returns the active applet name	296
<b>siebel_get_active_buscomp</b>	returns the active business component name	297
<b>siebel_get_active_busobj</b>	returns the active business object name	298
<b>siebel_get_active_control</b>	returns the active control name	298
<b>siebel_get_active_view</b>	returns the active view name	299
<b>siebel_get_chart_data</b>	returns the legend data and chart values from the specified chart	300
<b>siebel_get_control_value</b>	returns the active control value	300
<b>siebel_goto_record</b>	navigates to the specified record	301
<b>siebel_navigate_view</b>	navigates to the specified view	302
<b>siebel_obj_get_info</b>	returns the value of a single Siebel object property from the Siebel repository database	302
<b>siebel_obj_get_properties</b>	returns all properties of a Specified siebel object in the Siebel repository database.	304
<b>siebel_select_alpha</b>	selects a letter button from the alpha tab bar	305
<b>siebel_set_active_applet</b>	sets the specified applet as the active applet.	305
<b>siebel_set_active_control</b>	sets the specified control as the active control	306

Function	Description	See Page
<b>siebel_set_control_value</b>	sets a new value for the active control	306
<b>siebel_terminate</b>	closes the Siebel application	307

## Spin Object Functions

Function	Description	See Page
<b>spin_down</b>	scrolls a spin control down a specified number of times	308
<b>spin_get_info</b>	returns the value of a spin property	308
<b>spin_get_pos</b>	returns the position of a spin object	309
<b>spin_get_range</b>	returns the minimum and maximum positions of a spin	309
<b>spin_max</b>	sets a spin to its maximum value	310
<b>spin_min</b>	sets a spin to its minimum value	310
<b>spin_next</b>	sets a spin to its next value	310
<b>spin_prev</b>	sets a spin to its previous value	311
<b>spin_set</b>	sets a spin to the specified value	312
<b>spin_up</b>	scrolls a spin control up the specified number of times	312
<b>spin_wait_info</b>	waits for the value of a spin property	313

## Static Text Object Functions

Function	Description	See Page
<b>static_check_info</b>	checks the value of a static text object property	316
<b>static_check_text</b>	checks the contents of a static text object	316
<b>static_get_info</b>	returns the value of a static text property	317
<b>static_get_text</b>	returns the contents of a static text object	317
<b>static_wait_info</b>	waits for the value of a static text property	318

## Statusbar Functions

Function	Description	See Page
<b>statusbar_get_field_num</b>	returns the numeric index of a field on a status bar	318
<b>statusbar_get_info</b>	returns the value of a status bar property	319
<b>statusbar_get_text</b>	reads text from a field on a status bar	320
<b>statusbar_wait_info</b>	waits for the value of a status bar property	320

## Synchronization Functions

Function	Description	See Page
<b>button_wait_info</b>	waits for the value of a button property	119
<b>edit_wait_info</b>	waits for the value of an edit property	176
<b>list_wait_info</b>	waits for the value of a list property	248
<b>menu_wait_info</b>	waits for the value of a menu property	256
<b>obj_wait_info</b>	waits for the value of an object property	276
<b>scroll_wait_info</b>	waits for the value of a scroll property	290

Function	Description	See Page
<b>spin_wait_info</b>	waits for the value of a spin property	313
<b>static_wait_info</b>	waits for the value of a static text property	318
<b>statusbar_wait_info</b>	waits for the value of a status bar property	320
<b>tab_wait_info</b>	waits for the value of a tab property	325
<b>win_wait_info</b>	waits for the value of a window property	451

## Tab Object Functions

Function	Description	See Page
<b>tab_get_info</b>	returns the value of a tab property	323
<b>tab_get_item</b>	returns the name of a tab item	323
<b>tab_get_selected</b>	returns the name of the selected tab item	324
<b>tab_select_item</b>	selects a tab item	324
<b>tab_wait_info</b>	waits for the value of a tab property	325

## Table Functions

Function	Description	See Page
<b>tbl_activate_cell</b>	double-clicks the specified cell in a table	326
<b>tbl_activate_col</b>	double-clicks the specified column	328
<b>tbl_activate_header</b>	double-clicks the specified column header in a table	328
<b>tbl_activate_row</b>	double-clicks the specified row	330
<b>tbl_deselect_col</b>	deselects the specified column	333
<b>tbl_deselect_cols_range</b>	deselects the specified range of columns	334
<b>tbl_deselect_row</b>	deselects the specified row	335
<b>tbl_deselect_rows_range</b>	deselects the specified range of rows	336
<b>tbl_extend_col</b>	adds a column to the currently selected columns	338
<b>tbl_extend_cols_range</b>	adds columns to the currently selected columns	339
<b>tbl_extend_row</b>	adds a row to the currently selected rows	340
<b>tbl_extend_rows_range</b>	adds rows to the currently selected rows	340
<b>tbl_get_cell_data</b>	retrieves the contents of the specified cell from a table	342
<b>tbl_get_cols_count</b>	retrieves the number of columns in a table	344
<b>tbl_get_column_name</b>	retrieves the column header name of the specified column in a table	346
<b>tbl_get_column_names</b>	returns the names and number of columns in a table for PowerBuilder applications	347

Function	Description	See Page
<b>tbl_get_rows_count</b>	retrieves the number of rows in the specified table	348
<b>tbl_get_selected_cell</b>	returns the cell currently in focus in a table	349
<b>tbl_get_selected_row</b>	returns the row currently selected in a table	351
<b>tbl_select_cells_range</b>	selects the specified range of cells	352
<b>tbl_select_col_header</b>	clicks the specified column header of a table	354
<b>tbl_select_cols_range</b>	selects the specified range of columns	355
<b>tbl_select_rows_range</b>	selects the specified range of rows	356
<b>tbl_set_cell_data</b>	sets the contents of a cell to the specified text in a table	357
<b>tbl_set_cell_focus</b>	sets the focus to the specified cell in a table	360
<b>tbl_set_selected_cell</b>	selects the specified cell in a table	361
<b>tbl_set_selected_col</b>	selects the specified column in a table	363
<b>tbl_set_selected_row</b>	selects the specified row in a table	364

## Terminal Emulator Functions

The following functions are available for the Year 2000 add-in and WinRunner EURO users only:

Function	Description	See Page
<b>TE_add_screen_name_location</b>	instructs WinRunner where to look for the logical name of a screen	367
<b>TE_bms2gui</b>	teaches WinRunner the user interface from a BMS file	368
<b>TE_check_text</b>	captures and compares the text in a terminal emulator window	368
<b>TE_create_filter</b>	creates a filter in the test database	369
<b>TE_define_sync_keys</b>	sets keys that enable automatic synchronization in <b>type</b> , <b>win_type</b> and <b>obj_type</b> commands	370
<b>TE_delete_filter</b>	deletes a specified filter from the test database	370
<b>TE_edit_field</b>	inserts text into an unprotected field	371
<b>TE_edit_hidden_field</b>	inserts text into a hidden field	372
<b>TE_edit_screen</b>	types a string in the specified location in a screen	372
<b>TE_find_text</b>	returns the location of a specified string	373
<b>TE_force_send_key</b>	defines a key causing a screen to change	374
<b>TE_get_active_filter</b>	returns the coordinates of a specified active filter.	374

Function	Description	See Page
<b>TE_get_auto_reset_filters</b>	indicates whether or not filters are automatically deactivated at the end of a test run	375
<b>TE_get_auto_verify</b>	indicates whether automatic text verification is on or off	376
<b>TE_get_cursor_position</b>	returns the position of the cursor	376
<b>TE_get_field_content</b>	returns the contents of a field to a variable	377
<b>TE_get_filter</b>	returns the properties of a specified filter	378
<b>TE_get_merge_rule</b>	returns the rule for merging fields	379
<b>TE_get_refresh_time</b>	returns the time WinRunner waits for the screen to refresh	379
<b>TE_get_screen_name_location</b>	returns the screen name location	380
<b>TE_get_sync_time</b>	returns the system synchronization time	380
<b>TE_get_text</b>	reads text from screen and stores it in a string	381
<b>TE_get_timeout</b>	returns the current synchronization time	381
<b>TE_merge_fields</b>	sets the rule for merging fields	382
<b>TE_reset_all_filters</b>	deactivates all filters in a test	382
<b>TE_reset_all_force_send_key</b>	deactivates the execution of <b>TE_force_send_key</b> functions	383
<b>TE_reset_all_merged_fields</b>	deactivates the merging of fields	383
<b>TE_reset_filter</b>	deactivates a specified filter	384

Function	Description	See Page
<b>TE_reset_screen_name_location</b>	resets the screen name location to 0	384
<b>TE_send_key</b>	sends to the mainframe the specified F-key function	385
<b>TE_set_auto_reset_filters</b>	deactivates the automatic reset of filters when a test run is completed	385
<b>TE_set_auto_transaction</b>	defines a recorded <b>TE_wait_sync</b> statement as a transaction	386
<b>TE_set_auto_verify</b>	activates/deactivates automatic text	386
<b>TE_set_BMS_name_tag</b>	changes a name tag that appears in your BMS file	387
<b>TE_set_cursor_position</b>	defines the position of the cursor	388
<b>TE_set_field</b>	specifies the field that will receive subsequent input	388
<b>TE_set_filter</b>	creates and activates a filter	389
<b>TE_set_filter_mode</b>	specifies whether to assign filters to all screens or to the current screen	390
<b>TE_set_record_method</b>	specifies the recording method for operations on terminal emulator objects	390
<b>TE_set_refresh_time</b>	sets the interval that WinRunner waits for the screen to refresh	391
<b>TE_set_screen_name_location</b>	resets the screen name location to 0 and instructs WinRunner where to look for the logical name of a screen	392

Function	Description	See Page
<b>TE_set_sync_time</b>	defines the system synchronization time	392
<b>TE_set_timeout</b>	sets the maximum time WinRunner waits for a response from the server	393
<b>TE_set_trailing</b>	determines whether WinRunner types spaces and tabs in fields during test execution	394
<b>TE_user_attr_comment</b>	enables a user to add a user-defined comment property to the physical description of fields in the GUI map	394
<b>TE_user_reset_all_attr_comment</b>	resets all user-defined comment properties	395
<b>TE_wait_field</b>	waits for a specified string in a specified field to appear on screen	395
<b>TE_wait_string</b>	waits for a string to appear on screen	396
<b>TE_wait_sync</b>	instructs WinRunner to wait for the terminal emulator screen to be redrawn	396

## Text Checkpoint Functions

Function	Description	See Page
<b>obj_click_on_text</b>	clicks on text in an object	262
<b>obj_find_text</b>	returns the location of a string in an object	265
<b>obj_get_text</b>	reads text from an object	267
<b>obj_move_locator_text</b>	moves the mouse to a string in an object	272
<b>win_find_text</b>	returns the location of a string in a window	439
<b>win_click_on_text</b>	clicks on text in a window	436
<b>win_get_text</b>	reads text from a window	441
<b>win_move_locator_text</b>	moves the mouse to a string in a window	447

## Toolbar Object Functions

Function	Description	See Page
<b>toolbar_button_press</b>	clicks on a toolbar button	400
<b>toolbar_get_button</b>	returns the name of a toolbar button	400
<b>toolbar_get_button_info</b>	returns the value of a toolbar button property	402
<b>toolbar_get_button_num</b>	returns the position of a toolbar button	403
<b>toolbar_get_buttons_count</b>	returns the number of buttons on a toolbar	403
<b>toolbar_select_item</b>	selects an item from a menu-like toolbar, as in Microsoft Internet Explorer 4.0 or the Start menu in Windows 98	404

## Web Functions

The following functions are available only when the WebTest add-in is loaded:

Function	Description	See Page
<b>web_browser_invoke</b>	invokes the browser and opens a specified site	412
<b>web_cursor_to_image</b>	moves the cursor to an image on a page.	412
<b>web_cursor_to_label</b>	moves the cursor to a label on a page	413
<b>web_cursor_to_link</b>	moves the cursor to a link on a page	413
<b>web_cursor_to_obj</b>	moves the cursor to an object on a page	414
<b>web_file_browse</b>	clicks a browse button	414
<b>web_file_set</b>	sets the text value in a file-type object	416
<b>web_find_text</b>	returns the location of text within a page	417
<b>web_frame_get_text</b>	retrieves the text content of a page	418
<b>web_frame_get_text_count</b>	returns the number of occurrences of a regular expression in a page	419
<b>web_frame_text_exists</b>	returns a text value if it is found in a frame	419
<b>web_get_timeout</b>	returns the maximum time that WinRunner waits for response from the web	420
<b>web_image_click</b>	clicks a hypergraphic link or an image	421
<b>web_label_click</b>	clicks the specified label	421

Function	Description	See Page
<b>web_link_click</b>	clicks a hypertext link	422
<b>web_link_valid</b>	checks whether a URL name of a link is valid (not broken)	422
<b>web_obj_click</b>	clicks an object in a frame	423
<b>web_obj_get_child_item</b>	returns the description of the children in an object	423
<b>web_obj_get_child_item_count</b>	returns the count of the children in an object	424
<b>web_obj_get_info</b>	returns the value of an object property	425
<b>web_obj_get_text</b>	returns a text string from an object	425
<b>web_obj_get_text_count</b>	returns the number of occurrences of a regular expression string in an object	426
<b>web_obj_text_exists</b>	returns a text value if it is found in an object	427
<b>web_set_timeout</b>	sets the maximum time WinRunner waits for a response from the web	431
<b>web_set_tooltip_color</b>	sets the colors for the WebTest ToolTip	431
<b>web_sync</b>	waits for the navigation of a frame to be completed	432
<b>web_url_valid</b>	checks whether a URL is valid	432

## Table Functions for WebTest

Function	Description	See Page
<b>tbl_get_cell_data</b>	retrieves the contents of the specified cell from a table	342
<b>tbl_get_cols_count</b>	retrieves the number of columns in a table	344
<b>tbl_get_column_name</b>	retrieves the column header name of the specified column	346
<b>tbl_get_rows_count</b>	retrieves the number of rows in the specified table	348

## Window Object Functions

Function	Description	See Page
<b>set_window</b>	specifies the window to receive input, according to the window's logical name	293
<b>_set_window</b>	specifies a window to receive input, according to the window's physical description	294
<b>win_activate</b>	activates a window	433
<b>win_check_bitmap</b>	compares a current window bitmap to an expected bitmap	433
<b>win_check_gui</b>	compares current GUI data to expected GUI data	434
<b>win_check_info</b>	checks the requested window property	435
<b>win_click_help</b>	clicks the help button in a window title bar	435
<b>win_click_on_text</b>	clicks on text in a window	436
<b>win_close</b>	closes a window	437
<b>win_drag</b>	drags an object from a source window	437
<b>win_drop</b>	drops an object on a target window	438

Function	Description	See Page
<b>win_exists</b>	checks whether a window is displayed	438
<b>win_find_text</b>	returns the location of a string in a window	439
<b>win_get_desc</b>	returns the physical description of a window	440
<b>win_get_info</b>	returns the value of a window property	441
<b>win_get_text</b>	reads text from a window	441
<b>win_highlight</b>	highlights a window	442
<b>win_max</b>	maximizes a window	442
<b>win_min</b>	minimizes a window to an icon	443
<b>win_mouse_click</b>	clicks in a window	443
<b>win_mouse_dbl_click</b>	double-clicks in a window	444
<b>win_mouse_drag</b>	drags the mouse in a window	445
<b>win_mouse_move</b>	moves the mouse in a window	446
<b>win_move</b>	moves a window to a new absolute location	446
<b>win_move_locator_text</b>	moves the mouse to a string in a window	447
<b>win_open</b>	opens a window	448
<b>win_resize</b>	resizes a window	448
<b>win_restore</b>	restores a window from a minimized or maximized state to its previous size	449
<b>win_type</b>	sends keyboard input to a window	449
<b>win_wait_bitmap</b>	waits for a window bitmap	450
<b>win_wait_info</b>	waits for the value of a window property	451

## Year 2000 Functions

The following functions are available for WinRunner 2000 users only:

Function	Description	See Page
<b>Y2K_age_string</b>	ages date string and returns the aged date	452
<b>Y2K_align_day</b>	ages dates to a business day or to the same day of the week	453
<b>Y2K_calc_days_in_field</b>	calculates the number of days between two dates	454
<b>Y2K_calc_days_in_string</b>	calculates the number of days between two numeric strings	455
<b>Y2K_change_field_aging</b>	overrides aging on a specified date object	455
<b>Y2K_change_original_new_formats</b>	overrides automatic date recognition for a specified object	456
<b>Y2K_check_date</b>	checks all dates in the current screen of a terminal emulator application	457
<b>Y2K_disable_format</b>	disables a date format	457
<b>Y2K_enable_format</b>	enables a date format	458
<b>Y2K_field_to_Julian</b>	translates a date field to a Julian number	458
<b>Y2K_is_date_field</b>	determines whether a field contains a valid date	459
<b>Y2K_is_date_string</b>	determines whether a numeric string contains a valid date	459

Function	Description	See Page
<b>Y2K_is_leap_year</b>	determines whether a year is a leap year	460
<b>Y2K_leading_zero</b>	determines whether to add a zero before single-digit numbers when aging and translating dates	460
<b>Y2K_month_language</b>	sets the language used for month names	461
<b>Y2K_set_aging</b>	sets aging in a test script	461
<b>Y2K_set_attr</b>	sets the record configuration mode for a field	462
<b>Y2K_set_auto_date_verify</b>	automatically generates a date checkpoint for the current screen in a terminal emulator application.	463
<b>Y2K_set_capture_mode</b>	determines how WinRunner 2000 captures dates in terminal emulator applications	463
<b>Y2K_set_replay_mode</b>	changes the Year 2000 run mode in the test script	464
<b>Y2K_set_system_date</b>	changes the system date and time	465
<b>Y2K_set_year_limits</b>	sets the minimum and maximum years valid for date verification and aging	465
<b>Y2K_set_year_threshold</b>	sets the year threshold	466

Function	Description	See Page
<b>Y2K_string_to_Julian</b>	translates a numeric string to a Julian number	466
<b>Y2K_type_mode</b>	disables overriding of automatic date recognition for all date objects in a GUI application	467

## Customization Functions

Customization functions let you enhance your testing tool for your own needs. For example, you can add functions to the Function Generator or create custom GUI checkpoints.

Customization functions are divided into the following categories:

- custom record
- Function Generator
- GUI checkpoint
- custom user interface

## Custom Record Functions

Function	Description	See Page
<b>add_cust_record_class</b>	registers a custom record function and/or logical name function	112
<b>add_record_attr</b>	registers a custom property	114
<b>add_record_message</b>	adds a message to the list of Windows messages that WinRunner processes	114
<b>delete_record_attr</b>	removes a custom property	159

## Custom User Interface Functions

Function	Description	See Page
<b>create_browse_file_dialog</b>	displays a browse dialog box from which the user selects a file	131
<b>create_custom_dialog</b>	creates a custom dialog box.	132
<b>create_input_dialog</b>	creates a dialog box with an edit field for use in interactive test execution	133
<b>create_list_dialog</b>	creates a dialog box with a list of items for use in interactive test execution	133
<b>create_password_dialog</b>	creates a password dialog box	134

## Function Generator Functions

Function	Description	See Page
<b>generator_add_category</b>	adds a category to the Function Generator	198
<b>generator_add_function</b>	adds a function to the Function Generator	198
<b>generator_add_function_to_category</b>	adds a function defined in the Function Generator to a category	199
<b>generator_add_subcategory</b>	adds a subcategory to a category in the Function Generator	200
<b>generator_set_default_function</b>	sets a default function for a Function Generator category	200

## GUI Checkpoint Functions

Function	Description	See Page
<b>gui_ver_add_check</b>	registers a new check for a GUI checkpoint	224
<b>gui_ver_add_check_to_class</b>	adds a check to an object class, which can be viewed in the GUI Checkpoint dialog boxes	224
<b>gui_ver_add_class</b>	adds a checkpoint for a new object class	225
<b>gui_ver_set_default_checks</b>	sets default checks for a GUI object class	226

## Standard Functions

Standard functions include all the general elements of a programming language, such as basic input and output, control-flow, mathematical, and array functions.

Standard functions are divided into the following categories:

- arithmetic
- array
- call statements
- compiled module
- exception handling
- I/O
- load testing
- miscellaneous
- operating system
- password
- QuickTest 2000
- string
- TDAPI
- test option/configuration parameter
- TestDirector
- time-related

## Arithmetic Functions

Function	Description	See Page
<b>atan2</b>	returns the arctangent of y/x, in radians	115
<b>cos</b>	returns the cosine of an angle, in radians	130
<b>exp</b>	calculates the exponential function of <i>ex</i>	192
<b>int</b>	returns the integer part of a real number	228
<b>log</b>	returns a natural logarithm	250
<b>rand</b>	returns a pseudo-random real number	279
<b>sin</b>	calculates the sine of an angle	307
<b>sqrt</b>	returns the square root of its argument	314
<b>strand</b>	defines a seed parameter for the rand function	315

## Array Functions

Function	Description	See Page
<b>delete</b>	removes an element from an array	158
<b>split</b>	divides an input string into fields, stores them in an array, and indicates the number of fields generated	313

## Call Statements

Function	Description	See Page
<b>call</b>	invokes a test from within another test script	124
<b>call_chain_get_attr</b>	obtains information about a test or function in the current call chain	125
<b>call_chain_get_depth</b>	returns the number of items in the current call chain	126
<b>call_close</b>	invokes a test from within a script and closes the test when the test is completed	126
<b>return</b>	returns a value to the calling function or test	282
<b>texit</b>	stops execution of a called test	397
<b>treturn</b>	stops a called test and returns control to the calling test	405

## Compiled Module Functions

Function	Description	See Page
<b>load</b>	loads a compiled module into memory	248
<b>reload</b>	removes a compiled module from memory and loads it again	280
<b>unload</b>	removes a compiled module or selected functions from memory	407

## Exception Handling Functions

Function	Description	See Page
<b>define_object_exception</b>	defines a GUI object exception	156
<b>define_popup_exception</b>	defines a popup window exception	157
<b>define_tsl_exception</b>	defines a TSL exception	158
<b>exception_off</b>	deactivates handling for an exception	191
<b>exception_off_all</b>	deactivates handling of all exceptions	191
<b>exception_on</b>	enables detection and handling of a previously defined exception	192

## I/O Functions

Function	Description	See Page
<b>file_close</b>	closes a file opened with <b>file_open</b>	192
<b>file_compare</b>	compares the contents of two files	193
<b>file_getline</b>	reads a line from a file	194
<b>file_open</b>	opens a file for reading or printing, or creates a new file	194
<b>file_printf</b>	prints formatted output to a file	195
<b>pause</b>	pauses a test and displays a message	278
<b>report_msg</b>	inserts a message in a test report	281
<b>sprintf</b>	returns a formatted string to a variable	314
<b>str_map_logical_to_visual</b>	converts a logical string to a visual string or vice-versa	321

## Load Testing Functions

The following functions are available for LoadRunner GUI Vusers only.

Function	Description	See Page
<b>declare_rendezvous</b>	declares a rendezvous	154
<b>declare_transaction</b>	declares a transaction	155
<b>end_transaction</b>	marks the end of a transaction for performance analysis	176
<b>error_message</b>	sends an error message to the controller	177
<b>get_host_name</b>	returns the name of a host	202
<b>get_master_host_name</b>	returns the name of the controller's host	202
<b>lr_whoami</b>	returns information about the Vuser executing the script	252
<b>output_message</b>	sends a message to the controller	276
<b>rendezvous</b>	sets a rendezvous point in a Vuser script	280
<b>start_transaction</b>	marks the beginning of a transaction for performance analysis	315
<b>user_data_point</b>	records a user-defined data sample	409

## Miscellaneous Functions

Function	Description	See Page
<b>eval</b>	evaluates and executes the enclosed TSL statements	190
<b>getenv</b>	returns the value of any environment variable, as defined in the [WrCfg] section of <i>wrun.ini</i> in the WinRunner runtime environment	207
<b>load_16_dll</b>	performs a runtime load of a 16-bit Dynamic Link Library	249
<b>load_dll</b>	performs a runtime load of a Dynamic Link Library	250
<b>nargs</b>	returns the number of arguments passed to the function or test	259
<b>tl_step</b>	divides a test script into sections and inserts a status message in the test results for the previous section. When WinRunner is connected to a TestDirector project, the message is inserted in the TestDirector “step” table for each statement.	398
<b>tl_step_once</b>	divides a test script into sections and inserts a status message in the test results for the previous section. When WinRunner is connected to a TestDirector project, the message is inserted in the TestDirector “step” table once for each step name.	398
<b>unload_16_dll</b>	unloads a 16-bit DLL from memory	408
<b>unload_dll</b>	unloads a DLL from memory	408

## Operating System Functions

Function	Description	See Page
<b>dos_system</b>	executes a DOS command	162
<b>invoke_application</b>	invokes a Windows application from within a test script	228

## Password Functions

Function	Description	See Page
<b>password_edit_set</b>	sets the value of a password edit field to a given value	277
<b>password_encrypt</b>	encrypts a plain password	277

## QuickTest 2000 Functions

The following functions are available for QuickTest 2000 users only:

Function	Description	See Page
<b>qt_force_send_key</b>	instructs WinRunner 2000 to recognize an edit field which prompts a screen change when information is inserted	278
<b>qt_reset_all_force_send_key</b>	negates screen change configurations previously made using the <b>qt_force_send_key</b> function	279

## String Functions

Function	Description	See Page
<b>ascii</b>	returns the ASCII code of the first character in a string	115
<b>compare_text</b>	compares two strings	130
<b>index</b>	indicates the position of one string within another	227
<b>length</b>	counts characters in a string	231
<b>match</b>	finds a regular expression in a string	252
<b>split</b>	divides an input string into fields and stores them in an array	313
<b>sprintf</b>	returns a formatted string to a variable	314
<b>substr</b>	extracts a substring from a given string	322
<b>tolower</b>	converts uppercase characters to lowercase	399
<b>toupper</b>	converts lowercase characters to uppercase	405

## TDAPI Functions

To add the TDAPI functions to WinRunner's Function Generator, run the *tdapi* test in the *lib* folder of your WinRunner installation directory.

For explanations and examples of all TDAPI functions, refer to the *TestDirector Open Test Architecture Guide*.

### Project Connection Functions

Project connection functions let you select the TestDirector remote agent and project to which you want to connect. The TDAPI includes the following project connection functions:

Function	Description
<b>TDServerInitInstance</b>	creates a connection to the TestDirector remote agent
<b>TDServerRelease</b>	closes the connection to the TestDirector remote agent
<b>TDAPI_Connect</b>	connects to the specified project
<b>TDAPI_Disconnect</b>	disconnects from the currently connected project
<b>TDAPI_CreateTDDatabasesList</b>	creates a list of projects.
<b>TDAPI_GetDatabaseNameFromList</b>	retrieves the name of a project from a project list

### Test Functions

Test functions let you retrieve information relating to the tests stored in TestDirector's test repository. The TDAPI contains the following test functions:

Function	Description
<b>TDAPI_CreateTest</b>	creates a new test
<b>TDAPI_CreateTestList</b>	creates a list of all tests in the project
<b>TDAPI_DeleteTest</b>	deletes a test

Function	Description
<b>TDAPI_FindTestByPath</b>	locates a test by its file system path
<b>TDAPI_FindTestBySubjectPath</b>	locates a test by its subject path
<b>TDAPI_GetTestFieldSize</b>	returns the size of a field in a test.
<b>TDAPI_GetTestFullPath</b>	retrieves the full path of a test
<b>TDAPI_GetTestSubjectPath</b>	retrieves a test's subject path.
<b>TDAPI_GetTestValue</b>	retrieves the value of a field in a test
<b>TDAPI_SetTestValue</b>	updates a field in a test
<b>TDAPI_TestExists</b>	locates a test
<b>TDAPI_TestListMove</b>	steps through a list of tests

### Design Steps Functions

TestDirector tests are divided into design steps. These are detailed step-by-step instructions that describe the actions the tester (manual tests) or testing tool (automated tests) should perform as the test is executed. The TDAPI contains the following design steps functions:

Function	Description
<b>TDAPI_CreateDesStep</b>	creates a design step in a test
<b>TDAPI_CreateDesStepList</b>	creates a list of design steps
<b>TDAPI_DeleteDesStep</b>	deletes a design step in a test
<b>TDAPI_DesStepListMove</b>	steps through a list of design steps
<b>TDAPI_GetDesStepFieldSize</b>	returns the size of a design step field
<b>TDAPI_GetDesStepValue</b>	retrieves the value of a field in a design step
<b>TDAPI_SetDesStepValue</b>	updates a field in a design step record

## Defect Tracking Functions

Defect records contain errors discovered during test execution. Defect tracking functions let you add, locate, update defect information in your project. The TDAPI contains the following defect tracking functions:

Function	Description
<b>TDAPI_BugListMove</b>	steps through a list of defects
<b>TDAPI_CreateBug</b>	creates a new defect
<b>TDAPI_CreateBugList</b>	creates a list of defects in the project
<b>TDAPI_DeleteBug</b>	deletes a defect from the TestDirector project
<b>TDAPI_GetBugFieldSize</b>	returns the size of a defect field
<b>TDAPI_GetBugValue</b>	retrieves the value of a field in a defect
<b>TDAPI_SetBugValue</b>	updates a field in a defect

## Test Set Functions

A test set is a group of tests designed to meet a specific testing goal. For example, to verify that the application under test is functional and stable, you create a sanity test set that checks the application's basic features. The TDAPI contains the following functions to help you build and maintain test sets:

Function	Description
<b>TDAPI_AddTestToCycle</b>	adds a test to a test set
<b>TDAPI_CreateCycle</b>	creates a new test set
<b>TDAPI_CreateCycleList</b>	creates a list of test sets in the project
<b>TDAPI_CreateTestinCycleList</b>	creates a list of test sets in the project
<b>TDAPI_CycleExists</b>	checks a test set exists
<b>TDAPI_CycleListMove</b>	steps through a list of test sets
<b>TDAPI_DeleteCycle</b>	deletes a test set
<b>TDAPI_DeleteTestFromCycle</b>	removes a test from a test set

Function	Description
<b>TDAPI_GetCyclesForTest</b>	retrieves names of the test sets to which the test belongs
<b>TDAPI_GetCycleValue</b>	retrieves value of a field in a test set record
<b>TDAPI_GetCycleFieldSize</b>	returns the size of a field in a test set
<b>TDAPI_GetTestInCycleFieldSize</b>	returns the size (in bytes) of a field of a test in a test set.
<b>TDAPI_GetTestInCycleValue</b>	retrieves the value of a field in a test in a test set record
<b>TDAPI_SetCycleValue</b>	updates a field of a test set record to new value
<b>TDAPI_SetTestInCycleValue</b>	updates the specified field of a test set record to new value
<b>TDAPI_TestInCycleExists</b>	looks for a test in a test set
<b>TDAPI_TestInCycleListMove</b>	steps through a list of tests in a test set

### Test Run Functions

A test run stores information about how each test performs during test execution. The TDAPI includes the following functions to let you create and manage test runs:

Function	Description
<b>TDAPI_CreateRun</b>	creates a test run for a test
<b>TDAPI_CreateRunList</b>	creates a list of test runs
<b>TDAPI_CreatesStepList</b>	creates a list of steps
<b>TDAPI_DeleteRun</b>	deletes a test run
<b>TDAPI_GetRunFieldSize</b>	returns the size of a field in a test run
<b>TDAPI_GetRunValue</b>	retrieves value of a field in a test run
<b>TDAPI_RunListMove</b>	steps through a list of test runs
<b>TDAPI_SetRunValue</b>	updates a field in a test run record

## Test Step Functions

Test steps record the performance of each test step during a test run. Each test step contains detailed information on what actions were performed during each test run. These include the IDs of the test and test run, the name of the step, the status of the step, and the line number of where the step will appear within the test script. The TDAPI contains the following functions to help you create and manage test runs:

Function	Description
<b>TDAPI_AddStepToRun</b>	creates a step in a test run
<b>TDAPI_DeleteStep</b>	deletes a step in a test run
<b>TDAPI_GetStepFieldSize</b>	retrieves size of a field in a step
<b>TDAPI_GetStepValue</b>	returns the value of a field in a step
<b>TDAPI_SetStepValue</b>	updates a step to a new value
<b>TDAPI_StepListMove</b>	steps through a list of defects

## Test Plan Tree Functions

The test plan tree is a representation of how information is stored within your project. When you access the project, you use the tree to locate information in the project. The TDAPI contains the following functions to help you create and manage test plan trees:

Function	Description
<b>TDAPI_GetCategoryTreeRoot</b>	returns the ID of a the test plan tree's subject folder
<b>TDAPI_TreeAddNode</b>	adds a folder to the test plan tree
<b>TDAPI_TreeChanged</b>	indicates if changes were made to the test plan tree
<b>TDAPI_TreeCreateRoot</b>	sets a parent folder in the test plan tree
<b>TDAPI_TreeGetChild</b>	returns the ID of a subfolder in a test plan tree folder

Function	Description
<b>TDAPI_TreeGetNodeAttribute</b>	returns the ID of a subfolder in the test plan tree
<b>TDAPI_TreeGetNumberOfChildren</b>	returns the number of subfolders contained in a folder
<b>TDAPI_TreeGetRoot</b>	returns the ID of the current parent folder
<b>TDAPI_TreeGetSubjectIDFromPath</b>	returns the ID of a test plan tree folder

### Project Administration Functions

Project administration functions let you create and manage project users, return internal project error information, and view project statistics. The TDAPI includes the following project administration functions:

Function	Description
<b>TDAPI_CreateUser</b>	creates a new user
<b>TDAPI_CreateUserList</b>	creates a list of TestDirector users
<b>TDAPI_DeleteUser</b>	deletes a user
<b>TDAPI_GetFieldProperty</b>	returns information from the System_fields table
<b>TDAPI_GetFunctionStatistics</b>	returns performance statistics of TDAPI functions
<b>TDAPI_GetLastErrorString</b>	returns a description of an error
<b>TDAPI_GetStackErrorString</b>	returns all the errors in the error stack
<b>TDAPI.GetUserFieldSize</b>	returns the size of the field in a user record.
<b>TDAPI_GetUserValue</b>	returns value of a field in a user record
<b>TDAPI_SetUserValue</b>	updates a field in a user record
<b>TDAPI_UserExists</b>	checks whether a user record exists
<b>TDAPI_UserListMove</b>	returns the current user name.

## Testing Option Functions

Function	Description	See Page
<b>get_aut_var</b>	returns the value of a variable that determines how WinRunner learns descriptions of objects, records tests, and runs tests on Java applets or applications.	201
<b>getvar</b>	returns the value of a testing option	207
<b>set_aut_var</b>	sets how WinRunner learns descriptions of objects, records tests, and runs tests on Java applets or applications	290
<b>setvar</b>	sets the value of a testing option	294

## TestDirector Functions

The following functions are only available when working with TestDirector:

Function	Description	See Page
<b>tddb_get_step_value</b>	returns the value of a field in the "dessteps" table in a TestDirector database	365
<b>tddb_get_test_value</b>	returns the value of a field in the "test" table in a TestDirector database	366
<b>tddb_get_testset_value</b>	returns the value of a field in the "testcycl" table in a TestDirector database.	366
<b>tl_step</b>	divides a test script into sections	398

## Time-Related Functions

Function	Description	See Page
<b>end_transaction</b>	marks the end of a transaction for performance analysis	176
<b>get_time</b>	returns the current system time	206
<b>pause</b>	pauses test execution and displays a message	278
<b>start_transaction</b>	marks the beginning of a transaction for performance analysis	315
<b>time_str</b>	converts the integer returned by <b>get_time</b> to a string	397
<b>wait</b>	causes test execution to pause for the specified amount of time	410



# 5

---

## Return Values

Unless otherwise specified, functions may return one of the general return values listed below. This function returns one of the return values listed in “General Return Values,” on page 98.

In addition, some functions may return specialized return values.

- For database functions (**db\_**), see also “Return Values for PowerBuilder and Table Functions,” on page 103.
- For table and PowerBuilder functions (**tbl\_** and **datawindow\_**), see also “Return Values for Database Functions,” on page 102.
- For Terminal Emulator functions (**TE\_**), see also “Return Values for Terminal Emulator Functions,” on page 104.

## General Return Values

Unless otherwise specified, all functions may return one of the general return values listed below.

Error Code	Number	Description
E_OK	0	Operation successful.
E_FILE_OK	0	Operation successful.
E_GENERAL_ERROR	-10001	General error occurred.
E_NOT_FOUND	-10002	Window or object not found.
E_NOT_UNIQUE	-10003	More than one window or object responds to the physical description.
E_ILLEGAL_OPERATION	-10004	Operation invalid for object. For more information, see the note on page 102.
E_OUT_OF_RANGE	-10005	Parameter is out of range.
E_ILLEGAL_PARAMETER	-10006	Specified value for one or more parameters is invalid.
E_FILE_OPEN	-10007	Cannot open file. File may already be open.
E_NOT_IN_MAPPING	-10011	Cannot find window or object in the GUI map.
E_EXIST	-10012	Object already exists.
E_OPERATION_NOT_PERFORMED	-10018	Cannot perform requested operation.
E_FUNCTION_NOT_LOADED	-10019	Specified function is not currently loaded. In the case of a handler function, the exception is undefined.
E_NO_FONT	-10024	No font was loaded.
E_SYNTAX	-10025	Syntax error in TSL statement.

Error Code	Number	Description
E_NO_SVC	-10026	Called function does not exist.
E_FUNCTION_NOT_IMPLEMENTED	-10028	Called function could not be implemented.
E_ATTR_IN_DESC	-10029	Specified property is used in the object's physical description in the GUI map.
E_NO_LABEL	-10030	Label property is not used in the window's physical description in the GUI map.
E_FILE_NOT_OPEN	-10032	File is not open.
E_FILE_NOT_FOUND	-10033	File is not found.
E_FILE_LINE_TRUNC	-10034	File line is truncated.
E_FILE_EOF	-10035	End of file.
E_FILE_NOT_READ_MODE	-10036	Cannot read file because file is not in read mode.
E_FILE_READ_MODE	-10037	Cannot write to file because file is in read mode.
E_BAD_PATH	-10038	Incorrect path.
E_ACCESS_DENIED	-10039	Access is denied.
E_DISK_FULL	-10040	Disk is full.
E_SHARING_VIOLATION	-10041	Sharing violation.
E_FILE_ERROR	-10042	General file error.
E_NOT_PARAMETER	-10044	Parameter is invalid.
E_NOT_DISPLAYED	-10101	Window or object is not displayed.
E_DISABLED	-10102	Window or object is disabled.
E_IMPROPER_CLASS	-10103	Operation cannot be performed on this object class.

Error Code	Number	Description
E_ILLEGAL_KEY	-10104	Key or mouse button name is illegal.
E_ITEM_NOT_FOUND	-10105	Item in list or menu not found.
E_OBJECT_SYNTAX	-10107	Illegal syntax used.
E_ILLEGAL_NUM_OF_PARAMS	-10112	Number of parameters does not match those for the command.
E_AUT_DISCONNECTED	-10114	The application under test was disconnected.
E_ATTR_NOT_SUPPORTED	-10115	Property in function is not supported.
E_MISMATCH	-10116	Verification mismatch found.
E_ITEM_NOT_UNIQUE	-10117	More than one item in list or menu has this name.
E_TEXT_TOO_LONG	-10118	Text to be inserted exceeds maximum number of characters. The string will be truncated to the appropriate length.
E_DIFF	-10119	GUI checkpoint mismatch found.
E_CMP_FAILED	-10120	Comparison failed.
E_CAPT_FAILED	-10121	Capture failed.
E_WRONG_OBJ_FAILED	-10122	Object in checklist is not the object in the command.
E_SET_WIN	-10123	Window setting parameters missing.
E_BITMAP_TIMEOUT	-10124	The <b>wait_bitmap</b> operation exceeded specified wait time.

Error Code	Number	Description
E_BAD_CHECK_NAME	-10125	Syntax error in requested check.
E_OBJ_CAPT_FAILED	-10126	Capture failed for specified object.
E_UNEXP_WIN	-10127	Window in checklist is not the window in the command.
E_CAPT_FUNC_NOT_FOUND	-10128	Capture function not defined.
E_CMP_FUNC_NOT_FOUND	-10129	Compare function not defined.
E_TSL_ERR	-10130	Syntax error detected.
E_TOOLKIT_MISMATCH	-10131	Incorrect toolkit detected.
E_RECT_COVERED	-10132	Desired rectangle is hidden.
E_RECT_OUT	-10133	Desired rectangle does not appear on screen.
E_AREA_COVERED	-10134	Desired area is hidden.
E_AREA_OUT	-10135	Desired area does not appear on screen.
E_STR_NOT_FOUND	-10136	Text string not located.
E_WAIT_INFO_TIMEOUT	-10137	The <b>wait_info</b> operation exceeded specified wait time.
E_SYNC_FAILED	-10138	Synchronization failed.
E_DIFF_SIZE	-10139	Expected and actual bitmaps are different sizes.
E_DROP_WITHOUT_DRAG	-10141	Drop operation is performed without a drag operation preceding it.
E_VIR_OBJ	-10142	Function not supported for virtual objects.

Error Code	Number	Description
E_MISSING_ATTR	-10143	Lack of x-, y-, height, or width coordinates in the description of the virtual object.
E_EDIT_SET_FAILED	-10144	The <b>edit_set</b> operation failed.

**Note about E\_ILLEGAL\_OPERATION:** A function may fail if the method does not exist, the parameter number is wrong, the parameter types are wrong, etc. For more information regarding a failure, insert the following statement and then rerun the function. This will provide you with more details.

```
set_aut_var("DEBUG_GCALL", ON);
```

---

## Return Values for Database Functions

Unless otherwise specified in the function description, database functions (**db\_**) may return one of the following return values in addition to the regular return values.

Error Code	Number	Description
E_SESSION_NOT_STARTED	-10160	The database session was not started.
E_CONNECTION_FAILED	-10161	The connection to the database failed.
E_SQL_SYNTAX_ERROR	-10162	Syntax error in the SQL statement.
E_PASSED_LAST_ROW	-10163	The row number exceeded the row number of the last row in the table.
E_QUERY_CAPTURE_FAILED	-10164	General error while capturing data.

## Return Values for PowerBuilder and Table Functions

Unless otherwise specified, table and PowerBuilder functions (**tbl\_** and **datawindow\_**) may return one of the following return values in addition to the regular return values.

Error Code	Number	Description
PB_E_NO_PBTAPI	-10145	Internal error.
PB_E_ROW_COL_INVALID	-10146	Parameter is out of range.
PB_E_ROW_INVALID	-10147	Parameter is out of range.
PB_E_DESC_OVERFLOW	-10149	Internal error.
PB_E_DW_LIST_ITEM_NOT_FOUND	-10150	Item not found.
PB_E_DESC_NOT_FOUND	-10151	Internal error.
PB_E_CELL_NOT_VISIBLE	-10152	Cell not visible.
PB_E_PARSE_ERROR	-10153	Internal error.
PB_E_TAPI_ERROR	-10154	Internal error.
PB_E_BUF_NOT_INIT	-10155	Internal error.
PB_E_CELL_NOT_FOUND	-10156	Cell not found.
PB_E_API_ERROR	-10157	General error.
PB_E_INVALID_COL_TYPE	-10158	Unknown column type.
PB_E_ILLEGAL_COORDS	-10159	Illegal coordinates.

## Return Values for Terminal Emulator Functions

Unless otherwise specified in the function description, terminal emulator functions (**TE\_**) may return one of the following return values in addition to the regular return values.

WinRunner/TE Error Code	Number	Description
E_PROT_FIELD	-10400	Field is protected and cannot accept input.
E_TERM_DISCONNECTED	-10401	Terminal is probably disconnected.
E_TERM_LOCKED	-10402	Terminal is locked. In an interactive run, the user can continue, pause, or unlock the terminal. In a batch run, WinRunner unlocks the terminal and sends a report message.
E_TERM_BUSY	-10403	Terminal is synchronizing. In an interactive run, user can continue, pause, or perform <b>wait_sync</b> . In a batch run, WinRunner synchronizes and sends a report message.
E_RULE_NOT_FOUND	-10405	Cannot write to a merged field after all merged fields were reset.

# 6

---

## Alphabetical Reference

This chapter contains an alphabetical reference of all TSL functions in WinRunner. The name of each function appears, along with the type and the category to which the function belongs. The following additional information is provided for each function:

- description
- complete syntax
- parameter definitions
- return values
- availability

For additional information and examples of usage, refer to the *TSL Online Reference*. You can open the *TSL Online Reference* from the WinRunner group in the Start menu or from WinRunner's Help menu. To open the online reference to a specific function, click the context-sensitive Help button and then click a TSL statement in your test script, or place your cursor on a TSL statement in your test script and then press the F1 key. Check Mercury Interactive's Customer Support Web site for updates to the *TSL Online Reference*.

## ActiveBar\_combo\_select\_item

Context Sensitive • Active Bar

selects an item in a ComboBox tool.

**ActiveBar\_combo\_select\_item ( *band\_tool* , *item\_name* );**

*band\_tool*

A string containing the band identifier (Name or Caption) and tool identifier (Name, Caption or ToolID), separated by semicolon ( ; ).

The *band identifier* can be specified either by Name or Caption

The *tool identifier* can be specified either by Name, Caption, or ToolID. The ampersand character ( & ) in Caption is ignored.

*item\_name*

Either item text or item number in the "#" format.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for DataDynamics ActiveBar 1.0.

---

**Note:** This function is not recordable.

---

---

## ActiveBar\_dump

Context Sensitive • Active Bar

stores information about ActiveBar bands and tools. This information includes captions, names, types and IDs.

**ActiveBar\_dump ( *file\_name* );**

*file\_name*

The file pathname in which the ActiveBar information will be dumped.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for DataDynamics ActiveBar 1.0 and Sheridan ActiveToolbars 1.01.

---

**Note:** This function is not recordable.

---

## ActiveBar\_select\_menu

Context Sensitive • Active Bar

selects a menu item in a toolbar.

**ActiveBar\_select\_menu ( *band\_tool* [ , *events\_only* ] );**

*band\_tool*

A string containing the band identifier (Name or Caption) and tool identifier (Name, Caption or ToolID), separated by semicolon ( ; ).

The *band identifier* can be specified either by Name or Caption

The *tool identifier* can be specified either by Name, Caption, or ToolID. The ampersand character ( & ) in Caption is ignored.

*events\_only*

TRUE or FALSE.

If this parameter set to TRUE, then executing this function during a test run uses events.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for DataDynamics ActiveBar 1.0 and Sheridan ActiveToolbars 1.01.

---

**Note:** The *events\_only* parameter is supported only for the DataDynamics ActiveBar.

---

---

## ActiveBar\_select\_tool

Context Sensitive • Active Bar

selects a tool in the toolbar.

**ActiveBar\_select\_tool** (*band\_tool* [ , *events\_only* ]);

*band\_tool*

A string containing the band identifier (Name or Caption) and tool identifier (Name, Caption or ToolID), separated by semicolon ( ; ).

The *band identifier* can be specified either by Name or Caption

The *tool identifier* can be specified either by Name, Caption, or ToolID. The ampersand character ( & ) in Caption is ignored.

*events\_only*

TRUE or FALSE.

If this parameter set to TRUE, then executing this function during a test run uses events.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for DataDynamics ActiveBar 1.0 and Sheridan ActiveToolbars 1.01.

---

**Note:** The *events\_only* parameter is supported only for the DataDynamics ActiveBar.

---

## ActiveX\_activate\_method

Context Sensitive • ActiveX/Visual Basic

invokes an ActiveX method of an ActiveX control.

**ActiveX\_activate\_method** (*object*, *ActiveX\_method*, *return\_value*  
[*param*<sub>4</sub>, ..., *param*<sub>8</sub>]);

<i>object</i>	The name of the object.
<i>ActiveX_method</i>	The ActiveX control method to be invoked.
<i>return_value</i>	Return value of the method.
<i>param</i> <sub>4</sub> , ..., <i>param</i> <sub>8</sub>	The parameters of the method (optional). These parameters may only be call variables and not constants.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## ActiveX\_get\_info

Context Sensitive • ActiveX/Visual Basic

returns the value of an ActiveX/Visual Basic control property.

**ActiveX\_get\_info** (*object*, *property*, *out\_value*);

<i>object</i>	The name of the ActiveX/Visual Basic control.
<i>property</i>	Any ActiveX/Visual Basic control property.
<i>out_value</i>	The output variable that stores the property value.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## ActiveX\_set\_info

Context Sensitive • ActiveX/Visual Basic

sets the value of a property in an ActiveX/Visual Basic control.

**ActiveX\_set\_info ( *object*, *property*, *value* [ ,*type* ] );**

<i>object</i>	The name of the ActiveX/Visual Basic control.	
<i>property</i>	Any ActiveX/Visual Basic control property.	
<i>value</i>	The value to be applied to the property.	
<i>type</i>	The value type to be applied to the property. The following types are available:	
VT_I2 (short)	VT_I4 (long)	VT_R4 (float)
VT_R8 (float double)	VT_DATE (date)	VT_BSTR (string)
VT_ERROR (S code)	VT_BOOL (boolean)	VT_UI1 (unsigned char)

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

**add\_cust\_record\_class**

Customization • Custom Record

associates a custom record function or a logical name function with a custom class.

**add\_cust\_record\_class ( *MSW\_class*, *dll\_name* [ , *rec\_func* ] [ , *log\_name\_func* ] );**

*MSW\_class*                   The custom class with which the function is associated.

*dll\_name*                   The full path of the DLL containing the function.

*rec\_func*                   The name of the custom record function defined in the DLL. This custom record function returns the statement recorded in the test script.

*log\_name\_func*           The name of the logical name function defined in the DLL. This logical name function supplies custom logical names for GUI objects in the custom class, *MSW\_class*.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**add\_dolph\_obj**

Context Sensitive • Delphi

adds a Delphi object.

**add\_dolph\_obj** (*MSW\_class*, *class*, *oblig\_attr*, *optional\_attr*, *default\_check\_prop*, *item*);

<i>MSW_class</i>	The custom class with which the function is associated.
<i>class</i>	The name of the Mercury class, <i>MSW_class</i> , or <i>X_class</i> .
<i>oblig_attr</i>	A list of obligatory properties (separated by blank spaces).
<i>optional_attr</i>	A list of optional properties (separated by blank spaces), in descending order, to add to the description until the object is uniquely identified.
<i>default_check_prop</i>	The default status of the object.
<i>item</i>	Indicates whether the item is an object or a grid.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available only for WinRunner with Delphi support.

---

## add\_record\_attr

Customization • Custom Record

registers a custom property.

**add\_record\_attr ( *attr\_name*, *dll\_name*, *query\_func\_name*, *verify\_func\_name* );**

*attr\_name*                   The name of the custom property to register. This cannot be a standard WinRunner property name.

*dll\_name*                   The full path of the DLL in which the query and verify functions are defined.

*query\_func\_name*           The name of the query function included in the DLL.

*verify\_func\_name*          A WinRunner standard property verification function (see below) or a custom property verification function included in the DLL.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## add\_record\_message

Customization • Custom Record

adds a message to the list of Windows messages.

**add\_record\_message ( *message\_number* );**

*message\_number*           The number or identifier of the Windows message.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**ascii**

Standard • String

returns the ASCII code of the first character in a string.

**ascii ( *string* );**

*string*                   A string expression.

Return Values

This function returns the ASCII code of the first character in the string.

Availability

This function is always available.

---

**atan2**

Standard • Arithmetic

returns the arctangent of y/x.

**atan2 ( *y*, *x* );**

Return Values

This function returns a real number.

Availability

This function is always available.

**button\_check\_info**

Context Sensitive • Button Object

checks the value of a button property.

**button\_check\_info ( *button*, *property*, *property\_value* );**

*button*                   The logical name of the button.

*property*               The property to check.

*property\_value*       The property value.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**button\_check\_state**

Context Sensitive • Button Object

checks the state of a radio or check button.

**button\_check\_state ( *button*, *state* );**

*button*                   The logical name of the button.

*state*                   The state of the button. The value can be 1 (ON) or 0 (OFF). A value of 2 indicates that the button is DIMMED.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**button\_get\_info**

Context Sensitive • Button Object

returns the value of a button property.

**button\_get\_info ( *button*, *property*, *out\_value* );**

*button*                   The logical name of the button.

*property*               Any of the properties listed in the *User's Guide*.

*out\_value*              The output variable that stores the value of the specified property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**button\_get\_state**

Context Sensitive • Button Object

returns the state of a radio or check button.

**button\_get\_state ( *button*, *out\_state* );**

*button*                   The logical name of the button.

*out\_state*              The output variable that stores the state of the button. For check and radio buttons, the value can be 1 (ON) or 0 (OFF). A value of 2 indicates that the button is DIMMED. For push buttons, the value is 0.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

button\_press

clicks on a push button.

**button\_press ( *button* );**

Context Sensitive • Button Object

*button* The logical name of the button.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

button\_set

Context Sensitive • Button Object

**sets the state of a radio or check button.**

**button\_set ( *button*, *state* );**

***button*** The logical name of the button.

**state** One of the following states can be specified: DIMMED, ON, OFF, or TOGGLE.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**button\_wait\_info**

Context Sensitive • Button Object

waits for the value of a button property.

**button\_wait\_info ( *button*, *property*, *value*, *time* );**

<i>button</i>	The logical name of the button.
<i>property</i>	Any of the properties listed in the <i>WinRunner User's Guide</i> .
<i>value</i>	The property value.
<i>time</i>	Indicates the maximum interval, in seconds, before the next statement is executed.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**calendar\_activate\_date**

Context Sensitive • Calendar

double-clicks the specified date in a calendar.

**calendar\_activate\_date ( *calendar*, *date* );**

<i>calendar</i>	The logical name of the calendar.
<i>date</i>	The date in the calendar.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is supported for ActiveX controls.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

## calendar\_get\_selected

Context Sensitive • Calendar

retrieves and counts the selected dates in a calendar.

**calendar\_get\_selected** (*calendar*, *selected\_dates*, *selected\_dates\_count*  
[ ,*selected\_time* ]);

<i>calendar</i>	The logical name of the calendar.
<i>selected_dates</i>	The output variable that stores the dates selected in the calendar.
<i>selected_dates_count</i>	The output variable that stores the total number of selected dates in the calendar.
<i>selected_time</i>	The output variable that stores the time selected. This parameter is valid for the Date Time control only.

### Return Values

This function returns a string representing the date and an integer representing the number of dates chosen.

### Availability

This function is supported for ActiveX controls.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

---

## calendar\_get\_status

Context Sensitive • Calendar

retrieves the selection status.

**calendar\_get\_status** (*calendar*, *selection\_status*);

<i>calendar</i>	The logical name of the calendar.
<i>selection_status</i>	The status of the date; it may either be valid or invalid.

Based on the validity of the date, **calendar\_get\_status** retrieves the integer 1 (valid) or 0 (invalid).

## Return Values

This function returns an integer, 1 or 0, based on whether or not the status is valid or invalid.

## Availability

This function is supported for the Date Time control only.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

## `calendar_get_valid_range`

Context Sensitive • Calendar

retrieves the range of allowed values for a calendar control.

`calendar_get_valid_range ( calendar, in_range_type, allowed_min_time,  
                                  allowed_max_time );`

*calendar*                         The logical name of the calendar.

*in\_range\_type*                 DATE\_TYPE (1) minimum and maximum allowed **date** values for the control.

TIME\_TYPE (0) minimum and maximum allowed **time** values for the control.

*allowed\_min\_time*             The minimum allowed date or time of the control, according to the *in\_range\_type* parameter.

*allowed\_max\_time*             The maximum allowed date or time of the control, according to the *in\_range\_type* parameter.

## Return Values

This function returns two strings representing the minimum and maximum dates allowed.

## Availability

This function is available for the Date Time and Month Calendar controls only.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

## calendar\_select\_date

Context Sensitive • Calendar

clicks the specified date in a calendar.

**calendar\_select\_date** (*calendar, date*);

**calendar** The logical name of the calendar.

**date** The date is recorded in the following format: DD-MMM-YYYY. Numbers as well letters may be used for months.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for ActiveX controls only.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

## calendar\_select\_range

Context Sensitive • Calendar

selects a range of dates in the DD-MMM-YYYY date format.

```
calendar_select_range ( calendar, start_date, end_date);
```

*calendar* The logical name of the calendar.

*start\_date* The first day in the range.

*end\_date* The last day in the range.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for the Month Calendar control with the multiple selection policy only.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

## calendar\_select\_time

Context Sensitive • Calendar

when a date is recorded with a time, WinRunner records the time using this function in the HH:MM:SS time format.

**calendar\_select\_time** (*calendar, time*);

*calendar* The logical name of the calendar.

*time* The time selected in the HH:MM:SS format.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is valid for the Date Time control only.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

**calendar\_set\_status**

Context Sensitive • Calendar

sets the selection status.

**calendar\_set\_status** (*calendar, selection\_status*);

*calendar*

The logical name of the calendar.

*selection\_status*

The status of the date may be valid (1) or invalid (2). The valid selection status selects the check box and the invalid selection clears the check box.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is valid for the Date Time control only.

This function is available for calendars included in Visual Studio version 6 and higher and in Internet Explorer Active Desktop version 4 and higher.

---

**call**

Standard • Call Statements

invokes a test from within a test script.

**call** *test\_name* ( [ *parameter<sub>1</sub>*, *parameter<sub>2</sub>*, ... *parameter<sub>n</sub>* ] );

*test\_name*

The name of the test to invoke.

*parameter*

The parameters defined for the called test.

#### Return Values

The **call** statement returns an empty string, unless the called test returns an expression using **treturn** or **texit**.

#### Availability

This function is always available.

---

**call\_chain\_get\_attr**

Standard • Call Statements

returns information about a test or function in the call chain.

**call\_chain\_get\_attr ( *property*, *level*, *out\_value* );**

*property* One of the properties listed in the table below.

*level* A number indicating the test or function in the call chain.  
0 indicates the current test/function; 1 indicates the  
test/function that called the current item; 2 indicates two  
levels above the current item, etc.

*out\_value* The output variable that stores the value of the specified  
*property*.

Property	Description
testname	The name of the test/function specified by level.
line_no	The line number where the test call statement or function call appears.
type	Indicates whether the call item is a test or a function.
function	If the specified call item is a function, its name.

#### Return Values

This statement returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

## call\_chain\_get\_depth

Standard • Call Statements

returns the number of items in the call chain.

`call_chain_get_depth ()`;

The **call\_chain\_get\_depth** statement returns the number of tests or functions in the current call chain.

### Return Values

This statement returns the number of items in the call chain, or 0 when the call chain is empty.

### Availability

This function is always available.

---

## call\_close

Standard • Call Statements

invokes a test from within a script and closes the test when the test is completed.

`call_close test_name ( [ parameter1, parameter2, ... parametern ] )`;

*test\_name*                   The name of the test to invoke.

*parameter*               The parameters defined for the called test.

### Return Values

The **call\_close** statement returns an empty string, unless the called test returns an expression using **treturn** or **texit**.

### Availability

This statement is always available.

---

## check\_window

Analog • Bitmap Checkpoint

compares a bitmap of a window to an expected bitmap.

---

**Note:** This function is provided for backward compatibility only. You should use the corresponding Context Sensitive **win\_check\_bitmap** and **obj\_check\_bitmap** functions.

---

**check\_window ( *time*, *bitmap*, *window*, *width*, *height*, *x*, *y* [, *relx*<sub>1</sub>, *rely*<sub>1</sub>, *relx*<sub>2</sub>, *rely*<sub>2</sub>] );**

<i>time</i>	Indicates the interval between the previous input event and the bitmap capture, in seconds. This interval is added to the <i>timeout_msec</i> testing option. The sum is the interval between the previous event and the bitmap capture, in seconds.
<i>bitmap</i>	A string identifying the captured bitmap. The string length is limited to 6 characters.
<i>window</i>	A string indicating the name in the window banner.
<i>width</i> , <i>height</i>	The size of the window, in pixels.
<i>x</i> , <i>y</i>	The position of the upper left corner of the window (relative to the screen). In the case of an MDI child window, the position is relative to the parent window.
<i>relx</i> <sub>1</sub> , <i>rely</i> <sub>1</sub>	For an area bitmap: the coordinates of the upper left corner of the rectangle, relative to the upper left corner of the client window (the <i>x</i> and <i>y</i> parameters).
<i>relx</i> <sub>2</sub> , <i>rely</i> <sub>2</sub>	For an area bitmap: the coordinates of the lower right corner of the rectangle, relative to the lower right corner of the client window (the <i>x</i> and <i>y</i> parameters).

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

The **check\_window** function is not available for LoadRunner GUI Vusers running on UNIX platforms. In this case, **check\_window** statements are treated as **wait\_window** statements.

---

## click

Analog • Input Device

inputs a mouse button click.

**click ( *mouse\_button* [ , *time* ] );**

*mouse\_button*      The name of the mouse button to be activated. The names (Left, Right, Middle) are defined by the XR\_INP\_MKEYS system parameter in the system configuration file.

*time*      The interval that elapses before the click is entered, in seconds. The default, if no *time* is specified, is 0.

## Return Values

The return value of the function is always 0.

## Availability

This function is always available.

---

**click\_on\_text**

Analog• Input Device

clicks on a string.

---

**Note:** This function is provided for backward compatibility only. You should use the correspondingly Context Sensitive **obj\_click\_on\_text** and **win\_click\_on\_text** functions.

---

**click\_on\_text ( *string*, *x<sub>1</sub>*, *y<sub>1</sub>*, *x<sub>2</sub>*, *y<sub>2</sub>* [ , *click\_sequence* ] );**

*string* A complete string, preceded and followed by a space outside the quotation marks. A regular expression with no blank spaces can be specified.

*x<sub>1</sub>,y<sub>1</sub>,x<sub>2</sub>,y<sub>2</sub>* The area of the screen to be searched, specified by the coordinates *x<sub>1</sub>,y<sub>1</sub>,x<sub>2</sub>,y<sub>2</sub>* , which define any two diagonal corners of a rectangle. The interpreter searches for the text in the area defined by the rectangle.

*click\_sequence* The mouse button clicks that are part of the string's input. The mouse button input is evaluated to a string using the conventions of the click function. (For further details, see the description under click.) The default, if no *click\_sequence* is specified, is a single click of the left mouse button.

#### Return Values

This function returns 0 if the text is located. If the text is not found, the function returns 1.

#### Availability

This function is always available.

**compare\_text**

Standard • String

compares two strings.

**compare\_text ( str<sub>1</sub>, str<sub>2</sub> [ , chars<sub>1</sub>, chars<sub>2</sub> ] );**

str<sub>1</sub>, str<sub>2</sub>                    The two strings to be compared.

chars<sub>1</sub>                        One or more characters in the first string.

chars<sub>2</sub>                        One or more characters in the second string. These characters are substituted for those in chars<sub>1</sub>.

**Return Values**

This function returns the value 1 when the two strings are the same, and 0 when they are different.

**Availability**

This function is always available.

---

**COS**

Standard • Arithmetic

calculates the cosine of an angle.

**cos ( x );**

x                                Specifies an angle, expressed in radians.

**Return Values**

This function returns a real number.

**Availability**

This function is always available.

---

**create\_browse\_file\_dialog**

Customization • Custom User Interface

displays a browse dialog box from which the user selects a file.

**create\_browse\_file\_dialog ( *filter<sub>1</sub>* [ ; *filter<sub>2</sub>*; *filter<sub>3</sub>*; ...*filter<sub>n</sub>* ] );**

*filter*

Sets one or more filters for the files to display in the browse dialog box. You can use wildcards to display all files (\*.\*) or only selected files (\*.exe or \*.txt, etc.). Multiple files are separated by semicolons and all the filters together are considered a single string.

**Return Values**

This function returns a string representing the label of the selected file.

**Availability**

This function is always available.

## create\_custom\_dialog

Customization • Custom User Interface

creates a custom dialog box.

**create\_custom\_dialog** (*function\_name*, *title*, *button\_name*, *edit\_name<sub>1</sub>*, [*edit\_name<sub>2</sub>*,]  
  *check\_name<sub>1</sub>* [, *check\_name<sub>2</sub>*]);

*function\_name*      The name of the function that is executed when you press the "execute" button.

*title*      An expression that appears in the window banner of the dialog box.

*button\_name*      The label that will appear on the "execute" button. You press this button to execute the contained function.

*edit\_name*      The labels of the edit box(es) of the dialog box. Multiple edit box labels are separated by commas, and all the labels together are considered a single string. If the dialog box has no edit boxes, this parameter must be an empty string (empty quotation marks).

*check\_name*      Contains the labels of the check boxes in the dialog box. Multiple check box labels are separated by commas, and all the labels together are considered a single string. If the dialog box has no check boxes, this parameter must be an empty string (empty quotation marks).

### Return Values

This function returns a string representing the return value of the function executed when the **Execute** button is clicked and an empty string is returned when the **Cancel** button is clicked.

### Availability

This function is always available.

---

## create\_input\_dialog

Customization • Custom User Interface

creates a dialog box with an edit box.

**create\_input\_dialog ( *message* );**

*message*

Any expression. This expression will appear in the dialog box as a single line.

Return Values

This function returns a string. If no string is found or if the Cancel button is pressed within the dialog box, then the function returns NULL.

Availability

This function is always available.

---

## create\_list\_dialog

Customization • Custom User Interface

creates a dialog box with a list of items.

**create\_list\_dialog ( *title*, *message*, *item\_list* );**

*title*

The expression that appears in the banner of the dialog box.

*message*

The message for the user.

*item\_list*

The items that make up the list, separated by commas.

Return Values

This function returns a string. If no string is found or if the Cancel button is pressed within the dialog box, then this function returns NULL.

Availability

This function is always available.

---

## create\_password\_dialog

Customization • Custom User Interface

creates a password dialog box.

**create\_password\_dialog ( *login*, *password*, *login\_out*, *password\_out*  
[ , *encrypt\_password* ] );**

<i>login</i>	The label of the first edit box, used for user-name input. If you specify an empty string (empty quotation marks), the default label "Login" is displayed.
<i>password</i>	The label of the second edit box, used for password input. If you specify an empty string (empty quotation marks), the default label "Password" is displayed. When the user enters input into this edit box, the characters do not appear on the screen, but are represented by asterisks.
<i>login_out</i>	The name of the parameter to which the contents of the first edit box (login) are passed. Use this parameter to verify the contents of the login edit box.
<i>password_out</i>	The name of the parameter to which the contents of the second edit box (password) are passed. Use this parameter to verify the contents of the password edit box.
<i>encrypt_password</i>	A Boolean parameter which allows the output edit field value to be encrypted. If this parameter is left blank, the default value is FALSE.

### Return Values

This function returns the number “1” if the **OK** button is pressed and “0” if the **Cancel** button is pressed.

### Availability

This function is always available.

---

**datawindow\_get\_info**

Context Sensitive • PowerBuilder

retrieves the value of a DataWindow object property.

**datawindow\_get\_info ( *DataWindow\_object*, *property*, *out\_value* );**

<i>DataWindow_object</i>	The logical name of the DataWindow object.
<i>property</i>	The full property description (similar to the formats in the PowerBuilder Describe function, e.g. obj.property...).
<i>out_value</i>	The output variable that stores the value of the specified property (maximum size 2,000 characters).

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for PowerBuilder and Table Functions,” on page 103.

Availability

This function is available whenever the PowerBuilder add-in is loaded.

---

**datawindow\_text\_click**

Context Sensitive • PowerBuilder

clicks a DataWindow text object.

**datawindow\_text\_click ( *DataWindow\_object*, *DataWindow\_text\_object* );**

<i>DataWindow_object</i>	The logical name of the DataWindow object.
<i>DataWindow_text_object</i>	The text property of the DataWindow object (and NOT the internal PowerBuilder name).

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for PowerBuilder and Table Functions,” on page 103.

Availability

This function is available whenever the PowerBuilder add-in is loaded.

**datawindow\_text dbl click**

Context Sensitive • PowerBuilder

double-clicks a DataWindow text object.

**datawindow\_text dbl click** ( *DataWindow\_object*, *DataWindow\_text\_object* );

*DataWindow\_object*      The logical name of the DataWindow object.

*DataWindow\_text\_object*      The text property of the DataWindow object  
(and NOT the internal PowerBuilder name).

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for PowerBuilder and Table Functions,” on page 103.

**Availability**

This function is available whenever the PowerBuilder add-in is loaded.

---

**db\_check**

Context Sensitive • Database

compares current database data to expected database data.

**db\_check** ( *checklist*, *expected\_results\_file* [ , *max\_rows* [ , *paramater\_array* ] ] );

*checklist*      The name of the checklist specifying the checks to perform.

*expected\_results\_file*      The name of the file storing the expected database data.

*max\_rows*      The maximum number of rows retrieved in a database. If no maximum is specified, then by default the number of rows is not limited. If you change this parameter in a **db\_check** statement recorded in your test script, you must run the test in Update mode before you run it in Verify mode.

***paramater\_array***

The array of parameters for the SQL statement. For information on working with this advanced feature, refer to the “Checking Databases” chapter in the *WinRunner User’s Guide*.

**Return Values**

This function returns 1 for a successful bitmap capture or comparison. Otherwise, this function returns 0. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

**Availability**

This function is always available.

---

**db\_connect**

Context Sensitive • Database

creates a new database session and establishes a connection to an ODBC database.

**db\_connect ( *session\_name*, *connection\_string* );**

*session\_name*                   The logical name of the database session.

*connection\_string*           The connection parameters to the ODBC database.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

**Availability**

This function is always available.

---

**db\_disconnect**

Context Sensitive • Database

disconnects from the database and ends the database session.

**db\_disconnect ( *session\_name* );**

*session\_name*      The logical name of the database session.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

Availability

This function is always available.

---

**db\_dj\_convert**

Context Sensitive • Database

runs a Data Junction export file (\*.djs file).

**db\_dj\_convert ( *djs\_file* [ , *output\_file* [ , *headers* [ , *record\_limit* ] ] ] );**

*djs\_file*      The Data Junction export file.

*output\_file*      An optional parameter to override the name of the target file.

*headers*      An optional Boolean parameter that will include or exclude the column headers from the Data Junction export file.

*record\_limit*      The maximum number of records that will be converted.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

Availability

This function is only available for users working with Data Junction.

---

**db\_execute\_query**

Context Sensitive • Database

executes the query based on the SQL statement and creates a record set.

**db\_execute\_query ( *session\_name*, *SQL*, *record\_number* );**

*session\_name*                   The logical name of the database session.

*SQL*                           The SQL statement.

*record\_number*               An out parameter returning the number of records in the result query.

For information on this advanced feature, refer to the “Checking Databases” chapter in the *WinRunner User’s Guide*.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

#### Availability

This function is always available.

**db\_get\_field\_value**

Context Sensitive • Database

returns the value of a single field in the database.

**db\_get\_field\_value ( *session\_name*, *row\_index*, *column* );**

*session\_name*

The logical name of the database session.

*row\_index*

The numeric index of the row. (The first row is always numbered “#0”.)

*column*

The name of the field in the column or the numeric index of the column within the database. (The first column is always numbered “#0”.)

**Return Values**

In case of an error, an empty string will be returned. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

**Availability**

This function is always available.

---

**db\_get\_headers**

Context Sensitive • Database

returns the number of column headers in a query and the content of the column headers, concatenated and delimited by tabs.

**db\_get\_headers ( *session\_name*, *header\_count*, *header\_content* );**

*session\_name*

The logical name of the database session.

*header\_count*

The number of column headers in the query.

*header\_content*

The column headers concatenated and delimited by tabs.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

## Availability

This function is always available.

---

### db\_get\_last\_error

Context Sensitive • Database

returns the last error message of the last ODBC or Data Junction operation.

**db\_get\_last\_error ( *session\_name*, *error* );**

*session\_name*                   The logical name of the database session.

*error*                         The error message.

---

**Note:** When working with Data Junction, the *session\_name* parameter is ignored.

---

## Return Values

If there is no error message, an empty string will be returned.

## Availability

This function is always available.

---

**db\_get\_row**

Context Sensitive • Database

returns the content of the row, concatenated and delimited by tabs.

**db\_get\_row** (*session\_name*, *row\_index*, *row\_content*);

*session\_name*      The logical name of the database session.

*row\_index*      The numeric index of the row. (The first row is always numbered “0”.)

*row\_content*      The row content as a concatenation of the fields values, delimited by tabs.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

#### Availability

This function is always available.

---

**db\_write\_records**

Context Sensitive • Database

writes the record set into a text file delimited by tabs.

**db\_write\_records** (*session\_name*, *output\_file* [ , *headers* [ , *record\_limit* ] ]);

*session\_name*      The logical name of the database session.

*output\_file*      The name of the text file in which the record set is written.

*headers*      An optional Boolean parameter that will include or exclude the column headers from the record set written into the text file.

*record\_limit*      The maximum number of records in the record set to be written into the text file. A value of NO\_LIMIT (the default value) indicates there is no maximum limit to the number of records in the record set.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98 and “Return Values for Database Functions,” on page 102.

## Availability

This function is always available.

---

## dbl\_click

Analog • Input Device

double-clicks a mouse button.

**dbl\_click ( *mouse\_button* [ , *time* ] );**

***mouse\_button***      The mouse button to activate. The names ("Left," "Right," "Middle") are defined by the XR\_INP\_MKEYS system parameter in the system configuration file.

***time***      The interval that elapses before the click is entered, in seconds. The default, if no *time* is specified, is 0.

## Return Values

This function always returns 0.

## Availability

This function is always available.

**ddt\_close**

Context Sensitive • Data-Driven Test

closes a data table file.

**ddt\_close ( *data\_table\_filename* );**

*data\_table\_filename*      The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**ddt\_export**

Context Sensitive • Data-Driven Test

exports the information of one data table file into a different data table file.

**ddt\_export ( *data\_table\_filename*<sub>1</sub>, *data\_table\_filename*<sub>2</sub> );**

*data\_table\_filename*<sub>1</sub>      The source data table filename.

*data\_table\_filename*<sub>2</sub>      The destination data table filename.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**ddt\_get\_current\_row**

Context Sensitive • Data-Driven Test

retrieves the active row of a data table.

**ddt\_get\_current\_row ( *data\_table\_filename*, *out\_row* );**

***data\_table\_filename***      The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters. This row is labeled row 0.

***out\_row***      The output variable that stores the active row in the data table.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**ddt\_get\_parameters**

Context Sensitive • Data-Driven Test

returns a list of all parameters in a data table.

**ddt\_get\_parameters ( *table*, *params\_list*, *params\_num* );**

***table***      The pathname of the data table.

***params\_list***      This out parameter returns the list of all parameters in the data table, separated by tabs.

***params\_num***      This out parameter returns the number of parameters in *params\_list*.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

**ddt\_get\_row\_count**

Context Sensitive • Data-Driven Test

retrieves the number of rows in a data table.

**ddt\_get\_row\_count ( *data\_table\_filename*, *out\_rows\_count* );**

*data\_table\_filename*      The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters.

*out\_rows\_count*      The output variable that stores the total number of rows in the data table.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**ddt\_is\_parameter**

Context Sensitive • Data-Driven Test

returns whether a parameter in a data table is valid.

**ddt\_is\_parameter ( *data\_table\_filename*, *parameter* );**

*data\_table\_filename*      The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters.

*parameter*      The parameter name to check in the data table.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**ddt\_next\_row** Context Sensitive • Data-Driven Test

changes the active row in a data table to the next row.

**ddt\_next\_row ( *data\_table\_filename* );**

*data\_table\_filename* The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters.

#### Return Values

If the active row is the last row in a data table, then the E\_OUT\_OF\_RANGE value is returned.

#### Availability

This function is always available.

---

**ddt\_open** Context Sensitive • Data-Driven Test

creates or opens a data table file so that WinRunner can access it.

**ddt\_open ( *data\_table\_filename*, *mode* );**

*data\_table\_filename* The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters. This row is labeled row 0.

*mode* The mode for opening the data table: DDT\_MODE\_READ (read-only) or DDT\_MODE\_READWRITE (read or write).

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**ddt\_report\_row**

Context Sensitive • Data-Driven Test

reports the active row in a data table to the test results.

**ddt\_report\_row ( *data\_table\_filename* );**

*data\_table\_filename*

The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters. This row is labeled row 0.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**ddt\_save**

Context Sensitive • Data-Driven Test

saves the information in a data table.

**ddt\_save ( *data\_table\_filename* );**

*data\_table\_filename*

The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**ddt\_set\_row**

Context Sensitive • Data-Driven Test

sets the active row in a data table.

**ddt\_set\_row ( *data\_table\_filename*, *row* );**

*data\_table\_filename*      The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters. This row is labeled row 0.

*row*      The new active row in the data table.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**ddt\_set\_val**

Context Sensitive • Data-Driven Test

sets a value in the current row of the data table.

**ddt\_set\_val ( *data\_table\_filename*, *parameter*, *value* );**

<i>data_table_filename</i>	The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters. This row is labeled row 0.
<i>parameter</i>	The name of the column into which the value will be inserted.
<i>value</i>	The value to be written into the table.

---

**Note:** You can only use this function if the data table was opened in DDT\_MODE\_READWRITE (read or write mode).

---

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

**ddt\_set\_val\_by\_row**

Context Sensitive • Data-Driven Test

sets a value in a specified row of the data table.

**ddt\_set\_val\_by\_row ( *data\_table\_filename*, *row*, *parameter*, *value* );**

<i>data_table_filename</i>	The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters. This row is labeled row 0.
<i>row</i>	The row number in the table.
<i>parameter</i>	The name of the column into which the value will be inserted.
<i>value</i>	The value to be written into the table.

---

**Note:** You can only use this function if the data table was opened in DDT\_MODE\_READWRITE (read or write mode).

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## ddt\_show

Context Sensitive • Data-Driven Test

shows or hides the table editor of a specified data table.

**ddt\_show ( *data\_table\_filename*, *show\_flag* );**

*data\_table\_filename*      The name of the data table.

*show\_flag*      The value indicating whether the editor is to be shown.  
The *show\_flag* value is 1 if the table editor is to be shown  
and is 0 if the table editor is to be hidden.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## ddt\_update\_from\_db

Context Sensitive • Data-Driven Test

imports data from a database into a data table.

**ddt\_update\_from\_db ( *data\_table\_filename*, *file*, *out\_row\_count* [ , *max\_rows* ] );**

*data\_table\_filename*      The name of the data table file.

*file*      Either an \*.sql file containing an ODBC query or a \*.djs file containing a conversion defined by Data Junction.

*out\_row\_count*      An out parameter containing the number of rows retrieved from the data table.

*max\_rows*      An in parameter specifying the maximum number of rows to be retrieved from a database. If no maximum is specified, then by default the number of rows is not limited.

---

**Note:** You must use a **ddt\_open** statement to open the data table in READWRITE mode before you can use this function.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## ddt\_val

Context Sensitive • Data-Driven Test

returns the value of a parameter in the active row in a data table.

**ddt\_val** (*data\_table\_filename*, *parameter*);

*data\_table\_filename*      The name of the data table file. The data table is a Microsoft Excel 5.0/95 file or a tabbed text file. The first row in the file contains the names of the parameters.

*parameter*      The name of the parameter in the data table.

## Return Values

This functions returns the value of a parameter in the active row in a data table.

In the case of an error, this function returns an empty string.

## Availability

This function is always available.

---

**ddt\_val\_by\_row**

Context Sensitive • Data-Driven Test

returns the value of a parameter in the specified row in a data table.

**ddt\_val\_by\_row ( *data\_table\_filename*, *row\_number*, *parameter* );**

<i>data_table_filename</i>	The name of the data table file. The data table is a Microsoft Excel 5.0 file/95 or a tabbed text file. The first row in the file contains the names of the parameters. This row is labeled row 0.
<i>row_number</i>	The number of the row in the data table.
<i>parameter</i>	The name of the parameter in the data table.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**declare\_rendezvous**

Standard • Load Testing

declares a rendezvous.

**declare\_rendezvous ( *rendezvous\_name* );**

<i>rendezvous_name</i>	The name of the rendezvous. This must be a string constant and not a variable or an expression. The <i>rendezvous_name</i> can be a maximum of 128 characters. It cannot contain any spaces.
------------------------	--

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for LoadRunner GUI Vusers only.

---

**declare\_transaction**

Standard • Load Testing

declares a transaction.

**declare\_transaction ( *transaction\_name* );**

*transaction\_name*

The name of the transaction. This must be a string constant and not a variable or an expression. The *transaction\_name* can be a maximum of 128 characters. It cannot contain any spaces. The first character cannot be a number.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for LoadRunner GUI Vusers only.

**define\_object\_exception**

Standard • Exception Handling

defines an object exception.

**define\_object\_exception** ( *exception\_name*, *handler*, *window*, *object*, *property*  
[ , *value* ]);

<i>exception_name</i>	The name of the exception.
<i>handler</i>	The name of the handler function.
<i>window</i>	The logical name of the window.
<i>object</i>	The logical name of the object.
<i>property</i>	An object property.
<i>value</i>	The value of the object property to detect.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

**define\_popup\_exception**

Standard • Exception Handling

defines a popup exception.

**define\_popup\_exception ( *exception\_name*, *handler*, *window* );**

*exception\_name*      The name of the exception.

*handler*      The name of the handler function. The handler can be a built-in handler or a user-defined handler. For a list of built-in handlers, see below.

*window*      The name of the popup window.

Built-In Handler Function	Description
<b>win_press_cancel</b>	Clicks the Cancel button in the window
<b>win_press_ok</b>	Clicks the OK button in the window
<b>win_press_return</b>	Presses the Return key (the equivalent of clicking the default button in the window)

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

## define\_tsl\_exception

## Standard • Exception Handling

defines a TSL exception.

```
define_ts1_exception ( exception_name, handler, return_code [ , function] );
```

*exception\_name* The name of the exception.

*handler* The name of the handler function.

*return\_code* The return code to detect. To detect any return code with a value less than zero, you can set E\_ANY\_ERROR as the argument.

*function* The TSL function to monitor.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

delete

Standard • Array

**remove** removes an element from an array.

**delete** *array* [ *subscript* ];

**array** The array from which the element is deleted.

**subscript** An expression that specifies the subscript of the array element to delete.

## Return Values

This function always returns an empty string.

## Availability

This function is always available.

---

**delete\_record\_attr**

Customization • Custom Record

removes a custom property that was registered using **add\_record\_attr**.

**delete\_record\_attr** ( *attr\_name* [ , *dll\_name*, *query\_func\_name*, *verify\_func\_name* ] );

*attr\_name*

The name of the custom property to remove. Note that you cannot remove any standard WinRunner properties.

*dll\_name*

The full path of the DLL (Dynamic Link Library) in which the query and verify functions are defined.

*query\_func\_name*

The name of the user-defined query function that was called by the **add\_record\_attr** statement which registered the custom property.

*verify\_func\_name*

The name of the verify function that was called by the **add\_record\_attr** statement which registered the custom property (either a WinRunner standard property verification function or a custom property verification function included in the DLL).

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

## dIph\_edit\_set

Context Sensitive • Delphi

replaces the entire contents of a Delphi edit object.

**dlph\_edit\_set** (*edit*, *text*);

<i>edit</i>	The logical name of the Delphi edit object.
<i>text</i>	The new contents of the Delphi edit object

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available only for WinRunner with Delphi support.

## dlph\_list\_select\_item

Context Sensitive • Delphi

selects a Delphi list item.

**dlph\_list\_select\_item** (*list*, *item*);

<i>list</i>	The logical name of the Delphi list.
<i>item</i>	The item to select in the Delphi list.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available only for WinRunner with Delphi support.

---

**dlph\_obj\_get\_info**

Context Sensitive • Delphi

retrieves the value of a Delphi object.

**dlph\_obj\_get\_info ( *name*, *property*, *out\_value* );**

*name*                   The logical name of the Delphi object.

*property*              Any property associated with the Delphi object.

*out\_value*             The value of the property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available only for WinRunner with Delphi support.

---

**dlph\_obj\_set\_info**

Context Sensitive • Delphi

sets the value of a Delphi object.

**dlph\_obj\_set\_info ( *name*, *property*, *in\_value* );**

*name*                   The logical name of the Delphi object.

*property*              Any property associated with the Delphi object.

*in\_value*              The new value of the Delphi property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available only for WinRunner with Delphi support.

**dlph\_panel\_button\_press**

Context Sensitive • Delphi

clicks a button within a Delphi panel.

**dlph\_panel\_button\_press ( *panel*, *button* );**

*panel*                   The object.

*button*                 The Delphi name.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available only for WinRunner with Delphi support.

---

**dos\_system**

Standard • Operating System

executes a DOS system command from within a WinRunner test script.

**dos\_system ( *expression* );**

*expression*             A string expression specifying the system command to be executed.

## Return Values

The return value of the function is the return value of the DOS system command that was executed.

## Availability

This function is available for WinRunner and LoadRunner GUI Vusers running on PC platforms only. To execute Windows executables, use **invoke\_application**. To execute UNIX system commands, use **system**. To execute OS2 commands, use **os2\_system**.

---

**edit\_activate**

Context Sensitive • Oracle

double clicks an object in an Oracle application.

**edit\_activate ( *object* );**

*object*

The logical name of the object.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**edit\_check\_info**

Context Sensitive • Edit Object

checks the value of an edit object property.

**edit\_check\_info ( *edit*, *property*, *property\_value* );**

*edit*

The logical name of the edit object.

*property*

The property to check.

*property\_value*

The property value.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## edit\_check\_selection

Context Sensitive • Edit Object

checks that a string is selected.

**edit\_check\_selection ( *edit*, *selected\_string* );**

**edit** The logical name of the edit object.

*selected\_string* The selected string. The string is limited to 256 characters. It cannot be evaluated automatically when used with the Function Generator.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## edit\_check\_text

Context Sensitive • Edit Object

checks the contents of an edit object.

**edit\_check\_text ( *edit*, *text*, *case\_sensitive* );**

**edit** The logical name of the edit object.

**text** The contents of the edit object (up to 256 characters).

**case\_sensitive** Indicates whether the comparison is case sensitive. This value is either TRUE or FALSE.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**edit\_delete**

Context Sensitive • Edit Object

Deletes the contents of an edit object.

**edit\_delete ( *edit*, *start\_column*, *end\_column* );**

*edit*

The logical name of the edit object.

*start\_column*

The column at which the text starts.

*end\_column*

The column at which the text ends. Note that if this is greater than the last column of the first line, then part of the following line will also be deleted.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## edit\_delete\_block

Context Sensitive • Edit Object

deletes a text block from an edit object.

**edit\_delete\_block ( *edit*, *start\_row*, *start\_column*, *end\_row*, *end\_column* );**

<i>edit</i>	The logical name of the edit object.
<i>start_row</i>	The row at which the text block starts.
<i>start_column</i>	The column at which the text block starts.
<i>end_row</i>	The row at which the text block ends.
<i>end_column</i>	The column at which the text block ends.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## edit\_get\_block

Context Sensitive • Edit Object

returns block of text in an edit object.

**edit\_get\_block ( *edit*, *start\_row*, *start\_column*, *end\_row*, *end\_column*, *out\_string* );**

<i>edit</i>	The logical name of the edit object.
<i>start_row</i>	The row at which the text block starts.
<i>start_column</i>	The column at which the text block starts.
<i>end_row</i>	The row at which the text block ends.
<i>end_column</i>	The column at which the text block ends.
<i>out_string</i>	The output variable that stores the text string.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## edit\_get\_info

Context Sensitive • Edit Object

returns the value of an edit object property.

**edit\_get\_info ( *edit*, *property*, *out\_value* );**

*edit*                   The logical name of the edit object.

*property*           Any of the properties listed in the *User's Guide*.

*out\_value*           The output variable that stores the value of the specified property.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## edit\_get\_row\_length

Context Sensitive • Edit Object

returns the length of a row in an edit object.

**edit\_get\_row\_length ( *edit*, *row*, *out\_length* );**

<i>edit</i>	The logical name of the edit object.
<i>row</i>	The row to measure.
<i>out_length</i>	The output variable that stores the number of characters in the row.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## edit\_get\_rows\_count

Context Sensitive • Edit Object

returns the number of rows written in an edit object.

**edit\_get\_rows\_count ( *edit*, *out\_number* );**

<i>edit</i>	The logical name of the edit object.
<i>out_number</i>	The output variable that stores the number of rows written in the edit object.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**edit\_get\_selection**

Context Sensitive • Edit Object

returns the selected string in an edit object.

**edit\_get\_selection ( *edit*, *out\_string* );**

*edit*

The logical name of the edit object.

*out\_string*

The output variable that stores the selected string. The string is limited to 256 characters. It cannot be evaluated automatically when used with the Function Generator.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

**edit\_get\_selection\_pos**

Context Sensitive • Edit Object

returns the position at which the selected block starts and ends.

**edit\_get\_selection\_pos ( edit, out\_start\_row, out\_start\_column, out\_end\_row, out\_end\_column );**

<i>edit</i>	The logical name of the edit object.
<i>out_start_row</i>	The output variable which stores the row at which the selected block starts.
<i>out_start_column</i>	The output variable which stores the column at which the selected block starts.
<i>out_end_row</i>	The output variable which stores the row at which the selected block ends.
<i>out_end_column</i>	The output variable which stores the column at which the selected block ends.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**edit\_get\_text**

Context Sensitive • Edit Object

returns the text in an edit object.

**edit\_get\_text ( edit, out\_string );**

<i>edit</i>	The logical name of the edit object.
<i>out_string</i>	The output variable that stores the string found in the edit object.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## edit\_insert

Context Sensitive • Edit Object

inserts text in the first line of an edit object.

**edit\_insert ( *edit*, *text*, *column* );**

*edit*                   The logical name of the edit object.

*text*                   The text to be inserted in the edit object.

*column*               The column at which the insertion is made.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**edit\_insert\_block**

Context Sensitive • Edit Object

**inserts text in a multi-line edit object.****edit\_insert\_block ( *edit*, *text*, *row*, *column* );**    *edit*                        The logical name of the edit object.    *text*                       The text to be inserted in the edit object.    *row*                       The row at which the insertion is made.    *column*                  The column at which the insertion is made.**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**edit\_replace**

Context Sensitive • Edit Object

**replaces the contents of an edit object.****edit\_replace ( *edit*, *text*, *start\_column*, *end\_column* );**    *edit*                        The logical name of the edit object.    *text*                       The new contents of the edit object.    *start\_column*             The column at which the text block starts.    *end\_column*               The column at which the text block ends.**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**edit\_replace\_block**

Context Sensitive • Edit Object

replaces a block of text in an edit object.

**edit\_replace\_block ( *edit*, *text*, *start\_row*, *start\_column*, *end\_row*, *end\_column* );**

<i>edit</i>	The logical name of the edit object.
<i>text</i>	The new contents of the edit object.
<i>start_row</i>	The row at which the text block starts.
<i>start_column</i>	The column at which the text block starts.
<i>end_row</i>	The row at which the text block ends.
<i>end_column</i>	The column at which the text block ends.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**edit\_set**

Context Sensitive • Edit Object

replaces the entire contents of an edit object.

**edit\_set ( *edit*, *text* );**

<i>edit</i>	The logical name of the edit object.
<i>text</i>	The new contents of the edit object.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## edit\_set\_focus

Context Sensitive • Edit Object

focuses on an object in an Oracle application.

**edit\_set\_focus ( *object* );**

*object* The logical name of the object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## edit\_set\_insert\_pos

Context Sensitive • Edit Object

places the cursor at a specified point in an edit object.

**edit\_set\_insert\_pos ( *edit*, *row*, *column* );**

*edit* The logical name of the edit object.

**row** The row position at which the insertion point is placed.

***column*** The column position at which the insertion point is placed.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## edit\_set\_selection

Context Sensitive • Edit Object

**selects text in an edit object.**

```
edit_set_selection ( edit, start_row, start_column, end_row, end_column );
```

**edit** The logical name of the edit object.

*start\_row* The row at which the selection starts.

*start\_column* The column at which the selection starts.

*end\_row* The row at which the selection ends.

*end\_column* The column at which the selection ends.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

edit\_type

Context Sensitive • Edit Object

**types a string in an edit object.**

**edit\_type** ( *edit*, *text* );

***edit*** The logical name of the edit object.

*text* The string to type into the edit object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**edit\_wait\_info**

Context Sensitive • Edit Object

waits for the value of an edit object property.

**edit\_wait\_info ( *edit*, *property*, *value*, *time* );**

<i>edit</i>	The logical name of the edit object.
<i>property</i>	Any of the properties listed in the <i>WinRunner User's Guide</i> .
<i>value</i>	The property value.
<i>time</i>	The maximum amount of time the test will wait before resuming execution.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**end\_transaction**

Standard • Load Testing

marks the end of a transaction for performance analysis.

**end\_transaction ( *transaction* [ , *status* ] );**

<i>transaction</i>	A string, with no spaces, naming the transaction.
<i>status</i>	The status of the transaction: pass (0), or fail (any non-zero value). If no value is specified, the default value is pass.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is available for LoadRunner GUI Vusers only.

---

**error\_message**

Standard • Load Testing

sends an error message to the controller.

**error\_message ( *message* );**

*message* Any string.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for LoadRunner GUI Vusers only.

---

**EURO\_check\_currency**

Context Sensitive • EURO

captures and compares the currencies in a window.

**EURO\_check\_currency ( *file\_name*, *x<sub>1</sub>*, *y<sub>1</sub>*, *x<sub>2</sub>*, *y<sub>2</sub>* );**

*file\_name* The file containing the expected results of the EURO checkpoint.

*x<sub>1</sub>*, *y<sub>1</sub>* The position of the upper left corner of the area to be checked.

*x<sub>2</sub>*, *y<sub>2</sub>* The position of the lower right corner of the area to be checked.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner EURO only.

---

## EURO\_compare\_columns

Context Sensitive • EURO

compares two currency columns (dual display) and returns the number of mismatches.

**EURO\_compare\_columns ( *check\_name*, *column<sub>1</sub>\_field<sub>1</sub>*, *column<sub>1</sub>\_field<sub>n</sub>*, *column<sub>2</sub>\_field<sub>1</sub>*, *column<sub>2</sub>\_field<sub>n</sub>* );**

<i>check_name</i>	The file name that stores the data.
<i>column<sub>1</sub>_field<sub>1</sub></i>	The first column first field to be included in the comparison.
<i>column<sub>1</sub>_field<sub>n</sub></i>	The first column last field to be included in the comparison.
<i>column<sub>2</sub>_field<sub>1</sub></i>	The second column first field to be included in the comparison.
<i>column<sub>2</sub>_field<sub>n</sub></i>	The second column last field to be included in the comparison.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WinRunner EURO only.

---

## EURO\_compare\_fields

Context Sensitive • EURO

compares two fields while converting.

**EURO\_compare\_fields ( *field<sub>1</sub>*, *field<sub>2</sub>*, *currency<sub>1</sub>*, *currency<sub>2</sub>*, *align\_mode*, *align\_value* );**

<i>field<sub>1</sub></i>	The name of the first field.
<i>field<sub>2</sub></i>	The name of the second field.

<i>currency<sub>1</sub></i>	The country whose currency you want to compare to currency <sub>2</sub> . One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.
<i>currency<sub>2</sub></i>	The country whose currency is compared to currency <sub>1</sub> . One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.
<i>align_mode</i>	<p>One of the following modes can be specified:</p> <p>ALIGN_NONE: No currency alignment</p> <p>ALIGN_ROUND: Rounds the converted currency to the nearest multiple specified in align_value.</p> <p>ALIGN_SUFFIX_DOWN: Rounds down the converted currency value to end with the suffix value indicated in align_value.</p> <p>ALIGN_SUFFIX_UP: Rounds up the converted currency value to end with the suffix value indicated in align_value.</p> <p>ALIGN_TRUNC: Rounds the converted currency value down to the nearest unit.</p>
<i>align_value</i>	The value to align the currency.

#### Return Values

The **EURO\_compare\_fields** function returns E\_OK or E\_DIFF.

#### Availability

This function is available for WinRunner EURO only.

---

## EURO\_compare\_numbers

Context Sensitive • EURO

compares two numbers while converting.

**EURO\_compare\_numbers** (*number<sub>1</sub>*, *number<sub>2</sub>*, *currency<sub>1</sub>*, *currency<sub>2</sub>*, *align\_mode*, *align\_value*);

<i>number<sub>1</sub></i>	The first number to compare.
<i>number<sub>2</sub></i>	The second number to compare.
<i>currency<sub>1</sub></i>	The country whose currency you want to compare to <i>currency<sub>2</sub></i> . One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.
<i>currency<sub>2</sub></i>	The country whose currency is compared to <i>currency<sub>1</sub></i> . One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.
<i>align_mode</i>	One of the following modes can be specified:  ALIGN_NONE: No currency alignment  ALIGN_ROUND: Rounds the converted currency to the nearest multiple specified in <i>align_value</i> .  ALIGN_SUFFIX_DOWN: Rounds down the converted currency value to end with the suffix value indicated in <i>align_value</i> .  ALIGN_SUFFIX_UP: Rounds up the converted currency value to end with the suffix value indicated in <i>align_value</i> .  ALIGN_TRUNC: Rounds the converted currency value down to the nearest unit.
<i>align_value</i>	The value to align the currency.

## Return Values

The **EURO\_compare\_numbers** function returns E\_OK or E\_DIFF.

## Availability

This function is available for WinRunner EURO only.

## EURO\_convert\_currency

Context Sensitive • EURO

returns the converted currency value between two currencies.

**EURO\_convert\_currency** ( *number, original\_currency, new\_currency, align\_mode, align\_value* );

<i>number</i>	The amount of currency to be converted.
<i>original_currency</i>	The country from whose currency you want to compute its value in the <i>new_currency</i> . One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.
<i>new_currency</i>	The country to whose currency the <i>original_currency</i> is being computed. One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.
<i>align_mode</i>	<p>One of the following modes can be specified:</p> <p>ALIGN_NONE: No currency alignment</p> <p>ALIGN_ROUND: Rounds the converted currency to the nearest multiple specified in <i>align_value</i>.</p> <p>ALIGN_SUFFIX_DOWN: Rounds down the converted currency value to end with the suffix value indicated in <i>align_value</i>.</p> <p>ALIGN_SUFFIX_UP: Rounds up the converted currency value to end with the suffix value indicated in <i>align_value</i>.</p>

**ALIGN\_TRUNC:** Rounds the converted currency value down to the nearest unit.

***align\_value***      The value to align the currency.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WinRunner EURO only.

## EURO\_override\_field

Context Sensitive • EURO

overrides the original currency in a field to a new currency.

**EURO\_override\_field** ( *field\_name*, *original\_currency*, *new\_currency*, *align\_mode*,  
*align\_value* );

***field\_name***      The name of the field in which you want to override the currency.

***original\_currency***      The country from whose currency you want to override to *new\_currency*. One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.

***new\_currency***      The country to whose currency the *original\_currency* is being overridden. One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.

***align\_mode***      One of the following modes can be specified:

ALIGN\_NONE: No currency alignment

ALIGN\_ROUND: Rounds the converted currency to the nearest multiple specified in *align\_value*.

**ALIGN\_SUFFIX\_DOWN:** Rounds down the converted currency value to end with the suffix value indicated in align\_value.

**ALIGN\_SUFFIX\_UP:** Rounds up the converted currency value to end with the suffix value indicated in align\_value.

**ALIGN\_TRUNC:** Rounds the converted currency value down to the nearest unit.

***align\_value*** The value to align the currency.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WinRunner EURO only.

---

## EURO\_set\_auto\_currency\_verify

Context Sensitive • EURO

activates/deactivates automatic EURO verification.

**EURO\_set\_auto\_currency\_verify ( mode );**

***mode*** The mode can be set to ON or OFF.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WinRunner EURO only.

---

## EURO\_set\_capture\_mode

Context Sensitive • EURO

determines how WinRunner EURO captures currency in terminal emulator applications.

**EURO\_set\_capture\_mode ( *capture\_mode* );**

*capture\_mode*

The currency capture mode. One of the following modes can be specified:

**FIELD\_METHOD:** Captures currencies in the context of the screens and fields in your terminal emulator application (Context Sensitive). This is the default mode.

**POSITION\_METHOD:** Identifies and captures currencies according to the unformatted view of the screen.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WinRunner EURO only.

---

## EURO\_set\_conversion\_mode

Context Sensitive • EURO

sets the EURO conversion run mode in the test script.

**EURO\_set\_conversion\_mode ( *conversion\_mode* );**

*conversion\_mode*

The EURO conversion run mode. One of the following modes can be specified:

**NO\_CHANGE:** No change is made to objects containing numeric values during the test run.

**CONVERT:** Performs EURO conversion during the test run.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WinRunner EURO only.

---

## **EURO\_set\_conversion\_rate**

Context Sensitive • EURO

sets the conversion rate between the EURO currency and a national currency.

**EURO\_set\_conversion\_rate ( *currency, rate* );**

*currency*

The country whose currency rate you want to set. One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.

*rate*

The conversion rate of the specified country's currency to the EURO.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WinRunner EURO only.

---

## **EURO\_set\_cross\_rate**

Context Sensitive • EURO

sets the cross rate method between two currencies.

**EURO\_set\_cross\_rate ( currency<sub>1</sub>, currency<sub>2</sub>, conversion\_mode, decimal, direct\_rate );**

*currency<sub>1</sub>*

The country whose currency you want to compare to *currency<sub>2</sub>*. One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.

*currency<sub>2</sub>*

The country whose currency is compared to *currency<sub>1</sub>*. One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.

*conversion\_mode*

The cross rate method of conversion. You can specify one of the following rates:

EURO Triangulation (default): indicates that the cross rates conversion from one national currency unit into another is done via the EURO currency, and that the EURO amount is rounded to no less than three decimal places.

Direct Cross Rate: indicates that the conversion is not done via triangulation.

*decimal*

Indicates the number of decimals to which the EURO amount is rounded (default is set to 3).

*direct\_rate*

The direct cross rate to be used for the conversion between the two currencies.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WinRunner EURO only.

---

**EURO\_set\_currency\_threshold**

Context Sensitive • EURO

sets the minimum value of an integer which will be considered a currency.

**EURO\_set\_currency\_threshold ( *threshold* );**

*threshold*

The minimum value.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner EURO only.

---

**EURO\_set\_decimals\_precision**

Context Sensitive • EURO

sets the number of decimals in the conversion results.

**EURO\_set\_decimals\_precision ( *decimals* );**

*decimals*

Indicates the number of decimals to be displayed in the results (STANDARD, 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15).

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner EURO only.

---

**EURO\_set\_original\_new\_currencies**

Context Sensitive • EURO

sets the original and new currencies of the application.

**EURO\_set\_original\_new\_currencies** ( *original\_currency*, *new\_currency*, *align\_mode*,  
  *align\_value* );

<i>original_currency</i>	The country whose currency you want to set to <i>new_currency</i> . One of the following countries can be specified: Austria, Belgium, Finland, France, Germany, Ireland, Italy, Luxembourg, Netherlands, Portugal, Spain, Great Britain, Denmark, Greece, Sweden, and EURO.
<i>new_currency</i>	The country to whose currency you want to convert <i>original_currency</i> .
<i>align_mode</i>	One of the following modes can be specified:  ALIGN_NONE: No currency alignment  ALIGN_ROUND: Rounds the converted currency to the nearest multiple specified in <i>align_value</i> .  ALIGN_SUFFIX_DOWN: Rounds down the converted currency value to end with the suffix value indicated in <i>align_value</i> .  ALIGN_SUFFIX_UP: Rounds up the converted currency value to end with the suffix value indicated in <i>align_value</i> .  ALIGN_TRUNC: Rounds the converted currency value down to the nearest unit.
<i>align_value</i>	The value to align the currency.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WinRunner EURO only.

---

**EURO\_setRegionalSymbols**

Context Sensitive • EURO

sets the character used as decimal separator and the character used to separate groups of digits to the left of the decimal.

**EURO\_setRegionalSymbols ( *decimal\_symbol*, *grouping\_symbol* );**

*decimal\_symbol*      The decimal symbol: `"."`

*grouping\_symbol*      The grouping symbol: `","`

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner EURO only.

---

**EURO\_setTriangulationDecimals**

Context Sensitive • EURO

sets the default decimals precision for the EUR triangulation.

**EURO\_setTriangulationDecimals ( *decimals* );**

*decimals*      The number of decimals to which the EURO amount is rounded. (The default is set to 3.)

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner EURO only.

---

## EURO\_type\_mode

Context Sensitive • EURO

disables/enables overriding of automatic currency recognition for all integer objects in a GUI application.

**EURO\_type\_mode ( mode );**

*mode*

The type mode. One of the following modes can be specified:

DISABLE\_OVERRIDE: Disables all overrides on integer objects.

ENABLE\_OVERRIDE: Enables all overrides on integer objects.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WinRunner EURO only.

---

## eval

Standard • Miscellaneous

evaluates and executes the enclosed TSL statements.

**eval ( statement<sub>1</sub> [ ; statement<sub>2</sub>; ... statement<sub>n</sub> ; ] );**

*statement*

Can be composed of one or more TSL statements.

### Return Values

This function normally returns an empty string. For the **treturn** statement, **eval** returns the value of the enclosed parameter.

### Availability

This function is always available.

---

**exception\_off**

Standard • Exception Handling

disables exception handling.

**exception\_off ( *exception\_name* );**

*exception\_name*      The name of the exception.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**exception\_off\_all**

Standard • Exception Handling

disables handling of all exceptions.

**exception\_off\_all ( );**

Return Values

This function has no return value.

Availability

This function is always available.

**exception\_on**

Standard • Exception Handling

enables exception handling.

**exception\_on ( *exception* );**

**exception**

A string expression that names the exception. The string cannot contain any spaces.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**exp**

Standard • Arithmetic

calculates the exponential function,  $e^x$ , where  $e$  is the natural logarithm base and “ $x$ ” is the exponent.

**exp ( *x* );**

**Return Values**

This function returns a real number.

**Availability**

This function is always available.

---

**file\_close**

Standard • I/O

closes a file that was opened with **file\_open**.

**file\_close ( *file\_name* );**

***file\_name***

The name of the file to close.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## file\_compare

Standard • I/O

compares the contents of two files.

**file\_compare ( *file<sub>1</sub>*, *file<sub>2</sub>* [ ,*save\_file* ] );**

*file<sub>1</sub>*                   The name of a file to compare to *file<sub>2</sub>*. If the file is not in the current test directory, then include the full path.

*file<sub>2</sub>*                   If the file is not in the current test directory, then include the full path.

*save\_file*               The name of a file that stores the differences between *file<sub>1</sub>* and *file<sub>2</sub>*.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## file\_getline

Standard • I/O

reads the next line from a file and assigns it to a variable.

**file\_getline ( *file\_name*, *out\_line* );**

*file\_name*                   The name of an open file.

*out\_line*                  The output variable that stores the line that is read.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## file\_open

Standard • I/O

opens a file or creates a new file.

**file\_open ( *file\_name*, *mode* );**

*file\_name*                  The name of the file to open or create.

*mode*                      The file mode:

FO\_MODE\_READ, or 0 (read only);

FO\_MODE\_WRITE, or 1 (write only);

FO\_MODE\_APPEND, or 2 (write only, to the end of the file).

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

## file\_printf

Standard • I/O

**print** prints formatted output to an open file.

**file\_printf** (*file\_name*, *format*, *exp*<sub>1</sub> [ , *exp*<sub>2</sub>, ... *exp*<sub>30</sub> ]);

*file\_name* The file to which the output is printed.

*format* May include both literal text to be printed and formatting specifications.

*exp*<sub>1</sub>, *exp*<sub>2</sub>,... *exp*<sub>30</sub>      The expressions to format and print.

# Formatting Specifications

The first character of the format argument is always a percent sign (%). The last character of format is a letter code that determines the type of formatting. One or more format modifiers can appear between the first and last character of the format argument (see below). The possible letter codes are as follows:

**c** Prints a character from its decimal ASCII code.

*d* Prints the decimal integer portion of a number.

**e** Converts input to scientific notation.

*f* Pads with zeros to the right of the decimal point.

**g** Prints a decimal value while suppressing non-significant zeros.

***o*** Prints the octal value of the integer portion of a number.

**s** Prints an unmodified string.

**x** Prints the hexadecimal value of the integer portion of a number.

**%** Prints a literal percent sign (%).

## Modifying Formats

The output generated by a particular formatting code can be modified. Three types of modifiers can appear between the percent sign (%) and the format code character:

<i>- (justification)</i>	A hyphen (-) indicates that the printed output is to be left-justified in its field.
<i>field width</i>	A number by itself or to the left of a decimal point, indicates how many characters the field should be padded. When this number is preceded by a 0, the padding is done with zeros to the left of the printed value.
<i>precision</i>	A number to the right of a decimal point indicates the maximum width of the printed string or how many digits are printed to the right of the output decimal point.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**find\_text**

Analog • I/O

searches for a string in an area of the screen.

---

**Note:** This function is provided for backward compatibility only. You should use the corresponding Context Sensitive **win\_find\_text** and **obj\_find\_text** functions.

---

**find\_text ( *string*, *out\_coord\_array*, *search\_area* [ , *string\_def* ] );**

<i>string</i>	The string that is searched for. The string must be complete, contain no spaces, and it must be preceded and followed by a space outside the quotation marks. To specify a literal, case-sensitive string, enclose the string in quotation marks. Alternatively, you can specify the name of a string variable. In this case, the string variable can include a regular expression.
<i>out_coord_array</i>	The name of the array that stores the screen coordinates of the text (see explanation below).
<i>search_area</i>	The area to search, specified as coordinates <i>x1,y1,x2,y2</i> . These define any two diagonal corners of a rectangle. The interpreter searches for the text in the area defined by the rectangle.
<i>string_def</i>	Defines the type of search to perform. If no value is specified, (0 or FALSE, the default), the search is for a single complete word only. When 1, or TRUE, is specified, the search is not restricted to a single, complete word.

#### Return Values

If the text is located, this function returns 0. If the text is not found, this function returns 1.

#### Availability

This function is always available.

**generator\_add\_category**

Customization • Function Generator

adds a category to the Function Generator.

**generator\_add\_category** (*category\_name*);

*category\_name*      The name of the category to add.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**generator\_add\_function**

Customization • Function Generator

adds a TSL function to the Function Generator.

**generator\_add\_function** (*function\_name*, *description*, *arg\_number*, *arg\_name<sub>1</sub>*,  
*arg\_type<sub>1</sub>*, *default\_value<sub>1</sub>*, [ ... *arg\_name<sub>n</sub>*, *arg\_type<sub>n</sub>*, *default\_value<sub>n</sub>* ]);

*function\_name*      The name of the function being defined, expressed as a string.

*description*      A brief description of the function. This need not be a valid string expression, meaning it may have spaces within the sentence.

*arg\_number*      The number of arguments in the function being defined. This can be any number from zero to eight.

For each argument in the function being defined, repeat each of the parameters below; **generator\_add\_function** can be used to define a function with up to eight arguments.

*arg\_name*      The name of the argument.

*arg\_type*      Defines how the user fills in the value of the argument in the Function Generator. This can be:

*browse()*: user points to a file in a browse file dialog box

*point\_window*: user points to a window

*point\_object*: user points to a GUI object

*select\_list(0 1)*: user selects a value from a list. The *select\_list* argument is defined in the Function Generator by using a combo box.

*type\_edit*: user types in a value

*default\_value*      The default value of the argument.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## generator\_add\_function\_to\_category

Customization • Function

### Generator

adds a function in the Function Generator to a category.

**generator\_add\_function\_to\_category ( *category\_name*, *function\_name* );**

*category\_name*      The name of an existing category.

*function\_name*      The name of an existing function.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**generator\_add\_subcategory**

Customization • Function Generator

adds a subcategory to a category in the Function Generator.

**generator\_add\_subcategory** (*category\_name*, *sub\_category\_name*);

*category\_name*      The name of an existing category.

*sub\_category\_name*      The name of an existing category.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**generator\_set\_default\_function**

Customization • Function Generator

sets a default function for a category in the Function Generator.

**generator\_set\_default\_function** (*category\_name*, *function\_name*);

*category\_name*      An existing category.

*function\_name*      An existing function.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**get\_aut\_var**

Standard • Testing Option

returns the value of a variable that determines how WinRunner or XRunner learns descriptions of objects, records tests, and runs tests on Java applets or applications.

**get\_aut\_var ( *variable*, *value* );**

*variable*                   The variable to get.

*value*                   The value of the variable.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available only for WinRunner with Java support.

---

**get\_class\_map**

Context Sensitive • GUI Map Configuration

returns the standard class associated with a custom class.

**get\_class\_map ( *custom\_class*, *out\_standard\_class* );**

*custom\_class*                   The name of the custom class.

*out\_standard\_class*           The output variable that stores the Mercury class or the standard MS Windows class associated with the custom class.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner and LoadRunner GUI Vusers on PC platforms only.

## **get\_host\_name**

Standard • Load Testing

returns the name of a host.

**get\_host\_name () ;**

### Return Value

This function returns the host name if the operation is successful or null if the operation fails.

### Availability

This function is available for LoadRunner GUI Vusers only.

---

## **get\_master\_host\_name**

Standard • Load Testing

returns the name of the controller's host.

**get\_master\_host\_name () ;**

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for LoadRunner GUI Vusers only.

## get\_record\_attr

Context Sensitive • GUI Map Configuration

returns the properties learned for an object class.

`get_record_attr ( class, out_obligatory, out_optional, out_selector );`

**class** The name of the Mercury class, MSW\_class, or X\_class.

*out\_obligatory* The output variable that stores the list of obligatory properties that are always recorded.

*out\_optional* The output variable that stores the list of optional properties.

***out\_selector*** The output variable that stores the selector used for this GUI object class.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## get\_record\_method

Context Sensitive • GUI Map Configuration

returns the record method used for an object class.

**get\_record\_method** (*class*, *out\_method*);

*class* The name of the object class.

***out\_method*** The record method used for the object class, as described below:

Method	Description
RM_RECORD	Records operations using Context Sensitive functions. This is the default method for all the standard classes, except the object class (for which the default is MIC_MOUSE).
RM_IGNORE	Turns off recording.
RM_AS_OBJECT	Instructs WinRunner to record all functions on a GUI object as though its class were “object” class.
RM_PASSUP	Records mouse operations (relative to the parent of the object) and keyboard input.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

**This function is always available.**

---

## get\_text

Analog • Text Checkpoint

reads text from the screen.

---

**Note:** This function is provided for backward compatibility only. You should use the corresponding Context Sensitive **win\_get\_text** and **obj\_get\_text** functions. When working with RTL-style windows, use the **str\_map\_logical\_to\_visual** function.

---

**get\_text ( *location* );**

The **get\_text** function reads text from the area of the screen indicated by *location*. The *location* can be any one of the following:

<b>x<sub>1</sub>,y<sub>1</sub>,x<sub>2</sub>,y<sub>2</sub></b>	Describes a rectangle that encloses the text to be read. The pairs of coordinates can designate any two diagonally opposite corners of the rectangle.
<b>x, y</b>	The coordinates of a particular point on the screen. This parameter causes the string closest to the specified point to be read. The search radius around the specified point is defined by the <b>XR_TEXT_SEARCH_RADIUS</b> parameter.
<b>()</b>	When no <i>location</i> is specified (empty parentheses), the string closest to the mouse pointer position is read. The search radius around the pointer position is defined by the <b>XR_TEXT_SEARCH_RADIUS</b> parameter.

### Return Values

This function returns a string. By default, the returned string does not include blanks at the beginning or end of the string. (This is determined by the **XR\_TEXT\_REMOVE\_BLANKS** parameter in the **wrun.ini** file). If no string is found, an empty string is returned.

### Availability

This function is always available.

## get\_time

Standard • Time-Related

returns the current system time, expressed in terms of the number of seconds that have elapsed since 00:00 GMT, January 1, 1970.

**get\_time ():**

Return Values

This function returns an integer.

Availability

This function is always available.

---

## get\_x

Analog • Input Device

returns the x-coordinate of the current position of the mouse pointer.

**get\_x ():**

Return Values

This function returns an integer.

Availability

This function is always available.

---

## get\_y

Analog • Input Device

returns the y-coordinate of the current position of the mouse pointer.

**get\_y ():**

Return Values

This function returns an integer.

Availability

This function is always available.

---

**getenv**

Standard • Miscellaneous

returns the value of any environment variable, as defined in the [WrCfg] section of *wrun.ini* or in the WinRunner runtime environment.

**getenv ( *environment\_variable* );**

*environment\_variable*    A variable chosen from the environment variable list in the [WrCfg] section of the *wrun.ini* file.

Return Values

This function returns the value of the specified environment variable.

Availability

This function is always available.

---

**getvar**

Standard • Testing Option

returns the value of a testing option.

**getvar ( *option* );**

*option*                      A testing option.

The **getvar** function reads the current value of a testing option. For a list and an in-depth explanation of **getvar** options, refer to the “Setting Testing Options from a Test Script” chapter in the *WinRunner User’s Guide*.

Return Values

This function returns the value of the specified testing option.

Availability

This function is always available.

---

## GUI\_add

Context Sensitive • GUI Map Editor

adds an object to a GUI map file.

**GUI\_add** (*file path, window, object, physical\_desc*);

<i>file</i>	The GUI map file to which the object is added. If an empty string is entered, the object is added to the temporary GUI map file.
<i>window</i>	The logical name of the window containing the object.
<i>object</i>	The logical name of the object.
<i>physical_desc</i>	The physical description of the object.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## GUI\_buf\_get\_desc

Context Sensitive • GUI Map Editor

returns the physical description of an object in a GUI map file.

**GUI\_buf\_get\_desc** (*file, window, object, out\_desc*);

<i>file</i>	The full path of the GUI map file containing the object.
<i>window</i>	The logical name of the window containing the object.
<i>object</i>	The logical name of the object. If a null string is specified, the function returns the physical description of the window itself.
<i>out_desc</i>	The output variable that stores the physical description.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## GUI\_buf\_get\_desc\_attr

Context Sensitive • GUI Map Editor

returns the value of a GUI object property in a GUI map file.

**GUI\_buf\_get\_desc\_attr ( *file*, *window*, *object*, *property*, *out\_prop\_value* );**

<i>file</i>	The full path of the GUI map file containing the object.
<i>window</i>	The logical name of the window containing the object.
<i>object</i>	The logical name of the object. If no object is specified, the function returns the physical description of the window itself.
<i>property</i>	The property whose value is to be returned.
<i>out_prop_value</i>	The output variable that stores the property value.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**GUI\_buf\_get\_logical\_name**

Context Sensitive • GUI Map Editor

returns the logical name of an object in a GUI map file.

**GUI\_buf\_get\_logical\_name ( *file*, *physical\_desc*, *window*, *out\_name* );**

<i>file</i>	The full path of the GUI map file containing the object.
<i>physical_desc</i>	The physical description of the GUI object.
<i>window</i>	The window containing the GUI object.
<i>out_name</i>	The output variable that stores the logical name.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**GUI\_buf\_new**

Context Sensitive • GUI Map Editor

creates a new GUI map file.

**GUI\_buf\_new ( *file* );**

<i>file</i>	The GUI map file to create.
-------------	-----------------------------

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**GUI\_buf\_set\_desc\_attr**

Context Sensitive • GUI Map Editor

sets the value of a property for an object in a GUI map file.

**GUI\_buf\_set\_desc\_attr ( *file*, *window*, *object*, *property*, *value* );**

<i>file</i>	The full path of the GUI map file containing the object.
<i>window</i>	The window containing the object.
<i>object</i>	The logical name of the object.
<i>property</i>	The property whose value is to be set.
<i>value</i>	The value set for the property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**GUI\_close**

Context Sensitive • GUI Map Editor

closes a GUI map file.

**GUI\_close ( *file* );**

<i>file</i>	The full path of the GUI map file to be closed.
-------------	---

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## GUI\_close\_all

Context Sensitive • GUI Map Editor

closes all GUI map files, except the temporary GUI map file. To close the temporary GUI map file, use the **GUI\_close** function.

**GUI\_close\_all ()**

The **GUI\_close\_all** function closes all GUI map files that are currently loaded or open.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## GUI\_delete

Context Sensitive • GUI Map Editor

**deletes an object from a GUI map file.**

**GUI\_delete ( *file*, *window*, *obj* );**

<i>file</i>	The full path of the GUI map file containing the object.
<i>window</i>	The logical name of the window containing the object.
<i>obj</i>	The logical name of the object to delete.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**GUI\_desc\_compare**

Context Sensitive • GUI Map Editor

compares two physical descriptions.

**GUI\_desc\_compare ( *desc<sub>1</sub>*, *desc<sub>2</sub>* );**

*desc<sub>1</sub>*, *desc<sub>2</sub>*

The physical descriptions to compare.

Return Value

This function returns 1 when the comparison fails and returns 0 when it succeeds.

Availability

This function is always available.

---

**GUI\_desc\_get\_attr**

Context Sensitive • GUI Map Editor

gets the value of a property from a physical description.

**GUI\_desc\_get\_attr ( *physical\_desc*, *property*, *out\_property\_value* );**

*physical\_desc*                   The physical description of a GUI object.

*property*                       The property to return.

*out\_property\_value*           The output variable that stores the property value.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

**GUI\_desc\_set\_attr**

Context Sensitive • GUI Map

sets the value of a property.

**GUI\_desc\_set\_attr ( *physical\_desc*, *property*, *value* );**

*physical\_desc*      The physical description of an object. This must be a variable and not a constant.

*property*      The property name.

*value*      The property value.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**GUI\_get\_name**

Context Sensitive • GUI Map Editor

returns the type of GUI for the application under test.

**GUI\_get\_name ( *out\_name*, *out\_version* );**

*out\_name*      An output variable that stores the name of the current GUI.

*out\_version*      An output variable that stores the current version of the GUI, as described below:

Operating System	Name	Version
Microsoft Windows 95	"Windows 95"	"4.0"
Microsoft Windows 98	"Windows 95"	"4.1"
Microsoft Windows NT	"Windows NT"	"4.0"

---

**Note:** Windows 98 is called Windows 95 for purposes of backward compatibility. The major version number for both operating systems is 4. The minor version number is 0 for Windows 95 or 1 for Windows 98.

---

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

## GUI\_get\_window

Context Sensitive • GUI Map Editor

returns the active window in the GUI map.

**GUI\_get\_window ( );**

#### Return Values

This function returns the name of the active window if it succeeds, or an empty string if it fails.

#### Availability

This function is always available.

---

## GUI\_list\_buf\_windows

Context Sensitive • GUI Map Editor

lists all windows in a GUI map file.

**GUI\_list\_buf\_windows ( *file*, *out\_windows*, *out\_number* );**

<i>file</i>	The full path of the GUI map file.
<i>out_windows</i>	The output variable that stores all windows in the GUI map file in an array.
<i>out_number</i>	The output variable assigned to the number of windows in the GUI map file.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## GUI\_list\_buffers

Context Sensitive • GUI Map Editor

lists all open GUI map files.

**GUI\_list\_buffers ( *out\_files*, *out\_number* );**

<i>out_files</i>	The output variable array that stores all open GUI map files in an array.
<i>out_number</i>	The output variable that stores the number of opened GUI map files.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## GUI\_list\_desc\_attrs

Context Sensitive • GUI Map Editor

lists property values for a GUI object.

**GUI\_list\_desc\_attrs ( *physical\_desc*, *out\_array* );**

*physical\_desc*

The physical description of a GUI object.

*out\_array*

The output variable that stores the object's properties and values in an array. The subscript of each array element is the name of the property. The value of each array element is the value of the property. For instance, if the *out\_array* is called *property\_value*, then: *property\_value* ["attr1"] = "val1".

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## GUI\_list\_map\_buffers

Context Sensitive • GUI Map Editor

lists all loaded GUI map files.

**GUI\_list\_map\_buffers ( *out\_file*, *out\_number* );**

*out\_file*                   The output variable that stores all loaded GUI map files in an array.

*out\_number*               The output variable that stores the number of loaded GUI map files.

---

**Note:** The GUI map files must be loaded and not simply open.

---

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## GUI\_list\_win\_objects

Context Sensitive • GUI Map Editor

lists all objects in a window.

**GUI\_list\_win\_objects ( *file*, *window*, *out\_objects*, *out\_number* );**

*file*                   The full path of the GUI map file.

*window*               The name of the window containing the objects.

*out\_objects*           The output variable that stores all objects in the window in an array.

*out\_number*           The output variable that stores the number of objects in the window.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## GUI load

Context Sensitive • GUI Map Editor

loads a GUI map file.

**GUI\_load ( *file\_name* );**

*file\_name* The full path of the GUI map.

## Return Values

This function always returns 0.

## Availability

This function is always available.

## GUI\_map\_get\_desc

Context Sensitive • GUI Map Editor

returns the description of an object in the GUI map.

**GUI\_map\_get\_desc** ( *window*, *object*, *out\_desc*, *out\_file* );

**window** The name of the window containing the GUI object.

*object* The logical name of the GUI object.

*out\_desc* The output variable that stores the description of the GUI object.

***out\_file*** The output variable that stores the GUI map file containing the description.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**GUI\_map\_get\_logical\_name**

Context Sensitive • GUI Map Editor

returns the logical name of an object in the GUI map.

```
GUI_map_get_logical_name ( physical_desc, window, out_obj, out_file );
```

*physical\_desc* The physical description of the object. For more information regarding *physical descriptions*, refer to the “Introducing Context Sensitive Testing” chapter in the *WinRunner User’s Guide*.

**window** The logical name of the window containing the object. If no window is specified, the function looks for one.

***out\_obj*** The output variable that stores the object's logical name.

***out\_file*** The output variable that stores the name of the GUI map file containing the object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

GUI\_open

Context Sensitive • GUI Map Editor

opens a GUI map file.

**GUI\_open ( *file\_name* );**

*file\_name* The full path of the GUI map file to open.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## GUI save

Context Sensitive • GUI Map Editor

saves a GUI map file.

**GUI save ( *file name* );**

*file\_name* The full path of the GUI map file to save.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**GUI\_save\_as**

Context Sensitive • GUI Map Editor

saves a GUI map file under a new name.

**GUI\_save\_as ( *current\_file\_name*, *new\_file\_name* );**

*current\_file\_name*      The name of the GUI map file to save.

*new\_file\_name*      The name of the new file.

---

**Note:** When you save the temporary GUI map file, which doesn't have a *current\_file\_name*, the statement should have the following syntax:

**GUI\_save\_as ( " ", "new\_file\_name" );**

---

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

**GUI\_set\_window**

Context Sensitive • GUI Map Editor

sets the scope for GUI object identification within the GUI map.

**GUI\_set\_window ( *window\_name* );**

*window\_name*      The name of the window to be activated.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**GUI\_unload**

Context Sensitive • GUI Map Editor

unloads a GUI map file.

**GUI\_unload ( *file* );***file*

The full path of the GUI map file to unload.

Return Values

This function always returns 0.

Availability

This function is always available.

---

**GUI\_unload\_all**

Context Sensitive • GUI Map Editor

unloads all loaded GUI map files.

**GUI\_unload\_all ( );**

Return Values

The return value of this function is always 0 and is returned when all the GUI map files have been unloaded.

Availability

This function is always available.

---

## GUI\_ver\_add\_check

Customization • GUI Checkpoint

registers a new GUI check.

**GUI\_ver\_add\_check** (*check\_name*, *capture\_function*, *comparison\_function*  
[ , *display\_function*] [ , *type*]);

<i>check_name</i>	The name of the check to add.
<i>capture_function</i>	The name of the capture function defined for the check.
<i>comparison_function</i>	The name of the comparison function defined for the check. If no <i>comparison_function</i> is specified, the default display is used.
<i>display_function</i>	The name of the function that displays check results.
<i>type</i>	The type of GUI object on which this check operates: 1 for a window, 0 for any other GUI object class. If no <i>type</i> is specified, the default 0 is assumed.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## GUI\_ver\_add\_check\_to\_class

Customization • GUI Checkpoint

adds a check to an object class, which can be viewed in the GUI Checkpoint dialog boxes.

**GUI\_ver\_add\_check\_to\_class** (*class*, *check\_name*);

<i>class</i>	The name of the class.
<i>check_name</i>	The name of the check to add, as defined with <b>GUI_ver_add_check</b> .

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## GUI\_ver\_add\_class

Customization • GUI Checkpoint

Creates a GUI checkpoint for a new class.

**GUI\_ver\_add\_class ( *TOOLKIT\_class* [ , *ui\_function* ] [ , *default\_check\_function* ] );**

*TOOLKIT\_class*      The MSW\_class or X\_class of the object.

*ui\_function*      The name of the function used to develop and display the GUI checkpoint dialog boxes with a customized user interface.

*default\_check\_function*      The name of the function that controls the default checks for the object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## GUI\_ver\_set\_default\_checks

Customization • GUI Checkpoint

sets the default GUI checks for an object class.

**GUI\_ver\_set\_default\_checks ( *class*, *check\_names* );**

*class* The name of the object class.

*check\_names* The names of the checks set as defaults, separated by spaces.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

icon\_move

## Context Sensitive • Icon Object

moves an icon to a new location on the screen.

**icon\_move ( *icon*, *x*, *y* );**

*icon* The logical name of the icon.

**x, y** The new position of the upper left corner of the icon.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WinRunner and LoadRunner GUI Vusers running on PC platforms only.

icon\_select

## Context Sensitive • Icon Object

selects an icon with a mouse click.

**icon\_select ( *icon* );**

*icon*

The logical name of the icon.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WinRunner and LoadRunner GUI Vusers running on PC platforms only.

## index

Standard • String

indicates the position of one string within another.

**index** (*string*<sub>1</sub>, *string*<sub>2</sub>);

*string*<sub>1</sub>, *string*<sub>2</sub>

## Two string expressions.

## Return Values

The return value indicates the position of the string. The value 0 is returned if the string does not exist.

## Availability

This function is always available.

**int**

Standard • Arithmetic

returns the integer portion of a positive real number.

**int ( *x* );**

Return Values

This function returns an integer.

Availability

This function is always available.

---

**invoke\_application**

Standard • Operating System

invokes a Windows application from within a test script.

**invoke\_application ( *file*, *command\_option*, *working\_dir*, *show* );**

*file*                   The full path of the application to invoke.

*command\_option*       The command line options to apply.

*working\_dir*           The working directory for the specified application.

*show*                  Specifies how the application appears when opened. This parameter can be one of the following constants:

Value	Description
SW_HIDE	hides the window and passes activation to another window
SW_MINIMIZE	minimizes the window and activates the top-level window in the system list
SW_RESTORE	activates and displays the window. If the window is minimized or maximized, WinRunner restores it to its original size and position (same as SW_SHOWNORMAL).
SW_SHOW	activates the window and displays it in its current size and position

Value	Description
SW_SHOWMAXIMIZED	activates the window and displays it as a maximized window
SW_SHOWMINIMIZED	activates the window and displays it as an icon
SW_SHOWMINNOACTIVE	displays the window as an icon. The window that is currently active remains active.
SW_SHOWNA	displays the window in its current state. The currently active window remains active.
SW_SHOWNOACTIVATE	displays the window in its most recent size and position. The currently active window remains active.
SW_SHOWNORMAL	activates and displays the window. If the window is minimized or maximized, WinRunner restores it to its original size and position (same as SW_SHOWRESTORE).

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WinRunner and LoadRunner GUI Vusers running on PC platforms only.

## java\_activate\_method

invokes the requested Java method for the given object.

`int java_activate_method ( object, method, retval [ , param1, ... param8 ] );`

<i>object</i>	The object name
<i>method</i>	The name of the java method to invoke
<i>retval</i>	An output variable that will hold a return value from the invoked method*
	*Required even for void Java methods
<i>param</i> <sub>1</sub> ... <sub>8</sub>	Parameters to be passed to the Java method. The Parameters must belong to one of the following supported types: Boolean, boolean, Integer, int, String.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WinRunner with Java support only.

---

**length**

Standard • String

counts the number of characters in a string.

**length ( *string* );***string*

A valid string expression.

Return Values

The return value of the function indicates the number of characters in the argument string. If no string is included, **length** returns the value 0.

Availability

This function is always available.

---

**list\_activate\_item**

Context Sensitive • List Object

activates an item in a list.

**list\_activate\_item ( *list*, *item* [ , *offset* ] );***list*

The logical name of the list.

*item*

The item to activate within the list.

*offset*

The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional).

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

## list\_check\_info

Context Sensitive • List Object

checks the value of a list property.

**list\_check\_info ( *list*, *property*, *property\_value* );**

*list*                   The logical name of the list.

*property*           The property to be checked.

*property\_value*     The expected property value.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## list\_check\_item

Context Sensitive • List Object

checks the content of an item in a list.

**list\_check\_item ( *list*, *item\_num*, *item\_content* );**

*list*                   The logical name of the list.

*item\_num*           The location of the item in the designated list. Note that the first item in a list is numbered 0.

*item\_content*       The expected contents of the item.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## list\_check\_selected

Context Sensitive • List Object

checks that the specified item is selected.

**list\_check\_selected ( *list*, *selected\_items* );**

*list*

The logical name of the list.

*selected\_item*

The item(s) that should be selected in the list. If there are multiple items, they should be separated by commas. This argument should be a string or a list of strings.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## listCollapse\_item

Context Sensitive • List Object

hides items in a TreeView object.

**listCollapse\_item ( *list*, *item* [ , *mouse\_button* ] );**

*list*

The logical name of the list.

*item*

The expanded heading under which the items appear.

*mouse\_button*

A constant that specifies the mouse button to use. The value can be LEFT, MIDDLE, or RIGHT. The default is the left button.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for TreeView objects only.

## list\_deselect\_item

Context Sensitive • List Object

deselects an item in a list.

**list\_deselect\_item** ( *list*, *item* [ , *mouse\_button* [ , *offset* ] ] );

<i>list</i>	The logical name of the list.
<i>item</i>	The item to deselect from the list.
<i>mouse_button</i>	A constant that specifies the mouse button to use. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the left button.
<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional). This parameter may only be used if the <i>mouse_button</i> argument is used

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## list\_deselect\_range

Context Sensitive • List Object

deselects all items between two specified items.

**list\_deselect\_range** ( *list*, *item<sub>1</sub>*, *item<sub>2</sub>* [ , *offset* ] );

<i>list</i>	The logical name of the list.
<i>item<sub>1</sub></i>	The first item of the range.
<i>item<sub>2</sub></i>	The last item of the range.
<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional).

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## list\_drag\_item

Context Sensitive • List Object

drags an item from a source list.

**list\_drag\_item ( *source\_list*, *item* [ , *mouse\_button* ] );**

<i>source_list</i>	The logical name of the list.
<i>item</i>	The item to drag from the list.
<i>mouse_button</i>	A constant that specifies the mouse button to hold down while dragging the item. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the button that performs the select function.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is not supported for ListBox objects.

**list\_drop\_on\_item**

Context Sensitive • List Object

drops an object onto a target list item.

**list\_drop\_on\_item** (*target\_list*, *target\_item*);

*target\_list*                   The logical name of the list.

*target\_item*                 The list item on which to drop the source object.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is not supported for ListBox objects.

---

**list\_expand\_item**

Context Sensitive • List Object

displays hidden items in a TreeView object.

**list\_expand\_item** (*list*, *item* [ , *mouse\_button* ]);

*list*                         The logical name of the list.

*item*                         The expandable heading under which the items will be displayed.

*mouse\_button*               A constant that specifies the mouse button to use. The value can be LEFT, MIDDLE, or RIGHT. The default is the left button.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is supported for TreeView objects only.

---

**list\_extend\_item**

Context Sensitive • List Object

adds an item to a list of selected items.

**list\_extend\_item ( *list*, *item* [ , *button* ] [ , *offset* ] );**

<i>list</i>	The logical name of the list.
<i>item</i>	The item to add from the list.
<i>button</i>	The mouse button used (optional). In the case of a combo object or a list that is not a ListView or a TreeView, only the left mouse button can be used.
<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional). This argument can be used only if the button argument is defined.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

**list\_extend\_multi\_items**

Context Sensitive • List Object

adds multiple items to the items already selected in a list.

**list\_extend\_multi\_items** ( *list*, *item\_list* [ , *mouse\_button* ] [ , *offset* ] );

<i>list</i>	The logical name of the list.
<i>item_list</i>	The items to select, separated by commas.
<i>mouse_button</i>	A constant that specifies the mouse button to use. The value can be LEFT, MIDDLE, or RIGHT. The default is the left button.
<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional). This argument can be used only if the button argument is defined.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**list\_extend\_range**

Context Sensitive • List Object

selects a range of items and adds them to the current selection.

**list\_extend\_range** ( *list*, *item<sub>1</sub>*, *item<sub>2</sub>* [ , *button* ] [ , *offset* ] );

<i>list</i>	The logical name of the list.
<i>item<sub>1</sub></i>	The first item of the range.
<i>item<sub>2</sub></i>	The last item of the range.
<i>button</i>	The mouse button used (optional). In the case of a combo object or a list that is not a ListView or a TreeView, only the left mouse button can be used.

<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional). This argument can be used only if the button argument is defined.
---------------	--

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

## list\_get\_checked\_items

Context Sensitive • List Object

retrieves the number and the value of items marked as checked.

**list\_get\_checked\_items ( *list*, *items*, *number* );**

<i>list</i>	The logical name of the ListView or TreeView with check boxes.
<i>items</i>	The concatenated list of the returned values of the items with selected check boxes.
<i>number</i>	The number of items with selected check boxes.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**list\_get\_column\_header**

Context Sensitive • List Object

returns the value of a ListView column header.

**list\_get\_column\_header** (*listview\_object*, *in\_column\_index*, *out\_header\_value*);

*listview\_object*      The name of the list.

*in\_column\_index*      The column index.

*out\_header\_value*      The column header that is returned.

---

**Note:** The **list\_get\_column\_header** function is effective for ListView objects having a report view (style) only.

---

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

The **list\_get\_column\_header** function is effective for ListView objects having a report view (style) only.

---

**list\_get\_info**

Context Sensitive • List Object

returns the value of a list property.

**list\_get\_info** (*list*, *property*, *out\_value*);

*list*      The logical name of the list.

*property*      Any of the properties listed in the *WinRunner User's Guide*.

*out\_value*      The output variable that stores the value of the specified property.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## list\_get\_item

Context Sensitive • List Object

returns the contents of a list item.

**list\_get\_item** (*list*, *item\_num*, *out\_value*);

*list* The logical name of the list.

*item\_num* The location of the item in the designated list. Note that the first item in a list is numbered 0.

*out\_value* The contents of the designated item.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**list\_get\_item\_info**

Context Sensitive • List Object

returns the state of a list item.

**list\_get\_item\_info ( *list*, *item*, *state*, *out\_value* );**

<i>list</i>	The logical name of the list.
<i>item</i>	The item in the list.
<i>state</i>	The state property of the item. The state property can be either CHECKED or SELECTED.
<i>out_value</i>	The output variable that stores the value of the state property.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**list\_get\_item\_num**

Context Sensitive • List Object

returns the position of a list item.

**list\_get\_item\_num ( *list*, *item*, *out\_num* );**

<i>list</i>	The logical name of the list.
<i>item</i>	The string of the item.
<i>out_num</i>	The output variable that stores the position of the list item.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

## list\_get\_selected

Context Sensitive • List Object

returns the numeric and string values of the selected item in a list.

**list\_get\_selected ( *list*, *out\_item*, *out\_num* );**

*list*

The logical name of the list.

*out\_item*

The output variable that stores the name of the selected items. For a multi-selection list, the variable contains a list of items, sorted alphabetically, and separated by the special character ASCII30 (^^).

*out\_num*

The output variable that stores the items. Note that the first item in a list is numbered 0. For a standard list, stores the index of the selected item. For a multi-selection list, stores the number of selected items.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## list\_get\_subitem

Context Sensitive • List Object

returns the value of a ListView subitem.

**list\_get\_subitem ( *list*, *item*, *subitem\_index*, *subitem* );**

<i>list</i>	The logical name of the ListView.
<i>item</i>	The name of the item.
<i>subitem_index</i>	The index indicating the field of the requested subitem.
<i>subitem</i>	The value of the returned subitem.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## list\_rename\_item

Context Sensitive • List Object

activates the edit mode on the label of a ListView or a TreeView item in order to rename it.

**list\_rename\_item ( *list*, *item* );**

<i>list</i>	The logical name of the ListView or TreeView.
<i>item</i>	The item to select and rename.

---

**Note:** A **list\_rename\_item** statement must be followed by a type statement in order to rename the item. The item can be denoted by its logical name or numeric index.

---

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## list\_select\_item

Context Sensitive • List Object

selects a list item.

**list\_select\_item ( *list*, *item* [ ,*button* [ , *offset* ] ] );**

<i>list</i>	The logical name of the list.
<i>item</i>	The item to select in the list.
<i>button</i>	The mouse button used (optional). In the case of a combo object or a list that is not a ListView or a TreeView, only the left mouse button can be used.
<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional). This argument can be used only if the button argument is defined.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**list\_select\_multi\_items**

Context Sensitive • List Object

selects multiple items in a list.

**list\_select\_multi\_items ( *list*, *item\_list* [ , *mouse\_button* [ , *offset* ] ] );**

<i>list</i>	The logical name of the list.
<i>item_list</i>	The items to select, separated by commas.
<i>mouse_button</i>	A constant that specifies the mouse button to use. The value can be LEFT, MIDDLE, or RIGHT. The default is the left button.
<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional). This argument can be used only if the button argument is defined.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**list\_select\_range**

Context Sensitive • List Object

selects all items between two specified items.

**list\_select\_range ( *list*, *item<sub>1</sub>*, *item<sub>2</sub>* [ , *button* [ , *offset* ] ] );**

<i>list</i>	The logical name of the list.
<i>item<sub>1</sub></i>	The first item of the range.
<i>item<sub>2</sub></i>	The last item of the range.
<i>button</i>	The mouse button used (optional). In the case of a combo object or a list that is not a ListView or a TreeView, only the left mouse button can be used.

<i>offset</i>	The horizontal offset (in pixels) of the click location relative to the left margin of the item's text (optional). This argument can be used only if the button argument is defined.
---------------	--

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

## list\_set\_item\_state

Context Sensitive • List

sets the state of an icon of the specified ListView or TreeView.

**list\_set\_item\_state ( *list*, *item*, *value* [ , *button* ] );**

<i>list</i>	The logical name of the ListView or TreeView.
<i>item</i>	The name of the icon.
<i>value</i>	The value of the state icon (check box).
<i>button</i>	The mouse button (optional).

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

## list\_wait\_info

Context Sensitive • List Object

waits for the value of a list property.

**list\_wait\_info ( *list*, *property*, *value*, *time* );**

<i>list</i>	The logical name of the list.
<i>property</i>	Any of the properties listed in the <i>User's Guide</i> .
<i>value</i>	The property value.
<i>time</i>	Indicates the maximum interval, in seconds, before the next statement is executed.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## load

Standard • Compiled Module

loads a compiled module into memory.

**load ( *module\_name* [ ,1|0 [ ,1|0 ] ]);**

<i>module_name</i>	A string expression indicating the name of an existing compiled module.
1 0	1 indicates a system module. 0 indicates a user module. The default value is 0.
1 0	1 indicates that a user module will not remain open after it is loaded. 0 indicates that the module remains open in the WinRunner window. The default value is 0.

**Note:** If you make changes to a function in a loaded compiled module, you must unload and reload the compiled module in order for the changes to take effect.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function returns 0 for success, and 1 for failure.

load 16.dll

## Standard • Miscellaneous

performs a runtime load of a 16-bit dynamic-link (external) library.

**load\_16\_dll ( *pathname* );**

*pathname*

The full pathname of the dynamic-link library (DLL) to be loaded.

**Note:** To call an external function, you must declare it with the `extern` function declaration.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**load\_dll**

Standard • Miscellaneous

performs a runtime load of a dynamic-link (external) library.

**load\_dll ( *pathname* );**

***pathname***                    The full pathname of the dynamic-link library (DLL) to be loaded.

---

**Note:** To call an external function, you must declare it with the `extern` function declaration.

---

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**log**

Standard • Arithmetic

returns the natural (base *e*) logarithm of the specified number.

**log ( *x* );**

***x***                    Specifies a positive, nonzero number.

**Return Values**

This function returns a real number.

**Availability**

This function is always available.

## lov\_get\_item

Context Sensitive • Oracle

retrieves an item from a list of values in an Oracle application.

**lov\_get\_item ( *list*, *column*, *row*, *out\_value* );**

*list* The name of the list of values.

*column* The column number of the item.

*row* The row number of the item.

*out\_value* The parameter where the item will be stored.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## lov\_select\_item

Context Sensitive • Oracle

selects an item from a list of values in an Oracle application.

**lov\_select\_item ( *list*, *item* );**

*list* The list name.

*item* The logical name of the item.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Developer 2000 support only.

---

**lr\_whoami**

Standard • Load Testing

returns information about the Vuser executing the script.

**lr\_whoami ( *vuser* [ , *sgroup* ] );**

*vuser*                           The output variable that stores the ID of the Vuser.

*sgroup*                           The output variable that stores the name of the Sgroup.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for LoadRunner GUI Vusers only.

---

**match**

Standard • String

finds the occurrence of a regular expression in a string.

**match ( *string*, *regular\_expression* );**

*string*                           The enclosing string.

*regular\_expression*           The expression to locate in the string.

Return Values

This function returns the character position at which the regular expression starts. If no match is found, the value 0 is returned.

Availability

This function is always available.

---

**menu\_get\_desc**

Context Sensitive • Menu Object

returns the physical description of a menu.

**menu\_get\_desc ( *menu*, *oblig*, *optional*, *selector*, *out\_desc* );**

*menu*

The full menu path, consisting of the menu's logical name and the menu item, separated by a semicolon (such as file;open). For submenus, the path includes the menu name, menu item, and submenu item.

*oblig*

The list of obligatory properties (separated by blank spaces).

*optional*

The list of optional properties (separated by blank spaces).

*selector*

The type of selector to be used (location or index).

*out\_desc*

The output variable that stores the description of the menu.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

## menu\_get\_info

Context Sensitive • Menu Object

returns the value of a menu property.

**menu\_get\_info ( *menu*, *property*, *out\_value* );**

*menu*

The full menu path, consisting of the menu's logical name and the menu item, separated by a semicolon (such as file;open). For submenus, the path includes the menu name, menu item, and submenu item.

*property*

The property to be checked. The following properties may be specified: class, label, value, enabled, MSW\_id, sub\_menu, count, sys\_menu, and position.

*out\_value*

The output variable that stores the value of the specified property.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## menu\_get\_item

Context Sensitive • Menu Object

returns the contents of a menu item.

**menu\_get\_item ( *menu*, *item\_number*, *out\_contents* );**

*menu*

The logical name of the menu. For submenus, the full path, consisting of the menu's logical name and the menu item, separated by a semicolon (such as file;type).

*item\_number*

The numeric position of the item in the menu. Note that the first position is numbered 0.

*out\_contents*

The output variable to which the value of the designated menu item is assigned.

The **menu\_get\_item** function determines the contents of a menu item at the specified numeric position in the menu.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

### menu\_get\_item\_num

Context Sensitive • Menu Object

returns the position of a menu item.

**menu\_get\_item\_num** (*menu*, *item*, *out\_position*);

<i>menu</i>	The logical name of the menu. For submenus, the full path, consisting of the menu's logical name and the menu item separated by a semicolon (such as file;type).
<i>item</i>	The name (string value) of the item as it appears in the menu.
<i>out_position</i>	The output variable which stores the numeric value of the item.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**menu\_select\_item**

Context Sensitive • Menu Object

selects a menu item.

**menu\_select\_item ( *menu*; *item* [ *x*, *y* ] );**

*menu*                   The logical name of the menu.

*item*                   The item to select.

*x,y*                   The position of the mouse click, expressed as x- and y-  
(pixel) coordinates.

## Return Values

This function returns one of a list of return values. For more information, see  
“General Return Values,” on page 98

## Availability

This function is always available.

---

**menu\_wait\_info**

Context Sensitive • Menu Object

waits for the value of a menu property.

**menu\_wait\_info ( *menu*, *property*, *value*, *time* );**

*menu*                   The logical name of the menu.

*property*              Any of the properties listed in the *User's Guide*.

*value*                  The property value.

*time*                  Indicates the maximum interval, in seconds, before the  
next statement is executed.

## Return Values

This function returns one of a list of return values. For more information, see  
“General Return Values,” on page 98.

## Availability

This function is always available.

---

**move\_locator\_abs**

Analog • Input Device

moves the mouse pointer to a new absolute position.

**move\_locator\_abs ( *x*, *y* [ , *time* ] );**

*x*, *y*

The absolute screen coordinates of the new pointer position, in pixels.

*time*

The interval, in milliseconds, that elapses before the locator is moved.

Return Values

This function always returns 0.

Availability

This function is always available.

---

**move\_locator\_rel**

Analog • Input Device

moves the mouse pointer to a new relative position.

**move\_locator\_rel ( *x*, *y* [ , *time* ] );**

*x*, *y*

The screen coordinates of the new pointer position, in pixels, relative to the current pointer position.

*time*

The interval that elapses before the locator is moved, in milliseconds.

Return Values

The return value of the function is always 0.

Availability

This function is always available.

**move\_locator\_text**

Analog • Input Device

moves the screen pointer to a string.

**move\_locator\_text ( *string*, *search\_area* [ , *x\_shift* [ ,*y\_shift* ] ] );**

*string*

A valid string expression. The string must be complete, and preceded and followed by a space. A regular expression with no blank spaces can be specified.

*search\_area*

The area to search, specified as  $x_1, y_1, x_2, y_2$  coordinates that define any two diagonal corners of a rectangle. The interpreter searches for the text in the area defined by the rectangle.

*x\_shift*, *y\_shift*

Indicates the offset of the pointer position from the specified string, in pixels.

**Return Values**

This function returns 0 if the text is located, and 1 if the text is not found.

**Availability**

This function is always available.

---

**move\_locator\_track**

Analog • Input Device

moves the mouse pointer along a prerecorded track.

**move\_locator\_track ( *track\_id* );**

*track\_id*

A code that points to tracking information stored in the test database. The specified track is a series of continuous pointer movements uninterrupted by input from keyboard or mouse.

**Return Values**

This function always returns the value 0.

**Availability**

This function is always available.

---

**mtype**

Analog• Input Device

specifies mouse button input.

**mtype ( *button\_input* [ , *technical\_id* ] );**

*button\_input*

A string expression representing mouse button input.

*technical\_id*

Points to internal timing and synchronization data. This parameter is only present when the mtype statement is recorded.

Return Values

This function always returns the value 0.

Availability

This function is always available.

---

**nargs**

Standard • Miscellaneous

returns the number of arguments passed.

**nargs ( );**

Return Values

This function returns the number of arguments actually passed, not the number specified in the definition of the function or test.

Availability

This function is always available.

---

## obj\_check\_bitmap

Context Sensitive • Object

compares an object bitmap to an expected bitmap.

**obj\_check\_bitmap ( *object*, *bitmap*, *time* [ , *x*, *y*, *width*, *height* ] );**

<i>object</i>	The logical name of the GUI object. The object may belong to any class.
<i>bitmap</i>	A string expression that identifies the captured bitmap.
<i>time</i>	The interval, which is added to the <i>timeout_msec</i> testing option, marking the maximum delay between the previous input event and the capture of the current bitmap, in seconds. For more information, refer to the “Setting Testing Options from a Test Script” chapter in the <i>WinRunner User’s Guide</i> .
<i>x</i> , <i>y</i>	For an area bitmap: the coordinates of the upper left corner, relative to the window in which the area is located.
<i>width</i> , <i>height</i>	For an area bitmap: the size of the area, in pixels.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## obj\_check\_gui

Context Sensitive • Object

compares current GUI object data to expected data.

**obj\_check\_gui ( *object*, *checklist*, *expected\_results\_file*, *time* );**

<i>object</i>	The logical name of the GUI object. The object may belong to any class.
<i>checklist</i>	The name of the checklist defining the GUI checks.
<i>expected_results_file</i>	The name of the file that stores the expected GUI data.

<i>time</i>	The interval, which is added to the timeout test option, marking the maximum delay between the previous input event and the capture of the current GUI data, in seconds. This interval is added to the timeout testing option during test execution.
-------------	--

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

## obj\_check\_info

Context Sensitive • Object

checks the value of an object property.

**obj\_check\_info** (*object*, *property*, *property\_value*);

*object*                   The logical name of the GUI object. The object may belong to any class.

*property*               The property to check.

*property\_value*          The property value.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**obj\_click\_on\_text**

Context Sensitive • Object

clicks on text in an object.

**obj\_click\_on\_text ( *object*, *string* [ , *search\_area* ] [ , *string\_def* [ , *mouse\_button* ] ] );***object*

The logical name of the object to search.

*string*

The text to locate. To specify a literal, case sensitive string, enclose the string in quotation marks. Alternatively, you can specify a string variable, which can include a regular expression. The regular expression need not begin with an exclamation mark.

*search\_area*The region of the object to search, relative to the object. This area is defined as a pair of coordinates, with  $x_1, y_1, x_2, y_2$  specifying any two diagonally opposite corners of the rectangular search region. If no *search\_area* is defined, then the entire object is considered as the search area.*string\_def*Defines how the text search is performed. If no *string\_def* is specified (0 or FALSE, the default parameter), the interpreter searches for a single, complete word only. If 1, or TRUE, is specified, the search is not restricted to a single, complete word.*mouse\_button*Specifies the mouse button that clicks on the text string. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the left button. Note that if you specify 1, or TRUE, for *string\_def*, then you must specify the mouse button to use. Similarly, if you specify the mouse button to use, then you must specify the *string\_def*.**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**obj\_drag**

Context Sensitive • Object

drags an object from a source object.

**obj\_drag ( *source\_object*, *x*, *y* [ , *mouse\_button* ] );**

<i>source_object</i>	The logical name of the GUI object. The object may belong to any class.
<i>x</i> , <i>y</i>	The <i>x,y</i> coordinates of the mouse pointer when clicked on the source object, relative to the upper left corner of the source object.
<i>mouse_button</i>	A constant that specifies the mouse button to hold down while dragging. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the button that performs the select function. This optional parameter is available for WinRunner only.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

## obj\_drop

Context Sensitive • Object

drops an object onto a target object.

**obj\_drop ( *target\_object*, *x*, *y* );**

*target\_object*

The logical name of the GUI object. The object may belong to any class.

*x*, *y*

The *x*, *y* coordinates of the pointer when released over the target object, relative to the upper left corner of the target object.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## obj\_exists

Context Sensitive • Object

checks whether an object is displayed on the screen.

**obj\_exists ( *object* [ , *time* ] );**

*object*

The logical name of the object. The object may belong to any class.

*time*

The sum of this number and the original *timeout\_msec* testing option is the amount of time (in seconds) before the next statement is executed.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**obj\_find\_text**

Context Sensitive • Object

returns the location of a string within an object.

**obj\_find\_text ( *object*, *string*, *result\_array* [ , *search\_area* ] [ , *string\_def* ] );**

*object*

The logical name of the object. The object may belong to any class.

*string*

A valid string expression or the name of a string variable, which can include a regular expression. The regular expression should not include an exclamation mark (!), however, which is treated as a literal character.

*result\_array*

The name of the four-element array that stores the location of the string. The elements are numbered 1 to 4. Elements 1 and 2 store the x- and y-coordinates of the upper left corner of the enclosing rectangle; elements 3 and 4 store the coordinates for the lower right corner.

*search\_area*

Indicates the area of the screen to search as coordinates that define any two diagonal corners of a rectangle, expressed as a pair of x,y coordinates. The coordinates are stored in *result\_array*.

*string\_def*

Defines the type of search to perform. If no value is specified (0 or FALSE, the default), the search is for a single, complete word only. When 1, or TRUE, is specified, the search is not restricted to a single, complete word.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**obj\_get\_desc**

Context Sensitive • Object

returns an object's physical description.

**obj\_get\_desc** (*object*, *oblig*, *optional*, *selector*, *out\_desc*);

<i>object</i>	The logical name of the GUI object. The object may belong to any class.
<i>oblig</i>	The list of obligatory properties (separated by blank spaces).
<i>optional</i>	The list of optional properties (separated by blank spaces).
<i>selector</i>	The type of selector used for this object class (location or index).
<i>out_desc</i>	The output variable that stores the description of the GUI object.

#### Return Values

If the *oblig*, *optional*, and *selector* parameters are null strings, **obj\_get\_desc** returns the current learning configuration for the object.

#### Availability

This function is always available.

---

**obj\_get\_info**

Context Sensitive • Object

returns the value of an object property.

**obj\_get\_info** (*object*, *property*, *out\_value*);

<i>object</i>	The logical name of the GUI object. The object may belong to any class.
<i>property</i>	Any of the properties listed in the <i>User's Guide</i> .
<i>out_value</i>	The output variable that stores the value of the property.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## obj\_get\_text

Context Sensitive • Object

reads text from an object.

**obj\_get\_text ( *object*, *out\_text* [ , *x<sub>1</sub>, y<sub>1</sub>, x<sub>2</sub>, y<sub>2</sub>* ] );**

*object*                   The logical name of the GUI object. The object may belong to any class.

*out\_text*               The name of the output variable that stores the captured text.

*x<sub>1</sub>,y<sub>1</sub>,x<sub>2</sub>,y<sub>2</sub>*           An optional parameter that defines the location from which text will be read, relative to the specified object. The pairs of coordinates can designate any two diagonally opposite corners of a rectangle.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## obj\_highlight

Context Sensitive • Object

highlights an object.

**obj\_highlight ( *object* [ , *flashes* ] );**

***object***      The logical name of the object. The object may belong to any class.

***flashes***      The number of times the object flashes. The default number is four.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## obj\_mouse\_click

Context Sensitive • Object

clicks on an object.

**obj\_mouse\_click ( *object*, *x*, *y* [ , *mouse\_button*] [ , *modifier* ] );**

***object***      The logical name of the object. The object may belong to any class.

***x*, *y***      The position of the mouse click expressed as x and y (pixel) coordinates. Coordinates are relative to the upper left corner of the GUI object.

***mouse\_button***      A constant that specifies the mouse button to click. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the button that performs the **select** function.

***modifier***      A constant that specifies the modifier key used with the mouse button. The value can be CONTROL, SHIFT, or CONTROL\_SHIFT.

---

**Note:** When running a test with an **obj\_mouse\_click** statement, the object that the mouse clicks must be fully displayed.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## obj\_mouse dbl\_click

Context Sensitive • Object

performs a double-click within an object.

**obj\_mouse dbl\_click** (*object*, *x*, *y* [ , *mouse\_button* ][ , *modifier* ]);

<i>object</i>	The logical name of the GUI object. The object may belong to any class.
<i>x</i> , <i>y</i>	The position of the double-click expressed as <i>x</i> and <i>y</i> (pixel) coordinates. Coordinates are relative to the upper left corner of the GUI object.
<i>mouse_button</i>	A constant that specifies the mouse button to click. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the button that performs the <b>select</b> function.
<i>modifier</i>	A constant that specifies the modifier key used with the mouse button. The value can be CONTROL, SHIFT, or CONTROL_SHIFT.

---

**Note:** When running a test with an **obj\_mouse dbl\_click** statement, the object that the mouse clicks must be fully displayed.

---

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**obj\_mouse\_drag**

Context Sensitive • Object

drags the mouse within an object.

**obj\_mouse\_drag ( *object*, *start\_x*, *start\_y*, *end\_x*, *end\_y* [ , *mouse\_button*] [ , *modifier*] );***object*

The logical name of the object. The object may belong to any class.

*start\_x*, *start\_y*

The x and y coordinates of the start point of the mouse drag. The coordinates are relative to the upper left corner of the GUI object.

*end\_x*, *end\_y*

The x and y coordinates of the end point of the mouse drag. The coordinates are relative to the upper left corner of the GUI object.

*mouse\_button*A constant that specifies the mouse button to hold down. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the button that performs the **select** function.*modifier*

A constant that specifies the modifier key used with the mouse button. The value can be CONTROL, SHIFT, or CONTROL\_SHIFT.

---

**Note:** When running a test with an **obj\_mouse\_drag** statement, the object that the mouse drags must be fully displayed.

---

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**obj\_mouse\_move**

Context Sensitive • Object

moves the mouse pointer within an object.

**obj\_mouse\_move ( *object*, *x*, *y* );***object*

The logical name of the GUI object. The object may belong to any class.

*x, y*

The position of the mouse pointer, expressed as *x* and *y* (pixel) coordinates. Note that the specified coordinates are relative to the upper left corner of the object. This position is relative to the upper left corner of the object.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**obj\_move\_locator\_text**

Context Sensitive • Object

moves the mouse pointer to a string in an object.

**obj\_move\_locator\_text ( *object*, *string* [ , *search\_area* ] [ , *string\_def* ] );***object*

The logical name of the object.

*string*

The text to locate. To specify a literal, case sensitive string, enclose the string in quotation marks. Alternatively, you can specify the name of a string variable. The value of the string variable can include a regular expression (the regular expression need not begin with an exclamation mark).

<i>search_area</i>	The region of the object to search, relative to the window. This area is defined as a pair of coordinates, with $x_1,y_1,x_2,y_2$ specifying any two diagonally opposite corners of the rectangular search region. If this parameter is not defined, then the entire <i>object</i> is considered the search area.
<i>string_def</i>	Defines how the text search is performed. If no <i>string_def</i> is specified, (0 or FALSE, the default parameter), the interpreter searches for a complete word only. If 1, or TRUE, is specified, the search is not restricted to a single, complete word.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**obj\_set\_info**

Context Sensitive • Object

sends the value of an object property.

**obj\_set\_info ( *object*, *property*, *out\_value* );**

*object*                   The logical name of the object. The object may belong to any class.

*property*               Any of the properties listed in the *User's Guide*.

*out\_value*              The output variable that stores the value of the property.

**Return Values**

This function returns one of the standard return values. It returns E\_ATTR\_NOT\_SUPPORTED for a specified property (for example, value) if one of the following events occur:

- The object does not have the method setValue.
- The method setValue exists, but it either has more than one parameter or the parameter does not belong to one of the following Java classes: String, int, boolean, Integer, Boolean.
- The parameter given in a TSL call statement cannot be converted to one of the Java classes mentioned above.
- The method setValue throws a Java exception when using the parameters provided in the call statement.

**Availability**

This function is always available.

---

**obj\_type**

Context Sensitive • Object

sends keyboard input to an object.

**obj\_type ( *object*, *keyboard\_input* );**

*object*                   The logical name of the GUI object.

*keyboard\_input*          A string expression that represents keystrokes.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## obj\_wait\_bitmap

## Context Sensitive • Object

waits for an object bitmap to be drawn on the screen.

**obj\_wait\_bitmap** (*window*, *bitmap*, *time* [, *x*, *y*, *width*, *height*]);

**object** The logical name of the object. The object may belong to any class.

*bitmap* A string expression that identifies the captured bitmap.

**time** Indicates the interval between the previous input event and the capture of the current bitmap, in seconds. This parameter is added to the *timeout\_msec* testing option and the sum indicates how much time WinRunner will wait for the capture of the bitmap.

**x, y** For an area bitmap: the coordinates of the upper left corner, relative to the object in which the selected region is located.

***width, height*** For an area bitmap: the size of the selected region, in pixels.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## obj\_wait\_info

Context Sensitive • Object

waits for the value of an object property.

**obj\_wait\_info ( *object*, *property*, *value*, *time* );**

<i>object</i>	The logical name of the object.
<i>property</i>	Any of the properties listed in the <i>User's Guide</i> .
<i>value</i>	The property value for which the function waits.
<i>time</i>	The interval, in seconds, before the next statement is executed.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## output\_message

Standard • Load Testing

sends a message to the controller.

**output\_message ( *message* );**

<i>message</i>	Any string.
----------------	-------------

The **output\_message** function sends a message from a Vuser script to the controller's Output window.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98

### Availability

This function is available for LoadRunner GUI Vusers only.

---

**password\_edit\_set**

Standard • Password

sets the value of a password edit field to a given value.

**password\_edit\_set ( *edit\_object*, *encrypted\_password* );**

*edit\_object*                   The logical name of the edit object.

*encrypted\_password*       The encrypted password as it appears in the script.

---

**Note:** You can also use the **edit\_set**, **type**, and **obj\_type** TSL functionsto set a password, however the **password\_edit\_set** function provides extra security by eliminating the password from the test script.

---

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**password\_encrypt**

Context Sensitive • Password

encrypts a plain password.

**password\_encrypt ( *password* );**

*password*                   The plain password.

**Return Values**

This function returns the encrypted password.

**Availability**

This function is always available.

**pause**

Standard • I/O

pauses test execution and displays a message box.

**pause ( [ *expression* ] );**

*expression*                  Any valid expression.

**Return Values**

This function always returns 0.

**Availability**

This function is always available.

---

**qt\_force\_send\_key**

Standard • QuickTest 2000

instructs WinRunner with the Year 2000 add-in to recognize an edit field which prompts a screen change when information is inserted.

**qt\_force\_send\_key ( *window\_name*, *field\_name* [ , *additional\_key* ] );**

*window\_name*                  The name of the window.

*field\_name*                  The name of the edit field.

*additional\_key*                  The key which causes the screen change.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is available for QuickTest 2000 only.

---

**qt\_reset\_all\_force\_send\_key**

Standard • QuickTest 2000

negates screen change configurations previously made using the **qt\_force\_send\_key** function.

**qt\_reset\_all\_force\_send\_key ()**

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**rand**

Standard • Arithmetic

returns a pseudo-random floating point number (*n*) in the range of  $0 \leq n < 1$ .

**rand ()**

Return Values

This function returns a real number.

Availability

This function is always available.

**reload**

Standard • Compiled Module

removes a compiled module from memory and loads it again.

**reload ( *module\_name* [ ,*1|0* [ ,*1|0* ] ] );**

***module\_name*** A string expression indicating the name of an existing compiled module.

**1|0** 1 indicates a system module. 0 indicates a user module. The default values is 0.

**1|0** This parameter is optional and only implemented if the second parameter is implemented. 1 indicates that a user module will not remain open after it is loaded.

0 indicates that the module remains open in the WinRunner window. The default value is 0.

---

**Note:** If you make changes to a function in a loaded compiled module, you must unload and reload the compiled module in order for the changes to take effect. For additional information, refer to the “Creating Compiled Modules” chapter in the *WinRunner User’s Guide*.

---

**Return Values**

This function returns 0 for success, and 1 for failure.

**Availability**

This function is always available.

---

**rendezvous**

Standard • Load Testing

sets a rendezvous point in a Vuser script.

**rendezvous ( *rendezvous\_name* );**

***rendezvous\_name*** The name of the rendezvous declared in a **declare\_rendezvous** statement.

## Return Value

This function returns 0 if the operation is successful, or one of the following error codes if it fails:

Error code	Number	Description
E_OK	0	operation successful
E_TIMEOUT	-10016	timeout reached before operation performed
E_REND_NF	-10218	rendezvous not defined
E_REND_NOT_MEM	-10219	vuser not defined as a participant in the rendezvous
E_REND_INVALID	-10220	rendezvous disabled

## Availability

This function is available for LoadRunner GUI Vusers only.

## report\_msg

Standard • I/O

writes a message in the test report.

**report\_msg ( *message* );**

*message*                           A valid string expression.

## Return Values

This function always returns 0.

## Availability

This function is always available.

**return**

Standard • Call Statements

returns an expression to the calling function or test.

**return** [ *expression* ];

*expression*                    The expression to return.

The **return** statement returns an expression to the calling function or test. It is used exclusively in functions. It also halts execution of the called function and passes control back to the calling function or test.

#### Return Values

If no expression is used, then an empty string is returned. Otherwise, the return statement does not have a return value.

#### Availability

This statement is always available.

## scroll\_check\_info

Context Sensitive • Scroll Object

checks the value of a scroll property.

**scroll\_check\_info ( scroll, property, property\_value );**

*scroll* The logical name of the scroll.

*property* The property to be checked.

*property\_value* The expected property value.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

scroll\_check\_pos

Context Sensitive • Scroll Object

checks the current position of a scroll.

**scroll\_check\_pos ( scroll, position );**

*scroll* The logical name of the scroll.

*position* A number indicating the expected scroll position.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

scroll\_drag

## Context Sensitive • Scroll Object.

scrolls to the specified location.

**scroll\_drag** ( *scroll, orientation, position* );

<i>scroll</i>	The logical name of the scroll.
<i>orientation</i>	The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).
<i>position</i>	The absolute position within the scroll.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function can be used for scroll bar and slider objects.

## scroll\_drag\_from\_min

Context Sensitive • Scroll Object

scrolls from the minimum position.

**scroll\_drag\_from\_min** ( *scroll, orientation, position* );

<i>scroll</i>	The logical name of the scroll object.
<i>orientation</i>	The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).
<i>position</i>	The number of units from the minimum position to drag the scroll.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function can be used for scroll bar and slider objects.

---

**scroll\_get\_info**

Context Sensitive • Scroll Object

returns the value of a scroll property.

**scroll\_get\_info ( scroll, property, out\_value );**

*scroll*

The logical name of the scroll.

*property*

Any of the properties listed in the *WinRunner User's Guide*.

*out\_value*

The output variable that stores the value of the specified property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function can be used for scroll bar and slider objects.

---

**scroll\_get\_max**

Context Sensitive • Scroll Object

returns the maximum (end) position of a scroll.

**scroll\_get\_max ( scroll, orientation, out\_max );**

*scroll*

The logical name of the scroll.

*orientation*

The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).

*out\_max*

The output variable which stores the maximum value of the scroll.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function can be used for scroll bar and slider objects.

## scroll\_get\_min

Context Sensitive • Scroll Object

returns the minimum (start) position of a scroll.

**scroll\_get\_min ( scroll, orientation, out\_min );**

<i>scroll</i>	The logical name of the scroll.
<i>orientation</i>	The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).
<i>out_min</i>	The output variable that stores the minimum (starting) value of the scroll.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function can be used for scroll bar and slider objects.

---

## scroll\_get\_pos

Context Sensitive • Scroll Object

returns the current scroll position.

**scroll\_get\_pos ( scroll, orientation, out\_pos );**

<i>scroll</i>	The logical name of the scroll.
<i>orientation</i>	The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).
<i>out_pos</i>	The output variable which stores the current position of the scroll.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function can be used for scroll bar and slider objects.

## scroll\_get\_selected

Context Sensitive • Scroll Object

returns the minimum and maximum values of the selected range on a slider.

**scroll\_get\_selected ( *slider*, *min\_value*, *max\_value* );**

*slider* The logical name of the slider.

***min\_value*** The output variable that stores the minimum value of the selected range.

**max\_value** The output variable that stores the maximum value of the selected range.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

The scroll\_get\_selected function works only for slider objects, for which the TBS\_ENABLESEL RANGE flag is set. This flag allows a selection range within the scroll to be displayed.

## scroll\_line

Context Sensitive • Scroll Object

scrolls the specified number of lines.

**scroll\_line ( scroll, orientation, [+|-] lines );**

<i>scroll</i>	The logical name of the scroll.
<i>orientation</i>	The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).
[+ -] <i>lines</i>	The number of scrolled lines. "+" indicates the scroll is performed downward or to the right; "-" indicates the scroll is performed upward or to the left. The default is "+".

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function can be used for scroll bar and slider objects.

---

## scroll\_max

Context Sensitive • Scroll Object

sets a scroll to its maximum (end) position.

**scroll\_max ( scroll, orientation );**

<i>scroll</i>	The logical name of the scroll.
<i>orientation</i>	The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function can be used for scroll bar and slider objects.

---

**scroll\_min**

Context Sensitive • Scroll Object

sets the scroll to its minimum (start) position.

**scroll\_min ( *scroll*, *orientation* );**

*scroll*

The logical name of the scroll object.

*orientation*

The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function can be used for scroll bar and slider objects.

---

**scroll\_page**

Context Sensitive • Scroll Object

moves the scroll the specified number of pages.

**scroll\_page ( *scroll*, *orientation*, [+|-] *pages* );**

*scroll*

The logical name of the scroll.

*orientation*

The direction of the scroll; either VSCROLL (vertical) or HSCROLL (horizontal).

[+|-] *pages*

The number of scrolled pages. "+" indicates that the scroll is performed downward or to the right; "-" indicates that the scroll is performed upward or to the left. The default is '+'.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function can be used for scroll bar and slider objects.

**scroll\_wait\_info**

Context Sensitive • Scroll Object

waits for the value of a scroll property.

**scroll\_wait\_info ( scroll, property, value, time );**

<i>scroll</i>	The logical name of the scroll.
<i>property</i>	Any of the properties listed in the <i>WinRunner User's Guide</i> .
<i>value</i>	The property value.
<i>time</i>	The interval, in seconds, before the next statement is executed.

**Return Values**

This function returns one of a list of return values. For more information, see "General Return Values," on page 98.

**Availability**

This function can be used for scroll bar and slider objects.

---

**set\_aut\_var**

Standard • Testing Option

sets how WinRunner learns descriptions of objects, records tests, and runs tests on Java applets or applications.

**set\_aut\_var ( variable, value );**

<i>variable</i>	The variable to set.
<i>value</i>	The value of the variable.

**Return Values**

This function returns one of a list of return values. For more information, see "General Return Values," on page 98.

**Availability**

This function is available only for WinRunner with Java support.

---

**set\_class\_map** Context Sensitive • GUI Map Configuration

associates a custom class with a standard class.

**set\_class\_map** (*custom\_class*, *standard\_class*);

*custom\_class* The name of the custom class used in the application.

*standard\_class* The name of the Mercury class or the MS Windows standard class with the same behavior as the custom class.

---

**Note:** You should store **set\_class\_map** statements in a startup test.

---

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WinRunner and GUI Vusers running on PC platforms only.

## set\_record\_attr

Context Sensitive • GUI Map Configuration

sets the properties to learn for an object class.

**set\_record\_attr** (*class*, *oblig\_prop*, *optional\_prop*, *selector*);

**class** The name of the Mercury class, MSW\_class, or X\_class.

*oblig\_prop* A list of properties (separated by blank spaces) to always learn.

*optional\_prop* A list of descending properties (separated by blank spaces) to add to the description until unique identification of the object is achieved.

**selector** The type of selector to be applied in case both obligatory and optional properties do not achieve a unique object identification. This may be either index or location.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## set\_record\_method

Context Sensitive • GUI Map Configuration

specifies the record method for a class.

**set\_record\_method** (*class, method*);

***class*** The name of a standard class, MSW\_class, or TOOLKIT\_class.

**method** The record method to use, as described in the table below.

Method	Description
RM_RECORD	Records operations using Context Sensitive functions. This is the default method for all the standard classes, except the object class (for which the default is MIC_MOUSE).
RM_IGNORE	Turns off recording.
RM_PASSUP	Records mouse operations (relative to the parent of the object) and keyboard input.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

set window

Context Sensitive • Window Object

specifies the window to receive subsequent input.

```
set window ( window[ ,time ] );
```

## *window*

The logical name of the window.

*time*

The time is added to the `timeout_msec` testing option to give the maximum interval, in seconds, before the next statement is executed.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**\_set\_window**

Context Sensitive • Window Object

specifies a window to receive input.

**\_set\_window ( desc, time );**

*desc*

The physical description of the window.

*time*

The time is added to the *timeout\_msec* testing option to give the maximum interval, in seconds, before the next statement is executed.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**setvar**

Standard • Testing Option

sets the value of a testing option.

**setvar ( option, value );**

*option*

A testing option.

*value*

The value to assign to the testing option.

The **setvar** function changes the value of a testing option. For a list and an in-depth explanations of **setvar** options, refer to the “Setting Testing Options from a Test Script” chapter in the *WinRunner User’s Guide*.

**Return Values**

This function always returns 0.

**Availability**

This function is always available.

---

**siebel\_click\_history**

Context Sensitive •Siebel

clicks the Siebel History button

**siebel\_click\_history ( *thread\_bar\_object* );**

*thread\_bar\_object*      The logical name of the Siebel bar object containing the History button.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_connect\_repository**

Context Sensitive •Siebel

connects to the Siebel repository database.

**siebel\_connect\_repository ( *connection\_string* );**

*connection\_string*

The string that activates the connection to the Siebel repository database.

---

**Note:** You only need to call this function once per connection.

---

If you encounter difficulties connecting the repository using an existing DSN, use the ODBC Data Source Administrator from the Windows Control Panel to define a new User Data Source (DSN) that refers to the Siebel Repository database.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_get\_active\_applet**

Context Sensitive •Siebel

returns the active applet name.

**siebel\_get\_active\_applet ( *applet\_name* );**

*applet\_name*

The output variable that stores the name of the active applet.

---

**Note:** A **set\_window** statement must precede this function in order to direct the input to the correct application window.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

### **siebel\_get\_active\_buscomp**

Context Sensitive •Siebel

returns the active business component name.

**siebel\_get\_active\_buscomp ( *bus\_comp\_name* );**

<i>bus_comp_name</i>	The output variable that stores the name of the active business component.
----------------------	--

---

**Note:** A **set\_window** statement must precede this function in order to direct the input to the correct application window.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_get\_active\_busobj**

Context Sensitive •Siebel

returns the active business object name.

**siebel\_get\_active\_busobj ( *bus\_obj\_name* );**

*bus\_obj\_name*

The output variable that stores the name of the active business object.

---

**Note:** A **set\_window** statement must precede this function in order to direct the input to the correct application window.

---

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_get\_active\_control**

Context Sensitive •Siebel

returns the active control name.

**siebel\_get\_active\_control ( *control\_name* );**

*control\_name*

The output variable that stores the name of the active control.

---

**Notes:** This function makes it possible to use the **siebel\_get\_control\_value** and **siebel\_set\_control\_value** functions. A **set\_window** statement must precede this function in order to direct the input to the correct application window.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

## siebel\_get\_active\_view

Context Sensitive • Siebel

returns the active view name.

**siebel\_get\_active\_view ( *view\_name* );**

**`view_name`** The output variable that stores the name of the active View object.

**Note:** A `set_window` statement must precede this function in order to direct the input to the correct application window.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

## siebel\_get\_chart\_data

Context Sensitive •Siebel

returns the legend data and chart values from the specified chart.

**siebel\_get\_chart\_data ( *chart\_object*, *ret\_legend\_array*, *ret\_values\_array* );**

*chart\_object*                   The logical name of the chart or the chart's legend.

*ret\_legend\_array*               The output variable that stores the array of legend elements.

*ret\_values\_array*              The output variable that stores the array of chart values.

---

**Note:** Either the legend or the chart may be selected, and that both will return the same data.

---

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for WinRunner with Siebel support.

---

## siebel\_get\_control\_value

Context Sensitive •Siebel

returns the value of the active control.

**siebel\_get\_control\_value ( *value* );**

*value*                          The output variable that stores the value of the active control.

---

**Note:** The **siebel\_set\_active\_control** function must precede this statement in order to establish the active control.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

## siebel\_goto\_record

Context Sensitive •Siebel

navigates to the specified record.

**siebel\_goto\_record ( *direction* );**

*direction*

The direction in which to move to get to the desired record from the current location. Possible values are: "First", "Last", "Previous", or "Next".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_navigate\_view**

Context Sensitive •Siebel

navigates to the specified view.

**siebel\_navigate\_view ( *view\_name* );***view\_name*

The internal name of the view to be reached.

---

**Note:** Navigation is sensitive to the record context.

---

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_obj\_get\_info**

Context Sensitive •Siebel

returns the value of a single Siebel property from the Siebel repository database.

**siebel\_obj\_get\_info ( *obj\_type*, *obj\_name*, *applet\_name*, *property\_name*, *ret\_prop\_val* );***obj\_type*

The Siebel type for which to retrieve the attribute.

Possible values for this parameter are:

S\_APPLET, S\_BUSCOMP, S\_BUSOBJ, S\_CONTROL,  
S\_FIELD, or S\_VIEW*obj\_name*

The internal object name for which to retrieve the attribute.

*applet\_name*

The applet name

Required only with *obj\_type*: CONTROL or FIELD. For all other *obj\_types*, enter "".*property\_name*

The name of the property to retrieve.

<i>ret_prop_val</i>	The output variable that stores the value of the specified object property.
---------------------	---

---

**Note:** You must connect to the Siebel repository database with a **siebel\_connect\_repository** statement before you use this function.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

## siebel\_obj\_get\_properties

Context Sensitive •Siebel

returns all properties of a specified Siebel in the Siebel repository database.

```
siebel_obj_get_properties ( obj_type, obj_name, applet_name, ret_prop_array);
```

*obj\_type* The Siebel type for which to retrieve the properties.

Possible values for this parameter are:

S\_APPLET, S\_BUSCOMP, S\_BUSOBJ, S\_CONTROL,  
S\_FIELD, or S\_VIEW

*obj\_name* The internal object name for which to retrieve the properties.

*applet\_name* The applet name.

Required only with obj\_type: CONTROL or FIELD. For all other obj\_types, enter "".

*ret\_prop\_array* The output variable that stores the array of values for the specified object property.

**Note:** You must connect to the Siebel repository database with a `siebel_connect_repository` statement before you use this function.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_select\_alpha**

Context Sensitive •Siebel

selects a letter key from the alpha tab bar.

**siebel\_select\_alpha ( *alpha\_tab\_object*, *key* );**

*alpha\_tab\_object*      The logical name of the alpha tab object; usually "alpha tab".

*key*      The letter key to select from the alpha tab.

Return Values

This function returns one of a list of return values. For more information, see "General Return Values," on page 98.

Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_set\_active\_applet**

Context Sensitive •Siebel

sets the specified applet as the active applet.

**siebel\_set\_active\_applet ( *applet\_name* );**

*applet\_name*      The internal name of the of the applet to activate.

If you do not know the applet's internal name, you may use the **siebel\_get\_active\_applet** to retrieve it.

Return Values

This function returns one of a list of return values. For more information, see "General Return Values," on page 98.

Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_set\_active\_control**

Context Sensitive •Siebel

sets the specified control as the active control.

**siebel\_set\_active\_control ( *control\_name* );**

*control\_name*

The internal name of the control to activate.

If you do not know the control's internal name, you can use the **siebel\_get\_active\_applet** function to retrieve it.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_set\_control\_value**

Context Sensitive •Siebel

sets the value of the active control.

**siebel\_set\_control\_value ( *new\_value* );**

*new\_value*

The value to be assigned to the active control.

---

**Note:** The **siebel\_set\_active\_control** function must precede this statement in order to establish the active control.

---

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is supported for WinRunner with Siebel support.

---

**siebel\_terminate**

Context Sensitive • Siebel

closes the Siebel application.

**siebel\_terminate ( );**

---

**Note:** Call this function to terminate the Siebel application or immediately after manually closing the application.

---

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is supported for WinRunner with Siebel support.

---

**sin**

Standard • Arithmetic

calculates the sine of an angle expressed in radians.

**sin ( *x* );**

**Return Values**

This function returns a real number.

**Availability**

This function is always available.

spin\_down

Context Sensitive • Spin Object

scrolls a spin control down a specified number of times.

**spin\_down** ( *spin\_obj*, *spins* );

*spin\_obj* The name of the spin control.

*spins* The number of times the control is moved down.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Visual Basic support.

## spin\_get\_info

Context Sensitive • Spin Object

returns the value of a spin property.

```
spin_get_info ( spin, property, out_value );
```

*spin* The logical name of the spin object.

*property* Any of the properties listed in the *User's Guide*.

***out\_value*** The output variable that stores the value of the specified property.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**spin\_get\_pos**

Context Sensitive • Spin Object

returns the current position of a spin object.

**spin\_get\_pos ( *spin*, *out\_value* );**

*spin*

The logical name of the spin object.

*property*

Any of the properties listed in the *User's Guide*.

*out\_value*

The output variable that stores the value of the specified property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**spin\_get\_range**

Context Sensitive • Spin Object

returns the minimum and maximum positions of a spin object.

**spin\_get\_range ( *spin*, *out\_min\_pos*, *out\_max\_pos* );**

*spin*

The logical name of the spin object.

*out\_min\_pos*

The output variable that stores the minimum position of the spin object.

*out\_max\_pos*

The output variable that stores the maximum position of the spin object.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

**spin\_max**

Context Sensitive • Spin Object

sets a spin object to its maximum value.

**spin\_max ( *spin* );***spin*

The logical name of the spin object.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**spin\_min**

Context Sensitive • Spin Object

sets a spin object to its minimum value.

**spin\_min ( *spin* );***spin*

The logical name of the spin object.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**spin\_next**

Context Sensitive • Spin Object

sets a spin object to its next value.

**spin\_next ( *spin* [ , *index* ] );***spin*

The logical name of the spin object.

*index*

The number of the text field in the spin object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

spin\_prev

Context Sensitive • Spin Object

sets a spin object to its previous value.

**spin\_prev ( *spin* );**

*spin* The logical name of the spin object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## spin\_set

## Context Sensitive • Spin Object

**sets a spin object to an item.**

**spin\_set** ( *spin*, *item* );

*spin* The logical name of the spin object.

*item* The item to select in the spin object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

spin\_up

## Context Sensitive • Spin Object

scrolls a spin control up the specified number of times.

**spin\_up** (*spin\_obj*, *spins*);

*spin\_obj* The name of the spin control.

*spins* The number of times the control is moved up.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Visual Basic support.

**spin\_wait\_info**

Context Sensitive • Spin Object

waits for a spin property to attain a specified value.

**spin\_wait\_info ( *spin*, *property*, *value*, *time* );**

<i>spin</i>	The logical name of the spin.
<i>property</i>	Any of the properties listed in the <i>WinRunner User's Guide</i> .
<i>value</i>	The property value for which the function waits.
<i>time</i>	The interval, in seconds, before the next statement is executed.

#### Return Values

This function returns one of a list of return values. For more information, see "General Return Values," on page 98.

#### Availability

This function is always available.

**split**

Standard • Array

divides an input string into fields and stores them in an array.

**split ( *string*, *array* [ , *field\_separator*<sub>1</sub>, ... *field\_separator*<sub>n</sub> ] );**

<i>string</i>	A valid string expression.
<i>array</i>	The name of the storage array.
<i>field_separator</i>	The characters in the string which designate where the string is to be split into fields. More than one character can be used as a separator. The default is a single blank.

#### Return Values

This function returns the number of elements in the array.

#### Availability

This function is always available.

**sprintf**

Standard • I/O

returns a formatted string to a variable.

**sprintf ( format, exp<sub>1</sub>, exp<sub>2</sub>, ... exp<sub>n</sub> );**

**format** May include both a literal string to be printed and  
formatting specifications.

**exp** The expressions to format.

**Return Values**

This function returns a formatted string.

**Availability**

This function is always available.

---

**sqrt**

Standard • Arithmetic

returns the square root of its argument.

**sqrt ( x );**

**x** A variable.

**Return Values**

This function returns a real number.

**Availability**

This function is always available.

---

**srand**

Standard • Arithmetic

defines a seed parameter for the **rand** function, which returns a pseudo-random floating point number (*n*) within the range of  $0 \leq n \leq 1$ .

**srand ( [ *x* ] );**

*x*                      Specifies the seed parameter. If no seed is entered, the time of day is the value of the seed.

---

**Note:** The seed parameter provided by **srand** starts the random sequence..

---

**Return Values**

This function returns a real number indicating the user-defined seed parameter, or, if no seed is given, the value returned by **get\_time**.

**Availability**

This function is always available.

---

**start\_transaction**

Standard • Load Testing

marks the beginning of a transaction for performance analysis.

**start\_transaction ( *transaction\_name* );**

*transaction\_name*        A string expression that names the transaction. The string must not contain any spaces.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is available for LoadRunner GUI Vusers only.

**static\_check\_info**

Context Sensitive • Static Text Object

checks the value of a static text object property.

**static\_check\_info ( *static*, *property*, *property\_value* );**

*static*                   The logical name of the static text object.

*property*               The property to check.

*property\_value*          The expected property value.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**static\_check\_text**

Context Sensitive • Static Text Object

checks the content of a static text object.

**static\_check\_text ( *static*, *text*, *case\_sensitive* );**

*static*                   The logical name of the static text object.

*text*                     The contents of the static text object.

*case\_sensitive*          Indicates whether the comparison is case sensitive. This value is either TRUE or FALSE.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**static\_get\_info**

Context Sensitive • Static Text Object

returns the value of a static text object property.

**static\_get\_info ( *static*, *property*, *out\_value* );**

*static*

The logical name of the static text object.

*property*

Any of the properties listed in the *User's Guide*.

*out\_value*

The output variable that stores the value of the specified property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**static\_get\_text**

Context Sensitive • Static Text Object

returns the contents of a static text object.

**static\_get\_text ( *static*, *out\_string* );**

*static*

The logical name of the static text object.

*out\_string*

The output variable that stores the string found in the static text object.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## static\_wait\_info

Context Sensitive • Static Text Object

waits for the value of a static text object property.

**static\_wait\_info** (*static, property, value, time*);

<i>static</i>	The logical name of the static text object.
<i>property</i>	Any of the properties listed in the <i>User's Guide</i> .
<i>value</i>	The expected property value.
<i>time</i>	The maximum interval, in seconds, before the next statement is executed.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## statusbar\_get\_field\_num

Context Sensitive • Statusbar

returns the numeric index of a field on a status bar.

**statusbar\_get\_field\_num** (*statusbar*, *field*, *field\_index*);

<i>statusbar</i>	The logical name of the status bar.
<i>field</i>	The text in the status bar field. If the text in the field changes, you can use a regular expression.
<i>field_index</i>	The output variable that stores the numeric index of the field. Note that the first field in the status bar is numbered 0.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## statusbar\_get\_info

Context Sensitive • Statusbar

returns the value of a status bar property.

**statusbar\_get\_info ( *statusbar*, *property*, *out\_value* );**

*statusbar*

The logical name of the status bar.

*property*

The following properties may be specified: *abs\_x*, *abs\_y*, *active*, *attached\_text*, *class*, *count*, *displayed*, *enabled*, *focus*, *handle*, *height*, *label*, *MSW\_class*, *MSW\_id*, *nchildren*, *parent*, *value* (default), *width*, *x*, *y*

*out\_value*

The output variable that stores the value of the specified property.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**statusbar\_get\_text**

Context Sensitive • Statusbar

reads text from a field on a status bar.

**statusbar\_get\_text ( *statusbar*, *field\_index*, *out\_text* );*****statusbar***

The logical name of the status bar.

***field\_index***

The index number of the field containing the text you want to read. The first field in the status bar is numbered 0.

***out\_text***

The name of the output variable that stores the text.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**statusbar\_wait\_info**

Context Sensitive • Statusbar

waits for the value of a status bar property.

**statusbar\_wait\_info ( *statusbar*, *property*, *value*, *time* );*****statusbar***

The logical name of the status bar.

***property***The property to wait for. The following properties may be specified: *abs\_x*, *abs\_y*, *active*, *attached\_text*, *class*, *count*, *displayed*, *enabled*, *focus*, *handle*, *height*, *label*, *MSW\_class*, *MSW\_id*, *nchildren*, *parent*, *value* (default), *width*, *x*, *y****value***

The property value.

***time***

Indicates the interval, in seconds, before the next statement is executed.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## str\_map\_logical\_to\_visual

Standard • I/O

converts a logical string to a visual string or vice-versa.

**str\_map\_logical\_to\_visual** (*logical\_string*, *visual\_string*);

*logical\_string*      A valid logical string expression.

*visual\_string*      The corresponding returned valid visual string expression.

The **str\_map\_logical\_to\_visual** function returns a valid visual string expression for a valid logical string expression. Alternatively, it returns a valid logical string expression for a valid visual string expression.

---

**Note:** This function is primarily intended for use with RTL-style windows. When working with applications with RTL-style windows, the **get\_text** function sometimes returns a logical string instead of a visual string.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**substr**

Standard • String

extracts a substring from a string.

**substr ( *string*, *position* [ , *length* ] );**

*string*

A valid string expression.

*position*

An integer that indicates the position of the first character of the substring. The position of the first character of the string is 1, the second is 2, etc.

*length*

Defines the number of characters (starting from *position*) to include in the substring.

Return Values

This function returns a string. If the value of *position* is greater than the length of the specified string, then the function returns the null string.

Availability

This function is always available.

---

**system**

Standard • Operating System

executes an operating system command.

**system ( *expression* );**

*expression*

A string expression that specifies the system command to execute.

Return Values

The return value of the function is the value of the operating system command executed.

Availability

This function is available for WinRunner and LoadRunner GUI Vusers on UNIX platforms. The **system** function is also supported on other platforms for purposes of porting and backward compatibility.

---

**tab\_get\_info**

Context Sensitive • Tab Object

returns the value of a tab property.

**tab\_get\_info ( *tab*, *property*, *out\_value* );**

*tab*

The logical name of the tab object.

*property*

Any of the properties listed in the *User's Guide*.

*out\_value*

The output variable that stores the value of the specified property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**tab\_get\_item**

Context Sensitive • Tab Object

returns the name of a tab item.

**tab\_get\_item ( *tab*, *item\_num*, *out\_item* );**

*tab*

The logical name of the tab.

*item\_num*

The location of the tab item. Note that the first tab item in a property sheet is numbered 0.

*out\_item*

The output variable that stores the tab name.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

tab\_get\_selected

Context Sensitive • Tab Object

returns the name and number of the selected tab item.

**tab\_get\_selected** ( *tab*, *out\_item*, *out\_num* );

*tab*

## The logical name of the tab.

*out\_item*

The output variable that stores the name of the selected tab item. Note that the first tab item in a property sheet is numbered 0.

*out\_num*

The output variable that stores the index of the selected tab item.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## tab\_select\_item

Context Sensitive • Tab Object

selects a tab item.

**tab\_select\_item ( *tab*, *item* );**

*tab*

The logical name of the tab.

### *item*

The item to select. The item can be denoted by either its name or its numeric index. The index is specified as a string preceded by the character #. The first tab item is numbered 0.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**tab\_wait\_info**

Context Sensitive • Tab Object

waits for the value of a tab property.

**tab\_wait\_info ( *tab*, *property*, *value*, *time* );**

<i>tab</i>	The logical name of the tab.
<i>property</i>	Any of the properties listed in the <i>User's Guide</i> .
<i>value</i>	The property value for which the function waits.
<i>time</i>	The maximum interval, in seconds, before the next statement is executed.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**tbl\_activate\_cell**

Context Sensitive • Table

double-clicks the specified cell in a table.

**tbl\_activate\_cell ( *table*, *row*, *column* );**

*table*

The logical name of the table.

*row*

**By location:** # <row\_location>

The location of the row within the table, specified by a string preceded by the character #, such as "#2".

For WinRunner with PowerBuilder support, the *row* can also be in the following format:

**By content:** <Column\_name>=<column\_content<sub>1</sub>  
[column\_content<sub>n</sub>....]>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row.

*column*

The *column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number". When the column name is specified, WinRunner takes the name from the database itself, and not from the application.

---

**Note for PowerBuilder users:** When *row* is specified **by content**, *column* must also be specified **by content**.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is not supported for WebTest.

This function is supported for WinRunner with Java support. It is supported for the following Java toolkit packages: JFC, EWT (Oracle), and KLG.

This function is supported for WinRunner with PowerBuilder or Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl\_activate\_col

## Context Sensitive • Table

double-clicks the specified column in a table.

**tbl\_activate\_col** (*table*, *column*);

**table** The logical name of the table.

*column* The *column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number".

When the column name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

### Availability

This function is available only for WinRunner with Java support. It is supported for the following Java toolkit packages: JFC and KLG.

## tbl\_activate\_header

## Context Sensitive • Table

double-clicks the specified column header in a table.

**tbl activate header ( *table*, *column* );**

**table** The logical name of the table.

The *column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number".

## Return Values

This function returns one of a list of return values. For more information, see "General Return Values," on page 98, and "Return Values for PowerBuilder and Table Functions," on page 103.

## Availability

This function is not supported for WebTest.

This function is supported for WinRunner with Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl\_activate\_row

Context Sensitive • Table

double-clicks the specified row in a table.

**tbl\_activate\_row ( *table*, *row* );**

**table** The logical name of the table.

**By location:** # <column\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner with Java support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, and KLG.

This function is supported for WinRunner with Siebel support.

## tbl\_click\_cell

## Analog • Table

clicks in a cell in a JFC JTable object.

**tbl\_click\_cell** (*table\_name*, *cell\_index*, *column\_name* [, *mouse\_button*] );

*table\_name* The name of the table.

*cell\_index* An index number denoting the position of the cell in the column. The index number is preceded by #, for example #2.

***column\_name*** The name of the column in which the cell is located.

***mouse\_button*** The mouse button used to click on the cell (optional).

---

**Note:** WinRunner records this function only after the **set\_aut\_var** function is used to set the TABLE\_RECORD\_METHOD variable to ANALOG.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support.

---

## tbl dbl\_click\_cell

Analog • Table

double-clicks in a cell in a JFC JTable object.

**tbl dbl\_click\_cell ( *table\_name*, *cell\_index*, *column\_name* [ , *mouse\_button* ] );**

<i>table_name</i>	The name of the table.
<i>cell_index</i>	An index number denoting the position of the cell in the column. The index number is preceded by #, for example #2.
<i>column_name</i>	The name of the column in which the cell is located.
<i>mouse_button</i>	The mouse button used to click on the cell (optional).

---

**Note:** WinRunner records this function only after the **set\_au\_var** function is used to set the TABLE\_RECORD\_METHOD variable to ANALOG.

---

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

### Availability

This function is available only for WinRunner with Java Add-in support.

tbl deselect col

## Context Sensitive • Table

deselects the specified column in a table.

**tbl\_deselect\_col ( *table*, *column* );**

**table** The logical name of the table.

The *column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight\_Number".

When the column name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

### Availability

This function is available only for WinRunner with Java support. It is supported for the JFC Java toolkit package.

## tbl\_deselect\_cols\_range

Context Sensitive • Table

deselects the specified range of columns in a table.

```
tbl_deselect_cols_range ( table, from_column, to_column );
```

*table* The logical name of the table.

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight\_Number".

When a column name is specified, WinRunner takes the name from the database itself, and not from the application.

*to\_column* The *to\_column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight\_Number".

When a column name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java support. It is supported for the JFC Java toolkit package.

## tbl\_deselect\_row

Context Sensitive • Table

deselects the specified row in a table.

**tbl\_deselect\_row ( *table*, *row* );**

*table* The logical name of the table.

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, and KLG.

## tbl\_deselect\_rows\_range

Context Sensitive • Table

deselects the specified range of rows in a table.

**tbl\_deselect\_rows\_range** (*table*, *from\_row*, *to\_row*);

table

The logical name of the table.

*from\_row*

The *from\_row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

*to\_row*

The *to\_row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC and Visual Cafe.

tbl\_drag

Analog • Table

drags a cell to a different location within a JFC JTable object.

```
tbl_drag ( table_name, start_row, start_col, end_row, end_col [ , mouse_button ] );
```

*table name*

The name of the table.

<i>start_row</i>	The row name or an index number denoting the row which contains the cell before the drag operation is performed. The index number is preceded by #, for example #3.
<i>start_col</i>	The column name or an index number denoting the column which contains the cell before the drag operation is performed. The index number is preceded by #, for example #2.
<i>end_row</i>	The row name or an index number denoting the row which contains the cell after the drag operation is performed. The index number is preceded by #, for example #5.
<i>end_col</i>	The column name or an index number denoting the column which contains the cell after the drag operation is performed. The index number is preceded by #, for example #7.
<i>mouse_button</i>	The mouse button used to drag the cell (optional).

---

**Note:** WinRunner records this function only after the **set\_aut\_var** function is used to set the TABLE\_RECORD\_METHOD variable to ANALOG.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support.

## tbl\_extend\_col

Context Sensitive • Table

**Add Column** adds a column to the currently selected columns in a table.

**tbl\_extend\_col** ( *table*, *column* );

**table** The logical name of the table.

*column* The column can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number".

When the column name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the JFC Java toolkit package.

## tbl\_extend\_cols\_range

Context Sensitive • Table

adds columns to the currently selected columns in a table.

**tbl\_extend\_cols\_range** (*table*, *from\_column*, *to\_column*);

*table* The logical name of the table.

The *from\_column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight\_Number".

When a column name is specified, WinRunner takes the name from the database itself, and not from the application.

*to\_column* The *to\_column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight Number".

When a column name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

### Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the JFC Java toolkit package.

## tbl\_extend\_row

Context Sensitive • Table

adds a row to the currently selected rows in a table.

**tbl\_extend\_row ( *table*, *row* );**

**table** The logical name of the table.

*row*                          The *row* can either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, and KLG.

## tbl\_extend\_rows\_range

Context Sensitive • Table

adds rows to the currently selected rows in a table.

**tbl\_extend\_rows\_range** (*table*, *from\_row*, *to\_row*);

**table** The logical name of the table.

*from row* The *from row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight 2".

***to\_row***

The *to\_row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

#### Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC and Visual Cafe.

---

## tbl\_get\_cell\_data

Context Sensitive • Table

retrieves the contents of the specified cell from a table.

**tbl\_get\_cell\_data ( *table*, *row*, *column*, *out\_text* );**

*table*

The logical name of the table.

*row*

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

For WinRunner with PowerBuilder, Java, or WebTest support, the *row* can also be in the following format:

**By content:** <Column\_name>=<column\_content1  
[column\_contentn....]>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row.

*column*

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number". When the column name is specified, WinRunner takes the name from the database itself, and not from the application.

*out\_text*

For WinRunner with Oracle, Java, or WebTest support, *out\_text* is the output variable that stores the string found in the specified cell.

For WinRunner with PowerBuilder support, *out\_text* is the output variable that stores the string found in the

specified cell; the actual string retrieved depends on the style of the cell, as follows:

*DropDown*: The name of the item selected.

*Radio Button*: The label of the selected radio button in the cell. (PowerBuilder only)

*Edit*: The contents of the cell.

*EditMask*: The contents of the cell.

*Checkbox*: Either "OFF" or "ON".

---

**Note for PowerBuilder, Java, and WebTest support users:** When *row* is specified by content, *column* must also be specified by content.

---

---

**Note:** When *row\_location* and *column\_location* are both zero, the **tbl\_get\_cell\_data** function returns the content of all the cells in the table.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner the Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, EWT (Oracle), and KLG.

This function is supported for WebTest and for WinRunner with Oracle, PowerBuilder, or Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	<b>MSW_class</b>
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl\_get\_cols\_count

Context Sensitive • Table

retrieves the number of columns in a table.

```
tbl_get_cols_count ( table, out_cols_count );
```

**table** The logical name of the table.

***out\_cols\_count*** The output variable that stores the total number of columns in the table.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, EWT (Oracle), and KLG.

This function is supported for WebTest and for WinRunner with Oracle, PowerBuilder, or Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl\_get\_column\_name

Context Sensitive • Table

retrieves the column header name of the specified column in a table.

**tbl\_get\_column\_name** (*table*, *col\_index*, *out\_col\_name*);

*table* The logical name of the table.

*col\_index* The numeric index of the column within the table, specified by an integer.

***out\_col\_name*** The parameter into which the retrieved name is stored.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, and KLG.

This function is supported for WebTest and for WinRunner with Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

---

**tbl\_get\_column\_names**

Context Sensitive • Table

retrieves the names and number of columns in a table.

**tbl\_get\_column\_names ( *table*, *out\_col\_names*, *out\_cols\_count* );**

*table*

The name of the table.

*out\_col\_names*

The output variable that stores the names of the columns in the table.

*out\_cols\_count*

The output variable that stores the total number of columns in the table.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

#### Availability

This function is supported only for WinRunner with PowerBuilder support. The corresponding function for WinRunner without PowerBuilder support is **tbl\_get\_column\_name**.

This function is not supported for WebTest.

## tbl\_get\_rows\_count

Context Sensitive • Table

retrieves the number of rows in the specified table.

**tbl\_get\_rows\_count** (*table*, *out\_rows\_count*);

**table** The logical name of the table.

***out\_rows\_count*** The output variable that stores the total number of rows in the table.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, EWT (Oracle), and KLG.

This function is supported for WebTest and for WinRunner with Oracle, PowerBuilder or Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

---

**tbl\_get\_selected\_cell**

Context Sensitive • Table

returns the cell currently in focus in a table.

**tbl\_get\_selected\_cell ( *table*, *out\_row*, *out\_column* );**

*table*

The logical name of the table.

*out\_row*

**By location:** # <row\_location>

The location of the row within the table, specified by a string preceded by the character #, such as "#2".

For WinRunner with PowerBuilder support, the *out\_row* can also be in the following format:

**By content:** <Column\_name>=<column\_content1  
[column\_contentn....]>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row.

*out\_column*

The output variable that stores the column name of the cell.

---

**Note for PowerBuilder users:** When *out\_row* is specified **by content**, *out\_column* must also be specified **by content**.

---

---

**Note:** The column name is taken from the database itself and not from the application.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, EWT (Oracle), and KLG.

This function is supported for WebTest and for WinRunner with PowerBuilder, Oracle or Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

---

**tbl\_get\_selected\_row**

Context Sensitive • Table

returns the row currently selected in a table.

**tbl\_get\_selected\_row ( *table*, *row* );**

*table*

The logical name of the table.

*row*

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

For WinRunner with PowerBuilder support, the *row* can also be in the following format:

**By content:** <Column\_name>=<column\_content1  
[column\_contentn....]>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row.

For WinRunner with PowerBuilder support, *row* specifies the selected row following the row whose index is specified in the function.

#### Return Values

This function returns one of a list of return values. For more information, see "General Return Values," on page 98, and "Return Values for PowerBuilder and Table Functions," on page 103.

#### Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, and KLG.

This function is supported for WinRunner with PowerBuilder, Oracle or Siebel support.

This function is not supported for WebTest.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Sheridan Data Grid Control	SSDataWidgets.SSDBG.ctrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl select cells range

Context Sensitive • Table

clicks the specified range of cells in a table.

```
tbl_select_cells_range ( table, start_row, start_col, end_row, end_col);
```

**table** The logical name of the table.

The *start row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight 2".

*start col*      The *start column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight Number".

The *end\_row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2"

*end\_col*

The *end\_column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java support. It is supported for the following Java toolkit packages: JFC and KLG

## tbl\_select\_col\_header

Context Sensitive • Table

**selects the specified column header of a table.**

**tbl\_select\_col\_header** ( *table*, *column* );

**table** The logical name of the table.

*column* The *column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character#, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner with Siebel or Java add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, and KLG.

This function is not supported for WebTest.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl\_select\_cols\_range

Context Sensitive • Table

clicks the specified range of columns in a table.

**tbl\_select\_cols\_range** ( *table*, *from\_column*, *to\_column* );

**table** The logical name of the table.

*from\_column* The *from\_column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight\_Number".

When a column name is specified, WinRunner takes the name from the database itself, and not from the application.

*to\_column* The *to\_column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight Number".

When a column name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

**This function is available only for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC and KLG.**

## tbl\_select\_rows\_range

Context Sensitive • Table

**selects the specified range of rows in a table.**

```
tbl_select_rows_range ( table, from_row, to_row );
```

table

The logical name of the table.

*from\_row*

The *from\_row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

When a row name is specified, WinRunner takes the name from the database itself, and not from the application.

*to\_row*

The *to\_row* can be either:

**By location:** # <row\_location> The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <row\_name> The row name, such as "Flight\_2".

When a row name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, and KLG.

---

**tbl\_set\_cell\_data**

Context Sensitive • Table

sets the contents of a cell to the specified text in a table.

**tbl\_set\_cell\_data ( *table*, *row*, *column*, *data* );**

*table*

The logical name of the table.

*row*

**By location:** # <row\_location>

The location of the row within the table, specified by a string preceded by the character #, such as "#2".

For WinRunner with PowerBuilder, Java, or WebTest support, the *row* can also be in the following format:

**By content:** <Column\_name>=<column\_content1  
[column\_contentn....]>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row.

*column*

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number".

*data*

For WinRunner with Oracle, Java, or WebTest support, the *data* is a string denoting the contents to be entered into the specified cell.

For WinRunner with PowerBuilder support, *data* is a string denoting the contents to be entered into the specified cell; the nature of the string depends on the style of the cell, as follows:

*DropDown DataWindow:* The name of the item selected.

**Radio Button:** The label of the selected radio button in the cell.

**Edit:** The contents of the cell.

**EditMask:** The contents of the cell.

**Checkbox:** Either "OFF" or "ON".

---

**Note for PowerBuilder users:** When *row* is specified **by content**, *column* must also be specified **by content**.

---

When a column name is specified, WinRunner takes the name from the database itself and not from the application.

For a column with a DropDown DataWindow style, *data* can specify the contents of any of the columns, and not only the one that is displayed in the table. (See the example below.) For a column with a DropDown DataWindow or DropDown list style, the item can be a string denoting the row number of the cell, preceded by the character #.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

#### Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, EWT (Oracle), and KLG.

This function is not supported for WebTest.

This function is supported for WinRunner with PowerBuilder , Oracle, or Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl\_set\_cell\_focus

Context Sensitive • Table

sets the focus to the specified cell in a table.

**tbl\_set\_cell\_focus ( *table*, *row*, *column* );**

**table** The logical name of the table.

*row*                      The column can be either:

**By location:** # <row\_location>

The location of the row within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name>=<column\_content1  
<column\_contentn....>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row. If the values match more than one row WinRunner refers to the first matching row.

*column* The column can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <column\_name> The column name, such as "Flight\_Number".

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is supported only for WinRunner with Siebel support.

`tbl_set_selected_cell`

## Context Sensitive • Table

selects (clicks) the specified cell in a table.

**tbl\_set\_selected\_cell** ( *table*, *row*, *column* );

**table** The logical name of the table.

**row** By location: # <row\_location>

The location of the row within the table, specified by a string preceded by the character #, such as "#2".

For WinRunner with PowerBuilder support, the *row* can also be in the following format:

**By content:** <Column\_name>=<column\_content1 [column\_contentn....]>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row.

### *column*

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number". When a column name is specified, WinRunner takes the name from the database itself and not from the application.

---

**Note for PowerBuilder users:** When *row* is specified **by content**, *column* must also be specified **by content**.

---

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, EWT (Oracle), and KLG.

This function is not supported for WebTest.

This function is supported for WinRunner with PowerBuilder, Oracle, or Siebel support.

This function is supported for the following ActiveX controls:

ActiveX Control	MSW_class
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
Sheridan Data Grid Control	SSDataWidgets.SSDBGridCtrl.1
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tbl\_set\_selected\_col

Context Sensitive • Table

**selects the specified column in a table.**

**tbl\_set\_selected\_col ( *table*, *column* );**

**table** The logical name of the table.

The *column* can be either:

**By location:** # <column\_location> The location of the column within the table, specified by a string preceded by the character #, such as "#2".

**By content:** <Column\_name> The column name, such as "Flight\_Number".

When a column name is specified, WinRunner takes the name from the database itself, and not from the application.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

This function is available only for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC and EWT (Oracle).

---

**tbl\_set\_selected\_row**

Context Sensitive • Table

selects the specified row in a table.

**tbl\_set\_selected\_row ( *table*, *row* );**

*table*

The logical name of a table.

*row*

**By location:** # <row\_location>

The location of the row within the table, specified by a string preceded by the character #, such as "#2".

For WinRunner with PowerBuilder support, the *row* can also be in the following format:

**By content:** <Column\_name>=<column\_content<sub>1</sub>  
[column\_content<sub>n</sub>....]>

The contents of one or more cells in the row, separated by semicolons and preceded by the name of the column in which they appear and an equal sign, such as

"Flight\_Number=306;From=LAX". The contents of all the cells specified must be present in order to specify the row. Choose this format to specify a row by the contents of cells in that row. If the contents of some cells appear in multiple rows, specify multiple cells whose contents will uniquely identify the row.

#### Return Values

This function returns one of a list of return values. For more information, see "General Return Values," on page 98, and "Return Values for PowerBuilder and Table Functions," on page 103.

#### Availability

This function is available for WinRunner with Java Add-in support. It is supported for the following Java toolkit packages: JFC, Visual Cafe, EWT (Oracle), and KLG.

This function is not supported for WebTest.

This function is supported for WinRunner with PowerBuilder, Oracle, or Siebel support.

This function is supported for the following ActiveX controls:

<b>ActiveX Control</b>	<b>MSW_class</b>
Data Bound Grid Control	MSDBGrid.DBGrid
FarPoint Spreadsheet Control	FPSpread.Spread.1
MicroHelp MH3d List Control	MHGLBX.Mh3dListCtrl.1
Microsoft Grid Control	MSGGrid.Grid
True DBGrid Control	TrueDBGrid50.TDBGrid and TrueDBGrid60.TDBGrid

## tddb\_get\_step\_value

Standard • TestDirector

returns the value of a field in the "dessteps" table in a TestDirector project database.

**tddb get step value ( field, step index [, td path ] );**

**field** The logical name of the field.

*step\_index* The index of the step.

*td\_path* The TestDirector test path (optional argument - the default is the current test).

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

The **tddb\_get\_step\_value** function is only available when WinRunner is connected to a TestDirector project database.

## tddb\_get\_test\_value

Standard • TestDirector

returns the value of a field in the "test" table in a TestDirector project database.

**tddb\_get\_test\_value ( *field* [ , *td\_path* ] );**

*field* The logical name of the field.

***td\_path*** The TestDirector test path (optional argument - the default is the current test).

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

The **tddb\_get\_test\_value** function is only available when WinRunner is connected to a TestDirector project database.

## tddb\_get\_testset\_value

Standard • TestDirector

returns the value of a field in the "testcycl" table in a TestDirector project database.

**tddb\_get\_testset\_value** ( *field* [, *td\_path*] [, *test\_set*] );

*field* The logical name of the field.

***td\_path*** The TestDirector test path (optional argument - the default is the current test).

***test\_set*** The name of the test\_set (optional argument - the default is the current TestSet).

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for PowerBuilder and Table Functions,” on page 103.

## Availability

The **tddb\_get\_testset\_value** function is only available when WinRunner is connected to a TestDirector project database.

---

## TE\_add\_screen\_name\_location

Context Sensitive • Terminal Emulator

adds a screen name location.

**TE\_add\_screen\_name\_location ( *x, y, length* );**

*x*                   The x-coordinate of the new area to search.

*y*                   The y-coordinate of the new area to search.

*length*           The number of characters to the right of the Y position that WinRunner will search for a string.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_bms2gui

Context Sensitive • Terminal Emulator

teaches WinRunner the user interface from a BMS file.

**TE\_bms2gui ( *bms\_filename*, *gui\_filename*, LEARN/RELEARN );**

*bms\_filename*      The full path of the BMS file containing the description of the application's user interface.

*gui\_file\_name*      The full path of the GUI map file into which the descriptions are learned. If no file name is given, the default is the temporary GUI map file of the test.

LEARN|RELEARN      Instructs WinRunner how to deal with name/description conflicts in the BMS file.

### Return Values

This function has no return value.

### Availability

This function is available for applications running on 3270 mainframes only.

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_check\_text

Context Sensitive • Terminal Emulator

captures and compares the text in a terminal emulator window.

**TE\_check\_text ( *file\_name* [ , *start\_column*, *start\_row*, *end\_column*, *end\_row* ] );**

*file\_name*      A string expression given by WinRunner that identifies the captured window.

*start\_column/row*      The column/row at which the captured text begins.

*end\_column/row*      The column/row at which the captured text ends.

### Return Values

This function returns 0 if the function succeeds, -1, if it fails, and 1 if a mismatch is found; otherwise, it returns a standard value. For more information, see

“General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_create\_filter

Context Sensitive • Terminal Emulator

creates a filter in the test database.

**TE\_create\_filter** (*filter\_name*, *start\_column*, *start\_row*,  
    *end\_column*, *end\_row*, EXCLUDE|INCLUDE, *screen\_name*);

*filter\_name*                         The filter name.

*start\_column/row*                 The column/row at which the filter starts.

*end\_column/row*                 The column/row at which the filter ends.

EXCLUDE/INCLUDE                 The type of filter.

*screen\_name*                         The name of the screen to which you want to create the filter or ALL\_SCREENS to create the filter for all screens in the application.

## Return Values

This function returns 0 if the function succeeds; -1 in the case of an illegal number of parameters; 2 if the filter already exists; and 5 in case of an IO error. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_define\_sync\_keys

Context Sensitive • Terminal Emulator

sets keys that enable automatic synchronization in **type**, **win\_type** and **obj\_type** commands.

**TE\_define\_sync\_keys ( keys, string, mode [ , x<sub>1</sub>, y<sub>1</sub>, x<sub>2</sub>, y<sub>2</sub> ] );**

<i>keys</i>	The keys that will enable automatic synchronization. Use a comma as the delimiter between keys.
<i>string</i>	The string that WinRunner waits for to appear or disappear on the screen.
<i>mode</i>	The waiting mode:  SYNC_WHILE: WinRunner waits until the string disappears.  SYNC_UNTIL: WinRunner waits until the string appears.  SYNC_DEFAULT: WinRunner waits the default synchronization time used by the <b>TE_wait_sync</b> function.
<i>x<sub>1</sub>, y<sub>1</sub>, x<sub>2</sub>, y<sub>2</sub></i>	Optional parameters that define a rectangle on the screen in which to search for the string. If these parameters are missing, the entire screen is used.

### Return Values

This function always returns 0.

### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_delete\_filter

Context Sensitive • Terminal Emulator

deletes a specified filter from the test database.

**TE\_delete\_filter ( filter\_name );**

<i>filter_name</i>	The filter to be deleted.
--------------------	---------------------------

## Return Values

This function returns 0 if the function succeeds; -1 in the case of an illegal number of parameters; 1 if the filter cannot be found in the database; and 5 in case of an IO error. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_edit\_field

Context Sensitive • Terminal Emulator

inserts text into an unprotected field.

**TE\_edit\_field ( *field\_logical\_name*, *string* [ , *x\_shift* ] );**

***field\_logical\_name***      The logical name of the field into which the string is inserted.

***string***      The text to be inserted in the field.

***x\_shift***      Indicates the offset of the insertion position from the first character in the field, in characters. If no offset is specified, the default is 0.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_edit\_hidden\_field**

Context Sensitive • Terminal Emulator

inserts text into a hidden field.

**TE\_edit\_hidden\_field ( *field\_logical\_name*, *coded\_string* );**

*field\_logical\_name*      The logical name of the field.

*coded\_string*      A pointer to a coded string that WinRunner decodes and inserts into the field.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_edit\_screen**

Context Sensitive • Terminal Emulator

types a string in the specified location in a screen.

**TE\_edit\_screen ( *x*, *y*, *string* );**

*x,y*      The screen coordinates at which the string is inserted.

*string*      The text to be written on the screen.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_find\_text

Context Sensitive • Terminal Emulator

**returns the location of a specified string**

**TE\_find\_text** ( *string*, *out\_x\_location*, *out\_y\_location* [ , *x<sub>1</sub>*, *y<sub>1</sub>*, *x<sub>2</sub>*, *y<sub>2</sub>* ] );

*string* The text that you want to locate.

***out\_x\_location*** The output variable that stores the x coordinate of the test string.

***out\_y\_location*** The output variable that stores the x coordinate of the test string.

$x_1, y_1, x_2, y_2$       Describe a rectangle that define the limits of the search area.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_force\_send\_key**

Context Sensitive • Terminal Emulator

defines a key causing a screen to change.

**TE\_force\_send\_key** (*in\_screen*, *in\_field* [ , *in\_key* ]);

*in\_screen*

The name of the screen containing the field.

*in\_field*

The name of the field.

*in\_key*

The name of the key causing the screen to change (optional). The key name can be a mnemonic (such as @E for Enter) or one of the WinRunner macros. See the **TE\_send\_key** function for details.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

#### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_get\_active\_filter**

Context Sensitive • Terminal Emulator

returns the coordinates of a specified active filter.

**TE\_get\_active\_filter** (*filter\_num* [ , *out\_start\_column*, *out\_start\_row*, *out\_end\_column*,  
*out\_end\_row* ], *screen\_name* );

*filter\_num*

The filter number representing the order in which filters were activated for the test, beginning with 0.

*out\_start\_column*

The output variable that stores the starting column of the filter.

*out\_start\_row*

The output variable that stores the starting row.

*out\_end\_column*

The output variable that stores the end column.

*out\_end\_row*

The output variable that stores the end row.

<i>screen_name</i>	The output variable that stores the name of the screen in which the active filter is located. If the filter appears on all screens in the application, the function returns ALL_SCREENS.
--------------------	--

#### Return Values

This function returns 0 if the filter exists, -1 if there is an illegal number of parameters and 1 if the filter cannot be found in the database. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

#### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_get\_auto\_reset\_filters

Context Sensitive • Terminal Emulator

indicates whether or not filters are automatically deactivated at the end of a test run.

#### TE\_get\_auto\_reset\_filters ()

#### Return Values

This function returns ON to indicate that all filters are automatically deactivated at the end of a test run; OFF indicates that filters are not automatically deactivated. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

#### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_get\_auto\_verify

Context Sensitive • Terminal Emulator

indicates whether automatic text verification is on or off.

**TE\_get\_auto\_verify();**

## Return Values

This function returns ON if automatic text verification is active; OFF indicates that automatic text verification is not active. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_get\_cursor\_position

Context Sensitive • Terminal Emulator

**cursor** returns the position of the cursor.

**TE\_get\_cursor\_position ( *x*, *y* );**

**x,y** The current screen coordinates of the cursor.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_get\_field\_content

Context Sensitive • Terminal Emulator

**returns the contents of a field to a variable.**

**TE\_get\_field\_content ( *field\_name*, *content* );**

*field name*

The logical name of the field.

content

**The output variable that stores the contents of the field as a string.**

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_get\_filter

Context Sensitive • Terminal Emulator

returns the properties of a specified filter.

```
TE_get_filter ( filter_name [ , out_start_column, out_start_row, out_end_column,  
                 out_end_row, out_type, out_active, screen_name ] );
```

<i>filter_name</i>	The name of the filter.
<i>out_start_column</i>	The output variable that stores the starting column of the filter.
<i>out_start_row</i>	The output variable that stores the starting row.
<i>out_end_column</i>	The output variable that stores the end column.
<i>out_end_row</i>	The output variable that stores the end row.
<i>out_type</i>	The output variable that stores the filter type (INCLUDE EXCLUDE).
<i>out_active</i>	The output variable that stores the filter state.
<i>screen_name</i>	The variable that stores the screen name.

### Return Values

This function returns 0 if the function succeeds; -1 if illegal parameters are used; 1 if a filter is not found; 2 if the parameter value is incorrect. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_get\_merge\_rule

Context Sensitive • Terminal Emulator

gets the rule for merging fields in a terminal emulator application.

**TE\_get\_merge\_rule ( *from\_field*, *to\_field*, *rule* );**

*from\_field* The logical name of the first field to be merged.

*to\_field* The logical name of the last field to be merged.

*rule* The merging rule.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_get\_refresh\_time

Context Sensitive • Terminal Emulator

returns the time WinRunner waits for the screen to refresh.

`TE_get_refresh_time();`

## Return Values

The return value of this function is an integer representing the refresh time. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_get\_screen\_name\_location**

Context Sensitive • Terminal Emulator

returns the screen name location.

**TE\_get\_screen\_name\_location ( *index, x, y, length* );*****index***

A number between 0 - 10. 0 indicates that the screen name location was set by the function **TE\_set\_screen\_name\_location**. 1 - 10 indicates that the screen name was added with the function **TE\_add\_screen\_name\_location**.

***x,y***

The screen coordinates where WinRunner locates the logical name of the screen name.

***length***

The number of characters to the right of the y position that WinRunner locates the screen name string. The default length is 30 (maximum).

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_get\_sync\_time**

Context Sensitive • Terminal Emulator

returns the system synchronization time.

**TE\_get\_sync\_time ( );**

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

**Availability**

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_get\_text**

Context Sensitive • Terminal Emulator

reads text from screen and stores it in a string.

**TE\_get\_text ( *x<sub>1</sub>*, *y<sub>1</sub>*, *x<sub>2</sub>*, *y<sub>2</sub>* );**

*x<sub>1</sub>, y<sub>1</sub>, x<sub>2</sub>, y<sub>2</sub>* Describes a rectangle that encloses the text to be read. The pairs of coordinates can designate any two diagonally opposite corners of the rectangle.

**Return Values**

This function returns the text read from the screen. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

**Availability**

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_get\_timeout**

Context Sensitive • Terminal Emulator

returns the current synchronization time.

**TE\_get\_timeout ( );**

**Return Values**

The return value is the current value of the timeout. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

**Availability**

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_merge\_fields

Context Sensitive • Terminal Emulator

sets the rule for merging fields in a terminal emulator application.

**TE\_merge\_fields** (*rule*);

*rule* The merging rule.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_reset\_all\_filters

Context Sensitive • Terminal Emulator

**deactivates all filters in a test.**

**TE\_reset\_all\_filters();**

## Return Values

The return value of this function is always 0.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_reset\_all\_force\_send\_key**

Context Sensitive • Terminal Emulator

deactivates the execution of **TE\_force\_send\_key** functions.

**TE\_reset\_all\_force\_send\_key ()**

Return Values

This function always returns 0.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_reset\_all\_merged\_fields**

Context Sensitive • Terminal Emulator

deactivates the merging of fields in a Terminal Emulator application.

**TE\_reset\_all\_merged\_fields ()**

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_reset\_filter**

Context Sensitive • Terminal Emulator

deactivates a specified filter.

**TE\_reset\_filter ( *filter\_name* );***filter\_name*

Indicates the name of the filter to be deactivated.

**Return Values**

This function returns 0 if the function succeeds; -1 if illegal parameters are used; 1 if a filter is not found; 2 if the parameter value is incorrect. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

**Availability**

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_reset\_screen\_name\_location**

Context Sensitive • Terminal Emulator

Resets the screen name location to 0.

**TE\_reset\_screen\_name\_location ( );****Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

**Availability**

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_send\_key**

Context Sensitive • Terminal Emulator

sends to the mainframe the specified F-key function.

**TE\_send\_key ( key );**

**key**

The F-key that is sent. The keys supported for this function are described in *the TSL Online Reference*.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_set\_auto\_reset\_filters**

Context Sensitive • Terminal Emulator

deactivates the automatic reset of filters when a test run is completed.

**TE\_set\_auto\_reset\_filters ( ON|OFF );**

**ON|OFF**

ON indicates that upon completion of a test run, all filters are deactivated. OFF indicates that filters are not automatically deactivated. The default value is ON.

Return Values

This function returns 0 if it succeeds and -1 if it fails. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_set\_auto\_transaction**

Context Sensitive • Terminal Emulator

defines a recorded **TE\_wait\_sync** statement as a transaction.

**TE\_set\_auto\_transaction ( ON|OFF );**

ON|OFF

ON activates set automatic transaction. OFF (the default) disables set automatic transaction is disabled.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

#### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_set\_auto\_verify**

Context Sensitive • Terminal Emulator

activates/deactivates automatic text verification.

**TE\_set\_auto\_verify ( ON|OFF [ ,  $x_1, y_1, x_2, y_2$  ] [ , FIRST|LAST ] );**

ON|OFF

Activates or deactivates automatic text verification during recording.

$x_1, y_1, x_2, y_2$

Describes a rectangle that encloses the text to be verified. The pairs of coordinates can designate any two diagonally opposite corners of the rectangle.

FIRST|LAST

An optional parameter indicating the partial check coordinates to use: FIRST indicates the first incidence of partial text capture in the script, LAST indicates the partial text immediately before the current statement.

#### Return Values

The return value of this function is always 0.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

TE\_set\_BMS\_name\_tag

Context Sensitive • Terminal Emulator

allows you to change a name tag that appears in your BMS file.

**TE\_set\_BMS\_name\_tag ( *name* );**

The name being set.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is available for applications running on 3270 mainframes only.

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_set\_cursor\_position**

Context Sensitive • Terminal Emulator

defines the position of the cursor at the specified location on the screen of your mainframe application.

**TE\_set\_cursor\_position ( *x, y* );***x,y*

The current screen coordinates of the cursor.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_set\_field**

Context Sensitive • Terminal Emulator

specifies the field that will receive subsequent input.

**TE\_set\_field ( *field\_logical\_name* [ , *x\_offset* ] );***field\_logical\_name*      The name of the field.*x\_offset*      Indicates the offset of the insertion position from the first character in the field, in characters. If no offset is specified, the default is 0. The property byte is -1.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_set\_filter

Context Sensitive • Terminal Emulator

creates and activates a filter.

**TE\_set\_filter ( *filter\_name* [ , *start\_column*, *start\_row*, *end\_column*, *end\_row*,  
EXCLUDE|INCLUDE, *screen\_name* ] );**

<i>filter_name</i>	The name of the filter.
<i>start_column/row</i>	The column/row at which the filter starts.
<i>end_column/row</i>	The column/row at which the filter ends.
EXCLUDE/INCLUDE	The type of filter.
<i>screen_name</i>	The name of the screen in which you want to set the filter or ALL_SCREENS to set the filter in all screens in the application.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_set\_filter\_mode**

Context Sensitive • Terminal Emulator

specifies whether to assign filters to all screens or to the current screen.

**TE\_set\_filter\_mode ( mode );***mode*

The mode:

ALLSCREENS: assigns filters to all screens.

CURRENTSCREEN: assigns filters to the current screen (default).

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

**Availability**

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_set\_record\_method**

Context Sensitive • Terminal Emulator

specifies the recording method for operations on terminal emulator objects.

**TE\_set\_record\_method ( method );***method*

This can be one of two constants: FIELD\_METHOD (or 2), or POSITION\_METHOD (or 1). FIELD\_METHOD, the default, is full Context Sensitive recording. When POSITION\_METHOD (partial Context Sensitive) is specified, keyboard and mouse input only is recorded for operations on objects in mainframe applications.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

For applications running on VT100, only POSITION\_METHOD is available.

### TE\_set\_refresh\_time

Context Sensitive • Terminal Emulator

sets the interval that WinRunner waits for the screen to refresh.

**TE\_set\_refresh\_time ( *time* );**

The interval (in seconds) WinRunner waits for the screen to refresh. The default time is one second.

## Return Values

This function always returns 0.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

**TE\_set\_screen\_name\_location**

Context Sensitive • Terminal Emulator

resets the screen name location to 0 and then instructs WinRunner where to look for the logical name of a screen.

**TE\_set\_screen\_name\_location ( *x, y, length* );**

*x,y*

The screen coordinates where WinRunner begins looking for the logical name of all screens in the test. The default location is 1,1.

*length*

The number of characters to the right of the *y* position that WinRunner will search for a string. The default length is 30 (maximum).

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

#### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_set\_sync\_time**

Context Sensitive • Terminal Emulator

defines the system synchronization time.

**TE\_set\_sync\_time ( *time* );**

*time*

The minimum number of seconds that WinRunner will wait for the host to respond in order to determine that synchronization has been achieved before continuing test execution.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_set\_timeout

Context Sensitive • Terminal Emulator

sets the maximum time WinRunner waits for a response from the server.

**TE\_set\_timeout ( *timeout* );**

*timeout*                    The interval (in seconds) WinRunner waits for a response from the server before continuing test execution. The default timeout is 60 seconds.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

## Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_set\_trailing

Context Sensitive • Terminal Emulator

Determines whether WinRunner types spaces and tabs in fields during test execution.

**TE\_set\_trailing ( mode, field\_length );**

*mode*

One of two modes can be specified. ON or OFF.

*field\_length*

The field length affected by the trailing mode. For example, if the field length is 5, the trailing mode affects all fields containing up to five spaces. Fields above the designated field length are not affected.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_user\_attr\_comment

Context Sensitive • Terminal Emulator

enables a user to add a user-defined comment property to the physical description of fields in the GUI map.

**TE\_user\_attr\_comment ( name );**

*name*

The name of the user-defined comment property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_user\_reset\_all\_attr\_comments** Context Sensitive • Terminal Emulator  
Resets all user-defined comment properties.

**TE\_user\_reset\_all\_attr\_comments ()**

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

#### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

**TE\_wait\_field** Context Sensitive • Terminal Emulator

waits for a specified string in a specified field to appear on screen.

**TE\_wait\_field ( *field\_logical\_name*, *content*, *timeout* );**

*field\_logical\_name* The logical name of the field.

*content* The text string WinRunner waits for.

*timeout* The number of seconds that WinRunner waits for the string to appear before continuing test execution.

#### Return Values

This function returns 0 if the string is found; 1 if the string is not found; -1 if the function fails. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

#### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

## TE\_wait\_string

Context Sensitive • Terminal Emulator

waits for a string to appear on screen.

**TE\_wait\_string ( *string* [ , *start\_column*, *start\_row*, *end\_column*, *end\_row* ] [ , *timeout* ] );**

<i>string</i>	The text WinRunner waits for.
<i>start_column/row</i>	The starting column/row at which the text will be searched for.
<i>end_column/row</i>	The end column/row at which the text will be searched for.
<i>timeout</i>	The number of seconds that the interpreter waits for the string to appear before continuing test execution.

### Return Values

This function returns 0 if the string is found; 1 if the string is not found; -1 if the function fails. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

### Availability

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

---

## TE\_wait\_sync

Context Sensitive • Terminal Emulator

instructs WinRunner to wait for the terminal emulator screen to be redrawn.

**TE\_wait\_sync ( );**

The **TE\_wait\_sync** function instructs WinRunner to wait, during execution, for the screen of the terminal emulator to be redrawn before continuing test execution.

### Return Values

This function returns the actual time that the terminal emulator screen took to redraw. For more information, see “General Return Values,” on page 98, and “Return Values for Terminal Emulator Functions,” on page 104.

**Availability**

This function is supported for WinRunner EURO and WinRunner with Year 2000 Add-in support only.

It is superfluous for the VT100.

**texit**

Standard • Call Statement

stops execution of the current test.

**texit ( [ *expression* ] );**

*expression*

The value that is returned to the call statement that invokes the called test. If no value is specified, then the return value of the call statement is 0.

**Return Values**

The texit statement is a keyword, not a function. It does not have a return value.

**Availability**

This statement is always available.

**time\_str**

Standard • Time-Related

converts the integer returned by the get\_time function to a string.

**time\_str ( [ *expression* ] );**

*expression*

The value of this expression must be expressed in the format generated by **get\_time** (the time expressed in the number of seconds that have elapsed since 00:00 GMT, January 1, 1970). If expression is not included (null), **time\_str** converts the current value returned by **get\_time**.

**Return Values**

This function returns a string in the format "Day Month Date Hour:Min:Sec Year."

**Availability**

This function is always available.

## tl\_step

Standard • Miscellaneous

divides a test script into sections and inserts a status message in the test results for the previous section.

**tl\_step ( *step\_name*, *status*, *description* );**

<i>step_name</i>	the name of the test step.
<i>status</i>	sets whether the step passed or failed. Set to 0 for pass, or any other integer for failure.
<i>description</i>	a short explanation of the step.

The **tl\_step** function divides test scripts into sections and determines whether each section passes or fails. When the test run is completed, you view the test results in the Test Results window. The report displays a result (pass/fail) for each step you defined.

When WinRunner is connected to a TestDirector project, the message is inserted in the TestDirector “step” table as well.

### Return Values

This function returns 0 if the step passes. If the return value is not zero, the step fails.

### Availability

This function is always available.

---

## tl\_step\_once

Standard • Miscellaneous

divides a test script into sections and inserts a status message in the test results for the previous section.

**tl\_step\_once ( *step\_name*, *status*, *description* );**

<i>step_name</i>	the name of the test step.
<i>status</i>	sets whether the step passed or failed. Set to 0 for pass, or any other integer for failure.
<i>description</i>	a short explanation of the step.

The **tl\_step\_once** function divides test scripts into sections and determines whether each section passes or fails. When the test run is completed, you view the test results in the Test Results window. The report displays a result (pass/fail) for each step you defined.

When WinRunner is connected to a TestDirector project, the message is inserted in the TestDirector “step” table as well. Note that the message is inserted in the TestDirector “step” table once per *step\_name*.

#### Return Values

This function returns 0 if the step passes. If the return value is not zero, the step fails.

#### Availability

This function is always available.

---

## tolower

Standard • String

converts all uppercase characters in a string to lowercase.

**tolower ( *string* );**

*string*                           A string expression.

#### Return Values

This function returns a lower case string.

#### Availability

This function is always available.

**toolbar\_button\_press**

Context Sensitive • Toolbar Object

clicks on a toolbar button.

**toolbar\_button\_press ( *toolbar*, *button*, *mouse\_button* );***toolbar*

The logical name of the toolbar.

*button*

The button to press. This can be either the logical name or the numeric index of the button. The logical name reflects the button's attached text (tooltip). The index is specified as a string preceded by the character #. The first button in a toolbar is #0.

*mouse\_button*

The name of the mouse button pressed when pressing the button in the toolbar. The names (Left, Right, Middle) are defined by the XR\_INP\_MKEYS system parameter in the system configuration file. This parameter is optional.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**toolbar\_get\_button**

Context Sensitive • Toolbar Object

returns the name of toolbar button.

**toolbar\_get\_button ( *toolbar*, *button\_num*, *out\_text* );***toolbar*

The logical name of the toolbar.

*button\_num*

The numeric index of the button in the toolbar.

*out\_text*

The output variable that stores the text.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## toolbar\_get\_buttons\_count

Context Sensitive • Toolbar Object

**returns the number of buttons in a toolbar.**

**toolbar\_get\_buttons\_count ( *toolbar*, *out\_num* );**

## toolbar

The logical name of the toolbar.

*out num*

**The output variable that stores the number of buttons on the toolbar.**

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

**toolbar\_get\_button\_info**

Context Sensitive • Toolbar Object

returns the value of a toolbar button property.

**toolbar\_get\_button\_info ( *toolbar*, *button*, *property*, *out\_value* );**

<i>toolbar</i>	The logical name of the toolbar.
<i>button</i>	The logical name or the numeric index of the button. The logical name reflects the button's attached text (tooltip). The index is specified as a string preceded by the character #. The first button in a toolbar is #0.
<i>property</i>	Any of the properties listed in the "Configuring the GUI Map" in the <i>WinRunner User's Guide</i> .
<i>out_value</i>	The output variable that stores the value of the specified property.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**toolbar\_get\_button\_num**

Context Sensitive • Toolbar Object

returns the position of a toolbar button.

**toolbar\_get\_button\_num ( *toolbar*, *button*, *out\_num* );**

*toolbar*

The logical name of the toolbar.

*button*

The logical name of the button. The logical name reflects the button's attached text. The index is specified as a string preceded by the character #. The first button in a toolbar is #0.

*out\_num*

The output variable that stores the numeric position of the button on the toolbar. The first button is automatically number 0.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**toolbar\_get\_buttons\_count**

Context Sensitive • Toolbar Object

returns the number of buttons in a toolbar.

**toolbar\_get\_buttons\_count ( *toolbar*, *out\_num* );**

*toolbar*

The logical name of the toolbar.

*out\_num*

The output variable that stores the number of buttons on the toolbar.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## toolbar\_select\_item

Context Sensitive • Toolbar Object

selects an item from a menu-like toolbar, as in Microsoft Internet Explorer 4.0 or the Start menu in Windows 98.

**toolbar\_select\_item** ( *toolbar*, *toolbar\_item\_chain* [ , *mouse\_button* ] );

*toolbar*                   The logical name of the toolbar containing the first item in **toolbar\_item\_chain**.

*toolbar\_item\_chain*       The chain of toolbar items separated by the TreeView separator (by default, a semi-colon). You can configure the separator in the General Options dialog box. If the item string is not available, then the item index will be recorded instead.

*mouse\_button*           The name of the mouse button pressed when selecting the last item in **toolbar\_item\_path**. The names (Left, Right, Middle) are defined by the XR\_INP\_MKEYS system parameter in the system configuration file. This parameter is optional.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**toupper**

Standard • String

converts all lowercase characters in a string to uppercase.

**toupper ( *string* );**

*string*

A string expression.

Return Values

This function returns an uppercase string.

Availability

This function is always available.

---

**treturn**

Standard • Call Statements

stops a called test and returns control to the calling test.

**treturn [ ( *expression* ) ];**

*expression*

The value that is returned to the call statement invoking the called test. If no value is specified, then the return value of the call statement is 0.

Return Values

The **treturn** statement is a keyword, not a function, and does not have a return value.

Availability

This statement is always available.

**type**

Analog • Input Device

specifies keyboard input.

**type (** *keyboard\_input* **[,** *technical\_id* **]** **);**

*keyboard\_input* A string expression that represents keystrokes.

*technical\_id* Points to timing and synchronization data. This parameter is only present when the **type** statement is generated during recording.

The **type** function depicts the keyboard input sent to the application under test. Keyboard input is evaluated to a string using the following conventions. The *TSL Online Reference* contains the conventions for evaluating keyboard input to a string.

**Return Values**

The return value of the function is always 0.

**Availability**

This function is always available.

---

**unload**

Standard • Compiled Module

removes a compiled module or selected functions from memory.

**unload (** **[** *module* **|** *test* **]** **[,** *function\_name* **]** **);**

*module* / *test* A string expression indicating the name of an existing compiled module or test.

*function\_name* A string expression indicating the name of an existing compiled function.

**Return Values**

This function returns 0 for success, and 1 for failure.

**Availability**

This function is always available.

---

**unload**

Standard • Compiled Module

removes a compiled module or selected functions from memory.

**unload ( [ *module / test* ] [, *function\_name* ] );**

*module / test*      A string expression indicating the name of an existing compiled module or test.

*function\_name*      A string expression indicating the name of an existing compiled function.

The **unload** function can remove an entire module from memory, or a selected function. When only a module or test name is specified, all functions within that module/test are removed.

If no arguments are specified, **unload** removes all compiled modules from memory.

A system module is generally a closed module that is “invisible” to the tester. It is not displayed when it is loaded, cannot be stepped into, and is not stopped by a pause command. A system module is not unloaded when you execute an **unload** statement with no parameters (global **unload**).

A user module is the opposite of a system module in these respects. Generally, a user module is one that is still being developed. In such a module you might want to make changes and compile them incrementally.

---

**Note:** If you make changes to a function in a loaded compiled module, you must unload and reload the compiled module in order for the changes to take effect.

---

#### Return Values

This function returns 0 for success, and 1 for failure.

#### Availability

This function is always available.

## unload\_16\_dll

Standard • Miscellaneous

unloads a 16-bit DLL from memory.

**unload\_16\_dll ( *pathname* );**

***pathname***      The full pathname of the Dynamic Link Library (DLL) to be unloaded.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## unload\_dll

Standard • Miscellaneous

unloads a DLL from memory.

**unload\_dll ( *pathname* );**

***pathname***      The full pathname of the Dynamic Link Library (DLL) to be unloaded.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**unset\_class\_map**

Context Sensitive • GUI Map Configuration

unbinds a custom class from a standard class.

**unset\_class\_map ( *custom\_class* );**

*custom\_class*

The name of the custom class to unbind.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner and GUI Vusers running on PC platforms only.

---

**user\_data\_point**

Standard • Load Testing

records a user-defined data sample.

**int user\_data\_point ( LPCSTR *sample\_name*, double *value* );**

*sample\_name*                   A string indicating the name of the sample type.

*value*                       The value to record.

Return Values

This function returns 0 if it succeeds, and -1 if it fails to write the sampled data.

Availability

This function is available for LoadRunner GUI Vusers only.

**wait**

Standard • Time-Related

pauses test execution.

**wait ( seconds [ , milliseconds ] );**

*seconds*

The length of the pause, in seconds. The valid range of this parameter is from 0 to 32,767 seconds.

*milliseconds*

The number of milliseconds that are added to the *seconds*.

**Return Values**

The return value of the function is always 0.

**Availability**

This function is always available.

---

## wait\_window

Analog • Synchronization Functions

waits for a window bitmap to appear.

---

**Note:** This function is provided for backward compatibility only. The Context Sensitive versions of this function are **win\_check\_bitmap** and **obj\_check\_bitmap**. You should use these functions instead.

---

**wait\_window ( *time, image, window, width, height, x, y [ , relx<sub>1</sub>, rely<sub>1</sub>, relx<sub>2</sub>, rely<sub>2</sub> ]* );**

<i>time</i>	The <i>time</i> is added to the <i>timeout_msec</i> testing option to give the maximum interval between the previous input even and the screen capture.
<i>image</i>	A string expression identifying the captured bitmap.
<i>window</i>	A string expression indicating the name in the window banner.
<i>width, height</i>	The size of the window, in pixels.
<i>x, y</i>	The position of the upper left corner of the window.
<i>relx<sub>1</sub>, rely<sub>1</sub></i>	For an area bitmap: the coordinates of the upper left corner of the rectangle, relative to the upper left corner of the window, expressed in pixels (the <i>x</i> and <i>y</i> parameters).
<i>relx<sub>2</sub>, rely<sub>2</sub></i>	For an area bitmap: the coordinates of the lower right corner of the rectangle, relative to the lower right corner of the window (the <i>x</i> and <i>y</i> parameters).

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

**web\_browser\_invoke**

Context Sensitive • Web

invokes the browser and opens a specified site.

**web\_browser\_invoke ( *browser, site* );**

*browser*                   The name of browser (Microsoft Internet Explorer or Netscape).

*site*                      The address of the site.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is available for WebTest only.

---

**web\_cursor\_to\_image**

Context Sensitive • Web

moves the cursor to an image on a page.

**web\_cursor\_to\_image ( *image, x, y* );**

*image*                   The logical name of the image.

*x,y*                     The x- and y-coordinates of the mouse pointer when moved to an image, relative to the upper left corner of the image.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is available for WebTest only.

---

**web\_cursor\_to\_label**

Context Sensitive • Web

moves the cursor to a label on a page.

**web\_cursor\_to\_label ( *label*, *x*, *y* );**

*label*

The name of the label.

*x,y*

The x- and y- coordinates of the mouse pointer when moved to a label, relative to the upper left corner of the label.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WebTest only.

---

**web\_cursor\_to\_link**

Context Sensitive • Web

moves the cursor to a link on a page.

**web\_cursor\_to\_link ( *link*, *x*, *y* );**

*link*

The name of the link.

*x,y*

The x- and y- coordinates of the mouse pointer when moved to a link, relative to the upper left corner of the link.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WebTest only.

**web\_cursor\_to\_obj**

Context Sensitive • Web

moves the cursor to an object on a page.

**web\_cursor\_to\_obj ( *object*, *x*, *y* );**

<i>object</i>	The name of the object.
<i>x,y</i>	The x- and y-coordinates of the mouse pointer when moved to an object, relative to the upper left corner of the object.

The **web\_cursor\_to\_obj** function moves the cursor to an object on a frame. The x- and y-coordinates of the mouse pointer when moved to an object are relative to the upper left corner of the object.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

**web\_file\_browse**

Context Sensitive • Web

clicks a browse button.

**web\_file\_browse ( *object* );**

<i>object</i>	A file-type object.
---------------	---------------------

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

**web\_event**

Context Sensitive • Web

runs an event on a specified object.

**web\_event ( *object*, *event\_name* [ , *x*, *y* ] );**

*object*

The logical name of the recorded object.

*event\_name*

The name of an event handler. Use one of the following events:

**blur:** An event occurs when an object loses focus, or when a window or a frame loses focus.

**change:** An event occurs when a value of an object has been modified.

**click:** An event occurs when an object is clicked.

**focus:** An event occurs when an object receives focus by clicking the mouse or by tabbing with the keyboard.

**mousedown:** An event occurs when the mouse button is clicked down.

**mouseout:** An event occurs when the mouse pointer leaves an object from inside that object.

**mouseover:** An event occurs when the mouse pointer moves over an object from outside that object.

**mouseup:** An event occurs when the mouse button is released.

*x,y*

The x- and y-coordinates of the mouse pointer when moved to an object, relative to the upper left corner of the object.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

## **web\_file\_set**

Context Sensitive • Web

sets the text value in a file-type object.

**web\_file\_set ( *object*, *value* );**

*object*                    A file-type object.

*value*                    A text string.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

**web\_find\_text**

Context Sensitive • Web

returns the location of text within a frame.

**web\_find\_text ( *frame*, *text\_to\_find*, *result\_array* [ , *text\_before*, *text\_after*, *index*, *show* ] );**

<i>frame</i>	The name of the frame.
<i>text_to_find</i>	The specified text string to locate.
<i>result_array</i>	The name of the output variable that stores the location of the string as a four-element array.
<i>text_before</i>	Defines the start of the search area for a particular text string.
<i>text_after</i>	Defines the end of the search area for a particular text string.
<i>index</i>	The occurrence number to locate. (The default parameter number is numbered 1.)
<i>show</i>	Indicates whether to highlight the location of the string. If TRUE (default parameter) is specified, the text location is highlighted. If FALSE is specified, the text location is not highlighted.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

**web\_frame\_get\_text**

Context Sensitive • Web

retrieves the text content of a frame.

**web\_frame\_get\_text ( *frame*, *out\_text* [ , *text\_before*, *text\_after*, *index* ] );**

<i>frame</i>	The name of the frame.
<i>out_text</i>	The captured text content.
<i>text_before</i>	Defines the start of the search area for a particular text string.
<i>text_after</i>	Defines the end of the search area for a particular text string.
<i>index</i>	The occurrence number to locate. (The default parameter number is numbered 1).

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is available for WebTest only.

## web\_frame\_get\_text\_count

Context Sensitive • Web

returns the number of occurrences of a regular expression in a frame.

`web_frame_get_text_count ( frame, regex_text_to_find, count );`

*frame* The name of the frame.

*regex\_text\_to\_find* The specified regular expression to locate.

*count* The output variable that stores the count number.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

web\_frame\_text\_exists

Context Sensitive • Web

returns a text value if it is found in a frame.

```
web_frame_text_exists ( frame, text_to_find [ , text_before, text_after ] );
```

**frame** The name of the frame to search.

*text\_to\_find* The string that is searched for.

***text\_before*** Defines the start of the search area for a particular text string.

*text\_after* Defines the end of the search area for a particular text string.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

## web\_get\_run\_event\_mode

Context Sensitive • Web

returns the current run mode.

**web\_get\_run\_event\_mode ( *out\_mode* );**

*out\_mode*

The run mode in use. If the mode is FALSE (the default) the test runs by mouse operations. If TRUE is specified, the test runs by events.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

## web\_get\_timeout

Context Sensitive • Web

returns the maximum time that WinRunner waits for response from the web.

**web\_get\_timeout ( *out\_timeout* );**

*out\_timeout*

The maximum response interval in seconds.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WebTest only.

---

**web\_image\_click**

Context Sensitive • Web

clicks a hypergraphic link or an image.

**web\_image\_click ( *image*, *x*, *y* );**

*image*

The logical name of the image.

*x,y*

The x- and y-coordinates of the mouse pointer when clicked on a hypergraphic link or an image. The coordinates are relative to the upper left corner of the image.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WebTest only.

---

**web\_label\_click**

Context Sensitive • Web

clicks the specified label.

**web\_label\_click ( *label* );**

*label*

The name of the label.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WebTest only.

## web\_link\_click

Context Sensitive • Web

clicks a hypertext link.

**web\_link\_click ( *link* );**

*link* The name of link.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

web link valid

Context Sensitive • Web

checks whether a URL name of a link is valid (not broken).

**web\_link\_valid** (*name, valid*);

*name* The logical name of a link.

**valid** The status of the link may be valid (TRUE) or invalid (FALSE)

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

---

**web\_obj\_click**

Context Sensitive • Web

clicks an object in a frame.

**web\_obj\_click ( *object*, *x*, *y* );***object*

The name of an object.

*x,y*

The x- and y-coordinates of the mouse pointer when clicked on an object. The coordinates are relative to the upper left corner of the object.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

**web\_obj\_get\_child\_item**

Context Sensitive • Web

returns the description of the children in an object.

**web\_obj\_get\_child\_item ( *object*, *table\_row*, *table\_column*, *object\_type*, *index*,  
                          *out\_object* );***object*

The name of object.

*table\_row*

The row number in the table.

*table\_column*

The column number in the table.

*object\_type*

Specifies the object type.

*index*

Unique number assigned to the object.

*out\_object*

The output variable that stores the description.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

---

## web\_obj\_get\_child\_item\_count

Context Sensitive • Web

function returns the count of the children in an object.

**web\_obj\_get\_child\_item\_count** (*object*, *table\_row*, *table\_column*, *object\_type*,  
*object\_count*);

<i>object</i>	The name of object.
<i>table_row</i>	The row number in the table.
<i>table_column</i>	The column number in the table.
<i>object_type</i>	Specifies the object type.
<i>object_count</i>	The output variable that stores the object count number.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

## web\_obj\_get\_info

Context Sensitive • Web

**get** returns the value of an object property.

**web\_obj\_get\_info ( *object*, *property\_name*, *property\_value* );**

*object* The name of the object.

*property\_name* The name of the property (PARENT, SCR, TEXT, TYPE, URL).

***property\_value*** The output variable that stores the value of the property.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

## web\_obj\_get\_text

Context Sensitive • Web

**returns a text string from an object.**

**web\_obj\_get\_text** (*object*, *table\_row*, *table\_column*, *out\_text* [, *text\_before*, *text\_after*, *index*]):

*object* The name of the object.

*table\_row* If the object is a table, it specifies the location of the row within a table. The string is preceded by the # character.

*table\_column* If the object is a table, it specifies the location of the column within a table. The string is preceded by the # character

*out\_text* The output variable that stores the text string.

***text\_before*** Defines the start of the search area for a particular text string.

***text\_after*** Defines the end of the search area for a particular text string.

<b><i>index</i></b>	The occurrence number to locate. (The default parameter number is numbered 1).
---------------------	--

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

---

## **web\_obj\_get\_text\_count**

Context Sensitive • Web

returns the number of occurrences of a regular expression in an object.

**web\_obj\_get\_text\_count ( *object*, *table\_row*, *table\_column*, *regex\_text\_to\_find*, *count* );**

<b><i>object</i></b>	The name of the object.
<b><i>table_row</i></b>	If the object is a table, it specifies the location of the row within a table. The string is preceded by the character #.
<b><i>table_column</i></b>	If the object is a table, it specifies the location of the column within a table. The string is preceded by the character #.
<b><i>regex_text_to_find</i></b>	The specified regular expression to locate.
<b><i>count</i></b>	The output variable that stores the count number.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

---

**web\_obj\_text\_exists**

Context Sensitive • Web

returns a text value if it is found in an object.

**web\_obj\_text\_exists ( *object*, *table\_row*, *table\_column*, *text\_to\_find* [ , *text\_before*,  
  *text\_after* ] );**

*object*

The name of the object to search.

*table\_row*

If the object is a table, it specifies the location of the row within a table. The string is preceded by the character #.

*table\_column*

If the object is a table, it specifies the location of the column within a table. The string is preceded by the character #.

*text\_to\_find*

The string that is searched for.

*text\_before*

Defines the start of the search area for a particular text string.

*text\_after*

Defines the end of the search area for a particular text string.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

## **web\_restore\_event\_default**

Context Sensitive • Web

resets all events to their default settings.

**web\_restore\_event\_default ( );**

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is available for WebTest only.

---

**web\_set\_event**

Context Sensitive • Web

sets the event status.

**web\_set\_event ( *class*, *event\_name*, *event\_type*, *event\_status* );*****class***

The MSW class of the object.

***event\_name***

The name of an event handler. Use one of the following:

**blur:** An event occurs when an object loses focus, or when a window or a frame loses focus.**change:** An event occurs when a value of an object has been modified.**click:** An event occurs when an object is clicked.**focus:** An event occurs when an object receives focus by clicking the mouse or by tabbing with the keyboard.**mousedown:** An event occurs when the mouse button is clicked down.**mouseout:** An event occurs when the mouse pointer leaves an object from inside that object.**mouseover:** An event occurs when the mouse pointer moves over an object from outside that object.**mouseup:** An event occurs when the mouse button is released.***event\_type***

The name of an event type. Use one of the following:

**ANYCASE:** Connects to the event in any case.**BEHAVIOR:** Connects to an event only when the behavior is associated with the object class.**HANDLER:** Connects to an event only when the handler exists in the HTML script.**BEHAVIOR\_OR\_HANDLER:** Connects to an event only when the handler exists in the HTML script, or when the behavior is associated with the object class.

<i>event_status</i>	The name of an event status. Use one of the following: <b>ENABLE:</b> The event is recordable. <b>DISABLE:</b> Disables the recordable event for an object class. <b>DELETE:</b> Deletes and disables an event from the map of recordable events.
---------------------	--

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

**web\_set\_run\_event\_mode**  
sets the event run mode.

Context Sensitive • Web

**web\_set\_run\_event\_mode ( *mode* );**

*mode*                   The event run mode can be set to TRUE or FALSE. If set to FALSE, the test runs by mouse operations. If set to TRUE, the test runs by events.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is available for WebTest only.

This function is available only when using Microsoft Internet Explorer.

---

**web\_set\_timeout**

Context Sensitive • Web

sets the maximum time WinRunner waits for a response from the web.

**web\_set\_timeout ( *timeout* );**

*timeout*                           The maximum interval in seconds.

The **web\_set\_timeout** function sets the maximum time WinRunner waits for a response from the web.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WebTest only.

---

**web\_set\_tooltip\_color**

Context Sensitive • Web

sets the colors of the WebTest ToolTip.

**web\_set\_tooltip\_color ( *fg\_color*, *bg\_color* );**

*fg\_color*                           A hexadecimal number denoting a color value of the foreground color. Default color is set to black.

*bg\_color*                           A hexadecimal number denoting a color value of the background color. Default color is set to aqua.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WebTest only.

## web\_sync

Context Sensitive • Web

waits for the navigation of a frame to be completed.

**web\_sync ( *timeout* );**

*time*

The maximum interval in seconds.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

web\_url\_valid

Context Sensitive • Web

checks whether a URL is valid.

**web\_url\_valid** (*URL*, *valid*);

## URL

**Address of a link.**

*valid*

The status of the link may be valid (TRUE) or invalid (FALSE).

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WebTest only.

---

**win\_activate**

Context Sensitive • Window Object

activates a window.

**win\_activate ( *window* );**

*window*

The logical name of the window.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available in WinRunner only.

---

**win\_check\_bitmap**

Context Sensitive • Window Object

compares a window bitmap to an expected bitmap.

**win\_check\_bitmap ( *window, bitmap, time [ , x, y, width, height ]* );**

*window*

The logical name of the window.

*bitmap*

A string expression that identifies the captured bitmap.

*time*

The interval marking the maximum delay between the previous input event and the capture of the current bitmap, in seconds. This interval is added to the *timeout\_msec* testing option.

*x, y*

For an area bitmap: the coordinates or the upper left corner, relative to the window in which the selected area is located.

*width, height*

For an area bitmap: the size of the selected area, in pixels.

The analog version of **win\_check\_bitmap** is **check\_window**.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

## win\_check\_gui

## Context Sensitive • Window Object

compares current GUI data to expected GUI data for a window.

```
win_check_gui ( window, checklist, expected_results_file, time );
```

*window* The logical name of the window.

***checklist*** The name of the checklist specifying the checks to perform.

*expected\_results\_file* The name of the file storing the expected GUI data.

*time* The *time* is added to the *timeout\_msec* testing option to give the maximum interval between the previous input even and the screen capture.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**win\_check\_info**

Context Sensitive • Window Object

checks the requested window property.

**win\_check\_info** (*window*, *property*, *property\_value*);

*window*                   The logical name of the window.

*property*               The property to check.

*property\_value*       The expected value of the property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**win\_click\_help**

Context Sensitive • Window Object

clicks the help button in a window title bar.

**win\_click\_help** (*window*);

*window*                   The logical name of the window.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## win\_click\_on\_text

Context Sensitive • Window Object

searches for text in a window.

**win\_click\_on\_text** (*window*, *string* [ ,*search\_area* ] [ , *string\_def* [ , *mouse\_button* ] ]);

*window*

The logical name of the window.

*string*

The text to locate. To specify a literal, case sensitive string, enclose the string in quotation marks. Alternatively, you can specify the name of a string variable. The value of the string variable can include a regular expression (the regular expression need not begin with an exclamation mark).

*search\_area*

The region of the object to search, relative to the window. This area is defined as a pair of coordinates, with *x1,y1,x2,y2* specifying any two diagonally opposite corners of the rectangular search region. If this parameter is not defined, then the entire window specified is considered the search area.

*string\_def*

Defines how the text search is performed. If no *string\_def* is specified, (0 or FALSE, the default parameter), the interpreter searches for a complete word only. If 1, or TRUE, is specified, the search is not restricted to a single, complete word.

*mouse\_button*

Specifies the mouse button that clicks on the text string. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the left button.

The analog version of this function is **click\_on\_text**.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**win\_close**

Context Sensitive • Window Object

closes a window.

**win\_close ( *window* );**

*window*

The logical name of the window.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**win\_drag**

Context Sensitive • Window Object

drags an object from a source window.

**win\_drag ( *source\_window*, *x*, *y* [ , *mouse\_button* ] );**

*source\_window*

The logical name of the window.

*x,y*

The coordinates of the mouse pointer when clicked on the source window, relative to the upper left corner of the client area of the source window expressed in pixels.

*mouse\_button*

A constant that specifies the mouse button to hold down while dragging. The value can be LEFT, MIDDLE, or RIGHT. If no button is specified, the default is the button that performs the select function.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

## win\_drop

Context Sensitive • Window Object

drops an object onto a target window.

**win\_drop ( *target\_window*, *x*, *y* );**

*target\_window*

The logical name of the window.

*x,y*

The coordinates of the mouse pointer when released over the target window, relative to the upper left corner of the client area of the target window, expressed in pixels.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

## win\_exists

Context Sensitive • Window Object

checks whether a window is displayed on the screen.

**win\_exists ( *window* [ , *time* ] );**

*window*

The logical name of the window.

*time*

The time is added to the *timeout\_msec* testing option to give the maximum interval, in seconds, before the next statement is executed.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**win\_find\_text**

Context Sensitive • Window Object

returns the location of a string within a window.

**win\_find\_text ( *window*, *string*, *result\_array* [ , *search\_area*] [ , *string\_def* ] );**

***window***

The logical name of the window to search.

***string***

The text to locate. To specify a literal, case sensitive string, enclose the string in quotation marks. Alternatively, you can specify the name of a string variable. The value of the string variable can include a regular expression. The regular expression should not include an exclamation mark (!), however, which is treated as a literal character.

***result\_array***

The name of the output variable that stores the location of the string as a four-element array.

***search\_area***

The region of the object to search, relative to the window. This area is defined as a pair of coordinates, with *x1,y1,x2,y2* specifying any two diagonally opposite corners of the rectangular search region. If this parameter is not defined, then the entire *window* is considered the search area.

***string\_def***

Defines how the text search is performed. If no *string\_def* is specified, (0 or FALSE, the default parameter), the interpreter searches for a complete word only. If 1, or TRUE, is specified, the search is not restricted to a single, complete word.

The Analog version of this function is **find\_text**.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

## win\_get\_desc

Context Sensitive • Window Object

returns the physical description of a window.

**win\_get\_desc** (*window, obligatory, optional, selector, out\_desc*);

<i>window</i>	The logical name of the window.
<i>obligatory</i>	The list of obligatory properties (separated by spaces).
<i>optional</i>	The list of optional properties (separated by spaces).
<i>selector</i>	The type of selector used for this object class (location or index).
<i>out_desc</i>	The output variable that stores the description of the window.

### Return Values

This function returns the value 0 if it succeeds and -1 if it fails. If obligatory, optional, and selector are null strings, **win\_get\_desc** returns the current learning configuration for the object

### Availability

This function is always available.

---

**win\_get\_info**

Context Sensitive • Window Object

returns the value of a window property.

**win\_get\_info ( *window*, *property*, *out\_value* );**

*window*

The logical name of the window.

*property*

Any of the properties listed in the User's Guide.

*out\_value*

The variable that stores the value of the specified property.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**win\_get\_text**

Context Sensitive • Window Object

reads text from the indicated area of a window.

**win\_get\_text ( *window*, *out\_text* [ , *x<sub>1</sub>*, *y<sub>1</sub>*, *x<sub>2</sub>*, *y<sub>2</sub>* ] );**

*window*

The window from which text is read.

*out\_text*

The output variable that holds the captured text.

*x<sub>1</sub>,y<sub>1</sub>,x<sub>2</sub>,y<sub>2</sub>*

An optional parameter that defines the location from which to read text relative to the specified window in pixels. The coordinate pairs can designate any two diagonally opposite corners of a rectangle. The interpreter searches for the text in the area defined by the rectangle.

The Analog version of this function is **get\_text**.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## win\_highlight

Context Sensitive • Window Object

highlights the specified window.

**win\_highlight ( *window* [ , *flashes* ] );**

*window*                   The logical name of the window.

*flashes*               The number of times the window flashes on screen.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## win\_max

Context Sensitive • Window Object

maximizes a window to fill the entire screen.

**win\_max ( *window* );**

*window*                   The logical name of the window.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is available for WinRunner and LoadRunner GUI Vusers running on PC platforms only.

---

**win\_min**

Context Sensitive • Window Object

minimizes a window to an icon.

**win\_min ( *window* );**

*window*

the logical name of the window.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is available for WinRunner and LoadRunner GUI Vusers running on PC platforms only.

---

---

**win\_mouse\_click**

Context Sensitive • Window Object

performs a mouse click within a window.

**win\_mouse\_click ( *window*, *x*, *y* [ , *mouse\_button* ] [ , *modifier* ] );**

*window*

The logical name of the window.

*x*, *y*

The position of the mouse click expressed as *x* and *y* (pixel) coordinates. Coordinates are relative to the upper left corner of the client area of the window, and not to the screen.

*mouse\_button*

A constant specifying the mouse button to click. The value can be LEFT, MIDDLE, or RIGHT. If no *mouse\_button* is specified, the default is the button performing the select function.

*modifier*

A constant specifying the modifier key used with the mouse button. The value can be CONTROL, SHIFT, or CONTROL\_SHIFT.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

## win\_mouse dbl click

Context Sensitive • Window Object

performs a double-click within a window.

**win\_mouse dbl click** (*window*, *x*, *y* [ , *mouse\_button* ] [ , *modifier* ]);

*window*

The logical name of the window.

*x*, *y*

The position of the double-click expressed as *x* and *y* (pixel) coordinates. Coordinates are relative to the upper left corner of the client area of the window, and not to the screen.

*mouse\_button*

A constant specifying the mouse button to click. The value can be LEFT, MIDDLE, or RIGHT. If no *mouse\_button* is specified, the default is the button performing the select function.

*modifier*

A constant specifying the modifier key used with the mouse button. The value can be CONTROL, SHIFT, or CONTROL\_SHIFT.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is always available.

---

**win\_mouse\_drag**

Context Sensitive • Window Object

performs a mouse drag within a window.

**win\_mouse\_drag** ( *window, start\_x, start\_y, end\_x, end\_y* [ , *mouse\_button* ]  
[ ,*modifier* ] );

*window*

The logical name of the window.

*start\_x, start\_y*

The x- and y-coordinates of the start point of the mouse drag in pixels. Coordinates are relative to the upper left corner of the client area of the window, and not to the screen.

*end\_x, end\_y*

The x- and y-coordinates of the end point of the mouse drag in pixels. Coordinates are relative to the upper left corner of the client area of the window, and not to the screen.

*mouse\_button*

A constant specifying the mouse button to click (LEFT, MIDDLE, RIGHT). If no *mouse\_button* is specified, the default is the one performing the selection.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**win\_mouse\_move**

Context Sensitive • Window Object

moves the mouse pointer to the designated position within a window.

**win\_mouse\_move ( *window*, *x*, *y* );**

*window*

The logical name of the window.

*x, y*

The position of the mouse pointer, expressed as *x* and *y* (pixel) coordinates. The coordinates are relative to the upper left corner of the client area of the window, and not to the screen.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

**win\_move**

Context Sensitive • Window Object

moves a window to a new absolute location.

**win\_move ( *window*, *x*, *y* );**

*window*

The logical name of the window.

*x, y*

The *x* and *y* coordinates are relative to the upper left corner of the screen.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

---

**win\_move\_locator\_text**

Context Sensitive • Window Object

moves the mouse pointer to a string in a window.

**win\_move\_locator\_text** ( *window*, *string* [ , *search\_area* ] [ ,*string\_def* ] );

*window*

The logical name of the window.

*string*

The text to locate. To specify a literal, case sensitive string, enclose the string in quotation marks. Alternatively, you can specify the name of a string variable. The value of the string variable can include a regular expression (the regular expression need not begin with an exclamation mark).

*search\_area*

The region of the object to search, relative to the window. This area is defined as a pair of coordinates, with *x1,y1,x2,y2* specifying any two diagonally opposite corners of the rectangular search region. If this parameter is not defined, then the entire window specified is considered the search area.

*string\_def*

Defines how the text search is performed. If no *string\_def* is specified, (0 or FALSE, the default parameter), the interpreter searches for a complete word only. If 1, or TRUE, is specified, the search is not restricted to a single, complete word.

The Analog version of this function is **move\_locator\_text**.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

**win\_open**

Context Sensitive • Window Object

opens an application window.

**win\_open ( *window* );**

*window*                           the logical name of the window.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**win\_resize**

Context Sensitive • Window Object

resizes a window.

**win\_resize ( *window*, *width*, *height* );**

*window*                           The logical name of the window.

*width*                           The new width of the window, in pixels.

*height*                           The new height of the window, in pixels.

**Return Values**

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

**Availability**

This function is always available.

---

**win\_restore**

Context Sensitive • Window Object

restores a window to its previous size.

**win\_restore ( *window* );**

*window*

The logical name of the window.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

**win\_type**

Context Sensitive • Window Object

sends keyboard input to a window.

**win\_type ( *window*, *keyboard\_input* );**

*window*

The logical name of the window.

*keyboard\_input*

A string expression that represents keystrokes.

Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

Availability

This function is always available.

---

## win\_wait\_bitmap

Context Sensitive • Window Object

waits for a window bitmap.

---

**Note:** This function is provided for backward compatibility only. You should use the **win\_check\_bitmap** and **obj\_check\_bitmap** functions instead of this function.

---

**win\_wait\_bitmap** ( *window, bitmap, time [ , x, y, width, height ]* );

<i>window</i>	The logical name of the window.
<i>bitmap</i>	A string expression identifying the captured bitmap.
<i>time</i>	The <i>time</i> is added to the <i>timeout_msec</i> testing option to give the maximum interval between the previous input even and the screen capture.
<i>x, y</i>	For an area bitmap: the coordinates of the upper left corner, relative to the window in which the selected region is located in pixels.
<i>width, height</i>	For an area bitmap: the size of the selected region, in pixels.

For an Analog version of the **win\_wait\_bitmap**, see **wait\_window**.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is always available.

---

**win\_wait\_info**

Context Sensitive • Window Object

waits for the value of a window property.

**win\_wait\_info ( *window*, *property*, *value*, *time* );**

<i>window</i>	The logical name of the window.
<i>property</i>	Any of the properties listed in the <i>User's Guide</i> .
<i>value</i>	The property value for which the function waits.
<i>time</i>	The interval, in seconds, before the next statement is executed.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is always available.

## Y2K\_age\_string

Context Sensitive • Year 2000

ages a date string and returns the aged date.

**Y2K\_age\_string ( *date*, *years*, *month*, *days*, *new\_date* );**

<i>date</i>	The date to age.
<i>years</i>	The number of years to age the date.
<i>month</i>	The number of months to age the date.
<i>days</i>	The number of days to age the date.
<i>new_date</i>	The new date after the date string is aged the specified number of years, months, and days.

### Return Values

This function returns 0 if it succeeds; -1 if it fails.

### Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

**Y2K\_align\_day**

Context Sensitive • Year 2000

ages dates to a specified day of the week or type of day.

**Y2K\_align\_day ( align\_mode, day\_in\_week );*****align\_mode***

You can select one of the following modes:

Mode	Description
NO_CHANGE	No change is made to the aged dates.
BUSINESSDAY_BACKWARD	Ages dates to the closest business day before the actual aged date. For example, if the aged date falls on Saturday, WinRunner changes the date so that it falls on Friday.
BUSINESSDAY_FORWARD	Ages dates to the closest business day after the actual aged date. For example, if the aged date falls on a Saturday, WinRunner changes the date so that it falls on a Monday.
DAYOFWEEK_BACKWARD	Ages dates to the closest week day before the actual aged date. For example, if the aged date falls on a Sunday, WinRunner changes the date so that it falls on a Friday.
DAYOFWEEK_FORWARD	Ages dates to the closest week day after the actual aged date. For example, if the aged date falls on a Sunday, WinRunner changes the date so that it falls on a Monday.
SAMEDAY_BACKWARD	Ages dates to the same day of the week, occurring before the actual aged date. For example, if the original date falls on a Thursday, and the aged date falls on a Friday, WinRunner changes the date so that it falls on the Thursday before the Friday.
SAMEDAY_FORWARD	Ages dates to the same day of the week, occurring after the actual aged date. For example, if the original date falls on a Thursday, and the aged date falls on a Friday, WinRunner changes the date so that it falls on the Thursday after the Friday.

<i>day_in_week</i>	A day of the week (Monday, Tuesday, Wednesday, Thursday, Friday, Saturday, or Sunday.) This parameter is only necessary when the DAYSOFWEEK_BACKWARD or DAYSOFWEEK_FORWARD option is specified for <i>align_mode</i> .
--------------------	--

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_calc\_days\_in\_field

Context Sensitive • Year 2000

calculates the number of days between two date fields.

**Y2K\_calc\_days\_in\_field ( *field\_name*<sub>1</sub>, *field\_name*<sub>2</sub> );**

*field\_name*<sub>1</sub>                  The name of the 1st date field.

*field\_name*<sub>2</sub>                  The name of the 2nd date field.

#### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

#### Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_calc\_days\_in\_string

Context Sensitive • Year 2000

calculates the number of days between two numeric strings.

**Y2K\_calc\_days\_in\_string** (*string*<sub>1</sub>, *string*<sub>2</sub>);

*string*<sub>1</sub> The name of the 1st string.

*string*<sub>2</sub> The name of the 2nd string.

## Return Values

This function returns 0 if it succeeds; -1 if it fails.

## Availability

This function is supported for WinRunner 2000 only.

## Y2K\_change\_field\_aging

Context Sensitive • Year 2000

overrides the aging on a specified date object.

**Y2K\_change\_field\_aging** (*field\_name*, *aging\_type*, *days*, *months*, *years*);

*field\_name* The name of the date object.

*aging\_type* The type of aging to apply to the date object:

**INCREMENTAL:** Ages the date a specified number of days, months, and years.

**STATIC:** Ages the date to a specific date, for example, "9, 2, 2005" (February 9, 2005). Note that the year must be in YYYY format.

**DEFAULT\_AGING:** Ages the date using the default aging applied to the entire test, and ignores the days, months, and years parameters.

**days** The number of days to increment the test script.

*months* The number of months to age the test script.

*years* The number of years to age the test script.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_change\_original\_new\_formats

Context Sensitive • Year 2000

overrides the automatic date format for an object.

**Y2K\_change\_original\_new\_formats ( *object\_name*, *original\_format*, *new\_format* [ , TRUE|FALSE ] );**

<i>object_name</i>	The name of the object.
<i>original_format</i>	The original date format used to identify the object.
<i>new_format</i>	The new date format used to identify the object.
TRUE FALSE	TRUE tells WinRunner to use the original date format. FALSE (default) tells WinRunner to use the new date format. This parameter is optional.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_check\_date

Context Sensitive • Year 2000

checks all dates in the current screen of a terminal emulator application.

**Y2K\_check\_date ( *filename* );**

*filename*

The file containing the expected results of the date checkpoint.

Return Values

This function return 0 if it succeeds or 1 if it fails.

Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_disable\_format

Context Sensitive • Year 2000

disables a date format.

**Y2K\_disable\_format ( *format* );**

*format*

The name of a date format or "ALL" to choose all formats.

Return Values

This function returns one of a list of return values. For more information, see "General Return Values," on page 98.

Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_enable\_format

Context Sensitive • Year 2000

enables a date format.

**Y2K\_enable\_format ( *format* );**

## *format*

## The name of a date format.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_field\_to\_Julian

Context Sensitive • Year 2000

translates a date field to a Julian number.

**Y2K\_field\_to\_Julian ( *date\_field* );**

### *date field*

The name of the date field.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_is\_date\_field

Context Sensitive • Year 2000

determines whether a field contains a valid date.

**Y2K\_is\_date\_field** (*field\_name*, *min\_year*, *max\_year*);

*field\_name*

The name of the field containing the date.

*min\_year*

Determines the minimum year allowed.

*max\_year*

Determines the maximum year allowed.

## Return Values

This function returns 1 if the field contains a valid date and 0 if the field does not contain a valid date.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_is\_date\_string

Context Sensitive • Year 2000

determines whether a string contains a valid date.

**Y2K\_is\_date\_string ( *string*, *min\_year*, *max\_year* );**

*string*

The numeric string containing the date.

*min\_year*

Determines the minimum year allowed.

*max\_year*

Determines the maximum year allowed.

## Return Values

This function returns 1 if the string contains a valid date and 0 if the string does not contain a valid date.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_is\_leap\_year

Context Sensitive • Year 2000

determines whether a year is a leap year.

```
Y2K_is_leap_year ( year );
```

*year* A year, for example "1998".

## Return Values

This function returns 1 if a year is a leap year, or 0 if it is not.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_leading\_zero

Context Sensitive • Year 2000

determines whether to add a zero before single-digit numbers when aging and translating dates.

**Y2K\_leading\_zero( mode );**

*mode* One of two modes can be specified: ON or OFF.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_month\_language

Context Sensitive • Year 2000

sets the language used for month names.

**Y2K\_month\_language ( *language* );**

*language*

The language used for month names.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_set\_aging

Context Sensitive • Year 2000

sets aging in the test script.

**Y2K\_set\_aging ( *format*, *type*, *days*, *months*, *years* );**

*format*

The date format to which aging is applied (default is ALL).

*aging\_type*

The type of aging to apply to the test script:

INCREMENTAL: Ages the test script a specified number of days, months, and years.

STATIC: Ages the test script to a specific date, for example, "9, 2, 2005" (February 9, 2005).

DEFAULT\_AGING: Ages the test script using the default aging applied to the entire test, and ignores the days, months, and years parameters.

*days*

The number of days to increment the test script.

*months*

The number of months to age the test script.

*years*

The number of years to age the test script.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_set\_attr

Context Sensitive • Year 2000

sets the record configuration mode for a field.

**Y2K\_set\_attr ( *index* );**

***index***                   The record configuration mode (INDEX or ATTACHED TEXT).

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_set\_auto\_date\_verify

Context Sensitive • Year 2000

automatically generates a date checkpoint for the current screen in a terminal emulator application.

**Y2K\_set\_auto\_date\_verify ( ON|OFF );**

ON|OFF

If ON, WinRunner automatically generates a date checkpoint for the current screen.

The **Y2K\_set\_auto\_date\_verify** function automatically captures all date information in a screen of a terminal emulator window and inserts a date checkpoint in the test script.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_set\_capture\_mode

Context Sensitive • Year 2000

determines how WinRunner 2000 captures dates in terminal emulator applications.

**Y2K\_set\_capture\_mode ( *mode* );**

*mode*

The date capture mode. Use one of the following modes:

**FIELD\_METHOD:** Captures dates in the context of the screens and fields in your terminal emulator application (Context Sensitive). This is the default mode.

**POSITION\_METHOD:** Identifies and captures dates according to the unformulated view of the screen.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_set\_replay\_mode

Context Sensitive • Year 2000

sets the Year 2000 run mode in the test script.

**Y2K\_set\_replay\_mode ( *mode* );**

<i>mode</i>	The Year 2000 run mode. Use one of the following modes:
	NO_CHANGE: No change is made to objects containing dates during the test run.
	AGE: Performs aging during the test run.
	TRANSLATE: Translates dates to the new date format.
	TRANSLATE_AND_AGE: Translates date formats and performs aging.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_set\_system\_date

Context Sensitive • Year 2000

**sets the system date and time.**

**Y2K\_set\_system\_date ( year, month, day [ , hour, minute, second ] );**

*year* The year, for example, "2005".

*month* The month, for example, "8" (August).

**day** The day, for example, "15".

*hour* The hour, for example, "2". (optional)

*minute* The minute, for example, "15". (optional)

*second* The second, for example, "30". (optional)

## Return Values

This function always returns 0.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_set\_year\_limits

Context Sensitive • Year 2000

sets the minimum and maximum years valid for date verification and aging.

```
Y2K_set_year_limits ( min_year, max_year );
```

***min\_year*** The minimum year to be used during date verification and aging.

***max\_year*** The maximum year to be used during date verification and aging.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

## Y2K\_set\_year\_threshold

Context Sensitive • Year 2000

sets the year threshold.

**Y2K\_set\_year\_threshold ( *number* );**

*number* the threshold number

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner 2000 only.

## Y2K\_string\_to\_Julian

Context Sensitive • Year 2000

**translate Julian** translates a string to a Julian number.

**Y2K\_string\_to\_Julian ( *string* );**

*string* The numeric date string.

## Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

## Availability

This function is supported for WinRunner with Year 2000 Add-in support only.

---

## Y2K\_type\_mode

Context Sensitive • Year 2000

disables overriding of automatic date recognition for all date objects in a GUI application.

**Y2K\_type\_mode ( mode );**

*mode*

The type mode. Use one of the following modes:

DISABLE\_OVERRIDE: Disables all overrides on date objects.

ENABLE\_OVERRIDE: Enables all overrides on date objects.

### Return Values

This function returns one of a list of return values. For more information, see “General Return Values,” on page 98.

### Availability

This function is supported for WinRunner with Year 2000 Add-in support only.



---

# Index

## Symbols

! operator 14  
!= operator 13  
&& operator 14  
< operator 13  
<= operator 13  
== operator 13  
> operator 13  
>= operator 13  
|| operator 14

## A

Acrobat Reader vi  
ActiveBar functions 44  
ActiveBar\_combo\_select\_item function 106  
ActiveBar\_dump function 107  
ActiveBar\_select\_menu function 108  
ActiveBar\_select\_tool function 109  
ActiveX functions 44  
ActiveX\_activate\_method function 110  
ActiveX\_get\_info function 110  
ActiveX\_set\_info function 111  
add\_cust\_record\_class function 112  
add\_dlpf\_obj function 113  
add\_record\_attr function 114  
add\_record\_message function 114  
ampersand character 13  
Analog functions  
    by category 40–42  
    coordinate conventions 3  
    numbering conventions 3  
    overview 3  
and operator 14  
arithmetic functions 81

arithmetical operators 12  
    applying to string 8  
    assignment 15  
array operator 26  
arrays 22–27  
    declaration 23  
    for loop 26  
    functions 27, 81  
    initializing 24  
    multidimensional 25  
    operator 26  
ascii function 115  
assignment operators 15  
associativity 16  
atan2 function 115  
auto 35  
auto variables 10

B

bitmap checkpoint functions  
    Analog 40  
    Context Sensitive 44  
break statement 21  
built-in functions 29–30  
    return value 29  
    syntax 29  
button object functions 45  
button\_check\_enabled 35  
button\_check\_info function 116  
button\_check\_state function 116  
button\_get\_info function 117  
button\_get\_state function 117  
button\_get\_value 35  
button\_press function 118  
button\_set function 118  
button\_wait\_info function 119

## C

calendar function 45  
 calendar\_activate\_date function 119  
 calendar\_get\_selected function 120  
 calendar\_get\_status function 120  
 calendar\_get\_valid\_range function 121  
 calendar\_select\_date function 122  
 calendar\_select\_range function 122  
 calendar\_select\_time function 123  
 calendar\_set\_status function 124  
 call statement 124  
 call statements 82  
 call\_chain\_get\_attr statement 125  
 call\_chain\_get\_depth statement 126  
 call\_close statement 126  
 case 35  
 char 35  
 check\_file 35  
 check\_wid 35  
 check\_window function 127  
 click function 128  
 click\_on\_text function 129  
 comments 29  
 compare\_text function 130  
 compiled module functions 82  
 concatenation operator 13  
 conditional operator 14  
 const 35  
 constant declarations 11  
 constants 7–11  
 Context Sensitive functions  
     by category 42–77  
     numbering conventions 4  
     object naming conventions 4  
     overview 3  
 continue 35  
 continue statement 22  
 control flow 18–22  
     break statement 21  
     continue statement 22  
     do statement 21  
     for statement 20  
     if-else statement 18  
     loop statement 21  
     switch statement 19  
     while statement 20

coordinate conventions, Analog functions 3  
 cos function 130  
 create\_browse\_file\_dialog function 131  
 create\_custom\_dialog function 132  
 create\_input\_dialog function 133  
 create\_list\_dialog function 133  
 create\_password\_dialog function 134  
 custom record functions 78  
 custom user interface functions 78  
 Customization functions  
     by category 77–79  
     overview 5

## D

Data Junction 46  
 data objects 7  
 database functions 46  
     for working with Data Junction 46  
     return values for 102  
 data-driven test functions 47  
 datawindow\_text\_click function 135  
 datawindow\_text\_dbl\_click function 136  
 db\_check function 136  
 db\_connect function 137  
 db\_disconnect function 138  
 db\_dj\_convert function 138  
 db\_execute\_query function 139  
 db\_get\_field\_value function 140  
 db\_get\_headers function 140  
 db\_get\_last\_error function 141  
 db\_get\_row function 142  
 db\_write\_records function 142  
 dbl\_click function 143  
 ddt\_close function 144  
 ddt\_export function 144  
 ddt\_get\_current\_row function 145  
 ddt\_get\_parameters function 145  
 ddt\_get\_row\_count function 146  
 ddt\_is\_parameter function 146  
 ddt\_next\_row function 147  
 ddt\_open function 147  
 ddt\_report\_row function 148  
 ddt\_save function 148  
 ddt\_set\_row function 149  
 ddt\_set\_val function 150

**ddt\_set\_val\_by\_row** function 151  
**ddt\_show** function 152  
**ddt\_update\_from\_db** function 152  
**ddt\_val** function 153  
**ddt\_val\_by\_row** function 154  
**declare\_rendezvous** function 154  
**declare\_transaction** function 155  
**default** 35  
**define\_object\_exception** function 156  
**define\_popup\_exception** function 157  
**define tsl\_exception** function 158  
**delete** function 27, 158  
**delete\_record\_attr** function 159  
**Delphi** functions 48  
**display\_date\_result** 35  
**display\_euro\_result** 35  
**dlph\_button\_panel\_press** function 162  
**dlph\_edit\_set** function 160  
**dlph\_list\_select\_item** function 160  
**dlph\_obj\_get\_info** function 161  
**dlph\_obj\_set\_info** function 161  
**do statement** 21  
**dos\_system** function 162  
**double** 35

## E

**edit object** functions 49  
**edit\_activate** function 163  
**edit\_check\_content** 35  
**edit\_check\_format** 35  
**edit\_check\_info** function 163  
**edit\_check\_selection** function 164  
**edit\_check\_text** function 164  
**edit\_delete** function 165  
**edit\_delete\_block** function 166  
**edit\_get\_block** function 166  
**edit\_get\_info** function 167  
**edit\_get\_row\_length** function 168  
**edit\_get\_rows\_count** function 168  
**edit\_get\_selection** function 169  
**edit\_get\_selection\_pos** function 170  
**edit\_get\_text** function 170  
**edit\_insert** function 171  
**edit\_insert\_block** function 172  
**edit\_replace** function 172

**edit\_replace\_block** function 173  
**edit\_set** function 173  
**edit\_set\_focus** function 174  
**edit\_set\_insert\_pos** function 174  
**edit\_set\_selection** function 175  
**edit\_type** function 175  
**edit\_wait\_info** function 176  
**else** 35  
**end\_transaction** function 176  
**endif** 35  
**equal to (relational)** operator 13  
**error\_message** function 177  
**EURO** functions 50  
**EURO\_check\_currency** function 177  
**EURO\_compare\_columns** function 178  
**EURO\_compare\_fields** function 178  
**EURO\_compare\_numbers** function 180  
**EURO\_convert\_currency** function 181  
**EURO\_override\_field** function 182  
**EURO\_set\_auto\_currency\_verify** function 183  
**EURO\_set\_capture\_mode** function 184  
**EURO\_set\_conversion\_mode** function 184  
**EURO\_set\_conversion\_rate** function 185  
**EURO\_set\_cross\_rate** function 186  
**EURO\_set\_currency\_threshold** function 187  
**EURO\_set\_decimals\_precision** function 187  
**EURO\_set\_original\_new\_currencies** function 188  
**EURO\_setRegional\_symbols** function 189  
**EURO\_set\_triangulation\_decimals** function 189  
**EURO\_type\_mode** function 190  
**eval** function 190  
**exception handling** functions 83  
**exception\_off** function 191  
**exception\_off\_all** function 191  
**exception\_on** function 192  
**exception\_on\_print** 35  
**exit** 35  
**exp** function 192  
**expressions** 12–17  
**extern** 35  
  declarations 32–34  
  variables 10

F

file\_close function 192  
file\_compare function 193  
file\_getline function 194  
file\_open function 194  
file\_printf function 195  
find\_text\_function 197  
float 35  
for statement 20  
function 35  
Function Generator functions 79  
function types, overview 2

G

general return values 98–102  
generator\_add\_category function 198  
generator\_add\_function function 198  
generator\_add\_function\_to\_category  
    function 199  
generator\_add\_subcategory function 200  
generator\_set\_default\_function function 200  
get\_aut\_var function 201  
get\_class\_map function 201  
get\_host\_name function 202  
get\_lang 35  
get\_master\_host\_name function 202  
get\_obj\_record\_method 35  
get\_record\_attr function 203  
get\_record\_method function 204  
get\_runner\_str 35  
get\_text function 205  
get\_time function 206  
get\_x function 206  
get\_y function 206  
getenv function 207  
getline 35  
getvar function 207  
grab 35  
greater than operator 13  
greater than or equal to operator 13  
gsub 35

GUI checkpoint functions

    Context Sensitive 52  
    Customization 79

GUI map configuration functions 52

GUI map editor functions 52  
GUI\_add function 208  
GUI\_buf\_get\_data 35  
GUI\_buf\_get\_data\_attr 35  
GUI\_buf\_get\_desc function 208  
GUI\_buf\_get\_desc\_attr function 209  
GUI\_buf\_get\_logical\_name function 210  
GUI\_buf\_new function 210  
GUI\_buf\_set\_data\_attr 36  
GUI\_buf\_set\_desc\_attr function 211  
GUI\_close function 211  
GUI\_close\_all function 212  
GUI\_data\_get\_attr 36  
GUI\_data\_set\_attr 36  
GUI\_delete function 212  
GUI\_desc\_compare function 213  
GUI\_desc\_get\_attr function 213  
GUI\_desc\_set\_attr function 214  
GUI\_get\_name function 214  
GUI\_get\_window function 215  
GUI\_list\_buf\_windows function 216  
GUI\_list\_buffers function 216  
GUI\_list\_data\_attrs 36  
GUI\_list\_descAttrs function 217  
GUI\_list\_map\_buffers function 218  
GUI\_list\_win\_objects function 218  
GUI\_load function 219  
GUI\_map\_get\_desc function 220  
GUI\_map\_get\_logical\_name function 220  
GUI\_mark 36  
GUI\_open function 221  
GUI\_point\_to 36  
GUI\_replay\_wizard 36  
GUI\_save function 221  
GUI\_save\_as function 222  
GUI\_set\_window function 222  
GUI\_unload function 223  
GUI\_unload\_all function 223  
GUI\_ver\_add\_check function 224  
GUI\_ver\_add\_check\_to\_class function 224  
GUI\_ver\_add\_class function 225  
GUI\_ver\_set\_default\_checks function 226

I

i/o functions 83  
 icon object functions 54  
 icon\_move function 226  
 icon\_select function 227  
 if 36  
 if/else statement 18  
 in 36  
 index function 227  
 inout 36  
 input device functions 41  
 input/output functions 28  
 input\_to\_description\_int 36  
 int function 228  
 invoke\_application function 228

J

Java function 54  
 java\_activate\_method function 230

L

length function 231  
 less than operator 13  
 less than or equal to operator 13  
 list object functions 55  
 list\_activate\_item function 231  
 list\_check\_info function 232  
 list\_check\_item function 232  
 list\_check\_multi\_selection 36  
 list\_check\_row\_num 36  
 list\_check\_selected function 233  
 list\_check\_selection 36  
 list\_collapse\_item function 233  
 list\_deselect\_item function 234  
 list\_deselect\_range function 234  
 list\_drag\_item function 235  
 list\_drop\_on\_item function 236  
 list\_expand\_item function 236  
 list\_extend\_item function 237  
 list\_extend\_multi\_items function 238  
 list\_extend\_range function 238  
 list\_get\_checked\_items function 239  
 list\_get\_column\_header function 240  
 list\_get\_info function 240

list\_get\_item function 241  
 list\_get\_item\_info function 242  
 list\_get\_item\_num function 242  
 list\_get\_items\_count 36  
 list\_get\_multi\_selected 36  
 list\_get\_selected function 243  
 list\_get\_subitem function 244  
 list\_rename\_item function 244  
 list\_select\_item function 245  
 list\_select\_multi\_items function 246  
 list\_select\_range function 246  
 list\_set\_item\_state function 247  
 list\_wait\_info function 248  
 load function 248  
 load testing functions 84  
 load\_16\_dll function 249  
 load\_dll function 250  
 log function 250  
 logical operators 14  
 long 36  
 loop modification statements 21  
 looping statements 20  
 lov\_get\_item function 251  
 lov\_select\_item function 251  
 lr\_whoami function 252

M

match function 252  
 menu object functions 56  
 menu\_get\_desc function 253  
 menu\_get\_info function 254  
 menu\_get\_item function 254  
 menu\_get\_item\_num function 255  
 menu\_get\_items\_count 36  
 menu\_select\_item function 256  
 menu\_verify 36  
 menu\_wait\_info function 256  
 miscellaneous functions 85  
 move\_locator\_abs function 257  
 move\_locator\_rel function 257  
 move\_locator\_text function 258  
 move\_locator\_track function 258  
 move\_mouse\_abs 36  
 move\_mouse\_rel 36  
 move\_window 36

**mtype** function 259  
multidimensional arrays 25

## N

next 36  
not (unary) operator 14  
not equal to (relational) operator 13  
numbering conventions  
    Analog functions 3  
    Context Sensitive functions 4

## O

**obj\_check\_attr** 36  
**obj\_check\_bitmap** function 260  
**obj\_check\_enabled** 36  
**obj\_check\_focused** 36  
**obj\_check\_gui** function 260  
**obj\_check\_info** function 261  
**obj\_check\_label** 36  
**obj\_check\_pos** 36  
**obj\_check\_size** 36  
**obj\_check\_style** 36  
**obj\_click\_on\_text** function 262  
**obj\_drag** function 263  
**obj\_drop** function 264  
**obj\_exists** function 264  
**obj\_find\_text** function 265  
**obj\_get\_desc** function 266  
**obj\_get\_info** function 266  
**obj\_get\_text** function 267  
**obj\_highlight** function 268  
**obj\_mouse\_click** function 268  
**obj\_mouse\_dbl\_click** function 270  
**obj\_mouse\_drag** function 271  
**obj\_mouse\_move** function 272  
**obj\_move\_locator\_text** function 272  
**obj\_set\_focus** 36  
**obj\_set\_info** function 274  
**obj\_type** function 274  
**obj\_verify** 36  
**obj\_wait\_bitmap** function 275  
**obj\_wait\_info** function 276  
object functions 57

object naming conventions, Context Sensitive functions 4  
online help vi  
online resources vi  
operating system functions 85  
operators 12–17  
    arithmetical 12  
    assignment 15  
    conditional 14  
    precedence and associativity 16  
    relational 13  
    string 13  
or (logical) operator 14  
oracle functions 58  
out 36  
**output\_message** function 276

## P

password functions 86  
**password\_edit\_set** function 277  
**password\_encrypt** function 277  
pause function 278  
pause\_test 36  
PowerBuilder functions 58  
    return values for 103  
precedence 16  
printf 36  
**process\_return\_value** 36  
prvars 36  
public 36  
public variables 10

## Q

**qt\_force\_send\_key** function 278  
**qt\_reset\_all\_force\_send\_key** function 279  
quad\_click 36  
QuickTest 2000 functions 86

## R

rand function 279  
Readme file vi  
relational operators 9, 13  
reload function 280  
rendezvous function 280

report\_event 36  
report\_msg function 281  
report\_param\_msg 36  
reserved words 35–37  
reset\_filter 36  
reset\_internals 36  
return 36  
return statement 31, 282  
return values 97–104  
    for database functions 102  
    for PowerBuilder functions 103  
    for table functions 103  
    for terminal emulator functions 104  
general 98–102

## S

sample tests vii  
save\_report\_info 36  
scroll object functions 59  
scroll\_check\_info function 283  
scroll\_check\_pos function 283  
scroll\_drag function 284  
scroll\_drag\_from\_min function 284  
scroll\_get\_info function 285  
scroll\_get\_max function 285  
scroll\_get\_min function 286  
scroll\_get\_pos function 286  
scroll\_get\_selected function 287  
scroll\_get\_value 36  
scroll\_line function 288  
scroll\_max function 288  
scroll\_min function 289  
scroll\_page function 289  
scroll\_wait\_info function 290  
set\_aut\_var function 290  
set\_class\_map function 291  
set\_filter 36  
set\_obj\_record\_method 36  
set\_record\_attr function 292  
set\_record\_method function 292  
set\_window function 293  
setvar function 294  
short 36  
siebel\_click\_history function 295  
siebel\_connect\_repository function 296

siebel\_get\_active\_applet function 296  
siebel\_get\_active\_buscomp function 297  
siebel\_get\_active\_busobj function 298  
siebel\_get\_active\_control function 298  
siebel\_get\_active\_view function 299  
siebel\_get\_chart\_data function 300  
siebel\_get\_control\_value function 300  
siebel\_goto\_record function 301  
siebel\_navigate\_view function 302  
siebel\_obj\_get\_info function 302  
siebel\_obj\_get\_properties function 304  
siebel\_select\_alpha function 305  
siebel\_set\_active\_applet function 305  
siebel\_set\_active\_control function 306  
signed 36  
sin function 307  
spin object functions 61  
spin\_down function 308  
spin\_get\_info function 308  
spin\_get\_pos function 309  
spin\_get\_range function 309  
spin\_max function 310  
spin\_min function 310  
spin\_next function 310  
spin\_prev function 311  
spin\_set function 312  
spin\_up function 312  
spin\_wait\_info function 313  
split function 27, 313  
sprintf function 314  
sqrt function 314  
rand function 315  
Standard functions  
    by category 80–95  
    overview 5  
start\_transaction function 315  
statements 17  
static 37  
static text object functions 62  
static variables 10  
static\_check\_info function 316  
static\_check\_text function 316  
static\_get\_info function 317  
static\_get\_text function 317  
static\_wait\_info function 318  
statusbar functions 62

statusbar\_get\_field\_num function 318  
statusbar\_get\_info function 319  
statusbar\_get\_text function 320  
statusbar\_wait\_info function 320  
str\_map\_logical\_to\_visual function 321  
string 37  
    functions 87  
    operators 13  
strings 8  
sub 37  
substr function 322  
support information vii  
switch statement 19  
synchronization functions  
    Analog 41  
    Context Sensitive 62  
system function 322

## T

tab object functions 63  
tab\_get\_info function 323  
tab\_get\_item function 323  
tab\_get\_page 37  
tab\_get\_selected function 324  
tab\_get\_selected\_page 37  
tab\_select\_item function 324  
tab\_select\_page 37  
tab\_wait\_info function 325  
table functions  
    Analog 41  
    Context Sensitive 64  
    for WebTest 73  
    return values for 103  
tbl\_activate\_cell function 326  
tbl\_activate\_col function 328  
tbl\_activate\_header function 328  
tbl\_activate\_row function 330  
tbl\_click\_cell function 330  
tbl\_dbl\_click\_cell function 332  
tbl\_deselect\_col function 333  
tbl\_deselect\_cols\_range function 334  
tbl\_deselect\_row function 335  
tbl\_deselect\_rows\_range function 336  
tbl\_drag function 336  
tbl\_extend\_col function 338

tbl\_extend\_cols\_range function 339  
tbl\_extend\_row function 340  
tbl\_extend\_rows\_range function 340  
tbl\_get\_cell\_coords 37  
tbl\_get\_cell\_data function 342  
tbl\_get\_cols\_count function 344  
tbl\_get\_column\_name function 346  
tbl\_get\_column\_names function 347  
tbl\_get\_rows\_count function 348  
tbl\_get\_selected\_cell function 349  
tbl\_get\_selected\_row function 351  
tbl\_select\_cells\_range function 352  
tbl\_select\_col\_header function 354  
tbl\_select\_cols\_range function 355  
tbl\_select\_rows\_range function 356  
tbl\_set\_cell\_data function 357  
tbl\_set\_selected\_cell function 361  
tbl\_set\_selected\_col function 363  
tbl\_set\_selected\_row function 364  
tbl\_synchronize 37  
TDAPI functions  
    defect tracking functions 90  
    design steps functions 89  
    project administration functions 93  
    project connection functions 88  
    test functions 88  
    test plan tree functions 92  
    test run functions 91  
    test set functions 90  
    test step functions 92  
TDAPI functions by category 88–93  
    database administration functions 93  
    database connection functions 88  
    defect tracking functions 90  
    design steps functions 89  
    test functions 88  
    test plan tree functions 92  
    test run functions 91  
    test set functions 90  
    test step functions 92  
tddb\_get\_step\_value function 365  
tddb\_get\_test\_value function 366  
tddb\_get\_testset\_value function 366  
TE\_add\_screen\_name\_location function 367  
TE\_bms2gui function 368  
TE\_check\_text function 368

TE\_create\_filter function 369  
TE\_define\_sync\_keys function 370  
TE\_delete\_filter function 370  
TE\_edit\_field function 371  
TE\_edit\_hidden\_field function 372  
TE\_edit\_screen function 372  
TE\_find\_text function 373  
TE\_force\_send\_key function 374  
TE\_get\_active\_filter function 374  
TE\_get\_auto\_reset\_filters function 375  
TE\_get\_auto\_verify function 376  
TE\_get\_cursor\_position function 376  
TE\_get\_field\_content function 377  
TE\_get\_filter function 378  
TE\_get\_merge\_rule function 379  
TE\_get\_refresh\_time function 379  
TE\_get\_screen\_name\_location function 380  
TE\_get\_sync\_time function 380  
TE\_get\_text function 381  
TE\_get\_timeout function 381  
TE\_merge\_fields function 382  
TE\_reset\_all\_filters function 382  
TE\_reset\_all\_force\_send\_key function 383  
TE\_reset\_all\_merged\_fields function 383  
TE\_reset\_filter function 384  
TE\_reset\_screen\_name\_location function 384  
TE\_send\_key function 385  
TE\_set\_auto\_reset\_filters function 385  
TE\_set\_auto\_transaction function 386  
TE\_set\_auto\_verify function 386  
TE\_set\_BMS\_name\_tag function 387  
TE\_set\_cursor\_position function 388  
TE\_set\_field function 388  
TE\_set\_filter function 389  
TE\_set\_filter\_mode function 390  
TE\_set\_record\_method function 390  
TE\_set\_refresh\_time function 391  
TE\_set\_screen\_name\_location function 392  
TE\_set\_sync\_time function 392  
TE\_set\_timeout function 393  
TE\_set\_trailing function 394  
TE\_user\_attr\_comment function 394  
TE\_user\_reset\_all\_attr\_comments function 395  
TE\_wait\_field function 395  
TE\_wait\_string function 396  
TE\_wait\_sync function 396  
tech 37  
technical support online vii  
terminal emulator functions 66  
    return values for 104  
TestDirector functions 94  
testing option functions 94  
tests, sample vii  
texit statement 397  
text checkpoint functions  
    Analog 42  
    Context Sensitive 70  
time\_str function 397  
time-related functions 95  
tl\_get\_status 37  
tl\_set\_status 37  
tl\_setvar 37  
tl\_step function 398  
tl\_step\_once function 398  
tolower function 399  
toolbar object functions 70  
toolbar\_button\_press function 400  
toolbar\_get\_button function 400  
toolbar\_get\_button\_info function 402  
toolbar\_get\_button\_num function 403  
toolbar\_get\_buttons\_count function 401, 403  
toolbar\_get\_info 37  
toolbar\_select\_item function 404  
toolbar\_wait\_info 37  
toupper function 405  
treturn 37  
treturn statement 405  
trpl\_click 37  
TSL language 7–34  
    introduction 1–5  
TSL Online Reference vii  
tsl\_set\_module\_mark 37  
tsl\_test\_is\_module 37  
type (of constant or variable) 8  
type function 406  
typographical conventions viii

U

ungrab 37  
unload function 406, 407  
unload\_16\_dll function 408  
unload\_dll function 408  
unsigned 37  
user\_data\_point function 409  
user-defined functions 30–32  
    class 30  
    declarations 31  
    parameters 30  
    return statement 31

V

variables 7–11  
    declarations 9–11  
    names 7  
    undeclared 9  
vendor 37  
Visual Basic functions 44  
vuser\_status\_message 37

W

wait function 410  
wait\_stable\_window 37  
wait\_window function 411  
Web functions 71  
    *See also* WebTest functions  
web\_browser\_invoke function 412  
web\_cursor\_to\_image function 412  
web\_cursor\_to\_label function 413  
web\_cursor\_to\_link function 413  
web\_cursor\_to\_obj function 414  
web\_event function 415  
web\_file\_browse function 414  
web\_file\_set function 416  
web\_find\_text function 417  
web\_frame\_get\_text function 418  
web\_frame\_get\_text\_count function 419  
web\_frame\_text\_exists function 419  
web\_get\_run\_event\_mode function 420  
web\_get\_timeout function 420  
web\_image\_click function 421  
web\_label\_click function 421

web\_link\_click function 422  
web\_link\_valid function 422  
web\_obj\_click function 423  
web\_obj\_get\_child\_item function 423  
web\_obj\_get\_child\_item\_count function 424  
web\_obj\_get\_info function 425  
web\_obj\_get\_text function 425  
web\_obj\_get\_text\_count function 426  
web\_obj\_text\_exists function 427  
web\_restore\_event\_default function 428  
web\_set\_event function 429  
web\_set\_run\_event\_mode function 430  
web\_set\_timeout function 431  
web\_set\_tooltip\_color function 431  
web\_sync function 432  
web\_url\_valid function 432  
WebTest functions 71  
    for tables 73  
WebTest User's Guide vi  
What's New in WinRunner help vi  
while statement 20  
win\_activate function 433  
win\_check\_attr 37  
win\_check\_bitmap function 433  
win\_check\_gui function 434  
win\_check\_info function 435  
win\_check\_label 37  
win\_check\_pos 37  
win\_check\_size 37  
win\_click\_help function 435  
win\_click\_on\_text function 436  
win\_close function 437  
win\_drag function 437  
win\_drop function 438  
win\_exists function 438  
win\_find\_text function 439  
win\_get\_desc function 440  
win\_get\_info function 441  
win\_get\_text function 441  
win\_highlight function 442  
win\_max function 442  
win\_min function 443  
win\_mouse\_click function 443  
win\_mouse\_dbl\_click function 444  
win\_mouse\_drag function 445  
win\_mouse\_move function 446

win\_move function 446  
win\_move\_locator\_text function 447  
win\_open function 448  
win\_press\_cancel 37  
win\_press\_ok 37  
win\_press\_return 37  
win\_resize function 448  
win\_restore function 449  
win\_set\_focus 37  
win\_type function 449  
win\_verify 37  
win\_wait\_bitmap function 450  
win\_wait\_info function 451  
window object functions 73  
WinRunner  
    context-sensitive help vi  
    online resources vi  
    sample tests vii  
WinRunner Customization Guide vi  
WinRunner Installation Guide vi  
WinRunner Tutorial vi  
WinRunner User's Guide v, vi

## Y

Y2K\_age\_string function 452  
Y2K\_align\_day function 453  
Y2K\_calc\_days\_in\_field function 454  
Y2K\_calc\_days\_in\_string function 455  
Y2K\_change\_field\_aging function 455  
Y2K\_change\_original\_new\_formats function  
    456  
Y2K\_check\_date function 457  
Y2K\_disable\_format function 457  
Y2K\_enable\_format function 458  
Y2K\_field\_to\_Julian function 458  
Y2K\_is\_date\_field function 459  
Y2K\_is\_date\_string function 459  
Y2K\_is\_leap\_year function 460  
Y2K\_leading\_zero function 460  
Y2K\_month\_language function 461  
Y2K\_set\_agging function 461  
Y2K\_set\_attr function 462  
Y2K\_set\_auto\_date\_verify function 463  
Y2K\_set\_capture\_mode function 463  
Y2K\_set\_replay\_mode function 464

Y2K\_set\_system\_date function 465  
Y2K\_set\_year\_limits function 465  
Y2K\_set\_year\_threshold function 466  
Y2K\_string\_to\_Julian function 466  
Y2K\_type\_mode function 467  
Year 2000 functions 75







MERCURY INTERACTIVE

**Mercury Interactive Corporation**  
1325 Borregas Avenue  
Sunnyvale, CA 94089 USA

**Main Telephone:** (408) 822-5200  
**Sales & Information:** (800) TEST-911  
**Customer Support:** (877) TEST-HLP  
**Fax:** (408) 822-5300

**Home Page:** [www.merc-int.com](http://www.merc-int.com)  
**Customer Support:** [web.merc-int.com](http://web.merc-int.com)

