

# HP SiteScope

For the Windows, Solaris and Linux operating systems

Software Version: 11.21

---

## Failover Guide

Document Release Date: December 2012

Software Release Date: December 2012



# Legal Notices

## Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

## Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

## Copyright Notice

© Copyright 2012 Hewlett-Packard Development Company, L.P.

## Trademark Notices

Adobe® and Acrobat® are trademarks of Adobe Systems Incorporated.

Intel®, Pentium®, and Intel® Xeon® are trademarks of Intel Corporation in the U.S. and other countries.

iPod is a trademark of Apple Computer, Inc.

Java is a registered trademark of Oracle and/or its affiliates.

Microsoft®, Windows®, Windows NT®, and Windows® XP are U.S registered trademarks of Microsoft Corporation.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

## Acknowledgements

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

This product includes software developed by the JDOM Project (<http://www.jdom.org/>).

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

**<http://h20230.www2.hp.com/selfsolve/manuals>**

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

Or click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

**This document was last updated: Saturday, November 17, 2012**

# Support

Visit the HP Software Support Online web site at:

**<http://www.hp.com/go/hpsoftwaresupport>**

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

To find more information about access levels, go to:

**[http://h20230.www2.hp.com/new\\_access\\_levels.jsp](http://h20230.www2.hp.com/new_access_levels.jsp)**

# Contents

Failover Guide .....	1
Contents .....	5
Welcome to SiteScope Failover .....	6
Introduction to SiteScope Failover .....	7
About SiteScope Failover .....	7
The SiteScope Failover Main Operations .....	7
SiteScope Failover Considerations and Limitations .....	9
Before Installing SiteScope Failover .....	11
Requirements for SiteScope Failover .....	11
Additional Information Related to the Installation .....	11
Before You Begin .....	12
Installing SiteScope .....	13
Installing Using the Installation Wizard .....	13
Installing on Solaris or Linux Using the Console Mode .....	18
Additional Installation Actions .....	24
Configuring SiteScope Failover .....	25
How to Configure SiteScope Failover .....	25
Test SiteScope Failover Configuration .....	27
SiteScope Failover and BSM Integration .....	29
Troubleshooting SiteScope Failover .....	30

---

# Welcome to SiteScope Failover

Welcome to the HP SiteScope Failover Guide. This guide provides detailed instructions on how to deploy and use the SiteScope Failover configuration to provide a backup SiteScope server to enable infrastructure monitoring availability after a SiteScope server failure.

## How This Guide Is Organized

This guide contains the following sections:

- **Introduction to SiteScope Failover**

Describes the SiteScope Failover functionality and environment.

- **Before Installing SiteScope Failover**

Describes the installation requirements and additional information to read before installing SiteScope Failover.

- **Installing SiteScope Failover**

Describes how to install the SiteScope Failover server.

- **Configuring SiteScope Failover**

Describes the SiteScope Failover configuration process.

- **Troubleshooting SiteScope Failover**

Describes how to troubleshoot problems with SiteScope operations and mirroring.

# Chapter 1

---

## Introduction to SiteScope Failover

This chapter includes:

- "About SiteScope Failover" below
- "The SiteScope Failover Main Operations" below
- "SiteScope Failover Considerations and Limitations" on page 9

## About SiteScope Failover

HP SiteScope Failover is a special version of SiteScope that includes automated mirroring and failover functionality. It enables you to implement failover capability for infrastructure monitoring performed by a primary SiteScope by provisioning for backups, redundant, and failover mechanisms.

A failover is a backup operation that automatically switches the functions of a primary system to a standby server if the primary system fails or is temporarily taken out of service. Provisioning for a failover is an important fault tolerance function for mission-critical systems that require high availability. Ideally, a failover system automatically and transparently transfers the service provided by the failed system to the backup system. The backup system "mirrors" the services of the primary system. SiteScope Failover is a special SiteScope installation that performs the following:

- Automated, periodic mirroring of monitoring configurations from the primary SiteScope installation to the failover installation.
- Automated monitoring of the availability of the primary SiteScope installation.
- Automated transition to the failover from standby to active if the primary system fails or is temporarily taken out of service.

## The SiteScope Failover Main Operations

This section gives an overview of the SiteScope Failover functionality and concepts. It contains the following:

- "Mirroring Configurations" below
- "Monitoring Primary Availability" on next page
- "Failover Transition" on page 9

## Mirroring Configurations

An important part of failover functionality is mirroring. Mirroring is an operation by which configuration data is replicated from the primary system to the failover system. SiteScope Failover


## Failover Guide

### Chapter 1: Introduction to SiteScope Failover

mirrors monitor configurations so that the failover can provide the same infrastructure monitoring in the event that the primary SiteScope is unavailable.

As a system management tool, SiteScope can have a dynamic monitor configuration state. The SiteScope Failover installation periodically mirrors (copies) configuration data from the primary SiteScope to stay current with any changes to the monitoring configurations.

The following figure shows how new monitor instances added to the primary SiteScope are copied to the SiteScope Failover.




By default, SiteScope Failover is set to query the primary SiteScope every four hours and that is when any new or changed monitor configurations are copied

**Note:** Do not make monitor configuration changes on the failover server. They are not copied back to the primary machine and will therefore be overwritten by the next mirroring operation. Perform all monitor configurations on the primary SiteScope and they will be mirrored to SiteScope Failover.

## Monitoring Primary Availability


While the primary system is operational, failover systems are generally in standby mode. SiteScope Failover monitors the availability of the primary SiteScope by requesting its health status using Web services.





## Failover Transition

When the failover monitor detects that the primary SiteScope is unresponsive, the SiteScope Failover installation activates (enables) the mirrored monitors and begins running them, as indicated by the following figure.



When SiteScope Failover first receives a health status indicating that the primary SiteScope is unavailable, it waits 3 minutes (by default) before starting the activation process.

When SiteScope Failover becomes active:

- Users should direct web browsers to the address of the failover SiteScope server to log in and view monitoring results.
- There may be a delay in viewing monitor results immediately after failover activation. On the SiteScope Failover machine, monitors that have recently been activated continue to be displayed with a disabled status until the monitors are updated for the first time. The time it takes to update the monitors is generally based on their update frequency.

SiteScope Failover updates monitors in ascending order of update frequency. This means that monitors with the shortest frequency interval are run first after the failover is activated. For example, monitors that are configured to run every minute will be run before monitors scheduled for every ten minutes. Monitors with longer update intervals are initially displayed as disabled until their respective update intervals have past.

- The SiteScope Failover instance continues to watch for reactivation of the primary SiteScope. When it detects that the primary is again operational, SiteScope Failover returns to standby as follows:
  - If SiteScope Failover is configured for BSM integration, SiteScope Failover is restarted; all monitors are set to suspended.
  - If SiteScope Failover is not configured for BSM integration, SiteScope Failover remains started but changes all monitors to suspended.

## SiteScope Failover Considerations and Limitations

This section describes considerations and limitations when using SiteScope Failover.

- Do not make monitor configuration changes on the failover server. They are not copied back to the primary machine and will therefore be overwritten by the next mirroring operation. Perform all monitor configurations on the primary SiteScope and they will be mirrored to SiteScope Failover.
- To provide continuity of configuration and report data across a failover period, the SiteScope Failover can merge configuration data and daily log files from the SiteScope Failover to the primary SiteScope after it has recovered. Existing configuration data on the primary SiteScope is backed up and can be restored.
- If a primary SiteScope server is configured to report to BSM, when a SiteScope Failover instance becomes active, it automatically resumes reporting to BSM. Likewise, when the SiteScope Failover instance goes into standby mode, it stops reporting to BSM.
- The Reset operation in **Preferences > Integration Preferences > BSM Preferences Available Operations** is not supported on the SiteScope Failover server, even when SiteScope Failover is active.
- Monitors configured to target the primary SiteScope server do not mirror to the SiteScope Failover. If you configure a monitor on the primary SiteScope server to target the SiteScope server (either by accepting the default **SiteScope Server** in the **Server** field of the Monitor Settings area, or by typing the IP address of the SiteScope server machine), when the monitor settings are copied to the failover machine, the monitor targets the SiteScope Failover server instead of the primary SiteScope server.
- The table below lists the services, features and monitors that are not supported or tested in the SiteScope Failover environment:

SiteScope Failover Support Limitations	
Not supported by SiteScope Failover	<ul style="list-style-type: none"><li>■ LDAP authentication</li><li>■ Database Driven Configuration (DDC)</li><li>■ Any Application monitors that use what is called the "Dispatcher" interface. This includes the Tuxedo Monitor and Sybase Monitor as of SiteScope version 8.0. The SAP Monitor, Oracle DB Monitor, DB2 Monitor and MAPI Monitor are also in this category for earlier versions of SiteScope.</li><li>■ Some Integration (EMS) monitor types</li></ul>
Not tested in the SiteScope Failover environment	<ul style="list-style-type: none"><li>■ Dispatcher type monitors</li><li>■ Logging SiteScope monitor data to an external database</li><li>■ Use of a proxy</li><li>■ SSL connectivity</li><li>■ SSH for connecting to remote servers</li></ul>

## Chapter 2

---

### Before Installing SiteScope Failover

Installing SiteScope Failover is similar to a regular SiteScope installation. Most of the actions required for the initial SiteScope Failover setup are automated and are performed as part of the installation procedure or when you first access the server. Additional actions may be required depending on the configuration of the primary SiteScope. You can install SiteScope Failover on a Windows or UNIX platform.

This chapter includes:

- "Requirements for SiteScope Failover" below
- "Additional Information Related to the Installation" below
- "Before You Begin" on next page

### Requirements for SiteScope Failover

The following outlines the basic requirements for installing and using SiteScope Failover:

- Primary SiteScope and failover SiteScope both require the same version of SiteScope. If you upgrade the primary SiteScope, you must also upgrade the failover to the same version.
- Primary SiteScope and SiteScope Failover must be installed on separate machines but in the same relative drive and directory path. For example, if the primary SiteScope is installed in `C:\SiteScope` on the primary machine, you should install SiteScope Failover in `C:\SiteScope` on the failover machine. The reason is that your primary SiteScope may have monitors that refer to files within its SiteScope home directory. Installing SiteScope Failover with the same home directory ensures integrity in such file references.
- SiteScope Failover should be installed on a server with similar or identical server resources (processor speed and memory) as the primary SiteScope server. Since the failover is not intended to store monitor data for extended periods of time, the available disk space need not be as large as for the primary SiteScope.
- SiteScope Failover must be installed and run using the same basic permission levels as the primary SiteScope, to ensure that both can access needed file outside of SiteScope.
- The host names of the primary SiteScope and SiteScope Failover server should be resolved and be visible to each other using the common SiteScope port (by default, it is 8080 for a typical installation, and 8443 for SiteScope enabled for SSL).

### Additional Information Related to the Installation

Review the following sections in the "Installing SiteScope" chapter of the HP SiteScope Deployment Guide, as relevant to your target operating system:

- Preparing for Solaris or Linux Installation
- Installing SiteScope on an Oracle Enterprise Linux Environment
- Installing Dependencies Required by the HP Operations Agent
- Preparing for a 64-Bit SiteScope installation
- Troubleshooting and Limitations
- Installing SiteScope Using the Installation Wizard on a Machine Without X11 Server

## Before You Begin

Obtain the following before you start the installation program:

- A SiteScope Failover license. Contact your HP sales representative for assistance.
- The installation path of the primary SiteScope. For example, `C:\SiteScope`

# Chapter 3

---

## Installing SiteScope

You can install SiteScope Failover on Windows, Solaris, or Linux environments using the Installation Wizard. Alternatively, you can install SiteScope on Solaris and Linux platforms using a command line or console mode.

**Note:** The installation instructions that follow are for SiteScope 11.20. SiteScope 11.21 must be installed on top of SiteScope 11.20. For specific instructions for installing SiteScope 11.21, see the "Installation Notes" section of the SiteScope 11.21 Release Notes.

This chapter includes:

- "Installing Using the Installation Wizard " below
- "Installing on Solaris or Linux Using the Console Mode" on page 18
- "Additional Installation Actions" on page 24

## Installing Using the Installation Wizard

Use the following steps to install SiteScope Failover on supported Windows, Solaris, or Linux environments using the installation wizard.

### To install SiteScope Failover:

1. Insert the installation media containing the SiteScope software into the drive on the machine where you want to install SiteScope. (Alternatively, you can download the SiteScope archive from the HP Downloads site.)

Both the standard and failover SiteScopes are installed from the same installation program.

2. Run the SiteScope installation according to your operating system.

### For Windows:

- a. Determine which executable you need to use.

- **HPSiteScope\_11.20\_setup.exe**

This installer automatically determines which SiteScope architecture type to install. On a 32-bit operating system, SiteScope is installed as a 32-bit application. On a 64-bit operating system, SiteScope is installed as a 64-bit application.

- **HPSiteScope32on64\_11.20\_setup.exe**

This installer is for 64-bit Windows operating systems only. SiteScope is installed as 32-bit application. This installation allows monitors that are not supported on the 64-bit Windows operating system to be supported.

- b. In a command-line or Run window, enter the executable name.

For example:

```
<DVD_ROOT>\Windows_Setup\SiteScope\HPSiteScope_11.20_setup.exe
```

or

```
<DVD_ROOT>\Windows_Setup\SiteScope\HPSiteScope32on64_11.20_
setup.exe
```

#### For Linux or Solaris:

- a. Log in to the server as user **root**.
- b. Run the installer by typing: `./HPSiteScope_11.20_setup.bin`.

**Note:** If your server has Microsoft Terminal Server service running, the service must be in **Install Mode** when you install SiteScope. If the service is not in the correct mode, the wizard displays an error message and then exits the installation. Change to install mode using the **change user** command. For details, refer to the Microsoft support site (<http://support.microsoft.com/kb/320185>).

3. The Choose Locale screen is displayed.

Click **OK** to continue with the installation. The Initialization screen is displayed.

4. Read the warnings, if any, that appear in the Application requirement check warnings screen and follow the instructions as described in the screen.

If the installer detects an anti-virus program you can try installing SiteScope without disabling the anti-virus program.

Click **Continue** to continue with the installation.

5. In the Introduction (Install) screen that opens, click **Next**.

6. The License Agreement screen opens.

Read the SiteScope License Agreement.

To install SiteScope, select **I accept the terms of the License Agreement**, and then click **Next**.

7. In the Product Customization screen, select **HP SiteScope Failover**.

Click **Next** to continue.

8. The Select Features screen opens, displaying the HP SiteScope Failover folder.

Click **Next** to continue.

9. If installing on Solaris or Linux platforms, SiteScope is automatically installed in the **/opt/HP/SiteScope/** folder. Skip to step 10 on page 22.

If installing on Windows, the Choose the folders screen opens.

Accept the default directory location. C:\SiteScope, or click **Browse** to select another directory.

**Note:** Choose a directory in the same relative location as the primary SiteScope installation.

The installation path must not contain spaces or non-Latin characters in its name, and must end with a folder named **SiteScope** (the folder name is case sensitive). To restore the default installation path, click **Reset**.

Click **Next** to continue.

**Note:** The SiteScope Failover Manager option is deprecated and is available for backward compatibility only.

If you plan to use SiteScope Failover Manager to provide a backup monitoring availability, you must install SiteScope as a shared resource.

- On Windows, you must install SiteScope using the UNC path of the SiteScope installation folder. For example, \\lab1\users\SiteScopes\Version\_11.20\Build\_2000\SiteScope
- On Linux or Solaris, you must mount the shared resource to the **/opt/HP/SiteScope** folder.

10. The Install Checks screen opens and runs verification checks.

Click **Next** after the free disk space verification completes successfully.

If the free disk space verification is not successful, do the following:

- Free disk space, for example by using the Windows Disk Cleanup utility.
- Repeat steps 8 and 9.

11. In the Pre-Install Summary screen, click **Install**.

12. The Installing screen opens and the installer selects and installs the required SiteScope software components. Each software component and its installation progress is displayed on your screen during installation.

13. After installing the SiteScope components, the Introduction screen of the SiteScope Configuration Wizard opens.

Click **Next**.

14. The Settings screen of the HP SiteScope Configuration Wizard opens.

Enter the required configuration information and click **Next**.

- **Port.** The SiteScope port number. If the port number is already in use (an error message is displayed), enter a different port. If necessary, you can change the port later using the Configuration Tool. The default port is 8080.

**Note:** If you plan to use SiteScope Failover Manager to monitor more than one primary SiteScope from a single failover machine, each primary SiteScope installation must be configured to answer on a unique port number. You can check the ports used by the

SiteScope server using the SiteScope Configuration Tool. For details, see *Running the Configuration Tool on Windows Platforms* in the *Installing SiteScope* chapter of the HP SiteScope Deployment Guide.

- **License file.** Enter the path to the license file, or click **Select** and select the SiteScope license key file. A license must be purchased if intending to use SiteScope beyond the 60-day trial period. It is not necessary to enter license information at this point to use SiteScope during the free evaluation period.

**Note:** License keys from versions of SiteScope earlier than 11.00 are not compatible with this version. License key delivery can be fulfilled automatically through <http://webware.hp.com>.

- **Service name** (not applicable for Solaris or Linux installations). The name of the SiteScope service. If the machine has a previous version of SiteScope installed, enter another name for the SiteScope service. The default service name is HP SiteScope Failover.
- **Use local system account** (not applicable for Solaris or Linux installations). By default, SiteScope is installed to run as a Local System account. This account has extensive privileges on the local computer, and has access to most system objects. When SiteScope is running under a Local Systems account, it attempts to connect to remote servers using the name of the server.
- **Use this account** (not applicable for Solaris or Linux installations). Select to change the user account of the SiteScope service. You can set the SiteScope service to log on as a user with domain administration privileges. This gives SiteScope access privileges to monitor server data within the domain. Enter an account and password (and confirm the password) that can access the remote servers.

**Note:** When SiteScope is installed to run as a custom user account, the account used must have **Log on as a service** rights. To grant a user logon service access:

- i. In Windows Control Panel, double-click **Administrative Tools**.
- ii. Double-click Local Security Policy, and select **Local Policies > User Rights Assignment > Log On as a Service**.
- iii. Click **Add User or Group**, and select the user you want to grant logon service access to, and click **OK**.
- iv. Click **OK** to save the updated policy.

- Start SiteScope service after install (not applicable for Solaris or Linux installations). Automatically starts the SiteScope service after the installation is complete.
15. The Import Configuration screen opens. Choose **Do not import configuration data** and click **Next**.

You cannot import configuration data to SiteScope Failover.

16. The HP Operations Agent screen opens. If the primary SiteScope has monitors that require the



HP Operations agent, then SiteScope Failover also requires HP Operations agent.

Select one of the following options and click **Next**:

- **Do not install HP Operations Agent.** The HP Operations agent is not installed.
- **Install HP Operations Agent.** Select to install the HP Operations agent on the SiteScope server. The agent enables SiteScope to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM.

**Note:**

- If you install SiteScope and the HP Operations agent on a machine that already has the agent installed, SiteScope overrides it and upgrades the current agent.
- The HP Operations agent is supported on SiteScopes running on the environments listed in the HP SiteScope Support Matrices section in the release notes (in SiteScope, select **Help > What's New?**). Consequently, the SiteScope integration with HPOM and BSM is only supported on these environments.
- If you encounter problems installing the HP Operations agent on a 32-bit Windows machine, see Troubleshooting and Limitations in the HP SiteScope Deployment Guide.

17. The Summary screen opens.

Check that the information is correct and click **Next** to continue, or **Back** to return to previous screens to change your selections.

18. The Done screen opens.

To access the SiteScope user interface, click the URL on the screen.

**Note:** If you did not select **Start SiteScope service after install** in the Configuration Settings screen, you need to start the SiteScope service before you can connect to SiteScope. For details, see Getting Started with SiteScope in the HP SiteScope Deployment Guide.

Click **Finish** to close the SiteScope Configuration Wizard.

19. When the installation finishes, the Installation Complete window opens displaying a summary of the installation paths used and the installation status.

If the installation was not successful, review the installation log file for any errors by clicking the **View log file** link in the Installation Complete window to view the log file in a web browser.

For more information about the installed packages, click the **Details** tab.

Click **Done** to close the installation program.

If the installation program determines that the server must be restarted, it prompts you to restart the server.

20. After installing SiteScope on a Linux or Solaris environment, set the permissions for the SiteScope installation directory to have read, write, and execute permissions for the user account that is used to run the SiteScope application. The permissions must also be set for all subdirectories within the SiteScope installation directory.

21. Download and install any SiteScope service packs that have been applied to the primary SiteScope. Service packs are available from the location from which you downloaded SiteScope.
22. Other changes may be required on the SiteScope Failover system. See ["Additional Installation Actions"](#) on page 24.

**Note:** SiteScope Failover requires configuration before it can be made active. For details, see ["How to Configure SiteScope Failover"](#) on page 25.

## Installing on Solaris or Linux Using the Console Mode

You can install SiteScope on Solaris or Linux environments using a command line or console mode. Use this option if you are installing SiteScope on a remote server, or for any other reason that prevents you from using the user interface.

**Note:** Running SiteScope on a Solaris platform is now deprecated. The next release is not planned to include a Solaris Installer.

### To install SiteScope using the console mode:

1. Download the SiteScope setup file to the machine where you want to install SiteScope.  
Alternatively, copy the SiteScope setup file to a disk or network location where it is accessible to the user account that is to be used to install SiteScope.

2. Run the following command:

```
HPSiteScope_11.20_setup.bin -i console
```

The installation script initializes the Java Virtual Machine to begin the installation.

3. The Choose Locale screen is displayed.

```
Preparing to install...
Extracting the JRE from the installer archive...
Unpacking the JRE...
Extracting the installation resources from the installer archive...
Configuring the installer for this system's environment...
Preparing CONSOLE Mode Installation...

=====
Choose Locale...
-----

    1- Deutsch
    ->2- English
    3- Fran?ais

CHOOSE LOCALE BY NUMBER: █
```

Enter the number to select the desired locale, and press `ENTER` to continue.

4. A confirmation screen is displayed.

Press **ENTER** to continue.

5. The Introduction screen is displayed.

```
=====
Introduction
-----

Welcome to the installation for HP SiteScope 11.20
HP Software Installer will guide you through the installation. It is strongly
recommended that you quit all programs before continuing with this
installation.

Application Media Location :
/install/SiteScope/3497/SiteScope/LinuxSetup/packages/
Installation Log File : /tmp/HPOvInstaller/HPSiteScope_11.20/HPSiteScope_11.20_
2012.03.16_18_58_HPOvInstallerLog.txt
Respond to each prompt to proceed to the next step in the installation.
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

PRESS <ENTER> TO CONTINUE: █
```

Press **ENTER** to continue with the installation.

6. The text of the license agreement is displayed. The SiteScope License Agreement requires several pages to display. Read each page as it is presented. Press **ENTER** to continue to the next page. When you have viewed all the pages of the license agreement, you have the option to accept or not accept the license agreement.

```
PRESS <ENTER> TO CONTINUE:

Additional License Authorizations:
Additional license authorizations and restrictions applicable to your software
product are found at: http://www.hp.com/go/SW Licensing

I accept the terms of the License Agreement (Y/N): Y █
```

To install SiteScope, you must accept the terms of the license agreement. The default selection is to not accept the agreement. To accept the license agreement and continue the installation, enter **Y**.

**Note:** To cancel the installation after viewing the SiteScope License Agreement, enter **N**.

7. The SiteScope setup type screen opens.

```
=====

Install Groups are combined sets of features.
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

->1- HP SiteScope: ()
   2- HP SiteScope Failover: ()
   3- HP SiteScope Failover Manager: (Deprecated: Supported for backward compabili
ty only)

Please select one of the following groups ...: █
```

Type 2 and then press `ENTER` to continue.

8. The Select Features screen opens.

```
=====
Select Features
-----

Install Features represent a group of functionality
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

->1- HP SiteScope(Required)

Please Select Features(Use a comma to separate your choices)
: 1
```

Enter the number 1 (required) to install SiteScope.

Press `ENTER` to continue with the installation.

9. The Install Requirements screen opens.

```
=====
Install Requirements Checks
-----

=====
Verifying : Verifying free disk space ... [Completed]
Verifying : Checking for previous installations... [Completed]
=====

Performing checks ...
Details : performing checks ... please wait
Executing initialize action :
Install check requirements successfully completed
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

Please hit Enter to continue: 
```

Press `ENTER` to continue with the installation.

10. The Pre-Installation Summary screen opens.

```
=====
Pre-Installation Summary
-----

Review the following before continuing:

Application Name
  HP SiteScope

Application Shortname
  HPSiteScope

Application Revision
  11.20

Application Directory
  /opt/HP/SiteScope/

Data Directory
  /var/opt/HP/SiteScope/

If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

PRESS <ENTER> TO CONTINUE: █
```

Press ENTER to continue with the installation.

11. The Install Features screen opens and the installation process starts.

```
=====
Install Features
-----

Checking the status of packages

Checking the installation status of selected packages

Processing of 9 packages (Using Native rpm) scheduled.
Completed checking the installation status of all packages.
This process might take a while. Please do not interrupt...
```

When the installation process is complete, the post-installation configuration screen opens.

12. The port prompt is displayed.

```
=====
Installing...
-----

[=====|=====|=====|=====]
[-----|-----|-----|-----]
: =====
-----

Enter the HP SiteScope port number
Port [8080]
PRESS <1> to accept the value [8080], or <2> to change the value
█
```

Enter the number 1 to accept the default port 8080, or enter number 2 to change the port, and then enter a different number in the change port prompt.

**Note:** If you plan to use SiteScope Failover Manager to monitor more than one primary SiteScope from a single failover machine, each primary SiteScope installation must be configured to answer on a unique port number. You can check the ports used by the SiteScope server using the SiteScope Configuration Tool. For details, see Running the Configuration Tool on Solaris or Linux Platforms in the HP SiteScope Deployment Guide.

Press **ENTER** to continue with the installation.

13. The license file path prompt is displayed.

```
Enter the path to license file
File name []
PRESS <1> to accept the value [], or <2> to change the value
█
```

Enter the number 1 to leave the license file path empty (it is not necessary to enter license information at this point to use SiteScope during the free evaluation period), or enter the number 2, and then enter the license file path in the next text box.

**Note:** License keys from previous versions of SiteScope are not compatible with this version. License key delivery can be fulfilled automatically through <http://webware.hp.com>.

Press **ENTER** to continue with the installation.

14. The Import Configuration Data screen opens.

```
Import configuration data from an existing configuration file or SiteScope
installation
->1 - Do not import: ()
   2 - Import from file: ()
   3 - Import from folder: ()
█
```

Enter the number 1.

You cannot import configuration data to SiteScope Failover.

Press **ENTER** to continue with the installation.

15. The Install HP Operations Agent screen opens.

```
Install HP Operations Agent
->1 - Do not install: ()
   2 - Install: ()
█
```

Enter the number 1 if you do not want to install the HP Operations agent.

Enter the number 2 to install the HP Operations agent on the SiteScope server. The agent is required to enable SiteScope to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM.

**Note:**

- If the primary SiteScope has monitors that require the HP Operations agent, then SiteScope Failover also requires the HP Operations agent.
- If you install SiteScope and the HP Operations agent on a machine that already has the agent installed, SiteScope overrides it and upgrades the current agent.
- The HP Operations agent is supported on SiteScopes running on the environments listed in the HP SiteScope Support Matrices section in the release notes (in SiteScope, select **Help > What's New?**). Consequently, the SiteScope integration with HPOM and BSM is supported on these environments only.

Press `ENTER` to continue with the installation.

16. The console displays the installation parameters for confirmation.

```
HP SiteScope will be configured with the following settings
SiteScope user interface port: 8080
License file: None
HP Operations agent will not be installed
Press <1> to continue, or <2> to change values:
```

Enter 1 to proceed with the installation using the parameters indicated or enter 2 to return to make changes, and then press `ENTER`.

The installation process completes. An installation status message is displayed.

```
=====
Installation Complete
-----

Congratulations!
HP SiteScope 11.20
The installation has been successfully completed.
Application Directory: /opt/HP/SiteScope/

View log file./tmp/HPOvInstaller/HPSiteScope_11.20/HPSiteScope_11.20_2012.03.16
_18_58_HPOvInstallerLog.txt
[root@VMAMQA297 /]#
```

17. After installing SiteScope on a Linux or Solaris environment, set the permissions for the SiteScope installation directory to have read, write, and execute permissions for the user account that is used to run the SiteScope application. The permissions must also be set for all subdirectories within the SiteScope installation directory.
18. Download and install any SiteScope service packs that have been applied to the primary SiteScope. Service packs are available from the location from which you downloaded SiteScope.
19. Other changes may be required on the SiteScope Failover system. See ["Additional Installation Actions"](#) on next page.

**Note:** SiteScope Failover requires configuration before it can be made active. See ["How to Configure SiteScope Failover"](#) on page 25.

## Additional Installation Actions

The following are additional actions you may need to perform depending on the configuration of the primary SiteScope. In some cases, you may need to restart the SiteScope Failover instance for the changes to take effect. See the corresponding sections of the SiteScope Help for more information.

- Make changes to the Windows registry on the failover system to match any changes made on the primary SiteScope server.
- ODBC database connections must be set up on the failover machine to match those on the primary SiteScope.
- JDBC drivers must be copied, installed, and set up on the failover machine to match any database monitoring being performed on the primary SiteScope.
- Secure Shell (SSH) servers must be copied, installed, and set up on the failover machine to match any SSH logins and monitoring performed on the primary SiteScope.
- Client libraries, custom scripts, and other API "helper" programs for any application monitors on the primary SiteScope (for example, BroadVision, WebLogic, WebSphere, and so forth) must be installed and set up on the failover machine.
- DHCP library files must be copied from the primary to failover machine in order to enable the DHCP monitor type.



# Chapter 4

---

## Configuring SiteScope Failover

This chapter includes:

- "How to Configure SiteScope Failover" below
- "Test SiteScope Failover Configuration" on page 27
- "SiteScope Failover and BSM Integration" on page 29

## How to Configure SiteScope Failover

This section includes information about configuring SiteScope Failover for its initial use.

### 1. Access the user interface

After you have installed SiteScope Failover, access the user interface to configure SiteScope Failover.

Open a supported Web browser and enter the SiteScope Failover server name with the port number selected during the installation.

For example, `http://localhost:8080/SiteScope`.

The user interface to SiteScope Failover is very similar to the primary user interface. However, title bar indicates SiteScope Failover.

### 2. Verify the License

You activate SiteScope Failover by installing SiteScope Failover and entering a valid SiteScope Failover license key. No special license key is needed for primary SiteScopes in order for them to be mirrored by a failover. SiteScope Failover can mirror and provide failover functionality for any regular SiteScope installation of the same version number.

**Note:** SiteScope Failover uses 6 points to monitor the primary SiteScope.

- a. In the SiteScope Failover user interface, choose **Preferences > General Preferences**.
- b. Expand the **Licenses** group.
- c. Enter a new license file if needed, and click **Save**.

### 3. Configure LW-SSO for the Authentication Strategy

SiteScope Failover and primary SiteScope must be configured with the same LW-SSO passphrase.

- a. Access the primary SiteScope user interface.
- b. Select **Preferences > General Preferences > LW SSO Settings**.
- c. Write down or copy the text from the **Communication security passphrase** field.

- d. Access the SiteScope Failover user interface.
- e. Navigate to **Preferences > General Preferences > LW SSO Settings**.
- f. Paste or enter the communication security passphrase, and then click **Save**.
- g. Restart SiteScope Failover.

### 4. Add Certificates to SSL-Enabled SiteScope Failover

SiteScope Failover must be enabled for SSL if the primary SiteScope is enabled for SSL. Also, if the primary SiteScope is not enabled for SSL then SiteScope Failover cannot be enabled for SSL.


The procedure to enable SiteScope Failover to use SSL is the same as the procedure for standard SiteScope. See Configuring SiteScope to Use SSL in the HP SiteScope Deployment Guide.

If self-signed certificates are used, both primary and SiteScope Failover must have the same certificates imported. For example, assume the following SiteScope server URLs:


- Primary: `https://primary.company.com:8443\`
- Failover: `https://failover.company.com:8443\`

On the primary.company.com server, the certificates for **primary.company.com** and **failover.company.com** should be added. Similarly, on the failover.company.com server, the certificates for **primary.company.com** and **failover.company.com** should also be added:

On primary SiteScope:



On SiteScope Failover:



For information about viewing and importing certificates by using the Certificate Management page, see the SiteScope Help.

### 5. Specify Schedule Settings

The schedule settings can determine how often the mirroring operation occurs and how often the SiteScope Failover checks the primary SiteScope availability.

- a. In the SiteScope Failover user interface, select **Preferences > Schedule Preferences**.
- b. In the Failover Schedule Preferences group, create a new absolute or range schedule.  
For information about creating absolute or range schedules, see the SiteScope Help.

**Note:** You do not need to define schedule settings if you want to use the default schedule for these operations.

## 6. Specify Notification Settings

The notification settings determine the email server configuration, the notifications template, and other related settings.

- a. In the SiteScope Failover user interface, select **Preferences > High Availability Preferences**.
- b. Select **Default Settings > Edit**.  
The Default Failover Settings dialog appears.  
For information about notification settings, see the SiteScope Help.
- c. Specify the settings as required, and then click **OK**.

## 7. Create a New Failover Profile

You define a profile to store the configuration settings that control how SiteScope Failover operates. These behaviors include frequency of checking primary SiteScope availability and mirroring.

- a. In the SiteScope Failover user interface, select **Preferences > High Availability Preferences**.
- b. In the right panel, click **New Profile** to open the New Failover Profile dialog.  
For information about defining a profile by using this dialog, see the SiteScope Help.
- c. Specify the settings as required, and then click **OK**.  
The profile is created and displayed by name in the High Availability Preferences page.  
The new profile is also listed on the primary SiteScope High Availability Preferences page.

## 8. Test the SiteScope Failover Configuration

For details, see "[Test SiteScope Failover Configuration](#)" below.


# Test SiteScope Failover Configuration

SiteScope Failover configuration is tested from both the SiteScope Failover user interface and the primary SiteScope interface.

### To test the SiteScope Failover configuration from the SiteScope Failover machine:

1. In the SiteScope Failover user interface, select **Preferences > High Availability Preferences**.
2. In the right panel, select **Default Settings > Test**.  
The Test High Availability dialog box appears.
3. (optional) To test the email notifications, enter an email address and click **Send Test Notifications**.
4. To test the SiteScope Failover configuration, click **Test**.

The test results appear:




5. Review the results for failure information, then click **OK**.

### To test the SiteScope Failover configuration from the primary SiteScope machine:

1. In the SiteScope Failover user interface, select **Preferences > High Availability Preferences**.
2. In the right panel, select **Default Settings > Test**. The Test High Availability dialog box appears.

The test results appear:



3. Review the results for failure information, then click **OK**.

## SiteScope Failover and BSM Integration

If a primary SiteScope is configured for reporting to BSM and the failover SiteScope is activated, SiteScope Failover automatically configures itself to report to BSM. In some cases, you may want to disable reporting to BSM from SiteScope Failover.

### To disable reporting to BSM from SiteScope Failover:

1. In the SiteScope Failover user interface, select **Preferences > High Availability Preferences**.
2. Select the profile for which you want to disable reporting to BSM and click **Edit**.
3. Expand the **Advanced Settings** panel.
4. Click **Disable BSM Integration**, and then click **OK**.

**Note:** SiteScope Failover reports to BSM only after the first mirroring occurred since the primary SiteScope was registered to BSM.

# Chapter 5

---

## Troubleshooting SiteScope Failover

This chapter describes procedures for diagnosing and troubleshooting problems that may occur when working with SiteScope Failover.

This chapter includes:

- "Error Log File" below
- "Failover Activation Issues" below
- "Authorization Errors Related to LW-SSO" on next page
- "Incorrect Report Data" on next page
- "Notifications Not Received" on next page

### Error Log File

Errors encountered during SiteScope Failover mirroring operations are written to the **high\_availability.log**. This log is located in the **<SiteScope root directory>\logs** directory on the failover server.

Entries are made to this file if the SiteScope Failover is scheduled to mirror configurations from the primary SiteScope but is unable to connect to the primary. Entries are also made to this file if individual mirroring operations fail or encounter errors.

### Failover Activation Issues

This section includes the troubleshooting suggestions for issues relating to SiteScope Failover activation and general operations.

- **Detecting if a SiteScope Failover was Activated**

To determine if a SiteScope Failover has been activated:

- Ask the recipients in the notifications list if they received an email about SiteScope Failover has been activated.
- Review the **high\_availability.log**.

- **SiteScope Failover License Issues**

If the license is other than a SiteScope Failover license, the failover will try to operate as a regular SiteScope installation.

To resolve a SiteScope Failover license:

- a. Check the license key entered on the SiteScope Failover server by opening the General Preferences page. If the license does not start with the letters **HA** then it is the incorrect license type.

- b. Contact your HP Sales person to obtain a valid SiteScope Failover license.
- c. Enter the new license on the SiteScope Failover server.
- d. Restart the SiteScope Failover service. On Windows platforms, the default service name is **Failover**.

After entering a valid Failover license and restarting the service or process, SiteScope Failover disables the mirrored monitors as long as it can detect the primary SiteScope.

## Authorization Errors Related to LW-SSO

If the LW-SSO init string differs for the primary SiteScope and SiteScope Failover, authorization errors occur.

To resolve authorization errors, see "Configure LW-SSO for the Authentication Strategy " on page 25.

## Incorrect Report Data

If reports seem to contain incorrect data, check that both the primary SiteScope and SiteScope Failover machines have synchronized time.

You can use the OS embedded time synchronization services (see [http://en.wikipedia.org/wiki/Network\\_Time\\_Protocol](http://en.wikipedia.org/wiki/Network_Time_Protocol)).

## Notifications Not Received

If notifications are not being received as expected, check the following areas:

1. In the SiteScope Failover user interface, select **Preferences > High Availability Preferences**.
2. Select **Default Settings > Test**.

In the Default Failover Settings dialog box, enter an email address and click **Send Test Message**. This also allows you to test the format of the notification.

3. If the email message was not received:
  - a. Select **Preferences > High Availability Preferences**.
  - b. In the High Availability Preferences page, click **Default Settings > Edit**.
  - c. Review the settings on the dialog for correctness.