

HP Network Node Manager iSPI Performance for Metrics Software

Software Version: 10.10
for the Windows® and Linux® operating systems

Deployment Reference

Document Release Date: March 2016
Software Release Date: October 2015



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Oracle Technology — Notice of Restricted Rights

Programs delivered subject to the DOD FAR Supplement are 'commercial computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement. Otherwise, programs delivered subject to the Federal Acquisition Regulations are 'restricted computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the restrictions in FAR 52.227-19, Commercial Computer Software-Restricted Rights (June 1987). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

For the full Oracle license text, see the license-agreements directory on the NNMi product DVD.

Copyright Notice

© Copyright 2013-2016 Hewlett-Packard Development Company, L.P.

Trademark Notices

Adobe® is a trademark of Adobe Systems Incorporated.

Linux® is the registered trademark of Linus Torvalds in the U.S. and other countries.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

Acknowledgements

This product includes libjpeg library. This software is copyright (C) 1991-1998, Thomas G. Lane.

The Graphics Interchange Format(c) is the Copyright property of CompuServe Incorporated. GIF(sm) is a Service Mark property of CompuServe Incorporated.

This product includes libxml2 library. Copyright (C) 1998-2003 Daniel Veillard. All Rights Reserved.

This product includes libxp library. Copyright © 2001,2003 Keith Packard.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.

- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to:
<https://softwaresupport.hp.com>

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to:
<https://hpp12.passport.hp.com/hppcf/createuser.do>

Or click the **Register** link at the top of the HP Software Support page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

Visit the HP Software Support Online web site at: **<https://softwaresupport.hp.com>**

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

<https://hpp12.passport.hp.com/hppcf/createuser.do>

To find more information about access levels, go to:

<https://softwaresupport.hp.com/web/softwaresupport/access-levels>

HP Software Solutions Now accesses the HPSW Solution and Integration Portal Web site. This site enables you to explore HP Product Solutions to meet your business needs, includes a full list of Integrations between HP Products, as well as a listing of ITIL Processes. The URL for this Web site is
<http://h20230.www2.hp.com/sc/solutions/index.jsp>

Contents

Overview	6
Part I: Installation Models	7
Introduction to Different Installation Models	8
Support for NNMi Application Failover	8
Achieving Scale Through Distribution	9
Roles	9
Guidelines for Deploying NPS in a Distributed Environment	11
Part II: Preinstallation Planning and Creating a Distributed Deployment	12
Creating a Distributed Environment	14
Identify Systems	14
Installing NPS	14
Prerequisites	14
General Prerequisites	14
Port Availability	15
Requirements on Linux	15
Enable Access Control List on Systems with Mounted File Systems (Only on Linux)	17
Prerequisites for Installing on Multi-homed Systems	18
Firewall	18
Enabling NNMi to Work with NPS	18
Installing NPS on Each System in the Environment	24
Assign Roles	26
Install iSPIs and Extension Packs	31
Install iSPIs and Custom Poller Extension Packs in an Environment with a Single ETL Server	31
Install iSPIs and Custom Poller Extension Packs in an Environment with Multiple ETL Servers	31
Switching from a Standalone Environment	38
Creating a Separate ETL Server	39
Record the Details of Your Existing NPS Environment	39
Disable the ETL Server Role on the Original NPS System	40
Install a New instance of NPS	41
Enable the ETL Server Role on the New NPS System	42
Run the nnmenableperspi.ovpl Script	44
Creating a Separate DB Server	44
Record the details of your existing NPS environment	44
Take a Backup of the Database	45
Install a New Instance of NPS	46
Restore the Database on the New System	46
Enable Only the DB Server Role on the New System	46

Disable the DB Server Role on the Original System	47
Reconcile the DB Server FQDN on Other Servers	48
Creating a Separate UiBi Server	49
Record the Details of Your Existing NPS Environment	50
Take a Backup of Files and the Content Store	50
Install a New Instance of NPS.	51
Enable Only the UiBi Server Role on the New NPS System	51
Disable the UiBi Server Role on the Original NPS System	54
Reconcile the UiBi Server FQDN on Other Servers	56
Run the nnmenableperfspl.ovpl Script	56
Modifying Data Retention Settings	57
Part III: Upgrading an Existing Distributed Deployment of NPS	59
Upgrade NPS to Version 10.10	59
Additional Configuration Task on the UiBi Server	61
Additional Configuration Task on the ETL Server	62
Upgrade All iSPIs	62
Post-Upgrade Steps	63
Part IV: Maintaining NPS	69
Modifying the FQDN of the NPS System	70
Modifying the Default Communication Port	70
Maintaining the NPS Database	72
Changing the Default Database Password	72
Checking the Database Health	72
Back Up and Restore	73
Incremental Backup	74
Backing Up and Restoring on the Same System	75
Restoring a Backup Made on a Previous Product Version	75
Restoring a Backup Made on a Different System with Different Installation Directories	77
Restoring a Backup When Additional Files Were Added to Extend the Database	77
Post-Restore Steps on Windows	78
Recreating the NPS Database	78
Tuning NPS	81
Tuning the Business Intelligence Server	81
Monitoring the Performance of the Business Intelligence Server	81
Best Practices	82
Configuring Business Intelligence Server Settings	83
Resolving Problems with Jobs and Report Scheduling	85
Tuning the NPS Database	85
Log Files	87
Part V: Using Certificate Authority	88
Part VI: Troubleshooting	92
Send Documentation Feedback	94

Overview

This document describes the system design considerations involved in building and maintaining the Network Performance Server (NPS) component of your network monitoring solution. This document provides detailed guidelines on how to set up a distributed deployment of NPS, how to configure different components of NPS for optimal performance, and how to maintain the environment. This document supplements the Interactive Installation Guide and the Support Matrix.

The latest version of this document is available [here](#).

This document includes the following information:

- "[Introduction to Different Installation Models](#)" on page 8. Provides an introduction to the concept of distributed NPS deployment.
- "[Creating a Distributed Environment](#)" on page 14. Provides instructions to create a new distributed deployment of NPS.
- "[Switching from a Standalone Environment](#)" on page 38. Describes how to migrate a standalone NPS system to a distributed environment.
- "[Maintaining the NPS Database](#)" on page 72. Describes how to back up, restore, and recreate the NPS database.
- "[Tuning the Business Intelligence Server](#)" on page 81. Describes how to fine-tune different settings of the Business Intelligence Server for optimal performance.

Part I: Installation Models

While deploying NPS, you can use one of the three available deployment architecture. The size of your monitoring environment is an important factor in deciding the right deployment architecture. This section of the document provides information about each deployment architecture.

Introduction to Different Installation Models

Single-Server Model

You can install NPS on the NNMi management server when you plan to monitor a small or medium-sized environment. The procedure to install NPS (and the NNM iSPI Performance for Metrics) on the NNMi management server involves running the NNM iSPI Performance for Metrics on the NNMi management server. See the *NNM iSPI Performance for Metrics Support Matrix* for information about the sizes of environments that are supported by this *same-server* installation model where NPS co-exists with NNMi on the same server.

Dedicated Server Model

To achieve greater performance and scale, you can install NPS (and the NNM iSPI Performance for Metrics) on a standalone, dedicated server. Installing NPS in this model involves running the `nnmenableperfspi.ovpl` script on the NNMi management server and running the NNM iSPI Performance for Metrics installer on a dedicated server. You can opt for this installation model when you want to monitor a large or very large environment.

Distributed Deployment of NPS

You can deploy NPS across a number of systems to take advantage of more computing resources and achieve greater scale. The **distributed deployment of NPS** enables you to distribute the computing load across multiple systems and designate each system to perform a specific operation determined by the **role** assigned to the system and provides a way to get past resource constraints on a single server. Distributed environments are best-suited to large scale network monitoring with high scale needs in the area of scheduled report generation, real-time analytics, or custom collection reporting.

Support for NNMi Application Failover

Application Failover for NNMi ensures redundancy. Failover allows a secondary NNMi server to take over immediately after the failure of a primary NNMi server. Failover relies on jboss clustering technology, ongoing file system synchronization, and a Java keystore file that must be copied from NNM to NPS. For details, see the *HP Network Node Manager iSPI Performance for Metrics Installation Guide*.

NPS supports NNMi Application Failover, which is transparent to users. Aside from an interruption in service lasting about 15 minutes while failover is in progress, users are not aware that a failover took place, and the administrator is not required to perform any special tasks related to failover.

The ability of NPS to support Application Failover depends on files it retrieves from the primary server in the cluster. NPS retrieves these files during startup. As soon as NPS has the files, it begins monitoring the status of the primary server by checking for status changes every 5 minutes. If NPS detects a status change, the following events take place automatically:

- NPS determines which server is the new primary server.
- NPS redirects data collection to a shared directory on the new primary server.
- NPS begins collecting data (metrics and topology files) from the new primary server in the cluster.

Note: After failing over to the standby server, all reportlet dashboards and bookmark links will stop working. You must regenerate all reportlet dashboards and bookmark links after failover.

Immediately after failover, NPS users are able to link from NPS to NNMi views on the new primary server, just as they could before failover.

Achieving Scale Through Distribution

Server resources include CPU, memory, and disk I/O. When any one of these resources is fully consumed, you experience performance limitations that can prevent NPS from processing and loading the incoming data fast enough. The following behaviors indicate that NPS is unable to process the data optimally with the available resources:

You can address these problems, to a point, by adjusting how the server memory and CPU resources are allocated with the help of different tuning parameters provided by NPS. See ["Tuning the Business Intelligence Server" on page 81](#) and ["Tuning the NPS Database" on page 85](#) for more information. If you continue to experience resource bottleneck after tuning NPS, consider spreading NPS processes across multiple servers by creating a distributed deployment of NPS.

You can plan to create a distributed deployment of NPS if you observe the following:

- One or more Extension Packs routinely fail to complete loading within its polling interval (usually 5 minutes). To assess this, launch the ETL Performance by ExtPk Report View (from the **Self Monitoring > Quicklaunch Diagnostic Reports** menu in the navigation pane in the NPS console). Monitor the value of the `Process Time (secs) (avg)` metric for each Extension Packs. If the value exceeds 300 seconds for an Extension Pack, you can consider creating a distributed deployment with a dedicated server with the Extract, Transform, and Load Server (ETL Server) role.
- After launching the NPS console, the navigation pane appears empty for several seconds. In this case, you can consider creating a distributed deployment with a dedicated server with the User Interface and Business Intelligence Server (UiBi Server).
- If scheduled reports often fail to complete, consider configuring a separate server with the UiBi Server role.

Roles

You can assign one, two, or all three of the following roles to an NPS system in a distributed deployment:


- **Database Server:** The Database Server (DB Server) role is responsible for creating and hosting the NPS database and running database queries. The NNM iSPI Performance for Metrics installs Sybase IQ on each NPS system. When you assign the DB Server role to a system, NPS starts the Sybase IQ database on the system and creates a shared directory.
In a deployment, you can assign the DB Server role to *only one* system.
- **User Interface and Business Intelligence Server:** The User Interface and Business Intelligence Server (UiBi Server) role is responsible for rendering the available data into reports with the help of templates provided with Extension Packs. When you assign the UiBi Server role to a system, NPS starts the BI server and creates a shared directory.

You can assign the UiBi Server role to *only one* system.

- **Extract, Transform, and Load Server:** The Extract, Transform, and Load Server (ETL Server role) is responsible for performing Extract, Transform, and Load (ETL) operations for the collected metrics.


You can assign the ETL Server role to as many systems as you like. However, each Extension Pack must be enabled on only one ETL Server.

Distributed Deployment of NPS with a Single ETL Server



When you configure multiple ETL Servers, you must allocate specific Extension Packs to be processed by each ETL Server. In other words, you must identify which Extension Packs are going to be processed by which ETL Server.

Distributed Deployment of NPS with Two ETL Servers



Guidelines for Deploying NPS in a Distributed Environment

You can configure NPS in a distributed environment from day one of your operation by installing NPS on multiple systems and assigning specific roles to each NPS system. This configuration is recommended for very large scale environment. For more information about the scale of the environment where the distributed deployment of NPS could be an ideal solution, see the *Support Matrix*.

To create a distributed environment in phases, follow these guidelines:

- All NPS systems in the distributed deployment must run on the same operating system.
- All NPS systems in the distributed deployment must have the same time zone configuration.
- While creating a distributed deployment, use the following sequence while configuring server roles:
 - a. Configure the DB Server role.
 - b. Configure the UiBi Server role.
 - c. Configure the ETL Server role.

Part II: Preinstallation Planning and Creating a Distributed Deployment

This section of the document provides step-by-step instructions to plan and create a distributed deployment of NPS. You can also migrate your standalone NPS installation to a distributed environment by following the instructions provided in this section.

Creating a Distributed Environment

At the time of installation, the NNM iSPI Performance for Metrics installer automatically assigns all three roles to the NPS system. If you want to deploy NPS in a distributed environment, you must install NPS on each system in the distributed environment, and then run the `configureNpsServer.ovpl` script on each system to assign roles.

To create a distributed environment, follow these steps:

1. ["Identify Systems"](#).
2. ["Installing NPS"](#).
3. ["Assign Roles" on page 26](#)

Identify Systems

Identify the systems on which you want to install NPS. Make sure all systems meet the hardware and software requirements listed in the *HP Network Node Manager iSPI Performance for Metrics Software Support Matrix* and the Prerequisites section in the *HP Network Node Manager iSPI Performance for Metrics Software Installation Guide*.

Note: All systems must run with the same operating system.

Installing NPS

With the help of the *HP Network Node Manager iSPI Performance for Metrics Software 10.10* media, install NPS on each system. Follow the instructions in this section.

Prerequisites

Before you begin, make sure that the following prerequisites are met:

General Prerequisites

Primary Domain Name System (DNS) suffix

The system where you plan to install NPS must have a primary DNS suffix configured. The system must be reachable on the network using the fully-qualified domain name (FQDN).

The NNMi management server and the NPS systems must have the same domain name.

Verify that the NPS systems and NNMi management server are in the same DNS domain; for example, `mycompany.com`. Membership in different subdomains is allowed, but the parent domain must be the same. For example, the following systems can be used as the NNMi management server and the NPS systems:

- `nmm.mycompany.com`
- `nps.reporting.mycompany.com`

Automatic operating system updates

Disable the automatic update feature of the operating system to prevent automatic installation of operating system fixes and enhancements while you install NPS. You can enable the feature after successful installation of NPS.

Network

It is recommended that you install NPS on a system with Gigabit Ethernet LAN interfaces.

The network interface card (NIC) on each system should have at least 1 Gbps link speed.

Tip: If you plan to store large volumes of data in the NPS database, you can choose SAN disks for the NPS system. However, if you plan to use a single SAN disk for NPS and a few other applications, you might observe poor NPS performance due to inference from other applications.

Use a benchmark tool to assess the performance of the disk prior to installing NPS.

On Linux, use a benchmark tool (like `bonnie++`) to assess the performance of the disk prior to installing NPS. On high-performing I/O systems, `bonnie++` should have a total run time of 1 minute 10 seconds or less.

Port Availability

The following ports must be available on the system:

Port	Type	Purpose	Configuration
9300	TCP	Default HTTP port – used for Web UI and BI Web Services	After installation, you can change this port by using <code>configureWebAccess.ovpl</code> .
9305	TCP	Default Secure HTTPS port (SSL) – used for Web UI and BI Web Services	After installation, you can change this port by using <code>configureWebAccess.ovpl</code> .
9301	TCP	Sybase ASE	Change not supported
9302	TCP	Sybase IQ Agent service	Change not supported
9303	TCP	Sybase IQ—the NPS database	Change not supported
9306	TCP	Database SQL Rewrite Proxy—the NPS database	Change not supported
9308	TCP	Sybase ASE backup server for the BI content manager database	Change not supported

For NMMi on Linux. Make sure that the Samba software is installed on the management server. Configure the security policies or firewall settings to make exceptions for the SMB traffic.

Requirements on Linux

Required libraries

The NPS installer requires a set of libraries to be present on the system. The installer performs a prerequisite check and, if any prerequisite libraries are missing, shows a list of missing libraries. You can then install the missing libraries manually or by using the `yum` command, and then start the installer again.

List of Prerequisite Libraries

- `libstdc++.i686`
- `compat-libstdc++-296.i686`
- `compat-libstdc++-33.i686`
- `compat-libstdc++-33.x86_64`
- `libpng.i686`
- `libpng.x86_64`
- `libXp.i686`
- `libXp.x86_64`
- `ncurses`
- `openmotif.i686`
- `openmotif.x86_64`
- `tclsh`
- `unixODBC.i686`
- `unixODBC.x86_64`
- `unixODBC-devel.i686`
- `unixODBC-devel.x86_64`
- `libXtst.i686`
- `libXtst`
- `libXi.i686`
- `libXi`
- `libaio`
- `nspr.i686`
- `nspr.x86_64`
- `nss.i686`
- `nss.x86_64`

IPv4 address in the hosts file

The hosts file (in the `/etc` directory) must include at least one IPv4 address for localhost.

Time zone

You must set the time zone to UTC or to a geographic time zone using `/usr/bin/system-config-date`.

All systems in the distributed deployment of NPS must be in the same time zone.

Set the Maximum Number of Open Files

You must set the maximum number of open files to at least 8192.

To set this limit, follow these steps:

1. Log on to the system as root.
2. Open the following file with a text editor:
`/etc/security/limits.conf`
3. Check that the value of the `nofile` parameter (against both the hard and soft types) is higher than 8192.

If a lower value is set, change the value to at least 8192.

For example:

```
* soft nofile 8192
```

```
* hard nofile 8192
```

4. Save the file.

Installing on ext4 File Systems

If you plan to install NPS on an ext4 file system, disable the journaling feature to enhance performance. To check that journaling is enabled, run the following command:

```
tune2fs -l /<device> | grep "Filesystem features"
```

In this instance, `<device>` is the name of the file system on which you plan to install NPS.

If the output of the command shows `has_journal`, the journaling feature is enabled.

To disable journaling, follow these steps:

1. Make sure that the file system is unmounted or mounted as read only.
2. Run the following command:

```
tune2fs -O ^has_journal /<device>
```

Enable Access Control List on Systems with Mounted File Systems (Only on Linux)

You must perform this additional step if the `/var/opt` directory exists on a mounted file system on one of these systems:

- NNMi management server
- The system where you want to configure the DB Server
- The system where you want to configure the UiBi Server

Follow these steps on each of the above systems if the `/var/opt` directory exists on a mounted drive:

1. Open the `/etc/fstab` file with a text editor.
2. Find the line that starts with the following:
`<file_system> <mount_point>`
`<file_system>` is the `/var/opt` directory (either `/var` or `/var/opt`)
3. In the line, add `acl` to the list of options.
4. Save the file.
5. Run the following command to remount `/var/opt`:

```
mount -o remount /var/opt
```

Or

```
mount -o remount /var
```

Prerequisites for Installing on Multi-homed Systems

While installing NPS on a system with multiple IP addresses, make sure that one of the IP addresses is present in the hosts file. Follow these steps:

1. Log on to the system where you are going to install NPS.
2. Go to the following directory:
 - On Windows*
 - C:\Windows\System32\drivers\etc
 - On Linux*
 - /etc
3. Open the `hosts` file with a text editor.
4. Add one of the IP addresses and the FQDN of the system in a new line.
5. Save the file.

Firewall

Firewall configuration must be disabled on all NPS systems in the distributed deployment.

To disable firewall, follow these steps:

On Windows

1. Log on to the system.
2. Click **Start > Control Panel > Network and Internet > Network and Sharing Center**.
3. Click **Windows Firewall**.
4. Click **Turn Windows Firewall on or off**.
5. Select the Turn off Windows Firewall options.

On Linux

1. Log on to the system.
2. Run the following commands:
 - a. **/etc/init.d/iptables save**
 - b. **/etc/init.d/iptables stop**
 - c. **chkconfig iptables off**

Enabling NNMi to Work with NPS

You must run a set of scripts on the NNMi management server to enable NNMi to work with the distributed deployment of NPS.

These scripts perform the following tasks:

- Adding a new menu item (NNM iSPI Performance) in the Actions menu of the NNMi console
- Enabling the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server
- Creating a shared directory on the NNMi management server where NNMi can store the performance data collected from the managed network (NPS collects the data from this shared directory)
- Creating a user on the NNMi management server with write privilege to the newly created shared directory

To enable NNMi to work with NPS, follow these steps:

Note: If NNMi is installed in a high-availability or Application Failover cluster, follow these steps on each node in the cluster.

When NNMi is installed on Linux

1. Log on to the NNMi management server as root.
2. If the `/var/opt` directory on the NNMi management server is on a mounted file system, you must perform the following additional steps:
 - a. Open the `/etc/fstab` file with a text editor.
 - b. Find the line that starts with the following:
`<file_system> <mount_point>`
`<file_system>` is the `/var/opt` directory (either `/var` or `/var/opt`)
 - c. In the line, add `acl` to the list of options.
 - d. Save the file.
 - e. Run the following command to remount `/var/opt`:
mount -o remount /var/opt
 Or
mount -o remount /var
3. Go to the following directory:
`/opt/OV/bin`
4. To run the script in the interactive mode:
 - a. Run the following command:
./nnmenableperfspi.ovpl
 The script prompts you for the fully qualified domain name of the NPS system.
 - b. Type the fully qualified domain name of the system on which you want to assign the UiBi Server role, and then press **Enter**.
 The script verifies the availability of the NPS system with a ping command.
 After successful verification, the script prompts you to specify the port that will be used by the NPS system.
 - c. Type a port number that is available for use, and then press **Enter**.

- The script prompts you to specify the communication protocol for NPS.
- d. Type **HTTPS** if you want to use the secure communication mode, and then press **Enter**.
If you want to use the non-secure HTTP mode of communication, press **Enter** without specifying anything.
The script prompts you to choose the type of file-sharing technique to exchange data between the NNMi management server and the NPS system. Available options are **CIFS**¹ and **NFS**².
 - e. Type **CIFS**, and then press **Enter**.

Note: While creating a distributed deployment of NPS, always choose CIFS. Using an NFS share with the distributed deployment of NPS is not supported. While creating a distributed deployment of NPS, you must always select the CIFS share while running the `nnmenableperfspl.ovpl` script.

The script enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server, adds new items under the **Actions** menu, and enables file sharing between the NNMi management server and the NPS system.

Follow these steps:

- i. The script prompts you to specify a user name that will be assigned as the owner of the shared file system.
Type a user name of your choice, and then press **Enter**. You need not type a pre-existing user name.
The script prompts you to type a password for the user that it is going to create.
- ii. Type a password that meets the operating system's password policy requirements, and then press **Enter**.
The script prompts you to specify the directory that will be used as the shared file system.
- iii. Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system, and then press **Enter**

The script performs the following tasks:

- Enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server
- Adds menu items under the Actions menu in the NNMi console to launch the NPS console
- Creates the shared file system
- Creates a user (if necessary) that can access the newly created shared file system

5. To run the script in the non-interactive (silent) mode:

- a. In a text editor, add the following content:

```
spiHost=
spiPort=
```

¹Common Internet File System (CIFS) is an application-layer file sharing protocol.

²Network File Share (NFS) is a file sharing protocol between systems running on UNIX/Linux.

```
spiProtocol=
shareType=
userName=
password=
shareName=
sharedDir=
```

- b. Specify a value for each parameter:

Parameter	Description
spiHost	Type the fully qualified domain name of the system on which you want to assign the UiBi Server role.
spiPort	Type the port that will be used by the NPS system. Type a port number that is available for use.
spiProtocol	Type HTTPS if want to use the secure communication mode. Type HTTP if you want to use the non-secure mode of communication.
shareType	Type CIFS.
userName	Type a user name of your choice. You need not type a pre-existing user name. This user name that will be assigned as the owner of the shared file system.
password	Type the password of the above user. The password must meet the operating system's password policy requirements.
shareName	Type a name of your choice for the shared file system.
sharedDir	Specify the directory that will be used as the shared file system. Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system.

- c. Save the file on the NNMi management server.

- d. Run the following command:

```
./nnmenableperfspi.ovpl -f <configFile>
```

In this instance, *<configFile>* is the name of the configuration file (with complete path to the file).

The script performs the following tasks:

- o Enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server
- o Adds menu items under the Actions menu in the NNMi console to launch the NPS console
- o Creates the shared file system
- o Creates a user (if necessary) that can access the newly created shared file system

When NNMi is Installed on Windows

1. Log on to the NNMi management server as Administrator.
2. Go to the following directory:

```
%nnminstalldir%\bin
```

3. To run the script in the interactive mode:

- a. Run the following command:

```
nnmenableperfspi.ovpl
```

The script prompts you for the fully qualified domain name of the NPS system.

- b. Type the fully qualified domain name of the system on which you want to assign the UiBi Server role, and then press **Enter**.

The script verifies the availability of the NPS system with a ping command.

After successful verification, the script prompts you to specify the port that will be used by the NPS system.

- c. Type a port number that is available for use, and then press **Enter**.

The script prompts you to specify the communication protocol for NPS.

- d. Type HTTPS if want to use the secure communication mode, and then press **Enter**.

If you want to use the non-secure HTTP mode of communication, press **Enter** without specifying anything.

The script prompts you to choose the type of file-sharing technique to exchange data between the NNMi management server and the NPS system.

- e. When you use a Windows NNMi management server, you must choose only the **CIFS**¹ protocol for file sharing.

Type CIFS, and then press **Enter**.

The script prompts you to specify a user name that will be assigned as the owner of the shared file system.

- f. Type a user name of your choice, and then press **Enter**. You need not type a pre-existing user name.

Tip: If you specify a user name that does not already exists, the script creates a new local user (and not a Windows domain user).

You can specify a pre-existing Windows domain user.

Always use the following format while specifying a pre-existing domain user name:

```
<domain>\<user_name>
```

In this instance, <domain> is the domain name and <user_name> is the user name.

The script prompts you to specify a password of the user that it is going to create.

- g. Type a password that meets the operating system's password policy requirements, and then press **Enter**.

The script prompts you to specify the directory that will be used as the shared file system.

¹Common Internet File System (CIFS) is an application-layer file sharing protocol.

- h. Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system, and then press **Enter**.

The script performs the following tasks:

- o Enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server
- o Adds menu items under the Actions menu in the NNMi console to launch the NPS console
- o Creates the shared file system
- o Creates a user (if necessary) that can access the newly created shared file system

- 4. To run the script in the non-interactive (silent) mode:

- a. In a text editor, add the following content:

```
spiHost=
spiPort=
spiProtocol=
shareType=
userName=
password=
shareName=
sharedDir=
```

- b. Specify a value for each parameter:

Parameter	Description
spiHost	Type the fully qualified domain name of the system on which you want to assign the UiBi Server role.
spiPort	Type the port that will be used by the NPS system. Type a port number that is available for use.
spiProtocol	Type the communication protocol for NPS. Type HTTPS if want to use the secure communication mode. Type HTTP if you want to use the non-secure mode of communication.
shareType	Type CIFS. When NNMi is installed on Windows, you can use only the CIFS ¹ protocol.
userName	Type a user name of your choice, and then press Enter . You need not type a pre-existing user name. Tip: If you specify a user name that does not already exists, the script creates a new local user (and not a Windows domain user).

¹Common Internet File System (CIFS) is an application-layer file sharing protocol.

Parameter	Description
	<p>You can specify a pre-existing Windows domain user.</p> <p>Always use the following format while specifying a pre-existing domain user name:</p> <p><code><domain>\<user_name></code></p> <p>In this instance, <code><domain></code> is the domain name and <code><user_name></code> is the user name.</p>
password	Type the password of the above user.
shareName	Type a name of your choice for the shared file system.
sharedDir	<p>Specify the directory that will be used as the shared file system.</p> <p>Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system.</p>

- c. Save the file on the NNMi management server.
- d. Run the following command:

nnmenableperfspi.ovpl -f <configFile>

In this instance, `<configFile>` is the name of the configuration file (with complete path to the file).

Installing NPS on Each System in the Environment

To install NPS on each system., follow these steps:

1. Insert the NNM iSPI Performance for Metrics installation media into the DVD drive.
2. Use the `cd` command to change to the media directory.
3. From the media root, run the setup file:

On Windows, double-click the **setup.exe** file.

On Linux, run the following command:

./setup.bin

The installation wizard opens.

Select the language of the wizard, and then click **OK**.

If the application requirement check warnings dialog box opens, review the warning messages, take appropriate action, and the click Continue.

4. On the Introduction page, click Next. The License Agreement page opens.
5. Select I accept the terms, and click Next. The Select Features page opens.
6. Clear the NNM iSPI Performance for Metrics–ExtensionPacks check box.

Note: You must clear the check box at this step. After installation and configuration, you can activate the NNM iSPI Performance for Metrics Extension Packs with the help of the


```
metricsExtensionPacks.ovpl script.
```

7. Click **Next**.

On Windows only. The Choose the Installation Directory page opens. If you want to install NPS in a non-default directory (or drive), make appropriate selections, and then click **Next**.

The installer program initiates the system-checking process and verifies that system requirements are met.

8. When the installation check succeeds, click **Next**.

If the installation check shows warnings and errors, review the messages, take appropriate action, and then click **Next**.

If the installer check shows necessary libraries are missing, follow these steps:

- a. Note down the names of missing libraries indicated by the installation wizard.
- b. Make sure the system is connected to the Internet and set up to work with Red Hat Network updates.
- c. To install each missing library, run the following command:

```
yum install<library>
```

In this instance, <library> is the name of the missing library as indicated by the installation wizard.

You can specify multiple libraries in the command—each separated by a space. (For example, **yum install openmotif.x86_64 libXp.x86_64 libpng.x86_64**.)

- d. Type **Y** to install the libraries.

While installing these libraries, you may see the following error message:

```
Error: Multilib version problems found.
```

To resolve this issue, run the following command:

```
yum update<library_name>
```

In this instance, <library_name> is the library name without the architecture field (i686 or x86_64).

For example, if you see the error while installing `libXp.i686`, run the following command:

```
yum update libXp
```

After successfully running the **yum update** command, run the command to install the missing library ([step c](#)).

The Pre-Install Summary page opens.

9. Click **Install**. The installation process begins.

Toward the end of the installation process, the HP NNM iSPI Performance Configuration window opens.

Do the following:

- a. Select the Remote CIFS Share Access option, and then specify the share name, account name, and password. Use the same details that you provided while running the `nnmenableperfspi.ovpl` script.

Tip: You can find the network share and user account details specified during the last run of the `nnmenableperfspi.ovpl` file in the following file on the NNMi management server:

(The file does not store the password.)

On Linux:

```
/var/opt/OV/log/nnmenableperfspi.txt
```

On Windows:

```
%nnmdatadir%\log\nnmenableperfspi.txt
```

Do not modify the data retention period values. Do not click **Start** under Service Status.

- b. Click **Apply**.
- c. Click **Exit**.

Assign Roles

You can assign roles to an NPS system by configuring the `serverRoleConfig.cfg` file first, and then running the `configureNpsServer.ovpl` command.

Note: Once role assignment is complete, you cannot configure an NPS system in a distributed deployment to assume a different role.

In this configuration step, you need to specify the details of the network share and user account specified while running the `nnmenableperfspi.ovpl` script. As a best practice, you must always securely note down share and user account details that are specified while running the `nnmenableperfspi.ovpl` script.

You can find the network share and user account details specified during the last run of the `nnmenableperfspi.ovpl` file in the following file on the NNMi management server:

(The file does not store the password.)

On Linux:

```
/var/opt/OV/log/nnmenableperfspi.txt
```

On Windows:

```
%nnmdatadir%\log\nnmenableperfspi.txt
```

The NPS installer places the `serverRoleConfig.cfg` file in the following directory:

- *On Windows:* %NPSInstallDir%\config
- *On Linux:* \$NPSInstallDir/config

To configure the `serverRoleConfig.cfg` file, follow these steps:

1. Log on to the NPS system.
2. Open the `serverRoleConfig.cfg` file with a text editor.

3. Make only the following changes to the file:

- To configure only the DB Server role, set the following properties to the values shown here:

Property	Value
Role.Etl	0
Role.UiBi	0
Role.DB	1

- To configure only the UiBi Server role, set the following properties to the values shown here:

Property	Value
Role.Etl	0
Role.Db	0
Role.UiBi	1
UiBi.DbServer.Hostname	Type the FQDN of the DB Server.
UiBi.NnmServer.Hostname	Type the FQDN of the NNMi management server.
UiBi.NnmServer.Share.Name	Type the name of the network share created on the NNMi management server while running the nnmenableperfspi.ovpl script.
UiBi.NnmServer.Share.User	Type the name of the user account specified while running the nnmenableperfspi.ovpl script.
UiBi.NnmServer.Share.Pass	Type the password of the above user account.

- To configure only the ETL Server role, set the following properties to the values shown here:

Property	Value
Role.ETL	1
Role.Db	0
Role.UiBi	0
Etl.DbServer.Hostname	Type the FQDN of the DB Server.
Etl.UiBiServer.Hostname	Type the FQDN of the UiBi Server.
Etl.NnmServer.Hostname	Type the FQDN of the NNMi management server.
Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL	0

Note: If you want to configure multiple ETL

Property	Value
	Servers, make sure, at a given point, this value is set to 0 only on one ETL Server.
Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL	0 Note: If you want to configure multiple ETL Servers, make sure, at a given point, this value is set to 0 only on one ETL Server.

- To configure the DB Server and ETL Server roles, set the following properties to the values shown here:

Property	Value
Role.ETL	1
Role.UiBi	0
Role.Db	1
Etl.DbServer.Hostname	Type the FQDN of the DB Server.
Etl.UiBiServer.Hostname	Type the FQDN of the UiBi Server.
Etl.NnmServer.Hostname	Type the FQDN of the NNMi management server.
Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL	0 Note: If you want to configure multiple ETL Servers, make sure, at a given point, this value is set to 0 only on one ETL Server.
Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL	0 Note: If you want to configure multiple ETL Servers, make sure, at a given point, this value is set to 0 only on one ETL Server.

- To configure the UiBi Server and ETL Server roles, set the following properties to the values shown here:

Property	Value
Role.ETL	1
Role.UiBi	1

Property	Value
Role.Db	0
Etl.DbServer.Hostname	Type the FQDN of the DB Server.
Etl.NnmServer.Hostname	Type the FQDN of the NNMi management server.
Etl.NnmServer.Share.Name	Type the name of the network share created on the NNMi management server while running the <code>nnmenableperfspl.ovpl</code> script.
Etl.NnmServer.Share.User	Type the name of the user account specified while running the <code>nnmenableperfspl.ovpl</code> script.
Etl.NnmServer.Share.Pass	Type the password of the above user account.
UiBi.DbServer.Hostname	Type the FQDN of the DB Server.
UiBi.NnmServer.Hostname	Type the FQDN of the NNMi management server.
UiBi.NnmServer.Share.Name	Type the name of the network share created on the NNMi management server while running the <code>nnmenableperfspl.ovpl</code> script.
UiBi.NnmServer.Share.User	Type the name of the user account specified while running the <code>nnmenableperfspl.ovpl</code> script.
UiBi.NnmServer.Share.Pass	Type the password of the above user account.
Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL	0 Note: If you want to configure multiple ETL Servers, make sure, at a given point, this value is set to 0 only on one ETL Server.
Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL	0 Note: If you want to configure multiple ETL Servers, make sure, at a given point, this value is set to 0 only on one ETL Server.

- To configure only the DB Server and UiBi Server roles, set the following properties to the values shown here:

Property	Value
Role.ETL	0
Role.UiBi	1

Property	Value
Role.Db	1
Etl.DbServer.Hostname	Type the FQDN of the DB Server.
Etl.UiBiServer.Hostname	Type the FQDN of the UiBi Server.
UiBi.DbServer.Hostname	Type the FQDN of the DB Server.
UiBi.NnmServer.Hostname	Type the FQDN of the NNMi management server.
UiBi.NnmServer.Share.Name	Type the name of the network share created on the NNMi management server while running the <code>nnmenableperfspi.ovpl</code> script.
UiBi.NnmServer.Share.User	Type the name of the user account specified while running the <code>nnmenableperfspi.ovpl</code> script.
UiBi.NnmServer.Share.Pass	Type the password of the above user account.

4. Save the file.

Tip: Always retain a backup of this file.

5. Drop the database from NPS systems where the DB Server role will not be present.
 - a. Identify the systems where you are not going to enable the DB Server role. You can do this by inspecting the contents of the `serverRoleConfig.cfg` file that you have modified on each system.

If the `Role.Db` parameter is set to 0 in the `serverRoleConfig.cfg` file, the system will not have the DB Server role activated after this procedure is complete.

- b. Log on as `root` or `administrator` to the systems where the DB Server role will not be present, and then run the following command:

initializeNPS.ovpl -a DropPerfSPIDB

Caution: Running this command on an incorrect NPS system (that is, the system where the DB Server role is going to remain active) will lead to data loss.

6. Log on as `root` or `administrator` to each NPS system, and then run the following command:

Note: Run this command on NPS system in the following order:

- a. The DB Server first
- b. The UiBi Server
- c. The ETL Servers

configureNpsServer.ovpl -f<config_file>

In this instance, `<config_file>` is the name (with the full path) of the configuration file.

Tip: As a best practice, take a backup of the `serverRoleConfig.cfg` file that you configured

for use with the `configureNpsServer.ovpl` script.

Install iSPIs and Extension Packs

Install iSPIs and custom poller Extension Packs only after assigning roles to all systems in the distributed deployment of NPS. If you install iSPIs and custom poller Extension Packs before configuring roles for NPS systems, duplicate instances of Extension Packs will be installed in your environment.

Install iSPIs and Custom Poller Extension Packs in an Environment with a Single ETL Server

Before you install any iSPIs, follow these steps:

1. Make sure that the `Et1.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL` property is set to 0 in the `serverRoleConfig.cfg` file on the ETL Server.
2. Make sure that the `Et1.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL` property is set to 0 in the `serverRoleConfig.cfg` file on the ETL Server.

Tip: Changes in the `serverRoleConfig.cfg` file take effect only after you run the `configureNpsServer.ovpl -f <config_file>` command on the system.

3. If you want to use the NNM iSPI Performance for Metrics Extension Packs, you must install the NNM iSPI Performance for Metrics on the ETL Server by running the following command:
metricsExtensionPacks.ovpl install
4. Install the iSPI by following the instructions in the iSPI documentation.
5. Install the custom poller Extension Packs by following the instructions in the NPS Online Help.
6. After installation, restart the NPS processes by running the following commands on each NPS system in the environment:
stopALL.ovpl
startALL.ovpl

Install iSPIs and Custom Poller Extension Packs in an Environment with Multiple ETL Servers


The benefit of assigning the ETL Server role on multiple systems is you can distribute the load of processing multiple Extension Packs across a series of servers. The `Et1.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL` and `Et1.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL` properties help you distribute this load.

The iSPI Extension Packs are automatically transferred to the ETL Server where `Et1.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL` is set to 0. Similarly, the custom poller Extension Packs are automatically transferred to the ETL Server where `Et1.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL` is set to 0.

To distribute the load across multiple ETL Servers, follow this work-flow:


For iSPI Extension Packs

1. Identify the ETL Server on which you want to install first set of iSPI Extension Packs.



2. Make sure that `Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL` is set to 0 in the `serverRoleConfig.cfg` file on the identified ETL Server.

`Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL` must be set to 1 in the `serverRoleConfig.cfg` file on all other ETL Servers.



3. Install the first set of iSPIs by following the iSPI documentation. After the iSPI installation is complete, the Extension Packs are automatically transferred and installed on the identified ETL Server.
4. Run the **about.ovpl** command on the ETL Server to verify that Extension Packs are installed correctly.

If you see that an Extension Pack, which you did not originally plan to install on this server, has been installed inadvertently, you can disable that Extension Pack on this server by running the following command:


disableExtensionPackEtl.ovpl -p <Extension_Pack>

In this instance, <Extension_Pack> is the name of the Extension Pack displayed by the about.ovpl command.

Note: You can enable an Extension Pack by running the following command:


enableExtensionPackEtl.ovpl -p <Extension_Pack>

5. Identify the ETL Server on which you want to install the second set of iSPI Extension Packs.



6. Make sure that `Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL` is set to 0 in the `serverRoleConfig.cfg` file on the identified ETL Server.

`Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL` must be set to 1 in the `serverRoleConfig.cfg` file on all other ETL Servers.



7. Install the second set of iSPIs by following the iSPI documentation. After the iSPI installation is complete, the Extension Packs are automatically transferred and installed on the identified ETL Server.
8. Run the **about.ovpl** command on the ETL Server to verify that Extension Packs are installed correctly.

If you see that an Extension Pack, which you did not originally plan to install on this server, has been installed inadvertently, you can disable that Extension Pack on this server by running the following command:

```
disableExtensionPackEtl.ovpl -p <Extension_Pack>
```


In this instance, *<Extension_Pack>* is the name of the Extension Pack displayed by the `about.ovpl` command.

Note: You can enable an Extension Pack by running the following command:

```
enableExtensionPackEtl.ovpl -p <Extension_Pack>
```


For Custom Poller Extension Packs

1. Identify the ETL Server on which you want to install first set of custom poller Extension Packs.



2. Make sure that `Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL` is set to 0 in the `serverRoleConfig.cfg` file on the identified ETL Server.

`Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL` must be set to 1 in the `serverRoleConfig.cfg` file on all other ETL Servers.



3. Install the first set of custom poller Extension Packs by following the NPS Online Help.
4. Run the `about.ovpl` command on the ETL Server to verify that Extension Packs are installed correctly.


If you see that an Extension Pack, which you did not originally plan to install on this server, has been installed inadvertently, you can disable that Extension Pack on this server by running the following command:

disableExtensionPackEtl.ovpl -p <Extension_Pack>


In this instance, `<Extension_Pack>` is the name of the Extension Pack displayed by the `about.ovpl` command.

Note: You can enable an Extension Pack by running the following command:
`enableExtensionPackEtl.ovpl -p <Extension_Pack>`

- Identify the ETL Server on which you want to install the second set of custom poller Extension Packs.



- Make sure that `Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL` is set to 0 in the `serverRoleConfig.cfg` file on the identified ETL Server.
`Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL` must be set to 1 in the `serverRoleConfig.cfg` file on all other ETL Servers.



- Install the second set of custom poller Extension Packs by following the NPS Online Help.

8. Run the **about.ovpl** command on the ETL Server to verify that Extension Packs are installed correctly.

If you see that an Extension Pack, which you did not originally plan to install on this server, has been installed inadvertently, you can disable that Extension Pack on this server by running the following command:

```
disableExtensionPackEtl.ovpl -p <Extension_Pack>
```

In this instance, *<Extension_Pack>* is the name of the Extension Pack displayed by the `about.ovpl` command.

Note: You can enable an Extension Pack by running the following command:

```
enableExtensionPackEtl.ovpl -p <Extension_Pack>
```

9. After installation, restart the NPS processes by running the following commands on each NPS system in the environment:

```
stopALL.ovpl
```

```
startALL.ovpl
```

Switching from a Standalone Environment

Note: You cannot directly upgrade an NPS 9.20 or 9.10 standalone environment to an NPS 10.10 distributed deployment. You must first upgrade to NPS 10.10, and then follow the steps in this chapter to switch to a distributed environment. For instructions to upgrade NPS 9.10 or 9.20 to 10.10, see the *NNM iSPI Performance for Metrics Interactive Installation Guide*.

You can also start your operation with only one NPS system, and gradually expand into a distributed deployment by installing additional servers and spreading the load across them. If you observe performance degradation in your single-NPS environment due to resource bottleneck (CPU, memory, or disk I/O), you can consider building a distributed NPS environment. To create a distributed environment in phases, follow these guidelines:

1. **Split out the ETL Server to a separate server.**

Install NPS on a new, dedicated system, and then assign the ETL Server role to the new system. On the original NPS system, configure only the DB Server and UiBi Server roles.

2. **Split out the UiBi Server or DB Server to a separate server.**

If you continue to experience resource bottleneck on the original NPS system, disable one of the existing roles (the UiBi Server or DB Server role) on the original system, install NPS on a third system, and then assign the UiBi Server or DB Server role to the new system.

3. **Split out the ETL Server role to multiple servers.**

If you experience resource bottleneck on the new NPS system where you configured the ETL Server role, install NPS on yet another new system, and then assign the ETL Server role to the new system. This configuration helps you distribute the ETL processing load across two different servers.

Note: While using multiple systems with the ETL Server role, you must enable a unique set of Extension Packs on each ETL server.

- If you continue to experience performance issues on systems with the ETL Server role, install NPS on additional systems and assign only the ETL Server role to those systems. You cannot configure the UiBi Server or DB Server on multiple systems.
- Before you start migrating to a distributed deployment, always take complete backup of the existing NPS installation.

Note: This is a precautionary step. Although you need to back up the content store and database separately, taking a complete backup will help prevent loss of data in the event of disruptive system failure during the process of migration.

Run the following command to take a complete backup of NPS:

```
backup.ovpl -b <dir>
```

In this instance, *<dir>* is the local directory where you want to store the backup file.

The command creates a single `.tar.gz` file.

Creating a Separate ETL Server

You can segregate out the ETL Server role by installing NPS onto a separate system and configuring the ETL Server role on that system.

To create a separate ETL Server, follow these steps:

1. ["Record the Details of Your Existing NPS Environment" below](#)
2. ["Disable the ETL Server Role on the Original NPS System" on the next page](#)
3. ["Install a New instance of NPS" on page 41\](#)
4. [" Enable the ETL Server Role on the New NPS System" on page 42](#)
5. ["Run the nnmenableperspi.ovpl Script" on page 44](#)

Record the Details of Your Existing NPS Environment

It is important to note down the details of your current NPS setup. You may migrate the ETL Server from a standalone, single-server NPS, or from an already created distributed deployment with the ETL Server co-existing with another server role on a single system.

Fill out the following table with the details of your existing environment.

Details of your existing NPS environment			
Standalone		Distributed deployment	
FQDN of the NPS system		FQDN of DB Server	
		FQDN of UiBi Server	
FQDN of the NNMI management server		FQDNof existing ETL Server	
		FQDN of the NNMI management server	

Also, correctly note down the share and user details that were specified while running the nnmenableperfsapi.ovpl script. you can find these details specified during the last run of the nnmenableperfsapi.ovpl file in the following directory on the NNMI management server:

(The file does not store the password.)

On Linux:

`/var/opt/OV/log/nnmenableperfsapi.txt`

On Windows:

`%nnmdatadir%\log\nnmenableperfsapi.txt`

Fill out the following table with the details:

NNMI details

NNMi share name	
NNMi share user name	
NNMi share user password	

Disable the ETL Server Role on the Original NPS System

1. Run the following command on the original NPS system to take a backup of archived files:

Note: Since you are going to migrate the ETL Server role onto a different system, you must take a backup of all files. This backup will later be restored on the new system.

Tip: Before you begin, make sure sufficient disk space exists on the NPS system to run the backup procedure and store the backed-up data. Determine the size of the configuration and archived data files by measuring size of the following directory:

On Windows

%npsdatadir%\NNMPerformance

On Linux


/var/opt/OV/NNMPerformance

backup.ovpl -b <dir_file> -f

In this instance, <dir_file> is the local directory where you want to store the backup file. The command creates a backup file in the <dir_file> directory, which is a .tar.gz file.

2. Stop all NPS processes on the original NPS server:

stopALL.ovpl



3. Configure the serverRoleConfig.cfg file to disable the ETL Server role on the original NPS system. The following table lists the parameters that must be modified to disable the ETL Server role:

Tip: The serverRoleConfig.cfg file is located in the following directory:

- *On Windows:* %NPSInstallDir%\config
- *On Linux:* \$NPSInstallDir/config

Take a copy of the default `serverRoleConfig.cfg` file to a different directory and modify the copied file.

Property	Value	Description
Role.ETL	0	Make sure this value is set to 0.

- Run the following command to check that the configuration file is correctly updated:

configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>


Check that the contents of <outputFile> is error free.

Note: If you see any errors, review the contents of the `serverRoleConfig.cfg` file, and then run the command again.

- Run the following command on the NPS system to disable the ETL Server role:

configureNpsServer.ovpl -f <config_file>

The ETL Server role is now disabled on this system.




- Check that only the DB Server and UiBi Server roles are enabled by running the `about.ovpl` command.
- Restart all processes by running the following command:

startALL.ovpl

Install a New instance of NPS

Install a new instance of NPS on a new system. While installing, choose to install the NNM iSPI Performance for Metrics Extension Packs. Do not start the ETL process on this system at the end of the installation.

As a result of the installation, a new NPS system is created where all roles are enabled.



Enable the ETL Server Role on the New NPS System

1. Log on to the newly created NPS system.
2. Run the following command on this new NPS system to restore all backed-up files (that were backed up in [step 2](#)):

```
restore.ovpl -b <backup_file>
```

3. Drop all database tables on this system by running the following command:

Caution: Make sure you run this command on the right system (that is, the new system where you installed NPS). Running this command on an incorrect NPS system will lead to data loss.

initializeNPS.ovpl -a DropPerfSPIDB

4. Configure the `serverRoleConfig.cfg` file to assign the ETL Server role to this NPS system:

Tip: The `serverRoleConfig.cfg` file is located in the following directory:

- *On Windows:* %NPSInstallDir%\config
- *On Linux:* \$NPSInstallDir/config

Take a copy of the default `serverRoleConfig.cfg` file to a different directory and modify the copied file.

Property	Value	Description
Role.ETL	1	Make sure this property is set to 1.
Role.Db	0	Make sure this property is set to 0.
Role.UiBi	0	Make sure this property is set to 0.
Etl.DbServer.Hostname	Type the FQDN of the system with the DB Server role.	This could be the original server from which you are migrating the ETL Server.

Property	Value	Description
		Refer to the table where you noted down the details.
Etl.UiBiServer.Hostname	Type the FQDN of the system with the UiBi Server role.	This could be the original server from which you are migrating the ETL Server. Refer to the table where you noted down the details.
Etl.RuntimeConfig.PRSPI_DISABLE_EXTENSIONPACK_AUTOINSTALL	0	Make sure this property is set to 0.
Etl.RuntimeConfig.PRSPI_DISABLE_CUSTOMCOLLECTION_AUTOINSTALL	0	Make sure this property is set to 0.
Etl.NnmServer.Hostname	Type the FQDN of the NNMi server.	Refer to the table where you noted down the details.
Etl.NnmServer.Share.Name	Type the name of the share created by nnmenableperfspi.ovpl.	Refer to the table where you noted down the details.
Etl.NnmServer.Share.User	Type the name of the user created by nnmenableperfspi.ovpl	Refer to the table where you noted down the details.
Etl.NnmServer.Share.Pass	Type the password of the above user.	Refer to the table where you noted down the details.

- Run the following command to check that the configuration file is correctly updated:

```
configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>
```


Check that the contents of *<outputFile>* is error free.

Note: If you see any errors, review the contents of the serverRoleConfig.cfg file, and then run the command again.

- Run the following command on this new NPS system:

```
configureNpsServer.ovpl -f <config_file>
```

The ETL Server role is now enabled on this system.



7. Check that only the ETL Server is enabled by running the `about.ovpl` command.
8. Start all processes by running the following command:
startALL.ovpl

Run the `nnmenableperspi.ovpl` Script

Note: If the original NPS system was configured to use the CIFS share (and *not* the NFS share), skip this section.

After moving the ETL Server role to a new system, you must run the `nnmenableperfspi.ovpl` script once again on the NNMi management server and you must select the CIFS share this time. Using an NFS share with the distributed deployment of NPS is not supported.

Creating a Separate DB Server

You can segregate out the DB Server role by installing NPS onto a separate system and configuring the DB Server role on that system.

To create this setup, follow these steps:

1. ["Record the details of your existing NPS environment" below](#)
2. ["Take a Backup of the Database " on the next page](#)
3. ["Install a New Instance of NPS" on page 46](#)
4. ["Enable Only the DB Server Role on the New System" on page 46](#)
5. ["Disable the DB Server Role on the Original System" on page 47](#)
6. [" Reconcile the DB Server FQDN on Other Servers" on page 48](#)

Record the details of your existing NPS environment

It is important to note down the details of your current NPS setup. You may migrate the DB Server from a standalone, single-server NPS, or from an already created distributed deployment with the DB Server co-existing with another server role on a single system.

Fill out the following table with the details of your existing environment.

Details of your existing NPS environment			
Standalone		Distributed deployment	
FQDN of the NPS system		FQDN of DB Server	
		FQDN of UiBi Server	
FQDN of the NNMi management server		FQDN of existing ETL Server	
		FQDN of the NNMi management server	

In this configuration step, you need to specify the details of the network share and user account specified while running the `nnmenableperfspi.ovpl` script. As a best practice, you must always securely note down share and user account details that are specified while running the `nnmenableperfspi.ovpl` script.

You can find the network share and user account details specified during the last run of the `nnmenableperfspi.ovpl` file in the following file on the NNMi management server:

(The file does not store the password.)

On Linux:

```
/var/opt/OV/log/nnmenableperfspi.txt
```

On Windows:

```
%nmmdatadir%\log\nnmenableperfspi.txt
```

Fill out the following table with the details:

NNMi details	
NNMi share name	
NNMi share user name	
NNMi share user password	

Take a Backup of the Database

1. Run the following command on the original NPS system to take a database backup:

Note: Since you are going to migrate the DB Server role onto a different system, you must take a backup of the entire database. This backup will later be restored on the new system.

Tip: Before you begin, make sure sufficient disk space exists on the NPS system to run the backup procedure and store the backed-up data. Determine the size of the NPS database by running the following command:

```
dbsize.ovpl -q
```

```
backup.ovpl -b<dir_db> -d
```

In this instance, `<dir_db>` is the local directory where you want to store the backup file. The command creates a backup file (with the `.tar.gz` extension) in the `<dir_db>` directory.

2. Stop all NPS processes on the original NPS server where the DB Server role is currently enabled:
stopALL.ovpl

Install a New Instance of NPS

Install a new instance of NPS on a new system. While installing, *do not* choose to install the NNM iSPI Performance for Metrics Extension Packs. Do not start the ETL process on this system at the end of the installation.

As a result of the installation, a new NPS system is created where all roles are enabled.

Restore the Database on the New System

Run the following command on this new NPS system to restore all backed-up database files (that were backed up in [step 1](#)):

restore.ovpl -b <backup_db>

In this instance, `<backup_db>` is the backed-up database file.

Enable Only the DB Server Role on the New System

1. Log on to the newly created NPS system.
2. Configure the `serverRoleConfig.cfg` file to enable the DB Server role to this NPS system. The following table lists the properties that must be modified to enable the DB Server role:

Tip: The `serverRoleConfig.cfg` file is located in the following directory:

- *On Windows:* `%NPSInstallDir%\config`
- *On Linux:* `$NPSInstallDir/config`

Take a copy of the default `serverRoleConfig.cfg` file to a different directory and modify the copied file.

Property	Value
Role.ETL	0
Role.Db	1
Role.UiBi	0

3. Run the following command to check that the configuration file is correctly updated:
configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>
Check that the contents of `<outputFile>` is error free.

Note: If you see any errors, review the contents of the `serverRoleConfig.cfg` file, and then run the command again.

- Run the following command on this new NPS system:
configureNpsServer.ovpl -f <config_file>
 The DB Server role is now enabled on this system.
- Check that only the DB Server role is enabled by running the `about.ovpl` command.

Disable the DB Server Role on the Original System

- Drop all databases on the original NPS system by running the following command:
initializeNPS.ovpl -a DropPerfSPIDB
- Configure the `serverRoleConfig.cfg` file to disable the DB Server role on the original NPS system. The following table lists the properties that must be modified to disable the DB Server role:

Tip: The `serverRoleConfig.cfg` file is located in the following directory:

- On Windows: `%NPSInstallDir%\config`
- On Linux: `$NPSInstallDir/config`

Take a copy of the default `serverRoleConfig.cfg` file to a different directory and modify the copied file.

Property	Value	Description
Role.Db	0	Make sure this property is set to 0.
All properties that end with <code>DbServer.Hostname</code>	FQDN of the new DB Server.	Type the FQDN of the new NPS system where you will be configuring the DB Server role.

- Run the following command to check that the configuration file is correctly updated:
configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>
 In this instance, `<config_file>` is the complete path (including the file name) to the `serverRoleConfig.cfg` file that you edited.
 Check that the contents of `<outputFile>` is error free.

Note: If you see any errors, review the contents of the `serverRoleConfig.cfg` file, and then run the command again.

- Run the following command on the NPS system to disable the DB Server role:
configureNpsServer.ovpl -f <config_file>
 The DB Server role is now disabled on this system.
- Check that only the DB Server role is completely disabled by running the `about.ovpl` command.

- Restart all processes by running the following command:

startALL.ovpl

Reconcile the DB Server FQDN on Other Servers

Only if you started off with an existing distributed deployment.

If you performed this procedure in an existing distributed deployment, you must configure all other servers in the deployment to communicate with the new DB Server.

For example, if your original setup consisted of a single system with the DB Server and UiBi Server roles and a single system for the UiBi Server, you must configure the ETL Server now to communicate with the new DB Server.

Follow these steps:

- Log on to the system as root or administrator.
- Configure the `serverRoleConfig.cfg` file to specify the FQDN of the new DB Server.

Tip: The `serverRoleConfig.cfg` file is located in the following directory:

- *On Windows:* %NPSInstallDir%\config
- *On Linux:* \$NPSInstallDir/config

Take a copy of the default `serverRoleConfig.cfg` file to a different directory and modify the copied file.

Property	Value	Description
Role.Db	0	Make sure this property is set to 0. This setting ensures the DB Server is not enabled on this system.
Role.UiBi and Role.ETL	1 or 0	Make sure to correctly set these properties depending on the role of the system.
All properties that end with <code>DbServer.Hostname</code>	FQDN of the new DB Server.	Type the FQDN of the new NPS system where you will be configuring the DB Server role.
All properties that end with <code>nnmserver.hostname</code>	FQDN of the NNMi management server	Type the FQDN of the NNMi management server.
All properties that end with <code>NnmServer.Share.Name</code>	The NNMi share name	Type the NNMi share name that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow

Property	Value	Description
		the details noted down in the worksheet .
All properties that end with <code>NnmServer.Share.User</code>	The NNMI share user name	Type the NNMI share user name that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet .
All properties that end with <code>NnmServer.Share.Pass</code>	The NNMI share user password	Type the NNMI share user password that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet .

Look for the properties that end with `Dbserver.hostname` and set those properties to the new FQDN of the DB Server.

- Run the following command to check that the configuration file is correctly updated:

```
configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>
```

In this instance, is the complete path (including the file name) to the `serverRoleConfig.cfg` file that you edited.

Check that the contents of `<outputFile>` is error free.

Note: If you see any errors, review the contents of the `serverRoleConfig.cfg` file, and then run the command again.

- Run the following command:
configureNpsServer.ovpl -f <config_file>.
- Restart all processes by running the following command:
startALL.ovpl

Creating a Separate UiBi Server

You can segregate out the UiBi Server role by installing NPS onto a separate system and configuring the UiBi Server role on that system.

To create this setup, follow these steps:

- ["Record the Details of Your Existing NPS Environment" on the next page](#)
- ["Take a Backup of Files and the Content Store" on the next page](#)
- ["Install a New Instance of NPS." on page 51](#)
- ["Enable Only the UiBi Server Role on the New NPS System" on page 51](#)
- [" Disable the UiBi Server Role on the Original NPS System" on page 54](#)
- ["Reconcile the UiBi Server FQDN on Other Servers" on page 56](#)
- ["Run the nnmenableperfspi.ovpl Script" on page 56](#)

Record the Details of Your Existing NPS Environment

It is important to note down the details of your current NPS setup. You may migrate the DB Server from a standalone, single-server NPS, or from an already created distributed deployment with the DB Server co-existing with another server role on a single system.

Fill out the following table with the details of your existing environment.

Details of your existing NPS environment			
Standalone		Distributed deployment	
FQDN of the NPS system		FQDN of DB Server	
		FQDN of UiBi Server	
FQDN of the NNMi management server		FQDN of existing ETL Server	
		FQDN of the NNMi management server	

Tip: In this configuration step, you need to specify the details of the network share and user account specified while running the `nnmenableperfspi.ovpl` script. As a best practice, you must always securely note down share and user account details that are specified while running the `nnmenableperfspi.ovpl` script.

You can find the network share and user account details specified during the last run of the `nnmenableperfspi.ovpl` file in the following file on the NNMi management server:

(The file does not store the password.)

On Linux:

```
/var/opt/OV/log/nnmenableperfspi.txt
```

On Windows:

```
%nnmdatadir%\log\nnmenableperfspi.txt
```

Fill out the following table with the details:

NNMi details	
NNMi share name	
NNMi share user name	
NNMi share user password	

Take a Backup of Files and the Content Store

Creating a new UiBi Server server requires you to transfer all the necessary data from the old system to the new system. This is achieved by taking a backup of all files and the content store on the original

NPS system and restoring the backed-up data to the newly configured UiBi Server server. Therefore, before you begin the migration of the UiBi Server role, you must take a backup.

1. Run the following command on the original NPS system to take a backup of archived data files:

Note: Since you are going to migrate the UiBi Server role onto a different system, you must take a backup of all files. This backup will later be restored on the new system.

Tip: Before you begin, make sure sufficient disk space exists on the NPS system to run the backup procedure and store the backed-up data. Determine the size of the configuration and archived data files by measuring size of the following directory:

On Windows

```
%npsdatadir%\NNMPerformance
```

On Linux

```
/var/opt/OV/NNMPerformance
```

backup.ovpl -b <dir_file> -f

In this instance, <dir_file> is the local directory where you want to store the backup file.

2. Run the following command on the original NPS system to take a content store backup:

Note: Since you are going to migrate the UiBi Server role onto a different system, you must take a backup of the content store. This backup will later be restored on the new system.

Tip: Before you begin, make sure sufficient disk space exists on the NPS system to run the backup procedure and store the backed-up data. Determine the size of the NPS content store by running the following command:

cssize.ovpl -q

backup.ovpl -b <dir_cs>-c

In this instance, <dir_cs> is the local directory where you want to store the backup file.

Install a New Instance of NPS.

Install a new instance of NPS on a new system. While installing, *do not* choose to install the NNM iSPI Performance for Metrics Extension Packs. Do not start the ETL process on this system at the end of the installation.

Enable Only the UiBi Server Role on the New NPS System

1. Log on to the newly created NPS system.
2. Run the following command on this new NPS system to restore all backed-up files (that were backed up in [step 1](#)):

restore.ovpl -b <backup_file>

In this instance, <backup_file> is the backed-up NPS files.

- Run the following command on this new NPS system to restore the content store (that were backed up in [step 2](#)):

restore.ovpl -b <backup_cs>

In this instance, <backup_cs> is the backed-up NPS content store.

- Drop all database tables on this system by running the following command:

Caution: Make sure you run this command on the right system (that is, the new system where you installed NPS). Running this command on an incorrect NPS system will lead to data loss.

initializeNPS.ovpl -a DropPerfSPIDB

- Configure the serverRoleConfig.cfg file to enable the UiBi Server role to this NPS system. The following table lists the properties that must be modified to enable the UiBi Server role:

Tip: The serverRoleConfig.cfg file is located in the following directory:

- On Windows: %NPSInstallDir%\config
- On Linux: \$NPSInstallDir/config

Take a copy of the default serverRoleConfig.cfg file to a different directory and modify the copied file.

Property	Value	Description
Role.ETL	0	Make sure this property is set to 0. This setting ensures the ETL Server is not enabled on this system.
Role.Db	0	Make sure this property is set to 0. This setting ensures the DB Server is not enabled on this system.
Role.UiBi	1	Make sure this property is set to 1.
UiBi.Share.User	The share user name.	NNMi share user name that was configured while running the nnmenableperfspi.ovpl script. Follow the details noted down in the worksheet . Do not modify if you are using the default share

Property	Value	Description
		user.
UiBi.Share.Pass	The share user password	NNMi share user password that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet . Do not modify if you are using the default share user.
UiBi.DbServer.Hostname	The FQDN of the DB Server.	The FQDN of the system that is configured as the DB Server.
UiBi.DbServer.User	The share user name.	NNMi share user name that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet . Do not modify if you are using the default share user.
UiBi.DbServer.Pass	The share user password	NNMi share user password that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet . Do not modify if you are using the default share user.
UiBi.NnmServer.Hostname	The FQDN of the NNMi management server.	Type the FQDN of the NNMi management server.
UiBi.NnmServer.Share.Name	NNMi network share	Type the name of the network share created on

Property	Value	Description
		the NNMi management server while running the <code>nnmenableperfspl.ovpl</code> script.
UiBi.NnmServer.Share.User	Type the name of the user account specified while running the <code>nnmenableperfspl.ovpl</code> script.	Type the name of the user account specified while running the <code>nnmenableperfspl.ovpl</code> script.
UiBi.NnmServer.Share.Pass	Type the password of the above user account.	Type the password of the above user account.

- Run the following command to check that the configuration file is correctly updated:

```
configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>
```

Check that the contents of `<outputFile>` is error free.

Note: If you see any errors, review the contents of the `serverRoleConfig.cfg` file, and then run the command again.

- Run the following command on this new NPS system:

```
configureNpsServer.ovpl -f <config_file>
```

The UiBi Server role is now enabled on this system.

- Check that only the UiBi Server role is enabled by running the `about.ovpl` command.

Tip: You can delete the edited `serverRoleConfig.cfg` file at this point.

- Restart all processes by running the following command:

```
startALL.ovpl
```

Disable the UiBi Server Role on the Original NPS System

At this point, you must go back to the original NPS system and disable the UiBi Server role.

- Stop all NPS processes on the original NPS system:

```
stopALL.ovpl
```

- Configure the `serverRoleConfig.cfg` file to disable the UiBi Server role on the original NPS system. The following table lists the properties that must be modified to disable the UiBi Server role:

Tip: The `serverRoleConfig.cfg` file is located in the following directory:

- On Windows: `%NPSInstallDir%\config`
- On Linux: `$NPSInstallDir/config`

Take a copy of the default `serverRoleConfig.cfg` file to a different directory and modify the copied file.

Property	Value	Description
Role.UiBi	0	Make sure this property is set to 0.
All properties that end with <code>UiBiServer.Hostname</code>	FQDN of the new UiBi Server.	Type the FQDN of the new NPS system where you have configured the UiBi Server role.
All properties that end with <code>nnmserver.hostname</code>	FQDN of the NNMi management server	Type the FQDN of the NNMi management server.
All properties that end with <code>NnmServer.Share.Name</code>	The NNMi share name	Type the NNMi share name that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet .
All properties that end with <code>NnmServer.Share.User</code>	The NNMi share user name	Type the NNMi share user name that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet .
All properties that end with <code>NnmServer.Share.Pass</code>	The NNMi share user password	Type the NNMi share user password that was configured while running the <code>nnmenableperfspi.ovpl</code> script. Follow the details noted down in the worksheet .

- Run the following command to check that the configuration file is correctly updated:

configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>

In this instance, is the complete path (including the file name) to the `serverRoleConfig.cfg` file that you edited.

Check that the contents of `<outputFile>` is error free.

Note: If you see any errors, review the contents of the `serverRoleConfig.cfg` file, and then run the command again.

- Run the following command on the original NPS system to disable the UiBi Server role:
configureNpsServer.ovpl -f <config_file>
The UiBi Server role is now disabled on this system.
- Check that only the UiBi Serverrole is completely disabled by running the `about.ovpl` command.

Tip: You can delete the edited `serverRoleConfig.cfg` file at this point.

- Restart all processes by running the following command:
startALL.ovpl

Reconcile the UiBi Server FQDN on Other Servers

Only if you started off with an existing distributed deployment.

If you performed this procedure in an existing distributed deployment, you must configure all other servers in the deployment to communicate with the new UiBi Server. For example, if your original setup consisted of a single system with the DB Server and UiBi Server roles and a single system for the ETL Server, you must configure the ETL Server now to communicate with the new UiBi Server.

Follow these steps:

1. Log on to the system as root or administrator.
2. Configure the `serverRoleConfig.cfg` file to specify the FQDN of the new DB Server.

Tip: The `serverRoleConfig.cfg` file is located in the following directory:

- *On Windows:* %NPSInstallDir%\config
- *On Linux:* \$NPSInstallDir/config

Take a copy of the default `serverRoleConfig.cfg` file to a different directory and modify the copied file.

Look for the properties that end with `UiBiserver.hostname` and set those properties to the new FQDN of the DB Server.

3. Run the following command to check that the configuration file is correctly updated:

```
configureNpsServer.ovpl -f <config_file> -m validate -o <outputFile>
```

In this instance, is the complete path (including the file name) to the `serverRoleConfig.cfg` file that you edited.

Check that the contents of `<outputFile>` is error free.

Note: If you see any errors, review the contents of the `serverRoleConfig.cfg` file, and then run the command again.

4. Run the following command:
configureNpsServer.ovpl -f <config_file>.
5. Restart all processes by running the following command:
startALL.ovpl

Run the `nnmenableperfspi.ovpl` Script

After moving the UiBi Server role to a new system, you must run the `nnmenableperfspi.ovpl` script once again on the NNMi management server and you must provide the FQDN of the new UiBi Server this time.

Modifying Data Retention Settings

By default, NPS is installed with the following settings:

- Daily data retention period: 800 days
- Hourly data retention period: 70 days
- Raw/detailed data retention period: 14 days

If you want to modify the data retention settings in a distributed deployment of NPS, follow these steps:

1. Decide the new retention periods. The retention period of the raw data must be smaller than the retention period of the hourly data; the retention period of the hourly data again must be smaller than that of the daily data.
2. Decide if the modified retention periods will apply to all Extension Packs or just to a subset of Extension Packs installed in the environment.
3. To modify the retention periods of all Extension Packs on a system with the ETL Server role:
 - a. Log on to the ETL Server as administrator or root.
 - b. Launch the NNM iSPI Performance Configuration window.
4. To configure different retention periods for different Extension Packs on an ETL Server:
 - a. Log on to the ETL Server as administrator or root.
 - b. Go to the following directory:

On Windows

Click **Start > All Programs > HP > NNM iSPI Performance > Configuration Utility**.

On Linux

Run the following command:

`/opt/OV/NNMPerformanceSPI/bin/runConfigurationGUI.ovpl`

- c. Specify the changes in data retention settings, and then click **Apply**. The change is applied to all the Extension Packs that are installed (and enabled) on the system.
- d. If you have created an environment with multiple ETL Servers and want to change the data retention settings on the other ETL Servers, perform similar steps ([step a](#) through [step c](#)) on them.

On Windows

`%npsdatadir%\NNMPerformanceSPI\rconfig\<Extension_Pack_Name>`

On Linux

`/var/opt/OV/NNMPerformanceSPI/rconfig/<Extension_Pack_Name>`

Tip: To find out the names of installed Extension Packs, run the following command:

`about.ovpl`

- c. Locate the `customConfig.cfg` file in this directory.
- d. Create an empty `userConfig.cfg` file, and then transfer all the parameters that are available in the `customConfig.cfg` file to the `userConfig.cfg` file.

- e. In the `userConfig.cfg` file, change the values of the following properties to modify the data retention periods:
 - `PRSPI_DataRetention_Raw` (for raw data)
 - `PRSPI_DataRetention_Hour` (for hourly data)
 - `PRSPI_DataRetention_Day` (for daily data)
- f. Save the `userConfig.cfg` file.
- g. Restart the ETL process for the changes to take effect by running the following commands:
 - **stopETL.ovpl**
 - **startETL.ovpl**

Part III: Upgrading an Existing Distributed Deployment of NPS

You can upgrade an existing distributed deployment created with NPS 10.00 to NPS 10.10.

Tip: If possible, take a backup of all the copies of the `serverRoleConfig.cfg` files that you used while assigning server roles.

To upgrade a distributed deployment of NPS, perform these tasks:

1. **Task 1:** ["Upgrade NPS to Version 10.10" below](#)
2. **Task 2:** ["Additional Configuration Task on the UiBi Server" on page 61](#)
3. **Task 3:** ["Upgrade All iSPIs" on page 62](#)
4. **Task 4:** ["Post-Upgrade Steps" on page 63](#)

Upgrade NPS to Version 10.10

1. Stop NPS services on the UiBi Server by running the following command:
stopALL.ovpl
2. Stop NPS services on the ETL Servers by running the following command:
stopALL.ovpl
3. Stop NPS services on the DB Server by running the following command:
stopALL.ovpl
4. Upgrade NPS to 10.10 on each system by following these steps:

Note: While upgrading NPS, follow this sequence:

- a. Upgrade the DB Server.
- b. Upgrade the UiBi Server.
- c. Upgrade the ETL Server.

Do not start upgrading the UiBi Server until the DB Server is completely upgraded; do not start upgrading the ETL Servers until the UiBi Server is completely upgraded.

- a. Extract the contents of the NNM iSPI Performance for Metrics media.
- b. Use the `cd` command to change to the media directory.
- c. From the media root, run the `setup` file (`setup.exe` for Windows; `setup.bin` for Linux).
The installation wizard opens.

Note: *For Linux Only.* If you are performing these steps from a remote server by using an XServer, and if the `DISPLAY` variable is not set correctly, the following message may appear:

Choose locale....

1- Deutsch

->2- English

3- Espanol

4- Francais

CHOOSE LOCALE BY NUMBER:

If you see this message, do not continue with the installation. Stop the installation by pressing **Ctrl+C**, make sure that the `DISPLAY` variable is set correctly, and then run the setup file again.

Select the language of the wizard, and then click **OK**.

If the application requirement check warnings dialog box opens, review the warning messages, take appropriate action, and then click **Continue**.

- d. On the Introduction page, click **Next**. The License Agreement page opens.
- e. Select **I accept the terms**, and click **Next**.
- f. When the upgrade check succeeds, click **Next**.

If the upgrade check shows warnings and errors, review the messages, take appropriate actions, and then click **Next**.

Tip: *For Linux only.* If the installer check shows necessary libraries are missing, click here.

To install missing libraries on the system, follow these steps:

- i. Note down the names of missing libraries indicated by the installation wizard.
- ii. Make sure the system is connected to the Internet and set up to work with Red Hat or SUSE package repositories.
- iii. To install each missing library, run the following command:

On Red Hat Enterprise Linux

yum install <library>

Tip: You can specify multiple libraries in the command—each separated by a space. (For example, **yum install openmotif.x86_64 libXp.x86_64 libpng.x86_64**.)

On SUSE Linux Enterprise Server

zypper install <library>

In this instance, <library> is the name of the missing library as indicated by the installation wizard.

- iv. Type **Y** to install the libraries.

The Pre-Upgrade Summary page opens.

- g. Make sure that the NNM iSPI Performance for Metrics—ExtensionPacks check box is not

- selected.
- h. Click **Upgrade**. The upgrade process begins.
- Toward the end of the upgrade process, the HP NNM iSPI Performance Configuration window opens.
- On the DB Server and UiBi Server, click **Exit**.

Note: On the DB Server and UiBi Server, do not change any settings. Do not click **Start**.

After the upgrade procedure is complete, you cannot configure an NPS system in a distributed deployment to assume a different role.

On the ETL Server, make sure that the correct share path is specified, make sure that CIFS is selected as the sharing mode, and then click **Apply** if you had to make any changes; otherwise, click **Exit**.

Additional Configuration Task on the UiBi Server

1. Log on to the UiBi Server as root or administrator.
2. Do one of the following:
 - Reconfigure the `serverRoleConfig.cfg` file:
 - i. Retrieve the copy of the `serverRoleConfig.cfg` file that was used to configure the server role on this system.

Tip: If you are unable to retrieve the copy of the `serverRoleConfig.cfg` file that was used before, follow the [alternative procedure](#).

- ii. Add the following properties:

```
UiBi.NnmServer.Hostname =
UiBi.NnmServer.Share.Name =
UiBi.NnmServer.Share.User =
UiBi.NnmServer.Share.Pass =
```

- iii. Set the newly added properties to the following values:

Property	Value
UiBi.NnmServer.Hostname	Type the FQDN of the NNMi management server.
UiBi.NnmServer.Share.Name	Type the name of the network share created on the NNMi management server while running the <code>nnmenableperfspl.ovpl</code> script.
UiBi.NnmServer.Share.User	Type the name of the user account specified while running the <code>nnmenableperfspl.ovpl</code> script.
UiBi.NnmServer.Share.Pass	Type the password of the above user account.

- iv. Save the file.
 - Alternatively, create a new copy of the `serverRoleConfig.cfg` file:
Create a new `serverRoleConfig.cfg` file by following the instructions in the ["Assign Roles" on page 26](#) section.
3. Configure the UiBi Server role again by running the following command:
`configureNpsServer.ovpl -f <config_file>`
In this instance, `<config_file>` is the name (with the full path) of the configuration file.

Additional Configuration Task on the ETL Server

1. Log on to the ETL Server as root or administrator.
2. Do one of the following:
 - Retrieve the copy of the `serverRoleConfig.cfg` file that was used to configure the server role on this system.

Tip: If you are unable to retrieve the copy of the `serverRoleConfig.cfg` file that was used before, follow the [alternative procedure](#).

- Alternatively, create a new copy of the `serverRoleConfig.cfg` file:
Create a new `serverRoleConfig.cfg` file by following the instructions in the ["Assign Roles" on page 26](#) section.
3. Configure the ETL Server role again by running the following command:
`configureNpsServer.ovpl -f <config_file>`
In this instance, `<config_file>` is the name (with the full path) of the configuration file.

Upgrade All iSPIs

Upgrade all other iSPIs to 10.10. Follow the information in the iSPI documentation.

If you are using the NNM iSPI Performance for Metrics Extension Packs, do one of the following:

- In a single-ETL Server deployment, log on to the ETL Server as root or administrator, and then run the following command:
`metricsExtensionPacks.ovpl install`
- In a multi-ETL Server deployment, log on (as root or administrator) to the ETL Server where the NNM iSPI Performance for Metrics Extension Packs were originally installed, and then run the following command:
`metricsExtensionPacks.ovpl install`

Post-Upgrade Steps

1. Run the `nnmenableperfspi.ovpl` script on the NNMi management server.

Tip: To provide the same configuration details that existed prior to upgrading NPS to 10.10, see the contents of the following file:

(The file does not store the password.)

On Linux:

```
/var/opt/OV/log/nnmenableperfspi.txt
```

On Windows:

```
%nnmdatadir%\log\nnmenableperfspi.txt
```

When NNMi is installed on Linux

- a. Log on to the NNMi management server as root.
- b. If the `/var/opt` directory on the NNMi management server is on a mounted file system, you must perform the following additional steps:
 - i. Open the `/etc/fstab` file with a text editor.
 - ii. Find the line that starts with the following:
`<file_system> <mount_point>`
`<file_system>` is the `/var/opt` directory (either `/var` or `/var/opt`)
 - iii. In the line, add `acl` to the list of options.
 - iv. Save the file.
 - v. Run the following command to remount `/var/opt`:
mount -o remount /var/opt
Or
mount -o remount /var
- c. Go to the following directory:
`/opt/OV/bin`
- d. To run the script in the interactive mode:
 - i. Run the following command:
./nnmenableperfspi.ovpl
The script prompts you for the fully qualified domain name of the NPS system.
 - ii. Type the fully qualified domain name of the system on which you want to assign the UiBi Server role, and then press **Enter**.
The script verifies the availability of the NPS system with a ping command.
After successful verification, the script prompts you to specify the port that will be used by the NPS system.
 - iii. Type a port number that is available for use, and then press **Enter**.

The script prompts you to specify the communication protocol for NPS.

- iv. Type HTTPS if you want to use the secure communication mode, and then press **Enter**.
If you want to use the non-secure HTTP mode of communication, press **Enter** without specifying anything.

The script prompts you to choose the type of file-sharing technique to exchange data between the NNMi management server and the NPS system. Available options are **CIFS**¹ and **NFS**².

- v. Type **CIFS**, and then press **Enter**.

Note: While creating a distributed deployment of NPS, always choose CIFS. Using an NFS share with the distributed deployment of NPS is not supported. While creating a distributed deployment of NPS, you must always select the CIFS share while running the `nnmenableperfspi.ovpl` script.

The script enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server, adds new items under the **Actions** menu, and enables file sharing between the NNMi management server and the NPS system.

Follow these steps:

- A. The script prompts you to specify a user name that will be assigned as the owner of the shared file system.

Type a user name of your choice, and then press **Enter**. You need not type a pre-existing user name.

The script prompts you to type a password for the user that it is going to create.

- B. Type a password that meets the operating system's password policy requirements, and then press **Enter**.

The script prompts you to specify the directory that will be used as the shared file system.

- C. Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system, and then press **Enter**

The script performs the following tasks:

- Enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server
- Adds menu items under the Actions menu in the NNMi console to launch the NPS console
- Creates the shared file system
- Creates a user (if necessary) that can access the newly created shared file system

- e. To run the script in the non-interactive (silent) mode:

- i. In a text editor, add the following content:

¹Common Internet File System (CIFS) is an application-layer file sharing protocol.

²Network File Share (NFS) is a file sharing protocol between systems running on UNIX/Linux.

spiHost=
 spiPort=
 spiProtocol=
 shareType=
 userName=
 password=
 shareName=
 sharedDir=

ii. Specify a value for each parameter:

Parameter	Description
spiHost	Type the fully qualified domain name of the system on which you want to assign the UiBi Server role.
spiPort	Type the port that will be used by the NPS system. Type a port number that is available for use.
spiProtocol	Type HTTPS if want to use the secure communication mode. Type HTTP if you want to use the non-secure mode of communication.
shareType	Type CIFS.
userName	Type a user name of your choice. You need not type a pre-existing user name. This user name that will be assigned as the owner of the shared file system.
password	Type the password of the above user. The password must meet the operating system's password policy requirements.
shareName	Type a name of your choice for the shared file system.
sharedDir	Specify the directory that will be used as the shared file system. Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system.

iii. Save the file on the NNMi management server.

iv. Run the following command:

```
./nnmenableperfspi.ovpl -f <configFile>
```

In this instance, <configFile> is the name of the configuration file (with complete path to the file).

The script performs the following tasks:

- Enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server

- Adds menu items under the Actions menu in the NNMi console to launch the NPS console
- Creates the shared file system
- Creates a user (if necessary) that can access the newly created shared file system

When NNMi is Installed on Windows

- Log on to the NNMi management server as Administrator.
- Go to the following directory:


```
%nnminstalldir%\bin
```
- To run the script in the interactive mode:
 - Run the following command:


```
nnmenableperfspi.ovpl
```

The script prompts you for the fully qualified domain name of the NPS system.
 - Type the fully qualified domain name of the system on which you want to assign the UiBi Server role, and then press **Enter**.

The script verifies the availability of the NPS system with a ping command.

After successful verification, the script prompts you to specify the port that will be used by the NPS system.
 - Type a port number that is available for use, and then press **Enter**.

The script prompts you to specify the communication protocol for NPS.
 - Type HTTPS if want to use the secure communication mode, and then press **Enter**.

If you want to use the non-secure HTTP mode of communication, press **Enter** without specifying anything.

The script prompts you to choose the type of file-sharing technique to exchange data between the NNMi management server and the NPS system.
 - When you use a Windows NNMi management server, you must choose only the **CIFS**¹ protocol for file sharing.

Type CIFS, and then press **Enter**.

The script prompts you to specify a user name that will be assigned as the owner of the shared file system.
 - Type a user name of your choice, and then press **Enter**. You need not type a pre-existing user name.

Tip: If you specify a user name that does not already exists, the script creates a new local user (and not a Windows domain user).

You can specify a pre-existing Windows domain user.

Always use the following format while specifying a pre-existing domain user name:

`<domain>\<user_name>`

In this instance, `<domain>` is the domain name and `<user_name>` is the user name.

¹Common Internet File System (CIFS) is an application-layer file sharing protocol.

The script prompts you to specify a password of the user that it is going to create.

- vii. Type a password that meets the operating system's password policy requirements, and then press **Enter**.

The script prompts you to specify the directory that will be used as the shared file system.

- viii. Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system, and then press **Enter**.

The script performs the following tasks:

- Enables the evaluation license of the NNM iSPI Performance for Metrics on the NNMi management server
- Adds menu items under the Actions menu in the NNMi console to launch the NPS console
- Creates the shared file system
- Creates a user (if necessary) that can access the newly created shared file system

- d. To run the script in the non-interactive (silent) mode:

- i. In a text editor, add the following content:

```
spiHost=  
spiPort=  
spiProtocol=  
shareType=  
userName=  
password=  
shareName=  
sharedDir=
```

- ii. Specify a value for each parameter:

Parameter	Description
spiHost	Type the fully qualified domain name of the system on which you want to assign the UiBi Server role.
spiPort	Type the port that will be used by the NPS system. Type a port number that is available for use.
spiProtocol	Type the communication protocol for NPS. Type HTTPS if you want to use the secure communication mode. Type HTTP if you want to use the non-secure mode of communication.
shareType	Type CIFS.

Parameter	Description
	When NNMi is installed on Windows, you can use only the CIFS ¹ protocol.
userName	Type a user name of your choice, and then press Enter . You need not type a pre-existing user name. <div style="background-color: #f0f0f0; padding: 5px;"> <p>Tip: If you specify a user name that does not already exist, the script creates a new local user (and not a Windows domain user). You can specify a pre-existing Windows domain user. Always use the following format while specifying a pre-existing domain user name: <code><domain>\<user_name></code> In this instance, <code><domain></code> is the domain name and <code><user_name></code> is the user name.</p> </div>
password	Type the password of the above user.
shareName	Type a name of your choice for the shared file system.
sharedDir	Specify the directory that will be used as the shared file system. Type the complete path to the directory that you want to use as the shared file system between the NNMi management server and the NPS system.

iii. Save the file on the NNMi management server.

iv. Run the following command:

nnmenableperfspi.ovpl -f <configFile>

In this instance, `<configFile>` is the name of the configuration file (with complete path to the file).

2. Log on to the DB Server, and then run the following commands:

a. **stopALL.ovpl**

b. **startALL.ovpl**

3. Log on to the UiBi Server, and then run the following commands:

a. **stopALL.ovpl**

b. **startALL.ovpl**

4. Log on to each ETL Server, and then run the following commands:

Note: In an environment with multiple ETL Servers, perform this step on each system where the ETL Server role is enabled.

a. **stopALL.ovpl**

b. **startALL.ovpl**

¹Common Internet File System (CIFS) is an application-layer file sharing protocol.

Part IV: Maintaining NPS

After installing and configuring NPS, you might want to make changes to your environment like changing the IP address or hostname of the NPS system or the NNMi management server. You might want to free up ports used by NPS and configure non-default ports for NPS. This chapter provides you with steps to make these changes after NPS is completely installed and configured.

Modifying the FQDN of the NPS System

If you change the FQDN of the NPS system, you must perform the following steps before using NPS:W

1. Log on to the NNMI management server as root or administrator.
2. *In a co-located setup.*

If NPS co-exists with NNMI, you must run the `nnmsetofficialfqdn.ovpl` command.

- a. Go to `%nnminstalldir%\bin` on Windows and `/opt/OV/bin` on Linux.
- b. Run the `nnmsetofficialfqdn.ovpl` script.
- c. Go to `%nnminstalldir%\NNMPerformanceSPI\bin` on Windows and `/opt/OV/NNMPerformanceSPI/bin` on Linux.
- d. Run the `configureServerID.ovpl` script.

3. *In a dedicated NPS setup.*

If NPS is installed on a dedicated server, follow these steps:

- a. On the NNMI management server, run the `nnmdisableperfspi.ovpl` script.
The `nnmdisableperfspi.ovpl` script is available in the `%nnminstalldir%\bin` directory on Windows and `/opt/OV/bin` directory on Linux.
- b. *Linux only.* If NPS is installed on Linux, run the following command on the NPS system to unmount the shared drive that was created to facilitate data exchange between NPS and NNMI.
umount /<share_name>
In this instance, `<share_name>` is the name of the share created while installing NPS.
- c. On the NPS system, run the `configureServerID.ovpl` script.
The `configureServerID.ovpl` script is available in the `%npsinstalldir%\bin` directory on Windows and `/opt/OV/NNMPerformanceSPI/bin` directory on Linux.
- d. On the NNMI management server, run the `nnmenableperfspi.ovpl` script.
The `nnmenableperfspi.ovpl` script is available in the `%nnminstalldir%\bin` directory on Windows and `/opt/OV/bin` directory on Linux.

Modifying the Default Communication Port

By default, NPS uses the port 9300 (for HTTP) or 9305 (for HTTPS) for communication via a web browser. After NPS is installed and configured, you can modify the NPS configuration to change the NPS communication port.

To change the communication port:

Note: When NPS is installed in a high availability cluster, perform this task on the active server first, fail over to the other server, and then perform the task again on the server that is currently

active.

In a distributed deployment of NPS, perform this task on the UiBi Server.

1. Log on to the NPS system as root or administrator.
2. If NPS is configured for HTTP communication, run the following command:

```
configureWebAccess.ovpl -newport <port_number>
```

If NPS is configured for HTTPS communication, run the following command:

```
configureWebAccess.ovpl -newport <port_number> -ssl
```

In this instance, *<port_number>* is the new communication port number.

Maintaining the NPS Database

The NPS database store a large amount of data that is gathered from different sources (like NNMI and iSPIs) and enables NPS to compute aggregates from a large number of data points. The database can keep daily aggregated data for up to 800 days, hourly aggregated data for up to 400 days, and raw/detailed data for up to 400 days.

With scripts and utilities available with NPS, you can monitor the health and performance of the database and perform maintenance tasks like checking the health of the database, deleting and recreating the database, and so on.

Changing the Default Database Password

The NPS installer installs the NPS database with a default password.

To change the default database password, log on to the NPS system as root or administrator, and then run the following command:

```
changeDBpwd.ovpl <new_password>
```

In this instance, <new_password> is the password of your choice.

Note: In a distributed deployment of NPS, you must run the above command on each NPS system in the following order:

1. DB Server
2. UiBi Server
3. ETL Server

Checking the Database Health

The `dbsize.ovpl` utility enables you to check the health of the NPS database.

To use the `dbsize.ovpl` utility to check the health of the NPS database, follow these steps:

1. Log on to the NPS system as root or administrator. In a distributed deployment of NPS, log on to the DB Server as root or administrator.
2. Open a command line console, and then run one of the following commands:

Command	Description
dbsize.ovpl -q	The command output displays the usage summary of different dbspaces within the database. (NPS creates the following dbspaces within the database: IQ_SYSTEM_MAIN, IQ_SYSTEM_TEMP, and USER_MAIN).
dbsize.ovpl -s	The command output displays the size of different fact tables

Command	Description
	for each Extension Pack.
statusDB.ovpl	The command output displays the status of the NPS database.

Back Up and Restore

NPS provides command-line tools that back up and restore all NPS data.

To back up the NPS data:

Tip: Before you begin, make sure sufficient disk space exists on the NPS system to run the backup procedure and store the backed-up data. Determine the size of the NPS database, content store, and configuration and archived data files.

To determine the size of the NPS database, run the following command:

dbsize.ovpl -q

To determine the size of the content store, run the following command:

cssize.ovpl -q

To determine the total size of all configuration and archived data files, measure the size of the following directory:

On Windows

%npsdatadir%

On Linux

/var/opt/OV/NNMPerformanceSPI

1. Log on to the NPS system with the same account used to install NPS.
2. Run the following command:

```
backup.ovpl -b <dir> [-c] [-d] [-f]
```

In this instance, <dir> is the location where you want to place the backed-up data. Do not use environment variables with this option.

Options

- Use the `-c` option to back up the content store.
- Use the `-d` option to back up the database.
- Use the `-f` option to back up all NPS configuration and archived data files.
- Use the `-t` option to suppress creating a single compressed archive (tar.gz) file. This option leaves the directory as is on the file system, and greatly speeds up the backup process.

You must specify a valid directory location as an argument of the `-b` option. If you do not specify any other options, the backup script will back up the content store and the database.

The duration of the backup process depends on the size of the database. Before you start the backup process, verify the amount of disk space used by the data you want to back up, and make sure the

system has enough free disk space. Although the script produces compressed output, the backup process requires sufficient temporary disk space.

For command details, see backup.ovpl

To restore NPS data:

1. Log in to the NPS system with the same account used to install NPS.
2. Run the following command:

```
restore.ovpl [-h] [-b <file>] [-l] [-r DBFILE=>NEW_PATH_TO_DBFILE.iq
[,DBFILE=>NEW_PATH_TO_DBFILE.iq]]
```

In this instance:

-h	displays this text
-b <file>	specifies backup file
-l	lists file content without restoring
-r DBFILE=>NEW_PATH_TO_DBFILE.iq[,DBFILE=>NEW_PATH_TO_DBFILE.iq]	allows one or more database file to be restored to the specified (non-default) location

The restore operation overwrites all preceding NPS data.

When the restore is complete, the ETL service will not be running. You must restart the service to resume the processing of new data. To start ETL, run the startETL.ovpl, startALL.ovpl command, or use the Start button on the Configuration Utility.

If you change the password of the database after a backup operation, you must change it again after restoring the backed-up database.

Incremental Backup

A comprehensive backup strategy is essential for disaster recovery. Although full backups are simple to implement and easy to execute when restoration is required, they can slow down processes that are running, take a long time to complete, and require large (sometimes excessively large) amounts of storage.

Incremental backups, however, can balance speed, resource conflicts, and required storage against ease of restoration.

The purpose of a backup is to provide a recovery point. Different systems have different requirements for recovery points. A backup strategy that offers daily recovery points can be implemented through a weekly schedule of full backups combined with incremental daily backups on all other days.

For additional security, each backup should be stored on removable media and made secure. This should also include creating several generations of media.

To implement a backup strategy that incorporates four generational copies:

1. Run a full backup.ovpl backup on a weekly basis.
Use no backup flags (that is, c, d, or f) so that the database, the content store, and the file system are backed up.

Here is an example:

- Linux:

```
$NPSInstallDir/bin/backup.ovpl -b /var/backup/full
```

- Windows:

```
%NPSInstallDir%\bin\backup.ovpl -b E:\backup\full
```

2. Copy the backed up data to one of four versions of backup tapes.

Backup tapes should be kept off site. Alternatively, they can be created directly using WAN links to copy data.

3. Run an incremental backup on a daily basis.

Use no backup flags (c, d, or f) , so that the database, the content store, and the file system are backed up.

Use the optional `-i` flag to perform an incremental backup.

Here is an example:

- Linux

```
$NPSInstallDir/bin/backup.ovpl -b /var/backup/incremental -i
```

- Windows

```
%NPSInstallDir%\bin\backup.ovpl -b E:\backup\incremental -i
```

Only changes since the last backup (full or incremental) are saved.

4. Copy the backed up data to one of four backup tapes.

Append the data. Do not overwrite existing backed up data.

If restoration is required:

- Restore from the desired full backup. See the reference page or man page for `restore.ovpl`.
- Restore (in sequential order) each incremental backup from oldest to most recent.

Note: When restoring an incremental backup that includes the content store, you must restore each backup in turn without starting the BI Server. If you start the BI Server, it will write to the content store database and prohibit restoring from any further incremental backups.

If you do write to the content store database before restoring an incremental backup, you must return to the full backup and start the restoration process again.

Backing Up and Restoring on the Same System

If the backup is restored on the same system with the same installation directories and product version as the backup, the entire contents of data directory will be restored, including all configuration files, archived data files, the database, and the content store.

Restoring a Backup Made on a Previous Product Version

Backups made on earlier product versions can be restored with some limitations.

- User configurable settings (retention and installed Extension Pack list) are merged into the current settings.
- The database and content store are restored.
- Other (internal) configuration files are not restored. The restore command
- Archived data files are not restored.
- All Extension Packs must be installed again to ensure that the reports and database structures are upgraded to the latest version.

To restore the data that was backed up on a previous version of NPS, follow these steps:

Note: In a distributed deployment of NPS, you must perform these steps on the DB Server.

1. Transfer the backup file to the NPS system
2. Log in to the NPS system as root or administrator.
3. Run the following command:

```
restore.ovpl -b <backup_file>
```

In this instance, *<backup_file>* is the backup file.

Note: If the command fails to work and shows an error message (C API (dbcapi) could not be loaded), open a new command prompt and run the command again.

4. After running the `restore.ovpl` command, follow these steps:
 - a. Run the Configuration Utility again and check that all the settings (share name, user name, data retention periods, and so on) are correct.
To open the Configuration Utility, run the following command:
runConfigurationGUI.ovpl
 - b. Run the following command to configure the communication protocol and port:
configureWebAccess.ovpl -newport <port_number> [-ssl]
In this instance, *<port_number>* is the communication port that you have chosen while running the `nnmenableperfspi.ovpl` command. Use the `-ssl` parameter only if you want to use the HTTPS communication.
 - c. Run the following commands:
 - i. **initializeNPS.ovpl -a StartBIServer**
 - ii. **initializeNPS.ovpl -a SetupCSRolesAndSecurity**
 - iii. **initializeNPS.ovpl -a ConfigBIAccess**
 - iv. **initializeNPS.ovpl -a RestartBIServer**
 - v. **startDB.ovpl**
 - vi. **addSdkUser.ovpl -u npssdkuser**
 - vii. **changeSdkUserPwd.ovpl -u npssdkuser -p HP_NPS**
 - d. Run the following command to complete the upgrade of each Extension Pack:
installExtensionPack.ovpl -x -e <Extension_Pack>.tar.gz
In this instance, *<Extension_Pack>* is the name of the Extension Pack bundle.

Note: To view the names of Extension Pack bundles, run the following command:

about.ovpl

- e. Run the following command if the Path Health Extension Pack was in use with the previous version of NPS:
installPathHealth.ovpl -e Path_Health.tar.gz
- f. Run the following command if you created security groups in NNMI:
installUgSg.ovpl -e ugsg.tar.gz
- g. Run the following command if Custom Poller Extension Packs were in use with the previous version of NPS:
initializeNPS.ovpl -a InitializeCustomCollections

Restoring a Backup Made on a Different System with Different Installation Directories

Backups made on a different system with different installation directories can be restored with some limitations.

- User configurable settings (retention and installed Extension Pack list) are merged into the current settings.
- Other (internal) configuration files are not restored.
- Archived data files are not restored.
- The database and content store are restored.
- All Extension Packs must be installed again to ensure that the reports and database structures are upgraded to the latest version.
- You might have to rerun the `nnmenableperfspi.ovpl` script and Configuration Utility.

Restoring a Backup When Additional Files Were Added to Extend the Database

If the `dbsize.ovpl` utility was used to extend a database by adding additional files to the DBSPACE, the backup will attempt to restore these files to the same directory as the standard database files.

To relocate database files during a restore:

The `-r` option enables you to identify one or more DBFile names and corresponding OS path or file name locations where each should be restored.

When `dbsize.ovpl` is used to add files, the DBFile names used will look like `perfspi_USER_MAIN_<timestamp>`. You can use the `-l` option to determine the files to be included in your backup (for backups made on 9.20 and later).

You can specify a different OS path or file name when restoring by using the `-r` option; for example, `restore.ovpl -b backup.20111027135608.tar.gz -r "perfspi_USER_MAIN_3466235673656=>C:/new_location/perfspi_USER_MAIN_3466235673656.iq"`.

If you backed up the content store using the standard backup utility provided in earlier releases, you will not be able to restore them in the current release. The current database backup format is incompatible with earlier releases.

Post-Restore Steps on Windows

Skip this section if NPS is installed on Linux.

After restoring the NPS data on a new system, you must run the following commands on the NPS system:

Note: Run the commands by logging in as the user that was configured while running the `nnmenableperfspi.ovpl` command.

- **addSdkUser.ovpl -u <user_name>**
- **changeSdkUserPwd.ovpl -u <user_name> -p <password>**

In this instance, `<user_name>` is a user name of your choice and `<password>` is a password that you need to choose for `<user_name>`.

If you do not run the above commands, you will not be able to use the Performance Analysis inventory view and the Interface Health and Component Health dashboards in the NNMi console.

Recreating the NPS Database

You can recreate your Sybase IQ database and start over with the installation default size of 2.5 GB. This feature can be useful if your existing database has grown too large, or if you want to lower your retention settings. Lowering the retention settings will maintain the smaller size of the database for a longer period of time. The `resetNPS.ovpl` utility enables you to delete and recreate the NPS database. When the NPS database becomes irrecoverably corrupt, you can delete and recreate the database.

Modifying Default Settings

Note: If you do not want to modify any settings of the NPS database, skip this section and go to [Recreate the Database](#).

1. Open the `databaseSetup.cfg` file from the following directory:
 - *On Windows:* `%NPSInstallDir%\config`
 - *On Linux:* `$NPSInstallDir/config`
2. Make the following changes:
 - **Cache settings:**
 - To allocate a specific volume to the main cache, specify a value in MB for the `Db.Cfg.Iqmc` property.
For example, to allocate 12 GB for the main cache, specify `Db.Cfg.Iqmc=12288`.

- To allocate a specific volume to the temporary cache, specify a value in MB for the `Db.Cfg.Iqtc` property.
For example, to allocate 12 GB for the temporary cache, specify `Db.Cfg.Iqtc=12288`.

- **Dbospace settings:**

- Number of Dbospace files:
By default, NPS creates 20 Dbospace files. You can configure NPS to create more Dbospace files by appending additional `Db.DbFile` lines under the line `Db.DbFile.020`.

For example:

```
Db.DbFile.021=default
```

```
Db.DbFile.022=default.
```

- Dbospace location:

If you want to store the Dbospace files in a non-default location in a non-default file, you can specify the location by replacing `default` with the complete path to the file.

For example:

```
Db.DbFile.021=C:\Data\user_main_021.iq
```

Note: File name must have the extension `iq`.

3. Save the file.

Recreate the Database

1. Log on to the NPS system as root or administrator. In a distributed deployment of NPS, log on to the DB Server as root or administrator.
2. Take a backup of the NPS database. For more information, see ["To back up the NPS data:" on page 73](#)
3. Open a command line console, and then run the following command:

```
resetSPI.ovpl
```

4. Select the option 2.

This option deletes the database, creates a new database, and then restores the archived data.

After processing, deleting, and recreating the database, the command shows the following message:

```
Do you want to start the ETL service now? (Y/N)
```

5. Type **N**, and then press Enter. The following message appears:

```
Hit Enter key to exit...
```

6. Press **Enter**.

7. Run the **resetSPI.ovpl** command again.

8. Select the option 5.

This option deletes the database (along with the archived data), and then creates a new database.

After processing, deleting, and recreating the database, the command shows the following message:

Hit Enter key to exit...

9. Press **Enter**.
10. Start the ETL process:
startETL.ovpl

Tuning NPS


This chapter describes how to fine-tune different settings for an optimal performance of NPS in a large environment.

Tuning the Business Intelligence Server

The Business Intelligence Server enables you to generate insightful, web-based reports from the data in the database. The performance of the Business Intelligence Server depends on the number of scheduled reports and jobs, number of users trying to launch reports concurrently, and the underlying hardware. You can adjust the values of certain configuration parameters to resolve degrading performance of the Business Intelligence Server (or problems with launching reports) in a very large scale environment. This chapter provides guidelines for adjusting the configuration parameters to address performance issues.

Common symptoms of performance problems with the Business Intelligence Server are:

- Report takes a very long time to appear; the *Select a delivery method* prompt remains visible for a very long time.



- The NPS console shows a blank page instead of the report
- Error messages appear in the `Cognos.log` file (available in `%npsdatadir%\logs` on Windows, in `/var/opt/NNMPerformanceSPI/logs` on Linux)

Tip: In a distributed deployment of NPS, the UiBi Server hosts the Business Intelligence Server component.

Monitoring the Performance of the Business Intelligence Server

You can monitor the performance of the Business Intelligence Server with the help of performance monitoring tools provided by the operating system.

On Windows, you can use the Windows task manager and any Windows I/O benchmarking tools.

On Linux, you can use the `iostat` and `top` commands.

You can also detect performance problems with the help of the BI Portal. Follow these steps:

1. Log on to the NNMi console as administrator.
2. Click **Actions > NNM iSPI Performance > Reporting - Report Menu**. The NPS console opens.
3. In the NPS console, click the **BI Server** workspace in the navigation pane.
4. Click **Administration**. The BI Server Administration page opens.
5. In the BI Server Administration page, select **Interactive activities** in the Filter section, and then click **Apply**. The right pane displays the number of reports that are currently running.
6. Select **Background activities** in the Filter section, and then click **Apply**. The right pane displays the following details:
 - Number of reports that are running in the background (Executing)
 - Number of reports that are waiting to be run (Waiting)
 - Number of pending reports (Pending)
 - Number of suspended reports (Suspended)

Too many pending and waiting reports lead to poor performance of the Business Intelligence Server.

You can also check the `Cognos.log` file (available in `%npsdatadir%\logs` on Windows, in `/var/opt/NNMPerformanceSPI/logs` on Linux) for errors. The following error messages in the `Cognos.log` file indicate performance problems:

- `http-9300-55 caf 2047 1 Audit.dispatcher.caf Request Failure SecureErrorId: <date>-<time>.646-#44 Original Error: DPR-ERR-2002 Unable to execute the request because there were no connections to the process available within the configured time limit`

This error indicates that the system has too many reports currently in progress.

To avoid this error, follow the steps in the [Configuring Business Intelligence Server Settings](#) section.

- `-567911568 QOS 5000 1 Audit.RTUsage.QOS <message code="-232" severity="error" title="QE-DEF-0459 CCLException" type="general">RQP-DEF-0177 An error occurred while performing operation 'sqlScrollBulkFetch'; status='-'-232';. UDA-SQL-0107`

This error indicates that NPS received an error from the underlying database.

To avoid this error, limit the number of very large-scale reports over long time periods with very fine granularity.

Best Practices

- For frequently used reports, use Report Views. See the *Using Report Views* section in *Online Help*.
- You can also schedule frequently used reports. Do not schedule high-frequency schedules for reports that are viewed rarely.
- Reports that run with very long time ranges tend to be slow and put greater load onto the database. Consider using reports with short time ranges whenever possible.

- Reports that run with very fine time grains require excess resources from NPS while creating chart images or HTML table structures with drillthrough links. Consider using fewer reports that run with very fine time grains to speed up report runs and reduce the load.

Configuring Business Intelligence Server Settings

You can adjust the values of certain configuration parameters to resolve some performance problems. The changes outlined below enable the Business Intelligence Server to process more interactive report requests in parallel. This will place a larger load on the database server, but may be appropriate for a distributed deployment of NPS with multiple users all requesting reports simultaneously.

1. Log on to the NNMi console as administrator.
2. Click **Actions > NNM iSPI Performance > Reporting - Report Menu**. The NPS console opens.
3. In the NPS console, click the **BI Server** workspace in the navigation pane.
4. Click **Administration**. The BI Server Administration page opens.
5. In the BI Server Administration page, go to the Configuration tab.
6. In the left pane, click **Dispatchers and Services**.
7. Click the dispatcher on the Configuration page.

Tip: You may see multiple dispatchers on this page if you used the `configureWebAccess.ovpl` command to change the default communication port of NPS. On the Configuration page, each dispatcher appears in the following format:


`<hostname> : <port>/p2pd`

In this instance, `<hostname>` is the hostname of the NPS system; `<port>` is the communication port for NPS.

When you see multiple dispatchers, choose the active dispatcher that runs with the current NPS port.

8. Modify the `BatchReportService` parameters by following these steps:
 - a. In the list of services, locate `BatchReportService`.




- b. Against `BatchReportService`, click .
- c. Go to the Settings tab.
- d. You can modify the following properties:


Property	Default	Suggested Maximum Value
Number of high affinity connections for the batch report service during non-peak period	2	2

Property	Default	Suggested Maximum Value
Number of low affinity connections for the batch report service during non-peak period	4	10
Maximum number of processes for the batch report service during non-peak period	2	10
Number of high affinity connections for the batch report service during peak period	2	2
Number of low affinity connections for the batch service during peak period	4	10
Maximum number of processes for the batch report service during peak period	2	10

9. Modify the ReportService parameters by following these steps:
 - a. In the list of services, locate ReportService.



Tip: If you are unable to locate ReportService, click  **Next Page**.

- b. Against ReportService, click .
 - c. Go to the Settings tab.
 - d. You can modify the following properties:

Property	Default	Suggested Maximum Value
Number of high affinity connections for the report service during non-peak period	2	10
Number of low affinity connections for the report service during non-peak period	8	10
Maximum number of processes for the report service during non-peak period	2	10
Number of high affinity connections for the report service during peak period	2	10
Number of low affinity connections for the report service during peak period	8	10

Property	Default	Suggested Maximum Value
Maximum number of processes for the report service during peak period	2	10

- Click **OK**. Changes take effect immediately.

Resolving Problems with Jobs and Report Scheduling

To resolve problems with jobs and report scheduling, modify the `max_online_engines` parameter. If you see problems like scheduled reports failing to run or configured jobs not appearing in the navigation panel, follow these steps:

- Log on to the NPS system (the UiBi Server in case of a distributed deployment of NPS).
- Open the following file with a text editor:
 - On Windows:*
 - `%npsinstalldir%\nonOV\sybasease\ASE-15_0\ASECONTENTSERVER.cfg`
 - On Linux:*
 - `/opt/OV/nonOV/sybasease/ASE-15_0/ASECONTENTSERVER.cfg`
- Set the value of the `max_online_engines` property to an integer (recommended value is 2 for a standalone NPS; set it to a value higher than 2 in a distributed deployment of NPS).
- If you see the error message `CM-SYS-5025 Content Manager cannot update an object in the Cognos.log` file (available in `%npsdatadir%\logs` on Windows, in `/var/opt/NNMPerformanceSPI/logs` on Linux), set the `procedure_cache_size` property to a higher value.
- Run the following commands:
 - stopCS.ovpl**
 - startCS.ovpl**

Tuning the NPS Database

The NPS database stores the data used for building reports. The performance of the database depends on the database configuration, volume of data stored in the database, the number of scheduled reports and jobs, number of users trying to launch reports concurrently, and the underlying hardware.

In a very large scale environment, you can adjust the values of certain configuration parameters to resolve degrading performance. This chapter provides guidelines for adjusting the configuration parameters to address performance issues.

You can configure the `perfspi.cfg` file to modify the NPS database to use non-default values for the main and temporary cache of the database.

To change the default cache size, follow these steps:

1. Log on to the NPS system as root or administrator. In a distributed deployment of NPS, log on to the DB Server as root or administrator.
2. Go to the following directory:
On Windows:
`%npsdatadir%\database`
On Linux:
`$NPSDataDir/database`
3. Open the `perfspi.cfg` file with a text editor.
4. Specify the temporary cache size (in MB) against the `-iqtc` property.
5. Specify the main cache size (in MB) against the `-iqmc` property.
6. Save the file.
7. Run the following commands to restart the database:
 - a. **stopDB.ovpl**
 - b. **startDB.ovpl**

Log Files

NPS creates the following log files in the logs directory:

Note: The log directory is located in:

On Windows

%npsdatadir%\NNMPerformanceSPI

On Linux

/var/opt/OV/NNMPerformanceSPI/

Log Files

File Name	Description
prspi.log	Contains all operational details of NPS.
perfspi.srv.log	Contains all operational details of the Sybase IQ database used by NPS. This file can grow up to 512 MB.
perfspi.iqmsg	Sybase IQ messages file. This file can grow up to 512 MB.
dbproxy.log	Records all database queries triggered by NPS.
perfspiUI.log	Log file created and updated by the Business Intelligence Server and content store.

Part V: Using Certificate Authority

NPS 10.10 enables you to use certificates signed by a third-party certificate authority (CA). By using a third-party certificate authority, you can ensure secure communication between the NPS system and the browser used to access different parts of the NPS console.

To configure NPS to use a third-party CA:

1. [Enable the HTTPS Mode](#)
2. [Generate the Third-Party CA Certificate](#)
3. [Import the Third-Party CA Certificate](#)

Task 1: Enable the HTTPS Mode

If you select the HTTPS mode of communication while running the `nnmenableperfspi.ovpl` script on the NNMI management server, NPS starts running in the HTTPS mode after the installation is complete. In that case, you need not perform this task.

If did not select the HTTPS mode of communication while running the `nnmenableperfspi.ovpl` script, follow these steps:

Note: In a distributed deployment of NPS, perform this task on the UiBi Server.

1. Log on to the NPS system as administrator or root.
2. Run the following command:
 - *On Windows:* `%ovinstalldir%\NNMPerformanceSPI\bin\configureWebAccess.ovpl`
 - *On Linux:* `/opt/OV/NNMPerformanceSPI/bin/configureWebAccess.ovpl`
3. Restart the Business Intelligence Server by running the following commands:
 - On Windows:*
 - a. `%ovinstalldir%\NNMPerformanceSPI\bin\stopBI.ovpl`
 - b. `%ovinstalldir%\NNMPerformanceSPI\bin\startBI.ovpl`
 - On Linux:*
 - a. `/opt/OV/NNMPerformanceSPI/bin/stopBI.ovpl`
 - b. `/opt/OV/NNMPerformanceSPI/bin/startBI.ovpl`

Task 2: Generate the Third-Party CA Certificate

To generate the third-party CA certificate, follow these steps:

Note: In a distributed deployment of NPS, perform this task on the UiBi Server.

1. Log on to the NPS system as administrator or root.
2. Run the following command:

- *On Windows:* %ovinstalldir%\NNMPerformanceSPI\bin\runBIConfigGUI.ovpl
- *On Linux:* /opt/OV/NNMPerformanceSPI/bin/runBIConfigGUI.ovpl

The HP NNM iSPI Performance BI Configuration window opens.

3. In the Explorer pane, click **Security > Cryptography > Cognos**.
4. In the right pane, under the Signing Key Settings section, change the Signing key store password.
Note down this new password.
5. In the right pane, under the Encryption Key Settings section, change the Encryption key store password.
Note down this new password.
6. Close the HP NNM iSPI Performance BI Configuration window.
7. Go to the following directory:
 - *On Windows:* %ovinstalldir%\nonOV\conos\bi\configuration
 - *On Linux:* /opt/OV/nonOV/cognos/bi/configuration
8. Take a backup of the following files and directories:
 - cogstartup.xml
 - encryptkeypair/
 - signkeypair/
9. Set the JAVA_HOME environment variable to the following directory:
 - *On Windows:* %ovinstalldir%\nonOV\jdk\hpsw
 - *On Linux:* /opt/OV/nonOV/jdk/hpsw
10. Go to the following directory:
 - *On Windows:* %ovinstalldir%\nonOV\conos\bi\bin
 - *On Linux:* /opt/OV/nonOV/cognos/bi/bin
11. Run the following commands:
 - *On Windows:*
 - **ThirdPartyCertificateTool.bat -c -s -d "CN=<NPS_FQDN>,O=<org name>,C=<Country>" -r signRequest.csr -D ../configuration/signkeypair -p <password_sign>**
 - **ThirdPartyCertificateTool.bat -c -e -d "CN=<NPS_FQDN>,O=<org name>,C=<Country>" -r encryptRequest.csr -D ../configuration/encryptkeypair -p <password_encrypt>**
 - *On Linux:*
 - **./ThirdPartyCertificateTool.sh -c -s -d "CN=<NPS_FQDN>,O=<org name>,C=<Country>" -r signRequest.csr -D ../configuration/signkeypair -p**

<password_sign>

- `./ThirdPartyCertificateTool.sh -c -e -d "CN=<NPS_FQDN>,O=<org name>,C=<Country>" -r encryptRequest.csr -D ../configuration/encryptkeypair -p <password_encrypt>`

In this instance, <password_sign> is the password that you assigned in [step 4](#); <password_encrypt> is the password that you assigned in [step 5](#); <NPS_FQDN> is the fully qualified domain name of the NPS system.

The above commands create the `signRequest.csr` and `encryptRequest.csr` files. Use these `.csr` files to obtain corresponding `signRequest.cer` and `encryptRequest.cer` files and the root certificate (`ca.cer`) from the third-party signing authority.

Task 3: Import the Third-Party CA Certificate

To import the third-party CA certificate into the Business Intelligence Server of NPS, follow these steps:

Note: In a distributed deployment of NPS, perform this task on the UiBi Server.

1. Log on to the NPS system as administrator or root.
2. Go to the following directory:
 - *On Windows:* `%ovinstalldir%\nonOV\conos\bi\bin`
 - *On Linux:* `/opt/OV/nonOV/cognos/bi/bin`
3. Place the `signRequest.cer`, `encryptRequest.cer`, and `ca.cer` files (created in the previous [task](#)) in this directory.
4. Rename the `signRequest.cer` and `encryptRequest.cer` files to `signCertificate.cer` and `encryptCertificate.cer`.
5. Run the following commands:
 - *On Windows:*
 - `ThirdPartyCertificateTool.bat -i -s -r signCertificate.cer -D ../configuration/signkeypair -p <password_sign> -t ca.cer`
 - `ThirdPartyCertificateTool.bat -i -e -r encryptCertificate.cer -D ../configuration/encryptkeypair -p <password_encrypt> -t ca.cer`
 - `ThirdPartyCertificateTool.bat -i -T -r ca.cer -D ../configuration/signkeypair -p <password_ca>`
 - *On Linux:*
 - `./ThirdPartyCertificateTool.sh -i -s -r signCertificate.cer -D ../configuration/signkeypair -p <password_sign> -t ca.cer`
 - `./ThirdPartyCertificateTool.sh -i -e -r encryptCertificate.cer -D ../configuration/encryptkeypair -p <password_encrypt> -t ca.cer`
 - `./ThirdPartyCertificateTool.sh -i -T -r ca.cer -D ../configuration/signkeypair -p NoPassWordSet`

In this instance, `<password_sign>` is the password that you assigned in [step 4](#); `<password_encrypt>` is the password that you assigned in [step 5](#).

6. Go to the following directory:

- *On Windows:* `%ovinstalldir%\nonOV\conos\bi\configuration`
- *On Linux:* `/opt/OV/nonOV/cognos/bi/configuration`

7. Undo the JAVA_HOME variable configuration that was set in [step 9](#).

8. Open the `cogstartup.xml` file with a text editor and make sure that the `crn:parameter` element contains the following content:

```
<crn:parameter name="thirdPartyCA">  
  <crn:value xsi:type="xsd:boolean">true</crn:value>  
</crn:parameter>
```

9. Restart the Business Intelligence Server by running the following commands:

On Windows:

- a. `%ovinstalldir%\NNMPerformanceSPI\bin\stopBI.ovpl`
- b. `%ovinstalldir%\NNMPerformanceSPI\bin\startBI.ovpl`

On Linux:

- a. `/opt/OV/NNMPerformanceSPI/bin/stopBI.ovpl`
- b. `/opt/OV/NNMPerformanceSPI/bin/startBI.ovpl`

Part VI: Troubleshooting

- **Problem:** Installation of the Cross Domain Extension Pack fails in a distributed deployment of NPS. The following error message appears in the installation log file:

```
WARN: Failed command system("<Install_Dir>/nonOV/perl/a/bin/perl" -I"<Install_Dir>/NNMPerformanceSPI/lib/perllibs/lib" "<Install_Dir>/NNMPerformanceSPI/bin/mkCrossDomainExtensionPack.ovpl"): 3
```

Solution: Install the Cross Domain Extension Pack manually with the help of the following command:

mkCrossDomainExtensionPack.ovpl.

To double the temporary dbspace, follow these steps:

- a. Log on to the NPS system that has the DB Server role assigned.
- b. Run the following command:

dbsize.ovpl -d IQ_SYSTEM_TEMP

- **Problem:** When you try to launch a report, the following error message appears in the reports pane of the NPS console:

```
An error occurred while performing operation 'sqlScrollBulkFetch' status = '232'.
```

Cause: If the temporary dbspace of the Sybase IQ database runs out of space, this error message appears.

Solution: Increase the temporary dbspace.

To double the temporary dbspace, follow these steps:

- a. Log on to the NPS system that has the DB Server role assigned.
- b. Run the following command:

dbsize.ovpl -d IQ_SYSTEM_TEMP

- **Problem:** When you try to launch a report, the following error message appears in the reports pane of the NPS console:

```
Unable to execute the request because there were no connections to the process available within the configured time limit.
```

Cause: If the actual number of concurrent users exceeds the maximum number of users specified in the `perfspi.cfg` file, this error appears.

Solution: Increase the maximum number of users in the `perfspi.cfg` file.

Follow these steps:

- a. Log on to the NPS system that has the DB Server role assigned.
- b. Go to the following directory:

On Windows

```
%NPSDataDir%\NNMPerformanceSPI/database
```

On Linux

```
/var/opt/OV/NNMPerformanceSPI/database
```

- c. Open the `perfspi.cfg` file with a text editor.
- d. Change the value of the `-gm` parameter from 100 to 200.
- e. Restart the database processes:
 - i. **stopDB.ovpl**
 - ii. **startDB.ovpl**

Send Documentation Feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this system, click the link above and an email window opens with the following information in the subject line:

Feedback on Deployment Reference (Network Node Manager iSPI Performance for Metrics Software 10.10)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to network-management-doc-feedback@hpe.com.

We appreciate your feedback!