



HP Integration Bridge

Software Version: 1.05

Installation Guide for Windows

Document Release Date: February 2016
Software Release Date: February 2016

Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

All third party code is managed by HP Software, and is available upon request.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notice

© Copyright 2012-2016 Hewlett-Packard Development Company, L.P.

Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<https://softwaresupport.hp.com>.

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to

<https://softwaresupport.hp.com> and click **Register**.

Support

Visit the HP Software Support Online web site at: <https://softwaresupport.hp.com>

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to: <https://softwaresupport.hp.com> and click **Register**.

To find more information about access levels, go to: <https://softwaresupport.hp.com/web/softwaresupport/access-levels>.

HP Software Solutions & Integrations and Best Practices

Visit **HP Software Solutions Now** at <https://softwaresupport.hp.com/group/softwaresupport/search-result/-/facetsearch/document/KM01702710> to explore how the products in the HP Software catalog work together, exchange information, and solve business needs.

Visit the **Cross Portfolio Best Practices Library** at <https://hpln.hp.com/group/best-practices-hpsw> to access a wide variety of best practice documents and materials.

About this PDF Version of Online Help

This document is a PDF version of the online help. This PDF file is provided so you can easily print multiple topics from the help information or read the online help in PDF format. Because this content was originally created to be viewed as online help in a web browser, some topics may not be formatted properly. Some interactive topics may not be present in this PDF version. Those topics can be successfully printed from within the online help.

Contents

HP Integration Bridge overview	5
Download and install the bridge	7
Installing multiple bridges	10
Integration Bridge security	12
Manage connection setup	15
Endpoint Credentials Manager	15
Set ALM credentials (Endpoint Credentials Manager)	15
Set ALM credentials (CLI)	16
Configure a proxy for ALM connections	23
Set Agile Manager credentials	24
Configure a proxy for Agile Manager connections	25
NextGen Synchronizer proxy support	27
Start and stop the Integration Bridge	28
Uninstall/Remove the Integration Bridge	30
To uninstall a bridge permanently	30
To uninstall a bridge in order to upgrade or move it	31
Upgrade the Integration Bridge	33
Integration Bridge troubleshooting	36
Send Us Feedback	39

HP Integration Bridge overview

The HP Integration Bridge is a software component installed on the customer system to mediate between Agile Manager and on-premise applications located behind firewalls, such as HP ALM, enabling two-way communication between the two.

When you install the Integration Bridge, you install both an Integration Bridge application, and a Windows service that manages the application. The service makes sure that the Integration Bridge is automatically started when your system starts.

Integration Bridge system requirements

Verify that your system has the following minimum system requirements to install the Integration Bridge:

Operating system	One of the following: <ul style="list-style-type: none">• Windows Server 2008 R2 SP1 64-bit• Windows Server 2012 R2 SP1 64-bit
Memory	8 GB
Free disk space	80 GB

Note:

- The Integration Bridge must be installed to a path named only with ASCII characters.
- The installation includes the Integration Bridge application, and the corresponding Windows service.

Integration Bridge tasks

To start using NextGen Synchronizer, download and install the Integration Bridge, and then define credentials for connecting to ALM.

For details, see:

- ["Download and install the bridge" on page 7](#)
- ["Manage connection setup" on page 15](#)

Continue by creating synchronization links in Agile Manager. For details, see the Agile Manager Help Center (**Help > Help on This Page**).

See the following maintenance topics as needed.

- ["Integration Bridge security" on page 12](#)
- ["Start and stop the Integration Bridge" on page 28](#)
- ["Uninstall/Remove the Integration Bridge" on page 30](#)
- ["Integration Bridge troubleshooting" on page 36](#)

Download and install the bridge

Download the Integration Bridge from Agile Manager and install it on a computer that can access both Agile Manager and ALM. The bridge communicates with both applications, enabling data synchronization between the two.

See also ["Installing multiple bridges" on page 10](#).

Install the bridge as a Windows administrator user. You can run the bridge as a non-administrator user with the relevant permissions.

For more detail, see ["Security recommendations" on page 13](#).

Prerequisites


- Make sure that you are assigned to the **Integration Administrator** role (**Site > Users** or **Workspace > Users** configuration page).
- Obtain a client ID and secret to enter during the Integration Bridge installation. The bridge uses these credentials to access Agile Manager.

On the **Integrations > API** configuration page, add an Integration Bridge client. For details, see the *Agile Manager User Guide*.

Note: This step must be performed by a Site Administrator.

Agile Manager generates a **client ID** and **secret** for the bridge.

Download the bridge from Agile Manager

Click **Configuration**  on the top right of the page, and select **Integrations** from the navigation menu on the left.

Tab: Integrations > Synchronizer. This tab is visible to **Integration Administrators** only.



Tip: If you have just assigned yourself to the Integration Administrator role, you do not need to log out and log in again. Simply refresh your browser window to access the **Integrations** configuration area.

On the **Integrations > Synchronizer** configuration page, do one of the following:

Installation	Instruction
If this is the first time you are installing the bridge	In the checklist, click the link in the second step to download the bridge, according to your operating system.

Installation	Instruction
If you are installing an additional bridge or performing an upgrade	Select More Actions > Download Integration Bridge > Windows

Install the Integration Bridge

1. On the computer where you want to install the bridge, extract the downloaded zip file (**hp-integration-bridge-windows.zip**). You must extract this zip file to a path named only with English characters.

The zip file contains the following:



- The installation executable file.
 - A configuration file (**server-connection.conf**) containing the URL and site ID that the bridge will use to connect to Agile Manager.
 - The HP Integration Bridge Installation Guide, in which you can find installation instructions and more.
2. Run the **hp-integration-bridge.exe** file to begin the installation. When the wizard opens, click **OK** to get started.
 3. Follow the instructions in the installation process to complete the installation.

When provided, accept the default values, which are configured to connect to your workspace.

Note:

- The Integration Bridge must be installed to a path named only with ASCII characters, and must not contain consecutive spaces.
- If you select the **Modify an Existing Instance** option, the bridge you select is uninstalled. After uninstalling, run the installation again to install a new instance.

- In the **Setup connection** step for configuring the connection to Agile Manager:

Settings	Description
Bridge name	Define a name for the bridge.
URL	<p>The URL of your Agile Manager site.</p> <p>Format: http(s)://<hostname or IP address>:<port number>/agm</p> <p>This URL will be used in email notifications, such as to Integration Administrators and when creating URL attachments in ALM.</p> <div data-bbox="574 646 1378 772" style="border: 1px solid #ccc; background-color: #e6f2e6; padding: 5px;">  Tip: We recommend ensuring that this URL is accessible to email recipients and from the ALM client. </div> <p>By default, this URL is provided for you, from the downloaded server-connection.conf file.</p> <div data-bbox="574 890 1378 1016" style="border: 1px solid #ccc; background-color: #ffe0b2; padding: 5px;">  Caution: If you modify this URL, make sure not to end it with a slash ('/'). </div> <p>It is stored in the <HP Integration Bridge installation folder>\product\conf folder.</p>
Site ID (Read only)	<p>The site ID of the Agile Manager site.</p> <p>You can find the site ID in your Agile Manager's URL, in the tenant ID attribute. For example: TENANTID=123456789.</p> <p>This is also stored in the server-connection.conf file.</p>
Client ID and Client Secret fields	<p>The client ID and secret that Agile Manager generated on the Integration > API page.</p> <p>If you need to modify these credentials later on, see "Set Agile Manager credentials" on page 24.</p>
Proxy server	<p>If you will be using a proxy server to access Agile Manager, select Use proxy server.</p> <p>Enter details for the proxy server and the user who will be logging into the proxy server:</p> <ul style="list-style-type: none"> ○ Host. A valid address for the proxy server. ○ Port. A valid port number (integer, between 1-65535) <p>For details about modifying the proxy credentials later, see "Configure a proxy for Agile Manager connections" on page 25.</p>



Tip:

You can click **Test Connection** to verify that the bridge can connect to Agile Manager.

After you enter this information, the connection to Agile Manager is tested. If the test fails, you can reenter the connection settings or continue the bridge installation and modify the credentials later.

- In the **Setup service** step for configuring the HP Integration Bridge service, accept the default service name and port number, or modify as needed.



Tip: If you install multiple bridges, use a name that will help you associate the service with the corresponding bridge.

4. When the installation is finished, the **Installation complete** message is displayed. Press **ENTER** to quit the installer.
5. The Endpoint Credentials Manager application opens automatically. Define credentials for connecting to ALM, as described in "[Manage connection setup](#)" on page 15.



Note: You must configure ALM credentials before you configure your links.

If the credentials manager does not open automatically, you can open it manually or configure the credentials using the CLI. For details, see "[Manage connection setup](#)" on page 15.

In Agile Manager, the new bridge is identified within a few moments. If you do not see your new bridge, refresh the page. From there, click **Create synchronization links** to start creating your links.

Installing multiple bridges

Installing multiple bridges is necessary only in certain cases. For example:

- If you need to synchronize Agile Manager with ALM projects that reside on different networks.
- If you define a large number of synchronization links and you want to distribute the load between multiple bridges.
- If you install bridges for multiple Agile Manager sites. Each bridge communicates with one site.

In this case, you must download each bridge separately, from the site with which it will communicate. The downloaded files contain the configuration necessary for the bridge to connect to the relevant site.

Recommendations if you install multiple bridges:

- Use a separate set of Agile Manager credentials (client ID and secret) for each bridge.
- Instead of using the default installation folder, provide a name that helps identify the bridge. For example, if you install multiple bridges to communicate with multiple Agile Manager sites, include the site name in the installation folder name.

Integration Bridge security

The Integration Bridge does not expose any internal information. Additionally, HP application JAR files are signed by HP, helping to validate the code's origin.

This topic includes:

- ["Communication with Agile Manager using OAuth authentication" below](#)
- ["Communication via SSL" below](#)
- ["Connections using a certificate that is not signed by a well-known Certificate Authority" below](#)
- ["Password encryption" on the next page](#)
- ["Security recommendations" on the next page](#)
- ["Integration Bridge automatic upgrades" on page 14](#)

Communication with Agile Manager using OAuth authentication

The Integration Bridge can use OAuth authentication when connecting to Agile Manager, instead of using the credentials of an Agile Manager user.

All new Integration Bridge installations use OAuth authentication.

Existing bridges upgraded to version 1.03 or later continue to use Agile Manager user credentials until the password expires or until you manually update the bridge to use OAuth.

For details, see "Synchronizer Integration Bridge: New way to connect to Agile Manager", in the What's New section of the *Agile Manager User Guide*.

Communication via SSL

Communication between the Integration Bridge and Agile Manager is secured by SSL.

The bridge logs in to Agile Manager using the Agile Manager user credentials or client ID and secret provided during installation, or later as described in ["Set Agile Manager credentials" on page 24](#).

Connections using a certificate that is not signed by a well-known Certificate Authority

If you connect to a secured ALM server using a certificate that is not signed by a well-known Certificate Authority, you must establish trust for the certificate.

To establish this trust, import the issuer's certificate to the JRE's truststore in the following directory:

<Integration Bridge installation directory>\product\util\3rd-party\jre1.7.0_51\jre\lib\security

Do the following:

1. With Agile Manager or ALM open in your browser window, export the certificate from the browser, and save it to a file named **server.cer**.
2. On the Integration Bridge machine, place the **server.cer** file in the **<Integration Bridge installation>\product\util\3rd-party\jre1.7.0_51\jre\bin** directory.
3. Use the keytool command from the **<Integration Bridge installation>\product\util\3rd-party\jre1.7.0_51\jre\bin** directory to import the **server.cer** file to the **<Integration Bridge installation>\product\util\3rd-party\jre1.7.0_51\jre\lib\security\cacerts** directory.

For example:

```
keytool.exe -import -v -trustcacerts -alias <alias>  
-file server.cer -storepass <password> -keystore <Integration Bridge  
installation>\product\util\3rd-party\jre1.7.0_51\jre\lib\security\cacerts
```

Note: You may need to repeat this command for the rest of the certificate chain, using a different alias each time.

4. Restart the Integration Bridge.


Password encryption

Passwords for connecting to endpoints are encrypted and saved on the customer's machine, preventing credentials from being transferred to another machine.

The encryption method uses keys that are randomly generated during installation. The bridge uses AES 128 as the main encryption method.

Security recommendations

Security recommendations	
Download sources	Do not download the Integration Bridge installation file or updates from unknown sources.
Integration Bridge machine	Install the Integration Bridge on a dedicated, hardened machine.

Security recommendations	
Integration Bridge network	<p>Deploy the Integration Bridge in an isolated network, with a firewall between the bridge and the target on-premise application.</p> <ul style="list-style-type: none"> • Port 443 must be open for communication with Agile Manager. • Additional ports may be required to be opened for internal communications with other on-premise applications.
Integration Bridge permissions	<p>By default, the Integration Bridge service runs using the Windows Local System service user.</p> <p>To increase system security, assign a simple Windows user to run the Integration Bridge.</p> <ul style="list-style-type: none"> • Install the Integration Bridge in a folder other than the Program Files folder. This will enable you to grant the simple user permissions on the Integration Bridge installation folder. • Grant the user full permissions (Read/Write/Execute) on the installation folder. • Grant the user permissions to manage the Integration Bridge Windows service. • Open the Windows Service Manager, modify the HP Integration Bridge service to run using the simple user's account and then restart the service. <div style="border: 1px solid #ccc; background-color: #e6f2ff; padding: 5px; margin-top: 10px;">  <p>Tip: You can protect the Integration Bridge installation folder by granting permissions to that folder only to administrators, the Local System service user, and the dedicated user you created.</p> </div>
Installing multiple Integration Bridges	<p>If you install multiple bridges, we recommend that you use a separate set of Agile Manager credentials (client ID and secret) for each bridge.</p>
Integration Bridge user	<p>The Agile Manager user with the Integration Bridge role should not have any other additional roles.</p>
On-premise application users	<p>When defining permissions for users of on-premise applications that communicate with Agile Manager, such as ALM users, limit permissions to specifically required operations only.</p>

Integration Bridge automatic upgrades

When a new version of the Integration Bridge is available, it is automatically downloaded from Agile Manager. The HP signature on the downloaded file is verified before the new version is installed.

Manage connection setup

Credentials are used to provide secure, two-way communication between the Integration Bridge and Agile Manager or ALM.

Endpoint Credentials Manager

The Endpoint Credentials Manager application opens automatically after installing the Integration Bridge. This application is used to manage ALM credentials.

Note:

You must set ALM credentials before synchronizing entities between Agile Manager and ALM, and modify them later on if these credentials change.

If the Endpoint Credentials Manager application does not open automatically, or if you need to modify credentials again later, open the application manually. The Endpoint Credentials Manager is installed together with the Integration Bridge.

This section includes the following:

Set ALM credentials (Endpoint Credentials Manager)

Perform this procedure as a user with permissions to run the Integration Bridge.

If you are working on a Linux machine that does not support GUI, set the ALM credentials using the Command Line Interface (CLI).

1. On the Integration Bridge machine, open the Endpoint Credentials Manager application as described above.
2. Click *** New** to create a set of credentials.
3. Enter the credentials on the right, and then click **Save** .

Field	Description
Display name	The name used to identify this particular credentials record when configuring a link in Agile Manager.
User	The name of the user connecting to ALM.
Password	The password used to connect to ALM.
Confirm password	Enter the password a second time to confirm it.

Credentials are encrypted and stored on your system in the **credentialsStore.xml** and **bridgeCredentialStore.xml** files, located in the **<Bridge_installation_directory>\product\conf** folder.

- To update a credential record, select it and make your changes on the right. Then click **Save**.
- To delete a credential record, select it, and click **Delete**.

Connecting to ALM using SiteMinder single sign-on (SSO)

If the Integration Bridge needs to connect to ALM using SiteMinder single sign-on (SSO):

- Configure SiteMinder to support basic authentication.
- You may need to change the CSSChecking parameter in the SiteMinder settings to allow the characters **>**, **<**, and **'** in URLs. Otherwise, SiteMinder may reject communication messages sent by NextGen Synchronizer and synchronizations may fail.

See also: "[Integration Bridge security](#)" on page 12.

Set ALM credentials (CLI)

Use the **credentials_mng_console** command line tool to set the credentials used to connect to ALM.

You must set ALM credentials before synchronizing entities between Agile Manager and ALM, and later on if these credentials change.

Note: Alternatively, set ALM credentials using the Endpoint Credentials Manager. For details, see "[Manage connection setup](#)" on the previous page.

To open the **credentials_mng_console** command line tool:

1. Open the **<Bridge_installation_directory>\product\util\opb** directory.
2. Run the **credentials_mng_console.bat** file.

The **credentials_mng_console** tool supports the following commands:

"list"	"listEndpointTypes"	"listCredentialIds"
"listEndpointTypeParams"	"create"	"update"
"delete"	"help"	

list

Lists available credential records for connecting to ALM from the Integration Bridge.

Usage

```
credentials_mng_console.bat list -endpoint <ENDPOINT TYPE>
```

Parameters

-endpoint <ENDPOINT TYPE>	Endpoint type name, such as an ALM version (optional). This type name must be a value available in the "listEndpointTypes" command.
--	---

Sample Results

```
=====
Endpoint type : sample-endpoint-type-11.5
ID : 9460b7
Name : sample credentials record
User : sample username
Password : *****
Parameters :
Key | Value
-----
sample.secret.property | *****
sample.url.property | 123
```

listEndpointTypes

Lists available ALM endpoint types accessible to the Integration Bridge, such as ALM versions. You can filter the endpoints by type name.

Usage

```
credentials_mng_console.bat listEndpointTypes -endpoint <ENDPOINT TYPE>
```

Parameters

-endpoint <ENDPOINT TYPE>	Endpoint type name (optional)
---------------------------	-------------------------------

Sample Results

```
Endpoint types :  
1. alm
```

listCredentialIds

Lists all ALM credential record IDs and the ALM endpoint type related to each credential ID.

Usage

```
credentials_mng_console.bat listCredentialIds -endpoint <ENDPOINT TYPE>
```

Parameters

-endpoint <ENDPOINT TYPE>	Endpoint type name, such as the ALM version (optional). This type name must be a value available in the "listEndpointTypes" command.
---------------------------	---

Sample Results

```
Endpoint type : alm-11.5  
Name | ID :  
1. sample credentials record name | 11e7  
=====
```

```
Endpoint type : sample-endpoint-type-11.5  
Name | ID :  
1. sample credentials record name | 21e0
```

```
2. sample credentials record #2 name | 7e0
Endpoint type : alm-11.5
Name | ID :
1. sample credentials record name | 11e7
=====
Endpoint type : sample-endpoint-type-11.5
Name | ID :
1. sample credentials record name | 21e0
2. sample credentials record #2 name | 7e0
```

listEndpointTypeParams

Lists the specific parameters required for saving credentials for each ALM endpoint type.

Usage

```
credentials_mng_console.bat listEndpointTypeParams -endpoint <ENDPOINT TYPE>
```

Parameters

-endpoint <ENDPOINT TYPE>	Endpoint type name, such as an ALM version (optional). This type name must be a value available in the "listEndpointTypes" command.
--	--

Sample Results

```
=====
Endpoint type   : sample-endpoint-type-11.5
Output format:
Parameter:
Label:
Description:
Mandatory:
-----
Endpoint type specific parameters:
Parameter: sample.url.property
```

```
Label: Server URL
Description: URL address for sample server
Mandatory: true
Parameter: sample.secret.property
Label: Secret key
Description: Secret key for sample server
Mandatory: false
```

create

Creates a credentials record for accessing ALM from the Integration Bridge.

Usage

```
credentials_mng_console.bat create -file <path to data file> -user <USER> -
pass <PASSWORD> -endpoint <ENDPOINT TYPE> -name <CREDENTIALS RECORD NAME> -
param <KEY> <VALUE> -param <KEY> <VALUE>
```

Usage example - generic

```
credentials_mng_console.bat create -user <USER> -pass <PASSWORD> -endpoint
sample-endpoint-type-11.5 -name <CREDENTIALS NAME> -param sample.url.property
<PARAMETER_VALUE> -param sample.url.property <PARAMETER_VALUE>
```

Usage example - ALM specific

```
credentials_mng_console.bat create -user <USER> -pass <PASSWORD> -endpoint
alm-11.5 -name <CREDENTIALS NAME>
```

Parameters

<code>-file <FILE></code>	Read parameters from the property file (optional). Parameters will be overwritten if they are specified in the console.
<code>-user <USER></code>	User name
<code>-pass <PASSWORD></code>	Password
<code>-endpoint <ENDPOINT TYPE></code>	Endpoint type name, such as an ALM version. This type name must be a value available in the "listEndpointTypes" command.

<code>-name <CREDENTIALS NAME></code>	Credentials record name
<code>-param <KEY> <VALUE></code>	Custom parameters (optional)
<code>-replace</code>	Replace all existing parameters with input parameters (optional)

The property file is a text file that describes the credential's properties. The file format is:

```
endpoint=<ENDPOINT TYPE>
name=<NAME>
user=<USER>
pass=<PASSWORD>
customParam1=value1
customParam2=value2
```

Sample Results

```
endpoint=<ENDPOINT TYPE>
name=<NAME>
customParam1=value1
customParam2=value2
```

update

Updates an existing credentials record for accessing ALM from the Integration Bridge.

Usage

```
credentials_mng_console.bat update -user <USER> -pass <PASSWORD> -
credentialsId <CREDENTIALS ID> -endpoint <ENDPOINT TYPE> -param <KEY> <VALUE>
-param <KEY> <VALUE> -replace
```

Usage example

```
credentials_mng_console.bat update -user <USER> -pass <PASSWORD> -
credentialsId <CREDENTIALS ID> -endpoint alm-11.5 -replace
```

Parameters

-file <FILE>	Reads parameters from the property file (optional). Parameters will be overwritten if they are specified in the console.
-user <USER>	New user name
-pass <PASSWORD>	New password
-credentialsId <CREDENTIALS ID>	The credentials record ID you want to update
-endpoint <ENDPOINT TYPE>	New endpoint name, such as an ALM version. This type name must be a value available in the " listEndpointTypes " command.
-param <KEY> <VALUE>	Custom parameters (optional)
-replace	Replace all existing parameters with input parameters (optional)

delete

Deletes an ALM credential record.

Note: You cannot delete a single parameter from a credential record. You can only delete an entire credential record.

Usage

```
credentials_mng_console.bat delete -endpoint <ENDPOINT TYPE> -credentialsId  
<CREDENTIALS ID>
```

Parameters

-endpoint <ENDPOINT TYPE>	Endpoint type name, such as the ALM version. This type name must be a value available in the " listEndpointTypes " command.
-credentialId <CREDENTIALS ID>	The credentials record ID

help

Provides help for the current command when configuring ALM credentials for the Integration Bridge.

Usage

```
credentials_mng_console.bat help
```

Configure a proxy for ALM connections

By default, the connection between the Integration Bridge and ALM is not authenticated by proxy. To configure a proxy, do the following:

Note:

Perform this procedure as a user with permissions to run the Integration Bridge.

1. In the **<Integration Bridge installation directory>\product\domain\alm\conf** folder, open the **proxy.properties** file.
2. To use a proxy, change the **setProxy** value to **true**.
If this value is **false**, proxy settings are ignored and no proxy is used.
3. Set the proxy host and port values:
 - a. Change the **proxyHost** value to the proxy IP address or server name.
 - b. Change the **proxyPort** value to the relevant port for the proxy.
When **proxyHost** has a value, **proxyPort** is mandatory.

Example

```
setProxy=true  
proxyHost=123.45.6.7  
proxyPort=1234  
proxyUser=  
proxyPass=
```

4. If the proxy requires authentication:
 - a. Change the **proxyUser** value to the proxy user name.
 - b. Change the **proxyPass** value to the proxy password.When **proxyUser** has a value, **proxyPass** is mandatory.

Example

```
setProxy=true  
proxyHost=123.45.6.7  
proxyPort=1234  
proxyUser=MyUserName  
proxyPass=MyPassword
```

5. Save the **proxy.properties** file.
6. Restart the Integration Bridge. For details, see ["Start and stop the Integration Bridge" on page 28](#).



Tip: If authentication fails, verify that the contents of the **proxy.properties** file are syntactically correct and contain valid values.

Set Agile Manager credentials

Use the **bridgeAuthentication** command line tool to set the credentials used to connect to Agile Manager.

The credentials consist of a client ID and secret generated by Agile Manager. To obtain a client ID and secret, add an Integration Bridge client on the **Integrations > API** configuration page.

Note: If you are not a Site Administrator on your Agile Manager system, have your administrator add the Integration Bridge client and provide you with the generated client ID and secret .

Use this tool in the following cases:

- You want to use credentials other than the ones you entered when you first installed the Integration Bridge.
- You need to update your bridge so that it connects to Agile Manager using OAuth authentication. The Integration Bridge bridge now uses a client ID and secret to connect to Agile Manager instead of Agile Manager user credentials.

Run the **bridgeAuthentication** command line tool

As an administrator, or as a user with permissions to run the Integration Bridge:

1. Open the **<Bridge_installation_directory>\product\util\opb** directory.
2. Run the **bridgeAuthentication.bat** file.

The **bridgeAuthentication** tool supports the following commands:

["setAuth" below](#)

["help" below](#)

setAuth

Sets credentials for connecting to Agile Manager from the Integration Bridge.

Usage

```
bridgeAuthentication.bat setAuth -clientId <CLIENT_ID> -secret <SECRET>
```

Parameters

-clientId <CLIENT_ID>	The client ID to use when connecting to Agile Manager.
-secret <SECRET>	The secret for the client that is connecting to Agile Manager.

help

Provides help for the current command when configuring Agile Manager credentials for the Integration Bridge.

Usage

```
bridgeAuthentication.bat help
```

Configure a proxy for Agile Manager connections

Use the **proxyConfiguration** command line tool to set credentials for accessing Agile Manager through a proxy server.

1. Open the **<Bridge_installation_directory>\product\util\opb** directory.
2. Run the **proxyConfiguration.bat** file.

Parameters

-user <USER NAME>	The name of the user connecting to the proxy server.
-pass <PASSWORD>	The password of the user connecting the proxy server.

removeAuth

Deletes a set of credentials previously used to connect to Agile Manager through a proxy server.

Usage

```
proxyConfiguration.bat removeAuth
```

help

Provides help for the current command when configuring access to Agile Manager through a proxy server.

Usage

```
proxyConfiguration.bat help
```

NextGen Synchronizer proxy support

NextGen Synchronizer supports the following types of proxy authentication:

Between the Integration Bridge and...		Agile Manager	ALM
Forward	No authentication	√	√
	Basic authentication	√	√
Reverse	No authentication	√	√
	Basic authentication	x	x

Note: NTLM authentication is not supported for any types of proxy.

Start and stop the Integration Bridge

If the Integration Bridge Windows service is installed, the Integration Bridge is automatically started when your system starts.

This topic describes how to manage the bridge activation manually.

Perform this procedure as a user with permissions to run the Integration Bridge.

Note:

- The Integration Bridge service is installed as part of the Integration Bridge installation.

```
<Bridge_installation_directory>/product/bin/HPIntegrationBridge.sh  
install
```

- The bridge must be running for Agile Manager to communicate with on-premise applications such as ALM.
- If you have upgraded your ALM projects, you'll need to restart the bridge manually after upgrade to continue synchronizing data between ALM and Agile Manager.

Start the bridge	Search or browse for, and select the StartHPIntegration Bridge application.
Stop the bridge	Search or browse for, and select the StopHPIntegration Bridge application.
Manage the bridge using Windows Services	<ol style="list-style-type: none">1. Run the services.msc command.2. Select the HPIntegration Bridge service.3. Stop or start the service as required. This starts and stops the bridge application as well.

Manage the bridge from the command line

Use the **HPIntegrationBridge** command line tool:

1. Open the **<Bridge_installation_directory>\product\bin** directory.
2. Run the **HPIntegrationBridge.bat** file.

Use the following commands:


Task	Command
Start the bridge	HPIntegrationBridge.bat start
Stop the bridge	HPIntegrationBridge.bat stop
Restart the bridge	HPIntegrationBridge.bat restart
Install the Integration Bridge service	HPIntegrationBridge.bat install
Remove the Integration Bridge service	HPIntegrationBridge.bat remove

Uninstall/Remove the Integration Bridge

Uninstall a bridge if you no longer need it, or before upgrading.

Remove a bridge from the Link Configuration navigation tree if you no longer need it, or are no longer using it.

To uninstall a bridge permanently


1. In the Agile Manager **Integrations** >  **Link Configuration** page, expand the navigation tree on the left.
Verify that no synchronizations are currently running on the bridge's links.
Right-click on any links that are in automatic mode and select **Stop Automatic Mode**. Wait for the completion of any current synchronization runs before uninstalling the bridge.
2. Close all tools, folders, and files related to the Integration Bridge, such as the Endpoint Credentials Manager.
3. Do the following:

Task	Description
Uninstall the bridge	As a Windows administrator user, uninstall the Integration Bridge using the Start menu option or the Windows Control Panel. During the uninstall process, select Remove credentials if you also want to remove any associated credentials. By default, credentials are kept, and you can use them in a subsequent installation.

Task	Description
Remove the bridge from the Agile Manager user interface (optional)	<p>In Agile Manager:</p> <ol style="list-style-type: none">Verify that the bridge has no links configured. If there are any existing links, remove them: Select the link in the tree and then select More Actions > Remove. <div data-bbox="690 541 1380 709" style="border: 1px solid #ccc; background-color: #fff9e6; padding: 10px;"><p>Caution: You cannot recover a link removed from the NextGen Synchronizer. Only remove a link if you no longer need to synchronize its data between the endpoints.</p></div> <ol style="list-style-type: none">Select the bridge name and either select Remove Bridge from the context menu, or select More Actions > Remove. <div data-bbox="690 829 1380 1071" style="border: 1px solid #ccc; background-color: #fff9e6; padding: 10px;"><p>Caution: Only remove the bridge from the user interface if you have no intention of recovering it.</p><p>You cannot recover a bridge removed from the NextGen Synchronizer, even if you have not yet uninstalled it.</p></div>

When you uninstall the Integration Bridge, properties customized in the **server-connection.conf** file are deleted. The information in the **server-connection.conf** file is backed up in the **server-connection.bak** file.

To uninstall a bridge in order to upgrade or move it

- In the Agile Manager **Integrations >  Link Configuration** page, expand the navigation tree on the left.
Verify that no synchronizations are currently running on the bridge's links.
Right-click on any links that are in automatic mode and select **Stop Automatic Mode**. Wait for the completion of any current synchronization runs before uninstalling the bridge.
- Close all tools, folders, and files related to the Integration Bridge, such as the Endpoint Credentials Manager.
- As a Windows administrator user, uninstall the Integration Bridge using the **Start** menu option or the Windows Control Panel.

During the uninstall process, do not select **Remove credentials**. When you install the upgraded version, you can use the existing credentials.

Properties customized in the **server-connection.conf** file are deleted. The information in the **server-connection.conf** file is backed up in the **server-connection.bak** file. Use this file when you install the upgraded version.

For more details, see ["Upgrade the Integration Bridge" on the next page](#).

Upgrade the Integration Bridge

When a new Agile Manager version includes a new version of the Integration Bridge, any existing bridges automatically detect the need for upgrade.

The following process takes place without user intervention:

- The existing bridge is disabled.
- The new version of the Integration Bridge is downloaded and verified.
- The new bridge is installed in place of the existing one and then enabled. Any previous configuration settings and security certificates are retained.

Email notifications are sent at the beginning and end of the upgrade. Upgrade notifications are sent to the Integration Administrator users that you specify on the bridge's Notification tab (**Integrations > Synchronizer** configuration page). For details, see the *Agile Manager Synchronization User Guide*.

If, for some reason, you need to manually upgrade the Integration Bridge, use one of the following methods:


- ["Upgrade an existing bridge on the same server as the previous bridge" below](#)
- ["Upgrade the Integration Bridge, and install it in new location" on the next page](#)

Both upgrade methods retain the configured endpoint credentials.

When performing a manual upgrade, if your Integration Bridge communicates with ALM using a certificate that is not signed by a well-known Certificate Authority, you need to reinstall the certificate after upgrading the bridge. For details, see ["Connections using a certificate that is not signed by a well-known Certificate Authority" on page 12](#).

Upgrade an existing bridge on the same server as the previous bridge

This procedure registers the upgraded bridge as an existing bridge.

1. Uninstall the Integration Bridge, as described in ["Uninstall/Remove the Integration Bridge" on page 30](#). During the uninstall process, do *not* select **Remove credentials**.
2. Download the new version of the Integration Bridge from the **Integrations >  Link Configuration** page.
Select **More Actions > Download Integration Bridge > Windows**
3. Extract the downloaded zip file (**hp-integration-bridge-windows.zip**) to a new folder.

4. Copy values from the previous installation to the new installation. Do the following:
 - a. In the installation directory of the previous version, access the **\product\conf\server-connection.bak** file.



Tip: By default, the installation directory is **C:\Program Files\HP\HP Integration Bridge**.


- b. In a parallel window, browse to the **server-connection.conf** file downloaded with the new version of the Integration Bridge, and open it for editing.
 - c. Copy the **agent.guid** property and its value from the previous installation file, and append it to the new file. Save the new file.
5. Run the newly downloaded **hp-integration-bridge.exe** to begin the installation.

During the installation, on the **Select installation** folder screen, select the installation folder that was used for the previous version.

For more details, see ["Download and install the bridge" on page 7](#).

Upgrade the Integration Bridge, and install it in new location

This procedure installs the upgraded Integration Bridge in a new directory on the same server as the previous version, or on an entirely new machine.

1. Uninstall the Integration Bridge, as described in ["Uninstall/Remove the Integration Bridge" on page 30](#). During the uninstall process, do *not* select **Remove credentials**.
2. Download the new version of the Integration Bridge from the **Integrations >  Link Configuration** page.
Select **More Actions > Download Integration Bridge > Windows**
3. Extract the downloaded zip file (**hp-integration-bridge-windows.zip**) to a new folder.
4. Copy files and values from the previous installation to the new installation. Do the following:
 - a. In the directory where you want to install the new version, create the following folder structure:**product\conf**
 - b. Copy the following files from the installation directory of the previous version to the **conf** directory you created in the previous step.
 - **credentialsStore.xml**
 - **key.bin**
 - c. In the installation directory of the previous version, access the **\product\conf\server-connection.bak** file.



Tip: By default, the installation directory is **C:\Program Files\HP\HP Integration Bridge**.

- d. In a parallel window, browse to the **server-connection.conf** file downloaded with the new version of the Integration Bridge, and open it for editing.
 - e. Copy the **agent.guid** property and its value from the previous installation file, and append it to the new file. Save the new file.
5. Run the **hp-integration-bridge.exe** to begin the installation.

During the installation, in the **Select installation** step, select the directory where you want to install the new version.

For more details, see "[Download and install the bridge](#)" on page 7.

Integration Bridge troubleshooting

This topic covers the following scenarios:

- "Bridge is not identified after installation" below
- "Bridge name is displayed in red in Agile Manager" below
- "Integration Bridge remains Offline even after stopping and starting the bridge" below
- "Bridge connection status displayed as Unknown in Agile Manager" on the next page
- "Bridge cannot log in to Agile Manager or ALM" on the next page
- "A '403' or 'Authorization Exception' error occurs" on the next page
- "Errors during synchronization: "Missing required field"" on the next page
- "How do I modify the URL that the Integration Bridge uses to connect to Agile Manager?" on page 38

Bridge is not identified after installation

If the bridge does not appear on the **Integrations > Synchronizer** or  **Link Configuration** page in Agile Manager after installation is complete, click **Refresh**, or refresh the browser page.

- If the bridge still does not appear, make sure the bridge is running. For details, see "[Start and stop the Integration Bridge](#)" on page 28.

The Integration Bridge Windows service attempts to start the bridge several times. If it is not successful, the application shuts down and the service stops.

- If the bridge does not start, make sure the value of the **Drmi.server.port** in the **<installation folder>\product\log\controller\wrapper.log** file is set to an available port.
- If the defined port is in use by another application when the Integration Bridge Windows service attempts to start the bridge, the following errors are printed to log files:

In the wrapper log file	java.rmi.server.ExportException: Port already in use: <port>
In the controller log file	java.rmi.NotBoundException: ControllerAPI

Bridge name is displayed in red in Agile Manager

The Integration Bridge is down. In Agile Manager, click the bridge name to view the last time the bridge accessed the server.

Integration Bridge remains Offline even after stopping and starting the bridge

If the connection status of your bridge is displayed as **Offline** in Agile Manager, try restarting the bridge. For details, see "[Start and stop the Integration Bridge](#)" on page 28.

If the bridge remains offline, the Integration Bridge user's Agile Manager password may have expired. Modify your bridge to connect to Agile Manager using OAuth and no longer depend on user credentials:

1. On the , add an Integration Bridge client. Agile Manager generates a client ID and secret for the bridge. For details, see the *Agile Manager User Guide*.

Note: If you are not a Site Administrator on your Agile Manager system, have your administrator add the Integration Bridge API client and provide you with the generated client ID and secret.

2. Use the generated client ID and secret for the credentials that the bridge uses to connect to Agile Manager. For details, see "[Manage connection setup](#)" on page 15.

Bridge connection status displayed as Unknown in Agile Manager

Check the following log files in the Integration Bridge log folder (**<Bridge_installation_directory>\product\log\controller**):

- **controller.log**
- **wrapper.log**

Additionally, check the **<Endpoint type name>.log** file located in the **<Bridge_installation_directory>\product\log\<Endpoint type name>** directory.

Bridge cannot log in to Agile Manager or ALM

Check the connection setup defined for the endpoint:

- Check the credentials defined for the endpoint.
- Check proxy configuration if relevant.
- If ALM is configured to require HTTPS for logging in, configure the bridge to connect to ALM using HTTPS.

For details, see "[Manage connection setup](#)" on page 15 and "[Integration Bridge security](#)" on page 12.

A '403' or 'Authorization Exception' error occurs

The user accessing Agile Manager from the Integration Bridge is not defined with the **Integration Bridge** role.

Modify this user's role in the Agile Manager configuration area (**Site > Users**).

Note: For security purposes, the **Integration Bridge** user should not have any additional roles.

Errors during synchronization: "Missing required field"

Issue: During a synchronization run, some entities fail to synchronize. The errors indicate that a

required field is missing. However, in the Link Configuration page, I do not see any mandatory fields that are not mapped.

Cause:

A field that is currently mandatory in ALM is not mapped, or it is mapped to an Agile Manager field that does not contain a value.

- The field in question may have been marked as mandatory in ALM after the link or entity itself was created.
- The field might be mandatory in ALM only when other fields contain certain values.

Solution:

Map the field to an Agile Manager field that contains a value, or manually enter a value in Agile Manager for the relevant field.

How do I modify the URL that the Integration Bridge uses to connect to Agile Manager?

The URL that the Integration Bridge uses to connect to Agile Manager is downloaded from Agile Manager with the Integration Bridge. In most cases, you should not need to modify this URL.

If the URL for your Agile Manager changed, do the following:

1. Navigate to the **<HP Integration Bridge installation folder>\product\conf** folder.
2. Open the **server-connection.conf** file for editing.
3. Update the **agm.base.url** property with the new URL.

Format: `http(s)://<server hostname or IP address>:<port number>/agm`



Tip: If you can login to the Agile Manager that you want the Integration Bridge to use, login and then use the URL from your address bar. Take the URL from the beginning up to **/agm**. Ignore the rest.

4. Restart the bridge.

Send Us Feedback



Let us know how we can improve your experience with the Installation Guide for Windows.

Send your email to: docteam@hpe.com

