

IT Business Analytics

Software Version: 10.10 Linux operating system

Content Extension Guide for ITBA IDE Version 10.10

Document Release Date: March 2016 Software Release Date: March 2016

Legal Notices

Warranty

The only warranties for Hewlett Packard Enterprise products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Hewlett Packard Enterprise shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from Hewlett Packard Enterprise required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notice

© 2011-2016 Hewlett Packard Enterprise Development LP

Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

This product includes an interface of the 'zlib' general purpose compression library, which is Copyright © 1995-2002 Jean-loup Gailly and Mark Adler.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to: https://softwaresupport.hp.com/.

This site requires that you register for an HP Passport and to sign in. To register for an HP Passport ID, click **Register** on the HP Support site or click **Create an Account** on the HP Passport logon page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

Visit the HP Software Support site at: https://softwaresupport.hpe.com.

This website provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support website to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patchesManage support contracts
- Manage support contracts
 Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and to sign in. Many also require a support contract. To register for an HP Passport ID, click Register on the HP Support site or click Create an Account on the HP Passport logon page.

To find more information about access levels, go to: https://softwaresupport.hpe.com/web/softwaresupport/access-levels.

HP Software Solutions Now accesses the HPSW Solution and Integration Portal website. This site enables you to explore HP Product Solutions to meet your business needs, includes a full list of Integrations between HP Products, as well as a listing of ITIL Processes. The URL for this website is http://h20230.www2.hp.com/sc/solutions/index.jsp.

About this PDF Version of Online Help

This document is a PDF version of the online help. This PDF file is provided so you can easily print multiple topics from the help information or read the online help in PDF format. Because this content was originally created to be viewed as online help in a web browser, some topics may not be formatted properly. Some interactive topics may not be present in this PDF version. Those topics can be successfully printed from within the online help.

Contents

Getting Started with Content Extension	6
IDE Terms	9
IDE Audience	11
Prerequisite Knowledge for Performing Content Development Tasks	11
IDE End-to-End Extension Scenario	12
Content Development Process	15
Design and Analysis Phase	16
Design and Analysis	16
Architecture	17
Design and Analysis - Discover Data Evidence	19
Development	21
Development - Modeling	21
DWH Content Development	22
DWH Content Development - Content Packs and Data Modeling	24
Development - Application Content	28
Development - Content Extension Best Practices	29
Content Extension Rules	30
IDE User Interface Overview	31
IDE Main Page	32
The IDE Eclipse Main Page	32
Package Explorer	35
Data Source Browser	36
Diagram Editor	37
Diagram Editor - Architect Target Designer Tasks	42
Create a new Architect Target Designer in the IDE	43
Define a new Target entity	43
Load an existing Target entity	44
Extend a Target Entity	44
Add a column	45
Link a Dimension to a Dimension	45
Link a Fact to a Dimension	45
Diagram Editor - Engineer Stream Designer Tasks	54

Create a new Engineer Stream Designer in the IDE5	56
Define a new Target entity5	57
Load an existing Target entity5	57
Define a new integration entity5	57
Load an existing integration entity5	57
Define a new source entity5	58
Load an existing source entity5	58
Add a column5	58
Map from the Integration to Target5	59
The DW Content menu6	36
Common Extension Scenarios	38
Extension of the existing entity in the existing Content Pack6	38
Extraction of a new entity in an existing Content Pack6	38
Populating an existing entity from a new data source6	39
Extracting a new entity from a new source6	39
Import Existing Content	70
Define New Content Pack Project	71
Create new projects from content directories7	71
Define the Target Model	76
Extend the Period Entity	77
Delete an Entity Permanently	78
Manage Validation	30
View the errors and warnings that occurred during content development 8	31
Manually perform validation8	31
Quick Fix8	32
Validation Table8	34
Generate Content) 2
Create a new entity and a new Content Pack with the ETL Generator9) 2
Package and Deploy Content	94
Package and deploy content9	94
Activate New Content) 5
Activate a new Content Pack9) 5
CP Activation Page Options9	96
Advanced Development	
Data Source Explorer	

Create a new database connection in the Data Source Explorer	
Modify driver definitions	100
Generate Entities Automatically	108
Automatically generate entities from database tables or views	108
Data Source Extraction Customization	115
Customize the Source Model	115
Make changes in a field name	116
Make changes in a table name	116
Update the data warehouse metadata	117
Customize the Extraction Model and the EXT ETL Scripts	118
Customize the SSI Layer	119
Consolidate Entities - Cross-CP Lookup	121
Customize Views	123
Customize the PREFILL case	124
Customize a Stream Priority	125
Customize the Maximum Execution Time of a Stream	126
Next Steps	127
Release Notes	129
What's New in this Version	129
Send Documentation Feedback	130

Getting Started with Content Extension

The Integrated Development Environment (IDE) allows you to develop content and DWH models, as well as develop new entities and extend existing content using the Designers. Once the entities are defined and mapped, they are run through the ETL Generator to produce the metadata and workflows. You can then package the data into Content Packs for use in the Data Warehouse.

Note: The IDE only supports the usage of UTF-8 (Latin) characters.

IDE Set up

- 1. **Prerequisite:** When creating or extending content make sure that you have set up ITBA. For IT Business Analytics installation and administration details, see the *Administrator Guide*.
- Install the contents of the IDE DVD. The IDE can be downloaded from HP Live Network (HPLN) (https://hpln.hp.com/) (https://hpln.hp.com/group/it-business-analytics) and contains:
 - **IDE:** Unzip the file and double-click **eclipse.exe** to run the IDE Eclipse application.
 - **IDE Content:** Contains the OOTB Content Packs.

Content Extension Process

The development of new content comprises the following steps:

- Understand IDE. For details, see "IDE Terms" on page 9, "IDE Audience" on page 11, "IDE Main Page" on page 32, and "DWH Content Development - Content Packs and Data Modeling" on page 24.
- Design and analyze the purposes of the extension. For details, see "Design and Analysis Phase" on page 16.
- Data Evidence: Understanding and analyzing what data needs to be included, based on your information needs and objectives. For details, see "Design and Analysis - Discover Data Evidence" on page 19.
- 4. Import existing content for extension or new Content Pack directories if required. For details, see "Import Existing Content" on page 70.
- If needed, define new Content Pack projects. For details, see "Define New Content Pack Project" on page 71.
- 6. Modeling: The architect creates the Target model. For details, see "Define the Target Model" on page 76 and "Diagram Editor Architect Target Designer Tasks" on page 42.
- Data Source Integration: The engineer maps the data from the Source to Target. For details, see "Diagram Editor - Engineer Stream Designer Tasks" on page 54, "Delete an Entity Permanently" on page 78, and "Manage Validation" on page 80.
- 8. ETL development and generation. For details, see "Generate Content" on page 92.
- 9. ETL orchestration and management. For details, see "Package and Deploy Content" on page 94.
- 10. Activate new content. For details, see "Activate New Content " on page 95
- 11. Consolidation
- 12. Context (universe) building and adjustments.
- 13. KPIs additions and modifications.
- 14. Advanced development. For details, see "Advanced Development" on page 98.
- 15. Next steps. For details, see "Next Steps" on page 127.

Content Extension Guide for ITBA IDE Version 10.10

IDE Terms

• **IDE: Integrated Development Environment.** The Eclipse workspace where you can create or extend content using modeling tools in the relevant designers.

Note: The path to the workspace should not contain blank spaces. For example: **C:/workspaces/ide_workspace/**.

- **KPI: Key Performance Indicator.** KPIs reflect how well the organization is doing in areas that most impact financial measures valued by shareholders, such as profitability and revenues.
- **API: Application Programming Interface.** A specification intended to be used as an interface by software components to communicate with each other.
- ETL: Extract, Transform, Load. An end-to-end transfer of external source data through several staging layers and into the target layer of the data warehouse. The data warehouse uses the ETL process to extract, consolidate, and transform the source data into a meaningful target model that populates relevant business analytics.
- UDM: Unified Data Model. Provides a bridge between the user and the data sources.
- **DWH: Data Warehouse.** The data warehouse is an end-to-end solution for extracting source data and consolidating disparate source data models into a consolidated data model. The data organized to reflect this model resides in target tables that become the source for ITBA.
- **ITBA: IT Business Analytics.** An application that enables executives to continuously improve their business by measuring what happened and what is happening, analyzing that information, and planning new strategies using the gathered information.
- File Based Integration (FBI) Extractor.

FBI enables you to extract data from a specific data source according to a set of instructions. It consists of a plug-able extractor framework for each data source. The extractor gathers data according to the specific instructions it receives, placing it into a relevant .txt flat file. If you want to develop your own extractor for use with extended content, see the *DCS Extractor SDK Guide*.

The supported extractors for the OOTB Content Packs are as follows:

Content Pack	Extractor Type
PPM(Oracle)	DB

Content Pack	Extractor Type
SM(MSSQL, Oracle, DB2)	DB
ALM	REST API
CSA	REST API
AWS	SDK
AWSCW	SDK
AM	DB
SA	DB
VPV	"REST API"
AZURE	"REST API"

- Entity. An entity is an object of interest included in the data model.
- **Designer.** A designer in the IDE is the model you create in order to perform content extension and definition. It is a collection of certain entities that may share some relevancy in common. The IDE contains the Architect Target Designer and the Engineer Stream Designer.
- Content Packs. A content pack is a set of entities from a certain type. There are three types of content packs:
 - **Source.** Contains all of the artifacts needed to connect to the relevant data source and pull data from that data source.
 - Integration. Integrates the information from the source, using the DWH schema and loading process in order for the data to be brought to the Target tables. Takes the schema and entities of the source data and transforms it into usable data.
 - **Target.** Defines the content of the Data Warehouse as well as the look of the target tables according to the Unified Data Model (UDM).

IDE Audience

This document assumes basic data warehouse modeling knowledge, understanding of the ETL concepts, good familiarity with databases including the Vertica database.

Requirements for DWH Architects

- Understanding of Business Intelligence tools, data warehouse modeling and database design principles.
- ITBA DWH Target schema.

Requirements for DWH ETL Engineers

- Understanding ETL principles.
- Familiarity with the source schema.

Requirements for DWH Integration Engineers

• Java programming skills


Prerequisite Knowledge for Performing Content Development Tasks

- Unified Data Model (UDM).
- Target Model: The existing supported model of the DWH
- Basic architecture of the data warehouse and the advantages of the templates.
- Basic familiarity with the Integrated Development Environment (IDE).
- Vertica and data modeling.

IDE End-to-End Extension Scenario


This section provides an end to end scenario.

The following illustrates the typical flow, tasks, and procedures in the IDE process. The tasks correspond to the relevant tasks in the Designers.




To extend the existing target entity LOCATION:

1. Create all the required project folders for the new Content Pack.



2. Create the extension entity in the Architect Designer, and then link the extension entity to the OOTB entity using the Target Extension link. For details, see "Extend a Target Entity" on page 44.

In this scenario, add two columns **CALENDAR_ID** and **CURRENCY_ID** to the OOTB entity **LOCATION**.



 Create a new integration and source entity in the Engineer Designer, then map the columns from integration to target entity. For details, see "Diagram Editor - Engineer Stream Designer Tasks" on page 54.

PPMCT.9.1.ORACLE.LOCATION_CSTM		
	,	
S LOCATION_CSTM	PPMCT - LOCATION_CSTM Tra	LOCATION_CSTM
♦ CALENDAR_ID	Columns	Columns
♦ CURRENCY_ID		
LAST_UPDATE_DATE		
♦ REGION_ID	Associated Dimensions	Associated Dimensions
	Extension	Extension
	LOCATION	LOCATION


- 4. Generate the ETL artifacts.
- Configure the cross-Content Pack configuration file in the \$HPBA_ HOME/ContentPacks/PPMCT/CONF/dataSourceParamsConfig.xml file.


For details, see "Consolidate Entities - Cross-CP Lookup" on page 121.

6. In the Context Designer, you can link the new target entity with an OOTB target entity, or you can link them in the customized views. Then the new target entity and the OOTB target entity can be used by the KPI formula.

For details, see Semantic Layer - Context Designer in the Content Reference Guide.

Content Development Process





Design and Analysis Phase


The information design and analysis phase help you determine your organization's objectives and information needs and discover the data in the organization that supports the business requirements.



Design and Analysis

This phase is the preparation for the actual implementation but usually consumes more time and resources as the outcome of it should be exact design of the end user solution.

This phase has the following stages:



Business Discovery

A structured methodology for understanding the company's objectives and Information needs.

This methodology includes the following steps:

1. User Analysis.

- Define the personas
- Define the personas business requirements
- 2. Decision Based Analysis.
 - KPIs
 - Reports

- Metrics
- Dashboards
- 3. Information Availability.
 - · Identify the Source systems that support business requirements
- 4. Assign Priorities.

The output of this stage is the design document that describes the solution from business perspective.

Information Discovery

This stage implies discovering the data in the Organization that supports the Business requirements synchronizing between the available information, means of extracting it and information required by the business. It's also known as "Data Evidence" process

Discover the data in the organization that supports the business requirements. Synchronize the available information and the means of extracting it with information required. This is the Data Evidence process. Information discovery includes the following steps.

1. Select the Source Contact Point.

• Select a source expert to accompany the information discovery process

2. Define the Source Extraction Method.

- Common extraction methods are DB query, API, Web Services
- The new extractors can be developed based on the DCS API.
- 3. Identify the Source Table.
 - Identify configuration tables to populate Dimensions
 - Identify transactional tables to populate Facts

4. Define the Source to Target Mapping.

- Identify Source Columns Mapping to Target Columns
- Define data-processing requirements


Architecture

During this stage the Target data model is visualized using the Star-Scheme Model approach. Star Schema is a design method of dimensional modeling, in which data is organized in:

- Facts: An event that is counted or measured, such as a sale or logon. Table Structure contains business measurements (numeric or time based) and Dimensional Intersection Point.
- **Dimensions:** Reference information about the fact, such as period, product, or customer. Common Table Structure contains descriptive attributes.

A star schema is diagrammed by surrounding each fact with its associated dimensions. The resulting diagram resembles a star. Star schemas are optimized for querying large data sets and performing analytical queries that are used in data warehouses and Business intelligence systems.

Sample Star Schema



The Star-Scheme architecture creation process includes:

- Review the ITBA UDM catalog.
 - Review the ITBA UDM Catalog, by the business context defined in Business Discovery phase.
- Gap Analysis
 - Identify the OOB Target entities matches.
 - Identify the OOB Target entities to be extended.
 - Identify the New Target entities.
- Design Dimension Tables
 - Define the Attributes.
 - Mark Slowly Changing Dimension columns

Note: DWH supports 2 types of Slowly Changing Dimensions:

- **SCD1**: no history preserving an update on one or more attributes will override the old value
- SCD2: history preserving an update on one or more attributes that were marked as SCD2 will be added as new record and previous record will be marked as not active.
- Design Fact tables
 - Define measures
 - Define granularity
- Define Dimensional Intersection Points
 - Identify Fact to Dimension Links

Note: The IDE tool is used only for designing Fact and Dimension tables and their intersection points.

Design and Analysis - Discover Data Evidence

It is necessary to understand and be familiar with the new data you want to develop. When there is a new source system involved, you must first understand how the data from the source appears and operates.



Discover data evidence

Data Evidence can be discovered as follows:

- 1. Understand how to extract the data.
- 2. Take sample files extracted from the source.
- 3. Examine the different fields that this source provides: It is important to recognize the fields and data that come from the source and to define the names of the fields as the source tables.
- 4. Define and plan in advance which extractors provide data for specific entities.


- 5. Understand variety, different lists of values, and end-cases.
- 6. Observe data behavior over time:
 - a. Understand what happens with data across time is it the same file, only different dates?
 - b. Sizes of rows and volumes by types of customers.
 - c. Identify how this data correlates with existing data in the Data Warehouse.

At the end you should have a good sense of what this data looks like and how to develop extraction code for it.

- 7. Identify:
 - a. What is the required data to be available in the Target schema to support required KPIs.
 - b. What is the data that can come from the source (depending on technology).
 - c. Where do they meet in the middle, so eventually we have the outcomes of the extracted data and the DWH Target model.
 - d. For which columns do you want to preserve history.

After mapping between the Source and the Target, the design process is complete.

Development



Development - Modeling

This stage is done completely in the IDE tool.

The IDE tool has the following ITBA DWH definition:

• Target Entity is a Fact or Dimension.

Entity name along with column names is defined according to the Star-Schema Architecture.

• Integration Entity is the source table representation.


Entity name along with column names and data types is defined according to source table design.

• Source Entity is the actual and accurate representation of an entity to be extracted from the source.

It describes how and what data is extracted from the source. It is generated automatically according to integration entity design however depending on the extractor being used it may require some changes as the automatic generation is targeted for the DB extractor only.

- **Transformation Entity** is the logical representation of all the transformations that are performed by the DWH during the data processing. It's the accurate representation of the Target Entity.
- Column Mapping Source to target column mapping

The modeling approach:



The Solution Modeling Highlights:

- Different functions are collaborating on same models simultaneously until reaching a final version.
- Actually serves as a high-level DB Studio + ETL tool. No need to touch the DB directly.
- 95% of the solution is defined by this high-level modeling.

DWH Content Development

This stage is the final stage of the content development on DataWarehouse side. The outcome of this step is the ready-to-be-distributed Product Content Pack (iCP) and the delta artifacts for the Core content pack.

The **Product Content Pack (iCP)** is the set of the artifacts that describe the data flows and data transformations for the logical entities. The iCP belongs to one source product only (e.g. AM, PPM, SM) and contains the metadata of:

Source Content Packs

- The content packs that contain all source entities metadata
- The separate source content pack exists for each product version and the type of extractor used

Integration Content Pack

- Contains the Integration Entities metadata
- Unlike Source entities, the integration entity is not dependent on the product version and extractor type therefore multiple source entities are mapped to the one integration entity.
- Column Mapping
 - Contains the metadata of the column mappings between the Integration entity and the Target entity.

	PROBSUMMARY	I SM - INCIDENT Transformati	
SM.9.2.mssql.PROBSUMMARY	SRC_LASTMODDATE	Columns	Columns
	♦ STATUS	INCIDENT_STATUS	INCIDENT_STATUS
SM.9.2.oracle.PROBSUMMARY	♦ INCIDENT_TYPE	NCIDENT_TYPE	INCIDENT_TYPE
	♦ CATEGORY	CATEGORY	CATEGORY
	SUBCATEGORY	SUBCATEGORY	
SM.7.11.mssql.PROBSUMMARY	ACTIVE PROCESS	ACTIVE_PROCESS	ACTIVE_PROCESS
		PRIORITY	
SM.7.11.oracle.PROBSUMMARY	PRIORITY_CODE		REFERENCE_NUMBER
SM./.II.oracie.PROBSUMMARY	♦ INCIDENT_NUMBER	REFERENCE_NUMBER	
	♦ RESOLUTION_CODE	COMPLETION_CODE	
SM.9.3.mssql.PROBSUMMARY	♦ INITIAL_IMPACT —	MPACT_SCOPE	IMPACT_SCOPE
· ······	♦ SEVERITY	URGENCY	URGENCY
	ESCALATION	SCALATION	SCALATION
SM.9.3.oracle.PROBSUMMARY	DOWNTIME_START	OUTAGE_START	OUTAGE_START
	DOWNTIME_END		
SM.7.11.dbdict_mssql.PROBSUMMARY	♦ CLOSE_TIME		
	AFFECTED_ITEM		
	♦ REOPEN_TIME		REOPEN_TIME
SM.7.11.dbdict_oracle.PROBSUMMARY	♦ OPEN_TIME	Associated Dimensions	Associated Dimensions
	♦ COMPANY		INCIDENT
	ASSIGNMENT	OUTAGE_START	OUTAGE_START
	♦ LOCATION	OUTAGE_END	
SM.7.11.dbdict_db2.PROBSUMMARY			
-			
		REQUESTED_BY_ORG	REQUESTED_BY_ORG
		ASSIGNED_TO_ORG	ASSIGNED_TO_ORG
		ROBLEM	PROBLEM

The **Core Content pack** contains the metadata for all the target entities and the intersections between them and is the basic content pack for the DataWarehouse. It is deployed automatically during ITBA Content Pack installation

DWH Content Development includes the following steps:

- 1. Define the target model in the Architect Designer.
- 2. Define the ETL in the Engineer Designer.
- 3. Generate ETL artifacts from IDE .
- 4. Customize the SSI scripts.
- 5. Copy the artifacts into your ITBA environment.

- 6. Deploy the Content Pack.
- 7. Run the ETL and verify the operation and correctness.

DWH Content Development - Content Packs and Data Modeling

Content packs contain all the artifacts needed to connect to the relevant data source and gather data from that data source. The mapping between the raw data from the data source and the target database in the Data Warehouse is included in the ETL.



Content Pack contents

Content Packs include:

- The definition of the data model used for the connection.
- The type of data gathered from the data source.
- The ETL definitions.
- The definition files.
- The configuration files.
- The scripts that help build and define the Data Warehouse.

Content Pack Types

- **Target Content Pack.** Responsible for the transfer of data from consolidation to the target database. The Target CP defines the content of the Data Warehouse as well as the look of the target tables.
- Integrated Content Pack (iCP). The iCPs are responsible for bringing the data from the specific data sources and transforming it into the consolidation level. From there, the Target CP transfers the data to the target. The iCPs integrate the information from the source, using the DWH schema and loading process in order for the data to be brought to the target tables.

Content Pack directories

Content Packs contain the following directories:

- STREAM. Contains files that define the ETL stream at the entity level, and the general flow of steps of the ETL process. The files list the order of the steps as well as the link between the parent and child steps. These files are necessary if you have to add a step to the ETL process.
- **Data Model.** The Data Model in the Core Content Pack contains the xml files that define the target schema. The Data Model in the Integration Content Pack contains the xml files that define the staging and extraction schema.
- ETL. Contains the jobs and workflows of the ETL and defines how data goes through the processes.
- **cp_manifest.properties.** The manifest file provides additional information to the Content Pack to allow the system to perform sets of validations.
- dw_app.properties.

Data Model Types

Data models describe the source, extraction, consolidation, and target components for a single entity:

- Target Entity. Fact or Dimension: Entity name and column names defined according to the Star-Schema architecture.
- **Source Entity.** The actual representation of an entity extracted from the source. Generated automatically according to the integration entity design.
- Integration Entity. Entity name, column names, and data types defined according to source table design.
- Column Mapping. Integration to Target column mapping.

Logical Data Models

DWH supports the following types of logical data models:

- Target Data Models:
 - Target Model Dimension or Fact. The target data models describe the format of the data that produces business intelligence analytics. The instantiated data models are dimension, fact, and hierarchy tables.

• iCP Data Models:

- **Extraction Model.** ETL processes obtain the data in native format and stages it in intermediate tables that conform to the extraction data model for that entity. Extraction also validates the data to ensure that it is usable.
- **Source Model.** The source entity models represent the design of DII (Data Integration Interface).

Physical Data Models

DWH logical Data Models generate multiple physical tables that support the ETL processing logic.

- **Source entity models.** The source entity models are the data produced by an external application. Used for a specific version of the product.
- Extraction models. ETL processes obtain the data in native format and stage it in intermediate tables that conform to the extraction data model for that entity. Extraction also validates the data to ensure that it is usable.
- **Consolidation models.** Consolidation models transform the data further by merging extracted data from diverse sources into meaningful data required by applications.
- **Target models.** The target models describe the final version of the data that adheres to the design required by applications.

Data models describe the source and extraction format so that the data warehouse can consume this data and integrate it into a common view that you can use to populate comprehensive business intelligence reports and dashboards.

Each table contains both designed columns and static columns, also known as metadata columns, so that the administrator can have the visibility of ETL processing over the entity's data.

Data Warehouse Internal Fields

The following are the internal Data Warehouse fields, in addition to those in the IDE, that are added to the model.

Field Name Prefixes	Description
MD_BATCH_ID	ETL stream ID displayed on all Physical Models.
MD_PROCESS_ID	ETL Process ID running the specific job.
MD_DURABLE_KEY	Entity's unique identifier populated with MD_QUALIFIER which should be

Field Name Prefixes	Description
	considered as the identifier to consolidate records.
	Displayed only in Consolidation Physical Models
MD_ENTERPRISE_	Entity's unique identifier in the DWH system.
KEY	Displayed only in Target Physical Models
MD_BUSINESS_KEY	Entity's unique key as it comes from the source systems.
	Displayed only in Target and Extraction Physical Models
MD_TRANSLASTIND	Indicator whether the line is the last transaction of a specific MD_ ENTERPRISE_KEY.
	Displayed only in Target Physical Models
MD_	Indicator whether the line is active (simulates delete operation).
ACTIVESTATUSIND	Displayed only in Target Physical Models
MD_	Transaction end date.
TRANSENDDATE	Displayed only in Target Physical Models
MD_DELETEDDATE	Delete date (date record was marked as inactive).
	Displayed only in Target Physical Models
MD_CREATEDDATE	Date record was created.
	Displayed only in Target Physical Models
MD_LASTMODDATE	Date record was last modified and updated.
	Displayed only in Target Physical Models
MD_FLAG	Flag that indicates whether row is new, updated, or requires a delete.
	Displayed only in Extractions Physical Models
MD_PF_FLAG	Flag that indicates whether row is pre-filled or not.
	Displayed only in Extractions Physical Models
MD_CP_ID	Source instance ID

Development - Application Content

This stage implies creating the end-user artifacts based on the target data model that was developed above.

It has the following steps:

- Generate Interface
 - Create ITBA views (If Needed)
 - Serves for normalizing the data for the KPI modeling purposes and filtering the unnecessary DWH metadata fields.
- -Create Business Contexts
 - Based on ITBA Views or Target Tables
 - Similar to the Star-Scheme usually includes one fact entity which context is based on and the multiple dimension entities linked to the fact.
- Create Artifacts
 - KPIs
 - Metrics
 - Webi Reports
 - Xcelsius Reports
- Calculate and Verify
 - Run Calculation Engine
 - Check validity
- Packaging
 - Export Artifacts to create distributable Content Acceleration Pack

Development - Content Extension Best Practices

There is set of best-practices and guidelines for creating customization tracks

- Do not modify the OOTB entities
 - This includes avoiding linking the custom dimensions to the OOTB entities
 - Use the Target Extension link from the custom entity to the OOTB entity instead.
- Use the _CSTM suffix when naming the custom entities.
- Generate the ETL artifacts.
- Do not modify OOTB ITBA views, Business Contexts, BO Universes and Webi Reports

Enforcing those guidelines will guarantee that the solution will never be overridden in the future and be upgradable

Content Extension Rules

This section includes a set of best-practices and guidelines for creating customization tracks.

- Do not modify the OOTB entities:
 - Avoid modifying:
 - Any existing files in any OOTB Content Pack directories.
 - Any existing OOTB engineercontext diagram and architectcontext diagram in the IDE.
 - Avoid linking the custom dimensions to the OOTB entities.

Note: Instead of linking the custom dimensions to the OOTB entities, use the Target Extension link from the custom entity to the OOTB entity.

- Use the _CSTM suffix when naming the custom entities.
- Generate the ETL artifacts.
- Do not modify OOTB ITBA views, Business Contexts, BO Universes, CAPs, and Webi Reports.

Enforcing those guidelines will guarantee that the solution will never be overridden in the future and be upgradable.

IDE User Interface Overview

The ITBA IDE is the Eclipse based plug-in that offers the visual tools for modeling the DWH entities and creating the distributable ITBA content packs.

The IDE UI consists of three parts:


- 1. Package Explorer
- 2. Data Source Browser
- 3. Diagram Editor

IDE Main Page

The IDE main page enables you to create Designers for the purpose of extending content to entities. The following describes the IDE main page and icons.

The IDE Eclipse Main Page

The IDE requires basic knowledge of Eclipse and its capabilities. The following describes the IDE layout and icons. Select **Window > Show View** to add to and change the view of the various tabs and areas.



BA IDE - cp-alm-engineer/cycle.engine					_ # X
File Edit Source Refactor Diagram DW					
] 📑 🕶 🔛 🐚] 📀] Tahoma	▼9 ▼ B I A * 3 *.	¢ × → • @ ‰ • ﻫ • ‰ • ₫ ⊬ × «	• 100% <u>•</u> EIL		🗈 🌌 BA IDE 🐉 Java
Package Explorer 😫 📃	*cycle.engineercontext_clagram				
🗆 😫 🗸					A 😳 Palette 👂
🕑 😂 co-alm					
🗄 🧽 cp-alm-11-generic					
🗄 🗁 cp-alm-engineer		CYCLE		C CYCLE	🗁 Target Entity 🛛 🖘
🕀 😂 cp-am		NAME	ALM - CYCLE Transformation	Golumns	2 New Target Entity
E 😂 cp-am-9.5-oracle		START_DATE	Columns	COULTINS CYCLE_NAME	🚪 Load Target Entity
B Grans		♦ END_DATE	CYCLE_NAME	DATE START	11 Target Column
🗄 😂 cp-aws-1-csv		DEV_PROJECT	DATE_START		🕞 Integration En 😄
🗄 🥁 cp-aws-engineer			DATE_END	TATE_END	
🗄 🗁 cp-awscw		OOMAIN_	PROJECT_GROUP	PROJECT_GROUP	New Integration Entity
B 😂 cp-awscw-1-cw B 🥪 cp-awscw-1-ec2	G ALM.11.generic.CYCLE	♦ ID	S PROJECT_GROUP	Associated Dimensions	Load Integration Entity
B C cp-awscw-engineer	ADMITIGENERICIC TOLL	♦ PARENT ID	Associated Dimensions	ROJECT	
🗄 😂 cp-azure			ROJECT	all respect	Integration Column
🗄 😂 cp-azure-1-generic					Source Entity 🗠
B 🗁 cp-azure-engineer					New Source Entity
B 😂 cp-core B 🎲 cp-core-architect					Load Source
B 😓 (p-csa					Entity
🕀 🗁 cp-csa-3.1-generic					A Source to
🗄 😂 cp-csa-4.0-generic					Integration Relation
B 🗁 cp-csa-4.5-generic					22
B 😂 op-csa-engineer B 😂 op-cstm					😕 Transformation 🗠
🗄 🧽 co-cstm-9.2-mssal					Column Mapping
😑 😉 🔚 🤜 🚵 🖆 🗄 🎽					
- 🗁 Database Connections					
CDA Data Sources Plat File Data Source					
Web Services Data Source					
- 🦢 XML Data Source					<u>×</u>
	<u> </u>				Þ
	Properties 🕴 🥐 Problems				👍 🐉 🕾 🛃 🔍 🖻
	Property		Value		[.
	L		1		
10					

IDE Workspace: Main area where all IDE functions are located.

User interface elements are described below (when relevant, unlabeled elements are shown in angle brackets):

UI Element	Description
Package Explorer	A list of all of the available loaded Content Packs and Designer diagrams.
Canvas	Displays model diagram.
Problems	Displays validation errors and warnings.
Properties	Displays property tabs according to the selected entity in the Designer.
Error Log	Reports system errors.
Data Source Explorer	Enables you to connect to a specific data source and browse the database.
EIL	ETL Generation. Appears when a designer is open in the canvas. Click to perform the ETL process and generate the artifacts and create a new Content Pack. For details, see "Generate Content" on page 92.
	Save. Click to validate and save your mappings and configurations.
*	Report a Bug. Click to gather information for a bug report packaged in a ZIP file.
O	Validate. Click to manually perform validations on the Designer.
Ê	Perspective. Select to switch to recommended IDE perspective.
	This perspective contains all of the relevant buttons, areas, and functionality for working in the IDE.

IDE Icons

lcon	Description
C	Indicates a Target entity.
G	Indicates an Integration entity.
	Indicates a Source entity.
1	Indicates a Target extension entity.

lcon	Description
*	Indicates a Integration entity column.
	Indicates a Fact entity column.
	Indicates a Dimension entity column.
5	Indicates an association between Fact and Dimension entities.
2	Indicates an association between Dimension entities.
	Indicates a column which exists both as a Fact and as a Dimension.
•	Indicates a consolidation column.
	Warning that appears when you save a problematic change to a model that might cause an error at a later stage in the process. You can view the details by hovering over the icon on the model or in the Problems tab.
8	Error that appears when there is a design problem with your model in a designer. For example, the length of a column is too long. You can view the details by hovering over the icon on the model or in the Problems tab. Right-click an error to check if Quick Fix has been enabled for the problem. For details, see "Manage Validation" on page 80.


Package Explorer

The Package Explorer shows and allows importing\creating the content pack directories.

All the pieces of the DWH entities modeled in the IDE – target, integration and source entities - are stored as the metadata in the core, integration and source content packs directories correspondingly as the xml files.

There is one directory for the Core CP (**cp-core**), one integration content pack directory per product (**cp-Product_Name>**) and multiple directories for the source content packs per product per version per extractor type (**cp_<Product_Name>_<Product_Version>_<Extractor_Type>**).

There are also directories where the data flow and data model diagrams are stored (**cp_<Product_ Name>_<engineer\architect>**).



All the OOTB content packs source directories are shipped with the IDE package and can be imported into the Package Explorer for extension or reference.

Data Source Browser

The Data Source Browser allows connecting to the data sources or multiple kinds to be able to browse the source structure and data for reference purposes as well as to create the DWH entity and the entity diagram automatically based on the data source metadata.

The currently supported data source types are:

Databases

Diagram Editor

There are two types of diagrams in the IDE:

- Architect Target Designer
- Engineer Stream Designer

The **Architect Target Designer** is used for modeling the Target data model: the target entities and the links between them.


The Designer refers to the Core CP directory – all the entities modeled in it are created as the xml files in the Core CP directory once the Designer is saved.

The entity is visualized as the table with the fields, it has the properties with entity type selections (fact and/or dimension) and the set of fields attributes based on the entity type.

The designer has the Palette with the available actions:

- Entities
 - New Target Entity create a new target entity placeholder on the canvas
 - Load Target Entity load the existing target entity from the Core CP directory (cp-core)
 - Target Column add the column to the target entity
- Target Entities Relation
 - Dimension to Dimension create the intersection point between the dimensions.
 - Fact to Dimension create the intersection point between fact and dimension.
 - Target Extension create the reference between the OOTB and the custom entity that is created as the extension.

Physically the link between the entities is presented as a FK column in the entity table that refers to the record in the linked dimension table.



The Engineer Scream Designer allows creating the data path from the source to the target entity.

The Designer works with the selected Source, Integration and Core CP so that the new\existing entities are created\loaded in\from the specific source, integration or core CP directories.

The usual approach is to load the Target Entity that was previously created in the Architect Target Designer and create the new Source\Integration entities and map the fields to the Target entity.

In rare cases when the Target Entity is not supposed to be linked to any other dimension entities, it can be created directly in the Engineer Stream Designer.

The Integration Entity has the Properties where the columns data types and lengths of the fields should be set as well as the Business Key, Last Modified and nullable columns should be selected.

Integration	on							
General								
Columns	Columns							
Appearance	ID	Business Name	Description	Data Type	Length	Null Allowed	Business Key	Last Modified
	SRC_LASTMODDATE	Last Modification Date	Last Modification Date	Date Time	_	•		۲
	STATUS	Incident Status	Incident Status	VARCHAR	60	v		0
	INCIDENT_TYPE	Incident Type	Incident Type	VARCHAR	60	-		0
	CATEGORY	Category	Category	VARCHAR	60	•		0
	SUBCATEGORY	Subcategory	Subcategory	VARCHAR	60	×		0
	ACTIVE_PROCESS	Active Process	Active Process	VARCHAR	1	✓		0
	PRIORITY_CODE	Priority	Priority	VARCHAR	60	-		0
	INCIDENT_NUMBER	Reference Number	Reference Number	VARCHAR	100		1	0
	RESOLUTION_CODE	Completion Code	Completion Code	VARCHAR	60	•		0
	INITIAL_IMPACT	Impact Scope	Impact Scope	VARCHAR	60	√		0
	SEVERITY	Urgency	Urgency	VARCHAR	60	✓		0
	ESCALATION	Escalation	Escalation	VARCHAR	1	~		0
	DOWNTIME_START	Outage Start Date	Outage Start Date	Date Time		~		0
	DOWNTIME_END	Outage End Date	Outage End Date	Date Time		•		0
	CLOSE_TIME	Close Time	Close Time	Date Time		-		0
	AFFECTED_ITEM	Service Name	Service Name	VARCHAR	100	√		0
	REOPEN_TIME	Reopen Time	Reopen Time	Date Time		•		0
	OPEN_TIME	Create Time	Create Time	Date Time		~		0
	COMPANY	Requested By Org	Requested By Org	VARCHAR	100	•		0
	ASSIGNMENT	Assigned To Org	Assigned To Org	VARCHAR	100	-		0
	LOCATION	LOCATION	Location	VARCHAR	100	×		0

The Source Entity has the Properties that are based on the DB query concept and where the extraction attributes like Table\Join Condition, Where clause and the columns names\aliases and rules can be defined.

Properties 8	3		g v - D
Source			
General	General Attributes		
Columns Appearance	ID: PROBSUMMAR Content Pack: SM-9.2-MSSQL		
	Data Source SQL Clauses		
	Group By:		*
	Table Name / Join Condition:	PROBSUMMARYM1 P1 INNER JOIN PROBSUMMARYM2 P2 on P1.NUMBER = P2.NUMBER	*
	Where:		*

Source							
eneral							
olumns	Columns						
ppearance	ID	Туре	Not Applicable	Table Name	Column Name	Fixed Value	Calculation Rule
	SRC_LASTMODDATE	Direct	N	P1	SYSMODTIME		
	STATUS	Direct	N	P1	PROBLEM_STATUS		
	INCIDENT_TYPE	Rule	N				CASE WHEN P1.CATEGO
	CATEGORY	Direct	N	P1	CATEGORY		
	SUBCATEGORY	Direct	N	P1	SUBCATEGORY		
	ACTIVE_PROCESS	Rule	N				CASE WHEN P1.FLAG = '.
	PRIORITY_CODE	Direct	N	P1	PRIORITY_CODE		
	INCIDENT_NUMBER	Direct	N	P1	NUMBER		
	RESOLUTION_CODE	Direct	N	P1	RESOLUTION_CODE		
	INITIAL_IMPACT	Direct	N	P2	INITIAL_IMPACT		
	SEVERITY	Direct	N	P1	SEVERITY		
	ESCALATION	Rule	N				CASE WHEN P1.STATUS .
	DOWNTIME_START	Direct	N	P1	DOWNTIME_START		
	DOWNTIME_END	Direct	N	P1	DOWNTIME_END		
	CLOSE_TIME	Direct	N	P1	CLOSE_TIME		
	AFFECTED_ITEM	Direct	N	P2	AFFECTED_ITEM		
	REOPEN_TIME	Direct	N	P2	REOPEN_TIME		
	OPEN_TIME	Direct	N	P1	OPEN_TIME		
	COMPANY	Direct	N	P1	COMPANY		
	ASSIGNMENT	Direct	N	P1	ASSIGNMENT		
	LOCATION	Direct	Y	PROBSUMMARYM1 P1	location		

Upon the linkage of the Source Entity to the Integration entity the attributed are populated automatically:

- The Integration Entity name is populated into Table Name field
- The Integration Entity columns are populated into the Columns fields.

Physically the Source Entity is saved as the source entity xml based on which the queries\calls to the data source are built.

The Palette has the set of available actions:

- Target Entity
 - New Target Entity
 - Load Target Entity
 - Target Column
- Integration Entity
 - New Integration Entity
 - Load Source Entity
 - Integration Column
- Source Entity
 - New Source Entity
 - Load Source Entity

- Source to Integration Relation (the source entity columns are not modeled by inherited from the Integration entity which the Source entity linked to)
- Transformation
 - Column Mapping create a direct mapping from the Integration Entity fields to the Target\Transformation Entity fields.




Diagram Editor - Architect Target Designer Tasks

The Architect Target Designer enables you to define a Target entity as well as link associations, or extend an existing entity. Each Target entity in the Architect Target Designer contains columns of fact, or dimension (or both) and associations to other Target entities.

Architect Target Designers can contain one or more Target entities. Usually each Architect Target Designer includes several entities that are related to the same subject (Designer). Target entities can be included in several Architect Target Designers.

The IDE supports the extension of a target entity by creating an association called Target Extension. This enables you to extend an entity by adding to the new entity columns. Adding an extension enables Fact extension and the ability to link a group of Dimensions specifically to the same group. You then use the extension entity to make all associations and links.

Note: Make sure you have selected the IDE perspective before beginning to work on your designer diagram.

Note: It is recommended to create a separate general project in the Package Explorer for the Architect Target Designer files.

To access:

In the IDE main page, select File > New >Other > DWH IDE Wizards > Architect Target Designer.





The Architect Target Designer enables the following:

- Create a new entity metadata which is translated into the Target model.
- Load an existing Target entity.
- Add columns which affect entity generation.
- Add associations between entities.

- Link a Fact to Dimension
- Link a Dimension to a Dimension
- Link an entity to an extension



This section includes:

Create a new Architect Target Designer in the IDE	43
Define a new Target entity	. 43
Load an existing Target entity	44
Extend a Target Entity	44
Add a column	45
Link a Dimension to a Dimension	45
Link a Fact to a Dimension	45

Create a new Architect Target Designer in the IDE

- In the IDE main page, select File > New > Other > DWH IDE Wizards > Architect Target Designer and click Next.
- 2. Select the parent directory and enter the file name for the Stream Designer diagram make sure you do not change the suffix of the file name and click **Next**.
- 3. Select the relevant Target Content Pack directory and click **Finish**.

Define a new Target entity

- 1. In the Architect Target Designer, in the palette area, select **New Target Entity** and click on the canvas.
- 2. Name the entity.
- 3. Add relevant columns to the entity.



Load an existing Target entity

- 1. In the Architect Target Designer, in the palette area, select **Load Target Entity** and click on the canvas. The Resource Selector dialog box opens.
- 2. Expand the target directory and select an entity. The entity is displayed with all of the previously added columns and dimensions.
- 3. Add relevant columns to the entity. You can then edit and configure columns in the Properties view.
- 4. Click **Save**.

Extend a Target Entity

- 1. In the Architect Target Designer, in the palette area, select **Load Target Entity** and click on the canvas to load the target entity that you want to extend. The Resource Selector dialog box opens.
- 2. Expand the target directory and select an entity. The entity is displayed with all of the previously added columns and dimensions.
- 3. Select **New Target Entity** and click on the canvas to add the entity which will be the target extension.
- Name the entity. If you are extending the Person entity, for example, you can enter PERSON_ CSTM.
- 5. In the Properties tab of the new entity, configure the entity Type (**Fact** or **Dimension**). Must be the same entity type as the base entity.
- 6. In the palette area, click **Target Extension**.
- 7. Drag the arrow from the new extending entity to the original loaded entity.
- 8. This relation creates an extension to the new entity. The new entity name is displayed as an extension in the original entity. You can add relevant columns and configure the extended entity as necessary. Mapping is then done from the Integration to the Target extension.

Note:

• The extending and base targets are referred to as a single entity. Therefore, you can not add a column with the same Column ID of one in the original base entity.

- When you add an extension, make sure that the Source and Target are from the same type.
- Target Extensions can also be extended.
- The name of the extension is derived from the name of the extended entity and cannot be changed.

Add a column

- 1. In the Architect Target Designer, in the palette area, select **Target Column**.
- 2. Click in the Column area of your entity and enter the Column ID in the text box.

The column is added to the entity. You can then edit and configure columns in the Properties view.

3. Click Save.

Link a Dimension to a Dimension

- 1. In the Architect Target Designer, in the palette area, click **Dimension to Dimension**.
- 2. Drag the arrow from a Dimension to the Dimension you want it linked to.
- 3. The New Dimension to Dimension dialog box opens. The default name is displayed and can be edited. This relation links a Dimension entity to another Dimension.

Note: If you link to an entity from an existing association, you can connect using the arrow without naming the Associated Dimension.

The default Associated Dimension name is the Target entity.

4. Click Save.

Link a Fact to a Dimension

- 1. In the Architect Target Designer, in the palette area, click **Fact to Dimension**.
- 2. Drag the arrow from the Fact entity to the Dimension you want it linked to.
- 3. The New Fact to Dimension dialog box opens. The default name is displayed and can be edited.

This relation links a Fact entity to another Dimension.

Note: If you link to an entity from an existing association, you can connect using the arrow without naming the associated Dimension.

The default associated dimension name is the Target entity.

4. Click Save.



Create Architect Target Designer

🚝 New DWH Architect Target Designer	
Create Architect Target Designer Select a project which will contain the architect target designer file.	
Enter or select the parent folder:	
<pre></pre>	
cp-sm-engineer	-
File name: default.architectcontext_diagram Advanced >>	
Sack Next > Finish	Cancel

UI Element	Description
Enter or select the parent directory	Select the directory in which this Designer will be contained, from the directory list.

UI Element	Description
File Name	Enter a file name for your Designer diagram.

Target Content Pack

New DWH Architect Target Designer	
Target Content Pack Select target content pack directory	
Target content pack:	Browse
Reck Next > Fini	sh Cancel

UI Element	Description
Target Content Pack	Select or browse for the Target Content Pack directory.

Architect Target Designer View

File Edit Diagram DW Content Window Help						
			• 🈂 • 🔄 🖂 🛪 😑 • 🛛 100%	≠ EIL		🗈 🖬 BA IDE 💐 Java
📬 • 🔛 🚱 🕐 Tahoma 🗵 🖓 💌	Tellbis and	Proteene Concerned Attributes Grand attributes	C BILLING C BILLING MARKEN, FAM MARKEN, FAM MARKEN, FAM C BARKY, JAK C BARKY, JAK C BARKY, JAK C BARKY, JAK S, SENSZ,		C PERIOD Conne	C ALL V V V V C ALL V V V V V C ALL V V V V V V V V V V V V V V V V V V
	Stream Appearance	ID: Busines Name: Description ID: Description ID: Foct			/EPICO Period Period	

Palette Area

UI Element	Description
Entities	 Contains the following Target entity options: * New Target Entity. Creates a new Target entity. Entity type can be defined in the Properties tab. To view the Properties tab, right-click on the specific entity and click Show Properties View. * Load Target Entity. Opens the Resource Selector dialog box. Select the relevant entity for your model.

UI Element	Description
	Resource Selector
	CORE ABC / ABC ACTUALCOST / Actual Cost Lines APPLICATION / Applications BACKUP_POLICY / Backup Policys BACKUP_SESSION / Backup Session BUDGET / Budgets BUDGET LINE / Budget Lines BUSINESS_APP_STATUS / Business Application Status BUSPROCESS / Business Process OK Cancel
	 Target Column. Adds columns to entities. Column properties, for example column type, can be edited in the Properties tab. Each added attribute impacts the relevant entity generations.
Target Entities Relation	 Click a link to create connections for building the model. Dimension to Dimension. Link from one Dimension to another Dimension. A red arrow is displayed between the entities. Fact to Dimension. Link from a Fact to a Dimension. This type of relation
	 requires that the fact type was defined in the entity properties. A blue arrow is displayed between the entities. Target Extension. Link from a new target entity to the base/original target entity. A black arrow is displayed between the entities.

Properties tab for Target entity and specific fields

To view the Properties tab, right-click on the specific entity and click **Show Properties View**.

You first configure the Target entity properties, and then the properties for each specific column.

UI Element	Description
General tab	Displays the Entity, Dimension and Fact attributes for the target entity.
	General Target entity attributes:
	• ID : The ID of the entity.
	Business Name: The complete business name.
	• Description: Enter a description of the entity.
	Dimension/Fact Checkbox: Select one or both for the entity.
	If you change the selection, a dialog opens, warning that you may lose information previously entered in the Columns tab.
	Note: Make sure to select the required option connected to the relevant Fact or Dimension column properties.
Columns tab	Displays information for each column in the Target entity. Column property options are displayed according to the entity selection of Fact or Dimension in the General tab.
	• ID. The ID of the entity.
	Business name. The complete business name.
	• Description. Enter a description of the entity.
	Data Type. Varchar, Int 16, Int 32, Float, Localized Date Time
	• Length. Only for Varchar data type. The length of a Varchar column must be more than 0 and less than 4000.
	• Null Allowed. Select if the field can have the value NULL.
	 SCD Type. Slowly Changing Dimension type can be either 1 or 2. Only for Dimension.
	SCD1: For update.
	SCD2: For preserving history.
	Measure. Select only for Fact.
	Calculation Formula. The calculation of the measure. (Optional)

UI Element	Description
	• Summary. Select SUM, MIN, MAX, or AVG. (Optional)
Appearance tab	Displays font and appearance information.


New Associated Dimension Dialog Box

When you link to an unlinked Dimension, the following dialog box opens.

nsert associated dimension na	ame
BUSPROCESS2	

Edit an Associated Dimension name. The default is the Target entity name.

Target Extension Entity



Properties tab for Associated Dimensions

To view the Properties tab, right-click on the specific entity and click **Show Properties View.**

UI Element	Description
Associations tab	Displays Dimension association information:
	• ID. The ID of the entity.
	Business Name. The complete business name.
	• Description. Enter a description of the entity.
	• Type. Select Dimension, Fact, or Both.
	SCD Type. For Dimension only.
	• From Target. The Target entity.
	To Target. The Associated Dimension
Appearance tab	Displays font and appearance information.

Diagram Editor - Engineer Stream Designer Tasks


The Engineer Stream Designer enables you to define the integrations and how they are transformed and connected. This view defines the mapping relations for the entity from the source to the target. You can create new integrations based on graphical diagrams, using the Engineer Stream Designer in the IDE tool.

Note: Make sure you have selected the IDE perspective before beginning to work on your designer diagram.

To access:

In the IDE main page, select File > New > Other > DWH IDE Wizards > Engineer Stream Designer.





The Engineer Stream Designer enables you to extend and add content from the Integration and Source Content Packs into the target model. Using a new or existing Target entity, you can add new or existing content from the Integration and Source entities. You then perform transformation and Source Integration mapping for new and pre-loaded entities. The Source, Integration and Target entities are mapped using the Transformation Mapping connector, which creates a new mapping entity. All further mapping is done to the new entity in order to complete the Target model.

Note: All Source entities must be connected to an Integration entity.

Entities in the Engineer Stream Designer are mapped as follows:

- Source Entity: Mapping to the correct source, meaning the version the data is extracted from.
- Integration Entity: Contains the mapping of all fields.
- Target Entity: Several consolidation entities can be consolidated into one entity.

It is recommended to map from the Source to the Target.

Source Extractors

OOTB set of existing supported extractors are:

- Generic Extractors
 - DB Extractor: Supports MSSQL, Oracle and MySQL databases.
 - File Extractor: Supports general CSV file.
- Source Specific Extractor

Connecting to the integration:

ETL Gen templates in the back-end generate integration templates which utilize Data Collection Service (DCS). Load the Source metadata to the IDE and then map it to the correct consolidation entity in the relevant fields. To create a custom DCS extractor, see the DCS Extractor SDK Guide.


Important Information

Note: Creating new Target entities with Associated Dimensions can only be done in the Architect Target Designer.

Recommended

When you generate ETL artifacts with IDE, if you just put the source and integration entities in the engineer diagram, but do not map any columns with target attributes (no associated dimensions) from source to target (Left to Right), the IDE does not generate the data model correctly, and the ConsolidationReferences in the Extraction model is incomplete.

It is recommended to map at least one column to the target attributes for every integration entity.





This section includes:

Create a new Engineer Stream Designer in the IDE	56
Define a new Target entity	57
Load an existing Target entity	57
Define a new integration entity	57
Load an existing integration entity	57
Define a new source entity	58
Load an existing source entity	58
Add a column	58
Map from the Integration to Target	59

Create a new Engineer Stream Designer in the IDE

- In the IDE main page, select File > New > Other > DWH IDE Wizards > Engineer Stream Designer and click Next.
- 2. Enter or select the parent directory and enter the file name for the Engineer Stream Designer

diagram - make sure you do not change the suffix of the file name - and click Next.

3. Select the Target, Integration, and Source Content Pack directories and click Finish.

Define a new Target entity

- 1. In the Engineer Stream Designer, in the palette area, select **New Target Entity** and click on the canvas.
- 2. Name the entity.
- 3. Add relevant columns to the entity.
- 4. Click Save.

Load an existing Target entity

- 1. In the Engineer Stream Designer, in the palette area, select **Load Target Entity** and click on the canvas. The Resource Selector dialog box opens.
- 2. Select an entity. The entity is displayed with all of the previously added columns and dimensions.
- 3. Click Save.

Define a new integration entity

- 1. In the Stream Designer, in the palette area, select **New Integration Entity** in the Integration section and click on the canvas. An integration entity is displayed.
- 2. Enter a name. The name can be up to 44 characters. An Integration entity is created.
- 3. Click Integration Column to add a column to the entity.
- 4. Perform mapping if required.
- 5. Click Save.

Load an existing integration entity

- 1. In the Stream Designer, in the palette area, select **Load Integration Entity** in the Integration section and click on the canvas. The Resource Selector dialog box opens.
- 2. Select an entity. The entity is displayed with all of the previously added mappings.

Define a new source entity

- 1. In the Engineer Stream Designer, in the palette area, select **New Source Entity** in the Source section and click on the canvas. A Source entity is displayed.
- Click Source-Integration Relation and drag the display arrow from the Source entity to an Integration entity. All columns from the Integration entity are copied to the Source entity with default values.
- 3. Click **Save**.

Note: The Source-Integration Relation tool only enables you to link Source entities to Integration entities of the same product (content pack). For example, a Source entity from cp-sm-9.4-dbdict-mssql can only be linked to Integration entities from cp-sm and not cp-ppm.

Load an existing source entity

- 1. In the Engineer Stream Designer, in the palette area, select **Load Source Entity** in the Source section and click on the canvas. The Resource Selector dialog box opens.
- 2. Select an entity. The entity is displayed with its mapped integration entity.

Add a column

- 1. In the Engineer Stream Designer, in the palette area, select **Target Column** or **Integration Column**.
- 2. Click in the Column area of your entity and enter the Column ID in the text box.

The column is added to the entity.



Note: Source data is replicated from the integration entity. If you add or delete columns from the Integration, however, it is not automatically done in the Source.

To add: Once you have added the column, delete the mapping link and re-map from the Source to Integration.

To delete: Right-click the deleted column, delete the mapping link and re-map from the Source to Integration.

Alternatively, you can use the Quick Fix mechanism on the error that appears in the Problems tab. For details, see "Manage Validation" on page 80.

Map from the Integration to Target

Once you have added columns to the Integration entity you can perform SSI mapping.

- 1. In the Engineer Stream Designer, in the palette area, click **Column Mapping** in the Relations section to map the Integration to the Target entity.
- 2. Drag the arrow from the Integration column to the Target column.
- 3. After you have performed the first SSI mapping, a transformation SSI entity is created to which you can perform further mapping. Any integration entity from the same CP that should be mapped to this Target, must be mapped to the transformation entity.
- 4. Click Save.

Note: If an Integration column is already mapped to a Target column, you cannot perform further mapping from the same Content Pack.

Two Integration entity columns from the same Content Pack cannot be mapped to the same Target entity column.



Engineer Stream Designer View

File Edit Diagram DW Content Window Help		
	87 入・ジ・ブ・ヨ・	😭 🌌 BA IDE 🐉 Java
😫 Package Explorer 🖾 📄 🍇 🏱 🖓 🗎	PPPM_ORG_engineercontext_dagram_33	- 8)
🖲 🥁 g-core-architect		A Palette
B 📴 q-ca		[]. Q. Q
🗄 🗁 cp-csa-3.1-generic		
🕀 🗁 op-csa-engineer	E DRG	🗁 Target Enkity 🗢
B 😂 cp-ppm		🛬 New Target Entity
🗄 😁 cp-ppm-8.0-orade	Laures	Sa Load Target Entity
8 🗁 cp-ppm-9:1-oracle 8 😂 cp-ppm-engineer-context	A COLOR MANY	Target Column
PPM_ACTUALCOST.engineercontext_diagram	I MANAGER LD	
PPM BLDGET engineercontext diagram	PAREIIT_ORG_INIT_ID CRG_NAME_ALT RAG_INITERNAL	🕞 Integration En 🗢
PPN_BLDGETLINE.engineercontext_diagram	PLAG INTERNAL	Sa New Integration
PPM_COSTCATEGORY.engineercontext_diagram	PPML8.0.oracle.KRSC_ORG_UNITS	Entity
PPM_EXCHANGE.engineercontext_diagram	© ORG_DALL_D	Real Load Integration
PPN_LOCATION.engineercontext_diagram	+ SPC_LASTMODOATE	Entity
PPM_ORG.engineercontext_diagram	Associated Dimensions	Column
PPM_PERSON.engineercontext_diagram		
PPM_PLANNEDCOST.engineercontext_dagram	Veri Wenkalar Right Parent	🕒 Source Entity 🗠
PPM_PRJOBJECTIVE.ongineercontext_dagram	EG MACHI	1 New Source Entity
PPM_PROGRAM.engineercontext_dagram PPM_project.engineercontext_diagram		Ca Load Source
PPM_project.engineercontext_diagram		
PPN projecttask engineercontext_diagram		
PPN_request.engineercontext_dagram		Relation
PPM_requestdetaiphd.engineercontext_diagram		- Transformation
PPM_requestheaderphd.engineercontext_diagram		
- PPM_requesttypeudphd.engineercontext_diagram		_,≓ Column Napping
🗄 😂 qə-sm 📃		
🙀 Data Source Explorer 23		
- % E * b 4 E *		
		-
- E Flat Fle Data Source		>
Web Services Data Source	Properties 23 A Problems	
>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>	• Engineer Context	
	* Engineer Context	
	Rulers & Grid Display Measurement	
	Appearance Show Puter Ruler Units Trackes V	
	Gid In Franz	
	⊂ Gid Une 🔽 Snap To Gid	
	Style Spaced Dut 💌 Restore Defaults	
1		

Palette Area

UI Element	Description
Target Entity	• Target Entity. Select to display a new Target entity.
	 Load Target Entity. Opens the Resource Selector dialog box. Select the relevant entity for your model.

UI Element	Description
	Resource Selector
	CORE ABC / ABC ACTUAL COST / Actual Cost Lines APPLICATION / Applications BACKUP_POLICY / Backup Policys BACKUP_SESSION / Backup Session BUDGET / Budgets BUDGET / Budget Lines BUSINESS_APP_STATUS / Business Application Status BUSPROCESS / Business Process OK Cancel
	 Target Column. Adds columns to entities. Column properties, for example column type, can be edited in the Properties tab. Each added attribute impacts the relevant entity generations.
Integration	Contains the following Integration entity options:
Entity	• The work of the select to the display a new Integration entity.
	• Load Integration Entity. Opens the Resource Selector dialog box. Select the relevant entity for your model.

UI Element	Description
	Resource Selector
	example column type, can be edited in the Properties tab.
	Each added attribute impacts the relevant entity generations.
Source Entity	Contains the following Source entity options:
	 New Source Entity. Select to display a new Source entity.
	 Load Source Entity. Opens the Resource Selector dialog box. Select the relevant entity for your model.

UI Element	Description
	Resource Selector Image: PPM.9.1.oracle Image: SM.7.11.dbdict_db2 Image: SM.7.11.dbdict_oracle Image: SM.7.11.dbdict_oracle Image: SM.7.11.dbdict_oracle Image: SM.9.2.oracle Image: SM.9.2.oracle Image: SM.9.3.oracle Image: SM.9.4.dbdict_oracle Image
Transformation	 Click to map the displayed entities. Column Mapping. Mapping between the Integration and Target columns. First time mapping is done from the Integration column to the Target column. A black arrow is displayed between the entities.
	First-time mapping creates a new entity for Transformation. Subsequent mappings are done to the new Transformation entity.

Properties tab for Integration

To view the Properties tab, right-click on the specific entity and click Show Properties View.

Note: Properties data is replicated in the Integration and Source columns. If you add or delete columns from the Integration, however, it is not automatically done in the Source.

To add: Once you have added the column in the properties tab, delete the mapping link and re-map from the Source to Integration.

To delete: Right-click the deleted column, delete the mapping link and re-map from the Source to Integration.

UI Element	Description
General tab	Displays the General entity attributes.
Columns tab	Displays column information:
	• ID. The ID of the column. It is taken from the mapped integration column and is read-only.
	Business name. The complete business name.
	• Description. Enter a description of the entity.
	• Data Type. Varchar, Int 16, Int 32, Float, Localized Date Time
	• Length. Only for Varchar data type. The length of a Varchar column must be more than 0 and less than 4000.
	• Null Allowed. Select if the field can have the value NULL. If you specify a Business Key, at least one of the columns must not Null Allowed.
	• Business Key. Primary key of the Integration field order. Select a number for the order of columns for placement. When no number has been assigned, you can only select 1. Subsequently you can assign any number to a column. If you change a number, all other assigned columns are automatically shifted down a spot in the order.
	Example If you change the Business Key of a column to 1 , the one that was specified previously as 1 becomes 2 .
	• Last Modified. The last date that the source has been changed. Select the button if you want a query from a certain date and not all possible data.

Properties tab for Source

To view the Properties tab, right-click on the specific entity and click Show Properties View.

UI Element	Description
General	General attributes:
tab	• ID. The entity ID.
	Content Pack. The Source Content Pack information.
	Data Source SQL Clauses:
	• Group by. The section in the SQL Query for the aggregation.
	• Table Name/Join Condition. Default is Integration entity name. If you change the table name, you must also change it in the columns. Enter the Join Condition for an SQL query with join.
	• Where. Where to extract for the SQL query for filtering data from the source.
Columns tab	Displays column information. The Source entity receives all of the Integration entity properties.
	• ID. The ID of the column. It is taken from the mapped integration column and is read- only.
	 Type. Select Fixed, Direct, or Rule. If you select Fixed, you must enter a Fixed Value. if you select Rule, you must enter the Calculation Rule.
	Not Applicable.
	 Table Name. Based on table name entered in the General tab. Relevant only if Direct type is selected.
	Column Name. The field name. Must be what appears in the Source entity.
	• Fixed Value. The fixed value of the column. Relevant only if Fixed type is selected.
	 Calculation Rule. The calculation rule of the column. Relevant only if Rule type is selected. The IDE does not support non UTF-8 characters in the Calculation Rule field.

For details on the Properties for Target entities, see "Properties tab for Target entity and specific fields" on page 51

For details on the Properties tab for Associated Dimensions, see "Properties tab for Associated Dimensions" on page 53.

The DW Content menu

The DW Content menu has several actions (that are also duplicated on the Toolbar):

- Report a Bug (the workspace is exported to the zip archive and can be sent to Support for investigation)
- Upgrade (applicable in case the entity was created in the previous IDE versions)
- Validate (check the opened diagrams for errors)
- ETL Gen (The generation of the ETL based on the opened diagram)

Obviously the most usable action is the ETL Gen.

By clicking this menu item\tool bar button the ETL Generator dialog is opened.

🚝 ETL Generator				×
BA ETL Version:	10.0	•		
Content Type:	BA Content	-		
🗖 Generate Conte	nt Pack			
Directory:				Browse
			OK	Cancel

Since the ETL artifacts are different in different ITBA versions, it is important to select the correct ITBA version.

The Content Type is **BA Content**...

Selecting the Generate Content Pack check-box allows generating the full content pack directory structure. It is applicable whenever the new content pack is selected. In case of the extension of the existing content packs, the generation of the CP directory structure is not required because only the delta artifacts are generated and merged to the existing content pack directory in the **\$HPBA_Home/ContentPacks** directory.

After specifying the settings above the location for the generated ETL artifacts should be selected.

The ETL artifacts are generated only for the Designer in context of which the ETL Generator dialog in opened.

The two directories are generated: Core – the target entity artifacts, and <Product_Name> - the source entity, integration entity and mappings artifacts. These two directories should be then copied into the **\$HPBA_Home/ContentPacks** directory.

Common Extension Scenarios

There are several most common extension scenarios:

- 1. Extension of the existing entity in the existing content pack
- 2. Extraction of the new entity in the existing content pack
- 3. Populating the existing entity from the new source
- 4. Extraction of the new entity from the new source

Extension of the existing entity in the existing Content Pack

In this scenario the main goal is to add more fields of the existing entity.

The approach is the following:

- 1. Use the existing Integration and Source (the required product version) content packs.
- 2. Model the new target entity and link it to the OOTB target entities using the Target Extension link.

Note: Make sure the name of the new entity includes the suffix _CSTM.

- 3. Model the new Integration and Source entity
- 4. Generate the ETL without creating the new content pack (just the delta is generated).
 - a. Only new entity artifacts are used (not the whole content pack) for both Core and Product content packs and merged with existing CP directories in the ITBA content packs directory.

Extraction of a new entity in an existing Content Pack

The purpose is to bring the new entity from the data source which already has the OOTB integration with ITBA.

The approach is similar to the previous scenario; the only difference is that instead of the Target Extension link the Fact to Dimension or Dimension to Dimension link is used for linking the new entity with the OOTB entities.

Note:

• Make sure the name of the new entity includes the suffix _CSTM.

Populating an existing entity from a new data source

When the customer does has source systems with which ITBA does not have an OOTB integration but does have the necessary target entities with all the necessary fields, the approach for developing the integration is as follows:

- 1. Create new Integration and Source content packs.
- 2. Use the existing Target entity
- 3. Create new Integration and Source entities.

Note: Make sure the name of the new entity includes the suffix _CSTM.

- 4. Generate the ETL with the Generate Content Pack feature in order to create the new CP.
 - a. Only the Product Content Pack artifacts are used (the Core CP has the entity already) and are copied to the ITBA content packs directory as a new directory.

Extracting a new entity from a new source

There are cases when ITBA does not provide either the OOTB CPs or the suitable target entities that could fulfill the integration requirements. In this case the modeling of the all pieces is required.

- 1. Model the target entities and the references between them
- 2. Create new Source and Integration Content Packs

Note: Make sure the name of the new entity includes the suffix _CSTM.

- 3. Model new Integration and Source entities.
- 4. Generate the ETL with the Generate Content Pack feature in order to create the new CP.
 - a. The product CP directory is copied to ITBA content packs directory as a new directory
 - b. The Core CP directory (delta) is merged with the existing Core directory in the ITBA content packs directory.

Import Existing Content

When you extend your existing content using the IDE, you must import the relevant content packs you want to work with.

Note: You must import the Target Content Pack (cp-core) in order to extend or create content in the IDE.



Import existing content

- 1. Navigate to File > Import > General > Existing Projects into workspace and click Next.
- 2. Browse for the cp-core directory and click OK, click Finish to import the project.
- 3. Import all of the relevant content packs you need to work with.
- 4. Proceed to creating the Designers.

Define New Content Pack Project

The IDE comes with out of the box Content Packs which you can import to add and extend content. You can also create projects based on data from new content directories, which you must manually add and define.

Note: You must import the Target Content Pack (cp-core) in order to extend or create content in the IDE.

To access:

In the IDE main page, select File > New > Other > DWH IDE Wizards > Content Pack.





Create new projects from content directories

To create new projects from content directories:

- 1. Select File > New > Other > DWH IDE Wizards > Content Pack.
- 2. Select the type of project: **Source** or **Integration**.
- 3. Enter the relevant details for the project and click Next.
- 4. Select the relevant Content Pack reference for the project:
 - For new Integration CP select the Target Content Pack for the project.
 - For new Source CP select the Integration Content Pack for the project.
- 5. Click Finish.
- Proceed with defining the Architect Target and Engineer Stream Designer projects. For details, see "Diagram Editor - Architect Target Designer Tasks" on page 42 and "Diagram Editor -Engineer Stream Designer Tasks" on page 54.



Integration Project

Integratio	on Project	
	n Project ew integration content pack project.	
Product n	ame:	
🗾 Use de	efault location	
Location:	C:\Users\sussmanr\workspace	Browse
Working	sets	
	project to working sets	
Working	setsi	The Select
?	< Back Next >	Finish Cancel

UI Element	Description
Product Name	Name of the source product.
	Make sure that after you define the product name, you can view the file under the Integration project icp.dwmodelappintegration file.
Use Default Location	Select to use the displayed location for your new project.

UI Element	Description
Location	Browse to the location of the content directory.
Add project to working sets	Select to add this project to the current set of projects.
Working Sets	Select new working sets.

Target Content Pack Reference

Integration	Project	
	t ent Pack Reference t content pack.	
Referenced p	irojects:	
<table-cell></table-cell>	ore	
?	< Back Next >	Finish Cancel

UI Element	Description
Referenced projects	Select the Target Content pack for the new Integration project.

Source Project

Source Project	
Source Project	
Create a new source content pack project.	
Product Name	
Version	
Product Type	
Use default location	
Location: C:\Users\sussmanr\workspace\IDE	E Browse
Choose file system: default 👻	
Working sets	
Add project to working sets	
Working sets:	- Select
	xt > Finish Cancel
< Back Ne	xt > Finish Cancel

UI Element	Description
Product Name	Name of the source product.
	Make sure that after you define the product name, you can view the file under the Source project scp.dwmodelappsource file.
Version	Enter the data source version.
Product Type	Enter the data source type.
Use Default Location	Select to use the displayed location for your new project.

UI Element	Description
Location	Browse to the location of the content directory.
Add project to working sets	Select to add this project to the current set of projects.
Working Sets	Select new working sets.

Integration Content Pack Reference

🖶 Source Project				
Integration Content Pack Select integration content pack.	< Referenc	e		
Referenced projects:				
?	< Back	Next >	Finish	Cancel

UI Element	Description
Referenced projects	Select the Integration Content pack for the new Source project.

Define the Target Model

Before working with a specific designer, you should define the Target model and the related associations and mappings. The Target model describes the final version of the data that adheres to the design required by applications. Each table in the model contains both designed columns and static columns, which comprises the metadata, so that the administrator can have the visibility of ETL processing over the entity's data.


Target Model – Dimension or Fact: The target data models describe the format of the data that produces business intelligence analytics. The instantiated data models are dimension, fact, and hierarchy tables.

In the Architect Target Designer you define the target model containing the entities and links between them.

Extend the Period Entity

The Period target entity requires special mapping requirements in the IDE. The entity contains time and date related mapping and can only connect to date related sources and dimensions, for example START_TIME.

When you connect to a data source that has a Period entity, the data source consistently changes depending on configurations. Therefore you can only map to date-related entities and dimensions.



Delete an Entity Permanently

The IDE enables you to permanently delete an entity that is not needed or supported, from the file system. Make sure that no other entity contains any reference to the deleted entity.

Note: When you right-click a selected entity and click **Delete From Model**, the entity is only removed from the current designer and not from the file system.



Permanently delete an entity

To permanently delete an entity:

- 1. Delete the relevant entity from the canvas.
- 2. In the Package Explorer, expand the content pack that contains the entity you want to delete, for example **cp-sa**.

- ~ -増 Package Explorer 🖾 F ۸ 👂 🗁 cp-ppm b > > cp-ppm-8.0-oracle b > > cp-ppm-9.1-oracle b > cp-ppm-engineer-context 👂 🗁 cp-sm b > cp-sm-7.11-dbdict-db2 b > cp-sm-7.11-dbdict-mssql b 🗁 cp-sm-7.11-dbdict-oracle b 🗁 cp-sm-7.11-mssql b > > cp-sm-7.11-oracle b 🗁 cp-sm-9.2-mssql b > cp-sm-9.2-oracle Ξ b 🗁 cp-sm-9.3-mssql b > > cp-sm-9.3-oracle cp-sm-9.4-dbdict-mssql b 🗁 cp-sm-9.4-dbdict-oracle Ш ٠ 📃 þ
- 3. Delete the actual entity, for example **POLICY**, from the Package Explorer.


Manage Validation

The IDE performs validations on all Designers and entities created in the Designers. After you save your changes, you can view the errors and warnings that occurred during content development. You can perform a manual validation or use the Quick Fix solution to make the required fixes for validation.

Note: All validations are performed only after you have saved your changes to the Designers.

To access:

Click the **Problems** tab.



This section includes the following topics:

View the errors and warnings that occurred during content development	81
Manually perform validation	81
Quick Fix	82
Validation Table	84

View the errors and warnings that occurred during content development

After you save your changes, click the **Problems** tab, below, to view the errors and warnings that occurred during content development.

escription 🔺	Resource	Path	Location	Туре
🖃 😣 Errors (4 items)				
😣 Integration KNTA_REGIONS column: REGION_NAME - id is not unique	PPM_LOCA	/cp-ppm-engine	Integration	DWEnginee
😣 Integration KNTA_REGIONS column: REGION_NAME - id is not unique	PPM_LOCA	/cp-ppm-engine	Integration	DWEnginee
😣 Target LOCATION column LOCATION_NAME - id is not unique	PPM_LOCA	/cp-ppm-engine	Target Col	DWEnginee
😣 Target LOCATION column LOCATION_NAME - id is not unique	PPM_LOCA	/cp-ppm-engine	Target Col	DWEnginee
🖃 🙆 Warnings (11 items)				
🐁 Integration ASSIGNMENTM1 column MD_QUALIFIER: id attribute violates DW	P SM_ORG.e	/cp-sm-engineer	Unknown	DWEnginee
Integration USAGE column OPERATION: the id is a DB reserved word	aws_usage	/cp-aws-engineer	Unknown	DWEnginee
Integration USAGE column RESOURCE: the id is a DB reserved word	aws_usage	/cp-aws-engineer	Unknown	DWEnginee
🐁 Target ACTUALCOST_CSTM: no column is defined as measure for fact entity	Cost Model	/cp-core-architect	Unknown	DWArchite
A Target AWS_USAGE column OPERATION: the id is a DB reserved word	aws_usage	/cp-aws-engineer	Unknown	DWEnginee
Target AWS_USAGE column RESOURCE: the id is a DB reserved word	aws_usage	/cp-aws-engineer	Unknown	DWEnginee
💊 Target CFGITEM: no column is defined as measure for fact entity	SM_CFGIT	/cp-sm-engineer	Unknown	DWEnginee
🔈 Target INTERACTION: no column is defined as measure for fact entity	INTERACTI	/cp-core-architect	Unknown	DWArchite
💊 Target INTERACTION: no column is defined as measure for fact entity	SM_INTER	/cp-sm-engineer	Unknown	DWEnginee
🔈 Target PLANNEDCOST_CSTM: no column is defined as measure for fact entity	Cost Model	/cp-core-architect	Unknown	DWArchite
🔈 Target PROJECTISSUE: no column is defined as measure for fact entity	PPM_proje	/cp-ppm-engine	Unknown	DWEnginee

Manually perform validation

Additionally, you can manually perform validations on all Designers and fix relevant errors and warnings.

- 1. To activate, click 🔮 in the toolbar, or select **DW Content > Validate**.
- 2. During the validation process, a Progress Information dialog box appears specifying the current validated designer and its progress.

Progress Information	
Validating: /cp-bsm-engineer/ORG.engineercontext_diagram	
	Cancel

In case of an unreadable designer, an error dialog appears, listing the problem designer diagrams.

Validation Error		x
The following contexts failed validation:		
/cp-NNM-engineer/default.engineercontext_diagram /cp-alm-engineer/DEFECT.engineercontext_diagram /cp-alm-engineer/DEFECT_HIST.engineercontext_diagram /cp-alm-engineer/DEFECT_PLHD.engineercontext_diagram /cp-alm-engineer/DOMAIN_PROJECT.engineercontext_diagram /cp-alm-engineer/PROJECT.engineercontext_diagram /cp-alm-engineer/REQUIREMENT.engineercontext_diagram /cp-alm-engineer/REQUIREMENT.engineercontext_diagram /cp-alm-engineer/REQUIREMENTHISTORY.engineercontext_diagram /cp-alm-engineer/REQUIREMENT_BRIDGE.engineercontext_diagram /cp-alm-engineer/REQUIREMENT_PLHD.engineercontext_diagram /cp-alm-engineer/REQUIREMENT_PLHD.engineercontext_diagram		4 III >
	Close	

3. Click **Cancel** to cancel the validation process.

All validations are performed only after you have saved your changes to the Designers.

Quick Fix

The validation process also includes a Quick Fix validation which provides recommendations for solutions for validation problems displayed in the Problems tab.

To use the Quick Fix option:

1. In the **Problems** tab, under the **Warnings** or **Errors** list, right-click a warning or error and select **Quick Fix** to open the Quick Fix dialog box.

Quick Fix		- O X
Quick Fix Select the fix for 'Source VALIDATIONS: columns are not	synchronized with integration entity columr	ıs'.
Select a fix:		
Synchronize source with integration		
Problems: Resource	🔁 Location	Select All
👿 😣 default.engineercontext_diagram	Source VALID.1.VALID.VA	Deselect All
0	Finish	Cancel

- 2. Select the fix for the specific warning and click **Finish**.
- 3. Click **Save** and the error is removed.



Validation Table

Make sure all entities have been configured properly according to the following validations. An error or warning appears in the Problems tab once you have made the problematic change, and saved it. Note the validations that have the Quick Fix option available.

Error Text	Validation	Source	Integration	Target	Quick Fix
Target <target id=""> column <column id=""> - id length is greater than allowed</column></target>	Length of column names (including system suffix)	Up to 60 characters	Up to 60 characters	Up to 60 characters	
Integration <integration id=""> column <column id="">:- id length is greater than allowed</column></integration>					
Target <target id="">: id length is greater than 50 characters</target>	Length of entity names (including	Up to 60 characters	Up to 44 characters	Up to 50 characters	
Integration <integration id=""> id length is greater than 44 characters</integration>	system suffix)				
Sample errors:	Backslash (\) is	✓	✓	✓	✓
Target <target id="">: 'Business Name' field contains backslash (\) character</target>	not permitted in any field text.				
Integration <integration id=""> 'Description' field contains backslash (\) character</integration>					
Source <source id=""/> : 'Group By' field contains backslash (\) character					
Target <target id=""> column <column id=""> id attribute violates DW Platform reserved prefixes: starts with non alphabetic character</column></target>	Entity names and column names must start with alphabetic characters.	✓	✓	✓	√

Error Text	Validation	Source	Integration	Target	Quick Fix
Integration <integration id=""> column <column id="">: id attribute violates DW Platform reserved prefixes: starts with non alphabetic character</column></integration>					
Target entity is invalid. File containing the metadata was deleted Integration entity is invalid. File containing the metadata was deleted Source entity is invalid. File containing the metadata was deleted	Make sure an entity deleted from the file system is also deleted from the designer diagram.	✓	✓	✓	
Target <target id=""> column <column id=""> DataType is not defined</column></target>	Make sure Data Type is defined for all Target columns.			*	
Target <target id="">: no column is defined as SCD for dimension entity</target>	Make sure when a Target entity is defined as a Dimension that SCD Type is defined for at least one column.			✓	✓
Target <target id="">: no column is defined as measure for fact entity</target>	Make sure when a Target entity is defined as a Fact that Measure is selected for at least one column.			✓	•
Target <target id="">: not defined as FACT or DIMENSION</target>	Make sure a Target entity is defined as a Fact, or Dimension, or both. The entity type cannot be left unselected.			✓	

Error Text	Validation	Source	Integration	Target	Quick Fix
Target <target id="">: no column is defined as SCD for dimension entity Target <target id="">: no column is defined as measure for fact entity</target></target>	Make sure that when a Target entity is defined as a Dimension and a Fact, that at least one column in the entity is defined accordingly for each type.			✓	✓
	Note: If the Target entity contains only associated Dimensions, this validation is not performed.				
Target <target id="">: Invalid target extension. Target type doesn't match</target>	Make sure that the data type in the extended entity equals the type of the base entity.			~	
Target <target id=""> column <column id=""> - id is not unique in target extension</column></target>	Make sure column or Associated Dimension ID is unique in the Target extension			✓	
Target <target id="">: Target extension contains loop</target>	Make sure Target extension does not contain a loop, meaning the extension of a base entity can not also have the base entity as an extension. That would place the			✓	

Error Text	Validation	Source	Integration	Target	Quick Fix
	entities in a loop with each other.				
Target <target id=""> column <column id=""> id attribute violates DW Platform reserved prefixes: starts with non alphabetic character</column></target>	Integration names and in the columns first character must be a letter: [a-z][A-Z].	✓	✓	✓	~
Target <target id="">: id attribute violates DB character constraints (a-z A-Z 0-9 \$ # _) Target <target id=""> Associated Dimension <associated Dimension ID> id attribute violates DB character constraints (a-z A-Z 0-9 \$ # _)</associated </target></target>	Integration names and in the columns next characters should be a letter, a digit, or '_', '\$', or '#'.	~	✓	~	•
Target <target id=""> column <column id=""> id attribute violates DB character constraints (a-z A-Z 0-9 \$ # _)</column></target>					
Integration <integration id=""> id attribute violates DB character constraints (a-z A-Z 0-9 \$#_)</integration>					
Integration <integration id=""> column <column id="">: id attribute violates DB character constraints (a-z A-Z 0-9 \$#_)</column></integration>					
Source <source id=""/> <column ID>: 'Column Name' field violates DB character constraints (a-z A-Z 0-9 \$#_)</column 					
Target <target id="">: id attribute violates DW Platform reserved prefixes: MD_ or DI_ Target <target id=""> Associated Dimension <associated Dimension ID> id attribute violates DW Platform reserved prefixes: MD_ or DI_"</associated </target></target>	Integration names and in the columns must not start with one of the DW Platform reserved prefixes: MD_ or DI	✓	✓	✓	 Image: A start of the start of

Error Text	Validation	Source	Integration	Target	Quick Fix
Target <target id=""> column <column id=""> id attribute violates DW Platform reserved prefixes: MD_ or DI_</column></target>					
Integration <integration id="">id attribute violates DW Platform reserved prefixes: MD_ or DI_</integration>					
Integration <integration id=""> column <column id="">: id attribute violates DW Platform reserved prefixes: MD_ or DI_</column></integration>					
Integration <integration id=""> no business key is defined</integration>	Make sure that the Business		✓		
Integration <integration id=""> Business key sequence is not defined properly (Doesn't start at 1 or numbers are not sequential)</integration>	Key is specified. In case of more than one Business Key, they must be in order (1, 2, 3) without spaces in the numbering.				
Integration <integration id=""> Business key sequence must contain at least one column which is not Nullable</integration>	Make sure Null Allowed is not selected for at least one of the Business Keys.		✓		*
Target <target id=""> : No id is defined for column</target>	Make sure that the column has		✓	✓	
Target <target id=""> column <column id=""> - id is not unique</column></target>	an ID and it is unique.				
Integration <integration id=""> column <column id="">:- id is not unique</column></integration>					
Source <source id=""/> <column ID>: no value at table name field Source <source id=""/> <column< td=""><td>If a Source column has Type set as Direct, then make sure Table Name and</td><td>✓</td><td></td><td></td><td></td></column<></column 	If a Source column has Type set as Direct, then make sure Table Name and	✓			
ID>: no value at db column name field	Column Name are not empty.				

Error Text	Validation	Source	Integration	Target	Quick Fix
Source <source id=""/> <column ID>: no value at fixed value field</column 	If a Source column has Type set as Fixed, then make sure Fixed Value is not empty.	✓			
Source <source id=""/> <column ID>: no value at calculation rule field</column 	If a Source column has Type set as Rule, then make sure Calculation Rule is not empty.	✓			
Source <source id=""/> <column ID>: 'Column Name' field contains backslash (\) character Source <source id=""/> <column ID>: 'Column Name' field violates DB character constraints (a-z A-Z 0-9 \$#_)</column </column 	If a Source column has Type set as Direct, then make sure Column Name does not contain special characters. This validation runs only if the Product Type in the source Content Pack is the database type of either MSSQL, Oracle or MySQL.	✓			✓
Source <source id=""/> doesn't include join condition	Make sure that the Source entity has a Join Condition and Table Name specified.	✓			
Source <source id=""/> contained in <cp name=""> is not referencing to any integration entity</cp>	Make sure that a Source entity is mapped to an Integration entity.	✓	✓		
Source <source id=""/> : columns are not synchronized with integration entity columns	Make sure that the Source and Integration	*	*		

Error Text	Validation	Source	Integration	Target	Quick Fix
	entities are synchronized.				
Integration <integration id=""> column <column id="">: is not mapped to target column and data type is undefined Integration <integration id=""> column <column id="">: contains invalid mapping</column></integration></column></integration>	Make sure all mapped Integration columns are mapped accordingly to the Target or have been assigned a data type.		•		
Target <target id=""> column <column id=""> is defined as VARCHAR but has no length Integration <integration id=""> column <column id="">: is defined as VARCHAR but has no length</column></integration></column></target>	Make sure that the length of a Varchar column is more than 0.		✓	✓	
Target <target id=""> column <column id=""> is defined as VARCHAR but length is greater than allowed (4000) Integration <integration id=""> column <column id="">: is defined as VARCHAR but length is greater than allowed (4000)</column></integration></column></target>	Make sure that the length of a Varchar column is less than or equal to 4000.	✓	✓	✓	•
No id is defined for target entity No id is defined for integration entity	Make sure each entity has an ID defined.	*	✓	✓	
Target <target id=""> column <column id=""> the id is a DB reserved word Integration <integration id=""> column <column id="">: the id is a DB reserved word</column></integration></column></target>	Make sure the defined column name does not contain a reserved word. For details, see MSDN Microsoft SQL Server	✓	✓	✓	

Error Text	Validation	Source	Integration	Target	Quick Fix
	reserved keywords list.				

Generate Content

The IDE can generate the relevant schemas and ETLs that are required for the integration.


The ETL Generator generates the required artifacts based on the modeling in the previous steps. The artifacts contain ETL SQL scripts as well as the data models and stream configuration XML files that are imported into the Data Warehouse metadata repository. Once the metadata has been loaded, the schema generation mechanism performs the schema changes in the target and the staging databases.

To access:

When a designer is open, the ETL button is displayed in the top right toolbar in the IDE workspace. If it is not displayed, navigate to **Window** > **Customize Perspective** and make sure **BA IDE** is selected.

Click **EIL** to begin the ETL Generator.





Content Pack Creation Tool

The Content Pack Creation Tool enables you to create a new Content Pack structure using existing source content packs. This allows you to use the IDE to extend content as well as develop entirely new Content Packs for use in the Data Warehouse and ITBA.

The ETL Generator action is relevant to the selected designer. The ETL button is only displayed when a designer is open.



Create a new entity and a new Content Pack with the

ETL Generator

To create a new entity and a new Content Pack with the ETL Generator:

1. Click **IIL** in the toolbar on the top right of the IDE workspace to begin the ETL Generator. The ETL Generator dialog box opens.

🚝 ETL Generator				×
BA ETL Version: Content Type:	10.0 BA Content	-		
Generate Conte	ent Pack			Browse
			OK	Cancel

- 2. In the dialog box:
 - In **BA ETL Version**, select **10.10**.
 - In Content Type: select BA Content.
 - Select the Generate Content Pack check box if you are creating a new Content Pack (not existing content). This creates a new content pack structure along with the generated ETL files. This capability is only available when generating the ETL files in the Designer.

Note: The Generate Content Pack check box is not available when generating the ETL files from the Architect Target Designer.

When you generate the ETL files from the Engineer Stream Designer, the **Generate Content Pack** check box is disabled if there are no source entities in the Engineer Stream Designer.

- In **Directory**, browse to the directory where you want the generated Content Pack to be placed.
- 3. Click **OK**. The process may take some time.
- 4. Proceed to package and deploy your content.

Package and Deploy Content

After you have run the ETL Generator and saved the Content Pack, you must package your new or extended content solution.



Package and deploy content

Copy the generated files to the Content Packs directory on the DWH server.

• For Content Packs with added or extended entities: Go to UI to install the Content pack.

Users and Roles					
Notifications	Install Content Packs				
Semantic Layer	In this page you can easily install or Upgrade Content Packs				
	Content Pack Name	Content Pack Version	Status Update Date		
Settings	AWS	1.0	Not Installed	Install	
 Data Management 	CSA	1.0	Not Installed	Install	
Data Management Guide	AWSCW	1.0	Not Installed	Install	
Install Content Pack	PPM	1.0	Installed 2015-04-07 11:16:47 AM	Upgrade	
Connect Data Source	SM	1.0	Installed 2015-04-07 10:33:10 AM	Upgrade	
Configure Consolidation					
Run ETL	ALM	1.0	Not Installed	Install	
Activate CAP					
	-				

• For new Integrated Content Packs: Make sure your new CP is packaged in the correct directory structure by selecting the Generate Content Pack checkbox in the ETL Generator, and then copying it to the ContentPacks directory in your DWH installation.

Activate New Content

After you package and deploy new Content Packs, you activate the content in the ITBA Connect Data Source UI. Content that is created from databases (MSSQL,ORACLE and MYSQL) according to your specific Content Pack source.

To access:

In the ITBA application, select **ADMIN > Data Management > Connect Data Source**. Click **Add Data Source** and select the relevant Content Pack you have created.





Activate a new Content Pack

- 1. In the ITBA application, select Admin > Data Management > Connect Data Source.
- 2. Click the Add data source to open the Data source wizard. The Add Data Source page opens.
- 3. Select the CP you created and click **Next**.

The relevant data source page opens.

- 4. Enter and select the configuration parameters.
- 5. Complete the wizard.

The data source instance is activated.

For details on all ITBA Connect Data Source capabilities, see Connect the Data Source in the *Administrator Guide*.



CP Activation Page Options

Activation parameters are based on the Data Source Type of your Content Pack.

MSSQL Database Source CP

UI Element	Description
Instance name	Enter a name for the data source instance you are activating.
<cp name=""> Version</cp>	1
Time Zone	Select the time zone for the data source.
Data Source Type	Select MSSQL.
Username	Enter your username used to log on to the database.
Password	Enter your password used to log on to the database.
Hostname/IP Address	Enter the SQL server database hostname or IP address.
Port	Enter the server port number.
Database Name	Enter the database name used by the CP.
Initial Load Period (months)	Select the number of months from which you want the initial data loaded.

MySQL Database Source CP

UI Element	Description
Instance name	Enter a name for the data source instance you are activating.
<cp name=""> Version</cp>	1
Time Zone	Select the time zone for the data source.
Data Source Type	Select MySQL.
Username	Enter your username used to log on to the database.
Password	Enter your password used to log on to the database.

UI Element	Description
Hostname/IP Address	Enter the MySQL server hostname or IP address.
Port	Port for database connections.
Initial Database Name Load Period (months)	Select the number of months from which you want the initial data loaded.

Oracle Database Source CP

Note: The Oracle database can have both Server ID (SID) and Service Name properties, but the user should specify only one. If you define the SID, then the SID is used, and if you define Service Name, then Service Name is used. If you define both in the UI, only SID is used.

UI Element	Description
Instance name	Enter a name for the data source instance you are activating.
<cp name=""> Version</cp>	1
Time Zone	Select the time zone for the data source.
Data Source Type	Select Oracle.
Username	Enter your username used to log on to the database.
Password	Enter your password used to log on to the database.
Hostname/IP Address	Enter the Oracle server hostname or IP address.
SID	Enter the unique name of the database.
Service Name	Enter the alias used when connecting.
Initial Load Period (months)	Select the number of months from which you want the initial data loaded.

Advanced Development

Following the ETL Generator process, you can optionally access the following features and processes for advanced content development.

Data Source Explorer

Following the ETL Generator process, you can optionally access the following features and processes for advanced content development.

The IDE provides a Data Tool Platform plug-in which enables you to connect to a specific data source and browse the database. The Data Source Explorer enables connection to the data sources through the SQL, Oracle and MySQL drivers. You can then browse the database tables, make queries, and view the data source information.

To access:

To create a new data source connection profile, in the IDE main page, select Window > Show
 View > Other > Data Management > Data Source Explorer, right click Database Connections and right-click New.



This section includes:

Create a new database connection in the Data Source Explorer	99
Modify driver definitions	100

Create a new database connection in the Data Source Explorer

- Navigate to Window > Show View > Other > Data Management > Data Source Explorer. The Data Source EXPLORER tab is displayed.
- 2. Right-click **Database Connections** and then right-click **New**.
- 3. Select Oracle, SQL Server, or MySQL and click Next.
- 4. Enter the Database, Host, Port number, Username and Password.
- 5. Click **Test Connection** to check for errors with the connection to the database.
- 6. Click **Finish** to enable the connection to the database.

You can change the driver definitions or create another driver.

Modify driver definitions

Note: IDE provides out-of-the-box drivers for MSSQL, Oracle, and MySQL.


- 1. Navigate to Window > Preferences > Data Management > Connectivity > Driver Definitions.
- 2. Select the driver you want to change, or click Add to add an additional driver.

For details on the Data Tool Platform, see the Eclipse DTP tutorials.



Data Source Explorer

Note: IDE provides out-of-the-box drivers for MSSQL, Oracle, and MySQL.



 Right-click Database Connections and select New to create a new database connection. For details, see "Data Source Connection Profile" on the next page

Data Source Connection Profile

New Connection Profile	
Connection Profile Create a DB2 for Linux, UNIX, and Windows connection profile.	
Connection Profile Types: type filter text	
 DB2 for Linux, UNIX, and Windows DB2 for i5/OS DB2 for z/OS Derby Generic JDBC HSQLDB Informix Ingres MaxDB MySQL Oracle PostgreSQL SQL Server SQL Server 	
Name: New DB2 for Linux, UNIX, and Windows Description (optional):	
Seck Next > Finish	Cancel

UI Element	Description
<driver list=""></driver>	Select SQL, Oracle, or MySQL Server.

Specify a Driver and Connection Details

MSSQL Server

New Connection P	rofile
Specify a Driver an i Conter a user name	d Connection Details
Drivers: Microsoft S Properties Database: Host: Port number: Use integrated User name: Password: Save password Connection URL:	QL Server 2008 JDBC Driver pubs localhost 1433 authentication jdbc:sqlserver://localhost:1433;databaseName=pubs
Connect when the Connect every time	wizard completes the workbench is started < Back Next > Finish Cancel

UI Element	Description
Database	Enter the specific database name.
Host	Enter the host server.
Port number	Enter the database port.
User name	Enter the database user name.
Password	Enter the database password.
*	New Driver Definition. Click to configure new driver definitions. For details, see the Eclipse DTP tutorials.
Δ	Edit Driver Definition. Click to edit the current driver definitions. If you receive an error for the driver, check that the correct path is displayed in the driver files of the JAR list.

Oracle Server

6		
ivers: Oracle 11	hin Driver	• * /
Properties General Optio	nal	
SID:	db	
Host:	server	
Port number:	1521	
User name:		······································
Password:		
📝 Save passwo		
Connection URI		
Catalog:	User 👻	
	e wizard completes	Test Connecti
Connect every tin	ne the workbench is started	

UI Element	Description
SID	Enter the Server ID, the unique name of the database.

UI Element	Description
Host	Enter the host server.
Port number	Enter the database port.
User name	Enter the database username.
Password	Enter the database password.
*	New Driver Definition. Click to configure new driver definitions. For details, see the Eclipse DTP tutorials.
Δ	Edit Driver Definition. Click to edit the current driver definitions. If you receive an error for the driver, check that the correct path is displayed in the driver files of the JAR list.

MySQL Server

Select a driver f	er and Connection Details	
connection.		
Drivers: MySQI	. JDBC Driver	• * 🛆
Properties		
General O	ptional	
Database:	database	
URL:	jdbc:mysql://localhost:3306/database	
User name:	root	
Password:		
📝 Save pas	sword	
] Connect whe	n the wizard completes	Test Connection
] Connect ever	y time the workbench is started	

UI Element	Description
Database	Enter the specific database name.
URL	Enter the database URL.
User name	Enter the database username.
Password	Enter the database password.
۲	New Driver Definition. Click to configure new driver definitions. For details, see the Eclipse DTP tutorials.
Δ	Edit Driver Definition. Click to edit the current driver definitions. If you receive an error for the driver, check that the correct path is displayed in the driver files of the JAR list.

Generate Entities Automatically

You can generate entities from the source database tables or views. This enables you to automatically create Source, Integration or Target entities. Using the Data Source Explorer, you can connect to the source database and navigate to the source table or view. The entities are created based on the specific source metadata. MSSQL, Oracle, and MySQL source databases are supported. You can then load the entity to a new designer located in an existing project. The entity is then displayed in the new Engineer Stream Designer.





This section includes:

Automatically generate entities from database tables or views

Note: You can generate Source, Integration or Target entities using the Entity Generator wizard.

- Navigate to Window > Show View > Other > Data Management > Data Source Explorer. The Data Source EXPLORER tab is displayed.
- 2. Select either an SQL, Oracle, or MySQL Database and connect to the database.
- 3. Navigate to **Tables** or **Views** and right-click the relevant table or view from which you want to generate the entity and select **Generate DWH Entity**.

🎁 Data Source Explorer	×	
⊳	📅 db_securityadmin	
⊳	🛱 dbo	
4	n and a state of the state of t	
	Dependencies	
	Stored Procedures	
	🔺 🧰 Tables	
	AACOST_FACT	
	ACTUALCOST_FACT	
	ALLOCATION_METRIC	
	ALLOCATION_METRIC_REQUIRED_DIMS	
	APCOST_FACT	
	ASSET_FACT Data	•
	▷ III BACKUP_POL	
	BACKUP_SESS *	
	BUDGET_DIM Refresh	F5
	BUDGETLINE Generate DWH Entity	

- 4. In the Scenario page:
 - a. Select the type of content pack: **Source Content Pack**, **Integration Content Pack**, or **Target**.
 - b. If you have selected **Source Content Pack**, **Integration Content Pack**, select the relevant content pack.

When you select the Source Content Pack, the Integration Content Pack is automatically displayed.

If you have selected Target, select whether the entity is defined as a Fact or Dimension.

Note: When you generate an entity from an Oracle database, make sure that if you use reserved words, they are placed in quotation marks, for example, "NUMBER".

- 5. Click Next.
- 6. In the Load to Designer page, select to either load the entity to a New Designer, or No Designer .
- 7. If you selected **New Designer**, select from the drop down list, the project where you want the specific Designer to be located.
- 8. Click **Finish** to complete the wizard and create the entity. The new entity is now displayed in the IDE Package Explorer, and if relevant, loaded in the assigned designer canvas.



Entity Generator Wizard

"Scenario page" below > "Load to Designer page" on page 112 > "Complete Entity Generation with SSI mapping displayed in Stream Designer" on page 113

Scenario page

🚝 Entity Generator			_ 🗆 🗙
Scenario			
Select required entity genera	tor scenario		
ID:	CHANGE_CSTM		
Source Content Pack	PPM 9.1 oracle		•
☑ Integration Content Pack	PPM		
🔽 Target	Dimension	C Fact	
	<back next=""></back>	Finish	Cancel

Note: If you select to generate Integration and Target entities, **SSI Column Mapping** is automatically performed and displayed in the relevant designer.


UI Element	Description
ID	Enter entity name. The current table or view name is the default.
Source Content Pack	Select the checkbox and the Source content pack for the specific entity. This generates a Source entity and automatically selects the relevant Integration content pack.

UI Element	Description
	Notes:
	 If there is only one Source content pack in the workspace it is entered automatically and cannot be changed.
	This checkbox is disabled if there is no Source content pack in the workspace.
Integration Content Pack	Select the checkbox and the Integration content pack for the specific entity. The Integration content pack is automatically populated when the Source CP is selected.
Fack	Notes:
	 If there is only one Integration content pack in the workspace it is entered automatically and cannot be changed.
	• If only Integration Content Pack is selected, the Next button is disabled, and the entity cannot be loaded to a designer.
	• This checkbox is disabled if there is no Integration content pack in the workspace.
Target	Select the checkbox and whether the Target entity is defined as a Dimension or Fact . The entity is placed in the core-cp.
	If only Target is selected, the entity is loaded to the Architect Target Designer.

Load to Designer page

🚝 Entity Generator				
Load to Designer				
Select whether to load th	ne entities to	designer		
🔿 No Designer				
New Designer		cp-ppm		
	< Back	Next >	Finish	Cancel

UI Element	Description
No Designer	Select the checkbox and the generated entity is not displayed in a designer canvas.
New Designer	Select the checkbox for the generated entity to be displayed in a designer canvas. Select an existing project from the drop down list where the designer will be located.
	Note: If a Target entity was generated then the entity is loaded into an Architect Target Designer only. For Source and Integration entities, they are loaded into an Engineer Stream Designer.



Complete Entity Generation with SSI mapping displayed in Stream Designer

IDE Data Types

The follows shows Database Data Types and the conventions used for them in the IDE entity columns.

Database Data Type	IDE Data Type
BIGINT	Int32
INTEGER(INT), SMALLINT, NUMERIC, NUMBER	Int16
FLOAT, DOUBLE_PRECISION	Float
CHARACTER, NVARCHAR, VARCHAR, VARCHAR(2), CHARACTER_VARYING, CHARACTER_VARYING	VarChar (size)
CHARACTER_LARGE_OBJECT, CLOB, TEXT	VarChar (4000)

Database Data Type	IDE Data Type
DATE, TIMESTAMP, TIME, DATETIME,	Integration: Date Time Target: Localized Date Time
RAW16	No IDE Data Type. User must select a data type or delete the column.
IMAGE	No IDE Data Type. User must select a data type or delete the column.
BLOB	No IDE Data Type. User must select a data type or delete the column.

Data Source Extraction Customization

Integration with data sources is performed using the Data Collection Service (DCS). In order to generate the query executed for the data source, the Content Flow Manager tells the DCS framework which source entity to extract. The DCS then extracts the correlating metadata definitions, and uses them in order to formulate a query.



This section includes:

Customize the Source Model	115
Make changes in a field name	116
Make changes in a table name	116
Update the data warehouse metadata	

Customize the Source Model

You can customize the generated query by modifying the source entity xml file. This updates the source metadata in the Data Warehouse and matches it to the customized source.

- 1. Modify the XML and load it into the Data Warehouse metadata repositoryby logging on DWH and using the user interface.
- 2. Change the SQL query from the DCS log and run the query on the source database make sure the query is correct and can run without errors.
- 3. Identify all of the changes.

There are various types of customizations to the source models supported by the DWH. This document emphasizes cases where the data source that you extract information from is based on RDBMS, and entities which are already modeled in the DWH have had field names or table names changed in the data source's structure.

The Data Source's source model metadata xml files are located under:

\$HPBA_

HOME/ContentPacks/<CPname>/INBUILT/DATAMODEL/DATAINTEGRATION/SOURCE/<produ ct_version>/<DB_type>/<entity_name>.xml

Example

\$HPBA_ HOME/ContentPacks/SM/INBUILT/DATAMODEL/DATAINTEGRATION/SOURCE/9.2/oracle/ SM_INCIDENTSM1_SRC.xml

Make changes in a field name

Open the entity xml source model file and update the source field names in the **datasourcecolumnname** property in the **ColumnMapping** tag:

Example

<ns1:ColumnMapping extractioncolumnidentifier="<identifier>" notapplicable="N" >

<ns1:DataSourceMapping datasourcetablenameoraliasname=" <name>" datasourcecolumnname=" source field name" datasourcecolumntype="XXXXX"/>

</ns1:ColumnMapping>

Make changes in a table name

1. Open the entity xml source model file and update the **DataSourceJoin** and **DataSourceWhere** tags with the changes.

Examples

<ns1:DataSourceJoin>table name</ns1:DataSourceJoin>

<ns1:DataSourceWhere>field name=1</ns1:DataSourceWhere>

<ns1:DataSourceJoin>table1 A LEFT JOIN table2 B ON A.AAAAA =

B.BBBBB</ns1:DataSourceJoin>

<ns1:DataSourceWhere>A.AAAAAAAA IS NOT NULL</ns1:DataSourceWhere>

2. Change the **datasourcetablenameoraliasname** property in the **ColumnMapping** tag to the new value.

Example

<ns1:ColumnMapping extractioncolumnidentifier="XXXX" notapplicable="N" >

<ns1:DataSourceMapping datasourcetablenameoraliasname=" A" datasourcecolumnname=" XXXX" datasourcecolumntype="XXXXX"/>

</ns1:ColumnMapping>

Update the data warehouse metadata

- 1. Go to Admin > Data Management >Install Content Pack, and upgrade the changes.
- 2. Start the ETL again using the DW ABC Streams Management UI. For details, see Content Flow Management in the *Administrator Guide*.

Customize the Extraction Model and the EXT ETL Scripts

The IDE generates ETL scripts that, by default, support deleting cases. You can change the default if you do not need to delete cases.

 Modify the flag isDelete = 'Y' in the extraction model to isDelete = 'N', then DCS does not extract the delete flat file any more.

The extraction model is located under:

\$HPBA_ Home /ContentPacks/<CPname>/INBUILT/DATAMODEL/DATAINTEGRATION/EXTRACTION/

2. Remove the relevant SQL clause from the EXT ETL scripts.

Relevant SQL causes are all the SQL clauses with a table name that has the post-fix **DEL_SRC**.

The EXT ETL script is located under:

\$HPBA_Home/ContentPacks/<CPname>/INBUILT/ETL/ENTITY_NAME/%NTEGRATION_ ENTITY

Customize the SSI Layer

The Single Source Identity (SSI) processes restructure the diverse source system data from the EXT tables into standard structures. The SSI tables contain this conformed data. Since the Data Warehouse uses data from multiple source systems that do not use the same business keys for the same entities, the ETL process creates an internal enterprise key to link entity records. The ETL process uses data in the SSI tables to generate these enterprise keys, which are used during the consolidation process.

For details, see ETL Process and Architectural Overview in PDF format.

Tip: When customizing the SSI layer:

- 1. Do not modify the SSI table creation clause.
- 2. Do not remove the commit keyword from the end of the script.

Tip: When customizing your ETL script, you can only modify the SSI layer script.

1. To customize the SSI layer, go to **\$HPBA_HOME/ContentPacks/<Product_** Name>/ETL/<Product_Name>_<Entity_Name>_SSI_DF.sql.

2. Modify the script and save.

Example:

```
--SSI step
   -Create SSI table
DROP TABLE IF EXISTS $(dws).AM_LOCATION_$(MD_CP_ID)_SSI CASCADE;
CREATE TABLE $(dws).AM_LOCATION_$(MD_CP_ID)_SSI(
      BUILDING VARCHAR(140) NULL,
CITY VARCHAR(80) NULL,
                                                                                                                                     Table creation
       COUNTRY VARCHAR(80) NULL,
      LOCATION CATEGORY VARCHAR(60) NULL,
       LOCATION_NAME VARCHAR(140) NULL,
      LOCATION_NAME_ALT_VARCHAR(200) NULL,
PARENT BUSINESS KEY_VARCHAR(1000) NULL,
       PARENT_ENTERPRISE_KEY INT NULL,
      POSTAL CODE VARCHAR(40) NULL,
SITE VARCHAR(140) NULL,
      STATE_PROVINCE VARCHAR(80) NULL,
MD_BATCH_ID INT NOT NULL ,
MD_BAICH_ID INT NOT NULL,

MD_FRCCESS_ID INT NOT NULL,

MD_CP_ID INT NOT NULL,

MD_FLAG VARCHAR(10) NOT NULL,

MD_BUSINESS_KEY VARCHAR(1000) NOT NULL

) ORDER BY MD_BUSINESS_KEY SEGMENTED BY HASH(MD_BUSINESS_KEY) ALL NODES;
--Put ext data into SSI table
--If mutiple source join or merge, please add the join condition to below SQL,
--and please map the md business key of target entity to some columns of source entities,
--and please map the md flag of target entity to one of source entities
INSERT INTO ${dws}.AM_LOCATION_${MD_CP_ID}_SSI(
      BUILDING ,
       СІТУ ,
      COUNTRY
      LOCATION_CATEGORY
      LOCATION_NAME
      LOCATION NAME ALT
       PARENT_BUSINESS_KEY
      PARENT_ENTERPRISE_KEY ,
      POSTAL_CODE ,
      SITE ,
STATE PROVINCE ,
      MD_BATCH_ID ,
      MD_PROCESS_ID
MD_CP_ID_,
      MD FLAG ,
      MD BUSINESS KEY
SELECT
       NULL AS BUILDING
      AMLOCATION.CITY AS CITY ,
AMCOUNTRY.NAME AS COUNTRY
       AMLOCATION.LOCATIONTYPE AS LOCATION_CATEGORY ,
      AMLOCATION.NAME AS LOCATION_NAME ,
      NULL AS LOCATION_NAME_ALT
       DECODE (AMLOCATION.LPARENTID, 0, NULL, AMLOCATION.MD_CP_ID || ':' || AMLOCATION.LPARENTID) AS PARENT_BUSINESS_KEY
       NULL PARENT ENTERPRISE KEY
      AMLOCATION.ZIP AS POSTAL_CODE ,
AMLOCATION.STATEX AS STATE ,
AMLOCATION.STATEX AS STATE PROVINCE ,
      ${MD_BATCH_ID} AS MD_BATCH_ID ,
${MD_PROCESS ID} AS MD_PROCESS ID
      AMLOCATION.MD_CP_ID ,
ABLOCATION.MD_CF_ID ;

AMLOCATION.MD_CF_ID ;| ':' || AMLOCATION.MD_BUSINESS_KEY MD_BUSINESS_KEY

FROM ${dws}, AM_AMLOCATION_LOCATION ${MD_CF_ID}_EXT AS AMLOCATION

LEFT JOIN ${dws}, AM_AMCOUNTRY_LOCATION_${MD_CF_ID}_EXT AS AMCOUNTRY ON (AMLOCATION.LCOUNTRYID = AMCOUNTRY.LCOUNTRYID )

LEFT JOIN ${dws}, AM_AMCOMFANY_LOCATION_${MD_CF_ID}_EXT AS AMCOMFANY ON (AMLOCATION.LSOCID = AMCOMFANY.LCPYID )

MHERE AMCOUNTRY.MD_FF_ELAG = 'D' OR AMLOCATION.MD_FF_ELAG = 'D' ;
 COMMIT
                    nmit key word
```

Consolidate Entities - Cross-CP Lookup

A Content Pack (CP) includes several entities. Some entities have relationships with other entities in the same Content Pack. In such cases, the ETL process looks up for the relational entities in the same Content Pack.

In some cases, you may need to develop several Content packs for the same entities. For example, the AWS and AWSCW integrations are performed using two different Content Packs including similar entities.

To set up the priority order:

1. Go to **\$ITBA_HOME**\$\ContentPacks\\$DATASOURCE_ NAME\$\CONF\dataSourceParamsConfig.xml.

Note: The configuration file is optional. Without the configuration file, the ETL process follows the regular look up way, meaning that one entity looks up the other entity in the same Content Pack with the same instance and the instance ID is replaced automatically by the ETL service.

2. Modify the file, and save it.

The entity uses first the value in the first instance, for example PPM_1, if there is no such value, it uses the value in the second instance, for example PPM_2, or if there is no such value, it uses the default value. You can have more than two <ParamValue Value=... Instance Name=.../> lines.

The format must be as follows:

where:

- DataSourceName is the name of the Content Pack that is installed.
- EntityName is the entity for which you must do a cross_CP lookup.
- Parameter DefaultValue is the default value if you did not configure the parameter value.

- **Parameter Name** is the name of the parameter that you use in the SSI layer.
- **ParamValue** is the value for the parameter that is used for the SSI layer customization.
- InstanceName is the data source instance used for the cross -CP lookup.

Note: Multiple instance cross-CP lookup is supported.

This configuration file is optional. Without the configuration file, the ETL process follows the regular lookup way.

Customize Views

To customize a view:

- 1. Go to **\$HPBA_HOME\DW_Content\CORE\INBUILT\SCRIPTS\APPLICATION**.
- 2. Duplicate the relevant OOTB view and make the changes or create your own script.

Tip: Do not modify an OOTB view script.

Example of a customized script:

AS	
SELECT	<pre>\${target.schema}.CHANGE_FACT_V.MD_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.SERVICE_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.CREATE_TIME_PERIOD_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.CLOSE_TIME_PERIOD_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.OUTAGE_START_FERIOD_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.OUTAGE_END_PERIOD_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.CURRENCY_BASE,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.CURRENCY_LOC,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.COST_BASE,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.COST_LOC,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.EXCHANGE_BASE_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_FACT_V.EXCHANGE_LOC_DURABLE_KEY,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.URGENCY,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.PRIORITY,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.APPROVAL_STATUS,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.CHANGE_CATEGORY,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.COMPLETION_CODE,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.REFERENCE_NUMBER,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.EMERGENCY_CHANGE,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.UNPLANNED_CHANGE,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.CREATE_TIME_PERIOD_LOC,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.CLOSE_TIME_PERIOD_LOC,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.OUTAGE_START_PERIOD_LOC,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.OUTAGE_END_PERIOD_LOC,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.CHANGE_SUBCATEGORY,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.UPDATE_TIME_PERIOD_LOC,</pre>
	<pre>\${target.schema}.CHANGE_DIM_V.ACTIVE_PROCESS</pre>
FROM	<pre>\${target.schema}.CHANGE_DIM_V LEFT OUTER JOIN</pre>
	<pre>\${target.schema}.CHANGE_FACT_V ON \${target.schema}.CHANGE_DIM_V.MD_DURABLE_KEY = \${target.schema}.CHANGE_FACT_V.CHANGE_DURABLE_KEY</pre>
WHERE	(\${target.schema}.CHANGE_FACT_V.MD_ACTIVESTATUSIND = 'Y') AND (\${target.schema}.CHANGE_FACT_V.MD_TRANSLASTIND = 'Y')
	AND (\${target.schema}.CHANGE_DIM_V.MD_ACTIVESTATUSIND = 'Y') AND (\${target.schema}.CHANGE_DIM_V.MD_TRANSLASTIND = 'Y');

- 3. Save the customized script.
- 4. Open the ITBA application, click **ADMIN > Data Management > Install Content Pack**, upgrade the Core Content Pack. The customization views will be created .

Customize the PREFILL case

The IDE generates ETL scripts that support, by default, prefill cases. You can modify the default if you do not need it. The prefill dataflow is needed to support multi-source join cases.

Remove the relevant SQL clause from the EXT ETL scripts. The relevant SQL clause includes the -- **Prefill tsnp into ext for the mutiple source join logic** annotation.

Customize a Stream Priority

In general, all the streams should be running in parallel. You can assign a higher priority to one of the streams, by adding **originaldwid="PRIOR_EXECUTION"** to the stream configuration file. The stream with the addition is executed first. Then when the stream completes its run, the other streams are executed.

More than one stream can have priority. Streams with priority run in parallel. When they complete, the streams without priority start running in parallel.

Example:

<ns1:JobStream xmIns:ns1="http://schemas.hp.com/bto/dwh/v1/dw_etl_stream" dwid="PPM_EXCHANGE" businessname="PPM" originaldwid="PRIOR_EXECUTION">

Customize the Maximum Execution Time of a Stream

You can customize the maximum execution time of a stream.

By default, the maximum execution time of a stream is 900 seconds (15 minutes) and is specified in a stream file as **maxexectime="900"**.

If a step takes longer than 15 minutes to execute, the ETL fails. You can modify the maximum execution time manually by changing the default value of **maxexectime** in the stream configuration

Next Steps

Following the IDE content development and extension process, you have created additional Content Packs for use in the Data Warehouse. This provides data to ITBA. Using the tools of ITBA, you can customize and modify your data, in order to access and display it according to specific formulas and parameters. The process includes:

- Create a custom FBI Extractor: Enables you to develop and modify an extractor for use with new content. For details, see the DCS Extractor SDK Guide.
- Manage the Data Sources: Enables you to manage the integration of extended or new data into the data warehouse through the activation of data sources.

To access: In ITBA, select **ADMIN> Data Management > Connect Data Source.** For details, see Connect the Data Source in the *Administrator Guide*.

 Manage the ETL: Enables you to perform the essential tasks related to ETL and stream functionality. It displays the state of active streams, and enables you to schedule and control stream activity. It also allows you to view the historical data and the archived stream definitions. All ETL management and functionality is accessed and performed through the Content Flow Management men in the ADMIN tab.

To access: In ITBA select **ADMIN > Data Management > Run ETL**. For details, see Run ETL - Content Flow ManagementRun ETL - Content Flow Management in the *Administrator Guide*.

• Create your Context in the Context Designer: Enables you to create and manage Contexts (universes). The universes can be based on your target schema tables or on .CSV files that can be uploaded to the target schema using the Context Designer.

To access: In ITBA, select **ADMIN** >**Semantic Layer** > **Semantic Layer**. The Context Management page opens. For details, see Semantic Layer - Context Designerin the *Content Reference Guide*.

• Create KPIs in the Studio: Enables you to create and manage all of the displayed KPI elements (based on your content), as well as their interactions with each other: wiring, drill downs, and other features.

To access: In ITBA, select **Studio**. For details, see Create the Dashboard Contents in the Studio in the *Business Analyst Guide*.

• Create Executive Pages in the ITBA Dashboard: Enables you to set up pages that include components that are of interest to specific users or groups of users. For each page, the administrator defines the layout of components on the page, and the interaction of the page

components with one another.

To access: In ITBA, select **Studio**. For details, see Dashboard Display in the *Business Analyst Guide*.

• Create CAPs: Enables you to create Content Acceleration Packs that include Scorecards, KPIs, Dashboard pages that display the Scorecards and KPI components, Contexts (universes), and .CSV files.

To access: In ITBA, select **ADMIN > Data Management > Activate CAP**. For details, see Create Content Acceleration Packs in the *Guide to Content Acceleration Packs*.

Release Notes

What's New in this Version

- "IDE End-to-End Extension Scenario" on page 12
- "Customize the SSI Layer" on page 119
- "Consolidate Entities Cross-CP Lookup" on page 121
- "Customize Views" on page 123

IDE 10.10 is compatible with ITBA 10.10

Send Documentation Feedback

If you have comments about this document, you can contact the documentation team by email. If an email client is configured on this system, click the link above and an email window opens with the following information in the subject line:

Feedback on Content Extension Guide for ITBA IDE Version 10.10 (IT Business Analytics 10.10)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to SW-Doc@hpe.com.

We appreciate your feedback!



