

Universal CMDB

Software Version: 10.31

Developer Reference Guide

Document Release Date: December 2016 Software Release Date: December 2016



Legal Notices

Warranty

The only warranties for Hewlett Packard Enterprise products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Hewlett Packard Enterprise shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from Hewlett Packard Enterprise required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial licensed.

Copyright Notice

© 2002 - 2016 Hewlett Packard Enterprise Development LP

Trademark Notices

Adobe™ is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

Documentation Updates

To check for recent updates or to verify that you are using the most recent edition of a document, go to: https://softwaresupport.hpe.com/.

This site requires that you register for an HP Passport and to sign in. To register for an HP Passport ID, click **Register** on the HPE Software Support site or click **Create an Account** on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HPE sales representative for details.

Support

Visit the HPE Software Support site at: https://softwaresupport.hpe.com/.

This website provides contact information and details about the products, services, and support that HPE Software offers.

HPE Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support website to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HPE support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and to sign in. Many also require a support contract. To register for an HP Passport ID, click **Register** on the HPE Support site or click **Create an Account** on the HP Passport login page.

To find more information about access levels, go to: https://softwaresupport.hp.com/web/softwaresupport/access-levels

HPSW Integrations Catalog accesses the new HPSW Integrations and Solutions Catalog website. This site enables you to explore HPE Product Solutions to meet your business needs, includes a full list of Integrations between HPE Products, as well as a listing of ITIL Processes. The URL for this website is https://softwaresupport.hpe.com/km/KM01702731.

About this PDF Version of Online Help

This document is a PDF version of the online help. This PDF file is provided so you can easily print multiple topics from the help information or read the online help in PDF format. Because this content was originally created to be viewed as online help in a web browser, some topics may not be formatted properly. Some interactive topics may not be present in this PDF version. Those topics can be successfully printed from within the online help.

Contents

Part I: Creating Discovery and Integration Adapters	17
Chapter 1: Adapter Development and Writing	18
Adapter Development and Writing Overview	18
Content Creation	19
The Adapter Development Cycle	19
Data Flow Management and Integration	22
Associating Business Value with Discovery Development	23
Researching Integration Requirements	24
Developing Integration Content	27
Developing Discovery Content	30
Discovery Adapters and Related Components	30
Separating Adapters	31
Implement a Discovery Adapter	32
Step 1: Create an Adapter	34
Step 2: Assign a Job to the Adapter	41
Step 3: Create Jython Code	42
Configure Remote Process Execution	43
Chapter 2: Developing Jython Adapters	45
HP Data Flow Management API Reference	45
Create Jython Code	45
Use External Java JAR Files within Jython	46
Execution of the Code	46
Modifying Out-of-the-Box Scripts	47
Structure of the Jython File	47
Imports	48
Main Function – DiscoveryMain	48
Functions Definition	49
Results Generation by the Jython Script	50
The ObjectStateHolder Syntax	50
Sending Large Amounts of Data	52
The Framework Instance	53
Finding the Correct Credentials (for Connection Adapters)	56

Handling Exceptions from Java	59
Troubleshooting Migration from Jython Version 2.1 to 2.5.3	59
Support Localization in Jython Adapters	61
Add Support for a New Language	62
Change the Default Language	63
Determine the Character Set for Encoding	63
Define a New Job to Operate With Localized Data	64
Decode Commands Without a Keyword	65
Work with Resource Bundles	66
API Reference	67
Record DFM Code	69
Jython Libraries and Utilities	71
Chapter 3: Error Messages	74
Error Messages Overview	74
Error-Writing Conventions	74
Error Severity Levels	78
Chapter 4: Mapping Consumer-Provider Dependencies	80
Dependency Discovery Overview	80
Providers and Consumers	
Service Connection Point	81
Configuration Signatures	82
Dependency Mapping Flow	82
Configuration Signature Files	84
Structure of a Configuration Signature File	84
Variables	85
Search Connection Strings	
Search connection strings from command line	88
Search connection strings from configuration documents	89
Generate Service Connection Points	93
Chapter 5: Developing Generic Database Adapters	96
Generic Database Adapter Overview	97
TQL Queries for the Generic Database Adapter	
Reconciliation	
Hibernate as JPA Provider	99
Prepare for Adapter Creation	101
Prepare the Adapter Package	105

Configure the Adapter – Minimal Method	108
Configure the adapter.conf File	109
Example: Populating a Node and IP Address using the Simplified Method	109
Configure the Adapter – Advanced Method	113
Implement a Plug-in	117
Deploy the Adapter	120
Edit the Adapter	121
Create an Integration Point	121
Create a View	121
Calculate the Results	121
View the Results	122
View Reports	122
Enable Log Files	122
Use Eclipse to Map Between CIT Attributes and Database Tables	122
Adapter Configuration Files	130
The adapter.conf File	132
The simplifiedConfiguration.xml File	133
The orm.xml File	136
The reconciliation_types.txt File	150
The reconciliation_rules.txt File (for backwards compatibility)	150
The transformations.txt File	152
The discriminator.properties File	153
The replication_config.txt File	154
The fixed_values.txt File	154
The Persistence.xml File	155
Connect to Database Using NT Authentication	156
Configure the Persistence.xml File for the SCCM Integration to	
Use NTLM Authentication	
Out-of-the-Box Converters	
Plug-ins	
Configuration Examples	
Adapter Log Files	
External References	174
Troubleshooting and Limitations – Developing Generic Database Adapters	175
Chapter 6: Developing Java Adapters	177

Federation Framework Overview	177
Adapter and Mapping Interaction with the Federation Framework	182
Federation Framework for Federated TQL Queries	183
Interactions between the Federation Framework, Server, Adapter, and	j
Mapping Engine	184
Federation Framework Flow for Population	194
Adapter Interfaces	195
Debug Adapter Resources	198
Add an Adapter for a New External Data Source	198
Create a Sample Adapter	206
XML Configuration Tags and Properties	207
The DataAdapterEnvironment Interface	210
OutputStream openResourceForWriting(String resourceName) throws FileNotFoundException;	210
InputStream openResourceForReading(String resourceName) throws FileNotFoundException;	
Properties openResourceAsProperties(String propertiesFile) throw	
IOException;	
String openResourceAsString(String resourceName) throws IOException;	212
public void saveResourceFromString(String relativeFileName,	
String value) throws IOException;	212
boolean resourceExists(String resourceName);	213
boolean deleteResource(String resourceName);	213
Collection <string> listResourcesInPath(String path);</string>	213
DataAdapterLogger getLogger();	214
DestinationConfig getDestinationConfig();	214
int getChunkSize();	214
int getPushChunkSize();	214
ClassModel getLocalClassModel();	215
CustomerInformation getLocalCustomerInformation();	215
Object getSettingValue(String name);	215
Map <string, object=""> getAllSettings();</string,>	215
boolean isMTEnabled();	215
String getUcmdbServerHostName();	216
Chapter 7: Developing Push Adapters	217
Developing and Deploying Push Adapters	217

Build an Adapter Package	218
Troubleshooting	221
TQL Best Practices for Push Adapters	222
Create Mappings	222
Build a Mapping File	222
Prepare the Mapping Files	223
Write Jython Scripts	225
Support Differential Synchronization	230
Generic XML Push Adapter SQL Queries	232
Generic Web Service Push Adapter	232
Mapping File Reference	252
Mapping File Schema	254
Mapping Results Schema	264
Customization	267
Chapter 8: Developing Generic Adapters	269
Instance Sync	269
Achieving Data Push using the Generic Adapter	269
Push Overview	270
The Mapping File	270
The Groovy Traveler	273
Write Groovy Scripts	276
Implement PushAdapterConnector Interface	277
Achieving Data Population using the Generic Adapter	278
The Population Framework Architecture	279
Main Artifacts involved in Population	
Population TQL Queries	
Population Mapping Files	
Automatic Link Population	
Manual Link Population	
The Population Connector	
Population Request Input	287
Population Request Output	
Population Adapter Modes	
Explicit External ID Mapping	
Global ID Pushback	
Achieving Data Federation using the Generic Adapter	294

Federation Mapping Approach	294
Generic Adapter Federation API	295
Generic Adapter Connector Interface for Federation	296
Supported Federation Queries	297
How to Set Up Federation	298
Configure the Adapter Settings	298
Set Up Static Federation TQL Queries	298
Federation Setup Example	301
Sample Data	306
Incident Federation	308
Incident Related to Node Federation	310
Incident Related to Node and Business Service Federation	312
Mapping Conventions	313
Reconciliation	314
Generic Adapter API	314
Resource Locator APIs	314
Create a Generic Adapter Package	315
Build an Adapter Package	316
Population TQL Queries	317
Sample Package	319
Differences Between Push and Population Mapping	321
Generic Adapter Log Files	321
Adapters Using the Generic Adapter Framework	322
Generic Adapter XML Schema Reference	322
Part II: Using APIs	323
Chapter 9: Introduction to APIs	324
APIs Overview	324
Chapter 10: HPE Universal CMDB API	325
Conventions	325
Using the HPE Universal CMDB API	325
General Structure of an Application	327
Put the API Jar File in the Classpath	329
Create an Integration User	330
UCMDB API Use Cases	332
Examples	334
Chapter 11: HPE Universal CMDB Web Service API	

Conventions	335
HPE Universal CMDB (UCMDB) Web Service API Overview	336
Getting Started with HPE Universal CMDB Web Service	339
How to Generate the Java Web Service Client Jar	339
How to Write a Simple Java Web Service Client for UCMDB	340
Call the HP Universal CMDB Web Service	341
Query the CMDB	341
Update the CMDB	345
Query the UCMDB Class Model	346
getClassAncestors	347
getAllClassesHierarchy	347
getCmdbClassDefinition	348
Query for Impact Analysis	348
UCMDB General Parameters	349
UCMDB Output Parameters	352
UCMDB Query Methods	353
executeTopologyQueryByNameWithParameters	354
executeTopologyQueryWithParameters	355
getChangedCls	356
getClNeighbours	356
getClsByID	357
getClsByType	358
getFilteredClsByType	358
getQueryNameOfView	362
getTopologyQueryExistingResultByName	362
getTopologyQueryResultCountByName	363
pullTopologyMapChunks	364
releaseChunks	365
UCMDB Update Methods	366
addClsAndRelations	366
addCustomer	367
deleteClsAndRelations	368
removeCustomer	368
updateClsAndRelations	368
UCMDB Impact Analysis Methods	369
calculateImpact	369

getImpactPath	370
getImpactRulesByNamePrefix	371
Actual State Web Service API	371
UCMDB Web Service API Use Cases	373
Examples	375
Chapter 12: HPE Universal CMDB REST API	376
Deployment and Configuration	376
Standalone Deployment	376
Configuration	377
Using the REST API	378
Authorization	378
REST API Endpoint	378
Tips	379
A Usage Example	379
Reference	380
Authenticate	381
URL	381
Method	381
Headers	381
Request type	381
Response type	381
URL Parameters	382
Payload	382
Success response	382
Error response	382
Notes	
Sample Data Model	
URL	383
Method	
Headers	
Request type	383
Response type	383
URL Parameters	
Payload	
Success response	384
Error response	385

Insert Topology	385
URL	
Method	385
Headers	386
Request type	386
Response type	
URL Parameters	386
Payload	386
Success response	388
Error response	389
Note	389
Get CI	389
URL	389
Method	389
Headers	389
Request type	390
Response type	390
URL Parameters	390
Payload	390
Call example	390
Success response	390
Error response	392
Note	392
Update CI	392
URL	392
Method	392
Headers	392
Request type	393
Response type	393
URL Parameters	393
Payload	393
Success response	394
Error response	395
Note	396
Delete CI	396
IIRI	396

Method	396
Headers	396
Request type	396
Response type	396
URL Parameters	397
Payload	397
Success response	397
Error response	398
Note	398
Get Related Cls	398
URL	398
Method	398
Headers	398
Request type	399
Response type	
URL Parameters	
Payload	399
Success response	
Error response	401
Note	401
Get Relation	401
URL	401
Method	401
Headers	401
Request type	402
Response type	402
URL Parameters	402
Payload	402
Call example	
Success response	
Error response	
Note	
Update Relation	
URL	
Method	
Headers	405

Request type	405
Response type	405
URL Parameters	405
Payload	405
Success response	407
Error response	407
Note	408
Delete Relation	408
URL	408
Method	408
Headers	408
Request type	408
Response type	409
URL Parameters	409
Payload	409
Success response	409
Error response	410
Note	410
Sample Topology Query	410
URL	410
Method	411
Headers	411
Request type	411
Response type	411
URL Parameters	411
Payload	411
Success response	411
Error response	413
Execute Query By Name	413
URL	413
Method	414
Headers	414
Request type	414
Response type	414
URL Parameters	414
Payload	414

Success response	414
Error response	416
Note	416
Execute Query By Definition	416
URL	416
Method	416
Headers	416
Request type	417
Response type	417
URL Parameters	417
Payload	417
Success response	419
Error response	420
Note	421
Run Impact Analysis	421
URL	421
Method	421
Headers	421
Request type	422
Response type	422
URL Parameters	422
Payload	422
Success response	423
Error response	424
Multiple CMDB Calls	424
Converting UCMDB IDs to Global Ids	424
URL	424
Method	424
Headers	424
Request type	424
Response type	425
URL Parameters	425
Payload	425
Success response	
Error response	
Notes	426

Converting Global IDs to UCMDB IDs	426
URL	426
Method	426
Headers	426
Request type	427
Response type	427
URL Parameters	427
Payload	427
Success response	427
Error response	428
Notes	428
History Changes	428
Get Removed CIs	428
URL	429
Method	429
Headers	429
Request type	429
Response type	429
URL Parameters	429
Payload	430
Success response	430
Error response	430
Get Changes	430
URL	430
Method	431
Headers	
Request type	431
Response type	431
URL Parameters	431
Payload	432
Success response	432
Error response	434
Get Data Layout	435
URL	435
Method	435
Headers	435

Request type	435
Response type	436
URL Parameters	436
Payload	436
Success response	437
Error response	437
Chapter 13: Data Flow Management Java API	438
Using the Data Flow Management Java API	438
IP Range Management API	
Sample Script for IP Range Management API	440
Chapter 14: Data Flow Management Web Service API	443
Data Flow Management Web Service API Overview	443
Conventions	444
Creating the Web Service Client	444
Call the HP Data Flow Management Web Service	
Data Flow Management Methods and Data Structures	445
Data Structures	446
Managing Discovery Job Methods	447
Managing Trigger Methods	449
Domain and Probe Data Methods	451
Credentials Data Methods	454
Data Refresh Methods	456
Code Samples	458
Managing Discovery Job Methods	459
Managing Trigger Methods	462
Domain and Probe Data Methods	
Credentials Data Methods	470
Data Refresh Methods	476
Send documentation feedback	480

Part I: Creating Discovery and Integration Adapters

Chapter 1: Adapter Development and Writing

This chapter includes:

Adapter Development and Writing Overview	18	
Content Creation	19	
Developing Integration Content	27	
Developing Discovery Content	30	
Implement a Discovery Adapter	32	
Step 1: Create an Adapter	34	
Step 2: Assign a Job to the Adapter	41	
Step 3: Create Jython Code	42	
Configure Remote Process Execution	43	

Adapter Development and Writing Overview

Prior to beginning actual planning for development of new adapters, it is important for you to understand the processes and interactions commonly associated with this development.

The following sections can help you understand what you need to know and do to successfully manage and execute a discovery development project.

This chapter:

- Assumes a working knowledge of Universal CMDB and some basic familiarity with the elements of the system. It is meant to assist you in the learning process and does not provide a complete guide.
- Covers the stages of planning, research, and implementation of new discovery content for Universal CMDB, together with guidelines and considerations that need to be taken into account.
- Provides information on the key APIs of the Data Flow Management Framework. For full
 documentation on the available APIs, see the HP Universal CMDB Data Flow Management API
 Reference. (Other non-formal APIs exist but even though they are used on out-of-the-box adapters,
 they may be subject to change.)


Content Creation

This section includes:

- "The Adapter Development Cycle" below
- "Data Flow Management and Integration" on page 22
- "Associating Business Value with Discovery Development" on page 23
- "Researching Integration Requirements" on page 24

The Adapter Development Cycle

The following illustration shows a flowchart for adapter writing. Most of the time is spent in the middle section, which is the iterative loop of development and testing.




Each phase of adapter development builds on the last one.

Once you are satisfied with the way the adapter looks and works, you are ready to package it. Using either the UCMDB Package Manager or manual exporting of the components, create a package *.zip file. As a best practice, you should deploy and test this package on another UCMDB system before releasing it to production, to ensure that all the components are accounted for and successfully packaged. For details on packaging, see Package Manager in the HPE Universal CMDB Administration Guide.

The following sections expand on each of the phases, showing the most critical steps and best practices:

- "Research and Preparation Phase" below
- "Adapter Development and Testing" on the next page
- "Adapter Packaging and Productization" on the next page

Research and Preparation Phase



The Research and Preparation phase encompasses the driving business needs and use cases, and also accounts for securing the necessary facilities to develop and test the adapter.

- When planning to modify an existing adapter, the first technical step is to make a backup of that
 adapter and ensure you can return it to its pristine state. If you plan to create a new adapter, copy
 the most similar adapter and save it under an appropriate name. For details, see Resources Pane
 in the HPE Universal CMDB Data Flow Management Guide.
- 2. Research the method which the adapter should use to collect data:
 - Use external tools/protocols to obtain the data
 - Develop how the adapter should create CIs based on the data
 - You now know what a similar adapter should look like
- 3. Determine most similar adapter based on:
 - Same CIs created
 - Same Protocols used (SNMP)
 - Same kind of targets (by OS type, versions, and so on)
- 4. Copy the entire package.
- Unzip the package contents into the work space and rename the adapter (XML) and Jython (.py)

files.



Adapter Development and Testing

The Adapter Development and Testing phase is a highly iterative process. As the adapter begins to take shape, you begin testing against the final use cases, make changes, test again, and repeat this process until the adapter complies with the requirements.

Startup and Preparation of Copy

- Modify XML parts of the adapter: Name (id) in line 1, Created CI Types, and Called Jython script name.
- Get the copy running with identical results to the original adapter.
- Comment out most of the code, especially the critical result-producing code.

Development and Testing

- Use other sample code to develop changes
- · Test adapter by running it
- Use a dedicated view to validate complex results, search to validate simple results

Adapter Packaging and Productization

The **Adapter Packaging and Productization** phase accounts for the last phase of development. As a best practice, a final pass should be made to clean up debugging remnants, documents, and comments, to look at security considerations, and so on, before moving on to packaging. You should always have at least a readme document to explain the inner workings of the adapter. Someone (maybe even you) may need to look at this adapter in the future and will be aided greatly by even the most limited documentation.

Cleanup and Document

- · Remove debugging
- Comment all functions and add some opening comments in the main section

Create sample TQL and view for the user to test

Create Package

- Export adapters, TQL, and so on with the Package Manager. For details, see Package Manager in the *HPE Universal CMDB Administration Guide*.
- Check any dependencies your package has on other packages, for example, if the CIs created by those packages are input CIs to your adapter.
- Use Package Manager to create a package zip. For details, see Package Manager in the HPE Universal CMDB Administration Guide.
- Test deployment by removing parts of the new content and redeploying, or deploying on another test system.

Data Flow Management and Integration

DFM adapters are capable of integration with other products. Consider the following definitions:

- DFM collects specific content from many targets.
- Integration collects multiple types of content from one system.

Note that these definitions do not distinguish between the methods of collection. Neither does DFM. The process of developing a new adapter is the same process for developing new integration. You do the same research, make the same choices for new vs. existing adapters, write the adapters the same way, and so on. Only a few things change:

- The final adapter's scheduling. Integration adapters may run more frequently than discovery, but it depends on the use cases.
- Input CIs:
 - Integration: non-CI trigger to run with no input: a file name or source is passed through the adapter parameter.
 - o Discovery: uses regular, CMDB CIs for input.

For integration projects, you should almost always reuse an existing adapter. The direction of the integration (from Universal CMDB to another product, or from another product to Universal CMDB) may affect your approach to development. There are field packages available for you to copy for your own uses, using proven techniques.

From Universal CMDB to another project:

- Create a TQL that produces the CIs and relations to be exported.
- Use a generic wrapper adapter to execute the TQL and write the results to an XML file for the external product to read.

Note: For examples of field packages, contact HPE Software Support.

To integrate another product to Universal CMDB, depending on how the other product exposes its data, the integration adapter acts differently:

Integration Type	Reference Example to Be Reused	
Access the product's database directly	HP ED	
Read in a csv or xml file produced by an export	HP ServiceCenter	
Access a product's API	BMC Atrium/Remedy	

Associating Business Value with Discovery Development

The use case for developing new discovery content should be driven by a business case and plan to produce business value. That is, the goal of mapping system components to CIs and adding them to the CMDB is to provide business value.

The content may not always be used for application mapping, although this is a common intermediate step for many use cases. Regardless of the end use of the content, your plan should answer the following questions:

- Who is the consumer? How should the consumer act on the information provided by the CIs (and the relationships between them)? What is the business context in which the CIs and relationships are to be viewed? Is the consumer of these CIs a person or a product or both?
- Once the perfect combination of CIs and relationships exists in the CMDB, how do I plan on using them to produce business value?
- What should the perfect mapping look like?
 - What term would most meaningfully describe the relationships between each CI?
 - What types of CIs would be most important to include?
 - What is the end usage and end user of the map?
- What would be the perfect report layout?

Once the business justification is established, the next step is to embody the business value in a document. This means picturing the perfect map using a drawing tool and understanding the impact and dependencies between CIs, reports, how changes are tracked, what change is important, monitoring, compliance, and additional business value as required by the use cases.

This drawing (or model) is referred to as the **blueprint**.

For example, if it is critical for the application to know when a certain configuration file has changed, the file should be mapped and linked to the appropriate CI (to which it relates) in the drawn map.

Work with an SME (Subject Matter Expert) of the area, who is the end user of the developed content. This expert should point out the critical entities (CIs with attributes and relationships) that must exist in the CMDB to provide business value.

One method could be to provide a questionnaire to the application owner (also the SME in this case). The owner should be able to specify the above goals and blueprint. The owner must at least provide a current architecture of the application.

You should map critical data only and no unnecessary data: you can always enhance the adapter later. The goal should be to set up a limited discovery that works and provides value. Mapping large quantities of data gives more impressive maps but can be confusing and time consuming to develop.

Once the model and business value is clear, continue to the next stage. This stage can be revisited as more concrete information is provided from the next stages.

Researching Integration Requirements

The prerequisite of this stage is a **blueprint** of the CIs and relationships needed to be discovered by DFM, which should include the attributes that are to be discovered. For details, see "Adapter Development and Writing Overview" on page 18.

This section includes the following topics:

- "Modifying an Existing Adapter" on the next page
- "Writing a New Adapter" on the next page
- "Model Research" on the next page
- "Technology Research" on page 26
- "Guidelines for Choosing Ways to Access Data" on page 26
- "Summary" on page 27

Modifying an Existing Adapter

You modify an existing adapter when an out-of-the-box or field adapter exists, but:

- · It does not discover specific attributes that are needed
- A specific type of target (OS) is not being discovered or is being incorrectly discovered
- · A specific relationship is not being discovered or created

If an existing adapter does some, but not all, of the job, your first approach should be to evaluate the existing adapters and verify if one of them almost does what is needed; if it does, you can modify the existing adapter.

You should also evaluate if an existing field adapter is available. Field adapters are discovery adapters that are available but are not out-of-the-box. Contact HPE Software Support to receive the current list of field adapters.

Writing a New Adapter

A new adapter needs to be developed:

- When it is faster to write an adapter than to insert the information manually into the CMDB (generally, from about 50 to 100 CIs and relationships) or it is not a one-time effort.
- · When the need justifies the effort.
- If out-of-the-box or field adapters are not available.
- If the results can be reused.
- When the target environment or its data is available (you cannot discover what you cannot see).

Model Research

- Browse the UCMDB class model (CI Type Manager) and match the entities and relations from your blueprint to existing CITs. It is highly recommended to adhere to the current model to avoid possible complications during version upgrade. If you need to extend the model, you should create new CITs since an upgrade may overwrite out-of-the-box CITs.
- If some entities, relations, or attributes are lacking from the current model, you should create them. It is preferable to create a package with these CITs (which will also later hold all the discovery, views, and other artifacts relating to this package) since you need to be able to deploy these CITs

on each installation of Universal CMDB.

Technology Research

Once you have verified that the CMDB holds the relevant CIs, the next stage is to decide how to retrieve this data from the relevant systems.

Retrieving data usually involves using a protocol to access a management part of the application, actual data of the application, or configuration files or databases that are related to the application. Any data source that can provide information on a system is valuable. Technology research requires both extensive knowledge of the system in question and sometimes creativity.

For home-grown applications, it may be helpful to provide a questionnaire form to the application owner. In this form the owner should list all the areas in the application that can provide information needed for the blueprint and business values. This information should include (but does not have to be limited to) management databases, configuration files, log files, management interfaces, administration programs, Web services, messages or events sent, and so on.

For off-the-shelf products, you should focus on documentation, forums, or support of the product. Look for administration guides, plug-ins and integrations guides, management guides, and so on. If data is still missing from the management interfaces, read about the configuration files of the application, registry entries, log files, NT event logs, and any artifacts of the application that control its correct operation.

Guidelines for Choosing Ways to Access Data

Relevance: Select sources or a combination of sources that provide the most data. If a single source supplies most information whereas the rest of the information is scattered or hard to access, try to assess the value of the remaining information by comparison with the effort or risk of getting it. Sometimes you may decide to reduce the blueprint if the value or cost does not warrant the invested effort.

Reuse: If Universal CMDB already includes a specific connection protocol support it is a good reason to use it. It means the DFM Framework is able to supply a ready made client and configuration for the connection. Otherwise, you may need to invest in infrastructure development. You can view the currently supported Universal CMDB connection protocols in the Data Flow Management > Data Flow Probe Setup > Domains and Probes pane. For details about each protocol, see the section describing the supported protocols in the HPE Universal CMDB Discovery and Integrations Content Guide.

You can add new protocols by adding new CIs to the model. For details, contact HPE Software Support.

Note: To access Windows Registry data, you can use either WMI or NTCMD.

Security: Access to information usually requires credentials (user name, password), which are entered in the CMDB and are kept secure throughout the product. If possible, and if adding security does not conflict with other principles you have set, choose the least sensitive credential or protocol that still answers access needs. For example, if information is available both through JMX (standard administration interface, limited) and Telnet, it is preferable to use JMX since it inherently provides limited access and (usually) no access to the underlying platform.

Comfort: Some management interfaces may include more advanced features. For example, it might be easier to issue queries (SQL, WMI) than to navigate information trees or build regular expressions for parsing.

Developer Audience: The people who will eventually develop adapters may have an inclination towards a certain technology. This can also be considered if two technologies provide almost the same information at an equal cost in other factors.

Summary

The outcome of this stage is a document describing the access methods and the relevant information that can be extracted from each method. The document should also contain a mapping from each source to each relevant blueprint data.

Each access method should be marked according to the above instructions. Finally you should now have a plan of which sources to discover and what information to extract from each source into the blueprint model (which should by now have been mapped to the corresponding UCMDB model).

Developing Integration Content

Before creating a new integration, you must understand what the integration's requirements are:

- Should the integration copy data into the CMDB? Should the data be tracked by history? Is the source unreliable?
 - If you answer yes to these questions, then **Population** is needed.
- Should the integration federate data on the fly for views and TQL queries? Is the accuracy of changes to data critical? Is the amount of data too large to copy to the CMDB, but the requested

amount of data is usually small?

If you answer yes to these questions, then **Federation** is needed.

Should the integration push data to remote data sources?

If you answer yes to these questions, then **Data Push** is needed.

Is the length of any CI's ID greater than 60 characters?

If you answer yes to this question, then **decrease** the ID length for all concerning CIs, so that their IDs do not exceed the maximum length of 60 characters.

Note: Federation and Population flows may be configured for the same integration, for maximum flexibility.

For details about the different types of integrations, see Integration Studio in the *HPE Universal CMDB Data Flow Management Guide*.

Five different options are available for creating integration adapters:

- 1. Jython Adapter:
 - The classic discovery pattern
 - Written in Jython
 - Used for population

For details, see "Developing Jython Adapters" on page 45.

2. Java Adapter:

- An adapter that implements one of the adapter interfaces in the Federation SDK Framework.
- May be used for one or more of Federation, Population, or Data Push (depending on the required implementation).
- Written from scratch in Java, which allows writing code that will connect to any possible source or target.
- Suitable for jobs that connect to a single data source or target.

For details, see "Developing Java Adapters" on page 177.

3. Generic DB Adapter:

- An abstract adapter based on the Java Adapter that uses the Federation SDK Framework.
- Allows creation of adapters that connect to external data repositories.

- Supports both Federation and Population (with a Java plug-in implemented for changes support).
- Relatively easy to define, as it is based mainly on XML and property configuration files.
- Main configuration is based on an orm.xml file that maps between UCMDB classes and database columns.
- Suitable for jobs that connect to a single data source.

For details, see "Developing Generic Database Adapters" on page 96.

4. Generic Push Adapter:

- An abstract adapter based on the Java Adapter (the Federation SDK Framework) and the Jython Adapter.
- Allows creation of adapters that push data to remote targets.
- Relatively easy to define, as you need only to define the mapping between UCMDB classes and XML, and a Jython script that pushes the data to the target.
- Suitable for jobs that connect to a single data target.
- Used for Data Push.

For details, see "Developing Push Adapters" on page 217.

- 5. Enhanced Generic Push Adapter:
 - All the above features of the Generic Push Adapter
 - A root-element-based adapter
 - Maps a UCMDB tree data structure to a target tree data structure

For details, see "Achieving Data Push using the Generic Adapter" on page 269.

The following table displays the capabilities of each adapter:

Flow/Adapter	Jython Adapter	Java Adapter	Generic DB Adapter	Generic Push Adapter	Enhanced Generic Push Adapter
Population	Yes	Yes	Yes	No	No
Federation	No	Yes	Yes	No	No
Data Push	No	Yes	No	Yes	Yes


Developing Discovery Content

This section includes:

- "Discovery Adapters and Related Components" below
- "Separating Adapters" on the next page

Discovery Adapters and Related Components

The following diagram shows an adapter's components and the components they interact with to execute discovery. The components in green are the actual adapters, and the components in blue are components that interact with adapters.



Note that the minimum notion of an adapter is two files: an XML document and a Jython script. The Discovery Framework, including input CIs, credentials, and user-supplied libraries, is exposed to the adapter at run time. Both discovery adapter components are administered through Data Flow Management. They are stored operationally in the CMDB itself; although the external package remains, it is not referred to for operation. The Package Manager enables preservation of the new discovery and integration content capability.

Input CIs to the adapter are provided by a TQL, and are exposed to the adapter script in system-supplied variables. Adapter parameters are also supplied as destination data, so you can configure the adapter's operation according to an adapter's specific function.

The DFM application is used to create and test new adapters. You use the Universal Discovery, Adapter Management, and Data Flow Probe Setup pages during adapter writing.

Adapters are stored and transported as packages. The Package Manager application and the JMX console are used to create packages from newly created adapters, and to deploy adapters on new systems.

Separating Adapters

An entire discovery could be defined in a single adapter. But good design demands that a complex system be separated into simpler, more manageable components.

The following are guidelines and best practices for dividing the adapter process:

- Discovery should be done in stages. Each stage should be represented by an adapter that should
 map an area or tier of the system. Adapters should rely on the previous stage or tier to be
 discovered, to continue discovery of the system. For example, Adapter A is triggered by an
 application server TQL result and maps the application server tier. As part of this mapping, a JDBC
 connection component is mapped. Adapter B registers a JDBC connection component as a trigger
 TQL and uses the results of adapter A to access the database tier (for example, through the JDBC
 URL attribute) and maps the database tier.
- The two-phase connect paradigm: Most systems require credentials to access their data. This means that a user/password combination needs to be tried against these systems. The DFM administrator supplies credentials information in a secure way to the system and can give several, prioritized login credentials. This is referred to as the Protocol Dictionary. If the system is not accessible (for whatever reason) there is no point in performing further discovery. If the connection is successful, there needs to be a way to indicate which credential set was successfully used, for future discovery access.

These two phases lead to a separation of the two adapters in the following cases:

- Connection Adapter: This is an adapter that accepts an initial trigger and looks for the existence of a remote agent on that trigger. It does so by trying all entries in the Protocol Dictionary which match this agent's type. If successful, this adapter provides as its result a remote agent CI (SNMP, WMI, and so on), which also points to the correct entry in the Protocol Dictionary for future connections. This agent CI is then part of a trigger for the content adapter.
- Content Adapter: This adapter's precondition is the successful connection of the previous adapter (preconditions specified by the TQLs). These types of adapters no longer need to look through all of the Protocol Dictionary since they have a way to obtain the correct credentials from the remote agent CI and use them to log in to the discovered system.
- Different scheduling considerations can also influence discovery division. For example, a system
 may only be queried during off hours, so even though it would make sense to join the adapter to the
 same adapter discovering another system, the different schedules mean that you need to create

two adapters.

 Discovery of different management interfaces or technologies to discover the same system should be placed in separate adapters. This is so that you can activate the access method appropriate for each system or organization. For example, some organizations have WMI access to machines but do not have SNMP agents installed on them.

Implement a Discovery Adapter

A DFM task has the aim of accessing remote (or local) systems, modeling extracted data as CIs, and saving the CIs to the CMDB. The task consists of the following steps:

1. Create an adapter.

You configure an adapter file that holds the context, parameters, and result types by selecting the scripts that are to be part of the adapter. For details, see "Step 1: Create an Adapter" on page 34.

2. Create a Discovery job.

You configure a job with scheduling information and a trigger query. For details, see "Step 2: Assign a Job to the Adapter" on page 41.

3. Edit Discovery code.

You can edit the Jython or Java code that is contained in the adapter files and that refers to the DFM Framework. For details, see "Step 3: Create Jython Code" on page 42.


To write new adapters, you create each of the above components, each one of which is automatically bound to the component in the previous step. For example, once you create a job and select the relevant adapter, the adapter file binds to the job.

Adapter Code


The actual implementation of connecting to the remote system, querying its data, and mapping it as CMDB data is performed by the Jython code. For example, the code contains the logic for connecting to a database and extracting data from it. In this case, the code expects to receive a JDBC URL, a user name, a password, a port, and so on. These parameters are specific for each instance of the database that answers the TQL query. You define these variables in the adapter (in the Trigger CI data) and when the job runs, these specific details are passed to the code for execution.

The adapter can refer to this code by a Java class name or a Jython script name. In this section we discuss writing DFM code as Jython scripts.


An adapter can contain a list of scripts to be used when running discovery. When creating a new adapter, you usually create a new script and assign it to the adapter. A new script includes basic templates, but you can use one of the other scripts as a template by right-clicking it and selecting **Save** as:



For details on writing new Jython scripts, see "Step 3: Create Jython Code" on page 42. You add scripts through the Resources pane:



The list of scripts are run one after the other, in the order in which they are defined in the adapter:



Note: A script must be specified even though it is being used solely as a library by another script. In this case, the library script must be defined before the script using it. In this example, the processdbutils.py script is a library used by the last host_processes.py script. Libraries are distinguished from regular runnable scripts by the lack of the DiscoveryMain() function.

Step 1: Create an Adapter

An adapter can be considered as the definition of a function. This function defines an input definition, runs logic on the input, defines the output, and provides a result.

Each adapter specifies input and output: Both input and output are Trigger CIs that are specifically defined in the adapter. The adapter extracts data from the input Trigger CI and passes this data as parameters to the code. Data from related CIs is sometimes passed to the code too. For details, see "Related CIs Window" in the *HPE Universal CMDB Data Flow Management Guide*. An adapter's code is generic, apart from these specific input Trigger CI parameters that are passed to the code.

For details on input components, see "Data Flow Management Concepts" in the *HPE Universal CMDB Data Flow Management Guide*.

This section includes the following topics:

- "Define Adapter Input (Trigger CIT and Input Query)" on the next page
- "Define Adapter Output" on page 37

- "Override Adapter Parameters" on page 38
- "Override Probe Selection Optional" on page 39
- "Configure a classpath for a remote process Optional" on page 41

Define Adapter Input (Trigger CIT and Input Query)

You use the Trigger CIT and Input Query components to define specific CIs as adapter input:


- The Trigger CIT defines which CIT is used as the input for the adapter. For example, for an adapter that is going to discover IPs, the input CIT is Network.
- The Input query is a regular, editable query that defines the query against the CMDB. The Input
 Query defines additional constraints on the CIT (for example, if the task requires a hostID or
 application_ip attribute), and can define more CI data, if needed by the adapter.
 - If the adapter requires additional information from the CIs that are related to the Trigger CI, you can add additional nodes to the input TQL. For details, see "How to Add Query Nodes and Relationships to a TQL Query" in the HPE Universal CMDB Modeling Guide.
- The Trigger CI data contains all the required information on the Trigger CI as well as information from the other nodes in the Input TQL, if they are defined. DFM uses variables to retrieve data from the CIs. When the task is downloaded to the Probe, the Trigger CI data variables are replaced with actual values that exist on the attributes for real CI instances.
- If the value of the destination data is a list, you can define the number of items from the list to be sent to the probe. To define it, add a colon after the default value followed by the number of items. If there is no default value for the destination data, enter two colons.

For example, if the following destination data is entered: name=portId, value= \${PHYSICALPORT.root_id:NA:1} or name=portId, value= \${PHYSICALPORT.root_id::1}, only the first port from the port list is sent to the probe.

Example of Replacing Variables with Actual Data:

In this example, variables replace the **IpAddress** CI data with actual values that exist on real **IpAddress** CI instances in your system.


The Triggered CI data for the **IpAddress** CI includes a fileName variable. This variable enables the replacement of the **CONFIGURATION_DOCUMENT** node in the Input TQL with the actual values of the configuration file located on a host:




The Trigger CI data is uploaded to the Probe with all variables replaced by actual values. The adapter script includes a command to use the DFM Framework to retrieve the actual values of the defined variables:

Framework.getTriggerCIData ('ip_address')

The fileName and path variables use the data_name and document_path attributes from the **CONFIGURATION_DOCUMENT** node (defined in the Input Query Editor – see previous example).




thumbnail to view full size image.




2. Define Adapter Output

The output of the adapter is a list of discovered CIs (**Data Flow Management > Adapter Management > Adapter Definition** tab **> Discovered CITs**) and the links between them:



You can also view the CITs as a topology map, that is, the components and the way in which they are linked together (click the **View Discovered CITs as Map** button):



The discovered CIs are returned by the DFM code (that is, the Jython script) in the format of UCMDB's <code>ObjectStateHolderVector</code>. For details, see "Results Generation by the Jython Script" on page 50.

Example of Adapter Output:

In this example, you define which CITs are to be part of the IP CI output.

- a. Access Data Flow Management > Adapter Management.
- b. In the Resources pane, select **Network > Adapters > NSLOOKUP_on_Probe**.
- c. In the Adapter Definition tab, locate the Discovered CITs pane.
- d. The CITs that are to be part of the adapter output are listed. Add CITs to, or remove from, the list. For details, see "Adapter Definition Tab" in the *HPE Universal CMDB Data Flow Management Guide*.


3. Override Adapter Parameters

To configure an adapter for more than one job, you can override adapter parameters. For example, the adapter SQL_NET_Dis_Connection is used by both the MSSQL Connection by SQL and the Oracle Connection by SQL jobs.

Example of Overriding an Adapter Parameter:

This example illustrates overriding an adapter parameter so that one adapter can be used to discover both Microsoft SQL Server and Oracle databases.

- a. Access Data Flow Management > Adapter Management.
- b. In the Resources pane, select Database_Basic > Adapters > SQL_NET_Dis_
 Connection.
- c. In the Adapter Definition tab, locate the **Adapter Parameters** pane. The protocolType parameter has a value of **all**:



- d. Right-click the SQL_NET_Dis_Connection_MsSql adapter and choose Go to
 Discovery Job > MSSQL Connection by SQL.
- e. Display the **Properties** tab. Locate the Parameters pane:

Parameters		
Override	Name	Value
✓	protocolType	MicrosoftSQLServer

The all value is overwritten with the MicrosoftSQLServer value.

Note: The **Oracle Connection by SQL** job includes the same parameter but the value is overwritten with an Oracle value.

For details on adding, deleting, or editing parameters in the Adapter Parameters pane, see "Adapter Definition Tab" in the *HPE Universal CMDB Data Flow Management Guide*.

DFM begins looking for Microsoft SQL Server instances according to this parameter.

Override Probe Selection - Optional

On the UCMDB server there is a dispatching mechanism that takes the trigger CIs received by the UCMDB and automatically chooses which probe should run the job for each trigger CI according to one of the following options:

- For the IP address CI type: Take the probe that is defined for this IP.
- For the running software CI type: Use the attributes application ip and application ip

domain and choose the probe that is defined for the IP in the relevant domain.

For other CI types: Take the node's IP according to the CI's related node (if it exists).

The automatic probe selection is done according to the CI's related node. After obtaining the CI's related node, the dispatching mechanism chooses one of the node's IPs and chooses the probe according to the probe's network scope definitions.

In the following cases, you need to specify the probe manually and not use the automatic dispatching mechanism:


- You already know which probe should be run for the adapter and you do not need the automatic dispatching mechanism to select the probe (for example if the trigger CI is the probe gateway).
- The automatic probe selection might fail. This can happen in the following situations:
 - A trigger CI does not have a related node (such as the network CIT)
 - A trigger CI's node has multiple IPs, each belonging to a different probe.

To manually specify which probe to use with the adapter:

- Select the adapter and click the **Adapter Configuration** tab.
- Under Trigger Dispatch Options, select Override default probe selection.
- In the box, enter the Probe in one of the following formats:

Probe name	The name of the Probe
IP address	The Probe's IP address—can be defined in either IPv4 or IPv6 format
IP,Domain	IPv4 format: 16.59.63.86,DefaultDomain
	IPv6 format: 2001:0:9d46:953c:34a9:1e6b:f2ff:fffe,CustomDomain
Domain name	The domain from which the Probe should be selected.

For example:




5. Configure a classpath for a remote process - Optional

For details, see "Configure Remote Process Execution" on page 43.

Step 2: Assign a Job to the Adapter

Each adapter has one or more associated jobs that define the execution policy. Jobs enable scheduling the same adapter differently over different sets of Triggered CIs and also enable supplying different parameters for each set.

The jobs appear in the Discovery Modules tree, and this is the entity that the user activates, as shown in the picture below.



Choose a Trigger TQL

Each job is associated with Trigger TQLs. These Trigger TQLs publish results that are used as Input Trigger CIs for the adapter of this job.

A Trigger TQL can add constraints to an Input TQL. For example, if an input TQL's results are IPs connected to SNMP, a trigger TQL's results can be IPs connected to SNMP within the range 195.0.0.0-195.0.0.10.

Note: A trigger TQL must refer to the same objects that the input TQL refers to. For example, if an input TQL queries for IPs running SNMP, you cannot define a trigger TQL (for the same job) to query for IPs connected to a host, because some of the IPs may not be connected to an SNMP object, as required by the input TQL.

Set Scheduling Information

The scheduling information for the Probe specifies when to run the code on Trigger CIs. If the **Invoke** on new triggered CIs Immediately check box is selected, the code also runs once on each Trigger CI when it reaches the Probe, regardless of future schedule settings.



For each scheduled occurrence for each job, the Probe runs the code against all Trigger CIs accumulated for that job. For details, see Discovery Scheduler Dialog Box in the *HPE Universal CMDB Data Flow Management Guide*.

Override Adapter Parameters

When configuring a job you can override the adapter parameters. For details, see "Override Adapter Parameters" on page 38.

Step 3: Create Jython Code

Universal CMDB uses Jython scripts for adapter-writing. For example, the SNMP_Connection.py script is used by the SNMP_NET_Dis_Connection adapter to try and connect to machines using SNMP. Jython is a language based on Python and powered by Java.

For details on how to work in Jython, you can refer to these websites:

- http://www.jython.org
- http://www.python.org

For details, see "Create Jython Code" on page 45.

Configure Remote Process Execution

You can run discovery for a discovery job in a process separate from the Data Flow Probe's process.

For example, you can run the job in a separate remote process if the job uses **.jar** libraries that are a different version than the Probe's libraries or that are incompatible with the Probe's libraries.

You can also run the job in a separate remote process if the job potentially consumes a lot of memory (brings a lot of data) and you want to isolate the Probe from potential **OutOMemory** problems.

To configure a job to run as a remote process, define the following parameters in its adapter's configuration file:

Parameter	Description
remoteJVMArgs	JVM parameters for the remote Java process.
runInSeparateProcess	When set to true , the discovery job runs in a separate process.
remoteJVMClasspath	(Optional) Enables customization of the classpath of the remote process, overriding the default Probe classpath. This is useful if there might be version incompatibility between the Probe's jars and custom jars required for the customer-defined discovery.
	If the remoteJVMClasspath parameter is not defined, or is left empty, the default Probe classpath is used.
	If you develop a new discovery job and you want to ensure that the Probe jar library version does not collide with the job's jar libraries, you must use at least the minimal classpath required to execute basic discovery. The minimal classpath is defined in the <code>DataFlowProbe.properties</code> file in the <code>basic_discovery_minimal_classpath</code> parameter.
	Examples of remoteJVMClasspath customization:
	To prepend or append custom jars to the default Probe classpath. customize the remoteJVMClasspath parameter as follows:
	custom1.jar;%classpath%;custom2.jar -
	In this case, custom1.jar is placed before default Probe classpath, and custom2.jar is appended to the Probe classpath.
	To use the minimal classpath, customize the remoteJVMClasspath

Parameter	Description	
	parameter as follows:	
	custom1.jar;%minimal_classpath%;custom2.jar	

Chapter 2: Developing Jython Adapters

This chapter includes:

HP Data Flow Management API Reference	45
Create Jython Code	45
Support Localization in Jython Adapters	61
Record DFM Code	69
Jython Libraries and Utilities	7

HP Data Flow Management API Reference

For full documentation on the available APIs, see *HP Universal CMDB Data Flow Management API Reference*. These files are located in the following folder:

<UCMDB install directory>\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\DDM_
JavaDoc\index.html

Create Jython Code

Universal CMDB uses Jython scripts for adapter-writing. For example, the **SNMP_Connection.py** script is used by the **SNMP_NET_Dis_Connection** adapter to try to connect to machines using SNMP. Jython is a language based on Python and powered by Java.

For details on how to work in Jython, you can refer to these websites:

- http://www.jython.org
- http://www.python.org

The following section describes the actual writing of Jython code inside the DFM Framework. This section specifically addresses those contact points between the Jython script and the Framework that it calls, and also describes the Jython libraries and utilities that should be used whenever possible.

Note:

- Scripts written for Universal Discovery should be compatible with Jython version 2.5.3.
- For full documentation on the available APIs, see the *HP Universal CMDB Data Flow Management API Reference*.

This section includes the following topics:

- "Use External Java JAR Files within Jython" below
- "Execution of the Code" below
- "Modifying Out-of-the-Box Scripts" on the next page
- "Structure of the Jython File" on the next page
- "Results Generation by the Jython Script" on page 50
- "The Framework Instance" on page 53
- "Finding the Correct Credentials (for Connection Adapters)" on page 56
- "Handling Exceptions from Java" on page 59

Use External Java JAR Files within Jython

When developing new Jython scripts, external Java Libraries (JAR files) or third-party executable files are sometimes needed as Java utility archives, connection archives such as JDBC Driver JAR files, or executable files (for example, **nmap.exe** is used for credential-less discovery).

These resources should be bundled in the package under the **External Resources** folder. Any resource put in this folder is automatically sent to any Probe that connects to your Universal CMDB server.

In addition, when discovery is launched, any JAR file resource is loaded into the Jython's classpath, making all the classes within it available for import and use.

Execution of the Code

After a job is activated, a task with all the required information is downloaded to the Probe.

The Probe starts running the DFM code using the information specified in the task.

The Jython code flow starts running from a main entry in the script, executes code to discover CIs, and provides results of a vector of discovered CIs.

Modifying Out-of-the-Box Scripts

When making out-of-the-box script modifications, make only minimal changes to the script and place any necessary methods in an external script. You can track changes more efficiently and, when moving to a newer Universal CMDB version, your code is not overwritten.

For example, the following single line of code in an out-of-the-box script calls a method that calculates a Web server name in an application-specific way:

```
serverName = iplanet_cspecific.PlugInProcessing(serverName, transportHN, mam_utils)
```

The more complex logic that decides how to calculate this name is contained in an external script:

Save the external script in the External Resources folder. For details, see Resources Pane in the *HPE Universal CMDB Data Flow Management Guide*. If you add this script to a package, you can use this script for other jobs, too. For details on working with Package Manager, see Package Manager in the *HPE Universal CMDB Administration Guide*.

During upgrade, the change you make to the single line of code is overwritten by the new version of the out-of-the-box script, so you will need to replace the line. However, the external script is not overwritten.

Structure of the Jython File

The Jython file is composed of three parts in a specific order:

- 1. Imports
- 2. Main Function DiscoveryMain
- 3. Functions definitions (optional)

The following is an example of a Jython script:

```
# imports section
from appilog.common.system.types import ObjectStateHolder
from appilog.common.system.types.vectors import ObjectStateHolderVector
# Function definition
def foo:
    # do something
# Main Function
def DiscoveryMain(Framework):
    OSHVResult = ObjectStateHolderVector()
    ## Write implementation to return new result CIs here...
    return OSHVResult
```

Imports

Jython classes are spread across hierarchical namespaces. In version 7.0 or later, unlike in previous versions, there are no implicit imports, and so every class you use must be imported explicitly. (This change was made for performance reasons and to enable an easier understanding of the Jython script by not hiding necessary details.)

To import a Jython script:

```
import logger
```

• To import a Java class:

```
from appilog.collectors.clients import ClientsConsts
```

Main Function – DiscoveryMain

Each Jython runnable script file contains a main function: DiscoveryMain.

The DiscoveryMain function is the main entry into the script; it is the first function that runs. The main function may call other functions that are defined in the scripts:


```
def DiscoveryMain(Framework):
```

The Framework argument must be specified in the main function definition. This argument is used by the main function to retrieve information that is required to run the scripts (such as information on the Trigger CI and parameters) and can also be used to report on errors that occur during the script run.

You can create a Jython script without any main method. Such scripts are used as library scripts that are called from other scripts.

Functions Definition

Each script can contain additional functions that are called from the main code. Each such function can call another function, which either exists in the current script or in another script (use the import statement). Note that to use another script, you must add it to the Scripts section of the package:



Example of a Function Calling Another Function:

In the following example, the main code calls the doQueryOSUsers(...) method which calls an internal method doOSUserOSH(...):

```
OSUserOSH.setContainer(_hostObj)
   OSHVResult.add(OSUserOSH)

def DiscoveryMain(Framework):
   OSHVResult = ObjectStateHolderVector()
   try:
        client = Framework.createClient(Framework.getTriggerCIData
(BaseClient.CREDENTIALS_ID))
   except:
        Framework.reportError('Connection failed')
   else:
        doQueryOSUsers(client, OSHVResult)
        client.close()
   return OSHVResult
```

If this script is a global library that is relevant to many adapters, you can add it to the list of scripts in the jythonGlobalLibs.xml configuration file, instead of adding it to each adapter (Adapter Management > Resources Pane > AutoDiscoveryContent > Configuration Files).

Results Generation by the Jython Script

Each Jython script runs on a specific Trigger CI, and ends with results that are returned by the return value of the DiscoveryMain function.

The script result is actually a group of CIs and links that are to be inserted or updated in the CMDB. The script returns this group of CIs and links in the format of <code>ObjectStateHolderVector</code>.

The ObjectStateHolder class is a way to represent an object or link defined in the CMDB. The ObjectStateHolder object contains the CIT name and a list of attributes and their values. The ObjectStateHolderVector is a vector of ObjectStateHolder instances.

The ObjectStateHolder Syntax

This section explains how to build the DFM results into a UCMDB model.

Example of Setting Attributes on the CIs:

The ObjectStateHolder class describes the DFM result graph. Each CI and link (relationship) is placed inside an instance of the ObjectStateHolder class as in the following Jython code sample:

siebel application server 1 appServerOSH = ObjectStateHolder('siebelappserver') 2 appServerOSH.setStringAttribute('data_name', sblsvrName) 3 appServerOSH.setStringAttribute ('application_ip', ip) 4 appServerOSH.setContainer(appServerHostOSH)

- Line 1 creates a CI of type siebelappserver.
- Line 2 creates an attribute called data_name with a value of sblsvrName which is a Jython variable set with the value discovered for the server name.
- Line 3 sets a non-key attribute that is updated in the CMDB.
- Line 4 is the building of containment (the result is a graph). It specifies that this application server is contained inside a host (another ObjectStateHolder class in the scope).

Note: Each CI being reported by the Jython script must include values for all the key attributes of the CI's CI Type.

Example of Relationships (Links):

The following link example explains how the graph is represented:

1 linkOSH = ObjectStateHolder('route') 2 linkOSH.setAttribute('link_end1', gatewayOSH) 3 linkOSH.setAttribute('link_end2', appServerOSH)

- Line 1 creates the link (that is also of the ObjectStateHolder class. The only difference is that route is a link CI Type).
- Lines 2 and 3 specify the nodes at the end of each link. This is done using the **end1** and **end2** attributes of the link which must be specified (because they are the minimal key attributes of each link). The attribute values are <code>ObjectStateHolder</code> instances. For details on End 1 and End 2, see Link in the HPE Universal CMDB Data Flow Management Guide.

Caution: A link is directional. You should verify that End 1 and End 2 nodes correspond to valid CITs at each end. If the nodes are not valid, the result object fails validation and is not reported correctly. For details, see CI Type Relationships in the *HPE Universal CMDB Modeling Guide*.

Example of Vector (Gathering CIs):

After creating objects with attributes, and links with objects at their ends, you must now group them together. You do this by adding them to an ObjectStateHolderVector instance, as follows:

```
oshvMyResult = ObjectStateHolderVector()
oshvMyResult.add(appServerOSH)
oshvMyResult.add(linkOSH)
```

For details on reporting this composite result to the Framework so that it can be sent to the CMDB server, see the sendObjects method.

Once the result graph is assembled in an <code>ObjectStateHolderVector</code> instance, it must be returned to the DFM Framework to be inserted into the CMDB. This is done by returning the <code>ObjectStateHolderVector</code> instance as the result of the <code>DiscoveryMain()</code> function.

Note: For details on creating OSH for common CITs, see "modeling.py" on page 73.

Sending Large Amounts of Data

Sending large amounts of data (usually more than 20 KB) is difficult to process in UCMDB. Data of this size should be split into smaller chunks before sending to UCMDB. In order for all the chunks to be correctly inserted to UCMDB, each chunk needs to contain required identification information for the CIs in the chunk. This is a common scenario when developing Jython integrations. The sendObjects method is used to send the results in chunks. If the Jython script sends a large number of results (the default value is 20,000, but this value can be configured in the DataFlowProbe.properties File using the appilog.agent.local.maxTaskResultSize key) it should chunk the results according to their topology. This chunking should be performed taking into account identification rules so that the results are entered correctly in UCMDB. If the Jython script does not chunk the results, the probe attempts to chunk them; however, this can lead to poor performance for a large result set.

Note: Chunking should be used for Jython integration adapters and not for regular discovery jobs. This is because discovery jobs usually discover information regarding a specific trigger and do not send large amounts of information. With Jython integrations, large amounts of data are discovered on the single trigger of the integration.

It is also possible to use chunking for a small number of results. In such a case, there is a relationship between CIs in different chunks and the developer of the Jython script has two options:

- Send the entire CI and all of its identification information again in every chunk that contains a link to it.
- Use the UCMDB ID of the CI. To do this, the Jython script has to wait for each chunk to be
 processed in the UCMDB server in order to get the UCMDB IDs. To enable this mode (called
 synchronous result sending), add the SendJythonResultsSynchronously tag to the adapter. This
 tag ensures that when you finish sending the chunk, the UCMDB IDs of the CIs in the chunk have

already been received by the probe. The adapter developer can use the UCMDB IDs for generating the next chunk. To use the UCMDB IDs, use the framework API getIdMapping.

Example of Using getIdMapping

In the first chunk you send nodes. In the second chunk you send processes. The root container of the process is a node. Instead of sending the entire objectStateHolder of the node in the process root_container attribute, you can get the UCMDB ID of the node using the getIdMapping API and use only the node ID in the process root_container attribute to make the chunk smaller.

The Framework Instance

The Framework instance is the only argument that is supplied in the main function in the Jython script. This is an interface that can be used to retrieve information required to run the script (for example, information on trigger CIs and adapter parameters), and is also used to report on errors that occur during the script run. For details, see "HP Data Flow Management API Reference" on page 45.


The correct usage of Framework instance is to pass it as argument to each method that uses it.

This section describes the most important Framework usages:

- "Framework.getTriggerCIData(String attributeName)" on the next page
- "Framework.createClient(credentialsId, props)" on the next page
- "Framework.getParameter (String parameterName)" on page 55
- "Framework.reportError(String message) and Framework.reportWarning(String message)" on page 56

Framework.getTriggerCIData(String attributeName)

This API provides the intermediate step between the Trigger CI data defined in the adapter and the script.



Framework.createClient(credentialsId, props)

You make a connection to a remote machine by creating a client object and executing commands on that client. To create a client, retrieve the ClientFactory class. The getClientFactory() method receives the type of the requested client protocol. The protocol constants are defined in the ClientsConsts class. For details on credentials and supported protocols, see the HPE Universal CMDB Discovery and Integrations Content Guide.

```
Example of Creating a Client Instance for the Credentials ID:

To create a Client instance for the credentials ID:

properties = Properties()

codePage = Framework.getCodePage()

properties.put( BaseAgent.ENCODING, codePage)

client = Framework.createClient(credentailsID, properties)

You can now use the Client instance to connect to the relevant machine or application.
```


Example of Creating a WMI Client and Running a WMI Query:

To create a WMI client and run a WMI guery using the client:

Note: To make the createClient() API work, add the following parameter to the Trigger CI data parameters: **credentialsId = \${SOURCE.credentials_id}** in the Triggered CI Data pane. Or you can manually add the credentials ID when calling the function:

wmiClient = clientFactory().createClient(credentials_id).

The following diagram illustrates the hierarchy of the clients, with their commonly-supported APIs:



For details on the clients and their supported APIs, see BaseClient, ShellClient, and QueryClient in the DFM Framework. These files are located in the following folder:

<UCMDB root directory>\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\DDM_
Schema\webframe.html

Framework.getParameter (String parameterName)

In addition to retrieving information on the Trigger CI, you often need to retrieve an adapter parameter value. For example:



Example of Retrieving the Value of the protocolType Parameter:

To retrieve the value of the protocol Type parameter from the Jython script, use the following API:

```
protocolType = Framework.getParameterValue('protocolType')
```

Framework.reportError(String message) and Framework.reportWarning(String message)

Some errors (for example, connection failure, hardware problems, timeouts) can occur during a script run. When such errors are detected, Framework can report on the problem. The message that is reported reaches the server and is displayed for the user.

Example of a Report Error and Message:

```
The following example illustrates the use of the reportError(<Error Msg>) API:

try:
    client = Framework.createClient(Framework.getTriggerCIData
(BaseClient.CREDENTIALS_ID))

except:
    strException = str(sys.exc_info()[1]).strip()
    Framework. reportError ('Connection failed: %s' % strException)
```

You can use either one of the APIs—Framework.reportError(String message),

Framework.reportWarning(String message)—to report on a problem. The difference between the two APIs is that when reporting an error, the Probe saves a communication log file with the entire session's parameters to the file system. In this way you are able to track the session and better understand the error.

For details on error messages, see "Error Messages" on page 74.

Finding the Correct Credentials (for Connection Adapters)

An adapter trying to connect to a remote system needs to try all possible credentials. One of the parameters needed when creating a client is the credentials ID. The connection script gains access to possible credential sets and tries them one by one using the Framework.getAvailableProtocols() method. When one credential set succeeds, the adapter reports a CI connection object on the host of this trigger CI (with the credentials ID that matches the IP) to the CMDB. Subsequent adapters can use this connection object CI directly to connect to the credential set (that is, the adapters do not have to try all possible credentials again).

Note: Access to sensitive data (passwords, private keys, and so on) is blocked for the following protocol types:

sshprotocol, ntadminprotocol, as400protocol, vmwareprotocol, wmiprotocol, vcloudprotocol, sapjmxprotocol, websphereprotocol, siebelgtwyprotocol, sapprotocol, ldapprotocol, udaprotocol, ntcmdprotocol, snmpprotocol, jbossprotocol, telnetprotocol, powershellprotocol, sqlprotocol, weblogicprotocol

Utilization of these protocol types should be done by using dedicated clients.

The following example shows how to obtain all entries of the SNMP protocol. Note that here the IP is obtained from the Trigger CI data (# Get the Trigger CI data values).

The connection script requests all possible protocol credentials (# Go over all the protocol credentials) and tries them in a loop until one succeeds (resultVector). For details, see the **two-phase connect paradigm** entry in "Separating Adapters" on page 31.

Example

```
import logger
import netutils
import sys
import errorcodes
import errorobject
# Java imports
from java.util import Properties
from com.hp.ucmdb.discovery.common import CollectorsConstants
from appilog.common.system.types.vectors import ObjectStateHolderVector
from com.hp.ucmdb.discovery.library.clients import ClientsConsts
from com.hp.ucmdb.discovery.library.scope import DomainScopeManager
TRUE = 1
FALSE = 0
def mainFunction(Framework, isClient, ip_address = None):
       _vector = ObjectStateHolderVector()
       errStr = ''
       ip_domain = Framework.getDestinationAttribute('ip_domain')
       # Get the Trigger CI data values
       ip address = Framework.getDestinationAttribute('ip address')
          if (ip domain == None):
             ip domain = DomainScopeManager.getDomainByIp(ip address, None)
          protocols = netutils.getAvailableProtocols(Framework,
          ClientsConsts.SNMP_PROTOCOL_NAME, ip_address, ip_domain)
          if len(protocols) == 0:
              errStr = 'No credentials defined for the triggered ip'
```

```
logger.debug(errStr)
      errObj = errorobject.createError(errorcodes.NO CREDENTIALS FOR
 TRIGGERED_IP, [ClientsConsts.SNMP_PROTOCOL_NAME], errStr)
      return ( vector, errObj)
  connected = 0
 # Go over all the protocol credentials
 for protocol in protocols:
     client = None
     try:
         try:
              logger.debug('try to get snmp agent for: %s:%s' % (ip_
  address, ip_domain))
              if (isClient == TRUE):
                  properties = Properties()
                  properties.setProperty
  (CollectorsConstants.DESTINATION DATA IP ADDRESS, ip address)
                  properties.setProperty
  (CollectorsConstants.DESTINATION_DATA_IP_DOMAIN, ip_domain)
                  client = Framework.createClient(protocol, properties)
              else:
                  properties = Properties()
                  properties.setProperty
  (CollectorsConstants.DESTINATION_DATA_IP_ADDRESS, ip_address)
                  client = Framework.createClient(protocol, properties)
              logger.debug('Running test connection queries')
              testConnection(client)
              Framework.saveState(protocol)
              logger.debug('got snmp agent for: %s:%s' % (ip_address,
 ip_domain))
              isMultiOid = client.supportMultiOid()
              logger.debug('snmp server isMultiOid state=%s'
 %isMultiOid)
           client.close()
           client = None
          except:
              if client != None:
                  client.close()
                  client = None
              logger.debugException('Unexpected SNMP_AGENT Exception:')
              lastExceptionStr = str(sys.exc_info()[1]).strip()
      finally:
         if client != None:
              client.close()
              client = None
return (_vector, error)
```

Handling Exceptions from Java

Some Java classes throw an exception upon failure. It is recommended to catch the exception and handle it, otherwise it causes the adapter to terminate unexpectedly.

When catching a known exception, in most cases you should print its stack trace to the log and issue a proper message to the UI.

Note: It is very important to import the Java base exception class as shown in the following example due to the presence of the base exception class in Python with the same name.

If the exception is not fatal and the script can continue, you should omit the call for the reportError() method and enable the script to continue.

Troubleshooting Migration from Jython Version 2.1 to 2.5.3

Universal Discovery now uses Jython version 2.5.3. All out-of-the-box scripts have been properly migrated. If you developed your own Jython scripts prior to this upgrade for use by Discovery, you may run into the following issues and have to make the fixes indicated.

Note: You must be an experienced Jython developer to make these changes.

String Formatting

- Error message: TypeError: int argument required
- Possible cause: Using string formatting to decimal integer from string variable containing integer data.
- Problematic Jython 2.1 code:

```
variable = "43"
print "%d" % variable
```

• Correct Jython 2.5.3 code:

```
variable = "43"
print "%s" % variable

or

variable = "43"
print "%d" % int(variable)
```

Checking String Type

The code below may not work correctly if input contains unicode strings:

- Problematic Jython 2.1 code: isinstance(unicodeStringVariable, '')
- Correct Jython 2.5.3 code: isinstance(unicodeStringVariable, basestring)

The comparison should be done with basestring to test whether an object is an instance of str or unicode.

Non-ASCII character in file

• Error Message:

```
SyntaxError: Non-ASCII character in file 'x', , but no encoding declared; see http://www.python.org/peps/pep-0263.html for details
```

• Correct Jython 2.5.3 code: (add this to the first line in the file)

```
# coding: utf-8
```

Import sub-packages

Error message:

```
AttributeError: 'module' object has no attribute 'sub package name'
```

- **Possible cause**: A sub-package is imported without explicitly specifying the name of sub-package in the import statement.
- Problematic Jython 2.1 code:

```
import a
print dir(a.b)
```

The sub-package is not explicitly imported.

• Correct Jython 2.5.3 code:

```
import a.b
or
from a import b
```

Iterator Changes

Starting from Jython 2.2, the __iter__ method is used to loop over a collection in the scope of a for-in block. The iterator should implement the next method, returning an appropriate element or throw the **StopIteration** error if it reached the end of the collection. If the __iter__ method is not implemented, the getitem method is used instead.

Raising Exceptions

Jython 2.1 method for raising exceptions is obsolete:

```
raise Exception, 'Failed getting contents of file'
```

• Recommended Jython 2.5.3 method for raising exceptions:

```
raise Exception('Failed getting contents of file')
```

Support Localization in Jython Adapters

The multi-lingual locale feature enables DFM to work across different operating system (OS) languages, and to enable appropriate customizations at runtime.

This section includes:

- "Add Support for a New Language" on the next page
- "Change the Default Language" on page 63
- "Determine the Character Set for Encoding" on page 63
- "Define a New Job to Operate With Localized Data" on page 64
- "Decode Commands Without a Keyword" on page 65

- "Work with Resource Bundles" on page 66
- "API Reference" on page 67

Add Support for a New Language

This task describes how to add support for a new language.

This task includes the following steps:

- "Add a Resource Bundle (*.properties Files)" below
- "Declare and Register the Language Object" below

1. Add a Resource Bundle (*.properties Files)

Add a resource bundle according to the job that is to be run. The following table lists the DFM jobs and the resource bundle that is used by each job:

Job	Base Name of Resource Bundle
File Monitor by Shell	langFileMonitoring
Host Resources and Applications by Shell	langHost_Resources_By_ TTY, langTCP
Hosts by Shell using NSLOOKUP in DNS Server	langNetwork
Host Connection by Shell	langNetwork
Collect Network Data by Shell or SNMP	langTCP
Host Resources and Applications by SNMP	langTCP
Microsoft Exchange Connection by NTCMD, Microsoft Exchange Topology by NTCMD	msExchange
MS Cluster by NTCMD	langMsCluster

For details on bundles, see "Work with Resource Bundles" on page 66.

^{2.} Declare and Register the Language Object

To define a new language, add the following two lines of code to the **shellutils.py** script, that currently contains the list of all supported languages. The script is included in the

AutoDiscoveryContent package. To view the script, access the Adapter Management window. For details, see Adapter Management Window in the *HPE Universal CMDB Data Flow Management Guide*.

a. Declare the language, as follows:

```
LANG_RUSSIAN = Language(LOCALE_RUSSIAN, 'rus', ('Cp866', 'Cp1251'), (1049,),
866)
```

For details on class language, see "API Reference" on page 67. For details on the Class Locale object, see http://docs.oracle.com/javase/1.5.0/docs/api/java/util/Locale.html. You can use an existing locale or define a new locale.

b. Register the language by adding it to the following collection:

```
LANGUAGES = (LANG_ENGLISH, LANG_GERMAN, LANG_SPANISH, LANG_RUSSIAN, LANG_JAPANESE)
```

Change the Default Language

If the OS language cannot be determined, the default one is used. The default language is specified in the **shellutils.py** file.

```
#default language for fallback
DEFAULT_LANGUAGE = LANG_ENGLISH
```

To change the default language, you initialize the DEFAULT_LANGUAGE variable with a different language. For details, see "Add Support for a New Language" on the previous page.

Determine the Character Set for Encoding

The suitable character set for decoding command output is determined at runtime. The multi-lingual solution is based on the following facts and assumptions:

- 1. It is possible to determine the OS language in a locale-independent way, for example, by running the **chcp** command on Windows or the **locale** command on Linux.
- 2. Relation Language-Encoding is well known and can be defined statically. For example, the Russian language has two of the most popular encoding: Cp866 and Windows-1251.
- 3. One character set for each language is preferable, for example, the preferable character set for Russian language is Cp866. This means that most of the commands produce output in this encoding.
- 4. Encoding in which the next command output is provided is unpredictable, but it is one of the

- possible encoding for a given language. For example, when working with a Windows machine with a Russian locale, the system provides the **ver** command output in Cp866, but the **ipconfig** command is provided in Windows-1251.
- 5. A known command produces known key words in its output. For example, the ipconfig command contains the translated form of the IP-Address string. So the ipconfig command output contains IP-Address for the English OS, IP-Adpec for the Russian OS, IP-Adresse for the German OS, and so on.

Once it is discovered in which language the command output is produced (# 1), possible character sets are limited to one or two (# 2). Furthermore, it is known which key words are contained in this output (# 5).

The solution, therefore, is to decode the command output with one of the possible encoding by searching for a key word in the result. If the key word is found, the current character set is considered the correct one.

Define a New Job to Operate With Localized Data

This task describes how to write a new job that can operate with localized data.

Jython scripts usually execute commands and parse their output. To receive this command output in a properly decoded manner, use the API for the **ShellUtils** class. For details, see "HPE Universal CMDB (UCMDB) Web Service API Overview" on page 336.

This code usually takes the following form:

```
client = Framework.createClient(protocol, properties)
shellUtils = shellutils.ShellUtils(client)
languageBundle = shellutils.getLanguageBundle ('langNetwork',
shellUtils.osLanguage, Framework)
strWindowsIPAddress = languageBundle.getString('windows_ipconfig_str_ip_address')
ipconfigOutput = shellUtils.executeCommandAndDecode('ipconfig /all',
strWindowsIPAddress)
#Do work with output here
```

1. Create a client:

```
client = Framework.createClient(protocol, properties)
```

2. Create an instance of the **ShellUtils** class and add the operating system language to it. If the language is not added, the default language is used (usually English):

```
shellUtils = shellutils.ShellUtils(client)
```

During object initialization, DFM automatically detects machine language and sets preferable encoding from the predefined Language object. Preferable encoding is the first instance appearing in the encoding list.

Retrieve the appropriate resource bundle from shellclient using the getLanguageBundle method:

```
languageBundle = shellutils.getLanguageBundle ('langNetwork',
shellUtils.osLanguage, Framework)
```

4. Retrieve a keyword from the resource bundle, suitable for a particular command:

```
strWindowsIPAddress = languageBundle.getString('windows_ipconfig_str_ip_
address')
```

Invoke the executeCommandAndDecode method and pass the keyword to it on the ShellUtils object:

```
ipconfigOutput = shellUtils.executeCommandAndDecode('ipconfig /all',
strWindowsIPAddress)
```

The ShellUtils object is also needed to link a user to the API reference (where this method is described in detail).

6. Parse the output as usual.

Decode Commands Without a Keyword

The current approach for localization uses a keyword to decode all of the command output. For details, see the step about retrieving a keyword from the resource bundle in "Define a New Job to Operate With Localized Data" on the previous page.

However, another approach uses a keyword to decode the first command output only, and then decodes further commands with the character set used to decode the first command. To do this, you use the **getCharsetName** and **useCharset** methods of the **ShellUtils** object.

The regular use case works as follows:


- 1. Invoke the executeCommandAndDecode method once.
- 2. Obtain the most recently used character set name through the getCharsetName method.
- 3. Make **shellUtils** use this character set by default, by invoking the **useCharset** method on the **ShellUtils** object.
- 4. Invoke the **execCmd** method of **ShellUtils** one or more times. The output is returned with the character set specified in the previous step. No additional decoding operations occur.

Work with Resource Bundles

A resource bundle is a file that takes a properties extension (*.properties). A properties file can be considered a dictionary that stores data in the format of key = value. Each row in a properties file contains one key = value association. The main functionality of a resource bundle is to return a value by its key.

Resource bundles are located on the Probe machine:

C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryConfigFiles. They are downloaded from the UCMDB Server as any other configuration file. They can be edited, added, or removed, in the Resources window. For details, see Configuration File Pane in the HPE Universal CMDB Data Flow Management Guide.



When discovering a destination, DFM usually needs to parse text from command output or file content. This parsing is often based on a regular expression. Different languages require different regular expressions to be used for parsing. For code to be written once for all languages, all language-specific data must be extracted to resource bundles. There is a resource bundle for each language. (Although it is possible for a resource bundle to contain data for different languages, in DFM each resource bundle contains data for one language only.)

The Jython script itself does not include hard coded, language-specific data (for example, language-specific regular expressions). The script determines the language of the remote system, loads the proper resource bundle, and obtains all language-specific data by a specific key.

The base_name format reflects the intended purpose of this bundle. For example, **langMsCluster** means the resource bundle contains language-specific resources used by the MS Cluster jobs.

The language_identifier format is a 3-letter acronym used to identify the language. For example, rus stands for the Russian language and ger for the German language. This language identifier is included in the declaration of the Language object.

API Reference

This section includes:

- "The Language Class" below
- "The executeCommandAndDecode Method" on the next page
- "The getCharsetName Method" on the next page
- "The useCharset Method" on the next page
- "The getLanguageBundle Method" on page 69
- "The osLanguage Field" on page 69

The Language Class

This class encapsulates information about the language, such as resource bundle postfix, possible encoding, and so on.

Fields

Name	Description
locale	Java object which represents locale.
bundlePostfix	Resource bundle postfix. This postfix is used in resource bundle file names to identify the language. For example, the langNetwork_ger.properties bundle includes a ger bundle postfix.
charsets	Character sets used to encode this language. Each language can have several character sets. For example, the Russian language is commonly encoded with the Cp866 and Windows-1251 encoding.
wmiCodes	The list of WMI codes used by the Microsoft Windows OS to identify the language. All possible codes are listed at http://msdn.microsoft.com/en-us/library/aa394239 (VS.85).aspx (the OSLanguage section). One of the methods for identifying the OS language is to query the WMI class OS for the OSLanguage property.

Name	Description
codepage	Code page used with a specific language. For example, 866 is used for Russian machines and 437 for English machines. One of the methods for identifying the OS language is to retrieve its default codepage (for example, by the chcp command).

The executeCommandAndDecode Method

This method is intended to be used by business logic Jython scripts. It encapsulates the decoding operation and returns a decoded command output.

Arguments

Name	Description
cmd	The actual command to be executed.
keyword	The keyword to be used for the decoding operation.
framework	The Framework object passed to every executable Jython script in DFM.
timeout	The command timeout.
waitForTimeout	Specifies if client should wait when timeout is exceeded.
useSudo	Specifies if sudo should be used (relevant only for UNIX machine clients).
language	Enables specifying the language directly instead of automatically detecting a language.

The getCharsetName Method

This method returns the name of the most recently used character set.

The useCharset Method

This method sets the character set on the ShellUtils instance, which uses this character set for initial data decoding.

Arguments

Name	Description
charsetName	The name of the character set, for example, windows-1251 or UTF-8.

See also "The getCharsetName Method" on the previous page.

The getLanguageBundle Method

This method should be used to obtain the correct resource bundle. This replaces the following API:

Framework.getEnvironmentInformation().getBundle(...)

Arguments

Name	Description
baseName	The name of the bundle without the language suffix, for example, langNetwork.
language	The language object. The ShellUtils.osLanguage should be passed here.
framework	The Framework, common object which is passed to every executable Jython script in DFM.

The osLanguage Field


This field contains an object that represents the language.

Record DFM Code

It can be very useful to record an entire execution, including all parameters, for example, when debugging and testing code. This task describes how to record an entire execution with all relevant variables. Furthermore, you can view extra debug information that is usually not printed to log files even at the debug level.

To record DFM code:

- 1. Access **Data Flow Management > Universal Discovery**. Right-click the job whose run must be logged and select **Go to Adapter** to open the Adapter Management application.
- 2. Locate the Execution Options pane in the Adapter Configuration tab, as shown below.



3. Change the **Create communication log** box to **Always**. For details on setting logging options, see Execution Options Pane in the *HPE Universal CMDB Data Flow Management Guide*.

The following example is the XML log file that is created when the **Host Connection by Shell** job runs and the **Create communication logs** box is set to **Always** or **On Failure**:

The following example shows the message and stacktrace parameters:

Note: CDATA mechanism is used to store information retrieved from user environment in the communication logs. When scan files get some characters or XML segments that cannot be parsed by the CDATA mechanism, the information will be saved in binary format for further troubleshooting purpose. HPE Software Support will decode the binary data in the communication logs to perform troubleshooting.

Jython Libraries and Utilities

Several utility scripts are used widely in adapters. These scripts are part of the AutoDiscovery package and are located under:


C:\hp\UCMDB\DataFlowProbe\runtime\probeManager\discoveryScripts with the other scripts that are downloaded to the Probe.

Note: The discoveryScript folder is created dynamically when the Probe begins working.

To use one of the utility scripts, add the following import line to the import section of the script:

import <script name>

The AutoDiscovery Python library contains Jython utility scripts. These library scripts are considered DFM's external library. They are defined in the jythonGlobalLibs.xml file (located in the Configuration Files folder).



Each script that appears in the jythonGlobalLibs.xml file is loaded by default at Probe startup, so there is no need to use them explicitly in the adapter definition.

This section includes the following topics:

- "logger.py" below
- "modeling.py" on the next page
- "netutils.py" on the next page
- · "shellutils.py" on the next page

logger.py

The **logger.py** script contains log utilities and helper functions for error reporting. You can call its debug, info, and error APIs to write to the log files. Log messages are recorded in **C:\hp\UCMDB\DataFlowProbe\runtime\log**.

Messages are entered in the log file according to the debug level defined for the PATTERNS_DEBUG appender in the C:\hp\UCMDB\DataFlowProbe\conf\log\probeMgrLog4j.properties file. (By default, the level is DEBUG.) For details, see "Error Severity Levels" on page 78.

```
################
                    PATTERNS DEBUG log
#####################
log4j.category.PATTERNS DEBUG=DEBUG, PATTERNS DEBUG
log4j.appender.PATTERNS_DEBUG=org.apache.log4j.RollingFileAppender
log4j.appender.PATTERNS
DEBUG.File=C:\hp\UCMDB\DataFlowProbe\runtime\log/probeMgr-patternsDebug.log
log4j.appender.PATTERNS DEBUG.Append=true
log4j.appender.PATTERNS DEBUG.MaxFileSize=15MB
log4j.appender.PATTERNS DEBUG.Threshold=DEBUG
log4j.appender.PATTERNS_DEBUG.MaxBackupIndex=10
log4j.appender.PATTERNS DEBUG.layout=org.apache.log4j.PatternLayout
log4j.appender.PATTERNS DEBUG.layout.ConversionPattern=<%d> [%-5p] [%t] - %m%n
log4j.appender.PATTERNS DEBUG.encoding=UTF-8
```

The info and error messages also appear in the Command Prompt console.

There are two sets of APIs:

- logger.<debug/info/warn/error>
- logger.<debugException/infoException/warnException/errorException>

The first set issues the concatenation of all its string arguments at the appropriate log level and the second set issues the concatenation as well as issuing the stack trace of the most recently-thrown exception, to provide more information, for example:

```
logger.debug('found the result')
logger.errorException('Error in discovery')
```

modeling.py

The **modeling.py** script contains APIs for creating hosts, IPs, process CIs, and so on. These APIs enable the creation of common objects and make the code more readable. For example:

```
ipOSH= modeling.createIpOSH(ip)
host = modeling.createHostOSH(ip_address)
member1 = modeling.createLinkOSH('member', ipOSH, networkOSH)
```

netutils.py

The **netutils.py** library is used to retrieve network and TCP information, such as retrieving operating system names, checking if a MAC address is valid, checking if an IP address is valid, and so on. For example:

```
dnsName = netutils.getHostName(ip, ip)
isValidIp = netutils.isValidIp(ip_address)
address = netutils.getHostAddress(hostName)
```

shellutils.py

The **shellutils.py** library provides an API for executing shell commands and retrieving the end status of an executed command, and enables running multiple commands based on that end status. The library is initialized with a Shell Client, and uses the client to run commands and retrieve results. For example:

Chapter 3: Error Messages

This chapter includes:

Error Messages Overview	74
Error-Writing Conventions	74
Error Severity Levels	78

Error Messages Overview

During discovery, many errors may be uncovered, for example, connection failures, hardware problems, exceptions, time-outs, and so on. These errors are displayed in the Universal Discovery window whenever the regular discovery flow does not succeed. You can drill down from the Trigger CI that caused the problem to view the error message itself.

DFM differentiates between errors that can sometimes be ignored (for example, an unreachable host) and errors that must be dealt with (for example, credentials problems or missing configuration or DLL files). Moreover, DFM reports errors once, even if the same error occurs on successive runs, and reports an error even it if occurs once only.

When creating a package, you can add appropriate messages as resources to the package. During package deployment, the messages are also deployed in the correct location. Messages must conform to conventions, as described in "Error-Writing Conventions" below.

DFM supports multi-language error messages. You can localize the messages you write so that they appear in the local language.

For details on searching for errors, see "Discovery Progress and Results" in the *HPE Universal CMDB Data Flow Management Guide*.

For details on setting communication logs, see "Execution Options Pane" in the *HPE Universal CMDB Data Flow Management Guide*.

Error-Writing Conventions

• Each error is identified by an error message code and an array of arguments (int, String[]). A combination of a message code and an array of arguments defines a specific error. The array of

parameters can be null.

Each error code is mapped to a short message which is a fixed string and a detailed message
which is a template string contains zero or more arguments. Matching is assumed between the
number of arguments in the template and the actual number of parameters.

Example of Error Message Code:

10234 may represent an error with the short message:

Connection Error

and the detailed message:

Could not connect via {0} protocol due to timeout of {1} msec

where

{0} = the first argument: a protocol name

{1} = the second argument: the timeout length in msec

This section also includes the following topics:

- "Property File Content" below
- "Error Messages Property File" on the next page
- "Locale Naming Conventions" on the next page
- "Error Message Codes" on the next page
- "Unclassified Content Errors" on page 77
- "Changes in Framework" on page 77

Property File Content

A property file should contain two keys for each error message code. For example, for error 45:

- DDM_ERROR_MESSAGE_SHORT_45. Short error description.
- DDM_ERROR_MESSAGE_LONG_45. Long error description (can contain parameters, for example, {0},{1}).

Error Messages Property File

A property file contains a map between an error message code and two messages (short and detailed).

Once a property file is deployed, its data is merged with existing data, that is, new message codes are added while old message codes are overridden.

Infrastructure property files are part of the AutoDiscoveryInfra package.

Locale Naming Conventions

- For the default locale: <file name>.properties.errors
- For a specific locale: <file name>_xx.properties.errors
 where xx is the locale (for example, infraerr_fr.properties.errors or infraerr_en_us.properties.errors).

Error Message Codes

The following error codes are included by default with Universal CMDB. You can add your own error messages to this list.

Error Name	Error Code	Description
Internal	100- 199	Mostly resolved from exceptions thrown during Jython script runs
Connection	200- 299	Connection failed, no agent on target machine, destination unreachable, and so on
Credential Related	300- 399	Permission denied, connection attempt blocked due to a lack of credentials
Timeout	400- 499	Time-out during connection/command
Unexpected or Invalid Behavior	500- 599	Missing configuration files, unexpected interruptions, and so on
Information	600-	Missing information on target machines, failure querying agent for

Error Name	Error Code	Description	
Retrieval	699	information, and so on	
Resources Related	700- 799	Errors relating to out-of-memory or clients not released properly	
Parsing	800- 899	Error parsing text	
Encoding	900	Error in input, unsupported encoding	
SQL Related	901- 903, 924	Errors received from SQL operations	
HTTP Related	904- 909	Errors generated during HTTP connections, parsed from HTTP error codes.	
Specific Application	910- 923	Error reported due to application-specific problems, for example, wrong LSOF version, No Queue Managers found, and so on	

Unclassified Content Errors

To support old content without causing a regression, the application and SDK relevant methods handle errors of message code 100 (that is, unclassified script error) differently.

These errors are not grouped (that is, they are not considered as being errors of the same type) by their message code but are grouped by the content of the message. That is, if a script reports an error by the old, deprecated methods (with a message string and without an error code), all messages receive the same error code, but in the application or in the SDK relevant methods, different messages are displayed as different errors.

Changes in Framework

(com.hp.ucmdb.discovery.library.execution.BaseFramework)

The following methods are added to the interface:

- void reportError(int msgCode, String[] params);
- void reportWarning(int msgCode, String[] params);

void reportFatal(int msgCode, String[] params);

The following old methods are still supported for backward compatibility purposes but are marked as deprecated:

- void reportError(String message);
- void reportWarning (String message);
- void reportFatal (String message);

Error Severity Levels

When an adapter finishes running against a trigger CI, it returns a status. If no error or warning is reported, the status is **Success**.

Severity levels are listed here from the narrowest to widest scope:

Fatal Errors

This level reports serious errors such as a problem with the infrastructure, missing DLL files, or exceptions:

- Failed generating the task (Probe is not found, variables are not found, and so on)
- It is not possible to run the script
- Processing of the results fails on the Server and the data is not written to the CMDB

Errors

This level reports problems that cause DFM not to retrieve data. Look through these errors as they usually require some action to be taken (for example, increase time-out, change a range, change a parameter, add another user credential, and so on).

- In cases where user intervention may help, an error is reported, either a credentials or network problem that may need further investigation. (These are not errors in discovery but in configuration.)
- Internal failure, usually because of unexpected behavior from the discovered machine or application, for example, missing configuration files, and so on

Warnings

When a run is successful but there may be non-serious problems that you should be aware of, DFM marks the severity as **Warning**. You should look at these CIs to see whether data is missing before beginning a more detailed debugging session. **Warning** can include messages about the lack of an installed agent on a remote host, or that invalid data caused an attribute to be calculated incorrectly.

- Missing connection agent (SNMP, WMI)
- Discovery succeeds, but not all available information is discovered

Chapter 4: Mapping Consumer-Provider Dependencies

This chapter includes:

Dependency Discovery Overview	80
Configuration Signature Files	84
Search Connection Strings	88

Dependency Discovery Overview

Dependency mapping provides a flexible method of discovering relationships between deployable components or running software. This method allows the use of user-defined dependency mapping rules (using simple programming syntax), which the Universal Discovery process uses to automatically discover dependencies.

A service can be either a business or IT service. A business service is a service that a business provides to another business (B2B) or that one organization provides to another within a business (such as payment processing). An IT service is a business service that an IT organization provides to support business services or IT's own operations.

A deployable component is a software component that is deployed within running software, such as an application server or web server. Examples of deployable components are JEE EAR components or a schema within an Oracle database. For the purpose of dependency discovery, running software is considered to be a deployable component.

A **provider** deployable component delivers a service, and declares how other deployable components can consume that service. A **consumer** deployable component "consumes" a service provided by a provider deployable component. The dependency between these deployable components is a **consumer-provider** dependency.

Note: The Dependency Signature File included in CP16 (or an earlier version) is obsolete and has been replaced by Configuration Signature in CP 17.

For more information, see the following chapters:

- "Providers and Consumers" on the next page
- "Service Connection Point" on the next page

- "Configuration Signatures" on the next page
- "Dependency Mapping Flow" on the next page

Providers and Consumers

You connect to providers using connection strings. For example, if an Oracle database is a provider, to connect to its services, you might need:

- . The IP address of the machine
- The SID
- The TCP port

These three pieces of information would comprise the connection strings required by a consumer, which are needed to connect to a service offered by that provider. For example, an Oracle connection string could contain the following information:

• IP addresses: 1.1.1.1, 2.2.2.2

Port: 1521SID: abcd

A consumer is aware of at least one connection string for a provider, and this connection string is found in a known location, such as a configuration document, a database table, Windows registry, and so on. By searching through these locations, dependencies between consumers and providers can be discovered.

If the connection strings of a provider are found in a certain configuration document, then the provider and the container of the configuration document are connected with a consumer-provider relationship.

The process of discovering consumer-provider dependencies then becomes straightforward: Connection strings from the provider are searched for in the consumer's configuration documents, and the search results contain all configuration documents owned by the consumers of the specified provider.

Service Connection Point

A service connection point (SCP) is a provider descriptor, which is configured in the consumer. The SCP is used to discover the provider from the consumer and to map dependency between them.

An SCP saves the following information from the connection string:

- Service connection type: the provider type or protocol to connect the provider (required).
- Service host name: the host name of the provider (optional if the service IP address is specified).
 The service host name should be able to be resolved into an IP address.
- Service IP address: the IP address of the provider (required, can be resolved from the service host name).
- Service port: the listening port of the provider (required). A default port will be assigned according to the connection type. For example: 80 for HTTP, 443 for HTTPS, and 1521 for Oracle.
- Service context: the context defined in the connection string. Service context varies in different connection type. For example, service context can be the web context of HTTP or HTTPS connection, the schema name or SID of a database, or the JNDI name of an EJB reference.

SCPs can be generated from configuration signatures or TCP connection snapshots. For more information, see "Configuration Signatures" below.

Configuration Signatures

A different search term can be used for each configuration and provider type. These search terms are defined in a configuration signature file.

A configuration signature is a rule that defines how to find connection strings of providers from process command line, system environment variables, or configuration documents, and how to generate service connection points from the connection strings.

For more information, see "Configuration Signature Files" on page 84.

Dependency Mapping Flow

This section provides a brief overview of the basic flow that occurs during dependency mapping:

- 1. The first service connection point (SCP) is generated from the service entry URL of the business element.
- Each service connection point triggers a new discovery job against the host and listening port if their owner has direct or indirect consumer-provider relationship with the business element in the scope.
- 3. A running software instance and its deployable components are discovered. Their SCPs are also generated.

At this step, the process first uses configuration signatures to discover the running software, and then uses TCP connection if configuration signatures are unsuccessful. The process no longer uses TCP connection if configuration signatures succeed.


4. The dependency job queries all discovered running software CIs against the IP address, listening port, and service context in the SCPs generated in the previous step.

If one's (provider) IP address, listening port, and service context match the corresponding data in the other's (consumer) SCP, the consumer-provider relationship is created between the two running software CIs (or deployable components).

Note: The dependency mapping process also creates the containment relationship between business element and its immediate next-hop.

5. Repeat from step 2 to discover the next hop.

The following diagram illustrates the dependency mapping flow and shows how the topology map is updated during the process.



Configuration Signature Files

This chapter introduces the content and structure of the configuration signature files.

Structure of a Configuration Signature File

The configuration signature file defines rules to find provider's connection string in consumer's configurations. You can find the configuration signature file at **UCMDB UI > Data Flow Management**

> Adapter Management > Packages > ASM_Enhanced > Configuration Files > ConfigurationFileSignature.xml.

The following example shows the content and structure of the configuration signature file:

```
<ConfigurationFileSignature>
    <Application name="application1">
        <PropertyFile name="properties file name">
        </PropertyFile>
        <Output>
            <SCP type="ucmdb" host="${hostname}" port="${port}"/>
        </Output>
    </Application>
    <Application cit="application2">
        <CommandLine>
       </CommandLine>
        <Output>
            <SCP type="${db.type}" host="${db.host}" context="${db.name}"/>
        </Output>
    </Application>
</ConfigurationFileSignature>
```

Rules can be grouped by running software name, product name, or CI Type. Each kind of running software is defined as an <Application> element, and each <Application> element may contain one or more configuration search methods and one <Output> element. The <Output> element defines how to generate service end points from connection strings.

The ConfigurationFileSignature.xsd file can help you understand the syntax of the configuration signature file. This file locates in the same folder as the ConfigurationFileSignature.xml file.

The dependency job can search connection strings from command line or from the configuration documents in the file system. For more information, see the following chapters:

- "Search Connection Strings" on page 88
- "Search Connection Strings" on page 88

Variables

Variables are used to generate service connection points. They can save connection strings from difference sources. Variables can also help to find connections strings in configuration documents if their names or locations are configurable.

Declaration

Variables do not need to be declared first. Except predefined variables, other variables are defined at the first time they are assigned a value.

Naming

Variable names are case-sensitive. A variable name can be a string of any length that contains English letters, digits, underscore (_), or dot (.).

Value

A variable can contain multiple values. Each variable value must be a string value. When a variable is assigned with more than one value, the values are saved as an ordered list.

Predefined variables

Some variables are predefined to help with searching connection strings in command line or file system:

- scp.type: The connection type or protocol of the trigger service connection point.
- scp.ip: The IP address of the trigger service connection point.
- scp.port: The listening port of the trigger service connection point.
- scp.context: The context of the trigger service connection point.
- process.name: A list of process names of discovering running software.
- process.path: A list of process paths of discovering running software.
- process.<process name>.path: A list of process paths with specified name of discovering running software. For example, variable process.tomcat.path saves the paths of all Tomcat processes belong to current discovering running software.

Note: All process names are saved in lower case. On Windows, the ".exe" file extension for executable files is not needed.

Use

A variable can be used in a file name, file path, file content, property key, XPath, or regular expression. The syntax to use a variable is \${<Variable name>}. For example, part of the connection string might

be the IP address(es) of the provider. To save the IP address(es) in the configuration document, you can define a variable named IP_ADDRESS and use it in the expression in this way: \${IP_ADDRESS}.

Note: Variables that are used but are not assigned will be ignored or be treated as empty strings. Such a variable may cause an error during the discovery.

Scope

The scope of all variables are inside an <Application> element.

Group

Variables defined in the same element are grouped. For example, some variables are defined as the example below:

In this example, variable name and value are grouped. Variable oracle_home and tns_home are standalone variables.

When variables of the same group have more than one values, and the variables are used in the same element, they share the same iterator. Variables that are not in the same group use different iterators when the expression is being resolved.

For example, the following expression uses two variables (path and file) to express the full path, and each variable has multiple values.

```
<Path>${path}/${filename}</Path>
```

If the two variables are in the same variable group, this expression will be resolved to a string list as follows:

```
<path1>/<filename1>, <path2>/<filename2>, <path3>/<filename3> ...
```

If the two variables are not in the same variable group, this expression will be resolved to the following:

```
<path1>/<filename1>, <path1>/<filename2>, <path1>/<filename3> ... <path2>/<filename1>, <path2>/<filename2>, <path2>/<filename3> ... <path3>/<filename1>, <path3>/<filename2>, <path3>/<filename3> ... <path3> ... <path3>/<filename3> ... <path3> ...
```

Note: A grouped variable should have the same number of values as the other variables in the same variable group. The only exception is that the variable has only one value.

Assignment

Configuration signature supports several different ways to assign one or more values to a variable:

- Get value from the system environment variable: <SystemVariable>.
- Get values from an XML file by using XPath expression: <XPath> or <XPathVariable>.
- Get values from a string by using regular expression: <Regex>. Can be embedded in other sources
 of variables.

Default Values

Variables can have default values. When the specified value is not found for a variable, the default value will be assigned. If the default value is not defined in this case, the signature processor ignores all ungrouped variables and assigns an empty string to grouped variables to make the lengths of their value lists consistent.

Note: For embedded variables, if their parent does not match its condition or has no result, the whole block of variables will be ignored and the default value will not be assigned.

Search Connection Strings

Each application can have multiple rules for searching connection strings. There is no restriction on the sequence of the rules. The rules are processed in the order as they appear in the configuration signature file. Variables defined in rules can be reused or be assigned with more values in all remaining rules in the same application.

Search connection strings from command line

The following example shows a sample configuration signature used to search connection strings from command line.

```
<CommandLine>
<Regex expr="\s*(\S+)=\s*(\S+).*">
```

In this example, the <CommandLine> element is used to define rules to search connection strings from command lines or system variables. It can contain the following elements:

- <Regex>: extract connection strings by using a regular expression.
- <SystemVariable>: get values from the system environment variables.
- <Execute>: execute a shell command on the remote machine, and then use a regular expression to get connection strings.

Search connection strings from configuration documents

The following example demonstrates the content of a configuration signature file used to search connection strings from configuration documents.

To search connection strings from configuration documents, configuration signature uses several elements to define rules:

- <TextFile>: get strings from a generic text configuration document.
- <PropertyFile>: get strings from a property file by using specified property key.

- <XmlFile>: get strings from an XML-format configuration document.
- <CustomFile>: get strings from a file by using a custom script.

Each of these "File" elements requires a file name, which can use variables. When the collect attribute is set to true (which is by default false), the file will be reported to UCMDB as a ConfigurationDocument CI with file name, full path, and file content. It is useful for troubleshooting. The first child element of a "File" element should be either <FileLocations> or <FileContent>.

<FileLocations>

The <FileLocations> element can contain one or more file paths, which indicate the full paths to search the specified configuration documents. The <FileLocations> element supports the use of wildcard variables with multiple values for file names or file paths, and the processor will try to find all resolved paths and file names in the destination file system.

The <Path> element can use the os attribute as the <CommandLine> element to filter result by operation system. Another optional attribute of the <Path> element is includeSub. When this attribute is set to true, the processor will search the specified file in the specified path and all subdirectories.

In the above example, if the filename and pluginPath variables are not in the same variable group and both variables have two saved values, and the destination operation system is Windows. The processor will try to search following configuration documents:

```
<pluginPath1>/<filename1>*.loc
<pluginPath2>/<filename2>*.loc
<pluginPath1>/<filename2>*.loc
<pluginPath2>/<filename1>*.loc
C:\Windows\System*\<filename1>*.loc
C:\Windows\System*\<filename1>*.loc
```

If the two variables are grouped and the destination operation system is not Windows, only the first two paths will be searched.

<FileContent>

Unlike the <FileLocations> element, the <FileContent> element does not read the configuration document from file system. Instead, it directly specifies the content to be search for by using expressions. In this case, wildcard is not allowed in the file name attribute. Usually, the <FileContent> element is used when the result of the shell command defined in an <Execute> element is a property or XML file.

<TextFile>

The <TextFile> element is a basic "File" element. You can use this element to parse any type of configuration document. This element only supports the <Regex> sub element to get connection strings by using a regular expression, as shown in the following example:

```
<TextFile name="text file">
    <FileLocations> or <FileContent>
    <Regex expr='(.*)\plugin-cfg.xml'>
         <Variable name="pluginHome" group="1"/>
         </Regex>
</TextFile>
```

<PropertyFile>

The <PropertyFile> element is used to parse property files, which save configuration in the "<key>=<value>" format. This element supports three types of sub elements:

- <Property>: get strings from a specified key, and then use the embedded Regex element to get values.
- <PropertyVariable>: directly assign the value for specified key to a variable.
- <Regex>: regular expressions are also supported for a property file.

The following example demonstrates the content of the <PropertyFile> element:

<XmlFile>

The <XmlFile> element is used to parse an XML-format configuration documents. This element

supports XPath 2.0 expressions and regular expressions by using the following sub elements respectively:

- <XPath>: get XML element by XPath, and then use relative XPath and regular expressions to get values.
- <XPathVariable>: directly assign the value of an XPath expression to a variable.

The following example demonstrates the content of the <XmlFile> element:

<CustomFile>

The <CustomFile> element is used to parse those non-standard configuration documents (such as httpd.conf of Apache) by using Jython script.

The following example demonstrates the content of the <CustomFile> element:

```
<CustomFile name="httpd.conf" plugin="config_parser_apache">
     <FileLocations>
          <Path>${home}/conf/</Path>
          <Path>${home}/httpd/conf/</Path>
          </FileLocations>
</CustomFile>
```

The plugin attribute specifies the Jython script name. The file extension .py can be omitted. The script should be deployed as a normal job scripts under the **discoveryScripts** folder of a package. The script should define a method as follows:

```
def parseConfigFile(shell, configFilePath, configFileName, fileContent,
    variableResolver)
```

Parameters

- shell: the shell utility instance, which can execute commands by remote shell. It has the following methods:
 - execCmd(cmdLine): execute command line by shell, and returns its result.
 - get0sType(): get the operation system type.
 - isWinOs(): check if the destination operation system is Windows.
 - getOsVersion(): get the version of the operation system.
 - getOsLanguage(): get the language of the operation system.
 - getCommandSeparator(): get the command line separator of the operation system.

For more information, see the content of shellUtils.py, which is available under UCMDB UI > Data Flow Management > Adapter Management > Packages > AutoDiscoveryContent > Scripts.

- configFilePath: the full path of the configuration document to parse.
- configFileName: the file name of the configuration document.
- fileContent: the full content of the configuration file as string.
- variableResolver: the variable utility instance, which is used to assign value to variables and get values from existing variables. It has the following methods:
 - add(name, value): add the value to the variable with the specified name.
 - addGroup(names, values): add values to the variables with the specified names as a variable group. Names and values should be iterable and should have the same length.
 - get(name): get the values of the variable with the given name. Always returns the result as a list. If the variable is not defined, the method will return an empty list.

Generate Service Connection Points

Each <Application> element must contain one <Output> vector to generate connection string points for the discovering running software. The following example demonstrates the content of the <Output> element:

```
<Output>
    <SCP type="${client_protocol}" host="${client_host}" />
    <SCP type="sqlserver" host="${sqlserver_host}" port="${sqlserver_port}"</pre>
```

The <0utput> element can have one or more <SCP> elements. Each <SCP> element defines a set of service connection points by collected connection strings or predefined string constant. <SCP> has four attributes:

- type: the service connection type (required).
- host: the host name or destination IP address of the service connection point (required). Host names will be resolved to IP addresses by the remote shell.
- port: the port number of the service connection point (optional for predefined service connection type, but required for custom connection types). A default port number will be assigned according to its connection type if predefined. For example, 80 for HTTP, 443 for HTTPS, 1521 for Oracle, and 1433 for Microsoft SQL Server (which is defined as the sqlserver type).
- context: the context of the service connection point (optional).

The whole service connection point set will be ignored if any required attribute has no value.

Predefined Service Connection Type and their default port numbers:

Service Connection Type	Default Port Number
http	80
https	443
oracle	1521
sqlserver	1433
postgres	5432
db2	50000
websphere	9080
oam	5575

Service Connection Type	Default Port Number
isapi	8009
mq	1414

Chapter 5: Developing Generic Database Adapters

This chapter includes:

Generic Database Adapter Overview	97
TQL Queries for the Generic Database Adapter	97
Reconciliation	98
Hibernate as JPA Provider	99
Prepare for Adapter Creation	101
Prepare the Adapter Package	105
Configure the Adapter – Minimal Method	108
Configure the Adapter – Advanced Method	113
Implement a Plug-in	117
Deploy the Adapter	120
Edit the Adapter	121
Create an Integration Point	121
Create a View	121
Calculate the Results	121
View the Results	122
View Reports	122
Enable Log Files	122
Use Eclipse to Map Between CIT Attributes and Database Tables	122
Adapter Configuration Files	130
Out-of-the-Box Converters	158
Plug-ins	163
Configuration Examples	164
Adapter Log Files	172

External References		
Troubleshooting and Limitations – Developing Generic Database Adapters	.175	

Generic Database Adapter Overview

The purpose of the generic database adapter platform is to create adapters that can integrate with relational database management systems (RDBMS) and run TQL queries and population jobs against the database. The RDBMS supported by the generic database adapter are Oracle, Microsoft SQL Server, and MySQL.

This version of the database adapter implementation is based on a JPA (Java Persistence API) standard with the Hibernate ORM library as the persistence provider.


TQL Queries for the Generic Database Adapter

For population jobs, every required layout of a CI must be checked in the Layout Settings Dialog Box in the Modeling Studio. For details, see Query Node/Relationship Properties Dialog Box in the *HPE Universal CMDB Modeling Guide*. It is important to note that a CI might require an attribute to be identified, and without those attributes the CI will fail to be added to UCMDB.

The following limitations exist on the TQL queries calculated by the Generic Database Adapter only:


- · subgraphs are not supported
- · compound relationships are not supported
- cycles or cycle parts are not supported

The following TQL query is an example of a cycle:



· Function layout is not supported.

- 0..0 cardinality is not supported.
- The Join relationship is not supported.
- Qualifier conditions are not supported.
- To connect between two CIs, a relationship in the form of a table or foreign key must exist in the
 external database source.



Reconciliation

Reconciliation is carried out as part of the TQL calculation on the adapter side. For reconciliation to occur, the CMDB side is mapped to a federated entity called reconciliation CIT.

Mapping. Each attribute in the CMDB is mapped to a column in the data source.

Although mapping is done directly, transformation functions on the mapping data are also supported. You can add new functions through the Java code (for example, lowercase, uppercase). The purpose of these functions is to enable value conversions (values that are stored in the CMDB in one format and in the federated database in another format).

Note:

- To connect the CMDB and external database source, an appropriate association must exist in the database. For details, see "Prerequisites" on page 101.
- · Reconciliation with the CMDB ID is also supported
- Reconciliation with the Global ID is also supported.

Hibernate as JPA Provider

Hibernate is an object-relational (OR) mapping tool, which enables mapping Java classes to tables over several types of relational databases (for example, Oracle and Microsoft SQL Server). For details, see "Functional Limitations" on page 175.

In an elementary mapping, each Java class is mapped to a single table. More advanced mapping enables inheritance mapping (as can occur in the CMDB database).

Other supported features include mapping a class to several tables, support for collections, and associations of types one-to-one, one-to-many, and many-to-one. For details, see "Associations" on the next page below.

For our purposes, there is no need to create Java classes. The mapping is defined from the CMDB class model CITs to the database tables.

This section also includes the following topics:

- "Examples of Object-Relational Mapping" below
- · "Associations" on the next page
- "Usability" on page 101

Examples of Object-Relational Mapping


The following examples describe object-relational mapping:

Example of One CMDB Class Mapped to One Database Table:

Class M1, with attributes A1, A2, and A3, is mapped to table 1 columns c1, c2, and c3. This means that any M1 instance has a matching row in table 1.




Example of One CMDB Class Mapped to Two Database Tables:




Example of Inheritance:

This case is used in the CMDB, where each class has its own database table.



Example of Single Table Inheritance with Discriminator:

An entire hierarchy of classes is mapped to a single database table, whose columns comprise a super-set of all attributes of the mapped classes. The table also contains an additional column (Discriminator), whose value indicates which specific class should be mapped to this entry.



Associations

There are three types of associations: one-to-many, many-to-one and many-to-many. To connect between the different database objects, one of these associations must be defined by using a foreign

key column (for the one-to-many case) or a mapping table (for the many-to-many case).

Usability

As the JPA schema is very extensive, a streamlined XML file is provided to make it easier to define associations.

The use case for using this XML file is as follows: Federated data is modeled into one federated class. This class has many-to-one relations to a non-federated CMDB class. In addition, there is only one possible relation type between the federated class and the non-federated class.

Prepare for Adapter Creation

This task describes the preparations that are necessary for creating an adapter.

Note: You can view samples for the Generic DB adapter in the UCMDB API. Specifically, the DDMi Adapter sample contains a complicated **orm.xml** file, as well as the implementations for some plug-in interfaces.

This task includes the following steps:

- "Prerequisites" below
- "Create a CI Type" on page 103
- "Create a Relationship" on page 103

1. Prerequisites

To validate that you can use the database adapter with your database, check the following:

• The reconciliation classes and their attributes (also known as multinodes) exist in the database. For example, if the reconciliation is run by node name, verify that there is a table that contains a column with node names. If the reconciliation is run according to node cmdb_id, verify that there is a column with CMDB IDs that matches the CMDB IDs of the nodes in the CMDB. For details on reconciliation, see "Reconciliation" on page 98.

ID NAME		IP_ADDRESS
31	BABA	16.59.33.60
33	ext3.devlab.ad	16.59.59.116

ID	NAME	IP_ADDRESS
46	LABM1MAM15	16.59.58.188
72	cert-3-j2ee	16.59.57.100
102	labm1sun03.devlab.ad	16.59.58.45
114	LABM2PCOE73	16.59.66.79
116	CUT	16.59.41.214
117	labm1hp4.devlab.ad	16.59.60.182

To correlate two CITs with a relationship, there must be correlation data between the CIT tables. The correlation can be either by a foreign key column or by a mapping table. For example, to correlate between node and ticket, there must be a column in the ticket table that contains the node ID, a column in the node table with the ticket ID that is connected to it, or a mapping table whose end1 is the node ID and end2 is the ticket ID. For details on correlation data, see "Hibernate as JPA Provider" on page 99.

The following table shows the foreign key NODE_ID column:

NODE_ ID	CARD_ ID	CARD_TYPE	CARD_NAME
2015	1	Serial Bus Controller	Intel 82801EB USB Universal Host Controller
3581	2	System	Intel 631xESB/6321ESB/3100 Chipset LPC
3581	3	Display	ATI ES1000
3581	4	Base System Peripheral	HP ProLiant iLO 2 Legacy Support Function

 Each CIT can be mapped to one or more tables. To map one CIT to more than one table, check that there is a primary table whose primary key exists in the other tables, and is a unique value column.

For example, a ticket is mapped to two tables: ticket1 and ticket2. The first table has columns c1 and c2 and the second table has columns c3 and c4. To enable them to be

considered as one table, both must have the same primary key. Alternatively, the first table primary key can be a column in the second table.

In the following example, the tables share the same primary key called CARD_ID:

CARD_ID	CARD_TYPE	CARD_NAME		
1	Serial Bus Controller	Intel 82801EB USB Universal Host Controller		
2	System	Intel 631xESB/6321ESB/3100 Chipset LPC		
3	Display	ATI ES1000		
4	Base System Peripheral	HP ProLiant iLO 2 Legacy Support Function		

CARD_ID	CARD_VENDOR
1	Hewlett-Packard Company
2	(Standard USB Host Controller)
3	Hewlett-Packard Company
4	(Standard system devices)
5	Hewlett-Packard Company

2. Create a CI Type


In this step you create a CIT that represents the data in the RDBMS (the external data source).

- a. In UCMDB, access the CI Type Manager and create a new CI Type. For details, see How to Create a CI Type in the *HPE Universal CMDB Modeling Guide*.
- Add the necessary attributes to the CIT, such as last access time, vendor, and so on. These
 are the attributes that the adapter will retrieve from the external data source and bring into
 CMDB views.


3. Create a Relationship


In this step you add a relationship between the UCMDB CIT and the new CIT that represents the data from the external data source.

Add appropriate, valid relationships to the new CIT. For details, see Add/Remove Relationship Dialog Box in the *HPE Universal CMDB Modeling Guide*.



Note: At this stage, you cannot yet view the federated data or populate the external data, as you have not yet defined the method for bringing in the data.





Prepare the Adapter Package

In this step, you locate and configure the Generic DB adapter package.

- Locate the db-adapter.zip package in the C:\hp\UCMDB\UCMDBServer\content\adapters
 folder.
- Extract the package to a local temporary directory.
- 3. Edit the adapter XML file:
 - Open the discoveryPatterns\db_adapter.xml file in a text editor.
 - Locate the **adapter id** attribute and replace the name:

If the adapter supports population, the following capability should be added to the **<adapter-capabilities>** element:

```
<support-replicatioin-data>
```

The display label or ID appears in the list of adapters in the Integration Point pane in Universal CMDB.

When creating a Generic DB Adapter it is not necessary to edit the **changes-source** tag in the **support-replicatioin-data** tag. If the **FcmdbPluginForSyncGetChangesTopology** plug-in is implemented, the changed topology from the last run will be returned. If the plug-in is not implemented, the full topology will be returned and the auto-delete will be performed according to the returned CIs.

For details about populating the CMDB with data, see "Integration Studio Page" in the *HPE Universal CMDB Data Flow Management Guide*.

 If the adapter is using the mapping engine from version 8.x (meaning that it is not using the new reconciliation mapping engine), replace the following element:

```
<default-mapping-engine>
with:

<default-mapping-engine>com.hp.ucmdb.federation.
mappingEngine.AdapterMappingEngine</default-mapping-engine>
```

To revert to the new mapping engine, return the element to the following value:

```
<default-mapping-engine>
```

Locate the category definition:

```
<category>Generic</category>
```

Change the **Generic** category name to the category of your choice.

Note: Adapters whose categories are specified as **Generic** are not listed in the Integration Studio when you create a new integration point.

 The connection to the database can be described using a user name (schema), password, database type, database host machine name, and database name or SID.

For this type of connection, parameters have the following elements in the **parameter** section of the adapter's XML file:

```
<parameters>
```

```
<!--The description attribute may be written in simple text or HTML.-
->
    <!--The host attribute is treated as a special case by UCMDB-->
    <!--and will automatically select the probe name (if possible)-->
    <!--according to this attribute's value.-->
    <!--Display name and description may be overwritten by I18N values-->
        <parameter name="host" display-name="Hostname/IP" type="string"</pre>
description="The host name or IP address of the remote machine"
mandatory="false" order-index="10" />
        <parameter name="port" display-name="Port" type="integer"</pre>
description="The remote machine's connection port" mandatory="false"
order-index="11" />
        <parameter name="dbtype" display-name="DB Type" type="string"</pre>
description="The type of database" valid-
values="Oracle; SQLServer; MySQL; BO" mandatory="false" order-
index="13">Oracle</parameter>
        <parameter name="dbname" display-name="DB Name/SID" type="string"</pre>
description="The name of the database or its SID (in case of Oracle)"
mandatory="false" order-index="13" />
        <parameter name="credentialsId" display-name="Credentials ID"</pre>
type="integer" description="The credentials to be used" mandatory="true"
order-index="12" />
</parameters>
```

Note: This is the default configuration. Therefore, the **db_adapter.xml** file already contains this definition.

There are situations in which the connection to the database cannot be configured in this way. For example, connecting to Oracle RAC or connecting using a database driver other than the one supplied with the CMDB.

For these situations, you can describe the connection using user name (schema), password, and a connection URL string.

To define this, edit the adapter's XML parameters section as follows:

```
order-index="12" />
</parameters>
```

An example of a URL that connects to an Oracle RAC using the out-of-the- box Data Direct driver is:

jdbc:mercury:oracle://labm3amdb17:1521;ServiceName=RACQA;AlternateServers= (labm3amdb18:1521);LoadBalancing=true.

- 4. In the temporary directory, open the **adapterCode** folder and rename **GenericDBAdapter** to the value of **adapter id** that was used in the previous step.
 - This folder contains the adapter's configuration, for example, the adapter name, the queries and classes in the CMDB, and the fields in the RDBMS that the adapter supports.
- Configure the adapter as required. For details, see "Configure the Adapter Minimal Method" below.
- 6. Create a *.zip file with the same name as you gave to the **adapter id** attribute, as described in the step "Edit the adapter XML file:" on page 105.

Note: The descriptor.xml file is a default file that exists in every package.

7. Save the new package that you created in the previous step. The default directory for adapters is: C:\hp\UCMDB\UCMDBServer\content\adapters.

Configure the Adapter – Minimal Method

The simplified (minimal) method is a method for creating the **simplifiedConfiguration.xml** mapping file that is used by the adapter. This method enables a basic population or federation of a single CIT.

The instructions provided in this section describes a method of mapping the class model for certain CI Types in the CMDB to an RDBMS.

All of the configuration files mentioned in this section are located in the **db-adapter.zip** package in the **C:\hp\UCMDB\UCMDBServer\content\adapters** folder that you extracted in "Prepare the Adapter Package" on page 105.

Note: The **orm.xml** file that is automatically generated as a result of running this method is a good example that you can use when working with the advanced method.

You would use this minimal method when you need to:

- Federate/populate a single node such as a node attribute.
- Demonstrate the Generic Database Adapter capabilities.

This method:

- Supports one-node federation/population only
- · Supports many-to-one virtual relationships only

Configure the adapter.conf File

To change the settings in the adapter.conf file so that the adapter uses the simplified configuration method:

- 1. Open the adapter.conf file in a text editor.
- 2. Locate the following line: use.simplified.xml.config=<true/false>.
- 3. Change it to use.simplified.xml.config=true.

Example: Populating a Node and IP Address using the Simplified Method

This example demonstrates populating a **Node** related by a containment link to **IP Address** into UCMDB. The RDBMS has a table named **simpleNode** that contains data on the computer name, computer node, and the IP address of the computer.

The content of the **simpleNode** table is shown below:

	host_id	host_name	note	ip_address
	1	Comp1	Test Computer 1	12.33.211.52
	2	Comp2	Test Computer 2	12.33.211.53
	3	Comp3	Test Computer 3	12.33.211.54
.0	4	Comp4	Test Computer 4	12.33.211.55

The population is performed in three stages, as follows:

- 1. "Create the simplifiedConfiguration.xml" on the next page
- 2. "Create the TQL" on page 111
- 3. "Create an Integration Point" on page 112

Create the simplifiedConfiguration.xml

Create the simplifiedConfiguration.xml as follows:

1. Create a cmdb-class entity as follows:

```
<cmdb-class cmdb-class-name="node" default-table-name="simpleNode">
```

The CI Type is **node** and the RDBMS table name is **simpleNode**.

2. Set the primary-key of the table as follows:

```
<primary-key column-name="host_id"/>
```

This primary key is equivalent to entity id in the **orm.xml** file.

3. Set the **reconciliation-by-two-nodes** rule as follows:

```
<reconciliation-by-two-nodes connected-node-cmdb-class-name="ip_address" cmdb-
link-type="containment">
```

This tag defines the relation between the **Node** and the **IpAddress** CI types. The relation type is Containment link. The reconciliation is done by the two connected CI Types. The attribute mapping of the connected node (in this case IpAddress) is defined in the **connected-node** attribute.

4. Add the **or** condition between the reconciliation attributes as follows:

```
<or is-ordered="true">
```

This tag defines an OR relationship between the reconciliation attributes, meaning the first reconciliation attribute that is **true** sets the whole reconciliation rule to **true**.

5. Add the following attributes:

```
<attribute cmdb-attribute-name="name" column-name="host_name" ignore-case="true"/>
```

This tag sets a mapping between the **node.name** in the UCMDB to the column **host_name** in the **simpleNode** table.

Do the same with **data_note** attribute:

```
<attribute cmdb-attribute-name="data_note" column-name="note" ignore-
    case="true"/>
```

Add the connected node attribute:

```
<connected-node-attribute cmdb-attribute-name="name" column-name="ip_address"/>
```

This tag sets a mapping between the **ip_address.name** to the column **ip_address** in the **simpleNode** table.

6. Close the opened tag by order:


```
</or>
</reconciliation-by-two-nodes>
</cmdb-class>
```

The contents of the simplifiedConfiguration.xml file now appear as follows:

```
<?xml version="1.0" encoding="UTF-8"?>
<generic-db-adapter-config xmlns:xsi="http://www.w3.org/2001/</pre>
XMLSchema-instance" xsi:noNamespaceSchemaLocation="../META-
CONF/simplifiedConfiguration.xsd">
   <cmdb-class cmdb-class-name="node" default-table-name="simpleNode">
       <primary-key column-name="host id"/>
   <reconciliation-by-two-nodes connected-node-cmdb-class-name="ip_address" cmdb-</pre>
link-type="containment">
       <or is-ordered="true">
       <attribute cmdb-attribute-name="name" column-name="host_name" ignore-</pre>
case="true"/>
       <attribute cmdb-attribute-name="data_note" column-name="note" ignore-</pre>
case="true"/>
          <connected-node-attribute cmdb-attribute-name="name" column-name="ip_</pre>
address"/>
       </reconciliation-by-two-nodes>
   </cmdb-class>
</generic-db-adapter-config>
```

Create the TQL

The TQL is a **node** connected by a containment link to **ip_address**. The node should be marked as **root**, as shown below.



To create the TQL:

- 1. Go to Modeling > Modeling Studio.
- 2. Click the **New** button and create a new query.
- 3. Go to the CI Types tab and drag the Node CI Type and IpAddress CI Type to the TQL screen.
- 4. Connect **Node** and **IpAddress** with a Containment relationship.
- 5. Right-click on the **Node** element and choose Query Node Properties.
- 6. Change **Element name** to **Root**.
- Go to the Element Layout tab. Select Specific Attributes as the Attributes condition. Choose Name and Note from the Available Attributes window and move them to the Specific Attributes window.
- 8. Right-click on the **IpAddress** element and choose Query Node Properties.
- 9. Go to the **Element Layout** tab. Select **Specific Attributes** as the Attributes condition. Choose **Name** from the Available Attributes window and move it to the Specific Attributes window.
- 10. Save the TQL.

Create an Integration Point

Create the Integration Point as follows:

- Go to Data Flow Management > Integration Studio, and click the New Integration Point button.
- 2. Insert the details of the Integration Point and click **OK**.
- 3. In the Population tab, select the **New Integration Job** button, and add the TQL previously created.
- 4. Save the Integration Point and click the **Run Full Synchronization** button.

Configure the Adapter – Advanced Method

These configuration files are located in the **db-adapter.zip** package in the **C:\hp\UCMDB\UCMDBServer\content\adapters** folder that you extracted when preparing the adapter package. For details, see "Prepare the Adapter Package" on page 105.

This task includes the following steps:

- "Configure the orm.xml File" below
- "Configure the reconciliation_rules.txt File " on page 117

Configure the orm.xml File

In this step, you map the CITs and relationships in the CMDB to the tables in the RDBMS.

1. Open the **orm.xml** file in a text editor.


This file, by default, contains a template that you use to map as many CITs and relationships as needed.

Note: Do not edit the **orm.xml** file in any version of Notepad from Microsoft Corporation. Use Notepad++, UltraEdit, or some other third-party text editor.

2. Make changes to the file according to the data entities to be mapped. For details, see the following examples.


The following types of relationships may be mapped in the **orm.xml** file:

o One to one:




The code for this type of relationship is:

o Many to one:



The code for this type of relationship is:

o Many to many:



The code for this type of relationship is:

For details about naming conventions, see "Naming Conventions" on page 140.

Example of Entity Mapping Between the Data Model and the RDBMS:

Note: Attributes that do not have to be configured are omitted from the following examples.

The class of the CMDB CIT:

```
<entity class="generic_db_adapter.node">
```

• The name of the table in the RDBMS:

• The column name of the unique identifier in the RDBMS table:

```
<column name="Device ID" />
```

• The name of the attribute in the CMDB CIT:

```
<basic name="name">
```

• The name of the table field in the external data source:

```
<column name="Device_Name" />
```

The name of the new CIT you created in "Create a CI Type" on page 103:

```
<entity class="generic_db_adapter.MyAdapter">
```

• The name of the corresponding table in the RDBMS:

- The unique identity in the RDBMS:
- The attribute name in the CMDB CIT and the name of the corresponding attribute in the RDBMS:

Example of Relationship Mapping Between the Data Model and the RDBMS:

• The class of the CMDB relationship:

```
<entity class="generic_db_adapter.node_containment_MyAdapter">
```

• The name of the RDBMS table where the relationship is performed:

• The unique ID in the RDBMS:

The relationship type and the CMDB CIT:

```
<many-to-one target-entity="node" name="end1">
```

The primary key and foreign key fields in the RDBMS:

```
<join-column updatable="false" insertable="false"
referenced-column-name="[column_name]" name="Device_ID" />
```

Configure the reconciliation_rules.txt File

In this step you define the rules by which the adapter reconciles the CMDB and the RDBMS (only if Mapping Engine is used, for backward compatibility with version 8.x):

- 1. Open META-INF\reconciliation_rules.txt in a text editor.
- 2. Make changes to the file according to the CIT you are mapping. For example, to map a node CIT, use the following expression:

```
multinode[node] ordered expression[^name]
```

Note:

- If the data in the database is case sensitive, do not delete the control character (^).
- o Check that each opening square bracket has a matching closing bracket.

For details, see "The reconciliation_rules.txt File (for backwards compatibility)" on page 150.

Implement a Plug-in

This task describes how to implement and deploy a Generic DB Adapter with plug-ins.

Note: Before writing a plug-in for an adapter, make sure you have completed all the necessary steps in "Prepare the Adapter Package" on page 105.

- 1. Option 1 Write a Java based plug-in
 - a. Copy the following jar files from the UCMDB server installation directory to your development class path:
 - Copy the db-interfaces.jar file and db-interfaces-javadoc.jar file from the tools\adapter-dev-kit\db-adapter-framework folder.
 - Copy the federation-api.jar file and federation-api-javadoc.jar file from the \tools\adapter-dev-kit\SampleAdapters\production-lib folder.

Note: More information about developing a plug-in can be found in the **db-interfaces-javadoc.jar** and **federation-api-javadoc.jar** files and in the online documentation at:

- C:\hp\UCMDB\UCMDBServer\deploy\ucmdbdocs\docs\eng\APIs\DBAdapterFramework_JavaAPI\index.html
- C:\hp\UCMDB\UCMDBServer\deploy\ucmdbdocs\docs\eng\APIs\Federation_JavaAPI\index.html
- b. Write a Java class implementing the plug-in's Java interface. The interfaces are defined in the db-interfaces.jar file. The table below specifies the interface that must be implemented for each plug-in:

Plug-in Type	Interface Name	Method
Synchronize Full Topology	FcmdbPluginForSyncGetFullTopology	getFullTopology
Synchronize Changes	FcmdbPluginForSyncGetChangesTopology	getChangesTopology
Synchronize Layout	FcmdbPluginForSyncGetLayout	getLayout
Retrieve Supported Queries	FcmdbPluginForSyncGetSupportedQueries	getSupportedQueries
Alter TQL query definition and results	FcmdbPluginGetTopologyCmdbFormat	getTopologyCmdbFormat
Alter layout request for CIs	FcmdbPluginGetCIsLayout	getCisLayout
Alter layout request for links	FcmdbPluginGetRelationsLayout	getRelationsLayout
Push Back IDs	FcmdbPluginPushBackIds	getPushBackIdsSQL

The plug-in's class must have a public default constructor. Also, all of the interfaces expose a method called initPlugin. This method is guaranteed to be called before any other method and is used to initialize the adapter with the containing adapter's environment object.

If **FcmdbPluginForSyncGetChangesTopology** is implemented, there are two different ways to report the changes:

Report the entire root topology at all times. According to this topology, the auto-delete
function finds which CIs should be removed. In this case, the auto-delete function should
be enabled by using the following:

• Report each CI instance that was removed/updated. In this case the auto-delete mechanism should be disabled by using the following:

- c. Make sure you have the Federation SDK JAR and the Generic DB Adapter JARs in your class path before compiling your Java code. The Federation SDK is the **federation_api.jar** file, which can be found in the **C:\hp\UCMDB\UCMDBServer\lib** directory.
- d. Pack your class into a jar file and put it under the adapterCode\<Your Adapter Name> folder in the adapter package, prior to deploying it.
- 2. Option 2 Write a Groovy based plug-in
 - a. Create a Groovy code file (MyPlugin.groovy) in the Adapter Management Menu, under the adapter package configuration files.
 - b. In the Groovy class, implement the appropriate interfaces. The interfaces are defined in the db-interfaces.jar file, see the table above.
- 3. The plug-ins are configured using the **plugins.txt** file, located in the **\META-INF** folder of the adapter.

The following is an example of the file from the DDMi adapter:

```
# mandatory plugin to sync full topology
[getFullTopology]
com.hp.ucmdb.adapters.ed.plugins.replication.EDReplicationPlugin
# mandatory plugin to sync changes in topology
[getChangesTopology]
com.hp.ucmdb.adapters.ed.plugins.replication.EDReplicationPlugin
```

```
# mandatory plugin to sync layout
[getLayout]
com.hp.ucmdb.adapters.ed.plugins.replication.EDReplicationPlugin
# plugin to get supported queries in sync. If not defined return all tqls
names
[getSupportedQueries]
# internal not mandatory plugin to change tql definition and tql result
[getTopologyCmdbFormat]
# internal not mandatory plugin to change layout request and CIs result
[getCisLayout]
# internal not mandatory plugin to change layout request and relations
result
[getRelationsLayout]
# internal not mandatory plugin to change action on pushBackIds
[pushBackIds]
```

Legend:

#-A comment line.

[<Adapter Type>] – Start of the definition section for a specific adapter type.

There can be an empty line under each [<Adapter Type>], meaning that there is no plug-in class associated, or the fully qualified name of your plug-in class can be listed.

4. Pack your adapter with the new jar file and the updated **plugins.xml** file. The remainder of the files in the package should be the same as in any adapter based on the Generic DB adapter.

Deploy the Adapter

- 1. In UCMDB, access the Package Manager. For details, see "Package Manager Page" in the *HPE Universal CMDB Administration Guide*.
- Click the Deploy Packages to Server (from local disk) icon and browse to your adapter package. Select the package and click Open, then click Deploy to display the package in the Package Manager.
- 3. Select your package in the list and click the **View package resources** icon to verify that the package contents are recognized by Package Manager.

Edit the Adapter

Once you have created and deployed the adapter, you can then edit it within UCMDB. For details, see "Adapter Management" in the *HPE Universal CMDB Data Flow Management Guide*.

Create an Integration Point

In this step you check that the federation is working. That is, that the connection is valid and that the XML file is valid. However, this check does not verify that the XML is mapping to the correct fields in the RDBMS.

- In UCMDB, access the Integration Studio (Data Flow Management > Integration Studio).
- 2. Create an integration point. For details, see New Integration Point/Edit Integration Point Dialog Box in the HPE Universal CMDB Data Flow Management Guide.

The Federation tab displays all CITs that can be federated using this integration point. For details, see Federation Tab in the *HPE Universal CMDB Data Flow Management Guide*.

Create a View

In this step you create a view that enables you to view instances of the CIT.

- 1. In UCMDB, access the Modeling Studio (Modeling > Modeling Studio).
- 2. Create a view. For details, see How to Create a Pattern View in the *HPE Universal CMDB Modeling Guide*.

Calculate the Results

In this step you check the results.

- 1. In UCMDB, access the Modeling Studio (Modeling > Modeling Studio).
- 2. Open a view.
- 3. Calculate results by clicking the Calculate Query Result Count button.
- 4. Click the **Preview** button to view the CIs in the view.

View the Results

In this step you view the results and debug problems in the procedure. For example, if nothing is shown in the view, check the definitions in the **orm.xml** file; remove the relationship attributes and reload the adapter.

- 1. In UCMDB, access the IT Universe Manager (Modeling > IT Universe Manager).
- 2. Select a CI. The Properties tab displays the results of the federation.

View Reports

In this step you view Topology reports. For details, see Topology Reports Overview in the *HPE Universal CMDB Modeling Guide*.

Enable Log Files

To understand the calculation flows, adapter lifecycle, and to view debug information, you can consult the log files. For details, see "Adapter Log Files" on page 172.

Use Eclipse to Map Between CIT Attributes and Database Tables

Caution: This procedure is intended for users with an advanced knowledge of content development. For any questions, contact HPE Software Support.

This task describes how to install and use the JPA plug-in, provided with the J2EE edition of Eclipse, to:

- Enable graphical mapping between CMDB class attributes and database table columns.
- Enable manual editing of the mapping file (orm.xml), while providing correctness. The correctness
 check includes a syntax check as well as verification that the class attributes and mapped
 database table columns are stated correctly.
- Enable deployment of the mapping file to the CMDB server and to view the errors, as a further correctness check.
- Define a sample query on the CMDB server and run it directly from Eclipse, to test the mapping file.

Version 1.1 of the plug-in is compatible with UCMDB version 9.01 or later and Eclipse IDE for Java EE Developers, version 1.2.2.20100217-2310 or later.

This task includes the following steps:

- "Prerequisites" below
- "Installation" below
- "Prepare the Work Environment" on the next page
- "Create an Adapter" on page 125
- "Configure the CMDB Plug-in" on page 125
- "Import the UCMDB Class Model" on page 125
- "Build the ORM File Map UCMDB Classes to Database Tables" on page 125
- "Map IDs" on page 126
- "Map Attributes" on page 126
- "Map a Valid Link" on page 127
- "Build the ORM File Use Secondary Tables" on page 127
- "Define a Secondary Table" on page 128
- "Map an Attribute to a Secondary Table" on page 128
- "Use an Existing ORM File as a Base" on page 128
- "Importing an Existing ORM File from an Adapter" on page 129
- "Check the Correctness of the orm.xml File Built-in Correctness Check" on page 129
- "Create a New Integration Point" on page 129
- "Deploy the ORM File to the CMDB" on page 129
- "Run a Sample TQL Query" on page 129

1. Prerequisites

Install the latest supported **Java Runtime Environment (JRE)** on the machine where you will run Eclipse from the following site:

http://www.oracle.com/technetwork/java/javase/downloads/index.html.

2. Installation

- a. Download and extract Eclipse IDE for Java EE Developers from http://www.eclipse.org/downloads to a local folder, for example, C:\Program Files\eclipse.
- b. Copy com.hp.plugin.import_cmdb_model_1.0.jar from
 C:\hp\UCMDB\UCMDBServer\tools\db-adapter-eclipse-plugin\bin to
 C:\Program Files\Eclipse\plugins.
- c. Launch C:\Program Files\Eclipse\eclipse.exe. If a message is displayed that the Java virtual machine is not found, launch eclipse.exe with the following command line:

"C:\Program Files\eclipse\eclipse.exe" -vm "<JRE installation folder>\bin"

3. Prepare the Work Environment

In this step, you set up the workspace, database, connections, and driver properties.

a. Extract the file workspaces_gdb.zip from C:\hp\UCMDB\
 UCMDBServer\tools\db-adapter-eclipse-plugin\workspace into C:\Documents and Settings\All Users.

Note: You must use the exact folder path. If you unzip the file to the wrong path or leave the file unzipped, the procedure will not work.

b. In Eclipse, choose **File > Switch Workspace > Other**:

If you are working with:

- SQL Server, select the following folder: C:\Documents and Settings\AII
 Users\workspace_gdb_sqlserver.
- MySQL, select the following folder: C:\Documents and Settings\AII Users\workspace_ gdb_mysql.
- Oracle, select the following folder: C:\Documents and Settings\AII Users\workspace_ gdb_oracle.
- c. Click OK.
- d. In Eclipse, display the Project Explorer view and select <Active project> > JPA Content > persistence.xml > <active project name> > orm.xml.
- e. In the Data Source Explorer view (the bottom left pane), right-click the database connection and select the **Properties** menu.
- f. In the **Properties for <Connection name>** dialog box, select **Common** and select the **Connect every time the workbench is started** check box. Select **Driver Properties** and fill in the connection properties. Click **Test Connection** and verify that the connection is

working. Click **OK**.

g. In the Data Source Explorer view, right-click the database connection and click **Connect**. A tree containing the database schemas and tables is displayed under the database connection icon.

4. Create an Adapter

Create an adapter using the guidelines in "Step 1: Create an Adapter" on page 34.

5. Configure the CMDB Plug-in

- a. In Eclipse, click **UCMDB > Settings** to open the **CMDB Settings** dialog box.
- b. If not already selected, select the newly created JPA project as the Active project.
- c. Enter the CMDB host name, for example, **localhost** or **labm1.itdep1**. There is no need to include the port number or http:// prefix in the address.
- d. Fill in the user name and password for accessing the CMDB API, usually admin/admin.
- e. Make sure that the C:\hp folder on the CMDB server is mapped as a network drive.
- f. Select the base folder of the relevant adapter under C:\hp. The base folder is the one that contains the dbAdapter.jar file and the META-INF subfolder. Its path should be C:\hp\UCMDB\UCMDBServer\runtime\fcmdb\CodeBase\<adapter name>. Verify that there is no backslash (\) at the end.

6. Import the UCMDB Class Model

In this step, you select the CITs to be mapped as JPA entities.

- a. Click UCMDB > Import CMDB Class Model to open the CI Types Selection dialog box.
- b. Select the CI types that you intend to map as JPA entities. Click **OK**. The CI types are imported as Java classes. Verify that they appear under the **src** folder of the active project.

7. Build the ORM File – Map UCMDB Classes to Database Tables

In this step, you map the Java classes (that you imported in the previous step) to the database tables.

a. Make sure the DB connection is connected. Right-click the active project (called myProject by default) in Project Explorer. Select the JPA view, select the **Override default schema** from connection check box, and select the relevant database schema. Click **OK**.

- Map a CIT: In the JPA Structure view, right-click the Entity Mappings branch and select Add
 Class. The Add Persistent Class dialog box opens. Do not change the Map as field (Entity).
- c. Click **Browse** and select the UCMDB class to be mapped (all UCMDB classes belong to the **generic_db_adapter** package).
- d. Click **OK** in both dialog boxes. The selected class is displayed under the **Entity Mappings** branch in the JPA Structure view.

Note: If the entity appears without an attribute tree, right-click the active project in the Project Explorer view. Choose **Close** and then **Open**.

e. In the JPA Details view, select the primary database table to which the UCMDB class should be mapped. Leave all other fields unchanged.

8. Map IDs

According to JPA standards, each persistent class must have at least one ID attribute. For UCMDB classes, you can map up to three attributes as IDs. Potential ID attributes are called **id1**, **id2**, and **id3**.

To map an ID attribute:

- a. Expand the corresponding class under the Entity Mappings branch in the JPA Structure view, right-click the relevant attribute (for example, id1), and select Add Attribute to XML and Map....
- b. The Add Persistent Attribute dialog box opens. Select Id in the Map as field and click OK.
- c. In the JPA Details view, select the database table column to which the ID field should be mapped.

9. Map Attributes

In this step, you map attributes to the database columns.

- a. Expand the corresponding class under the Entity Mappings branch in the JPA Structure view, right-click the relevant attribute (for example, host_hostname), and select Add Attribute to XML and Map....
- b. The **Add Persistent Attribute** dialog box opens. Select **Basic** in the **Map as** field and click **OK**.
- c. In the JPA Details view, select the database table column to which the attribute field should be mapped.

^{10.} Map a Valid Link

Perform the steps described above in the step "Build the ORM File – Map UCMDB Classes to Database Tables" on page 125 for mapping a UCMDB class denoting a valid link. The name of each such class takes the following structure: <end1 entity name>_link name>_<end 2 entity name>. For example, a Contains link between a host and a location is denoted by a Java class whose name is generic_db_adapter.host_contains_location. For details, see "The reconciliation rules.txt File (for backwards compatibility)" on page 150.

- a. Map the ID attributes of the link class as described in "Map IDs" on the previous page. For each ID attribute, expand the **Details** check box group in the JPA Details view and clear the **Insertable** and **Updateable** check boxes.
- b. Map the **end1** and **end2** attributes of the link class as follows: For each of the **end1** and **end2** attributes of the link class:
 - Expand the corresponding class under the Entity Mappings branch in the JPA Structure view, right-click the relevant attribute (for example, end1), and select Add Attribute to XML and Map....
 - In the Add Persistent Attribute dialog box, select Many to One or One to One in the Map as field.
 - Select Many to One if the specified end1 or end2 CI can have multiple links of this type.
 Otherwise, select One to One. For example, for a host_contains_ip link the host end should be mapped as Many to One, since one host can have multiple IPs, and the ip end should be mapped as One to One, since one IP can have only a single host.
 - In the JPA Details view, select Target entity, for example, generic_db_adapter.host.
 - In the Join Columns section of the JPA Details view, check Override Default. Click Edit. In the Edit Join Column dialog box, select the foreign key column of the link database table that points to an entry in the end1/end2 target entity's table. If the referenced column name in the end1/end2 target entity's table is mapped to its ID attribute, leave the Referenced Column Name unchanged. Otherwise, select the name of the column to which the foreign key column points. Clear the Insertable and Updatable check boxes and click OK.
 - If the **end1/end2** target entity has more than one ID, click the **Add** button to add additional join columns and map them in the same way as described in the previous step.

11. Build the ORM File – Use Secondary Tables

JPA enables a Java class to be mapped to more than one database table. For example, **Host** can

be mapped to the **Device** table to enable persistence of most of its attributes and to the **NetworkNames** table to enable persistence of **host_hostName**. In this case, **Device** is the primary table and **NetworkNames** is the secondary table. Any number of secondary tables can be defined. The only condition is that there must be a one-to-one relationship between the entries of the primary and secondary tables.

^{12.} Define a Secondary Table

Select the appropriate class in the JPA Structure view. In the **JPA Details** view, access the **Secondary Tables** section and click **Add**. In the **Add Secondary Table** dialog box, select the appropriate secondary table. Leave the other fields unchanged.

If the primary and the secondary table do not have the same primary keys, configure the join columns in the **Primary Key Join Columns** section of the **JPA Details** view.

^{13.} Map an Attribute to a Secondary Table

You map a class attribute to a field of a secondary table as follows:

- a. Map the attribute as described above in "Map Attributes" on page 126.
- b. In the **Column** section of the JPA Details view, select the secondary table name in the **Table** field, to replace the default value.

^{14.} Use an Existing ORM File as a Base

To use an existing **orm.xml** file as a basis for the one you are developing, perform the following steps:

- a. Verify that all CITs mapped in the existing orm.xml file are imported into the active Eclipse project.
- b. Select and copy all or part of the entity mappings from the existing file.
- c. Select the **Source** tab of the **orm.xml** file in the Eclipse JPA perspective.
- d. Paste all copied entity mappings under the <entity-mappings> tag of the edited orm.xml file, beneath the <schema> tag. Make sure that the schema tag is configured as described above in the step "Build the ORM File Map UCMDB Classes to Database Tables" on page 125. All pasted entities now appear in the JPA Structure view. From now on, mappings can be edited both graphically and manually through the xml code of the orm.xml file.
- e. Click Save.

15. Importing an Existing ORM File from an Adapter

If an adapter already exists, the Eclipse Plug-in can be used to edit its ORM file graphically. Import the **orm.xml** file into Eclipse, edit it using the plug-in and then deploy it back to the UCMDB machine. To import the ORM file, press the button on the Eclipse toolbar. A confirmation dialog is displayed. Click **OK**. The ORM file is copied from the UCMDB machine to the active Eclipse project and all relevant classes are imported from the UCMDB class model.

If the relevant classes do not appear in the JPA Structure view, right-click the active project in the Project Explorer view, choose **Close** and then **Open**.

From now on, the ORM file can be edited graphically using Eclipse, and then deployed back to the UCMDB machine as described below in "Deploy the ORM File to the CMDB" below.

16. Check the Correctness of the orm.xml File – Built-in Correctness Check

The Eclipse JPA plug-in checks if any errors are present and marks them in the **orm.xml** file. Both syntax (for example, wrong tag name, unclosed tag, missing ID) and mapping errors (for example, wrong attribute name or database table field name) are checked. If there are errors, their description appears in the **Problems** view.

17. Create a New Integration Point

If no integration point exists in the CMDB for this adapter, you can create it in the Integration Studio. For details, see Integration Studio in the *HPE Universal CMDB Data Flow Management Guide*.

Fill in the integration point name in the dialog box that opens. The **orm.xml** file is copied to the adapter folder. An integration point is created with all the imported CI types as its supported classes, except for multinode CITs, if they are configured in the **reconciliation_rules.txt** file. For details, see "The reconciliation_rules.txt File (for backwards compatibility)" on page 150.

^{18.} Deploy the ORM File to the CMDB

Save the **orm.xml** file and deploy it to the UCMDB server by clicking **UCMDB > Deploy ORM**. The **orm.xml** file is copied to the adapter folder and the adapter is reloaded. The operation result is shown in an **Operation Result** dialog box. If any error occurs during the reload process, the Java exception stack trace is displayed in the dialog box. If no integration point has yet been defined using the adapter, no mapping errors are detected upon deployment.

^{19.} Run a Sample TQL Query

- a. Define a query (not a view) in the Modeling Studio. For details, see Modeling Studio in the HPE Universal CMDB Modeling Guide.
- b. Create an integration point using the adapter that you created in the step "Create a New Integration Point" on the previous page. For details, see New Integration Point/Edit Integration Point Dialog Box in the HPE Universal CMDB Data Flow Management Guide.
- c. During the creation of the adapter, verify that the CI types that should participate in the query are supported by this integration point.
- d. When configuring the CMDB plug-in, use this sample query name in the Settings dialog box. For details, see the step above "Configure the CMDB Plug-in" on page 125.
- e. Click the **Run TWL** button to run a sample TQL and verify whether it returns the required results using the newly created **orm.xml** file.

Adapter Configuration Files

The files discussed in this section are located in the **db-adapter.zip** package in the **C:\hp\UCMDB\UCMDBServer\content\adapters** folder.

This section describes the following configuration files:

- "The adapter.conf File" on page 132
- "The simplifiedConfiguration.xml File" on page 133
- "The orm.xml File" on page 136
- "The reconciliation_types.txt File" on page 150
- "The reconciliation_rules.txt File (for backwards compatibility)" on page 150
- "The transformations.txt File" on page 152
- "The discriminator.properties File" on page 153
- "The replication_config.txt File" on page 154
- "The fixed_values.txt File" on page 154
- "The Persistence.xml File" on page 155

General Configuration

 adapter.conf. The adapter configuration file. For details, see "The adapter.conf File" on the next page.

Simple Configuration

• simplifiedConfiguration.xml. Configuration file that replaces orm.xml, transformations.txt, and reconciliation_rules.txt with less capabilities. For details, see "The simplifiedConfiguration.xml File" on page 133.

Advanced Configuration

- **orm.xml**. The object-relational mapping file in which you map between CMDB CITs and database tables. For details, see "The orm.xml File" on page 136.
- reconciliation_rules.txt. Contains the reconciliation rules. For details, see "The reconciliation_rules.txt File (for backwards compatibility)" on page 150.
- transformations.txt. Transformations file in which you specify the converters to apply to convert from the CMDB value to the database value, and vice versa. For details, see "The transformations.txt File" on page 152.
- Discriminator.properties. This file maps each supported CI type to a comma-separated list of possible corresponding values. For details, see "The discriminator.properties File" on page 153.
- Replication_config.txt. This file contains a comma-separated list of CI and relationship types
 whose property conditions are supported by the replication plug-in. For details, see "The replication_
 config.txt File" on page 154.
- **Fixed_values.txt.** This file enables you to configure fixed values for specific attributes of certain CITs. For details, see "The fixed_values.txt File" on page 154.

Hibernate Configuration

 persistence.xml. Used to override out-of-the-box Hibernate configurations. For details, see "The Persistence.xml File" on page 155.

Enabling Temporary Table Support for the Adapter

Enabling temporary tables allows the adapter to work more efficiently with the remote database, thus reducing stress on the database and network and also enhancing performance.

To enable temporary table support in General Database Adapter, the following conditions must be met:

- The credentials given to connect to the database, include permission to create, modify, and delete temporary tables.
- Configure the following settings in the adapter.conf configuration file:

temp.tables.enabled=true
performance.enable.single.sql=true

Note: Temporary tables are only supported for Microsoft SQL and Oracle.

The adapter.conf File

This file contains the following settings:

• use.simplified.xml.config=false.true: uses simplifiedConfiguration.xml.

Note: Using this file means that orm.xml, transformations.txt, and reconciliation_rules.txt are replaced with fewer capabilities.

- dal.ids.chunk.size=300. Do not change this value.
- dal.use.persistence.xml=false. true: the adapter reads the Hibernate configuration from persistence.xml.

Note: It is not recommended to override the Hibernate configuration.

- performance.memory.id.filtering=true. When the GDBA executes TQLS, in some cases a large
 number of IDs may be retrieved and sent back to the database using SQL. To avoid this excessive
 work and improve performance, the GDBA attempts to read the entire view/table and filters the
 results in-memory.
- id.reconciliation.cmdb.id.type=string/bytes. When mapping the Generic DB adapter using ID
 Reconciliation, you can either map the cmdb_id to a string or bytes/raw column type by changing
 the META-INF/ adapter.conf property.
- performance.enable.single.sql=true. This is an optional parameter. If it does not appear in the

file, its default value is **true**. When **true**, the Generic Database Adapter tries to generate a single SQL statement for each query being executed (either for population or a federated query). Using a single SQL statement improves the performance and memory consumption of the Generic Database Adapter. When **false**, the Generic Database Adapter generates multiple SQL statements, which may take longer and consume more memory than a single one. Even when this attribute is set to **true**, the adapter does not generate a single SQL statement in the following scenarios:

- The database the adapter connects to is not on an Oracle or SQL Server.
- The TQL being executed contains a cardinality condition other than 0..* and 1..* (for example, if there is a cardinality condition like 2..* or 0..2).
- in.expression.size.limit=950 (default). This parameter splits the 'IN' expression of the executed SQL, when the size limit of the list of arguments is reached.
- stringlist.delimiter.of.<CIT Name>.<Attribute Name>=<delimiter>. In order to map a string list attribute to a database column in the generic database adapter, the attribute needs to be mapped to a string column that contains a list of concatenated values. For example, to map the attribute policy_category with the CI Type policy, and the string column contains a list of values: value1##value2##value3 (that define a list of 3 values value1, value2, value3), use the setting: stringlist.delimiter.of.policy.policy category=##.
- temp.tables.enabled=true. Enables using temporary tables to improve performance. Only available when performance.enable.single.sql is enabled (only supported in Microsoft SQL and Oracle). Certain permissions in the database server may be required.
- **temp.tables.min.value=50**. Defines the number of condition values (or IDs) that are needed to use temporary tables.

The simplifiedConfiguration.xml File

This file is used for simple mapping of UCMDB classes to database tables. To access the template for editing the file, go to **Adapter Management > db-adapter > Configuration files**.

This section includes the following topics:

- "The simplifiedConfiguration.xml File Template" on the next page
- "Limitations" on page 135

The simplifiedConfiguration.xml File Template

• The **CMDB-class-name** property is the multinode type (the node to which federated CITs connect in the TQL):

- **reconciliation-by-two-nodes**. Reconciliation can be done using one node or two nodes. In this case example, reconciliation uses two nodes.
- connected-node-CMDB-class-name. The second class type needed in the reconciliation TQL.
- CMDB-link-type. The relationship type needed in the reconciliation TQL.
- link-direction. The direction of the relationship in the reconciliation TQL (from node to ip_address
 or from ip_address to node):

```
<reconciliation-by-two-nodes connected-node-CMDB-class-name="ip_address" CMDB-
link-type="containment" link-direction="main-to-connected">
```

The reconciliation expression is in the form of ORs and each OR includes ANDs.

• is-ordered. Determines if reconciliation is done in order form or by a regular OR comparison.

```
<or is-ordered="true">
```

If the reconciliation property is retrieved from the main class (the multinode), use the **attribute** tag, otherwise use the **connected-node-attribute** tag.

• **ignore-case.true**: when data in the UCMDB class model is compared with data in the RDBMS, case does not matter:

```
<attribute CMDB-attribute-name="name" column-name="[column_name]" ignore-case="true" />
```

The column name is the name of the foreign key column (the column with values that point to the multinode primary key column).

If the multinode primary key column is composed of several columns, there needs to be several foreign key columns, one for each primary key column.

```
<foreign-primary-key column-name="[column_name]" CMDB-class-primary-key-column="
[column_name]" />
```

If there are few primary key columns, duplicate this column.

```
<primary-key column-name="[column_name]"/>
```

- The from-CMDB-converter and to-CMDB-converter properties are Java classes that implement the following interfaces:
 - com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.
 FcmdbDalTransformerFromExternalDB
 - com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.
 FcmdbDalTransformerToExternalDB

Use these converters if the value in the CMDB and in the database are not the same.

In this example, GenericEnumTransformer is used to convert the enumerator according to the XML file that is written inside the parenthesis (generic-enum-transformer-example.xml):

```
<attribute CMDB-attribute-name="[CMDB_attribute_name]" column-name="[column_
name]" from-CMDB-converter="com.mercury.topaz.fcmdb.
adapters.dbAdapter.dal.transform.impl. GenericEnumTransformer
(generic-enum-transformer-example.xml)" to-CMDB-onverter="com.
mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.
GenericEnumTransformer(generic-enum-transformer-example.xml)" />
<attribute CMDB-attribute-name="[CMDB_attribute_name]" column-name="[column_
name]" />
<attribute CMDB-attribute-name="[CMDB_attribute_name]" column-name="[column_
name]" />
</class>
</generic-DB-adapter-config>
```

Limitations

- Can be used to map only TQL queries containing one node (in the database source). For example, you can run a node > ticket and a ticket TQL query. To bring the hierarchy of nodes from the database, you must use the advanced orm.xml file.
- Only one-to-many relations are supported. For example, you can bring one or more tickets on each node. You cannot bring tickets that belong to more than one node.
- You cannot connect the same class to different types of CMDB CITs. For example, if you define
 that ticket is connected to node, it cannot be connected to application as well.

The orm.xml File

This file is used for mapping CMDB CITs to database tables.

A template to use for creating a new file is located in the

C:\hp\UCMDB\UCMDBServer\runtime\fcmdb\CodeBase\GenericDBAdapter\META-INF directory.

To edit the XML file for a deployed adapter, navigate to **Adapter Management > db-adapter > Configuration files**.

This section includes the following topics:

- "The orm.xml File Template" below
- "Multiple ORM files" on page 140
- "Naming Conventions" on page 140
- "Using Inline SQL Statements Instead of Table Names" on page 140
- "The orm.xml Schema" on page 141
- "Example of Creating the orm.xml File" on page 146
- "Configuring a Specific orm.xml for each Remote Product Version" on page 149

The orm.xml File Template

Do not change the package name.

```
<package>generic_db_adapter</package>
```

entity. The CMDB CIT name. This is the multinode entity.

Make sure that **class** includes a **generic_db_adapter**. prefix.

```
<entity class="generic_db_adapter.node">
```

Use a secondary table if the entity is mapped to more than one table.

```
<secondary-table name="" />
<attributes>
```

For a single table inheritance with discriminator, use the following code:

```
<inheritance strategy="SINGLE_TABLE" />
<discriminator-value>node</discriminator-value>
<discriminator-column name="[column_name]" />
```

Attributes with tag **id** are the primary key columns. Make sure that the naming convention for these primary key columns are **idX** (id1, id2, and so on) where **X** is the column index in the primary key.

```
<id name="id1">
```

Change only the column name of the primary key.

basic. Used to declare the CMDB attributes. Make sure to edit only **name** and **column_name** properties.

For a single table inheritance with discriminator, map the extending classes as follows:

```
name]">
        <secondary-table name="" />
        <attributes>
           <id name="id1">
               <column updatable="false" insertable="false" name="[column_name]</pre>
" />
               <generated-value strategy="TABLE" />
           </id>
           <id name="id2">
               <column updatable="false" insertable="false" name="[column_name]</pre>
" />
               <generated-value strategy="TABLE" />
           </id>
           <id name="id3">
               <column updatable="false" insertable="false" name="[column_name]</pre>
" />
               <generated-value strategy="TABLE" />
           </id>
```

The following example shows a CMDB attribute name with no prefix:

This is a relationship entity. The naming convention is **end1Type_linkType_end2Type**. In this example **end1Type** is **node** and the **linkType** is **composition**.

```
<generated-value strategy="TABLE" />
</id>
```

The target entity is the entity that this property is pointing to. In this example, **end1** is mapped to **node** entity.

many-to-one. Many relationships can be connected to one node.

join-column. The column that contains end1 IDs (the target entity IDs).

referenced-column-name. The column name in the target entity (**node**) that contain the IDs that are used in the join column.

one-to-one. One relationship can be connected to one [CMDB_class_name].

node attribute. This is an example of how to add a node attribute.

```
</entity>
```

Multiple ORM files

Multiple mapping files are supported. Each mapping file name should end with **orm.xml**. All mapping files should be placed under the META-INF folder of the adapter.

Naming Conventions

- In each entity, the class property must match the name property with the prefix of generic_db_ adapter.
- Primary key columns must take names of the form idX where X = 1, 2, ..., according to the number
 of primary keys in the table.
- Attribute names must match class attribute names even as regards case.
- The relationship name takes the form end1Type_linkType_end2Type.
- CMDB CITs, which are also reserved words in Java, should be prefixed by gdba_. For example, for the CMDB CIT goto, the ORM entity should be named gdba_goto.

Using Inline SQL Statements Instead of Table Names

You can map entities to inline select clauses instead of to database tables. This is equivalent to defining a view in the database and mapping an entity to this view. For example:

In this example, the node attributes should be mapped to columns id1, name, and host_os, rather than id, name, and os.

The following limitations apply:

- The inline SQL statement is available only when using Hibernate as the JPA provider.
- Round brackets around the inline SQL select clause are mandatory.
- The <schema> element should not be present in the orm.xml file. In the case of Microsoft SQL
 Server 2005, this means that all table names should be prefixed with dbo., rather than defining them
 globally by <schema>dbo</schema>.

The orm.xml Schema

The following table explains the common elements of the **orm.xml** file. The complete schema can be found at http://java.sun.com/xml/ns/persistence/orm_1_0.xsd. The list is not complete, and it mainly explains the specific behavior of the standard Java Persistence API for the Generic Database Adapter.

Element Name and Path	Description	Attributes
entity-mappings	The root element for the entity mapping document. This element should be exactly the same as the one given in the GDBA sample files.	
description (entity- mappings)	A free text description of the entity mapping document. (Optional)	
package (entity-mappings)	The name of the Java package that will contain the mapping classes. Should always contain the text generic_db_adapter.	1. Name: name Description: The name of the UCMDB CI type to which this entity is mapped. If this is entity is mapped to a link in the CMDB, the name of the entity should be in the format <end_1>_<link_name>_<end_ 2="">. For example, node_ composition_cpu defines an entity that will be mapped to the composition link between a node and a CPU. If the name of the CI type is the same as the name of the Java class without the package prefix, this field can be omitted. Is required?: Optional Type: String 2. Name: class Description: The fully qualified</end_></link_name></end_1>

Element Name and Path	Description	Attributes
		name of the Java class that will be created for this DB entity. The name of the Java class' package should be the same as the name given in the package element. You may not use Java reserved words, such as interface or switch, as the class name. Instead, add the prefix gdba_to the name (so interface will be generic_db_adapter.gdba_interface. Is required?: Required Type: String
table (entity- mappings>entity)	This element defines the primary table of the DB entity. Can only appear once. Required.	Name: name Description: The name of the primary table. If the name of the table does not contain the schema to which it belongs, the table will be searched only in the schema of the user that was used to create the integration point. This can also be any valid SELECT statement. If this is a SELECT statement, it must be encapsulated with parentheses. Is required?: Required Type: String
secondary-table (entity-mappings > entity)	This element may be used to define a secondary table for the DB entity. This table must be connected to the primary table with a 1-to-1 relationship. You may define more than one secondary table. Optional.	Name: name Description: The name of the secondary table. If the name of the table does not contain the schema to which it belongs, the table will be searched only in the schema of the user that was used to create the integration point. This can also be any

Element Name and Path	Description	Attributes
		valid SELECT statement. If this is a SELECT statement, it must be encapsulated with parentheses. Is required?: Required Type: String
primary-key-join- column (entity-mappings > entity > secondary-table)	If the secondary table and primary table are not connected using fields with the same name, this element defines the name of the primary key field in the secondary table that needs to be connected to the primary key field of the primary table.	Name: name Description: The name of the primary key field in the secondary table. If this element does not exist, it is assumed that the primary key field has the same name as the primary key field of the primary table. Is required?: Optional Type: String
inheritance (entity-mappings > entity)	If the current entity is the parent entity for a family of DB entities, then use this element to mark it as such. Optional.	 Name: strategy Description: Defines the way the inheritance is implemented in your DB. Is required?: Required Type: One of the following values: SINGLE_TABLE: This entity and all child entities exist in the same table. JOINED: The child entities are in joined tables. TABLE_PER_CLASS: Each entity is completely defined by a separate table.
discriminator-column (entity-mappings > entity)	If the inheritance is of type SINGLE_TABLE, this element is used to define the name of the field used to determine the type of entity for each row.	Name: name Description: The name of the discriminator column. Is required?: Required Type: String

Element Name and Path	Description	Attributes
discriminator-value (entity-mappings > entity)	This element defines the type of the specific entity in the inheritance tree. This name needs to be the same as the name defined in the discriminator.properties file for the value group of this specific entity type.	
attributes (entity-mappings > entity)	The root element for all of the attribute mappings for an entity.	
id (entity-mappings > entity attributes)	This element defines the key field for the entity. There must be at least one id field defined. If more than one id element exists, its fields create a compound key for the entity. You should try and avoid compound keys for CI entities (not for links).	Name: name Description: A string of type idX, where X is a number between 1 and 9. The first id should be marked as id1, the second as id2 and so on. This is NOT the name of the key attribute in UCMDB. Is required?: Required Type: String
basic (entity-mappings > entity attributes)	This element defines a mapping between a field in the table, which is not part of the table's primary key, and a UCMDB attribute.	Name: name Description: The name of the UCMDB attribute to which the field is mapped. This attribute must exist in the UCMDB CI type to which the current entity is mapped. Is required?: Required Type: String
column (entity-mappings > entity > attributes >id -OR-	Defines the name of the column in the table for basic mapping or an id field.	 Name: name Description: The name of the field. Is required?: Required Type: String Name: table

Element Name and Path	Description	Attributes
(entity-mappings > entity > attributes > basic)		Description: The name of the table to which the field belongs. This must be either the primary table or one of the secondary tables defined for the entity. If this attribute is omitted, it is assumed that the field belongs to the primary table. Is required: Optional Type: String
one-to-one (entity-mappings > entity > attributes)	Defines a column whose value is in another table, and the two tables are connected using a one-to-one relationship. This element is only supported for link entity mappings and not for other CI types. This is the only way to define a mapping between a table and a UCMDB link.	 Name: name Description: Which of the two ends this field represents. Is required?: Required Type: Either end1 or end2 Name: target-entity Description: The name of the entity to which the end refers. Is required?: Required Type: One of the entity names defined in the entity mapping document.
join-column (entity-mappings > entity attributes > one- to-one)	Defines the way to join the target- entity defined in the parent one-to- one element and the current entity.	 Name: name Description: The name of the field in the current table that will be used to perform the one-to-one join. Is required?: Required Type: String Name: name Description: The name of a field in the joint entity by which to perform the join. If this attribute is omitted, it is assumes that the joint table has a column with the same name as the field defined in the name

Element Name and Path	Description	Attributes
		attribute. Is required?: Optional Type: String

Example of Creating the orm.xml File

The example presented here demonstrates how to create the **orm.xml file**. In this example, SQL tables in a remote database are mapped to CI types in UCMDB.

Given tables with the following format in the remote database, populate the **Hosts** table with nodes, the **IP_Addresses** table with IP Addresses, and create links between the nodes and IP Addresses as follows:

Hosts Table

host_name	host_id
Test1	1
Test2	2
Test3	3

IP_Addresses Table

ip_address	ip_id
10.1.1.1	1
10.2.2.2	2
10.3.3.2	3
10.4.4.4	4

Host_IP_Link Table (links between Nodes and IP Addresses)

host_id	ip_id
1	1

host_id	ip_id
2	2
2	3
3	4

The primary key for the **Hosts** table is the **host_id** field and the primary key in the **IP_Addresses Table** table is the **ip_id** field. In the **Host_IP_Link** table the **host_id** and the **ip_id** are foreign keys from the **Hosts Table** and **IP_Addresses Table**.

According to the tables above, create the **orm.xml** file according to the following steps. The entities used in this example are **node**, **ip_address**, and **node_containment_ip_address**

1. Create the **node** entity by mapping the **host_id** from the **Hosts** table as follows:

```
<entity-mappings xmlns="http://java.sun.com/xml/ns/persistence/orm"</pre>
        xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" version="1.0"
       xsi:schemaLocation="http://java.sun.com/xml/ns/persistence
      /orm_1_0.xsd">
    <description>test_integration</description>
    <package>generic_db_adapter</package>
    <entity class="generic_db_adapter.node">
       <attributes>
        <id name="id1">
                <column updatable="false" insertable="false" name=</pre>
                       "host id"/>
                <generated-value strategy="TABLE"/>
        </id>
        <basic name="name">
                <column updatable="false" insertable="false" name=</pre>
                       "host_name"/>
        </basic>
       </attributes>
    </entity>
```

The entity **class** must be a CI Type that already exists in UCMDB. The table **name** is the table within the database that contains both an ID and the Host information. The ID attribute is required to identify specific hosts and is used later in the mapping. In this example, the **name** attribute of this entity is populated with the **host_name** column in the hosts table.

2. For the next entity, map the IP Addresses from the Interfaces table:

 Next the link between the Node and the IP Address must be created by means of the mapping table, and reference the ip_id field (though it could reference both the host_id and ip_id fields if desired).

The entity name for the container has the format: [end1 CIT]_[link CIT]_[end2 CIT]. So for this example, since the link CI Type is **containment**, the entity name for the container is: **node_ containment_ip_address** and the entity class is **generic_db_adapter.node_containment_ip_ address**. The ID is required in this block of code, and while this example works with a single ID of the Interface, both columns could reference id1 and id2. The code for that would be:

The two ends of this link are 'many-to-one' and 'one-to-one', meaning each IP Address will be linked to 1 node, but a node may be linked to many IP Addresses. The columns included are from the Links table and reference the Hosts and Interfaces tables.

Configuring a Specific orm.xml for each Remote Product Version

It is possible to configure a specific **orm.xml** file so that the adapter uses a specific **orm.xml** for a given remote product version. For example, if the remote data store has two product versions x and y, for each version there can be a different mapping of entities.

To configure a specific orm.xml file per remote product version:

1. Add a parameter to the **adapter.xml** file called **version** and specify possible version values as **valid-values**.

- 2. In the adapter package, under the META-INF folder, create a folder called VersionOrm.
- In the VersionOrm folder, create an orm.xml file for each specific version. The filename should contain the version prefix. For example, if the version is called x, the filename should be x_ orm.xml.

Note: The **orm.xml** file in the META-INF folder is loaded for any remote product version, regardless of whether you create a specific **orm.xml** file for a remote product version. It can have entities that are mapped in the same manner for all versions.

The reconciliation_types.txt File

As of UCMDB 10.00, the **reconciliation_types.txt** file is no longer relevant. Any CIT can be used for reconciliation. The federation engine automatically executes the mapping.

The reconciliation_rules.txt File (for backwards compatibility)

This file is used to configure the reconciliation rules if you want to perform reconciliation when the DBMappingEngine is configured in the adapter. If you do not use the DBMappingEngine, the generic UCMDB reconciliation mechanism is used and there is no need to configure this file.

Each row in the file represents a rule. For example:

```
multinode[node] expression[^node.name OR ip_address.name] end1_type[node]
end2_type[ip_address] link_type[containment]
```

The multinode is filled with the multinode name (the CMDB CIT that is connected to the federated database CIT in the TQL query).

This expression includes the logic that decides whether two multinodes are equal (one multinode in the CMDB and the other in the database source).

The expression is composed of ORs or ANDs.

The convention regarding attribute names in the expression part is <code>[className].[attributeName]</code>. For example, <code>attributeName</code> in the <code>ip_address class</code> is written <code>ip_address.name</code>.

For an ordered match (if the first OR sub-expression returns an answer that the multinodes are not equal, the second OR sub-expression is not compared), use ordered expression instead of expression.

To ignore case during a comparison, use the control (^) sign.

The parameters end1_type, end2_type and link_type are used only if the reconciliation TQL query contains two nodes and not just a multinode. In this case, the reconciliation TQL query is end1_type > (link type) > end2 type.

There is no need to add the relevant layout as it is taken from the expression.

Types of Reconciliation Rules

Reconciliation rules take the form of OR and AND conditions. You can define these rules on several different nodes (for example, node is identified by name from nodeAND/ORname from ip_a address).

The following options find a match:

- Ordered match. The reconciliation expression is read from left to right. Two OR sub-expressions
 are considered equal if they have values and they are equal. Two OR sub-expressions are
 considered not equal if both have values and they are not equal. For any other case there is no
 decision, and the next OR sub-expression is tested for equality.
 - name from node OR from ip_address. If both the CMDB and the data source include name and they are equal, the nodes are considered as equal. If both have name but they are not equal, the nodes are considered not equal without testing the name of ip_address. If either the CMDB or the data source is missing name of node, the name of ip_address is checked.
- **Regular match.** If there is equality in one of the OR sub-expressions, the CMDB and the data source are considered equal.
 - **name from node OR from ip_address.** If there is no match on name of node, name of ip_address is checked for equality.

For complex reconciliations, where the reconciliation entity is modeled in the class model as several CITs with relationships (such as node), the mapping of a superset node includes all relevant attributes from all modeled CITs.


Note: As a result, there is a limitation that all reconciliation attributes in the data source should reside in tables that share the same primary key.


Another limitation states that the reconciliation TQL query should have no more than two nodes. For example, the node > ticket TQL query has a node in the CMDB and a ticket in the data source.


To reconcile the results, name must be retrieved from the node and/or ip address.

If the name in the CMDB is in the format of *.m.com, a converter can be used from CMDB to the federated database, and vice versa, to convert these values.

The node_id column in the database ticket table is used to connect between the entities (the defined association can also be made in a node table):







Note: The three tables must be part of the federated RDBMS source and not the CMDB database.

The transformations.txt File

This file contains all the converter definitions.

The format is that each line contains a new definition.

The transformations.txt File Template

```
entity[[CMDB_class_name]] attribute[[CMDB_attribute_name]] to_DB_class
[com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.
transform.impl.GenericEnumTransformer(generic-enum-transformer-example.xml)]
from_DB_class[com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.
GenericEnumTransformer(generic-enum-transformer-example.xml)]
```

entity. The entity name as it appears in the orm.xml file.

attribute. The attribute name as it appears in the orm.xml file.

to_DB_class. The full, qualified name of a class that implements the interface com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.FcmdbDalTransformerTo ExternalDB. The elements in the parenthesis are given to this class constructor. Use this converter to transform CMDB values to database values, for example, to append the suffix of .com to each node name.

from_DB_class. The full, qualified name of a class that implements the **com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.**

FcmdbDalTransformerFromExternalDB interface. The elements in the parenthesis are given to this class constructor. Use this converter to transform database values to CMDB values, for example, to append the suffix of **.com** to each node name.

For details, see "Out-of-the-Box Converters" on page 158.

The discriminator.properties File

This file maps each supported CI type (that is also used as a discriminator value in orm.xml) to a comma-separated list of possible corresponding values of the discriminator column, or a condition to match possible values of the discriminator column.

If a condition is used, use the syntax: like(condition), where condition is a string that can contain the following wildcards:

- % (percent sign) allows you to match any string of any length (including a zero length string)
- _ (underscore) allows you to match a single character

For example, like(%unix%) will match unix, linux, unix-aix, and so on. Like conditions may only be applied to string columns.

You can also have a single discriminator value mapped to any value that does not belong to another discriminator by stating 'all-other'.

If the adapter you are creating uses discriminator capabilities, you must define all the discriminator values in the **discriminator.properties** file.

Example of Discriminator Mapping:

For example, the adapter supports the CI types node, nt, and unix, and the database contains a single table named t_nodes that contains a column called **type**. If the type is 10001, the row represents a node; if the type is 10004, it represents a unix machine, and so on. The **discriminator.properties** file might look like this:

```
node=10001, 10005
nt=10002,10003
unix=2%
mainframe=all-other
```

The **orm.xml** file includes the following code:

```
<entity class="generic_db_adapter.node" >

     ...
```

The discriminator_column attribute is then calculated as follows:

- If type contains 10002 or 10003 for a certain entry, the entry is mapped to the nt CIT.
- If type contains 10001 or 10005 for a certain entry, the entry is mapped to the node CIT.
- If **type** starts with 2 for a certain entry, the entry is mapped to the **unix** CIT.
- Any other value in the **type** column is mapped to the **mainframe** CIT.

Note: The node CIT is also the parent of \mathbf{nt} and \mathbf{unix} .

The replication_config.txt File

This file contains a comma-separated list of CI and relationship types whose property conditions are supported by the replication plug-in. For details, see "Plug-ins" on page 163.

The fixed_values.txt File

This file enables you to configure fixed values for specific attributes of certain CITs. In this way, each of these attributes can be assigned a fixed value that is not stored in the database.

The file should contain zero or more entries of the following format:

```
entity[<entityName>] attribute[<attributeName>] value[<value>]
```

For example:

```
entity[ip_address] attribute[ip_domain] value[DefaultDomain]
```

The file also supports a list of constants. To define a constants list, use the following syntax:

```
entity[<entityName>] attribute[<attributeName>] value[{<Val1>, <Val2>, <Val3>, ...
}]
```

The Persistence.xml File

This file is used to override the default Hibernate settings and to add support for database types that are not out of the box (OOB database types are Oracle Server, Microsoft SQL Server, and MySQL).

If you need to support a new database type, make sure that you supply a connection pool provider (the default is c3p0) and a JDBC driver for your database (put the *.jar files in the adapter folder).

To see all available Hibernate values that can be changed, check the **org.hibernate.cfg.Environment** class (for details, refer to http://www.hibernate.org.)

```
Example of the persistence.xml File:
<persistence xmlns="http://java.sun.com/xml/ns/persistence" xmlns:xsi=</pre>
"http://www.w3.org/2001/XMLSchema-instance" xsi:schemaLocation=
"http://java.sun.com/xml/ns/persistence
   http://java.sun.com/xml/ns/persistence/persistence_1_0.xsd" version="1.0">
   <!-- Don't change this value -->
    <persistence-unit name="GenericDBAdapter">
        cproperties>
            <!-- Don't change this value -->
            cproperty name="hibernate.archive.autodetection" value="class,
               hbm" />
            <!--The driver class name"/-->
            operty name="hibernate.connection.driver class" value="com.
              mercury.jdbc.MercOracleDriver" />
            <!--The connection url"/-->
            cproperty name="hibernate.connection.url" value="jdbc:mercury:
              oracle://artist:1521;sid=cmdb2" />
            <!--DB login credentials"/-->
            cyproperty name="hibernate.connection.username" value="CMDB" />
            cproperty name="hibernate.connection.password" value="CMDB" />
            <!--connection pool properties"/-->
            cproperty name="hibernate.c3p0.min size" value="5" />
            cproperty name="hibernate.c3p0.max_size" value="20" />
            cproperty name="hibernate.c3p0.timeout" value="300" />
            cproperty name="hibernate.c3p0.max statements" value="50" />
            <property name="hibernate.c3p0.idle test period" value="3000" />
            <!--The dialect to use-->
            cproperty name="hibernate.dialect" value="org.hibernate.dialect.
               OracleDialect" />
        </properties>
    </persistence-unit>
</persistence>
```

Connect to Database Using NT Authentication

It is possible to connect to an MS SQL Server that requires NT authentication. To do so a driver that can parse domain is needed (that is, jTDS JDBC Driver).

The authentication is done according to the given parameters (domain, username, password), and not with the current running process NT credentials.

1. In the **persistence.xml** edit the following properties as follows:

```
<!--The driver class name"/-->
cproperty name="hibernate.connection.driver_class"
value="net.sourceforge.jtds.jdbc.Driver"/>
cproperty name="hibernate.connection.url" value="jdbc:jtds:sqlserver://[host name]:[port];DatabaseName=[database name];domain=[the domain]"/>
<!--DB login credentials"/-->
cproperty name="hibernate.connection.username" value="[username]"/>
cproperty name="hibernate.connection.password" value="[password]"/>
```

- 2. Place the JDBC driver file under: installation folder>\lib\.
- 3. Restart the probe.

Configure the Persistence.xml File for the SCCM Integration to Use NTLM Authentication

Note: This section applies to the SCCM integration only.

In order for the SCCM integration to use NTLM authentication, configure the **persistence.xml** file as follows:

- 1. Place the JDBC driver file under: installation folder>\lib\.
 - For example, you can put the **jtds-1.3.1.jar** file from http://sourceforge.net/projects/jtds/files/ in the **DataFlowProbe\lib** folder.
- 2. Start the server and the probe.
- 3. In UCMDB, go to Data Flow Management > Adapter Management > SCCMAdapter > .
- In the Resources pane, select the SCCM adapter configuration file in the Packages > SCCMAdapter > Configuration Files folder.
- 5. In the adapter.conf file, set dal.use.persistence.xml=true.

6. In the **persistence.xml** file, add the following:

```
<persistence xmlns="http://java.sun.com/xml/ns/persistence" xmlns:xsi=</pre>
"http://www.w3.org/2001/XMLSchema-instance" xsi:schemaLocation=
"http://java.sun.com/xml/ns/persistence
  http://java.sun.com/xml/ns/persistence/persistence 1 0.xsd" version="1.0">
    <persistence-unit name="GenericDBAdapter">
        cproperties>
            <!-- added to fix: org.hibernate.HibernateException:
'hibernate.dialect' must be set when no Connection avalable -->
            cproperty name="hibernate.dialect"
value="org.hibernate.dialect.HSQLDialect"/>
            cproperty name="hibernate.hbm2ddl.auto" value="create-drop"/>
            <!--The driver class name"/-->
            cproperty name="hibernate.connection.driver class"
value="net.sourceforge.jtds.jdbc.Driver"/>
            cproperty name="hibernate.connection.url"
value="jdbc:jtds:sqlserver://<DB host>:<port>;DatabaseName=<DB</pre>
name>;domain=<domain name> "/>
        </properties>
    </persistence-unit>
</persistence>
```

Note: Replace the highlighted part with your connection URL.

- 7. No user or password is required in the **persistence.xml** file.
- 8. Go to Data Flow Management > Integration Studio, and click the New Integration Point button.
- Provide values for required fields.

When you are required to enter credential ID, do the following:

- a. In the Choose Credential dialog box, select Generid DB Protocol (SQL) from the left Protocol pane.
- b. In the right Credentials pane, click the Create new connection details for selected protocol type button.
- c. In the new dialog box, select **MicrosoftSQLServerNTLM** as database type.
- d. Enter a port number.
- e. Provide a username in the following format: **domain\username**.
- f. Provide a password.

Out-of-the-Box Converters

You can use the following converters (transformers) to convert federated queries and replication jobs to and from database data.

This section includes the following topics:

- "Out-of-the-Box Converters" above
- "The SuffixTransformer Converter" on page 161
- "The PrefixTransformer Converter" on page 161
- "The BytesToStringTransformer Converter" on page 162
- "The StringDelimitedListTransformer Converter" on page 162
- "The Custom Converter" on page 162

The enum-transformer Converter

This converter uses an XML file that is given as an input parameter.

The XML file maps between hard-coded CMDB values and database values (enums). If one of the values does not exist, you can choose to return the same value, return null, or throw an exception.

The transformer performs a comparison between two strings using a case sensitive, or a case insensitive method. The default behavior is case sensitive. To define it as case insensitive use: case-sensitive="false" in the enum-transformer element.

Use one XML mapping file for each entity attribute.

Note: This converter can be used for both the to_DB_class and from_DB_class fields in the **transformations.txt** file.

Input File XSD:

```
<xs:element ref="value" minOccurs="0" maxOccurs="unbounded"/>
</xs:sequence>
<xs:attribute name="db-type" use="required">
  <xs:simpleType>
       <xs:restriction base="xs:string">
           <xs:enumeration value="integer"/>
           <xs:enumeration value="long"/>
           <xs:enumeration value="float"/>
           <xs:enumeration value="double"/>
           <xs:enumeration value="boolean"/>
           <xs:enumeration value="string"/>
           <xs:enumeration value="date"/>
           <xs:enumeration value="xml"/>
           <xs:enumeration value="bytes"/>
      </xs:restriction>
  </xs:simpleType>
</xs:attribute>
<xs:attribute name="cmdb-type" use="required">
  <xs:simpleType>
      <xs:restriction base="xs:string">
          <xs:enumeration value="integer"/>
          <xs:enumeration value="long"/>
          <xs:enumeration value="float"/>
          <xs:enumeration value="double"/>
          <xs:enumeration value="boolean"/>
          <xs:enumeration value="string"/>
          <xs:enumeration value="date"/>
          <xs:enumeration value="xml"/>
          <xs:enumeration value="bytes"/>
       </xs:restriction>
```

```
</xs:simpleType>
         </xs:attribute>
         <xs:attribute name="non-existing-value-action" use="required">
            <xs:simpleType>
                <xs:restriction base="xs:string">
                   <xs:enumeration value="return-null"/>
                   <xs:enumeration value="return-original"/>
                   <xs:enumeration value="throw-exception"/>
                </xs:restriction>
            </xs:simpleType>
        </xs:attribute>
        <xs:attribute name="case-sensitive" use="optional">
            <xs:simpleType>
                <xs:restriction base="xs:boolean">
                </xs:restriction>
            </xs:simpleType>
        </xs:attribute>
    </xs:complexType>
  </xs:element>
  <xs:element name="value">
    <xs:complexType>
        <xs:attribute name="cmdb-value" type="xs:string" use="required"/>
        <xs:attribute name="external-db-value" type="xs:string" use="required"/>
        <xs:attribute name="is-cmdb-value-null" type="xs:boolean"</pre>
use="optional"/>
        <xs:attribute name="is-db-value-null" type="xs:boolean" use="optional"/>
    </xs:complexType>
  </xs:element>
</xs:schema>
```

Example of Converting 'sys' Value to 'System' Value:

In this example, sys value in the CMDB is transformed into System value in the federated database, and System value in the federated database is transformed into sys value in the CMDB.

If the value does not exist in the XML file (for example, the string demo), the converter returns the same input value it receives.

Example of Converting an External or CMDB Value to a Null Value:

In this example, a value of **NNN** in the remote database is transformed into a null value in the CMDBdatabase.

```
<value cmdb-value="null" is-cmdb-value-null="true" external-db-value="NNN"/>
In this example, the value OOO in the CMDB is transformed into a null value in the remote database.
<value cmdb-value="000" external-db-value="null" is-db-value-null="true"/>
```

The SuffixTransformer Converter

This converter is used to add or remove suffixes from the CMDB or federated database source value.

There are two implementations:

- com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.AdapterToCmdb
 AddSuffixTransformer. Adds the suffix (given as input) when converting from federated database value to CMDB value and removes the suffix when converting from CMDB value to federated database value.
- com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.AdapterToCmdb
 RemoveSuffixTransformer. Removes the suffix (given as input) when converting from federated database value to CMDB value and adds the suffix when converting from CMDB value to federated database value.

The PrefixTransformer Converter

This converter is used to add or remove a prefix from the CMDB or federated database value.

There are two implementations:

- com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.AdapterToCmdb
 AddPrefixTransformer. Adds the prefix (given as input) when converting from federated database value to CMDB value and removes the prefix when converting from CMDB value to federated database value.
- com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.AdapterToCmdb
 RemovePrefixTransformer. Removes the prefix (given as input) when converting from federated database value to CMDB value and adds the prefix when converting from CMDB value to federated database value.

The BytesToStringTransformer Converter

This converter is used to convert byte arrays in the CMDB to their string representation in the federated database source.

The converter is:

 $com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.CmdbToAdapterBytes \\ ToStringTransformer.$

The StringDelimitedListTransformer Converter

This converter is used to transform a single string list to an integer/string list in the CMDB.

The converter is: **com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl. StringDelimitedListTransformer.**

The Custom Converter

It is possible to write your own custom converter (transformer) from scratch. This enables you to create any converter required for your needs.

There are two ways to write a custom converter:

- 1. Write a compiled Java converter
 - a. Create a Java Project in a Java IDE (such as Eclipse, Intellij, or Netbeans).
 - b. Add the federation-api.jar and db-interfaces.jar to your class path.
 - c. Create a Java class that implements the following interfaces (from **db-interfaces.jar**):
 - FcmdbDalTransformerFromExternalDB
 - FcmdbDalTransformerValuesToExternalDB

- FcmdbDalTransformerInit
- d. Compile the project and create a jar file.
- e. Place the jar file in the adapter's package (under adapterCode\<Adapter ID>)
- f. Deploy the package.
- g. Add the new converter class name to the transformations.txt file.
- 2. Write a Groovy (script based) converter

An example is found in the original GDBA package, **GroovyExampleTransformer.groovy**.

- a. Create a Groovy file in the adapter's package (under adapterCode\<Adapter ID>). You can do this directly using the Adapter Management menu.
- b. Create a Groovy class that implements the following interfaces (from db-interfaces.jar):
 - FcmdbDalTransformerFromExternalDB
 - FcmdbDalTransformerValuesToExternalDB
 - FcmdbDalTransformerInit
- c. Add the new converter Groovy class name to the **transformations.txt** file accordingly.

Note: Groovy is a scripting language that extends Java. Regular Java code is valid Groovy code as well.

Plug-ins

The generic database adapter supports the following plugins:

- An optional plug-in for full topology synchronization.
- An optional plug-in for synchronizing changes in topology. If no plug-in for synchronizing changes is implemented, it is possible to perform a differential synchronization, but that synchronization will actually be a full one.
- An optional plug-in for synchronizing layout.
- An optional plug-in to retrieve supported queries for synchronization. If this plugin is not defined, all TQL names are returned.
- An internal, optional plug-in to change the TQL definition and TQL result.
- An internal, optional plug-in to change a layout request and CIs result.

- An internal, optional plug-in to change a layout request and relationships result.
- An internal, optional plug-in to change the action of push Back IDs.

For details about implementing and deploying plug-ins, see "Implement a Plug-in" on page 117.

Configuration Examples

This section gives examples of configurations.

This section includes the following topics:

- "Use Case" below
- "Single Node Reconciliation" below
- "Two Node Reconciliation" on page 167
- "Using a Primary Key that Contains More Than One Column" on page 169
- "Using Transformations" on page 171

Use Case

A TQL query is:

node > (composition) > card

where:

- node is the CMDB entity
- · card is the federated database source entity
- composition is the relationship between them

The example is run against the ED database. ED nodes are stored in the Device table and card is stored in the hwCards table. In the following examples, card is always mapped in the same manner.

Single Node Reconciliation

In this example the reconciliation is run against the name property.

Simplified Definition

The reconciliation is done by node and it is emphasized by the special tag CMDB-class.

```
<?xml version="1.0" encoding="UTF-8"?>
<generic-DB-adapter-config xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:noNamespaceSchemaLocation=".../META-CONF/simplifiedConfiguration.xsd">
    <CMDB-class CMDB-class-name="node" default-table-name="Device">
        <primary-key column-name="Device ID" />
        <reconciliation-by-single-node>
            <or>
                <attribute CMDB-attribute-name="name" column-name="Device_Name"</pre>
/>
            </or>
        </reconciliation-by-single-node>
    </CMDB-class>
    <class CMDB-class-name="card" default-table-name="hwCards" connected-CMDB-
class-name="node" link-class-name="composition">
        <foreign-primary-key column-name="Device_ID" CMDB-class-primary-key-</pre>
column="Device ID
        <primary-key column-name="hwCards Seq" />
        <attribute CMDB-attribute-name="card_class" column-name="hwCardClass" />
        <attribute CMDB-attribute-name="card_vendor" column-name="hwCardVendor"</pre>
/>
        <attribute CMDB-attribute-name="card name" column-name="hwCardName" />
    </class>
</generic-DB-adapter-config>
```

Advanced Definition

The orm.xml File

Pay attention to the addition of the relationship mapping. For details, see the definition section in "The orm.xml File" on page 136.

Example of the orm.xml File:

```
insertable="false"
                                  updatable="false"/>
                               <generated-value strategy="TABLE"/>
                       </id>
                       <basic name="name">
                               <column name="Device_Name"/>
                       </basic>
               </attributes>
       </entity>
       <entity class="generic db adapter.card" >
               <attributes>
                       <id name="id1">
                               <column name="hwCards Seq" insertable="false"
                                   updatable="false"/>
                               <generated-value strategy="TABLE"/>
                       </id>
                       <basic name="card_class">
                               <column name="hwCardClass" insertable="false"</pre>
                                   updatable="false"/>
                       </basic>
                       <basic name="card vendor">
                               <column name="hwCardVendor" insertable="false"</pre>
                                  updatable="false"/>
                       </basic>
                       <basic name="card name">
                               <column name="hwCardName" insertable="false"</pre>
                                  updatable="false"/>
                       </basic>
               </attributes>
       </entity>
       <entity class="generic db adapter.node composition card" >
               <attributes>
                       <id name="id1">
                               <column name="hwCards_Seq" insertable="false"</pre>
                                  updatable="false"/>
                               <generated-value strategy="TABLE"/>
                       </id>
                       <many-to-one name="end1" target-entity="node">
                               <join-column name="Device_ID" insertable="false"</pre>
                                  updatable="false"/>
                       </many-to-one>
                       <one-to-one name="end2" target-entity="card"</pre>
                               <join-column name="hwCards Seq"
>
                               referenced-column-name="hwCards_Seq" insertable=
                               "false" updatable="false"/>
                       </one-to-one>
```

```
</entity>
</entity-mappings>
```

The reconciliation_rules.txt File

For details, see "The reconciliation_rules.txt File (for backwards compatibility)" on page 150.

```
multinode[node] expression[node.name]
```

The transformation.txt File

This file remains empty as no values need to be converted in this example.

Two Node Reconciliation

In this example, reconciliation is calculated according to the name property of node and of ip_address with different variations.

The reconciliation TQL query is **node > (containment) > ip_address**.

Simplified Definition

The reconciliation is by name of node OR of ip_address:

```
<?xml version="1.0" encoding="UTF-8"?>
<generic-DB-adapter-config xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:noNamespaceSchemaLocation=".../META-CONF/simplifiedConfiguration.xsd">
    <CMDB-class CMDB-class-name="node" default-table-name="Device">
        <primary-key column-name="Device_ID" />
        <reconciliation-by-two-nodes connected-node-CMDB-class-name="ip address"</pre>
CMDB-link-type="containment">
            <or>
                <attribute CMDB-attribute-name="name" column-name="Device_Name"</pre>
/>
                <connected-node-attribute CMDB-attribute-name="name" column-</pre>
name="Device PreferredIPAddress" />
            </or>
        </reconciliation-by-two-nodes>
    </CMDB-class>
    <class CMDB-class-name="card" default-table-name="hwCards" connected-CMDB-
class-name="node" link-class-name="containment">
        <foreign-primary-key column-name="Device ID" CMDB-class-primary-key-</pre>
column="Device_ID" />
        <primary-key column-name="hwCards Seq" />
        <attribute CMDB-attribute-name="card class" column-name="hwCardClass" />
        <attribute CMDB-attribute-name="card_vendor" column-name="hwCardVendor"</pre>
```

The reconciliation is name of node AND of ip_address:

```
<?xml version="1.0" encoding="UTF-8"?>
<generic-DB-adapter-config xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:noNamespaceSchemaLocation="../META-CONF/simplifiedConfiguration.xsd">
    <CMDB-class CMDB-class-name="node" default-table-name="Device">
        <primary-key column-name="Device ID" />
        <reconciliation-by-two-nodes connected-node-CMDB-class-name="ip address"</pre>
CMDB-link-type="containment">
            <and>
                <attribute CMDB-attribute-name="name" column-name="Device Name"
/>
                <connected-node-attribute CMDB-attribute-name="name" column-</pre>
name="Device PreferredIPAddress" />
            </and>
        </reconciliation-by-two-nodes>
    </CMDB-class>
    <class CMDB-class-name="card" default-table-name="hwCards" connected-CMDB-
class-name="node" link-class-name="containment">
        <foreign-primary-key column-name="Device ID" CMDB-class-primary-key-</pre>
column="Device ID" />
        <primary-key column-name="hwCards_Seq" />
        <attribute CMDB-attribute-name="card class" column-name="hwCardClass" />
        <attribute CMDB-attribute-name="card_vendor" column-name="hwCardVendor"</pre>
/>
        <attribute CMDB-attribute-name="card name" column-name="hwCardName" />
    </class>
</generic-DB-adapter-config>
```

The reconciliation is by name of ip_address:

Advanced Definition

The orm.xml File

Since the reconciliation expression is not defined in this file, the same version should be used for any reconciliation expression.

The reconciliation_rules.txt File

For details, see "The reconciliation_rules.txt File (for backwards compatibility)" on page 150.

```
multinode[node] expression[ip_address.name OR node.name] end1_type[node] end2_
type[ip_address] link_type[containment]
multinode[node] expression[ip_address.name AND node.name] end1_type[node] end2_
type[ip_address] link_type[containment]
multinode[node] expression[ip_address.name] end1_type[node] end2_type[ip_
address] link_type[containment]
```

The transformation.txt File

This file remains empty as no values need to be converted in this example.

Using a Primary Key that Contains More Than One Column

If the primary key is composed of more than one column, the following code is added to the XML definitions:

Simplified Definition

There is more than one primary key tag and for each column there is a tag.

```
<class CMDB-class-name="card" default-table-name="hwCards" connected-CMDB-</pre>
```

Advanced Definition

The orm.xml File

A new id entity is added that maps to the primary key columns. Entities that use this id entity must add a special tag.

If you use a foreign key (join-column tag) for such a primary key, you must map between each column in the foreign key to a column in the primary key.

For details, see "The orm.xml File" on page 136.

Example of the orm.xml File:

```
<entity class="generic_db_adapter.card" >
       <attributes>
           <id name="id1">
               <column name="Device_ID" insertable="false" updatable="false" />
               <generated-value strategy="TABLE" />
           </id>
           <id name="id2">
               <column name="hwBusesSupported_Seq" insertable="false"</pre>
updatable="false" />
               <generated-value strategy="TABLE" />
           </id>
           <id name="id3">
               <column name="hwCards Seq" insertable="false" updatable="false"</pre>
/>
               <generated-value strategy="TABLE" />
           </id>
<entity class="generic_db_adapter.node_containment_card" >
       <attributes>
           <id name="id1">
               <column name="Device_ID" insertable="false" updatable="false" />
```

```
<generated-value strategy="TABLE" />
            </id>
            <id name="id2">
                <column name="hwBusesSupported Seq" insertable="false"
updatable="false" />
                <generated-value strategy="TABLE" />
            </id>
            <id name="id3">
                <column name="hwCards Seq" insertable="false" updatable="false"</pre>
/>
                <generated-value strategy="TABLE" />
            </id>
            <many-to-one name="end1" target-entity="node">
                <join-column name="Device ID" insertable="false"</pre>
updatable="false" />
            </many-to-one>
            <one-to-one name="end2" target-entity="card">
                <join-column name="Device_ID" referenced-column-name="Device_ID"</pre>
insertable="false" updatable="false" />
                <join-column name="hwBusesSupported Seg" referenced-column-</pre>
name="hwBusesSupported Seq" insertable="false" updatable="false" />
                <join-column name="hwCards_Seq" referenced-column-name="hwCards_</pre>
Seq" insertable="false" updatable="false" />
            </one-to-one>
        </attributes>
    </entity>
</entity-mappings>
```

Using Transformations

In the following example, the generic **enum** transformer is converted from values 1, 2, 3 to values a, b, c respectively in the name column.

The mapping file is generic-enum-transformer-example.xml.

Simplified Definition

```
<reconciliation-by-two-nodes connected-node-CMDB-class-name="ip address"</pre>
          CMDB-link-type="containment">
            <or>
                <attribute CMDB-attribute-name="name" column-name="Device_Name"
                 from-CMDB-
converter="com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.
                 transform.impl.GenericEnumTransformer(generic-enum-transformer-
example.
                 xml)" to-CMDB-
converter="com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.
                 transform.impl.GenericEnumTransformer(generic-enum-transformer-
example.
                 xml)" />
                <connected-node-attribute CMDB-attribute-name="name"</pre>
                 column-name="Device_PreferredIPAddress" />
            </or>
        </reconciliation-by-two-nodes>
    </CMDB-class>
```

Advanced Definition

There is a change only to the **transformation.txt** file.

The transformation.txt File

Make sure that the attribute names and entity names are the same as in the orm.xml file.

```
entity[node] attribute[name]
to_DB_class[com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.
GenericEnumTransformer(generic-enum-transformer-example.xml)] from_DB_class
[com.mercury.topaz.fcmdb.adapters.dbAdapter.dal.transform.impl.
GenericEnumTransformer(generic-enum-transformer-example.xml)]
```

Adapter Log Files

To understand the calculation flows and adapter lifecycle, and to view debug information, you can consult the following log files.

This section includes the following topics:

- · "Log Levels" on the next page
- "Log Locations" on the next page

Log Levels

You can configure the log level for each of the logs.

In a text editor, open the C:\hp\UCMDB\UCMDBServer\conf\log\ fcmdb.gdba.properties file.

The default log level is **ERROR**:

#loglevel can be any of DEBUG INFO WARN ERROR FATAL loglevel = ERROR

- To increase the log level for all log files, change **loglevel=ERROR** to **loglevel=DEBUG** or **loglevel=INFO**.
- To change the log level for a specific file, change the specific **log4j** category line accordingly. For example, to change the log level of fcmdb.gdba.dal.sql.log to **INFO**, change:

```
log4j.category.fcmdb.gdba.dal.SQL=${log1eve1},fcmdb.gdba.dal.SQL.appender
to:
log4j.category.fcmdb.gdba.dal.SQL=INFO,fcmdb.gdba.dal.SQL.appender
```

Log Locations

The log files are located in the C:\hp\UCMDB\UCMDBServer\runtime\log directory.

Fcmdb.gdba.log

The adapter lifecycle log. Gives details about when the adapter started or stopped, and which CITs are supported by this adapter.

Consult for initiation errors (adapter load/unload).

· fcmdb.log

Consult for exceptions.

cmdb.log

Consult for exceptions.

· Fcmdb.gdba.mapping.engine.log

The mapping engine log. Gives details about the reconciliation TQL query that the mapping engine uses, and the reconciliation topologies that are compared during the connect phase.

Consult this log when a TQL query gives no results even though you know there are relevant CIs in the database, or the results are unexpected (check the reconciliation).

• Fcmdb.gdba.TQL.log

The TQL log. Gives details about the TQL queries and their results.

Consult this log when a TQL query does not return results and the mapping engine log shows that there are no results in the federated data source.

· Fcmdb.gdba.dal.log

The DAL lifecycle log. Gives details about CIT generation and database connection details.

Consult this log when you cannot connect to the database or when there are CITs or attributes that are not supported by the query.

Fcmdb.gdba.dal.command.log

The DAL operations log. Gives details about internal DAL operations that are called. (This log is similar to cmdb.dal.command.log).

Fcmdb.gdba.dal.SQL.log

The DAL SQL queries log. Gives details about called JPAQLs (object oriented SQL queries) and their results.

Consult this log when you cannot connect to the database or when there are CITs or attributes that are not supported by the query.

Fcmdb.gdba.hibrnate.log

The Hibernate log. Gives details about the SQL queries that are run, the parsing of each JPAQL to SQL, the results of the queries, data regarding Hibernate caching, and so on. For details on Hibernate, see "Hibernate as JPA Provider" on page 99.

External References

For details on the JavaBeans 3.0 specification, see

http://jcp.org/aboutJava/communityprocess/final/jsr220/index.html.

Troubleshooting and Limitations – Developing Generic Database Adapters

This section describes troubleshooting and limitations for the generic database adapter.

General Limitations

- When you update an adapter package, use Notepad++, UltraEdit, or some other third-party text
 editor rather than Notepad (any version) from Microsoft Corporation to edit the template files. This
 prevents the use of special symbols, which cause the deployment of the prepared package to fail.
- In most of the cases, after making a change, it is needed to reload the adapter on the probe side, otherwise the adapter will not function properly
 - a. Log in to the probe JMX console: https://localhost:8453/
 - b. Locate the **adapters** bean, and reload adapter with the integration point name.

If the adapter is not reloaded after each change, issues may occor (wrong error messages, query failures, and so on).

JPA Limitations

- All tables must have a primary key column.
- CMDB class attribute names must follow the JavaBeans naming convention (for example, names must start with lower case letters).
- Two CIs that are connected with one relationship in the class model must have direct association in the database (for example, if node is connected to ticket there must be a foreign key or linkage table that connects them).
- Several tables that are mapped to the same CIT must share the same primary key table.

Functional Limitations

You cannot create a manual relationship between the CMDB and federated CITs. To be able to
define virtual relationships, a special relationship logic must be defined (it can be based on
properties of the federated class).

- Federated CITs cannot be trigger CITs in an impact rule, but they can be included in an impact analysis TQL query.
- A federated CIT can be part of an enrichment TQL, but cannot be used as the node on which enrichment is performed (you cannot add, update, or delete the federated CIT).
- Using a class qualifier in a condition is not supported.
- Subgraphs are not supported.
- · Compound relationships are not supported.
- The external CI CMDBid is composed from its primary key and not its key attributes.
- A column of type bytes cannot be used as a primary key column in Microsoft SQL Server.
- TQL query calculation fails if attribute conditions that are defined on a federated node have not had their names mapped in the **orm.xml** file.

Chapter 6: Developing Java Adapters

This chapter includes:

Federation Framework Overview	177
Adapter and Mapping Interaction with the Federation Framework	182
Federation Framework for Federated TQL Queries	183
Interactions between the Federation Framework, Server, Adapter, and Mapping Engine	184
Federation Framework Flow for Population	194
Adapter Interfaces	195
Debug Adapter Resources	198
Add an Adapter for a New External Data Source	198
Create a Sample Adapter	206
XML Configuration Tags and Properties	207
The DataAdapterEnvironment Interface	210

Federation Framework Overview

Note:

- The term **relationship** is equivalent to the term **link**.
- The term CI is equivalent to the term object.
- A graph is a collection of nodes and links.

The Federation Framework functionality uses an API to retrieve information from federated sources. The Federation Framework provides three main capabilities:

- **Federation** on the fly. All queries are run over original data repositories and results are built on the fly in the CMDB.
- **Population.** Populates data (topological data and CI properties) to the CMDB from an external data source.

 Data Push. Pushes data (topological data and CI properties) from the local CMDB to a remote data source.

All action types require an adapter for each data repository, which can provide the specific capabilities of the data repository and retrieve and/or update the required data. Every request to the data repository is made through its adapter.

This section also includes the following topics:

- "Federation on the Fly" below
- "Data Push" on the next page
- "Population" on page 180


Federation on the Fly

Federated TQL queries enables data retrieval from any external data repository without replicating its data.


A federated TQL query uses adapters that represent external data repositories, to create appropriate external relationships between CIs from different external data repositories and the UCMDB CIs.

Example of Federation-on-the-Fly Flow:


1. The Federation Framework splits a federated TQL query into several subgraphs, where all nodes in a subgraph refer to the same data repository. Each subgraph is connected to the other subgraphs by a virtual relationship (but itself contains no virtual relationships).



2. After the federated TQL query is split into subgraphs, the Federation Framework calculates each subgraph's topology and connects two appropriate subgraphs by creating virtual relationships between the appropriate nodes.



3. After the federated TQL topology is calculated, the Federation Framework retrieves a layout for the topology result.



Data Push

You use the data push flow to synchronize data from your current local CMDB to a remote service or target data repository.

In data push, data repositories are divided into two categories: source (local CMDB) and target. Data is retrieved from the source data repository and updated to the target data repository. The data push process is based on query names, meaning that data is synchronized between the source (local CMDB) and target data repositories, and is retrieved by a TQL query name from the local CMDB.

The data push process flow includes the following steps:

- 1. Retrieving the topology result with signatures from the source data repository.
- 2. Comparing the new results with the previous results.
- 3. Retrieving a full layout (that is, all CI properties) of CIs and relationships, for changed results only.
- 4. Updating the target data repository with the received full layout of CIs and relationships. If any CIs or relationships are deleted in the source data repository and the query is exclusive, the replication process removes the CIs or relationships in the target data repository as well.

The CMDB has 2 hidden data sources (hiddenRMIDataSource and hiddenChangesDataSource), which are always the `source' data source in data push flows. To implement a new adapter for data push flows, you only have to implement the `target' adapter.

Population

You use the population flow to populate the CMDB with data from external sources.

The flow always uses one 'source' data source to retrieve the data, and pushes the retrieved data to the Probe in a similar process to the flow of a discovery job.

To implement a new adapter for population flows, you only have to implement the source adapter, since the Data Flow Probe acts as the target.

The adapter in the population flow is executed on the Probe. Debugging and logging should be done on the Probe and not on the CMDB.

The population flow is based on query names, that is, data is synchronized between the source data repository and the Data Flow Probe, and is retrieved by a query name in the source data repository. For example, in UCMDB, the query name is the name of the TQL query. However, in another data repository the query name can be a code name that returns data. The adapter is designed to correctly handle the query name.

Each job can be defined as an exclusive job. This means that the CIs and relationships in the job results are unique in the local CMDB, and no other query can bring them to the target. The adapter of the source data repository supports specific queries, and can retrieve the data from this data repository. The adapter of the target data repository enables the update of retrieved data on this data repository.

SourceDataAdapter Flow

- Retrieves the topology result with signatures from the source data repository.
- Compares the new results with the previous results.

- Retrieves a full layout (that is, all CI properties) of CIs and relationships, for changed results only.
- Updates the target data repository with the received full layout of CIs and relationships. If any CIs
 or relationships are deleted in the source data repository and the query is exclusive, the replication
 process removes the CIs or relationships in the target data repository as well.

SourceChangesDataAdapter Flow

- Retrieves the topology result that occurred since the last date given.
- Retrieves a full layout (that is, all CI properties) of CIs and relationships, for changed results only.
- Updates the target data repository with the received full layout of CIs and relationships. If any CIs
 or relationships are deleted in the source data repository and the query is exclusive, the replication
 process removes the CIs or relationships in the target data repository as well.

PopulateDataAdapter Flow

- Retrieves the full topology with requested layout result.
- Uses the topology chunk mechanism to retrieve the data in chunks.
- The probe filters out any data that was already brought in earlier runs
- Updates the target data repository with the received layout of CIs and relationships. If any CIs or relationships are deleted in the source data repository and the query is exclusive, the replication process removes the CIs or relationships in the target data repository as well.

PopulateChangesDataAdapter Flow

- Retrieves the topology with requested layout result that has changes since the last run.
- Uses the topology chunk mechanism to retrieve the data in chunks.
- The probe filters out any data that was already brought in earlier runs (including this flow).
- Updates the target data repository with the received layout of CIs and relationships. If any CIs or relationships are deleted in the source data repository and the query is exclusive, the replication process removes the CIs or relationships in the target data repository as well.

Instance-Based Population Flow

If the adapter is defined to support an instance-based flow (by means of the **<instance-based-data>** tag, as described in "XML Configuration Tags and Properties" on page 207), the population engine automatically finds removed CIs inside the instance and removes them from the UCMDB (assuming deletion is allowed for the specific population job). Each instance must have a Root CI, marked in the TQL definition with the name **Root**. Each time a root CI is passed, its entire instance (all the CIs

connected to it) are compared to the last time it was sent to UCMDB, and any CIs that were connected to the root but are now not connected to it are deleted from UCMDB. For the adapter to correctly support instance-based flow, any change to any CI or attribute in the entire instance must trigger a resend of the entire instance to UCMDB.

Adapter and Mapping Interaction with the Federation Framework

An adapter is an entity in UCMDB that represents external data (data that is not saved in UCMDB). In federated flows, all interactions with external data sources are performed through adapters. The Federation Framework interaction flow and adapter interfaces are different for replication and for federated TQL queries.

This section also includes the following topics:

- "Adapter Lifecycle" below
- "Adapter assist Methods" below

Adapter Lifecycle

An adapter instance is created for each external data repository. The adapter begins its lifecycle with the first action applied to it (such as, calculate TQL or retrieve/update data). When the **start** method is called, the adapter receives environmental information, such as the data repository configuration, logger, and so on. The adapter lifecycle ends when the data repository is removed from the configuration, and the **shutdown** method is called. This means that the adapter is stateful and can contain the connection to the external data repository if it is required.

Adapter assist Methods

The adapter has several assist methods that can add external data repository configurations. These methods are not part of the adapter lifecycle and create a new adapter each time they are called.

- The first method tests the connection to the external data repository for a given configuration.
 testConnection can be executed either on the UCMDB server or the Data Flow Probe, depending on the type of adapter.
- The second method is relevant only for the source adapter and returns the supported queries for replication. (This method is executed on the Probe only.)

• The third method is relevant only for federation and population flows, and returns supported external classes by the external data repository. (This method is executed on the UCMDB server.)

All these methods are used when you create or view integration configurations.

Federation Framework for Federated TQL Queries

This section includes the following topics:

- "Definitions and Terms" below
- · "Mapping Engine" on the next page
- "Federated Adapter" on the next page

See "Interactions between the Federation Framework, Server, Adapter, and Mapping Engine" on the next page for diagrams illustrating the interactions between the Federation Framework, UCMDB, adapter, and Mapping Engine.

Definitions and Terms

Reconciliation data. The rule for matching CIs of the specified type that are received from the CMDB and the external data repository. The reconciliation rule can be of three types:

- **ID reconciliation.** This can be used only if the external data repository contains the CMDB ID of reconciliation objects.
- **Property reconciliation.** This is used when the matching can be done by properties of the reconciliation CI type only.
- **Topology reconciliation.** This is used when you need the properties of additional CITs (not only of the reconciliation CIT) to perform a match on reconciliation CIs. For example, you can perform reconciliation of the node type by the name property that belongs to the ip address CIT.

Reconciliation object. The object is created by the adapter according to received reconciliation data. This object should refer to an external CI and is used by the Mapping Engine to connect between the external CIs and the CMDB CIs.

Reconciliation CI type. The type of CIs that represent reconciliation objects. These CIs must be stored in both the CMDB and in the external data repositories.

Mapping engine. A component that identifies relations between CIs from different data repositories that have a virtual relationship between them. The identification is performed by reconciling CMDB reconciliation objects and external CI reconciliation objects.

Mapping Engine

Federation Framework uses the Mapping Engine to calculate the federated TQL query. The Mapping Engine connects between CIs that are received from different data repositories and are connected by virtual relationships. The Mapping Engine also provides reconciliation data for the virtual relationship. One end of the virtual relationship must refer to the CMDB. This end is a reconciliation type. For the calculation of the two subgraphs, a virtual relationship can start from any end node.

Federated Adapter

The Federated adapter brings two kinds of data from external data repositories: external CI data and reconciliation objects that belong to external CIs.

- External CI data. The external data that does not exist in the CMDB. It is the target data of the external data repository.
- Reconciliation object data. The auxiliary data that is used by the federation framework to connect between CMDB CIs and external data. Each reconciliation object should refer to an External CI. The type of reconciliation object is the type (or subtype) of one of the virtual relationship ends from which data is retrieved. Reconciliation objects should fit the adapter received to reconciliation data. The reconciliation object can be one of three types: IdReconciliationObject, PropertyReconciliationObject, or TopologyReconciliationObject.

In the DataAdapter-based interfaces (DataAdapter, PopulateDataAdapter, and PopulateChangesDataAdapter), the reconciliation is requested as part of the query definition.

Interactions between the Federation Framework, Server, Adapter, and Mapping Engine

The following diagrams illustrate the interactions between the Federation Framework, UCMDB Server, the adapter, and the Mapping Engine. The federated TQL query in the example diagrams has only one virtual relationship, so that only the UCMDB and one external data repository are involved in the federated TQL query.


This section includes the following topics:

- "Calculation Starts at the Server End" below
- "Calculation Starts at the External Adapter End" on page 188
- "Example of Federation Framework Flow for Federated TQL Queries" on page 190

In the first diagram the calculation begins in the UCMDB and in the second diagram in the external adapter. Each step in the diagram includes references the appropriate method call of the adapter or mapping engine interface.

Calculation Starts at the Server End

The following sequence diagram illustrates the interaction between the Federation Framework, UCMDB, the adapter, and the Mapping Engine. The federated TQL query in the example diagram has only one virtual relationship, so that only UCMDB and one external data repository are involved in the federated TQL query.




The numbers in this image are explained below:

Number	Explanation
1	The Federation Framework receives a call for a federated TQL calculation.
2	The Federation Framework analyzes the adapter, finds the virtual relationship, and divides the original TQL into two sub-adapters—one for UCMDB and one for the external data repository.
3	The Federation Framework requests the topology of the sub-TQL from UCMDB.
4	After receiving the topology results, the Federation Framework calls the appropriate Mapping Engine for the current virtual relationship and requests reconciliation data. The

Number	Explanation	
	reconciliationObject parameter is empty at this stage, that is, no condition is added to reconciliation data in this call. The returned reconciliation data defines which data is needed to match the reconciliation CIs in UCMDB to the external data repository. The reconciliation data can be one of the following types:	
	IdReconciliationData. Cls are reconciled according to their ID.	
	PropertyReconciliationData. Cls are reconciled according to the properties of one of the Cls.	
	TopologyReconciliationData. Cls are reconciled according to the topology (for example, to reconcile node Cls, the IP address of IP is required too).	
5	The Federation Framework requests reconciliation data for the CIs of the virtual relationship ends that were received in step "3" on the previous page from UCMDB.	
6	The Federation Framework calls the Mapping Engine to retrieve the reconciliation data. In this state (by contrast with step "3" on the previous page), the Mapping Engine receives the reconciliation objects from step "5" above as parameters. The Mapping Engine translates the received reconciliation object to the condition on the reconciliation data.	
7	The Federation Framework requests the topology of the sub-TQL from the external data repository. The external adapter receives the reconciliation data from step "6" above as a parameter.	
8	The Federation Framework calls the Mapping Engine to connect between the received results. The firstResult parameter is the external topology result received from UCMDB in step "5" above and the secondResult parameter is the external topology result received from the External Adapter in step "7" above. The Mapping Engine returns a map where External CI ID from the first data repository (UCMDB in this case) is mapped to the External CI IDs from the second (external) data repository.	
9	For each mapping, the Federation Framework creates a virtual relationship.	
10	After the calculation of the federated TQL query results (only at the topology stage), the Federation Framework retrieves the original TQL layout for the resulting CIs and relationships from the appropriate data repositories.	

Calculation Starts at the External Adapter End



The numbers in this image are explained below:


Number	Explanation
1	The Federation Framework receives a call for an federated TQL calculation.
2	The Federation Framework analyzes the adapter, finds the virtual relationship, and divides the original TQL into two sub-adapters – one for UCMDB and one for the external data repository.
3	The Federation Framework requests the topology of the sub-TQL from the External

Number	Explanation	
	Adapter. The returned ExternalTopologyResult is not supposed to contain any reconciliation object, since the reconciliation data is not part of the request.	
4	After receiving the topology results, the Federation Framework calls the appropriate Mapping Engine with the current virtual relationship and requests reconciliation data. The reconciliationObjects parameter is empty at this state, that is, no condition is added to the reconciliation data in this call. The returned reconciliation data defines what data is needed to match the reconciliation CIs in UCMDB to the external data repository. The reconciliation data can be one of three following types:	
	IdReconciliationData. Cls are reconciled according to their ID.	
	 PropertyReconciliationData. Cls are reconciled according to the properties of one of the Cls. 	
	 TopologyReconciliationData. CIs are reconciled according to the topology (for example, to reconcile node CIs, the IP address of IP is required too). 	
5	The Federation Framework requests reconciliation objects for the CIs that were received in step 3 from the external data repository. The Federation Framework calls the getTopologyWithReconciliationData() method in the External Adapter, where the requested topology is a one-node topology with CIs received in step 3 as the ID condition and reconciliation data from step 4.	
6	The Federation Framework calls the Mapping Engine to retrieve the reconciliation data. In this state (by contrast with step 3), the Mapping Engine receives the reconciliation objects from step 5 as parameters. The Mapping Engine translates the received reconciliation object to the condition on the reconciliation data.	
7	The Federation Framework requests the topology of the sub-TQL with reconciliation data from step 6 from UCMDB.	
8	The Federation Framework calls the Mapping Engine to connect between the received results. The firstResult parameter is the external topology result received from the External Adapter at step 5 and the secondResult parameter is the external topology result received from UCMDB at step 7. The Mapping Engine returns a map where the External CI ID from the first data repository (the external data repository in this case) is mapped to the External CI IDs from the second data repository (UCMDB).	
9	For each mapping, the Federation Framework creates a virtual relationship.	
10	After the calculation of the federated TQL query results (only at the topology stage), the	

Number	Explanation
	Federation Framework retrieves the original TQL layout for the resulting CIs and relationships from the appropriate data repositories.


Example of Federation Framework Flow for Federated TQL Queries

This example explains how to view all open incidents on specific nodes. The ServiceCenter data repository is the external data repository. The node instances are stored in UCMDB, and the incident instances are stored in ServiceCenter. It is assumed that to connect the incident instances to the appropriate node, the node and <code>ip_address</code> properties of the host and IP are needed. These are reconciliation properties that identify the nodes from ServiceCenter in UCMDB.




Note: For attribute federation, the adapter's **getTopology** method is called. The reconciliation data is adapted in the user TQL (in this case, the CI element).


1. After analyzing the adapter, the Federation Framework recognizes the virtual relationship between Node and Incident and splits the federated TQL query into two subgraphs:




2. The Federation Framework runs the UCMDB subgraph to request the topology, and receives the following results:




3. The Federation Framework requests, from the appropriate Mapping Engine, the reconciliation data for the first data repository (UCMDB) that contains the information to connect between received data from two data repositories. The reconciliation data in this case is:




4. The Federation Framework creates a one-node topology query with the Node and ID conditions on it from the previous result (node in H1, H2, H3), and runs this query with the required reconciliation data on UCMDB. The result includes Node CIs that are relevant to the ID condition and the appropriate reconciliation object for each CI:




5. The reconciliation data for ServiceCenter should contain a condition for node and ip that is derived from the reconciliation objects received from UCMDB:



6. The Federation Framework runs the ServiceCenter subgraph with the reconciliation data to request the topology and appropriate reconciliation objects, and receives the following results:



7. The result after connection in Mapping Engine and creating virtual relationships is:



8. The Federation Framework requests the original TQL layout for received instances from UCMDB and ServiceCenter.

Federation Framework Flow for Population

This section includes the following topics:


- "Definitions and Terms" below
- "Flow Diagram" below

Definitions and Terms

Signature. Denotes the state of properties in the CI. If changes are made to property values in a CI, the CI signature must also be changed. The CI signature helps to detect whether a CI has changed without retrieving and comparing all CI properties. Both the CI and the CI signature are provided by the appropriate adapter. The adapter is responsible for changing the CI signature when the CI properties are altered.

Flow Diagram

The following sequence diagram illustrates the interaction between the Federation Framework and the source and target adapters in a population flow:



- The Federation Framework receives the topology for the query result from the source adapter. The
 adapter recognizes the query by its name and runs it on the external data repository. The topology
 result contains the ID and signature for each CI and relationship in the result. The ID is the logical
 ID that defines the CI as unique in the external data repository. The signature should be modified if
 the CI or relationship is modified.
- 2. The Federation Framework uses signatures to compare the newly received topology query results with the saved ones, and to determine which CIs have changed.
- After the Federation Framework finds the CIs and relationships that have changed, it calls the source adapter with the IDs of the changed CIs and relationships as a parameter to retrieve their full layout.
- 4. The Federation Framework sends the update to the target adapter. The target adapter updates the external data source with the received data.
- 5. After the update, the Federation Framework saves the last guery result.

Adapter Interfaces

This section includes the following topics:

- "Definitions and Terms" on the next page
- "Adapter Interfaces for Federated TQL Queries" on the next page

Definitions and Terms

External Relation. The relation between two external CI types that are supported by the same adapter.

Adapter Interfaces for Federated TQL Queries

Use the appropriate adapter interface for each adapter, as follows.

A Single Node topology interface is used when the adapter does not support any external
relations; that is, the adapter is never meant to receive a request with more than one external CI.
The reconciliation data needed to complete the operation can be described as complex query (see
SingleNodeFederationTopologyReconciliationAdapter below).

All SingleNode interfaces are created to simplify the workflow; for those cases where you need to use a more extensive query, use the **FederationTopologyAdapter** interface.

 A FederationTopologyAdapter interface is used to define adapters that support complex federated queries. The reconciliation request in these adapters is part of the QueryDefinition parameter.

The Federation engine uses reconciliation data in order to connect the federated data to the proper local CIs. Reconciliation data may be fetched in more than one request (calculated recursively according to results). In this case, the adapter receives a request with only reconciliation data.

SingleNode Interfaces

The following interfaces have different types of reconciliation data:

- SingleNodeFederationIdReconciliationAdapter. Use if the adapter supports a single-node TQL and the reconciliation between data repositories is calculated by the ID.
- SingleNodeFederationPropertyReconciliationAdapter. Use if the adapter supports a singlenode TQL and the reconciliation between data repositories is done by the properties of one CI.
- SingleNodeFederationTopologyReconciliationAdapter. Use if the adapter supports a singlenode TQL and the reconciliation between data repositories is done by topology. The adapter should support the case where the query element is empty and only reconciliation topology is requested.

Data Adapter Interfaces

• FederationTopologyAdapter. Use this adapter to support complex federated TQL queries. Allows the most diversity. The adapter should support the case where the query definition is describing

only reconciliation data.

- **PopulateDataAdapter.** Use this adapter to support complex federated TQL queries and population flows. In a population flow, this adapter retrieves the entire data set, and lets the probe filter the difference since the last execution of the job.
- PopulateChangesDataAdapter. Use this adapter to support complex federated TQL queries and
 population flows. In a population flow, this adapter supports the retrieval of only the changes that
 occurred since the last execution of the job.

Note: When developing an adapter that may return large data sets of data, its important to allow chunking by implementing the ChunkGetter Interface. See the Java document of the specific adapter for more information.

Resource Reporting Interfaces

The following interfaces enable the adapter to report the resources that can be configured to customize the adapter's behavior. This enables you to edit these resources directly from the Integration Studio. These interfaces should be used in addition to the regular adapter interfaces above.

- **PopulationQueriesResourcesLocator.** Defines which resources may be edited for each specific Population query.
- PushQueriesResourceLocator. Defines which resources may be edited for each Data Push
 query.
- GeneralResourcesLocator. Defines which general resources may be edited in this adapter.

Additional Interfaces

- SortResultDataAdapter. Use if you can sort the resulting CIs in the external data repository.
- Functional Layout Data Adapter. Use if you can calculate the functional layout in the external data repository.

Adapter Interfaces for Synchronization

- **SourceDataAdapter.** Use for source adapters in population flows.
- TargetDataAdapter. Use for target adapters in data push flows.

Debug Adapter Resources

This task describes how to use the JMX console to create, view, and delete adapter state resources (any resources created using the resource manipulation methods in the DataAdapterEnvironment interface, which are saved in the UCMDB database or the Probe database) for debugging and development purposes.

- 1. Launch the Web browser and enter the server address, as follows:
 - For the UCMDB server: https://localhost:8443/jmx-console
 - For the Probe: http://localhost:1977

You may have to log in with a user name and password (default user name: sysadmin).

- 2. To open the JMX MBEAN View page, do one of the following:
 - On the UCMDB server: click
 UCMDB:service=FCMDB Adapter State Resource Services
 - o On the Probe: click type=AdapterStateResources
- 3. Enter values in the operations that you want to use, and click Invoke.

Add an Adapter for a New External Data Source

This task explains how to define an adapter to support a new external data source.

This task includes the following steps:

- "Prerequisites" on the next page
- "Define Valid Relationships for Virtual Relationships" on the next page
- "Define an Adapter Configuration" on page 200
- "Define Supported Classes" on page 204
- "Implement the Adapter" on page 205
- "Define Reconciliation Rules or Implement the Mapping Engine" on page 205
- "Add Jars Required for Implementation to the Class Path" on page 205
- "Deploy the Adapter" on page 205
- "Update the Adapter" on page 206

Prerequisites

Model-supported adapter classes for CIs and relationships in the UCMDB Data Model. As an adapter developer, you should:

- have knowledge of the hierarchy of the UCMDB CI types to understand how external CITs are related to the UCMDB CITs
- model the external CITs in the UCMDB class model
- o add the definitions for new CI types and their relationships
- define valid relationships in the UCMDB class model for the valid relationships between adapter inner classes. (The CITs can be placed at any level of the UCMDB class model tree.)

Modeling should be the same regardless of federation type (on the fly or replication). For details on adding new CIT definitions to the UCMDB class model, see Working with the CI Selector in the HPE Universal CMDB Modeling Guide.

For the adapter to support federated attributes on CITs, add this CIT to the supported classes with supported attributes and the reconciliation rule for this CIT.

2. Define Valid Relationships for Virtual Relationships

Note: This section is only relevant for federation.

To retrieve federated CITs that are connected to local CMDB CITs, a valid link definition must exist between the two CITs in the CMDB.

- a. Create a valid links XML file that contains these links (if they do not already exist).
- b. Add the links XML file to the adapter package in the **\validlinks** folder. For details, see in the *HPE Universal CMDB Administration Guide*.

Example of Valid Relationship Definition:

In the following example, the relation of type containment between instances of type node to instances of type myclass1 is a valid relationship definition.

```
</Valid-Link>
</Valid-Links>
```

3. Define an Adapter Configuration

- a. Navigate to Adapter Management.
- b. Click the Create new resource button and select New Adapter.
- c. In the New adapter dialog box, select Integration and Java Adapter.
- d. Right-click the adapter that you created and select **Edit Adapter Source** from the shortcut menu.
- e. Edit the following XML tags:

```
<pattern xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
id="newAdapterIdName"
xsi:noNamespaceSchemaLocation="../../Patterns.xsd"
description="Adapter Description" schemaVersion="9.0"
displayName="New Adapter Display Name">
<deletable>true</deletable>
<discoveredClasses>
<discoveredClass>link</discoveredClass>
<discoveredClass>object</discoveredClass>
</discoveredClasses>
<taskInfo
className="com.hp.ucmdb.discovery.probe.services.dynamic.core.
AdapterService">
<params</pre>
className="com.hp.ucmdb.discovery.probe.services.dynamic.core.
AdapterServiceParams" enableAging="true"
enableDebugging="false" enableRecording=
"false" autoDeleteOnErrors="success" recordResult="false"
maxThreads="1" patternType="java adapter"
maxThreadRuntime="25200000">
<className>com.yourCompany.adapter.MyAdapter.MyAdapterClass
</className>
```

```
</params>
<destinationInfo
className="com.hp.ucmdb.discovery.probe.tasks.BaseDestinationDa
ta">
<!-- check -->
<destinationData name="adapterId"</pre>
description="">${ADAPTER.adapter_id}</destinationData>
<destinationData name="attributeValues"</pre>
description="">${SOURCE.attribute_values}</destinationData>
<destinationData name="credentialsId"</pre>
description="">${SOURCE.credentials_id}</destinationData>
<destinationData name="destinationId"</pre>
description="">${SOURCE.destination_id}</destinationData>
</destinationInfo>
<resultMechanism isEnabled="true">
<autoDeleteCITs isEnabled="true">
<CIT>link</CIT>
<CIT>object</CIT>
</autoDeleteCITs>
</resultMechanism>
</taskInfo>
<adapterInfo>
<adapter-capabilities>
<support-federated-query>
<!--<supported-classes/> <!-see the section about supported
classes-->
<topology>
<pattern-topology /> <!-or <one-node-topology> -->
```

```
</topology>
</support-federated-query>
<!--<support-replicatioin-data>
<source>
<changes-source/>
</source>
<target/>
</adapter-capabilities>
<default-mapping-engine />
<queries />
<removedAttributes />
<full-population-days-interval>-1</full-population-days-
interval>
</adapterInfo>
<inputClass>destination config</inputClass>
cols />
<parameters>
<!--The description attribute may be written in simple text or
HTML.-->
<!--The host attribute is treated as a special case by UCMDB-->
<!--and will automatically select the probe name (if possible)-
->
<!--according to this attribute's value.-->
<parameter name="credentialsId" description="Special type of</pre>
property, handled by UCMDB for credentials menu" type="integer"
display-name="Credentials ID" mandatory="true" order-index="12"
/>
```

```
<parameter name="host" description="The host name or IP address</pre>
of the remote machine" type="string" display-name="Hostname/IP"
mandatory="false" order-index="10" />
<parameter name="port" description="The remote machine's</pre>
connection port" type="integer" display-name="Port"
mandatory="false" order-index="11" />
</parameters>
<parameter name="myatt" description="is my att true?"</pre>
type="string" display-name="My Att" mandatory="false" order-
index="15" valid-values="True; False"/>True</parameters>
<collectDiscoveredByInfo>true</collectDiscoveredByInfo>
<integration isEnabled="true">
<category >My Category</category>
</integration>
<overrideDomain>${SOURCE.probe name}</overrideDomain>
<inputTQL>
<re><resource:XmlResourceWrapper</re>
xmlns:resource="http://www.hp.com/ucmdb/1-0-
0/ResourceDefinition" xmlns:ns4="http://www.hp.com/ucmdb/1-0-
0/ViewDefinition" xmlns:tql="http://www.hp.com/ucmdb/1-0-
0/TopologyQueryLanguage">
<resource xsi:type="tql:Query" group-id="2" priority="low" is-</pre>
live="true" owner="Input TQL" name="Input TQL">
<tql:node class="adapter config" id="-11" name="ADAPTER" />
<tql:node class="destination_config" id="-10" name="SOURCE" />
<tql:link to="ADAPTER" from="SOURCE" class="fcmdb conf
aggregation" id="-12" name="fcmdb conf aggregation" />
</resource>
</resource:XmlResourceWrapper>
</inputTQL>
```

```
<permissions />
</pattern>
```

For details about the XML tags, see "XML Configuration Tags and Properties" on page 207.

4. Define Supported Classes

Define supported classes either in the adapter code by implementing the *getSupportedClasses()* method, or by using the pattern XML file.

name	The name of the CI type
is-derived	Specifies whether this definition includes all inheriting children
is- reconciliation- supported	Specifies whether this class is used for reconciliation
is-id- reconciliation- supported	Specifies whether this class is used for id-reconciliation
federation-not- supported	Specifies whether this CIT should not be allowed for federation (blocking certain CITs, for example, a CIT defined solely for federation)
<supported-conditions></supported-conditions>	Specifies the supported conditions on each attribute

Implement the Adapter

Select the correct adapter implementation class according to its defined capabilities. The adapter implementation class implements the appropriate interfaces according to defined capabilities.

If the adapter implements **getTopologyWithReconciliationData** and adapter capabilities include the ability to be used as a starting point, the adapter should also support requesting topology with reconciliation data without any conditions (only type). In this case the adapter should return full reconciliation data of the found results.

Adapter reconciliation support can be defined according to **global_id**, in which case **global_id** must be defined as part of the reconciliation attributes in the adapter supported classes. If adapter reconciliation support is defined according to **global_id**, then

getTopologyWithReconciliationData() should return the **global_id** as part of the reconciliation object properties. The UCMDB uses **global_id** for reconciliation of federation results for a CIT instead of the identification rule.

Part of the federation API is the DataAdapterEnvironment interface. This interface represents the environment of the data adapter. It contains the environment API needed for the adapter to work. For more information on the DataAdapterEnvironment interface, see "The DataAdapterEnvironment Interface" on page 210.

6. Define Reconciliation Rules or Implement the Mapping Engine

If your adapter supports federated TQL queries, you have two options for defining your Mapping Engine:

- Use the default mapping engine, which uses the CMDB's internal reconciliation rules for mapping. To use it, leave the <default-mapping-engine> XML tag empty.
- Write your own mapping engine by implementing the mapping engine interface and placing the
 JAR with the rest of the adapter code. To do this, use the following XML tag: <defaultmapping-engine>com.yourcompany.map.MyMappingEngine</default-mappingengine>

7. Add Jars Required for Implementation to the Class Path

To implement your classes, add the **federation_api.jar** file to your code editor class path.

8. Deploy the Adapter

Deploy the adapter package. For general details on deploying a package, see Package Manager in

the HPE Universal CMDB Administration Guide.

The package should contain the following entities:

- New CIT definition (optional):
- Used only if the adapter supports new CI types that do not yet exist in UCMDB.
- The new CIT definitions are located in the class folder in the package.
- New data type definition (optional):
- Used only if the new CITs require new data types.
- The new data type definitions are located in the typedef folder in the package.
- New valid relationships definition (optional):
- Used only if the adapter supports the federated TQL.
- The new valid relationships definitions are located in the validlinks folder in the package.
- The pattern configuration XML file should be located in the discoveryPatterns folder in the package.
- **Descriptor.** Defines the package definitions.
- Place your compiled classes (normally a jar file) in the package under the adapterCode\<adapter id> folder.

Note: The adapter id folder name has the same value as in the adapter configuration.

 If you create your own configuration file, you should place the file in the package under the adapterCode\<adapter id> folder.

9. Update the Adapter

Changes to any of the adapter's non-binary files may be made in the Adapter Management module. Making changes to configuration files in the Adapter management module causes the adapter to reload with the new configurations.

Updates may also be made by editing the files in the package (both binary and non-binary files), and then redeploying the package by using the Package Manager. For details, see "How to Deploy a Package" in the *HPE Universal CMDB Administration Guide*.

Create a Sample Adapter

This example illustrates how to create a sample adapter. This task includes the following steps:

- "Select Adapter Logic" below
- "Load the Project" below

1. Select Adapter Logic

When you implement an adapter, you must choose how to handle the condition logic in the implementation (property conditions, ID conditions, reconciliation conditions, and link conditions).

- a. Retrieve the entire data into the adapter memory and let it select or filter the needed CI Instances.
- b. Convert all the conditions into the data source language and let it filter and select the data. For example:
 - Convert the condition into a SQL query.
 - Convert the condition into a Java API filter object.
- c. Filter some of the data on the remote service, and have the adapter select and filter the remainder.

In the MyAdapter example, the logic in option a is used.

2. Load the Project

Copy the files from the C:\hp\UCMDB\UCMDBServer\tools\
adapter-dev-kit\SampleAdapters folder and follow the instructions in the readme files.

Note: If you use an adapter with large data sets, you may need to use caching and indexing to improve performance for Federation.

Online javadocs documentation is available at:

C:\hp\UCMDB\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\DBAdapterFramework_ JavaAPI\index.html

XML Configuration Tags and Properties

id="newAdapterIdName"	Defines the adapter's real name. Used for logs and folder lookups.
displayName="New Adapter Display Name"	Defines the adapter's display name, as it appears in the UI.

<classname></classname> <category>My Category</category> <parameters></parameters>		Defines the adapter's interface implementing the Java class.
		Defines the adapter's category. Defines the properties for the configuration that are available in the UI when setting up a new integration point.
	description	The display hint of the property.
	type	String or integer (use valid values with string for Boolean).
	display-name	The name of the property in the UI.
	mandatory	Specifies whether this configuration property is mandatory for the user.
	order-index	The placing order of the property (small = up).
	valid-values	A list of possible valid values separated by `;' characters (for example, valid-values="Oracle;SQLServer;MySQL" or valid-values="True;False").
<adapterinfo></adapterinfo>		Contains the definition of the adapter's static settings and capabilities.
	<support-federated-query></support-federated-query>	Defines this adapter as capable of federation.
	<start-point-adapter></start-point-adapter>	Specifies that this adapter is the start point for TQL query calculation.
	<one-node-topology></one-node-topology>	The ability to federated queries with one federated query node.
	<pattern-topology></pattern-topology>	The ability to federate complex queries.
	<support-replicatioin-data></support-replicatioin-data>	Defines the capability to run data push and population flows.
	<source/>	This adapter may be used for population

	flows.
<push-back-ids></push-back-ids>	Push back the global ID of the CI to the global_id column of the table (must be defined in the orm.xml). The behavior can be overridden by implementing the FcmdbPluginPushBackIds plug-in.
<changes-source></changes-source>	This adapter may be used for population changes flows.
<instance-based-data></instance-based-data>	This tag defines that the adapter supports an instance based population flow.
<target></target>	This adapter may be used for data push flows.
<default-mapping-engine></default-mapping-engine>	Allows defining a mapping engine for the adapter (by default, the adapter uses the default mapping engine). For any other mapping engine, enter the implementing class name of the mapping engine
<removedattributes></removedattributes>	Forces the removal of specific attributes from the result.
<full-population-days- interval></full-population-days- 	Specifies when to execute a full population job instead of a differential job (every `x' days). Uses the aging mechanism together with the changes flow.
<adapter-settings></adapter-settings>	The list of settings of the adapter.
list.attributes.for.set>	Determines which attributes override the previous value (if one exists).

The DataAdapterEnvironment Interface

OutputStream openResourceForWriting(String resourceName) throws FileNotFoundException;

This method opens a resource with a given name for writing. It is used for saving persistent data for the integration. This method should be used instead of trying to load files using java methods. The user should ensure that the stream is closed when finished writing to the stream. close()/flush() will save the resource. This method creates a runtime resource (it may not overwrite files that came in the adapter package).

Parameter

resourceName: The name of the resource to retrieve. This name should be unique across all
integrations of the same adapter.

Return Value

Returns a stream to which to write.

Exceptions

- This method throws the FileNotFoundException if the resource type is file and the file does not
 exist, if the resource is a directory rather than a regular file, or for some other reason the resource
 cannot be opened for reading.
- This method throws the SecurityException if a security manager exists and its checkRead method denies access to the file.

InputStream openResourceForReading(String resourceName) throws FileNotFoundException;

This method opens a resource with a given name for reading. It is used for reading persistent data for the integration. This method should be used instead of trying to load a file using java methods. The user should ensure that the stream is closed when finished reading it. It first attempts to load files that came in the adapter package. If not found, it attempts to load a runtime created resource from <code>DataAdapterEnvironment.openResourceForWriting(String)</code>. The runtime resources can be viewed using JMX (of the probe and server accordingly).

Parameter

• **resourceName:** The name of the resource to retrieve. This name should be unique across all integrations of the same adapter.

Return Value

Returns a stream to read.

Exceptions

- This method throws the FileNotFoundException if the resource type is file and the file does not
 exist, if the resource is a directory rather than a regular file, or for some other reason the resource
 cannot be opened for reading.
- This method throws the SecurityException if a security manager exists and its checkRead method denies read access to the file.

Properties openResourceAsProperties(String propertiesFile) throws IOException;

This method opens a resource with a given name and loads it as a *Properties* structure. It is used for reading persistent data for the integration. This method should be used instead of attempting to load the **.properties** files using java methods. It first attempts to load files that came in the adapter package. If not found, it attempts to load a runtime created resource from

DataAdapterEnvironment.openResourceForWriting(String). The runtime resources can be viewed using JMX (of the probe and server accordingly).

Parameter

• **propertiesFile:** The name of the resource to retrieve. This name should be unique across all integrations of the same adapter.

Return Value

Returns the file content represented in Properties.

Exceptions

- This method throws the FileNotFoundException if the resource type is file and the file does not
 exist, if the resource is a directory rather than a regular file, or for some other reason the resource
 cannot be opened for reading.
- This method throws the *SecurityException* if a security manager exists and its *checkRead* method denies read access to the file.
- This method throws the IOException if the properties file failed to convert to the Properties Object.

String openResourceAsString(String resourceName) throws IOException;

This method opens a resource with a given name and loads it as a string. It is used for reading persistent data for the integration. This method should be used instead of trying to load files using java methods.

It first attempts to load files that came in the adapter package. If not found, it attempts to load a runtime created resource from *DataAdapterEnvironment.openResourceForWriting(String)*. The runtime resources can be viewed using JMX (of the probe and server accordingly).

Parameter

resourceName: The name of resource to retrieve. This name should be unique across all
integrations of the same adapter.

Return Value

Returns the file content represented in String format.

Exceptions

- This method throws the FileNotFoundException if the resource type is file and the file does not
 exist, if the resource is a directory rather than a regular file, or for some other reason the resource
 cannot be opened for reading.
- This method throws the SecurityException if a security manager exists and its checkRead method denies read access to the file.
- This method throws the *IOException* if an I/O error occurs.

public void saveResourceFromString(String relativeFileName, String value) throws IOException;

This method receives a String and saves it as a resource. It is used for saving persistent data for the integration. This method should be used instead of trying to save files using java methods. This method converts the String into a stream and saves it to the resource. It creates a runtime resource, but cannot overwrite files that came in the adapter package). The runtime resources can be viewed using JMX (of the probe and server accordingly).

Parameter

- **relativeFileName:** The name of resource to retrieve. This name should be unique across all integrations of the same adapter.
- · value: The String to save as a resource

Exceptions

This method throws the IOException if an I/O error occurs.

boolean resourceExists(String resourceName);

This method checks if the given resource name exists. It looks for files that came in the adapter package and for runtime created resources from *DataAdapterEnvironment.openResourceForWriting* (String).

Parameter

resourceName: The name of the resource to retrieve. This name should be unique across all
integrations of the same adapter.

Return Value

Returns True if resourceName exists.

boolean deleteResource(String resourceName);

This method deletes the given resource from persistent data. It deletes a runtime resource, and may not delete files that came in the adapter package. The runtime resources can be viewed using JMX (for the probe and server accordingly).

Parameter

• **resourceName:** The name of the resource to delete. This name should be unique across all integrations of the same adapter.

Return Value

Returns True if the resource is successfully deleted.

Collection < String > listResourcesInPath(String path);

This method retrieves a list of resources in the given resource path. It looks for files that came in the adapter package and for a runtime created resources from

Chapter 6: Developing Java Adapters

DataAdapterEnvironment.openResourceForWriting(String). The runtime resources can be viewed using JMX (for the probe and server accordingly).

Parameter

path: The resource path. For example, "META-INF/myfiles/"

Return Value

Return a list of resources in the path.

DataAdapterLogger getLogger();

Retrieves the logger to be used by the adapter. This logger is used for logging events in your adapter.

Return Value

Returns the logger that is used by the DataAdapter.

DestinationConfig getDestinationConfig();

This method retrieves the destination configuration of the integration. This configuration holds all connection and running settings for the integration.

Return Value

Returns the DestinationConfig of the Adapter.

int getChunkSize();

This method retrieves the population chunk size requested for this integration.

Return Value

Returns the population chunk size.

int getPushChunkSize();

This method retrieves the push chunk size requested for this integration.

Return Value

Returns the push chunk size.

ClassModel getLocalClassModel();

This method retrieves a class model for querying information about the local UCMDB's class model. This method brings an updated ClassModel. Once the ClassModel object is returned, it is not updated for any class model changes. In order to retrieve an updated class model, use this method again to retrieve it.

Return Value

Returns the UCMDB's class model.

CustomerInformation getLocalCustomerInformation();

This method retrieves customer information for the customer that is executing the adapter.

Return Value

Returns customer information for the customer that is executing the adapter.

Object getSettingValue(String name);

This method retrieves a specific adapter setting.

Parameter

name: The name of setting.

Return Value

Returns the Object setting value.

Map<String, Object> getAllSettings();

This method retrieves all adapter settings.

Return Value

Returns the adapter settings.

boolean isMTEnabled();

This method checks if the server environment supports Multiple Tenancy (MT).

Return Value

Returns **true** if the server environment supports MT, otherwise returns **false**.

String getUcmdbServerHostName();

This method returns the local UCMDB server host name.

Return Value

Returns the local UCMDB server host name.

Chapter 7: Developing Push Adapters

This chapter includes:

Developing and Deploying Push Adapters	217
Build an Adapter Package	218
Create Mappings	222
Write Jython Scripts	225
Support Differential Synchronization	230
Generic XML Push Adapter SQL Queries	232
Generic Web Service Push Adapter	232
Mapping File Reference	252
Mapping File Schema	254
Mapping Results Schema	264
Customization	267

Developing and Deploying Push Adapters

Generic Push Adapters provide a common platform that enables rapid development of integrations that push UCMDB data to external data repositories (databases and third-party applications). Generic Push Adapters are categorized according to the protocol used to push the data. For details on pushing via XML, using the Generic XML Push Adapter, see "Generic XML Push Adapter SQL Queries" on page 232. For details on pushing via Web Service, using the Generic Web Service Push Adapter, see "Generic Web Service Push Adapter" on page 232.

Developing a custom integration based on a Generic Push Adapter requires:

- Building a new adapter package from the appropriate Generic Push Adapter template files. For details, see "Build an Adapter Package" on the next page.
- Mappings between the UCMDB CI link types and the external data items. The mappings are stored
 as XML and are customized to each external data repository. For details, see "Create Mappings" on
 page 222.

- A Jython script to push the data items into the external data repository. For details, see "Write Jython Scripts" on page 225.
- Additional adapter-specific steps. For example, choosing the path of the file to be written for the XML push adapter, or creating a data receiver for the Web Service push adapter.

Build an Adapter Package

To create a new, MDR-specific push adapter, you should make a copy of the generic adapter and then edit it to customize it as an adapter for a specific push target.

Generic adapters packages can be found in one of the following two locations:

- Generic XML push adapter: hp\UCMDB\UCMDBServer\content\adapters\push-adapter.zip
- Generic web service adapter: hp\UCMDB\UCMDBServer\content\adapters\web-service-push-adapter.zip

To create a new push adapter from the generic push adapter:

- 1. Extract the content of the selected package zip file to a work folder.
- Review the following directories in preparation for the rename and replace phase:
 - adapterCode: Contains the directory that is deployed to the
 C:\hp\UCMDB\UCMDBServer\runtime\fcmdb\CodeBase directory. Jars deployed here do not automatically restart the probe and do not appear automatically in the probe's
 CLASSPATH.
 - discoveryConfigFiles: Contains the adapter's mappings definitions and points to the correct Jython script (push.properties)
 - discoveryPatterns: Contains the adapter's XML definition that is deployed on the UCMDB server
 - discoveryScripts: Contains the adapter's Jython scripts via which the connection to the third party data store is made and data is pushed
 - discoveryResources: Contains the UCMDBDataReceiver.jar containing the Java integration classes for the web service.

Note: When you deploy this package, the probe is restarted to include this **.jar** in the probe's CLASSPATH. No action is required beyond deploying the package.

Make the following changes within the unzipped adapter directory structure:

- a. discoveryConfigFiles\<Your_Push_Adapter_Name>: rename the directory "PushAdapter"
 or "XMLtoWebService" to the name of the new push adapter (for example, "myPushAdapter").
- b. discoveryConfigFiles\<Your_Push_Adapter_Name>\push.properties: In the push.properties file, do the following:
 - Update the name of **jythonScript.name** to the name of the Jython script to be used by the new push adapter (for example, **pushToMyService.py**).
 - Update the name of the mappings file to be used by the new push adapter (for example, myPushAdapter_mappings). Do no add the .xml extension, this is filled in automatically.
- c. discoveryPatterns\<push adapter name>.xml: Rename this file to the name of the new adapter's definition XML file (for example, my_push_adapter.xml).
- d. discoveryPatterns\<your_push_adapter>.xml: Update this file as follows:
 - For the XML element <pattern>: set the id and description attributes accordingly. For example:

```
<pattern id="PushAdapter"
xsi:noNamespaceSchemaLocation="../../Patterns.xsd" description="Discovery
Pattern Description" schemaVersion="9.0"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
is changed to:
<pattern id="MyPushAdapter" displayLabel="My Push Adapter"
xsi:noNamespaceSchemaLocation="../../Patterns.xsd" description="Discovery
Pattern Description" schemaVersion="9.0"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
```

- For the XML element parameters>: update the children elements according to the needs
 of your adapter. By default, the following children elements are used to define a push
 adapter. These values are assigned when the integration point is defined in the Integration
 Studio after the adapter is configured. Update the parameter list so that the list of
 parameters reflects the required connection attributes. Do not remove the probeName
 attribute.
 - host: the server name hosting the web service
 - port: port of the listening UCMDB Data Receiver service
 - Web Service Push Adapter: uri the remainder of the URL to form the service endpoint address of the data receiver.
 - probeName: defines on which data flow probe the push job runs

- For the XML element **<integration>**: update the value of the child element **<category>** to something other than Generic. By default integration adapters belonging to the Generic category are not shown in the Integration Studio. If you are integrating with a third-party data store, set this value to "Third Party". If you are integrating with an HPE BTO product, set this value to "HP BTO Products".
- e. **adapterCode\PushAdapter:** rename this folder with the adapter ID used in the previous step (for example, **adapterCode\MyPushAdapter**).
- f. discoveryScripts\<your_Jython_push_script>.py: create a file with the same name as the one defined in the push.properties jythonScript.name property. In the discoveryScript file, there is a script that inserts the CIs and links to an external Oracle database. Replace discoveryScripts\pushScript.py with the script you wrote (for details, see "Write Jython Scripts" on page 225). If you rename the script, the jythonScript.name property in adapterCode\<adapter ID>\push.properties should be updated accordingly.
 - XML Push Adapter: pushScript.py
 - Web Service Push Adapter: XMLtoWebService.py
- g. tql\<your_integration_TQLs>: like a regular package, place the TQL XML definition of your integration TQLs in this directory. All TQLs in this folder are deployed when the adapter package is deployed.
- h. discoveryConfigFiles\<Your_Push_Adapter_Name>\mappings: create an XML mapping file per TQL that you want to use in your integration. Note that the push adapter applies the transformations in the mapping file to the results of the integration TQLs and then sends that data in three parameters (addResult, updateResult, and deleteResult) of an ad hoc task to the data flow probe.
- adapterCode\<adapter ID>\mappings: replace the mappings.xml file with the mapping files you prepared (for details, see "Create Mappings" on page 222).
 - XML Push Adapter: This mapping example corresponds to the example of the tables created in ORACLE in the sql_queries file.
 - To use a mapping file for each TQL method, assign the name of the corresponding TQL to each XML file, followed by .xml. In this case, the mappings.xml file is used as by default, if no specific mapping file is found for the current TQL name. The name of the default mapping file can be modified by changing the mappingFile.default property in adapterCode\<adapter ID>\push.properties.
- 4. After making all the above changes, create a .zip file by selecting the folders and files specified in step 3 above (for example, my_Push_Adapter.zip).

- 5. Deploy the newly created .zip file on the UCMDB server via the Package Manager (go to Administration > Package Manager).
- 6. Create an integration point in **Data Flow Management > Integration Studio** and define the integration TQLs that the integration point uses. Set a schedule for automatic data push.

Troubleshooting

The procedure for building a new push adapter requires complete and correct re-naming and replacing. Any error will likely affect the adapter. The package must be unzipped and re-zipped correctly to act as a UCMDB package. Refer to the out-of-the-box packages as examples. Common errors include:

- Including another directory on top of the package directories in the ZIP file.
 - **Solution:** ZIP the package in the same directory as the package directories such as **discoveryResources**, **adapterCode**, etc. Do not include another directory level on top of this in the ZIP file.
- Omitting a critical re-name of a directory, a file, or a string in a file.
 - **Solution:** Following the instructions in this section very carefully.
- Misspelling a critical re-name of a directory, a file, or string in a file.
 - **Solution:** Do not change your naming convention in mid-stream once you begin the re-naming procedure. If you realize that you need to change the name, start over completely rather than trying to retroactively correcting the name, as there is a high risk of error. Also, use search and replace rather than manually replacing strings to reduce risk of errors.
- Deploying adapters with the same file names as other adapters, especially in the discoveryResources and adapterCode directories.

Solution: You may be using a UCMDB version with a known issue that prevents mappings files from having the same name as any other adapter in the same UCMDB environment. If you attempt to deploy a package with duplicates names, the package deployment will fail. This problem may occur even if these files are in different directories. Further, this problem can occur regardless of whether the duplicates are within the package or with other previously deployed packages.

At this point you can create a new push adapter job in the Integration Studio using the new adapter you just deployed.

TQL Best Practices for Push Adapters

- 1. Create a folder structure in the TQL and View trees, and keep all new TQLs and views there. Use a naming convention.
- 2. Unless the TQL is small, first copy the most similar TQL.
- Make one change at a time. Save, test, and preview after each change. Repeat until the results comply with your requirements.

Create Mappings

The raw TQL result data is in the form of the UCMDB class model schema. It is likely that the consumer uses a different data model. The push adapter provides a mapping mechanism to transform the data into a format more suitable for consumption. Mappings perform both direct and complex transformations, from direct, naming-type conversion, to parent/child aggregation and referencing functions.

The mapping specification can be found in the section "Mapping File Reference" on page 252. Use the reference to create a mapping file.

Note: The adapter properties file refers to the name of the mapping file. In adapter configuration files, the adapter implements a folder structure using the name of the adapter. Rename this folder when implementing an adapter to maintain uniqueness as required by the Package Manager.

Build a Mapping File

- 1. Start with a default mapping file.
- 2. Deploy the adapter and run it once.
- 3. Observe the results.
- 4. Identify and note what should be changed.
- 5. Make the changes identified in the previous step. The following list can help serve as a guide for the order of the changes.
 - a. Start with the top, non-transformative section. Make sure the adapter runs after each change.
 - b. Change the source CIs section to the UCMDB names in the TQL result.
 - c. First map the keys.

- d. Then add all the direct mappings.
- e. Add the complex mappings.
- f. Add the link mappings.

Repeat steps 2-5 until the mapped data is suitable for consumption. Select the appropriate Generic adapter package from which to create the new push adapter.

The mapping files work the same way for all types of push adapters. The Generic XML push adapter writes the mapped results to a file. The Generic Web Service Push Adapter sends the XML results to a data receiver. For more details, see "Generic Web Service Push Adapter" on page 232.

Prepare the Mapping Files

Note: You can retrieve all of the CIs and relationships as they are in the CMDB without mapping, by not creating the **mappings.xml** file. This returns all of the CIs and relationships with all of their attributes.

There are two different ways to prepare mapping files:

• You can prepare a single, global mapping file.

All mappings are placed in a single file named **mappings.xml**.

You can prepare a separate file for each push query.

Each mapping file is called **<query name>.xml**.

For details, see "Mapping File Schema" on page 254.

This task includes the following steps:

- "Create a mappings.xml File" below
- "Map CIs" on the next page
- "Map Links" on page 225
- 1. Create a mappings.xml File

The mapping file structure is created as follows (use an existing file as a template):

```
<?xml version="1.0" encoding="UTF-8"?>
<integration>
```

2. Map Cls

There are two ways to map CMDB CI types:

• Map a CI type so that CIs of that type and all inherited types are mapped in the same way:

 Map a CI type so that only CIs of that type are processed. CIs of inherited types are not processed unless their type is also mapped (in one of the two ways):

```
</target_ci_type>
</source_ci_type>
```

A CI type which is mapped indirectly (one of its ancestors is mapped using **source_ci_type_tree**), can also override its parent's map by having it appear in its own **source_ci_type_tree** or **source_ci_type**.

It is recommended to use **source_ci_type_tree** wherever possible. Otherwise, resulting CIs of a CI type that do not appear in the mapping files will not be transferred to the Jython script.

3. Map Links

There are two ways to map links:

Map a link so that links of that type and all inherited links are mapped in the same way:

 Map a link so that only links of that type are processed. Links of inherited types are not processed unless their type is also mapped (in one of the two ways):

Write Jython Scripts

The mapping script is a regular Jython script, and should follow the rules for Jython scripts. For details, see "Developing Jython Adapters" on page 45.

The script should contain the **DiscoveryMain** function, which may return either an empty **OSHVResult** or a **DataPushResults** instance upon success.

To report any failure, the script should raise an exception, for example:

```
raise Exception('Failed to insert to remote UCMDB using TopologyUpdateService. See log of the remote UCMDB')
```

In the DiscoveryMain function, the data items to be pushed to or deleted from the external application can be obtained as follows:

```
# get add/update/delete result objects (in XML format) from the Framework
addResult = Framework.getTriggerCIData('addResult')
updateResult = Framework.getTriggerCIData('updateResult')
deleteResult = Framework.getTriggerCIData('deleteResult')
```

The client object to the external application can be obtained as follows:

```
oracleClient = Framework.createClient()
```

This client object automatically uses the credentials ID, host name and port number passed by the adapter through the Framework.

If you need to use the connection parameters that you defined for the adapter (for details, see the step on editing the **discoveryPatterns\push_adapter.xml** file in "Build an Adapter Package" on page 218), use the following code:

```
propValue = str(Framework.getDestinationAttribute('<Connection Property Name'))
For example:</pre>
```

```
serverName = Framework.getDestinationAttribute('ip_address')
```

This section also includes:

- "Working with the Mapping's Results" below
- "Handling Test Connection in the Script" on page 229

Working with the Mapping's Results

Generic push adapters create XML strings that describe the data to be added, updated, or deleted from the target system. The Jython script needs to analyze this XML, and then performs the add, update, or delete operation on the target.

In the XML of the add operation that the Jython script receives, the mamId attribute for the objects and links is always the UCMDB identifier of the original object or link before its type, attribute, or other information was changed to the schema of the remote system.

In the XML of the update or remove operations, the mamId attribute of each object or link contains the string representation of the same ExternalId that was returned from the Jython script from the previous synchronization.

In the XML, the id attribute of a CI holds the cmdbId as an external id or the ExternalId of that CI if the CI got an ExternalId one when the CI was sent to the script. The end1Id and end2Id fields of the link hold for each of the link's ends the cmdbId as an external id or the ExternalId of that link's end if the CI at the link's end got an ExternalId when it was sent to the script.

When processing the CIs in the Jython script, the return value of the script is a mapping between the CI's CMDB id and the given id (the id given to each CI in the script). If a CI is pushed for the first time, the id that is in the XML of that CI is the CMDB id. If a CI is not pushed for the first time, the CI's id is the same id that was given to that CI in the script when it was first pushed.

The id is retrieved from the CI XML script as follows:

- From the CI Element in the XML, retrieve the id from the id attribute. For example: id = objectElement.getAttributeValue('id').
- 2. After retrieving the id from the XML, restore the id from the attribute (string). For example: objectId = CmdbObjectID.Factory.restoreObjectID(id).
- 3. Check if the objectId received in the previous step is the CMDB id. You can do this by checking if the objectId has the new id that is given to it by the script. If it does, the returned id is not the CMDB id. For example:

```
newId = objectId.getPropertyValue(<the name of the id attribute which is given
by the script>).
```

If newId is null, then the id that was returned in the XML is a CMDB id.

- 4. If the id is a CMDB id (that is, newId is null), perform the following (if the id is not a CMDB id, go to step 5):
 - a. Create a property for that CI that holds the new id. For example: propArray = [TypesFactory.createProperty('<the name of the id attribute which is given by the script>', '<new id>')].
 - b. Create an externalId to that CI. For example:

```
cmdbId = extI.getPropertyValue('internal_id')
className = extI.getType()
externalId = ExternalIdFactory.createExternalCiId(className, propArray)
```

- c. Map the CMDB id to the newly created externalId (and in the next step return that mapping to the adapter). For example: objectMappings.put(cmdbId, externalId)
- d. When all of the CIs and links are mapped:updateResult = DataPushResultsFactory.createDataPushResults(objectMappings,

```
linkMappings);
return updateResult
```

5. If the id is the new id (that is, newId is not null), then the externalId is the newId.

It is also possible to report on the push status for each CI and link as follows:

- updateStatus = ReplicationActionDataFactory.createUpdateStatus();
 where updateStatus is an instance of the UpdateStatus class that contains statuses of the CIs and links.
- 2. Add a status to updateStatus by calling the reportCIStatus or reportRelationStatus method.

For example:

```
status = ReplicationActionDataFactory.createStatus(Severity.FAILURE, 'Failed',
ERROR_CODE_CI, errorParams,Action.ADD);
updateStatus.reportCIStatus(externalId, status);
```

Where ERROR_CODE_CI is the number of the error messages as they appear in adapter properties.errors file (for details on the properties.errors file, see "Error-Writing Conventions" on page 74), and errorParams contains the parameters to pass to the message. See ReplicationActionDataFactory javadoc for more details.

3. Create a push result with the statuses as follows:

```
updateResult = DataPushResultsFactory.createDataPushResults(objectMappings,
linkMappings, updateStatus);
return updateResult
```

Example of the XML result

```
</objects>
    ks>
        <link targetRelationshipClass="TALK" targetParent="unix" targetChild="unix"</pre>
operation="add" mode="update_else_insert"
mamId="265e985c6ec51a8543f461b30fa58f81"
id="end1id%5BHiddenRmiDataSource%0Aunix%0A1%0Ainternal
id%3DSTRING%3D41372a1cbcaba27b214b84a2ec9eb535%0A%5D%0Aend2id%
5BHiddenRmiDataSource%0Aunix%0A1%0Ainternal
id%3DSTRING%3D0c82f591bc3a584121b0b85efd90b174%0A%5D%0AHiddenRmi
DataSource%OAtalk%OA1%OAinternal
id%3DSTRING%3D265e985c6ec51a8543f461b30fa58f81%0A">
        <field name="DiscoveryID1">41372a1cbcaba27b214b84a2ec9eb535</field>
        <field name="DiscoveryID2">0c82f591bc3a584121b0b85efd90b174</field>
        <field name="end1Id">HiddenRmiDataSource%0Aunix%0A1%0Ainternal
id%3DSTRING%3D41372a1cbcaba27b214b84a2ec9eb535%0A</field>
        <field name="end2Id">HiddenRmiDataSource%0Aunix%0A1%0Ainternal
id%3DSTRING%3D0c82f591bc3a584121b0b85efd90b174%0A</field>
        <field name="NAME" key="false" datatype="char" length="255">TALK4</field>
        <field name="DATA_NOTE" key="false" datatype="char" length="255"></field>
        </link>
    </links>
  </data>
</root>
```

Note: If datatype="BYTE", the returned result's value is a **String** that is generated as: new String([the byte array attribute]). The byte[] object can be reconstructed by: <the received String>.getBytes(). If there are differences in the default locale between the server and the probe, the reconstruction is performed according to the server's default locale.

Handling Test Connection in the Script

A Jython script can be invoked to test the connection with an external application. In this case, the testConnection destination attribute will be true. This attribute can be obtained from the Framework as follows:

```
testConnection = Framework.getTriggerCIData('testConnection')
```

When run in test connection mode, a script should raise an exception if a connection to the external application cannot be established. Otherwise, if the connection is successful, the **DiscoveryMain** function should return an empty **OSHVResult**.

Support Differential Synchronization

For the Push adapter to support differential synchronization, the **DiscoveryMain** function must return an object implementing the **DataPushResults** interface, which contains the mappings between the IDs that the Jython script receives from the XML and the IDs that the Jython script creates on the remote machine. The latter IDs are of the type **Externalld**.

The **ExternalIdUtil.restoreExternal** command, which receives the ID of the CI in the CMDB as a parameter, restores the external ID from the ID of the CI in the CMDB. This command can be used, for example, while performing differential synchronization, and a link is received where one of its ends is not in the bulk (it was already synchronized).

If the **DiscoveryMain** method in the Jython script on which the Push adapter is based returns an empty **ObjectStateHolderVector** instance, the adapter will not support differential synchronization. This means that even when a differential synchronization job is run, in actuality, a full synchronization is being performed. Therefore, no data can be updated or removed on the remote system, since all data is added to the CMDB during each synchronization.

Important: If you are implementing differential synchronization on an existing adapter that was created in version 9.00 or 9.01, you must use the push-adapter.zip file from version 9.02 or later to recreate your adapter package. For details, see "Build an Adapter Package" on page 218.

This task enables the Push adapter to perform differential synchronization.

The Jython script returns the **DataPushResults** object which contains two Java maps - one for object ID mappings (keys and values are ExternalCild type objects) and one for link IDs (keys and values are ExternalRelationId type objects).

• Add the following **from** statements to your Jython script:

```
from com.hp.ucmdb.federationspi.data.query.types import ExternalIdFactory from com.hp.ucmdb.adapters.push import DataPushResults from com.hp.ucmdb.adapters.push import DataPushResultsFactory from com.mercury.topaz.cmdb.server.fcmdb.spi.data.query.types import ExternalIdUtil
```

• Use the DataPushResultsFactory factory class to obtain the DataPushResults object from the

DiscoveryMain function.

```
# Create the UpdateResult object
updateResult = DataPushResultsFactory.createDataPushResults(objectMappings,
linkMappings);
```

• Use the following commands to create Java maps for the **DataPushResults** object:

```
#Prepare the maps to store the mappings if IDs
objectMappings = HashMap()
linkMappings = HashMap()
```

- Use the ExternalIdFactory class to create the following ExternalId IDs:
 - ExternalId for objects or links originating in a CMDB (for example, all of the CIs in an add operation are from the CMDB):

```
externaCIlId = ExternalIdFactory.createExternalCmdbCiId(ciType, ciIDAsString)
externalRelationId = ExternalIdFactory.createExternalCmdbRelationId(linkType,
end1ExternalCIId,
end2ExternalCIId, linkIDAsString)
```

 ExternalId for objects or links not originating in a CMDB (usually, every update and remove operation contains such objects):

```
myIDField = TypesFactory.createProperty("systemID", "1")
myExternalId = ExternalIdFactory.createExternalCiId(type, myIDField)
```

Note: If the Jython script updated existing information and the ID of the object (or link) changes, you must return a mapping between the previous external ID and the new one.

- Use the restoreCmdbCiIDString or restoreCmdbRelationIDString methods from the ExternalIdFactory class to retrieve the UCMDB ID string from an External ID of an object or link that originated in UCMDB.
- Use the restoreExternalCild and restoreExternalRelationId methods from the ExternalIdUtil
 class to restore the ExternalId object from the mamId attribute value of the XML of the update or
 remove operations.

Note: Externalld objects are actually an array of properties. This means that you can use an **Externalld** object to store any information you may need that will identify the data on the remote system.

Generic XML Push Adapter SQL Queries

In the adapter package, the **sql_queries** file located in **adapterCode > PushAdapter > sqlTablesCreation**, contains the queries needed to create tables in a new schema in Oracle for testing the adapter. The tables correspond to the adapterCode\<adapter ID>\mappings\mappings.xml file.

Note: The **sql_queries** file is not needed for the adapter. It is only an example.


Generic Web Service Push Adapter

The generic web service push adapter provides a UCMDB-initiated push of SOAP messages containing query data to a web service data receiver. The mapped results are sent in standard SOAP messages via the HTTP POST protocol to the data receiver. The data receiver must understand the SOAP messages produced by the push adapter. To facilitate the development of the proper data receiver, a WSDL is provided with this push adapter.


Custom processing of the SOAP message response XML is possible in the Jython script.

To understand the format of the incoming mapped data, the developer of the data receiver should communicate with the developer of the mappings file. An **.xsd** is currently not provided with this version of the web service push adapter, so data must be processed in a way reflective of the incoming data, which is a combination of the original TQL and the applied mappings.

The web service push adapter functions for pushing data to the client are shown below. The items in green are customized or supplied by the client to implement the adapter for a specific push target. The items in blue are out-of-the-box components.




An example of an implementation of the generic web service push adapter to an MDR-specific push adapter using an Enterprise Service Bus (ESB) is shown here:



WSDL

A WSDL is supplied to the client developer to create a data receiver capable of communicating with the UCMDB push adapter via a web service. The **UCMDBDataReceiver.wsdl** describes the SOAP messages that are used to communicate data from UCMDB to the data receiver. The design diagram from the WSDL is shown here:



The data receiver (which is in practice a server or "service endpoint" in SOAP terminology) should implement three methods: **addData**, **deleteData**, and **updateData**, corresponding to the data sets that the UCMDB pushes. The HTTP headers contain the correct **SoapAction** keyword that indicates the type of data that is being sent. The data receiver is responsible for implementing the business logic and processing the data.

The default WSDL URL is:

• http://localhost:8080/UCMDBDataReceiver/services/UCMDBDataReceiver?wsdl

As implemented by the Data Receiver, the URL could look similar to the following:

http://testWSPAserver:4444/MyCo.IT.SvcMgt.ws.us:provider/UCMDBDataReceiver?wsdl

The URL of the web service is the same as the WSDL URL without the "?wsdl" at the end.

The source for the WSDL is included below:

```
<?xml version="1.0" encoding="UTF-8"?>
<wsdl:definitions targetNamespace="http://ucmdb.hp.com"</pre>
xmlns:apachesoap="http://xml.apache.org/xml-soap"
xmlns:impl="http://ucmdb.hp.com" xmlns:intf="http://ucmdb.hp.com"
xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/"
xmlns:wsdlsoap="http://schemas.xmlsoap.org/wsdl/soap/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema">
<!--WSDL created by Apache Axis version: 1.4 Built on Apr 22, 2006 (06:55:48
PDT)-->
    <wsdl:types>
         <schema elementFormDefault="qualified"</pre>
         targetNamespace="http://ucmdb.hp.com"
         xmlns="http://www.w3.org/2001/XMLSchema">
             <element name="addData">
                 <complexType>
                      <sequence>
                      <element name="xmlAdded" type="xsd:string"/>
                      </sequence>
                 </complexType>
             </element>
             <element name="addDataResponse">
                 <complexType/>
             </element>
             <element name="deleteData">
                 <complexType>
                      <sequence>
                      <element name="xmlDeleted" type="xsd:string"/>
```

```
</sequence>
             </complexType>
        </element>
        <element name="deleteDataResponse">
             <complexType/>
        </element>
        <element name="updateData">
             <complexType>
                 <sequence>
                 <element name="xmlUpdate" type="xsd:string"/>
                 </sequence>
             </complexType>
        </element>
        <element name="updateDataResponse">
             <complexType/>
        </element>
    </schema>
</wsdl:types>
<wsdl:message name="addDataRequest">
    <wsdl:part element="impl:addData" name="parameters">
    </wsdl:part>
</wsdl:message>
<wsdl:message name="deleteDataResponse">
    <wsdl:part element="impl:deleteDataResponse" name="parameters">
    </wsdl:part>
</wsdl:message>
<wsdl:message name="updateDataResponse">
    <wsdl:part element="impl:updateDataResponse" name="parameters">
    </wsdl:part>
</wsdl:message>
```

```
<wsdl:message name="deleteDataRequest">
    <wsdl:part element="impl:deleteData" name="parameters">
    </wsdl:part>
</wsdl:message>
<wsdl:message name="addDataResponse">
    <wsdl:part element="impl:addDataResponse" name="parameters">
    </wsdl:part>
</wsdl:message>
<wsdl:message name="updateDataRequest">
    <wsdl:part element="impl:updateData" name="parameters">
    </wsdl:part>
</wsdl:message>
<wsdl:portType name="UCMDBDataReceiver">
    <wsdl:operation name="addData">
        <wsdlsoap:operation soapAction="addDataRequest"/>
        <wsdl:input message="impl:addDataRequest" name="addDataRequest">
        </wsdl:input>
        <wsdl:output message="impl:addDataResponse" name="addDataResponse">
        </wsdl:output>
    </wsdl:operation>
    <wsdl:operation name="deleteData">
        <wsdlsoap:operation soapAction="deleteDataRequest"/>
        <wsdl:input message="impl:deleteDataRequest"</pre>
        name="deleteDataRequest">
        </wsdl:input>
        <wsdl:output message="impl:deleteDataResponse"</pre>
        name="deleteDataResponse">
        </wsdl:output>
    </wsdl:operation>
    <wsdl:operation name="updateData">
        <wsdlsoap:operation soapAction="updateDataRequest"/>
```

```
<wsdl:input message="impl:updateDataRequest"</pre>
         name="updateDataRequest">
         </wsdl:input>
         <wsdl:output message="impl:updateDataResponse"</pre>
         name="updateDataResponse">
         </wsdl:output>
    </wsdl:operation>
</wsdl:portType>
<wsdl:binding name="UCMDBDataReceiverSoapBinding"</pre>
type="impl:UCMDBDataReceiver">
    <wsdlsoap:binding style="document"</pre>
    transport="http://schemas.xmlsoap.org/soap/http" />
    <wsdl:operation name="addData">
         <wsdl:input name="addDataRequest">
             <wsdlsoap:body use="literal" />
         </wsdl:input>
         <wsdl:output name="addDataResponse">
             <wsdlsoap:body use="literal" />
         </wsdl:output>
    </wsdl:operation>
    <wsdl:operation name="deleteData">
         <wsdl:input name="deleteDataRequest">
             <wsdlsoap:body use="literal" />
         </wsdl:input>
         <wsdl:output name="deleteDataResponse">
             <wsdlsoap:body use="literal" />
         </wsdl:output>
    </wsdl:operation>
    <wsdl:operation name="updateData">
         <wsdl:input name="updateDataRequest">
             <wsdlsoap:body use="literal" />
         </wsdl:input>
```

Response Handling

The data receiver should return a string in the addDataResponse, deleteDataResponse, or updateDataResponse structures. The adapter passes the response data unprocessed to the probe's probeMgr-adaptersDebug.log. The receiver can return any string data, and the responses are wrapped in SOAP-compliant XML. In the Jython script you can use the SOAPMessage and related Java classes to parse the response messages. The following is an example of a response message from the data receiver:

The message shown is an error message **<Error publishing config item changes>**, but the content can be anything that the data receiver is designed to respond with. The response is an error message

simply because that is the intent, because the designer says it is an error message and the push adapter expects the response to be some indication of success or failure. The content can be reconciliation IDs of all the successfully added CIs, or error messages for specific CIs. Customization of the GWSPA could include parsing the response message and taking actions such as resending certain CIs or performing other logging.

Testing the WSDL

The SOAPUI Eclipse plug-in is used to test web service layers during development. You can use SOAPUI to assist with customization of a web service. SOAPUI offers an integrated development environment (IDE) to test building, sending, and receiving of SOAP messages. In the SOAPUI perspective, the WSDL on pages 234-238 generated the following sample message:

The "?" in the **xmlAdded** element above is the location of the data, which is supplied by the web service push adapter integration.

Observing Results

When the push adapter is operating normally, in non-debug mode, the data is never written to a file until the final result is written (the intermediate TQL results and mapped data results are not normally visible in any log file). However, the results can be written to the probe's debug file by un-commenting the **logger.debug** statements (remove the "#" character) in the DiscoveryMain section as shown here:

Ensure the logger statement begins on the same column as the other preceding and following lines. Jython is indent-sensitive and the script will fail if the indention of all lines is not correct.

The debug log file **probeMgr-adaptersDebug.log** on the probe here shows the contents of the output:

```
<2011-12-07 14:02:23,019> [INFO ] [Thread-273] - XMLtoWebService.py started
<2011-12-07 14:02:23,019> [DEBUG] [Thread-273] - ESB Push parameters:
<2011-12-07 14:02:23,019> [DEBUG] [Thread-273] - Wshost=harpy.trtc.com
<2011-12-07 14:02:23,019> [DEBUG] [Thread-273] - WShostport=5555
<2011-12-07 14:02:23,019> [DEBUG] [Thread-273] -
WSuri=ws/DtITServiceManagement.esla.v1.ws.provider:UMDBDataReceiver
<2011-12-07 14:02:23,019> [INFO ] [Thread-273] - URL is
http://harpy.trtc.com:5555/ws/DtITServiceManagement.esla.v1.ws.
provider:UMDBDataReceiver
<2011-12-07 14:02:23,035> [DEBUG] [Thread-273] - Connected to
http://harpy.trtc.com:5555/ws/DtITServiceManagement.esla.v1.ws.
provider:UMDBDataReceiver
<2011-12-07 14:02:23,035> [ERROR] [Thread-273] - sending results
<2011-12-07 14:02:23,035> [DEBUG] [Thread-273] - <?xml version="1.0"
encoding="UTF-8"?>
<root>
    <data>
        <objects>
             <Object mode="" name="u_imp_ip_switch" operation="add"
             mamId="9e8c2f6bdfe4b7d0864c79e70833902c">
```

```
<field name="Correlation ID" key="true" datatype="char"
length="">9e8c2f6bdfe4b7d0864c79e70833902c</field>

<field name="name" key="false" datatype="char" length="">nma_
09sw</field>

<field name="location" key="false" datatype="char" length="" />

<field name="u_chassis_vendor_type" key="false" datatype="char"
length="">ciscoCat2960-24TT</field>

<field name="serial_number" key="false" datatype="char"
length="" />

<field name="ram" key="false" datatype="char" length="" />

<field name="ram" key="false" datatype="char" length="" />

<field name="os_version" key="false" datatype="char" length=""
/>
</Object>
```

Modifying the Jython Script

XMLtoWebService.py

The Jython script used by the Web Service push adapter is very similar to the XML push adapter. The script uses **UCMDBDataReceiver.jar**, included with the adapter. The script implements the **SendDataToReceiver()** method. **SendDataToReceiver()** uses three parameters:

- 1. Action (add, update, or delete)
- 2. The URL of the Data Receiver
- 3. The data

For example, the add block looks like: SendDataToReceiver("add", URL, addResult)

All web service and SOAP layers are wrapped. The URL is the service endpoint address of the UCMDB data receiver. This is the same URL used to obtain the wsdl via the "?wsdl" suffix.

The source of the Jython script is shown below. The web service integration wrapper lines are highlighted in green.

```
# This jython script accepts TQL data results (adds, updates, and deletes) from
the Integration adapter.
# and sends it to a web service. The web service is called UCMDBDataReceiver.
# A web service client of this name must be addressable at the URL provided by
the parameters.
# The SendDataToReceiver.jar exposes the SendDataToReceiver function, as well as
the service locator.
# examples of the service locator are in the testconnection section.
# regular expressions
import re
# logging
import logger
# web service interface
from com.hp.ucmdb import SendDataToReceiver
from com.hp.ucmdb.SendDataToReceiver import locateService
from com.hp.ucmdb.SendDataToReceiver import SendData
#######
           VARIABLES
                                 ##########
SCRIPT NAME = "XMLtoWebService.py"
logger.info(SCRIPT_NAME+" started")
def cleanUp(str):
   # replace mode=""
   str = re.sub("mode=\"\w+\"\s+", "", str)
   # replace mamId with id
   str = re.sub("\smamId=\"", " id=\"", str)
   # replace empty attributes
    str = re.sub("[\n|\s|\r]*<field name=\"\w+\" datatype=\"\w+\" />", "", str)
```

```
# replace targetRelationshipClass with name
    str = re.sub("\stargetRelationshipClass=\"", " name=\"", str)
    # replace Object with object with name
    str = re.sub("<Object mode=\"", "<object mode=\"", str)</pre>
    str = re.sub("<Object operation=\"", "<object operation=\"", str)</pre>
    str = re.sub("<Object name=\"", "<object name=\"", str)</pre>
    str = re.sub("</Object>", "</object>", str)
    # replace field to attribute
    str = re.sub("<field name=\"", "<attribute name=\"", str)</pre>
    str = re.sub("</field>", "</attribute>", str)
    #logger.debug("String = %s" % str)
    #logger.debug("cleaned up")
    return str
def isEmpty(xml, type = ""):
    objectsEmpty = 0
    linksEmpty = 0
    m = re.findall("<objects />", xml)
    if m:
        #logger.warn("\t[%s] No objects found" % type)
        objectsEmpty = 1
    m = re.findall("<links />", xml)
    if m:
        #logger.warn("\t[%s] No links found" % type)
        linksEmpty = 1
```

```
if objectsEmpty and linksEmpty:
        return 1
    return 0
########
            MAIN
                                 ##########
def DiscoveryMain(Framework):
   #fix this for web service export
   errMsg = "UCMDBDataReceiver Service not found."
   testConnection = Framework.getTriggerCIData("testConnection")
   # Get Web Service Push variables
   WShostName = Framework.getTriggerCIData("Host Name")
   WShostport = Framework.getTriggerCIData("Protocol Port")
   WSuri = Framework.getTriggerCIData("URI")
   logger.info(SCRIPT_NAME+":ESB Push parameters:")
   logger.info("Host Name="+WShostName)
   logger.info("Protocol Port="+WShostport)
   logger.info("URI="+WSuri)
   URL = "http://"+WShostName+":"+WShostport+"/"+WSuri
   logger.info("URL="+URL)
    if testConnection == 'true':
        # locate the service
        test_receiver = SendDataToReceiver()
        locator = test_receiver.locateService(URL)
       #locator = locateService(URL)
        if(locator):
           logger.info(SCRIPT_NAME+":Test connection was successful")
            return
        else:
            raise Exception, errMsg
```

```
return
# do same thing here if not just a test connection -
receiver = SendDataToReceiver()
locator = receiver.locateService(URL)
if(locator):
    logger.info(SCRIPT_NAME+":Connected to "+URL)
else:
    logger.error(SCRIPT_NAME+":no locator")
    raise Exception, errMsg
    return
# get add/update/delete result objects from the Framework
addResult = Framework.getTriggerCIData('addResult')
updateResult = Framework.getTriggerCIData('updateResult')
deleteResult = Framework.getTriggerCIData('deleteResult')
logger.debug(deleteResult)
# get referenced data - unused in this adapter implementation
#addRefResult = Framework.getTriggerCIData('referencedAddResult')
#updateRefResult = Framework.getTriggerCIData('referencedUpdateResult')
#deleteRefResult = Framework.getTriggerCIData('referencedDeleteResult')
# uncomment out the logger statements to see the data
empty = isEmpty(addResult, "addResult")
if not empty:
    addResult = cleanUp(addResult)
    # send to ESB web service
    logger.info(SCRIPT_NAME+":sending addData Result")
    rcvr = SendDataToReceiver()
    resp = rcvr.SendData("add", URL, addResult)
    logger.info(SCRIPT_NAME+":addData received response:"+resp)
    #logger.debug(addResult)
```

```
empty = isEmpty(updateResult, "updateResult")
if not empty:
    updateResult = cleanUp(updateResult)
    # send to ESB web service
    #logger.debug(updateResult)
    logger.info(SCRIPT_NAME+":sending updateData Result")
    rcvr = SendDataToReceiver()
    resp = rcvr.SendData("update", URL, updateResult)
    logger.info(SCRIPT_NAME+":received response:"+resp)
empty = isEmpty(deleteResult, "deleteResult")
if not empty:
    deleteResult = cleanUp(deleteResult)
    # send to ESB web service
    #logger.debug(deleteResult)
    logger.info(SCRIPT_NAME+":sending deleteData Result")
    rcvr = SendDataToReceiver()
    resp = rcvr.SendData("delete", URL, deleteResult)
    logger.info(SCRIPT_NAME+":received response:"+resp)
logger.info(SCRIPT NAME+" ended")
```

Customizing Response Message Processing

The data receiver should return a string containing any response or status desired. The web service push adapter passes by default the response to the probe's info-level log. The response message is SOAP-formatted XML containing the returned response string(s) inside. Any data can be returned by the receiver such as grouped or individual error or success messages. If additional processing is desired, the response can be processed by the adapter's Jython script. No Java programming is required.

An example of a return response message, sent using the following:

```
// stub example for building your own UCMDBDataData Receiver
public class UCMDBDataReceiver {
```

```
public String addData (String xmlAdd){
System.out.println(xmlAdd); // do something with the data
// send back a response message based on what you did
String tr = new String("a test response from addData!");
return tr;
}
```

is shown here:

Modifying the Data Receiver

A Java client can implement the classes contained in **UCMDBDataReceiver.jar** and call the web service in the same manner as Jython. In addition, the unwrapped methods may also be called. A Javadoc exists for the **UCMDBDataReceiver.jar** classes. The source code below shows how to use these essential methods to wrap the data in a SOAP message and send it to the receiver over HTTP.

The process is to create a **UCMDBDataReceiverServiceLocator** object, then assign the **UCMDBDataReceiverEndPointAddress** to the URL of the data receiver.

To send data, the locator's **getUCMDBDataReceiver** method is called to create a **UCMDBDataReceiver** object. The **UCMDBDataReceiver** object implements the methods to actually send the add/change/delete data. There are three identical code blocks to process each type of request.

```
The source code for the SendDataToReceiver class is listed below. Highlighted objects and methods are the essential elements to use.

/**

* Test SendData for the UCMDB Data Receiver for the UCMDB Web Service Push Adapter

*/
```

```
package com.hp.ucmdb;
import com.hp.ucmdb.SendDataToReceiver;
/**
* TestSendData can be used to verify the SOAP classes are working.
* TestSendData creates a SendDataToReceiver class and invokes its SendData
method.
* a response String is returned.
* The test URL is typically appended with "?wsdl" to get the WSDL of the
service.
*/
public class TestSendData {
    /**
    * @param args - test SOAP message.
    * optional arguments [0] a test string [1] a service endpoint URL of a
    Data Receiver.
    * the default URL is sent the incoming argument as a test message.
    * the default URL is
    "http://localhost:8080/UCMDBDataReceiver/services/UCMDBDataReceiver".
    * If any errors are encountered, TestClient will attempt to throw
    exceptions.
    */
    public static void main(String[] args) {
        // use test message if supplied, otherwise supply a default test string
        String teststring = new String("Test SOAP message from
        UCMDBDataReceiver TestSendData.");
        if(args.length > 0) {
            teststring = args[0];
        }
        // use test URL if supplied, otherwise supply the default URL
        String URL = new String("");
        if(args.length > 1) {
            URL = args[1];
```

```
// return response
    String response = new String("");
    // perform the tests
    try {
        if(URL.equals("")) {
             UCMDBDataReceiverServiceLocator locator = new
             UCMDBDataReceiverServiceLocator();
             UCMDBDataReceiver receiver = locator.getUCMDBDataReceiver();
             URL = locator.getUCMDBDataReceiverAddress();
             System.out.println("TestClient: tested
             URL="+locator.getUCMDBDataReceiverAddress());
             System.out.println("TestClient: receiver="+receiver.toString
             ());
        }
        SendDataToReceiver sdtr = new SendDataToReceiver();
        // this sends a test push and gets a response message
        response = sdtr.SendData("add", URL, args[0]);
        System.out.println("Response received was:"+response);
    } catch (Exception e) {
        System.out.println("TestClient: Remote Error:");
        e.printStackTrace();
    }
}
```

Source code is also included in the **UCMDBDataReceiver.jar** file for the other classes:

- TestClient.java
- UCMDBDataReceiver.java
- UCMDBDataReceiverProxy.java
- UCMDBDataReceiverService.java
- UCMDBDataReceiverServiceLocator.java
- UCMDBDataReceiverSoapBindingStub.java

The source was generated in the Eclipse IDE, then modified. Exercise caution when modifying the UCMDB code, as much of it is auto-generated to match the SOAP specification and the UCMDB data receiver.

Javadoc

A fully-commented **javadoc** is provided with the generic web service push adapter. The **javadoc** is included in the docs folder **javadoc**. Start with **index.html**. The overview page provides access to the documentation for all classes and methods in the SDK.

All Classes

• SendDataToReceiver: API for the web service wrapper

• TestClient: test client to verify connectivity to an service endpoint

• UCMDBDataReceiver: web service wrapper

The rest are automatically generated by the web service builder:

UCMDBDataReceiverProxy

UCMDBDataReceiverService

UCMDBDataReceiverServiceLocator

• UCMDBDataReceiverSoapBindingStub

Overview

Basic usage of the SDK, including source code examples, is explained in the documentation in the package. This **javadoc** is for the UCMDB web service push adapter. The API may be called from Jython or Java.

The SDK provides two source samples, **TestClient** and **SendDataToReceiver**. **TestClient** provides a very limited test of the responding local client. **SendDataToReceiver** is the main class used to send data to a web service.

First, use this SDK (mainly the enclosed WSDL) to implement a UCMDB data receiver to communicate with this web service. Then use this SDK to create a push adapter in the UCMDB to push UCMDB TQL result data to the data receiver. Basic usage of this API is described below, with both Jython and Java implementations.

Implementing SendDataToReceiver()

SendDataToReceiver() wraps all functions with a single method:

- Jython: SendDataToReceiver("add", yourURL, "Hello!")
- Java: SendDataToReceiver("add", yourURL, "Hello!");

Or, create a **SendDataToReceiver** object (for example, to manipulate other settings) and then call the **SendData** method separately, as shown here:

• Jython:

```
rcvr = SendDataToReceiver()
responseMsg = rcvr.SendData("add", yourURL, "Hello!")
```

Java:

```
SendDataToReceiver rcvr = new SendDataToReceiver();
String responseMsg = rcvr.SendData("add", yourURL, "Hello!");
```

Or, if you need to do it a step at a time, you can do the following:

- 1. Create a new **UCMDBDataReceiverServiceLocator()** object x, then set the object's endpoint address later, shown here:
 - Jython:

```
x = UCMDBDataReceiverServiceLocator()
x.setUCMDBDataReceiverEndPointAddress(URL)
```

Java :

```
UCMDBDataReceiverServiceLocator x = new UCMDBDataReceiverServiceLocator();
```

- x. setUCMDBDataReceiverEndPointAddress(URL);
- 2. Then, create a UCMDBDataReceiver with
 - o Jython: y = x.getUCMDBDataReceiver()
 - o Java: UCMDBDataReceiver y = x.getUCMDBDataReceiver();
- 3. Then, send the data via the SOAP web service like this:
 - Jython:
 - y.addData(yourData)
 - or y.updateData(yourData)
 - or y.deleteData(yourData)
 - Java:

- y.addData(yourData);
- or y.updateData(yourData);
- or y.deleteData(yourData);
- 4. It may be necessary to test connectivity, then if successful reuse the same locator object to return **UCMDBDataReceiver** to use for data transfer.

The classes contain no destructors and do not perform memory management.

Mapping File Reference

Using Mappings

A mapping must be created for each target attribute in the transformed XML output. The mappings specify where and how to obtain the data. If the data is in another corresponding attribute in UCMDB, then a direct mapping is used.

To pull data from multiple attributes, or attributes from the UCMDB CI's child or parent CI's attributes, other complex mappings may be necessary. The mapping schema below shows all possible mappings.

The mapping file is an XML file which defines which CI/Relationship types in UCMDB are mapped to which CI/Relationship types in the target data store. The format is explained in detail below. The mapping file controls which CI and relationship types are pushed, as well as controlling exactly which attributes are pushed.

A mapping entry exists for each attribute to be pushed to the target MDR. Each mapping entry may consist of one or more attributes in the raw UCMDB push data. Mapping entries allow completely granular control of the final structure and naming of the data to be pushed to the target MDR.

Direct Mappings

Mappings transform one data model to another (in this case, the UCMDB to the push target MDR). Transformations may be simple, in the case of a 1:1 relationship between the UCMDB attribute and the target, they differ only by name and perhaps type.

Most attribute mappings are direct. For example, the server name "ServerX", may be represented in UCMDB as a CI of type **unix** with an attribute name of **primary_server_name**, of type **string** with a length of 50. The target MDR's data model may specify the same logical entity with a CI type of **linux**, with an attribute name of **hostname** with a type of **char[]** with a maximum length of 250. Direct mappings can accomplish all these aforementioned types of translation tasks.

Here is an example of a direct mapping:

```
<target_attribute name="dns_domain" datatype="char">
<map type="direct" source_attribute="domain_name" />
</target attribute>
```

This direct mapping maps the UCMDB attribute **dns_domain** to the **domain_name** attribute in the target data model.

Use the **char** data type regardless of the actual data type, unless it is necessary to use the actual data type.

Complex Mappings

More complex mappings enable additional transformations:

- To map attribute values from multiple CIs to one target CI.
- To map attributes of children CIs (those having a container_f or contained relationship) to the
 parent CI in the target data store. For example, setting a value called Number of CPUs on a target
 Host CI. Another example could be setting the value Total Memory (by adding up the memory size
 values of all memory CIs of a host CI in UCMDB) on a target Host CI.
- To map attributes of parent CIs (those having a container_f or contained relationship) on the target data store's CI. For example, setting a value called Container Server on a target attribute called Installed Software CI, by getting the value from the containing host of the software CI in UCMDB.

Below is an example of a complex mapping, using two source attributes separated by a comma character, to create the target attribute **os**":

Reversing Link Directions

It is possible that the UCMDB contains data that differs in structure from source to source. For

example, the relationship between an IpAddress CI and an Interface CI may be a **parent**, as may occur with the HPE Network Node Manager integration. Or it may be a **containment** link as is commonly created by Universal Discovery. Furthermore, the direction of these links are opposite to each other.

It is currently not possible to reverse the direction of links in the mappings file. Reversal of the **_end1** and **_end2** variables either switches the order of the data in the transformed XML or the link is missing in the source data.

One possible solution to this problem is to define an Enrichment rule as follows:

- The enrichment's TQL part is a subset of a TQL that is used by the push adapter. This TQL in particular selects all the links that are in the opposite direction of what is desired in the transformed xml.
- 2. The enrichment part defines a new link of the correct direction and desired type.
- 3. Enrichment is activated and then creates the correct links.
- 4. The integration job TQL now refers to the enriched link rather than the original link.
- 5. The ink> mappings in the push adapter then refer to the enriched link as well and produce a set of links consistent in type and direction.

Mapping File Schema

Element Name and Path	Description	Attributes
integration	Defines the mapping contents of the file. Must be the outermost block in the file except for the beginning line and any comments.	
info (integration)	Defines information about the data repositories being integrated.	
source (integration > info)	Defines information about the source data repository.	 Name: type Description: Name of the source data repository. Is required?: Required

Element Name and Path	Description	Attributes
		Type: String 2. Name: versions Description: Version(s) of the source data repositories. Is required?: Required Type: String 3. Name: vendor Description: Vendor of the source data repository. Is required?: Required Type: String
target (integration > info)	Defines information about the target data repository.	 Name: type Description: Name of the source data repository. Is required?: Required Type: String Name: versions Description: Version(s) of the source data repository. Is required?: Required Type: String Name: vendor Description: Vendor of the source data repository. Is required?: Required Type: String
targetcis (integration)	Container element for all CIT mappings.	
source_ci_type_tree (integration > targetcis)	Defines a source CIT and all of the CI types which inherit from it.	 Name: name Description: Name of the source CIT. Is required?: Required Type: String Name: mode

Element Name and Path	Description	Attributes
		Description: The type of update required for the current CI type. Is required?: Required Type: One of the following strings: a. insert: Use this only if the CI does not already exist. b. update: Use this only if the CI is known to exist. c. update_else_insert: If the CI exists, update it; otherwise, create a new CI. d. ignore: Do nothing with this CI type.
source_ci_type (integration > targetcis)	Defines a source CIT without the CI types which inherit from it.	 Name: name Description: Name of the source CIT. Is required?: Required Type: String Name: mode Description: The type of update required for the current CI type. Is required?: Required Type: One of the following strings: a. insert: Use this only if the CI does not already exist. b. update: Use this only if the CI is known to exist. c. update_else_insert: If the CI exists, update it; otherwise, create a new CI. d. ignore: Do nothing with this CI type.
target_ci_type (integration > targetcis > source_ci_type -OR- integration > targetcis > source_ci_type_tree)	Defines a target CIT.	 Name: name Description: Target CI type name. Is required?: Required Type: String Name: schema Description: The name of the schema that will be used to store this CI type at the target.

Element Name and Path	Description	Attributes
		Is required?: Not Required Type: String 3. Name: namespace Description: Indicates the namespace of this CI type on the target. Is required?: Not Required Type: String
targetprimarykey (integration > targetcis > source_ci_type) -OR- (integration > targetcis > source_ci_type_tree -OR- (integration > targetrelations > link) -OR- (integration > targetrelations > source_link_type_tree)	Identifies target CIT primary key attributes.	
pkey (integration > targetcis > source_ci_type > targetprimarykey -OR- integration > targetcis > source_ci_type_tree > targetprimarykey -OR- (integration >	Identifies one primary key attribute. Required only if mode is update or insert_else_update.	

Element Name and Path	Description	Attributes
targetrelations > link > targetprimarykey) -OR- integration > targetrelations > source_link_type_tree > targetprimarykey)		
target_attribute (integration > targetcis > source_ci_type -OR- integration > targetcis > source_ci_type_tree -OR- integration > targetrelations > link -OR- integration > targetrelations > source_link_type_tree)	Defines the target CIT's attribute.	 Name: name Description: Name of the target CIT's attribute. Is required?: Required Type: String Name: datatype Description: Data type of the target CIT's attribute. Is required?: Required Type: String Name: length Description: For string/char data types, integer size of target attribute. Is required?: Not Required Type. Integer Name. option Description. The conversion function to be applied to the value. Is required. False Type. One of the following strings: a. uppercase – Convert to uppercase b. lowercase – Convert to lowercase If this attribute is empty, no conversion function will be applied.
map	Specifies how to obtain the source CIT's	1. Name. type

Element Name and Path	Description	Attributes
(integration > targetcis > source_ci_type > target_attribute -OR- integration > targetcis > source_ci_type_tree > target_attribute) -OR- (integration > targetrelations > link > target_attribute -OR- integration > targetrelations > source_link_type_tree > target_attribute)	attribute value.	Description. The type of mapping between the source and target values. Is required. Required Type. One of the following strings: a. direct – Specifies a 1-to-1 mapping from source attribute's value to target attribute's value. b. compoundstring – Sub-elements are joined into a single string and the target attribute value is set. c. childattr – Sub-elements are one or more child CIT's attributes. Child CITs are defined as those with composition or containment relationship. d. constant – Static string 2. Name. value Description. Constant string for type=constant Is required. Only required when type=constant Type. String 3. Name. attr Description. Source attribute name for type=direct Is required. Only required when type=direct Is required. Only required when
aggregation (integration > targetcis > source_ci_type > target_attribute > map -OR- integration >	Specifies how the source CI's child CI attribute values are combined into a single value to map to the target CI attribute. Optional.	 Name: type Description. The type of aggregation function Is required?: Required Type. One of the following strings: csv – Concatenates all included values into a comma-separated list (numeric or string/character). count – Returns a numeric count of all

Element Name and Path	Description	Attributes
targetcis > source_ci_ type_tree > target_ attribute > map -OR- (integration > targetrelations > link > target_attribute > map -OR- integration > targetrelations > source_link_type_tree > target_attribute > map) Only valid when the map's type is childattr		 sum – Returns the sum of all numeric included values. average – Returns a numeric average of all included values. min – Returns the lowest numeric/character included value. max – Returns the highest numeric/character included value.
source_child_ci_type (integration > targetcis > source_ci_type > target_attribute > map -OR- integration > targetcis > source_ci_type_tree > target_attribute > map -OR- (integration > targetrelations > link > target_attribute > map -OR- integration > targetrelations > link > target_attribute > map	Specifies from which connected CI the child attribute is taken.	 Name. name Description. The type of the child CI Is required. Required Type. String Name. source_attribute Description. The attribute of the child CI that is mapped. Is required. Required only if the childAttr aggregation type (which is on the same path) is not =count. Type. String

Element Name and Path	Description	Attributes
source_link_type_tree > target_attribute > map) Only valid when the map's type is childattr .		
validation (integration > targetcis > source_ci_type > target_attribute > map -OR- integration > targetcis > source_ci_type_tree > target_attribute > map -OR- (integration > targetrelations > link > target_attribute > map -OR- integration > targetrelations > link > target_attribute > map -OR- integration > targetrelations > source_link_type_tree > target_attribute > map) Only valid when the map's type is childatt	Allows exclusion filtering of the source CI's child CIs based on attribute values. Used with the aggregation sub-element to achieve granularity of exactly which children attributes are mapped to the target CIT's attribute value. Optional.	 Name. minlength Description. Excludes strings shorter than the given value. Is Required?: Not required Type. Integer Name. maxlength Description. Excludes strings longer than the given value. Is Required?: Not required Type. Integer Name. minvalue Description. Excludes numbers smaller than the specified value. Is Required?: Not required Type. Numeric Name. maxvalue Description. Excludes numbers greater than the specified value. Is Required?: Not required Type. Numeric
targetrelations (integration)	Container element for all relationship mappings. Optional.	
source_link_type_tree	Maps a source Relationship type	Name: name Description. Source relationship name.

Element Name and Path	Description	Attributes
(integration > targetrelations)	without the types which inherit from it to a target Relationship. Mandatory only if targetrelation is present.	Is required?:Required Type. String 2. Name: target_link_type Description. Target relationship name Is required?: Required Type. String 3. Name: nameSpace Description: The namespace for the link that will be created on the target. Is required?: Not required Type: String 4. Name: mode Description: The type of update required for the current link. Is required?: Required Type: One of the following strings: insert – Use this only if the CI does not already exist. update – Use this only if the CI is known to exist. update_else_insert – If the CI exists, update it; otherwise, create a new CI. ignore – Do nothing with this CI type. Name: source_ci_type_end1 Description: Source relationship's End1 CI type. Is required?: Required Type: String 6. Name: source_ci_type_end2 Description: Source relationship's End2 CI type. Is required?: Required Type: String

Element Name and Path	Description	Attributes
	Description Maps a source Relationship to a target Relationship. Mandatory only if targetrelation is present.	1. Name: source_link_type Description: Source relationship name. Is Required?: Required Type: String 2. Name: target_link_type Description: Target relationship name. Is required?: Required Type: String 3. Name: nameSpace Description: The namespace for the link that will be created on the target. Is required?: Not required Type: String 4. Name: mode Description: The type of update required for the current link. Is required?: Required Type: On the following strings: insert – Use this only if the CI does not already exist. update – Use this only if the CI is known to exist.
		update it; otherwise, create a new CI.
		o ignore – Do nothing with this CI type.
		 Name: source_ci_type_end1 Description: Source relationship's End1 CI type Is required?: Required Type: String
		6. Name: source_ci_type_end2 Description: Source relationship's End2 CI type Is required?: Required Type: String

Element Name and Path	Description	Attributes
target_ci_type_end1 (integration > targetrelations > link -OR- integration > targetrelations > source_link_type_tree)	Target relationship's End1 CI type.	 Name: name Description: Name of the target relationship's End1 CI type. Is required?: Required Type: String Name: superclass Description: Name of the End1 CI type's super-class. Is required?: Not required Type: String
target_ci_type_end2 (integration > targetrelations > link -OR- integration > targetrelations > source_link_type_tree)	Target relationship's End2 CI type.	 Name: name Description: Name of the target relationship's End2 CI type. Is required?: Required Type: String Name: superclass Description: Name of the End2 CI type's super-class. Is required?: Not required Type: String

Mapping Results Schema

Element Name and Path	Description	Attributes
root	The root of the result document.	
data (root)	The root of the data itself.	
objects (root > data)	The root element for the objects to update.	

Element Name and Path	Description	Attributes
Object (root > data > objects)	Describes the update operation for a single object and all of its attributes.	Name: name Description: Name of the CI type Is required?: Required Type: String
		 Name: mode Description: The type of update required for the current CI type. Is required?: Required Type: One of the following strings: a. insert – Use this only if the CI does not already exist. b. update – Use this only if the CI is known to exist. c. update_else_insert – If the CI exists, update it; otherwise, create a new CI. d. ignore – Do nothing with this CI type.
		 Name: operation Description: The operation to perform with this CI. Is required: Required Type: One of the following strings: a. add – The CI should be added b. update – The CI should be updated c. delete – The CI should be deleted If no value is set, then the default value of add is used.
		 Name: mamId Description: The ID of the object on the source CMDB. Is required?: Required Type: String
field (root > data > objects > Object -OR-	Describes the value of a single field for an object. The field's text is the new value in the	 Name: name Description: Name of the field. Is required?: Required Type: String

Element Name and Path	Description	Attributes
root > data > links > link)	field, and if the field contains a link, the value is the ID of one of the ends. Each end ID appears as an object (under <objects>).</objects>	 Name: key Description: Specifies whether this field is a key for the object. Is required?: Required Type: Boolean Name: datatype
		Description: The type of the field. Is required?: Required Type: String
		 Name: length Description: For string/character data types, this is the integer size of the target attribute. Is required?: Not Required Type: Integer
links (root > data)	The root element for the links to update.	 Name: targetRelationshipClass Description: The name of the relationship (link) in the target system. Is required?: Required Type: String
		 Name: targetParent Description: The type of first end of the link (parent). Is required?: Required Type: String
		 Name: targetChild Description: The type of the second end of the link (child). Is required?: Required Type: String
		 Name: mode Description: The type of update required for the current CI type. Is required?: Required

Element Name and Path	Description	Attributes
		Type: One of the following strings: a. insert – Use this only if the CI does not already exist. b. update – Use this only if the CI is known to exist. c. update_else_insert – If the CI exists, update it; otherwise, create a new CI. d. ignore – Do nothing with this CI type.
		 5. Name: operation Description: The operation to perform with this CI. Is required?: Required Type: One of the following strings: a. add – The CI should be added b. update – The CI should be updated c. delete – The CI should be deleted If no value is set, then the default value of add is used.
		 Name: mamId Description: The ID of the object on the source CMDB. Is required?: Required Type: String

Customization

This section explains some of the basic procedures for common types of customization for push adapters.

Adding an Attribute

- 1. Ensure that the attribute is included in the TQL result.
- 2. Add the attribute mapping to the mappings file in the correct CI mapping section.
- 3. Ensure the data receiver is prepared to receive the additional attribute in the data.

Removing an Attribute

To remove an attribute, remove the attribute from the mapping file. You should also remove the attribute from the TQL if it is no longer used in the result or as a conditional node.

Adding a CI Type

- 1. Add the CI type to the TQL.
- 2. Ensure the CI type and it's attribute data appear in the TQL result (use calculate and preview).
- 3. Add the CI type's mapping in the mappings file. Copy another CI type's mappings to quickly create a new CI type.
- 4. Modify the copied XML's name and attribute mappings to correspond to the new CI type and its attributes. See "Mapping File Reference" on page 252 for the available types of mappings.

Removing a CI Type

- 1. Remove the CI Type from the TQL
- 2. Remove the mapping section for that CI type in the mappings file.

Adding Links

- 1. Ensure the two end CIs are present in the data.
- 2. Ensure the link you need to add is in fact a valid link (check in the CI type manager).
- 3. Add the link elements in the relationships section of the mappings xml.

Removing Links

- 1. Remove the link section of the link you want to remove in the mappings file.
- 2. If possible, remove the link from the TQL (unless it affects the efficiency or function of the TQL).

Chapter 8: Developing Generic Adapters

This chapter includes:

Instance Sync	269
Achieving Data Push using the Generic Adapter	269
Achieving Data Population using the Generic Adapter	278
Achieving Data Federation using the Generic Adapter	294
Reconciliation	314
Generic Adapter API	314
Resource Locator APIs	314
Create a Generic Adapter Package	315
Differences Between Push and Population Mapping	321
Generic Adapter Log Files	321
Adapters Using the Generic Adapter Framework	322
Generic Adapter XML Schema Reference	322

Instance Sync

The push and population Generic Adapter operations work with instance data. For more information about the concepts of *instance* and *root*, see "Instance-Based Population Flow" on page 181 and "Achieving Data Push using the Generic Adapter" below.

Achieving Data Push using the Generic Adapter

Data Push uses the existing Enhanced Generic Push Adapter framework with minor XML schema changes.

Note: The Generic Adapter works in instance mode (meaning it does not work with single CI types, but with collections of CIs grouped together by a main root CI). For more information, see "Instance-Based Population Flow" on page 181.

The XML schema changes needed to accommodate bidirectional mapping semantics are:

- the <targetcis> tag has been renamed to <target_entities>.
- the <source_instance_type> tag has been renamed to <source_instance>.
- the <target_ci_type> tag has been renamed to <target_entity>.
- the <for-each-source-ci> tag thas been renamed to <for-each-source-entity>.
- the header versions attribute has been renamed to version and no longer requires a decimal.

This section provides information about pushing data using the Generic Adapter Framework:

Push Overview	270
The Mapping File	270
The Groovy Traveler	273
Write Groovy Scripts	276
Implement PushAdapterConnector Interface	277

Push Overview

The Generic Adapter works on data structures that represent the TQL query result. Each adapter built over the Generic Adapter Framework will handle this data structure and push it to its required target.

The data structure is named **ResultTreeNode** (**RTN**). The RTN is created according to the mapping file of the adapter and the results of the TQL query. The queries used for the Generic Adapter Framework must be root based, that is the query must contain one query node with element name **root**, or one or more relationship elements beginning with the prefix **root**. This CI or relationship serves as the root element of the query. For details, see Data Push in the *HPE Universal CMDB Data Flow Management Guide*.


There are two basic steps involved in developing enhanced push adapters:

- Implementing the PushAdapterConnector interface this interface receives the data to add, update and delete as a list of RTNs, and perform the push into the target.
- Creating the mapping file the mapping file determines the creating of the RTN structure, by mapping CIs and attributes of the TQL result.

The Mapping File

The following example demonstrates how to create the mapping file.


In this example, we will simulate a push of a node and an IP address. We will create a TQL query called: **Node Push**, as follows:




In the mapping file we create two target CI types: **Computer** and **IP**. Computer has one variable and two attributes. IP has one attribute.

The following is the mapping XML file:

The query results appear as follows:



Here is the RTN list built according to this mapping file:



Each root instance is mapped separately using the mapping file. Thus in this example, the PushAdapterConnector receives a list of two RTN roots.

Note: The previous push adapter had the ability to create a general mapping for a CI type. The new push adapter mapping is per TQL query. While running a push job that uses a query named \mathbf{x} ,

the adapter looks for the relevant mapping file (the one that has attribute: query-name=x).

You can calculate the values in the mapping file using groovy script language. For details, see "The Groovy Traveler" below.

The Groovy Traveler

Access the TQL query results in the following manner:

- Root[attr] returns the attribute attr of the Root element.
- Root.Query_Element_Name returns a list of the CI instances named in the TQL Query_Element_ Name and that are linked to the current root CI.
- Root.Query_Element_Name[2][attr] returns the attribute attr of the third Query_Element_Name
 that is linked to the current root CI.
- Root.Query_Element_Name*.getAt(attr) returns a list of the attributes attr of the CI instances
 named Query_Element_Name in the TQL and that are linked to the current root CI.

There are additional attributes that can be accessed by the groovy traveler:

- cmdb_id returns the UCMDB ID of the CI or relationship as a string.
- external_cmdb_id returns the external ID of the CI or relationship as a string.
- Element_type returns the element type of the CI or relationship as a string.

The import tag:

```
<import>
<scriptFile path="mappings.scripts.PushFunctions"/>
</import>
```

This means that we are declaring an import for all the groovy scripts in the mapping file. In this example, **PushFunctions** is a groovy script file that contains some static functions, and we can access them during the mapping (i.e. value="PushFunctions.foo()")

source_instance_type

The mapping is done per TQL, the query-name value is the related TQL of the current mapping. The '*' means that this mapping file is associated with all TQL queries beginning with the prefix: **Node Push**.

```
<source_instance_type query-name="Node Push*" root-element-name="Root">
```

The source_instance_type tag designates the root element we are mapping.

root-element-name should be exactly the same as the name of the root in the TQL.

target_entity

This tag is used for the creation of the RTN.

The name attribute represents the target_entity name: name=Computer

The **is-valid** attribute is a Boolean value that is calculated during the mapping, and determines if the current target_ci is valid. Invalid target_entities are not added to the RTN. In this example, we do not want to create a target_entity instance for which the **root_iscandidatefordeletion** attribute in UCMDB is true.

The target_entity can have variables that are calculated during the mapping:

```
<variable name="vSerialNo" datatype="STRING" value="Root['serial_number']"/>
```

The variable **vSerialNo** gets the value of the **serial_number** of the current root.

The attribute of the RTN is created by the **target_mapping** tag. The result of the execution of the groovy script in the **value** field, is assigned to the RTN attribute.

```
<target_mapping name="SerialNo" datatype="STRING" value="vSerialNo"/>
```

SerialNo assigns the value of the variable vSerialNo.

It is possible to define a target_entity as child of another target_entity as follows:

```
<target_entity name="Portfolio">

<variable name="vSerialNo" datatype="STRING" value="Root['global_id']"/>

<target_mapping name="CMDBId" datatype="STRING" value="globalId"/>

<target_entity name=Asset">

<target_mapping name="SerialNo" datatype="STRING" value="vSerialNo"/>

</target_entity>

</target_entity>
</target_entity></target_entity></target_entity>
</target_entity>
```

The RTN Portfolio will have child RTN named Asset.

for-each-source-entity


This tag lists the specific CIs of the root instance. It has the following fields:

• **source-entities=" "** – the list of CIs for which a target CI is created. This list is defined by the groovy traveler in the **Root.IpAddress** field.

- **count-index=""** a variable that holds the index of the CI in the current iteration of the loop.
- var-name=" " the name of the CI in the current iteration of the loop.

Let's modify our example mapping file:

The RTN list that will build according to this mapping file will look like this:



dynamic mapping

This tag adds the ability to create a mapping of data from the target data store during the creation of the RTN structure.

Example: Assume that the target is a database with a table named **Computer** that has an **id** column and a **name** column that is correlated to **Node.name** in UCMDB. Both columns are unique. The database also has a table named **IP** that has a referenced key to the **parentID** in the Computer table. The 'dynamic_mapping' can create a map that stores the name and id as <name,id>. Based on this map, the Adapter can match ids with computers and can push the correct value to the **parentID** attribute in the IP table. You can use this map to assign a value to the parentID attribute while creating the RTN.

The mapping is determined by the **map_property**. The dynamic_mapping is executed once for each chunk.

```
<dynamic_mapping name="IdByName " keys-unique="true">
```

The **name** attribute represents the name of the map. The **keys-unique** attribute indicates if the keys are unique (each key is mapped to one value, or to a set of values).

The name of the map in this example is **IdByName** and it has unique keys. In order to access the map in the script, execute the following command:

```
DynamicMapHolder.getMap('IdByName')
```

It returns a reference to that map.

The **map_property** tag creates the property on which the mapping is based.

Example:

```
<map_property property-name="SQLQuery" datatype="STRING"
property-value="SELECT name, id FROM Computer"/>
```

In this example the name of the property is **SQLQuery** and its value is an SQL statement that creates the map. The implementation of the methods **retrieveUniqueMapping** and **retrieveNonUniqueMapping** for the PushConnector interface will determine the actual content of the returned map.

Global Variables

The following global variables are accessible to the groovy script in the mapping file:

- **Topology** Type: Topology. An instance of the topology of the current chunk.
- QueryDefinition Type: QueryDefinition. An instance of the query definition of the current TQL.
- OutputCI Type: ResultTreeNode. The RTN of the root element in the current tree mapping.
- ClassModel Type: ClassModel. An instance of the class model.
- CustomerInformation Type: CustomerInformation. Information about the customer running the
 job.
- Logger Type: DataAdapterLogger. This logger is available in the adapter for writing logs to the UCMDB logging framework.

Write Groovy Scripts

In this section we create the **PushFunctions.groovy** file. This file will contain static functions that are used during the mapping of the root instance.

```
package mappings.scripts
```

```
public class PushFunctions {
    public static boolean isVirtual(def nodeRole){
        return isListContainsOne(def list, "MY_VM", "MY_SIMULATOR");
    }

public static String getDescription(boolean isVirtual){
        if(isVirtual){
            return "This is a VM";
        }
        else{
            return "This is physical machine";
        }
    }

private static boolean isListContainsOne(def list, ...stringList){
        //returns true if the list contains one of the values.
    }
}
```

Implement PushAdapterConnector Interface

The implementation should support the following basic steps:

```
public class PushExampleAdapter implements PushAdapterConnector
{

public UpdateResult pushTreeNodes(PushConnectorInput input) throws
DataAccessException{

// 1. build an UpdateResult instance - the UpdateResult is used to return
mappings between the sent ids to the actual ids that entered the data store.

// Also has an update status which allows to pass the status of data that was
actually pushed, detailed status reports on failed IDs, and actions actually
performed on successful ids.

// 2. handle the data:

// a. handle data to add. Can be retrieved by:
input.getResultTreeNodes.getDataToAdd();

// b. handle data to update.

// c. handle data to delete.
```


```
// 3. Return the Update result.
public void start(PushDataAdapterEnvironment env) throws DataAccessException{
       // this method is called when the integration point created,
or when the adapter is reloaded
       //(i.e after changing one of the mapping files
       // and pressing 'save').
}
public void testConnection(PushDataAdapterEnvironment env) throws
DataAccessException {
               // this method is called when pressing the 'test
connection' button in the
               //creation of the integration point.
               // For example if we push data to RDBMS this method
can create a connection
               //to the database and will run a dummy SQL statement.
               // If it fails it writes an error message to the log
and throws an exception.
      }
Map<Object, Object> retrieveUniqueMapping(MappingQuery mappingQuery){
//This method will create the map according to the given mappingQuery. It will
be called in the
// mapping stage of the adapter execution, before the 'UpdateResult
pushTreeNodes' method.
// This method is called when the 'keys-unique' attribute of the 'dynamic_
mapping' tag is true.
}
Map<Object, Set<Object>> retrieveNonUniqueMapping(MappingQuery mappingQuery){
 // This method is called when the 'keys-unique' attribute of the 'dynamic_
mapping' tag is false.
// In this case a key can be mapped to several values.
}
```

Achieving Data Population using the Generic Adapter

This section contains the following topics:

The Population Framework Architecture	279
Main Artifacts involved in Population	279
Population Adapter Modes	291
Explicit External ID Mapping	292
Global ID Pushback	293

The Population Framework Architecture



The mechanism is similar to that of the Push Adapter framework, meaning that a user of this Population Adapter framework must provide a mapping file and a connector implementation, and bundle them together in a UCMDB adapter package.


The operation flow contains the following steps

- 1. The UCMDB user triggers the population operation from the UI.
- 2. The command is sent to the population adapter.
- 3. The population adapter calls the population connector and retrieves data in chunks.
- 4. The population adapter applies the defined mapping on data from each chunk and sends it forward to the UCMDB Server.

Main Artifacts involved in Population


The main artifacts involved in population are:

- the TQL queries hat specify the data that will be populated in UCMDB
- the XML mapping files that specify how the connector-returned data will be mapped to UCMDB
- required data
- the population connector responsible for retrieving the external system data and returning it to the UCMDB Generic Adapter.



Population TQL Queries

The role of a population TQL query is to indicate the data that will be populated in UCMDB. For example, the TQL in the following figure is used to bring Node instances in UCMDB.




The population connector is responsible for understanding the population TQL queries and providing the required data from the external system.

Population Mapping Files

The XML mapping files have the same purpose as for push operations, except that the direction is reversed. These mapping files describe how the data returned by the connector will be mapped to the UCMDB data.

The information provided here is relevant for population mapping and is not already mentioned for the Enhanced Generic Push Adapter.

Following is an example of a mapping for UCMDB Nodes and Running Software. The first image shows the Nodes and Software Population TQL query. The second image displays the Nodes and Software Population Mapping.



```
<target_entities>
    <!-- The query name must match the one selected in the UI-->
    <source_instance query-name="Nodes And Software Population" root-element-name="PC">
       <!-- need to match case in UCMDB TQL -->
       <target entity name="RootLink">
            <target_mapping name="name" datatype="STRING" value="PC['name'] + 'has' + PC.Programs[0]['name']"/>
        </target entity>
       <target_entity name="Node" type="Util.getNodeType(PC)">
           <target_mapping name="name" datatype="STRING" value="PC['name']"/>
            <target_mapping name="description" datatype="STRING" value="PC['description']"/>
       </target_entity>
        <target_entity name="Software">
            <target_mapping name="name" datatype="STRING" value="PC.Programs[0]['name']"/>
            <target_mapping name="root_container_name" datatype="STRING" value="PC['name']"/>
            <target_mapping name="product_name" datatype="STRING" value="'ymware_hypervisor'"/>
        </target_entity>
    </source_instance>
</target entities>
```

This population job fetches data from an external system in the form of the ResultTreeNode (RTN) PC. The ResultTreeNode API was introduced by the Enhanced Generic Push Adapter and can be found in

the **push-interfaces.jar** file located in the UCMDB Server **lib** folder. For more information, see "Achieving Data Push using the Generic Adapter" on page 269.


The PC RTN contains general node information in the form of attributes as well as an embedded Programs entity that contains software type entities with the relevant attributes.

One PC instance will be mapped to 3 entities in UCMDB:

- a Node CI
- a Running Software CI
- a Composition link CI

For more information about the format of the PC instance, see "Population Request Output" on page 290.

The way in which connector data is mapped to UCMDB data is shown in the following figure:



Let's analyze the key lines:

```
<!--The query name must match the one selected in the UI-->
<source_instance query-name="Nodes And Software Population" root-element-name="PC">
```

The **source_instance** definition states that we will bring entities into UCMDB and the UCMDB topology that groups these entities is defined by the Nodes and Software Population TQL query. In addition, the data structure returned by the connector that will be used to create the UCMDB data is a **ResultTreeNode** named **PC**.

The **target_entity** tag states that a new UCMDB entity starts here and this entity corresponds to the **RootLink** element inside the Nodes and Software Population TQL query. This indication also includes the UCMDB CI type of the new entity.

The **RootLink** entity that will be created will have one attribute, **name**, whose value will be something like **Computer_22** has **MySQL Server**.

This sample mapping uses manual link population. We recommended using the automatic approach described in "Automatic Link Population" below.

The Population type Attribute

```
<target_entity name="Node" type="Util.getNodeType(PC)">
```

Note that the Node entity has a **type** attribute. This **type** indicates the exact CI type that this entity will have in UCMDB. The **type** attribute is not mandatory, because the entity's default creation type is obtained from the TQL element it refers to (in this case, Node). However, if we want to return multiple instances of the UCMDB Node CI type and some of the instances are Windows while others are Unix, we can use the **type** attribute to specify the exact UCMDB creation type. So in this case, we create a **getNodeType** function inside the **Util** function script file, which receives as input the PC tree and returns the valid UCMDB CI type identifier ("unix" for Unix and "nt" for Windows).

Note: The **target_entity type** attribute is only available in the context of a Population flow, and its value must be a valid Groovy expression.

We can describe the creation of the Software entity in the same way.

Automatic Link Population

In the mapping sample in "Population Mapping Files", we saw what is needed to explicitly map a populated link. A mapped target entity must be present for each TQL link element, such as the one shown below:

Using the Generic Adapter automatic link population mechanism, we no longer need to map the TQL link elements with mapping sections such as the one shown above. The framework will generate a link CI instance of the type specified in the TQL with empty properties. This operation will be performed for all the links in the population TQL query.

The sample mapping results in a link CI of type composition being created that has as link ends (end1 and end2) the Node and Running Software CI instances.

You should use Manual Link Population if the link you are populating requires:

- Dynamic link type (using the **type** attribute)
- Link properties

Manual Link Population

The Generic Adapter achieves the population of links by defining (mapping) the three entities required by a link:


- the Link entity
- · the Link's End 1 entity
- . the Link's End 2 entity

Let's analyze the mapping example shown in "Population Mapping Files" on page 281. In this case, we are populating three entity types in UCMDB: Nodes, Running Software, and the Composition link between them. Because we want to populate a link (the link named **RootLink** of type Composition), we also need to map the two link ends. Thus, from looking at the TQL query we see that the entities that need mapping are Node (end 1) and Software (end 2). The way the Generic Adapter framework understands the link structure is by looking at the created entity's element name and definition in the TQL query. Because the population job must also bring instances of Node and Running Software, the needed ends' mapping is already in place.

Types of Link Population


There are two types of link population situations:

Decomposing a complex external entity in multiple related UCMDB entities
 In this case, a complex external entity such as PC is converted into the UCMDB Node and Running Software types, which need to be linked by a Composition link. This type of link only exists in the context of UCMDB.



Links between complex external entities

In this case, we need to model a link between two complex external entities such as PCs.



The Population Connector

The population connector is responsible for retrieving external system data. This data is passed on to the Generic Adapter in the established API format (**ResultTreeNode**), which is then mapped to the UCMDB data structures and inserted in UCMDB through the data-in process.

Similar to the push connector, the population connector can be implemented in both Java and Groovy and must implement the Population Connector Java Interface shown in the figure below.

To configure the population connector, add the following line in the adapter configuration XML file:

```
* Used for both population and federation with the flow type flag which is present in the 
* (@link com.hp.ucmdb.adapters.population.connector.PopulationConnectorInput)
    @param input population request
    @return a population respon
@throws DataAccessException

    # @param env the adapter environment
    * @return a collection of the supported queries

    @param env the adapter environment
    @return a collection of the supported queries

    @param idMapping mapping between source id (external id) and target id (string)
void updateGlobalIDsFromTarget(FCmdbExtenalToTargetIdMappingSet idMapping);

    * @param input the requested information
    * @param output the returned resources
    * @see com.hp.ucmdb.federationspi.adapter.resource.PushQueriesResourceLocator

void locatePopulationQueriesResources(DataAdapterEnvironment env, LocatePopulationQueriesResourcesInput input,
LocatePopulationQueriesResourcesOutput output);
    @param env the Adapter env
@return collection of the supported classes
@throws DataAccessException in case of an error
```

The first method, populate, is the main connector method responsible for retrieving the data from the external system. This method receives as input a population TQL query and returns the results in the generic *ResultTreeNode* format. For more information, see "Achieving Data Push using the Generic Adapter" on page 269. Along with the main business data, the connector also returns status and chunking information.

The second method, getSupportedQueries, indicates the TQLs that are supported by the population connector.

The third and fourth methods refer to more advanced use cases, pushing back the IDs of the populated data and locating the relevant population resources within the adapter for a specific query. For more information about these APIs, see the **push-interfaces.jar** file.

Population Request Input

A population request is defined by a **QueryDefinition** object that describes the UCMDB population query. The population connector is responsible for reading this query object and translating it into the external system's query language.

In addition to the QueryDefinition object, there are:

- getResultTreeNodeStructure Indicates the required structure that the population result must return.
- getFlowType Used to determine if the request to the connector is of type POPULATION or FEDERATION.

getFromDate – Indicates the date from the last synchronization. If the date is null, then the FULL POPULATION runs otherwise the Diff POPULATION runs (if the flow type is FEDERATION the getFromDate method will always return null).

A sample population request is shown in the following figure:

In this example, the request contains the **Nodes Population** query. We can see that the query contains only one TQL element of type **Node**.

ResultTreeNodeStructure

To implement your **PopulationAdapterConnector**, you must read the UCMDB Population TQL, understand what UCMDB is asking for, and provide the results using external system entities. For example, UCMDB may be asking for all Nodes related to Business Service instances in your external system, and it might be that the external system equivalent for a computer is **PC**, which is related to a **Service** entity. Thus, your population connector must return instances of **PC** connected to instances of **Service**. In this case, the mapping will look something like this:

```
|
| Cource_instance query-name="Nodes And BS Population" root-element-name="PC">
| Cource_instance query-name="Nodes And BS Population" root-element-name="PC">
| Cource_instance query-name="Nodes And BS Population" root-element-name="PC">
| Cource_instance |
```

In this case, to return the **PC** instances related to **Service** instances, we are returning a **PC** RTN that contains **Service** as a child node. However, we could have chosen to create the mapping in the format of a **Service** RTN with a **PC** child like this (rendering the mapping invalid):

Thus, to aid the development of the population connector, the population request sent by the Generic Adapter also includes the RTN structure of the data used in the mapping file. This indicates to the implementing connector the needed format of the returned RTN.

In the first case the ResultTreeNodeStructure is:

PC • name Service • name • description

And in the second case the ResultTreeNodeStructure is:

```
Service

name
description
PC
name
```

Population Request Output

Upon processing a population request, the population connector must return a PopulationConnectorOutput.

```
public interface PopulationConnectorOutput {
     * The result trees representing the external entities in (glink com.hp.ucmdb.adapters.push.output.ResultTreeNode) format.
     * <u>Greturn</u> a list of result trees or an empty list
    List<ResultTreeNode> getResultTreeNodes();
     * Adds a result tree to the population output object.
    * <u>Sparam</u> resultTreeNode the result tree to add
    void addResultTreeNode(ResultTreeNode resultTreeNode);
    * This method indicates if the result received is the last chunk of data.
     * <u>Greturn</u> true if this is the last chunk, false otherwise.
    boolean isLastChunk();
     * Set whether this result object is the last chunk or not.
    void setLastChunk(boolean isLastChunk):
    * Returns the status information about the population result.
    UpdateStatus getStatus();
    * Set the population result status.
    void setStatus(UpdateStatus status);
```

This output object contains:

- the queried data, in ResultTreeNode format
- status information (needed in case of failure)
- · chunk information

A sample population response can be seen in the following figure:

In the response above, the connector returned four data instances (corresponding to the UCMDB Node), an empty status (signaling success) and a flag indicating that this is not the last chunk.

Population Adapter Modes

The UCMDB Adapter Framework allows two types of population adapters:

- Standard Population Adapter
 - Is characterized by the absence of the <changes-source/> tag in the adapter XML file
 - Will always bring the full query data from the external system. In this case, the UCMDB Probe Framework is responsible for determining the difference between two consecutive runs. The Probe Framework achieves this by comparing the previous result for the given query with the current result, and computing the differences. Full population is achieved by not comparing the current query result and treating it as the final result. This flow implies that the populated data is not filtered by a "from date", because filtering by a date would render data comparison meaningless.
- · changes-source Population Adapter
 - Is configured by the use of the <changes-source/> tag in the adapter XML file:

 The changes-source adapter is responsible for computing the difference between two consecutive runs.

Deleting CIs when using a changes-source adapter

If you are using a changes-source population adapter, your adapter is responsible for explicitly deleting CIs. This is done by using the **is-deleted** mapping file XML attribute, which accepts a valid Groovy expression.

For example, in the mapping file shown below, the population connector returns **Service** instances. Although the instances are still valid, some CIs that were part of those **Service** instances were deleted. To signal the delete of those CIs, you need to use the **is-deleted** attribute on the **BusinessService** mapping.

Explicit External ID Mapping

There may be situations where the populated data (CIs) will need to have a connector/adapter controlled **ExternalId**. Use the following mapping construct to do this:

In this case, the Root CI is populated with an ExternalId that was created at the connector level and placed on the Computer['external_id_obj']. The creation of the ExternalId can also be done at the mapping level using a Groovy script.

Note: The mechanism of explicitly creating an external ID overrides the target_entity **type** attribute. Thus, when creating an external ID either with the mapping script file or inside the connector, the **type** attribute is ignored, and the final UCMDB type of the populated CI will be the UCMDB type set in the **ExternalId** object.

Global ID Pushback

There are situations where populated CIs in UCMDB need to be kept in sync in the external system as well. For this scenario, the Generic Adapter framework allows the enabling of pushback IDs. To use this feature, a callback is performed for all the CIs that were populated in UCMDB, informing the Population Adapter about the assigned global ID for each CI.

To enable this functionality, add the line that is marked in the example below to the adapter configuration XML file:

You must also implement the PopulationAdapterConnector method as follows:

Achieving Data Federation using the Generic Adapter

Data federation is achieved by using the following:

Federation Mapping Approach	294
Generic Adapter Federation API	295
How to Set Up Federation	298
Sample Data	306
Mapping Conventions	313

Federation Mapping Approach

Federation mapping is achieved by mapping the sub-TQL queries used by the UCMDB Federation Framework to process a federation request. The general idea is that when a federation request is received by the Generic Adapter, what happens is this:

- 1. Analyze the dynamic federation TQL query and compare it with a list of *static* federation TQL queries defined by the user.
- 2. A static TQL query match is made. This TQL query is used to identify the needed mapping for the given federation request and to create the RTN Structure (a Java object that will illustrate the tree node structure that is needed from the connector) input argument that will be supplied to the federation connector. (For more information, see the push-interfaces.jar file)
- 3. Send the federation call with the TQL argument to the connector.
- 4. Map the incoming RTN trees sent by the connector in the same way as for population. See "Achieving Data Population using the Generic Adapter" on page 278.

Federation Link Mapping

Federation Link Mapping is performed automatically as is the case for population link mapping. See "Automatic Link Population" on page 283.

Generic Adapter Federation API

The Generic Adapter Federation API is very similar to the Generic Adapter Population API. This is because the Generic Federation Adapter Java interface is identical to the Generic Population Adapter interface.

```
* * *bbDescription:</boder>
* This Interface is used for implementing
* an adapter to allow the definition of Integration Points.dbr>
* An adapter that implements this Interface will expose
* this ability to run Population flows.dbr>
* The only Population flows.dbr>
* The only Population flow exposed by this adapter is the Simple Flow using (@link #getDataResult(com.hp.ucmdb.federationspl.adapter.federation.f
* which will return the entire data set of data each time, and compare it to the last data set (handled by framework).xp>
* It is highly recommended to allow better link validation by implementing (@link com.hp.ucmdb.federationspl.adapter.ReportsLinks).kbr>
* It is highly recommended to allow better link validation by implementing (@link com.hp.ucmdb.federationspl.adapter.ReportsLinks).kbr>
* It is highly recommended to allow better performance and control.Cpy
* @gee com.hp.ucmdb.federationspl.adapter.ChunkTopologyResultGetter
* @gee com.hp.ucmdb.federationspl.adapter.ChunkTopologyResultGetter
* @gee PopulationAdapter
* @gee PopulationAdapter
* @gee PopulationAdapter extends BasicSourceDataAdapter(

/**

* Retrieves the calculated result of the given (@code QueryOefinition).cbr>
* (1)*
* This method implementation may use the (@code QueryOefinition).cbr>
* (1)*
* This method implementation may use the (@code UpdateStatus) to report warnings for specific CIs or Relations.
* (4)/2
* When implementing this method, it should return the result by being aware to all the conditions
* that appear on the (@code QueryDefinition) like: topology, cardinality, id conditions and property conditions.
* (4)/2
* When implementing this method, one must be aware that different flows may actually be used:ebr>
* (1)*
* When implementing this method, one must be aware that different flows may actually be used:ebr>
* (2)* A layout only flow (a query definition with onditions or id conditions but with out any layout requested).cbr>
* (2)* A layout only flow (a query definition with onditions or id conditions but with out any layo
```

Generic Adapter Connector Interface for Federation

Federation requests use the same method that is used for population requests, so the same population connector implementation can be used. A new attribute was added in the PopulationConnectorInput Java class called **FlowType**. The **FlowType** attribute can have two values, FEDERATION or POPULATION. The Generic Adapter knows the request type based on this attribute.

```
**

* Population Connector that will be used by the UCMDB's Generic Population Adapter to provide the external data. The

* Adata provided by the connector will be mapped to the UCMDB entities by the adapter configured mapping files.

* 
* The Population Connector must be able to process population requests by analyzing the input query and the providing

* corresponding data from the external system.

* @ author Sergiu Indrie

* @ since 10.20

*/

public interface PopulationAdapterConnector extends GenericConnector, DynamicMappingConnector {

/**

* Executes a population request and provides the entities that will be populated in the format of

* {@ link com.hp.ucmdb.adapters.push.output.ResultTreeNode}

* Used for both population and federation with the flow type flag which is present in the

* {@ link com.hp.ucmdb.adapters.population.connector.PopulationConnectorInput}

* @ param input population request

* @ return a population response

* @ throws DataAccessException

*/

PopulationConnectorOutput populate(PopulationConnectorInput input) throws DataAccessException;
```

Supported Federation Queries

The federation and population queries are located in different folders. The **PopulationAdapterConnector** Java interface offers the following two methods for indicating the supported population and federation queries:

- **getPopulationQueries** Returns the collection of queries that the current connector supports for population.
- getFederationQueries Returns the collection of queries that the current connector supports for federation.

```
* Returns the collection of queries the current connector supports for population

* Note: this method is independent to the adapter life cycle (i.e. start/shutdown methods) and must work at all times.

* 
* The method also supports return of queries with their folders path: E.g.

* "Folder/Secondary Folder/Query Name 1"

* "Folder/Secondary Folder/Query Name 2"

* 

* & param env the adapter environment

* & return a collection of the supported queries

*//

*/*

* Returns the collection of queries the current connector supports for federation

* Note: this method is independent to the adapter life cycle (i.e. start/shutdown methods) and must work at all times.

* 
* The method also supports return of queries with their folders path: E.g.

* "Folder/Secondary Folder/Query Name 1"

* "Folder/Secondary Folder/Query Name 2"

* 

* & garam env the adapter environment

* & greturn a collection of the supported queries

*/

* Collection<String> getFederationQueries(DataAdapterEnvironment env);
```


How to Set Up Federation

This section contains:

Configure the Adapter Settings	.298
Set Up Static Federation TQL Queries	.298
Federation Setup Example	.301

Configure the Adapter Settings

For a given a TQL query, the Generic Adapter needs to declare all the nodes from that TQL query in the **<supported-classes>** tag. For example, if the TQL query has the form of an Incident linked to a Node, then you must declare both the node and the incident as supported classes in the adapter settings xml file located in the adapter package ZIP file in the **discoveryPatterns** folder.




Set Up Static Federation TQL Queries

The rules for determining what static TQL queries are needed for a federation TQL query are:

 Look at all the links in the federated TQL query which has one local end and one federated end. If there is such a link, then a static TQL query must be created exactly like the one from the federated TQL query. 2. Look at all nodes that are federated. A static TQL query with each federated node type must be created.

For example, taking the below TQL query as an example, three static TQL queries will be needed:

- Node Linked To Incident because the Node is only local and the incident is federated (this follows rule 1 described above)
- Business Service Linked To Incident because the Business Service is only local and the Incident is federated (this follows rule 1 described above)
- 3. Incident because the Incident is federated (this follows rule 2 described above)



The framework sends the following queries to the adapter:

- A query with only the incident
- A query with the incident linked to the node with a relation of type connection
- A query with the incident linked to the node with a relation of type membership
- A query with the incident linked to the business service with a relation of type connection
- A query with the incident linked to the business service with a relation of type membership

Note: All queries that the federation engine sends to the adapter have the name **User mapping union FTQL**.

After the results of the **User mapping union FTQL** query are processed, other calls are made to retrieve the attributes of the objects. These calls contain a query called **objects layout**. The federation engine will try to get all the attributes for a CI, but the connector does not need to provide them all; it is enough to return only the ones required by the mapping file.

The reason for sending the same query with different relations is because in the TQL query there is a **managed_relationship** type link between the node and incident/business service and incident, but the only valid links when trying to link these CI types together are connection and membership.

By using this approach we only need to define one static TQL with a generic **managed_relationship** type link, instead of defining two almost identical TQLs with different relationship link types, like below.

```
<tql:link from="incident_12" to="node_10050" class="managed_relationship" name="connection_1" id="1"/>
<tql:link from="incident_12" to="node_1000050" class="managed_relationship" name="connection_2" id="2"/>
<tql:link from="datacenter_20050" to="node_10050" class="composition" name="composition_30050" id="30050"/>
```


Also, similar to the relations, the adapter supports subtype CIs. For example, if you have a TQL Incident related to a Node, you can also receive subtypes of the Node (Windows, Unix).

For the TQL query example above, three static TQL queries are required in order to configure the federation:

- Incident TQL query
- Incident To Node TQL query with managed_relationship (if both connection and membership are required)
- Incident To Business Service TQL query with managed_relationship (if both connection and membership are required)


Federation Setup Example

The example will use the following federation TQL query:




For this TQL query, the adapter must declare the supported classes in the adapter settings XML file located in the adapter package ZIP file in the **discoveryPatterns** folder. The supported classes are **node**, **incident**, and **business_service**.

In the Integration Studio, the incident must be selected on the Federation tab, as shown below:



For this TQL query, the following 3 static TQL queries are needed in the adapter:

- 1. Incident (Incident)
- 2. Incident and node with **managed_relationship** (Incident to Node)
- 3. Incident and business_service with managed_relationship (Incident to BusinessService)



For information about how to obtain static TQLs, see "Set Up Static Federation TQL Queries" on page 298. Although these TQL queries have conditions dependent on the data present in UCMDB, this should not affect the structure of the TQL queries or how the mapping is performed.

For each of these TQL queries, a mapping file is required in the adapter:

Mapping for the Incident TQL query


Mapping for the Incident To Node TQL query

```
<?xml version="1.0" encoding="UTF-8"?>
<integration xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:noNamespaceSchemaLocation="../mappings_schema.xsd">
   <info>
      <source name="SM" version="9.40" vendor="HP"/>
<target name="UCMDB" version="10.20" vendor="HP"/>
   </info>
   <target_entities>
      <source_instance query-name="Incident To Node" root-element-name="ucmdbDevice">
         <target entity name="ci">
              <target_mapping name="name" datatype="STRING" value="ucmdbDevice['ConfigurationItem']"/>
             <target_mapping name="global_id" datatype="STRING" value="ucmdbDevice['UcmdbID']"/>
          </target entity>
          <for-each-source-entity count-index="i" source-entities="ucmdbDevice.ucmdbIncident">
             <target_entity name="incident">
                </target_entity>
          </for-each-source-entity>
       </source_instance>
   </target_entities>
</integration>
```

· Mapping for the Incident to Business Service TQL query

```
<?xml version="1.0" encoding="UTF-8"?>
<integration xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:noNamespaceSchemaLocation="../mappings_schema.xsd">
   <info>
      <source name="SM"
                           version="9.40"
      <target name="UCMDB" version="10.20" vendor="HP"/>
  </info>
   <target entities>
     <source_instance query-name="Incident To Business Service" root-element-name="ucmdbDevice">
         <target_entity name="ci">
            <target_mapping name="name" datatype="STRING" value="ucmdbDevice['ConfigurationItem']"/>
             <target_mapping name="global_id" datatype="STRING" value="ucmdbDevice['UcmdbID']"/>
         </target_entity>
         <for-each-source-entity count-index="i" source-entities="ucmdbDevice.ucmdbIncident">
            <target_entity name="incident">
               </target entity>
         </for-each-source-entity>
      </source instance>
   </target_entities>
```

After having the mappings and the static TQL queries in place, federation will work for all subtypes of **node** and **business_service**.




An optimization can be done in this case to reduce the number of mappings. Currently there are 3 mappings needed, but the mappings for **Incident To Node** and **Incident To Business Service** are the same, so you can use only one mapping by putting a wildcard in the query-name parameter as illustrated below:

```
<?xml version="1.0" encoding="UTF-8"?>
<integration xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:noNamespaceSchemaLocation="../mappings_schema.xsd">
   <info>
      <source name="SM" version="9.40" vendor="HP"/>
<target name="UCMDB" version="10.20" vendor="HP"/>
   </info>
   <target entities>
          <target_entity name="ci">
             <target_mapping name="name" datatype="STRING" value="ucmdbDevice['ConfigurationItem']"/>
             <target_mapping name="global_id" datatype="STRING" value="ucmdbDevice['UcmdbID']"/>
          </target_entity>
          <for-each-source-entity count-index="i" source-entities="ucmdbDevice.ucmdbIncident">
                 <target_entity name="incident">
             </target_entity>
          </for-each-source-entity>
      </source instance>
   </target entities>
```

By changing the query name to **Incident To***, it means that all the static TQL queries whose names start with **Incident To** will use this mapping file. Therefore, instead of having 2 mapping files for **Incident to Node** and **Incident To Business Service**, we can use only the one from above (**Incident To***).

Note: It is mandatory that the mapping files have the **query_name** attribute set to the corresponding TQL query like for population (see examples above).

These TQL queries and mapping files must be present in the adapter, as shown below:




Sample Data

By running the Generic Adapter Simulator package, it is possible to federate the following queries:

- 1. Incident Federation
- 2. Incident Related To Node Federation
- 3. Incident Related To Node and Business Service Federation

To ensure the sample federation TQL queries work as expected, create the following CIs in UCMDB:




Also, 3 new TQL queries are required in order to perform federation. Go to Modeling Studio, create the following 3 new TQL queries, and set the integration point on the incident:

- 4. Incident Federation
- 5. Incident Related To Node Federation
- 6. Incident Related To Node And Business Service Federation


This section contains:

Incident Federation

In this case, all incidents from the **gs** integration point are being requested:




Running this federated TQL query obtains the following result data (four instances of Incident):




Incident Related to Node Federation

In this case, all the incidents related to Node instances from UCMDB are being federated:




The result of the TQL query is:




Incident Related to Node and Business Service Federation

In this case, all incidents related to Node and Business Service instances are being federated:



The result of the TQL query is:



Mapping Conventions

To ensure that the Generic Adapter is able to process federation requests, the following preconditions must be met:

- Class Population Requirement. All nodes in the ResultTreeNodes (RTNs) results returned by the
 federation connector must be valid classes from the adapter-defined class model. For example, if
 the returned RTN is amComputer with a child of amPortfolio, both amComputer and
 amPortfolio must be classes defined in the ClassModel object returned by the adapter-specific
 ClassModelConnector.
- Relationship Population Requirement. A parent-child relationship in the RTN results returned by
 the federation connector implies a valid link between the parent RTN node and the child RTN node.
 For example, if the returned RTN is amComputer with a child of amPortfolio, then a
 relantionship/link between amComputer and amPortfolio must exist and must be defined as a
 ValidRelation in the ClassModel object returned by the adapter-specific ClassModelConnector.

Reconciliation

When using the Generic Adapter framework to populate or federate data, the CIs must always have the required reconciliation data in order to be accepted into UCMDB. When populating CI types such as Running Software that require a container CI type, always make sure to populate the needed container fields (for example, **root_container_name** and **product_name**) and the container CI (for example, **Node**). To populate CIs that depend on a root container, the CI, its root container, and the link between them must be created in the same step (either with explicit link population or auto-complete link population between the two CIs).

In addition, when mapping the populated/federated CIs, consider mapping the **global_id** attribute, as that will greatly aid the UCMDB reconciliation engine and should guarantee the exact CI reconciliation.

Generic Adapter API

The API exposed by the Generic Adapter framework is:

```
<UCMDB_Server>\lib\push-interfaces.jar
<UCMDB_Server>\lib\integrationFramework\GenericAdapter\generic-adapter-api-
factory.jar
```

The development of your Generic Adapter instance might also require the Federation API:

```
<UCMDB Server>\lib\federation-api.jar
```

Resource Locator APIs

The resource locator APIs can be used when editing Generic Adapter jobs. Implement the general and population resource locator APIs to help find the adapter resources that are related to a selected job's TQL query.

The following image shows General Resource Locator API in the Generic Connector Java Interface:

The following image shows Population Query Resource Locator API in PopulationAdapterConnector Java Interface:

To see the related resources for a job's TQL query:

- 1. In the Integration Studio, select an integration point.
- 2. In the Integration Jobs pane, select a job and click **Edit Query Resources** 2.

Create a Generic Adapter Package

A Generic Adapter package is similar to an Enhanced Generic Push Adapter package. To create the initial skeleton ZIP archive, it is recommended to copy an existing Generic Adapter package and customize it as required. For more information about the adapter package, see "Achieving Data Push using the Generic Adapter" on page 269.

The differences between an existing Enhanced Generic Push Adapter package and a Generic Adapter package are:

- · Adapter XML differences
 - The adapter class is changed from PushAdapter to GenericAdapter:

```
<className>com.hp.ucmdb.adapters.push.PushAdapter<className>com.hp.ucmdb.adapters.GenericAdapter
```

• The adapter capabilities include population

Along with the definition of the Population connector, performed by the adapter setting:

<adapter-setting name="PopulationConnector.class.name">com.hp.ucmdb,connector.dummy.DummyPopulationConnector</adapter-setting>

the Generic Adapter (using the population feature) also requires the definition of the Push Connector class:

<adapter-setting name="PushConnector.class.name">com.hp.ucmdb, connector.dummy.DummyPushConnector</adapter-setting>

Mapping file folders

As opposed to the Enhanced Generic Push Adapter (which requires its mapping files to be located in the <adapter_package_zip>/adapterCode/<adapter_name>/mappings folder, the Generic Adapter requires its mappings to be placed in three separate folders (one each for push, population, and federation). The required folders are:

```
<adapter_package_zip>/adapterCode/<adapter_name>/mappings/push
<adapter_package_zip>/adapterCode/<adapter_name>/mappings/population
<adapter_package_zip>/adapterCode/<adapter_name>/mappings/federation
```

where **<adapter_package_zip>** refers to the zip archive that you will create for the generic adapter package.

Note: Although the Generic Adapter supports all three types of data synchronization (push, population, and federation), a specific Generic Adapter can choose to supply only a subset of those types.

Points to remember when creating a new adapter from an existing adapter

- TestAdapter\discoveryPatterns\TestAdapter.xml
- Modify the TestAdapter.xml file:

```
o <pattern xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
id="TestAdapter" xsi:noNamespaceSchemaLocation="../../Patterns.xsd"
description="..." schemaVersion="9.0" displayName="...">
```

- o <adapter-id>TestAdapter</adapter-id>
- The ZIP file containing the new adapter should have the same name as the adapter itself -TestAdapter.

Build an Adapter Package

Ensure that the adapter package contains the following folders:

- adapterCode. Under this folder, create a folder named PushExampleAdapter, which will contain
 the .jar file we created from the PushExampleAdapter.java. It will also contain a folder named
 mappings, where you can place the mapping file created earlier, computerIPMapping.xml. It
 should also contain another folder named scripts that contains the PushFunctions.groovy file.
- **discoveryConfigFiles.** To contain configuration files such as the error codes used when reporting an error using UpdateResult. In this example, the folder is empty.
- discoveryPatterns. To contain the push_example_adapter.xml.
- **tql.** To contain the TQL query created for the example. This folder is optional, but when the package is deployed, the TQL query is automatically created.

Enable/Disable Attribute and Link Validation at Adapter Level

You can enable or disable attribute and link validation at adapter level for generic adapters by adding the following setting:

To enable adapter level validation of attribute and link, set the adapter setting **enable.attributes.links.validation** to **true**.

To disable adapter level validation of attribute and link, set the adapter setting **enable.attributes.links.validation** to **false**.

Note: If the setting is not present, its default value is **true**, which means that by default the attribute and link validation is enabled.

Population TQL Queries

The TQL queries to be used for population jobs must be included in the Generic Adapter's ZIP archive and deployed with the adapter in UCMDB. The indicated TQL query must exist in UCMDB when a population request is made, during the population flow.

These TQL queries must be included in the <zip>/tql/<folder_1>/../<folder_n>. Following is an example of the folder structure:

▼ tql.Integration.Generic Adapter Sample

▼ population

Node Links Population.xml

Nodes And IP Population.xml

Nodes And Software Population.xml

Nodes Population.xml

To push

Computer Push.xml

Computer Relation Push.xml

Although population TQL queries are placed in the folder indicated above, the Population connector must also confirm the supported population TQL queries in the corresponding method from the Java interface. For more information, see "The Population Connector" on page 285.

Sample Package

```
FOLDERS
M_BS.xml
          M_incident.xml
          M_Node.xml
      Node And Ip Population with links.xml
          Node Links Population.xml
          Node with ID.xml
          Nodes And IP Population.xml
          Nodes And Software Population.xml
          Nodes Population 2.xml
          Nodes Population.xml
      Computer Push.xml
          Computer Relation Push.xml
        generic-adapter.xsd
       🖺 generic-adapter-sample.jar
 🔓 computer.json
     UcmdbDevices.json

☐ GenericAdapterSample.xml

 ₩ 🗁 tql

▼  Integration

▼ Generic Adapter Sample

      M_BS.xml
           M_Incident.xml
           M_Node.xml
          🖰 Incident Federation.xml
          Incident Related to Node and Business Service Federation.xml
          Incident Related to Node Federation.xml
      Node And Ip Population with links.xml
          Node Links Population.xml
         Node with ID.xml
          Nodes And IP Population.xml
          Nodes And Software Population.xml
          Nodes Population.xml
      Computer Push.xml
          Computer Relation Push.xml
    descriptor.xml
```

Differences Between Push and Population Mapping

Although both push and population mapping files have the same underlying XML schema, the files have slightly different interpretations. For more information, see "Generic Adapter XML Schema Reference" on the next page.

In the following push mapping example, the interpretation is: take the results of the "Computer Push" TQL query (run in UCMDB) and present in the Root tree structure, and create the amComputer entity which will later on be sent to AM.

In the following population mapping example, the interpretation is: take the results of the "Nodes Population" TQL query (run in the external system) and present in the PC tree structure, and create the UCMDB Root entity (of type Node; as indicated by the TQL query), which will later be added in UCMDB.

Generic Adapter Log Files

For troubleshooting and debugging, use the following:

- Adjust logging levels in these files (set the loglevel variable to TRACE for the most detailed results):
 - <UCMDB_DataFlowProbe>\conf\log\fcmdb.push.properties
 - **<UCMDB_DataFlowProbe>** is the UCMDB Data Flow Probe installation directory.
 - <UCMDB_Server>\conf\log\reconciliation.properties
 - **<UCMDB_Server>** is the UCMDB Server installation directory.
- Analyze the following Generic Adapter log files:
 - <UCMDB_DataFlowProbe>\runtime\log\fcmdb.push.all.log
 - <UCMDB_DataFlowProbe>\runtime\log\fcmdb.push.configuration.log
 - <UCMDB_DataFlowProbe>\runtime\log\fcmdb.push.connector.all.log
 - <UCMDB_DataFlowProbe>\runtime\log\fcmdb.push.connector.configuration.log
 - <UCMDB_DataFlowProbe>\runtime\log\fcmdb.push.mapping.log
 - <UCMDB_DataFlowProbe>\runtime\log\fcmdb.push.all.log
- · Analyze the following generic log files:
 - <UCMDB_DataFlowProbe>\runtime\log\probe-error.log
 - <UCMDB_DataFlowProbe>\runtime\log\WrapperProbeGw.log
 - <UCMDB_Server>\runtime\log\error.log
 - <UCMDB_Server>\runtime\log\cmdb.reconciliation.log

Adapters Using the Generic Adapter Framework

As a reference for developing your custom Generic Adapter, refer to the following adapters that shipped with UCMDB as implementation guidelines, which should speed up your adapter development:

- · The Asset Manager Adapter
- The Service Manager Adapter

Generic Adapter XML Schema Reference

The Generic Adapter XML Schema can be found in the **cmdb.jar** file under the **schema** directory. The schema file should be referenced while writing Generic Adapter mapping files in external editors. The full path for the XSD file is:

<UCMDB_Server_Home>/lib/cmdb.jar/schema/generic-adapter.xsd

Part II: Using APIs

Chapter 9: Introduction to APIs

This chapter includes:

APIs Overview	324
APIS Overview	

APIs Overview

The following APIs are included with Universal CMDB:

- UCMDB Java API. Explains how third-party or custom tools can use the Java API to extract data
 and calculations and to write data to the UCMDB (Universal Configuration Management database).
 For details, see "HPE Universal CMDB API" on page 325.
- UCMDB Web Service API. Enables writing configuration item definitions and topological relations
 to UCMDB, and querying the information with TQL and ad hoc queries. For details, see "HPE
 Universal CMDB Web Service API" on page 335.
- Data Flow Management Java API. Enables managing probes, jobs, triggers and credentials for Data Flow Management. For details, see "Data Flow Management Java API" on page 438.
- Data Flow Management Web Service API. Enables managing probes, jobs, triggers and credentials for Data Flow Management. For details, see "Data Flow Management Web Service API" on page 443.

Note: To gain the full value of the API documentation, it is recommended to access the online documentation. The PDF version does not have the links into the API documentation that is generated in html format.

Chapter 10: HPE Universal CMDB API

This chapter includes:

Conventions	325
Using the HPE Universal CMDB API	325
General Structure of an Application	327
Put the API Jar File in the Classpath	329
Create an Integration User	330
UCMDB API Use Cases	332
Examples	334

Conventions

This chapter uses the following conventions:

- UCMDB refers to the Universal Configuration Management database itself. Universal CMDB refers to the application.
- UCMDB elements and method arguments are spelled in the case in which they are specified in the interfaces.

For full documentation on the available APIs, refer to the HP UCMDB API Reference.

These files are located in the following folder:

\\<UCMDB root directory>\hp\UCMDB\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\UCMDB_JavaAPI\index.html

Using the HPE Universal CMDB API

Note: Use this chapter in conjunction with the API Javadoc, available in the online Documentation Library.

The Universal CMDB API is used to integrate applications with the Universal CMDB (CMDB). The API provides methods to:

- · Add, remove, and update CIs and relations in the CMDB
- Retrieve information about the class model
- · Retrieve information from the UCMDB history
- Run what-if scenarios
- · Retrieve information about configuration items and relationships

Methods for retrieving information about configuration items and relationships generally use the Topology Query Language (TQL). For details, see Topology Query Language in the *HPE Universal CMDB Modeling Guide*.

Users of the Universal CMDB API should be familiar with:

- The Java programming language
- Universal CMDB

This section includes the following topics:

- "Uses of the API" below
- "Permissions" below

Uses of the API

The API is used to fulfill a number of business requirements. For example, a third-party system can query the class model for information about available configuration items (CIs). For more use cases, see "UCMDB API Use Cases" on page 332.

Permissions

The administrator provides login credentials for connecting with the API. The API client needs the user name and password of an integration user defined in the CMDB. These users do not represent human users of the CMDB, but rather applications that connect to the CMDB.

In addition, the user must have the **Access to SDK** general action permission in order to log in.

Caution: The API client can also work with regular users as long as they have API authentication permission. However, this option is not recommended.

For details, see "Create an Integration User" on page 330.

General Structure of an Application

There is only one static factory, the UcmdbServiceFactory. This factory is the entry point for an application. The UcmdbServiceFactory exposes getServiceProvider methods. These methods return an instance of the **UcmdbServiceProvider** interface.

The client creates other objects using interface methods. For example, to create a new query definition, the client:

- 1. Gets the query service from the main CMDB service object.
- 2. Gets a query factory object from the service object.
- 3. Gets a new query definition from the factory.

```
UcmdbServiceProvider provider =
   UcmdbServiceFactory.getServiceProvider(HOST_NAME, PORT);
UcmdbService ucmdbService =
   provider.connect(provider.createCredentials(USERNAME,
   PASSWORD), provider.createClientContext("Test"));
TopologyQueryService queryService = ucmdbService.getTopologyQueryService();
TopologyQueryFactory factory = queryService.getFactory();
QueryDefinition queryDefinition = factory.createQueryDefinition("Test Query");
queryDefinition.addNode("Node").ofType("host");
Topology topology = queryService.executeQuery(queryDefinition);
System.out.println("There are " + topology.getAllCIs().size() + " hosts in uCMDB");
```

The services available from **UcmdbService** are:

Service Methods	Use
getAuthorizationModelService	Perform authorization operations (create users and user groups, assign roles to users and groups, and so on).
getClassModelService	Information about types of CIs and relations
getConfigurationService	Infrastructure settings management, for server configuration
getDataStoreMgmtService	Query data store information including which CIs and attributes will be federated.

Service Methods	Use
getDDMConfigurationService	Configure the Data Flow Management system
getDDMManagementService	Analyze and view the progress, results, and errors of the Data Flow Management system
getDDMZoneService	Import and export management zones (with their activities).
getHistoryService	Information about history of monitored CIs (changes, removals, and so on)
getImpactAnalysisService	Run impact analysis scenario (also known as correlation).
getLicensingService	Query information about licenses installed in the system.
getMultipleCMDBService	Convert between global IDs and UCMDB IDs.
getMultiTenancyService	Create, read, update, and delete tenants.
getPersistencyService	Persist binary data into key-value pairs.
getQueryManagementService	Manage access to queries - save, delete, list existing. Also provides query validation and discovery of queries dependencies.
getReconciliationService	Supplies identification and merging capabilities.
getResourceBundleManagementService	Resource tagging ("bundling" services). Allows explicit creation of new tags and removal of tags from all tagged resources.
getResourceManagementService	Deploy resource packages (of TQL queries, views, users, and so on) to the system.
getSecurityService	Verify whether credentials are valid.
getServerService	Query generic information about the system.
getSnapshotService	Provide services for managing snapshots (get, save, compare, and so on)
getSoftwareSignatureService	Define software items to be discovered by the Data Flow Management system

Service Methods	Use
getStateService	Provide services for managing states (list, add, remove, and so on)
getSystemHealthService	Provide system health services (basic system performance indicators, capacity and availability metrics)
getTopologyQueryService	Note: Starting from version 10.00, you can not get the discoveryjob CI Type instance, because it is saved in Unified Resource Manager (URM). You can use DDMConfigurationService instead. For more details, see KM02529119.
getTopologyUpdateService	Change information in the IT universe
getUcmdbVersion	Query UCMDB and content pack versions and build information.
getViewArchiveService	View result archiving services. Allows saving the current view result and retrieving previously saved results.
getViewService	View execution service (execute definition, execute saved) and management service (save, delete, list existing). Also provides view validation and dependencies discovery.

The client communicates with the server over HTTP(S).

Put the API Jar File in the Classpath

The use of this API set requires the file ucmdb-api.jar. You can download the file by entering https://<localhost>:8443 in a Web browser where localhost is the machine where UCMDB is installed and clicking the API Client Download link.

Put the .jar file in the classpath before compiling or running your application.

Note: Use of the UCMDB Java API Jar requires you to have JRE version 6 or later installed.

Create an Integration User

You can create a dedicated user for integrations between other products and UCMDB. This user enables a product that uses the UCMDB client SDK to be authenticated in the server SDK and execute the APIs. Applications written with this API set must log on with integration user credentials.

Caution: It is also possible to connect with a regular UCMDB user (for instance, admin). However, this option is not recommended. To connect with a UCMDB user, you must grant the user API authentication permission.

To create an integration user:

1. Launch the Web browser and enter the server address, as follows:

https://localhost:8443/jmx-console

You may have to log in with a user name and password.

- 2. Under UCMDB, click service=UCMDB Authorization Services.
- 3. Locate the **createUser** operation. This method accepts the following parameters:
 - o customerId. The customer ID.
 - **username**. The integration user's name.
 - userDisplayName. The integration user's display name.
 - **userLoginName**. The integration user's login name.
 - password. The integration user's password.

The default password policy requires the password to include at least one of each of the four following types of characters:

- · Uppercase alphabetic characters
- Lowercase alphabetic characters
- Numeric characters
- Symbol characters ,\:/. _?&%=+-[]()|

It also requires the password to adhere to the minimum length, which is set by the **Password minimum length** infrastructure setting.

4. Click Invoke.

- 5. In a single-tenant environment, locate the **setRolesForUser** method and enter the following parameters:
 - userName. The integration user's name.
 - o roles. SuperAdmin.

Click Invoke.

- 6. Locate the setUserServerAdministratorValue method and enter the following parameters:
 - customerID. The customer ID.
 - userLoginName. The integration user's login name.
 - serverAdministratorValue. Select True.

Click Invoke.

- 7. In a multi-tenant environment, locate the **grantRolesToUserForAllTenants** method and enter the following parameters to assign the role in connection with all tenants:
 - **userName**. The integration user's name.
 - roles. SuperAdmin.

Click Invoke.

Alternatively, to assign the role in connection with specific tenants, invoke the **grantRolesToUserForTenants** method, using the same userName and roles parameter values. For the **tenantNames** parameter, enter the required tenants.

- 8. Either create more users, or close the JMX console.
- 9. Log on to UCMDB as an administrator.
- 10. From the **Administration** tab, run **Package Manager**.
- 11. Click the Create custom package icon.
- 12. Enter a name for the new package, and click **Next**.
- 13. In the Resource Selection tab, under **Settings**, click **Users**.
- 14. Select a user or users that you created using the JMX console.
- 15. Click **Next** and then **Finish**. Your new package appears in the Package Name list in Package Manager.
- 16. Deploy the package to the users who will run the API applications.

For details, see the section "How to Deploy a Package" in the *HPE Universal CMDB Administration Guide*.

Note: The integration user is per customer. To create a stronger integration user for cross-customer usage, use a **systemUser** with the **isSuperIntegrationUser** flag set to **true**. Use the **systemUser** methods (**removeUser**, **resetPassword**, **UserAuthenticate**, and so on).

There are two out-of-the-box system users. It is recommended to change their passwords after installation using the **resetPassword** method.

- sysadmin/sysadmin
- UISysadmin/UISysadmin (this user is also the SuperIntegrationUser).

If you change the UISysadmin password using **resetPassword**, you must do the following:

- i. In the JMX Console, locate the **UCMDB-UI:name=UCMDB Integration** service.
- ii. Run **setCMDBSuperIntegrationUser** with the user name and new password of the integration user.

UCMDB API Use Cases

The use cases listed in this section assume two systems:

- · Universal CMDB server
- A third-party system that contains a repository of configuration items

This section includes the following topics:

- "Populating the CMDB " below
- "Querying the CMDB" on the next page
- "Querying the Class Model" on the next page
- "Analyzing Change Impact" on the next page

Populating the CMDB

Use cases:

- A third-party asset management updates the CMDB with information available only in asset management
- A number of third-party systems populate the CMDB to create a central CMDB that can track changes and perform impact analysis
- A third-party system creates Configuration Items and Relations according to third-party business logic, to leverage the UCMDB query capabilities

Querying the CMDB

Use cases:

- A third-party system gets the Configuration Items and Relations that represent the SAP system by retrieving the results of the SAP TQL
- A third-party system gets the list of Oracle servers that have been added or changed in the last five hours
- A third-party system gets the list of servers whose host name contains the lab substring
- A third-party system finds the elements related to a given CI by getting its neighbors

Querying the Class Model

Use cases:

- A third-party system enables users to specify the set of data to be retrieved from the CMDB. A user
 interface can be built over the class model to show users the possible properties and prompt them
 for required data. The user can then choose the information to be retrieved.
- A third-party system explores the class model when the user cannot access the UCMDB user interface.

Analyzing Change Impact

Use case:

 A third-party system outputs a list of the business services that could be impacted by a change on a specified host.

Examples

See the following code samples:

- Create a Connection
- Create and Execute an Ad Hoc Query
- Create and Execute a View
- Add and Delete Data
- Execute an Impact Analysis
- Query the Class Model
- Query a History Sample

These files are located in the following directory:

\\<UCMDB root directory>\hp\UCMDB\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\JavaSDK_Samples\

Chapter 11: HPE Universal CMDB Web Service API

This chapter includes:

Conventions	
HPE Universal CMDB (UCMDB) Web Service API Overview	336
Getting Started with HPE Universal CMDB Web Service	339
Call the HP Universal CMDB Web Service	341
Query the CMDB	341
Update the CMDB	345
Query the UCMDB Class Model	346
Query for Impact Analysis	348
UCMDB General Parameters	349
UCMDB Output Parameters	352
UCMDB Query Methods	353
UCMDB Update Methods	366
UCMDB Impact Analysis Methods	369
Actual State Web Service API	371
UCMDB Web Service API Use Cases	373
Examples	375

Conventions

This chapter uses the following conventions:

- UCMDB refers to the Universal Configuration Management database itself. Universal CMDB refers to the application.
- UCMDB elements and method arguments are spelled in the case in which they are specified in the

schema. An element or argument to a method is not capitalized. For example, a relation is an element of type Relation passed to a method.

For full documentation on the request and response structures, refer to the HP UCMDB Web Service API Reference. These files are located in the following folder:

<UCMDB root directory>\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\CMDB_
Schema\webframe.html

HPE Universal CMDB (UCMDB) Web Service API Overview

Note: Use this chapter in conjunction with the UCMDB schema documentation, available in the online Documentation Library.

The Universal CMDB Web Service API is used to integrate applications with the HPE Universal CMDB (UCMDB). The API provides methods to:

- · Add, remove, and update CIs and relations in the CMDB
- · Retrieve information about the class model
- Retrieve impact analyses
- Retrieve information about configuration items and relationships
- Manage credentials: view, add, update, and remove
- Manage jobs: view status, activate, and deactivate
- Manage probe ranges: view, add, and update
- Manage triggers: add or remove a trigger CI, and add, remove, or disable a trigger TQL
- · View general data on domains and Probes

Methods for retrieving information about configuration items and relationships generally use the Topology Query Language (TQL). For details, see Topology Query Language in the *HPE Universal CMDB Modeling Guide*.

Users of the Universal CMDB Web Service API should be familiar with:

- The SOAP specification
- An object-oriented programming language such as C++, C# or Java

- Universal CMDB
- Data Flow Management

This section includes the following topics:

- "Uses of the API" below
- · "Permissions" below

Uses of the API

The UCMDB Web Services API is used to fulfill a number of business requirements. For example:

- A third-party system can query the class model for information about available configuration items (CIs).
- A third-party asset management tool can update the CMDB with information available only to that tool, thereby unifying its data with data collected by HP applications.
- A number of third-party systems can populate the CMDB to create a central CMDB that can track changes and perform impact analysis.
- A third-party system can create entities and relations according to its business logic, and then write the data to the CMDB to take advantage of the CMDB query capabilities.
- Other systems, such as the Release Control (CCM) system, can use the Impact Analysis methods for change analysis.

Permissions

To access the WSDL file for the web service, go to:

http://localhost:8080/axis2/services/UcmdbService?wsdl. You will need to provide server administrator user credentials to view the WSDL file.

Note: The Axis2 administration console is not accessible.

The user must have the Run Legacy API general action permission in order to log in.

The following table displays the additional required permissions for each Web Service API command:

Web Service API command	Required Permissions
addClsAndRelations	General Action: Data Update

Web Service API command	Required Permissions
deleteCIsAndRelations updateCIsAndRelations	
executeTopologyQueryByName(AdHoc) executeTopologyQueryByNameWithParameters(AdHoc) executeTopologyQueryWithParameters(AdHoc)	General Action: Run Query by Definition For each query: View permission
getTopologyQueryExistingResultByName getTopologyQueryResultCountByName releaseChunks pullTopologyMapChunks getCINeighbours getFilteredCIsByType getCIsById getCIsByType getRelationsById	General Action: View CIs For each query: View permission
getQueryNameOfView	General Action: View CIs For each view: View permission
getChangedCls	General Action: View History, View CIs
calculateImpact getImpactPath getImpactRulesByGroupName getImpactRulesByNamePrefix	General Action: Run Impact Analysis
getAllClassesHierarchy getClassAncestors getCmdbClassDefinition	None

Note: When the root context has been changed in UCMDB, follow these steps to enable access to the Web Service API:

1. Open the \UCMDB\UCMDBServer\deploy\axis2\WEB-INF\web.xml configuration file and locate the following section:

```
<servlet-class>
org.apache.axis2.transport.http.AxisServlet
</servlet-class>
```

Add the following lines after that:

```
<init-param>
<param-name>axis2.find.context</param-name>
<param-value>false</param-value>
</init-param>
```

2. Open the \UCMDB\UCMDBServer\deploy\axis2\WEB-INF\conf\axis2.xml configuration file and locate the following line:

```
<parameter name="enableSwA" locked="false">false</parameter>
```

Add the following line after it:

```
<parameter name="contextRoot" locked="false">test1/setup1/axis2
</parameter>
```

where test1/setup1 is your root context.

(To remove the root context, remove the text added to the path.)

3. Restart the UCMDB server.

Getting Started with HPE Universal CMDB Web Service

How to Generate the Java Web Service Client Jar

- 1. Download and install Axis2
 - a. Go to https://axis.apache.org/axis2/java/core/index.html, download and extract the latest Axis2 package. (Currently axis2-1.7.3-bin.zip)
 - b. Set up the AXIS2_HOME environment variable to the extraction directory. (In this example, C:\axis2-1.7.3)
- 2. Download and install Ant
 - a. Go to http://ant.apache.org/bindownload.cgi, download and extract the latest Ant package.
 (Currently apache-ant-1.9.7-bin.zip)

- b. Add the Ant **bin** directory to the Windows Path environment variable (In this case **C:\apache-ant-1.9.7**)
- 3. Obtain the needed UCMDB WSDL
 - a. Create a temp folder: C:\Temp
 - b. Copy the file <UCMDB_install_dir>\deploy\axis2\WEB-INF\services\ucmdb_service.aar from previous step into the Temp folder.
 - c. The ucmdb_service.aar file is a zip file. You can extract its content to C:\Temp.

Note: If for some reason Windows is not recognizing it as a zip file, change its extension to **.zip**. Depending on archiving utility a folder **ucmdb_service** may be created inside the **Temp** folder.

- 4. Generate the Web Service client jar
 - a. Create a working directory, for example, C:\WS Client.
 - b. Switch to the working directory and execute the following command to build the Java source files and the Ant **build.xml** file:

```
"C:\axis2-1.7.3\bin\wsdl2java.bat" -s -d adb -S generated_ws_code_client -uri "C:\Temp\ucmdb_service\META-INF\UcmdbService.wsdl" -p com.hp.ucmdb.generated.services
```

c. Execute the following command to build the Java client JAR file:

ant

- d. If everything completes successfully, you should have the following:
 - C:\WS Client\build\classes Will contain the generated classes
 - C:\WS Client\build\lib\UcmdbService-test-client.jar

How to Write a Simple Java Web Service Client for UCMDB

The following is an example for a Web Service client.

- 1. Inside the working directory, create a new folder **WS_Demo\src**, and switch to this folder.
 - a. Create a new file named **Demo.java**, and copy the content of the **WebServiceAPI_** Samples/WebServAPI_Example_Base_Class.html into this new file.
 - b. Create a new file named QueryDemo.java, and copy the content of the WebServiceAPI_ Samples/WebServAPI_QueryExample.html into this new file.
- Import the WS_Demo project using your favorite IDE.

Add the following folders as 3rd party libraries:

- C:\WS Client\build\lib\ We need the UcmdbService-test-client.jar file from this folder.
- C:\axis2-1.7.3\lib\ We need all jars from this folder.

Call the HP Universal CMDB Web Service

Use standard SOAP programming techniques in the Universal CMDB Web Service API to enable calling server-side methods. If the statement cannot be parsed or if there is a problem invoking the method, the API methods throw a SoapFault exception. When a SoapFault exception is thrown, the UCMDB populates one or more of the error message, error code, and exception message fields. If there is no error, the results of the invocation are returned.

SOAP programmers can access the WSDL at:

http://<server>[:port]/axis2/services/UcmdbService?wsdl

The port specification is only necessary for non-standard installations. Consult your system administrator for the correct port number.

The URL for calling the service is:

http://<server>[:port]/axis2/services/UcmdbService

For examples of connecting to the CMDB, see "UCMDB Web Service API Use Cases" on page 373.

Query the CMDB

The CMDB is queried using the APIs described in "UCMDB Query Methods" on page 353. The queries and the returned CMDB elements always contain real UCMDB IDs. For examples of using query methods, see Query Example.

This section includes the following topics:

- "Just In Time Response Calculation" below
- "Processing Large Responses" below
- "Specifying Properties to Return" on the next page
- "Concrete Properties" on the next page
- "Derived Properties" on page 344
- "Naming Properties" on page 344
- "Other Property Specification Elements" on page 344

Just In Time Response Calculation

For all query methods, the UCMDB server calculates the values requested by the query method when the request is received, and returns results based on the latest data. The result is always calculated at the time the request is received, even if the TQL query is active and there is a previously calculated result. Therefore, the results of running a query returned to the client application may be different from the results of the same query displayed on the user interface.

Tip: If your application uses the results of a given query more than once and the data is not expected to change significantly between uses of the result data, you can improve performance by having the client application store the data rather than repeatedly running the query.

Processing Large Responses

The response to a query always includes the structures for the data requested by the query method, even if no actual data is being transmitted. For many methods where the data is a collection or map, the response also includes the ChunkInfo structure, comprised of chunksKey and numberOfChunks. The numberOfChunks field indicates the number of chunks containing data that must be retrieved.

The maximum transmission size of data is set by the system administrator. If the data returned from the query is larger than the maximum size, the data structures in the first response contain no meaningful information, and the value of the numberOfChunks field is 2 or greater. If the data is not larger than the maximum, the numberOfChunks field is 0 (zero), and the data is transmitted in the first response. Therefore, in processing a response, check the numberOfChunks value first. If it is greater than 1, discard the data in the transmission and request the chunks of data. Otherwise, use the data in the response.

For information on handling chunked data, see "pullTopologyMapChunks" on page 364 and "releaseChunks" on page 365.

Specifying Properties to Return

CIs and relations generally have many properties. Some methods that return collections or graphs of these items accept input parameters that specify which property values to return with each item that matches the query. The CMDB does not return empty properties. Therefore, the response to a query may have fewer properties than requested in the query.

This section describes the types of sets used to specify the properties to return.

Properties can be referenced in two ways:

- · By their names
- By using names of predefined properties rules. Predefined properties rules are used by the CMDB to create a list of real property names.

When an application references properties by name, it passes a PropertiesList element.

Tip: Whenever possible, use PropertiesList to specify the names of the properties in which you are interested, rather than a rule-based set. The use of predefined properties rules usually results in returning more properties than needed, and incurs a price in performance.

There are two types of predefined properties: qualifier properties and simple properties.

- Qualifier properties. Use this when the client application should pass a QualifierProperties
 element (a list of qualifiers that can be applied to properties). The CMDB converts the list of
 qualifiers passed by the client application to the list of the properties to which at least one of the
 qualifiers applies. The values of these properties are returned with the CI or Relation elements.
- Simple properties. To use simple rule-based properties, the client application passes a SimplePredefinedProperty or SimpleTypedPredefinedProperty element. These elements contain the name of the rule by which the CMDB generates the list of properties to return. The rules that can be specified in a SimplePredefinedProperty or SimpleTypedPredefinedProperty element are CONCRETE, DERIVED, and NAMING.

Concrete Properties

Concrete properties are the set of properties defined for the specified CIT. The properties added by derived classes are not returned for instances of those derived classes.

A collection of instances returned by a method may consist of instances of a CIT specified in the method invocation and instances of CITs that inherit from that CIT. The derived CITs inherit the

properties of the specified CIT. In addition, the derived CITs extend the parent CIT by adding properties.

Example of Concrete Properties:

CIT T1 has properties P1 and P2. CIT T11 inherits from T1 and extends T1 with properties P21 and P22.

The collection of CIs of type T1 includes the instances of T1 and T11. The concrete properties of all instances in this collection are P1 and P2.

Derived Properties

Derived properties are the set of properties defined for the specified CIT and, for each derived CIT, the properties added by the derived CIT.

Example of Derived Properties:

Continuing the example from concrete properties, the derived properties of instances of T1 are P1 and P2. The derived properties of instances of T11 are P1, P2, P21, and P22.

Naming Properties

The naming properties are display_label and data_name.

Other Property Specification Elements

PredefinedProperties

PredefinedProperties can contain a QualifierProperties element and a SimplePredefinedProperty element for each of the other possible rules. A PredefinedProperties set does not necessarily contain all types of lists.

PredefinedTypedProperties

PredefinedTypedProperties is used to apply a different set of properties to each CIT.

PredefinedTypedProperties can contain a QualifierProperties element and a

SimpleTypedPredefinedProperty element for each of the other applicable rules. Because

PredefinedTypedProperties is applied to each CIT individually, derived properties are not relevant. A PredefinedProperties set does not necessarily contain all applicable types of lists.

CustomProperties

CustomProperties can contain any combination of the basic PropertiesList and the rule-based property lists. The properties filter is the union of all the properties returned by all the lists.

CustomTypedProperties

CustomTypedProperties can contain any combination of the basic PropertiesList and the applicable rule-based property lists. The properties filter is the union of all the properties returned by all the lists.

TypedProperties

TypedProperties is used to pass a different set of properties for each CIT. TypedProperties is a collection of pairs composed of type names and properties sets of all types. Each properties set is applied only to the corresponding type.

Update the CMDB

You update the CMDB with the update APIs. For details of the API methods, see "UCMDB Update Methods" on page 366.

This task includes the following steps:

- "UCMDB Update Parameters" below
- "Use of ID Types with Update Methods" on the next page

UCMDB Update Parameters

This topic describes the parameters used only by the service's update methods.

CIsAndRelationsUpdates

The CIsAndRelationsUpdates type consists of CIsForUpdate, relationsForUpdate, referencedRelations, and referencedCIs. A CIsAndRelationsUpdates instance does not necessarily include all three elements.

CIsForUpdate is a CIs collection. relationsForUpdate is a Relations collection. The CI and relation elements in the collections have a props element. When creating a CI or relation, properties that have either the required attribute or the key attribute in the CI Type definition must be populated with values. The items in these collections are updated or created by the method.

referencedCIs and referencedRelations are collections of CIs that are already defined in the CMDB. The elements in the collection are identified with a temporary ID in conjunction with all the

key properties. These items are used to resolve the identities of CIs and relations for update. They are never created or updated by the method.

Each of the CI and relation elements in these collections has a properties collection. New items are created with the property values in these collections.

Use of ID Types with Update Methods

The following describes ID CITs, and CIs and relations. When the ID is not a real CMDB ID, the type and key attributes are required.

Deleting or Updating Configuration Items

A temporary or empty ID may be used by the client when calling a method to delete or update an item. In this case, the CI type and the "Key Attributes" that identify the CI must be set.

Deleting or Updating Relations

When deleting or updating relations, the relation ID can be empty, temporary, or real.

If a Cl's ID is temporary, the CI must be passed in the referencedCIs collection and its key attributes must be specified. For details, see referencedCIs in "CIsAndRelationsUpdates" on the previous page.

Inserting New Configuration Items into the CMDB

It is possible to use either an empty ID or a temporary ID to insert a new CI. However, if the ID is empty, the server cannot return the real CMDB ID in the structure createIDsMap because there is no clientID. For details, see "addCIsAndRelations" on page 366 and "UCMDB Query Methods" on page 353.

. Inserting New Relations into the CMDB

The relation ID can be either temporary or empty. However, if the relation is new but the configuration items on either end of the relation are already defined in the CMDB, then those CIs that already exist must be identified by a real CMDB ID or be specified in a referencedCIs collection.

Query the UCMDB Class Model

The class model methods return information about CITs and relations. The class model is configured using the CI Type Manager. For details, see CI Type Manager in the *HPE Universal CMDB Modeling Guide*.

This section provides information on the following methods that return information about CITs and relations:

- "getClassAncestors" below
- "getAllClassesHierarchy" below
- "getCmdbClassDefinition" on the next page

getClassAncestors

The getClassAncestors method retrieves the path between the given CIT and its root, including the root.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
className	The type name. For details, see "Type Name" on page 351.

Output

Parameter	Comment
classHierarchy	A collection of pairs of class names and parent class name.
comments	For internal use only.

getAllClassesHierarchy

The getAllClassesHierarchy method retrieves the entire class model tree.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.

Output

Parameter	Comment
classesHierarchy	A collection of pairs of class name and parent class name.
comments	For internal use only.

getCmdbClassDefinition

The getCmdbClassDefinition method retrieves information about the specified class.

If you use getCmdbClassDefinition to retrieve the key attributes, you must also query the parent classes up to the base class. getCmdbClassDefinition identifies as key attributes only those attributes with the ID_ATTRIBUTE set in the class definition specified by className. Inherited key attributes are not recognized as key attributes of the specified class. Therefore, the complete list of key attributes for the specified class is the union of all the keys of the class and of all its parents, up to the root.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on the next page.
className	The type name. For details, see "UCMDB General Parameters " on the next page.

Output

Parameter	Comment
cmdbClass	The class definition, consisting of name, classType, displayLabel, description, parentName, qualifiers, and attributes.
comments	For internal use only.

Query for Impact Analysis

The Identifier in the impact analysis methods points to the service's response data. It is unique for the current response and is discarded from the server's memory cache after 10 minutes of non-use.

For examples of the use of the impact analysis methods, see Impact Analysis Example in the *HPE Universal CMDB API Reference*.

UCMDB General Parameters

This section describes the most common parameters of the service's methods.

This section includes the following topics:

- "CmdbContext" below
- "ID" below
- · "Key Attributes" below
- "ID Types" on the next page
- · "CIProperties" on the next page
- "Type Name" on page 351
- "Configuration Item (CI)" on page 351
- "Relation" on page 351

CmdbContext

All UCMDB Web Service API service invocations require a CmdbContext argument. CmdbContext is a callerApplication string that identifies the application that invokes the service. CmdbContext is used for logging and troubleshooting.

ID

Every CI and Relation has an ID field. It consists of a case-sensitive ID string and an optional temp flag, indicating whether the ID is temporary.

Key Attributes

For identifying a CI or Relation in some contexts, key attributes can be used in place of a CMDB ID. Key attributes are those attributes with the ID_ATTRIBUTE set in the class definition.

In the user interface, the key attributes have a key icon next to them in the list of Configuration Item Type attributes in the user interface. For details, see Add/Edit Attribute Dialog Box in the *HPE*

Universal CMDB Modeling Guide. For information about identifying the key attributes from within the API client application, see "getCmdbClassDefinition" on page 348.

ID Types

An ID element can contain a real ID, or a temporary ID.

A real ID is a string assigned by the CMDB that identifies an entity in the database. A temporary ID can be any string that is unique in the current request.

A temporary ID can be assigned by the client and often represents the ID of the CI as stored by the client. It does not necessarily represent an entity already created in the CMDB. When a temporary ID is passed by the client, if the CMDB can identify an existing data configuration item using the CI key properties, that CI is used as appropriate for the context as if it had been identified with a real ID.

CIProperties

A CIProperties element is composed of collections, each containing a sequence of name-value elements that specify properties of the type indicated by the collection name. None of the collections are required, so the CIProperties element can contain any combination of collections.

CIProperties are used by CI and Relation elements. For details, see "Configuration Item (CI)" on the next page and "Relation" on the next page.

The properties collections are:

- dateProps collection of DateProp elements
- doubleProps collection of DoubleProp elements
- floatProps collection of FloatProp elements
- intListProps collection of intListProp elements
- intProps collection of IntProp elements
- strProps collection of StrProp elements
- strListProps collection of StrListProp elements
- longProps collection of LongProp elements
- bytesProps collection of BytesProp elements
- xmlProps collection of XmlProp elements

Type Name

The type name is the class name of a configuration item type or relation type. The type name is used in code to refer to the class. It should not be confused with the display name, which is seen on the user interface where the class is mentioned, but which is meaningless in code.

Configuration Item (CI)

A CI element is composed of an ID, a type, and a props collection.

When using "UCMDB Update Methods" to update a CI, the ID element can contain a real CMDB ID or a client-assigned temporary ID. If a temporary ID is used, set the temp flag to true. When deleting an item, the ID can be empty. "UCMDB Query Methods" take real IDs as input parameters and return real IDs in the query results.

The type can be any type name defined in the CI Type Manager. For details, see CI Type Manager in the HPE Universal CMDB Modeling Guide.

The props element is a CIProperties collection. For details, see "UCMDB General Parameters" on page 349.

Relation

A Relation is an entity that links two configuration items. A Relation element is composed of an ID, a type, the identifiers of the two items being linked (end1ID and end2ID), and a props collection.

When using "UCMDB Update Methods" to update a Relation, the value of the Relation's ID can be a real CMDB ID or a temporary ID. When deleting an item, the ID can be empty. "UCMDB Query Methods" take real IDs as input parameters and return real IDs in the guery results.

The relation type is the Type Name of the UCMDB class from which the relation is instantiated. The type can be any of the relation types defined in the CMDB. For further information on classes or types, see "Query the UCMDB Class Model" on page 346.

For details, see CI Type Manager in the HPE Universal CMDB Modeling Guide.

The two relation end IDs must not be empty IDs because they are used to create the ID of the current relation. However, they both can have temporary IDs assigned to them by the client.

The props element is a CIProperties collection. For details, see "CIProperties" on the previous page.

UCMDB Output Parameters

This section describes the most common output parameters of the service methods. For more details, refer to the online schema documentation.

This section includes the following topics:

- "CIs" below
- "ShallowRelation" below
- "Topology" below
- "CINode" below
- "RelationNode" on the next page
- "TopologyMap" on the next page
- "ChunkInfo" on the next page

Cls

CIs is a collection of CI elements.

ShallowRelation

A ShallowRelation is an entity that links two configuration items, composed of an ID, a type, and the identifiers of the two items being linked (end1ID and end2ID). The relation type is the Type Name of the CMDB class from which the relation is instantiated. The type can be any of the relation types defined in the CMDB.

Topology

Topology is a graph of CI elements and relations. A Topology consists of a CIs collection and a Relations collection containing one or more Relation elements.

CINode

CINode is composed of a CIs collection with a label. The label in the CINode is the label defined in the node of the TQL used in the query.

RelationNode

RelationNode is a set of Relation collections with a label. The label in the RelationNode is the label defined in the node of the TQL used in the query.

TopologyMap

TopologyMap is the output of a query calculation that matches a TQL query. The labels in the TopologyMap are the node labels defined in the TQL used in the query.

The data of TopologyMap is returned in the following form:

- CINodes. This is one or more CINode (see "CINode" on the previous page).
- relationNodes. This is one or more RelationNode (see "RelationNode" above).

The labels in these two structures order the lists of configuration items and relations.

ChunkInfo

When a query returns a large amount of data, the server stores the data, divided into segments called chunks. The information the client uses to retrieve the chunked data is located in the ChunkInfo structure returned by the query. ChunkInfo is composed of the numberOfChunks that must be retrieved and the chunksKey. The chunksKey is a unique identifier of the data on the server for this specific query invocation.

For more information, see "Processing Large Responses" on page 342.

UCMDB Query Methods

This section provides information on the following methods:

- "executeTopologyQueryByNameWithParameters" on the next page
- "executeTopologyQueryWithParameters" on page 355
- "getChangedCIs" on page 356
- "getCINeighbours" on page 356
- "getCIsByID" on page 357
- "getCIsByType" on page 358

- "getFilteredCIsByType" on page 358
- "getQueryNameOfView" on page 362
- "getTopologyQueryExistingResultByName" on page 362
- "getTopologyQueryResultCountByName" on page 363
- "pullTopologyMapChunks" on page 364
- "releaseChunks" on page 365

executeTopologyQueryByNameWithParameters

The executeTopologyQueryByNameWithParameters method retrieves a topologyMap element that matches the specified parameterized query.

The values for the query parameters are passed in the parameterizedNodes argument. The specified TQL must have unique labels defined for each CINode and each relationNode or the method invocation fails.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
queryName	The name of the parameterized TQL in the CMDB for which to get the map.
parameterizedNodeList	The conditions each node must meet to be included in the query results.
queryTypedProperties	A collection of sets of properties to retrieve for items of a specific Configuration Item Type.

Output

Parameter	Comment
topologyMap	For details, see "TopologyMap" on the previous page.
chunkInfo	For details, see "ChunkInfo" on the previous page and "Processing Large

Parameter	Comment
	Responses" on page 342.

executeTopologyQueryWithParameters

The executeTopologyQueryWithParameters method retrieves a topologyMap element that matches the parameterized query.

The query is passed in the queryXML argument. The values for the query parameters are passed in the parameterizedNodeList argument. The TQL must have unique labels defined for each CINode and each relationNode.

The executeTopologyQueryWithParameters method is used to pass ad hoc queries, rather than accessing a query defined in the CMDB. You can use this method when you do not have access to the UCMDB user interface to define a query, or when you do not want to save the query to the database.

To use an exported TQL as the input of this method, do the following:

1. Launch the Web browser and enter the following address: http://localhost:8443/jmx-console.

You may have to log in with a user name and password.

- 2. Click UCMDB:service=TQL Services.
- 3. Locate the **exportTql** operation.
 - In the **customerId** parameter box, enter **1** (the default).
 - In the **patternName** parameter box, enter a valid TQL name.
- 4. Click Invoke.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
queryXML	An XML string representing a TQL without resource tags.
parameterizedNodeList	The conditions each node must meet to be included in the query results.

Output

Parameter	Comment
topologyMap	For details, see "TopologyMap" on page 353.
chunkInfo	For details, see "ChunkInfo" on page 353 and "Processing Large Responses" on page 342.

getChangedCls

The getChangedCIs method returns the change data for all CIs related to the specified CIs.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
ids	The list of the IDs of the root CIs whose related CIs are checked for changes. Only real CMDB IDs are valid in this collection.
fromDate	The beginning of the period in which to check if CIs changed.
toDate	The end of the period in which to check if CIs changed.

Output

Parameter	Comment
getChangedCIsResponseList	Zero or more collections of ChangedDataInfo elements.

getCINeighbours

The getCINeighbours method returns the immediate neighbors of the specified CI.

For example, if the query is on the neighbors of CI A, and CI A contains CI B which uses CI C, CI B is returned, but CI C is not. That is, only neighbors of the specified type are returned.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
ID	The ID of the CI for which to retrieve the neighbors. This must be a real CMDB or global ID.
neighbourType	The CIT name of the neighbors to retrieve. Neighbors of the specified type and of types derived from that type are returned. For details, see "Type Name" on page 351.
CIProperties	The data to be returned on each configuration item, called the Query Layout in the user interface. For details, see "TypedProperties" on page 345.
relationProperties	The data to be returned on each relation (called the Query Layout in the user interface). For details, see "TypedProperties" on page 345.

Output

Parameter	Comment
topology	For details, see "Topology" on page 352.
comments	For internal use only.

getClsByID

The getCIsByID method retrieves configuration items by their CMDB or global IDs.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
CIsTypedProperties	A typed properties collection. For details, see "Other Property Specification Elements" on page 344.
IDs	Only real CMDB or global IDs are valid in this collection.

Output

Parameter	Comment
Cls	A collection of CI elements.
chunkInfo	For details, see "ChunkInfo" on page 353 and "Processing Large Responses" on page 342.

getClsByType

The getCIsByType method returns the collection of configuration items of the specified type and of all types that inherit from the specified type.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
type	The class name. For details, see "Type Name" on page 351.
properties	The data to be returned on each configuration item. For details, see "CustomProperties" on page 344.

Output

Parameter	Comment
Cls	A collection of CI elements.
chunkInfo	For details, see: "ChunkInfo" on page 353 and "Processing Large Responses" on page 342.

getFilteredClsByType

The getFilteredCIsByType method retrieves the CIs of the specified type that meet the conditions used by the method. A condition is comprised of:

- A name field containing the name of a property
- An operator field containing a comparison operator
- An optional value field containing a value or list of values

Together, they form a Boolean expression:

<item>.property.value [operator] <condition>.value

For example, if the condition name is root_actualdeletionperiod, the condition value is 40 and the operator is Equal, the Boolean statement is:

<item>.root_actualdeletionperiod.value = = 40

The query returns all items whose root_actualdeletionperiod is 40, assuming there are no other conditions.

If the conditionsLogicalOperator argument is AND, the query returns the items that meet all conditions in the conditions collection. If conditionsLogicalOperator is OR, the query returns the items that meet at least one of the conditions in the conditions collection.

The following table lists the comparison operators:

Operator	Type of Condition/Comments
ChangedDuring	Date
	This is a range check. The condition value is specified in hours. If the value of the date property lies in the range of the time the method is invoked plus or minus the condition value, the condition is true.
	For example, if the condition value is 24, the condition is true if the value of the date property is between yesterday at this time and tomorrow at this time.
	Note: The name ChangedDuring is kept to preserve backward compatibility. In previous versions, the operator was used only with create and modify time properties.
Equal	String and numerical
EqualIgnoreCase	String
Greater	Numerical
GreaterEqual	Numerical
In	String, numerical, and list

Operator	Type of Condition/Comments
	The condition's value is a list. The condition is true if the value of the property is one of the values in the list.
InList	List
	The condition's value and the property's value are lists.
	The condition is true if all the values in the condition's list also appear in the item's property list. There can be more property values than specified in the condition without affecting the truth of the condition.
IsNull	String, numerical, and list
	The item's property has no value. When operator IsNull is used, the value of the condition is ignored, and in some cases can be nil.
Less	Numerical
LessEqual	Numerical
Like	String
	The condition's value is a substring of the value of the property's value. The condition's value must be bracketed with percentage signs (%). For example, %Bi% matches Bismark and Bay of Biscay, but not biscuit.
LikeIgnoreCase	String
	Use the LikeIgnoreCase operator as you use the Like operator. The match, however is not case-sensitive. Therefore, %Bi% matches biscuit.
NotEqual	String and numerical
UnchangedDuring	Date
	This is a range check. The condition value is specified in hours. If the value of the date property is in the range of the time the method is invoked plus or minus the condition value, the condition is false. If it lies outside that range, the condition is true.
	For example, if the condition value is 24, the condition is true if the value of the date property is before yesterday at this time or after tomorrow at this time.
	Note: The name UnchangedDuring is kept to preserve backward compatibility. In previous versions, the operator was used only with create

Operator	Type of Condition/Comments
	and modify time properties.

```
FloatCondition fc = new FloatCondition();
FloatProp fp = new FloatProp();
fp.setName("attr_name");
fp.setValue(11f);
fc.setCondition(fp);
fc.setFloatOperator(FloatCondition.FloatOperator.EQUAL);
```

Example of Querying for Inherited Properties:

The target CI is sample which has two attributes, name and size. sampleII extends the CI with two attributes, level and grade. This example sets up a query for the properties of sampleII that were inherited from sample by specifying them by name.

```
GetFilteredCIsByType request = new GetFilteredCIsByType()
request.setCmdbContext(cmdbContext)
request.setType("sampleII");
CustomProperties customProperties = new CustomProperties();
PropertiesList propertiesList = new PropertiesList();
propertiesList.setPropertyNames(Arrays.asList("name", "size"));
customProperties.setPropertiesList(propertiesList);
request.setProperties(customProperties);
```

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
type	The class name. For details, see "Type Name" on page 351. The type can be any of the types defined using the CI Type Manager. For details, see CI Type Manager in the HPE Universal CMDB Modeling Guide.
properties	The data to be returned on each CI (called the Query Layout in the user interface). For details, see "CustomProperties" on page 344.
conditions	A collection of name-value pairs and the operators that relate one to the other. For example, host_hostname like QA.

Parameter	Comment
conditionsLogicalOperator	AND. All the conditions must be met.
	OR. At least one of the conditions must be met.

Output

Parameter	Comment
Cls	Collection of CI elements.
chunkInfo	For details, see "ChunkInfo" on page 353 and "Processing Large Responses" on page 342.

getQueryNameOfView

The getQueryNameOfView method retrieves the name of the TQL on which the specified view is based.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
viewName	The name of a view, which is a sub-set of the class model in the CMDB.

Output

Parameter	Comment
queryName	The name of the TQL in the CMDB on which the view is based.

getTopologyQueryExistingResultByName

The getTopologyQueryExistingResultByName method retrieves the most recent result of running the specified TQL. The call does not run the TQL. If there are no results from a previous run, nothing is returned.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
queryName	The name of a TQL.
queryTypedProperties	A collection of sets of properties to retrieve for items of a specific Configuration Item Type.

Output

Parameter	Comment
topologyMap	For details, see "TopologyMap" on page 353.
chunkInfo	For details, see "ChunkInfo" on page 353 and "Processing Large Responses" on page 342.

get Topology Query Result Count By Name

The getTopologyQueryResultCountByName method retrieves the number of instances of each node that matches the specified query.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
queryName	The name of a TQL.
countInvisible	If true, the output includes CIs defined as invisible in the query.

Output

Parameter	Comment
getTopologyQueryResultCountByNameResponse	The number of instances matching

Parameter	Comment
	the query.

pullTopologyMapChunks

The pullTopologyMapChunks method retrieves one of the chunks that contain the response to a method.

Each chunk contains a topologyMap element that is part of the response. The first chunk is numbered 1, so the retrieval loop counter iterates from 1 to <response object>.getChunkInfo ().getNumberOfChunks().

For details, see "ChunkInfo" on page 353 and "Query the CMDB" on page 341.

The client application must be able to handle the partial maps.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
ChunkRequest	The number of the chunk to retrieve and the ChunkInfo that is returned by the query method.
queryTypedProperties	A collection of sets of properties to retrieve for items of a specific CI type.

Output

Parameter	Comment
topologyMap	For details, see "TopologyMap" on page 353.
comments	For internal use only.

Example of Handling Chunks:

```
GetCIsByType request =
    new GetCIsByType(cmdbContext, typeName, customProperties);
GetCIsByTypeResponse response =
    ucmdbService.getCIsByType(request);
ChunkRequest chunkRequest = new ChunkRequest();
```

```
chunkRequest.setChunkInfo(response.getChunkInfo());
for(int j=1; j<=response.getChunkInfo().getNumberOfChunks(); j++){</pre>
    chunkRequest.setChunkNumber(j);
    PullTopologyMapChunks req =new PullTopologyMapChunks
(cmdbContext,chunkRequest);
    PullTopologyMapChunksResponse res =
        ucmdbService.pullTopologyMapChunks(req);
        for(int m=0;
            m < res.getTopologyMap().getCINodes().sizeCINodeList();</pre>
            m++) {
            CIs cis =
            res.getTopologyMap().getCINodes().getCINode(m).getCIs();
            for(int i=0 ; i < cis.sizeCIList() ; i++) {</pre>
                // your code to process the CIs
            }
        }
}
GetCIsByType request =
     new GetCIsByType(cmdbContext, typeName, customProperties);
GetCIsByTypeResponse response =
     ucmdbService.getCIsByType(request);
ChunkRequest chunkRequest = new ChunkRequest();
chunkRequest.setChunkInfo(response.getChunkInfo());
for(int j=1; j <= response.getChunkInfo().getNumberOfChunks(); j++) {</pre>
    chunkRequest.setChunkNumber(j);
    PullTopologyMapChunks req = new PullTopologyMapChunks(cmdbContext,
chunkRequest);
    PullTopologyMapChunksResponse res =
        ucmdbService.pullTopologyMapChunks(req);
        for(int m=0 ;
            m < res.getTopologyMap().getCINodes().getCINodes().size();</pre>
            m++) {
            CIs cis =
            res.getTopologyMap().getCINodes().getCINodes().get(m).getCIs();
            for(int i=0 ; i < cis.getCIs().size(); i++) {</pre>
                // your code to process the CIs
            }
        }
```

releaseChunks

The releaseChunks method frees the memory of the chunks that contain the data from the query.

Tip: The server discards the data after ten minutes. Calling this method to discard the data as

soon as it has been read conserves server resources.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
chunksKey	The identifier of the data on the server that was chunked. The key is an element of ChunkInfo.

UCMDB Update Methods

This section provides information on the following methods:

- "addCIsAndRelations" below
- · "addCustomer" on the next page
- "deleteCIsAndRelations" on page 368
- "removeCustomer" on page 368
- "updateCIsAndRelations" on page 368

addClsAndRelations

The addCIsAndRelations method adds or updates CIs and relations.

If the CIs or relations do not exist in the CMDB, they are added and their properties are set according to the contents of the CIsAndRelationsUpdates argument.

If the CIs or relations do exist in the CMDB, they are updated with the new data, if updateExisting is **true**.

If updateExisting is **false**, CIsAndRelationsUpdates cannot reference existing configuration items or relations. Any attempt to reference existing items when updateExisting is false results in an exception.

If updateExisting is **true**, the add or update operation is performed without validating the CIs, regardless of the value of ignoreValidation.

If updateExisiting is **false** and ignoreValidation is **true**, the add operation is performed without validating the CIs.

If updateExisiting is **false** and ignoreValidation is **false**, the CIs are validated before the add operation.

Relations are never validated.

CreatedIDsMap is a map or dictionary of type ClientIDToCmdbID that connects the client's temporary IDs with the corresponding real CMDB IDs.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
updateExisting	Set to true to update items that already exist in the CMDB. Set to false to throw an exception if any item already exists.
CIsAndRelationsUpdates	The items to update or create. For details, see "CIsAndRelationsUpdates" on page 345.
ignoreValidation	If true, no check is performed before updating the CMDB.
dataStore	Changer information.

Output

Parameter	Comment
createdIDsMapList	The list of client IDs mapped to CMDB IDs. For details, see the description above.
comments	For internal use only.

addCustomer

The addCustomer method adds a customer.

Input

Parameter	Comment
CustomerID	The numeric ID of the customer.

deleteCIsAndRelations

The deleteCIsAndRelations method removes the specified configuration items and relations from the CMDB.

When a CI is deleted and the CI is one end of one or more Relation items, those Relation items are also deleted.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
CIsAndRelationsUpdates	The items to delete. For details, see "CIsAndRelationsUpdates" on page 345
dataStore	Changer information.

removeCustomer

The removeCustomer method deletes a customer record.

Input

Parameter	Comment
CustomerID	The numeric ID of the customer.

updateClsAndRelations

The updateCIsAndRelations method updates the specified CIs and relations.

Update uses the property values from the CIsAndRelationsUpdates argument. If any of the CIs or relations do not exist in the CMDB, an exception is thrown.

CreatedIDsMap is a map or dictionary of type ClientIDToCmdbID that connects the client's temporary IDs with the corresponding real CMDB IDs.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
CIsAndRelationsUpdates	The items to update. For details, see "CIsAndRelationsUpdates" on page 345.
ignoreValidation	If true, no check is performed before updating the CMDB.
dataStore	Changer information.

Output

Parameter	Comment
createdIDsMapList	The list of client IDs mapped to CMDB IDs. For details, see
	"addCIsAndRelations" on page 366.

UCMDB Impact Analysis Methods

This section provides information on the following methods:

- "calculateImpact" below
- "getImpactPath" on the next page
- "getImpactRulesByNamePrefix" on page 371

calculateImpact

The calculateImpact method calculates which CIs are affected by a given CI according to the rules defined in the CMDB.

This shows the effect of an event triggering of the rule. The identifier output of calculateImpact is used as input for "getImpactPath" on the next page.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
impactCategory	The type of event that would trigger the rule being simulated.
IDs	A collection of CMDB or global ID elements.
impactRulesNames	A collection of ImpactRuleName elements.
severity	The severity of the triggering event.

Output

Parameter	Comment
impactTopology	For details, see "Topology" on page 352.
identifier	The key to the server response.

getImpactPath

The getImpactPath method retrieves the topology graph of the path between the affected CI and the CI that affects it.

The identifier output of "calculateImpact" on the previous page is used as the identifier input argument of getImpactPath.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
identifier	The key to the server response that was returned by calculateImpact.
relation	A Relation based on one of the "ShallowRelation"s returned by calculateImpact in the impactTopology element.

Output

Parameter	Comment
impactPathTopology	A CIs collection and an ImpactRelations collection.
comments	For internal use only.

An ImpactRelations element consists of an ID, type, end1ID, end2ID, rule, and action.

getImpactRulesByNamePrefix

The getImpactRulesByNamePrefix method retrieves rules using a prefix filter.

This method applies to impact rules that are named with a prefix that indicates the context to which they apply, for example, SAP_myrule, ORA_myrule, and so on. This method filters all impact rule names for those beginning with the prefix specified by the ruleNamePrefixFilter argument.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
ruleNamePrefixFilter	A string containing the first letters of the rule names to match.

Output

Parameter	Comment
impactRules	<pre>impactRules is composed of zero or more impactRule. An impactRule, which specifies the effect of a change, is composed of ruleName, description, queryName, and isActive.</pre>

Actual State Web Service API

The Actual State Web Service API is used primarily by the Service Manager to retrieve Actual State information for a specific CMDB ID or Global ID and a specific customer ID. The API finds a matching query under the folder **Integration/SM Query** and executes the TQL with the CMDB ID or Global ID as a condition, and returns the output of the query.

Web Service URL: http://[machine name]:8080/axis2/services/ucmdbSMService

Web Service Schema: http://[machine_name]:8080/axis2/services/ucmdbSMService?xsd=xsd0

Flow

When the API method is called, it tries to find an appropriate Query in the Integration/SM Query folder. It tries to match the type of the requested CMDBID/GlobalID with one of the queries in the latter folder first by looking for a QueryElement with the name Root, and if one is not found it tries to use any QueryNode of the same type as the requested CMDBID/GlobalID. Once an appropriate Query and QueryNode are found, it puts the CMDBID/GlobalID as a condition on the QueryNode and executes the Query. The result is then returned to the caller of the API.

Manipulating the Result Using Transformations

In some cases you may want to apply additional transformations to the resulting XML (for example, to sum up the sizes of all the disks and add that sum as an additional attribute to the CI). To add additional transformations on the TQL results, place a resource called [tql_name].xslt in the adapter configuration as follows: Adapter Management > ServiceDeskAdapter7-1 > Configuration Files > [tql_name].xslt.

Logs for the Actual State Web Service API

The log configuration for UCMDB resides at: **UCMDBServer/Conf/log** in the various *.properties files.

To view logs of the SM Actual State flow:

- Open the cmdb_soaapi.properties file and change the log level to DEBUG as follows: loglevel=DEBUG.
- 2. Open the **fcmdb.properties** file and change the log level to DEBUG as follows: **loglevel=DEBUG**.
- 3. Wait 1 minute for the server to retrieve the changes.
- 4. Run the Actual State from the SM.
- 5. View the following log files at **UCMDBServer/Runtime/log**:
 - o cmdb.soaapi.log
 - fcmdb.log

Enabling Actual State of Replicated CIs after Changing Root Context

If you have changed the root context that is used to access UCMDB, you must make the following configuration changes to enable Actual State of Replicated CIs:

- 1. Under UCMDBServer\deploy\axis2\WEB-INF, open the file web.xml.
- 2. Add the following servlet init parameter to AxisServlet (paste these four lines after line 28):

```
<init-param>
<param-name>axis2.find.context</param-name>
<param-value>false</param-value>
</init-param>
```

This setting prevents Axis2 from trying to calculate the context root and tells it to look for it explicitly in axis2.xml.

- 3. Under UCMDBServer\deploy\axis2\WEB-INF\conf, open the file axis2.xml.
- 4. At line 58, remove comments from the parameter **contextRoot**, and edit it as follows:

```
<parameter name="contextRoot" locked="false">test/axis2</parameter>
(where test is the new root context in cmdb.xml).
```

Note: There is no slash at the beginning of test/axis2.

UCMDB Web Service API Use Cases

The following use cases assume two systems:

- Universal CMDB server
- · A third-party system that contains a repository of configuration items

This section includes the following topics:

- "Populating the CMDB" on the next page
- "Querying the CMDB" on the next page
- "Querying the Class Model" on the next page
- "Analyzing Change Impact" on the next page

Populating the CMDB

Use cases:

- A third-party asset management updates the CMDB with information available only in asset management
- A number of third-party systems populate the CMDB to create a central CMDB that can track changes and perform impact analysis
- A third-party system creates Configuration Items and Relations according to third-party business logic to leverage the CMDB query capabilities

Querying the CMDB

Use cases:

- A third-party system gets the Configuration Items and Relations that represent the SAP system by getting the results of the SAP TQL
- A third-party system gets the list of Oracle servers that have been added or changed in the last five hours
- A third-party system gets the list of servers whose host name contains the substring lab
- A third-party system finds the elements related to a given CI by getting its neighbors

Querying the Class Model

Use cases:

- A third-party system enables users to specify the set of data to be retrieved from the CMDB. A user
 interface can be built over the class model to show users the possible properties and prompt them
 for required data. The user can then choose the information to be retrieved.
- A third-party system explores the class model when the user cannot access the UCMDB user interface.

Analyzing Change Impact

Use case:

A third-party system outputs a list of the business services that could be impacted by a change on a specified host.

Examples

See the following code samples:

- The Example Base Class
- Query Example
- Update Example
- Class Model Example
- Impact Analysis Example

These files are located in the following directory:

\\<UCMDB root directory>\hp\UCMDB\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\WebServiceAPI_Samples\

Chapter 12: HPE Universal CMDB REST API

The Universal CMDB REST API allows you to perform topology modification and topology query related operations.

This chapter includes:

Deployment and Configuration	376
Using the REST API	378
Reference	380

Deployment and Configuration

The REST API can be deployed in the following ways:

- Embedded: the package is deployed on the UCMDB server. Since Universal CMDB 10.30, the REST API is deployed automatically in this way when you install the UCMDB server.
- Standalone: the package is deployed on a separate Tomcat server.

Standalone Deployment

The standalone deployment of the REST API can work with UCMDB Server 10.10 and higher versions.

You can obtain the WAR file for the REST API from the following locations:

- HPE Live Network: https://hpln.hpe.com/contentoffering/community-content-ud-0
- UCMDB 10.30 installation folder: <UCMDB_Server_Home>/tools/rest-api-standalone.war

Follow these steps to deploy the REST API on a separate Tomcat server:

Note: Tomcat is the only supported servlet container.

1. Copy the WAR file to the **webapps** directory of your Tomcat installation.

Note: It is recommended that you rename the WAR file to **rest-api.war** if you use the WAR file from the UCMDB installation folder.

2. Create a **rest_credentials.txt** file under **\$CATALINA_HOME/conf/**, and then specify the system administrator credentials of the UCMDB Server. For example:

```
username=sysadmin
password=sysadmin
```

3. Restart the Tomcat server.

Note: In the standalone deployment:

- The **\$CATALINA_HOME/conf/rest_jwt.bin** file contains REST authorization information. If you remove this file, all authorization tokens created from server startup will be invalidated.
- If you want to change the credentials that you specified during the deployment, delete the \$CATALINA_HOME/conf/rest_credentials.bin file, and then redo Step 2 and Step 3.

Configuration

The REST API can be configured by the **rest_api.properties** file, which locates in the following folder:

- Embedded: <UCMDB_Server_Home>/conf/
- Standalone: \$CATALINA HOME/conf/

The available options and default values are as follows:

```
#hostname of ucmdb server
ucmdb_host=localhost
#protocol to be used when connecting to ucmdb server(http or https)
ucmdb_protocol=http
#port of ucmdb server
ucmdb_port=8080
#default ucmdb customer
default_customer=1
#rest authorization token lifespan
token_expiration_minutes=30
```

Note: If the **rest_api.properties** file is not present in the above location, the REST API uses these default values.

For the embedded deployment, the REST API supports the HTTP and HTTPS protocols. You can choose a protocol by changing the value of the **Rest-Api Port Mapping** setting, which locates under

UCMDB UI > Administration > Infrastructure Settings Manager > Web Components to Connectors.

For the standalone deployment, you can configure the REST API to run on HTTP or HTTPS by following the Tomcat documentation.

Using the REST API

This chapter provides basic information about how to use the REST API.

Authorization

The REST API uses JSON Web Token (JWT) for authorization.

You can obtain a token by making a POST REST call to the endpoint:

 these_url>/authenticate with the payload that specifies the credentials and client context. The following example demonstrates the content of such a payload:

```
{ "username": "admin", "password": "admin", "clientContext": 1 }
```

The service then returns a token that has to be used for future REST calls. The token should be added in the header of a request in the following manner:

```
key: Authorization, value: Bearer TOKEN
```

TOKEN is the token returned by the authorization service.

Note: All REST calls require a token except the following ones:

- get sample data model
- get sample topology query

For an example about how to obtain a token, see "A Usage Example" on the next page.

REST API Endpoint

You must specify an endpoint when you make a REST call. An endpoint includes the following parts:

<base_url><resource_url>

<base_url>: The URL of where the REST API is deployed.

If you deploy the rest-api.war package under the webapps folder of Tomcat, the base URL is:

```
http(s)://<IP_or_FQDN_of_Tomcat>/rest-api
```

<resource_url>: See the URL section of each call in "Reference" on the next page.

Tips

- The logs produced by the REST API are in the following file:
 - Embedded: <UCMDB_Server_Home>/runtime/log/rest_api.log
 - Standalone: \$CATALINA_HOME/logs/rest_api.log
- The REST API prints and consumes every date attribute in the ISO8601 format:

```
yyyy-MM-dd'T'HH:mm:ss.SSSZZ
```

A Usage Example

This example demonstrates how to make a POST call to execute a TQL query by definition to return the name of all CPUs of which the attribute contains Pentium.

Step 1. Retrieve the authentication token

To do this, make a POST call to http://localhost:8080/rest-api/authenticate with the following payload:

```
{
"username": "sysadmin",
"password": "Sysadmin?123",
"clientContext": 1
}
```

Note: This example assumes that the REST API is deployed at the following location:

https://localhost:8443/rest-api

You then receive a response that resembles the following:

```
Status: 200
Response body:
{
    "token":
    "eyJ0eXAi0iJKV1QiLCJhbGci0iJIUzI1NiJ9.eyJleHAi0jE0NzQzNTc3MDYsImN1c3RvbWVyIjoxLC
J1c2VybmFtZSI6InN5c2FkbWluIn0.cVYsuum1CqaqfZV1K5KJ8nid0Oif8Wv9tZsLFFZPbSs"
}
```

Step 2. Make a POST call to run the TQL query

Make a POST call to https://localhost:8443/rest-api/topologyQuery with the following payload:

```
{
   "nodes": [
     {
       "type": "cpu",
       "queryIdentifier": "cpu1",
       "visible": true,
       "includeSubtypes": true,
       "layout": ["name"],
       "attributeConditions": [{
          "attribute": "name",
         "operator": "like",
         "value": "%Pentium%"
     }],
     "linkConditions": []
  }],
 "relations": []
}
```

At the same time you need to set the following header:

```
Authorization Bearer
eyJ0eXAi0iJKV1QiLCJhbGci0iJIUzI1NiJ9.eyJleHAi0jE0NzQzNTc3MDYsImN1c3RvbWVyIjoxLCJ
1c2VybmFtZSI6InN5c2FkbWluIn0.cVYsuum1CqaqfZV1K5KJ8nid0Oif8Wv9tZsLFFZPbSs
```

Note: The payload specifies the layout attribute to name, so that the CPU name will be returned.

Reference

This chapter provides detailed information on how to make the following calls through the REST API:

Authenticate	38′
Sample Data Model	383
Insert Topology	385
Get CI	389
Update CI	392
Delete CI	396
Get Related CIs	398
Get Relation	401

Update Relation	404
Delete Relation	408
Sample Topology Query	410
Execute Query By Name	413
Execute Query By Definition	416
Run Impact Analysis	421
Multiple CMDB Calls	424
History Changes	428

Authenticate

This call returns a token based on user credentials. The returned token has to be used in the following calls.

URL

/authenticate

Method

POST

Headers

None

Request type

JSON

Response type

JSON

URL Parameters

Required: None
Optional: None

Payload

```
{
  username: [string],
  password: [string],
  clientContext: [integer] @optional @ignored
}

Example:
{
  username: sysadmin,
  password: sysadmin,
  clientContext: 1
}
```

Success response

Code: 200

Content: <token>

Example:

Code: 200

Content:

{
"token":

"eyJ@eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE@NzQzNTc3MDYsImN1c3RvbWVyIjoxLCJ1c
2VybmFtZSI6InN5c2FkbWluIn@.cVYsuum1CqaqfZV1K5KJ8nid0Oif8Wv9tZsLFFZPbSs"
}

Error response

Code: 401

Content:

```
{
    error: [string]
}

Example:

Code: 401

Content:
{
    error: The following error has occurred: Invalid username received. Please consult logs for more details
}
```

Notes

The user needs access to SDK permission.

Sample Data Model

This call returns an example of data model structure that will be used in Data-In operations.

URL

/sampleDataModel

Method

GET

Headers

None

Request type

None

Response type

JSON

URL Parameters

Required: None

Optional: None

Payload

None

Success response

Hardcoded response:

```
{
    "cis": [
        {
             "ucmdbId": "1",
            "type": "unix",
             "properties": {
                 "stringList": [
                     "multiple",
                     "string",
                     "items"
                 "name": "unix1"
            }
        },
            "ucmdbId": "2",
            "type": "running_software",
             "properties": {
                 "discovered_product_name": "rs1",
                 "intList": [
                     "1",
                     "2",
                     "3"
                 ],
                 "name": "rs1"
            }
        },
{
            "ucmdbId": "3",
            "type": "running_software",
             "properties": {
                 "discovered_product_name": "rs2",
```

```
"name": "rs2"
            }
    ],
    "relations": [
        {
            "ucmdbId": "r1",
            "type": "composition",
            "properties": null,
            "end1Id": "1",
            "end2Id": "2"
        },
            "ucmdbId": "r2",
            "type": "composition",
            "properties": null,
            "end1Id": "1",
            "end2Id": "3"
        },
        {
            "ucmdbId": "r3",
            "type": "consumer_provider",
            "properties": null,
            "end1Id": "2",
            "end2Id": "3"
        }
    ]
}
```

Error response

None

Insert Topology

This call creates entities as described by the payload.

URL

/dataModel

Method

POST

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2 VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

JSON

Response type

JSON

URL Parameters

Required: None

Optional: None

Payload

Note: The ...(three dots) denotes that there can be 0 or more values.

Data Types:

```
[temp_id]
```

The string that represents a temporary ID of the objects. This temporary ID can be used for referring to the object inside this payload. For example, you can specify the two ends of a relationship, if you want to use an object that was defined in the same payload, use the object's temporary ID.

```
[ucmdb_cit]
```

The string that represents the name of a valid CI Type from the UCMDB. You have to use the name of the CI Type, not the display name. The name of the CI Type can be found inside the CI Type Manager.

```
[ucmdb cit prop value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb_cit_prop>
```

The valid property name of the CI Type. You can get the name and the list of all properties of a CI Type from the CI Type Manager. You have to use the name of the property, not its display name.

Example:

```
{
    cis: [{
        ucmdbId: 1,
        type: node,
        properties: {
            name: Test1
        }
    }, {
```

```
ucmdbId: 2,
    type: node,
    properties: {
        name: Test2
    }
}],
relations: [{
    ucmdbId: 3,
    type: managed_relationship,
    end1Id: 1,
    end2Id: 2,
    properties: {
    }
}]
```

Success response

```
Code: 200
```

```
Content:
```

```
{
    addedCis: list of [ucmdb_id]
    removedCis: list of [ucmdb_id],
    updatedCis: list of [ucmdb_id],
    ignoredCis: list of [ucmdb_id]
}
```

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a configuration item.

Example:

Code: 200

Content:

```
{
    addedCis: [
        4dc01bee04c76cc0ac4bb069f46e8b56,
        4b8416a13e686092b2a2e142ecceff46
    ],
    removedCis: [],
    updatedCis: [],
    ignoredCis: []
}
```

Error response

```
Code: 400
Content:
{
   error: [string]
}
```

Example:

Code: 400

Content:

```
{
   error: The following error has occurred: Class "nodeo" is not defined in the
class model. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for modifying the data inside UCMDB through the SDK.

Get CI

This call returns details of a CI.

URL

/dataModel/ci/{id}

Method

GET

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

None

Response type

JSON

URL Parameters

Path Parameters

Required:

{id}: [ucmdb_id]

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a configuration item.

Payload

None

Call example

GET <base_url>/dataModel/ci/4dc01bee04c76cc0ac4bb069f46e8b56

Success response

Status: 200

Response:

Note: The ...(three dots) denotes that there can be 0 or more values.

Data Types:

```
[ucmdb_id]
```

The string that represents the UCMDB ID of a CI.

```
[ucmdb_cit]
```

The string that represents the name of a valid CI Type from the UCMDB.

```
[ucmdb_cit_prop_value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb cit prop>
```

The valid property name of the CI Type. You can get the name and the list of all properties of a CI Type from the CI Type Manager.

Example:

Status: 200

Response:

```
{
  ucmdbId: 4dc01bee04c76cc0ac4bb069f46e8b56,
  type: node,
  properties: {
    root_candidatefordeletetime: 2016-07-31T08:41:54.189Z,
    data_operationisnew: false,
    root_class: node,
    display_label: test2,
    data_operationstate: 0:Normal,
    data_allow_auto_discovery: true,
  }
}
```

Error response

```
Status: 404 or 400

Content:

{
    error: [string]
}

Example:
```

Code: 404

Content:

```
{
   error: The following error has occurred: The CI with the specified id was not
found. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for viewing the data inside UCMDB through the SDK.

Update CI

This call updates the details of a CI.

URL

/dataModel/ci/{id}

Method

PUT

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer eyJ@eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE@Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2 VybmFtZSI6InN5c2FkbWluIn@.Ph8WHtzvpvfuH1j@CtwHqyBhX1uLlfhr@eQQ7m@_gT@

Request type

JSON

Response type

JSON

URL Parameters

Path Parameters

Required:

```
{id}: [ucmdb_id]
```

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a configuration item.

Payload

Note:

- The ...(three dots) denotes that there can be 0 or more values.
- You have to specify only the properties that you want to update. Do not specify all properties of the CI.
- You cannot update the type or the ID of the CI.

Data Types:

```
[ucmdb_id]
```

The string that represents the UCMDB ID of a CI.

```
[ucmdb_cit]
```

The string that represents the name of a valid CI Type from the UCMDB.

```
[ucmdb_cit_prop_value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb cit prop>
```

The valid property name of the CI Type. You can get the name and the list of all properties of a CI Type from the CI Type Manager.

Example:

```
{
  ucmdbId: 4dc01bee04c76cc0ac4bb069f46e8b56,
  type: node,
  properties: {
    root_candidatefordeletetime: 2016-07-31T08:41:54.189Z,
    data_operationisnew: false,
    root_class: node,
    display_label: test2,
    data_operationstate: 0:Normal,
    data_allow_auto_discovery: true,
  }
}
```

Success response

Status: 200

Response:

{

```
addedCis: list of [ucmdb_id]
     removedCis: list of [ucmdb_id],
     updatedCis: list of [ucmdb_id],
     ignoredCis: list of [ucmdb_id]
}
Data Types:
[ucmdb_id]
The string that represents the UCMDB ID of a CI.
Example:
Code: 200
Content:
    addedCis: [],
    removedCis: [],
    updatedCis: [
        4b8416a13e686092b2a2e142ecceff46
    ignoredCis: []
}
Error response
Status: 404 or 400
Content:
  error: [string]
Example:
Code: 404
Content:
   error: The following error has occurred: The CI with the specified id was not
found. Please consult logs for more details
```

Note

The user that the token belongs to must have the required permissions for updating the data inside UCMDB through the SDK.

Delete CI

This call deletes a CI.

URL

/dataModel/ci/{id}

Method

DELETE

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAi0iJKV1QiLCJhbGci0iJIUzI1NiJ9.eyJleHAi0jE0Njc50DQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

None

Response type

JSON

URL Parameters

Path Parameters

Required:

```
{id}: [ucmdb_id]
Data Types:
```

[ucmdb_id]

The string that represents the UCMDB ID of a configuration item.

Payload

None

Success response

```
Code: 200
```

```
Response:
```

```
{
    addedCis: list of [ucmdb_id]
    removedCis: list of [ucmdb_id],
    updatedCis: list of [ucmdb_id],
    ignoredCis: list of [ucmdb_id]
}
```

Data Types:

```
[ucmdb_id]
```

The string that represents the UCMDB ID of a CI.

Example:

Code: 200

Response:

```
{
    addedCis: [],
    removedCis: [
        4b8416a13e686092b2a2e142ecceff46
],
```

```
updatedCis: [],
ignoredCis: []
}
```

Error response

Status: 404 or 400

Content:

```
{
  error: [string]
}
```

Example:

Code: 404

Content:

```
{
   error: The following error has occurred: The CI with the specified id was not
found. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for deleting the data inside UCMDB through the SDK.

Get Related CIs

This call returns the details of the CIs related to the specified CI.

URL

/dataModel/relatedCI/{id}

Method

GET

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

None

Response type

JSON

URL Parameters

Path Parameters

Required:

```
{id}: [ucmdb_id]
```

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a configuration item.

Payload

None

Success response

Response: 200

Content:

```
cis: [
```

```
ucmdbId: [ucmdb id],
      type: [ucmdb_cit],
      properties: {
        <ucmdb_cit_prop>: [ucmdb_cit_prop_value],
      }
    },
  ],
  relations: [
      ucmdbId: [ucmdb_id],
      type: [ucmdb_cit],
      end1Id: [ucmdb_id],
      end2Id: [ucmdb_id],
      properties: {
        <ucmdb_cit_prop>: [ucmdb_cit_prop_value],
      }
    },
  ]
}
```

Note: The ...(three dots) denotes that there can be 0 or more values.

Data Types:

```
[ucmdb id]
```

The string that represents the ID of an object.

```
[ucmdb_cit]
```

The string that represents the name of a valid configuration item type from the UCMDB. The name of the CI Type can be found inside the CI Type Manager.

```
[ucmdb_cit_prop_value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb_cit_prop>
```

The valid property name of the CI Type. You can get the name and the list of all properties of a CI Type from the CI Type Manager.

Error response

```
Status: 404 or 400

Content:
{
   error: [string]
}
```

Example: Code: 404

Content:

```
{
    error: The following error has occurred: The CI with the specified id was not
found. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for viewing the data inside UCMDB through the SDK.

Get Relation

This call returns the details of a relation.

URL

/dataModel/relation/{id}

Method

GET

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

None

Response type

JSON

URL Parameters

Path Parameters

Required:

{id}: [ucmdb_id]

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a relation.

Payload

None

Call example

GET <base_ulr>/dataModel/relation/464106e644e5d86daea003a2cbbc648f

Success response

Status: 200

Response:

Note: The ...(three dots) denotes that there can be 0 or more values.

Data Types:

```
[ucmdb id]
```

The string that represents the UCMDB ID of a relation.

```
[ucmdb_cit]
```

The string that represents the name of a valid relation type from the UCMDB.

```
[ucmdb_cit_prop_value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb_cit_prop>
```

The valid property name of the relation type. You can get the name and the list of all properties of a relation from the CI Type Manager.

Example:

Status: 200

Response:

```
{
  ucmdbId: 464106e644e5d86daea003a2cbbc648f,
  type: composition,
  properties: {
    root_candidatefordeletetime: 2016-07-31T08:41:54.189Z,
    data_operationisnew: false,
    root_class: node,
    display_label: test2,
    data_operationstate: 0:Normal,
    data_allow_auto_discovery: true,
```

```
},
end1Id: 4c558e88e6910f6ebf642c9e07be8426,
end2Id: 4a2a4387a61951a1ba1b2b5338930985
}
```

Error response

Status: 404 or 400

Content:

```
{
   error: [string]
}
```

Example:

Code: 404

Content:

```
{
   error: The following error has occurred: Relation with specified ID was not
found. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for viewing the data inside UCMDB through the SDK.

Update Relation

This call updates the details of a relation.

URL

/dataModel/relation/{id}

Method

PUT

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

```
Authorization: Bearer eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2 VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0
```

Request type

JSON

Response type

JSON

URL Parameters

Path Parameters

Required:

```
{id}: [ucmdb_id]
Data Types:
[ucmdb_id]
```

The string that represents the UCMDB ID of a relation.

Payload

```
{
  ucmdbId: [ucmdb_id],
  type: [ucmdb_cit],
  properties: {
    <ucmdb_cit_prop>: [ucmdb_cit_prop_value],
    ...
```

```
},
end1Id: [ucmdb_id],
end2Id: [ucmb_id]
}
```

Note:

- The ...(three dots) denotes that there can be 0 or more values.
- You have to specify only the properties that you want to update. Do not specify all properties of the relation.
- You cannot update the type, id, end1 and end2 of a relationship.

Data Types:

```
[ucmdb_id]
```

The string that represents the UCMDB ID of a relation.

```
[ucmdb cit]
```

The string that represents the name of a valid relation type from the UCMDB.

```
[ucmdb_cit_prop_value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb cit prop>
```

The valid property name of the relation type. You can get the name and the list of all properties of a relation from the CI Type Manager.

Example:

```
{
  ucmdbId : 464106e644e5d86daea003a2cbbc648f,
  type : composition,
  properties: {
     root_enableageing: true
  },
  end1Id: 4c558e88e6910f6ebf642c9e07be8426,
  end2Id: 4a2a4387a61951a1ba1b2b5338930985
}
```

Success response

```
Code: 200

Response:
{
    addedCis: list of [ucmdb_id]
    removedCis: list of [ucmdb_id],
    updatedCis: list of [ucmdb_id],
    ignoredCis: list of [ucmdb_id]
}

Data Types:
[ucmdb_id]
```

The string that represents the UCMDB ID of a relation.

Example:

Code: 200

Content:

Error response

Status: 404 or 400

Content:

```
{
  error: [string]
}
```

Example:

Code: 404

Content:

```
{
   error: The following error has occurred: Relation with specified ID was not
found. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for updating the data inside UCMDB through the SDK.

Delete Relation

This call deletes a relation.

URL

/dataModel/relation/{id}

Method

DELETE

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer eyJ@eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE@Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2 VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j@CtwHqyBhX1uLlfhr@eQQ7m0_gT0

Request type

None

Response type

JSON

URL Parameters

Path Parameters

Required:

```
{id}: [ucmdb_id]
```

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a relation.

Payload

None

Success response

Code: 200

Response:

```
{
    addedCis: list of [ucmdb_id]
    removedCis: list of [ucmdb_id],
    updatedCis: list of [ucmdb_id],
    ignoredCis: list of [ucmdb_id]
}
```

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a relation.

Example:

Code: 200

Content:

```
{
   addedCis: [],
   removedCis: [
      464106e644e5d86daea003a2cbbc648f
   ],
   updatedCis: [],
   ignoredCis: []
}
```

Error response

```
Status: 404 or 400
```

Content:

```
{
  error: [string]
}
```

Example:

Code: 404

Content:

```
{
   error: The following error has occurred: Relation with specified ID was not
found. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for deleting the data inside UCMDB through the SDK.

Sample Topology Query

This call returns an example of the structure of an ad hoc TQL query. This structure can be used for future query related calls.

URL

/sampleToplogyQuery

Method

GET

Headers

None

Request type

None

Response type

JSON

URL Parameters

Required: None

Optional:None

Payload

None

Success response

Hardcoded response:

```
"visible": true,
    "includeSubtypes": true,
    "layout": [
        "ucmdb_id",
        "name"
    ],
    "attributeConditions": [
        {
             "attribute": "name",
            "value": "node1"
        },
            "attribute": "memory",
            "operator": "greaterThan",
             "value": "2"
        },
        {
            "attribute": "ala",
             "operator": "isNull"
        }
    ],
    "ids": []
},
    "type": "node",
    "queryIdentifier": "node2",
    "visible": true,
    "includeSubtypes": true,
    "layout": [
        "ucmdb_id",
        "name"
    ],
    "attributeConditions": [
            "logicalOperator": "or",
            "conditions": [
                 {
                     "attribute": "name",
                     "operator": "in",
                     "value": [
                         "node1",
                         "node2"
                     ]
                 },
                     "attribute": "memory",
                     "operator": "lessThan",
                     "value": "2"
                 },
```

```
{
                             "logicalOperator": "or",
                             "conditions": [
                                      "attribute": "name",
                                      "operator": "equals",
                                      "value": "node1"
                                 },
                                      "attribute": "memory",
                                      "operator": "greaterThan",
                                      "value": "2"
                                 }
                             ]
                         }
                     ]
            "ids": []
    ],
    "relations": [
            "type": "composition",
            "queryIdentifier": "link",
            "visible": true,
            "includeSubtypes": false,
            "from": "node1",
            "to": "node2"
        }
    ]
}
```

Error response

None

Execute Query By Name

This call executes a TQL query by the name it is already saved with.

URL

/topology

Method

POST

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

JSON

Response type

JSON

URL Parameters

Required: None

Optional:None

Payload

<tql_name>: string

The payload contains only the name of the TQL to be executed.

Success response

Response: 200

-

Content:

```
{
  cis: [
    {
      ucmdbId: [ucmdb_id],
      type: [ucmdb_cit],
      properties: {
        <ucmdb_cit_prop>: [ucmdb_cit_prop_value],
      }
    },
  ],
  relations: [
      ucmdbId: [ucmdb_id],
      type: [ucmdb_cit],
      end1Id: [ucmdb_id],
      end2Id: [ucmdb_id],
      properties: {
        <ucmdb_cit_prop>: [ucmdb_cit_prop_value],
      }
    },
  1
}
```

Note: The ...(three dots) denotes that there can be 0 or more values.

Data Types:

[ucmdb_id]

The string that represents the ID of an object.

```
[ucmdb_cit]
```

The string that represents the name of a valid CI Type from the UCMDB. The name of the CI Type can be found inside the CI Type Manager.

```
[ucmdb_cit_prop_value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb_cit_prop>
```

The valid property name of the CI Type. You can get the name and the list of all properties of a CI Type from the CI Type Manager. You have to use the name of the property, not its display name.

Error response

```
Status: 500
```

Content:

```
{
  error: [string]
}
```

Note

The user that the token belongs to must have the required permissions for executing the TQL query.

Execute Query By Definition

This call executes a TQL query defined by the payload.

URL

/topologyQuery

Method

POST

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

JSON

Response type

JSON

URL Parameters

Required: None

Optional:None

Payload

```
nodes: [
  queryIdentifier: [temp_id],
 type: [ucmdb_cit],
 visible: [boolean],
  includeSubtypes: [boolean],
  layout: list of [ucmdb_cit_prop],
  attributeConditions: [
     {
       attribute: [ucmdb_cit_prop],
       operator: [operator] @optional,
       value: [ucmdb_cit_prop_value],
       not: [boolean] @optional default=false
     },
       logicalOperator: [logic_operator] @optional default=and,
       conditions: list of [attributeConditions]
     },
  ],
  ids: list of [ucmdb_id],
  linkConditions: [
     {
        linkIdentifier: [temp_id],
        minCardinality: [cardinality],
        maxCardinality: [cardinality]
     },
     {
```

```
logicalOperator: [logic operator] @optional default=and,
         conditions: list of [linkCondition]
       },
    ]
   },
  ...
  ],
  relations: [
    {
    queryIdentifier: [temp_id],
    type: [ucmdb cit],
    visible: [boolean],
    includeSubtypes: [boolean],
    layout: list of [ucmdb_cit_prop],
    attributeCondtitions: list of [attributeCondition],
    from: [temp_id],
    to: [temp_id]
    },
}
```

Note:

- The ...(three dots) denotes that there can be 0 or more values.
- The visible attribute above specifies whether to return this node in the results.
- The includeSubtypes attribute specifies whether to include the subtypes of this node type.
- The layout attribute specifies which attributes of the objects will be returned (default: none).
- The attributeConditions attribute specifies conditions on the properties of the objects or relationships. You can use simple attributes (name, operator, or value) or complex attributes (a logical operator and a list of attributes that are joined by that logical operator).
- The linkConditions attribute specifies conditions on the links that the object participates into.
 You need to specify the link's temporary ID and the cardinality. You can also use complex conditions that are made of a logical operator and a list of conditions.
- The not property on the conditions specifies whether to negate the condition. If this property is unspecified, the default value is false.

Data Types:

```
[temp id]
```

The string that represents a temporary ID of the objects. This temporary ID can be used for referring to the object inside this payload. For example, you can specify the two ends of a relationship, if you want to use an object that was defined in the same payload, use the object's temp ID.

```
[ucmdb_cit]
```

The string that represents the name of a valid CI Type from the UCMDB. You have to use the name of the CI Type, not the display name. The name of the CI Type can be found inside the CI Type Manager.

```
<ucmdb_cit_prop>
```

This represents the valid property name of the CI Type. You can get the name and the list of all properties of a CI Type from the CI Type Manager.

```
[operator]
```

One of the following strings: isNull, equals, isNotEqualTo, like, greaterThan, greaterThanOrEqual, lessThan, lessThanOrEqual, in, containsAny, contains. If this is unspecified, the default value is equals.

```
[ucmdb cit prop value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

```
[logic operator]
```

The string that represents a logic operator, which can be "and" or "or".

```
[cardinality]
```

The string that represents the cardinality of a relationship end, which can be a number, *, or UNBOUNDED.

Example:

See the output of GET /sampleToplogyQuery.

Success response

Response: 200

Content:

```
{
    cis: [
        {
            ucmdbId: [ucmdb_id],
            type: [ucmdb_cit],
            properties: {
            <ucmdb_cit_prop>: [ucmdb_cit_prop_value],
}
```

```
"
}
},
...
],
relations: [
{
   ucmdbId: [ucmdb_id],
   type: [ucmdb_cit],
   end1Id: [ucmdb_id],
   end2Id: [ucmdb_id],
   properties: {
        <ucmdb_cit_prop>: [ucmdb_cit_prop_value],
        ...
}
},
...
]
```

Note: The ...(three dots) denotes that there can be 0 or more values.

Data Types:

```
[ucmdb id]
```

The string that represents the ID of an object.

```
[ucmdb_cit]
```

The string that represents the name of a valid CI Type from the UCMDB. The name of the CI Type can be found inside the CI Type Manager.

```
[ucmdb_cit_prop_value]
```

The property value, which can be integer, string, Boolean, long, double, ISO8601 date, or a list of values depending on the CIT property data type.

Custom fields:

```
<ucmdb_cit_prop>
```

The valid property name of the CI Type. You can get the name and the list of all properties of a CI Type from the CI Type Manager. You have to use the name of the property, not its display name.

Error response

Status: 400

Content:

```
{
    error: [string]
}

Example:

Code: 400

Content:
{
    error: The following error has occurred: Class "nodeo" is not defined in the class model. Please consult logs for more details
}
```

Note

The user that the token belongs to must have the required permissions for executing TQL queries by definition through the SDK.

Run Impact Analysis

This call runs an impact analysis with a given definition.

URL

/impactAnalysis

Method

POST

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer eyJ@eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE@Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2 VybmFtZSI6InN5c2FkbWluIn@.Ph8WHtzvpvfuH1j@CtwHqyBhX1uLlfhr@eQQ7m@ gT@

Request type

JSON

Response type

JSON

URL Parameters

Required: None

Optional: None

Payload

```
{
  "triggerCIs": [
      {
        "triggerId": [ucmdb_id],
        "severity": [severity]
      },
      ...
],
  "properties": ["name","label',...],
  "bundles": ["bundle1","bundle2",...]
}
```

Configure the payload's parameters as follows:

- "bundles". (Optional) Specify the bundles of rules used to run the analysis. If you do not specify a list of bundles, all bundles are used by default.
- "properties". (Optional) Specify the properties to be fetched for each affected CI that is identified by the impact analysis (as an array of strings names). If not specified, no extra property will be fetched. The CI type and the UCMDB ID are fetched by default.
- "triggerCIs". Specify the CIs that are triggered for this impact analysis (as an array of trigger CIs).

 At least one trigger CI should be specified. Each trigger CI has two fields:

"triggerld". [ucmdb_id]

The string that represents the CI's ID in UCMDB.

• "severity". [severity]

The string that represents the severity at which the trigger CI is affected.

Note:

- To check the available [severity] levels, see the output of GET /impactAnalysis/severities.
- The ...(three dots) denotes that there can be more values in the array.

Success response

Code: 200

Content:

The above parameters are described below:

- "affectedCIs". The list of affected CIs identified by the impact analysis. Each affected CI contains
 the following fields:
 - "ucmdbld" [ucmdb_id]. The string that represents the ID of an object.
 - "severity" [severity]. The string that represents the severity at which the CI is affected.
 - "type" [type]. The string that specifies the CI type of the affected CI.
 - "properties". The properties that were requested in the Payload.

Note: The ...(three dots) denotes that there can be 0 or more values.

Error response

```
Code: 400
```

Content:

```
{
  error: [string]
}
```

Multiple CMDB Calls

Converting UCMDB IDs to Global Ids

This call converts UCMDB IDs to Global IDs.

URL

/multipleCmdb/convertToGlobalIds

Method

POST

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAi0iJKV1QiLCJhbGci0iJIUzI1NiJ9.eyJleHAi0jE0Njc50DQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

JSON

Response type

JSON

URL Parameters

Required: None

Optional: None

Payload

```
[ list of ucmdb_id ]
```

Example:

```
[ "40967247acdd869fa52d1f42e4eeb59a", "48981ed7ff877904bbbeb7d5c72069fa"]
```

Data Types:

```
[ucmdb_id]
```

The string that represents the UCMDB ID of a CI.

Success response

Code: 200

Content:

```
{
"ids": [
{
ucmdbId: [ucmdb_id],
globalId: [String]
}, ...
]
}
```

Example:

Code: 200

Content:

```
"globalId": "4dd87eb2bba2cf59a177662dbb0e7a44"
},
{
"ucmdbId": "445519e389143825ad01aeccbf3f50ca",
"globalId": "445519e389143825ad01aeccbf3f50ca"
}
]
}
```

Data Types:

[ucmdb_id]

The string that represents the UCMDB ID of a CI.

Error response

Code: 400

Content:

```
{
  error: [string]
}
```

Notes

The user needs access to SDK permission.

Converting Global IDs to UCMDB IDs

This call converts Global IDs to UCMDB IDs.

URL

/multipleCmdb/convertToUcmdblds

Method

POST

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAi0iJKV1QiLCJhbGci0iJIUzI1NiJ9.eyJleHAi0jE0Njc50DQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

JSON

Response type

JSON

URL Parameters

Required: None

Optional: None

Payload

```
[ list of Strings ]
```

Example:

```
[ "40967247acdd869fa52d1f42e4eeb59a", "48981ed7ff877904bbbeb7d5c72069fa"]
```

Note: String represents the Global IDs.

Success response

Code: 200

Content:

```
{
"ids": [
{
ucmdbId: [ucmdb_id],
globalId: [String]
}, ...
]
```

Example:

Code: 200

Content:

```
{
  "ids": [
  {
    "ucmdbId": "4dd87eb2bba2cf59a177662dbb0e7a44",
    "globalId": "4dd87eb2bba2cf59a177662dbb0e7a44"
  },
  {
    "ucmdbId": "445519e389143825ad01aeccbf3f50ca",
    "globalId": "445519e389143825ad01aeccbf3f50ca"
  }
  ]
}
```

Data Types:

```
[ucmdb_id]
```

The string that represents the UCMDB ID of a CI.

Note: String represents the Global IDs.

Error response

Code: 400

Content:

```
{
  error: [string]
}
```

Notes

The user needs access to SDK permission.

History Changes

Get Removed Cls

This call returns the list of CIs removed in a specified time frame.

URL

/history/getRemovedCIs

Method

GET

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

None

Response type

JSON

URL Parameters

Required:

[from]

The starting time for retrieving the events, measured in milliseconds. (Long)

[to]

The ending time for retrieving the events, measured in milliseconds. (Long)

Optional:

[ciType]

The CI Type. (String)

For example:

```
https://localhost:8443/rest-api/history/getRemovedCIs?from=1475223669000&to=1475323669000&ciType=host
```

Payload

None

Success response

```
Response: 200
```

Content:

```
{
    "removedCis": [
        "495a4faf96729548a2603046dbf7efd9",
        "4c21a0fb4d6c0a69b99f34576c0efb67"
    ]
}
```

Error response

Status: 404, 500, or 400

Content:

```
{
error: [string]
\
```

Example:

Code: 404

Content:

```
{
   error: The server was not found.
}
```

Get Changes

This call retrieves the history changes occurred in a specified time frame.

URL

/history/getChanges

Method

GET

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

Authorization: Bearer

eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE0Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2

VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr0eQQ7m0_gT0

Request type

None

Response type

JSON

URL Parameters

Required:

[from]

The starting time for retrieving the events, measured in milliseconds. (Long)

[to]

The ending time for retrieving the events, measured in milliseconds. (Long)

Optional:

[change Type]

The types of changes you want to retrieve. The possible values are: ADD_OBJECT, UPDATE_OBJECT, REMOVE_OBJECT, ADD_LINK, UPDATE_LINK, REMOVE_LINK, ADD_RELATION, and REMOVE_RELATION. This parameter can be specified multiple times. (Set)

[id]

The list of UCMDB IDs for which history events should be retrieved. (Set)

For example:

```
https://localhost:8443/rest-api/history/getChanges?from=1475323669000&to=1476706069000&changeType=ADD_OBJECT
https://localhost:8443/rest-api/history/getChanges?from=1475323669000&to=1476706069000&changeType=ADD_OBJECT&changeType=UPDATE_OBJECT&id=4d08b8a5e349a7fdba5ba5ff60f47929&id=476948c54e4a86e1a32bb83c41cdc7c5
```

Payload

None

Success response

Response: 200

```
Content:
```

```
{
    "history": [
        {
            "id": "4d08b8a5e349a7fdba5ba5ff60f47929",
            "changes": [
                {
                    "time": 1476365233608,
                    "changer": "User:admin",
                     "dataStore": "UCMDB-UI",
                    "changeType": "ADD_OBJECT",
                     "data": {
                         "dataId": "4d08b8a5e349a7fdba5ba5ff60f47929",
                         "type": "nt",
                         "properties": {
                             "display label": "windows-0001",
                             "track changes": false,
                             "data_allow_auto_discovery": true,
                             "create time": 1476365233752,
                             "global_id": "4d08b8a5e349a7fdba5ba5ff60f47929",
                             "name": "windows-0001",
                             "lic_type_udf": false,
                             "default gateway ip address type": "IPv4",
                             "is_save_persistency": false,
                             "lic_type_udi": false,
                             "data source": "UCMDB-UI: User:admin",
                             "root_enableageing": false
```

```
}
                    }
                },
                    "time": 1476365768785,
                    "changer": "User:{UISysadmin:UCMDB},LoggedInUser:{admin:UCMDB}
                     "dataStore": "UCMDB",
                     "changeType": "UPDATE_OBJECT",
                     "data": {
                         "dataId": "4d08b8a5e349a7fdba5ba5ff60f47929",
                         "type": "nt",
                         "properties": {
                             "description": "decription 1"
                        }
                    }
                },
                    "time": 1476438324892,
                     "changer": "User:{UISysadmin:UCMDB},LoggedInUser:{admin:UCMDB}
۳,
                     "dataStore": "UCMDB",
                     "changeType": "UPDATE_OBJECT",
                     "data": {
                         "dataId": "4d08b8a5e349a7fdba5ba5ff60f47929",
                         "type": "nt",
                         "properties": {
                             "bios_source": "cosmos"
                        }
                    }
                },
                    "time": 1476438334455,
                     "changer": "User:{UISysadmin:UCMDB},LoggedInUser:{admin:UCMDB}
                    "dataStore": "UCMDB",
                    "changeType": "UPDATE_OBJECT",
                     "data": {
                         "dataId": "4d08b8a5e349a7fdba5ba5ff60f47929",
                         "type": "nt",
                         "properties": {
                             "bios_source": "cosmos-galaxy"
                        }
                    }
                }
            ]
        },
        {
            "id": "476948c54e4a86e1a32bb83c41cdc7c5",
```

```
"changes": [
                {
                     "time": 1476365263533,
                     "changer": "User:admin",
                     "dataStore": "UCMDB-UI",
                     "changeType": "ADD_OBJECT",
                     "data": {
                         "dataId": "476948c54e4a86e1a32bb83c41cdc7c5",
                         "type": "nt",
                         "properties": {
                             "display_label": "windows-0002",
                             "track_changes": false,
                             "data_allow_auto_discovery": true,
                             "create_time": 1476365263534,
                             "global_id": "476948c54e4a86e1a32bb83c41cdc7c5",
                             "name": "windows-0002",
                             "lic_type_udf": false,
                             "default_gateway_ip_address_type": "IPv4",
                             "is_save_persistency": false,
                             "lic_type_udi": false,
                             "data_source": "UCMDB-UI: User:admin",
                             "root_enableageing": false
                         }
                    }
                },
                     "time": 1476365784442,
                     "changer": "User:{UISysadmin:UCMDB},LoggedInUser:{admin:UCMDB}
                     "dataStore": "UCMDB",
                     "changeType": "UPDATE_OBJECT",
                     "data": {
                         "dataId": "476948c54e4a86e1a32bb83c41cdc7c5",
                         "type": "nt",
                         "properties": {
                             "description": "description 2"
                         }
                    }
                }
            ]
        }
    ]
}
```

Error response

Status: 404, 500, or 400

```
Content:
```

```
{
    error: [string]
}

Example:

Code: 404

Content:
{
    error: The server was not found or the value for changeType is not in the allowed domain.
}
```

Get Data Layout

This call returns the data layout at the specified date for the CIs that have one of the IDs provided.

URL

/history/getDataLayout

Method

POST

Headers

Required:

Authorization: Bearer <token>

Note: <token> is the token that is returned by the Authentication call.

Example:

```
Authorization: Bearer eyJ@eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJleHAiOjE@Njc5ODQ5MTcsImN1c3RvbWVyIjoxLCJ1c2 VybmFtZSI6InN5c2FkbWluIn0.Ph8WHtzvpvfuH1j0CtwHqyBhX1uLlfhr@eQQ7m0_gT0
```

Request type

JSON

Response type

JSON

URL Parameters

Required: none

Optional: none

```
Payload
    "data": [
        {
            "date": 1476365233608,
            "ciIDs": [
                "495a4faf96729548a2603046dbf7efd9",
                "476948c54e4a86e1a32bb83c41cdc7c5"
            ]
        },
         {
            "date" : 1476438324892,
            "ciIDs": [
                "4d08b8a5e349a7fdba5ba5ff60f47929",
                "476948c54e4a86e1a32bb83c41cdc7c5"
            ]
        },
            "date": 1476365784442,
            "ciIDs": [
                "476948c54e4a86e1a32bb83c41cdc7c5"
            ]
        }
    ],
    "layout" : [
        "name",
        "description",
        "bios_tag"
}
```

Success response

```
Response: 200
```

```
Content:
{
    "history": [
            "date": 1478699889366,
            "data": [
                {
                     "type": "node",
                     "isObject": true,
                     "dataId": "4a1c2ec8804ffa44aa2124de5921b8fe",
                     "properties": {
                         "name": "node1",
                         "description": "xxx"
                     }
                }
            ]
        }
    ]
}
```

Error response

Status: 404, 500, or 400

Content:

```
{
  error: [string]
}
```

Example:

Code: 404

Content:

{
 error: The server was not found or the value for changeType is not in the
allowed domain.
}

Chapter 13: Data Flow Management Java API

This chapter includes:

Using the Data Flow Management Java API	438
5	
IP Range Management API	439

Using the Data Flow Management Java API

Note: Use this chapter in conjunction with the DFM API Javadoc, available in the online Documentation Library.

This chapter explains how third-party or custom tools can use the HP Data Flow Management Java API to manage Data Flow. The API provides methods to:

- Manage credentials. View, add, update, and remove.
- Manage jobs. View status, activate, and deactivate.
- Manage probe ranges. View, add, and update.
- Manage triggers. Add or remove a trigger CI, and add, remove, or disable a trigger TQL.
- View general data. Data on domains and probes.

The following services are available in the Discovery Services package:

- DDMConfigurationService. Services to configure the Data Flow Probes, clusters, IP Ranges, and Credentials. The Universal Discovery server can be configured with an XML file or via the Data Flow Probe.
- DDMManagementService. Services to analyze and view the progress, results, and errors of the Universal Discovery run.
- DDMSoftwareSignatureService. Services to define software items to be discovered by the Data
 Flow Probe components. The definitions are system-wide. If more than one Data Flow probe
 component is defined, the definitions apply to all of them.
- DDMZoneService. Services to manage zone-based discovery.

In addition to these services, there are Data Flow Management client APIs, which are used in creating Jython adapters. For details, see "Developing Jython Adapters" on page 45.

Permissions

The administrator provides login credentials for connecting with the API. The API client needs the user name and password of an integration user defined in the CMDB. These users do not represent human users of the CMDB, but rather applications that connect to the CMDB.

In addition, the user must have the Access to SDK general action permission in order to log in.

Caution: The API client can also work with regular users as long as they have API authentication permission. However, this option is not recommended.

For details, see "Create an Integration User" on page 330.

IP Range Management API

In the Data Flow Management Java API, a new method **importIPRanges()** is introduced into the **DDMConfigurationService** class in UCMDB version 10.22. This method allows you to perform the following tasks by using a customized script to manage the IP ranges of specified Probes:

- Overwrite the IP ranges of specified Probes. The IPv4/6, Range, and Type settings of an IP range
 are manageable through this method.
- Assign certain probes in the same domain into a probe list, and then distribute the IP addresses in the specified ranges evenly to each probe in the group.

Note: Group is a temporary parameter used in this API method to group a set of probes assigned to the same domain, and to balance the IPs evenly among these probes.

You can perform this task on any computer that can access the UCMDB server. One or both of the following files are mandatory to set up the work environment on different computers:

- ucmdb-api.jar: On the UCMDB server or on a probe, you only need this file. This file is available for download from the UCMDB server through the following URL: https://<IP_or_ FQDN>:8443/ucmdb-api/download
- api-client.jar: On a computer other than the UCMDB server or a probe, you need this file in addition
 to the ucmdb-api.jar file. This file is available in the following directory on the UCMDB server:
 UCMDB_server>\lib\

For more information about how to use the UCMDB API, refer to the following documentation:

- The HP Universal CMDB API chapter in the HPE Universal CMDB Developer Reference Guide
- API Reference

For a sample script to perform the IP range management task, see "Sample Script for IP Range Management API" below.

Note:

- This method does not support Data Flow Probe clusters.
- You can specify the excluded IP ranges in the script. The API will calculate the whole IP ranges and the excluded IP ranges, and only assign the resulting IP ranges to a probe.
- For both IPv4 and IPv6, you must specify an IP range with a starting IP address and an ending IP address in the format of x.x.x.x.x.x.x. If you want to specify a single IP address, the starting IP address and the ending IP address are the same.
- An IP range should not overlap with another IP range in the script or with an IP range in another existing probe. Otherwise, the IP range will not be imported.
- When you add probe list in the Java API importIPRanges() method, make sure you only add
 the discovery probe list. Do not add integration probes (for example, Linux probes or integration
 services).

Linux Probes and integration services do not need IP ranges. If you add Linux probes or integration services, although the IPs in Linux probe or integration services do not display in the UI, they will be assigned to Linux Probes or integration services.

Sample Script for IP Range Management API

```
package com.hp.ucmdb.api.client.util;
import com.hp.ucmdb.api.UcmdbService;
import com.hp.ucmdb.api.UcmdbServiceFactory;
import com.hp.ucmdb.api.UcmdbServiceProvider;
import com.hp.ucmdb.api.client.types.IPRangeImpl;
import com.hp.ucmdb.api.client.types.IPRangeWithExcludingImpl;
import com.hp.ucmdb.api.discovery.types.IPRange;
import java.lang.reflect.Method;
import java.util.ArrayList;
import java.util.HashMap;
import java.util.List;
/**
```

```
* Created by dingmen on 8/12/2015.
 */
public class UpdateIpRangeTest {
    private static final String HOST_NAME = "16.187.189.134";
    private static final int HTTP PORT = 8080;
    private static final String HTTPS = "https";
    private static final String HTTP = "http";
    private static UcmdbService ucmdbService;
    public static void main(String[] args) {
        testSenario1();
    private static void testSenario1(){
        try {
            UcmdbServiceProvider provider = UcmdbServiceFactory.getServiceProvider
(HTTP, HOST NAME, HTTP PORT);
            ucmdbService = provider.connect(provider.createCredentials("admin",
"admin"), provider.createClientContext("Test"));
            HashMap<String, ArrayList<String>> probeLBGroup = new HashMap<String,</pre>
ArrayList<String>>();
            HashMap<String, ArrayList<IPRange>> IPRangeGroup = new HashMap<String,</pre>
ArrayList<IPRange>>();
            HashMap<String, ArrayList<String>> domainGroup = new HashMap<String,
ArrayList<String>>();
            //put domain name as key in domainGroup, and its value is a list of
groups.
         'DefaultDomain' is a existing name in UCMDB .
            domainGroup.put("DefaultDomain", new ArrayList<String>());
            domainGroup.get("DefaultDomain").add("PG1");
            //define 'PG1' as the first group name(The group name can be any other
values) in probeLBGroup ,
            //and its value is a list of probe name. 'Probe1' or 'Probe2' should be
existing name in UCMDB .
            probeLBGroup.put("PG1", new ArrayList<String>());
            probeLBGroup.get("PG1").add("Probe1");
            probeLBGroup.get("PG1").add("Probe2");
            //Below all ranges are defined in IPRangeGroup for 'PG1', and they
will balanced distributed to probes in 'PG1'.
            IPRangeGroup.put("PG1", new ArrayList<IPRange>());
            //should specify ip type 'IPV4/IPV6' , and ip category
'DataCenter/Client' for each range.
            IPRangeGroup.get("PG1").add(new IPRangeWithExcludingImpl("1.1.1.1",
"1.1.1.9", IPRange.IPType.IPV4, IPRange.RangeCategory.CLIENT, new
ArrayList<IPRangeImpl>()));
            List<IPRangeImpl> excludedRange1=new ArrayList<IPRangeImpl>();
```

```
IPRangeGroup.get("PG1").add(new IPRangeWithExcludingImpl("1.1.1.10",
"1.1.1.19", IPRange.IPType.IPV4,IPRange.RangeCategory.DATA_CENTER,
excludedRange1));
            excludedRange1.add(new IPRangeImpl
("1.1.1.10","1.1.1.19",IPRange.IPType.IPV4,IPRange.RangeCategory.DATA_CENTER));
            excludedRange1.add(new IPRangeImpl
("1.1.1.12","1.1.1.15",IPRange.IPType.IPV4,IPRange.RangeCategory.DATA_CENTER));
            IPRangeGroup.get("PG1").add(new IPRangeWithExcludingImpl
("fe80:0:0:0:41f8:4318:2000:80", "fe80:0:0:0:41f8:4318:2000:83",
IPRange.IPType.IPV6,IPRange.RangeCategory.CLIENT, new ArrayList<IPRangeImpl>()));
            //below is the second group 'PG2', and assign below 'GP2' range
(1.1.1.20~1.1.1.30) to below 'PG2' probe(Probe3) .
            domainGroup.get("DefaultDomain").add("PG2");
            probeLBGroup.put("PG2", new ArrayList<String>());
            probeLBGroup.get("PG2").add("Probe3");
            IPRangeGroup.put("PG2", new ArrayList<IPRange>());
            IPRangeGroup.get("PG2").add(new IPRangeWithExcludingImpl("1.1.1.20",
"1.1.1.30", IPRange.IPType.IPV4,IPRange.RangeCategory.DATA CENTER, new
ArrayList<IPRangeImpl>()));
            //the domain group with probe and range group in set to importIPRanges
API to update ip ranges.
            ucmdbService.getDDMConfigurationService().importIPRanges(probeLBGroup,
IPRangeGroup, domainGroup);
        } catch (Throwable e) {
            e.printStackTrace();
    }
}
```

Chapter 14: Data Flow Management Web Service API

This chapter includes:

Data Flow Management Web Service API Overview	443
Conventions	444
Creating the Web Service Client	444
Call the HP Data Flow Management Web Service	445
Data Flow Management Methods and Data Structures	445
Code Samples	458

Data Flow Management Web Service API Overview

This chapter explains how third-party or custom tools can use the HP Data Flow Management Web Service API to manage Data Flow.

The HP Data Flow Management Web Service API is used to integrate applications with Universal CMDB. The API provides methods to:

- Manage credentials. View, add, update, and remove.
- Manage jobs. View status, activate, and deactivate.
- Manage probe ranges. View, add, and update.
- Manage triggers. Add or remove a trigger CI, and add, remove, or disable a trigger TQL.
- View general data. Data on domains and probes.

Users of the HP Data Flow Management Web Service should be familiar with:

- The SOAP specification
- An object-oriented programming language such as C++, C# or Java
- Universal CMDB
- · Data Flow Management

Note:

- A user must have the Run Legacy API general action permission in order to log in.
- The logged-in user must have the **Run Discovery and Integrations** general action permission to access any of the methods.

For full documentation on the available operations, see *HP Universal Discovery Schema Reference*. These files are located in the following folder:

<UCMDB root directory>\UCMDBServer\deploy\ucmdb-docs\docs\eng\APIs\DDM_
Schema\webframe.html

Conventions

This chapter uses the following conventions:

- This style Element indicates that an item is an entity in the database or an element defined in the schema, including structures passed to or returned by methods. Plain text indicates that the item is being discussed in a general context.
- Data Flow Management elements and method arguments are spelled in the case in which they are specified in the schema. This usually means that a class name or generic reference to an instance of the class is capitalized. An element or argument to a method is not capitalized. For example, a credential is an element of type Credential passed to a method.

Creating the Web Service Client

Use the following recommended approach to generate the Web Service client by using Apache Axis2 and XMLBeans:

- Extract ucmdb_service.aar to a temporary folder.
 - The ucmdb_service.aar file is available under \hp\UCMDB\UCMDBServer\deploy\axis2\WEB-INF\services\.
- 2. Download the axis2-1.1.1-bin.zip file from the following address, and then unpack the file.
 - http://axis.apache.org/axis2/java/core/download.cgi
- 3. Run the following command:

```
<axis2-1.1.1 install folder>\bin\wsdl2java -uri <ucmdb_serverice.aar
extract folder>/META-INF/DiscoveryService.wsdl -d xmlbeans -p
com.hp.ucmdb.generated -s -a -o <output folder>
```

4. Under the <output folder>, run ant Build.xml to generate the Web Service client jar packages.

Now you can use the generated jar files together with all the jar files under \hp\UCMDB\UCMDBServer\deploy\axis2\WEB-INF\lib\ to develop codes to call the Data Flow Management Web Service API.

Call the HP Data Flow Management Web Service

The HP Data Flow Management Web Service API enables calling server-side methods using standard SOAP programming techniques. If the statement cannot be parsed or if there is a problem invoking the method, the API methods throw a SoapFault exception. When a SoapFault exception is thrown, the service populates one or more of the error message, error code, and exception message fields. If there is no error, the results of the invocation are returned.

To call the service, use:

- Protocol: http or https (depending on server configuration)
- URL: <UCMDB server>:8443/axis2/services/DiscoveryService
- Default username: "admin"

SOAP programmers can access the WSDL at:

axis2/services/DiscoveryService?wsdl

Data Flow Management Methods and Data Structures

This section lists the Data Flow Management Web Service API methods and data structures, and provides a brief summary of their uses. For full documentation of the request and response for each operation, see *HP Universal Discovery Schema Reference*.

This section includes the following topics:

- "Data Structures" on the next page
- "Managing Discovery Job Methods" on page 447

- "Managing Trigger Methods" on page 449
- "Domain and Probe Data Methods" on page 451
- "Credentials Data Methods" on page 454
- "Data Refresh Methods" on page 456

Data Structures

These are some of the data structures used in the Data Flow Management Web Service API.

CIProperties

CIProperties is a collection of collections. Each collection contains properties of a different data type. For example, there can be a dateProps collection, a strListProps collection, an xmlProps collection, and so on.

Each type collection contains individual properties of the given type. The names of these properties elements is the same as the container, but in singular. For example, dateProps contains dateProp elements. Each property is a name-value pair.

See CIProperties in the HP Universal Discovery Schema Reference.

IPList

A list of IP elements, each of which contains an IPv4 or IPv6 Address.

See IPList in the HP Universal Discovery Schema Reference.

IPRange

An IPRange has two elements, Start and End. Each element contains an Address element, which is an IPv4 or IPv6 Address.

See IPRange in the HP Universal Discovery Schema Reference.

Scope

Two IPRanges. Exclude is a collection of IPRanges to exclude from the job. Include is a collection of IPRanges to include in the job.

See Scope in the HP Universal Discovery Schema Reference

Managing Discovery Job Methods

activateJob

Activates the specified job.

See "Code Samples" on page 458.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.

deactivateJob

Deactivates the specified job.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.

dispatchAdHocJob

Dispatches a job on the probe ad hoc. The job must be active and contain the specified trigger CI.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.
CIID	The ID of the trigger CI.

Parameter	Comment
ProbeName	The name of the probe.
Timeout	In milliseconds

getDiscoveryJobsNames

Returns the list of job names.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.

Output

Parameter	Comment
strList	The list of job names.

isJobActive

Checks whether the job is active.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job to check.

Parameter	Comment
JobState	True if the job is active.

Managing Trigger Methods

addTriggerCI

Adds a new trigger CI to the specified job.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.
CIID	The ID of the trigger CI.

add Trigger TQL

Adds a new trigger TQL to the specified job.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.
TqlName	The name of the TQL to add.

disable Trigger TQL

Prevents the TQL from triggering the job, but does not permanently remove it from the list of queries that trigger the job.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.

Parameter	Comment
tqlName	The name of the TQL.

removeTriggerCl

Removes the specified CI from the list of CIs that trigger the job.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.
CIID	The ID of the trigger CI.

removeTriggerTQL

Removes the specified TQL from the list of queries that trigger the job.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.
tqlName	The name of the TQL.

set Trigger TQL Probes Limit

Restrict the probes in which the TQL is active in the job to the specified list.

Input

Parameter	Comment	
cmdbContext	For details, see "CmdbContext" on page 349.	
JobName	The name of the job.	

Parameter	Comment	
tqlName	The TQL name.	
probesLimit	The list of probes for which the TQL is active.	

getJobTriggerTqls

Get the TQL from the job.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
JobName	The name of the job.

Domain and Probe Data Methods

getDomainType

Returns the domain type.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The name of the domain.

Output

Parameter	Comment
domainType	The domain type.

getDomainsNames

Returns the names of the current domains.

See "Code Samples" on page 458.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.

Output

Parameter	Comment
domainNames	The list of domain names.

getProbelPs

Returns the IP addresses of the specified probe.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain to check.
probeName	The name of the probe used on that domain.

Output

Parameter	Comment
probelPs	The "IPList" of the addresses in the probe.

getProbesNames

Returns the names of the probes in the specified domain.

See "Code Samples" on page 458.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain to check.

Output

Parameter	Comment
probesName	The list of probes on the domain.

getProbeScope

Returns the scope definition of the specified probe.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain to check.
probeName	The name of the probe.

Output

Parameter	Comment
probeScope	The "Scope" of the probe.

isProbeConnected

Checks whether the specified probe is connected.

See "Code Samples" on page 458.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain to check.
probeName	The probe to check

Parameter	Comment
isConnected	True if the probe is connected.

updateProbeScope

Sets the scope of the specified probe, overriding the existing scope.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain.
probeName	The probe to update.
newScope	The "Scope" to set for the probe.

Credentials Data Methods

add Credentials Entry

Adds a credentials entry to the specified protocol for the specified domain.

See "Code Samples" on page 458.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain to update.
protocolName	The name of the protocol.
credentialsEntryParameters	The "CIProperties" collection of the new credentials.

Parameter	Comment
credentialsEntryID	The CI ID of the new credential entry.

get Credentials Entries IDs

Returns the IDs of the credentials defined for the specified protocol.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain for which to get the credentials.
protocolName	The name of a protocol used on that domain.

Output

Parameter	Comment
credentialsEntryIDs	The list of credential IDs for the protocol on the domain.

getCredentialsEntry

Returns the credentials defined for the specified protocol. Encrypted attributes are returned empty.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain for which to get the credentials.
protocolName	The name of a protocol used on that domain.
credentialsEntryID	The credential ID to get.

Parameter	Comment
credentialsEntryParameters	The "CIProperties" collection of the credentials.

removeCredentialsEntry

Removes the specified credentials from the protocol.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain.
protocolName	The name of a protocol used on the domain.
credentialsEntryID	The ID of the credential to remove.

updateCredentialsEntry

Sets new values for properties of the specified credentials entry.

The existing properties are deleted and these properties are set. Any property whose value is not set in this call is left undefined.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
domainName	The domain in which to update credentials.
protocolName	The name of a protocol used on the domain.
credentialsEntryID	The ID of the credentials to update.
credentialsEntryParameters	The "CIProperties" collection to set as properties for the credentials.

Data Refresh Methods

rediscoverCls

Locates the triggers that discovered the specified CI objects and reruns those triggers. **rediscoverCIs** runs asynchronously. Call **checkDiscoveryProgress** to determine when the rediscovery is complete.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
CmdblDs	Collection of IDs of the objects to rediscover.

Output

Parameter	Comment
isSucceed	True if the CIs rediscovery succeeded.

check Discovery Progress

Returns the progress of the most recent **rediscoverCIs** call on the specified IDs. The response is a value between 0-1. When the response is 1, the **rediscoverCIs** call has completed.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
CmdblDs	Collection of IDs of the objects in the rediscover call to track.

Output

Parameter	Comment
progress	A completed job has a progress of 1. Jobs that have not completed have a fraction less than 1.

rediscoverViewCls

Locates the triggers that created the data to populate the specified view, and reruns those triggers. rediscoverViewCIs runs asynchronously. Call checkViewDiscoveryProgress to determine when the rediscovery is complete.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
viewName	The views to check.

Output

Parameter	Comment
isSucceed	True if CIs rediscovery succeeded.

check View Discovery Progress

Returns the progress of the most recent **rediscoverViewCIs** call on the specified view. The response is a value from 0 to 1. When the response is 1, the **rediscoverCIs** call has completed.

Input

Parameter	Comment
cmdbContext	For details, see "CmdbContext" on page 349.
viewName	The collection of views to check.

Output

Parameter	Comment
progress	A completed job has a progress of 1. Jobs that have not completed have a fraction less than 1.

Code Samples

This section provides code samples for the following methods:

Managing Discovery Job Methods	459
Managing Trigger Methods	462
Domain and Probe Data Methods	466
Credentials Data Methods	470
Data Refresh Methods	476

Managing Discovery Job Methods

```
import java.net.URL;
import java.rmi.RemoteException;
import org.apache.axis2.transport.http.HTTPConstants;
import org.apache.axis2.transport.http.HttpTransportProperties;
import com.hp.schemas.ucmdb. 1.types.CmdbContext;
import com.hp.schemas.ucmdb.discovery. 1.params.ActivateJobRequest;
import com.hp.schemas.ucmdb.discovery. 1.params.ActivateJobRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.DeactivateJobRequest;
import com.hp.schemas.ucmdb.discovery._1.params.DeactivateJobRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.DispatchAdHocJobRequest;
import com.hp.schemas.ucmdb.discovery._1.params.DispatchAdHocJobRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetDiscoveryJobsNamesRequest;
import com.hp.schemas.ucmdb.discovery.
1.params.GetDiscoveryJobsNamesRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetDiscoveryJobsNamesResponse;
import com.hp.schemas.ucmdb.discovery.
1.params.GetDiscoveryJobsNamesResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.IsJobActiveRequest;
import com.hp.schemas.ucmdb.discovery. 1.params.IsJobActiveRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.IsJobActiveResponse;
import com.hp.schemas.ucmdb.discovery._1.params.IsJobActiveResponseDocument;
import com.hp.ucmdb.generated.DiscoveryServiceStub;
import com.hp.ucmdb.generated.UcmdbFault;
public class TestJob {
       static final String HOST_NAME = "<my_hostname>";
    static final int PORT = 8080;
    private static final String PROTOCOL = "http";
    private static final String FILE = "/axis2/services/DiscoveryService";
    private static final String PASSWORD = "admin";
    private static final String USERNAME = "admin";
    public static CmdbContext cmdbContext = CmdbContext.Factory.newInstance();
       public static void activateJob(String jobName) throws RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("activateJob");
                ActivateJobRequest activateJobRequest = ActivateJobRequest.Factory.newInstance
();
                activateJobRequest.setCmdbContext(cmdbContext);
                activateJobRequest.setJobName(jobName);
                ActivateJobRequestDocument activateJobRequestDocument =
ActivateJobRequestDocument.Factory.newInstance();
```

```
activateJobRequestDocument.setActivateJobRequest(activateJobRequest);
                serviceStub.activateJob(activateJobRequestDocument);
       }
       public static void deActivateJob(String jobName) throws RemoteException,
UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("deActivateJob");
                DeactivateJobRequest deactivateJobRequest =
DeactivateJobRequest.Factory.newInstance();
                deactivateJobRequest.setCmdbContext(cmdbContext);
                deactivateJobRequest.setJobName(jobName);
                DeactivateJobRequestDocument deactivateJobRequestDocument =
DeactivateJobRequestDocument.Factory.newInstance();
                deactivateJobRequestDocument.setDeactivateJobRequest(deactivateJobRequest);
                serviceStub.deactivateJob(deactivateJobRequestDocument);
       public static void isJobActive(String jobName) throws RemoteException, UcmdbFault{
               DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("isJobActive");
                IsJobActiveRequest isJobActiveRequest = IsJobActiveRequest.Factory.newInstance
();
                isJobActiveRequest.setCmdbContext(cmdbContext);
                isJobActiveRequest.setJobName(jobName);
                IsJobActiveRequestDocument isJobActiveRequestDocumentt =
IsJobActiveRequestDocument.Factory.newInstance();
                isJobActiveRequestDocumentt.setIsJobActiveRequest(isJobActiveRequest);
                IsJobActiveResponseDocument isJobActiveResponseDocument =
serviceStub.isJobActive(isJobActiveRequestDocumentt);
                IsJobActiveResponse isJobActiveResponse =
isJobActiveResponseDocument.getIsJobActiveResponse();
                System.out.println(isJobActiveResponse.toString());
       }
       public static void getDiscoveryJobsNames() throws RemoteException, UcmdbFault{
               DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("getDiscoveryJobsNames");
                GetDiscoveryJobsNamesRequest getDiscoveryJobsNamesRequest =
GetDiscoveryJobsNamesRequest.Factory.newInstance();
                getDiscoveryJobsNamesRequest.setCmdbContext(cmdbContext);
                GetDiscoveryJobsNamesRequestDocument getDiscoveryJobsNamesRequestDocument =
GetDiscoveryJobsNamesRequestDocument.Factory.newInstance();
                getDiscoveryJobsNamesRequestDocument.setGetDiscoveryJobsNamesRequest
(getDiscoveryJobsNamesRequest);
                GetDiscoveryJobsNamesResponseDocument getDiscoveryJobsNamesResponseDocument =
serviceStub.getDiscoveryJobsNames(getDiscoveryJobsNamesRequestDocument);
                GetDiscoveryJobsNamesResponse getDiscoveryJobsNamesResponse =
getDiscoveryJobsNamesResponseDocument.getGetDiscoveryJobsNamesResponse();
```

```
System.out.println(getDiscoveryJobsNamesResponse.toString());
       }
       //
       public static void dispatchAdHocJob(String probeName,String jobName,String
CIID,Long timeout) throws RemoteException, UcmdbFault{
                 DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("dispatchAdHocJob");
               DispatchAdHocJobRequest dispatchAdHocJobRequest =
DispatchAdHocJobRequest.Factory.newInstance();
               dispatchAdHocJobRequest.setCmdbContext(cmdbContext);
               dispatchAdHocJobRequest.setProbeName(probeName);
               dispatchAdHocJobRequest.setJobName(jobName);
               dispatchAdHocJobRequest.setCIID(CIID);
               dispatchAdHocJobRequest.setTimeout(timeout);
               DispatchAdHocJobRequestDocument dispatchAdHocJobRequestDocument
=DispatchAdHocJobRequestDocument.Factory.newInstance();
               dispatchAdHocJobRequestDocument.setDispatchAdHocJobRequest
(dispatchAdHocJobRequest);
               serviceStub.dispatchAdHocJob(dispatchAdHocJobRequestDocument);
       }
    public static DiscoveryServiceStub getService() {
       DiscoveryServiceStub serviceStub=null;
        try {
            URL url = new URL(PROTOCOL, HOST NAME, PORT, FILE);
            serviceStub = new DiscoveryServiceStub(url.toString());
            HttpTransportProperties.Authenticator auth = new
HttpTransportProperties.Authenticator();
            auth.setUsername(USERNAME);
            auth.setPassword(PASSWORD);
            serviceStub._getServiceClient().getOptions()
                    .setProperty(HTTPConstants.AUTHENTICATE, auth);
        } catch (Exception e) {
            e.printStackTrace();
        }
        return serviceStub;
    }
       public static void main (String[] args) throws Exception{
               //activateJob("Range IPs by ICMP");
               //deActivateJob("Range IPs by ICMP");
```

```
//isJobActive("Range IPs by ICMP");
//getDiscoveryJobsNames();
//some error
//dispatchAdHocJob("GDLITVM0136","Range IPs by
ICMP","21c90f8a46b3f7bb9aff055b461476a4",10000L);
}
```

Managing Discovery Job Methods

Managing Trigger Methods

```
import java.net.URL;
import java.rmi.RemoteException;
import org.apache.axis2.transport.http.HTTPConstants;
import org.apache.axis2.transport.http.HttpTransportProperties;
import com.hp.schemas.ucmdb. 1.types.CmdbContext;
import com.hp.schemas.ucmdb. 1.types.StrList;
import com.hp.schemas.ucmdb.discovery._1.params.AddTriggerCIRequest;
import com.hp.schemas.ucmdb.discovery._1.params.AddTriggerCIRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.AddTriggerTQLRequest;
import com.hp.schemas.ucmdb.discovery._1.params.AddTriggerTQLRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.DisableTriggerTQLRequest;
import com.hp.schemas.ucmdb.discovery. 1.params.DisableTriggerTQLRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetJobTriggerTqlsRequest;
import com.hp.schemas.ucmdb.discovery._1.params.GetJobTriggerTqlsRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetJobTriggerTqlsResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.RemoveTriggerCIRequestDocument;
import com.hp.schemas.ucmdb.discovery. 1.params.RemoveTriggerTQLRequest;
import com.hp.schemas.ucmdb.discovery._1.params.RemoveTriggerTQLRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.SetTriggerTQLProbesLimitRequest;
import com.hp.schemas.ucmdb.discovery.
1.params.SetTriggerTQLProbesLimitRequestDocument;
import com.hp.ucmdb.generated.DiscoveryServiceStub;
import com.hp.ucmdb.generated.UcmdbFault;
public class TestTriggerCI {
       static final String HOST_NAME = "<my_hostname>";
    static final int PORT = 8080;
```

```
private static final String PROTOCOL = "http";
    private static final String FILE = "/axis2/services/DiscoveryService";
    private static final String PASSWORD = "admin";
    private static final String USERNAME = "admin";
    public static CmdbContext cmdbContext = CmdbContext.Factory.newInstance();
    public static DiscoveryServiceStub getService() {
       DiscoveryServiceStub serviceStub=null;
        try {
            URL url = new URL(PROTOCOL, HOST NAME, PORT, FILE);
            serviceStub = new DiscoveryServiceStub(url.toString());
            HttpTransportProperties.Authenticator auth = new
HttpTransportProperties.Authenticator();
            auth.setUsername(USERNAME);
            auth.setPassword(PASSWORD);
            serviceStub. getServiceClient().getOptions()
                    .setProperty(HTTPConstants.AUTHENTICATE, auth);
        } catch (Exception e) {
            e.printStackTrace();
        }
        return serviceStub;
    }
       public static void main(String[] args) throws Exception, UcmdbFault{
               //getJobTriggerTqls("Range IPs by ICMP");
               //addTriggerTQL("Range IPs by ICMP", "probe_connected_rum");
               //removeTriggerTQL("Range IPs by ICMP", "probe_connected_rum");
               //StrList probesLimit = StrList.Factory.newInstance();
               //probesLimit.addStrValue("AMCBTEST02");
               //setTriggerTQLProbesLimit("Range IPs by ICMP", "probe_connected_
rum",probesLimit);
               disableTriggerTQL("Range IPs by ICMP", "probe_connected_rum");
               //addTriggerCI();
       public static void addTriggerCI(String jobName,String CIID) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("addTriggerCI");
                AddTriggerCIRequest addTriggerCIRequest =
AddTriggerCIRequest.Factory.newInstance();
                addTriggerCIRequest.setCmdbContext(cmdbContext);
                addTriggerCIRequest.setJobName(jobName);
```

```
AddTriggerCIRequestDocument addTriggerCIRequestDocument =
AddTriggerCIRequestDocument.Factory.newInstance();
                addTriggerCIRequestDocument.setAddTriggerCIRequest(addTriggerCIRequest);
                serviceStub.addTriggerCI(addTriggerCIRequestDocument);
       }
       public static void addTriggerTQL(String jobName,String TQLName) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("addTriggerTQL");
                AddTriggerTQLRequest addTriggerTQLRequest =
AddTriggerTQLRequest.Factory.newInstance();
                addTriggerTQLRequest.setCmdbContext(cmdbContext);
                addTriggerTQLRequest.setJobName(jobName);
                addTriggerTQLRequest.setTqlName(TQLName);
                AddTriggerTQLRequestDocument addTriggerTQLRequestDocument =
AddTriggerTQLRequestDocument.Factory.newInstance();
                addTriggerTQLRequestDocument.setAddTriggerTQLRequest(addTriggerTQLRequest);
                serviceStub.addTriggerTQL(addTriggerTQLRequestDocument);
       }
       public static void disableTriggerTQL(String jobName,String TQLName) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("DisableTriggerTQL");
                DisableTriggerTQLRequest disableTriggerTQLRequest =
DisableTriggerTQLRequest.Factory.newInstance();
                disableTriggerTQLRequest.setCmdbContext(cmdbContext);
                disableTriggerTQLRequest.setJobName(jobName);
                disableTriggerTQLRequest.setTqlName(TQLName);
                DisableTriggerTQLRequestDocument disableTriggerTQLRequestDocument =
DisableTriggerTQLRequestDocument.Factory.newInstance();
                {\tt disableTriggerTQLRequestDocument.setDisableTriggerTQLRequest}
(disableTriggerTQLRequest);
                serviceStub.disableTriggerTQL(disableTriggerTQLRequestDocument);
       }
       public static void removeTriggerTQL(String jobName,String TQLName) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("removeTriggerTQL");
               RemoveTriggerTQLRequest removeTriggerTQLRequest
=RemoveTriggerTQLRequest.Factory.newInstance();
               removeTriggerTQLRequest.setCmdbContext(cmdbContext);
               removeTriggerTQLRequest.setJobName(jobName);
               removeTriggerTQLRequest.setTqlName(TQLName);
               RemoveTriggerTQLRequestDocument removeTriggerTQLRequestDocument
=RemoveTriggerTQLRequestDocument.Factory.newInstance();
               remove Trigger TQL Request Document. set Remove Trigger TQL Request\\
```

```
(removeTriggerTQLRequest);
               serviceStub.removeTriggerTQL(removeTriggerTQLRequestDocument);
       }
       public static void getJobTriggerTqls(String jobName) throws RemoteException,
UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("getJobTriggerTqls");
               GetJobTriggerTqlsRequest getJobTriggerTqlsRequest
=GetJobTriggerTqlsRequest.Factory.newInstance();
               getJobTriggerTqlsRequest.setCmdbContext(cmdbContext);
               getJobTriggerTqlsRequest.setJobName(jobName);
               GetJobTriggerTqlsRequestDocument getJobTriggerTqlsRequestDocument
=GetJobTriggerTqlsRequestDocument.Factory.newInstance();
               getJobTriggerTqlsRequestDocument.setGetJobTriggerTqlsRequest
(getJobTriggerTqlsRequest);
               GetJobTriggerTqlsResponseDocument getJobTriggerTqlsResponseDocument =
serviceStub.getJobTriggerTqls(getJobTriggerTqlsRequestDocument);
               System.out.println(getJobTriggerTqlsResponseDocument.getGetJobTriggerTqlsResponse
().toString());
       }
       public static void removeTriggerCI(String jobName,String CIID) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("removeTriggerCI");
                AddTriggerCIRequest addTriggerCIRequest =
AddTriggerCIRequest.Factory.newInstance();
                addTriggerCIRequest.setCmdbContext(cmdbContext);
                addTriggerCIRequest.setJobName(jobName);
               RemoveTriggerCIRequestDocument removeTriggerCIRequestDocument
=RemoveTriggerCIRequestDocument.Factory.newInstance();
               removeTriggerCIRequestDocument.setRemoveTriggerCIRequest(addTriggerCIRequest);
               serviceStub.removeTriggerCI(removeTriggerCIRequestDocument);
       }
       public static void setTriggerTQLProbesLimit(String jobName,String tqlName,StrList
probesLimit) throws RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("setTriggerTQLProbesLimit");
                SetTriggerTQLProbesLimitRequest setTriggerTQLProbesLimitRequest =
SetTriggerTQLProbesLimitRequest.Factory.newInstance();
                setTriggerTQLProbesLimitRequest.setCmdbContext(cmdbContext);
                setTriggerTQLProbesLimitRequest.setJobName(jobName);
                setTriggerTQLProbesLimitRequest.setTqlName(tqlName);
```

Domain and Probe Data Methods

```
import java.net.URL;
import java.rmi.RemoteException;
import org.apache.axis2.transport.http.HTTPConstants;
import org.apache.axis2.transport.http.HttpTransportProperties;
import com.hp.schemas.ucmdb. 1.types.CmdbContext;
import com.hp.schemas.ucmdb.discovery._1.params.GetDomainTypeRequest;
import com.hp.schemas.ucmdb.discovery. 1.params.GetDomainTypeRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetDomainTypeResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetDomainsNamesRequest;
import com.hp.schemas.ucmdb.discovery._1.params.GetDomainsNamesRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetDomainsNamesResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetProbeIPsRequest;
import com.hp.schemas.ucmdb.discovery._1.params.GetProbeIPsRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetProbeIPsResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetProbeScopeRequest;
import com.hp.schemas.ucmdb.discovery._1.params.GetProbeScopeRequestDocument;
import com.hp.schemas.ucmdb.discovery. 1.params.GetProbeScopeResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetProbesNamesRequest;
import com.hp.schemas.ucmdb.discovery. 1.params.GetProbesNamesRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetProbesNamesResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.IsProbeConnectedRequest;
import com.hp.schemas.ucmdb.discovery. 1.params.IsProbeConnectedRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.IsProbeConnectedResponceDocument;
import com.hp.schemas.ucmdb.discovery. 1.params.UpdateProbeScopeRequest;
import com.hp.schemas.ucmdb.discovery._1.params.UpdateProbeScopeRequestDocument;
import com.hp.schemas.ucmdb.discovery. 1.types.IP;
import com.hp.schemas.ucmdb.discovery._1.types.IPRange;
import com.hp.schemas.ucmdb.discovery._1.types.Scope;
import com.hp.schemas.ucmdb.discovery. 1.types.Scope.Include;
import com.hp.ucmdb.generated.DiscoveryServiceStub;
import com.hp.ucmdb.generated.UcmdbFault;
```

```
public class TestDomain {
       static final String HOST NAME = "<my hostname>";
    static final int PORT = 8080;
    private static final String PROTOCOL = "http";
    private static final String FILE = "/axis2/services/DiscoveryService";
    private static final String PASSWORD = "admin";
    private static final String USERNAME = "admin";
    public static CmdbContext cmdbContext = CmdbContext.Factory.newInstance();
    public static DiscoveryServiceStub getService() {
        DiscoveryServiceStub serviceStub=null;
        try {
            URL url = new URL(PROTOCOL, HOST_NAME, PORT, FILE);
            serviceStub = new DiscoveryServiceStub(url.toString());
            HttpTransportProperties.Authenticator auth = new
HttpTransportProperties.Authenticator();
            auth.setUsername(USERNAME);
            auth.setPassword(PASSWORD);
            serviceStub._getServiceClient().getOptions()
                    .setProperty(HTTPConstants.AUTHENTICATE, auth);
        } catch (Exception e) {
            e.printStackTrace();
        }
        return serviceStub;
    }
       public static void getDomainsNames() throws RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("GetDomainsNames");
                GetDomainsNamesRequest getDomainsNamesRequest =
GetDomainsNamesRequest.Factory.newInstance();
                getDomainsNamesRequest.setCmdbContext(cmdbContext);
                GetDomainsNamesRequestDocument getDomainsNamesRequestDocument =
GetDomainsNamesRequestDocument.Factory.newInstance();
                getDomainsNamesRequestDocument.setGetDomainsNamesRequest
(getDomainsNamesRequest);
                GetDomainsNamesResponseDocument getDomainsNamesResponseDocument =
serviceStub.getDomainsNames(getDomainsNamesRequestDocument);
                System.out.println(getDomainsNamesResponseDocument.getGetDomainsNamesResponse
().toString());
```

```
}
       public static void getProbesNames(String domainName) throws RemoteException,
UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("GetProbesNames");
                GetProbesNamesRequest getProbesNamesRequest =
GetProbesNamesRequest.Factory.newInstance();
                getProbesNamesRequest.setCmdbContext(cmdbContext);
                getProbesNamesRequest.setDomainName(domainName);
                GetProbesNamesRequestDocument getProbesNamesRequestDocument =
GetProbesNamesRequestDocument.Factory.newInstance();
                getProbesNamesRequestDocument.setGetProbesNamesRequest(getProbesNamesRequest);
                GetProbesNamesResponseDocument getProbesNamesResponseDocument =
serviceStub.getProbesNames(getProbesNamesRequestDocument);
                System.out.println(getProbesNamesResponseDocument.getGetProbesNamesResponse
().toString());
       public static void getProbeScope(String domainName,String probeName) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("GetProbeScope");
                GetProbeScopeRequest getProbeScopeRequest =
GetProbeScopeRequest.Factory.newInstance();
                getProbeScopeRequest.setCmdbContext(cmdbContext);
                getProbeScopeRequest.setDomainName(domainName);
                getProbeScopeRequest.setProbeName(probeName);
                GetProbeScopeRequestDocument getProbeScopeRequestDocument =
GetProbeScopeRequestDocument.Factory.newInstance();
                getProbeScopeRequestDocument.setGetProbeScopeRequest(getProbeScopeRequest);
                GetProbeScopeResponseDocument getProbeScopeResponseDocument =
serviceStub.getProbeScope(getProbeScopeRequestDocument);
                System.out.println(getProbeScopeResponseDocument.getGetProbeScopeResponse
().toString());
       public static void getProbeIPs(String domainName,String probeName) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("GetProbeIPs");
                GetProbeIPsRequest getProbeIPsRequest = GetProbeIPsRequest.Factory.newInstance
();
                getProbeIPsRequest.setCmdbContext(cmdbContext);
                getProbeIPsRequest.setDomainName(domainName);
                getProbeIPsRequest.setProbeName(probeName);
                GetProbeIPsRequestDocument getProbeIPsRequestDocument =
GetProbeIPsRequestDocument.Factory.newInstance();
```

```
getProbeIPsRequestDocument.setGetProbeIPsRequest(getProbeIPsRequest);
                GetProbeIPsResponseDocument getProbeIPsResponseDocument =
serviceStub.getProbeIPs(getProbeIPsRequestDocument);
                System.out.println(getProbeIPsResponseDocument.getGetProbeIPsResponse().toString
());
       public static void getDomainType(String domainName) throws RemoteException,
UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("GetProbeScope");
                GetDomainTypeRequest getDomainTypeRequest =
GetDomainTypeRequest.Factory.newInstance();
                getDomainTypeRequest.setCmdbContext(cmdbContext);
                getDomainTypeRequest.setDomainName(domainName);
                GetDomainTypeRequestDocument getDomainTypeRequestDocument =
GetDomainTypeRequestDocument.Factory.newInstance();
                getDomainTypeRequestDocument.setGetDomainTypeRequest(getDomainTypeRequest);
                GetDomainTypeResponseDocument getDomainTypeResponseDocument =
serviceStub.getDomainType(getDomainTypeRequestDocument);
                System.out.println(getDomainTypeResponseDocument.getGetDomainTypeResponse
().toString());
       }
       public static void isProbeConnected(String domainName, String probeName) throws
RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("isProbeConnected");
                IsProbeConnectedRequest isProbeConnectedRequest =
IsProbeConnectedRequest.Factory.newInstance();
                isProbeConnectedRequest.setCmdbContext(cmdbContext);
                isProbeConnectedRequest.setDomainName(domainName);
                isProbeConnectedRequest.setProbeName(probeName);
                IsProbeConnectedRequestDocument isProbeConnectedRequestDocument =
IsProbeConnectedRequestDocument.Factory.newInstance();
                is Probe Connected Request Document. set Is Probe Connected Request \\
(isProbeConnectedRequest);
                IsProbeConnectedResponceDocument IsProbeConnectedResponceDocument =
serviceStub.isProbeConnected(isProbeConnectedRequestDocument);
                System.out.println(IsProbeConnectedResponceDocument.getIsProbeConnectedResponce
());
       }
       public static void updateProbeScope(String domainName,String probeName,Scope
newScope) throws RemoteException, UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("UpdateProbeScope");
                UpdateProbeScopeRequest updateProbeScopeRequest =
```

```
UpdateProbeScopeRequest.Factory.newInstance();
                updateProbeScopeRequest.setCmdbContext(cmdbContext);
                updateProbeScopeRequest.setDomainName(domainName);
                updateProbeScopeRequest.setProbeName(probeName);
                updateProbeScopeRequest.setNewScope(newScope);
                UpdateProbeScopeRequestDocument updateProbeScopeRequestDocument =
UpdateProbeScopeRequestDocument.Factory.newInstance();
                update Probe Scope Request Document.set Update Probe Scope Request\\
(updateProbeScopeRequest);
                serviceStub.updateProbeScope(updateProbeScopeRequestDocument);
       }
       public static void main(String[] args) throws Exception{
               //getDomainsNames();
               //getProbesNames("DefaultDomain");
               //getProbeScope("DefaultDomain", "AMCBTEST02");
               //isProbeConnected("DefaultDomain", "AMCBTEST02");
               //getProbeIPs("DefaultDomain","AMCBTEST02");
               //getDomainType("DefaultDomain");
       }
}
```

Credentials Data Methods

```
import java.net.URL;
import java.rmi.RemoteException;

import org.apache.axis2.transport.http.HTTPConstants;
import org.apache.axis2.transport.http.HttpTransportProperties;

import com.hp.schemas.ucmdb._1.types.BytesProp;
import com.hp.schemas.ucmdb._1.types.BytesProps;
import com.hp.schemas.ucmdb._1.types.CIProperties;
import com.hp.schemas.ucmdb._1.types.CIProperties;
import com.hp.schemas.ucmdb._1.types.StrProp;
import com.hp.schemas.ucmdb._1.types.StrProps;
import com.hp.schemas.ucmdb.discovery._1.params.AddCredentialsEntryRequest;
import com.hp.schemas.ucmdb.discovery._1.params.AddCredentialsEntryRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.AddCredentialsEntryResponse;
import com.hp.schemas.ucmdb.discovery._
1.params.AddCredentialsEntryResponseDocument;
```

```
import com.hp.schemas.ucmdb.discovery. 1.params.GetCredentialsEntriesIDsRequest;
import com.hp.schemas.ucmdb.discovery._
1.params.GetCredentialsEntriesIDsRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetCredentialsEntriesIDsResponse;
import com.hp.schemas.ucmdb.discovery._
1.params.GetCredentialsEntriesIDsResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.GetCredentialsEntryRequest;
import com.hp.schemas.ucmdb.discovery._1.params.RemoveCredentialsEntryRequest;
import com.hp.schemas.ucmdb.discovery.
1.params.RemoveCredentialsEntryRequestDocument;
import com.hp.schemas.ucmdb.discovery. 1.params.UpdateCredentialsEntryRequest;
import com.hp.schemas.ucmdb.discovery._
1.params.UpdateCredentialsEntryRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.UpdateProbeScopeRequest;
import com.hp.schemas.ucmdb.discovery._1.params.UpdateProbeScopeRequestDocument;
import com.hp.ucmdb.generated.DiscoveryServiceStub;
import com.hp.ucmdb.generated.UcmdbFault;
public class TestCredentials{
       static final String HOST_NAME = "<my_hostname>";
    static final int PORT = 8080;
    private static final String PROTOCOL = "http";
    private static final String FILE = "/axis2/services/DiscoveryService";
    private static final String PASSWORD = "admin";
    private static final String USERNAME = "admin";
    public static CmdbContext cmdbContext = CmdbContext.Factory.newInstance();
    public static DiscoveryServiceStub getService() {
        DiscoveryServiceStub serviceStub=null;
        try {
            URL url = new URL(PROTOCOL, HOST NAME, PORT, FILE);
            serviceStub = new DiscoveryServiceStub(url.toString());
            HttpTransportProperties.Authenticator auth = new
HttpTransportProperties.Authenticator();
            auth.setUsername(USERNAME);
            auth.setPassword(PASSWORD);
            serviceStub. getServiceClient().getOptions()
                    .setProperty(HTTPConstants.AUTHENTICATE, auth);
        } catch (Exception e) {
            e.printStackTrace();
        }
        return serviceStub;
```

```
}
       public static void addCreds(String user, String userlabel, String domain, String
ipaddress,String protocol, String password) {
        DiscoveryServiceStub serviceStub = getService();
        cmdbContext.setCallerApplication("addCred");
        CIProperties newCredsProperties = CIProperties.Factory.newInstance();
        String [] args = {user,userlabel,domain,ipaddress};
        newCredsProperties.setStrProps(strAddProps(args));
        newCredsProperties.setBytesProps(addByteProp(password));
        AddCredentialsEntryRequest addReq = AddCredentialsEntryRequest.Factory
                .newInstance();
        AddCredentialsEntryRequestDocument addReqDoc =
AddCredentialsEntryRequestDocument.Factory
                .newInstance();
        addReq.setCmdbContext(cmdbContext);
        addReq.setProtocolName(protocol);
        addReq.setDomainName("DefaultDomain");
        addReq.setCredentialsEntryParameters(newCredsProperties);
        addReqDoc.setAddCredentialsEntryRequest(addReq);
       try {
            AddCredentialsEntryResponseDocument addResDoc =
serviceStub.addCredentialsEntry(addReqDoc);
            AddCredentialsEntryResponse addRes =
addResDoc.getAddCredentialsEntryResponse();
            System.out.println(addRes.getCredentialsEntryID().toString());
        } catch (RemoteException e) {
            e.printStackTrace();
        } catch (Exception e) {
            e.printStackTrace();
        }
   }
    public static void updateCreds(String user, String userlabel, String domain,
String ipaddress, String protocol, String password,
```

```
String credid) {
        DiscoveryServiceStub serviceStub = getService();
        //set cmdbcontext
        cmdbContext.setCallerApplication("addCred");
        // create CI properties
        CIProperties newCredsProperties = CIProperties.Factory.newInstance();
        String [] args = {user,userlabel,domain,ipaddress,credid};
        newCredsProperties.setBytesProps(addByteProp(password));
        newCredsProperties.setStrProps(strAddProps(args));
        UpdateCredentialsEntryRequestDocument upReqDoc =
UpdateCredentialsEntryRequestDocument.Factory
                .newInstance();
        UpdateCredentialsEntryRequest upReq = UpdateCredentialsEntryRequest.Factory
                .newInstance();
        upReq.setDomainName("DefaultDomain");
        upReq.setProtocolName("ntadminprotocol");
        upReq.setCmdbContext(cmdbContext);
        upReq.setCredentialsEntryID(credid);
        upReq.setCredentialsEntryParameters(newCredsProperties);
        upReqDoc.setUpdateCredentialsEntryRequest(upReq);
        try {
            serviceStub.updateCredentialsEntry(upReqDoc);
        } catch (RemoteException e) {
            e.printStackTrace();
        } catch (Exception e) {
            e.printStackTrace();
        }
    }
    public static StrProps strAddProps(String args[]) {
        StrProps sP = StrProps.Factory.newInstance();
        if (args.length ==5){
            StrProp proAddress = sP.addNewStrProp();
```

```
proAddress.setName("cm credential id");
            proAddress.setValue(args[4]);
        }
        StrProp username = sP.addNewStrProp();
        username.setName("protocol username");
        username.setValue(args[0]);
        StrProp userLabel = sP.addNewStrProp();
        userLabel.setName("user_label");
        userLabel.setValue(args[1]);
        StrProp proAddress = sP.addNewStrProp();
        proAddress.setName("protocol_netaddress");
        proAddress.setValue(args[3]);
        StrProp proDomain = sP.addNewStrProp();
        proDomain.setName("ntadminprotocol_ntdomain");
        proDomain.setValue(args[2]);
        return sP;
   }
    public static void getCreds(String user, String userlabel, String domain,
String ipaddress,String protocol, String password) {
        DiscoveryServiceStub serviceStub = getService();
        cmdbContext.setCallerApplication("getCred");
        CIProperties newCredsProperties = CIProperties.Factory.newInstance();
        GetCredentialsEntryRequest addReq = GetCredentialsEntryRequest.Factory
                .newInstance();
        GetCredentialsEntriesIDsRequest getIDReq =
GetCredentialsEntriesIDsRequest.Factory.newInstance();
        GetCredentialsEntriesIDsRequestDocument getIDReqDoc =
GetCredentialsEntriesIDsRequestDocument.Factory.newInstance();
        addReq.setCmdbContext(cmdbContext);
        getIDReq.setCmdbContext(cmdbContext);
        addReq.setProtocolName(protocol);
        getIDReq.setProtocolName(protocol);
        addReq.setDomainName("DefaultDomain");
```

```
getIDReq.setDomainName("DefaultDomain");
        getIDReqDoc.setGetCredentialsEntriesIDsRequest(getIDReq);
        try {
            GetCredentialsEntriesIDsResponseDocument
getCredentialsEntriesIDsResponseDocument = serviceStub.getCredentialsEntriesIDs
(getIDReqDoc);
            GetCredentialsEntriesIDsResponse getCredentialsEntriesIDsResponse =
getCredentialsEntriesIDsResponseDocument.getGetCredentialsEntriesIDsResponse();
            for (String id :
getCredentialsEntriesIDsResponse.getCredentialsEntryIDs().getStrValueArray()) {
                System.out.println(id);
            }
        } catch (RemoteException e) {
            e.printStackTrace();
        } catch (Exception e) {
            e.printStackTrace();
        }
    }
    public static BytesProps addByteProp(String password){
        byte[] baytdizi = password.getBytes();
        BytesProps bProps = BytesProps.Factory.newInstance();
        BytesProp bprop =bProps.addNewBytesProp();
        bprop.setName("protocol password");
        bprop.setValue(baytdizi);
        return bProps;
   }
    public static void removeCredentialsEntry(String domainName,String
protocolName,String credentialsEntryID) throws RemoteException, UcmdbFault {
        DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("RemoveCredentialsEntry");
                RemoveCredentialsEntryRequest removeCredentialsEntryRequest =
RemoveCredentialsEntryRequest.Factory.newInstance();
                removeCredentialsEntryRequest.setCmdbContext(cmdbContext);
                removeCredentialsEntryRequest.setDomainName(domainName);
                removeCredentialsEntryRequest.setProtocolName(protocolName);
```

```
removeCredentialsEntryRequest.setCredentialsEntryID(credentialsEntryID);
                                                       RemoveCredentialsEntryRequestDocument removeCredentialsEntryRequestDocument =
RemoveCredentialsEntryRequestDocument.Factory.newInstance();
                                                       remove Credentials Entry Request Document. set Remove Credentials Entry Request Properties of the Remove Credentials and Properties of the Remove Credentials Entry Request Properties of the Remove Credentials Entry Remove Credential Entry R
(removeCredentialsEntryRequest);
                                                       serviceStub.removeCredentialsEntry(removeCredentialsEntryRequestDocument);
             public static void main(String[] args) throws Exception {
                            getCreds
("melo", "userlabelll", "DefaultDomain", "11.11.11.11", "ntadminprotocol", "passw");
                     //addCreds
("melo", "userlabelll", "DefaultDomain", "11.11.11.11", "ntadminprotocol", "passw");
                           //100 1 CMS
                        //updateCreds( "meli", "newlabel", "DefaultDomain", "22.22.22.22",
"ntadminprotocol", "passss","32_1_CMS");
                            removeCredentialsEntry("DefaultDomain", "ntadminprotocol", "");
             }
}
```

Data Refresh Methods

```
import java.net.URL;
import java.rmi.RemoteException;
import org.apache.axis2.transport.http.HTTPConstants;
import org.apache.axis2.transport.http.HttpTransportProperties;
import com.hp.schemas.ucmdb. 1.types.CmdbContext;
import com.hp.schemas.ucmdb. 1.types.StrList;
import com.hp.schemas.ucmdb.discovery. 1.params.CheckDiscoveryProgressRequest;
import com.hp.schemas.ucmdb.discovery.
1.params.CheckDiscoveryProgressRequestDocument;
import com.hp.schemas.ucmdb.discovery.
1.params.CheckDiscoveryProgressResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.CheckViewDiscoveryProgressRequest;
import com.hp.schemas.ucmdb.discovery._
1.params.CheckViewDiscoveryProgressRequestDocument;
import com.hp.schemas.ucmdb.discovery._
1.params.CheckViewDiscoveryProgressResponseDocument;
import com.hp.schemas.ucmdb.discovery. 1.params.RediscoverCIsRequest;
import com.hp.schemas.ucmdb.discovery._1.params.RediscoverCIsRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.RediscoverCIsResponseDocument;
import com.hp.schemas.ucmdb.discovery._1.params.RediscoverViewCIsRequest;
```

```
import com.hp.schemas.ucmdb.discovery. 1.params.RediscoverViewCIsRequestDocument;
import com.hp.schemas.ucmdb.discovery._1.params.RediscoverViewCIsResponseDocument;
import com.hp.ucmdb.generated.DiscoveryServiceStub;
import com.hp.ucmdb.generated.UcmdbFault;
public class TestDataRefresh {
       static final String HOST_NAME = "<my_hostname>";
    static final int PORT = 8080;
    private static final String PROTOCOL = "http";
    private static final String FILE = "/axis2/services/DiscoveryService";
    private static final String PASSWORD = "admin";
    private static final String USERNAME = "admin";
    public static CmdbContext cmdbContext = CmdbContext.Factory.newInstance();
    public static DiscoveryServiceStub getService() {
        DiscoveryServiceStub serviceStub=null;
        try {
            URL url = new URL(PROTOCOL, HOST_NAME, PORT, FILE);
            serviceStub = new DiscoveryServiceStub(url.toString());
            HttpTransportProperties.Authenticator auth = new
HttpTransportProperties.Authenticator();
            auth.setUsername(USERNAME);
            auth.setPassword(PASSWORD);
            serviceStub. getServiceClient().getOptions()
                    .setProperty(HTTPConstants.AUTHENTICATE, auth);
        } catch (Exception e) {
            e.printStackTrace();
        }
        return serviceStub;
    }
       public static void rediscoverCIs(StrList cmdbIDs) throws RemoteException,
UcmdbFault{
                DiscoveryServiceStub serviceStub = getService();
                cmdbContext.setCallerApplication("RediscoverCIs");
                RediscoverCIsRequest rediscoverCIsRequest =
RediscoverCIsRequest.Factory.newInstance();
                rediscoverCIsRequest.setCmdbContext(cmdbContext);
                rediscoverCIsRequest.setCmdbIDs(cmdbIDs);
                RediscoverCIsRequestDocument rediscoverCIsRequestDocument =
RediscoverCIsRequestDocument.Factory.newInstance();
                rediscoverCIsRequestDocument.setRediscoverCIsRequest(rediscoverCIsRequest);
```

```
RediscoverCIsResponseDocument rediscoverCIsResponseDocument =
serviceStub.rediscoverCIs(rediscoverCIsRequestDocument);
                              System.out.println(rediscoverCIsResponseDocument.getRediscoverCIsResponse
().toString());
             }
             public static void rediscoverViewCIs(String viewName) throws RemoteException,
UcmdbFault{
                              DiscoveryServiceStub serviceStub = getService();
                               cmdbContext.setCallerApplication("rediscoverViewCIs");
                              RediscoverViewCIsRequest rediscoverViewCIsRequest =
RediscoverViewCIsRequest.Factory.newInstance();
                              rediscoverViewCIsRequest.setCmdbContext(cmdbContext);
                              rediscoverViewCIsRequest.setViewName(viewName);
                              RediscoverViewCIsRequestDocument rediscoverViewCIsRequestDocument =
RediscoverViewCIsRequestDocument.Factory.newInstance();
                              rediscoverViewCIsRequestDocument.setRediscoverViewCIsRequest
(rediscoverViewCIsRequest);
                              RediscoverViewCIsResponseDocument rediscoverViewCIsResponseDocument =
serviceStub.rediscoverViewCIs(rediscoverViewCIsRequestDocument);
                              System.out.println
(rediscoverViewCIsResponseDocument.getRediscoverViewCIsResponse().toString());
             }
             public static void checkDiscoveryProgress(StrList cmdbIDs) throws RemoteException,
UcmdbFault{
                              DiscoveryServiceStub serviceStub = getService();
                              cmdbContext.setCallerApplication("RediscoverCIs");
                              CheckDiscoveryProgressRequest checkDiscoveryProgressRequest =
CheckDiscoveryProgressRequest.Factory.newInstance();
                              checkDiscoveryProgressRequest.setCmdbContext(cmdbContext);
                              checkDiscoveryProgressRequest.setCmdbIDs(cmdbIDs);
                              CheckDiscoveryProgressRequestDocument checkDiscoveryProgressRequestDocument =
CheckDiscoveryProgressRequestDocument.Factory.newInstance();
                              check Discovery Progress Request Document.set Document.s
(checkDiscoveryProgressRequest);
                              CheckDiscoveryProgressResponseDocument checkDiscoveryProgressResponseDocument =
serviceStub.checkDiscoveryProgress(checkDiscoveryProgressRequestDocument);
                              System.out.println
(checkDiscoveryProgressResponseDocument.getCheckDiscoveryProgressResponse
().toString());
             public static void checkViewDiscoveryProgresss(String viewName) throws
RemoteException, UcmdbFault{
                              DiscoveryServiceStub serviceStub = getService();
                              cmdbContext.setCallerApplication("RediscoverCIs");
```

```
CheckViewDiscoveryProgressRequest
                                                    checkViewDiscoveryProgressRequest =
CheckViewDiscoveryProgressRequest.Factory.newInstance();
                checkViewDiscoveryProgressRequest.setCmdbContext(cmdbContext);
                checkViewDiscoveryProgressRequest.setViewName(viewName);
                CheckViewDiscoveryProgressRequestDocument
checkViewDiscoveryProgressRequestDocument =
CheckViewDiscoveryProgressRequestDocument.Factory.newInstance();
                check View Discovery Progress Request Document. set Check View Discovery Progress Request Document. \\
(checkViewDiscoveryProgressRequest);
                CheckViewDiscoveryProgressResponseDocument
checkViewDiscoveryProgressResponseDocument =
serviceStub.checkViewDiscoveryProgress(checkViewDiscoveryProgressRequestDocument);
                System.out.println
(checkViewDiscoveryProgressResponseDocument.getCheckViewDiscoveryProgressResponse
().toString());
       }
       public static void main(String[] args) throws RemoteException, Exception{
               StrList cmdbIDs = StrList.Factory.newInstance();
               cmdbIDs.addStrValue("");
               rediscoverCIs(cmdbIDs);
       }
}
```

Send documentation feedback

If you have comments about this document, you can contact the documentation team by email. If an email client is configured on this system, click the link above and an email window opens with the following information in the subject line:

Feedback on Developer Reference Guide (Universal CMDB 10.31)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to cms-doc@hpe.com.

We appreciate your feedback!