



HPE Operations Bridge Reporter

Software Version: 10.10

Secure Deployment Guide

Document Release Date: January 2017
Software Release Date: January 2017


Hewlett Packard
Enterprise

Legal Notices

Warranty

The only warranties for Hewlett Packard Enterprise products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Hewlett Packard Enterprise shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from Hewlett Packard Enterprise required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notice

© 2015 - 2017 Hewlett Packard Enterprise Development LP

Trademark Notices

Adobe® is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

Documentation Updates

To check for recent updates or to verify that you are using the most recent edition of a document, go to: <https://softwaresupport.hpe.com/>.

This site requires that you register for an HP Passport and to sign in. To register for an HP Passport ID, click **Register** on the HPE Software Support site or click **Create an Account** on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HPE sales representative for details.

Support

Visit the HPE Software Support site at: <https://softwaresupport.hpe.com/>.

Most of the support areas require that you register as an HP Passport user and to sign in. Many also require a support contract. To register for an HP Passport ID, click **Register** on the HPE Support site or click **Create an Account** on the HP Passport login page.

To find more information about access levels, go to: <https://softwaresupport.hpe.com/web/softwaresupport/access-levels>.

HPE Software Solutions Now accesses the HPSW Solution and Integration Portal website. This site enables you to explore HPE Product Solutions to meet your business needs, includes a full list of Integrations between HPE Products, as well as a listing of ITIL Processes. The URL for this website is <https://softwaresupport.hpe.com/km/KM01702731>.

Contents

HPE Operations Bridge Reporter Security Features	6
Security Updates Since the Previous Versions	6
Related Documents	7
Security Overview	7
Security Concepts	7
Common Security Concepts	8
HPE OBR Terminology	8
Secure Implementation and Deployment	10
Default Security Settings	10
HPE OBR Security Hardening	10
Physical Security	11
HPE OBR in FIPS mode	11
Secure Installation Guidelines	13
Supported Operation Systems	13
Operating System Hardening Recommendations	13
Installation Permissions	13
Tomcat Hardening	14
Administration Interface Security	15
Accessing the Administration Interface	15
Securing the Administration Interface	15
User Management and Authentication	16
Authentication Model	16
Types of Users	16
Authentication, Administration and Configuration	17
User Authentication	18
Database Authentication	18
Authorization	19
Authorization Model	19
Authorization Administration	19
Backup	21
Encryption	22

Encryption Model	22
Encryption Administration	22
Digital Certificates	22
Log and Trace	24
Hardening the HPE Operation Bridge Reporter	25
Security Hardening Recommendations	25
Configuring the TLS Protocol	25
Clickjacking Protection	26
Send documentation feedback	27

HPE Operations Bridge Reporter Security Features

This guide helps you to deploy and manage HPE Operations Bridge Reporter (OBR) in a secure manner. The purpose of this guide is to help you make well informed decisions about various capabilities and features that HPE OBR provides to meet modern enterprise security needs. Security requirements for the enterprise are constantly evolving and this guide provides you with best practices to meet those stringent requirements.

Security Updates Since the Previous Versions

The following security updates were made between **HP SHR 9.x** and **HPE OBR 10.00**:

- Changing password during first time log on is made mandatory.
- No default passwords are provided during post install configuration for Administration Console, SAP BusinessObjects, postgresSQL database, or Vertica database users.
- Secure communication (HTTPS) is enabled between browser and Administration Console/SAP BusinessObjects application.
- Self-signed certificate is deployed on the server. You must configure CA signed certificate by following the instructions. For information on instructions, see *HPE Operations Bridge Reporter Interactive Installation Guide*.

The following security updates were made between **HPE OBR 10.00** and **10.01**:

- Configure HPE OBR to enable usage of FIPS certified libraries and FIPS compliant algorithms for encryption, signing and hashing. For information to enable FIPS, see *Configuring FIPS for HPE OBR* in *HPE Operations Bridge Reporter Configuration Guide*.
- The Administration console allows you to configure logon banner. The text that appears on logon banner is configurable. When you log on to Administration console or SAP BusinessObjects BI Launch Pad or CMC, the first screen warns you against unauthorized entry. For information to configure logon banner, see *Configuring Logon Banner for HPE OBR* in *HPE Operations Bridge*

Reporter Configuration Guide.

- Secure Communication - You can configure JDBC or ODBC connections over TLS for the following:
 - Vertica and HPE OBR server/SAP BusinessObjects
 - OBR collector and BSM/OMi Oracle database
 - OBR collector and BSM/OMi RTSM

Using the Administration Console, you can enable TLS for HP OM and BSM/OMi to connect with Oracle database using ODBC or JDBC. For more information, see *Data Source Configuration* in *HPE Operations Bridge Reporter Configuration Guide*.

Using the Administration Console, you can enable TLS for Vertica database. For more information, see *Enabling and Disabling TLS for Vertica* in *HPE Operations Bridge Reporter Configuration Guide*.

Related Documents

For more information about the security hardening of HPE OBR, see the following documents:

- HPE Operations Bridge Reporter Interactive Installation Guide
- HPE Operations Bridge Reporter Configuration Guide
- HPE Operations Bridge Reporter Administration Guide

Security Overview

This document provides an overview of the security models and recommendations for a secure implementation of HPE OBR. This includes subjects such as authentication, authorization, encryption, and more. Where relevant, there are references to other HPE OBR documents, which describe how to complete security-related tasks.

Security Concepts

This section provides information on common security concepts and terminologies.

Common Security Concepts

System Security

System Security is a process by which computer-based equipment, information, and services are protected from unintended or unauthorized access, change, or damage.

Least Privilege

The practice of limiting access to the minimal level that will allow normal functioning. This means giving a user account only those privileges that are essential to that user's work.

Authentication

The process of identifying an individual, usually based on a user name and password, or certificate.

Authorization

Permission to access system objects, based on an individual's identity.

Encryption

A way to enhance the security of a message or file by scrambling the contents so that it can be read only by someone who has the right key to decode it. For example, the TLS protocol encrypts the communication data.

HPE OBR Terminology

Term	Description
Permission	A permission is a predefined authorization to perform a task. A set of permissions can be assigned to roles.
Role	A role is a collection of permissions.
User	A user is an object associated with a person (or application identity) representing the person and defining their authorization. Roles are assigned to users, to define the actions they are authorized to perform.

It is possible to configure different kinds of users:

- **Internal users** - Log on to Administration Console using the user name and password that was set up locally.
- **LDAP users** - Define the user in the LDAP server and map LDAP groups to HPE OBR roles.

Secure Implementation and Deployment

This section describes default and physical security settings.

Default Security Settings

- **TLS Encryption** – The default SSL protocols for HTTPS communication with the HPE OBR are TLSv1.0, TLSv1.1 and TLSv1.2. It is recommended to work with the latest version.
- **HTTPS enabled** - Secure communication (HTTPS) is enabled between browser and Administration Console/SAP BusinessObjects application.
- **Certificate Authority (CA) signed certificate** - Self-signed certificate is deployed on the server. You must configure CA signed certificate by following the instructions. For information on instructions, see *HPE Operations Bridge Reporter Interactive Installation Guide*.

Note: The certificates shipped with HPE OBR are valid for three months.

- **Logon Banner** – You can enable a logon banner screen that appears and must be acknowledged before you can access the Administration Console, SAP BusinessObjects or CMC.

For information about enabling this functionality, see *Configuring Logon Banner for HPE OBR* in *HPE Operations Bridge Reporter Configuration Guide*.

- **Common Criteria (CC)** – By Default, HPE OBR uses FIPS compliant algorithms and libraries.

HPE OBR Security Hardening

The Hardening section provides recommendations for safeguarding your HPE OBR deployment from security risks or threats. Some of the most important reasons to secure an application include protecting the confidentiality, integrity, and availability of an organization's critical information.

To comprehensively protect your HPE OBR system, it is necessary to secure both HPE OBR and the computing environment (for example, the infrastructure and the operating system) upon which the application runs.

For more information, see "[Hardening the HPE Operation Bridge Reporter](#)" on page 25.

Physical Security

HPE Software recommends that HPE OBR is protected by physical security controls defined by your organization. The HPE OBR server components are installed in a physically secured environment, according to best practice. For example, the server must be in a closed room with access control.

HPE OBR in FIPS mode

When you configure HPE OBR to run in FIPS mode, the following components are also configured to operate in FIPS mode:

- Tomcat server
- Java Runtime Environment
- SAP BusinessObjects
- Vertica

Secure communication - following are the communication channels that are secured:

- Browser to OBR Administration Console and SAP BusinessObjects - This communication is secured using HTTPS.
- OBR server to Vertica - OBR uses JDBC and ODBC to connect to Vertica. OBR provides steps/tools to achieve the JDBC and ODBC connections over TLS.
- SAP BusinessObject to Vertica - SAP BusinessObject uses JDBC over TLS to connect to Vertica.
- OBR server to OBR collector and OBR collector to agent - LCore BBC is used as the communication framework. OBR provides steps/tools to configure HTTPS for this communication.
- OBR collector to OMi Oracle database - OBR connects to OMi oracle database over JDBC to fetch events. OBR uses DataDirect JDBC driver for communication. OBR provides steps/tools to achieve the JDBC connection over TLS.
- OBR collector to OMi RtSM - OBR allows to configure HTTPS for this communication.

RSA BSAFE Crypto-J version 6.20 is used for Java crypto functions and OpenSSL 01.00.010 is used for 'C' crypto functions.

For more information on configuring HPE OBR for FIPS, see *Configuring FIPS for HPE OBR* section in *HPE Operations Bridge Reporter Configuration Guide*.

Secure Installation Guidelines

This section provides information on supported operating systems, operating system hardening recommendations, and installation permissions.

Supported Operation Systems

For the types and versions of supported operating systems, see the *HPE Operations Bridge Reporter Support Matrix*.

Operating System Hardening Recommendations

Contact your operating system vendor for recommended best practices for hardening your operating system.

For example:

- Latest patches should be installed
- Unnecessary services/software should be removed or disabled
- Minimal permissions should be assigned to users
- Auditing should be enabled

Installation Permissions

The following permissions are required to install and run HPE OBR:

Function	Operating System-Level Security
Installing and running HPE OBR	Linux: Root user or equivalent root user or sudo user has permission to install and run the HPE OBR.

Function	Operating System-Level Security
	<p>For information to create sudo user, see <i>HPE Operations Bridge Reporter Interactive Installation Guide</i>.</p> <p>Windows: Administrator or equivalent to administrator has permission to install and run the HPE OBR.</p>

Tomcat Hardening

When you install HPE OBR, Tomcat is partially hardened by default. For more information, see the recommendations in the *CIS Apache Tomcat 7.0* document.

Administration Interface Security

This section provides information on accessing and securing the administration interface. The Administration Console is the administration interface in HPE OBR.

Accessing the Administration Interface

There are several ways to control access to the administration interface:

- LDAP users (recommended)
- Internal users
- Client Certificate

Securing the Administration Interface

The following are the recommendation for securing the administration interface:

- It is recommended to work with LDAP users, rather than internal users, because this is more secure. LDAP users should be defined with a strong password policy.
- For high security, it is recommended to set up authentication to access HPE OBR Administrator Console and SAP BusinessObjects via Client Authentication certificates. This is more secure than user passwords.

For information to configure Client Authentication certificates, see Client Authentication Certificate for HPE OBR section in *HPE Operations Bridge Reporter Configuration Guide*.

User Management and Authentication

This section provides information on authentication model, types of users, and database authentication.

Authentication Model

The following are the methods to enable authentication in HPE OBR:

- User name and password
- Client Authentication certificate
- LDAP users

Note: HPE OBR authenticates using the SAP BusinessObjects authentication mechanism.

Types of Users

HPE OBR has user types based on the following:

- **Administration Console**

HPE OBR Administration Console can be accessed by user belonging to Administrators group only. For example, **report user** and **report developer**.

- **SAP BusinessObject**

The following are the default user accounts in SAP BusinessObjects:

- **Administrator** - An administrator can perform all tasks in SAP BusinessObjects BI platform applications such as the CMC, CCM, Publishing Wizard, and BI launch pad. The administrator belongs to the Administrators and Everyone groups.
- **Guest** - The guest user is enabled by default and belongs to the Everyone group.
- **SMAAdmin** - The SMAAdmin is a read-only account used by SAP Solution Manager to access BI platform components.

The following are the default user groups in SAP BusinessObjects:

- Administrators
- Everyone
- QaaWS Group Designer
- Report Conversion Tool Users
- Translators
- Universe Designer Users

For more information on SAP BusinessObjects user types and groups, see *Business Intelligence Platform Administrator Guide*.

Authentication, Administration and Configuration

You can set up internal users with passwords or define the user in the LDAP server and map LDAP groups to HPE OBR roles. You can also configure HPE OBR to work with Client Authentication certificate using smart card.

For information to configure Client Authentication certificate for HPE OBR, see *HPE Operations Bridge Reporter Configuration Guide*.

HPE OBR uses the SAP BusinessObjects authentication mechanism. The following are some of the authentication types available in SAP BusinessObjects:

- **Enterprise** - This is the default authentication type. Use this if you prefer to create distinct accounts and groups for use with BI platform, or if you have not already set up a hierarchy of users and groups in an LDAP directory server, or a Windows AD server.
- **LDAP** - This type of authentication, allows you to use existing LDAP user accounts and groups in the BI platform. When you map LDAP accounts to the BI platform, users can access BI platform applications with their LDAP user name and password. This eliminates the need to recreate individual user and group accounts within the BI platform.
- **Windows AD** - This type of authentication allows you to use existing Windows AD user accounts and groups in the BI platform. When you map AD accounts to the BI platform, users can log on to BI platform applications with their AD user name and password. This eliminates the need to recreate individual user and group accounts within the BI platform.

For more information on SAP BusinessObjects authentication, see *Business Intelligence Platform Administrator Guide*.

User Authentication

Users can authenticate into the Administration console by using a local user account or by using one of several external authentication components. Each approach requires administrative setup.

Database Authentication

HPE OBR includes PostgreSQL and Vertica as database. The PostgreSQL database authentication is handled by allowing access only from within the HPE OBR system.

HPE OBR uses Vertica database for storing, processing, and managing the performance data of your IT environment. HPE OBR uses SSL to communicate with Vertica database.

We recommend using a strong database password for database authentication and using a strong password policy.

For information on changing the database password, see *Changing Password* section in HPE Operations Bridge Reporter *Administration Guide*.

Authorization

This section provides information about authorization model, configure and administer the authorization.

Authorization Model

User access to HPE OBR resources is authorized based on the user's role, and the permissions.

HPE OBR enforces resource access control on users/groups accessing resources. The resources include reports, folders, universe etc. The resource access control allows users or groups to gain access to the resources only if the user or group has the correct permission for the resource. HPE OBR users and groups can have either Granted, Denied, View or Full access permissions.

Minimal Permissions Guidelines

It is recommended to:

- Select appropriate permissions for the role.
- Use minimal permissions when creating new roles.
- Grant minimal permissions and extend the permissions only as needed to avoid unwanted privilege escalation.

Authorization Administration

Authorizing Administration Console User Accounts

An HPE OBR administrator can set the following general behaviors that apply to all local user accounts of Administration Console:

- Minimum and maximum password length
- Password complexity

- Password expiration
- Password reuse

Authorizing SAP BusinessObjects User Accounts

You can change the password settings for a specific user or for all users in the system. The various restrictions apply only to Enterprise accounts—that is, the restrictions do not apply to accounts that you have mapped to an external user database (LDAP or Windows AD). The following are the user and general password settings for user accounts of SAP BusinessObjects:

- User password settings:
 - Password never expires
 - User must change password at next log on
 - User cannot change password
- General password settings:
 - Enforce mixed-case passwords
 - Must contain at least N Characters
 - Must change password every N day(s)
 - Cannot reuse the N most recent password(s)
 - Must wait N minute(s) to change password
 - Disable account after N failed attempts to log on
 - Reset failed log on count after N minute(s)
 - Re-enable account after N minute(s)

Backup

In order to prevent data loss, it is highly recommended to back up your data on the servers onto secure media on a regular basis. This is also helpful for disaster recovery and business continuity.

For more information on backup and recovery, see *Database Backup and Recovery* section in *HPE Operations Bridge Reporter Configuration Guide*.

Encryption

This section describes the encryption, encryption model and digital certificates.

Encryption Model

Encryption is designed to prevent the exposure and modification of sensitive data, such as passwords, definitions, and so on, in the HPE OBR system.

It is important to use well known, standard algorithms without known vulnerabilities, in order to prevent decryption by unauthorized persons.

Static Data

All saved passwords are protected using well known algorithms and none are left in cleartext.

For example:

- The system account passwords are encrypted and protected.
- The database passwords are encrypted.

Encryption Administration

In order to reach higher levels of security and cryptography, HPE OBR uses FIPS compliant algorithms and libraries.

Digital Certificates

A digital certificate is an electronic "passport" for a person, server, station, and so on.

- To use encryption between a browser and the HPE OBR server, you need to install a digital certificate on the server side.

- To use Client Authentication certificate to authenticate the HPE OBR server, you need to install a Client Authentication certificate on the client side.

Access Control to KeyStore and TrustStore

It is recommended that the TrustStore and KeyStore are stored with read permissions only for the user that runs the Administration Console.

Replacing the HPE OBR Self-signed Certificate

It is recommended to replace the HPE OBR self-signed certificate with CA signed certificate after a new installation of HPE OBR or if your current certificate has expired.

For information to generate CA signed certificate, see *HPE Operations Bridge Reporter Interactive Installation Guide*.

Log and Trace

Logs let you trace errors, warnings, information, and debugging messages. The logs are saved in the file server, in the following locations:

- {PMDB_HOME}\log - Contains log messages related to administrator services, database, HPE OBR licensing, business objects, administration console, internal monitoring, collector, logger, mapper.
- {PMDB_HOME}\adminServer\logs - Contains log messages related to Administration Console.
- {PMDB}\BOWebServer\logs - Contains log messages related to SAP BusinessObjects launch pad.
- {PMDB_HOME}\log\VC_collector\ - Contains log messages related to VC collector.
- <Postgres_install_directory>/data/pg_log - Contains log messages related to PostgreSQL.

For more information on HPE OBR log files, see *Introducing the HPE OBR Log Files* section in *HPE Operations Bridge Reporter Troubleshooting Guide*.

Hardening the HPE Operation Bridge Reporter

This section describes how to configure security hardening for HPE Operations Bridge Reporter.

Security Hardening Recommendations

1. Install the latest version and patch of HPE Operations Bridge Reporter.
2. HPE OBR uses FIPS compliant algorithms and libraries.
3. Configure HPE OBR to use CA signed certificate. For more information, see *HPE Operations Bridge Reporter Interactive Installation Guide*.
4. Secure communication (HTTPS) is enabled between browser and Administration Console/SAP BusinessObjects application. For information to disable the HTTPs, see *HPE Operations Bridge Reporter Troubleshooting Guide*.

HPE OBR strongly recommends the use of HTTPS, for security reasons, so that the only communication channel will be on TLS and encrypted.

5. Configure the HPE OBR for TLS encryption and client certificate for strong authentication (mutual).
6. Configure the TLS protocol version.
7. Harden/secure the operating system and database.

Configuring the TLS Protocol

You can configure HPE OBR to define the supported TLS protocol version. By default, HPE OBR allows TLS v1, TLS v1.1 and TLS v1.2, but you can narrow this down.

To configure TLS protocol, follow these steps:

1. Open the `server.xml` file located at `%PMDB_HOME%\BOWebServer\conf` and `%PMDB_HOME%\adminServer\conf` (**for Windows**) or `$PMDB_HOME/BOWebServer/conf` and `$PMDB_`

HOME/adminServer/conf **(for Linux)**.

2. Locate the SSL connector.
3. Edit the default value of `sslEnabledProtocols`. For example, change

```
sslEnabledProtocols="TLSv1,TLSv1.1,TLSv1.2" to
```

```
sslEnabledProtocols="TLSv1.2"
```

4. Restart the server.

Clickjacking Protection

The protection against clickjacking is handled in HPE OBR by using the `x-frame` option. The preferred framing policy value `SAMEORIGIN` is used in the header to allow framing only by the specified site.

Send documentation feedback

If you have comments about this document, you can [contact the documentation team](#) by email. If an email client is configured on this system, click the link above and an email window opens with the following information in the subject line:

Feedback on Secure Deployment Guide (Operations Bridge Reporter 10.10)

Just add your feedback to the email and click send.

If no email client is available, copy the information above to a new message in a web mail client, and send your feedback to docfeedback@hpe.com.

We appreciate your feedback!

