

HP Network Node Manager iSPI for MPLS Software

for the HP-UX, Linux, Solaris, and Windows® operating system

Software Version: 9.10

Installation Guide

Document Release Date: March 2011
Software Release Date: March 2011



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notice

© Copyright 2008 - 2011 Hewlett-Packard Development Company, L.P.

Trademark Notices

Acrobat® is a trademark of Adobe Systems Incorporated.

HP-UX Release 10.20 and later and HP-UX Release 11.00 and later (in both 32 and 64-bit configurations) on all HP 9000 computers are Open Group UNIX 95 branded products.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

Oracle Technology — Notice of Restricted Rights

Programs delivered subject to the DOD FAR Supplement are 'commercial computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement. Otherwise, programs delivered subject to the Federal Acquisition Regulations are 'restricted computer software' and use, duplication, and disclosure of the programs, including documentation, shall be subject to the restrictions in FAR 52.227-19, Commercial Computer Software-Restricted Rights (June 1987). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

For the full Oracle license text, see the license-agreements directory on the NNMi product DVD.

Printed in the U.S.

Acknowledgements

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

Portions Copyright © 1999-2003 The Apache Software Foundation. All rights reserved.

This product includes ASM Bytecode Manipulation Framework software developed by Institute National de Recherche en Informatique et Automatique (INRIA). Copyright © 2000-2005 INRIA, France Telecom. All Rights Reserved.

This product includes Commons Discovery software developed by the Apache Software Foundation (<http://www.apache.org/>). Copyright © 2002-2008 The Apache Software Foundation. All Rights Reserved.

This product includes Netscape JavaScript Browser Detection Library software, Copyright © Netscape Communications 1999-2001

This product includes Xerces-J xml parser software developed by the Apache Software Foundation (<http://www.apache.org/>). Copyright © 1999-2002 The Apache Software Foundation. All rights reserved.

This product includes software developed by the Indiana University Extreme! Lab (<http://www.extreme.indiana.edu/>). Xpp-3 Copyright © 2002 Extreme! Lab, Indiana University. All rights reserved.

Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to:

<http://h20230.www2.hp.com/selfsolve/manuals>

This site requires that you register for an HP Passport and sign in. To register for an HP Passport ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

Or click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

Support

Visit the HP Software Support Online web site at:

www.hp.com/go/hpsoftwaresupport

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport user ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

To find more information about access levels, go to:

http://h20230.www2.hp.com/new_access_levels.jsp

1	Introduction	9
	MPLS Workspace	9
	Related Topics:	9
2	Before You Begin	11
	Installation Process on the NNMi Management Server	11
	Preinstallation Tasks	12
	Preparing for Installation	13
3	Installing the iSPI for MPLS	15
	Installing on a Windows Management Server	15
	Installing on a UNIX Management Server	17
	Steps to Install and Start the NNM iSPI for MPLS	20
	Silent Installation for NNM iSPI for MPLS	20
	Starting and Stopping the NNMi and iSPI for MPLS Processes	21
	Verifying the NNMi and iSPI for MPLS Processes	21
	Removing the iSPI for MPLS	21
	License-related Information	22
	Introduction to iSPI Points License	22
	iSPI Points Consumption Break-up	22
	Checking the License Type	23
	Checking the MPLS Object-related Point Usage	23
	Obtaining and Installing a Permanent License	23
	Extend the MPLS Licenses	24
	Accessing the Log Files	24
	List of MPLS log files	24
	Updating the NNMi Port Number	24
	Updating the Security Mode (HTTP to HTTPS)	25
	Updating the NNMi System Password	25
	Updating the iSPI for MPLS (Web Service Client Password)	26
4	Installing in a High-Availability Cluster Environment and Application Fail-over	27
	Prerequisites for installing iSPI for MPLS on HA	27
	Installing the iSPI for HA	27
	Steps to Install iSPI for MPLS when NNMi is Running on HA	27
	Steps to Uninstall iSPI for MPLS when NNMi is Running on HA	27
	Configuring the iSPI for HA	28
5	Getting Started with the iSPI for MPLS	29
	Accessing the iSPI for MPLS	29
	Starting the MPLS Discovery Process	29
	Accessing the Online Help	29
	Configuration Tasks in HP iSPI for MPLS	30
	Accessing the MPLS Reports	30

6	Upgrading to the NNM iSPI for MPLS 9.10	31
	License for Upgrading from the Earlier Versions	31
	License for Upgrading from the MPLS, Version 7.53 to Version 9.10	31
	License for Upgrading from the iSPI for MPLS, Version 8.10 to Version 9.10	31
	License for Upgrading from the iSPI for MPLS, Version 9.00 to Version 9.10	31
	Upgrading from Version 7.53 to Version 9.10	31
	Upgrading from Version 8.xx to Version 9.10	33
	Upgrading from Version 9.00 to Version 9.10	33
	Product Comparison	34
A	Troubleshooting the iSPI for MPLS	41
	Installing the iSPI for MPLS	41
	Uninstalling the iSPI for MPLS	42
	Additional Troubleshooting Information	43
	For All Platforms	43
	For Linux Platform	43

1 Introduction

The HP Network Node Manager i Software Smart Plug-in for MPLS (Multi Protocol Label Switching) (NNMi iSPI for MPLS) extends the capability of NNMi to monitor the network. The iSPI for MPLS presents additional views to indicate the status of discovered MPLS-enabled devices and display the overall health of the network.

The iSPI for MPLS, in conjunction with NNMi, performs the following tasks:

- Discovering and monitoring the MPLS-enabled nodes and interfaces.
- Displaying the MPLS-enabled objects in the MPLS inventory.
- Monitoring the status of the discovered MPLS object in the network.
- Monitoring the MPLS views from Global Network Manager's inventory.
- Monitoring the network by using the topology map views.
- Troubleshooting the network by viewing the MPLS reports.

After you install (and configure) the iSPI for MPLS on the NNMi management station, you can monitor and troubleshoot the problems in your network with by using the MPLS workspace.

The iSPI for MPLS integrates with the iSPI for IP Multicast, RAMS, iSPI for Metrics, and iSPI Performance for Quality Assurance to help you monitor the network by using the additional capabilities introduced by these products.

MPLS Workspace

The iSPI for MPLS uses NNMi console to introduce the MPLS-related views to monitor your network. The MPLS views provide a list of discovered MPLS objects. You can monitor the health of the MPLS objects by using the MPLS workspace.

The iSPI for MPLS monitors the health of MPLS Layer 3 Virtual Private Network (L3VPN), MPLS Layer 2 VPNs (L2VPNs), Multicast VPNs (MVPNs), MPLS PseudoWire VC, and Traffic Engineering (TE) tunnels. The MPLS views extend the properties of NNMi to perform the fault management of supported MPLS features.

You can use the NNMi user-level access for the MPLS workspace. The iSPI for MPLS uses the operator and administrator level security access for various tasks. With the operator-level privileges, you can perform the fault management tasks by monitoring the state, status, and incidents of the all the MPLS objects. With the administrator-level privileges, you can complete all the configuration tasks from the MPLS Configuration workspace.

Related Topics:

For more information about iSPI for MPLS, see the following documentation:

- [iSPI for MPLS Online Help](#)—includes information on the views, forms, and map views introduced by the iSPI for MPLS.
- [iSPI for MPLS Release Notes](#)
- [iSPI for MPLS Support Matrix](#)
- [iSPI for MPLS Deployment Guide](#)

2 Before You Begin

Before you start installing the iSPI for MPLS, you must plan the installation based on your deployment requirements. You must identify the ideal deployment scenario among the supported configurations. Make sure that all the prerequisites are met before you begin the installation process.

You can see the following documents before you start the installation process:

- *HP Network Node Manager 9.10 Installation Guide for Windows or HP Network Node Manager 9.10 Installation Guide for UNIX*
- *HP Network Node Manager 9.10 Deployment Guide*
- *HP Network Node Manager 9.10 Release Notes*
- *HP Network Node Manager 9.10 Support Matrix*

Before you begin the iSPI for MPLS installation, follow these steps:

- 1 Install NNMi. Make sure that NNMi is installed in the environment and running.
- 2 Install available NNMi patches, if any.
- 3 Start the iSPI for MPLS installation process.

You install the iSPI for MPLS on the NNMi management station. You can also install the iSPI for MPLS in High-Availability (HA) cluster environments that are supported by NNMi. For information about the steps to install the iSPI for MPLS in HA environment, see [Installing in a High-Availability Cluster Environment and Application Fail-over](#).

Installation Process on the NNMi Management Server

Before installing the iSPI for MPLS on the NNMi management server, you must note down all the configuration-related information of the NNMi installation. These details are required while you install the iSPI for MPLS.



Before installing the iSPI for MPLS, make sure to create the Web service Client user for the iSPI for MPLS.

NNMi Port Details

Note down the following port numbers of the NNMi installation:

- Port number of NNMi
- Port number of Java Naming and Directory Interface (JNDI) on the management station

To verify the port details, open the `nms-local.properties` file from the `%NnmDataDir%\conf\nnm\props` or `$NnmDataDir/conf/nnm/props` directory on the management server, and then note down the following values:

- `jboss.http.port` for the HTTP port number. The default value is 80.

- `jboss.https.port` for the HTTPS port number. The default value is 443.
- `jboss.jnp.port` for the JNDI port number. The default value is 1099.

For more information about the ports used by NNMi, see *NNMi Deployment Guide*.

Database Details

You can choose an external Oracle database instead of the embedded database to store NNMi data. The external Oracle database can reside either on the NNMi management station or on a remote server. You must note down the following details of the NNMi database.

- **Type:** The default embedded database or Oracle database.
- **Port:** The port used by the Oracle database.
- **Hostname:** The fully-qualified domain name of the Oracle server.
- **Oracle Database name:** The name of the Oracle database instance.
- **Oracle Database Username:** The Oracle username created to access NNMi data.
- **Password:** Password for the above user.



Before installing the iSPI for MPLS, make sure to note down the database details if you are using Oracle database or embedded database.

With the iSPI for MPLS, you must use a new Oracle instance, and not the Oracle instance configured with NNMi. Before you create a unique Oracle instance for the iSPI for MPLS, see the Database Installation section in the *HP Network Node Manager i Software Installation Guide* for additional details. If you are using a unique Oracle instance, note down the details for this instance as well.

Preinstallation Tasks

Before you start installing the iSPI for MPLS, complete the following tasks:

Task 1: Create a New User with the Web Service Client Role

Create a user from the NNMi console with the Web Service Client role. This user is used during the installation of the iSPI for MPLS. Do not use the NNMi system account while installing the iSPI for MPLS. Create a new web service client user as follows:

- 1 Go to Configuration -> Security -> User Account
- 2 Click **New** icon to open the User Account view
 - Enter a Username and password
 - Select External Account if applicable.
 - Use the ‘click here’ option from the view for more information on ‘External Account’.
- 3 Click **Save and close** icon

Assign a user group to your user account as follows:

- 1 Go to Configuration -> Security -> User Account Mappings
- 2 Click **New** icon to open the User Account Mapping view
 - Select a User account from the **User Account** list
 - Select **NNMi Web Service Clients** from the **User Group** list
- 3 Click **Save and close** icon

Task 2: *Only for Oracle. Create a New Oracle Instance*

Skip this task if you choose to use the embedded database. You must create a new Oracle instance before installing the iSPI for MPLS. While installing and configuring the iSPI for MPLS, do not use the same Oracle instance that was configured with NNMI.

Preparing for Installation

Before installing the iSPI for MPLS, make sure the management station meets all the hardware and software requirements.

See the *HP Network Node Manager i Software Smart Plug-in for MPLS Support Matrix* and *HP Network Node Manager i Software Smart Plug-in for MPLS Release Notes* documents for complete information about hardware and software requirements and dependencies.

Table 1 Preinstallation Checklist for Hardware and Software Requirements

Requirement	Reference Document	Complete(Yes/No)
Disk space	Support Matrix	Yes
Operating system	Support Matrix	Yes
Database	Support Matrix	Yes

3 Installing the iSPI for MPLS

You can install the iSPI for MPLS on both types of management server—Windows and UNIX. You can use the installation wizard. The installation wizard guides you through the installation process.

Installing on a Windows Management Server

To install the iSPI for MPLS on a Windows management server, follow these steps:

- 1 Log on to the management server with Administrator privileges.
- 2 Insert the iSPI for MPLS installation media into CD-ROM drive. The CD-ROM must start automatically. If it does not start from the root directory, double-click the setup.bat file. The installation wizard opens.

If the Application requirement check warnings dialog box opens, click and review each warning and take appropriate actions.

- 3 In the **Introduction** screen, check the iSPI for MPLS information and then click **Next**.
- 4 On the **License Agreement** page, check the iSPI for MPLS license terms. If you agree with the terms of the license agreement, select I accept...; then click **Next**. The **Product Customization Feature Selection** screen appears.
- 5 From the **Choose the database type** page, select any one of the options:

▶ Make sure to select the same database type (embedded or Oracle) that you have selected while installing NNMi.

- Select **HP Software Embedded Database**, and click **Next**. The **Install Checks** screen appears. Go to [step 10](#) on page 16.
- Select **Oracle**, and click **Next**.

- 6 *Skip the steps from 6 to 9 if you choose to use the embedded database.* If you select an Oracle database, from the **Choose Database Initialization Preferences** page, choose any one of the following:

▶ Select the same database type (Primary Server or Secondary Server) as NNMi.

- **Primary Server Installation** - Select this option for installing the iSPI for MPLS.
 - **Secondary Server Installation** - Select this option for installing the iSPI for MPLS in an Application Failover or High Availability (HA) environment.
- 7 From **Enter your database server information** page, specify the following information that you have used while creating a new Oracle instance for the iSPI for MPLS:
 - **Host** - The fully-qualified domain name of the Oracle server. Type the server name.
 - **Port** -The default Oracle port number (1521) appears in the dialog box.
 - **Instance** - Type the name of the Oracle database instance.

- 8 Type the following information that you have used while creating a new Oracle instance for the iSPI for MPLS:
 - **Username** - Type the Oracle username created to access MPLS data.
 - **Password** - Type the password for the mentioned user.
- 9 After completing the Oracle database configuration, click **OK**. The **Install Checks** screen appears. If the configuration process reports an error, check the credentials. To type the database instance information again, click the **Previous** button.
- 10 From the **Install Checks** screen, the wizard checks for the available disk space. The Product Requirements screen shows the required disk space and available disk space on the machine. Check the indicated values.
- 11 Click **Next**. The **Pre-Install Summary** screen appears.
- 12 Review the options, and click **Install**. The installation process begins.
- 13 Specify the following details in the MPLS SPI dialog box:



The NNMi configuration parameters should be same as you have entered while installing NNMi.

Make sure to select the same database type (embedded or Oracle) that you have selected while installing NNMi.

- Information required by MPLSSPI to communicate to NNMi



Specify the values configured with NNMi.

- **NNMi FQDN/IP Address** - The fully-qualified domain name (FQDN) of the NNMi management station. The hostname can be fullyqualified domain name or IP Address. Check the NNMi name from **Help->System Information-> Server**.
- **NNMi HTTP Port** - Specify the port configured with NNMi (default value is 80). To verify the port number, open the `nms-local.properties` file and check the `jboss.http.port` value from the `%NnmDataDir%\conf\nnm\props` directory. To update the NNMi port number, see [Updating the NNMi Port Number](#) on page 24.
- **NNMi HTTPS Port** - Specify the port configured with NNMi (default value is 443). To verify the port number, open the `nms-local.properties` file and check the `jboss.https.port` value from the `%NnmDataDir%\conf\nnm\props` directory. To update the NNMi port number, see [Updating the NNMi Port Number](#) on page 24.
- **NNMi Java Naming and Directory Interface (JNDI) Port** - Port number used by the jboss application server for internal communication. Specify the NNMi port number (default value is 1099). To verify the port number, open the `nms-local.properties` file and check the `jboss.jnp.port` value from the `%NnmDataDir%\conf\nnm\props` directory.
- **NNMi Username** - Type the Web Service Client username.
- **NNMi Password** - Type the Web Service Client password.
- **Retype Password** - Retype the password to confirm the password.
- **isSecure** - Select the option to enable HTTPS. By default, NNMi uses HTTP. This option specifies the mode of transmission such as secured or unsecured.

- For iSPI for MPLS Configuration Parameters, type the following:



The various cases for the (Fully Qualified Domain Name (FQDN) configuration parameters are listed below:

- The NNMi and iSPI for MPLS must use the same FQDN. If the NNM server is having more than one domain name, installation process chooses one and the iSPI for MPLS installation also must use the same domain name. To find the official FQDN of the NNMi server, use any *one* of following:
 - Run the `nnmofficialfqdn.ovpl` command.
 - From the NNMi console, click **Help > About Network Node Manager i Software**.
- At the time of NNMi installation, if you are using the partial domain name as <people> or the IP Address as <xx.xx.xx.xx> and not the fully qualified domain name, the Single Sign-on is disabled.
 - **MPLS FQDN/IP Address** - The FQDN of the NNMi management station.
 - **MPLS HTTP Port** - Type the unsecured port number. The default value is 24040. To modify the value after installing the iSPI for MPLS, open the `nms-mpls.ports.properties` file and check the `Djboss.http.port` value from the `%NnmDataDir%\shared\mpls\conf` directory.
 - **MPLS HTTPS Port** - Type the secured port number. The default value is 24043. To modify the value after installing the iSPI for MPLS, open the `nms-mpls.ports.properties` file and check the `Djboss.https.port` value from the `%NnmDataDir%\shared\mpls\conf` directory.
 - **JNDI Port** - The default JNDI iSPI port number is 24046. This port number is used by the jboss application server for internal communication. To modify the value after installing the iSPI for MPLS, open the `nms-mpls.ports.properties` file and check the `Djboss.jnp.port` value from the `%NnmDataDir%\shared\mpls\conf` directory.



Always select the same mode of transmission for NNMi and iSPI for MPLS.

- **isSecure** - Select the option to enable HTTPS. By default, the iSPI for MPLS uses HTTP. This option specifies the mode of transmission such as secured or unsecured.
- 14 Click **OK** to proceed with the installation process.
 - 15 When the installation process is complete, click **Done**. After the installation is done, start all the processes and start the discovery process.

You can check the necessary information about the installation from Summary and Details tab. If the installation process fails to complete, you can Rollback the Installation process and start again.

Installing on a UNIX Management Server

To install the iSPI for MPLS on a UNIX management server, follow these steps:

- 1 Log on to the management server with root privileges.
- 2 Insert the iSPI for MPLS installation media into the CD-ROM drive. The CD-ROM must start automatically. If the installation does not start, run the command `./setup`. The installation wizard opens.

If the Application requirement check warnings dialog box opens, click and review each warning and take appropriate actions.

- 3 In the **Introduction** screen, check the iSPI for MPLS information and then click **Next**.
- 4 On the **License Agreement** page, check the iSPI for MPLS license terms. If you agree with the terms of the license agreement, select I accept...; then click **Next**. The **Product Customization Feature Selection** screen appears.
- 5 From the **Choose the database type** page, select any *one* of the options:



Make sure to select the same database type (embedded or Oracle) that you have selected while installing NNMi.

- Select **HP Software Embedded Database**, and click **Next**. The **Install Checks** screen appears. Go to [step 10](#) on page 18.
 - Select **Oracle**, and click **Next**.
- 6 *Skip the steps from 6 to 9 if you choose to use the embedded database.* If you select an Oracle database, from the **Choose Database Initialization Preferences** page, choose any one of the following:



Select the same database type (Primary Server or Secondary Server) as NNMi.

- **Primary Server Installation** - Select this option for installing the iSPI for MPLS.
 - **Secondary Server Installation** - Select this option for installing the iSPI for MPLS in an Application Failover or High Availability (HA) environment.
- 7 From **Enter your database server information** page, specify the following information that you have used while creating a new Oracle instance for the iSPI for MPLS:
 - **Host** - The fully-qualified domain name of the Oracle server. Type the server name.
 - **Port** -The default Oracle port number (1521) appears in the dialog box.
 - **Instance** - Type the name of the Oracle database instance.
 - 8 Type the following information that you have used while creating a new Oracle instance for the iSPI for MPLS:
 - **Username** - Type the Oracle username created to access MPLS data.
 - **Password** - Type the password for the mentioned user.
 - 9 After completing the Oracle database configuration, click **OK**. The **Install Checks** screen appears. If the configuration process reports an error, check the credentials. To type the database instance information again, click the **Previous** button.
 - 10 From the **Install Checks** screen, the wizard checks for the available disk space. The Product Requirements screen shows the required disk space and available disk space on the machine. Check the indicated values.
 - 11 Click **Next**. The **Pre-Install Summary** screen appears.
 - 12 Review the options, and click **Install**. The installation process begins.
 - 13 Specify the following details in the MPLS SPI dialog box:



The NNMi configuration parameters should be same as you have entered while installing NNMi.

Make sure to select the same database type (embedded or Oracle) that you have selected while installing NNMi.

- Information required by MPLSSPI to communicate to NNMi



Specify the values configured with NNMi.

- **NNMi FQDN/IP Address** - The fully-qualified domain name (FQDN) of the NNMi management station. The hostname can be fullyqualified domain name or partial hostname or IP Address. Check the NNMi name from **Help->System Information-> Server**.
- **NNMi HTTP Port** - Specify the port configured with NNMi (default value is 80). To modify the port number after installing the iSPI for MPLS, open the `nms-local.properties` file and check the `jboss.http.port` value from the `$NnmDataDir\conf\nnm\props` directory. To update the NNMi port number, see [Updating the NNMi Port Number](#) on page 24.
- **NNMi HTTPS Port** - Specify the port configured with NNMi (default value is 443). To modify the port number after installing the iSPI for MPLS, open the `nms-local.properties` file and check the `jboss.https.port` value from the `$NnmDataDir\conf\nnm\props` directory. To update the NNMi port number, see [Updating the NNMi Port Number](#) on page 24.
- **NNMi Java Naming and Directory Interface (JNDI) Port** - Port number used by the jboss application server for internal communication. Specify the NNMi port number (default value is 1099). To modify the port number after installing the iSPI for MPLS, open the `nms-local.properties` file and check the `jboss.jnp.port` value from the `$NnmDataDir\conf\nnm\props` directory.
- **NNMi Username** - Type the Web Service Client username.
- **NNMi Password** - Type the Web Service Client password.
- **Retype Password** - Retype the password to confirm the password.
- **isSecure** - Select the option to enable HTTPS. By default, NNMi uses HTTP. This option specifies the mode of transmission such as secured or unsecured.
- For the iSPI for MPLS Configuration parameters, type the following:



The various cases for the (Fully Qualified Domain Name (FQDN) configuration parameters are listed below:

- The NNMi and iSPI for MPLS must use the same FQDN. If the NNM server is having more than one domain name, installation process chooses one and iSPI for MPLS installation must also use the same domain name. To find the official FQDN of the NNMi server, use any *one* of following:
 - Run the `nnmofficialfqdn.ovpl` command.
 - From the NNMi console, click **Help > About Network Node Manager i Software**.
- At the time of NNMi installation, if you are using the partial domain name as <people> or the IP Address as <xx.xx.xx.xx> and not the fully qualified domain name, the Single Sign-on is disabled.
 - **MPLS FQDN/IP Address** - The FQDN of the NNMi management station.
 - **MPLS HTTP Port** - Type the unsecured port number. The default value is 24040. To update the port number, open the `nms-mpls.ports.properties` file and check the `jboss.http.port` value from the `$NnmDataDir\shared\mpls\conf` directory.
 - **MPLS HTTPS Port** - Type the secured port number. The default value is 24043. To update the port number, open the `nms-mpls.ports.properties` file and check the `jboss.https.port` value from the `$NnmDataDir\shared\mpls\conf` directory.
 - **JNDI Port** - The default JNDI port number is 24046. This port number is used by the jboss application server for internal communication.



Always select the same mode of transmission for NNMi and iSPI for MPLS.

- **isSecure**: Select the option to enable HTTPS. By default, the iSPI for MPLS uses HTTP. This option specifies the mode of transmission such as secured or unsecured.
- 14 Click **OK** to proceed with the installation process.
 - 15 When the installation process is complete, click **Done**. After the installation is done, start all the processes and start the discovery process.

The iSPI for MPLS installation process is complete. You can check the necessary information about the installation from Summary and Details tab. If the installation process fails to complete you can Rollback the Installation process and start again.

Steps to Install and Start the NNM iSPI for MPLS

To complete the installation process of the iSPI for MPLS and start all the MPLS views for monitoring the network, follow these steps:

- 1 Install NNMi. Verify that all the available NNMi patches are installed.
- 2 Install the iSPI for MPLS.
- 3 Start the processes for NNMi and iSPI for MPLS.
- 4 Complete the discovery process. Use the `%InstallDir\bin\nmsmplsdisco.ovpl -u <user> -p <password> -all` or `$InstallDir/bin/nmsmplsdisco.ovpl -u <user> -p <password> -all` command.
- 5 After installing the iSPI for MPLS, log on to the NNMi console and verify the MPLS workspace.
- 6 Perform the necessary configurations such as Exclude Route Targets, VPWS, and Polling Frequencies from the **MPLS Configuration** workspace

Silent Installation for NNM iSPI for MPLS

NNM iSPI for MPLS supports silent installation. For the silent installation, use the `silentInstall.properties` file that comes with installation media within the root directory.

Follow these steps for silent installation:

- 1 Log on to the management server with Administrator privileges
- 2 Insert the NNM iSPI for MPLS installation media into the DVD drive
- 3 Place a copy of `silentInstall.properties` in a temporary location on the system
- 4 Edit the `silentInstall.properties` file. This file will have default values for the following:

```
SPI.HTTP.PORT
SPI.HTTPS.PORT
SPI.JNDI.PORT
SPI.WEB.SERVICE.USERNAME
SPI.WEB.SERVICE.PASSWORD
SPI.isSecure
```

dbType

- 5 If you choose dbType= Oracle, then you have to also enter the following details:

db.host

db.instance

db.user.loginname

db.user.loginpassword

db.port

- 6 Run `./setup.<bin/exe> -i silent` command to start the silent installation

Silent Installation is supported for both, Postgress and Oracle databases.



Silent installation runs as a background process and takes some time for completion. Progress Indicator is not available for silent installation.

Starting and Stopping the NNMi and iSPI for MPLS Processes

To start and stop the iSPI for MPLS, follow these steps:

- 1 Check the status of the NNMi process using the following command:

```
ovstatus -c ovjboss
```

If the NNMi is not running, start the NNMi process by using the following command:

```
ovstart -c ovjboss
```

- Start the MPLS process using the following command:

```
ovstart -c mplsjoboss
```

- Stop the MPLS process using the following command:

```
ovstop -c mplsjoboss
```

Verifying the NNMi and iSPI for MPLS Processes

Check if the NNMi and MPLS processes are running by using the following command: **ovstatus -c**

Removing the iSPI for MPLS

Before you start uninstalling the iSPI for MPLS, make sure that the MPLS processes are stopped but the NNMi process (ovjboss) is running. If the MPLS process is running, the process exits with an error message.

To uninstall the iSPI for MPLS from a management station, follow these steps:

- 1 Log on to the management station with the Administrator (for Windows) or root (for UNIX) privileges.
- 2 Run the following command:

On Windows: `%NmInstallDir%\Uninstall\HPOvMPLSiSPI\setup.exe`

On UNIX:

```
$NnmInstallDir/Uninstall/HPOvMPLSiSPI/setup.bin
```

A wizard opens.

- 3 Follow the instructions on the wizard and complete the procedure to remove the product.
- 4 When the process is complete, click **Done**.

License-related Information

Irrespective of your choice of deployment, you must always enable licenses for iSPIs only on the NNMi management server. You can use `nnmlicense.ovpl` script, available with NNMi, to enable licenses by installing license keys on the NNMi management server.

Introduction to iSPI Points License

The iSPI Points license is a points-based licensing scheme for all NNM iSPIs (other than the iSPI Performance for Metric). Every monitored object in the iSPI consumes certain number of points. This number may vary from different objects monitored in the iSPI. You can obtain iSPI points by purchasing iSPI Point Packs. The iSPI for MPLS includes a temporary Instant-On license key that is valid for 60 days after you install the iSPI for MPLS. You must obtain and install a permanent license key as soon as possible.

The three types of the iSPI for MPLS licenses are:

- **Instant-on** - The Instant-on license is an evaluation license. The valid period of this license is sixty days.
- **Points Based** - The Points-based license is the actual point consumption by the iSPI for MPLS. The points used appear in the iSPI for MPLS system information.
- **Migration** - The migration licenses are valid only for the user updating from previous versions (7.xx) of the MPLS SPI.

iSPI Points Consumption Break-up

In NNM iSPI for MPLS, you have to calculate points required for LSRs, Layer 3 VRFs, and Layer 2 Forwarding Interfaces.

For the NNM iSPI for MPLS, you require the following:

Table 2 NNM iSPI for MPLS iSPI Points

Topology Objects	Points Consumption
LSR	4
L3 VRF	4
L2 Forwarding Interface	5

For example, if NNM iSPI for MPLS is monitoring 5 LSRs, 5 VRFs, and L2 Forwarding Interfaces, then the total iSPI points required for deployment are $(5 \times 4) + (5 \times 4) + (5 \times 5) = 65$. When sufficient iSPI points are not available for deployment, a warning message appears

Checking the License Type

To find the iSPI for MPLS license information, use any *one* of the following:

- 1 In the NNMi console, click **Help > About Network Node Manager i Software**.
- 2 In the About Network Node Manager window, click **Licensing Information**.

OR

- 1 In the NNMi console, click **Help > System Information**.
- 2 From the System Information box, click **View Licensing Information**.

Checking the MPLS Object-related Point Usage

- 1 In the NNMi console, click **Help > NNMi iSPI Help ->iSPI for MPLS System Information**.
- 2 In the iSPI for MPLS window, click the **License Report** tab and **Topology Statistics** tab. The License report tab shows the total points used for the MPLS topology object. The Topology Statistics tab shows the total number of MPLS objects monitored by the iSPI for MPLS.

Obtaining and Installing a Permanent License

After you install your license from Autopass user interface, close the license window. The license points appear in the iSPI for MPLS system information only after you close the window.

To enable the NNM iSPI for MPLS licenses from the Autopass console, follow these steps on the NNMi management server:

- 1 Log on to the NNMi management server with the administrative or root privileges.
- 2 Enable the iSPI Points license.

At the command prompt, run the following command:

On Windows

```
%NnmInstallDir%\bin\nnmlicense.ovpl iSPI-Points -gui
```

On UNIX/Linux

```
/opt/OV/bin/nnmlicense.ovpl iSPI-Points -gui
```

The Autopass user interface opens.

Install the license key by following on-screen instructions.

Alternatively, to enable the NNM iSPI for MPLS licenses from the command line, follow these steps:

- 1 Log on to the NNMi management server with the administrative or root privileges.
- 2 With the help of a text editor, create a text file that contains only the license key.
- 3 Save the file on the system.
- 4 At the command prompt, run the following command:

On Windows

```
%NnmInstallDir%\bin\nnmlicense.ovpl iSPI-Points -f <license_file>
```

On UNIX/Linux

```
/opt/OV/bin/nnmlicense.ovpl iSPI-Points -f <license_file>
```

In this instance, *<license_file>* is the name of the file created in [step 2](#)

Extend the MPLS Licenses

To extend the licensed capacity, purchase and install an additional iSPI for MPLS license. Contact your HP Sales Representative or your Authorized Hewlett-Packard Reseller for information about the iSPI for MPLS licensing structure and to learn how to add license tiers for enterprise installations.

To obtain additional license keys, go to the HP License Key Delivery Service: <https://webware.hp.com/welcome.asp>

Accessing the Log Files

The iSPI for MPLS stores all the installation-related information into the following directory:

- For Windows: %Temp%\
- For Unix: /tmp/

List of MPLS log files

The log files are as follows:

- HPOvMPLSiSPI_9.10.000_HPOvInstaller.txt
- preInstall_mpls.log
- Pre_Remove_mpls.log
- postInstall_mpls.log
- postRemove_mpls.log

Updating the NNMi Port Number

When you install the iSPI for MPLS, type the same NNMi port numbers that you have specified while installing NNMi. If you want to update the NNMi port number while installing the iSPI for MPLS, follow these steps:

- 1 On the management server, open the `nms-mpls.ports.properties` file from the `%NnmdataDir%\shared\mpls\conf` or `$NnmdataDir/shared/mpls/conf` directory (depending on the type of the management server) with a text editor.
- 2 Update the `Djboss.nnm.port` value.

- 3 On the management server, open the `nms-local.properties` file from the `%NmdataDir%\conf\nnm\props` or `$NmdataDir/conf/nnm/props` directory (depending on the type of the management server) with a text editor.
- 4 Update the `com.hp.ov.nms.spi.mpls.Nnm.port` value in the `nms-local.properties` file.

Updating the Security Mode (HTTP to HTTPS)

After installing NNMi and iSPI for MPLS, if you want modify the security mode from HTTPS to HTTP or HTTP to HTTPS without installing NNMi and iSPI for MPLS again, follow these steps:

- 1 On the management server, open the `nnm.extended.properties` file from the `%NmdataDir%\shared\mpls\conf` or `$NmdataDir/shared/mpls/conf` directory (depending on the type of the management server) with a text editor.
- 2 Update the values to true or false from the following:
 - `com.hp.ov.nms.spi.mpls.spi.isSecure=false`
 - `com.hp.ov.nms.spi.mpls.Nnm.isSecure=false`

If the value is false, the mode of transmission is HTTP.

▶ Always select the same mode of transmission for NNMi and iSPI for MPLS.

Updating the NNMi System Password

If you modify the NNMi system account credentials after installing the iSPI for MPLS, follow these steps to synchronize the change with the iSPI for IP MPLS setup.

- 1 Log on to the NNMi management server.
- 2 Run the following command to copy the NNMi password:

```
encryptmplspasswd.ovpl -c mpls
```

where:

`c` - NNMi jboss to iSPI for MPLS jboss communication

`mpls` (case insensitive)

▶ Only user with root permission can run this script.

- 3 Restart the iSPI for MPLS with the following commands:

- **ovstop -c mplsjoboss**
- **ovstart -c mplsjoboss**

Updating the iSPI for MPLS (Web Service Client Password)

The iSPI for MPLS is configured with Web Service Client Username and Password to communicate with NNMi in the installation process. The user must be added in NNMi with the role of Web Service Client user to use the script to update the password.



Avoid System role for NNMi - iSPI for MPLS communication.

Only user with root permission can run this command.

If you want to update the iSPI for MPLS password, follow these steps:

1 Log on to the NNMi management server.

2 Run the following command:

```
encryptmplpasswd.ovpl -e <mpls> <password>
```

The **encryptmplpasswd.ovpl** command helps you update the iSPI for MPLS password.

3 Restart the iSPI for MPLS with the following commands:

- **ovstop -c mplsjboss**
- **ovstart -c mplsjboss**

4 Installing in a High-Availability Cluster Environment and Application Fail-over

You can install NNMi in a high-availability (HA) environment to achieve redundancy in your monitoring setup. You can install the iSPI for MPLS product in an HA environment where NNMi has been installed.

Prerequisites for installing iSPI for MPLS on HA

Before you begin the installation for HA environment, read the *Configuring HP NNMi Software in a High Availability Cluster* in *NNMi Deployment and Migration Guide* to understand the NNMi HA configuration.

Ensure to meet the following requirements before installing iSPI for MPLS in an HA environment.

- The iSPI for MPLS runs on the NNMi management server.
- The iSPI for MPLS uses the same Postgres instance as NNMi.

Installing the iSPI for HA

- ▶ If NNMi is not installed on HA environment, install NNMi and iSPI for MPLS together before configuring NNMi and iSPI for MPLS on HA environment.

Steps to Install iSPI for MPLS when NNMi is Running on HA

- 1 If NNMi is already configured and running on HA environment, unconfigure NNMi.
 - ▶ For steps to unconfigure NNMi, see *Configuring HP NNMi Software in a High Availability Cluster* in *NNMi Deployment and Migration Guide*.
- 2 Start the iSPI for MPLS installation, (see, [Installing the iSPI for MPLS](#)).
- 3 Configure NNMi and iSPI for MPLS on HA environment. To configure iSPI for MPLS, see [Configuring the iSPI for HA](#) on page 28.

Steps to Uninstall iSPI for MPLS when NNMi is Running on HA

- 1 If NNMi is already configured and running on HA environment, unconfigure iSPI for MPLS.
- 2 Unconfigure NNMi on HA environment.
 - ▶ For steps to configure and unconfigure NNMi, see *Configuring HP NNMi Software in a High Availability Cluster* in *NNMi Deployment and Migration Guide*.
- 3 Uninstall the iSPI for MPLS.

Configuring the iSPI for HA

▶ To configure iSPI for MPLS, first configure the iSPI in primary node and then in the secondary node.

Use the following commands to configure iSPI for MPLS

- Windows:

```
%NnmInstallDir%\misc\nnm\ha\nnmhaconfigure.ovpl NNM -addon MPLS
```

- UNIX:

```
$NnmInstallDir/misc/nnm/ha/nnmhaconfigure.ovpl NNM -addon MPLS
```

▶ To revert to the earlier configuration, revert the iSPI for MPLS from the secondary node and then from the primary node.

Use the following commands to revert to the earlier iSPI for MPLS configuration

- Windows:

```
%NnmInstallDir%\misc\nnm\ha\nnmhaunconfigure.ovpl NNM -addon MPLS
```

- UNIX:

```
$NnmInstallDir/misc/nnm/ha/nnmhaunconfigure.ovpl NNM -addon MPLS
```

5 Getting Started with the iSPI for MPLS

After you complete the installation of the iSPI for MPLS in your NNMi environment, you can start monitoring your network with NNMi and iSPI for MPLS. After installing the iSPI for MPLS, you can start the complete discovery process to view the MPLS-enabled nodes and MPLS objects from the MPLS workspace.

Accessing the iSPI for MPLS

You can monitor the network by using the NNMi and iSPI for MPLS. To start the iSPI for MPLS after the initiation of the first discovery polling cycle, follow these steps:

- 1 Launch the NNMi console.
- 2 Log on to the NNMi console with one of the following user roles:
 - Administrator
 - Operator level 1
 - Operator level 2
 - Guest
- 3 In the Workspace pane, click **MPLS**. The MPLS workspace shows the inventory views of MPLS objects. You also can navigate to the MPLS forms and map views from the workspace.

Starting the MPLS Discovery Process

The MPLS discovery process starts automatically after NNMi discovery process. To start the complete discovery for the iSPI for MPLS, use the following command:

For Windows: `%InstallDir/bin/nmsmplsdisco.ovpl -u <user> -p <password> -all`

For UNIX: `$InstallDir/bin/nmsmplsdisco.ovpl -u <user> -p <password> -all`

Accessing the Online Help

The iSPI for MPLS Help provides the iSPI for MPLS related information. The detailed information in the iSPI for MPLS help is organized into the following sections:

- Help for Operators
- Help for Administrators

To access the iSPI for MPLS help, click **Help -> Help for NNM iSPis ->Help for iSPI for MPLS**. The iSPI for MPLS help appears in the NNMi console only if the iSPI for MPLS installation is successful.

The MPLS Online Help provides you the comprehensive information about the MPLS Inventory, MPLS forms, Incidents, and map views.

Configuration Tasks in HP iSPI for MPLS

You can perform the following configuration tasks after installing the iSPI for MPLS.

- Configure the Polling Frequencies
- Configure the Router Targets
- Configure the VPWS VPN
- Configure the Regional Manager

Accessing the MPLS Reports

The iSPI for MPLS uses the basic capabilities of the HP NNMi iSPI Performance for Metrics (iSPI Performance for Metrics) and Network Performance Server (NPS) to present the MPLS reports.

The iSPI for MPLS introduces the following extension packs:

- MPLS_LSR_Node
- MPLS_LSR_Interface
- L3_VPN_VRF

The extension pack uses data collected by the iSPI for MPLS. Make sure that NPS and iSPI Performance for Metrics is up and running.

To view the MPLS reports, from the NNMi console, click **Actions-> Reporting-Report Menu**. The iSPI Performance for Metrics console appears with the reports.

For more information, see *Help for iSPI for MPLS Reports and Help for NNMi iSPI Performance for Metrics*.

6 Upgrading to the NNM iSPI for MPLS 9.10

Before you start upgrading the MPLS VPN SPI from 7.5x to newer version, make sure that you upgrade NNMi 7.5x version to 9.x version. For upgrading NNMi from the earlier versions, see the *NNMi Deployment Reference Guide*.

License for Upgrading from the Earlier Versions

If you are upgrading from the earlier versions of the MPLS SPI, then you can obtain the iSPI for MPLS, 9.10 upgrade licenses. You can contact HP sales to know about your upgrade license entitlement based on your order number for the earlier versions of the MPLS VPN SPI.

License for Upgrading from the MPLS, Version 7.53 to Version 9.10

To upgrade to the iSPI for MPLS, the Contract Migration is required. The Special Migration SKUs are available from http://support.openview.hp.com/software_updates.jsp. The iSPI for MPLS, 9.10 is password protected product so you have to acquire your technical password migration. You can obtain your password from the following URL http://support.openview.hp.com/software_updates.jsp.

License for Upgrading from the iSPI for MPLS, Version 8.10 to Version 9.10

To upgrade to the iSPI for MPLS, the Contract Migration is *not* required as both the versions use the same LTU's SKU. You only need the media product number. The iSPI for MPLS, 9.10 is password protected product so you have to acquire your technical password migration. You can obtain your password from the following URL http://support.openview.hp.com/software_updates.jsp.

License for Upgrading from the iSPI for MPLS, Version 9.00 to Version 9.10

To upgrade to the iSPI for MPLS, the Contract Migration is *not* required as both the versions use the same LTU's SKU. You only need the media product number. The iSPI for MPLS, 9.10 is password protected product so you have to acquire your technical password migration. You can obtain your password from the following URL http://support.openview.hp.com/software_updates.jsp.

Upgrading from Version 7.53 to Version 9.10

The MPLS VPN SPI, 7.53 is supported on Windows and UNIX 32 bit platform in contrast to the iSPI for MPLS which is supported on 64 bit Windows and UNIX platforms. For more information on supported database, hardware and software requirements, see the *iSPI for MPLS, Support Matrix, 9.10*.

There are no direct steps available for upgrading the MPLS VPN SPI, 7.53 to the iSPI for MPLS, 9.10.



After you migrate the community string configuration from NNM 7.53 installation to NNMi 9.10, make sure that community strings for MPLS nodes are also present in the NNMi communication configuration.

While migrating from MPLS VPN SPI, 7.53 to the iSPI for MPLS, 9.10 version, you can use the data specified in following configuration files:

- Migrate the data specified in the `MplsVpn.cfg` file of MPLS VPN SPI, 7.53. For version 9.x, only `ignoreRT` is supported, all the other values in `MplsVpn.cfg` are not applicable.

Install the iSPI for MPLS 9.10. Make a note of the Route Targets (RTs) specified in `Ignore RT` section of MPLS VPN SPI, 7.53. Add these RTs in `Exclude RT` section of the `MPLS Configuration` workspace of the iSPI for MPLS, 9.10.



Start the VPN computation only after you add and save all the RTs to be excluded from the MPLS Configuration workspace

You can add the RTs in the following ways:

- Add one RT value to be excluded and then, click **Save**. This automatically starts the L3 VPN computation.
- Add all the RT values to be excluded sequentially and then, click **Save**. This automatically starts the L3 VPN computation. This is a preferred option as you have to perform this task only once for the proper computation and grouping of all the VRFs that are already discovered in the network.
- Migrate the data specified in the `MgmtVpn.cfg` file of MPLS VPN SPI, 7.53 to the iSPI for MPLS, 9.10



The iSPI for MPLS, 9.10 does not support Management VPNs feature.

To migrate the data specified in the `MgmtVpn.cfg` file, follow the steps:

- a From the `MgmtVpn.cfg` file, select the RT values with `Active` settings across the `RT-PATTERN`.
 - b Add the selected RT values in the `MPLS Configuration` workspace under the **Exclude RT** tab.
- This automatically starts the L3 VPN computation after you add all the RTs and helps to get the consolidated group of the L3VPNs.
- Use the data specified in the `VpnNames.txt` file of MPLS VPN SPI, 7.53 to the iSPI for MPLS, 9.10.

The MPLS VPN SPI, 7.53 stores the VRF grouping relationships and VPN names in the `VpnNames.txt` file. You can rename the VPNs in the iSPI for MPLS, 9.10 according to the list in the `VpnNames.txt` file from MPLS views. *Mapping of VPNs to relevant VRF groups is done manually.* For more information, see *Help for MPLS, 9.10*.

- To retain the configuration from version 7.53 of NNM iSPI for MPLS, accept each value as it is presented in the `mpls.conf` file. Following are the values stored in the `mpls.conf` file:

— For QA integration

```
FREQUENCY=600
TIMEOUT=100
PINGMIBFREQ=600
PINGMIBTIMEOUT=1
PINGMIBPOLLINTERVAL=60
```


For more information, refer to *Deploy the iSPI for MPLS with the iSPI Performance for Quality Assurance*.

— For RAMS integration

```
HANDLE_RAM_EVENTS=true/false
```

```
RAMSVPN_NAMESYNC=true/false
```



The above parameter values are applicable only if NNM iSPI for MPLS is integrated with RAMS. `HANDLE_RAM_EVENTS` and `RAMSVPN_NAMESYNC` accept boolean values. You can configure the values of these parameters and take appropriate actions in RAMS.

For more information, refer to *Deploying the iSPI for MPLS with Route Analytics Management System*.

— For TE poller configuration

```
TEMANAGER_POLLER_INTERVAL=1m
```

This Maps to "TE polling configuration paramter name" in configuration user interface section and **Polling Frequencies** tab. For more information, refer to *Configure the Polling Frequency* in the *Online Help for MPLS 9.10*.

- If you have to customize `trapd.conf`, then please refer to 'Display Traps from Devices' section in *NNMi deployment reference*.

Upgrading from Version 8.xx to Version 9.10

To upgrade the iSPI for MPLS from version 8.xx to version 9.10, follow these steps:

- Uninstall the 8.xx version of the iSPI for MPLS.
- Install NNMi 9.10.
- Install the iSPI for MPLS 9.10.

Upgrading from Version 9.00 to Version 9.10

You can migrate to version 9.10 without uninstalling 9.00.



(*HP-UX users*): Contact the HP NNMi support *before* you start migrating from version 9.00 to version 9.10

Assuming that, you have successfully installed HP NNMi 9.10, and the MPLS jboss is running, follow these steps:



(*Linux Users*): To migrate NNMi iSPI for MPLS from version 9.00 to version 9.10, you must import the HP public key into the Linux RPM database before installing NNMi 9.10. To do this, point your browser to the following location and follow the instructions:

<https://h20392.www2.hp.com/portal/swdepot/displayProductInfo.do?productNumber=HPLinuxCodeSigning>

1 Stop MPLS jboss using `ovstop -c mplsjoboss`



For successful migration, ensure that the NNMi 9.10 is running properly and MPLS jboss has completely stopped. In case the upgrade fails, the only solution is to install 9.10. This may corrupt the version 9.00 database.

2 Insert the iSPI for MPLS installation media into CD-ROM drive

3 Proceed with the installation steps as mentioned in [Installing the iSPI for MPLS](#) on page 15.

4 Click **Upgrade**

NNM iSPI for MPLS version 9.10 supports automatic migration of configuration data from version 9.00 to version 9.10.

Product Comparison

You can compare the features of the iSPI for MPLS, 9.10 with the earlier versions of the MPLS VPN SPI. This section helps you to understand the product when you are upgrading from the earlier versions.

Comparing the MPLS L3 VPN Features

MPLS L3 VPN Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
Layer 3 VPN MPLS/BGP (RFC 2547 bis) discovery and management.	Yes	Yes	Yes	Yes
All the Provider Edge (PE) routers available in the MPLS inventory.	Yes	Yes	Yes	Yes
Discovery and management of VRF's from all PE's discovered.	Yes	Yes	Yes	Yes
Automatic grouping of the VRFs to form a single VPN.	Yes	Yes	Yes	Yes
Tabular view of PEs and related VRFs.	Yes	Yes	Yes	Yes
Customizing of the system-generated L3VPN names	Yes	Yes	Yes	Yes
Customization of RT inclusion and RT exclusion to form an L3 VPN.	Yes	Yes	Yes	Yes
Fault management of VRFs through incidents and traps.	Yes	Yes	Yes	Yes
CE nodes inventory in the network.	Yes	No	No	No
CE Management: Tabs and incidents.	Yes	No	Yes	Yes
HSRP/VRRP support on the PE/CE interfaces.	Yes	No	No	No
Duplicate IP Address support between the PE-CE link connectivity	Yes	No	Yes	Yes
Graphical views of the service-oriented L3VPNs.	No	No	Yes	Yes
Graphical views of PE-CE relationship in an L3VPN.	Yes	No	Yes	Yes
Cisco Support	Yes	Yes	Yes	Yes
Cisco IOS-XR Support	No	Yes	Yes	Yes

MPLS L3 VPN Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
Juniper J/M/T series routers	Yes	No	Yes	Yes
Juniper E series supported	Yes	No	No	No
Alcatel support	No	No	No	Yes
Redback Ericsson	No	No	No	Yes
Reachability tests between the PE routers through IP SLA between the PE router and corresponding CE router.	Yes	No	Yes	Yes
Reachability tests through PingMib between the PE router and corresponding CE router.	Yes	No	Yes	Yes
VRF-Lite/Shadow Router discovery	Yes	No	No	Yes
Discovery of Management VPNs	Yes	No	No	No
RMTool to support discovery of accurate L3VPNs with RTs configured in Route Maps.	Yes	No	No	No

Comparing the MPLS TE Tunnel Features

MPLS TE Tunnel Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
Discovery & Management of TE Tunnels	Yes	Yes	Yes	Yes
Monitoring the TE Tunnels (status / incidents)	Yes	Yes	Yes	Yes
Inventory of TE Tunnels	Yes	Yes	Yes	Yes
Discovery of TE Tunnel attributes	Yes	Yes	Yes	Yes
Map view of the TE Tunnel path.	Yes	No	Yes	Yes
Tabular view of TE Tunnel path.	Yes	No	Yes	Yes

MPLS TE Tunnel Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
Monitoring the TE Path and RCA.	Yes	No	No	No
Cisco support	Yes	Yes	Yes	Yes
Cisco IOS-XR support	No	Yes	Yes	Yes
Juniper J/M/T series support	Yes	No	Yes	Yes
Juniper E-series support	No	No	No	No
Alcatel support	No	No	No	Yes
Redback Ericsson	No	No	No	No

Comparing the PseudoWire VC Features

MPLS PseudoWire VC Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
Discovery and Management of point-to-point Pseudowires with encapsulation types (VPWS).	No	Yes	Yes	Yes
Discovery and Management of point-to-multipoint Pseudowires (VPLS).	No	Yes	Yes	Yes
Fault management of PWs through management incidents and traps.	No	Yes	Yes	Yes
Discovery and monitoring of the available VPWS VPNs.	No	No	Yes	Yes
Discovery and monitoring of the available VPLS VPNs.	No	No	Yes	Yes
Mapping point-to-point Pseudowires to customers.	No	No	Yes	Yes

Comparing the LSR Features

MPLS LSR Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
Discovery of all MPLS-enabled routers	Yes	Yes	Yes	Yes
Cross launch to TE Tunnels and VRFs configured on a particular device	Yes	Yes	Yes	Yes
Quick identification of MPLS features supported by LSR	No	Yes	Yes	Yes

Comparing the RAMS Features

RAMS Integration Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
Integration with the RAMS appliance to configure VPN names in the RAMS device based on RTs discovered	Yes	No	Yes	Yes
Path Monitoring by using RAMS and L3VPN impact analysis	Yes	No	No	No
Capability to launch LSP paths between the PE routers based on the information stored in the RAMS database	Yes	No	Yes	Yes
RAMS Trap resolution to MPLS-VPN objects	No	No	Yes	Yes

Comparing the iSPI Performance for Metrics Features

iSPI Performance for Metrics Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
L3VPN and VRF availability reports for Layer 3 VPN	Yes	No	Yes	Yes
MPLS traffic metrics (packets, octets, and so on) for LSR node & interfaces	No	No	Yes	Yes

Comparing the MVPN Features

MVPN Features	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
MVPN capability on an L3VPN	No	No	Yes	Yes
Identification of default MDTs	No	No	Yes	Yes
Identification of Data MDT (source and group)	No	No	Yes	Yes
MVPN flow indicated by upstream & downstream tabs	No	No	Yes	Yes
MVPN Tree maps indicating the flow of the multicast traffic	No	No	Yes	Yes
Cross launch menu to Multicast Reverse Path View	No	No	No	Yes

Comparing HA and Application Failover features

Feature	Version 7.xx	Version 8.xx	Version 9.00	Version 9.10
HA	Yes	Yes	Yes	Yes
Application Failover	No	No	Yes	Yes

A Troubleshooting the iSPI for MPLS

This chapter lists the trouble scenarios that you may encounter while installing the iSPI for MPLS and tips to resolve these issues.

Installing the iSPI for MPLS

- Problem:* The iSPI for MPLS installation process stops abruptly.

Solution: The installation process is not able to create and copy the folders. Check the error messages and the available disk space. In addition, check if you have necessary permissions on the management server.
- Problem:* The iSPI for MPLS process appears in the `Failed` state and you are not able to restart the process again.

Solution: Stop and start `ovspmd` (all the processes) again. Check `ovstatus -c` to verify if the state of the process is changed from `FAILED` state to `RUNNING` state.

This is a time consuming process but this is the only workaround available to start the processes.
- Problem:* The extension packs introduced by the iSPI for MPLS fails to start if you install NPS and iSPI Performance for Metrics after installing NNMi and iSPI for MPLS

Solution: Always install NPS and iSPI Performance for Metrics and then install the iSPI for MPLS. If you have installed NNMi and iSPI for MPLS before installing NPS and iSPI Performance for Metrics, remove the `<Extension Pack>.processed` copy from the following location:

On UNIX - `<$NNMDataDir>/shared/perfSpi/datafiles/extension/final` folder.

On Windows - `<%NNMDataDir%>\shared\perfSpi\datafiles\extension\final` folder.

After removing the file, the extension packs are installed automatically
- Problem:* The iSPI for MPLS jboss stops automatically after the start up or after running for some time. You cannot access the MPLS inventory and URL actions. The following log message appears `jbossServer.log` file:

```
[org.jboss.system.server.Server] Shutting down the server,
blockingShutdown: false

[org.jboss.system.server.Server] Server exit(0) called

[org.jboss.system.server.Server] Runtime shutdown hook called, forceHalt:
true
```

Solution: Stop and start the iSPI for MPLS jboss. Run the following commands:

 - Stop the process: `ovstop -c mplsjoboss`
 - Start the process: `ovstart -c mplsjoboss`

Uninstalling the iSPI for MPLS

- *Problem:* Removal process starts but does not complete
Solution: Stop the iSPI for MPLS process and then start uninstalling the iSPI for MPLS again. You can use the command to stop the iSPI for MPLS processes: **ovstop -c mplsjoboss**. Check the status again and start uninstalling the iSPI for MPLS.
- *Problem:* After removing the iSPI for MPLS, the memory of the system is still low.
Solution: Check if the java process is running with the iSPI for MPLS name. Stop and delete these processes manually. These processes increase the memory size.
- *Problem:* After removing the iSPI for MPLS, the status of mplsjoboss appears as Failed.
Solution: Run the following commands:
 - Stop the process: **ovstop -c**
 - Start the process: **ovstart -c**If you check the NNMi status again, mplsjoboss does not appear in the status.
- *Problem:* After you uninstall the iSPI for MPLS, the extension packs introduced by the iSPI for MPLS are not removed. If the iSPI Performance for Metrics is running, the extension packs introduced by the iSPI for MPLS, still appear. Remove the extension packs manually before you start installing the iSPI for MPLS again.
Solution: To remove the extension packs completely, follow these steps:
 - a Remove the extension packs using the `uninstallExtensionPack.ovpl` command:
 - Windows - `%PerfSPIInstallDir%\NNMPerformanceSPI\bin\uninstallExtensionPack.ovpl -p`
 - UNIX - `$PerfSPIInstallDir/NNMPerformanceSPI/bin/uninstallExtensionPack.ovpl -p`For example, use the command to uninstall the extension pack, **uninstallExtensionPack.ovpl -p MPLS_LSR_Interface**.For more information, see *NNMi iSPI Performance for Metrics, 9.10 Installation Guide*.
 - b Manually delete the extension packs introduced by the iSPI for MPLS from the following location:
 - For UNIX - `$NnmDataDir/shared/perfSpi/datafiles/extension/final`.
 - For Windows 2008/ Windows 2003 - `%NnmDataDir%\shared\perfSpi\datafiles\extension\final`.
 - c Stop and Start the processes of NNMi iSPI Performance for Metrics.
- *Problem:* For the non-windows platforms, the mplsjoboss does not start after increasing the heap size to 4GB and above. The message appears as follows:
Could not reserve enough space for object heap.
Solution: From the `/var/opt/OV/shared/mpls/conf/nms-mpls.jvm.properties` file, remove the comment from the `-d64` flag. The Xmx value is set to 4GB or above.

Additional Troubleshooting Information

The following information helps you to troubleshoot the problem you may encounter after installing the iSPI for MPLS

For All Platforms

- *Problem:* The iSPI for MPLS does not discover IPv6-enabled MPLS nodes. The `run.sh` file contains the following line:

```
JAVA_OPTS="$JAVA_OPTS -Djava.net.preferIPv4Stack=true"
```

Solution: Update the `run.sh` file to enable the discovery of the IPv6-enabled MPLS nodes. To update the `run.sh` file, follow these steps:

- a Stop the MPLS processes by using the command: **`ovstop -c mplsjoboss`**.
- b From the `/opt/OV/nonOV/mpls/joboss/bin/` location, open the `run.sh` file.
- c Update the following java opts parameter and change the value of `-Djava.net.preferIPv4Stack=true` to `-Djava.net.preferIPv4Stack=false`.

The updated lines appear as:

```
JAVA_OPTS="$JAVA_OPTS -Djava.net.preferIPv4Stack=false"
```

Restart the MPLS processes by using the command: **`ovstart -c mplsjoboss`**

For Linux Platform

- *Problem:* For the large scale Linux systems, when the iSPI for MPLS and NNMI open a lot processes and files and the file count reaches to a maximum value, the iSPI for MPLS stops working and is in an unusable state.

Solution: Increase the number of open files per process by updating the default max open files value. To increase the value, follow these steps:

- a Update the `limits.conf` file from the `/etc/security/limits.conf` file. Change the value to **2048** from the following:

```
Increase the default max open files for NNMI
```

```
soft nofile 2048
```

```
hard nofile 2048
```

- b Save the updated values.
- c Log out from the system and log on again. This file limit change is only applicable to the new shells.
- d Restart NNMI from the following commands:

```
— ovstop -c
```

```
— ovstart -c
```

This restart of NNMi is required only if you have already installed NNMi.



Perform these tasks before you start installing NNMi as the installer inherits the new file limits.