HP Business Service Management

for the Windows/Linux operating system

Software Version: 9.20

Multi-Tenancy Using BSM – Best Practices

Document Release Date: August 2012 Software Release Date: August 2012



Legal Notices

Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright Notices

© Copyright 2005-2012 Hewlett-Packard Development Company, L.P.

Trademark Notices

Adobe® and Acrobat® are trademarks of Adobe Systems Incorporated. Intel®, Pentium®, and Intel® Xeon® are trademarks of Intel Corporation in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates.

Microsoft®, Windows®, Windows NT®, and Windows® XP are U.S registered trademarks of Microsoft Corporation.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. UNIX® is a registered trademark of The Open Group.

Acknowledgements

This product includes software developed by the Apache Software Foundation (<u>http:///www.apache.org</u>). This product includes software developed by the JDOM Project (<u>http://www.jdom.org</u>).

Documentation Updates

The title page of this document contains the following identifying information:

Software Version number, which indicates the software version.

Document Release Date, which changes each time the document is updated.

Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to: <u>http://h20230.www2.hp.com/selfsolve/manuals</u>

This site requires that you register for an HP Passport and sign-in. To register for an HP Passport ID, go to: <u>http://h20229.www2.hp.com/passport-registration.html</u>

Or click the New users - please register link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

HP Software Support

Visit the HP Software support web site at: <u>http://www.hp.com/go/hpsoftwaresupport</u> The web site provides contact information and details about the products, services, and support that HP Software & Solutions offers. It provides customer self-solve capabilities, and is a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage a support contract
- Look up HP support contracts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

To find more information about access levels, go to: http://h20230.www2.hp.com/new_access_levels.jsp

Table of Contents

Та	ble of	Cont	ents	4
1	Intro	oduc	tion	5
	1.1	Sco	pe and motivation	5
	1.2	What	at is a tenant?	5
	1.3	What	at is multi-tenancy?	5
	1.4	Solu	ution overview	6
	1.5	Use	Cases	8
	1.5.	1	Dashboard	8
	1.5.2	2	uCMDB	8
	1.5.	3	Monitoring	8
2	Step	o-by-	Step Configurations	9
	2.1	Clas	ss model configuration in the central BSM	9
	2.2	Con	figuration changes in the tenant's CMS	11
	2.3	Con	figuration for End User Monitoring	16
	2.4	Con	ifiguration for OMi	17
	2.4.	1	Enriching events which are forwarded from OM	17
	2.4.2	2	Enriching events which are generated from within BSM	19
			Automatically assigning events to user groups	20
			Viewing the Tenant Owner attribute in the Event Console	22
	2.5	Crea	ate Views in BSM	23
	2.6	Crea	ate MyBSM Pages	26
	2.7	Con	ifigure Users and Permissions	26
	2.8	Mul	lti-Tenancy and Other Data Collectors	28

1 Introduction

1.1 Scope and motivation

Multi-tenancy means different things to different people. Different service providers have different multi-tenancy needs (for example SaaS – Software as a Service, MSP – Managed Services Provider, or IaaS – Infrastructure as a Service), and there may be shared or split ownerships between service providers and clients.

The implementation of global system integrators like MSP, and the common use of the BSM platform in a shared services environment, make it necessary to provide multi-tenant capabilities in a shared services platform. The following use cases were identified to demonstrate the multi-tenant capabilities of BSM in a shared service platform.

This document provides the following:

- Definition of multi-tenancy, solution overview, and high level architecture of multi-tenancy. ٠
- Use cases supporting multi-tenancy in BSM.
- Detailed explanations on how to configure BSM to provide multi-tenancy capabilities.

1.2 What is a tenant?

A tenant is a set of people (customers, service providers, or suppliers), whose access to data in support of customer contracts is managed as a collective whole. It is commonly referred to as an organization.

In the world of enterprise systems, a tenant is referred to as a customer receiving organization (CRO). Tenants are managed as part of the customer on-boarding process of the service provider.

For larger customers, a tenant can be defined based on business unit, contract segment, or geography, depending on contract entitlement. For example:

- Acme Manufacturing vs. Acme Sales
- Acme Web Hosting vs. Acme Workplace Services
- Acme North America vs. Acme Europe

Note that a user can be associated with more than one tenant; this is common for service provider personnel, but less common for customer personnel. A tenant is *not* a user group or resource group.

1.3 What is multi-tenancy?

Multi-tenancy refers to a principle in software architecture whereby a single instance of software runs on a logical system and serves multiple client organizations (tenants), thereby increasing resource utilization and reducing operational complexity and cost.

Multi-tenancy is contrasted with a multi-instance architecture, whereby separate software instances (or hardware systems) are set up for different client organizations. Multi-instance architecture increases the costs to clients and support organizations. Supporting multi-tenancy within a single system reduces these costs by leveraging common infrastructure and support models.

The advantages of multi-tenancy are not universally supported within the software industry, and this may be a source of competitive differentiation.

1.4 Solution overview


BSM 9.x does not support multi-tenancy out-of-the-box. This document describes the configuration steps required to enable BSM 9.x to support multi-tenancy use-cases.

The solution is based on the following:

- Tenant Management. Each tenant's data is identified within BSM by a dedicated attribute; this
 is the foundation of the entire solution. In some cases this attribute is automatically enriched,
 but in some cases the MSP administrator must update this attribute manually. This attribute
 identifies the tenant who owns the element, which means that the element is managed under
 the lifecycle of that tenant.
- 2) Data-to-Tenant Relationship. All the elements in BSM CIs, events, views, and so on are related to one (and only one) tenant. Based on this information, data can be filtered in the different BSM applications to show data for each tenant; for example you can filter events or RTSM views based on the tenant attribute.
- 3) Security Management. Using the BSM security model you can set permissions for different resources; BSM allows you to assign different permissions to different user groups. This can be used to define different permissions for different tenants. This security model is managed by the MSP administrator, and will probably be the most significant area requiring administration in the multi-tenancy solution on top of BSM 9.x.

The solution architecture is designed to address the use cases described in the following section. The main concept of the solution architecture is based on a local IT Operations environment for each customer, which is monitored by different monitoring tools (such as SiteScope, OM, BPM), and discovered by DDM. All this information is then sent to a central BSM/CMS platform, and accessed by different tenants.

The diagram below is one example of a deployment scenario; there are many variations to multitenancy but the basic concept will be similar. For example, some of the monitoring products such as BPM or SiteScope can also be leveraged across tenants (using remote monitoring); in this case they are configured and managed by the service provider using the central BSM platform, and the monitored data is accessed through the various BSM applications (Event Console, Service Health and so on).



1.5 Use Cases

The multi-tenancy solution should provide the following capabilities:

1.5.1 Dashboard

- **Different Dashboards for Different Tenants.** Show all IT components managed by the various monitoring tools (OM, SiteScope, BPM, and so on) in separate views for each tenant. This includes Service Health, Event Management, Reports, SLM, etc.
- Integrated Dashboard for the Operations Team. Show integrated views with data from all tenants, to be used by the MSP Operations team.
- Event Correlation. Provide event correlation for each tenant independently.

1.5.2 uCMDB

- **Discovery and Integration**. Provide integration of multiple CMDBs with one CMS system.
- Independent Discovery. Provide discovery and mapping capabilities for each tenant independently.

1.5.3 Monitoring

- **Distributed Monitoring.** Integrate all remote monitoring platforms using a central BSM platform.
- Event Views. Provide different event views for different tenants.
- **Reports.** Provide scheduled reports for different tenants.

2 Step-by-Step Configurations

2.1 Class model configuration in the central BSM

One of the major requirements of this solution is that each CI be associated with a specific tenant. To achieve this, we need to add an attribute to the RTSM class model which will identify the tenant owner.

Note: In UCMDB 9.02, the class model has already been defined to support multi-tenancy. You might want to consider creating the Tenant Owner attribute in BSM the same as in uCMDB 9.02, since it may be supported in a future upgrade, although this is not certain. You should also note that BSM 9.10 is compatible with uCMDB 9.03, which means these attributes will be available out-of-the-box.

If you are using BSM 9.0x, perform the following steps to extend the class model:

- 1) Within BSM, access Admin > RTSM Administration > Modeling > CI Type Manager.
- 2) Select the **Configuration Item** CI type.
- 3) Within the **Attributes** tab, click **Add** to add a new attribute.
- 4) Define the new attribute as follows:

Business Service Management - RTSN		Full Screen View	User: DSS Demo User
🏷 🗸 MyBSM Applications 🗸 Admin 👻 Help	Site Map		
eling > CI Type Manager			
Nodeling 🗾 Data Flow Management Administ			
<u>C</u> I Types ▼ Edit ▼ <u>View ▼ Layout ▼ Operations ▼</u>	37		
CI Types	Dependencies Details Attributes C	ualifiers Icon Attached	I Menu Default Label
CI Types 💌 \star 🗶 🔁 🔡 🌺 🔌	This page enables y 🛃 Add Attribute	1	
Managed Object (10548)			
ActivityLog (0)	€ Advanced		
-@ Asset (0)	Attribute Name: Lonast august	Editable Comparable	Required In
Attachment (0)	ack_cleare Display Name: Tenant Owner		Required
ConfigurationItem (10548)	ack id		
CostCategory (0)	Actual Dele Scope: CMS		
CostCenter (0)	Actual Dele Description:	×	
	Admin State		
- @ Kpi (0)	Allow CI Up	- S	
- 😰 KpiObjective (0)	See BODY_ICC Attribute Type:		
Project (0)	Calculated Primitive Enumeration/List		
	Change Co		
	Change Is		
	Change Sta Value Size: 20		
	CI Type Default Value:		
	City Classificatic		
	Container OK Cancel		
	Context Me	~	
	Country or Dravinage Leasurtry Latring Country or		
Module: CI Type Manager	Jser: Demo 🖉 Server Is Available 😭 🛼 🔯	88M of 247M	1 ?

5) Click **OK** to close the **Add Attribute** dialog box, then click **Save** in the left pane.

🛓 Edit Attribute		×
Details Advanced		
Attribute Name:	TenantOwner	
Display Name:	TenantOwner	
Scope:	CMS	
Description:	The Tenant Owner ID	
Attribute Type:		
Primitive	Enumeration/List	
	string	
Value Size:	32	
Default Value:	32	
berault value.		
		DK Cancel

Note: This is how the Tenant Owner attribute is defined in uCMDB 9.02:

	TenantsUses
Display Name:	TenantsUses
Scope:	CMS 🔻
Description:	The IDs of the Tenants who are associated with the CI
ribute Type:	
Primitive (◯ Enumeration/List
	list of strings
Value Size:	
Value Size: Default Value	
Value Size: - Default Value + X	
Default Value	
Default Value	

2.2 Configuration changes in the tenant's CMS

If your tenant will have discovery capabilities, the DDM probe in the tenant environment should be connected to the tenant's (local) CMS. You can then synchronize the relevant topology from this CMS into the central BSM/CMS.

To do this, you must perform the following configuration changes on each tenant's CMS:

- Repeat the procedure described in section 2.1 on the tenant's CMS. This updates the tenant's class model with the same attribute that you added in the central BSM.
 Although you can assign a default value for the Tenant Owner attribute in the CMS, this does not affect Cls which already exist. To update these Cls you need to perform the next step.
- Create an enrichment rule which will fill the Tenant Owner attribute for each CI in this local CMS. This is necessary so that when you synchronize CIs from the local CMS to the central CMS, the CIs will be associated with the correct tenant.
 - a. In each tenant's CMS, access **Modeling > Enrichment Manager**.

b. Create a new enrichment rule with a meaningful name. Activate the rule, and selectBase the Enrichment on a new Query, as seen in the following images:

ew Enrichment Rule						×		
Rule General Attri	butes							
of the general attribut	ea of the new enrichmar	nt rule.						
Steps								
	Rule Name:	Update Tenant Owner.	Attribute					
Rule General Attributes Rule Base Query	Rule Description:							
Wizard Completion								
	🗹 Rule is Active							
		< <u>B</u> ack	Next >	Enish Cane		Hdp		
ew Enrichment Rule								×
Rule Base Qu	lery							
🔆 🛛 Fill in the informati	on about the base q	uery of the new enric	shment rule.					
Steps	Base	Query Type						
Rule General Attribute								
Rule Base Query	• Ba	se the Enrichment or	a naw query					
Wizard Completion	🗌 🔘 8a	se the Enrichment on	i an existing qu	ery				
	Base	Query Attributes						
	Base	Query Name:	UpdateTena	ant Owner Attrit	etuc			
	Base	Query Description:						
	Base	Query Priority:	Nedur				-	
		aac y many.	- Median					
				_	-	_	_	_
			< <u>B</u> ack	<u>N</u> ext >	Enish	Cancel	He	p

- c. Click Finish.
- d. In Query Mode, select the Configuration Item CI type.

e. Within Enrichment Mode, right-click Configuration Item and select Update Query Node:

Update Tenant Owner Attribut	e				
Enrichment Mode 💌 🦾 🤌	i 🗉 🏠	Mode: 📐	Select	💌 📐 💈	×
			A		
		Configu	1∲ Add Re	elationship	
		er	Update	e Query Node	
			Delete	Relationship/Que	ry Node

f. Select the attribute you want to update; enter its value, and click **Save**:

	Name		Туре		Value
Tenant Owner		string			
Description		string			
Name		string			
Fenant Owner		string		Tenant1	
FenantsUses		list of strings			
Now CI Update		boolean			
Jser Label		string			
Enable Aging		boolean			
Vote		string			
) Value	Tenant1				
Advanced					5
By Attribute	ConfigurationItem		ack_cleared_ti	ime	

- g. Click Save to save the enrichment rule and activate it.
- h. You can validate the enrichment results in IT Universe Manager.
- 3) Modify the Integration TQLs that you will use to synchronize topology from the local CMS to the central CMS, to also synchronize the Tenant Owner attribute:
 - a. On each tenant's CMS, within Modeling Studio > Resource Type access Queries.

b. In each Integration TQL, right-click each of the query nodes and select **Query Node Properties**:

Query De								
î, 🗉) 🔍 🗙 🛃							
24		Location	Room 🗧					
•		0)						
P : 1			Men	nbership (I	0)			
1								
1				0				
18								
0 -				🖥 Query N	lode Prope	arties		
<u>a</u>				🥈 Show El	ement Inst	ances		
- Inc.				Sat Data	- Sources			
< Advar	ced layout settings:							
Query No	le Properties							
	uery Node Properties							
= Е	ables you to add attributes, cardinality, qualit	ifiers and C	l specific c	onditions				
ement nam	e: Root							
	L							
+ X (Advanced layout settings	-		_				
		-		_				
+ 🗙 1	Advanced layout settings	-		-	Criteria			
		+			deRole Is	null		
NOT	Advanced layout settings	+		Node Role	deRole Is	null	00"	
NOT		• •onize:			deRole Is	null	00"	
NOT the att	Advanced layout settings	• •onize:			deRole Is	null	00"	
NOT the att	Advanced layout settings (ribute that you want to synchr ings	ronize:	X		deRole Is	null	00"	
NOT the att	Advanced layout settings (ribute that you want to synchr ings Settings				deRole Is	null	op"	
NOT the att	Advanced layout settings (ribute that you want to synchr ings				deRole Is	null	00"	
NOT the att ayout Set Layout	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more				deRole Is	null	op"	
NOT the att	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for mon Attribute name		ı.		deRole Is	null	op"	
NOT the att	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry				deRole Is	null	00"	
NOT the att ayout Set Layout Set Select the Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for mor Attribute name Reference to the credentials dictionary entry root_iconproperties		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for mor Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout : Select the Calculate 	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for mor Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for mor Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Select the Calculate Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemory Size		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for mor Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Select the Calculate Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemorySize SysObjecttld		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Select the Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemory Size SysObjecttld System		ı.		deRole Is	null	op"	
NOT Avout Set Layout Set Select the Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber SnmpSysName State Store KPI History For Over Time Reports SwapMemorySize SysObjecttld System Tenant Owner		ı.		deRole Is	null	op"	
NOT The att ayout Set Layout Select the Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemory Size SysObjecttId System Tenant Owner Tenant Owner Tenant Owner		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate Calculate Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for mor Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemorySize SysObjecttld System Tenant Owner Tenant Owner Tenant Owner Tenant Uses		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate Calculate Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemorySize SysObjecttld System Tenant Owner Tenant Owner Tenant Uses Test Corr State		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate Calculate Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemorySize SysObjecttld System Tenant Owner Tenant Owner Tenant Uses Test Corr State Test Is New		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate Calculate Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemorySize SysObjecttld System Tenant Owner Tenant Owner Tenant Owner Tenant Uses Test Corr State Test Is New Test State		ı.		deRole Is	null	op"	
NOT the att ayout Set Layout Set Select the Calculate Calculate Calculate	Advanced layout settings (ribute that you want to synchr ings Settings ttributes to be calculated. Click help button for more Attribute name Reference to the credentials dictionary entry root_iconproperties SerialNumber Snmp SysName State Store KPI History For Over Time Reports SwapMemory Size SysObjecttld System Tenant Owner Tenant Owner Tenant Uses Test Corr State Test Is New Test State Track Configuration Changes		1.		deRole Is	null	op"	

- e. Click OK to close the **Layout Settings** dialog, then click OK to close the **Node Properties** dialog.
- f. Repeat the above step b step e for each element in the query, and then click **Save** in the left pane.
- 4) Within the central BSM, define an integration point to the tenant's CMS in order to synchronize CIs into BSM:
 - a. Within the central BSM, access Admin > RTSM Administration > Data Flow Management > Integration Studio.

(Note that you must connect the Data Flow Probe to BSM *before* performing these steps, and configure credentials to CMS in Probe administration. This is done using the Data Flow Probe set up; for details refer to the RTSM Data Flow Management pdf.)

b. Create a new integration point:

E	dit Integration Proper	ties	×
6	>> Edit Integratio	on Properties	
In	tegration Prope	rties	
*	Integration Name	CMS2RTSM	
	Integration Description		
	Adapter	UCMDB 9.x	Ŧ
	ls Integration Activated		
С	onnection Prop	erties	
*	Hostname/IP	UCMDB9VM	
	Port	8080	
	Customer Name	Default Client	
	State(default empty)		
*	Credentials	genericprotocol: admin	•••
	Push Back Ids	Disabled	•
	Probe Name	OBAAPP1	•
		Test connection	
		ОК Саг	icel

- c. Add new jobs; for each job select the Integration TQL for which you configured Layout Settings in step 4 above.
- d. Save the integration point, and perform full synchronization.

e. Within IT Universe Manager, check that you received CIs from the local CMS, and that they contain the Tenant Owner attribute:

🚈 bam9-dpa		Properties History Discovery
ama: bam9-dpa	ID: c415034d70755cf17d53a619f39642a4f	Ci Type: Windows
🗄 🔛 I 👔 I 🛎 🛎 I 🧷	Edit 🎦 Export 🔹	
ongin		5
OsDescription		
OsFamily	windows	
OsVendor		
PrimaryDnsName		
SerialNumber	VMWARE-56 4D FE 33	3 22 AF 07 CD-51 61 3A 49 5C A3 80 6E
SnmpSysName	BSM9-DPS	
SwapMemory Size		
Sys Object Id	13.6.1.4.1.311.1.1.3.1.	2
Tenant Owner	Tenanti 🚽	
Updated By	CMS2RTSM: DS_CMS	2RTSM_Basic Infrastructure Sync 🛛 🚽 🗌
User Label	sqb_emad	-
Vendor		

Note: In your deployment scenario, if each tenant's DDM will be connected directly to the central BSM, you need to employ a different approach to enrich the Tenant Owner attribute in BSM, such as using an Enrichment Rule.

2.3 Configuration for End User Monitoring

You can configure EUM-level permissions for users to restrict access to tenant-specific applications (see section 2.6). However, to separate the applications and application views in RTSM, you must add the **TenantOwner** attribute *manually* for all the Business Applications. This needs to be done once for each Business Application CI; it can be done before or after creating the Business Application configuration in EUM Administration.

- If you prefer to do this before EUM configuration, create the Business Application in Admin > RTSM Administration > Modeling Studio, and fill the TenantOwner attribute with the relevant value. In EUM Administration you will edit the CI and add BPM/RUM configuration.
- If you prefer to do this after EUM configuration, edit the Business Application CI's properties in Admin > RTSM Administration > IT Universe Manager, and fill the TenantOwner attribute with the relevant value. If you will use naming conventions for the Business Applications (such as using tenant name as suffix), you can easily assigning the TenantOwner attribute with an enrichment rule.

Once the application is configured for monitoring, you will use the Custom event template to add the TenantOwner attribute for automatic assignment of events to the respective event consoles (see section 2.4.2).

2.4 Configuration for OMi

To enable each tenant to only see their relevant events, you will assign a custom attribute to events. This custom attribute will be used for filters, and for auto-assignment of event to groups. There are several ways to assign this custom attribute, depending on the event source:

2.4.1 Enriching events which are forwarded from OM

If you cannot set the custom attribute within the OM monitoring policy directly (or the integration policy when using an integration adapter), you can enrich incoming events with tenant information on the OMi server as follows:

- 1. Access Admin > Operations Management > Tune Operations Management > Event Processing Customization.
- 2. Select **Before CI/ETI Resolution**, and add a new script.
- 3. Fill the Groovy script form as specified in the image below. Note that you must add each OM server and each tenant separately. For performance considerations, we recommended doing this in one script. A similar approach can be used for events received via the Integration Adapter, where the **source ci hint** can be used in the **if** statement.

AddTenantOwner - Create Ne	w Script		x
General	General		
Advanced			_
	ID:	3b452c2d-f744-f021-d9fd-1ae3d7fcefe1	-
	Name:	* AddTenantOwner	
	Description:	Add TenantOwner attribute for events which originated from OM servers	
	Script:	Nodelnfo originatedServer = event.getOriginatingServe String serverDnsName = originatedServer.getDnsName if ("omServer1.hp.com".equals(serverDnsName)) tenantOwner = "TenantGroup1"; else if ("omServer2.hp.com".equals(serverDnsName)) tenantOwner = "TenantGroup2"; // else if for each OM server/Tenant info event.addCustomAttribute("TenantOwner", tenantOwn }	
	Active:		•
		<back next=""> Finish Cancel Help</back>	

Here is the basic script:

```
NodeInfo originatedServer = event.getOriginatingServer();

String serverDnsName = originatedServer.getDnsName() ;

if ("omServer1.hp.com".equals(serverDnsName))

tenantOwner = "TenantGroup1";

else if ("omServer2.hp.com".equals(serverDnsName))

tenantOwner = "TenantGroup2";

// else if ... for each OM server/Tenant info

If (tenantOwner != null)

event.addCustomAttribute("TenantOwner", tenantOwner)

}

}
```

- 4. Click Next.
- 5. You can specify additional elements for your script in the **Advanced Tab** (for example, you can add an external jar which will be used by the script or events filter), or click **Finish**.

2.4.2 Enriching events which are generated from within BSM

Some events are generated from within BSM, such as alert actions, health indicator (HI) status changes, or events from SiteScope. For these events you must add the custom attribute in the event template, as described in the following section.

(This example is for BPM Alerts, but the procedure is similar for other events generated from within BSM.)

1. Within Admin > End User Management > Alerts, click BPM Transaction Templates:



2. Select the **BPM Trans Alert Default** template (marked with the Default icon), and click **Duplicate** selected template:

BPM Transaction Template Re	eposito
Templates	
* 🖬 🖻 💥	ľ
👸 BPM Trans Alert Default	

3. Edit the duplicated template, and rename the template name to be unique for a tenant.

4. In the **Custom Attributes** tab, add a new key. The key name should be **TenantOwner** (as in the Groovy script), and the value should be the tenant name:

M Trans Alert Default	(1)	
<u>ه</u>		
Properties		
* Template name	BPM Trans Aler	t template for Tenant1
Set the selected te	mplate to be the defau	it template
General Custom	Attributes	
* - 🗙		
* • 👗 Na	me	Value
· · · ·	me	Value < <transaction name="">></transaction>
Na	me	

- 5. Save your changes.
- 6. When you create a BPM transaction alert on a tenant's business application, make sure you select the correct event template:

0000	
Definition Details	
when trigger conditions occur <u>even once.</u> Actions Generate Event with <u>BPM Trans Alert template for Tenant1</u> template and <u>End User event:Critical</u> Event T Notification Frequency Send start for guarantic interpreted economics	ype Indicator
Send alert for every triggered occurrence	-

2.4.3 Automatically assigning events to user groups

As part of the solution, role-based access will be used to configure and provide access permissions to RTSM, Service Health, OMi and EUM for the respective tenants; for details see section 2.6. Events which are assigned to these groups/users contain associated permissions; events which are not assigned to them are not displayed.

Perform the following steps to automatically assign events to user groups based on the TenantOwner attribute:

- Within Admin > Operations Management > Tune Operations Management > User Group Assignments, create a new assignment rule.
- 2. Create a new event filter by clicking **Browse... > New Event Filter**.
- 3. Provide a meaningful name for the filter.

 In the Additional Event Properties tab, mark the Custom Attribute checkbox. Add TenantOwner as the attribute name, and enter the tenant name as its value (as you did in the Groovy script and event templates):

Filter Configuration		×
Filter Display Name: 🧍 Filter Description:	E Tenant1 events	
General Dates	Additional Event Properties	
Application:	equals 🗸	
Object:	equals v	≣
Key:	equals 🗸	
🔲 Original Data:	equals 🗸	
CI Type:	derived from 💌	
Solution:	equals 🔻	
Custom Attribut	te: TenantOwner equals V Tenant1	
		-
	OK Advanced Mode Cancel He	p

- 5. Click **OK**, and select your event filter.
- 6. In the assignment rule, select a user group or user that represents the tenant (creating user groups is explained in section 2.6):

Tenant1 - Create	New Event Assignment Rule	×
Filter: 🔹	Tenant1 events	
User Group: 🜸	Tenant1	·
Description:	Automatically assign Tenant1 events to the relevant user group	
		-
(≉) Required fie	ld	
	OK Cancel Help	

7. Click **OK**, and save your rule.

2.4.4 Viewing the Tenant Owner attribute in the Event Console

To enable a super-admin who is working across tenants to see the **Tenant Owner** event attribute as a column in the Event Console, configure the following infrastructure setting:

- 1. Within Admin > Platform Administration > Infrastructure Settings, select Applications: Operations Management.
- 2. In the section **Operations Management Custom Attribute Settings**, edit the setting **Available Custom Attributes.**
- 3. Add a semicolon (;), and then type **TenantOwner**. Save your changes.

You can then add a column that will show the tenant owner attribute in the Events Console.

You can also create Event Browser filters to only view events from a specific tenant. You can reuse the same filters you created in section 2.4.3.

A useful filter for the super-admin can be to show all events whose tenant owner attribute is empty.


2.5 Create Views in BSM

Use the following procedure to create different pattern-based views for different tenants, and to add conditions to the CITs in each view to collect data relevant to the tenants. In this procedure, the TenantOwner attribute is used to identify and limit the data relevant to the tenants, and user level permissions are configured for the respective tenants.

1. Within Admin > RTSM Administration > Modeling Studio, create a folder for each tenant. This will hold all the views belonging to that tenant and make it easy to manage the views.

Modeling > Modeling Studio	
Modeling Data Flow Management Administra	ation
<u>R</u> esource ▼ <u>E</u> dit ▼ <u>M</u> ew ▼ Layout ▼ <u>O</u> perations ▼	Editor It
* New - 🖺 🛞 🦻 🤁 🗖	
Resources CI selector CI Types Resource Type: Resource Type: New Folder Application Business Business Business Business Business Business Business Business Business Business Busi	 Image: A state of the state of

2. Right-click a view, and select **Save As** to create a view for a specific tenant.



3. Give the new view a relevant name and save it in the correct folder. Make sure you select the **New query** checkbox.

🕌 Save P	Pattern View 🛛 🕹
—	Save Pattern View Choose the View name, and path (Folder) in order save to it. You may also check the New Query in order to save the base query with a different name.
	e: End User Monitors(Tenant1)
	HP-SHR HPDemo IBM Web Sphere MQ Integrations J2EE Local impact views Locations Mainframe Monitors Network Operations Management Perspectives SAP Service Desk SLM SOA Storage Tenant1 Virtualization
<u>F</u> ind:	
	OK Cancel

4. Select the cloned view, and edit the node which will have tenant owner information for filtering. In this example, we will edit the Business Application CI (see section 2.3):

🛄 End User Monitors(Tenant1) 🗙					
🙀 View 🔒 Report					
Query Definition					
»	-	<u>7</u>	Query Node Properties		
@			Show Element Instances		
			Set Data Sources		
		9	Change Element Type		
	ä	•	Add Related Query Node		
		¶∳ ¢	Add Relationship		
	<u>e</u>	4	Add Join Relationship		
<u> </u>	2		Add Calculated Relationship		
*		2 ×	Add Compound Relationship	Dalata	
		~	Delete Set Element Invisible	Delete	

 Add a new property condition; select the TenantOwner attribute, and enter the relevant value. Do not harm the logic of the existing condition (if it exists); if necessary add parentheses to maintain the existing condition:

Query Node Properties						2
Query Node Propertie		d CI specific conditions				
Element name: BusinessApplication					Visible 🗸	Include subtypes
				A	attribute Cardinality Qua	lifier Identity
🕂 🗙 🏫 🤍 🔍 🛛 Advanced lay	/out settings					
NOT (Criteria)	And/Or
		Monitored E	y Contains "BPM"			OR
		Monitored B	y Contains "RUM"	-)	AND
		Tenant Own	er Equal "Tenant1"			•
Attribute name: Tenant Owner - (string)	Operator:	Parameterize				
Tenant Owner - (string)	Equal		Tenanti			

- 6. Click **OK.**
- 7. When you finish filtering the query nodes, click **Preview** to validate the view results.
- 8. When you finish validating, click Save.

Note: You might want to create a view which shows all the CIs that do not have the TenantOwner attribute defined as expected, or that are connected to such CIs. Such a view is very useful for the super-admin.


2.6 Create MyBSM Pages

You can create different MyBSM pages for different tenants. These pages can be filtered to specific views in order to differentiate tenants' workflows and provide each tenant with specific Dashboards. You can also configure permissions for each page, so users will not be able to modify the pages.

Components which contain a view selector are only populated with the views that a user has permissions to access.

You can also create new URL-based components in MyBSM, for example using a tenant's knowledge base portal. You can then assign permissions for these components (see section 2.7).

- 1. Within MyBSM, create a new page or open an existing page and save it with a new name.
- 2. Build your page by adding the relevant components.
- 3. Click **Filter** on a Service Health, SLM or EUM component.



- 4. Select the relevant filter criteria (view, SLAs or Business Applications) and click **OK**.
- 5. Click Save.

For more information on working with MyBSM, refer to the MyBSM part of the BSM User Guide pdf.

2.7 Configure Users and Permissions

Use the following procedure to define group-level role-based permissions. You will use user groups to identify tenants and distinguish between users of each tenant. By defining permissions on the user group level, you avoid managing permissions on the user level. Moreover, when a new user is added to a group, it inherits permissions from the group. If a user belongs to two groups, the user gains access to events and views of two tenants.

1. Access Admin > Platform Administration > Users and Permissions > User Management.

2. For each tenant, create a group:



- 3. Edit permissions for each group you create, as follows:
 - a. Select the group.
 - b. Select the Permissions tab; click Apply Permissions after each modification.
 - c. Select the **End User Management** context, and assign operations for each element (for example, you can grant View permissions for the tenant's applications only:

enant1		
End User Management	Operation Grant Change Image View Image Delete Image Execute Image Full Control Image Mouse-over the operation name resource.	me

d. Select the **Operations Management** context. Make sure that **Events not assigned to user** is not selected, and **Events assigned to user** is selected. You can also set permissions on tools, actions and other administration tasks.

- e. Select the **RTSM** context and assign View permissions to the specific views you created for this tenant. Make sure other tenants' views are not selected. You will probably want to de-select the out-of-the-box views for this tenant , they are Pattern views which are not filtered for specific tenant owner.
- f. Select the **Service Health** context and assign permissions to MyBSM pages for this tenant.
- g. If you created SLAs for this tenant, select the **Service Level Management** context and assign permissions for these SLAs.
- h. If you create custom, trend or service reports for this tenant, select the **User Defined Reports** context and assign permissions for each category for this tenant.

For more details on users and permissions, refer to the BSM *Platform Administration* pdf.

2.8 Multi-Tenancy and Other Data Collectors

Some data collectors support multi-tenancy more easily than others:

- 1) **BPM**. BSM can handle multiple BPM agents, which means that you can have different BPM agents for different tenants. This allows fully segregation between tenants.
- 2) **RUM.** BSM can handle multiple RUM engines and each engine can handle multiple RUM probes. This allows fully segregation between tenants.
- 3) **SiteScope.** BSM can handle multiple SiteScope instances, so you can have different SiteScope instances for different tenants. Since SiteScope creates topology in RTSM, you can also use the RoutingDomain attribute to segregate the topology that each SiteScope creates. You can populate the TenantOwner attribute using enrichment, or you can use the SiteScope Profile CI in your enrichment.
- 4) **Diagnostics.** Only one Diagnostics server/commander can be connected to BSM. You can connect multiple Diagnostics probes to the server/commander, but the data and topology that are sent into BSM will not have any tenant information; you must assign topology and data to specific tenants manually. You can assign permissions on the Application within User Management, in the context **Transaction Management**.
- 5) **NNMi.** Only one NNMi server can be connected to BSM. Future versions of NNMi will enable multi-tenancy, but currently you must manually assign the topology to tenants (or using enrichment, for example based on IP address ranges). This is also true for events with more complicated Groovy script.
- 6) **BSM Connector/IA.** BSM can work with multiple connectors, which means you can have a different connector for each tenant. You can also customize topology, and include the TenantOwner attribute in the topology sent by the connector. You can also customize events and include the TenantOwner attribute in the event itself.