

Peregrine

# Network Discovery

---

## Preparing for Installation

Version 5.1.1

Copyright © 2003 Peregrine Systems, Inc. or its subsidiaries. All rights reserved.

Information contained in this document is proprietary to Peregrine Systems, Incorporated, and may be used or disclosed only with written permission from Peregrine Systems, Inc. This book, or any part thereof, may not be reproduced without the prior written permission of Peregrine Systems, Inc. This document refers to numerous products by their trade names. In most, if not all, cases these designations are claimed as Trademarks or Registered Trademarks by their respective companies.

Peregrine Systems® and Network Discovery® are registered trademarks of Peregrine Systems, Inc. or its subsidiaries. Microsoft, Windows, Windows NT, Windows 2000, and other names of Microsoft products referenced herein are trademarks or registered trademarks of Microsoft Corporation. DB2 is a registered trademark of International Business Machines Corp.

This document and the related software described in this manual are supplied under license or nondisclosure agreement and may be used or copied only in accordance with the terms of the agreement. The information in this document is subject to change without notice and does not represent a commitment on the part of Peregrine Systems, Inc. Contact Peregrine Systems, Inc., Customer Support to verify the date of the latest version of this document.

The names of companies and individuals used in the sample database and in examples in the manuals are fictitious and are intended to illustrate the use of the software. Any resemblance to actual companies or individuals, whether past or present, is purely coincidental.

If you need technical support for this product, or would like to request documentation for a product for which you are licensed, contact Peregrine Systems, Inc. Customer Support by email at [support@peregrine.com](mailto:support@peregrine.com).

If you have comments or suggestions about this documentation, contact Peregrine Systems, Inc. Technical Publications by email at [doc\\_comments@peregrine.com](mailto:doc_comments@peregrine.com).

This edition of the document applies to version 5.1.1 of the licensed program.

Peregrine Systems, Inc.  
3611 Valley Centre Drive San Diego, CA 92130  
Tel 800.638.5231 or 858.481.5000  
Fax 858.481.1751  
[www.peregrine.com](http://www.peregrine.com)



# Contents

---

|                  |   |           |
|------------------|---|-----------|
| <b>Chapter 1</b> | <b>Welcome to Network Discovery . . . . .</b>   | <b>5</b>  |
|                  | About Network Discovery . . . . .   | 6         |
|                  | Peregrine Desktop Inventory can contribute data to Network Discovery . . . . .                    | 6         |
|                  | Peregrine Express Inventory (the WMI collector) can contribute data to Network Discovery. . . . . | 6         |
|                  | Why it's important to prepare . . . . .   | 6         |
|                  | Start by collecting information about your network . . . . .                                      | 7         |
| <br>             |   |           |
| <b>Chapter 2</b> | <b>Pre-setup Questionnaire . . . . .</b>  | <b>9</b>  |
|                  | Your contact information . . . . .  | 9         |
|                  | Describe your network's node and subnet setup. . . . .  | 10        |
|                  | Enter the Peregrine appliance network information . . . . .                                       | 10        |
|                  | Peregrine Systems Customer Support access . . . . .   | 11        |
|                  | List IPv4 ranges for Network Discovery to discover . . . . .                                      | 11        |
|                  | List IPv4 ranges for Network Discovery to avoid . . . . .   | 12        |
|                  | List the community strings of your network's devices . . . . .                                    | 12        |
|                  | Enter TCP/IP configuration . . . . .  | 13        |
|                  | What server will you use for the Peregrine appliance? . . . . .                                   | 14        |
|                  | Send the questionnaire . . . . .  | 15        |
| <br>             |   |           |
| <b>Chapter 3</b> | <b>Prepare the network . . . . .</b>  | <b>17</b> |
|                  | Turn on SNMP management in all routers and core switches . . . . .                                | 18        |
|                  | Set DHCP lease time . . . . .   | 18        |
|                  | (Optional) Turn on SNMP management in other devices. . . . .                                      | 19        |
|                  | About community strings . . . . .   | 19        |

|   |        |
|---|--------|
| Give the Peregrine appliance IP address to all devices using directed community strings . . . . . | 19     |
| (Optional) Adjust bridge aging . . . . .  | 20     |
| Plan the device and port to which the Peregrine appliance will be attached . . .                  | 20     |
| Choose how to receive Peregrine Systems Customer Support . . . . .                                | 21     |
| Through Internet access. . . . .  | 21     |
| Virtual Private Network over the Internet . . . . .   | 22     |
| By modem and dedicated telephone line. . . . .  | 22     |
| Through a Remote Access Server (RAS) . . . . .  | 22     |
| Enable firewall ports . . . . .   | 22     |
| Check Cisco devices . . . . .   | 24     |
| (Optional) Enable UDP port forwarding on routers . . . . .  | 25     |
| Check Committed Information Rate (CIR) values . . . . .   | 26     |
| Check the server that will be the Network Discovery appliance . . . . .                           | 26     |
| IBM Hardware . . . . .  | 26     |
| Dell Hardware. . . . .  | 29     |
| Check the management workstation. . . . .   | 34     |
| <br>Index. . . . .  | <br>35 |

# 1 Welcome to Network Discovery

## CHAPTER

Thank you for using Network Discovery. This book is intended for the Network Discovery Administrator, the person who will have the most control over the setup and operation of Network Discovery.

This information in *Preparing for Installation* is critical to your success with Network Discovery. Your sales representative may have given it to you as a separate pre-purchase handout; or you may be seeing it for the first time as the first three chapters of the *Network Discovery Setup Guide*. The information is exactly the same. If you have seen the information before and have already done the preparation, you can go to the *Network Discovery Setup Guide*. If you are seeing this information for the first time, let's get started.

---

**Important:** If you are migrating from InfraTools Network Discovery (IND) 4.2 or 4.3, see chapter *11 To Migrate from InfraTools Network Discovery or from Xanadu* on page 131 of the *Network Discovery Setup Guide*. Instructions for upgrading from Network Discovery 5.0, 5.0.1, 5.0.2, or 5.1 are in the 5.1.1 *Release Notes*.

---

# About Network Discovery

Network Discovery is a real-time web-based network manager. When integrated into your network, Network Discovery will discover and monitor all SNMP-managed devices in your network. You will use Network Discovery to find, diagnose and solve network problems.

## Peregrine Desktop Inventory can contribute data to Network Discovery

Peregrine Desktop Inventory (PDI) scanners can be scheduled from Network Discovery and scan files can be added to a shared directory on the Peregrine appliance, so the scanned devices will appear in the Network Discovery database, and on the Network Map.

For more information on setting up PDI to contribute data to Network Discovery, see *Using Network Discovery with Desktop Inventory*.

## Peregrine Express Inventory (the WMI collector) can contribute data to Network Discovery

ServiceCenter's WMI collector gathers information about Windows workstations using Windows Management Instrumentation (WMI). This WMI information can be added to the Network Discovery database.

For information on setting up and using the Express Inventory (WMI) collector, see your ServiceCenter Essentials documentation.

## Why it's important to prepare

Setting up Network Discovery is quick and easy, provided you properly prepare your network, and use the specified equipment for the Peregrine appliance and the management workstation.

To operate correctly, Network Discovery needs a constant supply of accurate data. To ensure that Network Discovery knows where and how to collect that data, you must do a little preliminary work. You only have to do this once.

The complete physical connectivity of your network can only be portrayed accurately when:

- all community strings are provided to Network Discovery
- all network connectivity devices are SNMP managed
- no network devices use proxy ARPing
- no critical entries appear in the Network Exceptions report

If devices do not conform to the standards or fail to respond correctly and consistently to SNMP polls, Network Discovery may not be able to create an accurate inventory.

## Start by collecting information about your network

The next chapter is a questionnaire designed to help you gather information about your network.

**Note:** If you wish, you may fill in the questionnaire and send it to Peregrine customer support. They can review your information and provide feedback on how you set up Network Discovery.

If you have already filled out this form and sent it in to Peregrine customer support, collecting all the information is done. Keep the completed questionnaire handy.

The questionnaire is designed to make the setup and use of Network Discovery as smooth as possible. Please answer all questions. Peregrine Systems recognizes that some information may be considered secure or private, but providing the information will allow us to create the optimal inventory and management environment. If you need help filling out the questionnaire, please contact your Peregrine or OEM/VAR (Original Equipment Manufacturer or Value Added Reseller) sales representative or contact Peregrine Systems Inc.

Current details of local Peregrine customer support offices are available through Peregrine's CenterPoint Web site at <http://support.peregrine.com>.

You can obtain a copy of the questionnaire:

- in a copy of *Preparing for Installation* from your OEM/VAR or Peregrine account representative

- by downloading an Adobe Acrobat PDF copy of *Preparing for Installation* from the CenterPoint web site at [support.peregrine.com](http://support.peregrine.com).
- by printing or photocopying the next chapter

When you have completed the questionnaire, send it to Peregrine Systems Inc. by e-mail, mail or by fax. To find the mailing address or fax number of the Peregrine office in your region, contact your OEM/VAR or check <http://support.peregrine.com>.



# 2 Pre-setup Questionnaire

CHAPTER

## Your contact information

Your Name

Organization

Address

Telephone

E-mail

Fax

---

---

---

---

---

---

---

---

---

---

## Describe your network's node and subnet setup

Enter the following information to help determine the scale of your network.

**Note:** Network Discovery defines a node as any network device with at least one MAC address. A managed device is a network device that has an SNMP agent and MIB so it can respond to SNMP requests.

How many nodes do you believe are active on your network? \_\_\_\_\_

Are there any remote sites to be managed? Yes \_\_\_\_\_ No \_\_\_\_\_

If yes, approximately how many managed nodes are at remote sites?  
\_\_\_\_\_

Is your network divided into subnets? Yes \_\_\_\_\_ No \_\_\_\_\_

If yes, how many subnets does your network contain? \_\_\_\_\_

## Enter the Peregrine appliance network information

Enter the information that you will assign to the Peregrine appliance at startup.

**Note:** You will give this IPv4 address to new users so they can log in easily.

**Note:** If your network uses DHCP, ensure that the IP address for the Peregrine appliance is static.

Planned IPv4 address for your Peregrine appliance \_\_\_\_\_

Subnet mask address \_\_\_\_\_

Default gateway IP address \_\_\_\_\_

## Peregrine Systems Customer Support access

Information on the options you have for receiving Customer Support is in *Choose how to receive Peregrine Systems Customer Support* on page 21.

If you will use a modem and a dedicated analog telephone line, enter the number of the telephone line.

Telephone number for access by  
Peregrine Systems Customer Support

---

## List IPv4 ranges for Network Discovery to discover

Network Discovery uses IPv4 ranges to discover the devices in your network. It works best when you give it a broad idea of where the devices in your network are—but exclude ranges where you know there are no devices.

**Note:** While you are making a list of devices in your networks, indicate bridges, routers, switches, and concentrators, so that you can identify them easily.

Please add the IPv4 ranges you want Network Discovery to discover in your network. For example, to discover an entire class C subnet with subnet mask 255.255.255.0 enter an IP range from xxx.xxx.xxx.0 to xxx.xxx.xxx.255 such as 172.17.1.0. to 172.17.1.255. If you require more space, please attach additional sheets as needed.

---

**Important:** When you assign IPv4 ranges, be aware of the size of the ranges you are requesting. If you request a large range of IPv4 addresses to sweep, it can take several hours or days.

---

|              | From | To |
|--------------|------|----|
| IPv4 range 1 |      |    |
| IPv4 range 2 |      |    |
| IPv4 range 3 |      |    |
| IPv4 range 4 |      |    |

|              | From | To |
|--------------|------|----|
| IPv4 range 5 |      |    |
| IPv4 range 6 |      |    |

## List IPv4 ranges for Network Discovery to avoid

If there are subsets of the above IPv4 ranges that you do not want Network Discovery to discover, enter them here.

---

**Important:** You do not need to enter ranges outside the ranges you have specified. Network Discovery does not discover ranges unless you specify them.

---

|              | From | To |
|--------------|------|----|
| IPv4 range 1 |      |    |
| IPv4 range 2 |      |    |
| IPv4 range 3 |      |    |
| IPv4 range 4 |      |    |

## List the community strings of your network's devices

For an explanation of community strings, see *About community strings* on page 19.

This is a list of non-directed community strings. Directed community strings are covered later.

Does Network Discovery need to know the write string?

- No. Network Discovery will operate without write strings. However, if you do give Network Discovery the write strings, the owner of an Administrator account will be able to manage the device from the Network Discovery interface.

|                  |                               | Rights granted |       |
|------------------|-------------------------------|----------------|-------|
| Community string | Associated device /IPv4 range | Read           | Write |
|                  |                               |                |       |
|                  |                               |                |       |
|                  |                               |                |       |
|                  |                               |                |       |
|                  |                               |                |       |
|                  |                               |                |       |

## Enter TCP/IP configuration

The Peregrine appliance must have its own static IP address, but it can manage devices with either static or dynamic IP addresses. Please enter the following information to show how the devices on your network receive IP addresses.

Are TCP/IP addresses static or dynamic?

Static \_\_\_\_\_ Dynamic \_\_\_\_\_

If dynamic, enter the following:

— The IPv4 address(es) of Dynamic Host Configuration Protocol (DHCP) server(s)

\_\_\_\_\_

\_\_\_\_\_

— The DHCP IPv4 address lease time (Peregrine Systems recommends a lease time of at least 7 days.)

\_\_\_\_\_

Is SNMP management enabled on the DHCP server?

Yes \_\_\_\_\_ No \_\_\_\_\_

**Tip:** Enable SNMP management on the DHCP server so that Network Discovery can poll the DHCP server ARP cache for the current IP and MAC address pair information of the devices on your network.

**Note:** Please list the IP addresses of any routers you want Network Discovery to monitor, that do not have SNMP management enabled now and will not have management enabled in the future (for example, a router controlled by an Internet Service Provider).

Unmanaged router number 1 \_\_\_\_\_

Unmanaged router number 2 \_\_\_\_\_

Unmanaged router number 3 \_\_\_\_\_

## What server will you use for the Peregrine appliance?

Please check one (for more information, see *Check the server that will be the Network Discovery appliance* on page 26):

### IBM xSeries 335

Small - 2GB, 1 CPU \_\_\_\_\_

Large - 4GB, 2 CPU \_\_\_\_\_

### IBM xSeries 330

Small - 1GB, 1 CPU \_\_\_\_\_

Large - 2GB, 2 CPU \_\_\_\_\_

### Dell 1750 Servers

Small - 2GB, 1 CPU \_\_\_\_\_

Large - 4GB, 2 CPU \_\_\_\_\_

### Dell 1650 Servers

Small - 1GB, 1 CPU \_\_\_\_\_

Large - 2GB, 2 CPU \_\_\_\_\_

## Send the questionnaire

When you have completed the questionnaire, send it to Peregrine Systems Inc. by e-mail, mail or by fax. To find the mailing address or fax number of the Peregrine office in your region, contact your OEM/VAR or check <http://support.peregrine.com>.

Current details of local Peregrine Systems Customer Support offices are available through Peregrine's CenterPoint Web site at <http://support.peregrine.com>.





# 3 Prepare the network

## CHAPTER

Topics in this chapter include:

- *Turn on SNMP management in all routers and core switches* on page 18
- *Set DHCP lease time* on page 18
- *(Optional) Turn on SNMP management in other devices* on page 19
- *About community strings* on page 19
- *Give the Peregrine appliance IP address to all devices using directed community strings* on page 19
- *(Optional) Adjust bridge aging* on page 20
- *Plan the device and port to which the Peregrine appliance will be attached* on page 20
- *Choose how to receive Peregrine Systems Customer Support* on page 21
- *Enable firewall ports* on page 22
- *Check Cisco devices* on page 24
- *(Optional) Enable UDP port forwarding on routers* on page 25
- *Check Committed Information Rate (CIR) values* on page 26
- *Check the server that will be the Network Discovery appliance* on page 26
- *Check the management workstation* on page 34

## Turn on SNMP management in all routers and core switches

Depending on the device, this may be a case of enabling an existing SNMP agent or setting up an SNMP agent.

You may also turn on SNMP management in other devices. The more managed devices in your network, the better. However, enable switches and routers first.

**Note:** If you use HSRP (Hot Standby Routing Protocol) in your network, ensure you turn on SNMP management in all the affected devices.

What if you don't turn on SNMP management in your switches and routers?

- Network Discovery will appear to work, but you'll eventually notice that it is working poorly. Once Network Discovery is up and running, the Exceptions reports can advise you of problems. Much of the information that Network Discovery collects comes from the SNMP MIB of devices in your network, so it is crucial that you enable SNMP management.

How do you turn on SNMP management?

- The exact procedure is different for every device. Consult the documentation that came with your switch or router.

**Note:** When you turn on SNMP management in a device, you often assign a community string. If you assign a new string later, be sure you give the community string to the Peregrine appliance. For more information, see *About community strings* on page 19.

## Set DHCP lease time

If you use DHCP (Dynamic Host Configuration Protocol) in your network, set the IP address lease time to at least 7 days and turn on SNMP management on the DHCP servers.

## (Optional) Turn on SNMP management in other devices

Your decision to turn on SNMP management in your remaining switches, hubs, servers and workstations depends on the results you expect from Network Discovery. For example, in many networks, monitoring the performance of workstations is not important.

### About community strings

A community string is like a password. A device uses a community string to protect its SNMP MIB—and it's the data from the SNMP MIB that Network Discovery relies on. Network Discovery must know at least one of a device's passwords to collect data from that device. If you do not give Network Discovery a device's community string, Network Discovery will behave as though the device does not have SNMP management turned on. Network Discovery will appear to work, but you'll eventually notice that it is working poorly. Once Network Discovery is up and running, the Exceptions reports can advise you of problems.

**Note:** Community strings are case-sensitive. “Public” and “public” are two different strings.

#### Directed community strings

Directed community strings give devices another layer of protection: a list of IP addresses of approved devices. When Network Discovery tries to get information from a device with a directed community string, the device asks not only “What's the password?” but also “Are you on the list?”

## Give the Peregrine appliance IP address to all devices using directed community strings

When directed community strings are used, it is not enough to give Network Discovery access to the device. You must also configure the device to recognize the Peregrine appliance. You must put it on the list of approved devices.

What happens if a device with directed community strings is not configured with the IP address of the Peregrine appliance?

- Network Discovery will behave as though the device does not have SNMP management turned on. Network Discovery will appear to work, but you'll eventually notice that it is working poorly. Once Network Discovery is up and running, the Exceptions reports can advise you of problems.

## (Optional) Adjust bridge aging

To improve the reliability and speed of Network Discovery, adjust bridge aging on your bridges, routers, switches, and concentrators. Turn bridge aging on, and set the bridge aging interval to 2-6 hours. Smaller networks can use shorter intervals; larger networks will need longer intervals. Network Discovery's Exceptions reports can tell you which devices should have their bridge aging adjusted.

## Plan the device and port to which the Peregrine appliance will be attached

Plan to attach the Peregrine appliance:

- behind your corporate firewall
- to an Ethernet port on a device close to the top of your network. Network Discovery works best if the port is SNMP managed.

**Note:** Attach a management workstation to the same device as the Peregrine appliance. This will make the setup process smoother. It also ensure that the management workstation does not become isolated from Network Discovery in the event of device failures.

# Choose how to receive Peregrine Systems Customer Support

Options for allowing Customer Support access (in the order in which Peregrine Systems recommends them) are as follows:

- through Internet access
- through a Virtual Private Network over Internet
- by a modem and a dedicated analog telephone line
- through a Remote Access Server (RAS)

## Through Internet access

For you to have Customer Support by means of the Internet you must enable certain ports in the corporate firewall. Peregrine Systems Customer Support requires access for the following IP address: 209.167.240.9 (sprocket.loran.com).

**Table 3-1: Firewall ports to enable for Customer Support**

| Used for   | Port     | Note |
|--|----------|------|
| Secure Shell (SSH)   | 22/tcp   |      |
| HTTP   | 80/tcp   |      |
| MIB browser  | 8100/tcp |      |
| Network Map  | 8101/tcp |      |
| Network Map proxy  | 8102/tcp | 1,2  |
| MIB browser proxy  | 8103/tcp | 1    |
| Telnet proxy   | 8104/tcp | 1    |
| HTTP proxy   | 8105/tcp | 1    |
| MySQL ODBC   | 8108/tcp |      |
| <b>Note:</b>   |          |      |
| 1. Depending on your settings for Appliance proxy services |          |      |
| 2. If you have an Aggregator license                       |          |      |

## Virtual Private Network over the Internet

Contact Peregrine Systems Customer Support to send them the software that will enable access. If you have a firewall, enable the firewall ports listed in the above table, *Firewall ports to enable for Customer Support*.

## By modem and dedicated telephone line

For customer support by way of a modem, assign a dedicated telephone line for the Peregrine appliance. Peregrine Systems will use this line for connection to the Peregrine appliance during its normal operation (not just during setup). An internal modem and an analog telephone line allow you to have access to Customer Support even when you cannot use the Internet.

**Note:** Keep this line available for use by the Peregrine appliance 24 hours a day, 365 days a year. Peregrine Systems cannot provide you with modem support unless it has access to your Peregrine appliance.)

Instructions for purchasing a modem and attaching the hardware are in the *Network Discovery Setup Guide*.

## Through a Remote Access Server (RAS)

Contact Peregrine Systems Customer Support to send them the IP address or telephone number that will enable access. If you have a firewall, enable the firewall ports listed in the above table, *Firewall ports to enable for Customer Support*.

## Enable firewall ports

Enabling these firewall ports is not just to allow access to Customer Support on the Internet; it is to enable any Network Discovery system to perform through a corporate firewall.

If you have a corporate firewall that could impede Network Discovery, configure the corporate firewall to allow ICMP (ping) to pass through, and enable the following ports:

**Table 3-2: Firewall ports to enable for Network Discovery to perform**

| Used for                                       | Port    | Note | From                                  | To                                |
|--|---------|------|---------------------------------------|-----------------------------------|
| Echo Reply                                     | 0/icmp  |      | device                                | Peregrine appliance               |
| Error Messages                                 | 3/icmp  |      | device                                | Peregrine appliance               |
| Echo Request                                   | 8/icmp  |      | Peregrine appliance                   | device                            |
| TTL Timeout                                    | 11/icmp | 5    | Peregrine appliance                   | device                            |
|  |         |      | device                                | Peregrine appliance               |
| Netmask Request                                | 17/icmp |      | Peregrine appliance                   | device                            |
| Netmask Reply                                  | 18/icmp |      | device                                | Peregrine appliance               |
| Secure Shell (SSH)                             | 22/tcp  |      | Peregrine Systems<br>Customer Support | Network Discovery<br>appliance    |
| Telnet   | 23/tcp  | 1    | Peregrine appliance                   | device                            |
|  |         | 1    | management workstation                | device                            |
| SMTP   | 25/tcp  |      | Peregrine appliance                   | SMTP server                       |
| DNS  | 53/udp  |      | Peregrine appliance                   | DNS server                        |
| HTTP   | 80/tcp  |      | management workstation                | Peregrine appliance               |
|  |         | 1    | management workstation                | device                            |
|  |         | 1    | Peregrine appliance                   | device                            |
|  |         | 2    | Peregrine appliance                   | aggregated Peregrine<br>appliance |
| NTP (network time)                             | 123/udp |      | Peregrine appliance                   | NTP server                        |
| NetBIOS-n (name server)                        | 137/udp |      | Peregrine appliance                   | device                            |
| NetBIOS-dgm (datagram)                         | 138/udp |      | management workstation                | Peregrine appliance               |
| NetBIOS-ssn (session—file and printer sharing) | 139/tcp |      | management workstation                | Peregrine appliance               |
| SNMP   | 161/udp |      | Peregrine appliance                   | device                            |

|                    |           |     |                        |  |
|--------------------|-----------|-----|------------------------|--|
| SNMP traps         | 162/udp   | 3   | Peregrine appliance    | external network management server                     |
| Peregrine Listener | 1738/udp  | 4   | Peregrine appliance    | device with Peregrine Desktop Inventory (PDI) Listener |
| MIB Browser        | 8100/tcp  |     | management workstation | Peregrine appliance                                    |
|                    |           | 2   | Peregrine appliance    | aggregated Peregrine appliance                         |
| Network Map        | 8101/tcp  |     | management workstation | Peregrine appliance                                    |
|                    |           | 2   | Peregrine appliance    | aggregated Peregrine appliance                         |
| Network Map proxy  | 8102/tcp  | 2   | management workstation | Peregrine appliance                                    |
| MIB browser proxy  | 8103/tcp  | 2   | management workstation | Peregrine appliance                                    |
| Telnet proxy       | 8104/tcp  | 1   | management workstation | Peregrine appliance                                    |
|                    |           | 1,2 | Peregrine appliance    | aggregated Peregrine appliance                         |
| HTTP proxy         | 8105/tcp  | 1   | management workstation | Peregrine appliance                                    |
|                    |           | 1,2 | Peregrine appliance    | aggregated Peregrine appliance                         |
| MYSQL ODBC         | 8108/tcp  | 1   | management workstation | Peregrine appliance                                    |
| ServiceCenter      | 12670/tcp |     | Peregrine appliance    | ServiceCenter server                                   |
| Traceroute         | 33263/udp |     | Peregrine appliance    | device   |
|                    | 33436/udp |     |                        |  |

**Note:**

1. Depending on your settings for Appliance proxy services
2. If you have and Aggregator license
3. If you are using SNMP trap notification
4. This listener port is the default. You can add more ports for Network Discovery to listen on in **Administration > System preferences > Listener communication**
5. TTL Timeout can go in either direction, from the Peregrine appliance or to the Peregrine appliance.

## Check Cisco devices

It is strongly recommended that firmware/software in your Cisco devices be IOS version 12 or higher. If you want ATM or Frame Relay support, IOS 12 is mandatory in your Cisco devices.



## (Optional) Enable UDP port forwarding on routers

If you want to have your Peregrine appliance communicate with listener agents across subnets, you will need to enable routing for the UDP packets. If you have routers separating the broadcast domains in your network, you should configure them to pass along listener broadcast traffic on port 1738, as well as on the ports you have configured on your Peregrine appliance.

**Note:** Port 1738 is the default, but you can add other listener ports in **Administration > System Preferences > Listener communication**.

By configuring the Peregrine appliance and your routers to listen for UDP broadcasts on the same ports, Network Discovery will find new workstations much faster.

For Cisco routers, a procedure is provided below. For any other manufacturer, Peregrine recommends checking the router documentation to find a way to forward UDP traffic between subnets.

### To configure your Cisco IOS router

- 1 Access the EXEC privilege level on the configuration interface.
- 2 Enter the following commands:

```
configure terminal <enter>
interface [source interface] <enter>
ip helper-address [destination listener] <enter> (repeat this command for
each appliance you want to send to)
exit <enter>
ip forward protocol udp 1738 <enter>
end <enter>
```

**Note:** Any interface can have multiple helper-addresses.

**Note:** The “ip forward protocol udp” command specifies the ports to forward. In this case, we recommend port 1738. You will need to list other ports if you have configured other listener ports in **Administration > System Preferences > Listener communication**.

- 3 Exit the configuration interface.

## Check Committed Information Rate (CIR) values

If your network uses Frame Relay, check your Committed Information Rate (CIR) values for your connectivity devices.

The CIR values for these devices are available from your service provider. Check the appropriate documentation to obtain these values.

## Check the server that will be the Network Discovery appliance

You must install the Network Discovery software onto a server meeting the following hardware requirements.

For a new installation, the IBM xSeries 335 or Dell 1750 Server are recommended. However, the IBM xSeries 330 or Dell 1650 can also be used.

**Note:** Failure to meet the hardware requirements described in the following tables will result in Network Discovery not installing.

**Note:** There is no need to order a keyboard, mouse, operating system, or monitor.

## IBM Hardware

### Summary of IBM servers certified for Network Discovery

| For a large Network Discovery appliance (managing up to 10,000 devices) | For a small Network Discovery appliance (managing up to 5,000 devices) |
|---|--|
| IBM xSeries 335, 1 CPU, 2GB RAM with two 36 or 73GB SCSI disks          | IBM xSeries 335, 1 CPU, 1GB RAM, with two 36 or 73GB SCSI disks        |
| IBM xSeries 330, 2 CPUs, 2GB RAM, with two 36 or 73GB SCSI disks        | IBM xSeries 330, 1 CPU, 1GB RAM with two 36 or 73GB SCSI disks         |

## IBM xSeries 335 Hardware Requirements

| Description  | Qty | Supplier  | Part Number              | Remarks  |
|--|-----|-----------|--------------------------|--|
| Processor<br>■ IBM xSeries 335 with 1 Xeon 2.4 GHz or better processor<br>■ Level 2 512KB full-speed cache per processor | 1   | IBM       | 8676-61x                 | Approved server. Manufacturer may install better system processor.                                   |
| Hard Disk<br>■ two 36 or 73GB SCSI disks   | 2   | IBM       | (included with 8676-61x) |  |
| RAM<br>■ 1 or 2GB RAM  |     | IBM       | (included with 8676-61x) | On the IBM xSeries 335 you will need 1 or 2 GB RAM depending on how many devices you wish to manage. |
| Modem<br>■ MultiModem ZPX Universal version  | 1   | Multitech | MT5634ZPX-P CI-U-NV      | (Optional) Required to receive customer support by telephone line.                                   |
| C2T Cable Kit  | 1   | IBM       | 06P4792                  | Contains the C2T breakout cable that enables you to connect a monitor and keyboard to the server.    |
| Keyboard   | 1   |           |                          | A USB keyboard is not supported. The keyboard is only required at startup.                           |
| Monitor  | 1   |           |                          | The monitor is only required at startup.   |

## IBM xSeries 330 hardware requirements

| Description   | Qty    | Supplier | Part Number             | Remarks  |
|---|--------|----------|-------------------------|--|
| Processor<br>■ IBM xSeries 330 with one or two Pentium III 1.4 GHz or better processors<br>■ Level 2 512KB full-speed cache per processor | 1 or 2 | IBM      | 867441x                 | Approved server.<br>Manufacturer may install better system processor.  |
| Hard Disk<br>■ two 36 or 73GB SCSI disks  | 2      | IBM      | (included with 867441x) |  |
| RAM<br>■ 1 or 2GB RAM   |        | IBM      | (included with 867441x) | On the IBM xSeries 330 you will need one processor and one GB RAM to manage up to 5,000 devices.<br><br>You will need two processors and two GB RAM to manage up to 10,000 devices.                                      |
| Modem<br>(Optional) Required to receive customer support by telephone line.   | 1      |          |                         | You can have one of these three options:<br>■ IBM 56K PCI modem model number 33L4618<br>■ Actiontec model number PCI56012-01/PM560LKi<br>■ MultiTech MultiModem ZPX model numbers MT5634ZPX-PCI-NV or MT5634ZPX-PCI-U-NV |
| C2T Cable Kit   | 1      | IBM      | 06P4792                 | Contains the C2T breakout cable that enables you to connect a monitor and keyboard to the server.  |
| Keyboard  | 1      |          |                         | A USB keyboard is not supported. The keyboard is only required at startup.   |
| Monitor   | 1      |          |                         | The monitor is only required at startup.   |

## Dell Hardware

### Summary of Dell servers certified for Network Discovery

| For a large Network Discovery appliance<br>(managing up to 10,000 devices) | For a small Network Discovery appliance<br>(managing up to 5,000 devices) |
|--|---|
| Dell 1750 Server with 1 2.40Ghz XEON processor (P17R24C)                   | Dell 1650 Server with 1 1.26Ghz processor (165126C)                       |
| Dell 1750 Server with 1 3.0Ghz XEON processor (P17R30C)                    | Dell 1650 Server with 1 1.40Ghz processor (165140C)                       |
| Dell 1750 Server with 1 2.40Ghz/533MHz Bus XEON processor (175245C)        |   |
| Dell 1750 Server with 1 2.80Ghz/533MHz Bus XEON processor (175285C)        |   |
| Dell 1750 Server with 1 3.06Ghz/533MHz Bus XEON processor (175305C)        |   |

**Note:** You can add a second Processor to any of these Dell servers.

## Dell 1750 hardware requirements

| Description   | Qty | Supplier | Part Number   | Remarks  |
|---|-----|----------|---|--|
| Processor   | 1   | Dell     |   |  |
| Dell 1750 Server with one of the following processors:  |     |          |   |  |
| 2.40Ghz XEON processor  |     | Dell     | P17R24C   |  |
| 3.0Ghz XEON processor   |     | Dell     | P17R30C   |  |
| 2.40Ghz/533MHz Bus XEON processor   |     | Dell     | 175245C   |  |
| 2.80Ghz/533MHz Bus XEON processor   |     | Dell     | 175285C   |  |
| 3.06Ghz/533MHz Bus XEON processor   |     | Dell     | 175305C   |  |
| Second Processor  | 1   | Dell     | choose one of the following:<br>2P24, 2P28,<br>2P24533,<br>2P28533, or<br>2P30533 | You can add a second processor to your Dell 1750 server. This is optional. |
| Hard Disk   | 2   |          |   | Two hard drives are required.  |
| You can have one of these options:  |     |          |   |  |
| 36GB 10,000 RPM SCSI device   |     | Dell     | 36HP10  |  |
| 73GB 10,000 RPM SCSI device   |     | Dell     | 73HP10  |  |
| RAM   | 1   | Dell     |   |  |
| You can have one of these four options:   |     |          |   |  |
| 1GB, 4x256MB DIMMs  |     | Dell     | 1GB4D   |  |
| 1GB, 2x512MB DIMMs  |     | Dell     | 1GB2D   |  |
| 2GB, 4x512MB DIMMs  |     | Dell     | 2GB4D   |  |
| 4GB, 4x1GB DIMMs  |     | Dell     | 4GB4D   |  |
| Modem   | 1   |          |   |  |
| If you have a Dell 1750 with the 5V PCI Slot option, you can have one of the following options: |     |          |   |  |
| IBM 56K PCI modem   |     | IBM      | 33L4618   |  |

| Description   | Qty | Supplier  | Part Number                                       | Remarks  |
|---|-----|-----------|---|--|
| Actiontec   |     | Actiontec | PCI56012-01 or<br>PM560LKi                        |  |
| MultiTech MultiModem ZPX  |     | MultiTech | MT5634ZPX-P<br>CI-NV or<br>MT5634ZPX-P<br>CI-U-NV |  |
| Modem<br>If you have a Dell 1750 with the 3V<br>PCI Slot option, you can use the<br>MultiTech MultiModem ZPX. |     | Multitech | MT5634ZPX-P<br>CI-U-NV                            |  |
| CD-ROM  | 1   | Dell      | CD24X   |  |
| 1x64bit 5V slot   | 1   | Dell      | 64BPCI1   | 64BPCI2 is not<br>recommended.   |
| Onboard SCSI  | 1   | Dell      | MS  | Required.  |
| Redundant Power Supply  | 1   | Dell      | REDPWR  | This is optional.  |
| Keyboard  | 1   |           |   | A USB keyboard is not<br>supported. The keyboard is<br>only required at startup. |
| Monitor   | 1   |           |   | The monitor is only required<br>at startup.                                      |

## Dell 1650 Server hardware requirements

| Description  | Qty | Supplier  | Part Number                                       | Remarks   |
|--|-----|-----------|---|---|
| Processor<br>Dell 1650 Server with one of the following processors:                                      | 1   | Dell      |   |   |
| 1.26Ghz processor  |     | Dell      | 165126C   |   |
| 1.40Ghz processor  |     | Dell      | 165140C   |   |
| Second Processor   | 1   | Dell      | choose one of the following:<br>2P126 or 2P140    | You can add a second processor to your Dell 1650 server. This is optional.  |
| Hard Disk<br>You can have one of these options:  | 2   |           |   | Two hard drives are required.   |
| 36GB 10,000 RPM SCSI device  |     | Dell      | 3610320   |   |
| 73GB 10,000 RPM SCSI device  |     | Dell      | 7310320   |   |
| RAM<br>You can have one of these three options:  | 1   | Dell      |   | On the Dell 1650 you will need one processor and one GB RAM to manage up to 5,000 devices.<br><br>You will need two processors and two GB RAM to manage up to 10,000 devices. |
| 1GB, 4x256MB DIMMs   |     | Dell      | 1GB4D   |   |
| 1GB, 2x512MB DIMMs   |     | Dell      | 1GB2D   |   |
| 2GB, 4x512MB DIMMs   |     | Dell      | 2GB4D   |   |
| Modem<br>If you have a Dell 1650 with the 5V PCI Slot option, you can have one of the following options: | 1   |           |   |   |
| IBM 56K PCI modem  |     | IBM       | 33L4618   |   |
| Actiontec  |     | Actiontec | PCI56012-01 or<br>PM560LKi                        |   |
| MultiTech MultiModem ZPX   |     | MultiTech | MT5634ZPX-P<br>CI-NV or<br>MT5634ZPX-P<br>CI-U-NV |   |



| Description   | Qty | Supplier  | Part Number            | Remarks  |
|---|-----|-----------|------------------------|--|
| Modem<br>If you have a Dell 1650 with the 3V PCI Slot option, you can use the MultiTech MultiModem ZPX. |     | Multitech | MT5634ZPX-P<br>CI-U-NV |  |
| CD-ROM  | 1   | Dell      | CD24X                  |  |
| 1x64bit/66MHz slot and<br>1x32bit/33MHz slot  | 1   | Dell      | 32BPCI1                | 64BPCI2 is not recommended.  |
| Onboard SCSI  | 1   | Dell      | MS                     | Required.  |
| SCSI Backplane  | 1   | Dell      | 1X3BKPL                |  |
| Redundant Power Supply  | 1   | Dell      | RDPWRAC                | This is optional.  |
| Keyboard  | 1   |           |                        | A USB keyboard is not supported. The keyboard is only required at startup. |
| Monitor   | 1   |           |                        | The monitor is only required at startup.                                   |

## Check the management workstation

Because Network Discovery is web-based, you can use any properly equipped workstation as a management console.

**Table 3-3: Requirements and recommendations for the management workstation**

| Item                | Required                                    | Recommended                          |
|---------------------|---|--------------------------------------|
| Web browser         | Netscape 6.2.2 or later                     | Netscape 6.2.2 or later              |
|                     | Internet Explorer 5.5 or later <sup>a</sup> | Internet Explorer 5.5 or later       |
| Java Runtime Engine | 1.4.1_01 or later <sup>b</sup>              | 1.4.1_01 or later                    |
| Video               | 16,000                                      | 65,000 or more                       |
| —colors             |   |                                      |
| —resolution         | 800×600                                     | 1024 ×768 or more                    |
| Memory (MB RAM)     | 128<br>(512, if using an Aggregator)        | 512 <sup>c</sup> or more             |
| CPU                 | Pentium II 233 equivalent or better         | Pentium III 800 equivalent or better |
| Operating system    |   | Windows 2000 or better               |

a Requires a Virtual Machine (VM) upgrade.

b Must be downloaded from [java.sun.com](http://java.sun.com), do not use the version that comes with your browser

c 512 MB is recommended for large network maps.

**Note:** Java and JavaScript must be enabled in order for Network Discovery to work properly.

# Index

---

## B

bridge aging 20

## C

CIR values 26

Cisco devices 24

collecting information 9  
questionnaire 7

color settings 34

Committed Information Rate values 26

community strings

about 19

directed 19

customer support access 11

## D

DHCP 13, 18

static address for Peregrine appliance 10

directed community strings 19

Dynamic Host Configuration Protocol *see* DHCP

## F

firewall ports 22–24

customer service access 21

Frame Relay, set up 26

## H

hardware requirements 26

Hot Standby Routing Protocol *see* HSRP

HSRP 18

## I

installation

before you install the Peregrine appliance 5

checking the management workstation

preparing the network 17

Internet Explorer

minimum version 34

IPv4 address 10

## J

Java

enable 34

JavaScript

enable 34

## L

listener configuration 25

## M

managed device

definition 10

management console *see* management workstation

management workstation 34

requirements

browser 34

CPU 34

memory 34

video 34

management workstation requirements 34

**N**

Netscape, minimum version 34  
network preparation 9  
node and subnode setup 10

**P**

Peregrine appliance  
    Dell hardware 29  
    hardware requirements 26  
    IBM hardware 26  
Peregrine Systems Customer Support  
    access 11  
    access options 21–24  
        Internet 21  
        Remote Access Server 22  
        telephone line 22  
        Virtual Private Network 22  
pre-installation 5  
    checking the management workstation 34  
    preparing the network 17  
    questionnaire 7, 9  
preliminary work 6  
preparation 6  
preparing the network 17  
Pre-setup Questionnaire 9  
proxy server 21

**Q**

questionnaire 9

**R**

RAS 22  
Remote Access Server 22  
requirements  
    management workstation  
    Peregrine appliance 26  
resolution 34  
routers  
    listener configuration 25

**S**

screen resolution 34  
server requirements 26  
setup 6  
    collecting network information 7

setup questionnaire 7  
SNMP  
    turn on  
        in network devices 19  
        in routers and switches 18  
SNMP management  
    definition 10  
specifications  
    management workstation  
    Peregrine appliance 26

**T**

telephone line 22

**V**

Virtual Private Network 22





September 16, 2003