

# HP Business Service Management

for the Windows operating system

Software Version: 9.00

---

## HP SiteScope Deployment Guide

Document Release Date: July 2010

Software Release Date: July 2010



# Legal Notices

## Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

## Restricted Rights Legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

## Copyright Notices

© Copyright 2005 - 2010 Hewlett-Packard Development Company, L.P.

## Trademark Notices

Adobe® and Acrobat® are trademarks of Adobe Systems Incorporated.

AMD and the AMD Arrow symbol are trademarks of Advanced Micro Devices, Inc.

Google™ and Google Maps™ are trademarks of Google Inc.

Intel®, Itanium®, Pentium®, and Intel® Xeon® are trademarks of Intel Corporation in the U.S. and other countries.

Java™ is a US trademark of Sun Microsystems, Inc.

Microsoft®, Windows®, Windows NT®, Windows® XP, and Windows Vista® are U.S. registered trademarks of Microsoft Corporation.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

## Acknowledgements

This product includes software developed by the Apache Software Foundation (**<http://www.apache.org/>**).

This product includes software developed by the JDOM Project (**<http://www.jdom.org/>**).

This product includes software developed by the MX4J project (**<http://mx4j.sourceforge.net>**).

## Documentation Updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates, or to verify that you are using the most recent edition of a document, go to:

**<http://h20230.www2.hp.com/selfsolve/manuals>**

This site requires that you register for an HP Passport and sign-in. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

Or click the **New users - please register** link on the HP Passport login page.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your HP sales representative for details.

# Support

Visit the HP Software Support web site at:

**<http://www.hp.com/go/hpsoftwaresupport>**

This web site provides contact information and details about the products, services, and support that HP Software offers.

HP Software online support provides customer self-solve capabilities. It provides a fast and efficient way to access interactive technical support tools needed to manage your business. As a valued support customer, you can benefit by using the support web site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract. To register for an HP Passport ID, go to:

**<http://h20229.www2.hp.com/passport-registration.html>**

To find more information about access levels, go to:

**[http://h20230.www2.hp.com/new\\_access\\_levels.jsp](http://h20230.www2.hp.com/new_access_levels.jsp)**

---

# Table of Contents

<b>Welcome to This Guide .....</b>	<b>9</b>
How This Guide Is Organized .....	9
Who Should Read This Guide .....	10
Additional Online Resources.....	11
Documentation Updates .....	11

## **PART I: INTRODUCTION TO SITESCOPE**

<b>Chapter 1: Introduction to SiteScope.....</b>	<b>15</b>
<b>Chapter 2: Getting Started Roadmap.....</b>	<b>17</b>
<b>Chapter 3: Deployment Methodology and Planning.....</b>	<b>19</b>
An Enterprise System Monitoring Methodology .....	19
Business System Infrastructure Assessment .....	21
SiteScope Server Sizing .....	22
Network Location and Environment .....	23
Considerations for Windows Environments .....	24
Considerations for UNIX Environments.....	25
<b>Chapter 4: Understanding Agentless Monitoring.....</b>	<b>27</b>
About SiteScope Monitoring Capabilities .....	27
Understanding the Agentless Monitoring Environment.....	29
<b>Chapter 5: SiteScope Licenses.....</b>	<b>33</b>
Introducing SiteScope Licensing .....	33
Understanding SiteScope License Types .....	34
Understanding Monitor Licensing.....	38
Estimating the Number of License Points.....	54
Adding SiteScope Licenses.....	58

**PART II: BEFORE INSTALLING SITESCOPE**

**Chapter 6: Before You Install SiteScope ..... 61**  
Installation Overview ..... 62  
System Requirements ..... 64  
Certified Configuration ..... 70  
SiteScope Capacity Limitations ..... 71  
HP SiteScope Support Matrixes ..... 72

**Chapter 7: Upgrading SiteScope ..... 75**  
Before Performing the Upgrade ..... 76  
Upgrading an Existing SiteScope Installation ..... 77  
Using the End of Life Monitor Viewer ..... 78  
Backing Up SiteScope Configuration Data ..... 81  
Naming the SiteScope Directory ..... 82  
Importing Configuration Data ..... 82  
Troubleshooting and Limitations ..... 83

**PART III: INSTALLING SITESCOPE**

**Chapter 8: Installing SiteScope ..... 89**  
Installation Flow ..... 89  
Preparing for Solaris or Linux Installation ..... 91  
Performing a Full Installation ..... 92  
Installing on Solaris or Linux Using Console Mode ..... 116  
Troubleshooting and Limitations ..... 126

**Chapter 9: Installing SiteScope in Silent Mode ..... 129**  
About Installing SiteScope in Silent Mode ..... 129  
Running a Silent Installation ..... 131

**Chapter 10: Using the SiteScope Configuration Tool ..... 133**  
Running the Configuration Tool on Windows Platforms ..... 133  
Running the Configuration Tool on Solaris or Linux Platforms ..... 140

**Chapter 11: Sizing SiteScope ..... 147**  
About Sizing SiteScope ..... 147  
SiteScope Capacity Calculator ..... 148  
Sizing SiteScope on Windows Platforms ..... 150  
Sizing SiteScope on Solaris and Linux Platforms ..... 154

**Chapter 12: Uninstalling SiteScope ..... 161**  
Uninstalling SiteScope on a Windows Platform ..... 161  
Uninstalling SiteScope on a Solaris or Linux Platform ..... 166

**PART IV: RUNNING SITESCOPE SECURELY**

<b>Chapter 13: Hardening the SiteScope Platform .....</b>	<b>169</b>
About Hardening the SiteScope Platform .....	169
Setting SiteScope User Preferences .....	170
Password Encryption .....	170
Using Secure Socket Layer (SSL) to Access SiteScope .....	170
Configuring SiteScope to Send Bulk Data to ODB .....	171
<b>Chapter 14: Permissions and Credentials .....</b>	<b>173</b>
<b>Chapter 15: Configuring SiteScope to Use SSL .....</b>	<b>195</b>
About Using SSL in SiteScope.....	195
Preparing SiteScope for Using SSL.....	196
Configuring SiteScope for SSL.....	200
Configuring SiteScope to Connect to a BSM Server That Requires a Client Certificate .....	202

**PART V: GETTING STARTED AND ACCESSING SITESCOPE**

<b>Chapter 16: Post-Installation Administration .....</b>	<b>209</b>
Post-Installation Administration Checklist.....	209
<b>Chapter 17: Getting Started with SiteScope .....</b>	<b>213</b>
About Starting the SiteScope Service.....	213
Starting and Stopping the SiteScope Service on Windows Platforms.....	214
Starting and Stopping the SiteScope Process on Solaris and Linux Platforms .....	215
Connecting to SiteScope .....	215
SiteScope Classic Interface.....	217
Troubleshooting and Limitations .....	217

**PART VI: APPENDIXES**

<b>Appendix A: Integrating IIS with SiteScope's Tomcat Server .....</b>	<b>227</b>
Configuring the Apache Tomcat Server Files.....	227
Configuring IIS .....	231

- Appendix B: Integrating SiteScope with SiteMinder .....235**
- Understanding Integration with SiteMinder .....236
- Integration Requirements .....237
- The Integration Process .....237
- Configuring the SiteMinder Policy Server .....238
- Configuring SiteScope for Using SiteMinder .....240
- Configuring IIS .....240
- Defining Permissions for the Different SiteScope Roles .....241
- Logging On to SiteScope .....241
- Notes and Guidelines .....242
- Index .....243**



---

# Welcome to This Guide

This guide provides detailed instructions on how to deploy and configure HP SiteScope.

**This chapter includes:**

- ▶ How This Guide Is Organized on page 9
- ▶ Who Should Read This Guide on page 10
- ▶ Additional Online Resources on page 11
- ▶ Documentation Updates on page 11

## How This Guide Is Organized

This guide contains the following parts:

**Part I Introduction to SiteScope**

Introduces SiteScope and provides a getting started roadmap. In addition, it provides information on deployment planning, agentless monitoring, and SiteScope licensing.

**Part II Before Installing SiteScope**

Provides an overview of the installation, and describes the system requirements and recommended server configurations. It also describes how to upgrade existing SiteScope installations.

### **Part III Installing SiteScope**

Describes how to install and uninstall SiteScope on Windows, Linux, and Solaris platforms. It also describes how to configure SiteScope using the Configuration Tool, and size your operating system and SiteScope and to achieve optimum performance when monitoring many instances.

### **Part IV Running SiteScope Securely**

Describes how to configure options to harden the SiteScope platform, set user permissions and credentials required to access the monitor, and configure SiteScope to use Secure Sockets Layer (SSL).

### **Part V Getting Started and Accessing SiteScope**

Describes how to start and stop the SiteScope service, and log in to SiteScope for the first time. It also describes the recommended administration steps you should perform following SiteScope installation.

### **Part VI Appendixes**

Describes how to configure IIS and integrate SiteScope with SiteMinder policy-based authentication.

## **Who Should Read This Guide**

This guide is for the following users of SiteScope:

SiteScope/Business Service Management administrators

Readers of this guide should be knowledgeable about enterprise system administration and HP Business Service Management data collectors.

## Additional Online Resources

**Troubleshooting & Knowledge Base** accesses the Troubleshooting page on the HP Software Support Web site where you can search the Self-solve knowledge base. Choose **Help > Troubleshooting & Knowledge Base**. The URL for this Web site is <http://h20230.www2.hp.com/troubleshooting.jsp>.

**HP Software Support** accesses the HP Software Support Web site. This site enables you to browse the Self-solve knowledge base. You can also post to and search user discussion forums, submit support requests, download patches and updated documentation, and more. Choose **Help > HP Software Support**. The URL for this Web site is [www.hp.com/go/hpsoftwaresupport](http://www.hp.com/go/hpsoftwaresupport).

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract.

To find more information about access levels, go to:

[http://h20230.www2.hp.com/new\\_access\\_levels.jsp](http://h20230.www2.hp.com/new_access_levels.jsp)

To register for an HP Passport user ID, go to:

<http://h20229.www2.hp.com/passport-registration.html>

**HP Software Web site** accesses the HP Software Web site. This site provides you with the most up-to-date information on HP Software products. This includes new software releases, seminars and trade shows, customer support, and more. Choose **Help > HP Software Web site**. The URL for this Web site is [www.hp.com/go/software](http://www.hp.com/go/software).

## Documentation Updates

HP Software is continually updating its product documentation with new information.

To check for recent updates, or to verify that you are using the most recent edition of a document, go to the HP Software Product Manuals Web site (<http://h20230.www2.hp.com/selfsolve/manuals>).

Welcome to This Guide

# Part I

---

## Introduction to SiteScope



# 1

---

## Introduction to SiteScope

HP SiteScope is an agentless monitoring solution designed to ensure the availability and performance of distributed IT infrastructures—for example, servers, operating systems, network devices, network services, applications, and application components.

This Web-based infrastructure monitoring solution is lightweight, highly customizable, and does not require that data collection agents be installed on your production systems. With SiteScope, you gain the real-time information you need to verify infrastructure operations, stay apprised of problems, and solve bottlenecks before they become critical.

SiteScope provides different tools, such as templates, the Publish Template Changes wizard, and automatic template deployment that enable you to develop a standardized set of monitor types and configurations into a single structure. SiteScope templates can be speedily deployed across the enterprise and quickly updated to make sure that the monitoring infrastructure is compliant with the standards set in the template.

SiteScope also includes alert types that you can use to communicate and record event information in a variety of media. You can customize alert templates to meet the needs of your organization.

SiteScope is licensed on the basis of the number of metrics to be monitored rather than the number of servers on which it is run. A metric is a system resource value, performance parameter, URL, or similar system response. This means that you can flexibly scale a SiteScope deployment to meet the needs of your organization and the requirements of your infrastructure. You can install SiteScope using either a permanent license that you receive from HP or the evaluation license that is part of a new SiteScope installation. You can upgrade your licensing as needed to expand the monitoring capacity of your initial deployment or to expand the deployment within your infrastructure.

SiteScope also acts as a monitoring foundation for other HP offerings such as HP Business Service Management, HP Software-as-a-Service, and HP LoadRunner. By starting with SiteScope and adding other HP solutions such as Business Service Management and Service Level Management, you can create a solid infrastructure monitoring that enables you to manage your IT infrastructure and service levels from a business point of view.

SiteScope can also work together with HP Operations Manager products to provide a powerful combination of agentless and agent-based infrastructure management. Serving as an agent of Operations Manager, SiteScope targets are automatically added to Operations Manager Service view maps, which enables Operations Manager to seamlessly display SiteScope data and monitor status. For event integration, SiteScope alerts and monitor metric status changes are sent directly to Operations Manager. The combined functionality of agentless and agent-based monitoring provides a powerful and in-depth monitoring solution. For more details on using Operations Manager products, refer to the Operations Manager documentation.



# 2

---

## Getting Started Roadmap

This chapter provides a basic step-by-step roadmap for getting up and running with SiteScope.

### **1 Register your copy of SiteScope.**

Register your copy of SiteScope to gain access to technical support and information on all HP products. You are also eligible for updates and upgrades. You can register your copy of SiteScope on the HP Software Support Web site (<http://www.hp.com/go/hpsoftwaresupport>).

### **2 Read about where to get help.**

Learn about the various sources of assistance, including HP Services and HP Software Support, as well as the SiteScope Help.

### **3 Plan your SiteScope deployment.**

Create a complete deployment plan prior to installing SiteScope software. Use "Deployment Methodology and Planning" on page 19 to assist you. For in-depth deployment planning best practices, consult your HP representative.

### **4 Install SiteScope.**

See "Installation Overview" on page 62 for a basic understanding of the steps involved in deploying the SiteScope application. For information on deploying SiteScope securely, see "Hardening the SiteScope Platform" on page 169.

### **5 Log in to SiteScope and initiate system administration.**

Log into the SiteScope Web interface using a Web browser. Use the checklist in "Post-Installation Administration" on page 209 to guide you through basic platform and monitor administration tasks to prepare SiteScope for operational deployment.

**6 Roll out SiteScope to business and systems users.**

Once the SiteScope system is up and running with defined users and incoming monitor data, begin the process of educating business and systems users on how to access and use SiteScope monitors, reporting and alerting functionality.

For complete details on using and administering SiteScope, see the SiteScope Help.

# 3

---

## Deployment Methodology and Planning

### **This chapter includes:**

- ▶ An Enterprise System Monitoring Methodology on page 19
- ▶ Business System Infrastructure Assessment on page 21
- ▶ SiteScope Server Sizing on page 22
- ▶ Network Location and Environment on page 23
- ▶ Considerations for Windows Environments on page 24
- ▶ Considerations for UNIX Environments on page 25

### **An Enterprise System Monitoring Methodology**

Deploying SiteScope is a process that requires resource planning, system architecture design, and a well-planned deployment strategy. This chapter outlines the methodology and considerations you need to take for successful deployment and use of SiteScope.

---

**Note:** Use the information below to assist you in your preparations before beginning the installation. For in-depth deployment planning best practices, consult your HP Professional Services representative.

---

Having a consistent methodology is essential for effective system monitoring. However, it is not always obvious how to approach, develop, and deploy an enterprise monitoring solution. The solution needs to consider the role of the IT infrastructure and how it contributes to the success of the organization. System monitoring is a tool you use to ensure the availability and function of services used by the organization to meet its key objectives. You can use the following as a guide to plan your system monitoring.

► **What to monitor**

Effective enterprise system management uses a multi-tiered monitoring approach. SiteScope gives you the tools to implement this. At one level, you want to monitor individual hardware elements in the infrastructure to see that they are running and available. You want to add to this monitoring of key services and processes on these systems. This includes low level operating system processes as well as processes indicating the health and performance of key applications. On top of this, you want to create transactional monitoring of business processes to see that key applications and services are available and function as expected.

► **What threshold level represents an event**

The availability and performance of information systems is critical to enterprise business success. The thresholds that you set for monitors is determined by the nature of the system or business process you are monitoring.

► **How often the system should be checked**

How often you have a system checked can be as important as the event threshold you set. The availability of mission critical information systems should be checked regularly during the periods that there are to be accessible. In many cases, systems need to be available 24 hours a day, 7 days a week. You control how often SiteScope checks a system with the Frequency setting for each monitor. Too much time between checks may delay detection of problems. Too frequent checking may load an already busy system unnecessarily.

► **What action to take when an event is detected**

As a monitoring application, SiteScope provides you with the tools to detect problems. You use SiteScope alerts to send timely notification when an event threshold has been triggered. An email notification is a commonly used alert action. SiteScope includes other alert types that can integrate with other systems.

You can develop an alert escalation scheme by defining multiple alert definitions with different alert trigger criteria. You use the **When** settings for alerts to customize the relation between detected events and alert actions.

Another event action may be to disable monitoring and alerting for systems that are dependent on a system that has become unavailable. SiteScope group and monitor dependency options can be used to avoid cascading series of alerts.

► **What automated response can be performed**

When problems are detected, an automated response to resolve the problem is ideal. While this is not possible for all systems, the SiteScope Script Alert type does provide a flexible and powerful tool for automating corrective actions for a variety of situations. You should consider what problems that may arise in your environment could be addressed with an automated response.

## **Business System Infrastructure Assessment**

- 1** Gather technical and business requirements before making architectural and deployment decisions. Actions for this stage include:
  - Develop a list of all business applications to be monitored. This should consider end-to-end services such as order processing, account access functions, data queries, updates and reporting.
  - Develop a list of servers that support the business applications. This must include servers supporting front-end Web interfaces, back-end databases, and applications servers.
  - Develop a list of network devices supporting the business applications. This includes network appliances and authentication services.

- ▶ Identify heartbeat elements to be monitored. Heartbeat elements are services that act as foundational indicators of the availability of a particular business system or resource.
  - ▶ Outline templates of monitors that represents the resources to be monitored for each system.
- 2** Identify stakeholders and key deliverables for the business system monitoring activity. Deliverables include:
- ▶ what reports should be generated
  - ▶ what alert actions should be taken when events are detected
  - ▶ to whom should alerts be sent
  - ▶ what users require access to view and manage SiteScope
  - ▶ what SiteScope elements need to be accessible to which stakeholders
  - ▶ what are the thresholds for any Service Level Agreements (if applicable)
- 3** Understand the constraints within which the system monitoring function must operate. This includes restrictions on the protocols that can be used, user authentication requirements, access to systems with business sensitive data, and network traffic restrictions.

## SiteScope Server Sizing

The foundation of successful monitoring deployment is proper sizing of the server where SiteScope is to run. Server sizing is determined by a number of factors including:

- ▶ the number of monitor instances to be run on the SiteScope installation
- ▶ the average run frequency for the monitors
- ▶ the types of protocols and applications to be monitored
- ▶ how much monitor data need to be retained on the server for reporting

Knowing the number of servers in the environment, their respective operating systems, and the application to be monitored is the starting point for estimating the number of monitors that may be needed.

See "Sizing SiteScope on Windows Platforms" on page 150 or "Sizing SiteScope on Solaris and Linux Platforms" on page 154 for a table of server sizing recommendations based on estimations of the number of monitors to be run.

## Network Location and Environment

The majority of SiteScope monitoring is performed by emulating Web or network clients that make requests of servers and applications in the network environment. For this reason, SiteScope must be able to access servers, systems, and applications throughout the network. This helps determine where SiteScope should be installed.

The methods used by SiteScope for monitoring systems, servers, and applications can be divided into two categories:

- ▶ Standards-based network protocols. This includes HTTP, HTTPS, SMTP, FTP, and SNMP.
- ▶ Platform-specific network services and commands. This includes NetBIOS, telnet, rlogin, and Secure Shell (SSH).

Infrastructure monitoring relies on platform-specific services. As an agentless solution, monitoring requires that SiteScope log in and authenticate frequently to many servers in the infrastructure. For performance and security reasons, it is best to deploy SiteScope within the same domain and as close to the system elements to be monitored as possible. It is also best to have SiteScope in the same subnet as the applicable network authentication service (for example Active Directory, NIS, or LDAP). The SiteScope interface can be accessed and managed remotely as needed using HTTP or HTTPS.

---

**Note:** Try to avoid deploying SiteScope in a location where a significant amount of the monitoring activity requires communication across a Wide Area Network (WAN).

---

For security reasons, it is recommended not to use SiteScope to monitor servers through a firewall because of the different protocols and ports required for server availability monitoring. SiteScope licensing is not server-based and supports having separate SiteScope installations for both sides of a firewall. Two or more separate SiteScope installations can be accessed simultaneously from a single workstation using HTTP or HTTPS.

## Considerations for Windows Environments

SiteScope must be installed using an account with administrator privileges. It is also recommended that the SiteScope service be run with a user account that has administrator privileges. A local system account can be used, but this affects the configuration of connection profiles to remote Windows servers.

The following are some additional considerations for using SiteScope in a Microsoft Windows network environment:

- ▶ **Remote Registry Service.** SiteScope uses the Windows performance registry on remote machines to monitor server resources and availability. To enable this monitoring capability, the Remote Registry Service for the remote machines must be activated.
- ▶ **Windows 2000 Service Pack 2.** There is a known issue with Windows 2000 Service Pack 2. The Remote Registry Service has a memory leak. This often causes SiteScope monitors for a remote Windows 2000 server with Service Pack 2 to work intermittently. The memory leak is fixed in Windows 2000 Service Pack 3. To avoid this problem, it is recommended that you install Service Pack 3 on all Windows 2000 servers that you plan to monitor with SiteScope.



## Considerations for UNIX Environments

SiteScope does not need to be installed or run by the root user unless the SiteScope Web server is run on a privileged port.

The following is additional information relating to the setup of agentless monitoring of remote UNIX servers with SiteScope:

- ▶ **Remote Login Account Shells.** SiteScope as an application can run successfully under most popular UNIX shells. When SiteScope communicates with a remote UNIX server it prefers communicating with either Bourne shell (sh) or tsch shell. The relevant login account on each remote UNIX server should, therefore, have its shell set to use one of these shells.

---

**Note:** Set shell profile only for the login accounts used by SiteScope to communicate with the remote machine. Other applications and accounts on the remote machine can use their currently defined shells.

---

- ▶ **Account Permissions.** It may be necessary to resolve command permissions settings for monitoring remote UNIX servers. Most of the commands that SiteScope runs to get server information from a remote UNIX server are located in the `/usr/bin` directories on the remote server. Some commands, however, such as the command to get memory information, are located in `/usr/sbin`. The difference between these two locations is that `/usr/sbin` commands are usually reserved for root user or other highly privileged users.

---

**Note:** Although SiteScope does require highly privileged account permissions, for security reasons, it is recommended not to run SiteScope using the root account or to configure it to use root login accounts on remote servers.

---

If you have problems with permissions, you need to either have SiteScope log in as a different user that has permissions to run the command, or have the permissions changed for the user account that SiteScope is using.

# 4

---

## Understanding Agentless Monitoring

### **This chapter includes:**

- About SiteScope Monitoring Capabilities on page 27
- Understanding the Agentless Monitoring Environment on page 29

### **About SiteScope Monitoring Capabilities**

This chapter introduces SiteScope's agentless monitoring concept. Agentless monitoring means that monitoring can be accomplished without the deployment of agent software onto the servers to be monitored. This makes deployment and maintenance of SiteScope relatively simple compared to other performance or operational monitoring solutions. Unlike agent-based monitoring approaches, SiteScope reduces total cost of ownership by:

- Gathering detailed performance data for infrastructure components.
- Eliminating the need for extra memory or CPU power on production systems to run a monitoring agent.
- Reducing the time and cost of maintenance by consolidating all monitoring components to a central server.
- Removing any requirement to take a production system offline in order to update its monitoring agent.
- Eliminating time needed to tune monitoring agents to coexist with other agents.

- ▶ Reducing installation time by eliminating the need to physically visit production servers or wait for software distribution operations.
- ▶ Reducing the possibility of an unstable agent causing system downtime on a production server.

SiteScope is a versatile operational monitoring solution that provides many different monitor types for monitoring systems and services at various levels. Many of the monitor types can be further customized for special environments.

Enterprises and organizations often need to deploy and maintain multiple solutions to monitor operations and availability at these different levels. Operational monitoring can be divided into several levels or layers as described in the following table:

Monitor Type	Description
Server Health	Monitors server machine resources such as CPU utilization, memory, storage space, as well as the status of key processes and services.
Web Process and Content	Monitors availability of key URLs, the function of key Web-based processes, and monitors key text content.
Application performance	Monitors performance statistics for mission critical applications such as Web servers, databases, and other application servers.
Network	Monitors connectivity and availability of services.

## Understanding the Agentless Monitoring Environment

The majority of SiteScope monitoring is performed by emulating Web or network clients that make requests of servers and applications in the network environment. For this reason, SiteScope must be able to access servers, systems, and applications throughout the network.

This section contains the following topics:

- "SiteScope Monitoring Methods" on page 29
- "Firewalls and SiteScope Deployment" on page 32

### SiteScope Monitoring Methods

The methods used by SiteScope for monitoring systems, servers, and applications can be divided into two categories:


➤ **Standards-based network protocols.**

This category includes monitoring via HTTP, HTTPS, FTP, SMTP, SNMP, and UDP. These types of monitors are generally independent of the platform or operating system on which SiteScope is running. For example, SiteScope installed on Linux can monitor Web pages, file downloads, email transmission, and SNMP data on servers running Windows 2000, HP-UX, and Solaris UNIX.

➤ **Platform-specific network services and commands.**

This category includes monitor types that log in as a client to a remote machine and request information. For example, SiteScope can use Telnet or SSH to log into a remote server and request information regarding disk space, memory, or processes. On the Microsoft Windows platform, SiteScope also makes use of Windows performance counter libraries. Some limitations exist in monitoring across different operating systems for monitor types that rely on platform-specific services. For example, SiteScope for Windows includes the Microsoft Exchange 2007/2010 and Microsoft Windows Dial-up monitors, which are not included in SiteScope for Solaris.

The following diagram shows a general overview of agentless monitoring with SiteScope. SiteScope monitors make requests of services on remote machines to gather data on performance and availability.



SiteScope Server monitors (for example, CPU, Disk Space, Memory, Service) can be used to monitor server resources on the following platforms:

- Windows NT/2000/2003 (x86 and Alpha, see note below)
- Sun Solaris (Sparc and x86)
- Linux
- AIX
- HP/UX (HP/UX 64-Bit)

- Digital Unix
- SGI IRIX
- SCO
- FreeBSD

---

**Note:** An SSH connection is required to monitor server resources (for example, CPU utilization, memory) on Windows machines from a SiteScope running on Solaris or Linux. A Secure Shell client must be installed on each Windows machine that you want to monitor in this way. For more information on enabling this capability, see "SiteScope Monitoring Using Secure Shell (SSH)" in SiteScope Help.

---

SiteScope includes an adapter configuration template that allows you to extend SiteScope capabilities to monitor other versions of the UNIX operating system. For more information, see "UNIX Operating System Adapters" in SiteScope Help.

You need to enable login accounts on each server for which you want SiteScope to access system data remotely. The login account on the monitored servers must be configured to match the account under which SiteScope is installed and running. For example, if SiteScope is running under an account with the username **sitescope**, remote login accounts on servers that are to be monitored by this SiteScope installation need to have user login accounts configured for the **sitescope** user.

## Firewalls and SiteScope Deployment

For security reasons, it is recommended not to use SiteScope to monitor servers through a firewall because of the different protocols and ports required for server monitoring. SiteScope licensing supports separate SiteScope installations for both sides of a firewall. Two or more SiteScope installations can be accessed from a single workstation using HTTP or HTTPS.

The following table lists the ports commonly used by SiteScope for monitoring and alerting in a typical monitoring environment:

SiteScope Function	Default Port Used
SiteScope Web server	Port 8080
FTP Monitor	Port 21
Mail Monitor	Port 25 (SMTP), 110 (POP3), 143 (IMAP)
News Monitor	Port 119
Ping Monitor	ICMP packets
SNMP Monitor	Port 161 (UDP)
URL Monitor	Port 80,443
Remote Windows Monitoring	Port 139
Email Alert	Port 25
Post Alert	Port 80,443
SNMP Trap Alert	Port 162 (UDP)
Remote UNIX ssh	Port 22
Remote UNIX Telnet	Port 23
Remote UNIX rlogin	Port 513



# 5

---

## SiteScope Licenses

### **This chapter includes:**

- Introducing SiteScope Licensing on page 33
- Understanding SiteScope License Types on page 34
- Understanding Monitor Licensing on page 38
- Estimating the Number of License Points on page 54
- Adding SiteScope Licenses on page 58

### **Introducing SiteScope Licensing**

SiteScope licensing controls the number of monitors that can be run and, in some cases, the types of monitors that can be used. Unlike software that is sold based on the number of sites, seats, or users, SiteScope licensing is based on the monitoring requirements. This provides an efficient and flexible way to scale SiteScope to your environment.

Purchasing a SiteScope license and registering your copy of SiteScope gives you important rights and privileges. Registered users can access technical support and information on all HP products and are eligible for free updates and upgrades. You are also given access to the HP Software Support Web site. You can use this access to search for technical information in the HP Software Self-solve knowledge base as well as downloading updates to the SiteScope documentation.

---

**Note:** The license mechanism has changed, and license keys from previous versions of SiteScope are not compatible with this version. License key delivery can be fulfilled automatically through <http://webware.hp.com>.

---

## Understanding SiteScope License Types

To use SiteScope, you must have a valid license. You can install SiteScope using a general license, or use the 60-day evaluation license that is available with each new installation or download of SiteScope. You can also purchase extension licenses to enable the use of SiteScope solution templates and optional monitors.

These are the different types of SiteScope license:

Type	Description	Duration	Points Displayed
<b>General License</b>	Enables the standard functionality of SiteScope, based on the number of monitor points included as part of the license. It does not include monitors that require an extension license.	This license type can be temporary (time-based) or permanent.	Displays the total number of points purchased with the license.

Type	Description	Duration	Points Displayed
<b>Evaluation License</b>	<p>During the free evaluation period, enables the standard functionality of SiteScope and usage of the following additional monitors:</p> <ul style="list-style-type: none"> <li>➤ Microsoft Exchange (via the solution templates)</li> <li>➤ SAP</li> <li>➤ Siebel</li> <li>➤ Web Script</li> <li>➤ WebSphere MQ Status</li> </ul> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>➤ Not all monitors included in the Evaluation license are included when upgrading to a General license. For the list of monitors that require additional licensing, see "Extension License" below.</li> <li>➤ After the evaluation period expires or the license is upgraded, monitors and solution templates that are not included in the General license are no longer available.</li> </ul>	<p>Fixed trial period of up to 60 days.</p> <p><b>Note:</b> The trial period terminates immediately once a permanent or time-based license is purchased.</p>	500 points
<b>OS Instance License</b>	<p>System monitors can be licensed by OS instance instead of points. For license details and the list of monitor types supported by this license, see "OS Instance Advanced license" on page 40.</p>	<p>This license type can be temporary (time-based) or permanent.</p>	<p>Displays the total number of OS/host licenses purchased.</p>
<b>Failover License</b>	<p>While SiteScope Failover is freely available out-of-the-box, it still requires a separate Failover license in case the general license is node locked on the primary SiteScope server. This license is applied on the SiteScope Failover when the primary SiteScope server is down.</p>	<p>This license type can be temporary (time-based) or permanent.</p>	<p>Displays the total number of points purchased with the primary SiteScope license.</p>

Type	Description	Duration	Points Displayed
<p><b>Extension License</b></p>	<p>Each extension license enables a specific solution template or an optional monitor type.</p> <p><b>Solution templates:</b></p> <ul style="list-style-type: none"> <li>▶ Active Directory</li> <li>▶ Microsoft Exchange</li> <li>▶ HP Quality Center</li> <li>▶ HP Service Manager</li> <li>▶ Microsoft IIS 6</li> <li>▶ Microsoft SQL Server</li> <li>▶ JBoss</li> <li>▶ .NET</li> <li>▶ Oracle Database</li> <li>▶ Operating System</li> <li>▶ Siebel</li> <li>▶ SAP</li> <li>▶ WebLogic Application Server</li> <li>▶ WebSphere Application Server</li> </ul> <p><b>Monitor types:</b></p> <ul style="list-style-type: none"> <li>▶ COM+ Server Monitor</li> <li>▶ SAP</li> <li>▶ Siebel</li> <li>▶ Web Script Monitor</li> <li>▶ WebSphere MQ Status Monitor</li> </ul>	<p>This license type can be temporary or permanent.</p>	<p>No points. Each monitor has its own point consumption. For details, see "License Point Usage For Monitors" on page 42 and "License Point Usage For Solution Templates" on page 52.</p>

The table below summarizes the differences between General and Extension licenses.

Topic	General License	Extension License
Number of installations per license key	Each installation of SiteScope requires a distinct general license key.	Each installation of SiteScope requires a distinct extension license to enable the optional functionality for that SiteScope server.
Monitor points	The license key includes a preset number of monitor points. The monitor points determine how many monitor instances can be created and how many metrics can be measured on an individual SiteScope server.	The extension license key enables extension monitor types for the SiteScope installation on which it is used. The extension license key does not increase the total number of monitor points governed by the general license key.  The monitor points used for creation of optional monitor types are deducted from total monitor points included in the general license key.
	For details on monitor point usage, see "Understanding Monitor Licensing" on page 38.	
Entering license key	General license keys can be imported from the license file selected in the Settings screen when installing SiteScope, or after installing SiteScope in the General Preferences page during the free evaluation period.	Extension license keys can be imported from the license file selected in the Settings screen when installing SiteScope, or after installing SiteScope in the General Preferences page.
	For details on importing a license file when installing SiteScope, see "License file" on page 107.  For details on importing a license file in the General Preferences page, see "Adding SiteScope Licenses" on page 58.	

SiteScope automatically sends an email notification 7 days before your license is about to expire, and a pop-up message is displayed each time you open SiteScope.

If you need to upgrade or renew your SiteScope license, visit the HP License Key Delivery Service site (<https://webware.hp.com/licensinghome/hppwelcome.asp>).

## Understanding Monitor Licensing

Licensing for SiteScope is based on a points system. The number of points consumed by SiteScope depends on the type of license that was purchased and the number and type of monitors being used.

This section includes:

- "Point System" on page 39.
- "OS Instance Advanced license" on page 40.
- "License Point Usage For Monitors" on page 42
- "License Point Usage For Solution Templates" on page 52

---

**Note:**

- SiteScope does not have user-based access licensing. There is no limit to the number of users that can access the SiteScope application server.
  - Each license can be node locked to avoid possible license confusion and abuse. This means that the license is only valid on a specific machine.
-

## Point System

Licensing for monitor types is based on a point system. A permanent SiteScope license provides a number of points that you use to activate a combination of monitor types.

The number of SiteScope monitors that you can create is based on two factors:

- ▶ total number of monitor points you have purchased
- ▶ types of SiteScope monitors you want to use

The monitor types are divided into categories based on how many points you need to activate them. For example, to set up one URL Monitor for a Web page, you need one monitor point per monitor instance. To set up an Apache Server Monitor, you need one monitor point for each server performance metric you want to monitor.

To set up a Microsoft Windows Resources Monitor or UNIX Resources Monitor, you need one monitor point per object instance. When you set up these monitors, you first select an object, then the relevant instances for the object, and then the relevant counters for each instance. In the following example for a Microsoft Windows Resources Monitor, the object selected is Process, the instance selected is explorer, and the counters selected are % Processor Time and % User Time. This costs one point for the explorer instance. If you selected another instance to monitor, it would cost two points, and so forth.

Available Measurements

Objects: Process

Instances:

All

- lida
- smss
- explorer
- FrameMaker

Counters:

All

- Working Set
- % User Time
- IO Other Byte
- Page File Bvt

Selected Measurements

Object	Instance	Counter
Process	explorer	% Processor Time
Process	explorer	% User Time

Total counters: 2

## OS Instance Advanced license

System monitors can be licensed by OS instance instead of points for the number of monitors used. For example, if you are using a CPU, a Disk Space, and a Memory monitor on the same operating system or host, this is counted as one OS instance, instead of counting monitors and points. For the list of supported monitors, see "OS Instance Advanced license - Supported Monitors" on page 41.

SiteScope applies the available OS Instance Advanced licenses to the busiest servers—the ones with the highest number of points consumed by supported monitors on the server. Points consumed by those monitor instances are freed, and can be used by other monitors that are not covered by the OS license.

You can view details of OS instance license consumption in **Preferences > General Preferences > Licenses**. The Point Consumption Per OS/Host table includes the OS instances covered by the license, license points used compared to the number of points required, and the number of points saved per host using the OS Instance Advanced license.

When an OS Instance Advanced license expires or is removed, all monitors belonging to hosts that had used the OS License, start consuming points. This may lead to a situation where the number of license points used by SiteScope monitors exceeds the number of points available. In this event, SiteScope sends a message that it will shut down within 7 days. To avoid a SiteScope shutdown, you should add more license points or reduce the number of monitors being used. To add more points, contact the HP License Key Delivery Service, and request a new license.

---

**Note:** The SAM license is not affected by the OS Instance Advanced license. SAM points are still counted for monitors reporting to BSM which appear under the OS Instance Advanced license. This information is displayed in the OS Instance License consumption report (total potential point usage and/or SAM point usage).

---



## **OS Instance Advanced license - Supported Monitors**

OS instance based licensing is used for the following monitor types.

- Amazon Web Services
- CPU
- Directory
- Disk Space
- File
- HP NonStop Event Log
- HP NonStop Resources
- Memory
- Microsoft Hyper-V
- Microsoft Windows Event Log
- Microsoft Windows Performance Counter
- Microsoft Windows Resources
- Microsoft Windows Services State
- Ping
- Port
- Service
- Solaris Zones
- UNIX Resources
- VMware Performance

## License Point Usage For Monitors

The following lists the point usage for each instance of the various SiteScope monitor types:

Monitor (A-Z)	Monitor Category	License Point Usage
Amazon Web Services	Server	1 point per metric <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Apache Server	Application	1 point per metric
BroadVision Application Server	Application	1 point per metric
Check Point	Application	1 point per metric
Citrix	Application	1 point per metric
ColdFusion Server	Application	1 point per metric
COM+ Server	Application	1 point per metric <b>Note:</b> Additional licensing is required to enable this monitor type in the SiteScope interface.
Composite	Generic	1 point per monitor <b>Note:</b> The sequence checking and compound monitoring functions provided by this monitor is used to group member monitors, which are counted at the applicable monitor point rate. This monitor can be set up at no additional cost in monitor points beyond that of the member monitors which they contain.

Monitor (A-Z)	Monitor Category	License Point Usage
CPU	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Database Counter	Database	1 point per metric
Database Query	Database	1 point per monitor
DB2 8.x and 9.x	Database	1 point per metric
DHCP	Server	1 point per monitor
Directory	Generic	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Disk Space	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
DNS	Network	1 point per monitor

Monitor (A-Z)	Monitor Category	License Point Usage
e-Business Transaction	Web Transaction	1 point per monitor
F5 Big-IP	Application	1 point per metric
File	Generic	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> </ul> If SiteScope is connected to HP Operations Manager.
Formula Composite	Network	1 point per monitor*
FTP	Network	1 point per monitor
HP iLO (Integrated Lights-Out)	Server	1 point per metric
HP NonStop Event Log	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>

Monitor (A-Z)	Monitor Category	License Point Usage
HP NonStop Resources	Server	1 point per object instance <b>Note:</b> <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
IPMI	Server	1 point per metric (Maximum: 120)
JMX	Generic	1 point per monitor
LDAP	Generic	1 point per monitor
Link Check	Web Transaction	1 point per monitor
Log File	Generic	1 point per monitor
Mail	Network	1 point per monitor
MAPI	Network	1 point per monitor
Memory	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Microsoft ASP Server	Application	1 point per metric
Microsoft Exchange 2007/2010	Application	1 point per metric

Monitor (A-Z)	Monitor Category	License Point Usage
Microsoft Exchange 2003 Mailbox	Application	3 points per monitor
Microsoft Exchange 2000/2003/2007 Message Traffic	Application	5 points per monitor
Microsoft Exchange 5.5 Message Traffic	Application	5 points per monitor
Microsoft Exchange 2003 Public Folder	Application	5 points per monitor
Microsoft Hyper-V	Virtualization	1 point for each monitored VM or physical server. <b>Note:</b> No points are consumed by this monitor if it is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.
Microsoft IIS Server	Application	1 point per metric
Microsoft SQL Server	Database	1 point per metric
Microsoft Windows Dial-up	Network	1 point per monitor
Microsoft Windows Event Log	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Microsoft Windows Media Player	Stream	1 point per metric

Monitor (A-Z)	Monitor Category	License Point Usage
Microsoft Windows Media Server	Stream	1 point per metric
Microsoft Windows Performance Counter	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Microsoft Windows Resources	Server	1 point per object instance <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Microsoft Windows Services State	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Network Bandwidth	Network	1 point per metric
News	Application	1 point per monitor
Oracle 10g Application Server	Application	1 point per metric

Monitor (A-Z)	Monitor Category	License Point Usage
Oracle 9i Application Server	Application	1 point per metric (Maximum: 7)
Oracle Database	Database	1 point per metric
Ping	Network	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Port	Network	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Radius	Application	1 point per metric
Real Media Player	Stream	1 point per metric
Real Media Server	Stream	1 point per metric
SAP CCMS	Application	1 point per metric
SAP CCMS Alert	Application	1 point per metric
SAP Java Web Application Server	Application	1 point per metric
SAP Performance	Application	1 point per metric
SAP Work Processes	Application	1 point per metric



Monitor (A-Z)	Monitor Category	License Point Usage
Script	Generic	1 point per monitor
Service	Server	1 point per monitor <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
Siebel Application Server	Application	1 point per metric
Siebel Log	Application	1 point per monitor
Siebel Web Server	Application	1 point per metric
SNMP	Network	1 point per monitor
SNMP by MIB	Network	1 point per metric
SNMP Trap	Network	1 point per monitor
Solaris Zones	Virtualization	1 point for each monitored zone (global or non-global) or physical server. <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
SunONE Web Server	Application	1 point per metric
Sybase	Database	1 point per metric
Tuxedo	Application	1 point per metric

Monitor (A-Z)	Monitor Category	License Point Usage
UDDI Server	Application	1 point per monitor
UNIX Resources	Server	1 point per object instance selected <b>Note:</b> <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>
URL	Web Transaction	1 point per monitor
URL Content	Web Transaction	1 point per monitor
URL List	Web Transaction	1 point per URL
URL Sequence	Web Transaction	1 point per URL (Step)
VMware Performance	Virtualization	1 point for each monitored VM or physical server. <b>Note:</b> No points are consumed by this monitor if: <ul style="list-style-type: none"> <li>▶ It is running on a host covered by the OS Instance Advanced license. For details, see "OS Instance Advanced license" on page 40.</li> <li>▶ If SiteScope is connected to HP Operations Manager.</li> </ul>

Monitor (A-Z)	Monitor Category	License Point Usage
Web Script	Web Transaction	4 points per transaction run by the monitor. A transaction can include as many URLs as needed. The monitor can include up to 12 measurements per transaction.
Web Server	Server	1 point per monitor
Web Service	Generic	1 point per monitor
WebLogic Application Server	Application	1 point per metric
WebSphere Application Server	Application	1 point per metric
WebSphere MQ Status	Application	1 point per instance
WebSphere Performance Servlet	Application	1 point per metric
XML Metrics	Generic	1 point per metric

## License Point Usage For Solution Templates

Solution templates are optimized monitor templates that include both optional and standard monitor types. Access to the template and the template-specific monitor types requires an extension license. Purchase of the extension license also includes access to Best Practices documentation for the specific solution template.

License point usage is based on the solution template cost, which is based on the number of points consumed by the monitors deployed by the template (each monitor has its own point consumption).

The table below displays the license points cost for solution templates that were configured on HP test environments. Note that license point consumption varies from one environment to another, depending on the size of the environment being monitored and the number of counters selected.

Solution Template	Typical License Point Usage
Active Directory with Global Catalog	34
Active Directory with no Global Catalog	33
AIX Host	13
ASP.NET	20
ASP.NET Applications	1
HP Quality Center Application Server for UNIX	11
HP Quality Center Application Server for Windows	11
HP Quality Center 10.0 License Status	12
HP Quality Center 9.2 License Status	6
HP QuickTest Professional License Server	3
HP Service Manager for UNIX	48
HP Service Manager for Windows	12
JBoss Application Server 4.x	3

Solution Template	Typical License Point Usage
Linux Host	13
Microsoft Exchange 2000	40
Microsoft Exchange 2003	49
Microsoft Exchange 2007	83
Microsoft Exchange 5.5	39
Microsoft IIS 6	98
Microsoft SQL Server 2005	18
Microsoft Windows Host	13
.NET CLR Data	1
Oracle Database 9i and 10g	202
SAP NetWeaver Application Server	13
SAP R/3 Application Server	13
Siebel Application Server 6.x-7.x for UNIX	93
Siebel Application Server 6.x-7.x for Windows	91
Siebel Application Server 8.x for UNIX	98
Siebel Application Server 8.x for Windows	101
Siebel Gateway Server for UNIX	6
Siebel Gateway Server for Windows	6
Siebel Web Server for UNIX	19
Siebel Web Server for Windows	19
Solaris Host	13
WebLogic 6.x, 7.x, 8.x Application Server	51
WebLogic 9.x-10.x Application Server	63
WebSphere 5.x Application Server	20
WebSphere 6.x Application Server	24

## Estimating the Number of License Points

The number of license points that you purchase depends on how you plan to deploy SiteScope and what level of systems and services you want to monitor. The following are some guidelines for estimating the number of license points you need.

This section includes the following topics:

- "Server Health Monitoring" on page 54
- "Web Process and Content Monitoring" on page 55
- "Application Performance Monitoring" on page 55
- "Network Monitoring" on page 56
- "Purchasing Monitor Points" on page 57

### Server Health Monitoring

The number of points for Server Health Monitoring is based primarily on the number of server machines you want to monitor. Each server to be monitored requires one point for each of the following:

- CPU monitoring
- each hard disk or key disk partition
- memory
- each key server process or service
- each key file, log, or directory

## Web Process and Content Monitoring

The number of points for Web process and content monitoring is based on the number of Web-based processes and pages you want to monitor. Web-based processes include any sequence of Web pages. For example, logging into a secure server to verify account balances and then logging out. In many cases, the sequences of URLs includes the same path with different destination pages. For online services, it may also be necessary to check back-end databases to confirm that data modified via the Web interface is being updated correctly. Other processes may include downloading files, and sending and receiving automated email messages.

- ▶ For monitoring each Web-based URL sequence, you need one sequence monitor instance for each Web-based process to be monitored, with one point for each URL or step in the sequence.
- ▶ For monitoring other Internet pages or processes, you need one point for each file download, email verification, or individual Web page content to be monitored.

## Application Performance Monitoring

Monitoring application performance is an important tool in assuring the availability of network-based services and detecting performance problems. Because of the complexity of many applications and systems, it is also the most difficult in terms of estimating the number of monitor points needed. SiteScope's flexible licensing model makes it easy to modify your monitoring capacity to fit your needs.

The number of points for Application Performance Monitoring is based on:

- ▶ the number of applications deployed
- ▶ the types of applications
- ▶ the number of performance metrics that are to be monitored

The performance metrics for some applications, such as some Web servers, may be available with a single monitor instance and with a metric count of less than 10 metric points. For example, an Apache Web server presents its performance metrics on a single URL that includes the total number of accesses, the server uptime, and requests per second. Other applications and systems may involve multiple server addresses, modules, and metrics that require multiple monitor instances. Some applications may also be integrated with a database application to be monitored.

The following are guidelines for estimating points for application monitoring depending on how the data is accessed:

- ▶ one application monitor instance for each application, with one point for each performance metric to be monitored
- ▶ one monitor instance for each application status URL, with one point for each performance metric to be monitored

## **Network Monitoring**

Network monitoring includes checking both connectivity and the availability of network services that allow users to access and use the network. This includes monitoring services like DNS, DHCP, LDAP, and Radius. Depending on your network hardware and configuration, you may also be able to access network performance statistics by querying network infrastructure via SNMP using the SiteScope SNMP monitor type.

The following are guidelines for estimating the number of points for network monitoring:

- ▶ one point for each key network destination
- ▶ one point for each key network service (for example, DNS or LDAP)
- ▶ one point for each metric to be monitored over SNMP



## Purchasing Monitor Points

SiteScope Monitor points are sold in sets of 50, 100, 500, and 2000 point blocks to provide flexibility in deployment of monitors. For example, a block of 100 points enables you to set up various monitoring options:

- ▶ 10 application monitors to watch five performance metrics each ( $10 \times 5 = 50$  points)
- ▶ a combination of two URL sequence monitors that traverse 10 transaction steps each ( $2 \times 10 = 20$  points)
- ▶ 30 1-point network service or server monitors ( $30 \times 1 = 30$  points)

You could also use the same block of 100 points to set up:

- ▶ 10 application monitors watching one metric each ( $10 \times 1 = 10$  points)
- ▶ one URL Sequence monitor with five steps (5 points)
- ▶ 85 Network Service or Server monitors (85 points)

When you install SiteScope, it includes a free evaluation license. To use SiteScope beyond the evaluation period, you must request and activate a general license key for your copy of SiteScope. For more information on purchasing monitor points, visit the HP License Key Delivery Service site (<https://webware.hp.com/licensinghome/hppwelcome.asp>).

## Adding SiteScope Licenses

After you install SiteScope, you can add to your licensing at any time. For information on how to obtain a new or additional monitoring licenses, visit the HP License Key Delivery Service site (<https://webware.hp.com/Welcome.asp>).

When you receive your license file from HP, import the license keys into SiteScope using the browser interface.

### To add a license in SiteScope:

- 1** From a Web browser, open the SiteScope instance you want to modify. The SiteScope service or process must be running.
- 2** Select **Preferences > General Preferences**, and expand the **Licenses** pane.
- 3** Enter the path to your SiteScope license file in the **License file** box, or click the **Select** button, and select the license file.
- 4** Click **Import**. After licenses have been successfully imported, information about the imported licenses is displayed in the licenses table. This includes the license type, description, expiration date, and the total number of monitor points permitted by the license.

# Part II

---

## Before Installing SiteScope



# 6

---

## Before You Install SiteScope

**This chapter includes:**

- ▶ Installation Overview on page 62
- ▶ System Requirements on page 64
- ▶ Certified Configuration on page 70
- ▶ SiteScope Capacity Limitations on page 71
- ▶ HP SiteScope Support Matrixes on page 72

## Installation Overview

There are several planning steps and actions you should consider before you install SiteScope to facilitate the deployment and management of your monitoring environment.

The following is an overview of the steps involved in deploying the SiteScope application.

### 1 Prepare a server where the SiteScope application is to be installed and run.

---

#### Note:

- ▶ It is recommended not to install more than one SiteScope on a single machine.
  - ▶ If upgrading from an earlier version of SiteScope, check the current configuration for end of life monitors and make a backup copy of key SiteScope data. For more information, see "Upgrading SiteScope" on page 75.
  - ▶ If you plan to use SiteScope Failover to provide backup monitoring availability in case of a SiteScope server failure, you must install SiteScope on a shared resource. For details, see the *SiteScope Failover Guide* located in <SiteScope root directory>\sisdocs\pdfs\**SiteScopeFailover.pdf**.
-

- 2 Obtain the SiteScope installation executable.**
- 3 Create a directory where the application is installed and set user permissions as necessary.**

---

**Note:** You must create a new directory for installation of SiteScope 11.00. Do not install version 11.00 into a directory used for a previous version of SiteScope.

---

- 4 Run the SiteScope installation executable or installation script, directing the script to install the application into the location you have prepared.**  
For more information, see "Installing SiteScope" on page 89.
- 5 Restart the server if necessary (Windows installations only).**
- 6 Confirm that SiteScope is running by connecting to it using a compatible Web browser.**  
For more information, see "Getting Started with SiteScope" on page 213.
- 7 Perform post-installation steps to prepare SiteScope for production use.**  
For more information, see "Post-Installation Administration" on page 209.

## System Requirements

This section describes the minimum system requirements and recommendations for running SiteScope on the various supported operating systems.

---

**Note:**

- ▶ Before beginning the installation, review the information in the HP SiteScope Release Notes file for any last minute notes and limitations regarding the installation process.
  - ▶ SiteScope can be installed as a 32-Bit application over 64-Bit environments for the supported Windows, Solaris, and Linux operating systems.
  - ▶ For troubleshooting and limitations for installing SiteScope on various environments, see "Troubleshooting and Limitations" on page 126.
- 

This section includes the following topics:

- ▶ "Server System Requirements for Windows" on page 65
- ▶ "Server System Requirements for Solaris" on page 65
- ▶ "Server System Requirements for RedHat Linux" on page 66
- ▶ "Server System Requirements for VMware" on page 66
- ▶ "Support for Monitoring 64-Bit Environments" on page 69
- ▶ "Client System Requirements" on page 69



## Server System Requirements for Windows

Use these system requirements when installing SiteScope on Windows platforms:

<b>Computer/Processor</b>	800 MHz or higher
<b>Operating System</b>	<ul style="list-style-type: none"> <li>▶ Microsoft Windows 2003 Standard/Enterprise SP1, SP2,</li> <li>▶ Microsoft Windows Server 2003 Enterprise R2 SP1, SP2</li> <li>▶ Microsoft Windows Server 2008 Standard/Enterprise R2, SP2</li> <li>▶ Microsoft Windows Server 2008 R2 Hyper-V</li> </ul>
<b>Memory</b>	1 GB minimum (2 GB or more is recommended)
<b>Free Hard Disk Space</b>	2 GB or more (10 GB or more is recommended)
<b>Java Plug-in (to view applets)</b>	JRE 1.6.0_14 or later

## Server System Requirements for Solaris

Use these system requirements when installing SiteScope on Solaris platforms:

<b>Computer/Processor</b>	Sun 400 MHz UltraSparc II Processor or higher
<b>Operating System</b>	Sun Solaris 9 or 10 (with latest recommended patch cluster)
<b>Memory</b>	1 GB minimum (2 GB or more is recommended)
<b>Free Hard Disk Space</b>	2 GB or more (10 GB or more is recommended)
<b>Java Plug-in (to view applets)</b>	JRE 1.6.0_14 or later

---

**Note:** To view SiteScope Management Reports on Solaris platforms, an X Window system must be running on the SiteScope server.

---

## Server System Requirements for RedHat Linux

Use these system requirements when installing SiteScope on RedHat Linux platforms:

<b>Computer/Processor</b>	800 MHZ or higher
<b>Operating System</b>	RedHat ES/AS Linux 4, 4.3, 5.2 <b>Note:</b> RedHat Linux 9 with Native POSIX Threading Library (NPTL) is not supported after this version of SiteScope.
<b>Memory</b>	1 GB minimum (2 GB or more is recommended)
<b>Free Hard Disk Space</b>	2 GB or more (10 GB or more is recommended)
<b>Java Plug-in (to view applets)</b>	JRE 1.6.0_14 or later

## Server System Requirements for VMware

The following VMware environments are supported in SiteScope according to the configurations tested below:

<b>Supported and Tested Environments</b>	<ul style="list-style-type: none"> <li>▶ VMware ESX 3.0</li> <li>▶ VMware VirtualCenter 3.0</li> </ul>
<b>Supported Environments Only</b>	<ul style="list-style-type: none"> <li>▶ VMware VirtualCenter 2.x</li> <li>▶ VMware ESX 2.5 via VirtualCenter 2.x</li> <li>▶ VMware ESX 3.x</li> <li>▶ VMware ESX 3.x via VirtualCenter 3.x</li> <li>▶ VMware vCenter Server 4.0</li> <li>▶ VMware ESX 4.0</li> <li>▶ VMware ESXi 4.0</li> </ul>

<p><b>VMware Configuration Tested</b></p>	<ul style="list-style-type: none"> <li>▶ 4 VMware Virtual Machines (VM) on one physical server</li> <li>▶ Each VM with 2 CPUs at 2.39Ghz, 8 GB memory, and 40 GB disk space</li> <li>▶ Storage used is HP EVA 8400/22G</li> <li>▶ Physical server: ESX host is HP BL490c G6 with 8x Intel Xeon x5570 CPU, 72GB RAM with VMware ESX 4.0 U1</li> <li>▶ No other VMs resident on this physical server</li> <li>▶ VMTools installed</li> </ul>
<p><b>SiteScope Configuration Tested</b></p>	<ul style="list-style-type: none"> <li>▶ Each SiteScope monitors:             <ul style="list-style-type: none"> <li>▶ 33 SUN remote servers</li> <li>▶ 2 Linux remote servers</li> <li>▶ ~100 servers in domain (Windows Resources Monitor)</li> <li>▶ 696 Windows remote servers</li> </ul> </li> <li>▶ Around 8880 monitors of the following type were created on each SiteScope:             <ul style="list-style-type: none"> <li>▶ CPU</li> <li>▶ Memory</li> <li>▶ DiskSpace</li> <li>▶ Windows Resources</li> <li>▶ Windows Event Logs</li> <li>▶ Windows Services State</li> <li>▶ Windows Performance Counters</li> <li>▶ Ping</li> <li>▶ Post</li> <li>▶ Service</li> <li>▶ UNIX Resources</li> </ul> </li> <li>▶ Around 900 monitor runs/min.</li> </ul>

Use these minimum system requirements when installing SiteScope on VMware environments (note that these are recommendations based on a tested environment, and are not support limitations):

<b>Computer/Processor</b>	4 Intel Xeon physical processors, 2 GHz each
<b>Operating System</b>	Microsoft Windows 2003 Standard/Enterprise SP1 (all operating systems supported on the physical server are of course supported on the VM server)
<b>Memory (RAM)</b>	4 GB
<b>Free Hard Disk Space</b>	20 GB (Hard Disk speed: 7200 rpm)
<b>Network Card</b>	1 physical gigabit Network Interface Card
<b>Other Software</b>	VMTools must be installed
<b>Java Plug-in (to view applets)</b>	JRE 1.6.0_14 or later

---

**Note:** Monitor capacity and velocity can be significantly impacted by numerous factors including, but not limited to the following: SiteScope server hardware, operating system, patches, third-party software, network configuration and architecture, location of the SiteScope server in relation to the servers being monitored, monitor types and distribution by type, monitor frequency, monitor execution time, Business Service Management integration, and Database Logging. The published maximums should not be assumed to be possible in every environment.

---

## Support for Monitoring 64-Bit Environments

SiteScope supports monitoring on the following 64-bit environments:

<b>Operating System</b>	<ul style="list-style-type: none"> <li>▶ Windows 2003 Server 64-Bit</li> <li>▶ Windows 2008 Server 64-Bit</li> <li>▶ Solaris 64-Bit</li> <li>▶ HP-UX 64-Bit</li> <li>▶ Linux 64-Bit</li> </ul>
<b>Supported SiteScope Monitors</b>	<ul style="list-style-type: none"> <li>▶ CPU Monitor</li> <li>▶ Disk Space Monitor</li> <li>▶ Memory Monitor</li> <li>▶ Microsoft Windows Resources Monitor</li> <li>▶ Microsoft Windows Event Log Monitor</li> <li>▶ Service Monitor</li> <li>▶ UNIX Resources Monitor</li> </ul>

## Client System Requirements

SiteScope client is supported by the following:

- ▶ All Microsoft Windows operating systems (including Microsoft Windows 7) using Microsoft Internet Explorer 7.x-8.0.
- ▶ Firefox 3.0x (certified on clients running on Windows environments only).

## Certified Configuration

The following configuration has been certified in a high load environment for an installation of SiteScope that was integrated with HP Business Service Management.

<b>Operating System</b>	Microsoft Windows Server 2003, Enterprise Edition Version: 5.2.3790 Service Pack 2 Build 3790
<b>System Type</b>	x86-based PC
<b>CPU</b>	4 Intel Xeon 5160 physical processors, 3 GHz each
<b>Total Physical Memory (RAM)</b>	16 GB
<b>Java Heap Memory</b>	1024 MB
<b>Total Number of Monitors</b>	16000
<b>Total Number of Remote Servers</b>	1250
<b>Monitor Runs per Minute</b>	2000

---

**Note:**

- Negative Topaz ID errors in the log should be ignored.
  - When working under high load, you should suspend all monitors before connecting to HP Business Service Management for the first time.
-

## SiteScope Capacity Limitations

When SiteScope is integrated with Business Service Management, performing various very high load operations might cause problems in SiteScope. Use the following guidelines:

- ▶ Do not run the Publish Template Changes Wizard for over 3,000 monitors at once.
- ▶ Do not run the Monitor Deployment Wizard to create over 3,000 monitors at once.
- ▶ Do not copy/paste over 3,000 monitors in a single action.
- ▶ Do not perform a Global Search and Replace to modify Business Service Management integration properties for over 2,500 monitors at one time.

SiteScope includes a tool that helps you predict system behavior and perform capacity planning for SiteScope. For details, see "SiteScope Capacity Calculator" on page 148.

## HP SiteScope Support Matrixes

This section describes matrixes for the following environments and components supported by HP SiteScope.

- "Business Service Management" on page 72
- "Business Process Monitor Support Matrix" on page 72
- "HP Operations Manager Support Matrix" on page 73

### Business Service Management

HP SiteScope Version	HP Business Service Management Version			
	9.00	8.0x	8.00	7.x
SiteScope 11.00	Recommended	Supported	Supported	Not Supported

### Business Process Monitor Support Matrix

Installation of SiteScope and Business Process Monitor is supported on a single server without any configuration changes required.

HP SiteScope Version	Business Process Monitor Version	
	9.00	8.03
SiteScope 11.00	Recommended	Supported



## HP Operations Manager Support Matrix

The following table displays the versions of HP Operations Manager that are compatible with SiteScope 11.00.

HP SiteScope Version	HP Operations Manager for UNIX	HP Operations Manager for Windows
	9.0x	8.1x
SiteScope 11.00	Supported	Supported

---

**Note:** The HP Operations agent is not supported on SiteScopes running on the following environments (consequently, the SiteScope integration with HPOM and BSM is not supported):

- RedHat ES/AS Linux 4, 4.3 (32-bit and 64-bit). Linux 4 and 4.3 (64-bit) are however supported using a 32-bit version of the agent.
  - VMware ESX 2.x, 3.0, 4.0
  - VMware ESX 2.5 via VirtualCenter 2.x
  - VMware ESX 3.x via VirtualCenter 3.x
  - VMware vCenter Server 4.0
  - VMware ESXi 4.0.
-



# 7

---

## Upgrading SiteScope

**This chapter includes:**

- Before Performing the Upgrade on page 76
- Upgrading an Existing SiteScope Installation on page 77
- Using the End of Life Monitor Viewer on page 78
- Backing Up SiteScope Configuration Data on page 81
- Naming the SiteScope Directory on page 82
- Importing Configuration Data on page 82
- Troubleshooting and Limitations on page 83

## Before Performing the Upgrade

This chapter describes how to upgrade existing HP SiteScope installations to HP SiteScope 11.00 with the minimum possible interruption to your system and operations.

SiteScope is designed for backward compatibility. This means you can install newer versions of SiteScope and transfer monitor configurations from an existing SiteScope installation with a minimum of disruption to your monitoring environment.

Before upgrading SiteScope, you should consider the following:

- ▶ Before beginning the upgrade, review the information in the SiteScope Release Notes file for any last minute notes and limitations regarding the upgrade process. Failure to follow procedures listed in the Release Notes could result in unexpected data loss or failure of the upgrade process.
- ▶ You can upgrade SiteScope versions 10.x directly to SiteScope 11.00. For versions of SiteScope earlier than 10.00, you must first upgrade to SiteScope 10.x. For versions of SiteScope earlier than 9.x, you must first upgrade to SiteScope 9.x.
- ▶ If your SiteScope configuration contains a group with more than 100 large subgroups, a memory overflow may occur during upgrade to SiteScope 11.00. Before you upgrade, you should split the problematic level of subgroups to contain less than 100 subgroups.
- ▶ Since SiteScope version 10.10, the HTTP method for connecting to a UNIX remote server is no longer supported. If during an upgrade, SiteScope finds a UNIX remote server that uses the HTTP method, the upgrade process fails. To avoid this, change the method property in the version to be upgraded to one of the other valid options (ssh, telnet, or rlogin). For a list of affected UNIX remote servers, see the `<SiteScope root directory>\logs\upgrade.log` file.

## Upgrading an Existing SiteScope Installation

It is recommended that you perform the following steps for upgrading:

- 1 Run the End of Life Monitor Viewer to ensure that end of life monitors do not exist in the current deployment.**

You must perform this step before installing a new version of SiteScope. For more information, see "Using the End of Life Monitor Viewer" on page 78.

- 2 Make a backup copy of key SiteScope data using the Configuration Tool.**

You must perform this step before installing a new version of SiteScope. For more information, see "Backing Up SiteScope Configuration Data" on page 81.

- 3 Install newer versions of SiteScope in a clean directory structure.**

For information on naming the directory, see "Naming the SiteScope Directory" on page 82.

For information on installing SiteScope, see "Installing SiteScope" on page 89.

- 4 After installation, import monitor configuration data from earlier versions of SiteScope using the Configuration Tool.**

For more information, see "Importing Configuration Data" on page 82.

- 5 After importing data from earlier versions of SiteScope, start SiteScope by running the batch file/start command shell script.**

To avoid SiteScope restarting itself after an upgrade if it takes longer than 15 minutes for the monitors to run, start SiteScope by running the **go.bat** file from the <SiteScope root directory>\bin directory (on Windows platforms), or by running the start command shell script using the syntax <installpath>/SiteScope/start (on Solaris or Linux platforms).

## Using the End of Life Monitor Viewer

The End of Life Monitor Viewer is an external tool that you can run on SiteScope configurations on any platform before an upgrade to check if the current configuration has any end of life monitors. Using the End of Life Monitor Viewer, you can prepare the SiteScope configuration for upgrade as follows:

- ▶ View details of end of life monitors (including template monitors). You can see monitor properties, monitor paths, and the recommended alternative monitor for the monitor type.
- ▶ Export this list of monitors with their properties to a .txt file.

---

**Note:** You cannot add, edit, or delete end of life monitors using the End Of Life Monitor Viewer.

---

### Running the End of Life Monitor Viewer

Run the End of Life Monitor Viewer on the SiteScope configuration to ensure that end of life monitors do not exist in the current deployment.


**To run the End of Life Monitor Viewer:**

- 1** Insert the installation media containing the SiteScope 11.00 software into the drive on the SiteScope machine you want to upgrade.
- 2** In the `\EndOfLifeMonitorViewer\<platform>` folder, extract the contents of the `upgrade.tools.zip` file to the `<SiteScope root directory>`.
- 3** From the `<SiteScope root directory>\upgrade` folder, run `EndOfLifeMonitorsViewer.bat` on Windows platforms, or `EndOfLifeMonitorsViewer.sh` file on Solaris or Linux platforms. The End of Life Monitor Viewer opens.
- 4** Click the **Select Persistency Path** button. The Open dialog box opens.
- 5** Enter the path to the persistency folder and click **Open**.


- 6 The End of Life Monitor Viewer checks the SiteScope configuration for end of life monitors, and displays the results.

If the configuration has end of life monitors, the following properties are displayed:


- Monitor ID
- End of life monitor name
- Full Path of the monitor
- Alternative monitor (if one exists)



Double-click a monitor row to display monitor details.



To view property details, select a property and click the **View Details** button.





- 7 To export information about the end of life monitors, select the monitors that you want to include in the .txt file and click **Export**. Enter the file name and location to which you want to save the file, and click **Save**. The selected monitors with their properties are saved in .txt format.
- 8 In the current SiteScope user interface, replace any end of life monitors with the recommended alternative monitors, and delete the end of life monitors.

For the lists of end of life and replacement monitors, see "List of Deprecated SiteScope Monitors" and "List of Deprecated Integration Monitors" in SiteScope Help.

## Backing Up SiteScope Configuration Data

The simplest way to prepare for a SiteScope upgrade is to use the Configuration Tool to make a backup of your current SiteScope installation directory and all of the subdirectories within the directory. Alternatively, you can manually back up your SiteScope installation. For details, see "Backing up and recovering a SiteScope installation if unable to start SiteScope" on page 220.

Using the Configuration Tool, you can export SiteScope data such as templates, logs, monitor configuration files, and so forth from your current SiteScope for later import into SiteScope. The user data is exported to a ZIP file.

---

**Note:** You should make a backup of the <SiteScope>\htdocs directory and copy it to the SiteScope 11.00 directory after an upgrade so that you can see old reports, since this directory is not copied when you export SiteScope data.

---

For details on exporting SiteScope data using the Configuration Tool, see "Using the SiteScope Configuration Tool" on page 133.

Alternatively, you can have SiteScope export SiteScope data as part of the installation process. For details, see "Installing SiteScope" on page 89.

## Naming the SiteScope Directory

The new directory you create for installing SiteScope must be named **SiteScope** and be located in a different directory path. For example, if the original SiteScope directory was C:\SiteScope, the new directory could be C:\11.00\SiteScope.

## Importing Configuration Data

After upgrading SiteScope, monitor configuration data can be copied into SiteScope 11.00 from earlier versions of SiteScope using the Configuration Tool. For details, see "Using the SiteScope Configuration Tool" on page 133.

Alternatively, if you manually created a back up, you must delete from the new installation directory all the folders and files that you backed up, and then copy the backed up folders and files to the installation directory. For details, see "Backing up and recovering a SiteScope installation if unable to start SiteScope" on page 220.

## Troubleshooting and Limitations

This section describes troubleshooting and limitations for SiteScope upgrades.

This section includes:

- "First SiteScope Restart After Upgrade Can Take a Long Time" on page 84
- "SiteScope Fails to Get the Customer ID" on page 84
- "Default Alert Action is Named According to Action Type" on page 85
- "Business Service Management/ServiceCenter or Service Manager Integration" on page 85
- "Moving SiteScope to a Different Server When Integrated With Business Service Management" on page 86
- "SiteScope Fails to Upgrade" on page 86

---

**Note:** You can also check for other information relating to upgrading SiteScope in the HP Software Self-solve knowledge base (<http://h20230.www2.hp.com/selfsolve/documents>). To enter the knowledge base, you must log in with your HP Passport ID.

---

## First SiteScope Restart After Upgrade Can Take a Long Time

**Problem:** The first SiteScope restart after an upgrade might take a long time (more than 15 minutes). If the monitors have not started to run after 15 minutes, SiteScope restarts itself.

### Possible Solution:

- ▶ To avoid SiteScope restarting itself if it takes longer than 15 minutes for the monitors to run, start SiteScope by running the **go.bat** file from the **<SiteScope root directory>\bin** directory (on Windows platforms), or by running the start command shell script using the syntax **<installpath>/SiteScope/start** (on Solaris or Linux platforms).
- ▶ Disable any monitors that are targeting environments that are not running. This saves time waiting for the system to reply.

## SiteScope Fails to Get the Customer ID

**Problem:** In versions of SiteScope earlier than 9.0, when SiteScope is connected to Business Service Management, SiteScope stores the customer ID in a settings file under **<SiteScope root directory>\cache\persistent\TopazConfiguration**.

When loading SiteScope for the first time after upgrading to 9.x, SiteScope attempts to read the settings file and retrieve the HP Business Service Management connection details. If this file is corrupt (this could be caused by in correctly performing the export configuration), SiteScope might not be able to get the customer ID and tries to retrieve it from HP Business Service Management. If Business Service Management is down during the restart, SiteScope is unable to retrieve the customer ID, and SiteScope restarts itself again.

**Possible Solution:** Make sure that any HP Business Service Management that is connected to SiteScope is up and running before starting SiteScope after an upgrade.

## Default Alert Action is Named According to Action Type

**Problem:** Alert actions were added to SiteScope 9.0. When upgrading to any version of SiteScope 9.0 or later, a default alert action is created that is named according to the action type (for example, Email, Pager, or SMS). This might be a problem if you want the default name to be concatenated with the alert holding the action.

**Possible Solution:** Before upgrading, open the **master.config** file located in `<SiteScope root directory>\groups` and change the `_AlertActionCompositeNameDelimiter` key to contain the delimiter you want to have in the concatenation.

## Business Service Management/ServiceCenter or Service Manager Integration

This note is relevant if you are upgrading SiteScope from a pre-10.00 version and are working with the Business Service Management/ServiceCenter or Service Manager integration. When setting up the ServiceCenter monitor in SiteScope, a file called **peregrine.jar** is created and placed in the **WEB-INF\lib** directory on the SiteScope machine. This file must be backed up before upgrading SiteScope or it will be deleted during the upgrade. After the upgrade is complete, copy the backed up **peregrine.jar** file back to the **WEB-INF\lib** directory.

## Moving SiteScope to a Different Server When Integrated With Business Service Management

This process is relevant if you are moving your SiteScope server to new hardware (with a new host name and IP address) and you are working with the Business Service Management integration. Perform the following steps to minimize the impact on the integration:

- 1 Make a backup of your current SiteScope installation. For details, see "Backing Up SiteScope Configuration Data" on page 81.
- 2 Install SiteScope on the new hardware, and import the SiteScope configuration data to the SiteScope installation directory. For details, see "Importing Configuration Data" on page 82.
- 3 Configure the SiteScope server with the same port number that was used on the old hardware.
- 4 If you are working with SiteScope versions earlier than 10.10, perform the following in Business Service Management:
  - ▶ Update the relevant fields for the SiteScope profile in the New SiteScope page.
  - ▶ Update the information about the SiteScope machine in the HOSTS table.

### SiteScope Fails to Upgrade

If the upgrade process fails, check the **upgrade.log** file located in the `<SiteScope root directory>\logs` directory for reasons for the upgrade failure.

If the upgrade process fails when installing SiteScope on a Windows environment, SiteScope keeps trying to perform a restart.

**Possible Solution:** Perform the SiteScope installation again.

# Part III

---

## Installing SiteScope





# 8

---

## Installing SiteScope

### **This chapter includes:**

- Installation Flow on page 89
- Preparing for Solaris or Linux Installation on page 91
- Performing a Full Installation on page 92
- Installing on Solaris or Linux Using Console Mode on page 116
- Troubleshooting and Limitations on page 126

### **Installation Flow**

SiteScope for Windows is available as a single, self-extracting executable file that can be downloaded from the HP Web site and is also available on DVD. SiteScope is installed on a single server and run as a single application on the Windows platform.

SiteScope for Solaris and SiteScope for Linux are available as a single, compressed archive file that can be downloaded from the HP Web site. It is also available on DVD. SiteScope is installed on a single server and runs as a single application or process.

#### **1 Prepare for the SiteScope 11.00 installation (for SiteScope installations on Solaris or Linux only).**

For details see "Preparing for Solaris or Linux Installation" on page 91.

## 2 Install SiteScope 11.00.

- ▶ For details on installing on Windows, see "Performing a Full Installation" on page 92.
  - ▶ SiteScope for Solaris and SiteScope for Linux have the following installation options:
    - ▶ Multi-platform installation executable with an interactive user interface. For details, see "Performing a Full Installation" on page 92.
    - ▶ Console mode installation script using command line input. For details, see "Installing on Solaris or Linux Using Console Mode" on page 116.
  - ▶ You can also install SiteScope using a silent installation. For details, see "Installing SiteScope in Silent Mode" on page 129.
- 

### Note:

- ▶ If there is an existing version of SiteScope installed, you must uninstall it before installing SiteScope 11.00.
  - ▶ If you previously exported SiteScope data using the Configuration Tool (for details, see "Using the SiteScope Configuration Tool" on page 133), you can import the user data ZIP file.
  - ▶ If you have third-party middleware and drivers, you must copy them manually.
- 

## 3 Connect to SiteScope.

## Preparing for Solaris or Linux Installation

Depending on your environment, preparation for installation of SiteScope on Solaris or Linux involves creating a user login account, selecting a suitable installation location, and setting account permissions.

### To prepare for installation of SiteScope on Solaris or Linux:

- 1** Create a user account that runs the SiteScope application. Set the default shell for the account.
- 2** The installation location for the SiteScope application is `/opt/HP/SiteScope`. Verify that the installation location has access to sufficient disk space for the installation and operation of SiteScope.

---

### Note:

- ▶ The Solaris and Linux installation directory cannot be changed during installation, and it is not recommended to change it after installation is complete.
  - ▶ Create a new directory for installation of SiteScope 11.00. Do not install version 11.00 into a directory used for a previous version of SiteScope.
  - ▶ While SiteScope does require highly privileged account permissions to enable the full range of server monitoring, it is recommended not to run SiteScope from the root account and not to configure SiteScope to use the root account to access remote servers.
  - ▶ You can also install SiteScope using a silent installation. For details, see "Installing SiteScope in Silent Mode" on page 129.
-

## Performing a Full Installation

Use the following steps to install SiteScope on supported Windows, Solaris, or Linux environments using the multi-platform wizard. For the list of supported environments, see "System Requirements" on page 64.

The multi-platform wizard automatically executes if X11 libraries have already been installed on the server. If these libraries are not installed, you can either:

- ▶ Install SiteScope in graphic mode on a machine without an X11 server. For details, see "Installing SiteScope Using the Multi-Platform Wizard on a Machine Without X11 Server" on page 115.
- ▶ Install SiteScope on Solaris or Linux platforms in console mode. For details, see "Installing on Solaris or Linux Using Console Mode" on page 116.

---

**Note:** You can also install SiteScope using a silent installation. For details, see "Installing SiteScope in Silent Mode" on page 129.

---

### To install SiteScope:

- 1** Download the SiteScope archive from the HP Downloads site or insert the installation media containing the SiteScope software into the drive on the machine where you want to install SiteScope.
- 2** Run the SiteScope installation.
  - ▶ On Windows platforms, run the **HPSiteScope\_11.00\_setup.exe** program.
  - ▶ On Solaris or Linux platforms, run the **HPSiteScope\_11.00\_setup.bin** program.

---

**Note:** If your server has Microsoft Terminal Server service running, the service must be in **Install Mode** when you install SiteScope. If the service is not in the correct mode, the wizard gives you an error message and then exits the installation. Change to install mode using the **change user** command. For details, refer to the Microsoft support site (<http://support.microsoft.com/kb/320185>).


---

SiteScope requires the Microsoft Visual C++ 2005 Redistributable. If it is missing, the Installer prompts you to accept its installation.

- 3 The Choose Locale screen is displayed.




Click **OK** to continue with the installation. The Initialization screen is displayed.




If the Installer detects any anti-virus program running on your system, it prompts you to examine the warnings before you continue with the installation.

- 4 Read the warnings, if any, that appear in the **Application requirement check warnings** screen and follow the instructions as described in the screen.




Click **Continue** to continue with the installation.

5 In the Introduction (Install) screen that opens, click **Next**.






6 The license agreement screen opens.



Read the SiteScope License Agreement.

To install SiteScope, select **I accept the terms of the License Agreement**, and then click **Next**.

- 7 In the Product Customization screen, select the SiteScope setup type.



- **HP SiteScope.** This is the standard SiteScope installation.
- **HP SiteScope Failover.** This setup type enables you to use a backup SiteScope server to monitor infrastructure availability if a SiteScope server fails.
- **HP SiteScope for Load Testing.** This setup type is used with an HP LoadRunner or HP Performance Center installation only. It enables users to define and use SiteScope monitors on a LoadRunner or Performance Center application. SiteScope provides additional monitoring that complements the native LoadRunner and Performance Center monitors. For more details, see the relevant LoadRunner or Performance Center documentation.


---

**Note:** This installation option is not available when installing on Solaris or Linux platforms.

---

Click **Next** to continue.


8 The Select Features screen opens, displaying the HP SiteScope folder.



Click **Next** to continue.

- 9 If installing on Solaris or Linux platforms, SiteScope is automatically installed in the `/opt/HP/SiteScope/` folder. Skip to step 10 on page 102.

The Choose the folders screen opens.




Accept the default directory location, or click **Browse** to select another directory. If you select another directory, the installation path must not contain spaces in its name and must end with a folder named **SiteScope** (the folder name is case sensitive). To restore the default installation path, click **Reset**.

**Note if using SiteScope Failover:** If you plan to use SiteScope Failover to provide a backup monitoring availability, you must install SiteScope as a shared resource.

- On Windows, you must install SiteScope using the UNC path of the SiteScope installation folder. For example,  
\\lab1\users\SiteScopes\Version\_11.0\Build\_2000\SiteScope
  - On Linux or Solaris, you must mount the shared resource to the **/opt/HP/SiteScope** folder.
- 

Click **Next** to continue.

- 10 The Install Checks screen opens and runs verification checks.




Click **Next** after the free disk space verification is completed successfully.

If the free disk space verification is not successful, do the following:

- Free disk space, for example by using the Windows Disk Cleanup utility.
- Repeat steps 9 and 10.


**11** In the Pre-Install Summary screen, click **Install**.

The Installer selects and installs the required SiteScope software components. Each software component and its installation progress is displayed on your screen during installation.



The Installer installs the Microsoft Visual C++ 2005 Redistributable, if required, and resumes the SiteScope installation.

- 12 After installing the SiteScope components, the Introduction screen of the SiteScope Installation Wizard opens.



Click **Next**.



**13** The Settings screen of the SiteScope Configuration Wizard opens.

The screenshot shows the 'Settings' screen of the HP SiteScope Configuration Wizard. The window title is 'HP SiteScope Configuration Wizard'. On the left, a navigation pane lists the steps: Introduction, Settings (selected), Import Configuration, HP Operations Agent, Summary, and Done. The main content area is titled 'Settings' and contains the instruction 'Enter values for the following deployment settings:'. It is divided into four sections: 'Basic settings' with fields for 'Port' (8080) and 'Administrator email'; 'License' with a 'License file' field and a 'Select ...' button; 'SiteScope service settings' with a 'Service name' field (SiteScope), radio buttons for 'Use local system account' (selected) and 'Use this account:' (with 'Password:' and 'Confirm Password:' fields); and 'Start SiteScope' with a checked checkbox for 'Start SiteScope service after install'. At the bottom right are 'Back', 'Next', and 'Cancel' buttons.

**HP SiteScope Configuration Wizard**

**Settings**

Enter values for the following deployment settings:

**Basic settings**

Port: 8080  
Administrator email: \_\_\_\_\_

**License**

License file: \_\_\_\_\_ **Select ...**

**SiteScope service settings**

Service name: SiteScope

Use local system account  
 Use this account: \_\_\_\_\_  
Password: \_\_\_\_\_  
Confirm Password: \_\_\_\_\_

**Start SiteScope**

Start SiteScope service after install

**Back** **Next** **Cancel**

Enter the required configuration information and click **Next**:

- ▶ **Port.** The SiteScope port number. If the port number is already in use (an error message is displayed), enter a different port. If necessary, you can change the port later using the Configuration Tool. The default port is 8080.

---

**Note:** If you plan to use SiteScope Failover to monitor more than one primary SiteScope from a single Failover machine, each primary SiteScope installation must be configured to answer on a unique port number. You can check the ports used by the SiteScope server using the SiteScope Configuration Wizard. For details, see "Running the Configuration Tool on Windows Platforms" on page 133.

---

- ▶ **Administrator email.** Enter the email address that SiteScope should use to send email alerts to the SiteScope administrator.

---

**Note:** You do not need to enter an email address at this point to install SiteScope. You can enter this information later using the Email Preferences settings in SiteScope.

If the mail server uses NTLM authentication, this administrator email address must be a legal email address.

---

- ▶ **License file.** Enter the path to the license file, or click **Select** and select the SiteScope license key file. A license must be purchased if intending to use SiteScope beyond the 60-day trial period. It is not necessary to enter license information at this point to use SiteScope during the free evaluation period.

---

**Note:** License keys from previous versions of SiteScope are not compatible with this version. License key delivery can be fulfilled automatically through <http://webware.hp.com>.

---

- ▶ **Use local system account** (not applicable for Solaris or Linux installations). By default, SiteScope is installed to run as a **Local System account**. This account has extensive privileges on the local computer, and has access to most system objects. When SiteScope is running under a Local Systems account, it attempts to connect to remote servers using the name of the server.
- ▶ **Use this account** (not applicable for Solaris or Linux installations). Select to change the user account of the SiteScope service. You can set the SiteScope service to log on as a user with domain administration privileges. This gives SiteScope access privileges to monitor server data within the domain. Enter an account and password (and confirm the password) that can access the remote servers.


---

**Note:** When SiteScope is installed to run as a custom user account, the account used must have **Log on as a service** rights. To grant a user logon service access:

1. In Windows Control Panel, double-click **Administrative Tools**.
  2. Double-click **Local Security Policy**, and select **Local Policies > User Rights Assignment > Log On as a Service**.
  3. Click **Add**, and select the user you want to grant logon service access to and click **OK**.
  4. Click **OK** to save the updated policy.
-

- ▶ **Service name** (not applicable for Solaris or Linux installations). The name of the SiteScope service. If the machine has a previous version of SiteScope installed, enter another name for the SiteScope service. The default service name is SiteScope.
- ▶ **Start SiteScope service after install** (not applicable for Solaris or Linux installations). Automatically starts the SiteScope service after the installation is complete.

**14** The Import Configuration screen opens, enabling you to import existing SiteScope configuration data to the new SiteScope installation.



Select one of the following options and click **Next**:


- ▶ **Do not import configuration data.**
- ▶ **Use existing exported configuration file.** Enables you to use SiteScope data such as templates, logs, monitor configuration files, and so forth, from an existing exported configuration file. SiteScope data is exported using the Configuration Tool, and is saved in ZIP format. Click the **Select** button and navigate to the user data file that you want to import.
- ▶ **Import from the following SiteScope installation.** Click the **Select** button and navigate to the SiteScope installation folder from which you want to import configuration data.
  - ▶ **Include log files.** Enables you to import log files from the selected SiteScope installation folder.

---

**Note:** When moving configuration data from one SiteScope installation to another, make sure that SiteScope server from which you are taking configuration data is in the same time zone as the SiteScope server to which the data is being imported.

---

- 15** The Install HP Operations Agent screen opens. The HP Operations agent is required if SiteScope is integrated to send events and metrics to an HP Operations Manager or BSM Gateway server.




Select one of the following options and click **Next**:

- ▶ **Do not install HP Operations Agent.** The HP Operations agent is not installed.
- ▶ **Install HP Operations Agent.** Select to install the HP Operations agent on the SiteScope server. The agent enables SiteScope to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM Gateway server.

**Note:**


- ▶ If you install SiteScope and the HP Operations agent on a machine that already has the agent installed, SiteScope overrides it and upgrades the current agent.
  - ▶ The HP Operations agent is supported on SiteScopes running on the environments listed in "HP Operations Manager Support Matrix" on page 73. Consequently, the SiteScope integration with HPOM and BSM is only supported on these environments.
  - ▶ If you encounter problems installing the HP Operations agent on a 32-bit Windows machine, see "Troubleshooting and Limitations" on page 126.
-

16 The Summary screen opens.



Check that the information is correct and click **Next** to continue, or **Back** to return to previous screens to change your selections.



**17** The Done screen opens.

To access the SiteScope user interface, click the connection address for this installation of SiteScope.


---

**Note:** If you did not select **Start SiteScope service after install** in the Configuration Settings screen, you need to start the SiteScope service before you can connect to SiteScope. For details, see "Getting Started with SiteScope" on page 213.

---

Click **Finish** to close the SiteScope Configuration Wizard.

- 18 When the installation finishes, the Installation Complete window opens displaying a summary of the installation paths used and the installation status.



If the installation was not successful, review the installation log file for any errors by clicking the **View log file** link in the **Installation Complete** window to view the log file in a web browser.

For more information about the installed packages, click the **Details** tab.

Click **Done** to close the installation program.

If the installation program determines that the server must be restarted, it prompts you to restart the server. After the server is restarted and you log in, the installation wizard performs other required setup procedures.

- 19 For the latest available functionality, download and install the latest SiteScope service pack from the same location from which you installed SiteScope. For information on accessing the SiteScope interface, see "Connecting to SiteScope" on page 215.

- 20** After installing SiteScope on a Linux or Solaris environment, set the permissions for the SiteScope installation directory to have read, write, and execute permissions for the user account that is used to run the SiteScope application. The permissions must also be set for all subdirectories within the SiteScope installation directory.

## **Installing SiteScope Using the Multi-Platform Wizard on a Machine Without X11 Server**

You can install SiteScope using the multi-platform wizard on a machine that does not have an X11 server either by:

- ▶ Using a VNC server (on many Linux and Solaris systems, a VNC server is installed by default).
- ▶ Editing the DISPLAY environment variable to make the programs use X server on another machine.

### **To install SiteScope on a machine without X11 using a VNC server:**

- 1** In command line, run `vncserver`. If it runs, select a password and note the display that the VNC server uses (usually :1).
- 2** Connect to your SiteScope machine via VNC client using the format: `hostname:display`. For example, `sitescope.company.name:1`
- 3** In the console that opens, navigate to the SiteScope installation directory and run the installation as usual.

### **To install SiteScope on a machine without X11 by redirecting X:**

- 1** Run any Linux or Solaris system with an X server, or install an X server on Windows (for example, `xming`).
- 2** Check that X access control allows your SiteScope machine to connect. On Linux or Solaris platforms, consult `man xhost`. On Windows platforms, see the documentation for X server implementation.
- 3** Run `export DISPLAY=x-server.machine.name:display` on your SiteScope machine (display is usually 0).
- 4** Navigate to the SiteScope installation directory in the same shell, and run the installation as usual.

## Installing on Solaris or Linux Using Console Mode

You can install SiteScope using a command line or console mode. Use this option if you are installing SiteScope on a remote server, or for any other reason that prevents the use of the installation option via the user interface.

**To install SiteScope on Solaris or Linux using the console mode:**

- 1 Download the SiteScope setup file to the machine where you want to install SiteScope.

Alternatively, copy the SiteScope setup file to a disk or network location where it is accessible to the user account that is to be used to install SiteScope.

- 2 Run the following command:

```
/bin/sh SiteScopeInstall/HPSiteScope_11.00_setup.bin -i console
```

The installation script initializes the Java Virtual Machine to begin the installation.

- 3 The Choose Locale screen is displayed.

```
bash-3.00# ./HPSiteScope_11.00_setup.bin -i console
Preparing to install...
Extracting the installation resources from the installer archive...
Configuring the installer for this system's environment...
Preparing CONSOLE Mode Installation...

=====
Choose Locale...
-----

->1- English

CHOOSE LOCALE BY NUMBER: █
```

Enter the number 1 to select English, and press ENTER to continue.

- 4 A confirmation screen is displayed.

```

bash-3.00# ./HPSiteScope_11.00_setup.bin -i console
Preparing to install...
Extracting the installation resources from the installer archive...
Configuring the installer for this system's environment...
Preparing CONSOLE Mode Installation...

=====
                                     (created with InstallAnywhere by Zero G)
=====

HP Software Installer
-----

PRESS <ENTER> TO CONTINUE:

```

Press ENTER to continue.

- 5 The Introduction screen is displayed.

```

Introduction
-----
Welcome to the installation for HP SiteScope 11.00
HP Software Installer will guide you through the installation. It is strongly
recommended that you quit all programs before continuing with this
installation.

Application Media Location : /opt/SiteScopeBuild/packages/
Installation Log File : /var/tmp/HPOvInstaller/HPSiteScope_11.00/HPSiteScope_11
.00_2010.04.21_12_56_HPOvInstallerLog.txt
Respond to each prompt to proceed to the next step in the installation.
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

PRESS <ENTER> TO CONTINUE: █

```

Press ENTER to continue with the installation.

- 6 The text of the license agreement is displayed. The SiteScope License Agreement requires several pages to display. Read each page as it is presented. Press ENTER to continue to the next page. When you have viewed all the pages of the license agreement, you have the option to accept or not accept the license agreement.

```
I accept the terms of the License Agreement (Y/N): Y
```

To install SiteScope, you must accept the terms of the license agreement. The default selection is to not accept the agreement. To accept the license agreement and continue the installation, enter Y.

---

**Note:** To cancel the installation after viewing the SiteScope License Agreement, enter N.

---

- 7 The SiteScope setup type screen opens.

```
Install Groups are combined sets of features.  
If you want to change something on a previous step, type 'back'.  
You may cancel this installation at any time by typing 'quit'.  
  
->1- HP SiteScope: ()  
   2- HP SiteScope Failover: ()  
Please select one of the following groups ...: [ ]
```

Choose the type that is suitable for your site. Enter the number of the setup type, and then press ENTER to continue.

**8** The Select Features screen opens.

```
Select Features
-----

Install Features represent a group of functionality
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

->1- HP SiteScope(Required)

Please Select Features(Use a comma to separate your choices)
:
```

Enter the number 1 (required) to install SiteScope.

Press ENTER to continue with the installation.

**9** The Install Requirements screen opens.

```
Install Requirements Checks
-----

=====
Verifying : Verifying free disk space ... [Completed]
=====

Performing checks ...
Details : performing checks ... please wait
Install check requirements successfully completed
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

Please hit Enter to continue:
```

Press ENTER to continue with the installation.

- 10 The Pre-Installation Summary screen opens.

```
Pre-Installation Summary
-----
Review the following before continuing:

Application Name
  HP SiteScope

Application Shortname
  HPSiteScope

Application Revision
  11.00

Application Directory
  /opt/HP/SiteScope/

Data Directory
  /var/opt/HP/SiteScope/

If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.

PRESS <ENTER> TO CONTINUE: █
```

Press ENTER to continue with the installation.

- 11 The Install Features screen opens and the installation process starts.

```
=====
Install Features
-----
Checking the status of packages

Checking the installation status of selected packages

Processing of 6 packages (Using Native pkg) scheduled.
Completed checking the installation status of all packages.
This process might take a while. Please do not interrupt...
```

When the installation process is complete, the post-installation configuration screen opens.



**12** The port prompt is displayed.

```

Completed 6/6 of packages.
Installation of features completed.

=====
Installing...
-----

[=====|=====|=====|=====]
[-----|-----|-----|-----]
: Listening for transport dt_socket at address: 8000
-----

Enter the HP SiteScope port number
Port [8080]
PRESS <1> TO ACCEPT THE VALUE [8080], 2 TO CHANGE

```

Enter the number 1 to accept the default port 8080, or enter number 2 to change the port, and then enter a different number in the change port prompt.

---

**Note:** If you plan to use SiteScope Failover to monitor more than one primary SiteScope from a single Failover machine, each primary SiteScope installation must be configured to answer on a unique port number. You can check the ports used by the SiteScope server using the SiteScope Configuration Wizard. For details, see "Running the Configuration Tool on Solaris or Linux Platforms" on page 140.

---

Press ENTER to continue with the installation.

- 13** The license file path prompt is displayed.

```
Enter the path to license file
File name []
PRESS <1> TO ACCEPT THE VALUE [], 2 TO CHANGE
```

Enter the number 1 to leave the license file path empty (it is not necessary to enter license information at this point to use SiteScope during the free evaluation period), or enter the number 2, and then enter the license file path in the next text box.

---

**Note:** License keys from previous versions of SiteScope are not compatible with this version. License key delivery can be fulfilled automatically through <http://webware.hp.com>.

---

Press ENTER to continue with the installation.

- 14** The administrator email address prompt is displayed.

```
Enter the administrator email
Email []
PRESS <1> TO ACCEPT THE VALUE [], 2 TO CHANGE
```

Enter the number 1 to leave this blank and continue to the next step. You can enter e-mail information later using the Email Preferences page once SiteScope is running.

To enter a SiteScope administrator email address, enter the number 2 and then type the address. For example, `sitescopeadmin@thiscompany.com`.

Press ENTER to continue with the installation.

**15** The Import Configuration Data screen opens.

```

Import configuration data from an existing configuration file or SiteScope
installation
->1 - Do not import: ()
   2 - Import from file: ()
   3 - Import from folder: ()
1
: Please select one of the options:
-----
HP SiteScope will be configured with the following settings
Port: 8080
License file:
Administrator email:
Press <1> to continue, <2> To change values:

```

Enter the number 1 if you do not want to import data.

Enter the number 2 to use SiteScope data such as templates, logs, monitor configuration files, and so forth, from an existing exported configuration file. If you select this option, enter the path to the configuration file in the next text box.

Enter the number 3 to import configuration data from a SiteScope installation directory. If you select this option, enter the path to the SiteScope installation folder from which you want to import configuration data.

Press ENTER to continue with the installation.

---

**Note:** When moving configuration data from one SiteScope installation to another, make sure that SiteScope server from which you are taking configuration data is in the same time zone as the SiteScope server to which the data is being imported.

---

**16** The Install HP Operations Agent screen opens.

```
: Please select one of the options:
-----
Install HP Operations Agent
->1 - Do not install: ()
   2 - Install: ()
█
```

Enter the number 1 if you do not want to install the HP Operations agent.

Enter the number 2 to install the HP Operations agent on the SiteScope server. The agent is required to enable SiteScope to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM Gateway server.

---

**Note:**

- ▶ If you install SiteScope and the HP Operations agent on a machine that already has the agent installed, SiteScope overrides it and upgrades the current agent.
- ▶ The HP Operations agent is supported on SiteScopes running on the environments listed in "HP Operations Manager Support Matrix" on page 73. Consequently, the SiteScope integration with HPOM and BSM is supported on these environments only.

---

Press ENTER to continue with the installation.

- 17** The console displays the installation parameters for confirmation.

```
HP SiteScope will be configured with the following settings
Port: 8080
License file:
Administrator email:
Press <1> to continue, <2> To change values:
```

Enter 1 to proceed with the installation using the parameters indicated or enter 2 to return to make changes, and then press ENTER.

The installation process starts. An installation status message is displayed.

```
-----
Installation Complete
-----
Congratulations!
HP SiteScope 11.00
The installation has been successfully completed.
Application Directory: /opt/HP/SiteScope/
bash-3.00#
```

- 18** After installing SiteScope, set the permissions for the SiteScope installation directory to have read, write, and execute permissions for the user account that is used to run the SiteScope application. The permissions must also be set for all subdirectories within the SiteScope installation directory.
- 19** To connect to SiteScope, follow the steps in the section "Starting and Stopping the SiteScope Process on Solaris and Linux Platforms" on page 215.

## Troubleshooting and Limitations

This section describes the following troubleshooting and limitations for installing SiteScope.

- ▶ "SiteScope might not install on 64-bit Linux using console mode" on page 126
- ▶ "SiteScope does not install on 64-bit Linux in graphic mode" on page 126
- ▶ "Unable to see entire license agreement in console mode installation" on page 126
- ▶ "HP Operations agent does not install on 32-bit Windows" on page 127
- ▶ "After uninstalling SiteScope, a subsequent SiteScope installation fails" on page 128
- ▶ "HP Operations agent fails to install when using UNC path" on page 128

### **SiteScope might not install on 64-bit Linux using console mode**

Installing SiteScope on Linux Red Hat 64-bit environments using console mode may fail if there are too many X sessions opened.

**Workaround:** Close some of the X sessions, or unset the DISPLAY variable.

### **SiteScope does not install on 64-bit Linux in graphic mode**

The SiteScope installer might not work on Linux Red Hat 64-bit environments using the graphical user interface wizard.

**Workaround:** Install SiteScope using the console mode instead.

### **Unable to see entire license agreement in console mode installation**

When installing SiteScope using the console mode, unable to read the whole of the license agreement.

**Workaround:** Install SiteScope in graphic mode, or increase the buffer size of the terminal.

## HP Operations agent does not install on 32-bit Windows

If the HP Operations agent fails to install on a 32-bit Windows machine, rename all the .msi files in <SiteScope root directory>/install/components/oa/win32 to their original names (see list below), and then reinstall the agent.

For example, HPOvAgtEx-06.20.105-WinNT4.0-release.msi should be renamed HPOvAgtEx.msi.

➤ HPOvAgtEx.msi	➤ HPOvLcja.msi
➤ HPOvBbc.msi	➤ HPOvLcko.msi
➤ HPOvConf.msi	➤ HPOvLczC.msi
➤ HPOvCtrl.msi	➤ HPOvPacc.msi
➤ HPOvDepl.msi	➤ HPOvPCO.msi
➤ HPOvEaAes.ms	➤ HPOvPerlA.msi
➤ HPOvEaAgt.msi	➤ HPOvSecCC.msi
➤ HPOvEaAja.msi	➤ HPOvSecCo.msi
➤ HPOvEaAko.msi	➤ HPOvXalanA.msi
➤ HPOvEaAzC.msi	➤ HPOvXercesA.msi
➤ HPOvLces.msi	➤ HPOvXpl.msi

### **After uninstalling SiteScope, a subsequent SiteScope installation fails**

After uninstalling SiteScope, a subsequent installation cannot be completed and the following message is displayed: "Please enable windows scripting host". This occurs because Windows is unable to resolve the %SystemRoot% variable in the PATH environment variable (even though %SystemRoot% does appear in the path).

**Workaround:** Replace the %SystemRoot% variable in the PATH environment variable with the actual path to **C:\Windows\system32**.

### **HP Operations agent fails to install when using UNC path**

The HP Operations agent fails to install if SiteScope is installed into a remote location using a UNC path (for example, when installing SiteScope Failover on a Windows platform).

**Workaround:**

- 1** After installing SiteScope, copy the **<SiteScope root directory>\install\components\oa\win32** or **\win64** folder locally.
- 2** Install the HP Operations agent manually by running the command: **cscript opc\_inst.vbs** from the **win32** or **\win64** folder.



# 9

---

## Installing SiteScope in Silent Mode

### **This chapter includes:**

- About Installing SiteScope in Silent Mode on page 129
- Running a Silent Installation on page 131

### **About Installing SiteScope in Silent Mode**

You can install SiteScope using a silent installation. A silent installation runs the entire setup process in the background without requiring you to navigate through the setup screens and input your selections. Instead, all configuration parameters are allocated values you define in a response file. To run silent installations for different configurations, you can create multiple response files.

## Notes and Limitations

Before running a silent installation, consider the following issues:

- When running an installation in silent mode, no messages are displayed. Instead, you can view installation information in the log file, including information on whether the installation was successful. The installation log file can be found under
  - `%tmp%\HPOvInstaller\HPSiteScope_11.00` on Windows platforms
  - `/var/tmp/HPOvInstaller/HPSiteScope_11.00` on Solaris platforms
  - `/tmp/HPOvInstaller/HPSiteScope_11.00` on Linux platforms
- The parameter `HPSiteScope_11.00_setup.exe -i silent` should appear only once, either in the response file or in the command line. If it appears in both the response file and the command line, the installation does not run. No error message displays.
- The SiteScope installation path (`prodInstallDir=<Installation_path>`) must not contain spaces in its name, and must end with a folder named **SiteScope** (the folder name is case sensitive).

## Running a Silent Installation

You run a silent installation using the **oviinstallparams.ini** file. Since this file has a very specific format, you should create the silent installation file using the sample **oviinstallparams.ini** file.

---

**Note:** The sample **oviinstallparams.ini** file is available only after installing SiteScope from the <SiteScope installation directory>\examples\silent\_installation folder.

---

### To run a silent installation:

- 1** Navigate to the **oviinstallparams.ini** file located in the <SiteScope installation directory>\examples\silent\_installation folder.
- 2** Make a copy of the file, and then modify it to meet your installation needs.
- 3** Copy the file to the setup folder where **HPSiteScope\_11.00\_setup.exe** or **HPSiteScope\_11.00\_setup.bin** is located.
- 4** Run the installer from the command line with **-i silent** flag. For example:  
HPSiteScope\_11.00\_setup.exe -i silent (Windows), or  
HPSiteScope\_11.00\_setup.bin -i silent (UNIX).



# 10

---

## Using the SiteScope Configuration Tool

### **This chapter includes:**

- Running the Configuration Tool on Windows Platforms on page 133
- Running the Configuration Tool on Solaris or Linux Platforms on page 140

### **Running the Configuration Tool on Windows Platforms**

The Configuration Tool is a convenient utility for moving configuration data from one SiteScope installation to another. You can export SiteScope data such as templates, logs, monitor configuration files, and so forth from your current SiteScope for later import into SiteScope. You can also use the wizard to optimize SiteScope's performance by making sizing changes in the Windows Registry keys, to change the ports assigned to SiteScope, and to install and uninstall the HP Operations agent.

If you exported SiteScope data during the installation process, you can import the data using the Configuration Tool. Alternatively, you can export data from your current SiteScope independently using the Configuration Tool. If you have created or modified monitor configuration files in previous versions of SiteScope, you may need to import them to the SiteScope 11.00 directory.

---

**Note:**

- ▶ You must stop the SiteScope service before exporting or importing the data, and restart the service after exporting or importing the data. For details, see "Starting and Stopping the SiteScope Service on Windows Platforms" on page 214.
  - ▶ When moving configuration data from one SiteScope installation to another, make sure that SiteScope server from which you are taking configuration data is in the same time zone as the SiteScope server to which the data is being imported.
  - ▶ When importing configurations to the same version of SiteScope, you must rename or delete all template example containers in order to import the new template examples.
- 

**To run the SiteScope Configuration Tool:**

- 1** On the SiteScope server, select **Start > Programs > HP SiteScope > Configuration Tool**. The SiteScope Configuration Wizard opens.
- 2** Select the actions that you want to perform, and then click **Next**.

The screenshot shows the 'Introduction' screen of the SiteScope Configuration Wizard. It contains the following text:

**Introduction**


This wizard enables you to make sizing changes to the SiteScope server, change the ports assigned to SiteScope, move configuration data from one SiteScope installation to another, and install/uninstall the HP Operations Agent.

Select the actions that you want to perform.

- Sizing
- Change ports
- Import configuration
- Export configuration
- Install HP Operations Agent

- **Sizing.** Enables optimizing SiteScope's performance by increasing JVM heap size, desktop heap size, and the number of file handles in the Windows Registry keys. For details, see step 3 on page 135.
- **Change port.** Enables changing any of the ports used by the SiteScope server. For details, see step 4 on page 136.
- **Import configuration.** Enables importing configuration data from an exported configuration data (.zip) file, or from an existing SiteScope installation. For details, see step 5 on page 137.
- **Export configuration.** Enables exporting SiteScope data such as templates, logs, and monitor configuration files from your current SiteScope for later import into SiteScope. For details, see step 6 on page 138.
- **Install HP Operations Agent.** Enables installing and unstalling the HP Operations agent. The agent enables SiteScope or SiteScope Failover Manager to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM Gateway server. For details, see step 7 on page 139.

3 If you selected the **Sizing** option, the Sizing screen opens. This screen lists the parameters in the Windows Registry opens.



You can optimize SiteScope's performance by making changes in the following Windows Registry keys:

- **JVM heap size.** The value is changed from 512 MB to 1024 MB. For more details on JVM heap size, refer to <http://java.sun.com/j2se/1.5.0/docs/guide/vm/gc-ergonomics.html>.
- **Desktop heap size.** The value is changed from 512 MB to 2048 MB. For more details on Desktop heap size, refer to <http://support.microsoft.com/kb/126962>.

- **Number of File Handles.** If Microsoft Windows 2000 SP4 is installed on the machine, changes the number of file handles from 10,000 to 18,000. For more details on changing file handles, refer to <http://support.microsoft.com/kb/326591>.

Click **Next** to complete the sizing operation.

- 4 If you selected the **Change ports** option, the Change Ports screen opens.

Change Ports	
You can change any of the ports used by the SiteScope server	
It is recommended to use ports in the 28000-28100 range so as not to interfere with ports used by other Business Service Management products.	
SiteScope user interface	<input type="text" value="8080"/>
Tomcat shutdown	<input type="text" value="28005"/>
Tomcat AJP connector	<input type="text" value="28009"/>
SSL	<input type="text" value="8443"/>
JMX console	<input type="text"/>
Classic user interface	<input type="text" value="8888"/>
Classic user interface (secure)	<input type="text"/>

Modify the ports used by the SiteScope server as required. Port numbers must be numeric and should be in the 1-65534 range. A port is mandatory for all components except Classic user interface.

---

**Tip:** It is recommended to use ports in the 28000-28100 range so as not to interfere with ports used by other Business Service Management products.

---

Click **Next** to complete the change port operation.



**5** If you selected the **Import Configuration** option, the Import Configuration screen opens.

### Import Configuration

---

Import configuration data from an existing configuration file or SiteScope installation.

It is recommended that you stop the target SiteScope.

Use existing exported configuration file

File

Import from the following SiteScope installation

Folder

Include log files

---

**Note:** You must stop the SiteScope service before importing the data, and restart the service after importing the data. For details, see "Starting and Stopping the SiteScope Service on Windows Platforms" on page 214

---

- If you select **Use existing exported configuration file**, enter the name of the user data file to import.
- If you select **Import the following SiteScope installation**, enter the SiteScope installation directory to which to import the user data file. If you also want to import log files, select **Include log files**.

Click **Next** to complete the import operation.

- 6 If you selected the **Export Configuration** option, the Export Configuration screen opens.

**Export Configuration**  
Export configuration data from an existing SiteScope.  
It is recommended that you stop SiteScope before processing.

From SiteScope folder

To file

Include log files

- In **From SiteScope folder**, accept the default directory given in the box, or enter the full path of the SiteScope installation directory. For example, if you do not want to accept the directory path as listed and the installation directory path is D:\SiteScope11\_0\SiteScope, enter D:\SiteScope11\_0\SiteScope.
- In **To file**, enter the directory to which to export the user data file (the directory must already exist) and the name for the exported user data file. The name must end in **.zip**. If you also want to export log files, select **Include log files**.

---

**Note:**

- You must stop the SiteScope service before exporting the data, and restart the service after exporting the data. For details, see "Starting and Stopping the SiteScope Service on Windows Platforms" on page 214.
- Since the **\htdocs** directory is not copied when you export SiteScope data, you should make a backup of this directory and copy it to the SiteScope 11.00 directory after an upgrade, so that you can see old reports.

---

Click **Next** to complete the export operation.

- 7 If you selected the **Install HP Operations Agent** option, the Install HP Operations Agent screen opens.

### HP Operations Agent

---

Install/Uninstall HP Operations Agent

The HP Operations agent is required to integrate SiteScope event and metrics data with HP Operations Manager and BSM. The agent sends events and acts as a data storage for metrics data that can be made available to HP Operations Manager and BSM applications.

Install HP Operations Agent

Uninstall HP Operations Agent

- **Install HP Operations Agent.** Select to install the HP Operations agent on the SiteScope server. The agent is required to enable SiteScope to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM Gateway server.
- **Uninstall HP Operations Agent.** Select to uninstall the HP Operations agent from the SiteScope server.


Click **Next** to complete the install/uninstall operation.

---

**Note:** If you install the HP Operations agent on a machine that already has the agent installed, SiteScope overrides it and upgrades the current agent.

---

- 8 The Summary screen opens, displaying the configuration status.



Click **Finish** to close the wizard.

---

**Tip:** After an upgrade, you can start SiteScope by running the **go.bat** file from the <SiteScope root directory>\bin directory. This avoids SiteScope automatically restarting itself if it takes longer than 15 minutes for the monitors to run.

---

## Running the Configuration Tool on Solaris or Linux Platforms

The Configuration Tool is a convenient utility for moving configuration data from one SiteScope installation to another. If you exported SiteScope data during the installation process, you can import the data using the Configuration Tool. If you have created or modified monitor configuration files in the previous SiteScope version, you may need to copy them to the 11.00 directory. You can also use the wizard to change any of the ports used by the SiteScope server, and to install and unistall the HP Operations agent.

---

**Note:** When moving configuration data from one SiteScope installation to another, make sure that SiteScope server from which you are taking configuration data is in the same time zone as the SiteScope server to which the data is being imported.

---

**To run the SiteScope Configuration Tool:**

- 1** On the SiteScope server, do either of the following:
  - a** In graphic mode, run `<SiteScope install Directory>/bin/config_tool.sh`
  - b** In console mode, run `<SiteScope install Directory>/bin/config_tool.sh -i console`

The SiteScope Configuration Wizard opens.

Click **Next**.

- 2** Select the actions that you want to perform in the Introduction screen, and then click **Next**.

**Introduction**

---

This wizard enables you to change the ports assigned to SiteScope, move configuration data from one SiteScope installation to another, and install/uninstall the HP Operations Agent.

Select the actions that you want to perform.

Change ports

Import configuration

Export configuration

Install HP Operations Agent

- **Change port.** Enables changing any of the ports used by the SiteScope server. For details, see step 3 on page 142.
- **Import Configuration.** Enables importing configuration data from an exported configuration data (.zip) file, or from an existing SiteScope installation. For details, see step 5 on page 144.
- **Export Configuration.** Enables exporting SiteScope data such as templates, logs, and monitor configuration files from your current SiteScope for later import into SiteScope. For details, see step 4 on page 143.
- **Install HP Operations Agent.** Enables installing and unstalling the HP Operations agent. The agent enables SiteScope or SiteScope Failover Manager to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM Gateway server. For details, see step 6 on page 145.

- 3 If you selected the **Change ports** option, the Change Ports screen opens.

### Change Ports

You can change any of the ports used by the SiteScope server

It is recommended to use ports in the 28000-28100 range so as not to interfere with ports used by other Business Service Management products.

SiteScope user interface	<input type="text" value="8080"/>
Tomcat shutdown	<input type="text" value="28005"/>
Tomcat AJP connector	<input type="text" value="28009"/>
SSL	<input type="text" value="8443"/>
JMX console	<input type="text"/>
Classic user interface	<input type="text" value="8888"/>
Classic user interface (secure)	<input type="text"/>

Modify the ports used by the SiteScope server as required. Port numbers must be numeric and should be in the 1-65534 range. A port is mandatory for all components except Classic user interface.

---

**Tip:** It is recommended to use ports in the 28000-28100 range so as not to interfere with ports used by other Business Service Management products.

---

Click **Next** to complete the change port operation.

- 4 If you selected the **Export Configuration** option, the Export Configuration screen opens.

**Export Configuration**

Export configuration data from an existing SiteScope.

It is recommended that you stop SiteScope before processing.

From SiteScope folder

To file

Include log files

---

**Note:** You must stop the SiteScope service before exporting the data, and restart the service after exporting the data. For details, see "Starting and Stopping the SiteScope Process on Solaris and Linux Platforms" on page 215.

---

- In **From SiteScope folder**, accept the default directory given in the box, or enter the full path of the SiteScope installation directory. For example, if you do not want to accept the directory path as listed and the installation directory path is `/opt/9_0/SiteScope`, enter `/opt/9_0/SiteScope`.
- In **To file**, enter the directory to which to export the user data file (the directory must already exist) and the name for the exported user data file. The name must end in **.zip**.
- If you also want to export log files, select **Include log files**.

Click **Next** to complete the export operation.

- 5 If you selected the **Import Configuration** option, the Import Configuration screen opens.

### Import Configuration

---

Import configuration data from an existing configuration file or SiteScope installation.

It is recommended that you stop the target SiteScope.

Use existing exported configuration file

File

Import from the following SiteScope installation

Folder

Include log files

---

**Note:** You must stop the SiteScope service before importing the data, and restart the service after importing the data. For details, see "Starting and Stopping the SiteScope Process on Solaris and Linux Platforms" on page 215

---

- If you select **Use existing exported configuration file**, enter the name of the user data file to import.
- If you select **Import the following SiteScope installation**, enter the SiteScope installation directory to which to import the user data file.
- If you also want to import log files, select **Include log files**.

Click **Next** to complete the import operation.



- 6** If you selected the **Install HP Operations Agent** option, the Install HP Operations Agent screen opens.

### HP Operations Agent

---

Install/Uninstall HP Operations Agent

The HP Operations agent is required to integrate SiteScope event and metrics data with HP Operations Manager and BSM. The agent sends events and acts as a data storage for metrics data that can be made available to HP Operations Manager and BSM applications.

Install HP Operations Agent	<input type="checkbox"/>
Uninstall HP Operations Agent	<input type="checkbox"/>

- **Install HP Operations Agent.** Select to install the HP Operations agent on the SiteScope server. The agent is required to enable SiteScope to send events and act as a data storage for metrics data when SiteScope is integrated with an HP Operations Manager or BSM server.
- **Uninstall HP Operations Agent.** Select to uninstall the HP Operations agent from the SiteScope server.

Click **Next** to complete the install/uninstall operation.

---

**Note:** If you install the HP Operations agent on a machine that already has the agent installed, SiteScope overrides it and upgrades the current agent

---

- 7** The Completed screen opens.

<p><b>Summary</b></p> <hr/> <p>Configuration completed</p> <p><b>Configuration completed</b></p>
---

Click **Finish** to close the wizard.



# 11

---

## Sizing SiteScope

### **This chapter includes:**

- ▶ About Sizing SiteScope on page 147
- ▶ SiteScope Capacity Calculator on page 148
- ▶ Sizing SiteScope on Windows Platforms on page 150
- ▶ Sizing SiteScope on Solaris and Linux Platforms on page 154

### **About Sizing SiteScope**

While the default SiteScope configuration allows running thousands of monitors, sizing the server where SiteScope is installed may be necessary to achieve optimum performance. Since each configuration is different, you should use the SiteScope Capacity Calculator to verify if your configuration requires sizing.

Proper sizing of the server where SiteScope is to run is the foundation of successful monitoring deployment. To ensure optimal sizing, HP strongly recommends the following SiteScope server environment:

- ▶ SiteScope runs as a stand-alone server. For best results, SiteScope should be the only program running on a server. Business Service Management, BMC, LoadRunner, databases, Web servers, and so forth, should not be on the SiteScope server.
- ▶ Only one instance of SiteScope exists and it runs on a single server. Running multiple instances of SiteScope on a single server can cause severe resource problems.
- ▶ SiteScope Failover needs to be sized just like the primary SiteScope server.

## SiteScope Capacity Calculator

SiteScope includes a tool that helps you predict system behavior and perform capacity planning for SiteScope. You enter the CPU and memory details of the system on which SiteScope is running, and the number of monitors of each type and the frequency that they are to run. The calculator then displays the expected CPU usage and memory usage for each monitor type, and the recommended system requirements for the given workload. This enables you to determine whether your configuration requires tuning.

---

**Note:** The SiteScope Capacity Calculator is supported in SiteScopes that are running on Windows versions only. For the list of monitors and solution templates supported by the capacity calculator, see "Supported Monitors and Solution Templates" on page 149.

---

### To use the SiteScope Capacity Calculator:

- 1** Open the SiteScope Capacity Calculator from `<SiteScope root directory>\tools\SiteScopeCapacityCalculator.xls` or from the link in the Home page of the SiteScope Documentation Library.
- 2** In the **Monitor Usage** tab, enter the following information in the **Requirements** section:
  - ▶ Average % CPU usage
  - ▶ CPU type
  - ▶ Memory heap size (in megabytes)
- 3** In the **Monitors** section, enter the number of monitors for each type, and the update frequency for each monitor.
- 4** The results and recommendations are displayed in the **Results and Recommendations** section. A difference of 30-40% between the expected results and the actual results should be considered as acceptable.

## Supported Monitors and Solution Templates

The following monitors and solution templates are supported by the SiteScope Capacity Calculator:

### Monitors

- CPU Monitor
- Database Counter Monitor
- Disk Space Monitor
- DNS Monitor
- Log File Monitor
- Memory Monitor
- Microsoft IIS Server Monitor
- Microsoft SQL Server Monitor
- Microsoft Windows Event Log Monitor
- Microsoft Windows Resources Monitor
- Ping Monitor
- SAP CCMS Monitor
- Script Monitor
- Service Monitor
- Siebel Application Server Monitor
- SNMP by MIB Monitor
- URL Monitor
- WebLogic Application Server Monitor
- WebSphere Application Server Monitor

### Solution Templates

- Microsoft Exchange 2003 Solution Template
- Siebel Solution Templates

## Sizing SiteScope on Windows Platforms

When sizing SiteScope installed on a Windows platform, you should perform the following sizing steps on SiteScope and on the Windows operating system:

### 1 Size SiteScope.

We recommend sizing SiteScope first and letting SiteScope run for at least 24 hours before proceeding to the next step. For details, see the procedure "Sizing SiteScope" on page 151.

### 2 Tune the Windows Operating System.

After sizing SiteScope and waiting at least 24 hours, you need to tune the Windows operating system and then restart the SiteScope server for the parameter changes to take effect. For details, see the procedure "Tuning Microsoft Windows Operating System" on page 152.

### 3 General Maintenance Recommendations.

In addition, certain general maintenance recommendations should be followed to ensure optimal tuning. For details, see "General Maintenance Recommendations" on page 153.

---

#### Caution:

- We recommend making backups of any file or parameter that you change, so that it can be restored from that backup if needed.
  - If the settings are not effective, do not randomly increase or decrease them. Contact HP Software Support for further analysis and troubleshooting.
-

## Sizing SiteScope

Sizing SiteScope involves checking that monitors use the **Verify error** option only when absolutely necessary. This option should be used on a very small number of monitors, and for monitors with a history of false **no data** alerts due to network issues or server load problems on the remote machine being monitored.

When this feature is enabled, a monitor that fails is immediately run again, bypassing the scheduler before the alert conditions are checked. Large numbers of these extra runs can significantly disrupt the scheduler and cause SiteScope performance to degrade. For monitors failing due to connection problems, verify error can take up to the connection timeout amount of time before the monitor is terminated. During this time, it locks the monitor thread and connection for 2 minutes, by default. This delay can cause other monitors to wait and the failing monitor to skip.

### To Size SiteScope:

- 1** For each monitor, select the **Properties** tab, open the **Monitor Run Settings** panel, and check whether **Verify error** is selected. Clear the check box for monitors that do not require this option.

---

**Tip:** For multiple monitors, we recommend using **Global Search and Replace** to perform this task.

---

- 2** Let SiteScope run for at least 24 hours before tuning the Windows operating system.

## Tuning Microsoft Windows Operating System

Tuning Microsoft Windows operating systems involves changing a number of parameters using the Configuration Tool. In addition, certain general maintenance recommendations should be followed to ensure optimal tuning.

### To tune Microsoft Windows operating systems:

- 1 Check that the appropriate Windows Service Pack or Hotfix has been installed on the SiteScope server:
  - ▶ For Windows 2000, Service Pack 4 must already be installed. For details about increasing file handles on Windows 2000 and for downloading the Service Pack, see <http://support.microsoft.com/kb/326591/en-us>.
  - ▶ For Windows XP, Hotfix 327699 must already be installed. For details about increasing file handles on Windows XP and for downloading the Hotfix, see <http://support.microsoft.com/kb/327699/en-us>.
- 2 Run the Configuration Tool, and select the **Sizing** option.

This tool increases JVM heap size to 1024 MB, desktop heap size to 2048 MB, and the number of file handles to 18,000. It also disables pop-up warnings for SiteScope executables. For details, see "Running the Configuration Tool on Windows Platforms" on page 133.

---

**Note:** The Configuration Tool supports the default **SiteScope** service name only. If you changed the service name, contact HP Software Support instead of running the Configuration Tool.

---

- 3 Restart the SiteScope server for the parameter changes to take effect.



## General Maintenance Recommendations

Follow these general maintenance recommendations to size SiteScope on Windows.

► **Determine appropriate monitor frequency.**

Check the monitor run frequency and ensure that monitors are running at an appropriate interval. For example, most disk monitors do not need to run every 5 minutes. Generally every 15, 30, or even 60 minutes is adequate for all volumes except, perhaps, */var*, */tmp*, and *swap*. Reducing monitor frequencies lowers the number of monitor runs per minute, and improves performance and capacity.

► **Optimize group structure.**

Group structure should take into account ease of use with SiteScope, and performance optimization for SiteScope. Ideally, the number of top-level groups should be minimized as should the depth of the structure.

Performance can degrade if a group structure has more than 50 top-level groups, or if it is more than 5 levels deep.

► **Resolve SiteScope configuration errors.**

Use the health monitors to resolve monitor configuration errors. Even a small number of errors can lead to performance and stability degradation. For more information on resolving these errors, contact HP Software Support.

► **Plan the physical location of SiteScope servers.**

SiteScope servers should be physically located as close as possible on the local network to the machines they are monitoring. It is not recommended to monitor over a WAN connection, although in some cases where the connection has sufficient capacity and low latency, this may be acceptable.

## Sizing SiteScope on Solaris and Linux Platforms

Sizing SiteScope on Solaris and Linux operating systems involves changing a number of parameters. In addition, certain general maintenance recommendations should be followed to ensure optimal tuning.

### 1 Tune the Operating System.

Configure the appropriate number of threads for the SiteScope instance and configure the Solaris or Linux operating system parameters. For details, see the procedure "Tuning the Operating System" on page 154.

### 2 Tune the Java Virtual Machine.

Configure the JVM heap size, thread stack size, and implement parallel garbage collection. For details, see the procedure "Tuning the Java Virtual Machine" on page 156.

### 3 General Maintenance Recommendations.

In addition, certain general maintenance recommendations should be followed to ensure optimal tuning. For details, see "General Maintenance Recommendations" on page 157.

## Tuning the Operating System

Tuning the operating system involves configuring the appropriate number of monitors for the SiteScope instance and configuring the Solaris or Linux operating system parameters.

### Configuring the Maximum Number of Running Monitors

You can configure the **Maximum monitor running** setting in **Preferences > Infrastructure Preferences > Server Settings**. For details, see "Infrastructure Preferences" in SiteScope Help.

### Configuring Solaris or Linux Operating System Parameters

The Solaris or Linux operating system can support large numbers of threads. To enable this feature, perform the following on the SiteScope server.

To configure the Solaris or Linux operating system parameters:

**1 Modify the kernel file descriptor limits.**

- a** Edit the `/etc/system` file and add the following line:

```
set rlim_fd_max=8192
```

---

**Note:** 1024 is the default (this limit does not apply to user root). The value 8192 is sufficient for even the largest instance of SiteScope. Use this high value rather than experiment with lower values. This avoids the need to restart the machine later if the lower value is not sufficient.

---

- b** Restart the server.

**2 Modify the user runtime limits.**

- a** In `<SiteScope root directory>\bin` directory, add the following line to the SiteScope startup scripts `start-monitor` and `start-service`:

```
ulimit -n 8192
```

- b** Check that the following parameters have the following minimum values. Contact your UNIX system administrator for more information.

Parameter	Minimum Value
core file size (blocks)	unlimited
data seg size (kbytes)	unlimited
file size (blocks)	unlimited
open files	8192
pipe size (512 bytes)	10
stack size (kbytes)	8192
cpu time (seconds)	unlimited
max user processes	8192
virtual memory (kbytes)	unlimited

You do not need to restart the SiteScope application or the server after modifying the runtime limits.

## Tuning the Java Virtual Machine

You should configure the JVM as follows for optimal performance.

To configure the JVM:

### 1 Increase heap space.

By default, the Java heap space for SiteScope is set to 512 MB. This is insufficient for the normal operation of large instances.

The heap space can be increased up to 1024 MB (this is the recommended heap size for large loads) by modifying **start-service** and **start-monitor** scripts in `<SiteScope root directory>\bin` directory.

### 2 Decrease thread stack size (-Xss).

Each thread created by SiteScope instantiates a stack with -Xss amount of allocated memory. The default UNIX JRE maximum thread stack size, -Xss, is 512 KB memory per thread.

Unless specified on the Java command line in `<SiteScope root directory>\bin\start-monitor`, the default maximum thread stack size is used. The default size can limit the number of threads by exceeding the available memory.

Instances of 4000 or more monitors can benefit from a -Xss of 128 KB.

## General Maintenance Recommendations

There are general maintenance recommendations to size SiteScope on Solaris and Linux platforms.

► **Utilize health monitors.**

Utilize health monitors with **Depends on** wherever possible, but especially for all monitors using remote UNIX connections. The health monitor can prevent server performance degradation by detecting if multiple machines become unavailable and lock SSH connection threads.

► **Minimize the use of the Verify error feature.**

When the **Verify error** option is enabled in the **Monitor Run Settings** panel, a monitor that fails is immediately run again, bypassing the scheduler before the alert conditions are checked. Large numbers of these extra runs can significantly disrupt the scheduler and cause SiteScope performance to degrade. For monitors failing due to connection problems, verify error can take up to the connection timeout amount of time before the monitor is terminated. During this time, it locks the monitor thread and connection for 2 minutes, by default. This delay can cause other monitors to wait and the failing monitor to skip.

► **Use SSH and internal Java libraries.**

Wherever possible, use SSH and Internal Java Libraries option when defining a remote preference with a SSH connection method. Internal Java Libraries is a third-party, Java-based, SSH client. This client significantly improves performance and scalability over Telnet and the host operating system's SSH client. This client supports SSH1, SSH2, Public Key Authentication, and so forth.

In SSH, set **Connection caching enabled**. The **Connection limit** should be adjusted to allow for all monitors running against a particular server to execute in a timely manner.

► **Determine appropriate monitor frequency.**

Check the monitor run frequency and ensure that monitors are running at an appropriate interval. For example, most disk monitors do not need to run every 5 minutes. Generally every 15, 30, or even 60 minutes is adequate for all volumes except, perhaps, `/var`, `/tmp`, and `swap`. Reducing monitor frequencies lowers the number of monitor runs per minute, and improves performance and capacity.

► **Optimize group structure.**

Group structure should take into account ease of use with SiteScope, and performance optimization for SiteScope. Ideally, the number of top-level groups should be minimized as should the depth of the structure.

Performance can degrade if a group structure has more than 50 top-level groups, or if it is more than 5 levels deep.

► **Resolve SiteScope configuration errors.**

Use the health monitors to resolve monitor configuration errors. Even a small number of errors can lead to performance and stability degradation. For more information on resolving these errors, contact HP Software Support.

► **Plan the physical location of SiteScope servers.**

SiteScope servers should be physically located as close as possible on the local network to the machines they are monitoring. When monitoring across WAN or slow network links, the network usually becomes the bottleneck. This can require additional time for the monitors to run. It is not recommended to monitor over a WAN connection, although in some cases where the connection has sufficient capacity and low latency, this may be acceptable.

► **Use local user accounts.**

Local user accounts are preferred over Directory Service accounts for UNIX Remote Authentication. Local user accounts avoid dependency on a Directory Service server for authentication. This ensures rapid authentication and prevents connection failures if the Directory Service server goes down.

In some cases, very large instances of SiteScope can negatively impact the performance of the Directory Services server. It is recommended that this server be physically close to the servers being monitored.





# 12

---

## Uninstalling SiteScope

### **This chapter includes:**

- Uninstalling SiteScope on a Windows Platform on page 161
- Uninstalling SiteScope on a Solaris or Linux Platform on page 166

### **Uninstalling SiteScope on a Windows Platform**


You can uninstall SiteScope from your server machine. For SiteScope running on Windows platforms, the SiteScope installation includes a program to uninstall the SiteScope software from your computer.

#### **To uninstall SiteScope on a Windows platform:**

- 1** Choose **Start > Programs > Administrative Tools > Services**. The Services dialog box opens.




- 3 Click **Start > Programs > HP SiteScope > Uninstall HP SiteScope** to start the HP Software Installer.



Select **Uninstall** and click **Next**.


4 In the Pre-Uninstall Summary screen, click **Uninstall**.



The Installer selects and uninstalls the HP SiteScope software components. Each software component and its uninstallation progress are displayed on your screen during the uninstallation operation.

After the uninstallation process is complete, the Uninstall Complete window opens showing you a summary of the uninstallation process.

- 5 In the Uninstall Complete window, click **Done** to close the uninstallation program.



From the **View log file** link, you can access the uninstallation log file that opens in a Web browser. For details on the removed packages, click the **Details** tab.

- 6 Restart your system to apply the changes made to it. Failure to restart may lead to unexpected problems for other applications.

## Uninstalling SiteScope on a Solaris or Linux Platform

For SiteScope running on Solaris or Linux platforms, the SiteScope installation includes a script to uninstall the SiteScope software from your computer. If you are unable to run the script, you can delete the SiteScope files and directories manually.

### To uninstall SiteScope on a Solaris or Linux platform:

- 1 Log in to the machine where SiteScope is running using the account authorized to execute scripts in the SiteScope directory. Normally this should be the account under which SiteScope is running.
- 2 Stop SiteScope by running the `stop` shell script included in the `<install_path>/SiteScope` directory. An example command line to run the script is:

```
SiteScope/stop
```

A message is displayed indicating that SiteScope is stopped.

```
SiteScope/stop
Stopped SiteScope process (6252)
Stopped SiteScope monitoring process (6285)
```

- 3 Run the `uninstall` script in the `<install_path>/SiteScope/_uninst` directory. An example command line to run the script is:  

```
SiteScope/_uninst/uninstall
```

At any point during the uninstall procedure, you can return to previous screens to check or change your answers by clicking **Back**.
- 4 The HP Software Installer starts. Select **Uninstall** and click **Next** to confirm that you want to uninstall SiteScope.
- 5 Complete steps 4 - 6 of "Uninstalling SiteScope on a Windows Platform" on page 161.

# Part IV

---

## Running SiteScope Securely





# 13

---

## Hardening the SiteScope Platform

### **This chapter includes:**

- ▶ About Hardening the SiteScope Platform on page 169
- ▶ Setting SiteScope User Preferences on page 170
- ▶ Password Encryption on page 170
- ▶ Using Secure Socket Layer (SSL) to Access SiteScope on page 170
- ▶ Configuring SiteScope to Send Bulk Data to ODB on page 171

### **About Hardening the SiteScope Platform**

This chapter describes several configuration and set up options that can be used to harden the SiteScope platform.

Network and system security has become increasingly important. As a system availability monitoring tool, SiteScope might have access to some system information which could be used to compromise system security if steps are not taken to secure it. You should use the configurations and set up options in this section to protect the SiteScope platform.

---

**Caution:** There are two Web servers that are active and serving two versions of the SiteScope product interface. To limit all access to SiteScope, you must apply the applicable settings to both the SiteScope Web server and the Apache Tomcat server supplied with SiteScope.

---

## Setting SiteScope User Preferences

SiteScope user profiles are used to require a user name and password in order to access the SiteScope interface. After installation, SiteScope is normally accessible to any user that has HTTP access to the server where SiteScope is running.

By default, SiteScope is installed with only one user account and this account does not have a default user name or password defined for it. This is the administrator account. You should define a user name and password for this account after installing and accessing the product. You can also create other user account profiles to control how other users may access the product and what actions they may perform. For more information on creating user accounts, see "User Management Preferences" in the SiteScope Help.

## Password Encryption

All SiteScope passwords are encrypted using a method called Triple Data Encryption Standard, or TDES. TDES applies the Data Encryption Algorithm on each 64-bit block of text three successive times, using either two or three different keys. As a result, unauthorized users cannot reproduce the original password in a reasonable amount of time.

## Using Secure Socket Layer (SSL) to Access SiteScope

SiteScope can be configured to use SSL to control access to the product interface. Enabling this option requires that users are authenticated using a certificate. For more information, see "Configuring SiteScope to Use SSL" on page 195.

## Configuring SiteScope to Send Bulk Data to ODB

SiteScope results can be sent to ODB either zipped or unzipped. The request includes a parameter that indicates to ODB whether the results being sent are in zipped or unzipped format.

**To send SiteScope results in a zipped format:**

- 1** Open the following file:  
`<SiteScope root directory>\discovery\discovery_agent.properties.`
- 2** Locate the line beginning `appilog.agent.probe.send.results.zipped`. If the line does not exist, add it to the file.
- 3** Change the value to `=true`.
- 4** Restart SiteScope. SiteScope results are zipped before being sent to ODB.



# 14

---

## Permissions and Credentials

This chapter contains a table of SiteScope monitors. Each monitor is listed with its corresponding protocol, the user permissions and credentials needed to access the monitor, and any further notes.

The purpose of this chapter is to provide you with basic information about the permissions needed to secure your SiteScope monitors.

Monitor Name	Protocol	User Permissions and Credentials	Notes
Amazon Web Services	HTTPS	AWS AccessKey ID, AWS SecretKey	This monitor uses secret access keys provided by Amazon. User can find them at Amazon's official site under the user's profile. The HTTP connection is secured.
Apache Server	HTTP HTTPS	None needed unless required to access the server statistics page.	
BroadVision	Proprietary		

Monitor Name	Protocol	User Permissions and Credentials	Notes
CheckPoint Firewall-1	SNMP	Community string.	This monitor does not support SNMP V3, so the community string passes plain text over the network. The target's SNMP agent may be configured so that the community string can only be used to read a subset of the MIB. The implication for such a configuration is that if an unauthorized person obtained the community string, he would only be able to read OIDs from the agent (but not be able to set them).

Monitor Name	Protocol	User Permissions and Credentials	Notes
Cisco Works	SNMP	Community string or user name/password, depending on SNMP version.	<p>The safest possible configuration for this monitor is running it against an agent configured to use SNMP V3 with authentication (SHA or MD5) and DES encryption for privacy. In this configuration, no unencrypted SNMP data passes over the network. This greatly reduces the risk that a malicious user could compromise the monitored device. It does not take into account security vulnerabilities from implementation bugs in the monitored device's SNMP agent.</p> <p>The riskiest configuration of this monitor is to use SNMP V1 with a community string that has both read and write access on the entire MIB implemented by the agent on the monitored device. In this configuration, a malicious user could obtain the community string by eavesdropping on the network, and then use that community string to reconfigure the device.</p>
Citrix Server	PDH/Perfex	Same as Microsoft ASP Server monitor.	
ColdFusion	Perfex	Same as Microsoft ASP Server monitor.	

Monitor Name	Protocol	User Permissions and Credentials	Notes
COM+	HTTP/ HTTPS		
CPU (Windows)	Perfex	Same as Microsoft ASP Server monitor.	<p>Add the server where SiteScope is running to the Domain Admin group in Active Directory (for Windows 2000 or later). With this option, the SiteScope service is set to log on as a local system account, but the machine where SiteScope is running is added to a group having domain administration privileges.</p> <p>Edit the registry access permissions for all machines in the domain to allow non-admin access. For details on enabling non-admin users to remotely monitor machines with perfmon, see Microsoft Knowledge Base article <a href="http://support.microsoft.com/kb/164018/en-us">http://support.microsoft.com/kb/164018/en-us</a>. This option requires changes to the registry on each remote machine that you want to monitor. This means that while the list of servers in the domain includes all machines in the domain, only those whose registry has been modified can be monitored without use of a connection profile.</p>



Monitor Name	Protocol	User Permissions and Credentials	Notes
CPU (Solaris/ Linux)	UNIX/ Linux Shell	Need shell access to the remote server. Supported access protocols are telnet, SSH, and rlogin. It is also necessary for the logged-in user to have permissions to run various executable programs.	It is possible to restrict logged-in users' access by using UNIX group permissions for the various commands that SiteScope would run. A list of the relevant commands for a particular operating system can be found in the <b>templates.os</b> files.
Database Counter	JDBC	User credentials are needed to authenticate access to the particular database. Each database has a particular method for providing access control to the particular tables that need to be accessed.	The user needs sufficient permission to execute any specified SQL statements.
Directory	Shell/Perfex	Need shell access to the remote server. Supported access protocols are telnet, SSH, and rlogin. It is also necessary for the logged-in user to have permissions to run various executable programs.	It is possible to restrict logged-in users' access by using UNIX group permissions for the various commands that SiteScope would run. A list of the relevant commands for a particular operating system can be found in the <b>templates.os</b> files.
Directory (Windows)	Netbios	Read-only file system access.	Permissions for specific files can be controlled at the operating system level.
Directory (Solaris/ Linux)	File System Access	Read-only file system access to the particular files.	Permissions for specific files can be controlled at the operating system level.
Disk Space (Windows)	Perfex	Same as Microsoft ASP Server monitor.	For Windows 2000, disk counters must be enabled in perfex.

Monitor Name	Protocol	User Permissions and Credentials	Notes
Disk Space (Solaris/Linux)	Shell	Need shell access to the remote server. Supported access protocols are telnet, SSH, and rlogin. It is also necessary for the logged-in user to have permission to run various executable programs.	It is possible to restrict logged-in users' access by using UNIX group permissions for the various commands that SiteScope would run. A list of the relevant commands for a particular operating system can be found in the <b>templates.os</b> files.

Monitor Name	Protocol	User Permissions and Credentials	Notes
F5 Big-IP	SNMP	Community string or user name/password depending on SNMP version.	<p>The safest possible configuration for this monitor is running it against an agent configured to use SNMP V3 with authentication (SHA or MD5) and DES encryption for privacy. In this configuration, no unencrypted SNMP data passes over the network. This greatly reduces the risk that a malicious user could compromise the monitored device. It does not take into account security vulnerabilities from implementation bugs in the monitored device's SNMP agent.</p> <p>The riskiest configuration of this monitor is to use SNMP V1 with a community string that has both read and write access on the entire MIB implemented by the agent on the monitored device. In this configuration, a malicious user could obtain the community string by eavesdropping on the network, and then use that community string to reconfigure the device.</p>

Monitor Name	Protocol	User Permissions and Credentials	Notes
File (Windows)	Netbios	Windows permissions for read-only access to log file.	
File (Solaris/Linux)	File System Access	Read-only file permission to the target file system.	
FTP	FTP	Valid user name and password for the FTP site with read-only permission to copy the user-specified file. The customer site may allow anonymous logon.	
HP iLO (Integrated Lights-Out)	SSH	Should be configured by the HP iLO system administrator.	When configuring the remote server, select <b>SSH version 2 only</b> in the Advanced Settings pane (to make it work faster).
LDAP	LDAP	Valid user name and password on the LDAP server to do simple authentication. Query or search operations require appropriate permissions. Anonymous authentication also supported in version 7.9.	
Link Check	HTTP/HTTPS	None needed unless the HTTP/HTTPS site requires a user name/password.	User needs sufficient permission to click on links.
Log File (Windows)	Netbios	Windows permissions for read-only access to log file.	

Monitor Name	Protocol	User Permissions and Credentials	Notes
Log File (Solaris/Linux)	Shell	Need shell access to the remote server. Supported access protocols are telnet, SSH, and rlogin. It is also necessary for the logged-in user to have permissions to run various executable programs. Read-only file permissions to the target file system.	It is possible to restrict logged-in users' access by using UNIX group permissions for the various command that SiteScope would run. A list of the relevant commands for a particular operating system can be found in the <b>templates.os</b> files.
Mail	SMTP	A valid email account and password.	
MAPI	MAPI	User name/password of one or two email accounts to send and receive test emails.	SiteScope must run as local administrator on the SiteScope server. Test email accounts must have local administrator authority in the SiteScope server.
Memory (Windows)	Perfex	Same as Microsoft ASP Server monitor.	
Memory (Solaris/Linux)	Shell	Need shell access to the remote server. Supported access protocols are telnet, SSH, and rlogin. It is also necessary for the logged-in user to have permissions to run various executable programs.	It is possible to restrict logged-in users' access by using UNIX group permissions for the various commands that SiteScope would run. A list of the relevant commands for a particular operating system can be found in the <b>templates.os</b> files.

Monitor Name	Protocol	User Permissions and Credentials	Notes
Microsoft ASP Server	Perfex	<p>Monitoring performance objects on Windows requires that a user have specific access permissions as described in the Microsoft Knowledge Base for article <a href="http://support.microsoft.com/kb/300702/en-us">http://support.microsoft.com/kb/300702/en-us</a> and article <a href="http://support.microsoft.com/kb/164018/en-us">http://support.microsoft.com/kb/164018/en-us</a>. These articles describe the permissions and security policies that should be granted to the user on the monitored server.</p>	<p><b>Perfmon User.</b> A user that was granted the required privileges to be able to monitor performance objects on Windows servers.</p> <p><b>Note:</b> The <b>Performance Monitor Users</b> (on Windows 2000 and Windows 2003), <b>Power Users</b>, and <b>Administrators</b> groups on Windows servers are already associated with the set of permissions and security policies that are required for a Perfmon User. In other words, any user that belongs to these groups has all required permissions to monitor the performance objects and automatically becomes a Perfmon User. The <b>Performance Monitor Users</b> group contains the exact set of privileges whereas the <b>Power Users</b> and <b>Administrators</b> groups are associated with multiple additional privileges that are not required for performance monitoring.</p>

Monitor Name	Protocol	User Permissions and Credentials	Notes
Microsoft ASP Server (continued)	Perfex (continued)		<p><b>SiteScope User.</b> The user that the SiteScope service logs on as.</p> <p>For SiteScope monitors to be able to collect perfmon data from remote servers, connections must be established to these servers using the credentials of a user defined as a Perfmon User. These connections can be established with the following options:</p> <p>Configure the SiteScope user to be a domain user that is also a user on the remote machines.</p> <p>In the case that the SiteScope User is not defined as a Perfmon User on remote machines, a Remote NT object must be configured in SiteScope using the credentials of a user that is defined as a Perfmon User on the remote machine. Monitors are then configured to use the Remote NT object.</p>
Microsoft IIS Server	Perfex	Same as Microsoft ASP Server monitor.	
Microsoft SQL Server	Perfex	Same as Microsoft ASP Server monitor.	

Monitor Name	Protocol	User Permissions and Credentials	Notes
Microsoft Windows Dialup	MODEM	User name/password to the ISP account being contacted. The account needs sufficient authority to execute its specified test monitors.	
Microsoft Windows Event Log	Perfex	Same as Microsoft ASP Server monitor.	
Microsoft Windows Media Player	File System Access	Read-only file permission to the target file system.	
Microsoft Windows Media Server	Perfex	Same as Microsoft ASP Server monitor.	
Microsoft Windows Performance Counter	Perfex	Same as Microsoft ASP Server monitor.	
Microsoft Windows Resources	PDH	Same as Microsoft ASP Server monitor.	



Monitor Name	Protocol	User Permissions and Credentials	Notes
Network Bandwidth	SNMP	Community string or user name/password depending on SNMP version.	<p>The safest possible configuration for this monitor is running it against an agent configured to use SNMP V3 with authentication (SHA or MD5) and DES encryption for privacy. In this configuration no unencrypted SNMP data passes over the network. This greatly reduces the risk that a malicious user could compromise the monitored device. It does not take into account security vulnerabilities from implementation bugs in the monitored device's SNMP agent.</p> <p>The riskiest configuration of this monitor is to use SNMP V1 with a community string that has both read and write access on the entire MIB implemented by the agent on the monitored device. In this configuration, a malicious user could obtain the community string by eavesdropping on the network, and then use that community string to reconfigure the device.</p>

Monitor Name	Protocol	User Permissions and Credentials	Notes
News	NNTP	A valid user name and password if the news server requires it, with read-only permission to query total number of messages in the news groups.	
Oracle 9i Application Server	HTTP/HTTPS		
Oracle Database	JDBC	An Oracle user logs in with the ability to execute all the SQL statements found in <SiteScope root directory>\ <b>templates.applications\commands.oraclejdbc</b> .	
Ping	ICMP	N/A	
Port	TCP	N/A	
Radius	Radius	A valid user name and password on the Radius server. No other permissions are needed.	SiteScope's IP must be added to the list of servers allowed to communicate with the Radius server. It must also be configured to do PAP authentication.
Real Media Player	File System Access	Read-only file permission on the target file system.	
Real Media Server	Perfex	Same as Microsoft ASP Server monitor.	
SAP CCMS	Proprietary	XMI authorization.	Profiles that have XMI authorization are S_A.SYSTEM, PD_CHICAGO, S_WF_RWTEST, and SAP_ALL.

Monitor Name	Protocol	User Permissions and Credentials	Notes
SAP CCMS Alert	Proprietary		
SAP Performance or SAP Work Processes	Proprietary	Still being researched.	
Script (Windows)	Remote shell	Same as Microsoft ASP Server monitor.	
Script (Solaris/Linux)	Shell	Need shell access to the remote server. Supported access protocols are telnet, SSH, and rlogin. It is also necessary for the logged-in user to have permissions to run various executable programs.	It is possible to restrict logged-in users' access by using UNIX group permissions for the various commands that SiteScope would run. A list of the relevant commands for a particular operating system can be found in the <b>templates.os</b> files.
Script on local machine (Solaris, Linux, and Windows)	File System Access/Perfex	Read-only file permission to the target file system.	
Service (Windows)	Perfex	Same as Microsoft ASP Server monitor.	
Service (Solaris/Linux)	Shell	Need shell access to the remote server. Supported access protocols are telnet, SSH, and rlogin. It is also necessary for the logged-in user to have permissions to run various executable programs.	It is possible to restrict logged-in users' access by using UNIX group permissions for the various commands that SiteScope would run. A list of the relevant commands for a particular operating system can be found in the <b>templates.os</b> files.

Monitor Name	Protocol	User Permissions and Credentials	Notes
Siebel Application Server (previously Siebel Server Manager)	CmdLine	User account must have Siebel Administrator Responsibility privileges to issue Siebel server manager (svrmgr) commands.	If the svrmgr client is remote, then a Remote (Windows or UNIX) must be set up with the appropriate user name and password credentials for executing the remote svrmgr command.
Siebel Log	File System Access	File read-only permission to the target Siebel server file system.	
Siebel Web Server	HTTP/HTTPS	User name and password are needed if target Siebel Extensions Page is behind third-party, HTML, form-based authentication software.	User must have permission to retrieve the Siebel SWE page.

Monitor Name	Protocol	User Permissions and Credentials	Notes
SNMP	SNMP	Community string or user name/password, depending on the SNMP version.	<p>The safest possible configuration for this monitor is running it against an agent configured to use SNMP V3 with authentication (SHA or MD5) and DES encryption for privacy. In this configuration, no unencrypted SNMP data passes over the network. This greatly reduces the risk that a malicious user could compromise the monitored device. It does not take into account security vulnerabilities from implementation bugs in the monitored device's SNMP agent.</p> <p>The riskiest configuration of this monitor is to use SNMP V1 with a community string that has both read and write access on the entire MIB implemented by the agent on the monitored device. In this configuration, a malicious user could obtain the community string by eavesdropping on the network, and then use that community string to reconfigure the device.</p>

Monitor Name	Protocol	User Permissions and Credentials	Notes
SNMP by MIB	SNMP	Community string or user name and password, depending on the SNMP version.	<p>The safest possible configuration for this monitor is running it against an agent configured to use SNMP V3 with authentication (SHA or MD5) and DES encryption for privacy. In this configuration, no unencrypted SNMP data passes over the network. It greatly reduces the risk that a malicious user could compromise the monitored device. It does not take into account security vulnerabilities from implementation bugs in the monitored device's SNMP agent.</p> <p>The riskiest configuration of this monitor is to use SNMP V1 with a community string that has both read and write access on the entire MIB implemented by the agent on the monitored device. In this configuration, a malicious user could obtain the community string by eavesdropping on the network, and then use that community string to reconfigure the device.</p>

Monitor Name	Protocol	User Permissions and Credentials	Notes
SNMP Trap	SNMP	None, although permissions to configure agents on the network to send traps to SiteScope are required. SiteScope must be running as a privileged user so that it can bind to port 162, a reserved port.	The security risk associated with SNMP V1 and V2 traps is that a malicious user could eavesdrop on the data that is passed in the traps.  Using V3 traps with authentication and privacy greatly reduces the chance that data can be used maliciously by eavesdroppers.
SunONE	HTTP/ HTTPS	None, unless using a proxy that requires authentication.	
Tuxedo	Proprietary	PeopleSoft Tuxedo comes with two preconfigured users, <b>PS</b> and <b>VP</b> , that are monitor-only accounts. No other user can be created or used for SiteScope monitoring.	
URL	HTTP/ HTTPS	None needed for SiteScope. The server may require a valid user name and password.	
URL Content	HTTP/ HTTPS	None needed for SiteScope. The server may require a valid user name and password.	
URL List	HTTP/ HTTPS	None needed for SiteScope. The server may require a valid user name and password.	

Monitor Name	Protocol	User Permissions and Credentials	Notes
URL Sequence	HTTP/ HTTPS	None needed for SiteScope. The server may require a valid user name and password.	
Web Server	Perfex	Same as Microsoft ASP Server monitor.	
Web Server (Solaris, Linux, and Windows)	File System Access	Read-only file permission to the target file system.	
Web Service	HTTP/ HTTPS	Supports basic, digest, and NTLM authentication if required by the target Web service.	
WebLogic Application Server 5.x	SNMP	Community string credential must match the string in the SNMP agent.	
WebLogic Application Server 6.x and above	RMI	Requires a user that belongs to a group with at least monitor role privilege.	
WebSphere Application Server 3.5x	RMI		
WebSphere Application Server 4.5	RMI	Requires a user that belongs to a group with at least monitor role privilege.	
WebSphere Application Server 5.x (SOAP over HTTP)	HTTP/ HTTPS	Requires a user that belongs to a group with at least monitor role privilege.	



Monitor Name	Protocol	User Permissions and Credentials	Notes
WebSphere MQ Status	Proprietary	SiteScope account must be a member of mqm group in the MQ Windows server.  In MQ UNIX, the server connection channel used must not require SSL authentication.	
WebSphere Performance Servlet	HTTP/HTTPS	HTTP authentication via user name and password to the URL of the servlet. Credentials can be customized by the user.	



# 15

---

## Configuring SiteScope to Use SSL

### **This chapter includes:**

- ▶ About Using SSL in SiteScope on page 195
- ▶ Preparing SiteScope for Using SSL on page 196
- ▶ Configuring SiteScope for SSL on page 200
- ▶ Configuring SiteScope to Connect to a BSM Server That Requires a Client Certificate on page 202

### **About Using SSL in SiteScope**

SiteScope can be configured to use Secure Sockets Layer (SSL) to restrict access to the SiteScope interface. You set a SiteScope server to support SSL by configuring the Web server used to serve the SiteScope interface to support SSL. You do this by importing a digital certificate to a key store file and then changing sever configuration settings to have SiteScope only respond to HTTPS requests. SiteScope can also be configured to connect to a BSM server that requires a client certificate.

---

**Caution:** To limit all access to SiteScope to HTTPS client connections, you must configure both the SiteScope Web server and the Tomcat server supplied with SiteScope to use SSL using the steps in this section.

---

## Preparing SiteScope for Using SSL

SiteScope is shipped with **Keytool.exe**. Keytool is a key and certificate management utility. It enables users to administer their own public/private key pairs and associated certificates for authentication using digital signatures. It also allows users to cache the public keys of other persons and organizations they communicate with. This is installed in the `<SiteScope install path>\SiteScope\java\bin` directory.

---

**Caution:** When you create, request, and install a digital certificate, make a note of the parameters and command line arguments that you use in each step of the process. It is very important that you use the same values throughout the procedure.

---

You can find out more about Keytool at <http://java.sun.com/j2se/1.3/docs/tooldocs/win32/keytool.html>.

This section includes the following topics:

- "Using a Certificate from a Certificate Authority" on page 196
- "Using a Self-Signed Certificate" on page 199

### Using a Certificate from a Certificate Authority

You can use a digital certificate issued by a Certificate Authority. To use this option, you need a digital certificate that can be imported into the key storage file used by Keytool. If your organization does not currently have a digital certificate for this purpose, you need to make a request to a Certificate Authority to issue you a certificate.

You use the following steps to create a KeyStore file and a digital certificate request.

**To create a certificate request file for a Certificate Authority:**

- 1** Remove the **serverKeystore** file that is located in the `<SiteScope root directory>\groups` directory. You can delete it or simply move it to a different directory.
- 2** Create a key pair by running the command line listed below from the `<SiteScope root directory>\java\bin` directory.

---

**Note:** This command and all others you use must be entered on a single line. The line is divided here to fit on this page.

---

```
keytool -genkey -dname "CN=www.yourDomain.com, OU=yourDepartment,
O=yourCompanyName, L=yourLocation, S=yourState, C=yourCountryCode" -
alias yourAlias -keypass keypass -keystore ..\..\groups\serverKeystore -
storepass passphrase -keyalg "RSA" -validity valdays
```

This command creates a file called **serverKeystore** in the `<SiteScope root directory>\groups` directory. SiteScope uses this file to store the certificates used in your secure sessions. Make sure you keep a backup copy of this file in another location.

**Guidelines and Limitations**

- The value of a `-dname` option must be in the following order where the italicized values are replaced by values of your choosing. The keywords are abbreviations for the following:

CN = *commonName* - Common name of a person (for example, Warren Pease)

OU = *organizationUnit* - Small organizational unit (for example, NetAdmin)

O = *organizationName* - Large organization name (for example, ACME-Systems, Inc.)

L = *localityName* - Locality (city) name (for example, Palo Alto)

S = *stateName* - State or province name (for example, California)

C = *country* - Two-letter country code (for example, US)

- ▶ The subcomponents within the `-dname` (distinguished name string) variable are case-insensitive and they are order-sensitive, although you do not have to include all of the subcomponents. The `-dname` variable should represent your company and the CN is the domain name of the Web server on which SiteScope is installed.
- ▶ The value of `-storepass` is a password used to protect the KeyStore file. This password must be at least 6 characters long. You need to use this password to import to and remove certificate data from the KeyStore file.
- ▶ The `-alias` variable is an alias or nickname you use to identify an entry in your KeyStore.

After you receive your certificate from a Certificate Authority (the reply message should include a file called **cert.cer**), you need to import this certificate into the KeyStore file you created using the steps above. The file should be called **serverKeystore**. You use the following steps to import the certificate for use with SiteScope.

**To import a certificate from a Certificate Authority:**

- 1** Import the certificate data into the KeyStore file by running the following command from the `<SiteScope root directory>\java\bin` directory:  

```
keytool -import -trustcacerts -alias yourAlias -file cert.cer -keystore  
..\..\groups\serverKeystore
```
- 2** To change SiteScope to use a secure connection, you need to add or modify certain settings or configuration files in SiteScope. For details, see "Configuring SiteScope for SSL" on page 200.

## Using a Self-Signed Certificate

Alternatively, you can generate a self-signed certificate for use with SiteScope. To do this, you use the `-selfcert` option to have the Keytool utility generate a self-signed certificate using the following steps.

**To use a self-signed certificate:**

- 1** Remove the `serverKeystore` file that is located in the `<SiteScope root directory>\groups` directory. You can delete it or simply move it to a different directory.
- 2** Run the following command from the `<SiteScope root directory>\java\bin` directory. The values in italics are variables that you fill in with information specific to your organization.

---

**Note:** This command and all others you use must be entered on a single line. The line is divided here to fit on this page.

---

```
keytool -genkey -dname "CN=www.yourDomain.com, OU=yourDepartment,
O=yourCompanyName, L=yourLocation, S=yourState, C=yourCountryCode" -
alias yourAlias -keypass keypass -keystore ..\..\groups\serverKeystore -
storepass passphrase -keyalg "RSA" -validity valdays
```

- 3** Run the following command, also from the `<SiteScope root directory>\java\bin` directory:

```
keytool -selfcert -alias yourAlias -sigalg "MD5withRSA" -keypass password -
dname "CN=www.yourDomain.com, OU=yourDepartment,
O=yourCompanyName, L=yourLocation, S=yourState, C=yourCountryCode" -
keystore ..\..\groups\serverKeystore
```
- 4** To change SiteScope to use a secured connection, you need to add or modify certain settings or configuration files in SiteScope. For details, see "Configuring SiteScope for SSL" on page 200.

## Configuring SiteScope for SSL

To enable SSL on Tomcat you need to make changes to the configuration files used by the Tomcat server.

- 1 Open the **server.xml** file that is located in the **<SiteScope root directory>\Tomcat\conf** directory.
- 2 Locate the section of the configuration file that looks like the following:

```
<!-- Define a SSL Coyote HTTP/1.1 Connector on port 8443 -->
<!--
<Connector port="8443"
maxThreads="150" minSpareThreads="25" maxSpareThreads="75"
enableLookups="false" disableUploadTimeout="true"
acceptCount="100" debug="0" scheme="https" secure="true"
clientAuth="false" sslProtocol="TLS" />
-->
```

- 3 Change this section to the following:

```
<!-- Define a SSL Coyote HTTP/1.1 Connector on port 8443 -->

<Connector port="8443"
maxThreads="150" minSpareThreads="25" maxSpareThreads="75"
enableLookups="false" disableUploadTimeout="true"
acceptCount="100" debug="0" scheme="https" secure="true"
clientAuth="false" sslProtocol="TLS"
keystoreFile="<SiteScope_install_path>\SiteScope\groups\serverKeystore"
keystorePass="testing"
/>
```

Where **<SiteScope\_install\_path>** is the path to your SiteScope installation.



**Note:**

- ▶ If there are other HP products installed on the same server as SiteScope, you might need to change port 8443 to another port to avoid conflict.
  - ▶ Tomcat log output is written to the `<SiteScope root dir>\logs\tomcat.log` file. Settings for the log file can be configured from the `<SiteScope root dir>\Tomcat\common\classes\log4j.properties` file.
- 

By default, Tomcat looks for a `.keystore` file in the SiteScope user's home directory.

For more information on enabling SSL for the Tomcat server, see <http://tomcat.apache.org/tomcat-5.5-doc/ssl-howto.html>.

After enabling Tomcat to use SSL using this example, the SiteScope interface is available at a URL with the following syntax:

`https://<sitescope_server>:8443/sitescope`

## Configuring SiteScope to Connect to a BSM Server That Requires a Client Certificate

To connect SiteScope to a BSM server that requires a client certificate, perform the following:

- 1 Connect to the SiteScope server.
- 2 Download a certificate from a Certificate Authority (if you are not using a publicly known Certificate Authority such as Verisign), and save it to **c:\ca.cer**.
- 3 Import the Certificate Authority certificate into the SiteScope java keystore by running the following command from the **<SiteScope root directory>\java\bin** directory:

```
keytool -import -trustcacerts -alias <your_CA> -keystore ..\lib\security\cacerts  
-file c:\ca.cer
```

For example:

```
keytool -import -trustcacerts -alias qaCA -keystore ..\lib\security\cacerts -file c:\ca.cer
```

- 4** Create a keystore under **<SiteScope root directory>/templates.certificates** by running the following command from the **<SiteScope root directory>\java\bin** directory:

```
keytool -genkey -keyalg RSA -alias sis -keystore
<SiteScope root directory>\templates.certificates\ks -storepass
<your_keystore_password>
```

For example:

```
keytool -genkey -keyalg RSA -alias sis -keystore
C:\SiteScope\templates.certificates\ks -storepass changeit
What is your first and last name?
[Unknown]: domain.name
What is the name of your organizational unit?
[Unknown]: dept
What is the name of your organization?
[Unknown]: XYZ Ltd
What is the name of your City or Locality?
[Unknown]: New York
What is the name of your State or Province?
[Unknown]: USA
What is the two-letter country code for this unit?
[Unknown]: US
Is CN=domain.name, OU=dept, O=XYZ Ltd, L=New York, ST=USA, C=US correct?
[no]: yes

Enter key password for <SiteScope>
```

Press **ENTER** to use the same password as the keystore password.

- 5** Create a certificate request for this keystore by running the following command from the **<SiteScope root directory>\java\bin** directory:

```
keytool -certreq -alias sis -file c:\sis.csr -keystore
<SiteScope root directory>\templates.certificates\ks -storepass
<your_keystore_password>
```

For example:

```
keytool -certreq -alias sis -file c:\sis.csr -keystore
C:\SiteScope\templates.certificates\ks -storepass changeit
```

- 6 Have your Certificate Authority sign the certificate request. Copy/paste the contents of the `.csr` file into your Certificate Authority Web form.
- 7 Download the signed client certificate in BASE-64 format to `<SiteScope root directory>\templates.certificates\clientcert.cer`.
- 8 Download the Certificate Authority certificate in BASE-64 format to `c:\.`
- 9 Import the Certificate Authority certificate into the keystore by running the following command:

```
keytool -import -alias ca -file c:\ca.cer -keystore  
<SiteScope root directory>\templates.certificates\ks -storepass  
<your_keystore_password>
```

For example:

```
keytool -import -alias ca -file c:\ca.cer -keystore  
C:\SiteScope\templates.certificates\ks -storepass changeit  
Owner: CN=dept-CA, DC=domain.name  
Issuer: CN=dept-CA, DC=domain.name  
Serial number: 2c2721eb293d60b4424fe82e37794d2c  
Valid from: Tue Jun 17 11:49:31 IDT 2008 until: Mon Jun 17 11:57:06 IDT 2013  
Certificate fingerprints:  
    MD5: 14:59:8F:47:00:E8:10:93:23:1C:C6:22:6F:A6:6C:5B  
    SHA1: 17:2F:4E:76:83:5F:03:BB:A4:B9:96:D4:80:E3:08:94:8C:D5:4A:D5  
Trust this certificate? [no]: yes  
Certificate was added to keystore
```

- 10 Import the client certificate into the keystore by running the following command:

```
keytool -import -alias sis -file  
<SiteScope root directory>\templates.certificates\certnew.cer -keystore  
<SiteScope root directory>\templates.certificates\ks -storepass  
<your_keystore_password>
```

For example:

```
keytool -import -alias sis -file c:\SiteScope\templates.certificates\certnew.cer -  
keystore C:\SiteScope\templates.certificates\ks -storepass changeit
```

The certificate reply is installed in the keystore `<SiteScope root directory>\java\bin` directory.

- 11** Check the keystore contents by running the following command from the **<SiteScope root directory>\java\bin** directory, and enter the keystore password:

```
keytool -list -keystore <SiteScope root directory>\templates.certificates\ks
```

For example:

```
keytool -list -keystore C:\SiteScope\templates.certificates\ks
Enter keystore password: changeit

Keystore type: jks
Keystore provider: SUN

Your keystore contains 2 entries

ca, Mar 8, 2009, trustedCertEntry,
Certificate fingerprint (MD5): 14:59:8F:47:00:E8:10:93:23:1C:C6:22:6F:A6:6C:5B
sis, Mar 8, 2009, keyEntry,
Certificate fingerprint (MD5): C7:70:8B:3C:2D:A9:48:EB:24:8A:46:77:B0:A3:42:E1

C:\SiteScope\java\bin>
```

- 12** To use this keystore for client certificate, add the following lines to the **<SiteScope root directory>\groups\master.config** file:

```
_urlClientCert=<keystoreName>
_urlClientCertPassword=<keystorePassword>
```

For example:

```
_urlClientCert=ks
_urlClientCertPassword=changeit
```

- 13** In SiteScope **Preferences > Integration Preferences > BSM Preferences Available Operations**, click **Reset** to delete all BSM related settings from the SiteScope server and all SiteScope configurations from BSM.

- 14** In BSM, select **Admin > System Availability Management Administration**, and click the **New SiteScope** button to add the SiteScope instance.

---

**Note:** If the connection between SiteScope and BSM fails, check the **<SiteScope root directory>\log\bac\_integration.log** for errors.

---

# Part V

---

## Getting Started and Accessing SiteScope





# 16

---

## Post-Installation Administration

### This chapter includes:

- Post-Installation Administration Checklist on page 209

### Post-Installation Administration Checklist

This section includes recommended steps you should perform after installing SiteScope.

✓	Step
	Register for SiteScope support. For more information, see "Getting Started Roadmap" on page 17.
	Log in to the SiteScope Web interface using a Web browser. For more information, see "Connecting to SiteScope" on page 215.
	If you are upgrading to SiteScope 11.00 from an earlier version of SiteScope, use the Configuration Tool to transfer monitor and group configuration data from the older SiteScope installation to the new installation. For more information on using the Configuration Tool, see "Using the SiteScope Configuration Tool" on page 133.
	If you did not enter your SiteScope license information during installation, enter it in the General Preferences page, as described in "General Preferences" of SiteScope Help. New installations operate with a 60 day evaluation license. For license details, see "SiteScope Licenses" on page 33.

✓	Step
	<p>Create a user name and password for the SiteScope administrator account. This is the default account that is active when the product is installed. It has full privileges to manage SiteScope and is the account that all users who access the product use unless you restrict the account. Create and configure other user accounts based on the requirements of the organization. For details, see "User Management Preferences" in SiteScope Help. If no user name and password are defined for the administrator user, SiteScope skips the Login page and logs in automatically.</p>
	<p>Configure the SiteScope Email Preferences email server with an administrators email address and specify a mail server that SiteScope can use to forward email messages and alerts to users. For details, see "Email Preferences" in SiteScope Help.</p>
	<p>Configure connection profiles for the remote servers you want to be able to monitor. Specify the connection method to use in accordance with your security requirements. For details, see "How to Configure SiteScope to Monitor a Remote Microsoft Windows Server" and "How to Configure SiteScope to Monitor a Remote UNIX Server" in SiteScope Help.</p>
	<p>If necessary, adjust Log Preferences to set how many days of monitor data are retained on the SiteScope server. By default, SiteScope deletes logs older than 40 days. If you plan to have monitor data exported to an external database, prepare the database, the necessary drivers, and configure the Log Preferences as applicable. For details, see "Log Preferences" in SiteScope Help.</p>
	<p>Install middleware drivers for connectivity with remote databases and applications for those monitors that require drivers.</p>
	<p>Configure SiteScope to report to HP Business Service Management. For details, see "Configuring the Connection" in SiteScope Help.</p>
	<p>Outline group and monitor organization based on the requirements and constraints identified in your assessment of the business system infrastructure.</p>
	<p>Create and develop templates to help speed the deployment of monitoring using standardized group structure, naming conventions, and configuration settings. For details, see "SiteScope Templates" in SiteScope Help.</p>

✓	Step
	Build dependencies between groups and key monitors to help control redundant alerting. For details, see "How to Manage a Group" in SiteScope Help.
	Roll out SiteScope to business stakeholders and system administrators.

Once the SiteScope system is up and running with defined users and incoming monitor data, begin the process of educating business and systems users on how to access and use SiteScope reporting and alerting functionality.



# 17

---

## Getting Started with SiteScope

### **This chapter includes:**

- ▶ About Starting the SiteScope Service on page 213
- ▶ Starting and Stopping the SiteScope Service on Windows Platforms on page 214
- ▶ Starting and Stopping the SiteScope Process on Solaris and Linux Platforms on page 215
- ▶ Connecting to SiteScope on page 215
- ▶ SiteScope Classic Interface on page 217
- ▶ Troubleshooting and Limitations on page 217

### **About Starting the SiteScope Service**

The SiteScope process is started on all platforms during installation.

- ▶ On Windows platforms, SiteScope is added as a service that is set to restart automatically if the server is rebooted.
- ▶ On Solaris and Linux platforms, whenever you reboot the server where SiteScope is installed, you must restart the SiteScope process.

You can start and stop the SiteScope process manually as necessary using the steps described in this section.

## Starting and Stopping the SiteScope Service on Windows Platforms

SiteScope is installed as a service on Microsoft Windows platforms. By default, the SiteScope Service is set to restart automatically whenever the server is rebooted. You can start and stop the SiteScope service manually by using the Services control panel.

**To start or stop the SiteScope service using Services control panel:**

- 1** Open the Services control panel by selecting **Start > Settings > Control Panel > Administrative Tools > Services**.
- 2** Select **SiteScope** in the list of services and right-click to display the action menu.
- 3** Select **Start** or **Stop** as applicable from the action menu.

### Netstart and Netstop Commands

You can also start and stop the SiteScope service by using the netstart and netstop commands.

**To start the SiteScope service using netstart:**

- 1** Open a command line window on the server where SiteScope is installed.
- 2** Run the netstart utility using the following syntax:

```
net start SiteScope
```

**To stop the SiteScope service using netstop:**

- 1** Open a command line window on the server where SiteScope is running.
- 2** Run the netstop utility using the following syntax:

```
net stop SiteScope
```

## Starting and Stopping the SiteScope Process on Solaris and Linux Platforms

You can start and stop SiteScope manually by using the shell scripts supplied with the product. You can automatically restart SiteScope when a server is rebooted by using an init.d script.

### To start the SiteScope process on Solaris and Linux:

- 1 Open a terminal window on the server where SiteScope is installed.
- 2 Run the start command shell script using the following syntax:

```
<installpath>/SiteScope/start
```

### To stop the SiteScope process on Solaris and Linux:

- 1 Open a terminal window on the server where SiteScope is running.
- 2 Run the stop command shell script using the following syntax:

```
<installpath>/SiteScope/stop
```

In each of the commands above, replace `<installpath>` with the path where SiteScope is installed. For example, if you installed SiteScope in the `/usr` directory, the command to stop SiteScope would be:

```
/usr/SiteScope/stop
```

## Connecting to SiteScope

SiteScope is designed as a Web application. This means that you view and manage SiteScope using a Web browser with access to the SiteScope server.

SiteScope is installed to answer on two ports: 8080 and 8888. If there is another service configured to use these ports, the installation process attempts to configure SiteScope to answer on another port.


On Windows platforms, the installation process also adds a link to SiteScope in the **Start > Programs** menu for SiteScope. The Start menu folder is selected during the installation procedure.

## Accessing SiteScope

To access SiteScope, enter the SiteScope address in a Web browser. The default address is: `http://localhost:8080/SiteScope`.

On Windows platforms, you can also access SiteScope from the Start menu by clicking **Start > Programs > HP SiteScope > Open HP SiteScope**.

The first time SiteScope is deployed, there is a delay for initialization of the interface elements. SiteScope opens to the Dashboard view, as shown below.



---

### Note:

- ▶ To restrict access to this account and its privileges, you need to edit the administrator account profile to include a user login name and login password. SiteScope then displays a login dialogue before SiteScope can be accessed. For information on editing the administrator account profile, see "User Management Preferences" in SiteScope Help.
  - ▶ When viewing SiteScope from another machine, it is recommended to use a machine that has Java Runtime Environment (JRE) 1.6.0\_14 or later installed.
-



## SiteScope Classic Interface

The SiteScope Classic interface that was available in earlier versions of SiteScope using the URL `http://<sitescope_host>:8888`, is no longer available for managing SiteScope.

You can still access specific pages in the Classic interface if they are listed in the `_serverFilter` property in the `master.config` file. Pages listed by default include the Monitor Summary and Alert Report pages.

---

**Note:** You should not remove SiteScope Classic interface pages that are enabled by default, as this may cause some functionality to fail.

---

## Troubleshooting and Limitations

This section contains troubleshooting and limitations for the following issues when logging on to SiteScope:

- ▶ "SiteScope does not start and "Several Java Virtual machines running in the same process caused an error" is displayed" on page 218
- ▶ "SiteScope does not start and an error message is displayed" on page 218
- ▶ "SiteScope applet loading fails with a "NoClassDefFound" exception" on page 219
- ▶ "The SiteScope menu bar opens but the applet fails to start, and you see a blank screen, an error, or an "x" image" on page 219
- ▶ "SiteScope hangs when opening the same SiteScope server on more than one tab in a browser window" on page 220
- ▶ "Backing up and recovering a SiteScope installation if unable to start SiteScope" on page 220

## **SiteScope does not start and "Several Java Virtual machines running in the same process caused an error" is displayed**

This is a known Java defect

([http://bugs.sun.com/view\\_bug.do?bug\\_id=6516270](http://bugs.sun.com/view_bug.do?bug_id=6516270)) that might occur when using Internet Explorer 7.

**Possible solution 1:** Use a browser other than Internet Explorer 7.

**Possible solution 2:** Upgrade to Java Runtime Environment 1.6.0\_14 or later.

**Possible solution 3:** In the Add or Remove Programs dialog box (**Start > Control Panel > Add or Remove Programs**), remove all Java/Java Runtime Environment installations except for the latest version.

## **SiteScope does not start and an error message is displayed**

If you encounter an error message such as "The Java Runtime Environment cannot be loaded", or any other unknown error while starting the SiteScope applet, perform the steps below.

After each step, try to reopen SiteScope. If SiteScope fails again, proceed to the next step.

- 1** Close all the browser's windows.
- 2** End all remaining browser processes (if any remained) using Windows Task Manager.
- 3** Clean the local Java applet cache. Select **Start > Control Panel > Java**. In the **General** tab, click **Settings > Delete Files** and then click **OK**.
- 4** Clean the local Java applet cache by deleting the content of the following folder: C:\Documents and Settings\\Application Data\Sun\Java\Deployment\cache.

## SiteScope applet loading fails with a "NoClassDefFound" exception

If applet loading fails with a "NoClassDefFound" exception, select the **Keep temporary files on my computer** option in your client Java configuration (**Control Panel > Java > General Tab > Temporary Files Settings > Settings**).

If security issues require it, delete the temporary files manually when you finished using the SiteScope applet:

- 1 Close the SiteScope applet.
- 2 Select **Control Panel > Java > General Tab > Temporary Files Settings**, and click **Delete Files**.

## The SiteScope menu bar opens but the applet fails to start, and you see a blank screen, an error, or an "x" image

This may occur if the Java control panel is not configured to use the Web browser.

### Possible solution:

- 1 Click **Start > Control Panel > Java**. In the **General** tab, click **Network Settings**, select the **Direct Connection** option, and then click **OK**.
- 2 In the **Advanced** tab, expand the **Default Java for browsers** folder (or **<APPLET> tag support** if you are using Java 5). Make sure that **Microsoft Internet Explorer** and **Mozilla family** are selected. Click **Apply** and then click **OK**.
- 3 Restart your browser.

## **SiteScope hangs when opening the same SiteScope server on more than one tab in a browser window**

When opening the same SiteScope server user interface in more than one tab of a browser window, SiteScope hangs when trying to navigate between the SiteScope server tabs.

### **Possible solution:**

- Close the redundant tabs, and make sure that only one tab is open for the same SiteScope server user interface.
- Alternatively, open a new browser window.

## **Backing up and recovering a SiteScope installation if unable to start SiteScope**

To recover the SiteScope configuration data if SiteScope goes down and you are unable to restart it, you should make a backup of your current SiteScope installation directory and all of the subdirectories within the directory before installing a new version of SiteScope. You can back up the current SiteScope installation using the Configuration Tool to export SiteScope data to a ZIP file, or you can manually back up the required files.

After reinstalling SiteScope, the monitor configuration data can be copied into SiteScope using the Configuration Tool (if you used the tool to make a backup of your installation directory), or by deleting from the new installation directory all the folders and files that you backed up, and then copying the backed up folders and files to the installation directory.

**To back up the SiteScope installation:****1** Stop SiteScope.

---

**Note:** Although it is not mandatory to stop SiteScope, it is recommended to do so before making a back up.

---

**2** Make a backup of your current SiteScope installation directory either by:

- Using the Configuration Tool to export your configuration into a zip file. For details, see "Using the SiteScope Configuration Tool" on page 133.
- Copy the following folders and files from the SiteScope installation to your backup destination:

Directory	Description
\cache	Contains data samples that were not reported to Business Service Management if Business Service Management was down.
\conf\ems	Contains key configuration and control files used with Integration monitor types. This is only applicable if you use SiteScope as an agent reporting to another Business Service Management application.
\conf\integration	Contains topology files used for integrations with Business Service Management.
\discovery\scripts\custom	Contains custom discovery scripts.
\groups	Contains monitor, alert, report, and other critical configuration data needed for SiteScope operation.

Directory	Description
\htdocs	Contains scheduled reports and user-customized style sheets for the SiteScope interface. Backup this directory and copy it to the SiteScope directory (within the same SiteScope versions) to avoid damaging the report pages and to see old reports. This folder cannot be backed up when the configuration is imported into a newer SiteScope version.
\logs	Contains a number of logs including date coded logs of monitoring data. Selectively back up the most recent monitoring data log files along with the other log types in this directory. You may also want to back up the <b>error.log</b> , <b>RunMonitor.log</b> , <b>access.log</b> , <b>alert.log</b> , and <b>monitorCount.log</b> logs for historical continuity:
\persistence	This is the main persistence directory of the product. All the defined monitors, groups, alerts, templates, and many other SiteScope entities are found in this directory.
\scripts	Contains scripts used by Script monitors.
\scripts.remote	Contains command scripts used by Script monitors to trigger other scripts on remote servers.
\templates.*	Includes data and templates used to customize monitor function, alert content, and other features. The group of subdirectories all begin with the name templates. <b>Example:</b> templates.mail, templates.os, templates.webscripts
\WEB-INF\lib\peregrine.jar	File that might have been altered (regenerated) when configuring the HP Service Manager integration.

**To recover the SiteScope installation:**

- 1** Perform a new installation of SiteScope. For details, see "Installing SiteScope" on page 89.
- 2** After installing SiteScope:
  - If you used the Configuration Tool to make a backup of your current SiteScope installation directory, use the Configuration Tool to import the previously created zip file. For details, see "Using the SiteScope Configuration Tool" on page 133.
  - If you manually created a back up, delete all the folders and files listed above from the new installation directory, and then copy the backed up folders and files to the installation directory.





# **Part VI**

---

## **Appendixes**



# A

---

## Integrating IIS with SiteScope's Tomcat Server

To integrate Internet Information Server (IIS) with the Apache Tomcat server included with SiteScope, you need to make changes to the configuration files used by the Apache Tomcat server and create the virtual directory in the corresponding Web site object in the IIS configuration.

### **This chapter includes:**

- Configuring the Apache Tomcat Server Files on page 227
- Configuring IIS on page 231

### **Configuring the Apache Tomcat Server Files**

To enable IIS integration with the Apache Tomcat server, you must edit the configuration files for the Apache Tomcat server included with SiteScope.

#### **To configure the Apache Tomcat server files:**

- 1** Download the latest version of Java Connector jk from the Apache download site for connector files (<http://tomcat.apache.org/download-connectors.cgi>).
- 2** Copy the `isapi_redirect.dll` file to the `<Tomcat installation>\bin\win32` directory. By default, a Tomcat server is installed as part of the SiteScope installation at `C:\SiteScope\Tomcat`. Create the `win32` directory if it does not exist.

**3** Perform one of the following:

- ▶ Create a configuration file in the same directory as the **isapi\_redirect.dll** file, and name it **isapi\_redirect.properties**. This is an example of the file:

```
# Configuration file for the Jakarta ISAPI Redirector

# The path to the ISAPI Redirector Extension, relative to the website
# This must be in a virtual directory with execute privileges
extension_uri=/jakarta/isapi_redirect.dll

# Full path to the log file for the ISAPI Redirector
log_file=C:\SiteScope\Tomcat\logs\isapi.log

# Log level (debug, info, warn, error or trace)
log_level=info

# Full path to the workers.properties file
worker_file=C:\SiteScope\Tomcat\conf\workers.properties.minimal

# Full path to the uriworkermap.properties file
worker_mount_file=C:\SiteScope\Tomcat\conf\uriworkermap.properties
```

This configuration points to the log file, which is recommended to put under the **<SiteScope root directory>\Tomcat\logs** directory, and the worker and worker mount files, which should be stored under the **<SiteScope root directory>\Tomcat\conf** directory.

- ▶ Add the same configuration entries (see above) to the registry at path: **HKEY\_LOCAL\_MACHINE\SOFTWARE\Apache Software Foundation\Jakarta Isapi Redirector\1.0**

- 4 Create the SiteScope workers file, named **workers.properties.minimal**, under the **<SiteScope root directory>\Tomcat\conf** directory. This is an example of the SiteScope workers file:

```
# workers.properties.minimal -
#
# This file provides minimal jk configuration
# properties needed to
# connect to Tomcat.
#
# Defining a worker named ajp13w and of type ajp13
# Note that the name and the type do not have to
# match.
worker.list=ajp13w
worker.ajp13w.type=ajp13
worker.ajp13w.host=localhost
worker.ajp13w.port=8009
#END
```

---

**Note:** If IIS and Tomcat are not on the same machine, change the host attribute in **workers.properties.minimal** to point to the other machine.

---

- 5 Create the SiteScope workers mount file under the **<SiteScope root directory>\Tomcat\conf** directory. This is the example of SiteScope's worker mount file, named **uriworkermap.properties**, as in the configuration example above:

```
# uriworkermap.properties - IIS
#
# This file provides sample mappings for example:
# ajp13w worker defined in workermap.properties.minimal
# The general syntax for this file is:
# [URL]=[Worker name]
/SiteScope=ajp13w
/SiteScope/*=ajp13w
#END
```

The new syntax combines the two rules for SiteScope into one rule:  
`/SiteScope/*=ajp13w`

---

**Note:** Tomcat log output is written to the `<SiteScope root dir>\logs\tomcat.log` file. Settings for the log file can be configured from the `<SiteScope root dir>\Tomcat\common\classes\log4j.properties` file.


---

## Configuring IIS

After you make changes to the configuration files used by the Tomcat server, you need to create the virtual directory in the corresponding Web site object in the IIS configuration.


To configure IIS:

- 1 From the Windows Start menu, click **Settings > Control Panel > Administrative Tools > Internet Information Services (IIS) Manager**.
- 2 In the right pane, right-click <Local Computer name>\Web Sites\<Your Web Site name>, and click **New\Virtual Directory**. Rename it **Jakarta**, and set **local path** to the directory with **isapi\_redirect.dll**.



- 3 Right click <Your Web Site name> and click **Properties**.

- 4 Click the **ISAPI Filters** tab, and then click **Add**. In the **Filter Name** column, select **Jakarta**, and browse to **isapi\_redirect.dll**. The filter is added, but at this stage it is still inactive.




Click **Apply**.

- 5 Right-click <Local Machine name>\Web Service extensions and click **Add new Web Service Extension**. The New Web Service Extension dialog box opens.



- 6 In the **Extension name** box, enter the name Jakarta, and under **Required files** browse to the **isapi\_redirect.dll** file. Select **Set Extension Status to Allowed**.



Click **OK**.

- 7 Restart the IIS Web Server, and try to access the application through the Web Service.



# B

---

## Integrating SiteScope with SiteMinder


SiteScope can be integrated with SiteMinder, a security access management solution, to leverage customer's user and access management configurations.

**This chapter includes:**

- ▶ Understanding Integration with SiteMinder on page 236
- ▶ Integration Requirements on page 237
- ▶ The Integration Process on page 237
- ▶ Configuring the SiteMinder Policy Server on page 238
- ▶ Configuring SiteScope for Using SiteMinder on page 240
- ▶ Configuring IIS on page 240
- ▶ Defining Permissions for the Different SiteScope Roles on page 241
- ▶ Logging On to SiteScope on page 241
- ▶ Notes and Guidelines on page 242

## Understanding Integration with SiteMinder

The following diagram illustrates how SiteScope integrates with SiteMinder to authenticate and authorize SiteScope users.



In this architecture, a SiteMinder agent is configured on the IIS Web server which is placed in front of SiteScope's Tomcat application server. The SiteMinder agent must reside on a Web server. The IIS Web server is connected to the SiteMinder policy server that manages all SiteScope users (over a LDAP or any other similar repository).

The SiteMinder agent intercepts all SiteScope's related traffic, and checks the user's credentials. The user's credentials are sent to the SiteMinder policy server for authentication and authorization. If SiteMinder authenticates the user, it sends SiteScope a token (via a special HTTP header) that describes the exact user that managed to log in and pass SiteMinder's authorization.

---

**Note:** It is recommended that the SiteScope client, IIS Web server, and the SiteScope's Tomcat application server are configured on the same machine.

---

## Integration Requirements

This section displays the system requirements for integrating SiteScope with SiteMinder.

<b>Operating System</b>	Windows 2000, Windows 2003 Standard/Enterprise SP1
<b>Web Server</b>	IIS 5.0, IIS 6.0
<b>Application Server</b>	Tomcat 5.0.x
<b>Java Connector</b>	Java Connector jk-1.2.21 or later

## The Integration Process

This section describes the SiteMinder integration process.

### To integrate SiteScope with SiteMinder:

#### 1 Prepare and configure the SiteMinder Policy Server.

Your SiteMinder administrator needs to prepare the SiteMinder policy server for installing the Web agent, install the Web agent on the IIS Web server, and configure the Web agent.

In addition, your SiteMinder administrator needs to configure the SiteMinder policy server. For the recommended SiteMinder configuration details, see "Configuring the SiteMinder Policy Server" on page 238.

#### 2 Configure SiteScope for using SiteMinder.

To enable SiteScope to integrate with SiteMinder, you need to make changes to the configuration files used by the Tomcat server. For details, see "Configuring the Apache Tomcat Server Files" on page 227.

#### 3 Configure IIS.

You need to create the virtual directory in the corresponding Web site object in the IIS configuration. For details, see "Configuring IIS" on page 231.

#### 4 Define permissions for the different SiteScope roles.

After you enable the SiteMinder integration, you must define the permissions for the different roles in SiteScope. For details, see "Defining Permissions for the Different SiteScope Roles" on page 241.

## Configuring the SiteMinder Policy Server

You configure the SiteMinder policy server by creating a SiteScope realm object, two SiteScope rules objects for authentication and forwarding the cookie with additional attributes, a SiteScope response object that transfers the additional LDAP attributes to SiteScope, and by adding SiteScope rules and responses to the Security policy object.

Before creating a SiteScope realm object on the policy server, make sure that:

- ▶ A special administrator above a domain (that in turn is bound to one or more User Directories) has been configured.
- ▶ One or more User Directories objects have been configured. These objects represent the users in the LDAP directory, or any other repository.
- ▶ You have defined an authentication scheme.

A domain is connected to one or more of User Directory objects. There is no need to create a special domain for the realm. You can use an existing domain.

#### To configure the SiteMinder policy server:

- 1 Log on to SiteMinder Administration.
- 2 Create a realm and enter the following information:
  - ▶ **Name.** Enter a name for the realm. For example, **SiteScope realm**.
  - ▶ **Resource Filter.** Enter **/SiteScope**. Everything under SiteScope is part of our realm.

- 3 Right-click the new realm and click **Create rule under realm**.
  - Create a rule for authentication purposes. Enter a meaningful name for the rule, such as **SiteScope rule**. In the **Action** section, select the **Web Agent Action** option and choose all HTTP request schemes (**Get**, **Post** and **Put**).
  - Create a second rule for forwarding cookies and other attributes to SiteScope. Enter a meaningful name for the rule, such as **Users role**. In the **Action** section, select the **Authentication events** option and select **OnAuthAccept** from the drop-down list.
- 4 Create a SiteScope response object to transfer the additional LDAP attributes to SiteScope with the relevant authentication information.
  - a Right-click **Responses** to open the Response Properties window.
  - b Enter a meaningful name for the Response. For example, **SiteScope Role**.
  - c Under the **Attribute List** section, click the **Create** button to open a new window to configure an attribute list.
  - d In the **Attribute Kind** section, select the **User Attribute** option.
  - e In the **Attribute Fields** section, choose **SITESCOPE\_ROLE** as a variable name, and choose the attribute name to be the chosen field from the predefined User Directory to be sent in the header to SiteScope. This is the User Directory attribute to be sent upon authentication.

---

**Note:** If you are using LDAP group objects or a nested group object to define the SiteScope role, special SiteMinder variables should be used for the **Attribute Name** field. You should use the **SM\_USERGROUPS** variable for regular groups and **SM\_USERNESTEDGROUPS** if you want the **SITESCOPE\_ROLE** HTTP header to contain the nested groups' information.

---

- 5 Add SiteScope rules and responses to the Security policy object.
  - a Click the **Policies** option to create a new security policy.
  - b Enter a meaningful name for the policy. For example, **SiteScope Policy**.
  - c Click the **Users** tab and add or remove the entities to which the policy applies. (You can choose entities only from the User Directories that are part of the same domain of the realm.)
  - d Click the **Rules** tab and choose the two rules described in step 3, **Users Role** and **SiteScope Rule**. In addition, add the **SiteScope Role** response that was defined earlier to be the response of the Users Role in step 4.

## Configuring SiteScope for Using SiteMinder

To enable SiteScope to integrate with SiteMinder, you need to make changes to the configuration files used by the Tomcat server. For information on configuring the Tomcat server files, see "Configuring the Apache Tomcat Server Files" on page 227.

## Configuring IIS

After you make changes to the configuration files used by the Tomcat server, you need to configure IIS. For information on configuring IIS, see "Configuring IIS" on page 231.



## Defining Permissions for the Different SiteScope Roles

After you enable the SiteMinder integration, you must define the permissions for the different roles in SiteScope (using the SiteScope regular users permissions model). The association of the users to these roles is done outside of SiteScope, such as in LDAP groups. When a new SiteScope user is added, it only has to be defined in SiteMinder, since the user automatically inherits the permissions from the relevant SiteScope role.

---

**Note:** You must ensure that the SiteScope user account used by SiteMinder does not require a password, otherwise SiteMinder is unable to log in. For details on creating user accounts, see "User Management Preferences" in SiteScope Help.

---

## Logging On to SiteScope

When a user attempts to log on to SiteScope, SiteMinder intercepts the request. If it authenticates the user's credentials, it sends an assigned SiteScope user name and role (group) to SiteScope (for example, User: Fred, Role: Accounting). If SiteScope fails to recognize the name as a valid user name, but it recognizes the role, the user is logged on to SiteScope using the role (in this instance, User: Accounting).

### To logon to SiteScope:

Open your Web browser and type the following URL:  
`http://<IIS_machine_name>/SiteScope.`

---

**Note:** If IIS and SiteScope reside on the same machine, you should connect to the default port 80, and not port 8080.

---

After SiteMinder successfully authenticates the user and logs on to SiteScope, SiteScope opens directly to the Dashboard view.

## Notes and Guidelines

- ▶ The names of all users logged in to SiteScope are listed in the audit log, which is located in the <SiteScope root directory>\logs directory. This is the case even when a user is logged in under a role name. For example, if user Fred is logged on under a role because SiteScope did not recognize Fred as a valid user but recognized the role, all operations are still listed with user name Fred in the audit log.
- ▶ You can specify a page where the browser is redirected after logging out the SiteMinder environment (this is the page that opens after you click the **LOGOUT** button in SiteScope). To activate the logout page, open the **master.config** file located in <SiteScope root directory>\groups, and add the following line:  

```
_siteMinderRedirectPageLogout=<url_to_go_to_after_logout>
```
- ▶ The user account that SiteMinder uses to log in to SiteScope must not require a password, otherwise SiteMinder is unable to log in. For details on setting up a user account in SiteScope, see "User Management Preferences" in SiteScope Help.
- ▶ To prevent users trying to access SiteScope directly using the SiteScope URL, you should consider disabling HTTP port 8080 and 8888 on the Tomcat server during SiteScope installation.

---

# Index

## A

- accessing SiteScope 216
- account permissions, security 25
- accounts
  - running SiteScope as root 25
- administrator, login account 210
- agentless monitoring, SiteScope 27
- application monitoring, estimating license point usage 55
- application performance monitoring, SiteScope installation 28

## C

- Configuration Tool, Solaris, Linux 140
- Configuration Tool, Windows 133
- configuring SiteScope 133
- connecting to SiteScope, default interface 215

## D

- deployment
  - infrastructure assessment 21
  - network considerations 23
  - planning outline 19
  - SiteScope server sizing 22

## E

- email, configuring SiteScope to use 210
- Encryption, Password Encryption 170
- End of Life Monitor Viewer 78
- evaluation period 57

## F

- firewalls, SiteScope monitoring through 32

## H

- HP Software Support Web site 11
- HP Software Web site 11

## I

### IIS

- configuring 231
- integrating with SiteScope 227
- installation
  - account permissions on Solaris or Linux platforms 115, 125
  - administration tasks after 209
  - deployment planning 19
  - do not run SiteScope as root 91
  - infrastructure assessment 21
  - network factors 23
  - on Windows, Solaris or Linux 89
  - overview of steps 62
  - performing a full 92
  - preparing for on Solaris or Linux 91
  - server sizing 22
  - user account on Windows 24
- installing SiteScope
  - using console mode 116
- installing SiteScope in silent mode 129

## K

- Knowledge Base 11

## Index

### L

- license
  - free evaluation 57
  - requesting for SiteScope 58
  - SiteScope monitors 33
- license points
  - estimating for application monitoring 55
  - estimating for Web monitoring 55
  - estimating the number of 54
- license types 34
  - understanding for SiteScope 34
- licensing
  - for solution templates 52
- Linux
  - preparation for SiteScope installation 91
  - requirements for SiteScope on 66
  - stopping SiteScope process 215
- log files
  - setting how much data is stored 210

### M

- monitoring
  - AIX platforms 30
  - HP/UX platforms 30
  - license types 34
  - methodology for enterprise systems 19
  - platforms supported in SiteScope 30
  - SCO platforms 31
  - through firewalls 32
  - understanding license types 34
  - using NT performance counters 29
  - using secure shell in SiteScope 31
- monitors
  - license point usage by type 42

### N

- network monitoring, SiteScope installation 28

### O

- online resources 11

### P

- permissions and credentials
  - Apache Server 173
  - ASP Server 182, 183
  - BroadVision 173
  - CheckPoint Firewall-1 174
  - CiscoWorks 175
  - Citrix Server 175
  - ColdFusion 175
  - COM+ 176
  - CPU (Solaris, Linux) 177
  - CPU (Windows) 176
  - Database 177
  - Directory 177
  - Directory (Solaris, Linux) 177
  - Directory (Windows) 177
  - Disk space (Solaris, Linux) 178
  - Disk space (Windows) 177
  - F5 Big-IP 179
  - File (Solaris, Linux) 180
  - File (Windows) 180
  - FTP 180
  - IIS 183
  - LDAP 180
  - Link check 180
  - Log file (Solaris, Linux) 181
  - Log file (Windows) 180
  - Mail 181
  - MAPI 181
  - Memory (Solaris, Linux) 181
  - Memory (Windows) 181
  - Network bandwidth 185
  - NEWS 186
  - NT Dialup 184
  - NT Event log 184
  - NT Perf counter 184
  - Oracle 9iAS 186
  - Oracle JDBC 186
  - Ping 186
  - Port 186
  - Radius 186

- Real Media Player 186
  - Real Media Server 186
  - SAP CCMS 186
  - SAP GUI 187
  - Script (Solaris, Linux) 187
  - Script (Windows) 187
  - Script on local machine (Solaris, Linux, Windows) 187
  - Service (Solaris, Linux) 187
  - Service (Windows) 187
  - Siebel Log 188
  - Siebel Server Manager 188
  - Siebel Web Server 188
  - SNMP 189
  - SNMP by MIB 190
  - SNMP trap 191
  - SOAP over HTTP 192
  - SQL Server 183
  - SunOne 191
  - Tuxedo 191
  - URL 191
  - URL content 191
  - URL list 191
  - URL sequence 192
  - Web Server 192
  - Web Server (Solaris, Linux, Windows) 192
  - Web service 192
  - WebLogic 5.x 192
  - WebLogic 6.x and above 192
  - WebSphere 3.5x 192
  - WebSphere 4.5 192
  - WebSphere 5.x 192
  - WebSphere MQ 193
  - WebSphere Performance Servlet 193
  - Windows Media Player 184
  - Windows Media Server 184
  - Windows Resource 184
  - ports
    - used for monitoring 32
- S**
- security
    - default login account 210
    - hardening SiteScope 169
    - SiteScope account permissions 91
    - using SSL 195
  - server health monitoring, SiteScope
    - installation 28
  - server monitoring, preferred shell on UNIX
    - remotes 25
  - silent installation 129
  - SiteScope
    - accessing administrator account 210
    - agentless monitoring, understanding 27
    - before upgrading 77
    - certified server configuration for installation 70
    - computing threads for UNIX 154
    - configuring for SSL 200
    - configuring to connect to BSM server
      - requiring client certificate 202
    - considerations in UNIX
      - environments 25
    - considerations in Windows NT or 2000 environment 24
    - hardening 169
    - installation, before you begin 61, 75
    - integrating IIS with 227
    - method for enterprise monitoring 19
    - monitoring other servers 30
    - ports used 32
    - post-install administration tasks 209
    - server health monitoring 28
    - sizing on Solaris and Linux platforms 154
    - sizing on Windows 150
    - system requirements 64
    - uninstall 161
    - using SSL 195
  - SiteScope Configuration tool 133
  - SiteScope Configuration Tool, Solaris, Linux 140
  - SiteScope Configuration Tool, Windows 133
  - SiteScope service
    - running 213
    - stopping 213
  - SiteSeer
    - integrating SiteScope with 235

## Index

### sizing

- heap space on UNIX 156
- SiteScope on Solaris and Linux platforms 154
- thread stack on UNIX 156

### Solaris

- preparation for SiteScope installation 91
- requirements for SiteScope on 65
- starting SiteScope process 215

### solution templates

- licensing for 52

### SSL

- configuring in SiteScope 195
- configuring SiteScope to use 200
- importing a CA certificate 198
- keytool utility 196
- to access SiteScope 170
- using a CA certificate 196
- using self-signed certificates 199

### system requirements

- for SiteScope on Linux 66
- for SiteScope on Solaris 65
- for SiteScope on Windows 65
- SiteScope certified server configuration 70
- SiteScope installation 64

## T

Troubleshooting and Knowledge Base 11

tuning SiteScope on Windows 152

## U

uninstall SiteScope 161

- on Solaris or Linux 166
- on Windows 161

### UNIX

- considerations for using SiteScope 25
- sizing for SiteScope 154
- sizing heap space 156
- sizing JVM 156
- sizing thread stack size 156

### UNIX/Linux

- general sizing recommendations 157
- preferred shell for SiteScope monitoring 25
- to uninstall SiteScope 166
- upgrading SiteScope 77

## V

VMware, supported environment 66

## W

### Web monitoring

- estimating license point usage 55
- SiteScope installation 28

### Windows

- general sizing recommendations 153
- requirements for SiteScope on 65
- using secure shell connections in SiteScope 31

### Windows 2000

- considerations for using SiteScope 24
- memory leak in SP2 24
- NT performance counter libraries 29

### Windows platform

- starting SiteScope service 214
- stopping SiteScope service 214