



# Unified Functional Testing Installation QuickStart Sheet

This sheet explains the steps to perform a basic installation of Unified Functional Testing (UFT). Complete details on all elements of the UFT installation can be found in the *HP Unified Functional Testing Installation Guide*.

## Before You Install

- ▶ **Upgrading:** If you are moving from a version of QuickTest 9.5 or later or Service Test 10.00 or later, the installation process will automatically uninstall your old version of QuickTest or Service Test and install UFT. If you have QuickTest 9.2, you must manually uninstall them and then install UFT.
- ▶ **Silent Installation:** UFT supports the MSI silent installation mechanism. For details, see the *HP Unified Functional Testing Installation Guide*.

## Installation Instructions

### 1 Prerequisites:

- ▶ Make sure you have administrator privileges on the drive to which you are installing UFT (must be a local drive). If you have problems installing, you may have to adjust other Windows settings. See the "Setting Required Access Permissions" section in the *HP Unified Functional Testing Installation Guide*.
- ▶ Make sure you have a supported version of Internet Explorer installed. For additional details on system requirements, see the *HP Unified Functional Testing Readme*.
- ▶ Know what type of license you are using. If you are using a concurrent license, have the license server URL available.
- ▶ Know if you want to install all UFT features or the Service Test run-time features only.

- ▶ Know which add-ins you want to install for GUI testing. It is recommend that you only install those you expect to use.

## 2 Start the installation.

When the startup screen opens, click **Unified Functional Testing Setup**. (If the startup screen does not automatically run, enter the following path in the command window: <DVD drive>/setup.exe.)

## 3 Follow the on-screen instructions.

### While You Install

#### Custom Installation Screen:

- ▶ If you are installing UFT, do not select the **HP Service Test Run Time** option. After installing the UFT feature, the UFT IDE, the UFT add-in for ALM, Service Test/API Testing design and runtime components, and the Run Results Viewer are all installed on your computer.
- ▶ If you want to install only the Service Test run time features without UFT (to run but not edit Service Test/API tests), select the **Entire feature will be unavailable** option for Unified Functional Testing.

#### Additional Installation Requirements Screen:

- ▶ Select only those requirements you need installed. All options can be installed later via the Start Menu. For details on the additional installation requirements, see the *HP Unified Functional Testing Installation Guide*.
- ▶ If your network requires special DCOM settings, clear the **Configure DCOM Settings** option. For details on manual configuration of the DCOM settings, see the *HP Unified Functional Testing Installation Guide*.