

# Unified Functional Testing Installation QuickStart Sheet

This sheet explains the steps to perform a basic installation of Unified Functional Testing (UFT). Complete details on all elements of the UFT installation can be found in the *HP Unified Functional Testing Installation Guide*.

## Before You Install

- **Upgrading:** If you are moving from a version of QuickTest 9.5 or later or Service Test 10.00 or later, the installation process will automatically uninstall your old version of QuickTest or Service Test and install UFT.
- **Silent Installation:** UFT supports the MSI silent installation mechanism. For details, see the *HP Unified Functional Testing Installation Guide*.

## Installation Instructions

### 1. Prerequisites

- Make sure you have administrator privileges on the drive to which you are installing UFT (must be a local drive). If you have problems installing, you may have to adjust other Windows settings. See the "Setting Required Access Permissions" section in the *HP Unified Functional Testing Installation Guide*.
- Make sure you have a supported version of Internet Explorer installed. For additional details on system requirements, see the *HP Unified Functional Testing Readme*.
- Know what type of license you are using. If you are using a concurrent license, have the license server URL available.
- Know if you want to install all UFT features or the Service Test run-time features only.
- Know which add-ins you want to use for GUI testing. It is recommended that you only install those you expect to use.

### 2. Start the Installation.

When the startup screen opens, select **Unified Functional Testing Setup**. (If the startup screen does not automatically run, enter the following path in the command window: <DVD drive>/setup.exe.)

### 3. Follow the on-screen instructions.

## While You Install

### Custom Installation Screen

- If you are installing UFT, do not select the **HP Service Test Run Time** option. After installing the UFT feature, the UFT IDE, the UFT add-in for ALM, Service Test/API Testing design and runtime components, and the Run Results Viewer are all installed on your computer.
- If you want to install only the Service Test run time features without UFT (to run but not edit Service Test/API tests), select the **Entire feature will be unavailable** option for Unified Functional Testing.

### Additional Installation Requirements Screen

- Select only those requirements you need installed. All options can be installed later via the **Start** menu. For details on the additional installation requirements, see the *HP Unified Functional Testing Installation Guide*.
- If your network requires special DCOM settings, clear the **Configure DCOM Settings** option. For details on manual configuration of the DCOM settings, see the *HP Unified Functional Testing Installation Guide*.