Unified Functional Testing Installation QuickStart Sheet

This sheet explains the steps to perform a basic installation of Unified Functional Testing (UFT). Complete details on all elements of the UFT installation can be found in the *HP Unified Functional Testing Installation Guide*.

The installation also automatically installs the Run Results Viewer on your machine.

Before You Install

- **Upgrading:** If you are moving from a version of QuickTest 9.5 or later or Service Test 10.00 or later, you must uninstall your old version of QuickTest or Service Test and install UFT.
- **Silent Installation:** UFT supports the MSI silent installation mechanism. For details, see the *HP Unified Functional Testing Installation Guide*.

Installation Instructions

1. Prerequisites

- Make sure you have administrator privileges on the drive to which you are installing UFT (must be a local drive). If you have problems installing, you may have to adjust other Windows settings.
 See the "Setting Required Access Permissions" section in the HP Unified Functional Testing Installation Guide.
- Make sure you have a supported version of Internet Explorer installed. For additional details on system requirements, see the *HP Unified Functional Testing Readme*.
- Know what type of license you are using. If you are using a concurrent license, have the license server URL available.
- Know which add-ins you want to use for GUI testing. It is recommended that you only install those you expect to use.
- If you plan to run tests created using Service Test or earlier versions of UFT, you must have the .NET Framework 3.5, WSE 2.0sp3 package, and WSE 3.0 package installed on your computer.
 - These prerequisites are not provided with the UFT installation. If they are not installed on your computer, you can install them from the following locations on the DVD:
 - NET 3.5 Framework:DVD/prerequisites/dotnet35 1/donetfx35 sp1.exe
 - WSE 2.0 sp3: DVD/prerequisites/wse20sp3/MicrosoftWSE2.0SP3Runtime.msi
 - WSE 3.0: DVD/prerequisites/wse30/MicrosoftWSE3.0Runtime.msi

2. Start the Installation.

3. Follow the on-screen instructions.

While You Install

Custom Setup Screen

- If you want to install the UFT Add-in for ALM as part of the installation, select the ALM Plugin option.
- If you are installing UFT on a non-English machine, choose whether to install UFT in the language of your operating system or in English.

UFT Configuration Screen

If your network requires special DCOM settings, clear the **Configure DCOM Settings for ALM Integration** and the **Configure DCOM Settings for Automation Scripts** options. For details on manual configuration of the DCOM settings, see the *HP Unified Functional Testing Installation Guide*.