



**Hewlett Packard
Enterprise**

Codar

Software version: 1.70

For Microsoft Windows® and Linux operating systems

Configuring Codar to work with Oracle RAC

Document release date: July 2016

Software release date: July 2016

Codar 1.70

Configuring Codar to work with Oracle RAC

Contents

Scope and purpose of this document	3
Oracle RAC	3
Codar database configuration for non-Oracle RAC	3
Codar database configuration for Oracle RAC.....	4
Upgrading a Codar database configuration for Oracle RAC	6
Send documentation feedback	8
Legal notices	8

Scope and purpose of this document

Enterprise applications such as HPE Cedar are usually deployed in high-availability database environments. This document describes Oracle Real Application Clusters (Oracle RAC) configuration for Cedar. This document does not cover how to install Cedar nor how to install and configure Oracle RAC.

Oracle RAC

Oracle RAC provides clustering and high availability for Oracle database environments. In an Oracle RAC environment, two or more database instances concurrently access a single database. A typical Oracle RAC environment includes the instances running on different physical machines with a Single Client Access Name (SCAN) that allows clients to access the database using a single hostname/IP address, instead of specifying the hostnames/IP addresses for each of the instances in the connection URL.

Cedar database configuration for non-Oracle RAC

The Cedar installer prompts users to enter database information (such as the server hostname/IP address, port, Oracle service name, username, and password). This information is stored in a configuration file and used by the Management Console to connect to the database.

In a **standalone environment**, the configuration file is located at:

- Windows: %CODAR_HOME%\jboss-as\standalone\configuration\standalone.xml
- Linux: \$CODAR_HOME/jboss-as/standalone/configuration/standalone.xml

All the database configuration information is specified in the <datasource> element. For example:

```
<!-- csa datasource setup -->
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="OracleDS">
  <connection-url>jdbc:oracle:thin:@//127.0.0.1:1521/XE</connection-url>
  <driver>oracleDriver</driver>
  <pool>
    <min-pool-size>10</min-pool-size>
    <max-pool-size>200</max-pool-size>
    <prefill>true</prefill>
    <use-strict-min>false</use-strict-min>
    <flush-strategy>FailingConnectionOnly</flush-strategy>
  </pool>
  <security>
    <security-domain>csa-encryption-sec</security-domain>
  </security>
</datasource>
```

Note: This example is for non-Oracle RAC environments.

In a **clustered environment**, the configuration file is located at:

- Windows: %CODAR_HOME%\jboss-as\standalone\configuration\standalone-full-ha.xml
- Linux: \$CODAR_HOME/jboss-as/standalone/configuration/standalone-full-ha.xml

All the database configuration information is specified in the <datasource> element. For example:

```
<!-- csa datasource setup -->
```

```

<datasource jta="true" jndi-name="java:jboss/datasources/csaDS" pool-name="OracleDS" enabled="true" use-java-context="true" use-ccm="true">
    <connection-url>jdbc:oracle:thin:@//127.0.0.1:1521/XE</connection-url>
    <driver>oracleDriver</driver>
    <pool>
        <min-pool-size>10</min-pool-size>
        <max-pool-size>200</max-pool-size>
        <prefill>true</prefill>
        <use-strict-min>false</use-strict-min>
        <flush-strategy>FailingConnectionOnly</flush-strategy>
    </pool>
    <security>
        <security-domain>csa-encryption-sec</security-domain>
    </security>
</datasource>

```

NOTE: This example is for non-Oracle RAC environments.

Codar database configuration for Oracle RAC

To configure Codar to work with Oracle RAC:

1. Install Codar. In the screen that asks for database information, enter the SCAN or hostname/IP address of one of the nodes when prompted for the database hostname in the Codar installer.

If this information is not correct, the installer is not able to connect to the database and installation cannot proceed until this issue is resolved.

2. After installing Codar, navigate to the configuration file located at:

Standalone Environment

- Windows: %CODAR_HOME%\jboss-as\standalone\configuration\standalone.xml
- Linux: \$CODAR_HOME/jboss-as/standalone/configuration/standalone.xml

Clustered Environment

- Windows: %CODAR_HOME%\jboss-as\standalone\configuration\standalone-full-ha.xml
- Linux: \$CODAR_HOME/jboss-as/standalone/configuration/standalone-full-ha.xml

3. Before modifying the standalone.xml or standalone-full-ha.xml file, back up the file by making a copy of it.
4. Find the section that configures the Codar datasource. An example is shown below:

Standalone Environment

```

<!-- csa datasource setup -->
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="OracleDS">
    <connection-url>jdbc:oracle:thin:@//127.0.0.1:1521/XE</connection-url>

```

Clustered Environment

```

<!-- csa datasource setup -->
<datasource jta="true" jndi-name="java:jboss/datasources/csaDS" pool-name="OracleDS" enabled="true" use-java-context="true" use-ccm="true">
    <connection-url>jdbc:oracle:thin:@//127.0.0.1:1521/XE</connection-url>

```

5. Replace the <connection-url> element with the following (the highlighted text must be replaced with appropriate values):

```

<connection-url>
    jdbc:oracle:thin:@(DESCRIPTION=(LOAD_BALANCE=on)(ADDRESS=(PROTOCOL=TCP)
    (HOST=<SCAN_hostname>)(PORT=<port>))(CONNECT_DATA=(SERVICE_NAME=<servicename>))

```

```
(FAILOVER_MODE=(TYPE=SELECT)(METHOD=BASIC)(RETRIES=10)(DELAY=5)))  
</connection-url>
```

6. Add the following <validation> element to the <datasource> element:

```
<validation>  
    <check-valid-connection-sql>select 1 from dual</check-valid-connection-sql>  
    <validate-on-match>false</validate-on-match>  
    <background-validation>true</background-validation>  
    <use-fast-fail>false</use-fast-fail>  
    <exception-sorter class-name=  
        "org.jboss.jca.adapters.jdbc.extensions.oracle.OracleExceptionSorter"/>  
</validation>
```

When you are done with these changes, the datasource configuration will look like the following:

NOTE: Elements highlighted below are the elements that you have changed and the bold text should be replaced with appropriate values.

Standalone Environment

```
<!-- csa datasource setup -->  
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="OracleDS">  
    <connection-url>  
        jdbc:oracle:thin:@(DESCRIPTION=(LOAD_BALANCE=on)(ADDRESS=(PROTOCOL=TCP)  
        (HOST=<SCAN_hostname>)(PORT=<port>))(CONNECT_DATA=(SERVICE_NAME=<servicename>))  
        (FAILOVER_MODE=(TYPE=SELECT)(METHOD=BASIC)(RETRIES=10)(DELAY=5)))    </connection-url>  
    <driver>oracleDriver</driver>  
    <pool>  
        <min-pool-size>10</min-pool-size>  
        <max-pool-size>200</max-pool-size>  
        <prefill>true</prefill>  
        <use-strict-min>false</use-strict-min>  
        <flush-strategy>FailingConnectionOnly</flush-strategy>  
    </pool>  
    <security>  
        <security-domain>csa-encryption-sec</security-domain>  
    </security>  
    <validation>  
        <check-valid-connection-sql>select 1 from dual</check-valid-connection-sql>  
        <validate-on-match>false</validate-on-match>  
        <background-validation>true</background-validation>  
        <use-fast-fail>false</use-fast-fail>  
        <exception-sorter class-name=  
            "org.jboss.jca.adapters.jdbc.extensions.oracle.OracleExceptionSorter"/>  
    </validation>  
</datasource>
```

Clustered Environment

```
<!-- csa datasource setup -->
<datasource jndi-name="java:jboss/datasources/csaDS" pool-name="OracleDS" enabled="true" jta="true" use-java-context="true" use-ccm="true">
    <connection-url>
        jdbc:oracle:thin:@(DESCRIPTION=(LOAD_BALANCE=on)(ADDRESS=(PROTOCOL=TCP)
        (HOST=<SCAN_hostname>)(PORT=<port>))(CONNECT_DATA=(SERVICE_NAME=<servicename>)
        (FAILOVER_MODE=(TYPE=SELECT)(METHOD=BASIC)(RETRIES=10)(DELAY=5)))</connection-url>
    <driver>oracleDriver</driver>
    <pool>
        <min-pool-size>10</min-pool-size>
        <max-pool-size>200</max-pool-size>
        <prefill>true</prefill>
        <use-strict-min>false</use-strict-min>
        <flush-strategy>FailingConnectionOnly</flush-strategy>
    </pool>
    <security>
        <security-domain>csa-encryption-sec</security-domain>
    </security>
    <validation>
        <check-valid-connection-sql>select 1 from dual</check-valid-connection-sql>
        <validate-on-match>false</validate-on-match>
        <background-validation>true</background-validation>
        <use-fast-fail>false</use-fast-fail>
        <exception-sorter class-name=
            "org.jboss.jca.adapters.jdbc.extensions.oracle.OracleExceptionSorter"/>
    </validation>
</datasource>
```

7. Restart Codar.

Codar is now connected to the Oracle RAC instance and supports failover. If one of the database instances goes down, Codar continues to function normally by connecting to another database instance that is up and running.

Upgrading a Codar database configuration for Oracle RAC

After upgrading Codar from version 1.00 to version 1.50, you must manually reconfigure Codar to work with Oracle RAC by completing the tasks described in the [Codar database configuration for Oracle RAC](#) section.

In a standalone environment:

The changes you need to make to the `standalone.xml` file in Codar version 1.50 are the same changes you made in the `standalone.xml` file for Codar version 1.00. The 1.00 version of the `standalone.xml` file was backed up during the upgrade and you may copy the changes from this file (copy only the changes; do not copy the entire file).

The `standalone.xml` file from Codar version 1.00 is backed up to the following location:

- Windows: `%CODAR_HOME%_CSA_4_50_0_installation\Backup\standalone\standalone.xml`
- Linux: `$CODAR_HOME/_CSA_4_50_0_installation/Backup/standalone/standalone.xml`

In a clustered environment:

The changes you need to make to the `standalone-full-ha.xml` file in Codar version 1.00 are the same changes you made in the `standalone-full-ha.xml` file for Codar version 1.00. The 1.00 version of the `standalone-full-ha.xml` file was backed up during the upgrade and you may copy the changes from this file (copy only the changes; do not copy the entire file).

The `standalone-full-ha.xml` file from Codar version 1.00 is backed up to the following location:

- Windows: `%CODAR_HOME%_CSA_4_50_0_installation\Backup\standalone\standalone-full-ha.xml`
- Linux: `$CODAR_HOME/_CSA_4_50_0_installation/Backup/standalone/standalone-full-ha.xml`

Send documentation feedback

If you have comments about this document, you can send them to clouddocs@hpe.com.

Legal notices

Warranty

The only warranties for Hewlett Packard Enterprise products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Hewlett Packard Enterprise shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Restricted rights legend

Confidential computer software. Valid license from Hewlett Packard Enterprise required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Copyright notice

© Copyright 2016 Hewlett Packard Enterprise Development LP

Trademark notices

Adobe® is a trademark of Adobe Systems Incorporated.

Microsoft® and Windows® are U.S. registered trademarks of Microsoft Corporation.

Oracle and Java are registered trademarks of Oracle and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

RED HAT READY™ Logo and RED HAT CERTIFIED PARTNER™ Logo are trademarks of Red Hat, Inc.

The OpenStack word mark and the Square O Design, together or apart, are trademarks or registered trademarks of OpenStack Foundation in the United States and other countries, and are used with the OpenStack Foundation's permission.

Documentation updates

The title page of this document contains the following identifying information:

- Software Version number, which indicates the software version.
- Document Release Date, which changes each time the document is updated.
- Software Release Date, which indicates the release date of this version of the software.

To check for recent updates or to verify that you are using the most recent edition of a document, go to the following URL and sign-in or register:
<https://softwaresupport.hpe.com>.

Select Manuals from the Dashboard menu to view all available documentation. Use the search and filter functions to find documentation, whitepapers, and other information sources.

You will also receive updated or new editions if you subscribe to the appropriate product support service. Contact your Hewlett Packard Enterprise sales representative for details.

Support

Visit the Hewlett Packard Enterprise Software Support Online web site at <https://softwaresupport.hpe.com>.