

# HP Test Data Management

Software version: 1.10

---

## Web Console and Query Server User Guide

Document release date: October 2010  
Software release date: October 2010



## Legal notices

### Warranty

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

### Restricted rights legend

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

### Licensing

The use of HP products is governed by the terms and conditions of the applicable End User License Agreement (EULA).

### Copyright notices

© Copyright 2010 Hewlett-Packard Development Company, L.P.

### Trademark notices

Microsoft®, Windows®, Windows NT®, Windows XP®, and Windows Vista® are U.S. registered trademarks of Microsoft Corporation.

Java™ is a U.S. trademark of Sun Microsystems, Inc.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates.

UNIX® is a registered trademark of The Open Group.

# Contents

|                                            |    |
|--------------------------------------------|----|
| About this document                        | 7  |
| Intended audience                          | 7  |
| Prerequisites                              | 7  |
| New and revised information                | 7  |
| Related documentation                      | 8  |
| Document conventions and symbols           | 8  |
| Documentation updates                      | 9  |
| Subscription service                       | 10 |
| Support                                    | 10 |
| Part I: Introduction                       | 11 |
| 1 Introduction to test data management     | 13 |
| Before you begin                           | 14 |
| Web Console overview                       | 14 |
| Part II: Tutorials                         | 15 |
| 2 Configuring the Web Console              | 17 |
| Starting the Web Console                   | 17 |
| Installing the repository                  | 18 |
| Creating an environment                    | 23 |
| Creating Web Console users (optional)      | 28 |
| Part III: Task reference                   | 33 |
| 3 Starting and configuring the Web Console | 35 |
| Starting and stopping the Web Console      | 35 |
| Installing a new repository                | 38 |
| Adding Web Console nodes                   | 42 |
| 4 Managing environments                    | 45 |
| Creating an environment                    | 45 |
| Setting the active environment             | 49 |
| Deleting an environment                    | 50 |
| Renaming an environment                    | 50 |
| Setting up a non-intrusive environment     | 51 |
| Deploying business flows                   | 56 |
| Configuring parameters                     | 61 |

|                                                                           |            |
|---------------------------------------------------------------------------|------------|
| Managing locations . . . . .                                              | 62         |
| Refreshing test environments . . . . .                                    | 66         |
| <b>5 Managing users . . . . .</b>                                         | <b>71</b>  |
| Understanding privileges . . . . .                                        | 71         |
| Adding Web Console users . . . . .                                        | 72         |
| Editing Web Console users . . . . .                                       | 73         |
| Enabling environment access . . . . .                                     | 73         |
| Managing your user account . . . . .                                      | 74         |
| Setting up email access from the Web Console . . . . .                    | 75         |
| <b>6 Running business flows and jobs from the Web Console . . . . .</b>   | <b>77</b>  |
| Before you begin . . . . .                                                | 77         |
| Running business flows . . . . .                                          | 77         |
| Scheduling jobs . . . . .                                                 | 79         |
| Recovering or cancelling business flows and jobs . . . . .                | 80         |
| Accessing the extracted data . . . . .                                    | 82         |
| <b>7 Running business flows and jobs from the command line . . . . .</b>  | <b>85</b>  |
| Before you begin . . . . .                                                | 85         |
| Running business flows . . . . .                                          | 86         |
| Recovering and cancelling business flows and jobs . . . . .               | 87         |
| Accessing the copied data . . . . .                                       | 89         |
| <b>8 Monitoring jobs . . . . .</b>                                        | <b>91</b>  |
| Monitoring current and past jobs . . . . .                                | 91         |
| Using log files . . . . .                                                 | 95         |
| <b>9 Managing the repository and encryption keys . . . . .</b>            | <b>99</b>  |
| Locking and unlocking the repository . . . . .                            | 99         |
| Changing encryption keys and the repository password . . . . .            | 102        |
| <b>10 Using the query server to access extracted data files . . . . .</b> | <b>105</b> |
| Installing the query server . . . . .                                     | 105        |
| Starting the query server . . . . .                                       | 106        |
| Installing and configuring the ODBC or OLE DB driver . . . . .            | 108        |
| Connecting to a data source . . . . .                                     | 113        |
| Creating file collections . . . . .                                       | 118        |
| Viewing your collection . . . . .                                         | 122        |
| Uninstalling the query server . . . . .                                   | 149        |
| <b>11 Query server administrative tasks . . . . .</b>                     | <b>151</b> |
| Using multiple data sources . . . . .                                     | 151        |
| Managing users, roles, and privileges . . . . .                           | 155        |
| Managing indexes . . . . .                                                | 157        |

|                                                                        |            |
|------------------------------------------------------------------------|------------|
| Managing server options . . . . .                                      | 159        |
| Viewing query server log files . . . . .                               | 163        |
| Exposing an ADO.NET driver . . . . .                                   | 164        |
| <b>A Configuration and runtime parameters . . . . .</b>                | <b>165</b> |
| Database to file configuration parameters . . . . .                    | 165        |
| File naming parameters . . . . .                                       | 169        |
| <b>B Advanced tasks . . . . .</b>                                      | <b>171</b> |
| SQL tuning . . . . .                                                   | 171        |
| Using views for customized reporting . . . . .                         | 181        |
| Enabling SQL trace for Oracle . . . . .                                | 181        |
| Enabling the Web Console scheduler through a Web service . . . . .     | 182        |
| <b>C Scripted product setup and business flow deployment . . . . .</b> | <b>183</b> |
| Understanding properties files . . . . .                               | 183        |
| Scripting the repository setup . . . . .                               | 184        |
| Scripting the environment creation . . . . .                           | 187        |
| Scripting business flow deployment . . . . .                           | 190        |
| <b>Glossary . . . . .</b>                                              | <b>193</b> |
| <b>Index . . . . .</b>                                                 | <b>199</b> |



# About this document

HP Test Data Management provides powerful tools to build an extraction solution that copies or moves data out of your production database and into less expensive storage.

This guide provides information about:

- configuring the Web Console
- deploying business flows
- running business flows and jobs
- monitoring business flows and jobs

## Intended audience

This guide is intended for:

- users configuring the Web Console
- users running business flows and jobs

## Prerequisites

Prerequisites for installing this product include:

- Knowledge of the operating system
- Database knowledge
- Application knowledge

## New and revised information

This document includes the following new and revised features in the HP Test Data Management software:

- The default port number for Web Console is 8090.
- Email server settings are configurable from the Web Console.
- Non-intrusive environments.

- The script `create_datatype_map` is available for checking and creating data type mapping files when uploading to non-native databases.
- Runtime parameters have been moved to configuration parameters under PDM.

## Related documentation

In addition to this guide, refer to other documents for this product:

- *HP Test Data Management Installation Guide*  
Explains how to use the Installer to install the product.
- *HP Test Data Management Concepts Guide*  
Explains the major concepts of Test Data Management.
- *HP Test Data Management Tutorial*  
Provides step-by-step instructions to build a sample test data module, deploy it, run it, and troubleshoot errors.
- *HP Test Data Management Designer User Guide*  
Explains how to use the Designer component to design, build, test, and deploy your test data projects.
- *HP Test Data Management Troubleshooting Guide*  
Explains how to diagnose and resolve errors, and provides a list of common errors and solutions.
- *HP Test Data Management Release notes*  
Lists any items of importance that were not captured in the regular documentation.

The latest documentation for the most recent HP Test Data Management release can be found on:

<http://support.openview.hp.com/selfsolve/manuals>

## Document conventions and symbols

| Convention | Element                                                              |
|------------|----------------------------------------------------------------------|
| [ ]        | Indicates that the enclosed element is optional and may be left out. |
| { }        | Indicates that you must specify one of the listed options.           |
|            | Separates alternatives.                                              |

| Convention                                                                            | Element                                                                                                                                                                                     |
|---------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <parameter_name>                                                                      | You must supply a value for a variable parameter.                                                                                                                                           |
| Medium blue text: <a href="#">Figure 1</a>                                            | Cross-reference links and e-mail addresses                                                                                                                                                  |
| Medium blue, underlined text<br>( <a href="http://www.hp.com">http://www.hp.com</a> ) | Web site addresses                                                                                                                                                                          |
| <i>Italics</i>                                                                        | Text emphasis                                                                                                                                                                               |
| <b>Bold</b>                                                                           | GUI elements that are clicked or selected, such as menu and list items, buttons, and check boxes                                                                                            |
| Monospace                                                                             | <ul style="list-style-type: none"> <li>• File and directory names</li> <li>• Text displayed on the screen, such as system output and application messages</li> <li>• Code syntax</li> </ul> |

△ **CAUTION** Indicates that failure to follow directions could result in damage to equipment or loss of data.

**NOTE** Provides additional information.

**TIP** Provides helpful hints and shortcuts.

**RECOMMENDATION** Provides guidance from HP for a best practice or for optimum performance.

## Documentation updates

For documentation for all versions of HP Test Data Management, you can go to:

<http://support.openview.hp.com/selfsolve/manuals>

**NOTE** This documentation is written to the latest patch version. If you have not installed the latest patch, there may be items in this documentation that do not apply to your environment.

## Subscription service

HP strongly recommends that customers sign up online using the Subscriber's choice web site:

<http://www.hp.com/go/e-updates>

- Subscribing to this service provides you with e-mail updates on the latest product enhancements, versions of drivers, and firmware documentation updates as well as instant access to numerous other product resources.
- After signing up, you can quickly locate your products under Product Category.

## Support

You can visit the HP Software Support web site at:

<http://www.hp.com/go/hpsoftwaresupport>

HP Software Support Online provides an efficient way to access interactive technical support tools. As a valued support customer, you can benefit by using the support site to:

- Search for knowledge documents of interest
- Submit and track support cases and enhancement requests
- Download software patches
- Manage support contracts
- Look up HP support contacts
- Review information about available services
- Enter into discussions with other software customers
- Research and register for software training

Most of the support areas require that you register as an HP Passport user and sign in. Many also require a support contract.

To find more information about access levels, go to:

[http://support.openview.hp.com/new\\_access\\_levels.jsp](http://support.openview.hp.com/new_access_levels.jsp)

---

# Part I: Introduction

This part provides an introduction to the basics of data extraction from a database. It includes:

- [Chapter 1, Introduction to test data management](#)



# Introduction to test data management

Test data management is a process where you typically copy a subset of data from your production database to a structured data file, such as an XML or comma separated values (CSV) file. Structured files provide open, standards-based formats that can be accessed using standard database mechanisms.

As part of the subsetting process, you perform the following:

- **Apply eligibility requirements to the data.** In most cases, you do not want all of the data from your production database. You need to define criteria that restrict the records copied. For example, you might only copy records that pertain to a certain period of time or customer.
- **Mask sensitive data.** Typically, your test database is not as secure as your production database. Hence, you need to mask any sensitive data, such as names, addresses, phone numbers, social security numbers, and so on. HP Test Data Management provides a variety of masking capabilities to help you protect confidential data.

Copying qualified records out of your active database and masking them is only the first leg in the lifecycle of test data management. After you have the desired subset of data in a data extract file, you can upload from the file to a compatible test database. HP Test Data Management enables you to upload to heterogeneous databases, if necessary. For example, you may have extracted from a SQL Server database but need to upload to an Oracle database. You can also implement schema mapping in order to change the schema name when you load the data in the test database.

In addition to uploading the data from the extract file, you may also want to create a spreadsheet with some portion of the test data for use with other quality management tools. HP Test Data Management's query server enables you to quickly populate spreadsheets with test data from one or many database tables. Because you are using the extract file, the data you load into the spreadsheet is masked to your specifications and you can join tables, if necessary, without re-querying your source database.

*This chapter includes:*

- [Before you begin](#) (page 14)
- [Web Console overview](#) (page 14)

*See also*

For a complete conceptual introduction to Test Data Management, refer to the *HP Test Data Management Concepts Guide*.

## Before you begin

Before you begin performing the tasks in this guide, you should:

- 1 Review the *HP Test Data Management Concepts Guide* to become familiar with the software and how you plan to use it.
- 2 Install HP Test Data Management according to the instructions in the *HP Test Data Management Installation Guide*.
- 3 Go through *HP Test Data Management Tutorial*. The tutorial enables you to get hands on with the product quickly and exposes you to many of the most commonly used features.
- 4 Use the *HP Test Data Management Designer User Guide* to design and develop or customize your test data solution.

## Web Console overview

Most of the work of extracting data is performed in the Web Console. The Web Console is a powerful browser-based interface used to:

- Configure the repository
- Create environments
- Create and modify users
- Deploy business flows
- Launch business flows to move data
- Monitor running business flows and their history

The Web Console enables you to remotely manage multiple environments for the extraction of data.

---

## Part II: Tutorials

This part provides a set of tutorials that build on the basic tutorial described in the HP Test Data Management Tutorial. It includes:

- [Chapter 2, Configuring the Web Console](#)



Before you can deploy, run, and monitor your business flows to copy data, you must configure the Web Console. The Web Console is the primary runtime interface to Test Data Management.

This tutorial walks you through the process of configuring the Web Console, including:

- Starting and stopping the Web Console
- Installing the repository
- Creating environments
- Managing Web Console users.

---

**NOTE** Before you begin this tutorial, ensure that you have installed HP Test Data Management according to the *HP Test Data Management Installation Guide*.

---

*This chapter includes:*

- [Starting the Web Console](#) (page 17)
- [Installing the repository](#) (page 18)
- [Creating an environment](#) (page 23)
- [Creating Web Console users \(optional\)](#) (page 28)

## Starting the Web Console

The Web Console must be running before you can connect to it in your browser and perform operations such as installing the repository, creating environments, and managing users.

---

**TIP** When you install HP Test Data Management, the Installer gives you options to start the Web Console and launch its interface in your browser when the installation completes. If you chose those options and the Web Console is already running, you need not perform the steps in this section.

---

1 Start the Web Console in one of the following ways:

- On Microsoft Windows:  
Select **Start > HP Test Data Management > Start Web Console**.
- From the command line:

For example, on Microsoft Windows, select **Start > Run**, enter **cmd**, and click **OK**. After you have accessed the command line, perform the following steps.

- a Change to the `bin` directory where you installed HP Test Data Management.

On Windows:

```
cd c:\Program Files\HPTDM1.10\obt\bin
```

On UNIX:

```
cd /home/HPDTDM1.10/obt/bin
```

- b Enter the start command.

On Windows:

```
webConsole start
```

On UNIX:

```
./webConsole.sh start
```

A message should appear indicating that the Web Console has started and displaying its URL. For example:

```
Starting the Web Console at http://localhost:8090/  
WebConsole
```

- 2 Launch your favorite browser, and connect to the Web Console using the following URL:

```
http://localhost:8090/WebConsole
```

The first time that you start the Web Console after installing HP Test Data Management, you must install the repository. Refer to [Installing the repository](#) (page 18).

## Installing the repository

HP Test Data Management stores metadata in a repository to facilitate the deployment and running of business flows, and administering the Web Console. You can create the repository in an Oracle or SQL Server database, or the embedded repository.

To install repository:

- 1 If the Web Console is not already started, start it according to the steps in [Starting the Web Console](#) (page 17).

The Repository installation screen displays:

Install a New Repository »

Upgrade from a Previous Release »

## Repository Installation

The Console could not detect an installed Repository.  
 The Repository is used to centralize information required by the software. In the next screens we will ask you to provide the necessary information needed to create the Repository.  
 Please press the 'Install a New Repository' button to install the Repository.

- 2 Click **Install a New Repository**. The Repository Database: Administrator page displays.
- 3 Select the repository type from the drop-down list:
  - **Oracle** means you want to use an Oracle database and connect to it using the basic Oracle connection method.
  - **SQL Server** means you want to use a SQL Server database.
  - **Embedded** means that you want to embed the repository in Test Data Management and not use an external database for the repository.
  - **JDBC URL** means you want to connect to a database using a JDBC URL string. One required usage of JDBC URL is to connect to an Oracle database with Real Application Clusters (RAC).

When you select a repository type, the properties of the Administrator page change accordingly. For example, when you choose SQL Server, a DB Server field is added, the default user changes to sa, and the default port changes to 1433.

*For Oracle*

An example for Oracle:

HP Test Data Management

Environment: Logout ?

Next »

### Repository Database: Administrator

The administrator account is used by the deployment assistant to create users and grant access to resources.

Repository Type: Oracle ▼

User:\* system

Password:\* .....

Host:\* localhost

Port:\* 1521

Service Name:\* or11prddb

For *SQL Server*

An example for SQL Server :

HP Test Data Management Environment: Logout

Next »

### Repository Database: Administrator

The administrator account is used by the deployment assistant to create users and grant access to resources.

Repository Type:

Authentication:

User:

Password:

Host:

Port:

DB Server:

- 4 After you have selected the repository type, enter the appropriate credentials for that database type:

**NOTE** None of these properties applies to the Embedded option.

| Field          | Description                                                                                                                                                                                                                                                                                        |
|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Authentication | (SQL Server only) Choose the type of authentication used by SQL Server: <ul style="list-style-type: none"><li>• Windows Authentication means that the SQL Server instance uses the same credentials as the Windows machine on which it is installed.</li><li>• SQL Server Authentication</li></ul> |
| User           | Enter the database administrator username. Note this option does not apply to embedded repositories.                                                                                                                                                                                               |
| Password       | Enter the database administrator password. Note this option does not apply to embedded repositories.                                                                                                                                                                                               |
| Host           | (Oracle and SQL Server) Enter the name of the machine where the database is installed.                                                                                                                                                                                                             |
| Port           | (Oracle and SQL Server) Enter the port number of your Oracle or SQL Server database.                                                                                                                                                                                                               |
| Service Name   | (Oracle only) Enter the name of your Oracle database, for example, ORCL.                                                                                                                                                                                                                           |
| DB Server      | (SQL Server only) Enter the name of the SQL Server database, for example, MSOLTP.                                                                                                                                                                                                                  |

5 Click **Next**.

The Repository Database: User page displays.

*For Oracle*

An example for Oracle:

The screenshot shows the 'Repository Database: User' page in the HP Test Data Management web console. The page has a blue header with the HP logo and 'HP Test Data Management'. On the right, there's an 'Environment:' section with a 'Logout' button and a help icon. Below the header, there are '« Back' and 'Next »' buttons. The main content area is titled 'Repository Database: User' and includes instructions: 'Create the repository user. Repository user is a database user for logging in to the repository schema.' The form contains the following fields: 'User:' with the value 'obt\_rep', 'Password:' with masked characters, 'Confirm Password:' with masked characters, 'Data Tablespace:' with a dropdown menu showing 'USERS (66 MB)', and 'Temp Tablespace:' with a dropdown menu showing 'TEMP (13 MB)'. Below this, there's another section titled 'Repository Database: Encryption Key' with instructions: 'The Encryption Key is used as Repository Master Password'. It contains 'Encryption Key:' and 'Confirm Encryption Key:' fields, both with masked characters.

*For SQL Server*

An example for SQL Server:

The screenshot shows the 'Repository Database: User' page in the HP Test Data Management web console for SQL Server. The layout is similar to the Oracle example, but with different fields. The 'User:' field has the value 'obt\_rep'. The 'Password:' and 'Confirm Password:' fields are masked. The 'DB Name:' field also has the value 'obt\_rep'. The 'Primary data Size:' field has the value '90', and the 'Transaction Log Size:' field has the value '50'. The 'Repository Database: Encryption Key' section is also present, with 'Encryption Key:' and 'Confirm Encryption Key:' fields, both masked.

6 Select or enter the following information for the repository user:

| Field            | Description                                                                           |
|------------------|---------------------------------------------------------------------------------------|
| User             | Enter the name you want to use for the repository user. The default value is obt_rep. |
| Password         | Enter the password for the user you created.                                          |
| Confirm Password | Enter the password again.                                                             |

| Field                  | Description                                                                                 |
|------------------------|---------------------------------------------------------------------------------------------|
| Data Tablespace        | (Oracle only) Select the data tablespace you want to use.                                   |
| Temp Tablespace        | (Oracle only) Select the temporary tablespace you want to use.                              |
| Primary Data Size      | (SQL Server only) Accept the default value or enter a maximum size in MB for the data file. |
| Transaction Log Size   | (SQL Server only) Accept the default value or enter a maximum size in MB for the log file.  |
| Encryption Key         | Enter the encryption key you want to use.                                                   |
| Confirm Encryption Key | Enter the encryption key again.                                                             |

7 Click **Next**.

The Console Administrator page displays.

8 Select or enter the following information:


| Field            | Description                                                                                                                           |
|------------------|---------------------------------------------------------------------------------------------------------------------------------------|
| User Name        | Enter the name you want to use for the Web Console administrator. The Web Console administrator is used to log on to the Web Console. |
| Password         | Enter the password for the administrator.                                                                                             |
| Confirm Password | Enter the password again.                                                                                                             |
| Real Name        | Optionally, enter the name of the administrator user.                                                                                 |
| Description      | Optionally, enter a description.                                                                                                      |
| Email            | Optionally, enter an email address.                                                                                                   |
| Phone Number     | Optionally, enter a phone number.                                                                                                     |

- 9 Click **Next**. The Summary page appears for your review.
- 10 Click **Finish**.

It may take several moments for the repository creation to complete. When the repository is created, the following message displays:

You have successfully installed the repository. Please do NOT close your browser. Web Console will restart.

After the Web Console restarts, the login screen displays.



- 11 Enter the Web Console administrator user name and password that you just created.
- 12 Click **Login**.

You are now logged in to the Web Console and can create a new environment.

## Creating an environment

Before you can deploy your business flows, you must create a deployment environment for them with the appropriate characteristics, such as the source database credentials and available data movement methods.

- 1 If the Web Console is not already started and open in your browser, you need to start it according to the instructions in [Starting the Web Console](#) (page 17).
- 2 If you have not previously installed the repository, you need to do so before you can continue. Refer to [Installing the repository](#) (page 18).
- 3 If you have not previously created an environment, the Web Console automatically prompts you to create one when you open it. Otherwise, click **Environment** at the top of the page and then **New** in the left navigation pane to display the New Environment wizard.
- 4 Specify a name for the new environment, for example, `Oracle_OLTP` or `SQLServer_OLTP`.

- 5 Specify whether you want a non-intrusive environment configuration. For the purposes of this tutorial, leave **Non-intrusive** unselected. For more information, see [Creating a non-intrusive environment](#) (page 56).
- 6 Select the source database type.


- **Oracle**
- **SQL Server**
- **Sybase**
- **JDBC URL**
- **DB2**

Selecting **JDBC URL** indicates that you want to connect to a database using a JDBC URL string. One common usage of JDBC URL is to connect to another data source for which you have a JDBC (or ODBC) driver.

- 7 Enter the necessary credentials for the source database.

*For Oracle*

An example for Oracle:



The screenshot shows the HP Test Data Management web console. The top navigation bar includes the HP logo, the title 'HP Test Data Management', and user information 'Environment: User: admin' with 'Logout' and '?' buttons. Below the navigation bar are tabs for 'Environment', 'Users', and 'Settings'. The 'Environment' tab is active, and a 'Manage' link is visible. The main content area is titled 'New Environment' and contains the following fields:

- Environment Name: Oracle\_OLTP
- Description: (empty)
- Non-intrusive: ☐
- Source Database Type: Oracle (selected from a dropdown)
- Administrative User: system
- Password: (masked with dots)
- Host: localhost
- Port: 1521
- Service Name: or11prddb

*For SQL Server*

An example for SQL Server:

HP Test Data Management Environment: DB2B\_OLTP User: admin Logout ?

Monitoring Launch Parameters Business Flow Deployment Environment Users Settings

Manage DB2B\_OLTP Locations Authorizations Rename

Next »

### New Environment

Environment Name: \* SQLServer\_OLTP

Description: Production SQL Server in

Non-Intrusive: ☐

### Source Database

Source Database Type: SQL Server

Authentication: SQL Server Authentication

Administrative User: \* sa

Password: \* .....

Host: \* maguro.cup.hp.com

Port: \* 5031

DB Server: \* MS3OLTP

8 Click **Next**.

9 Select where to store your user indexes.

Any user indexes you create in Designer using the File Indexes tab are saved to the location you specify.

10 Click **Next**.

The Interface User page displays.

*For Oracle*

An example for Oracle:

HP Test Data Management Environment: User: admin Logout ?

Environment Users Settings

Home » Environment » New

« Back Next »

### Interface User

The Interface User is created in the Source Database to store intermediate results.

User: \* obt\_if

Password: \* .....

Confirm Password: \* .....

Data Tablespace: USERS (63 MB)

Temp Tablespace: TEMP (13 MB)

For SQL Server

An example for SQL Server 2008:

HP Test Data Management

Environment: DB2B\_OLTP User: admin Logout

Monitoring Launch Parameters Business Flow Deployment Environment Users Settings

Home » Environment » New

« Back Next »

### Interface User

The Interface User is created in the Source Database to store intermediate results.

User:\*

Password:\*

Confirm Password:\*

DB Name:\*

Primary data Size:\*

Transaction Log Size:\*

11 Enter the following information for the interface user:

| Field                | Description                                                                                 |
|----------------------|---------------------------------------------------------------------------------------------|
| User                 | Enter the name you want to use for the Interface user. The default value is obt_if.         |
| Password             | Enter the password for the user you created.                                                |
| Confirm Password     | Enter the password again.                                                                   |
| Data Tablespace      | (Oracle only) Select the data tablespace you want to use.                                   |
| Temp Tablespace      | (Oracle only) Select the temporary tablespace you want to use.                              |
| Primary Data Size    | (SQL Server only) Accept the default value or enter a maximum size in MB for the data file. |
| Transaction Log Size | (SQL Server only) Accept the default value or enter a maximum size in MB for the log file.  |

12 Click **Next**.

The summary page for the environment appears. Review the settings that you have chosen.

*For Oracle*

An example for Oracle:

The screenshot shows the HP Test Data Management web console interface. The top navigation bar includes the HP logo, the title "HP Test Data Management", and the current environment "Environment: User: admin" with a "Logout" button. Below the navigation bar, there are tabs for "Environment", "Users", and "Settings". The main content area displays the configuration details for a new environment. It includes a "Summary" section with the following information:

- Configuration Type**
  - Environment Name: Oracle\_OLTP
  - Environment Description: Oracle\_OLTP
  - Database: "Oracle"
  - Non-intrusive: no
- Source Database Server**
  - Service Name: or11prddb
  - Host: localhost
  - Port: 1521
- Interface User**
  - User Name: obt\_if
  - Password: \*\*\*
  - Data tablespace: USERS
  - Temp tablespace: TEMP

*For SQL Server*

An example for SQL Server:

The screenshot shows the HP Test Data Management web console interface for a SQL Server environment. The top navigation bar includes the HP logo, the title "HP Test Data Management", and the current environment "Environment: DB2B\_OLTP User: admin" with a "Logout" button. Below the navigation bar, there are tabs for "Monitoring", "Launch", "Parameters", "Business Flow Deployment", "Environment", "Users", and "Settings". The main content area displays the configuration details for a new environment. It includes a "Summary" section with the following information:


- Configuration Type**
  - Environment Name: SQLServer\_OLTP
  - Environment Description: Production SQL Server instance
  - Database: "SQL Server"
  - Non-intrusive: no
- Source Database Server**
  - Server: MS30LTP
  - Host: maguro.cup.hp.com
  - Port: 5031
- Interface User**
  - User Name: obt\_if\_ss\_01
  - Password: \*\*\*
  - Primary Data Size: 50
  - Transaction Log Size: 25

- 13 Click **Finish** to create the environment.

It may take several moments to create the environment. When the environment is ready, the success message should appear at the top of the page. If you receive any errors, use the back button on your browser to review your choices and ensure that they are correct.

*For Oracle*

An example for Oracle:



*For SQL Server*

An example for SQL Server 2008:



For the purposes of this tutorial, you can now optionally create a Web Console user [Creating Web Console users \(optional\)](#) (page 28).

## Creating Web Console users (optional)


In most cases, more than one user needs to perform functions in the Web Console, but not every user needs the same privileges. For example, some users might only need to run jobs while others may need to deploy business flows, set parameter values, and run jobs. Web Console provides a user model that enables you to create as many users as you need, and grant or withhold privileges.

- In this section:*
- [Creating a new Web Console user](#) (page 28)
  - [Verifying the new Web Console user](#) (page 30)

### Creating a new Web Console user

- 1 If the Web Console is not started and open in your browser, refer to [Starting the Web Console](#) (page 17).
- 2 If you have not previously installed the repository and created an environment, you need to do so before you can continue. Refer to [Installing the repository](#) (page 18) and [Creating an environment](#) (page 23).
- 3 In the menu bar at the top of the page, select **Users**.

The User List page displays. If you have not previously created any other users, you should only see the user named admin.



4 Select **New User**.

The Create User page displays.

**Create User**

Login Name: \* tom\_baker

Full Name: Tom Baker

Password: \* .....

Enabled: ☒

Description:

Email:

Phone:

Assign Privilege:

- ☐ Administer
- ☐ Manage Users
- ☐ Manage Environments
- ☒ Deploy Business Flows
- ☒ Run Jobs
- ☒ Deploy and Execute Remotely
- ☒ Access Data
- ☒ Access System Parameters
- ☒ Access Application Parameters

Environments:

☐ Oracle\_OLTP


5 Enter at least the following values:

- Login Name: tom\_baker
- Full Name: Tom Baker
- Password: welcome
- Enabled: checked
- Assign Privilege: Check the following:
  - Deploy Business Flows
  - Run Jobs
  - Deploy and Execute Remotely
  - Access Data
  - Access System Parameters
  - Access Application Parameters

**NOTE** This new user is only expected to deploy, run, and monitor business flows in the specified environment. Hence, this user is not granted the privileges to create users, manage environments, or otherwise administer the Web Console.


- 6 Select the environment you want the user to access.
- 7 Click **Create** at the top of the page.

The Show User page displays.




The new user can deploy, run, and monitor business flows, and set parameters.

- 8 Click **User List** to confirm that the new user has been added.



## Verifying the new Web Console user

- 1 Click **Logout**.
- 2 Log back in as the user you just created.



Notice how the User link does not appear to Tom Baker. He does not have permissions to create users.

- 3 Click **Logout**.
- 4 Log back in as the Web Console administrator.



## Part III: Task reference

This part provides an advanced task reference to assist you in performing specific tasks within the Web Console and from the command line. It includes:

- [Chapter 3, Starting and configuring the Web Console](#)
- [Chapter 4, Managing environments](#)
- [Chapter 5, Managing users](#)
- [Chapter 6, Running business flows and jobs from the Web Console](#)
- [Chapter 7, Running business flows and jobs from the command line](#)
- [Chapter 8, Monitoring jobs](#)
- [Chapter 9, Managing the repository and encryption keys](#)
- [Chapter 10, Using the query server to access extracted data files](#)
- [Chapter 11, Query server administrative tasks](#)
- [Appendix A, Configuration and runtime parameters](#)
- [Appendix B, Advanced tasks](#)
- [Appendix C, Scripted product setup and business flow deployment](#)



# 3

## Starting and configuring the Web Console

The Web Console is the primary runtime interface to Test Data Management. You use it to deploy, run, and monitor jobs, and administer environments and users. The Web Console requires a repository in which to store its metadata. Hence, the first time you start the Web Console, you are prompted to install or upgrade the repository.

*In this chapter*

- [Starting and stopping the Web Console](#) (page 35)
- [Installing a new repository](#) (page 38)
- [Adding Web Console nodes](#) (page 42)

### Starting and stopping the Web Console

Before you can connect to the interface for the Web Console server in your Web browser and perform tasks, you must start the Web Console server. You can also stop Web Console server when it is not in use or when performing maintenance activities that require it be taken down.

*In this section*

- [Starting Web Console](#) (page 35)
- [Stopping the Web Console](#) (page 37)

### Starting Web Console

You can start Web Console from the Start menu on Microsoft Windows or from the command line on any platform.

*In this section*

- [Starting Web Console from the Start menu](#) (page 35)
- [Starting Web Console from the command line](#) (page 36)
- [Starting the Web Console on a different port](#) (page 36)
- [Starting Web Console with SSL enabled](#) (page 37)

#### Starting Web Console from the Start menu

- 1 After installing Test Data Management, start the Web Console from the Start menu:

**Start > All Programs > HP Test Data Management > Start Web Console**

where HP Test Data Management is the program group where you chose to install Test Data Management during installation.

A command window opens and closes automatically after the Web Console is started.

- 2 Launch your favorite browser, and connect to the Web Console using the following default URL:

```
http://<hostname>:8090/WebConsole
```

where <hostname> is the name of the machine on which you installed Test Data Management.

- 3 If you are starting Web Console for the first time after installation of Test Data Management, you are prompted to either install a new repository or upgrade an existing one. Refer to [Installing a new repository](#) (page 38).

## Starting Web Console from the command line

- 1 Open a command window and navigate to the directory that contains the Web Console script.

```
cd <install_directory>/obt/bin
```

where <install\_directory> is the location where you installed Test Data Management.

- 2 To start the Web Console server, enter the following command:

On Windows:

```
webConsole start
```

On UNIX:

```
./webConsole.sh start
```

- 3 Launch your favorite browser, and connect to the Web Console using the following default URL:

```
http://<hostname>:8090/WebConsole
```

where <hostname> is the name of the machine on which you installed Test Data Management.

- 4 If you are starting the Web Console for the first time after installation of Test Data Management, you are prompted to either install a new repository or upgrade an existing one. For more information, see [Installing a new repository](#) (page 38).

## Starting the Web Console on a different port

By default, the Web Console runs on port 8090. If you want to use a different port number, you must start the Web Console server from the command line and specify a different port number.

- 1 To start the Web Console using a different port number, enter the following command:

On Windows:

```
webConsole -p <port> start
```

On UNIX:

```
./webConsole.sh -p <port> start
```

where <port> is the port number you plan to use for Web Console.

- 2 Launch your favorite browser, and connect to Web Console using the following URL:

```
http://<hostname>:<port>/WebConsole
```

where: <hostname> is the name of the machine on which you installed HP Test Data Management, and <port> is the port number you specified in the previous step.

- 3 If you are starting Web Console for the first time after installation of HP Test Data Management, you are prompted to either install a new repository or upgrade an existing one. Refer to [Installing a new repository](#) (page 38).

## Starting Web Console with SSL enabled

You can configure Web Console to run with SSL using the XML configuration file (jetty.xml) for its application server, called Jetty. Refer to the following URL for more information about Jetty and how to configure it for SSL:

```
http://docs.codehaus.org/display/JETTY/Jetty+Wiki
```

If you choose to modify jetty.xml, you can no longer start the Web Console using the Start menu or command line scripts supplied with the product. You instead must use the following:

```
java -jar webConsole/start.jar
```

## Stopping the Web Console

You can stop Web Console from the Start menu on Microsoft Windows or from the command line on any platform.

*In this section*

- [Stopping Web Console from the Start menu](#) (page 37)
- [Stopping Web Console from the command line](#) (page 38)
- [Stopping Web Console on a different port](#) (page 38)

### Stopping Web Console from the Start menu

To stop Web Console from the Start menu:

**Start > All Programs > <HPDB\_Pgm\_Group> > Stop Web Console**

where <HPDB\_Pgm\_Group> is the program group where you chose to install HP Test Data Management during installation.

A command window opens and closes automatically after the Web Console is started.

## Stopping Web Console from the command line

To stop Web Console using the following command:

```
webConsole stop
```

## Stopping Web Console on a different port

If you started the Web Console server using a different port than 8090, then you must stop the Web Console from the command line and specify that port number.

To stop the Web Console using a different port number, enter the following command:

```
webConsole -p <port> stop
```

where <port> is the port number you used for Web Console.

# Installing a new repository

You can create a repository on an Oracle or SQL Server database, or the embedded repository. If you are creating the repository on Oracle or SQL Server, you have the option to connect with the standard Oracle or SQL Server connection formats, or to use a JDBC URL.

- See also*
- 1 If it is not already running, start the Web Console.  
[Starting Web Console](#) (page 35)
  - 2 Click **Install a New Repository**.  
The Repository Database: Administrator page displays.
  - 3 Select the RDBMS type for your repository and enter the appropriate information:
    - [Oracle](#) (page 38)
    - [SQL Server](#) (page 40)
    - [Embedded](#) (page 41)
    - [JDBC URL](#) (page 41)

## Oracle

- a Enter the following administrator information:

| Field    | Description                                |
|----------|--------------------------------------------|
| User     | Enter the administrator username.          |
| Password | Enter the password for the specified user. |

| Field        | Description                                                            |
|--------------|------------------------------------------------------------------------|
| Host         | Enter the name of the machine where your Oracle database is installed. |
| Port         | Enter the port number of your Oracle database, for example, 1521.      |
| Service Name | Enter the name of your Oracle database, for example, ORCL.             |

**b** Click **Next**.

The Repository Database: User page displays.

**c** Select or enter the following information for the repository user:

| Field                  | Description                                                                           |
|------------------------|---------------------------------------------------------------------------------------|
| User                   | Enter the name you want to use for the repository user. The default value is obt_rep. |
| Password               | Enter the password for the user you created.                                          |
| Confirm Password       | Enter the password again.                                                             |
| Data Tablespace        | Select the data tablespace you want to use.                                           |
| Temp Tablespace        | Select the temporary tablespace you want to use.                                      |
| Encryption Key         | Enter the encryption key you want to use.                                             |
| Confirm Encryption Key | Enter the encryption key again.                                                       |

## SQL Server

- a Enter or select the following administrator information:

| Field          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Authentication | Select SQL Server Authentication or Windows Authentication from the list of values. <ul style="list-style-type: none"><li>• <b>SQL Server Authentication</b> indicates that the SQL Server login is distinct from the operating system login for the machine, and logging in to the machine does not imply that you are authenticated for the SQL Server instance as well.</li><li>• <b>Windows Authentication</b> indicates that the operating system login for the machine is the same as the SQL Server login, and after you are logged in to the machine, you need not authenticate again for the SQL Server instance.</li></ul> |
| User           | Enter the administrator username. Required for SQL Server authentication only.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Password       | Enter the administrator password for the specified user. Required for SQL Server authentication only.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| Host           | Enter the host name of the machine where your SQL Server database is installed.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Port           | Enter the port number of your SQL Server database.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| DB Server      | Enter the name of your SQL Server database server.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

- b Click **Next**.

The Repository Database: User page displays.

- c Select or enter the following information for the repository user:

| Field             | Description                                                                           |
|-------------------|---------------------------------------------------------------------------------------|
| User              | Enter the name you want to use for the repository user. The default value is obt_rep. |
| Password          | Enter the password for the user you created.                                          |
| Confirm Password  | Enter the password again.                                                             |
| Primary Data Size | Accept the default value or enter a maximum size in MB for the data file.             |

| Field                  | Description                                                              |
|------------------------|--------------------------------------------------------------------------|
| Transaction Log Size   | Accept the default value or enter a maximum size in MB for the log file. |
| Encryption Key         | Enter the encryption key you want to use.                                |
| Confirm Encryption Key | Enter the encryption key again.                                          |

#### Embedded

- a Click **Next** to start the embedded repository.  
The Repository Database: User page displays.
- b Select or enter the following information for the repository user:

| Field                  | Description                                                                              |
|------------------------|------------------------------------------------------------------------------------------|
| User                   | Enter the name you want to use for the repository user.<br>The default value is obt_rep. |
| Password               | Enter the password for the user you created.                                             |
| Confirm Password       | Enter the password again.                                                                |
| Encryption Key         | Enter the encryption key you want to use.                                                |
| Confirm Encryption Key | Enter the encryption key again.                                                          |

#### JDBC URL

- a Enter the following administrator information:

| Field    | Description                                              |
|----------|----------------------------------------------------------|
| User     | Enter the administrator username.                        |
| Password | Enter the administrator password for the specified user. |
| URL      | Enter the URL for the database.                          |

- b Click **Next**.  
The Repository Database: User page displays.
- c Select or enter the following information for the repository user:

| Field            | Description                                                                           |
|------------------|---------------------------------------------------------------------------------------|
| User             | Enter the name you want to use for the repository user. The default value is obt_rep. |
| Password         | Enter the password for the user you created.                                          |
| Confirm Password | Enter the password again.                                                             |

| Field                  | Description                                      |
|------------------------|--------------------------------------------------|
| Data Tablespace        | Select the data tablespace you want to use.      |
| Temp Tablespace        | Select the temporary tablespace you want to use. |
| Encryption Key         | Enter the encryption key you want to use.        |
| Confirm Encryption Key | Enter the encryption key again.                  |

- 4 Click **Next**.

The Console Administrator page displays.

- 5 Enter the following information:

| Field            | Description                                                                                                                           |
|------------------|---------------------------------------------------------------------------------------------------------------------------------------|
| User Name        | Enter the name you want to use for the Web Console administrator. The Web Console administrator is used to log on to the Web Console. |
| Password         | Enter the password for the administrator.                                                                                             |
| Confirm Password | Enter the password again.                                                                                                             |
| Real Name        | Optionally, enter the name of the administrator user.                                                                                 |
| Description      | Optionally, enter a description.                                                                                                      |
| Email            | Optionally, enter an email address.                                                                                                   |
| Phone Number     | Optionally, enter a phone number.                                                                                                     |

- 6 Click **Next**.

The Summary page displays.

- 7 Click **Finish** to create the repository, or click **Back** to make changes.

The following message displays:

You have successfully installed the repository. Please do not close your browser. Web Console will restart.

After the Web Console restarts, the login screen displays.

## Adding Web Console nodes

In some cases, you may want to have additional Web Console nodes on other machines that operate upon the same repository. Having multiple Web Console nodes enables you to perform operations against the same repository from any one of several different machines, thus avoiding any performance bottlenecks on the

primary Web Console node. By copying certain files from your first or primary node of the Web Console, you can effectively clone the primary node on other machines.

---

**NOTE** This procedure assumes that you have already installed and fully configured one instance of Test Data Management according to the instructions in the *HP Test Data Management Installation Guide* and [Installing a new repository](#) (page 38).

---

To configure an additional Web Console node:

- 1 From the primary node, where you first installed Test Data Management and configured the Web Console, make copies of the following files and move them to a location accessible to the machine where you want to create an additional node:
  - `<prime_install_dir>\obt\config\connection-sources.xml`
  - `<prime_install_dir>\obt\config\hpdbackarchiving.auth`
  - `<prime_install_dir>\obt\sql_tuning.properties`
- 2 On the machine where you want to create the additional Web Console node, use the Installer to create and populate an installation directory tree just as you would for a new installation. Follow the instructions in the *HP Test Data Management Installation Guide*, but do not start the Web Console.
- 3 Overwrite the following files on the clone machine with the copies you made from the primary node:
  - `<clone_install_dir>\obt\config\connection-sources.xml`
  - `<clone_install_dir>\obt\config\hpdbackarchiving.auth`
  - `<clone_install_dir>\obt\sql_tuning.properties`
- 4 Start the cloned Web Console node as described in [Starting and stopping the Web Console](#) (page 35).
- 5 Confirm that you are operating upon the same repository as the primary node. You should not be prompted to install or upgrade a repository as you normally would for a new installation of the Web Console. Furthermore, if you are logged in as the administrator user, you should be able to see any environments that were created from the primary node.



An environment is a named deployment environment associated with a source (active) database. If you plan to perform database to file operations for the source database, the environment will also include a target location. From an environment, users with the necessary privileges can run business flows against the source database. You can create as many environments as you wish, thus supporting multiple source databases from a single installation of HP Test Data Management.

Before you can run business flows, you must create at least one environment into which you can deploy the business flows.

*In this chapter*

- [Creating an environment](#) (page 45)
- [Setting the active environment](#) (page 49)
- [Deleting an environment](#) (page 50)
- [Renaming an environment](#) (page 50)
- [Setting up a non-intrusive environment](#) (page 51)
- [Deploying business flows](#) (page 56)
- [Configuring parameters](#) (page 61)
- [Managing locations](#) (page 62)
- [Refreshing test environments](#) (page 66)

## Creating an environment

Because you can use multiple sources in the repository, each source and target combination requires a separate environment. Database to File copying is enabled for each environment.

To create an environment:

- 1 Ensure the Web Console has been started and the repository installed or upgraded.

*See also*

[Starting Web Console](#) (page 35)

[Installing a new repository](#) (page 38)

- 2 Log in to the Web Console as the administrator, for example, admin.

If you have not created any environments yet, the New Environment page displays. Otherwise, click **Environment** in the menu at the top of the page and then click **New**.

- 3 Enter the Environment Name and Description.

---

**NOTE** The environment name should not contain MBCS characters.

---

- 4 Select the appropriate Source Database Type from the list of values for your active database. The available fields change depending on the selected database.
- 5 Enter the information relevant to your database type:

*Oracle*

| Field    | Description                                                            |
|----------|------------------------------------------------------------------------|
| User     | Enter the administrator username.                                      |
| Password | Enter the administrator password.                                      |
| Host     | Enter the name of the machine where your Oracle database is installed. |
| Port     | Enter the port number of your Oracle database, for example, 1521.      |

*SQL Server*

| Field               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|---------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Authentication      | Select SQL Server Authentication or Windows Authentication from the list of values: <ul style="list-style-type: none"><li>• <b>SQL Server Authentication</b> indicates that the SQL Server login is distinct from the operating system login for the machine, and logging in to the machine does not imply that you are authenticated for the SQL Server instance as well.</li><li>• <b>Windows Authentication</b> indicates that the operating system login for the machine is the same as the SQL Server login, and after you are logged in to the machine, you need not authenticate again for the SQL Server instance.</li></ul> |
| Administrative User | Enter the administrator username. Required for SQL Server authentication only.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Password            | Enter the administrator password. Required for SQL Server authentication only.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Host                | Enter the host name of the machine where your SQL Server database is installed.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Port                | Enter the port number of your SQL Server database.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| DB Server           | Enter the name of your SQL Server database server.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

## Sybase

| Field               | Description                                                                 |
|---------------------|-----------------------------------------------------------------------------|
| Administrative User | Enter the administrator username.                                           |
| Password            | Enter the administrator password.                                           |
| Host                | Enter the host name of the machine where your Sybase database is installed. |
| Port                | Enter the port number of your Sybase database.                              |
| DB Server           | Enter the name of your Sybase database server.                              |

## JDBC URL

| Field    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| User     | Enter the administrator username.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| Password | Enter the administrator password.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| URL      | <p>Enter the connection URL for the database. JDBC URLs are often used to connect to an Oracle database with RAC.</p> <p>For example:</p> <pre>jdbc:oracle:thin:@(DESCRIPTION=(SDU=32768) (enable=broken)(LOAD_BALANCE=yes)(ADDRESS= (PROTOCOL=TCP)(HOST=gvu2707.austin.hp.com) (PORT=1525))(ADDRESS=(PROTOCOL=TCP)(HOST=gv u2923.austin.hp.com)(PORT=1525))(CONNECT_DA TA=(SERVICE_NAME=SAPDEMI)))</pre> <p>For more information about JDBC URLs, refer to <a href="#">Using JDBC URLs for your database connections</a> (page 49).</p> |

6 Click **Next**.

7 Select where to store your Database to File user indexes.

Any user indexes you create in Designer using the File Indexes tab are saved to the location you specify.

**NOTE** If you are deploying business flows into a different database type than your repository, Store Indexes in the Repository is disabled.

8 Click **Next**.

The Interface User page displays.

9 Enter or select the following information for the interface user:

| Field                | Description                                                                                          |
|----------------------|------------------------------------------------------------------------------------------------------|
| User                 | Enter the name you want to use for the Interface user. The default value is obt_if.                  |
| Password             | Enter the password for the user you created.                                                         |
| Confirm Password     | Enter the password again.                                                                            |
| Data Tablespace      | For Oracle, select the data tablespace you want to use.                                              |
| Temp Tablespace      | For Oracle, select the temporary tablespace you want to use.                                         |
| Primary Data Size    | For SQL Server and Sybase, accept the default value or enter a maximum size in MB for the data file. |
| Transaction Log Size | For SQL Server and Sybase, accept the default value or enter a maximum size in MB for the log file.  |

10 Click **Next**.

11 If you chose a distributed instance, enter the following values for the relocation user:

| Field                | Description                                                                               |
|----------------------|-------------------------------------------------------------------------------------------|
| User                 | Enter the name you want to use for the relocation user. The default value is obt_reloc.   |
| Password             | Enter the password for the user you created.                                              |
| Confirm Password     | Enter the password again.                                                                 |
| Data Tablespace      | For Oracle, select the data tablespace you want to use.                                   |
| Temp Tablespace      | For Oracle, select the temporary tablespace you want to use.                              |
| Primary Data Size    | For SQL Server, accept the default value or enter a maximum size in MB for the data file. |
| Transaction Log Size | For SQL Server, accept the default value or enter a maximum size in MB for the log file.  |

12 Click **Next**. The Summary page displays for your review.

13 Click **Finish** to create the environment.

After your environment is created, you can:

- create another new environment
- further configure the environment, such as, setting parameters
- deploy business flows into the environment

## Using JDBC URLs for your database connections

You can use a JDBC URL to connect to your repository and databases.

### JDBC URLs

To use a JDBC URL for your connections, you need enter the following information in the appropriate format:

| Database   | Expected URL                                                                                    |
|------------|-------------------------------------------------------------------------------------------------|
| Oracle     | <code>jdbc:oracle:thin:@&lt;Host&gt;:&lt;Port&gt;:&lt;OracleServiceName&gt;</code>              |
| SQL Server | <code>jdbc:hpdba:sqlserver://&lt;Host&gt;:&lt;Port&gt;;InstanceName=&lt;DatabaseName&gt;</code> |
| Sybase     | <code>jdbc:sybase://&lt;Host&gt;:&lt;Port&gt;;InstanceName=&lt;DatabaseName&gt;</code>          |

| Parameter         | Description                                          |
|-------------------|------------------------------------------------------|
| Host              | The fully qualified host address for the connection. |
| Port              | The port number for the connection.                  |
| OracleServiceName | The Oracle database service name.                    |
| DatabaseName      | The name of the SQL Server or Sybase database.       |

*Oracle example*     `jdbc:oracle:thin:@localhost:1521:ORCL`

## Setting the active environment

When you have multiple environments, you need to switch between them in order to make changes to them or run business flows. The Web Console acts on the currently active environment.

To change the active environment:

- 1 Start the Web Console, if it is not already started.  
*See also*     [Starting Web Console](#) (page 35)
- 2 Click **Environment** from the menu at the top of the page.  
The Manage Environments page displays all of the environments in your installation.
- 3 Select the environment.
- 4 Click **Set Active**. The selected environment is now active. The business flows and settings that you see in the Web Console are now the ones for that environment.

## Deleting an environment

When you delete an environment, the following occurs:

- All business flows are removed from the repository.
- All users that were created during environment creation are removed.

---

**NOTE** The repository user, `obt_rep`, is not affected.

---

- For SQL Server, any databases that were created remain, but will no longer be referenced.
- All historical data collected from the running of business flows in that environment are retained.

---

**NOTE** To delete the history data, you need to remove the business flows first. Refer to [Removing business flows](#) (page 60) for more information.

---

To delete an environment:

- 1 Start the Web Console, if it is not already started.
- 2 Select the environment you want to delete.

*See also*

[Starting Web Console](#) (page 35)

---

**NOTE** You can delete any environment except for the active environment. If the active environment is the only existing environment, you need to create a new environment and ensure that the new environment is active.

---

- 3 Click **Delete**.
- 4 Click **OK** at the prompt to continue the deletion.
- 5 Enter the source database administrator username and password.
- 6 Click **Finish** to delete the environment.

## Renaming an environment

When cloning an environment, you can rename the environment. See [Refreshing test environments](#) (page 66).

To rename an environment:

- 1 Start the Web Console, if it is not already started.
- 2 Click **Environment** from the menu at the top of the page.

*See also*

[Starting Web Console](#) (page 61)

The Manage Environments page displays all of the environments in your installation.

- 3 Select the environment.
- 4 Click **Rename** in the left navigation pane. The Rename Environment page displays.
- 5 Enter a new environment name and optionally a description.
- 6 Click **Rename** at the menu at the top of the page.  
A summary page displays, showing the results of the rename environment command.
- 7 Log out then log in to the Web Console to make sure that environment is renamed.

## Setting up a non-intrusive environment

When creating a new deployment environment, you can specify that it is non-intrusive. In a non-intrusive environment, data is extracted without an interface schema, and the corresponding JDBC driver for the database is used. (If you are using a non-native database, you must supply a JDBC driver for the non-native database.) A non-intrusive environment allows you to copy data from read-only sources, especially in cases where data is associated with older technologies that might not support basic SQL statements, or when database administrator or company policy prohibits write access to the production environment. Specifying a non-intrusive environment enables you to extract data from the production environment while avoiding any potential security risks. You can create a non-intrusive environments for natively supported platforms.

Non-intrusive environments support data masking. You can also upload files extracted from non-intrusive environments to supported databases just as you would any other extracted files. Column Inclusion, Name Override and Custom Properties are also supported in a non-intrusive environment.

## Uploads from or to non-native databases

When extracting and then uploading data between heterogeneous databases, consider carefully the mapping of data types between the databases. The data type mapping is handled through a mapping file. If you are uploading to a database that is non-native to HP Test Data Management, you need to create a mapping file. For native databases, you should be able to upload data extracted from one database and uploaded to another without updating the mapping file.

### Uploads to a native database

When uploading data to a native database, a mapping file already exists for the target database. During the upload process HP Test Data Management attempts to map the column type with the help of the existing mapping file. It also throws an exception if it finds any invalid mapping, such as the target column is incorrectly mapped, no mapping is found, or multiple mappings are found.

If the upload process fails, an exception is thrown and recorded in the log file. To fix the mapping issues, edit the mapping file then rerun the upload process. For information about logging, see [Using log files](#) (page 142). For information about editing mapping files, see [Mapping files](#) (page 52).

## Uploads to a non-native database

When uploading to a non-native database, a mapping file does not exist. In this case, HP Test Data Management creates a mapping file when you run the upload process. If invalid mappings are found, the upload process fails, and exceptions are thrown and logged. To fix the mapping issues, edit the mapping file then rerun the upload process. For information about editing mapping files, see [Mapping files](#) (page 52).

## Mapping files

When uploading to non-native databases, you can use a mapping file to handle the mapping of data types. HP Test Data Management supports and includes mapping files for the following databases:

- DB2
- Oracle
- SQL Server
- Sybase

The mapping files are XML files that specify how one data type should be mapped to another. The mapping can be:

- Simple—One data type is mapped to another without any considerations.
- Database specific—The data type mapping depends on which database is used as the source. For example, if the data type is real, it is mapped to float for SQL server. Otherwise, it is mapped to NUMBER.
- Auto-expansion—The data types being mapped have a precision, length, or scale values but have different maximums, so the mapping depends on the actual value. For example, if length exceed 4001 when mapping from varchar to a VARCHAR2 data type, it is mapped to CLOB instead of a VARCHAR2.

For the elements and structure required in a mapping file, see the mapping file schema `dataTypeMapping.xsd`. It is located in the directory:

```
<install_directory>/obt/foundation/components/config
```

where `<install_directory>` is the location where the HP Test Data Management is installed.

*Example* The following is a example of simple mapping:

```
<mapping>
  <columnInput>real</columnInput>
  <columnOutput>NUMBER</columnOutput>
</mapping>
```

In this example, the real data type in the source is mapped to the NUMER data type in target.

*Example* The following is an example of database specific mapping:

```
<mapping>
  <columnInput>real</columnInput>
  <exceptions>
    <exception>
      <sourceDBName>
        <![CDATA[.*(sql).*(server)*.]]>
      </sourceDBName>
      <columnOutput>float</columnOutput>
    </exception>
  </exceptions>
  <columnOutput>NUMBER</columnOutput>
</mapping>
```

In this example, the real data type is mapped to NUMBER for all source databases. However, if the source is a SQL Server database, real is mapped to float.

---

**NOTE** The upload process tries to match sourceDBName in the mapping element to the folder name generated in the /obt/config/dbms directory. For example, the regular expression ".\*(sql).\*(server)\*.\*" is matched with Microsoft\_SQL\_Server\_9\_0.

---

*Example* The following is an example of auto-expansion mapping:

```
<mapping applyRule="VARCHAR2_RULE">
  <columnInput>varchar</columnInput>
  <columnOutput>VARCHAR2</columnOutput>
</mapping>
<propertiesExceptions>
  <propertiesException ruleName="VARCHAR2_RULE">
    <condition minLength="4001">
      <columnOutput>CLOB</columnOutput>
    </condition>
    <condition isLengthSet="false">
      <columnOutput length="20">VARCHAR2</columnOutput>
    </condition>
  </propertiesException>
</propertiesExceptions>
```

In this example, varchar is mapped to VARCHAR2. Also, the ruleName attribute is set to VARCHAR2\_RULE and applies to the mapping. The rule specifies that if the length of varchar exceeds 4000, it is mapped to CLOB.

The propertiesException element is used to create rules. You can apply rules to mapping or exception elements. The condition elements are executed in order. When a condition is met, the data type specified in the columnOutput element is used. No subsequent conditions are applied. The condition element supports the following attributes:

- maxLength
- minLength
- maxPrecision
- minPrecision

- maxScale
- minScale
- isLengthSet
- isPrecisionSet
- isScaleSet

### Creating and editing mapping files

If your database is supported by HP Test Data Management, you do not need to edit or create a mapping file because a mapping file is already provided. However, if a database other than those supported is involved, you need to create and edit a mapping file.

When editing the mapping file, consider the following:

- The schema `dataTypeMapping.xsd` provides the usage information for
  - auto-expanding a target data type based on certain properties.
  - mapping for a specific source database is supported.
  - setting certain target column data type properties.
- The `sourceDBname` and `columnInput` elements can accept a regular expression. Regular expressions should be inside a CDATA section.

To create a mapping file:

- 1 Open a command window and navigate to the directory `<install_directory>/obt/bin`, where `<install_directory>` is the directory where the software is installed.
- 2 Run the script `create_datatype_map`.

On Windows:

```
create_datatype_map.bat
```

On UNIX:

```
create_datatype_map.sh
```

The script connects to target database to create mapping for the source to target column type.

---

**NOTE** Using the `create_database_map` is optional. However, running the script allows you to identify issues with data type mapping before running the upload process.

---

- 3 In a text editor, open the mapping file created by the script and fill in the data types for the target column. Skeleton mapping elements are added to the end of the mapping file.

## Validating the mapping file

To validate your mapping file against the schema (dataTypeMapping.xsd), run the following command:

On Windows:

```
create_datatype_map.bat <mapping_file_name> -v
```

On UNIX:

```
create_datatype_map.sh <mapping_file_name> -v
```

where <mapping\_file\_name> is the name of your mapping file.

## Creating mapping by connecting to the source database

If you want to create data type mapping in your mapping file by connecting to the source database, run the following command:

On Windows:

```
create_datatype_map.bat -f
```

On UNIX:

```
create_datatype_map.sh -f
```

The script connects to the source and target database to create mapping for the source to target column type.

## Behaviors and limitations of a non-intrusive environment

Before creating a non-intrusive environment, review the following behaviors and limitations:

- When deploying a database to file cartridge against a non-intrusive environment, no selection tables are created. Data movement is performed directly from the source environment.
- Because there is no interface schema, Eligibility Analytics are not supported. Also, Validation and File Index are not available. If you specify Validation or File Index in a database to file cartridge, they are ignored when the cartridge is deployed.
- You can upload extracted XML or CSV files. After extracting data from a non-intrusive environment, you can upload the files to any of the supported database platforms.
- Advanced Selection and chaining tables are not supported. If you specify Advanced Selection, cartridge deployment fails.
- Custom selection is supported in non-intrusive environments. However, you must include a SELECT statement against the driving table (rather than an INSERT statement). The SELECT statement must include all columns from the driving table. If all columns are not selected in the driving table, a runtime error occurs when you attempt to deploy the cartridge. The error occurs because the custom SQL is not parsed, and it cannot be determined whether all columns are included at the time of deployment.

## Creating a non-intrusive environment

To create a non-intrusive deployment environment:

- 1 Go to the Environment section of the Web Console
- 2 Click **New**.
- 3 Select Non-intrusive as part of creating environment as described in [Creating an environment](#) (page 45).

Note that for a non-intrusive environment, the user name and password correspond to a user who is able to access and extract data. In a standard environment, the user name and password correspond to the administration user.

## Deploying business flows

Business flows contain the activities that actually perform the movement, copying, and uploading of data, as well as other business logic (Groovy scripts). To run a business flow, you must first deploy and configure it in an environment. You can deploy business flows either from Designer or from the Web Console.

To deploy business flows using the Web Console, they must first be generated by you or someone else in Designer, and the resulting deployment files placed in a location accessible to the Web Console.

---

**NOTE** If you plan to use eligibility analytics, you must enable eligibility analytics in the model for your business flow before deploying, and the model must contain a pause after the selection step. For more information see the *HP Test Data Management Designer User Guide*.

---

- In this section*
- [Deploying business flows](#) (page 56)
  - [Importing business flows](#) (page 58)
  - [Redeploying business flows](#) (page 58)
  - [Removing business flows](#) (page 60)

## Deploying business flows

Generated business flows are zip files with a .busflow extension. By default, business flows are stored in one of the following locations, but you can import .busflow files from other locations as well as described in the following table.

| Location                                                    | Description                                                                                                           |
|-------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------|
| <install_directory>/obt/<br>businessflow                    | Business flows stored in the main business flow directory can be used by all users.                                   |
| <install_directory>/obt/<br>businessflow/<environment_name> | Business flows stored in an environment directory can only be accessed by users who are assigned to that environment. |

where <install\_directory> is the location where you installed the software, and <environment\_name> is the name of the environment.

To deploy a business flow in the Web Console:

- 1 Start the Web Console, if it is not already started.

*See also* [Starting Web Console](#) (page 35)

- 2 Click **Business Flow Deployment** from the menu at the top of the page.

The Business Flow Deployment page displays the business flows located in the default path that are eligible to be deployed or redeployed.

- 3 Select the business flows you want to deploy. You can select more than one if you wish. If you do not see the business flow that you want to deploy, refer to [Importing business flows](#) (page 58).

- 4 Optionally select the **Show latest versions only** checkbox to display the latest versions of all business flows.

- 5 Click **Next**.

If your business flow calls a reload to database cartridge, you are prompted for source and, for distributed instances, target database credentials, and access passwords. Skip directly to [step 7](#).

- 6 Enter the username and password for the source database administrator.

- 7 For distributed instances, enter the username and password for the target database administrator.

- 8 Click **Next**. The Summary page displays.

- 9 Click **Finish** to deploy the business flows. The deployed business flows are stored in the following directory:

```
<install_directory>/obt/artifacts/<environment_name>/  
businessflow/<businessflow_name>/
```

| Parameter         | Description                                                      |
|-------------------|------------------------------------------------------------------|
| install_directory | the location where you installed the software.                   |
| environment_name  | the name of the environment the business flow was deployed into. |
| businessflow_name | the name of the business flow.                                   |

---

**WARNING!** You should never remove the deployment directory or its contents manually from the file system. It must be properly uninstalled from the Web Console. Refer to [Removing business flows](#) (page 60). Otherwise, you will get unexpected results when you try to redeploy, run, or uninstall the business flow.

---

## Importing business flows

If you have no business flows in the default path, you need to import the generated business flows before you can deploy them.

To import a business flow in the Web Console:

- See also*      [Starting Web Console](#) (page 35)
- 1 Start the Web Console, if it is not already started.
  - 2 Click **Business Flow Deployment** from the menu at the top of the page.
  - 3 Click **Import** from the left navigation pane. The Import Business Flows page displays.
  - 4 Select the appropriate radio button:
    - **Path to the Server directory** indicates that you have a path on the server that contains the generated business flows you want to import for deployment.
    - **Business flow file to upload** indicates that you have the generated business flows you want to import for deployment on your client machine.
  - 5 If you chose **Path to the Server directory**:
    - a Enter a path that is valid on the server.
    - b Click **Copy**.

If you chose **Business flow file to upload**:

- a Click **Browse** to navigate to a location on the client machine.
- b Select the generated business flow you want to import.
- c Click **Open**.

The business flows are imported and can now be deployed. Refer to [Deploying business flows](#) (page 56).

## Redeploying business flows

At times, you may need to modify your business flows and their components to account for changes to the database, or business or legal requirements. When you modify the business flow or its components in Designer, you must then redeploy it.

As with a new deployment, if you plan to redeploy business flows using the Web Console, they must first be generated by you or someone else in Designer. You must then place the resulting deployment files placed in a location accessible to the Web Console.

*See also* [Deploying business flows](#) (page 56)

To deploy a business flow in the Web Console:

- 1 Start the Web Console, if it is not already started.

*See also* [Starting Web Console](#) (page 35)

- 2 Ensure that all jobs involving the business flows that you plan to redeploy are in a completed or cancelled state. If the job status is not in a completed or cancelled state, you need to either rerun the job until it completes successfully, or cancel it:

— [Recovering business flows and jobs](#) (page 81)

— [Cancelling business flows and jobs](#) (page 81)

- 3 Click **Business Flow Deployment** from the menu at the top of the page. The Business Flow Deployment page displays the business flows located in the default path that are eligible to be deployed or redeployed.
- 4 Select the business flows you want to redeploy. You can select more than one if you wish. If you do not see the business flow that you want to redeploy, refer to [Importing business flows](#) (page 58).
- 5 Click **Next**. The Job History Retention page displays the previously deployed business flows that would be replaced by the new deployment.
- 6 Select **Drop job history of existing Business Flows** to remove the job history.

The job history enables you to refer to previous runs of the business flow to review information such as parameter settings and job results. Typically, you want to retain this history for reference purposes, but you can drop it if you no longer plan to refer to it.

From this point onward, a redeployment proceeds much like a new deployment. For more information, see [Deploying business flows](#) (page 56). When you complete all of the necessary pages, the Summary page displays.

- 7 Click **Finish** to redeploy the business flows. The redeployed business flows are stored in the following directory:

```
<install_directory>/obt/artifacts/<environment_name>/  
businessflow/<businessflow_name>/
```

| Parameter         | Description                                                      |
|-------------------|------------------------------------------------------------------|
| install_directory | The location where you installed the software.                   |
| environment_name  | The name of the environment the business flow was deployed into. |
| businessflow_name | The name of the business flow.                                   |

---

**WARNING!** You should never remove the deployment directory manually or its contents from the file system. The deployment directory must be properly uninstalled from the Web Console. Otherwise, you will get unexpected results when you try to redeploy, run, or uninstall the business flow. For more information, see [Removing business flows](#) (page 60).

---

## Removing business flows

When you no longer need a particular business flow, you can use the Web Console to remove (uninstall) it. You should never remove a business flow manually from the file system. You should always uninstall it from the Web Console. Otherwise, you will get unexpected results when you try to redeploy, run, or uninstall the business flow.

To remove a business flow:

- See also*      [Starting Web Console](#) (page 35)
- 1 Start the Web Console, if it is not already started.
  - 2 Ensure that all jobs involving the business flows that you plan to remove are in a completed or cancelled state. If the job status is not in a completed or cancelled state, you need to either rerun the job until it completes successfully, or cancel it:
    - [Recovering business flows and jobs](#) (page 81)
    - [Cancelling business flows and jobs](#) (page 81)
  - 3 Click **Business Flow Deployment** from the menu at the top of the page.
  - 4 Click **Uninstall** from the left navigation pane. The Business Flow Uninstall page displays the business flows that are eligible to be removed.
  - 5 Select the business flows you want to remove.
  - 6 Select **Drop job history of existing Business Flows** to remove the job history.

The job history enables you to refer to previous runs of the business flow to review information such as parameter settings and job results. Typically, you want to retain this history for reference purposes, but you can drop it if you no longer plan to refer to it.
  - 7 Click **Next**.
  - 8 Enter the username and password for the source database administrator.
  - 9 For distributed instances, enter the username and password for the target database administrator.
  - 10 Click **Next**. The Summary page displays.
  - 11 Click **Finish** to remove the business flows.

# Configuring parameters

Before you run business flows, you should review and configure the parameters that govern execution. HP Test Data Management provides parameters at the following levels:

- At the database to file level, you configure parameters that apply to all database to file business flows and cartridges. For a listing of all of these parameters, see [Appendix A, Configuration and runtime parameters](#).
- At the business flow level, you configure the user-defined configuration parameters created in Designer, and those parameters apply to all business flows. For more information, see the *HP Test Data Management Designer User Guide*.
- At the cartridge level, you configure parameters that apply to the particular instance of the cartridge, and override the value of the database to file level parameter. If the same cartridge belongs to more than one business flow, each instance of the cartridge can have different parameter values.

*In this section*

- [Configuring database to file parameters](#) (page 61)
- [Configuring user-defined business flow parameters](#) (page 61)
- [Configuring cartridge parameters](#) (page 62)

## Configuring database to file parameters

To set database to file parameters:

- See also*
- 1 Start the Web Console, if it is not already started.  
[Starting Web Console](#) (page 35)
  - 2 Click **Parameters** from the menu at the top of the Web Console.
  - 3 Click **Database to File** from the left navigation pane. The Parameters - Database to File page displays.
  - 4 Review and change the parameter values as appropriate. The parameter values are listed in [Appendix A, Configuration and runtime parameters](#).
  - 5 Click **Apply** to save the parameters.

## Configuring user-defined business flow parameters

In Designer, you can create configuration parameters that are used as part of a business flow that is deployed into a particular environment. These parameters appear on the business flow level of the Parameters - Business Flows page. If no user-defined configuration parameters were created for your business flows, this page is empty.

For more information on user-defined parameters, see the *HP Test Data Management Designer User Guide*, or contact your extraction developer.

- 1 Start the Web Console, if it is not already started.

*See also* [Starting Web Console](#) (page 35)

- 2 Click **Parameters** from the menu at the top of the Web Console.
- 3 Click **Business Flows** from the left navigation pane, then click on **Global BF Settings** or a specific business flow name.
- 4 Change the parameter values as appropriate.
- 5 Click **Apply** to save the parameters.

## Configuring cartridge parameters

The cartridge level parameters apply to one instance of the selected cartridge, and are displayed on the Cartridge Configuration page. Except for the file naming parameters, all cartridge level parameters are a subset of the component level parameters listed in [Appendix A, Configuration and runtime parameters](#).

Because file naming parameters create the naming convention for each individual database to file cartridge, they can only be selected on the cartridge parameter pages.

- 1 Start the Web Console, if it is not already started.

*See also* [Starting Web Console](#) (page 35)

- 2 Click **Parameters** from the menu at the top of the Web Console.
- 3 Click **Cartridges** from the left navigation pane.

The Parameters - Cartridges page displays.

- 4 Select the cartridge you want to configure.
- 5 Change the parameter values as appropriate.

The parameter values are listed in [Appendix A, Configuration and runtime parameters](#).

- 6 Click **Apply** to save the parameters.

## Managing locations

For business flows to run correctly, each environment must have a number of locations associated with it, for example, source database locations and credentials, and a file system path. Locations are initially specified during installation and automatically loaded into the Web Console. You can then view and manage all of these locations from the Web Console.

---

**NOTE** If passwords are changed for any of your database to file schemas or databases, you must edit the location and change the password.

---

---

**TIP** While you can update location credentials within the Web Console, to ensure security, you cannot change the encryption key for an environment from the Web Console. To change the encryption key, use the Password Manager utility. For more information, see [Using password manager to change the encryption key](#) (page 102).

---

*In this section*

- [Viewing locations](#) (page 63)
- [Changing locations and updating passwords](#) (page 64)
- [Adding locations for database to file](#) (page 64)
- [Deleting locations](#) (page 66)

## Viewing locations

You can use the Web Console to view locations for an environment.

- 1 Start the Web Console, if it is not already started.

*See also*

[Starting Web Console](#) (page 35)

- 2 Click **Environment** from the menu at the top of the page. The active environment is displayed in the left navigation pane.

---

**TIP** By default, the Locations page displays the locations for the currently active environment. If you want to view the locations for an environment other than the currently active one, select the environment and click **Set Active**.

---

- 3 Click **Locations** from the left navigation pane. The Web Console displays a list of the existing locations.
- 4 Select the radio button next to a location to view the details for that location.

---

| Location name    | Description                                                               |
|------------------|---------------------------------------------------------------------------|
| DELETE_IDX_FS    | The path of the delete index.                                             |
| LOCAL_EXTRACT_FS | The path where database to file stores extracted XML or CSV files.        |
| LOCAL_TEMP_FS    | The path of the temporary file space.                                     |
| OBTINTF_DB       | The database location and credentials where the interface schema resides. |
| OLTP_DB          | The source (active) database location and credentials.                    |

---

## Changing locations and updating passwords

If you need to change a location, such as the extracted file location, or update a location's credentials, for example, the source database's password, you can do so from the Web Console.

To change a location or update passwords:

- 1 Follow the instructions in [Viewing locations](#) (page 63) to display the location that you want to modify.
- 2 Change the location properties as appropriate.
- 3 Click **Apply**.
- 4 For database to file with a distributed instance, if you changed the history relocation schema or database password:
  - a Log in to the active database as the interface user, for example, OBT\_IF.
  - b Drop the database link that points to the history relocation schema or database. This link was created when you deployed the business flow.
  - c Re-create the database link with the same name.
- 5 For database to file with a distributed instance, if you changed the OLTP interface schema or database password:
  - a Log in to the history database as the relocation user, for example, OBT\_RELOC.
  - b Drop the database link that points to the OLTP interface schema or database. This link was created when you deployed the business flow.
  - c Re-create the database link with the same name.

## Adding locations for database to file

In some cases, you may wish to add additional locations for database to file extraction. For example, in some cases you may wish to create structured data files on your file system.

To add locations:

- 1 Follow the instructions in [Viewing locations](#) (page 63) to display the location that you want to modify.
- 2 Select the **New** radio button.
- 3 Enter the name to assign to the location. The location name is case sensitive.
- 4 Select the type from the list of values.
  - [Oracle, SQL Server, or DB2, Sybase](#) (page 65)
  - [URL](#) (page 65)
  - [Filesystem](#) (page 65)

### Oracle, SQL Server, or DB2, Sybase

- a Enter or select values for the location properties:

| Field            | Expected value                                                                                  |
|------------------|-------------------------------------------------------------------------------------------------|
| Host             | Required.<br>Enter the database server name or the database IP address.                         |
| Port             | Required.<br>Enter the database listener port number.                                           |
| Database Service | Required.<br>(Sybase only)<br>Enter the case sensitive Oracle SID or SQL Server DB Server name. |
| Database Name    | (SQL Server, Sybase, and DB2 only)<br>Enter the case sensitive database name.                   |
| User ID          | Required.<br>Enter the case sensitive name of the user who owns the location.                   |
| Password         | Required.<br>Enter the case sensitive password for the user you selected.                       |
| Driver Type      | Required.<br>Select the JDBC driver type from the list of values.                               |
| Connection Type  | Required.<br>Select the connection type from the list of values.                                |

### URL

- a Enter values for the location properties:

| Field         | Expected value                                                                |
|---------------|-------------------------------------------------------------------------------|
| URL           | Required. Enter the JDBC URL.                                                 |
| User ID       | Required.<br>Enter the case sensitive name of the user who owns the location. |
| Password      | Required.<br>Enter the case sensitive password for the user you selected.     |
| Database Name | (SQL Server and Sybase only)<br>Enter the case sensitive database name.       |

### Filesystem

- a Enter a description for your location.
- b Enter the absolute directory location of the file.

- 5 Click **Apply**. The new location is created.
- 6 When you launch a business flow containing a database to file cartridge, choose the new location from the Destination Location list of values.

## Deleting locations

You can delete database to file extraction locations that you added to the environment. Locations that were created by the HP Test Data Management cannot be deleted.

To delete a location:

- 1 Follow the instructions in [Viewing locations](#) (page 63) to display the location that you want to modify.
- 2 Select the location you want to delete.
- 3 Click **Delete**. The location is deleted from the environment.

## Refreshing test environments

If you are maintaining a test environment that you use to design and test your models, cartridges, and business flows, you need to periodically refresh it from your production environment. For example, if the production schema has changed or been upgraded in some way, you need to reflect those changes in your test environment. You can duplicate changes to the production environment in your test environment without reinstalling HP Test Data Management.

### *Prerequisites*

For this process to work, your environments must meet the following criteria:

- Both environments must use the same version and configuration of Test Data Management.
- Both environments must use the same version and configuration of Oracle. This procedure only applies to Oracle databases.
- At least one extract job must have already completed in the production environment that you are cloning.

To refresh your test environment:

- 1 In the test environment, clone the following databases from the production environment:
  - the active (source) databases
  - the repository databases
- 2 In the cloned databases, update any database links to use the test environment's host names, port numbers, and so on. Otherwise, the database links will continue to resolve to the production databases rather than the test databases.
- 3 Navigate to the following directory:

<install\_directory>\obt\foundation\components\replicate  
where <install\_directory> is the location where you installed Test Data Management.

- 4 Create a text file for the environment properties. The default name for this file is replicate.properties, which is defined in replicate\_environment.xml as <property name="properties.file" value="replicate.properties" />.

The file must contain the following properties:

| Property                     | Description                                                                       |
|------------------------------|-----------------------------------------------------------------------------------|
| env1.product.path            | The path of the original environment.                                             |
| env1.repository.password     | The repository password for the original environment.                             |
| env1.encryption.key          | The encryption key for the original environment.                                  |
| env2.encryption.key          | The encryption key to be used for the duplicate environment.                      |
| env2.product.path            | The path to be used fro the duplicate environment.                                |
| env2.source.dbadmin.password | The database administrator password for the source database.                      |
| env2.source.dbadmin.userid   | The database administrator username for the source database.                      |
| env2.repository.password     | The repository password for the duplicate environment.                            |
| env2.interface.password      | The password for the interface user.                                              |
| env2.source.password         | The password for the interface user (for example, obt_if) on the source database. |
| env2.source.host             | The host name for the source database.                                            |
| env2.source.server           | The source database name.                                                         |
| env2.source.port             | The port number for the source database (for example, 1522).                      |
| env2.repo.host               | The host name for the repository database.                                        |
| env2.repo.server             | The repository database name.                                                     |
| env2.repo.port               | The port number for the repository database (for example, 1522).                  |

| Property            | Description                                                                                             |
|---------------------|---------------------------------------------------------------------------------------------------------|
| environment.id      | The name of the old environment from which this procedure is refreshed.                                 |
| configuration       | The environment's configuration. Set to OAt to indicate that the environment has only database to file. |
| repository.username | The repository user name, for example, obt_rep.                                                         |

*Database to file  
environment example*

```
env1.product.path=C:\\program files\\HPTDM\\obt
env1.repository.password=obt_rep2
env1.encryption.key=q2
```

```
env2.encryption.key=q2
env2.product.path=E:\\program files\\HPTDM\\obt
env2.source.dbadmin.password=manager
env2.source.dbadmin.userid=system
env2.hist.dbadmin.password=manager
env2.hist.dbadmin.userid=system
env2.repository.password=obt_rep2
env2.interface.password=obt_if2
env2.transparency.layer.password=obt_build_aa2
env2.transparency.layer.location=source
env2.relocation.interface.password=obt_reloc2
env2.source.password=obt_if2
env2.source.host=localhost
env2.source.server=orcl2
env2.source.port=1522
env2.repo.host=localhost
env2.repo.server=orcl2
env2.repo.port=1522
```

```
repository.username=obt_rep
```

**5** Run the appropriate script for your operating system:

| Platform | Syntax                                          |
|----------|-------------------------------------------------|
| UNIX     | <install_dir>/obt/bin/replicate_environment.sh  |
| DOS      | <install_dir>\obt\bin\replicate_environment.bat |

**NOTE** Remotely copying the production environment to another server on Unix is not supported.

- 6 To replicate more than one environment from the same production instance, repeat [step 3](#) (page 66) through [step 5](#) (page 68) with the following modifications:
  - The repository password and encryption key of the first environment should be changed to that of the new environment because they will have already been updated in the first run of `replicate_environment.bat`.
  - If the database links have to be renamed, set `replace.dblink` to `true` and provide the new link names.



In Web Console, you can create multiple users and provision them with various privileges depending upon their role. For example, some users might only need to run jobs while others may need to deploy business flows, set parameter values, and run jobs. In this way, you can secure access to the Web Console and its various environments.

*In this section*

- [Understanding privileges](#) (page 71)
- [Adding Web Console users](#) (page 72)
- [Editing Web Console users](#) (page 73)
- [Managing your user account](#) (page 74)
- [Setting up email access from the Web Console](#) (page 75)

## Understanding privileges

You can grant or withhold the following privileges for Web Console users:

| Privilege                   | Description                                                                                                                                        |
|-----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| Administer                  | Has full access to all Web Console functionality. The Console Administrator user created during repository installation has Administer privileges. |
| Manage Users                | Can create, edit, and delete Web Console users, and grant or revoke permissions for users to access environments.                                  |
| Manage Environments         | Can create and edit environments and locations, and grant permissions for users to access an environment.                                          |
| Deploy Business Flows       | Can deploy business flows directly into the environments they have access to.                                                                      |
| Run Jobs                    | Can run business flows and other Test Data Management jobs.                                                                                        |
| Deploy and Execute Remotely | Can launch and schedule jobs through Web services. For example, deploying into an environment from Designer using a remote connection.             |
| Access Data                 | Can monitor business flows and view eligibility analytics data.                                                                                    |

| Privilege                     | Description                                                                                                                                                                                                                                      |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Access System Parameters      | <p>Can set database to file configuration parameters that apply to all cartridges.</p> <p>Can set database to file configuration parameters at the cartridge level.</p> <p>Cannot set business flow parameters, but can view the parameters.</p> |
| Access Application Parameters | <p>Can set configuration parameters at the cartridge level.</p> <p>Can set business flow parameters.</p> <p>Cannot set database to file configuration parameters that apply to all cartridges, but can view the parameters.</p>                  |

## Adding Web Console users

After you have created an environment, you can create new users in the Web Console. Each user can have different privileges and be granted permissions for different environments.

- 1 Start the Web Console, if it is not already started.

*See also* [Starting Web Console](#) (page 35)

- 2 Click **Users** from the menu at the top of the page. The User List page displays. If you have not previously created any other users, you should only see the administrator user.
- 3 Click **New User**. The Create User page displays.
- 4 Enter the following values:
  - Login Name:
  - Full Name:
  - Password:
- 5 Select the Enabled checkbox to enable the user.
- 6 Optionally, enter the following values:
  - Description:
  - Email:
  - Phone:
- 7 Assign the appropriate privileges to the user.
- 8 Assign environments to the user.
- 9 Click **Create**. The Show User page displays the user information.

*See also* [Understanding privileges](#) (page 71)

## Editing Web Console users

Users with the Administer or Manage Users privilege can edit all existing Web Console users, and can delete or disable all users but themselves.

- See also*      [Starting Web Console](#) (page 35)
- 1 Start the Web Console, if it is not already started.
  - 2 Click **Users** from the menu at the top of the page. The User List page displays.
  - 3 Select the user you want to edit. The Edit User page displays the values and privileges you assigned to the user.
  - 4 Update the values as appropriate.
  - 5 Click **Update** to save the changes.
  - 6 Click **Delete** to delete the user.

---

**TIP** You can deselect the Enabled checkbox to disable the user without deleting the user information.

---

The Show User page displays the updated user information.

## Enabling environment access

Users with the Administer or Manage Environment privilege can grant or revoke authorization to different environments.

To grant or revoke access to an environment:

- 1 Click **Environment** from the menu at the top of the page. The active environment is displayed in the left navigation pane.

---

**TIP** If you want to view the authorizations for an environment other than the currently active one, select the environment and click **Set Active** before proceeding.

---

- 2 Click **Authorizations** from the left navigation pane. The Environment Authorizations page displays.
- 3 To add a user, select one from the list of values.
- 4 Click **Add** to add the user.
- 5 To remove an existing user, click **Remove** next to the user name.

---

**NOTE** Users with the Manage Users privilege can grant users access to an environment from the Edit User page. See [Editing Web Console users](#) (page 73).

---

# Managing your user account

Each Web Console user can manage certain settings for their own account.

---

**NOTE** Only the currently logged in user can change their individual settings this way.

---

- In this section*
- [Updating personal information](#) (page 74)
  - [Changing your password](#) (page 74)
  - [Managing email subscriptions](#) (page 75)

## Updating personal information

On the User Information page, you can update your personal information.

To update your personal information:

- See also*      [Starting Web Console](#) (page 35)
- 1 Start the Web Console, if it is not already started.
  - 2 Click **Settings** from the menu at the top of the page.
  - 3 Click **Information** from the left navigation pane. The User Information page displays.
  - 4 Optionally, enter your real name.  
This name appears in the title bar.
  - 5 Optionally, enter a description.
  - 6 Optionally, enter an email address.
  - 7 Optionally, enter a phone number.
  - 8 Click **Apply**. The new user information is saved.

## Changing your password

On the Change Password page, you can change the Web Console password.

To change your password:

- See also*      [Starting Web Console](#) (page 35)
- 1 Start the Web Console, if it is not already started.
  - 2 Click **Settings** from the menu at the top of the page.
  - 3 Click **Information** from the left navigation pane.  
The Change Password page displays.
  - 4 Enter the old password.
  - 5 Enter the new password.

- 6 Confirm the new password.
- 7 Click **Apply**.  
The new password is saved.

## Managing email subscriptions

On the Subscriptions page, you can manage when you receive automatic email notifications.

---

**NOTE** If the system is not configured to send email, see [Enabling SQL trace for Oracle](#) (page 181).

---

*See also*

- 1 Start the Web Console, if it is not already started.  
[Starting Web Console](#) (page 35)
- 2 Click **Settings** from the menu at the top of the page.
- 3 Click **Subscriptions** from the left navigation pane.  
The Subscriptions page displays.
- 4 Select the check boxes for the automatic email that you want to receive.
- 5 Clear the check boxes for the automatic email that you do not want.
- 6 Click **Apply**. Your email subscription information is updated.

## Setting up email access from the Web Console

Before you can send email using the Web Console, you need to configure the Server Email settings.

*See also*

- 1 Start the Web Console, if it is not already started.  
[Starting Web Console](#) (page 61)
- 2 Click **Settings** from the menu at the top of the page.
- 3 Click **Server Email** from the left navigation pane.  
The Email Settings page displays.
- 4 To require authentication, select **Authentication Required**.
- 5 Enter the email settings.

| Setting             | Description                                                                                                                          |
|---------------------|--------------------------------------------------------------------------------------------------------------------------------------|
| Server URL          | The URL for the server where the Web Console is running. This is the URL that other machines need to connect to the Web Console.     |
| Host                | The host name of the server where the Web Console is running.                                                                        |
| Port                | The port number used to connect to the Web Console.                                                                                  |
| User Name           | The user name use to log in to the server where the Console is running.                                                              |
| Password            | The password needed to connect to the server. This field is visible only if you selected <b>Authentication Required</b> .            |
| From                | The email associated with the user of the server where the Web Console is running.                                                   |
| Additional Settings | Enter any additional settings needed to connect to the server where the Web Console is running, such as SMTP socketFactory settings. |

6 Click **Apply**.

## 6

# Running business flows and jobs from the Web Console

HP Test Data Management uses business flows to run your logic for copying test data from the database. After copying, the post-copy jobs allow you to view and manipulate your data. After copying data to structured files, you can enable transparent access to your test data. After copying to file, you can query against, view, and relocate the XML data.

*In this chapter*

- [Before you begin](#) (page 77)
- [Running business flows](#) (page 77)
- [Scheduling jobs](#) (page 79)
- [Recovering or cancelling business flows and jobs](#) (page 80)
- [Accessing the extracted data](#) (page 82)

## Before you begin

Before you run business flows, you should perform some preparatory checks, for example, confirming parameter settings. Remember, before you can run a business flow, you must deploy it.

## Running business flows

To run a business flow from the Web Console:

- 1 Start the Web Console, if it is not already started.
- 2 Perform any needed preparatory checks and steps. Refer to [Before you begin](#) (page 77).
- 3 Click **Launch** from the menu at the top of the page. The Business Flows page displays the list of deployed business flows you can run.

*See also*

[Starting Web Console](#) (page 35)



- 4 Select the business flow you want to run. The Job Launch page displays for the selected business flow.

The screenshot shows the HP Test Data Management web console. The top navigation bar includes the HP logo, the application name 'HP Test Data Management', the environment 'Oracle OLTP', the user 'admin', and a 'Logout' button. Below the navigation bar is a menu with 'Monitoring', 'Launch', 'Parameters', 'Business Flow Deployment', 'Environment', 'Users', and 'Settings'. The 'Launch' menu is expanded, showing 'Launch' and 'Orders\_D2F\_BF\_1'. Below the menu is a row of buttons: 'Run', 'Schedule', 'Definition', and 'Advanced'. The main content area is titled 'Job Launch - Orders\_D2F\_BF\_1' and contains a section for 'Runtime Parameters'. This section has a label 'Min\_Months\_to\_Retain:' followed by a dropdown menu showing the value '24'.

- 5 Enter or select the values for the runtime parameters.

---

**TIP** If the parameter value is left blank, and a default value was defined in Designer, then the default value is used. If there is no default value, then NULL is used.

---

- 6 Optionally click **Definition** to view the business flow definition page.
- 7 Click **Back** to return to the Job Launch page.
- 8 Optionally click **Advanced** to view the following sections:
  - Command Line—displays the correct job syntax for the parameter values entered. You can copy the text directly if you plan to run the job from the command line.
  - Business Flow Parameters—displays any business flow parameters that exist for the business flow. The user-defined business flow parameters are created in Designer as configuration parameters, and can be modified using the Parameters - Business Flows page.
  - Dynamic Parameters—displays any dynamic parameters that exist for the business flow. Dynamic parameters are created in Designer and the values are set during deployment.
- 9 Click **Run** to run the job immediately.

---

**TIP** If you prefer to schedule the job for a later time rather than run it immediately, refer to [Scheduling business flows](#) (page 79).

---

- 10 Click **Confirm** to confirm the job.
- 11 Optionally, you can monitor the job status. Refer to [Chapter 8, Monitoring jobs](#).

# Scheduling jobs

In addition to running jobs immediately, you can use the Web Console to schedule business flows and jobs, view the existing scheduled jobs, and alter the schedule.

*This section includes*

- [Scheduling business flows](#) (page 79)
- [Editing scheduled business flows](#) (page 79)

## Scheduling business flows

To schedule a business flow:


- See also* [Starting Web Console](#) (page 35)
- 1 Start the Web Console, if it is not already started.
  - 2 Perform any needed pre-flight checks and preparatory steps. Refer to [Before you begin](#) (page 77).
  - 3 Click **Launch** from the menu at the top of the page. The Business Flows page displays the list of business flows you can run.
  - 4 Select the business flow you want to run.
  - 5 Enter or select the values for the runtime parameters.
  - 6 Click **Schedule**. The Schedule Job Launch page displays.
  - 7 Enter a title and optional description for the business flow.
  - 8 Make sure **Enabled** is checked to enable the job for running.
  - 9 Choose how often you want the business flow to run:
    - **Run Once** means you want to run the business flow once at a specified date and time. Enter the date and time you want the job to run.
    - **Monthly** means that you want to run the business flow once per month. Choose a day of the month and enter the time you want the job to run.
    - **Weekly** means that you want to run the business flow once per week. Choose a day of the week and enter the time you want the job to run.
    - **Daily** means that you want the business flow to run once per day. Enter the time you want the job to run.
  - 10 Click **Parameters** to ensure the parameters you choose are correct.
  - 11 Click **Save** to save the scheduled business flow.

## Editing scheduled business flows

You can view a list of all scheduled jobs, and edit or delete any of them.

- See also* [Starting Web Console](#) (page 35)
- 1 Start the Web Console, if it is not already started.
  - 2 Click **Launch** from the menu at the top of the page.

- Click **Schedule** from the left navigation pane. The Scheduler displays the list of scheduled jobs.



The screenshot shows the HP Test Data Management web console. The top navigation bar includes 'Monitoring', 'Launch', 'Parameters', 'Business Flow Deployment', 'Environment', 'Users', and 'Settings'. The 'Launch' tab is active, and the 'Schedule' sub-tab is selected. Below the navigation bar, the title 'List of Jobs added to Scheduler' is displayed. A table lists the scheduled jobs with columns for Title, Business Flow, Node, Status, and Next Launch Time. Two jobs are listed: 'MonthlyJobRun - D2F' and 'WeeklyJobRun', both associated with 'Orders\_D2F\_BF\_1' and 'amurray10' node, with status 'Running' (green dot) and next launch times of '2010-10-01 23:59:00.0' and '2010-09-24 23:59:00.0' respectively.

| Title               | Business Flow   | Node      | Status  | Next Launch Time      |
|---------------------|-----------------|-----------|---------|-----------------------|
| MonthlyJobRun - D2F | Orders_D2F_BF_1 | amurray10 | Running | 2010-10-01 23:59:00.0 |
| WeeklyJobRun        | Orders_D2F_BF_1 | amurray10 | Running | 2010-09-24 23:59:00.0 |

- Click the Title of a job to edit it. The Schedule page displays.
- Edit the values as desired.
- Click **Save** to save the edited values for the scheduled job.

---

**TIP** To delete a job, click **Delete**.

---

## Recovering or cancelling business flows and jobs

In general, it is best practice to never leave a business flow or job in one of the following states:

- Failed
- Suspended
- Not Responding

Otherwise, you may get unexpected results when you attempt to run the same or other, related business flows, or re-deploy the business flow.

---

**TIP** To check the status of a business flow or job, see [Viewing a job overview](#) (page 91).

---

If a business flow does not complete successfully, you can use the Web Console to:

- Recover it.** Recovering the job or business flow reruns it using the same parameters as the first run. If possible, recovering is the best option.
- Cancel it.** Cancelling the job or business flow should be your option of last resort. If you cannot recover for some reason and you need to redeploy the business flow, you can cancel the business flow. Cancelling updates the status of the business flow or job, but does not clean up any of the selection tables. Consequently, cancelling a job can lead to inconsistent results.

---

**WARNING!** If a business flow containing an advanced selection database to file cartridge does not complete successfully, see the troubleshooting guide for further information before rerunning the business flow.

---


## Recovering business flows and jobs

To recover a business flow or job:

- 1 Start the Web Console, if it is not already started.
- 2 Click **Monitoring** from the menu at the top of the page.
- 3 Select a business flow in Failed, Suspended, or Not Responding status.

See also


[Starting Web Console](#) (page 35)



The screenshot shows the HP Test Data Management Web Console interface. The top navigation bar includes 'Monitoring', 'Launch', 'Parameters', 'Business Flow Deployment', 'Environment', 'Users', and 'Settings'. The left sidebar has links for 'Overview', 'Commands', 'History', 'Logs', 'Global', and 'DB2 OLTP'. The main content area is titled 'Business Flow Status' and contains a table with the following data:

| Business Flow        | Rows | Status    | Start Time           | End Time             |
|----------------------|------|-----------|----------------------|----------------------|
| Orders_Model_D2F_BF  |      | FAILED    | 29-Sep-2010 11:08:30 | 29-Sep-2010 11:08:30 |
| Orders_Schema_D2F_BF | 1    | COMPLETED | 29-Sep-2010 09:34:10 | 29-Sep-2010 09:34:10 |

The Run Details page displays.



The screenshot shows the 'Run Detail for Orders\_Schema\_D2F\_BF' page. The top navigation bar is the same as the previous screenshot. The left sidebar has links for 'Home', 'Monitoring', 'Business Flow 61', 'Overview', 'Commands', 'History', 'Logs', 'Global', and 'DB2 OLTP'. The main content area has tabs for 'Command', 'Other Runs', 'Job Parameters', 'Eligibility Analytics', and 'Row Counts'. The 'Command' tab is selected, showing a table with the following data:

| Task                                                             | Rows | Status    | Start T |
|------------------------------------------------------------------|------|-----------|---------|
| Business Flow: Orders_Schema_D2F_BF                              | 1    | COMPLETED | 29-Sep  |
| Script: PreGroovyTask                                            |      | Processed | 29-Sep  |
| Cartridge BUNIT001: Archive Selection Step                       | 0    | COMPLETED | 29-Sep  |
| Cartridge BUNIT001: Copy by selection from database to backend   | 1    | COMPLETED | 29-Sep  |
| Cartridge BUNIT001: Archive Cleanup Step                         |      | COMPLETED | 29-Sep  |
| Cartridge COMPLAN001: Archive Selection Step                     | 0    | COMPLETED | 29-Sep  |
| Cartridge COMPLAN001: Copy by selection from database to backend | 0    | COMPLETED | 29-Sep  |

- 4 Click **Recover**. The recovery job starts.
- 5 Click **Monitoring** to view the status of the job. If the recovery is successful, the job status changes to COMPLETED. If the recovery is unsuccessful, you need to cancel the job.

## Cancelling business flows and jobs

To cancel a business flow or job:

- 1 If the job to be cancelled is a database to file job that employed table parallel movement, then you must perform the following steps to cleanup incomplete transactions before proceeding:
  - a Identify the rows that needs to be deleted from History by running the following Groovy script:

```
<install_dir>/obt/scripts/generateLaCleanupStmts.groovy
```

The script generates delete statements with the appropriate row ranges specified.
  - b Manually run the delete statements against the history tables in the target database.

- 2 Start the Web Console, if it is not already started.

*See also*

[Starting Web Console](#) (page 35)

- 3 Click **Monitoring** from the menu at the top of the page.
- 4 Select a business flow in Failed, Suspended, or Not Responding status.

| Business Flow        | Rows | Status    | Start Time           | End Time             |
|----------------------|------|-----------|----------------------|----------------------|
| Orders_Model_D2F_BF  | 1    | FAILED    | 29-Sep-2010 11:08:30 | 29-Sep-2010 11:08:30 |
| Orders_Schema_D2F_BF | 1    | COMPLETED | 29-Sep-2010 09:34:10 | 29-Sep-2010 09:34:10 |

The Run Details page displays.

| Task                                                             | Rows | Status    | Start T |
|------------------------------------------------------------------|------|-----------|---------|
| Business Flow: Orders_Schema_D2F_BF                              | 1    | COMPLETED | 29-Sep  |
| Script: PreGroovyTask                                            | 0    | Processed | 29-Sep  |
| Cartridge BUNIT001: Archive Selection Step                       | 0    | COMPLETED | 29-Sep  |
| Cartridge BUNIT001: Copy by selection from database to backend   | 1    | COMPLETED | 29-Sep  |
| Cartridge BUNIT001: Archive Cleanup Step                         | 0    | COMPLETED | 29-Sep  |
| Cartridge COMPLAN001: Archive Selection Step                     | 0    | COMPLETED | 29-Sep  |
| Cartridge COMPLAN001: Copy by selection from database to backend | 0    | COMPLETED | 29-Sep  |

- 5 Click **Cancel Job**.
- 6 Click **Monitoring** to view the status of the job. The job status will change to CANCELLED.

## Accessing the extracted data

After you copy your test data to a file, you still need to access it. From the Web Console, you can perform a variety of operations to facilitate access to the copied data:

- For database to file, you may relocate, copy, or delete the copied data from the Web Console.
- This section includes*
- [Relocating extracted data](#) (page 82)
  - [Accessing the structured data file](#) (page 84)

## Relocating extracted data

After you copy from database to file, you can relocate or copy the data to a variety of locations:

- another database

- another file location

To relocate data extracted to file from the Web Console:

- 1 Start the Web Console, if it is not already started.

*See also* [Starting Web Console](#) (page 35)

- 2 Click Launch from the menu at the top of the Web Console.
- 3 If you have extracted many times to file and your files are quite extensive, you probably need to select **Query** from the left navigation pane to query the indexes to find the exact data you want to relocate. Otherwise, you can select **Relocate** to see all of the available XML or CSV files.

---

**TIP** If you choose **Relocate**, you can use the date range search on the left navigation pane to narrow your choices. The date range search uses the format, mm/dd/yy hh:mm:ss AM/PM.

---

To perform a query:

- a The Database to File Queries page displays the available indexes from each installed cartridge.
- b Select the index you want to query. The query screen for the selected index displays.
- c Enter values on which to query or leave the parameter fields blank to query on all values.
- d Click **Run Query**. The cartridge runs that match the query display at the bottom of the page.

---

**NOTE** If you have not run a database to file extraction business flow at least once before querying, your extraction is empty and no rows are returned by the query.

---

- 4 Select the cartridge run that you wish to relocate and choose one of the following options:

---

**NOTE** The available options may vary slightly depending upon whether you chose **Relocate** or **Query** in [step 3](#) (page 83).

---

- **Refresh** to refresh the list.
- **Lineage Details** displays more detailed history of the file.
- **Upload** uploads the data to a different database, checks for missing schema objects, and creates any schema objects that are missing. Refer to [Schema mapping for upload](#) (page 84) if you want to map the extracted data into a schema name that is different from the source.

---

**NOTE** An upload operation is considered a copy operation for row counts. For example, coping selected x rows then uploading the rows, results in a count of 2x rows. To prevent a double row count, you can put the upload in a separate business flow.

---

---

**TIP** If you are planning to upload from an extraction file generated against Oracle to SQL Server, you should explicitly set the precision and scale on numeric columns, where appropriate, in the source database. Otherwise, if SQL Server has more restrictive precision and scale settings than Oracle, the upload may fail.

---

- **Copy** copies the data to an additional location.
  - **Move** moves the data to a new location and delete it from the current location.
  - **Delete from Backend** deletes the data from a backend. That is, the file location.
- 5 If prompted, select the location where you want to move or copy the data.

---

**TIP** If you do not see the location to which you want to relocate the data, you can create additional locations for the environment.

---

- 6 Click **Confirm** or **Cancel**.

## Schema mapping for upload

When uploading from a structured data file to a database, you may want to perform some level of schema mapping. Doing so enables you to upload into a different schema name than the one from which you copied the data. For example, if you copied from a SQL Server database and are uploading to an Oracle database, you may prefer to use a different schema name.

To create and use a schema mapping for your database to file cartridges:

- 1 Create a schema mapping file in a location that is accessible to your Test Data Management instance. The contents of the mapping file should adhere to this format:  
  
`<src_db>.<src_schema>=<target_db>.<target_schema>`  
or, if the databases are heterogeneous, you might use this format instead:  
  
`<src_db>.<src_schema>=<target_schema>`
- 2 In the Web Console, click **Parameters** from the menu at the top of the page.
- 3 In the left navigation area, click **Cartridges**.
- 4 Scroll down until you find the parameter named **Schema Mapping File for Upload**.
- 5 Enter the path and name of the schema mapping file that you created in [step 1](#).

## Accessing the structured data file

To access contents of your structured data files, you use the query server. Refer to [Chapter 10, Using the query server to access extracted data files](#).

# Running business flows and jobs from the command line

To provide additional flexibility, HP Test Data Management enables you to run business flows and jobs from the command line as well as from the Web Console. This capability is useful for environments where you cannot easily access the Web Console or need to script the running of business flows or jobs.

*In this chapter*

- [Before you begin](#) (page 85)
- [Running business flows](#) (page 86)
- [Recovering and cancelling business flows and jobs](#) (page 87)
- [Accessing the copied data](#) (page 89)

## Before you begin

Before you run business flows, you should perform some preparatory checks; for example, confirming parameter settings. Beyond that, certain types of business flows require that you perform preparatory tasks before running them.

- The preparatory tasks for running business flows from the Web Console also apply to running on the command line. For more information, see [Running business flows and jobs from the Web Console](#) (page 77).
- In order to run business flows or jobs from the command line, you may need some or all of the following information, which can be obtained from reviewing the deployed business flows in the Web Console:
  - environment name
  - environment ID
  - business flow name
  - job parameters
  - job name
  - job run ID
  - destination location

## Running business flows

To run business flows or jobs from the command line:

- 1 Make sure that you have performed the relevant tasks from [Before you begin](#) (page 85).
- 2 Open a command window.
- 3 Navigate to the following directory:  
`<install_directory>/obt/bin`  
where `<install_directory>` is the location where you installed the software.
- 4 Run the business flow using the appropriate syntax:

| Platform | Syntax                                                                                                                   |
|----------|--------------------------------------------------------------------------------------------------------------------------|
| UNIX     | <code>./launch_businessflow.sh [-r] -e &lt;environment_name&gt; -j &lt;business_flow_name&gt; &lt;parameters&gt;</code>  |
| DOS      | <code>launch_businessflow.bat [-r] -e &lt;environment_name&gt; -j &lt;business_flow_name&gt; "&lt;parameters&gt;"</code> |

| Parameter          | Description                                                                                                                                                                                                                                                                                                                                                                                     |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -r                 | The recover flag, -r, allows you to recover jobs and business flows. See <a href="#">Recovering business flows</a> (page 87).<br><br>Although the recover flag, -r, is optional, HP recommends that you use it whenever you run a job or business flow.                                                                                                                                         |
| environment_name   | The name of the environment. This is optional if you only have one environment.                                                                                                                                                                                                                                                                                                                 |
| business_flow_name | The name of the business flow.                                                                                                                                                                                                                                                                                                                                                                  |
| parameters         | The parameters as a space-separated list with each entry in the form <code>&lt;name&gt;=&lt;value&gt;</code> . For Windows, each individual entry must be enclosed by quotation marks. The parameter values for all cartridges included in the business flow are required.<br><br>For a date or time policy parameter, use the following format: <code>[YY]YY.MM.DD[ HH24:MI:[SS[.SSS]]]</code> |

**TIP** To verify the usage of the job from the command line, enter

`launch_businessflow.bat -h`.

The usage is displayed.

To verify the parameters for the job, enter `launch_businessflow.bat -j <business_flow_name> -e <environment_name> -h`.

After you enter the encryption key, the parameters are displayed.

*DOS example*

```
launch_businessflow.bat -e Oracle_env -j orders_flow_d2d  
-r "Min_Months_to_Retain=24"
```

---

**TIP** If the parameter value is left blank, and a default value was defined in Designer, the default value is used. If there is no default value, NULL is used.

---

**NOTE** Running an undo business flow requires the Run ID for the business flow you want to undo. The Run ID for the business flow is displayed on the Run Summary page.

---

- 5 Enter the encryption key at the prompt. The encryption key is case sensitive. The job runs, and displays a success or failure message.
- 6 Optionally, start the Web Console to monitor the progress of the job.

*See also*

[Chapter 8, Monitoring jobs](#)

## Recovering and cancelling business flows and jobs

*See also*

[Recovering or cancelling business flows and jobs](#) (page 80)

*In this section*

- [Recovering business flows](#) (page 87)
- [Recovering jobs using the recovery script](#) (page 88)
- [Cancelling jobs from the command line](#) (page 89)

### Recovering business flows

*See also*

[Recovering business flows and jobs](#) (page 81)

Using the recover flag, -r, allows you to rerun a business flow using the same parameters as the first time it was run. You can also use the -r flag to continue the business flow after a scheduled pause activity.

---

**NOTE** To recover a job, the job parameters must be exactly the same as the last time you ran it. If there are any differences in the syntax, even an extra space, a new job is launched instead of the previous job being recovered.

---

- 1 Make sure that you have performed the relevant tasks from [Before you begin](#) (page 85).
- 2 Open a command window.
- 3 Navigate to the following directory:  

```
<install_directory>/obt/bin
```

where <install\_directory> is the location where you installed the software.
- 4 Enter the same job name and parameters as the job you want to recover.

*DOS example*

If you ran the business flow example given in [Running business flows](#) (page 86), you would run:

```
launch_businessflow.bat -e Oracle_env -j orders_flow_d2d  
-r "Min_Months_to_Retain=24"
```

- 5 Optionally, start the Web Console to monitor the progress of the job.

*See also*

[Chapter 8, Monitoring jobs](#)

## Recovering jobs using the recovery script

Using the recovery script to recover jobs enables you to select the specific job you want to recover.

To recover a job using the recovery script:

- 1 Make sure that you have performed the relevant tasks from [Before you begin](#) (page 85).

- 2 Locate the Group ID of the failed job you want to recover.

The Group ID is displayed on the Web Console History page.

*See also*

[Viewing job history](#) (page 93)

- 3 Open a command window.

- 4 Navigate to the following directory:

```
<install_directory>/obt/bin
```

where <install\_directory> is the location where you installed the software.

- 5 Run the appropriate recovery script for the job you want to recover:

| Job                                       | Platform | Syntax                                                                            |
|-------------------------------------------|----------|-----------------------------------------------------------------------------------|
| Any business flow or database to file job | UNIX     | <code>./recover_job.sh -e &lt;environment_name&gt;<br/>-g &lt;group_ID&gt;</code> |
|                                           | DOS      | <code>recover_job.bat -e &lt;environment_name&gt;<br/>-g &lt;group_ID&gt;</code>  |

| Parameter        | Description                                                                     |
|------------------|---------------------------------------------------------------------------------|
| environment_name | The name of the environment. This is optional if you only have one environment. |
| group_ID         | The Group ID of the failed job as it appears in the Web Console.                |

*DOS example*

```
recover_job.bat -e "Oracle_env" -g "3"
```

- 6 Enter the encryption key at the prompt. The encryption key is case sensitive.  
The job runs, and displays a success or failure message.

- 7 Optionally, start the Web Console to monitor the progress of the job.

*See also*

[Chapter 8, Monitoring jobs](#)

## Cancelling jobs from the command line

*See also* [Cancelling business flows and jobs](#) (page 81)

Cancelling jobs from the command line requires the `cancelJob` API Groovy script. The script allows you to update the status of a job to Cancelled.

- 1 Locate the Group ID of the business flow you want to cancel.

The Group ID is displayed on the Web Console History page.

*See also* [Viewing job history](#) (page 93)

- 2 Navigate to the following directory:

`<install_directory>/obt/bin`

where `<install_directory>` is the location where you installed the software.

- 3 Run the `cancelJob` API using the appropriate syntax:

| Platform | Syntax                                                                                                   |
|----------|----------------------------------------------------------------------------------------------------------|
| UNIX     | <code>./launch_groovyscript.sh -e MyEnvironment -f ../scripts/cancelJob.groovy &lt;groupRunId&gt;</code> |
| DOS      | <code>launch_groovyscript.bat -e MyEnvironment -f ..\scripts\cancelJob.groovy &lt;groupRunId&gt;</code>  |

where `<groupRunID>` is the Group ID as defined on the Web Console.

- 4 Optionally, start the Web Console to monitor the progress of the job.

*See also* [Chapter 8, Monitoring jobs](#)

## Accessing the copied data

*See also* [Accessing the extracted data](#) (page 82)

*This section includes*

- [Relocating database to file extracted data](#) (page 89)
- [Accessing the structured data file](#) (page 90)

## Relocating database to file extracted data

*See also* [Relocating extracted data](#) (page 82)

To relocate database to file data from the command line:

- 1 Ensure that you have performed the relevant tasks from [Before you begin](#) (page 85).
- 2 Open a command window.
- 3 Navigate to the following directory:

<install\_directory>/obt/bin

where <install\_directory> is the location where you installed the software.

- 4 Run the job from the command line using the following syntax:

| Platform | Syntax                                                                                                                                               |
|----------|------------------------------------------------------------------------------------------------------------------------------------------------------|
| UNIX     | <code>./launch_ea_job.sh [-r] -e &lt;environment_name&gt; -j &lt;jobName&gt;<br/>sourceJobRunID=&lt;runID&gt; [destLocation=&lt;dest_loc&gt;]</code> |
| DOS      | <code>launch_ea_job.bat [-r] -e &lt;environment_name&gt; -j &lt;jobName&gt;<br/>sourceJobRunID=&lt;runID&gt; [destLocation=&lt;dest_loc&gt;]</code>  |

| Parameter        | Description                                                                                                                                                                                                                                                                                                                                                                         |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -r               | The recover flag, -r, allows you to recover jobs and business flows.                                                                                                                                                                                                                                                                                                                |
| environment_name | The name of the environment. This is optional if you only have one environment.                                                                                                                                                                                                                                                                                                     |
| jobName          | One of the following:<br><br>XML_DATA@COPY_BE_TO_DB      Copies data from a backend to a database.<br><br>XML_DATA@COPY_BE_TO_BE      Copies data from a backend to a backend.<br><br>XML_DATA@UPLOAD_BE_TO_DB    Uploads data from a backend to a different database than the original source, checks for missing schema objects, and creates any schema objects that are missing. |
| runID            | The run ID of the job that placed the extraction at the current location.                                                                                                                                                                                                                                                                                                           |
| dest_loc         | The name of the destination location as defined in the Web Console. Required for COPY_BE_TO_BE and UPLOAD_BE_TO_DB only.                                                                                                                                                                                                                                                            |

*DOS example*

```
launch_ea_job.bat -e "MyEnvironment" -j  
"XML_DATA@COPY_BE_TO_BE" -r "sourceJobRunId=3 "  
"destLocation=LOCAL_DATA_FS"
```

- 5 Enter the encryption key at the prompt. The encryption key is case sensitive. The job runs, and displays a success or failure message.
- 6 Optionally, start the Web Console to monitor the progress of the job.

*See also*

[Chapter 8, Monitoring jobs](#)

## Accessing the structured data file

To access contents of your structured data files, you use the query server. Refer to [Chapter 10, Using the query server to access extracted data files](#).

To effectively manage your system, you need to be able to monitor activity in a variety of ways. All of the following information can be helpful to you in managing your system:

- status of currently running jobs
- historical information about previously run jobs
- eligibility analytics
- log files

*In this chapter*

- [Monitoring current and past jobs](#) (page 91)
- [Using log files](#) (page 95)

## Monitoring current and past jobs

The Web Console provides you with a number of facilities to monitor the status and history of your jobs.

*In this section*

- [Viewing a job overview](#) (page 91)
- [Viewing detailed job status](#) (page 92)
- [Viewing job history](#) (page 93)
- [Viewing eligibility analytics](#) (page 94)

## Viewing a job overview

The Monitoring page in the Web Console provides you with an overview of the currently running and previously run jobs.

To view the Monitoring page:

- 1 Start the Web Console, if it is not already started.

*See also*

[Starting Web Console](#) (page 35)

- 2 Click **Monitoring** from the menu at the top of the page.

The overview page displays the status of your business flows as well as any currently running commands.

In the Business Flow Status section, the following information is displayed:

- Name of the business flow
- Number of rows affected
- Status of the business flow
- Start and end times of the business flow

---

**NOTE** Only the most recent run of each installed business flow is displayed.

---

In the Commands section, the following information is displayed about currently running jobs:

- Job ID number
- User
- Name of the running job
- Start and end times of the running job
- Node

---

**NOTE** After a job has finished running, it no longer appears in the Running Commands section. Click **Commands** from the left navigation pane to view all commands that have run.

---

## Viewing detailed job status

From the Monitoring page, you can drill down to more detailed job status information:

- From the Business Flow States section, you can drill down to the Run Details page, which displays a list of the individual tasks performed by the business flow and their status. If a business flow did not complete for some reason, the Run Details page can show you which task in the business flow was at fault.
- From the Running Commands section, you can drill down to the running log of the command.

### Viewing run details

To access the Run Details page:

- 1 Navigate to the Monitoring page according to the instructions in [Viewing a job overview](#) (page 91).
- 2 Click a highlighted business flow name or status to navigate to the Run Details page.
- 3 From the Run Details page, you can perform the following operations:
  - a Click **Command** to view the log file for the current run of the business flow.
  - b Click **Other Runs** to view all runs of the business flow.

- c Click **Job Parameters** to view the runtime parameters and their values for the current run of the business flow.
- d Click **Eligibility Analytics** to view the eligibility analytics for the current run of the business flow. Refer to [Viewing eligibility analytics](#) (page 94) for more information.
- e Click **Row Counts** to view the detailed row count information for the current run of the business flow.

### Viewing the log of a running command:

To view the logging of a running command:

- 1 Navigate to the Monitoring page according to the instructions in [Viewing a job overview](#) (page 91).
- 2 Click the highlighted job title to see information about the currently running job.

## Viewing job history

The History page displays all business flows and jobs that have ever been run in the environment you are currently viewing.

- 1 Navigate to the Monitoring page, using the instructions in [Viewing a job overview](#) (page 91).
- 2 Click **History** in the left navigation pane.
- 3 Optionally, filter the data by any of the following criteria:
  - group run id
  - run id
  - the date the job started (in yyyy-mm-dd hh:mm:ss or yyyy-mm-dd hh:mm:ss AM/PM format)
  - the date the job finished (in yyyy-mm-dd hh:mm:ss or yyyy-mm-dd hh:mm:ss AM/PM format)
  - the name of the job
  - the batch name of the job

Each filter you add is displayed at the top of the page.

- 4 Click the red X to clear individual filters.
- 5 Click **CSV** or **XML** to export the filtered data to a CSV or XML file.

## Viewing eligibility analytics

Eligibility analytics tell you which rows are selected for and excluded from movement. To see eligibility analytics, you must have done all of the following when the business flow was deployed:

- Paused your business flow after the selection task but before the movement task. Eligibility analytics are only available immediately after data selection. Refer to *HP Test Data Management Designer User Guide* for information about how to insert a pause in your business flow.
- Enabled eligibility analytics on your rules in the model in Designer. Refer to *HP Test Data Management Designer User Guide* for information about how to enable analytics on rules.
- Turned on the eligibility analytics parameter in the Web Console.

To view eligibility analytics:

- 1 Navigate to the Run Details page according to the instructions in [Viewing detailed job status](#) (page 92).
- 2 Click **Eligibility Analytics**. The Eligibility Analytics page displays.
- 3 Select a cartridge. The eligibility analytics for that cartridge display.
- 4 Select a table from the left navigation page to view the rows for that table.
- 5 To filter the data, perform any of the following operations:
  - Select **Exclusion Only**, **Selection Only**, or **All Data** from the left navigation pane.
  - Select a table name to view the eligibility analytics for that table.
- 6 To export the filtered data to a CSV or XML file, click **CSV** or **XML**.

## Viewing commands

In some cases, you may want to review the exact command that was used for a particular run of a business flow. For example, you may want this information for debugging purposes.

To view all commands that are running or have completed:

- 1 Navigate to the Monitoring page according to the instructions in [Viewing a job overview](#) (page 91).
- 2 Click **Commands** from the left navigation pane. The Commands page displays the commands.

- 3 To filter the list:
  - Click **Refresh** to refresh the list of commands.
  - Click **Show All Users** to show the jobs that belong to all users.
  - Click **Show Cleared** to show all cleared jobs.
  - Click **Clear Completed** to remove all completed jobs from the list.
- 4 Click a highlighted command to view details about the command and the log file.

## Using log files

When reviewing job status or diagnosing an issue, it can sometimes be helpful to view the complete information provided in the log files of HP Test Data Management. If you are regularly consulting the log files for a particular purpose, you may also want to adjust the logging properties to include or exclude certain information.

*In this section*

- [Viewing log files](#) (page 95)
- [Editing the obt.log file logging properties](#) (page 96)

## Viewing log files

Error messages from the Web Console and Test Data Management are captured and appended to log files. By default, the log files are saved to the <install\_directory>/obt/log/ directory and the logging level is set to INFO.

- 1 Navigate to the directory containing the log file.

*Example*

```
cd <install_directory>/obt/log/
```

where <install\_directory> is the location where you installed the software.

2 Open one of the following log files using a text editor of your choice:

| File name                                                                                         | Description                                                                                                                                                                                                                                                                     |
|---------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| obt.log                                                                                           | The obt.log file captures all logging information for HP Test Data Management.<br><br>New lines appended to the log file are displayed as they appear. Multiple log files are numbered in sequence, for example, obt.log1.                                                      |
| pdm_server_<runID>.log<br>where <runID> is the run ID of the job as displayed on the Web Console. | The pdm_server_<runID>.log file is used for advanced data selection and partitioned data movement.<br><br>The log file contains the generated statements, execution plans, and statistics from the execution of the advanced data selection and partitioned data movement jobs. |
| env_<env_name>.log<br>where <env_name> is the name of the environment.                            | The env_<env_name>.log file contains logging information specific to the environment. These logs are located in the directory <install_directory>/obt/log/<env_name>, where <install_directory> is the location where the software is installed.                                |

## Editing the obt.log file logging properties

You can edit the log4j.properties file to change the following logging properties for the obt.log file:

- where the log files are kept.
- what information is logged.
- the maximum size of the log file.
- how much logging information is kept.

By default, the obt.log file is limited to 10 MB. When it exceeds the default limit, the obt.log file is renamed to a backup file, and a new obt.log file is created. By default, a total of nine backup files are kept, limiting the log files to a 100 MB maximum size.

1 Navigate to the directory that contains the log4j.properties file.

*Example*

```
cd <install_directory>/obt/config/
```

where <install\_directory> is the location where you installed the software.

- 2 Create a backup copy of log4j.properties that you can roll back to in case of any problems.
- 3 Open the log4j.properties file with a text editor of your choice.
- 4 Make your desired changes to the file.
- 5 Save the log4j.properties file. The changes are applied automatically.

You can edit the `outerbay.properties` file to control the number of log files. To set the number of log files, perform the following steps:

- 1 Navigate to the directory that contains the `outerbay.properties` file.

*Example*

```
cd <install_directory>/obt/config/
```

where `<install_directory>` is the location where you installed the software.

- 2 Create a backup copy of `outerbay.properties` that you can roll back to in case of any problems.
- 3 Open the `outerbay.properties` file with a text editor of your choice.
- 4 Set the `envBasedLogging` and `runBasedLogging` properties to control the number of logging files as follows:
  - To have only the log file `obt.log`, set both `envBasedLogging` and `runBasedLogging` to `false`.
  - To have the log file `<envName>.log`, set `envBasedLogging` to `true`.
  - To have the log file `<envName>_run_<runID>.log`, set `runBasedLogging` to `true`.
  - To have all three logs, set both `envBasedLogging` and `runBasedLogging` to `true`.
- 5 Save the `outerbay.properties` file. The changes are applied automatically.



# Managing the repository and encryption keys

In certain situations, you may need to perform tasks such as locking the repository or changing its password. You might also need to change your environment encryption key for security purposes.

*In this chapter*

- [Locking and unlocking the repository](#) (page 99)
- [Changing encryption keys and the repository password](#) (page 102)

## Locking and unlocking the repository

In some situations, you may need to lock the repository. When you lock the repository, you can:

- prevent business flows and cartridges from being deployed in all environments.
- prevent business flows and cartridges from being deployed in a particular environment.
- prevent any new environments from being created.
- prevent any existing environments from being deleted.

For example, you may want to stop all deployments while you perform some system maintenance or upgrade activities. When you are ready, you can then unlock the repository to allow business flows and cartridges to again be deployed.

---

**NOTE** All new environments are unlocked by default.

---

*In this section*

- [Locking the repository](#) (page 99)
- [Unlocking the repository](#) (page 100)

## Locking the repository

To lock the repository:

---

**NOTE** If a business flow or cartridge deployment is already in process, locking the repository has no effect on that deployment.

---

- 1 Navigate to the <install\_directory>/obt/bin directory.  
where <install\_directory> is the location where you installed the software.
- 2 Run the lock\_repository script using the appropriate syntax:

| Platform | Syntax                                                                                                                          |
|----------|---------------------------------------------------------------------------------------------------------------------------------|
| UNIX     | <code>./lock_repository.sh [-m &lt;lock_mode&gt;] [-e &lt;environment_name&gt;] -u &lt;yourName&gt; [-c &lt;comment&gt;]</code> |
| DOS      | <code>lock_repository.bat [-m &lt;lock_mode&gt;] [-e &lt;environment_name&gt;] -u &lt;yourName&gt; [-c &lt;comment&gt;]</code>  |

| Parameter        | Description                                                                                                                                             |
|------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| lock_mode        | Optional. If you want to specify a lock mode, enter NO_CREATE_REPOS. This lock mode prevents any environments from being created or deleted.            |
| environment_name | Optional. The name of the environment.                                                                                                                  |
| yourName         | The name of the person locking the repository. Used for auditing purposes only. If name contains spaces, you need to use double-quotes around the name. |
| comment          | Optional. The reason why the repository is being locked.                                                                                                |

4 Enter the encryption key at the prompt.

#### *Windows examples*

- To prevent business flows and cartridges from being deployed in all environments:

```
lock_repository.bat -u Joe
```

- To prevent business flows and cartridges from being deployed in the environment Oracle\_Env:

```
lock_repository.bat -e Oracle_Env -u "Joe Smith"
```

- To prevent environments from being created or deleted:

```
lock_repository.bat -m NO_CREATE_ENV -u Paul -c "No new environment creation"
```

## Unlocking the repository

To unlock the repository:

- 1 Navigate to the <install\_directory>/obt/bin directory.

where <install\_directory> is the location where you installed the software.

2 Run the `unlock_repository` script using the appropriate syntax:

| Platform | Syntax                                                                                                                            |
|----------|-----------------------------------------------------------------------------------------------------------------------------------|
| UNIX     | <code>./unlock_repository.sh [-m &lt;lock_mode&gt;] [-e &lt;environment_name&gt;] -u &lt;yourName&gt; [-c &lt;comment&gt;]</code> |
| DOS      | <code>unlock_repository.bat [-m &lt;lock_mode&gt;] [-e &lt;environment_name&gt;] -u &lt;yourName&gt; [-c &lt;comment&gt;]</code>  |

| Parameter                     | Description                                                                                                                                                    |
|-------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>lock_mode</code>        | Optional. If you want to specify a lock mode, enter <code>NO_CREATE_REPOS</code> . This lock mode enables environment creation and deletion in the repository. |
| <code>environment_name</code> | Optional. The name of the environment.                                                                                                                         |
| <code>yourName</code>         | The name of the person unlocking the repository. Used for auditing purposes only. If name contains spaces, you need to use double-quotes around the name.      |
| <code>comment</code>          | Optional. The reason why the repository is being unlocked.                                                                                                     |

The script prompts for the encryption key.

3 Enter the encryption key at the prompt.

#### *Windows examples*

- To unlock all environments:  

```
unlock_repository.bat -u Paul -c "Unlock to allow check-ins"
```
- To unlock just the environment `Oracle_Env`, without affecting any other locked environments:  

```
unlock_repository.bat -e Oracle_Env -u Mike -c "Unlock Oracle_Env"
```
- To allow environments to be created or deleted:  

```
unlock_repository.bat -m NO_CREATE_ENV -u Paul -c "Allow environment creation"
```

# Changing encryption keys and the repository password

The password manager utility is used to change the encryption key and repository password.

*In this section*

- [Using password manager to change the encryption key](#) (page 102)
- [Using password manager to change the repository password](#) (page 102)

## Using password manager to change the encryption key

Use password manager to change the encryption key for the environment.

- 1 Open a command window.
- 2 Run the utility using the following syntax:

| Platform | Syntax                                          |
|----------|-------------------------------------------------|
| UNIX     | <install_directory>/obt/bin/runPwManager.sh -m  |
| DOS      | <install_directory>/obt/bin/runPwManager.bat -m |

where <install\_directory> is the location where you installed the software.

- 3 Enter values for the prompts. Enter ? to see a list of available values.

- Enter environment to modify:
- Enter CURRENT encryption key:
- Re-enter CURRENT encryption key:
- Enter NEW encryption key:
- Re-enter NEW encryption key:

All encrypted passwords in the connection-sources.xml file are re-encrypted using the new key. The encryption key values are not displayed on the window.

## Using password manager to change the repository password

If you need to change the password for your repository, use the password manager utility to update the password in the connection\_sources.xml file. HP recommends using the Web Console to modify location passwords for all other databases.

---

**NOTE** You can use the password manager utility when required for automation purposes.

---

To change the password for the repository owner on the database:

- 1 If you are using the embedded repository, perform the following steps:
  - a Ensure the embedded repository has been shut down.

- b Delete the following file:

`<install_directory>/obt/dbrep/access.cfg`

where `<install_directory>` is the location where you installed the software.

- c Navigate to the following directory:

`<install_directory>/obt/install`

where `<install_directory>` is the location where you installed the software.

- d Run the following script to reset the password:

```
<install_dir>\obt\install\obt_deployer.bat -buildfile
<install_dir>\foundation\components\install\deploy\
build_repository.xml create.obtrep.embedded.user
"-Drepository.rdbms.is.derbydb=true"
"-Drepository.owner.name=obt_rep"
"-Drepository.owner.password=<obt_rep_password>"
```

where `<install_dir>` is the location where you installed the software, and `<obt_rep_password>` is the new password for the embedded repository.

- e Restart the embedded repository.

- 2 Ensure the encryption key has not been changed.

The master encryption key is required for verification purposes. You can change the encryption key after completing the steps in this section.

- 3 Open a command window.

- 4 Run the password manager utility using the following syntax:

| Platform | Syntax                                                             |
|----------|--------------------------------------------------------------------|
| UNIX     | <code>&lt;install_directory&gt;/obt/bin/runPwManager.sh -p</code>  |
| DOS      | <code>&lt;install_directory&gt;/obt/bin/runPwManager.bat -p</code> |

where `<install_directory>` is the location where you installed the software.

- 5 Enter values for the prompts. Enter a question mark (?) to see a list of available values.

- Enter environment to modify:
- Enter master encryption key:
- Re-enter master encryption key:
- Enter location name to modify:
- Enter NEW password:
- Re-enter NEW password:

The password is changed, and the values are saved to the following file:

`<install_directory>/obt/config/connection-sources.xml`

where `<install_directory>` is the location where you installed the software.

## Using the query server to access extracted data files

After your data has been copied to XML or CSV files, you can use the query server to upload the data to a test database and populate spreadsheets.

The query server uses standard JDBC and ODBC clients to connect to your test data. The JDBC driver is installed during product installation, and requires no configuration. The ODBC driver and the Windows OLEDB driver are installed separately, and must be configured before use. You can also install an ado.net driver that you can use when compiling .NET programs.

The collections of test data you created are available from a data source. The xmlData source is created by default when you install the query server.

Depending on your needs, you can access all of your test data collections using the default data source, or you can create new data sources.

*In this chapter*

- [Installing the query server](#) (page 105)
- [Starting the query server](#) (page 106)
- [Installing and configuring the ODBC or OLE DB driver](#) (page 108)
- [Installing and configuring the OLE DB database driver on Windows](#) (page 111)
- [Connecting to a data source](#) (page 113)
- [Creating file collections](#) (page 118)
- [Viewing your collection](#) (page 122)
- [Uninstalling the query server](#) (page 149)

## Installing the query server

When installing HP Test Data Management, you have the option to install and start the query server during product installation as well as select the network ports for the server and agent. If the query server is not installed during product installation, you can install it later using the command line. This section describes how to install the query server.

Installing the query server also installs the query server agent and the default xmlData source. To use a different data source, or to create additional data sources, see [Using multiple data sources](#) (page 151).

By default, the query server is configured to run on port 19988, and the query server agent is configured to run on port 19985. You can specify the network ports for the server and agent during product installation. You can also specify the network port numbers when installing from the command line.

*In this section*

- [Installing the query server using the command line](#) (page 106)

## Installing the query server using the command line

Use the command line to install the query server on UNIX or Windows.

- 1 Navigate to the directory that contains the setup file, oaserver.sh (UNIX) or oaserver.bat (Windows).

*Example*

```
cd <install_directory>/obt/bin
```

where <install\_directory> is the location where the software was installed.

- 2 Run the setup file using the appropriate syntax:

| Platform | Command                                                      |
|----------|--------------------------------------------------------------|
| UNIX     | <code>./oaserver.sh -install [agent_port server_port]</code> |
| DOS      | <code>oaserver.bat -install [agent_port server_port]</code>  |

| Parameter   | Description                                                                                                 |
|-------------|-------------------------------------------------------------------------------------------------------------|
| install     | Installs the query server.                                                                                  |
| agent_port  | Optional. The port number you want to use for the query server agent. By default, the port number is 19985. |
| server_port | Optional. The port number you want to use for the query server. By default, the port number is 19988.       |

The query server and the xmlData data source are installed.

## Starting the query server

Clients communicate with the query server using the included JDBC database driver, or the ODBC or OLE DB drivers you install. However, the query server must be running for client communication to operate.

*In this section*

- [Starting the query server on Windows](#) (page 107)
- [Starting the query server on UNIX](#) (page 108)

## Starting the query server on Windows

You can run the query server as a Windows service or as a program. The user that starts the server needs to be part of the Administrator group. If you have Windows User Account Control (UAC) turned on, you need to be the Administrator user, not just in the Administrator group.

---

**NOTE** If you are using mapped network drives to store your collection information, you must run the query server as a program rather than as a service.

---

### Running the query server as a Windows service

By default, the query server runs as a Windows service.

- 1 Open a command window by selecting **Start > Run**, typing **cmd**, then clicking **OK**.

- 2 Change the directory to `<install_dir>\obt\bin`. For example:

```
cd C:\Program Files\HPTDM\obt\bin
```

- 3 Run the oaserver script with the start command.

```
oaserver -start
```

- 4 To make sure that the QueryServer and QueryServer\_Agent services are started, run the oaserver script with the status command.

```
oaserver -status
```

The output from the command indicates whether the service is active (installed and currently running) or inactive (installed but not running).

### Running the query server as a Windows console program

To run the query server as a Windows console program, you must stop the query server Windows service before starting the program.

- 1 Open a command window by selecting **Start > Run**, entering **cmd**, then clicking **OK**.

- 2 Change the directory to `<install_dir>\obt\bin`. For example:

```
cd C:\Program Files\HPTDM\obt\bin
```

- 3 Run the oaserver script with the stop command.

```
oaserver -stop
```

- 4 Ensure the following services are stopped:

- QueryServer
- QueryServer\_Agent

You can check the status of the services by opening the Services window, for example, **Start > Administrative Tools > Services**, or you can use the oaserver status command.

- 5 Open a command window, and navigate to the directory that contains the query server.

*Example*

```
cd <install_directory>/obt/bin
```

where <install\_directory> is the location where the software was installed.

- 6 Run the following command:

```
oaserver -startCmd
```

A new window opens with the title QS. This is the server. Normally the window stays blank. When you stop the server, the window closes. If you close the window, the server stops.

## Starting the query server on UNIX

- 1 Navigate to the directory that contains the query server.

*Example*

```
cd <install_directory>/obt/sqlxml/server/bin
```

where <install\_directory> is the location where the software was installed.

- 2 Start the query server.

| Syntax                             | Description                        |
|------------------------------------|------------------------------------|
| <code>./oaserver.sh -start</code>  | Starts the server.                 |
| <code>./oaserver.sh -stop</code>   | Stops the server.                  |
| <code>./oaserver.sh -status</code> | Displays the status of the server. |

## Installing and configuring the ODBC or OLE DB driver

If you want to use an ODBC client on Windows or UNIX, or an OLE DB client on Windows, you need to install the appropriate driver.

*In this section*

- [Installing and configuring the ODBC database driver on UNIX \(page 108\)](#)
- [Installing and configuring the ODBC database driver on Windows \(page 109\)](#)
- [Installing and configuring the OLE DB database driver on Windows \(page 111\)](#)

## Installing and configuring the ODBC database driver on UNIX

After you install the ODBC database driver on UNIX, you need to configure the `odbc.ini` file.

When you install the ODBC driver on UNIX, a default ODBC data source named QS is automatically configured to communicate with the server that is already installed. If you want to use a different data source name, connect to a different server, or if the server is not installed, you need to configure the driver by editing the `odbc.ini` file.

- 1 Navigate to the directory that contains the driver installation file, `oadriver.sh`.

*Example*

```
cd <install_directory>/obt/bin
```

where `<install_directory>` is the location where the software was installed.

- 2 Start the installation file.

*Example*

```
./oadriver.sh
```

- 3 Select Option 1 to install the driver.

The ODBC driver is installed.

## Installing and configuring the ODBC database driver on Windows

When you install the ODBC database driver on Windows, an ODBC data source named QS is automatically created and configured to communicate with the server that is already installed. The server uses the default query server database `xmlData`. If you want to use a different data source name or connect to a different database or host, you need to configure the ODBC driver. You can configure the ODBC database driver before or after you start the query server process, but you can only test the connection if the query server process is running.

### Installing the ODBC driver

- 1 Navigate to the directory that contains the driver installation file, `oadriver.bat`.

*Example*

```
cd <install_directory>/obt/bin
```

where `<install_directory>` is the location where the software was installed.

- 2 Double-click the installation batch file, `oadriver.bat`.
- 3 Select Option 1 to install the driver.
- 4 Select Option 1 to install the ODBC driver.

The ODBC driver is installed, and a default ODBC data source is automatically created and configured to communicate with the query server. The ODBC data source is named QS.

If you want to create additional data sources or communicate with a different server or database, see [Configuring the ODBC database driver](#) (page 110).

---

**NOTE** 64-bit Windows platforms have two ODBC administrators, one for 32-bit and one for 64-bit drivers. You must install the proper driver to work with your 32-bit or 64-bit application or applications. For more information, see [Configuring the ODBC database driver](#) (page 110).

---

## Configuring the ODBC database driver

- 1 From the Windows Start menu, choose **Control Panel**.
- 2 From the Control Panel, choose **Administrative Tools > Data Sources (ODBC)**.

The ODBC Data Source Administrator displays.

- 3 Click the **System DSN** tab.
- 4 Click **Add**.

The Create New Data Source window opens.

- 5 Select **Query Server ODBC Driver** from the list of values.
- 6 Click **Finish**.

The HP Query Server ODBC Driver Setup window opens.

- 7 Enter the following values:

| Field                          | Description                                                                                                                                                  |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Data Source Name               | Enter the name for the ODBC data source. The name must match the name of the Service Data Source.                                                            |
| OpenAccess Service Host        | Enter the name of the host machine or IP address on which the data source is running. If the query server is running on your local machine, enter localhost. |
| OpenAccess Service Port        | Enter 19988.                                                                                                                                                 |
| OpenAccess Service Data Source | Enter the name of the data source. The default data source name is xmlData. If you have added a new data source, enter the name of the new data source.      |

- 8 If you have started the query server process, click **Test Connect** to test the connection.

*See also*

[Starting the query server](#) (page 106)

The Login to OpenAccess Data Source window opens.

- 9 Enter the following information:

| Field                 | Expected value |
|-----------------------|----------------|
| Data Source User Name | install        |
| Data Source Password  | OA             |
| Custom Properties     | leave blank    |

- 10 Click **OK** to test the connection.
- 11 Click **OK** to close the confirmation window.
- 12 Click **OK** to save the configuration.

## Configuring the 32-bit ODBC database driver on 64-bit Windows

If you need to configuring the ODBC driver on a 64-bit Windows, you must use the 32-bit ODBC administration program.

To use the 32-bit ODBC administration program on 64-bit Windows:

- 1 Navigate to <system\_drive>\Windows\SysWoW64 directory
- 2 Run the ODBCAD32.EXE file.  
For more information, see <http://support.microsoft.com/kb/942976>.
- 3 Follow the ODBC configuration steps as described in [Configuring the ODBC database driver](#) (page 110).

## Installing and configuring the OLE DB database driver on Windows

After you install the OLE DB database driver on Windows, you need to configure the database driver. You can configure the OLE DB database driver before or after you start the query server process, but you can only test the connection if the query server process is running.

### Installing the OLE DB database driver

- 1 Navigate to the directory that contains the driver installation file, oadriver.bat.

*Example*

```
cd <install_directory>/obt/bin
```

where <install\_directory> is the location where the software was installed.

- 2 Double-click the installation batch file, oadriver.bat.
- 3 Select Option 1 to install the driver.
- 4 Select Option 2 to install the ADO OLE DB driver.

The OLE DB driver is installed along with the DataDirect OpenAccess SDK 6.0 program group.

- 5 Configure the driver as described under [Configuring the OLE DB database driver](#) (page 111).

### Configuring the OLE DB database driver

- 1 Start the DataDirect Configuration Manager from the DataDirect OpenAccess SDK 6.0 program group. For example, **All Programs > DataDirect OpenAccess SDK 6.0 > Client for ADO > Configuration Manager**.

The Configuration Manager displays.

- 2 Select **File > New > Data Source** from the menu bar. The New Data Source window opens.
- 3 Enter a unique name for the data source.
- 4 Select **DataDirect OpenAccess SDK for ADO 6.0 Provider** from the list of values.

- 5 Click **Set Up Data Source**. The DataDirect OpenAccess SDK for ADO Provider Setup window opens.
- 6 Enter the following values:

| Field                          | Description                                                                                                                                             |
|--------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| Description                    | Optionally enter a description for the data source name.                                                                                                |
| OpenAccess Service Host        | Enter the name of the host machine or IP address on which the data source is running. If you are running on your local machine, enter localhost.        |
| OpenAccess Service Port        | Enter 19988, or the port number on which you started QueryServer. Do not use the agent port number.                                                     |
| OpenAccess Service Data Source | Enter the name of the data source. The default data source name is xmlData. If you have added a new data source, enter the name of the new data source. |

- 7 If you have started the query server process, click **Test Connect** to test the connection.

*See also*

[Starting the query server](#) (page 106)

The Login to OpenAccess Data Source window opens.

- 8 Enter the following information:

| Field                 | Expected value |
|-----------------------|----------------|
| Data Source User Name | install        |
| Data Source Password  | OA             |

- 9 Click **OK** to test the connection.
- 10 Click **OK** to close the confirmation window.
- 11 Click **OK** to save the configuration.

## Installing 32-bit drivers on 64-bit Windows

If you need to run a 32-bit application on 64-bit Windows (such as most versions of Microsoft Excel) and have your application communicate with the query server, you must use a 32-bit driver. You can use JDBC or the 32-bit OLE-DB driver. If you need to use a 32-bit ODBC driver, contact your HP support representative for instructions. If you can use the 32-bit OLE-DB driver, see [Installing and configuring the OLE DB database driver on Windows](#) (page 111).

## Connecting to a data source

You can connect to the xmlData data source or other data sources that you create, using ODBC, OLE-DB, or JDBC clients. The JDBC database driver is included in the query server installation, and the JDBC driver does not need to be configured. The connection string syntax includes all of the connection information required to connect to any data source.

If you want to use an ODBC or OLE DB client, you need to install and configure the appropriate matching driver first.

*See also* [Installing and configuring the ODBC or OLE DB driver](#) (page 108)

By default, the data source is called xmlData. If you create a different data source, substitute the correct name.

This section assumes that the query server is installed and running.

- In this section*
- [Connecting using the Interactive SQL \(JDBC\) client](#) (page 113)
  - [Connecting using the Interactive JDBC client \(ij\)](#) (page 114)
  - [Connecting using a user-supplied JDBC client](#) (page 115)
  - [Connecting using the Interactive SQL \(ODBC\) client](#) (page 116)
  - [Connecting using the Interactive SQL \(OLE DB\) client](#) (page 117)

## Connecting using the Interactive SQL (JDBC) client

- 1 Navigate to the directory that contains the oaisql program.

*Example*

```
<install_directory>/obt/bin/
```

where <install\_directory> is the location where the software was installed.

- 2 Start the Interactive SQL (JDBC) program from the command line.

| Platform | Command    |
|----------|------------|
| UNIX     | oaisql.sh  |
| Windows  | oaisql.bat |

### 3 Connect to the server using the following syntax:

```
connect <username>*<password>@<host>:<port>;  
ServerDataSource=<datasource_name>;
```

**NOTE** if you want to connect to the default datasource xmlData, you can omit `ServerDataSource=<datasource_name>;` from the connect command.

| Parameter       | Description                                                                                                                                |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| username        | The name of the user with permissions to connect to the data source. The default value is install.                                         |
| password        | The password for the user. The default value is OA.                                                                                        |
| host            | The name of the host machine or IP address on which the data source is running. If you are running on your local machine, enter localhost. |
| port            | The port number for the host machine. The default value is 19988.                                                                          |
| datasource_name | The name of the data source you are connecting to. The default value is xmlData.                                                           |

#### *Default xmlData example*

```
connect install*OA@localhost:19988;  
ServerDataSource=xmlData;
```

The install user account is created by default and must be used the first time you connect.

**NOTE** An administrator should change the password for this default initial account if you are going to use security.

- See also*
- [Creating file collections](#) (page 118)
  - [Viewing your collection from the Interactive SQL or ij clients](#) (page 123).

## Connecting using the Interactive JDBC client (ij)

### 1 Start Interactive JDBC (ij).

| Platform | Command                                                     |
|----------|-------------------------------------------------------------|
| UNIX     | <code>./&lt;install_directory&gt;/obt/bin/tdm_sql.sh</code> |
| Windows  | <code>&lt;install_directory&gt;/obt/bin/tdm_sql.bat</code>  |

where `<install_directory>` is the location where the software was installed.

### 2 Connect to the driver using the following syntax:

```
driver 'com.hp.jdbc.openaccess.OpenAccessDriver';
```

### 3 Connect to the server using the following syntax:

```
connect 'jdbc:ags://  
<host>:<port>;serverDataSource=<datasource_name>;  
user=<username>;password=<password>';
```

| Parameter       | Description                                                                                                                                |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| host            | The name of the host machine or IP address on which the data source is running. If you are running on your local machine, enter localhost. |
| port            | The network port number used by the server on the host machine. The default value is 19988.                                                |
| datasource_name | The name of the data source you are connecting to. The default value is xmlData.                                                           |
| username        | The name of the user with permissions to connect to the data source. The default value is install.                                         |
| password        | The password for the user. The default value is OA.                                                                                        |

*default xmlData example*

```
connect 'jdbc:ags://  
localhost:19988;serverDataSource=xmlData;user=install;  
password=OA';
```

*See also*

- [Creating file collections](#) (page 118).
- [Viewing your collection from the Interactive SQL or ij clients](#) (page 123)

## Connecting using a user-supplied JDBC client

To connect to the data source using a different JDBC client, you need to know the following information:

| Connection information | Expected value                                                                                                                                                                                                    |
|------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| driver location        | <install_directory>/obt/lib/HPjc.jar<br>where <install_directory> is the location where you installed the software.                                                                                               |
| driver name            | com.hp.jdbc.openaccess.OpenAccessDriver                                                                                                                                                                           |
| JDBC URL               | jdbc:ags:<host>:<port>;serverDataSource=<br><datasource_name>;user=<username>;password=<br><password><br>Example: jdbc:ags://localhost:19988;<br>serverDataSource=xmlData;user=sample;<br>password=samplePassword |

| Parameter       | Description                                                                                            |
|-----------------|--------------------------------------------------------------------------------------------------------|
| host            | The name of the host machine or IP address on which the data source is running.                        |
| port            | The network port number used by the server on the host machine. The default value is 19988.            |
| datasource_name | The name of the data source you are connecting to. The default value is xmlData. This is not optional. |
| username        | Optional. The name of the user with permissions to connect to the data source.                         |
| password        | Optional. The password for the user.                                                                   |

## Connecting using the Interactive SQL (ODBC) client

This section assumes that the query server is installed and running, and that the ODBC driver has been installed and configured.

*See also*

- [Installing the query server](#) (page 105)
- [Starting the query server](#) (page 106)
- [Installing and configuring the ODBC or OLE DB driver](#) (page 108)

- 1 Navigate to the directory that contains the oaisql program.

*Example*

```
<install_directory>/obt/bin/
```

where <install\_directory> is the location where the software was installed.

- 2 Start the Interactive SQL (ODBC) program or your preferred SQL client.

| Platform | Command                                                                                                                                                                                                                                                                                                                                                                                  |
|----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| UNIX     | <code>oaisql.sh -odbc</code>                                                                                                                                                                                                                                                                                                                                                             |
| Windows  | <code>oaisql.bat -odbc</code><br><br>Or from the Start menu, choose <b>All Programs</b> > <install_folder> > <b>Client for ODBC</b> > <b>Interactive SQL (ODBC)</b><br><br>If you installed the OLE-DBclient <install_folder> is DataDirect OpenAccess SDK 6.0. If you installed the ODBC client, <install_folder> is the location where the Test Data Management software is installed. |

**NOTE** When using Interactive SQL (ODBC), the create collection, drop collection, and drop schema statements require a prefix of 'exec' or '!'. This is not required for Interactive SQL (JDBC).

- 3 Connect to the data source for the configured query server as the install user., using a configured ODBC data source.

*Example*

```
connect install*OA@<ODBC_DataSource_Name>
```

where <ODBC\_DataSource\_Name> is QS, the default ODBC data source, or the name you chose for an ODBC data source that you created and configured yourself.

The install user account is created by default and must be used the first time you connect.

---

**NOTE** The same connection string is used if you use the Interactive SQL (ODBC) program or your preferred SQL client.

---

- See also*
- [Creating file collections](#) (page 118)
  - [Viewing your collection from the Interactive SQL or ij clients](#) (page 123).

## Connecting using the Interactive SQL (OLE DB) client

This section assumes that the query server is installed and running, and that the OLE DB driver has been installed and configured.

---

**NOTE** When connecting to the query server while using a Microsoft client (for example, Excel/MSQuery or SQL Server), you can get an error when querying data that contains a date type field that contains very early dates. To avoid this type of error, start oaisql with the -oledb option, change the date data type to a varchar, or write a view that changes early dates (before Jan. 1,1753) to a valid value.

---

- See also*
- [Installing the query server](#) (page 105)
  - [Starting the query server](#) (page 106)
  - [Installing and configuring the ODBC or OLE DB driver](#) (page 108)

To connect using the interactive SQL (OLE DB) client:

- 1 Navigate to the directory that contains the oaisql program.

*Example*

```
<install_directory>/obt/bin/
```

where <install\_directory> is the location where the software was installed.

- 2 Start the Interactive SQL (OLE DB) program or your preferred SQL client.

---

| Platform | Command |
|----------|---------|
|----------|---------|

---

|     |                   |
|-----|-------------------|
| DOS | oaisql.bat -oledb |
|-----|-------------------|

---

|         |                                                                                                                             |
|---------|-----------------------------------------------------------------------------------------------------------------------------|
| Windows | From the Start menu, choose <b>All Programs &gt; DataDirect OpenAccess SDK 6.0 &gt; Client for ADO &gt; Interactive SQL</b> |
|---------|-----------------------------------------------------------------------------------------------------------------------------|

---

- 3 Enter **connect** at the prompt. The Data Link Properties window displays.
- 4 Select DataDirect OpenAccess SDK for ADO 6.0 Provider from the list of values.
- 5 Click **Next**. The Connection tab displays.
- 6 Test the connection using the following information:

| Field       | Expected value                                      |
|-------------|-----------------------------------------------------|
| Data Source | The name you supplied in the configuration manager. |
| User name   | install                                             |
| Password    | OA                                                  |

- 7 Click **Test Connection**.
- 8 Click **OK** to close the confirmation window.
- 9 Click **OK** to save the configuration and return to the ISQL prompt.

You can now type your queries at the prompt.

*See also*

- [Creating file collections](#) (page 118)
- [Viewing your collection from the Interactive SQL or ij clients](#) (page 123).

## Creating file collections

A data collection is a file system location and pattern or list containing the files created when you copied your data using database to file copying. Data contained in CSV, XML and XSD files compressed using GZIP can also be read. Creating the collection enables the SQL access system to view the files. A collection is defined by a specific file system directory and a wild-card filename pattern.

Collection configuration information is stored in the OASYSTEM.oa\_collections table.

You can create collections where the schema is based on the cartridge name or create your own schema name. The collections can be located on a local file system. You can also create a name for the collection or let the server create one for you automatically.

*In this section*

- [Creating collections](#) (page 119)
- [Using list files](#) (page 120)
- [Specifying the path for a local file system](#) (page 121)
- [Dropping collections, schemas, and connections](#) (page 121)

# Creating collections

You can create collections on a local file system or on external file systems. Both local and external file systems use the same syntax to create the collection, but the local file systems require a path, and external file systems require a connection.

- See also
- [Using list files](#) (page 120)
  - [Specifying the path for a local file system](#) (page 121)

To create collections:

- 1 Locate the folder or connection that contains the files created from running database to file.

---

**NOTE** If you plan to connect to an external file system, you must create the connection before you create the collection.

---

- 2 Ensure the server process is running.
- See also [Starting the query server](#) (page 106)
- 3 Start your preferred SQL client and connect to the xmlData data source.
  - 4 To create a collection use a statement like the following:

```
create collection [collection_name] [in schema
<schema_name>] using pattern '<path |
connection>\<pattern>';
```

| Parameter       | Description                                                                                                                                                                                                                                                       |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| collection_name | The name you choose for your collection that uniquely identifies this collection definition.                                                                                                                                                                      |
| schema_name     | An optional name to be used for the schema that will hold the tables discovered in the files selected by the pattern.                                                                                                                                             |
| path            | The location of the XML and XSD files from <a href="#">step 1</a> . Refer to <a href="#">Specifying the path for a local file system</a> (page 121) for more information.                                                                                         |
| connection      | The location of the XML and XSD files from <a href="#">step 1</a> . Refer to <a href="#">Dropping collections, schemas, and connections</a> (page 121) for more information.                                                                                      |
| pattern         | Typical filename matching wildcards: <ul style="list-style-type: none"><li>• * matches any number of any character</li><li>• ? matches one of any character.</li></ul> A typical pattern is *.xm* which matches the XML files whether compressed or uncompressed. |

---

**NOTE** Collection information is available in the table `OA_COLLECTIONS`, which is part of the query server schema. Detailed information of every file in a collection is available in `OA_FILES`, which is also part of the query server schema.

---

*Interactive SQL (JDBC)  
or ij example*

```
create collection my_collection using pattern 'C:\Program  
Files\HPTDM\data\ORDERS_D2F*.xm*';
```

*Interactive SQL (ODBC)  
example*

```
exec create collection my_collection using pattern  
'C:\Program Files\HPTDM\data\ORDERS_D2F*.xm*';
```

- 5 To create a collection using a schema name you specify, create the collection using a statement similar to the following:

```
create collection <collection_name> in schema  
<schema_name> using pattern '<path | connection>*.xm*';
```

where `<collection_name>` is the name you choose for your collection, `<schema_name>` is the name of the schema, and `<path | connection>` is the location of the files from [step 1](#).

*Interactive SQL (JDBC)  
or ij example*

```
create collection my_collection in schema my_schema using  
pattern 'C:\Program Files\HPTDM\data\*.xm*';
```

*Interactive SQL (ODBC)  
example*

```
exec create collection my_collection in schema my_schema  
using pattern 'C:\Program Files\HPTDB\data\*.xm*';
```

A collection is created containing all files in the directory that match the filename pattern, including those contained in gzip files.

---

**TIP** HP recommends using different directories for the files created when copying different business flows. If you have copied files from more than one business flow in the same directory, use wildcards to ensure that your pattern matches only files from a single business flow. Any files copied to this directory that match the pattern are automatically added to the collection.

---

## Using list files

Instead of using a pattern specified on the command line, you can reference a list file:

```
Create collection [<collection name>] [in schema <schema  
name>] using listfile <file> [errorfile <file>]
```

where `file` is a file specified with one of the three valid local path notations using proper directory separators and a valid filename.

The internal syntax of the file must adhere to these rules:

- Lines beginning with `#` are comments and not processed.
- No in-line comments are allowed.
- Blank lines are ignored.
- A line can contain either one of the following formats:

- /path/filename where path can be UNC or hierarchal form.
- Original filename<tab>/path/new\_filename
- Lines are tab delimited. That is, the tab character may not be used in path or filenames.
- Lines terminate in Unix or DOS style.
- Only one file definition is allowed per line.

If you add files to the list file, they are not automatically add to the collection. The list file is read once when creating the collection. If you want to add files, you should created a new list file and issue a new create collection statement. You should also specify a schema name to enable multiple collections to be accessed from the same schema.

## Specifying the path for a local file system

You can use three different types of path notation when you create a collection on a local file system. Depending on where your files are located, the pattern you type will differ from these examples:

| Notation                          | Pattern example                                                                                                               |
|-----------------------------------|-------------------------------------------------------------------------------------------------------------------------------|
| local mapped drive                | 'C:\Program Files\HPTDM\data\*.xm*'                                                                                           |
| UNC (Universal Naming Convention) | '\\192.168.1.11\NetFolder\HPTDM\data\*.xm*'<br>where 192.168.1.11 is a valid host and NetFolder is the name of a valid share. |
| URI (Uniform Resource Identifier) | 'file:///Z:/HPTDM/data/*.xm*'                                                                                                 |

**NOTE** If you are using mapped network drives on Windows to store your collection information, you must run the query server as a console program. For more information, see [Running the query server as a Windows console program](#) (page 107).

## Dropping collections, schemas, and connections

You can drop collections, schemas, and connections to clean up your data.

**NOTE** The last collection in a schema cannot be dropped. To remove the last collection, you need to drop the schema. Dropping collections or schemas does not alter or remove the original data files.

To drop a collection, use the following syntax:

```
drop collection <collection_name>;
```

where <collection\_name> is the name of the collection.

To drop a schema use the following syntax:

```
drop schema <schema_name>;
```

where <schema\_name> is the name of the schema.

To drop a connection use the following syntax:

```
drop connection <connection_name>;
```

where <connection\_name> is the name of the connection.

## Viewing your collection

After creating the collection, you can view it using different methods.

- [Viewing your collection from the Interactive SQL or ij clients](#) (page 123)
- [Viewing your collection from Microsoft Office Excel](#) (page 124)
- [Viewing your collection from OpenOffice.org Base](#) (page 127)
- [Viewing database to file data from Oracle](#) (page 129)
- [Viewing extracted data from SQL Server](#) (page 134)
- [Viewing extraction metadata](#) (page 136)
- [Viewing the extraction summary table](#) (page 137)
- [Viewing CSV files without using the query server](#) (page 138)
- [Viewing limitations](#) (page 139)
- [Using scalar functions to mask and unmask data](#) (page 140)

## Common queries

This section summarizes some of the commonly used queries that you might run against your collections. These queries are described in greater detail in the sections that follow.

### *Querying schema names*

To find out what schemas you have data in, use the following query:

```
select distinct schema from oa_collections;
```

### *Querying table names*

To find out what tables have been created from your collections, use a query similar to the following:

```
select table_qualifier, table_owner, table_name from  
oa_tables;
```

### *Querying from an Oracle database link*

Query a database link in Oracle to the XML file:

```
SELECT * FROM order_header@xmlData;
```

where the following database link was previously created in Oracle:

```
create public database link xmlData connect to "install"
identified by "OA" using
' (DESCRIPTION= (ADDRESS= (PROTOCOL=tcp) (HOST=<HOST>)
(PORT=<PORT>)) (CONNECT_DATA= (SERVICE_NAME=xmlData))
(HS=OK)) ' ;
```

*Querying from a SQL Server  
ODBC connection*

Query your data from within SQL Server using an ODBC connection to the file:

```
select * from XML_DATA.xmlData.SalesOrderOA.Customer
```

where xmlData is the remote link name.

xmlData is the XML server name.

SalesOrderOA is the cartridge name.

Customer is the table name.

*Querying metadata*

```
select workflowrunid, begintime from order_header where
orderid = 606
```

```
select orderid, memfreekb, memtotalkb from
vs.order_header where orderid in (1,100, 1000)
```

```
select distinct concat(workflowrunid,
concat(',', begintime)) as runString from vs.order_header
```

*Querying summary table*

```
select workflow_runid,param_name,param_value from
arcsum_multi where param_name in
('COMPRESSION_ALG', 'SOURCE_LOCATION', 'EXTRACT_FORMAT')
```

## Viewing your collection from the Interactive SQL or ij clients

After connecting using Interactive SQL or ij, you can use different SQL queries to view the data in your collection.

To find out what schemas you have data in, use the following query:

```
select distinct schema from oa_collections;
```

You should see results similar to the following:

```
schema
MySchema
orders_d2f
```

To find out what tables have been created from your collections, use a query similar to the following:

```
select table_qualifier, table_owner, table_name from
oa_tables;
```

You should see results similar to the following:

|                |                 |             |            |
|----------------|-----------------|-------------|------------|
| <i>Example</i> | table_qualifier | table_owner | table_name |
|                | SCHEMA          | SYSTEM      | OA_TABLES  |
|                | SCHEMA          | SYSTEM      | OA_COLUMNS |
|                | SCHEMA          | SYSTEM      | OA_TYPES   |
|                | SCHEMA          | SYSTEM      | OA_INFO    |

|         |            |                    |
|---------|------------|--------------------|
| SCHEMA  | SYSTEM     | OA_STATISTICS      |
| SCHEMA  | SYSTEM     | OA_FKEYS           |
| SCHEMA  | SYSTEM     | OA_PROC            |
| SCHEMA  | SYSTEM     | OA_PROCCOLUMNS     |
| xmlData | MySchema   | arcsum_MySchema    |
| xmlData | MySchema   | COMPLAN            |
| xmlData | MySchema   | CUSTOMER           |
| xmlData | MySchema   | ORDER_ATTACHMENT   |
| xmlData | MySchema   | ORDER_HEADER       |
| xmlData | MySchema   | ORDER_LINE         |
| xmlData | MySchema   | ORDER_LINE_DIST    |
| xmlData | MySchema   | ORDER_PAYMENT      |
| xmlData | MySchema   | ORDER_PAYMENT_LINE |
| xmlData | MySchema   | ORDER_STAR         |
| xmlData | MySchema   | ORDER_TAX          |
| xmlData | MySchema   | PRODUCT            |
| xmlData | MySchema   | SALESREP           |
| xmlData | MySchema   | STATUS             |
| xmlData | MySchema   | STORE              |
| xmlData | OASYSTEM   | OA_COLLECTIONS     |
| xmlData | OASYSTEM   | OA_CONNECTIONS     |
| xmlData | OASYSTEM   | OA_FILES           |
| xmlData | OASYSTEM   | OA_INDEXES         |
| xmlData | OASYSTEM   | OA_OPTIONS         |
| xmlData | OASYSTEM   | OA_PRIVILEGES      |
| xmlData | OASYSTEM   | OA_ROLES           |
| xmlData | OASYSTEM   | OA_USERS           |
| xmlData | ORDERS_D2F | arcsum_ORDERS_D2F  |
| xmlData | ORDERS_D2F | CUSTOMER           |
| xmlData | ORDERS_D2F | ORDER_ATTACHMENT   |
| xmlData | ORDERS_D2F | ORDER_HEADER       |
| xmlData | ORDERS_D2F | ORDER_LINE         |
| xmlData | ORDERS_D2F | ORDER_TAX          |
| xmlData | ORDERS_D2F | PRODUCT            |
| xmlData | ORDERS_D2F | SALESREP           |
| xmlData | ORDERS_D2F | STATUS             |

- The table qualifier column is the name of the data source.
- The table owner column is the name of the cartridge used to extract the data, the schema name, or the user if you created a view.
- The SYSTEM and OASYSTEM tables are system tables that contain information on the contents of the searchable data.
- The arcsum\_<schema\_name> contains all of the configuration and runtime parameter information for all collections within that particular schema.

## Viewing your collection from Microsoft Office Excel

You can view your collection in Microsoft Office Excel using the ODBC driver. You can use the Query Wizard to select what data is displayed, or you can use Microsoft Query to write your own queries.

---

**NOTE** Most versions of Excel are 32-bit applications. If you are using a 64-bit version of Windows and a 32-bit version of Excel, you need to use a 32-bit ODBC driver or the 32-bit OLE DB driver. For more information, see [Installing and configuring the ODBC database driver on Windows](#) (page 109) and [Installing and configuring the OLE DB database driver on Windows](#) (page 111).

---

**NOTE** Microsoft Office Excel does not support binary data or Unicode text. If your data file contains either of these types of data, you will not be able to import that data into Excel.

---

**TIP** If an object name contains special characters or punctuation marks, use quotation marks around the object names and end the query with a semicolon. For example, the following code:

```
SELECT ORDER_HEADER.ORDER&ID, ORDER_HEADER.DEPTNO+1
FROM xmlData.ORDER_OA.ORDER_HEADER
```

should be written as:

```
SELECT "ORDER_HEADER"."ORDER&ID", "ORDER_HEADER"."DEPTNO+1"
FROM "xmlData"."ORDER_OA"."ORDER_HEADER" "ORDER_HEADER";
```

---

*In this section:*

- [Viewing your collection using the query wizard](#) (page 125)
- [Viewing your collection using Microsoft Query](#) (page 126)

## Viewing your collection using the query wizard

- 1 Make sure the ODBC database driver has been installed and configured.  
*See also* [Installing and configuring the ODBC or OLE DB driver](#) (page 108)
- 2 Start Microsoft Office Excel.
- 3 Navigate to the Choose Data Source window.  
*Example* Data > Import External Data > New Database Query
- 4 Select the name of your ODBC source from the list of values.
- 5 Select the **Use the Query Wizard to create/edit queries** checkbox.
- 6 Click **OK**.  
The OpenAccess Login window opens.
- 7 Enter the user name and password for your user account.

---

| Field                 | Expected value |
|-----------------------|----------------|
| Data Source User Name | install        |
| Data Source Password  | OA             |
| Custom Properties     | leave blank    |

---

The Query Wizard - Choose Columns window opens.

- 8 Select the tables or columns you want to include, then Click **Next**.

The Query Wizard - Filter Data window opens.

- 9 Optionally, specify a filter to restrict the data, then click **Next**.

The Query Wizard - Sort Order window opens.

- 10 Optionally, specify the columns you want to use to sort the data, then Click **Next**.

The Query Wizard - Finish window opens.

- 11 Specify how the data should be returned into Excel, then click **Finish**.

The Import Data window opens.

- 12 Specify where you want the data returned.

- 13 Click **OK**. The data is loaded into the spreadsheet.

### Viewing your collection using Microsoft Query

- 1 Make sure the ODBC database driver has been installed and configured.

*See also* [Installing and configuring the ODBC or OLE DB driver](#) (page 108)

- 2 Start Microsoft Office Excel.

- 3 Navigate to the Choose Data Source window.

*Example* Data > Import External Data > New Database Query

- 4 Select the name of your ODBC source from the list of values.

- 5 Ensure the **Use the Query Wizard to create/edit queries** checkbox is not selected.

- 6 Click **OK**.

The OpenAccess Login window opens.

- 7 Enter the user name and password for your user account.

| Field                 | Expected value |
|-----------------------|----------------|
| Data Source User Name | install        |
| Data Source Password  | OA             |
| Custom Properties     | leave blank    |

The Microsoft Query window opens.

- 8 Enter a SQL query into Microsoft Query.

*Example* `select * from oa_users`

The results of the query are displayed in Excel.

## Viewing your collection from OpenOffice.org Base

You can view your connection in OpenOffice.org Base using either the ODBC or JDBC driver. If you are running on 64-bit Windows and using ODBC, you must use the appropriate driver to match the bit size of the application that is using the driver. For example, you must use a 32-bit driver with 32-bit applications and a 64-bit driver with 64-bit applications.

- In this section*
- [Connecting to OpenOffice.org Base using ODBC](#) (page 127)
  - [Connecting to Open Office.org Base using JDBC](#) (page 127)

### Connecting to OpenOffice.org Base using ODBC

- 1 If you plan on using the ODBC driver, ensure that the ODBC database driver has been installed and configured.

*See also* [Installing and configuring the ODBC or OLE DB driver](#) (page 108)
- 2 Ensure the server process is running.

*See also* [Starting the query server](#) (page 106)
- 3 Start the OpenOffice.org Base program.  
The Database Wizard window opens.
- 4 Connect to the database.
  - a Click the **Connect to an existing database** radio button.
  - b Select ODBC from the list of values.
  - c Click **Next**.
  - d On the Set up a connection to an ODBC database page, click **Browse**. The Data Source window opens.
  - e Select the data source and click **OK** to close the window.
  - f Click **Next** to select the data source.
  - g Enter the user name and select the Password required checkbox. The default user name is install, and the password is OA.
  - h Click **Test Connection**.  
The login window opens.
  - i Enter the password and click **OK** to test the connection.
  - j Click **OK** on the confirmation dialog.
  - k Click **Finish**.
- 5 Save the data source as an ODBC database.  
The Base program is connected to the server and ready to use.

### Connecting to Open Office.org Base using JDBC

- 1 Ensure the server process is running.

See also

[Starting the query server](#) (page 106)

- 2 Start the OpenOffice.org Calc program.
- 3 Configure the Java options.
  - a Select **Tools > Options**.  
The Options window opens.
  - b Select Java from the navigation tree.
  - c Click **Class Path**. The Class Path window opens.
  - d Click **Add Archive**.
  - e Navigate to the following directory:  
<install\_directory>/obt/lib
  - f Select oajc.jar and click **Open**.
  - g Click **OK** on the Class Path window.
  - h Click **OK** to return to the Calc program.
- 4 Exit all OpenOffice.org programs.
- 5 Connect to the database.

See also

[Connecting using the Interactive JDBC client \(ij\)](#) (page 114)

- a Start the OpenOffice.org Base program.  
The Database Wizard window opens.
- b Click the **Connect to an existing database** radio button.
- c Select JDBC from the list of values.
- d Enter the following JDBC database connection values:

| Field             | Expected value                                                       |
|-------------------|----------------------------------------------------------------------|
| Datasource URL    | jdbc:ags://<br><host>:<port>;serverDataSource=<datasource_<br>name>; |
| JDBC driver class | com.hp.jdbc.openaccess.OpenAccessDriver                              |

- e Click **Next**.
- f Enter the user name and select the **Password required** checkbox. The default user name is install, and the password is OA.
- g Enter the password and click **OK** to test the connection.
- h Click **OK** on the confirmation dialog.
- i Click **Finish**.
- 6 Save the data source as a JDBC database. The Base program is connected to the server and ready to use.

## Viewing database to file data from Oracle

With Oracle's Heterogeneous Services, you can access XML data from within an Oracle database. This enables you to use advanced SQL functions against the data, and even join the data with your source data for advanced querying.

---

**TIP** Oracle treats all columns and table names as upper-case. If your collection contains columns or tables that are in mixed-case or lower-case, you need to use double-quotes in your query. For example, `select column_name from table_name` returns a column called `COLUMN_NAME`, whereas `select "column_name" from table_name` returns a column called `column_name`.

---

*In this section*

- [Configuring Heterogeneous Services](#) (page 129)
- [Configuring Heterogeneous Services for releases prior to Oracle 11g on 64-bit operating systems](#) (page 131)
- [Creating an ODBC database link](#) (page 134)
- [Querying your data from Oracle](#) (page 134)

### Configuring Heterogeneous Services

To configure the Heterogeneous Services agent process, you need to perform the following tasks:

- [Creating an initialization file](#) (page 129)
- [Modifying the listener and tnsnames files](#) (page 130)

---

**NOTE** If you are running a version of Oracle prior to 11g on a 64-bit operating system, follow the instructions in [Configuring Heterogeneous Services for releases prior to Oracle 11g on 64-bit operating systems](#) (page 131).

---

#### Creating an initialization file

To create the initialization file:

- 1 Navigate to the following directory:

`$ORACLE_HOME/hs/admin`

2 Create a new text file, `initxmlData.ora`, that contains the following text:

| Mode    | Use                                                                                                                                                                                                                                                                                                                                                                         |
|---------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| UNIX    | <pre>HS_FDS_CONNECT_INFO = xmlData HS_AUTOREGISTER = TRUE HS_DB_NAME = hsodbc HS_FDS_SHAREABLE_NAME = &lt;QSODBC_install&gt;/obt/sqlxml/ client/lib/libodbc.so set ODBCINI=/&lt;AQSOBC_install&gt;/client/odbc.ini set LD_LIBRARY_PATH=/&lt;AQSOBC_install&gt;/client/lib:/ &lt;oracle-Home&gt;/10.2.0.4/lib32 set OASDK_ODBC_HOME=/&lt;AQSOBC_install&gt;/client/lib</pre> |
| Windows | <pre>set HS_FDS_CONNECT_INFO = xmlData set HS_AUTOREGISTER = TRUE set HS_DB_NAME = hsodbc</pre>                                                                                                                                                                                                                                                                             |

where `<QSODBC_install>` is where the query server ODBC drivers are installed.

**NOTE** For Oracle 11g, change the value of the `HS_DB_NAME` entry to `dg4odbc`.

If you use a different name than `xmlData` for the data source, edit the file and the file name accordingly. For example, if you used the name `MyData`, the file should be named `initMyData.ora`, and the value for `HS_FDS_CONNECT_INFO` should be `MyData`.

You can use the path variable appropriate to your environment to point to the necessary library for your operating system.

| Operating System       | Path variable   |
|------------------------|-----------------|
| IBM AIX                | LIBPATH         |
| HP-UX                  | SHLIB_PATH      |
| HP-UX on Intel Itanium | LD_LIBRARY_PATH |
| Linux                  | LD_LIBRARY_PATH |
| Solaris                | LD_LIBRARY_PATH |
| MS Windows             | PATH            |

### Modifying the listener and `tnsnames` files

To set up the listener on the agent to listen for incoming requests from the Oracle Database server:

1 Navigate to the directory that contains the `listener.ora` file.

### Example on MS Windows

```
cd $ORACLE_HOME/network/admin
```

- 2 Edit the `listener.ora` file to add the entries for the data source, for example:

```
SID_LIST_LISTENER =
  (SID_LIST =
    (SID_DESC =
      (SID_NAME = xmlData)
      (ORACLE_HOME = C:\oracle\product\10.2.0\db_1)
      (PROGRAM = hsodbc)
    )
  )
```

If you have a different Oracle home directory, edit the path accordingly.

---

**NOTE** For Oracle 11g, change the value of the `PROGRAM` entry to `dg4odbc`.

---

- 3 Ensure that the initialization parameter `GLOBAL_NAMES` is set to `FALSE` in the database initialization parameter file.
- 4 Edit the `tnsnames.ora` file to add the appropriate entry, for example:

---

**TIP** You do not need to add anything to `tnsnames.ora` on MS Windows.

---

### Example on Unix

```
HSALIAS = (DESCRIPTION=
  (ADDRESS= (PROTOCOL=tcp) (HOST=<oracle_host>) (PORT=1521))
  (CONNECT_DATA= (SID=xmlData))
  (HS=OK)
)
```

- 5 Restart the TNS Listener. When a request is received, the agent now spawns a Heterogeneous Services agent.

You are now ready to create a database link according to the instructions in [Creating an ODBC database link](#) (page 134).

## Configuring Heterogeneous Services for releases prior to Oracle 11g on 64-bit operating systems

When configuring the query server with Heterogeneous Services in releases prior to Oracle 11g on a 64-bit operating system, you must specify the 32-bit library using the path variable appropriate to your environment.

---

**TIP** If you cannot locate the 32-bit driver appropriate for your platform, contact HP Support.

---

### Example on Solaris

On Solaris with Oracle 10.2.0.4, your `initXMLData.ora` in `$ORACLE_HOME/hs/admin` would look similar to the following:

```
HS_FDS_CONNECT_INFO = xmlData
HS_FDS_SHAREABLE_NAME = /<QSODBC_install>/client/lib/
libodbc.so
set ODBCINI=/<QSODBC_install>/client/odbc.ini
set LD_LIBRARY_PATH=/<QSODBC_install>/client/lib:/
<oracle_home>/10.2.0.4/lib32
set OASDK_ODBC_HOME=/<QSODBC_install>/client/lib
```

where <QSODBC\_install> is the directory where the 32-bit query server ODBC drivers for Solaris are installed.

Your listener.ora would look similar to the following:

```
SID_LIST_LISTENER =
(SID_DESC =
(SID_NAME = xmlData)
(ORACLE_HOME = /remote/app/oracle/ra11510o/10.2.0.4)
(PROGRAM = hsodbc)
(ENVS=LD_LIBRARY_PATH=/<QSODBC_install>/client/lib:
/<Oracle_Home>/10.2.0.4/lib32)
)
```

where <QSODBC\_install> is the directory where the 32-bit query server ODBC drivers for Solaris are installed.

Your tnsnames.ora would look similar to the following:

```
HSALIAS = (DESCRIPTION=
(ADDRESS=(PROTOCOL=tcp) (HOST=stingray) (PORT=1527))
(CONNECT_DATA=(SID=xmlData))
(HS=OK)
)
```

Your odbc.ini would look similar to the following:

```
[xmlData]
Driver=/<QSODBC_install>/client/lib/ivoa22.so
Description=DataDirect OpenAccess SDK 6.0
Host=stingray
Port=19988
ServerDataSource=xmlData
UseLDAP=0
DistinguishedName=
Encrypted=0
LoadBalancing=0
AlternateServers=
ConnectionRetryCount=0
ConnectionRetryDelay=3
CustomProperties=
[ODBC]
Trace=0
IANAAppCodePage=4
TraceFile=odbctrace.out
TraceDll=/<QSODBC_install>/client/lib/odbctrac.so
InstallDir=/<QSODBC_install>/client
```

Where <QSODBC\_install> is the directory where the 32-bit query server ODBC drivers for Solaris are installed.

*Example on AIX*

On AIX with Oracle 10.2.0.4, your initXMLData.ora would look similar to the following:

```
HS_FDS_CONNECT_INFO=xmlData
HS_FDS_SHAREABLE_NAME=/home/verducci/TIGER/QS_CLIENTS
/obt/sqlxml/client/lib/libodbc.so
set ODBCINI=/home/verducci/TIGER/QS_CLIENTS/obt/sqlxml
/client/odbc.ini
```

```

set OASDK_ODBC_HOME=/home/verducci/TIGER/QS_CLIENTS/obt
/sqlxml/client/lib
set LIBPATH=/home/verducci/TIGER/QS_CLIENTS/obt/sqlxml
/client/lib:/remote/app/oracle/product/10.2.0.4/lib32

```

Your listener.ora would look similar to the following:

```

(SID_DESC =
  (SID_NAME = xmlData)
  (ORACLE_HOME = /remote/app/oracle/product/10.2.0.4)
  (PROGRAM = hsodbc)
  (ENVS=LIBPATH =/home/verducci/TIGER/QS_CLIENTS
    /obt/sqlxml/client/lib:/remote/app/oracle/product
    /10.2.0.4/lib32)
)

```

Your tnsnames.ora would look similar to the following:

```

HSALIAS = (DESCRIPTION=
  (ADDRESS=(PROTOCOL=tcp) (HOST=tiger) (PORT=1523))
  (CONNECT_DATA=(SID=xmlData))
  (HS=ok)
)

```

Your odbc.ini would look similar to the following:

```

[ODBC Data Sources]
xmlData=DataDirect OpenAccess SDK 6.0
[xmlData]
QEWS=40049
Driver=/home/verducci/TIGER/QS_CLIENTS/obt/sqlxml
/client/lib/ivoa22.so
Description=DataDirect OpenAccess SDK 6.0
Host=tiger
Port=19989
ServerDataSource=xmlData
UseLDAP=0
DistinguishedName=
Encrypted=0
LoadBalancing=0
AlternateServers=
ConnectionRetryCount=0
ConnectionRetryDelay=3
CustomProperties=
[ODBC]
Trace=0
IANAAppCodePage=4
TraceFile=odbctrace.out
TraceDll=/home/verducci/TIGER/QS_CLIENTS/obt/sqlxml
/client/lib/odbctrac.so
InstallDir=/home/verducci/TIGER/QS_CLIENTS/obt/sqlxml
/client

```

*Example on MS Windows*

On Microsoft Windows with Oracle 10.2.0.4, your initXMLData.ora would look similar to the following:

```

HS_FDS_CONNECT_INFO = xmlData
HS_AUTOREGISTER = TRUE
HS_DB_NAME = hsodbc

```

Your listener.ora would look similar to the following:

```
(SID_DESC =  
  (SID_NAME = xmlData)  
  (ORACLE_HOME = C:\oracle\product\10.2.0\db_2)  
  (PROGRAM = hsodbc)  
)
```

---

**TIP** You do not need to add anything to tnsnames.ora on MS Windows.

---

## Creating an ODBC database link

- 1 Invoke SQL\*Plus and log in as a user with privileges to create a database link. For example, SYSTEM.
- 2 Create a database link using the following syntax:

```
create public database link xmlData connect to "install"  
identified by "OA" using  
' (DESCRIPTION= (ADDRESS= (PROTOCOL=tcp) (HOST=<HOST>)  
(PORT=<PORT>)) (CONNECT_DATA= (SERVICE_NAME=xmlData))  
(HS=OK)) ' ;
```

---

| Parameter | Description                                                                                              |
|-----------|----------------------------------------------------------------------------------------------------------|
| HOST      | Enter the name of the machine where Oracle is installed.                                                 |
| PORT      | Enter the port number for your Oracle database that the TSN Listener is connected to. For example, 1521. |

---

*Related information* See your Oracle documentation.

## Querying your data from Oracle

- 1 Invoke SQL\*Plus and log in as a user with privileges to access the xmlData data.
- 2 Query your data using the database link.

*Example*

```
SELECT * FROM order_header@xmlData;
```

---

**TIP** In Oracle 10g and earlier, Unicode data types are not supported by Oracle Heterogeneous Services. To get support for Unicode data types, you must upgrade to Oracle Gateway 11g (DG4ODBC).

---

## Viewing extracted data from SQL Server

Using a linked server configuration allows you to access extracted data from within SQL Server. This enables you to use advanced SQL functions against the data, and even join the data with your source data for advanced querying.

*In this section*

- [Creating the ODBC connection](#) (page 135)
- [Querying your data from SQL Server](#) (page 135)

## Creating the ODBC connection

- 1 Start the SQL Server Management Studio.
- 2 Expand the Server Objects node.
- 3 Right-click Linked Servers and select **New Linked Server**. The New Linked Server window opens.
- 4 On the General panel, enter or select the following information:

| Field           | Expected value                                      |
|-----------------|-----------------------------------------------------|
| Linked server   | XML_DATA                                            |
| Server type     | Other data source                                   |
| Provider        | Microsoft OLE DB Provider for ODBC Drivers          |
| Product name    | Choose a name for the product. For example, sqlXML. |
| Data source     | xmlData                                             |
| Provider string | leave blank                                         |
| Location        | leave blank                                         |
| Catalog         | leave blank                                         |

- 5 On the Security panel, click **Add**.
- 6 Enter or select the following information for the local server login:

| Field           | Expected value                                                                     |
|-----------------|------------------------------------------------------------------------------------|
| Local Login     | Enter the login for the server you want to access the XML server. For example, sa. |
| Remote User     | Enter the username of the xmlData server. For example, install.                    |
| Remote Password | Enter the password for the user you selected. For example, OA.                     |

Leave the **Impersonate** check box unchecked.

- 7 Click **OK**.

## Querying your data from SQL Server

- 1 Start the SQL Server Management Studio.
- 2 Expand the Databases node.
- 3 Right-click on the database you configured and select **New Query**.
- 4 Query your data using the ODBC connection.

*Example*      `select * from <remote_link_name>.<xml_server_name>.  
<cartridge_name>.<table_name>`

| Parameter        | Description                                                                                                                |
|------------------|----------------------------------------------------------------------------------------------------------------------------|
| remote_link_name | The name of the linked server specified in <a href="#">Creating the ODBC connection</a> (page 135). For example, XML_DATA. |
| xml_server_name  | The name of the XML server. For example, xmlData.                                                                          |
| cartridge_name   | The name of the database to file cartridge.                                                                                |
| table_name       | The name of the table you want to query. For example, Customer.                                                            |

*Example*      `select * from XML_DATA.xmlData.SalesOrderOA.Customer`

## Viewing extraction metadata

The group XML file contains metadata about the extraction process, such as the start time and the workflow run ID. This information is available in queries using scalar functions.

The following functions expose group level metadata:

- workflowRunId
- sequence
- beginTime
- archiveGuid
- groupGuid
- productName
- productVersion
- runGuid
- cartridgeName
- cartridgeVersion
- sourceCategory
- sourceGuid
- sourceDatabase
- sourceDBServer
- sourceDriverType
- sourceHost
- sourcePort
- sourceUserID
- sourceStatus
- sourceType
- destinationCategory
- destinationGuid
- destinationDirectory
- destinationFile
- destinationHost
- destinationUserID
- destinationStatus
- destinationType

*Example query*      `select workflowrunid, begintime from order_header where  
orderid = 606`

*Example result*

| workflowrunid() | begintime()                         |
|-----------------|-------------------------------------|
| -----           | -----                               |
| 11              | 2007-11-07T18:56:41.000000000-08:00 |
| 11              | 2007-11-07T18:56:42.000000000-08:00 |

```

11                2007-11-07T18:57:24.000000000-08:00
11                2007-11-07T18:57:25.000000000-08:00
11                2007-11-07T18:57:26.000000000-08:00

```

The following functions read information from the Java virtual machine:

- MemFreeKB
- MemTotalKB

*Example query*      `select orderid, memfreekb, memtotalkb from vs.order_header  
where orderid in (1,100, 1000)`

*Example result*

| orderid | memfreekb() | memtotalkb() |
|---------|-------------|--------------|
| 1       | 3202        | 5184         |
| 100     | 3190        | 5184         |
| 1000    | 3190        | 5184         |

The following function concatenates the CHARACTER arguments into a single string:

- CONCAT(char1,char2)

*Example query*      `select distinct concat(workflowrunid, concat(', ', begintime))  
as runString from vs.order_header`

*Example result*

| runString                              |
|----------------------------------------|
| 11,2007-11-07T18:56:41.000000000-08:00 |
| 11,2007-11-07T18:56:42.000000000-08:00 |
| 11,2007-11-07T18:57:24.000000000-08:00 |
| 11,2007-11-07T18:57:25.000000000-08:00 |
| 11,2007-11-07T18:57:26.000000000-08:00 |

## Viewing the extraction summary table

Each summary XML file is a summary of the extraction process and data movement history for one run. The summary table contains much of the data from the summary XML file, including:

- summary of extraction groups,
- summary of data movements,
- what the user parameters were set to when the extraction was run
- the source location
- the destination location

The summary table contains the following columns:

- workflow\_Runid
- mv\_Workflow\_Runid
- dest\_Category
- task\_GUID
- mv\_Task\_GUID
- dest\_Type
- archive\_GUID
- mv\_Begin\_Time
- dest\_Hostdest\_User\_Id
- appsPack\_Name
- source\_GUID
- dest\_Desc
- appsPack\_Version
- source\_Category
- param\_name
- group\_GUID
- source\_Type
- param\_scope
- group\_sequence
- source\_Host
- param\_type
- group\_instance\_count
- source\_User\_Id
- param\_datatype
- mv\_Type
- source\_Desc
- param\_default\_value
- mv\_Product\_Version
- dest\_GUID
- param\_value

*Example query*      `select workflow_runid,param_name,param_value from  
arcsum_multi where param_name in  
( 'COMPRESSION_ALG', 'SOURCE_LOCATION', 'EXTRACT_FORMAT' )`

*Example result*

| workflow_runid | param_name      | param_value |
|----------------|-----------------|-------------|
| -----          | -----           | -----       |
| 7              | COMPRESSION_ALG | NONE        |
| 7              | SOURCE_LOCATION | OBTINTF_DB  |
| 7              | EXTRACT_FORMAT  | XML         |
| 9              | COMPRESSION_ALG | GZIP        |
| 9              | SOURCE_LOCATION | OBTINTF_DB  |
| 9              | EXTRACT_FORMAT  | CSV         |

## Viewing CSV files without using the query server

Although you can import CSV files directly into Microsoft Office Excel, many of the datatypes available in relational databases are not supported. Because your HP Test Data Management CSV files were created from a database, they may not be interpreted correctly if you use a spreadsheet to read the CSV files directly. In addition, the CSV files do not contain column headers. You have to add these manually yourself.

The following limitations apply to CSV files containing binary data and unicode text:

- You cannot open CSV files created by HP Test Data Management directly with Excel. They must be imported before you can view them.
- Excel does not support reading, manipulating, or storing binary data. If you import a CSV file with binary fields, the data in those fields will not be usable or recognizable in Excel.
- Excel 2003 requires a byte order marker (BOM) be added to CSV files with unicode text before importing. See your Professional Services representative for more information.

To import CSV files into Microsoft Excel 2007:

- 1 From Excel 2007, select **Data > Get External Data > From Text**.
- 2 Select the file you want to import.
- 3 In the Text Import wizard, ensure the following are set before you import:
  - File Origin is set to 65001: Unicode (UTF-8)
  - Delimiter is set to comma

To import CSV files into OpenOffice.org Calc 3.1:

- 1 From OpenOffice.org 3.1 Calc, select **File > Open**.
- 2 Select the file you want to import.
- 3 In the Text Import window, change the Character Set to Unicode (UTF-8).
- 4 Click **OK**.

## Viewing limitations

This section describes the limitations that exist for viewing the extracted data.

### Large object limitations in the xmlData

Because large objects are stored in memory differently than other data, there are limitations when accessing them. Large objects in Oracle include CLOBs, BLOBs, LONG and LONG RAW datatypes. Large objects in SQL Server include image, text, ntext, nvarchar(max), varchar(max), and XML datatypes.

Large object columns can only be used in a WHERE clause if used in conjunction with an IS NULL or IS NOT NULL operator. The following functions cannot be used to query columns with large objects:

- group by
- distinct
- order by
- set

### Extracting binary and varbinary data to XML

When binary and varbinary data is extracted, it is stored in base64 format in the CSV or XML data files generated by running database to file extraction.

*Example*

| original column | original row value | XML column and value                    |
|-----------------|--------------------|-----------------------------------------|
| binary_type     | 0x1111111111       | <binary_type>ERERERE=<br></binary_type> |

The data is returned to its original form when restored to a database or accessed by the query server.

---

**NOTE** Not all clients display binary data properly.

---

### Multi-byte characters in views

Views cannot be created from tables with multi-byte characters in the tablename, and multi-byte characters cannot be used in the name of the view.

### Truncation of certain numeric types

When viewing extracted data that is a numeric, float, or real number with 16 significant digits, you might see only 15 significant digits when using oaisql -odbc. This may result in either a missing least-significant digit or rounding of the least-significant digit.

## Using scalar functions to mask and unmask data

A number of scalar functions are available for masking and unmasking data returned from SQL queries. You can include these function in statements when using Interactive SQL or ij client to retrieve data from your collections and want to mask or unmask returned data. These function are useful when you extracted data that you did not want to mask, but you want to obfuscate access to certain fields of the data for some users.

This section describes the functions available for masking and unmasking data:

- [RandomInteger](#) (page 141)
- [FixedInteger](#) (page 141)
- [SkewInteger](#) (page 141)
- [Revert\\_SkewInteger](#) (page 142)
- [FixedFloat](#) (page 143)
- [SkewFloat](#) (page 143)
- [FixedNumber](#) (page 144)
- [SkewPercent](#) (page 144)
- [MaskString](#) (page 144)
- [RandomString](#) (page 145)
- [ReplaceString](#) (page 146)
- [MaskSSN](#) (page 146)
- [Groovy](#) (page 147)
- [MaskCreditCardNumber](#) (page 147)
- [MaskABANumber](#) (page 148)
- [SkewDate](#) (page 148)
- [Revert\\_SkewDate](#) (page 148)

## RandomInteger

This function generates a random number between a specified minimum and maximum number (inclusive). The min and max parameters for specifying the range of random numbers are optional. The behavior of the function is as follows, depending on how you specify min and max.

- The functions defaults min to 0 and max to 99 if no parameters are specified.
- Specifying only a positive number sets min to 0 and max to the argument.
- Specifying a only a negative number sets min to the argument and max is set to 0.
- If min is greater than max, the arguments are switched and min is used as the maximum value and max is used as the minimum value.
- If the argument or arguments can be interpreted as an integer, the function returns a value.
- If the argument or arguments cannot be returned as an integer, the function returns an error.

*Syntax*                      `RandomInteger ( [min,max] )`

*Parameters*

| Parameter | Description                                      |
|-----------|--------------------------------------------------|
| min       | The minimum number that the function can return. |
| max       | The maximum number that the function can return. |

*Example*                      `SELECT attachment, RandomInteger(0-attid,attid) AS rdm FROM order_attachment;`

## FixedInteger

Returns an integer of the specified value.

*Syntax*                      `FixedInteger(integer_value)`

*Parameters*

| Parameter     | Description                  |
|---------------|------------------------------|
| integer_value | The integer value to return. |

*Example*                      `SELECT attachment, concat('Attachment',FixedInteger(attid)) AS attachmentattid FROM order_attachment;`

## SkewInteger

This function returns a skewed value. The skewed value is created from an original integer value plus a user-specified number.

*Syntax*                      `SkewInteger(target, type, skew_amount)`

## Parameters

| Parameter   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| target      | Base value to be skewed                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| type        | <p>A string that specifies the method to use to skew the base value specified by target. The type is one of the following:</p> <ul style="list-style-type: none"><li>• SUBTRACT—subtracts skew_amount from target</li><li>• ADD—adds skew_amount to target</li><li>• MULTIPLY—multiplies the target by skew_amount.</li><li>• DIVIDE—divides target by skew_amount</li></ul> <p>You only need to specify the first letter of the type string. For example, specifying 'A' is the same as 'ADD'.</p> |
| skew_amount | The amount by which to skew the base value. This is the second value in the skew equation.                                                                                                                                                                                                                                                                                                                                                                                                          |

## Example

```
SELECT attachment, attid, SkewInteger(attid,'ADD',3) as  
skew_attid FROM order_attachment;
```

## Revert\_SkewInteger

This function performs the opposite function of SkewInteger, allowing you to revert the result. Revert\_SkewInteger performs the opposite operation from what you specify for type. For example, if you specify ADD, the Revert\_SkewInteger function performs a subtract operation.

## Syntax

```
RevertSkewInteger(target, type, skew_amount)
```

## Parameters

| Parameter   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| target      | Base value to be skewed                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| type        | <p>A string that specifies the method to use to skew the base value specified by target. The type is one of the following:</p> <ul style="list-style-type: none"><li>• SUBTRACT—adds skew_amount to target</li><li>• ADD—subtracts skew_amount to target</li><li>• MULTIPLY—divides target by skew_amount</li><li>• DIVIDE—multiplies target by skew_amount</li></ul> <p>You only need to specify the first letter of the type string. For example, specifying 'A' is the same as 'ADD'.</p> |
| skew_amount | The amount by which to skew the base value. This is the second value in the skew equation.                                                                                                                                                                                                                                                                                                                                                                                                   |

*Example*      `SELECT attachment, attid,  
Revert_SkewInteger(SkewInteger(attid, 'M', 3), 'M'3) as  
skew_attid FROM order_attachments;`

## FixedFloat

This function returns a float value. However, due to rounding, the value returned is not exactly the value you specify.

*Syntax*              `FixedFloat(float_value)`

### Parameters

| Parameter   | Description                  |
|-------------|------------------------------|
| float_value | The integer value to return. |

*Example*      `SELECT attachment, attid, FixedFloat(3.14159) AS float from  
order_attachment;`

## SkewFloat

This function returns a skewed value. The skewed value is created from an original float value plus a user-specified number. The SkewFloat function differs from SkewInteger in that it checks for illegal conditions.

*Syntax*              `SkewFloat(target, type, skew_amount)`

### Parameters

| Parameter   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| target      | Base value to be skewed                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| type        | <p>A string that specifies the method to use to skew the base value specified by target. The type is one of the following:</p> <ul style="list-style-type: none"> <li>SUBTRACT—subtracts skew_amount from target</li> <li>ADD—adds skew_amount to target</li> <li>MULTIPLY—multiplies the target by skew_amount.</li> <li>DIVIDE—divides target by skew_amount</li> </ul> <p>You only need to specify the first letter of the type string. For example, specifying 'A' is the same as 'ADD'.</p> |
| skew_amount | The amount by which to skew the base value. This is the second value in the skew equation.                                                                                                                                                                                                                                                                                                                                                                                                       |

*Example*      `SELECT attachment, attid,  
SkewFloat(attid, 'm', FixedFloat(3.1459)) as skew_attid FROM  
order_attachment;`

## FixedNumber

This function returns a numeric of a decimal value.

*Syntax*                `FixedNumber(decimal_value)`

*Parameters*

| Parameter     | Description                                       |
|---------------|---------------------------------------------------|
| decimal_value | The decimal value from which to return a numeric. |

*Example*                `SELECT attachment, attid,  
SkewFloat(attid, 'm', FixedNumber(3.1459)) as skew_attid FROM  
order_attachment;`

## SkewPercent

This function returns a skewed value where the original value is increased by a specified percentage. The SkewPercent function returns value \* (1 + skew)/100 as a float.

*Syntax*                `SkewPercent(value, skew)`

*Parameters*

| Parameter | Description                                   |
|-----------|-----------------------------------------------|
| value     | The base value to skew.                       |
| skew      | The value used to skew value by a percentage. |

*Example*                `SELECT attachment, attid, SkewPercent(attid,100) AS  
skew_attid FROM order_attachment;`

## MaskString

This functions returns a masked string. The string and string length returned is determined by the substitute character, whether the length of the string should be random or fixed, and the maximum length that should be returned.

*Syntax*                `MaskString(originalString, substituteCharacter,  
lengthType, maxLength)`

## Parameters

| Parameter           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|---------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| originalString      | String to be masked.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| substituteCharacter | Character to use for masking the string.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| lengthType          | <p>Length of the string returned. The following are the possible values for lengthType:</p> <ul style="list-style-type: none"><li>• R specifies that the masked string returned has a random length no longer than maxLength.</li><li>• O specifies that the masked string is always the same length as the original string. For example, if the original string is 5 characters long, the masked string returned is 5 characters long.</li><li>• S specifies that only the substitute character is returned as the string mask.</li></ul> |
| maxLength           | Maximum length of the masked string that can be returned by the function. For example, if the original string is 10 characters long, lengthType is 'S', and maxLength is 5, then the returned masked string is only 5 characters long.                                                                                                                                                                                                                                                                                                     |

*Example*      `SELECT lastname, MaskString(firstname,'X','O',5) AS  
firstname FROM customer;`

## RandomString

This function generates a random string of the specified type of the length specified by the length parameter. The query server allows you to abbreviate the type. For example, you can use 'L' for 'Lower\_Case'.

*Syntax*      `RandomString(type, length)`

## Parameters

| Parameters | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| type       | The type of string to generate. The types are: <ul style="list-style-type: none"><li>• ANY_ALPHA_CHAR—The string returned contains letters.</li><li>• ANY_NUMERIC_CHAR—The string returned contains alphanumeric characters.</li><li>• LOWER_CASE_ALPHA—The string returned contains only lower-case letters.</li><li>• UPPER_CASE_ALPHA—The string returned contains only uppercase letters.</li><li>• PRINTABLE_CHAR—The string returned contains can contains symbols as well as alphanumeric characters.</li></ul> |
| length     | The length of string to generate.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |

*Example* `SELECT attachment, attid, RandomString('PRINTABLE_CHAR',16)  
AS rdm_str FROM order_attachment;`

## ReplaceString

This function returns a constant string.

*Syntax* `FixedString(string)`

## Parameters

| Parameters | Description           |
|------------|-----------------------|
| string     | The string to return. |

*Example* `SELECT attachment, attid, FixedString('ALPHANUMERIC') AS  
fx_str FROM order_attachment;`

## MaskSSN

This function validates that the given US Social Security number adheres to a supported format. If the number adheres to a supported formation, the function one of the following, depending on what is specified for the type parameter:

- A Social Security Number with all numbers masked by X except for the last four numbers
- A new random Social Security Number starting with 897, which is not assigned to any individual and can be safely used. Otherwise, the mask returns the same input number. The random social security number will always be the same for the number that is input. That is, for the value x, the value y is always returned.

This mask supports both formats, xxx-xx-xxxx and xxxxxxxxxx. If the input contains dashes, this function returns a number with dashes inserted in the 4th and 7th place

*Syntax*            `MaskSSN(ssn, type)`

*Parameters*

| Parameters | Description                                                                                                                                                                                                                                                                                                                                        |
|------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ssn        | The social security number to mask.                                                                                                                                                                                                                                                                                                                |
| type       | The method to use to mask the social security number. <ul style="list-style-type: none"><li>• XXX—replaces all digits from the original number with letter X, except the last four digits.</li><li>• 897—returns a new, random Social Security Number starting with 897, which is not assigned to any individual and can be safely used.</li></ul> |

*Example*        `SELECT customerid, firstname, lastname, MaskSNN(social, 'XXX') as ssn FROM customer`

## Groovy

This function allows you to call a Groovy script.

*Syntax*            `Groovy(groovy_script_name, string_argument)`

*Parameters*

| Parameters         | Description                                              |
|--------------------|----------------------------------------------------------|
| groovy_script_name | The Groovy script to call.                               |
| string_argument    | A string that contains the parameters for Groovy script. |

*Example*        `SELECT attachment, attid, groovy(RandomString.groovy, 'XXX') as rdm_str FROM order_attachment;`

## MaskCreditCardNumber

This function validates that the given credit card number adheres to a supported format and, if it does, returns a new, random credit card number of the same type. Otherwise, it returns the same input number. This mask supports Visa, Master Card, American Express, and Discover card numbers.

*Syntax*            `MaskCreditCardNumber(original, maskType)`

*Parameters*

| Parameters | Description                             |
|------------|-----------------------------------------|
| original   | Credit card number to be masked.        |
| maskType   | Any string. This parameter is required. |

*Example*      `SELECT customerid, lastname, firstname,  
MaskCreditCardNumber(creditcard, 'NEW') AS card FROM  
customer;`

### MaskABANumber

This function validates that the given ABA number adheres to a supported format and, if it does, returns a new valid random ABA number. Otherwise, it returns the same input number. This mask supports a nine digit ABA number of the format XXXXXXXXXX, where X is any digit [0-9]. The random number returned will always be the same for the number that is input. That is, for a given value x, the value y is always returned.

*Syntax*              `MaskABANumber(original)`

*Parameters*

| Parameters | Description              |
|------------|--------------------------|
| original   | ABA number to be masked. |

*Example*      `SELECT customerid, lastname, firstname, MaskABANumber(aba)  
as RTN from customer;`

### SkewDate

This function returns a skewed value, the original date plus a specified number of days.

*Syntax*              `SkewDate(original, days)`

*Parameters*

| Parameters | Description                                                 |
|------------|-------------------------------------------------------------|
| original   | Original date to be skewed.                                 |
| days       | The number of days by which to increment the original date. |

*Example*      `SELECT orderid, customerid, SkewDate(orderdate, 3)  
AS order_date FROM order_header;`

### Revert\_SkewDate

This function performs the opposite function of SkewDate, allowing you to revert the result. Revert\_SkewDate performs the opposite operation from SkewDate, subtracting the specified number of days from the date.

*Syntax*              `Revert_SkewDate(skew_date, days)`

## Parameters

| Parameters | Description                                               |
|------------|-----------------------------------------------------------|
| skew_date  | Skewed date                                               |
| days       | The number of days by which to decrement the skewed date. |

*Example* `SELECT orderid, customerid,  
Revert_SkewDate(SkewDate(orderdate, 3),3) AS order_date FROM  
order_header;`

## Uninstalling the query server

Use the oaserverlscript to uninstall the query server and the client drivers. If you want to uninstall only the query server, or only the client drivers, add -server or -client to the syntax.

**NOTE** If you uninstall HP Test Data Management, the query server is uninstalled as well. This includes any query server data sources, indexes, users, privileges, and views.

- 1 Navigate to the directory that contains the oaserver script.

*Example* `cd <install_directory>/obt/bin`

where <install\_directory> is the location where the software was installed.

- 2 Run the appropriate script:

| Uninstall Action                                       | Platform | Command                         |
|--------------------------------------------------------|----------|---------------------------------|
| Uninstall both the query server and the client drivers | DOS      | oaserver uninstall              |
|                                                        | UNIX     | ./oaserver.sh -uninstall        |
| Uninstall the query server only                        | DOS      | oaserver uninstall server       |
|                                                        | UNIX     | ./oaserver.sh uninstall server  |
| Uninstall the client drivers only                      | DOS      | oaserver uninstall client       |
|                                                        | UNIX     | ./oaserverl.sh uninstall client |

**TIP** If any files remain in the <install\_directory>/obt/sqlxml/client/ or <install\_directory>/obt/sqlxml/server/ directories, you can delete them manually.

If you have installed either the ODBC driver or the OLE DB driver, you can use the oadriver script to uninstall the drivers without uninstalling the query server.

- 3 Navigate to the directory that contains the ODBC driver installation file.

*Example*

```
cd <install_directory>/obt/bin
```

where <install\_directory> is the location where the software was installed.

- 4 Run the appropriate script:

---

| Platform | Syntax |
|----------|--------|
|----------|--------|

---

|     |              |
|-----|--------------|
| DOS | oadriver.bat |
|-----|--------------|

---

|      |               |
|------|---------------|
| UNIX | ./oadriver.sh |
|------|---------------|

---

- 5 Select Option 2 to uninstall the driver.
- 6 For DOS, select Option 1 to uninstall the ODBC driver or Option 2 to uninstall the OLE DB driver.

The ODBC or OLE DB database driver is uninstalled.

The following administrative tasks can help you to manage your query server environment:

- [Using multiple data sources](#) (page 151)
- [Managing users, roles, and privileges](#) (page 155)
- [Managing indexes](#) (page 157)
- [Managing server options](#) (page 159)
- [Viewing query server log files](#) (page 163)
- [Exposing an ADO.NET driver](#) (page 164)

## Using multiple data sources

The xmlData data source is created by default when you install the query server. Adding additional data sources allows you to:

- change the name of the data source from xmlData
- split your test data to improve access performance
- create separate access to test data along organizational lines
- [Adding a data source](#) (page 152)
- [Dropping a data source](#) (page 152)
- [Configuring a new data source for ODBC on UNIX](#) (page 153)
- [Relocating a data source](#) (page 154)

*In this section*

## Adding a data source

You can add one or more data sources. All data sources must have a unique name, and must be stored in a unique directory.

- 1 Navigate to the directory that contains the oaserver script.

*Example*

```
<install_directory>/obt/bin
```

where <install\_directory> is the location where the software was installed.

---

**WARNING!** Use of the following special characters with the addoadb scripts may result in an operating system error:

```
` $ ! ^ & ) ( \ ' = | ; " < > ,
```

You should avoid these characters wherever possible when adding a data source.

---

- 2 Run the script using the appropriate syntax:

| Platform | Syntax                                                         |
|----------|----------------------------------------------------------------|
| DOS      | oaserver -add <datasource_name><br>[datasource_root_path]      |
| UNIX     | ./oaserver.sh -add <datasource_name><br>[datasource_root_path] |

---

| Parameter            | Description                                                                                                                                                                                                                                                               |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| datasource_name      | The name of the new data source you want to create.                                                                                                                                                                                                                       |
| datasource_root_path | The optional path where you want to place the data source.<br><br>By default, the data source is placed in the following path:<br><br><install_directory>/obt/sqlxml/<datasource_name><br><br>where <install_directory> is the location where you installed the software. |

---

## Dropping a data source

Dropping a data source removes the following:

- the data source
- the data source root directory
- the collection configuration created for this data source

All XML data related to the data source is retained.

- 1 Navigate to the directory that contains the drop data source script.

*Example*

```
<install_directory>/obt/bin
```

where <install\_directory> is the location where the software was installed.

- 2 Run the script using the appropriate syntax:

| Platform | Syntax                                |
|----------|---------------------------------------|
| DOS      | oaserver -drop <datasource_name>      |
| UNIX     | ./oaserver.sh -drop <datasource_name> |

where <datasource\_name> is the name of the data source you want to drop.

## Configuring a new data source for ODBC on UNIX

The following instructions are for adding a data source called MyDataSource. Change the name as appropriate to your environment.

To configure a new data source for ODBC on Windows, follow the instructions in [Installing and configuring the ODBC database driver on Windows](#) (page 109).

For JDBC, there is no need to configure the data source. Following the instructions in [Connecting using the Interactive SQL \(JDBC\) client](#) (page 113) or [Connecting using the Interactive JDBC client \(ij\)](#) (page 114).

To configure a new data source:

- 1 Navigate to the directory that contains the odbc.ini file.

*Example*

```
<install_directory>/obt/sqlxml/client/
```

where <install\_directory> is the location where the software was installed.

- 2 Open the odbc.ini file with a text editor, and locate the [ODBC Data Sources] and [ODBC\_datasource\_name] sections.

*Example of odbc.ini file*

```
[ODBC Data Sources]
ODBCDataSource=DataDirect OpenAccess SDK 6.0
[ODBCDataSource]
Driver=/home/myhome/sqlxml/client/lib64/ivoa22.so
Description=DataDirect OpenAccess SDK 6.0
Host=localhost
Port=19988
ServerDataSource=xmlData
UseLDAP=0
DistinguishedName=
Encrypted=0
LoadBalancing=0
AlternateServers=
ConnectionRetryCount=0
ConnectionRetryDelay=3
CustomProperties=
```

- 3 Add the following entry to the data sources block:

```
MyDataSource=Customer ODBC Driver 6.0
```

*Example*

```
[ODBC Data Sources]
ODBCDataSource=DataDirect OpenAccess SDK 6.0
```

```
MyDataSource=Customer ODBC Driver 6.0
[ODBCDataSource]
```

- 4 Duplicate the [ODBCDataSource] block and replace the existing bold values with the appropriate values for the MyDataSource data source:

*Example*

```
[ODBC Data Sources]
ODBCDataSource=DataDirect OpenAccess SDK 6.0
MyDataSource=Customer ODBC Driver 6.0
[ODBCDataSource]
Driver=/home/myhome/sqlxml/client/lib64/ivoa22.so
Description=DataDirect OpenAccess SDK 6.0
Host=localhost
Port=19988
ServerDataSource=xmlData
UseLDAP=0
DistinguishedName=
Encrypted=0
LoadBalancing=0
AlternateServers=
ConnectionRetryCount=0
ConnectionRetryDelay=3
CustomProperties=
[MyDataSource]
Driver=/home/myhome/sqlxml/client/lib64/ivoa22.so
Description=Customer ODBC Driver 6.0
Host=<host_name>
Port=<port_name>
ServerDataSource=MyDataSource
```

| Value     | Description                                                                                           |
|-----------|-------------------------------------------------------------------------------------------------------|
| host_name | The name of the host machine or IP address on which the query server is running.                      |
| port_name | The port number used by the remote query server you are connecting to.<br>The default value is 19988. |

- 5 Save the odbc.ini file.

## Relocating a data source

You can relocate a currently existing data source to a different directory by dropping the existing data source and creating a new one.

**NOTE** All data in your collections must be reindexed on the new data source. See [Managing indexes](#) (page 157) for more information.

- 1 To avoid data loss, make a backup copy of the directory you plan to move.
- 2 Move the data source files to the new location.

- 3 Drop the data source using the instructions in [Dropping a data source](#) (page 152).
- 4 Add the new data source using the instructions in [Adding a data source](#) (page 152).
- 5 Configure the data source to point to the new location using the instructions in [Configuring a new data source for ODBC on UNIX](#) (page 153).

## Managing users, roles, and privileges

The query server uses users, roles, and privileges to establish individual permission to access the xmlData.

|            |                                                                                                                                                                        |
|------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| users      | an individual with specific privileges and a password.                                                                                                                 |
| roles      | a grouping of users with the same privileges. You can assign privileges to each individual user, or grant the privileges to a role, and assign that role to each user. |
| privileges | granting of access to a database table.                                                                                                                                |

By default, the query server is installed with the install user that has the DBA role.

---

**NOTE** When using Interactive SQL (ODBC), the privileges and roles statements require a prefix of 'exec' or '!'. This is not required for Interactive SQL (JDBC) or Interactive SQL (OLE DB).

---

## Managing users

Use standard SQL statements to manage users.

---

**NOTE** Do not use multi-byte characters when you create the user or password.

---

- To view existing users:  

```
select * from oa_users;
```
- To create a new user:  

```
create user <user_name> identified by <password>;
```
- To change the password of an existing user:  

```
alter user <user_name> identified by <password>;
```
- To grant a role to an existing user:  

```
grant <role_name> to <user>;
```
- To revoke a role from an existing user:  

```
revoke <role_name> from <user_name>;
```

| Parameter | Description                                                                                                      |
|-----------|------------------------------------------------------------------------------------------------------------------|
| user_name | the name of the user you want to create or alter. By default, all new users are created with the NO_ACCESS role. |
| password  | the password for the user.                                                                                       |
| role_name | the role you want to grant to the user.                                                                          |

## Managing roles

The following roles exist at installation:

| Role      | Description                                                                                                                                                                                                                                                                                                     |
|-----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DBA       | Grants all permissions on all objects, including: <ul style="list-style-type: none"> <li>• creating and dropping users and roles</li> <li>• creating and dropping collections</li> <li>• changing user passwords</li> <li>• creating and dropping indexes</li> <li>• setting and removing privileges</li> </ul> |
| NO_ACCESS | The default role granted to new users. The NO_ACCESS role can connect to the xmlData, but has no other permissions.                                                                                                                                                                                             |

- To create a new role:  
`create role <role_name>;`
- To drop an existing role:  
`drop role <role_name>;`

| Parameter | Description                                        |
|-----------|----------------------------------------------------|
| role_name | The name of the role you are creating or dropping. |

## Managing privileges

By default, the following privileges are available:

READ grants read access to a single table.  
 READ\_ANY grants read access to all tables in any schema.  
 READ\_SYSTEM grants read access to all system tables.

If a user has access to all of the tables in a particular view, then the view can also be accessed.

- To grant read access for one or more tables:  

```
set privilege READ on {<object_name>|ALL} (object_type)
to (<user_name | role_name>);
```

### Example

```
set privilege READ on CUSTOMER table to USER1;
```

- To grant read access to all tables:

```
set privilege READ_ANY to <user_name | role_name>;
```

- To grant read access to all system tables:

```
set privilege READ_SYSTEM to <user_name | role_name>;
```

- To remove a privilege from a user or role:

```
remove privilege READ_SYSTEM from <user_name |  
role_name>;
```

| Parameter   | Description                                                                       |
|-------------|-----------------------------------------------------------------------------------|
| user_name   | the name of the user you want to grant privileges to.                             |
| role_name   | the name of the role you want to grant privileges to.                             |
| object_name | the name of the table you want to grant read access to.                           |
| object_type | the type of object you want to grant read access to. The expected value is table. |

**NOTE** Because ij has a system use for the remove command, use single quotes to separate the statement when removing privileges in ij.

```
'remove privilege READ_SYSTEM from USER1';
```

## Managing indexes

The query server uses indexes to optimize your SQL queries. Any index defined when you created the cartridge is included in the collection by default. The pre-created indexes can be disabled or dropped. Standard range indexes can be created at any time by a user with the DBA role. The indexes are built when the table is queried, or the administrator runs the build range index command. Indexes do not modify the XML or XSD files

To see information about existing indexes, query the oa\_indexes table. The oa\_indexes table displays the following information:

| Field | Description                      |
|-------|----------------------------------|
| table | The table affected by the index. |

| Field      | Description                                                                                                                                                                                                                                                       |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| index_name | The name of the index.                                                                                                                                                                                                                                            |
| builtin    | Displays T if the index was created as part of the cartridge.<br>Displays F if the index was created after the table was extracted.                                                                                                                               |
| enabled    | Displays T if the index is currently enabled, and F if the index is disabled. Disabled indexes are not visible to the query optimizer.<br><br>To see information about the index that is available to the query optimizer, query against the oa_statistics table. |

**NOTE** When using Interactive SQL (ODBC), the create index statements require a prefix of 'exec' or '!'. This is not required for Interactive SQL (JDBC) or Interactive SQL (OLE DB).

- To add an index:  

```
create range index <index_name> on <table_name>(<Column list>);
```
- To drop an index:  

```
drop range index <index_name>;
```
- To enable an index:  

```
enable index <index_name>;
```
- To disable an index:  

```
disable index <index_name>;
```
- To build an index:  

```
build range index on [all | schema <schema_name> | table <table_name>]
```

  - Use `all` to build all indexes currently defined on the system.
  - Use `schema <schema_name>` to build all indexes defined within that schema.
  - Use `table <table_name>` to build all indexes defined for that table.

**NOTE** You cannot create indexes on system tables or system schemas.

# Managing server options

Users with the DBA role can modify the behavior of the server through the use of options.

---

**NOTE** Overriding data types and server options is global to the database, and all occurrences are converted.

---

*In this section*

- [Understanding the override options](#) (page 159)
- [Understanding override options for database data types](#) (page 160)
- [Overriding database data types and server options](#) (page 161)
- [Viewing existing overrides for database data types](#) (page 162)

## Understanding the override options

Users with the DBA role can modify the behavior of the server through the use of options. The server features that can be controlled through options include the number of threads used for searching data, how to treat character data with embedded nulls, and memory usage for column storage.

The following options are available:

- threads

A positive whole number representing the number of independent threads that should be used for reading data. The default value, 8, works well on systems with up to four processors. If your system has more than four processors, this number can be increased up to two times the number of physical processors.

---

**NOTE** Larger thread numbers can decrease performance.

---

- type

You can override source database data types in order to report a different data type to the client.

See [Understanding override options for database data types](#) (page 160).

- colMaxSize

This value is the maximum internal memory size used for storage of a single column value. The default value, 32768, should only be changed if you experience memory issues. The colMaxSize option defines when to stop using physical memory and start using virtual memory. The minimum size is 1024 and the maximum size is 4194304.

- ignoreNull

When set to true, ignores any null values in a column with character data without raising an error. If set to false, returns an error when null values exist in a column with character data. The default value is false.

- `duplicateObjectRename`

The `duplicateObjectRename` option controls whether or not duplicate table names are renamed in a multi-cartridge schema. The default value, `false`, returns an error message. Set the `duplicateObjectRename` option to `true` to rename the duplicate tables. This option can only be changed by a DBA user, and is global for the entire database.

- `showOverrideNames`

When set to `false`, the original source database column names are reported back to the client. When set to `true`, if column names were overridden in order to make valid XML tags, then the new column name is reported to the client. This is global for the entire database and takes effect immediately. The default value is `false`.

- `searchSchema`

The `searchSchema` option allows you to specify which schema you want to search. Any user can use the `searchSchema` option, and it is only valid for that individual user.

| If you query on:                                                                   | Default behavior                                                     | Behavior with <code>searchSchema</code> option                                                                                                      |
|------------------------------------------------------------------------------------|----------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| A table name that is fully-qualified                                               | Run the query.                                                       | Run the query.                                                                                                                                      |
| A table that is not fully-qualified, but only table with that name exists          | Run the query.                                                       | Qualify the table name with the schema, and run the query. If the table does not exist in that schema, return a “table not found” error.            |
| A table that is not fully-qualified, and more than one table with that name exists | Return the following error:<br>Multiple matches of<br><table> found. | Qualify the table name with the schema, and run the query. If the table does not exist in that schema, return the following error: Table not found. |

## Understanding override options for database data types

Users with the DBA role can override how data types are reported to the client. If your preferred client does not work well with a particular option, you can change how the data type is reported so that the columns can still be read.

### Example

- If multi-byte characters are stored in a database column defined as holding single-byte ascii characters, then you can use the `set option type` statement to override the data type in order for the data to display correctly when accessed from the query server.
- For certain numeric data types you can set the scale and precision of the number. For example, for a decimal data type, you could add a precision of 2 to represent US dollars.
- For CHAR and BINARY data types you can set the maximum length for the data type. For example, you can limit the CHAR field to 50 characters by adding a maximum length of 50.

Overriding options does not change the XSD or XML information, or how the query server interprets the XML data. After you override the data type, the type is reported differently, and, if possible, the XML data is converted to the desired type.

For data type overrides, the following java SQL data types are supported:

| Data type     | Attributes you can set                                                                                                       |
|---------------|------------------------------------------------------------------------------------------------------------------------------|
| BINARY        | <ul style="list-style-type: none"> <li>maxLen between 1 and 255</li> </ul>                                                   |
| BIT           |                                                                                                                              |
| CHAR          | <ul style="list-style-type: none"> <li>maxLen between 1 and 254</li> </ul>                                                   |
| DATE          |                                                                                                                              |
| DOUBLE        |                                                                                                                              |
| FLOAT         |                                                                                                                              |
| INTEGER       |                                                                                                                              |
| LONGVARBINARY | <ul style="list-style-type: none"> <li>maxLen between 1 and 2147483647</li> </ul>                                            |
| LONGVARCHAR   | <ul style="list-style-type: none"> <li>maxLen between 1 and 2147483647</li> </ul>                                            |
| NUMERIC       | <ul style="list-style-type: none"> <li>precision between 1 and 40</li> <li>scale between 0 and value of precision</li> </ul> |
| REAL          |                                                                                                                              |
| SMALLINT      |                                                                                                                              |
| TIME          |                                                                                                                              |
| TIMESTAMP     | <ul style="list-style-type: none"> <li>scale values of 0, 3, 6, or 9</li> </ul>                                              |
| TINYINT       |                                                                                                                              |
| VARBINARY     | <ul style="list-style-type: none"> <li>maxLen between 1 and 4000</li> </ul>                                                  |
| VARCHAR       | <ul style="list-style-type: none"> <li>maxLen between 1 and 4000</li> </ul>                                                  |
| WCHAR         | <ul style="list-style-type: none"> <li>maxLen between 1 and 254</li> </ul>                                                   |
| WLONGVARCHAR  | <ul style="list-style-type: none"> <li>maxLen between 1 and 2147483647</li> </ul>                                            |
| WVARCHAR      | <ul style="list-style-type: none"> <li>maxLen between 1 and 4000</li> </ul>                                                  |

## Overriding database data types and server options

You can override data types and server options with the set option SQL statement.

- 1 Invoke SQL\*Plus and log in as a user with privileges to access the xmlData data.

- 2 Override the data type or server option using the following syntax:

```
SET OPTION <option_type> <option_value>
```

| Parameter    | Description                                                                                      |
|--------------|--------------------------------------------------------------------------------------------------|
| option_type  | The option you want to override, for example, TYPE.                                              |
| option_value | The value you want to use for the option. Do not include any spaces or tabs in the option_value. |

#### Examples

| Statement                                                 | Expected result                                                                                   |
|-----------------------------------------------------------|---------------------------------------------------------------------------------------------------|
| set option type<br>clob=wlongvarchar                      | All CLOB data types are converted to WLONGVARCHAR.                                                |
| set option type<br>date=varchar,<br>maxLen=12             | All DATE data types are converted to VARCHAR with a maximum length of 12 characters in the field. |
| set option type<br>var2=numeric,<br>precision=5, scale=15 | All VAR2 data types are converted to NUMERIC with precision of 5 and scale of 15.                 |
| set option type<br>text=varchar,<br>maxLen=64000          | All SQL Server TEXT data types are converted to VARCHAR with a maximum length of 64000.           |
| set option colmaxsize<br>2222                             | Changes the default buffer size for all columns to 2222 bytes.                                    |
| set option<br>ignorenull=true                             | Ignores any null values in a column with character data without raising an error.                 |

**NOTE** When using Interactive SQL (ODBC), the set option statements require a prefix of 'exec' or '!'. This is not required for Interactive SQL (JDBC) or Interactive SQL (OLE DB).

- 3 To revert back to the original default value, use the following syntax:

```
SET OPTION <option_type> <option_value>=default
```

## Viewing existing overrides for database data types

You can view existing data types and options that have been overridden by querying the OA\_OPTIONS table.

- 1 Invoke SQL\*Plus and log in as a user with privileges to access the xmlData data.
- 2 Use the following query to view existing overrides.

```
SELECT * FROM OA_OPTIONS;
```

The query displays the option, value and description columns for each override for the current server.

| Column      | Example value                                  |
|-------------|------------------------------------------------|
| OPTION      | type                                           |
| VALUE       | var2=numeric                                   |
| DESCRIPTION | override var2 database types, treat as numeric |

**NOTE** If you need to verify what server you are using, you can use a query similar to: `select distinct table_qualifier from oa_tables where table_qualifier != 'SCHEMA'`

## Viewing query server log files

Depending on the type of interaction, the query server logs are stored in different files.

| Log file              | Description                                                   |
|-----------------------|---------------------------------------------------------------|
| oaserver.log          | Windows server installation log file.                         |
| oaclient.log          | Windows client installation log file.                         |
| oaserveruninstall.log | Windows server uninstall log file.                            |
| oaclientuninstall.log | Windows client uninstall log file.                            |
| oaerror.log           | Configuration or runtime error log for both Windows and UNIX. |
| obt.log               | Query server interaction log for both Windows and UNIX.       |

All log files are located in the following directory:

`<install_directory>/obt/log/`

where `<install_directory>` is the directory where you installed the software.

See also [Using log files](#) (page 95)

## Exposing an ADO.NET driver

If you are a .NET developer, you may want to install an ADO.NET driver that you can use for compilation with your .NET code. To install this driver, you use the `oadriver.bat` batch file. After the driver is installed it is available for ADO.NET compilation with your .NET code.

To install the ADO.NET driver:

- 1 Navigate to the directory that contains the driver installation file, `oadriver.bat`.

*Example*

```
cd <install_directory>/obt/bin
```

where `<install_directory>` is the location where the software was installed.

- 2 Double-click the installation batch file, `oadriver.bat`.
- 3 Select Option 1 to install the driver.
- 4 Select Option 3 to install the ADO.NET DB driver.

The ADO.NET DB driver is installed.

# A

## Configuration and runtime parameters

The following parameters govern the running of business flows and jobs:

- [Database to file configuration parameters](#) (page 165)
- [File naming parameters](#) (page 169)

### Database to file configuration parameters

Selecting Database to file on the Parameters page displays the configuration parameters applied to all business flows and jobs that employ database to file extraction.

The configuration parameters are divided into the following sections:

- [Core parameters](#) (page 165)
- [Performance parameters](#) (page 166)
- [Validation parameters](#) (page 167)
- [PDM parameters](#) (page 168)

#### Core parameters

The following parameters are located in the Core section:

| Parameter name                 | Description                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Allow masked data on upload    | By default, prevents any data that has been masked from being uploaded into the database. Set to true if you want to upload masked data instead of the original values.                                                                                                                                                                                                               |
| Compression algorithm          | Specifies the compression algorithm to apply to the XML and CSV files created after running the database to file extraction. Valid values are NONE and GZIP. <ul style="list-style-type: none"><li>• None—places the files in the specified directory without compression.</li><li>• GZIP—compresses the files into GZIP format and places them in the specified directory.</li></ul> |
| Extract file format            | Specifies whether to create XML denormalized or CSV normalized output.                                                                                                                                                                                                                                                                                                                |
| Job engine SQL tracing enabled | Turns on SQL tracing for the job engine repository connection.                                                                                                                                                                                                                                                                                                                        |
| Preserve temporary files       | Saves the temporary files generated when running the job.                                                                                                                                                                                                                                                                                                                             |

| Parameter name                                          | Description                                                                                                                                                                                               |
|---------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Primary key index location                              | Displays the location where the primary key indices are stored.                                                                                                                                           |
| Source database location                                | Specifies the name of the active database.                                                                                                                                                                |
| Unmask data on upload                                   | If data mask is reversible, unmask the data on upload. For more information about masking data, see the <i>HP Test Data Management Designer User Guide</i> .                                              |
| Use Data Movement Key to move data                      | Indicates whether the Data Movement Key should be used to identify rows, if available. If set to false on Oracle, the ROWID value will be used on all tables. This has no affect on non-Oracle databases. |
| User index location                                     | Displays the location where the user indexes are stored.                                                                                                                                                  |
| Verify Row Counts                                       | Set to True to perform verification of row counts between the current job and its corresponding selection job. Set to False to bypass verification. True is the default value.                            |
| Write XSD and Summary even when there are no data files | Indicates whether to write XSD and Summary files even when there are no data files                                                                                                                        |

## Performance parameters

The following parameters are located in the performance section:

| Parameter name             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Combined statement count   | Defines the maximum number of database statements which can be combined in a single query.                                                                                                                                                                                                                                                                                                                                                                                                                          |
| Data movement Batch size   | <p>Defines the number of driving table rows per transaction. This is used for data movement operations that operate on related parent and child rows in the same transaction, which includes the following:</p> <ul style="list-style-type: none"> <li>• copies in the database to file transactional data movement option</li> <li>• all database to file operations.</li> </ul> <p>The total number of rows operated on can be larger that the value entered, and depends on the characteristics of the data.</p> |
| Denormalize lookup records | Indicates whether to combine retrieval of multiple lookup table records with the referencing record in a single statement. Set to true or false.                                                                                                                                                                                                                                                                                                                                                                    |

| Parameter name                               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Eligibility Analytics Configuration          | <p>By default, eligibility analytics is disabled. If you want to enable eligibility analytics for a business flow, you must enable it before you run the business flow. Enabling eligibility analytics allows querying of the analytics tables for information on record eligibility.</p> <ul style="list-style-type: none"> <li>• Select “Disable the eligibility analytics” to improve performance</li> <li>• Select “Enable the eligibility analytics” to enable eligibility analytics.</li> </ul> <p><b>NOTE</b> If you select this option, you must include an interrupt step in your business flow to view the data.</p> |
| Maximum number of parallel workers           | Defines the default maximum number of job workers for tasks that can take advantage of parallelism.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Selection batch size                         | Defines the number of driving table rows per transaction. This is used for selection operations that select related parent and child row IDs from the source database into the selection tables.                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Type of indexes to create on Uploaded tables | Specifies how to populate index tables on upload.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Units of work                                | Defines the number of units amongst which the total amount of work will be divided. Each worker picks up a whole unit at a time to ensure clear progress indication and manage the total work in units for the job engine.                                                                                                                                                                                                                                                                                                                                                                                                     |

## Validation parameters

The following parameters are located in the validation section:

| Parameter name                | Description                                                                                                                                                                                                                                                                           |
|-------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Check cardinality constraints | Indicates whether to validate that the extracted data does not violate cardinality constraints in the model instance definition.                                                                                                                                                      |
| Checksum algorithm            | Indicates whether to run the checksum algorithm on created files.                                                                                                                                                                                                                     |
| Match rowcounts               | Indicates whether to verify that rowcounts in the XML files match those in the database.                                                                                                                                                                                              |
| XML file checksum validation  | Indicates whether to validate that the XML file checksums have not changed.                                                                                                                                                                                                           |
| XML Schema validation         | <p>Indicates whether to validate that the XML files do not violate their XML schema.</p> <p><b>TIP</b> For database to file copying, if you have large BLOB, CLOB, LONG, or LONG RAW fields, HP recommends leaving the value of the XML schema validation parameter set to false.</p> |

## PDM parameters

The following parameter is located in the PDM section:

| Parameter name       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run Output Option    | <p>Controls how much PDM produces diagnostic output in the "PDM server side log." Choose from the following list to define the logging detail:</p> <ul style="list-style-type: none"><li>• <b>Run and Log the SQL</b> executes the job, provides the same logging detail as <b>Run</b>, and also prints every SQL statement that is run.</li><li>• <b>Log the SQL without running</b> prints all the SQL statements that are generated. The SQL statements are not executed.</li><li>• <b>Run</b> executes the job and reports the minimum amount of information.</li><li>• <b>Run and Log the SQL and the PLAN</b> executes the job, provides the same logging detail as <b>Run</b>, and also prints the execution plan for every SQL statement.</li><li>• <b>Log the SQL and the PLAN without running</b> prints all the SQL statements and the execution plan. The SQL statements are not executed.</li></ul> <p>This parameter is only used with advanced selection or partitioned data movement.</p> |
| Start Partition List | <p>The comma-separated list of partitions to be extracted. The partitions must exist in the table specified in Start Table Alias. No spaces can be used in the list. Defaults to null if missing or left blank. This parameter is only used with advanced selection or partitioned data movement.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Start Table Alias    | <p>Specifies the unique table alias of the table for which you want to extract partitions, as specified by Designer. Defaults to null if missing or left blank. This parameter is only used with advanced selection or partitioned data movement.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Unify MTU Selections | <p>Unify selections in multiple table uses (MTU) into one selection table, and remove duplicate rows. For database to file copying, the default value for this parameter is false, enabling multiple table users to retain the selected rows. There may be duplication of rows in the result.</p> <p>Set this parameter to true to remove duplicate rows.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |

## File naming parameters

The following file naming parameters are used only database to file extraction, and can be set for each individual cartridge:

| Parameter                      | Description                                                                                                                                                 |
|--------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Group File Prefix              | The prefix for the group XML or CSV files. The default value is <cartridge_name>_, where cartridge_name is the name of the cartridge.                       |
| Group File Suffix              | The suffix you want to use for the group XML or CSV files.                                                                                                  |
| Group XML Schema File Prefix   | The prefix for the group XML schema files. The default value is <cartridge_name>_, where cartridge_name is the name of the cartridge.                       |
| Group XML Schema File Suffix   | The suffix you want to use for the group XML schema files.                                                                                                  |
| Schema Mapping File for Upload | Specifies a schema mapping file to be applied on upload. For information about schema mapping, refer to <a href="#">Schema mapping for upload</a> (page 84) |
| Summary File Prefix            | The prefix for the summary files. The default value is <cartridge_name>_, where cartridge_name is the name of the cartridge.                                |
| Summary File Suffix            | The suffix you want to use for the summary files.                                                                                                           |
| Summary XML Schema File Prefix | The prefix for the summary XML schema files. The default value is <cartridge_name>_, where cartridge_name is the name of the cartridge.                     |
| Summary XML Schema File Suffix | The suffix you want to use for the summary XML schema files.                                                                                                |



This chapter covers advanced tasks that are less frequently performed.

*In this chapter*

- [SQL tuning](#) (page 171)
- [Using views for customized reporting](#) (page 181)
- [Enabling SQL trace for Oracle](#) (page 181)
- [Enabling the Web Console scheduler through a Web service](#) (page 182)

## SQL tuning

Test Data Management uses SQL hints, session variables, and custom pre-statement execution code to allow you to configure the SQL statements in your Oracle or SQL Server installation, and improve the performance of your selection and data movement statements.

*In this section*

- [About SQL tuning](#) (page 171)
- [About statements](#) (page 172)
- [About using session variable statements](#) (page 175)
- [Editing the sql\\_tuning.properties file](#) (page 176)
- [Specifying SQL hints for non-intrusive environments](#) (page 180)

## About SQL tuning

You can create hints, set session variables, or create custom pre-statement execution code that affects the selection and data movement statements for your installation.

Each modification is applied to a specific SQL statement for an individual cartridge in a business flow. For example, if the ORDERS\_BF business flow contains two cartridges, ORDERS\_DOM and ORDERS\_INTL, you would have to write separate hints for each cartridge, or use wildcards.

Each cartridge contains the following seed statement files in the cartridge directory:

| Seed statement files          | Description                                                                                                                                                                            |
|-------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| seed-selection-statements.xml | Contains SQL statements that apply to the cartridge selection process.<br><br>Data selection statements are supported for database to file cartridges and database to file cartridges. |
| seed-dm-sql-statements.xml    | Contains SQL statements that apply to the cartridge data movement process.<br><br>Data movement statements are supported for database to file cartridges.                              |

With wildcards, each modification can affect one or more statements in each seed statement file. The modifications are defined in the `sql_tuning.properties` file, which is stored in the following directory:

```
<install_directory>/obt/config
```

where `<install_directory>` is the location where you installed the software.

If you are using Advanced Selection, selection statements are created at runtime. If you want to use SQL tuning with Advanced Selection, you should run Advance Selection in diagnostic mode by setting the configuration parameter Run Output Option to `SHOW_PLAN` to get a list of all selection statements that Advanced Selection will execute along with the associated execution plans for each statement. You can use the diagnostic information to create specific SQL tuning hints.

## About statements

When you deploy database to file copying, the SQL statements in the `seed-selection-statements.xml` and `seed-dm-sql-statements.xml` files are generated. Each statement contains the following information:

- source environment
- context
- appspack\_name
- table\_identifier
- statement\_name

*Example*

```
<SRC_ENV>Oracle_OLTP</SRC_ENV>
<CONTEXT>OLTP_SELECTION</CONTEXT>
<APPSPACK_NAME>d2d_trans</APPSPACK_NAME>
<TABLE_IDENTIFIER>ORDER_HEADER</TABLE_IDENTIFIER>
<STATEMENT_NAME>INSERT_SELECTION_NO_ANALYTICS
</STATEMENT_NAME>
```

*In this section*

- [About context values](#) (page 173)
- [About statement\\_name values](#) (page 173)
- [About appspack\\_name and table\\_identifier values](#) (page 174)

### About context values

The following context values are valid:

| Context               | Description                 |
|-----------------------|-----------------------------|
| OLTP_SELECTION        | The extract selection step. |
| ELIGIBILITY_ANALYTICS | Eligibility analytics step. |

### About statement\_name values

Each context has one or more of the following statement names.

*In this section*

- [Selection statement names](#) (page 173)
- [Copy and move statement names](#) (page 173)
- [Eligibility analytics statement name](#) (page 174)

#### Selection statement names

The following statement values are used when inserting into the selection tables:

| Statement                     | Description                                                                                                                                                                                                                                                       |
|-------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| INSERT_SELECTION_ANALYTICS    | Used when the Eligibility Analytics Configuration configuration parameter in the Web Console is set to “Enable the eligibility analytics”.<br><br>Eligibility Analytics must be enabled in both Designer and the Web Console before eligibility analytics occurs. |
| INSERT_SELECTION_NO_ANALYTICS | Used when the Eligibility Analytics Configuration configuration parameter in the Web Console is set to “Disable the eligibility analytics”.                                                                                                                       |

#### Copy and move statement names

The following statement values are used when moving data between the source database and the target. Each move operation consists of an INSERT statement.

| Statement         | Description                                                           |
|-------------------|-----------------------------------------------------------------------|
| COPY_TRX_RANGE    | Used for fully transactional data moment when RANGE is applicable.    |
| COPY_TRX_NO_RANGE | Used for fully transactional data moment when NO_RANGE is applicable. |
| COPY_TP_RANGE     | Used for table parallel data moment when RANGE is applicable.         |
| COPY_TP_NO_RANGE  | Used for table parallel data moment when NO_RANGE is applicable.      |

NO\_RANGE will be executed when one of the following configuration combinations is set:

| Configuration parameter                  | Required value |
|------------------------------------------|----------------|
| Use database parallelism to extract data | TABLE_PARALLEL |
| Number of rows per commit                | 0              |

or

| Configuration parameter                  | Required value      |
|------------------------------------------|---------------------|
| Use database parallelism to extract data | FULLY_TRANSACTIONAL |
| Data movement batch size                 | 0                   |

If neither of these two combinations is set, RANGE will be used.

#### Eligibility analytics statement name

The following statement value is used for eligibility analytics:

| Statement             | Description                     |
|-----------------------|---------------------------------|
| ELIGIBILITY_ANALYTICS | Used for eligibility analytics. |

#### About appspack\_name and table\_identifier values

The appspack\_name and table\_identifier values depend on your cartridge and the tables included in that cartridge. The appspack\_name corresponds to the cartridge name designated in Designer, and the table\_identifier corresponds to the table alias designated in the model in Designer.

See the seed-selection-statements.xml and seed-dm-sql-statements.xml files for the valid values.

In Advanced Selection, the `table_identifier` values must be set using the wildcard operation because specific table name hints are not supported in advanced selection.

## About using session variable statements

Session variable statements require different commands depending on the database you are using.

| Database   | Command                                   |
|------------|-------------------------------------------|
| Oracle     | Uses the ALTER SESSION command arguments. |
| SQL Server | Uses the SET command arguments.           |

Because Test Data Management automatically wraps it with the appropriate command (ALTER SESSION or SET), the variable value is just the arguments for the database command.

### *SQL Server example*

For SQL Server, if you want to set the deadlock priority to low, and you would normally change the settings with:

```
SET deadlock_priority low
```

set the value to:

```
deadlock_priority_low
```

### *Oracle example*

For Oracle, if you want to set optimizer index caching to 10, and you would normally change the optimizer settings with:

```
ALTER SESSION set optimizer_index_caching=10
```

set the value to:

```
set optimizer_index_caching=10
```

*See also* [Editing the sql\\_tuning.properties file](#) (page 176)

## About using custom pre-statement execution code

The PreExec code enables you to specify custom code to be run before the selection or data movement statements.

Pre-statement execution code is run in different locations depending on the type of statement.

| Statement           | Location                                              |
|---------------------|-------------------------------------------------------|
| Selection statement | The PreExec code is run on the source local database. |
| Copy statement      | The PreExec code is run on the target local database. |

---

**NOTE** If the statement you are modifying is for a Reload job, the locations are reversed.

---

*Example*      `Oracle_OLTP.OLTP_SELECTION.INVENTORY.ITEM.INSERT_SELECTION_ANALYTICS.PREEEXEC_NAME=apps_initialization`

where `apps_initialization` is the name of a SQL block that you want to execute.

For advanced selection, the syntax for the session variable is:

```
<src_env>.ADVANCED_SELECTION.<appspack_name>.*.*.SESSION_VAR1=set optimizer_index_caching = 1
```

where `TABLE_IDENTIFIER` and `STATEMENT_NAME` are set to wildcards.

## Editing the `sql_tuning.properties` file

Use the `sql_tuning.properties` file to add SQL hints or set session variables.

- 1 Navigate to the directory that contains the seed statements for the cartridge you want to modify.

*Example*      `<install_directory>/obt/artifacts/businessflow/<business_flow_name>/cartridge/<product>/<cartridge_name>`

| Parameter                               | Description                                                                                                            |
|-----------------------------------------|------------------------------------------------------------------------------------------------------------------------|
| <code>&lt;install_directory&gt;</code>  | The location where you installed the software.                                                                         |
| <code>&lt;business_flow_name&gt;</code> | The name of the business flow that contains the cartridge you want to modify.                                          |
| <code>&lt;product&gt;</code>            | The copy method the cartridge uses. <ul style="list-style-type: none"><li>• <code>oa</code>—database to file</li></ul> |
| <code>&lt;cartridge_name&gt;</code>     | The individual cartridge you want to query.                                                                            |

---

**NOTE** Database to file cartridges only support selection statement hints.

---

- 2 Open the seed statement file you want to view.
  - `seed-selection-statements.xml`—contains selection statements
  - `seed-dm-sql-statements.xml`—contains data movement statements

---

**NOTE** Do not edit the seed statement files.

---

- 3 Search the seed statement file for the statement you want to modify.

You need to note the following information:

  - source environment
  - context

- appspack\_name
- table\_identifier
- statement\_name

*Example*

```
<SRC_ENV>Oracle_OLTP</SRC_ENV>
<CONTEXT>OLTP_SELECTION</CONTEXT>
<APPSPACK_NAME>d2d_trans</APPSPACK_NAME>
<TABLE_IDENTIFIER>ORDER_HEADER</TABLE_IDENTIFIER>
<STATEMENT_NAME>INSERT_SELECTION_NO_ANALYTICS
</STATEMENT_NAME>
```

- 4 Open the following file in a text editor:

```
<install_directory>/obt/config/sql_tuning.properties
```

where <install\_directory> is the location where you installed the software.

**NOTE** For Oracle, the sql\_tuning.properties file has default hints. The SQL Server sql\_tuning.properties file has no defaults.

*To add a hint*

- 5 Add a new hint using the following format:

```
<SRC_ENV>.<CONTEXT>.<APPSPACK_NAME>.<TABLE_IDENTIFIER>.<STATEMENT_ NAME>.<hintType>=<hint>
```

| Parameter          | Description                                                            |
|--------------------|------------------------------------------------------------------------|
| <SRC_ENV>          | The contents of the <SRC_ENV> tag in the seed statement file.          |
| <CONTEXT>          | The contents of the <CONTEXT> tag in the seed statement file.          |
| <APPSPACK_NAME>    | The contents of the <APPSPACK_NAME> tag in the seed statement file.    |
| <TABLE_IDENTIFIER> | The contents of the <TABLE_IDENTIFIER> tag in the seed statement file. |
| <STATEMENT_NAME>   | The contents of the <STATEMENT_NAME> tag in the seed statement file.   |
| <hintType>         | INSERT_HINT, SELECT_HINT or DELETE_HINT.                               |
| <hint>             | The SQL hint.                                                          |

*Example hint*

```
OLTP_SELECTION.d2d_trans.ORDER_HEADER.INSERT_SELECTION_NO_ANALYTICS.<hintType>=<hint>
```

**TIP** You can use wildcards to apply the changes to more than one statement. \*.\*.\*.\*.<hintType>=<hint> applies the hint to all statements in all installed cartridges.

*Example SQL in seed file*

A SQL statement in a seed file looks something like the following sample. The items between the ## symbols are the available hintTypes for that statement.

```

INSERT ##INSERT_HINT## INTO "CUSTOLTP_HIST"."ORD"
("ORDERDATE", "ORDID", "OBT_WF_RUN_ID", "OBT_ROW_SEQ",
"OBT_TIMESTAMP", "OBT_SAVED_ROWID" ) SELECT
##SELECT_HINT## "S"."ORDERDATE",
"S"."ORDID",
"S"."OBT_WF_RUN_ID",
"S"."OBT_ROW_SEQ",
sysdate,
"S"."OBT_SAVED_ROWID"
FROM "OBT_IF"."ORD_SVO"@ORCL3 "S"
WHERE ("S"."OBT_WF_RUN_ID"=?)
AND ("S"."OBT_ROW_SEQ" BETWEEN ? AND ?)

```

## 6 Fill in the appropriate SQL hint.

*Oracle example*

```

Oracle_OLTP.OLTP_SELECTION.d2d_trans.ORDER_HEADER.INSERT_
SELECTION_NO_ANALYTICS.SELECT_HINT=use_nl

```

*SQL Server example*

```

MSOLTP.OLTP_SELECTION.d2d_trans.ORDER_HEADER.INSERT_SELEC
TION_NO_ANALYTICS.SELECT_HINT=FAST 5

```

## 7 Save the sql\_tuning.properties file.

*To add a session variable*

## 8 Add a new session variable using the following format:

```

<SRC_ENV>.<CONTEXT>.<APPSPACK_NAME>.<TABLE_IDENTIFIER>.<S
TATEMENT_ NAME>.<SESSION_VARn>=<var>

```

| Parameter          | Description                                                            |
|--------------------|------------------------------------------------------------------------|
| <SRC_ENV>          | The contents of the <SRC_ENV> tag in the seed statement file.          |
| <CONTEXT>          | The contents of the <CONTEXT> tag in the seed statement file.          |
| <APPSPACK_NAME>    | The contents of the <APPSPACK_NAME> tag in the seed statement file.    |
| <TABLE_IDENTIFIER> | The contents of the <TABLE_IDENTIFIER> tag in the seed statement file. |
| <STATEMENT_NAME>   | The contents of the <STATEMENT_NAME> tag in the seed statement file.   |
| <SESSION_VARn>     | The identifier for the session variable.                               |
| <var>              | The session variable.                                                  |

*Example*

```

Oracle_OLTP.OLTP_SELECTION.d2d_trans.ORDER_HEADER.INSERT_
SELECTION_NO_ANALYTICS.<SESSION_VARn>=<var>

```

**TIP** You can use wildcards to apply the changes to more than one statement. `*.*.*.*.<SESSION_VARn>=<var>` applies the session variable to all statements in all installed cartridges.

For example, if the default statement is as follows:

```
DefEnv.OLTP_SELECTION.*.*.*.INSERT_HINT=APPEND
```

changing the statement to:

```
DefEnv.OLTP_SELECTION.INVENTORY.ITEM.*.INSERT_HINT=PARALLEL
```

will override the APPEND hint for only the ITEM table in INVENTORY.

## 9 Fill in the appropriate session variable.

*Oracle example*

```
Oracle_OLTP.OLTP_SELECTION.d2d_trans.ORDER_HEADER.INSERT_SELECTION_NO_ANALYTICS.SESSION_VAR3=set
optimizer_index_caching=10
```

*SQL Server example*

```
MSOLTP.OLTP_SELECTION.d2d_trans.ORDER_HEADER.INSERT_SELECTION_NO_ANALYTICS.SESSION_VAR3=deadlock_priority low
```

## 10 Save the sql\_tuning.properties file.

*To add a preexec statement*

## 11 Add a new pre-statement execution code using the following format:

```
<SRC_ENV>.<CONTEXT>.<APPSPACK_NAME>.<TABLE_IDENTIFIER>.<STATEMENT_NAME>.PREEXECNAME=<preexecname>
```

| Parameter          | Description                                                            |
|--------------------|------------------------------------------------------------------------|
| <SRC_ENV>          | The contents of the <SRC_ENV> tag in the seed statement file.          |
| <CONTEXT>          | The contents of the <CONTEXT> tag in the seed statement file.          |
| <APPSPACK_NAME>    | The contents of the <APPSPACK_NAME> tag in the seed statement file.    |
| <TABLE_IDENTIFIER> | The contents of the <TABLE_IDENTIFIER> tag in the seed statement file. |
| <STATEMENT_NAME>   | The contents of the <STATEMENT_NAME> tag in the seed statement file.   |
| <preexecname>      | The name of the custom code you want to execute.                       |

*Example*

```
Oracle_OLTP.OLTP_SELECTION.INVENTORY.ITEM.INSERT_SELECTION_NO_ANALYTICS.PREEXEC_NAME=apps_initialization
```

where apps\_initialization is the name of the custom code you want to execute.

**TIP** You can use wildcards to apply the changes to more than one statement. `*.*.*.*.<PREEXEC_NAME>=<preexecname>` applies the modification to all statements in all installed cartridges.

## 12 Save the sql\_tuning.properties file.

# Specifying SQL hints for non-intrusive environments

In the `sql_tuning.properties` file, you can add hints for optimizing particular SQL statements. You can specify hints for driving statements and cursor loops.

Hints for driving statements have the following syntax:

```
<env_name>.OLTP_LITE_SELECTION.<cartridge>.<table_alias>.  
DRIVING_STATEMENT.<hint_type>=<hint>
```

Hints for cursor loops have the following syntax:

```
<env_name>.OLTP_LITE_SELECTION.<cartridge>.<table_alias>.  
CURSOR_LOOP.<hint_type>=<hint>
```

**NOTE** You should understand how your particular database handles hints before implement them in your `sql_tunning.properties` file.

| Parameter     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <env_name>    | The database that the hints is being applied to. For example, SQL Server or Oracle.                                                                                                                                                                                                                                                                                                                                                                                                          |
| <cartridge>   | The name of the cartridge. You can specify * to apply the hint to all cartridges.                                                                                                                                                                                                                                                                                                                                                                                                            |
| <table_alias> | The table to apply the hint to. You can specify * to apply the hint to all tables.                                                                                                                                                                                                                                                                                                                                                                                                           |
| <hint_type>   | <p>The hint type specifies where in the SQL statement to insert the hint. The possible values are:</p> <ul style="list-style-type: none"><li>• PREFIX-HINT—The hint is at the beginning the SQL statement before the SELECT clause.</li><li>• SELECT_HINT—The hint is placed after SELECT in the SQL statement.</li><li>• TABLE_ALIAS_HINT—The hint is placed after each table alias in the FROM clause.</li><li>• SUFFIX_HINT—The hint is placed at the end of the SQL statement.</li></ul> |
| <hint>        | <p>The SQL hint.</p> <p>In Advanced Selection, the hint name is defined using the following format:</p> <p>HINT_x</p> <p>where x is an integer. You can obtain the hint number from the list of statements produced by running Advanced Selection in diagnostic mode, setting the configuration parameter "RUN_OUTPUT_OPTION" to "SHOW_PLAN".</p>                                                                                                                                            |

## Using views for customized reporting

HP Test Data Management supports the following views of the product metadata:

| View                   | Definition                                                                             |
|------------------------|----------------------------------------------------------------------------------------|
| OBTWC_BF_RUNS_V        | Displays business flow runs, but does not display the detailed steps.                  |
| OBTWC_RUN_DETAILS_V    | Displays business flow runs and the detailed steps of the business flow.               |
| OBTWC_RUN_PARAMETERS_V | Displays the name & value of each parameter and maps them to an individual job run_id. |

You can use these views to create customized reports for your installation.

## Enabling SQL trace for Oracle

You can enable or disable Oracle SQL trace using properties files. Because SQL trace can impact performance, HP recommends that you only enable it for performance tuning.

- To enable SQL tracing for the database to file selection, use the `sql_tuning.properties` file.
- To enable SQL tracing for database to file data movement, use the `outerbay.properties` file.

The trace files are saved to the `user_dump_dest` directory. For more information, see your Oracle documentation.

### Enabling SQL trace using the `sql_tuning.properties` file

Use the `sql_tuning.properties` file to enable SQL trace for database to file selection and data movement.

- 1 Open the `sql_tuning.properties` file.

*See also* [SQL tuning](#) (page 171)

- 2 Add a session variable to enable SQL trace.

*Example*

```
SESSION_VAR1=set events '10053 trace name context
forever, level 1'
```

The trace begins before the statement that the session variable is attached to.

For example, if you attach it to the following statement:

```
OLTP_SELECTION.INVENTORY.ITEM.INSERT_SELECTION_ANALYTICS.
SESSION_VAR1=set events '10053 trace name context
forever, level 1'
```

the trace command is issued before the `OLTP_SELECTION.INVENTORY.ITEM.INSERT_SELECTION_ANALYTICS` SQL statement is run.

### Enabling SQL trace using the `outerbay.properties` file

Use the `outerbay.properties` file to enable SQL trace for database to file data movement.

- 1 Navigate to the directory that contains the `outerbay.properties` file.

*Example*

```
<install_directory>/obt/config
```

where `<install_directory>` is the location where you installed the software.

- 2 Open the `outerbay.properties` file with a text editor.
- 3 Locate the SQL trace section.
- 4 Update the properties file. By default, the following properties are set:  
`DASL.sqlTrace.level=1`  
`DASL.sqlTrace.components=ALL`
- 5 Save the `outerbay.properties` file.

## Enabling the Web Console scheduler through a Web service

A Web Service Description Language (WSDL) file is available for creating a client for accessing the Web Console scheduler as a Web service. The WSDL file is `JobSchedulerService.wsdl`. You can access the file at `http://<host>:<port>/WebConsole/services/JobSchedulerService?wsdl`, where `<host>:<port>` is the location of the Web Console.

To use the Web service, generate a client proxy from `JobSchedulerService.wsdl`. You can then use your client proxy to interact with the Web Console scheduler. The `JobSchedulerService` Web service uses `UsernameToken` security as defined in the WS-Security specification.

# C

## Scripted product setup and business flow deployment

If you plan to set up and deploy HP Test Data Management multiple times, you can use scripted deployment. In this section

- [Understanding properties files](#) (page 183)
- [Scripting the repository setup](#) (page 184)
- [Scripting the environment creation](#) (page 187)
- [Scripting business flow deployment](#) (page 190)

*See also* Chapter 3 of the *HP Test Data Management Installation Guide* for information about scripted installation of the product.

### Understanding properties files

Scripted deployment requires that you create the following properties files to define the installation.

| Property file                   | Description                                                      |
|---------------------------------|------------------------------------------------------------------|
| repository.install.properties   | Contains properties to create your repository.                   |
| product.install.properties      | Contains properties to create environments with database to file |
| businessflow.install.properties | Contains properties to deploy your business flows.               |

You can create these files in one of two ways:

- Use the Web Console to generate the properties files.
- Use a text editor to manually create the files.

The instructions in this chapter assume that you have used the Web Console at least once to create the properties files in the install directory.

**NOTE** Properties files should contain property values with ISO 8859-1 character encoding only. For more information on using characters that cannot be expressed using ISO 8859-1 encoding, see [Using special characters in properties files](#) (page 184).

# Using special characters in properties files

Properties files should contain property values with ISO 8859-1 character encoding only. Unicode escapes can be used for characters that cannot be directly represented in this encoding. One u character can be used per escape sequence.

To convert properties files that contain non-ISO 8859-1 character encoding:

- 1 Run the Native-to-ASCII Converter, native2ascii, with the following syntax:

```
native2ascii -encoding <encoding_name> <input_file>
<output_file>
```

| Where           | Is                                                                                                                               |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------|
| <encoding_name> | A valid Java encoding. For more information, see the Sun Java website at <a href="http://java.sun.com">http://java.sun.com</a> . |
| <input_file>    | The original properties file with non-ISO 8859-1 character encoding.                                                             |
| <output_file>   | The new properties file with only ISO 8859-1 character encoding.                                                                 |

- 2 Use the new properties file for your scripted installation.

# Scripting the repository setup

To script your repository installation, you need to create a file with the properties you want to use, and then run the script. The following sections contain the scripting procedure, the properties in the properties file, and examples of the properties file.

**NOTE** If you are extracting data from Sybase, you must install your repository on either an Oracle or SQL Server database, or use the embedded repository.

*In this section*

- [Scripted repository installation procedure](#) (page 184)
- [Scripted repository installation properties](#) (page 185)
- [Scripted repository installation properties file example](#) (page 186)

# Scripted repository installation procedure

If you choose to include passwords or encryption.key properties in the properties file, they are saved in the text file and can be accessed. To ensure that the passwords are not saved, omit the entire password property line from the properties file. You will then be prompted for the passwords.

- 1 Ensure that HP Test Data Management has been installed.

*See also*      *HP Test Data Management Installation Guide*

- Example*      2    Navigate to the directory that contains the installation scripts:
- <install\_directory>/obt/install
- where <install\_directory> is the location you installed the software.
- 3    Open the repository.install.properties file in a text editor, or create the file if it does not exist.
- 4    Edit the properties file as necessary for your installation.
- See also*      [Scripted repository installation properties](#) (page 185)
- 5    Open a command window.
- 6    Install the repository using the appropriate syntax:

---

#### Platform Syntax

---

UNIX      ./deploy\_repository.sh <properties\_file\_name>

---

DOS      deploy\_repository.bat <properties\_file\_name>

---

Where `properties_file_name` is the name of the properties file you are using for the repository.

## Scripted repository installation properties

The following properties are used for installing the repository:

| Property name               | Expected value                                                                                                                                           |
|-----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------|
| encryption.key              | The encryption key to be created.<br>If you omit the line, you will be prompted for the encryption key.                                                  |
| repository.conn.rdbmstype   | sqlserver or oracle.<br>For the embedded repository, the value should be derbydb_10.                                                                     |
| repository.conn.dbserver    | Database SID or server name for the repository.                                                                                                          |
| repository.conn.host        | Host name for the repository.                                                                                                                            |
| repository.conn.port        | Port number for the repository.                                                                                                                          |
| repository.dbadmin.username | Repository database or database server administrator username. (Oracle, SQL Server only)                                                                 |
| repository.dbadmin.password | Repository database or database server administrator password. (Oracle, SQL Server only)<br>If you omit the line, you will be prompted for the password. |
| repository.owner.name       | Repository user to be created by the installer.                                                                                                          |
| repository.owner.password   | Repository user password to be created.<br>If you omit the line, you will be prompted for the password.                                                  |

---

| Property name                           | Expected value                                                                                          |
|-----------------------------------------|---------------------------------------------------------------------------------------------------------|
| repository.default.storagelocation      | Default tablespace to use when creating repository users. (Oracle only)                                 |
| repository.temp.storagelocation         | Temporary tablespace to use when creating repository users. (Oracle only)                               |
| repository.dbname                       | Repository database name. (SQL Server, embedded repository only)                                        |
| repository.default.storagelocation.size | Data device size to be allowed to the repository database in MB. (SQL Server, embedded repository only) |
| repository.log.storagelocation.size     | Log device size to be allocated to the repository database in MB. (SQLServer, embedded repository only) |
| console.admin.username                  | The username for the Web Console administrator.                                                         |
| console.admin.passwd                    | The password for the Web Console administrator.                                                         |
| console.admin.email                     | Optional. The email address of the Web Console administrator.                                           |
| console.admin.userRealName              | Optional. The real name of the Web Console administrator.                                               |
| console.admin.phone                     | Optional. The phone number of the Web Console administrator.                                            |
| console.admin.description               | Optional. The description of the Web Console administrator.                                             |

## Scripted repository installation properties file example

The following examples demonstrate the use of the properties file.

*Oracle*

```

encryption.key=myEncryptionKey
repository.conn.rdbmstype=oracle
repository.conn.dbserver=orcl1
repository.conn.host=myHost
repository.conn.port=1521
repository.dbadmin.username=system
repository.dbadmin.password=myPassword
repository.owner.name=obt_rep
repository.owner.password=myPassword
repository.default.storagelocation=USERS
repository.temp.storagelocation=TEMP
console.admin.username=admin
console.admin.passwd=admin

```

*SQL Server*

```

encryption.key=myEncryptionKey
repository.conn.rdbmstype=sqlserver
repository.conn.dbserver=MSOLTP
repository.conn.host=myHost
repository.conn.port=1433
repository.dbadmin.username=sa
repository.dbadmin.password=myPassword
repository.owner.name=obt_rep
repository.owner.password=myPassword
repository.dbname=obt_rep
repository.default.storagelocation.size=50
repository.log.storagelocation.size=50

```

*Embedded repository*

```
console.admin.username=admin
console.admin.passwd=admin

encryption.key=myEncryptionKey
repository.conn.conntype=default
repository.conn.rdbmstype=derbydb
repository.conn.dbserver=obt_rep
repository.conn.host=myHost
repository.conn.port=1527
repository.owner.name=obt_rep
repository.owner.password=myPassword
repository.dbname=obt_rep
console.admin.username=admin
console.admin.passwd=admin
```

## Scripting the environment creation

To script your environment creation, you need to create a file with the properties you want to use, and then run the script. The following sections contain the scripting procedure, the properties in the properties file, and examples of the properties file.

Each environment requires a separate `product.install.properties` file.

*In this section*

- [Scripted environment creation procedure](#) (page 187)
- [Scripted environment creation properties](#) (page 188)
- [Scripted environment creation properties file example](#) (page 189)

## Scripted environment creation procedure

The sample `product.install.properties` file is installed with HP Test Data Management.

If you choose to include passwords or `encryption.key` properties in the properties file, they are saved in the text file and can be accessed. To ensure that the passwords are not saved, omit the entire password property line from the properties file. You will then be prompted for the passwords.

---

**NOTE** Database to file extraction is installed with all environments.

---

- 1 Ensure that HP Test Data Management has been installed.

*See also* [HP Test Data Management Installation Guide](#)

- 2 Navigate to the directory that contains the installation scripts:

*Example*

```
<install_directory>/obt/install
```

where `<install_directory>` is the location you installed the software.

- 3 Open the `product.configure.properties` file in a text editor.
- 4 Edit the properties file as necessary for your installation.

See also [Scripted repository installation properties](#) (page 185)

- 5 Open a command window.
- 6 Create the environment and deploy the product using the appropriate syntax:

---

**Platform Syntax**

---

|      |                                                               |
|------|---------------------------------------------------------------|
| UNIX | <code>./deploy_product.sh &lt;properties_file_name&gt;</code> |
|------|---------------------------------------------------------------|

---

|     |                                                              |
|-----|--------------------------------------------------------------|
| DOS | <code>deploy_product.bat &lt;properties_file_name&gt;</code> |
|-----|--------------------------------------------------------------|

---

Where `properties_file_name` is the name of the properties file you are using.

## Scripted environment creation properties

The following properties are used for creating the environment and deploying database to file:

| Property name                                 | Expected value                                                                                                                 |
|-----------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------|
| encryption.key                                | Encryption key.<br>If you omit the line, you will be prompted for the encryption key.                                          |
| environment.id                                | The name you want to use for the environment.                                                                                  |
| environment.description                       | The optional description of the environment.                                                                                   |
| source.rdbms.name                             | Acceptable values are oracle, sqlserver, or sybase.                                                                            |
| source.conn.dbserver                          | The name of the Oracle database service, SQL Server or Sybase server name, or data source for the source database.             |
| source.conn.host                              | The host for the source database.                                                                                              |
| source.conn.port                              | The port number for the source database.                                                                                       |
| source.dbadmin.username                       | The source database or database server administrator username.                                                                 |
| source.dbadmin.password                       | The source database or database server administrator password.<br>If you omit the line, you will be prompted for the password. |
| source.interface.dbname                       | The interface database name. (SQL Server, Sybase only)                                                                         |
| source.interface.default.storagelocation.size | The data device size to be allocated to the interface database in MB. (SQL Server only)                                        |
| source.interface.log.storagelocation.size     | The log device size to be allocated to the interface database in MB. (SQL Server only)                                         |
| source.interface.default.storagelocation      | The location for the data device. (Sybase only)                                                                                |
| source.interface.log.storagelocation          | The location for the log device. (Sybase only)                                                                                 |

| Property name                            | Expected value                                                                                          |
|------------------------------------------|---------------------------------------------------------------------------------------------------------|
| source.interface.owner.name              | Interface user to be created by the installer.                                                          |
| source.interface.owner.password          | Interface user password. If you omit the line, you will be prompted for the password.                   |
| source.interface.default.storagelocation | The default tablespace to use when creating the interface user for the source database. (Oracle only)   |
| source.interface.temp.storagelocation    | The temporary tablespace to use when creating the interface user for the source database. (Oracle only) |
| user.index.location                      | The location for the user index. Possible values are source or repository.                              |

## Scripted environment creation properties file example

The following examples demonstrate the use of the properties file.

### *SQL Server example*

SQL Server with database to file only:

```
#Product Information
encryption.key=myEncryptionKey
environment.id=myEnvironment
environment.description=My Default Environment

#Source Database Information
source.rdbms.name=sqlserver
source.conn.dbserver=MSOLTP
source.conn.host=myHost
source.conn.port=5001
source.dbadmin.username=sa
source.dbadmin.password=myPassword

#Interface User Information
source.interface.dbname=obt_if
source.interface.owner.name=obt_if
source.interface.owner.password=myPassword
source.interface.default.storagelocation.size=50
source.interface.log.storagelocation.size=25
```

### *Sybase example*

Sybase with database to file only:

```
#Product Information
encryption.key=myEncryptionKey
environment.id=MySybaseEnv
environment.description=Sybase environment

#Repository Information
rdbms.name=derbydb
repository.dbname=obt_rep
repository.conn.rdbmstype=derbydb_10
repository.conn.dbserver=xxx
repository.conn.host=localhost
repository.conn.port=1527
```

```

repository.dbadmin.username=obt_rep
repository.owner.name=obt_rep

#Source Database Information
source.rdbms.name=sybase
source.conn.dbserver=SYBASE_OLTP125
source.conn.host=myHost
source.conn.port=5000
source.dbadmin.username=sa
source.interface.owner.name=obt_if
source.interface.dbname=obt_if
source.interface.default.storagelocation=my_device
source.interface.log.storagelocation=my_log_device

```

## Scripting business flow deployment

To script your business flow deployment, you need to create a file with the properties you want to use, and then run the script. The following sections contain the scripting procedure, the properties that can be used, and an example of the properties file.

- In this section*
- [Scripted business flow deployment procedure](#) (page 190)
  - [Scripted business flow deployment properties](#) (page 192)
  - [Scripted business flow deployment properties file example](#) (page 192)

### Scripted business flow deployment procedure

- 1 Ensure the repository and environment has been created.

---

**NOTE** If you plan to use eligibility analytics, you must enable eligibility analytics in the model for your business flow before deploying, and the model must contain a pause after the selection step. For more information, see the *HP Test Data Management Designer User Guide*.

---

- 2 Navigate to the directory that contains the generated business flows and the businessflow properties files.

Business flows located in the main businessflow directory can be accessed by all environments.

*Example* `<install_directory>/obt/businessflow`

where `<install_directory>` is the directory where you installed the software.

Business flows located in an environment directory can only be accessed by that environments.

*Example* `<install_directory>/obt/businessflow/<environment_name>`

where `<install_directory>` is the directory where you installed the software, and `<environment_name>` is the name of the environment.

- 3 Ensure that the business flow properties file has the same name as the generated business flow that you want to deploy.

*Example*

If the full name of the .businessflow file in the business flow directory is ORDERS\_D2F\_BF.1\_0\_0\_0.busflow, the properties file should be called ORDERS\_D2F\_BF.1\_0\_0\_0.properties.

- 4 Edit the properties file with the appropriate property values from [Scripted business flow deployment properties](#) (page 192).

If you choose to include passwords or encryption.key properties in the properties file, they are saved in the text file and can be accessed. To ensure that the passwords are not saved, omit the entire password property line from the properties file. You will then be prompted for the passwords.

- 5 Save the file.
- 6 Open a command window.
- 7 Navigate to the following directory:

```
<install_directory>/obt/install
```

where <install\_directory> is the directory where you installed the software.

- 8 Deploy the business flow using the appropriate command:

| Platform | Syntax                                                                  |
|----------|-------------------------------------------------------------------------|
| UNIX     | ./deploy_businessflow.sh <environment_name><br><businessflow_full_name> |
| DOS      | deploy_businessflow.bat <environment_name><br><businessflow_full_name>  |

where <businessflow\_full\_name> is the full name of the business flow you want to deploy, and <environment\_name> is the name of the environment.

*Example*

```
deploy_businessflow.bat MyEnvironment ORDERS_D2F_BF.1_0_0_0
```

**TIP** If you want to remove the job run history of any existing business flows, add the following command: -Dforce.job.history.drop=true

## Scripted business flow deployment properties

| Name                               | Values                                                                                                                             |
|------------------------------------|------------------------------------------------------------------------------------------------------------------------------------|
| environment.id                     | Environment ID                                                                                                                     |
| encryption.key                     | Encryption key. If you omit the line, you will be prompted for the encryption key.                                                 |
| businessflow.install.configuration | Possible values are: <ul style="list-style-type: none"><li>• PrepareOnly</li><li>• DeployOnly</li><li>• PrepareAndDeploy</li></ul> |
| rdbms.name                         | The rdbms.name of the source database. Acceptable values are sqlserver, oracle, sybase, or neoview.                                |
| source.dbadmin.username            | The source database administrative username.                                                                                       |
| source.dbadmin.password            | The password for the source database administrative user.<br>If you omit the line, you will be prompted for the password.          |
| source.location.name               | The location of the source database.<br>Required for business flows containing database to file cartridges.                        |

## Scripted business flow deployment properties file example

The following examples demonstrate the use of the properties file.

### *Oracle example*

Oracle database to file business flow

```
#Business Flow Install Properties
businessflow.install.configuration=PrepareAndDeploy
environment.id=MyEnv
rdbms.name=oracle
source.dbadmin.username=system
source.location.name=OBTINTF_DB
```

# Glossary

|                                 |                                                                                                                                                                                                                                                                                                                                                |
|---------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>active database</b>          | The database from which you plan to extract data. Typically, this database is your online transaction processing (OLTP) or production database. In a two-tiered configuration, the active database resides on tier one and is the source for data movement operations.                                                                         |
| <b>active environment</b>       | The Web Console views and acts upon only one environment at a time, the active environment. To switch the active environment, you use the Change Active option in the Web Console.                                                                                                                                                             |
| <b>activity</b>                 | In Designer, a component of a business flow, which is added by using the toolbar. Note, activities in a business flow are different from what you see at runtime and therefore do not necessarily map directly to what you see in Console.                                                                                                     |
| <b>advanced selection</b>       | A method of data selection that discovers all of the interrelated rows from multiple tables and conceptually places them in the same application partition for extraction.                                                                                                                                                                     |
| <b>annotation</b>               | In Designer, a comment associated with the project, or one of its objects or components. These comments are collected and published in a PDF file when you right click a project or business flow and select Generate Documentation.                                                                                                           |
| <b>application partitioning</b> | The concept of partitioning related rows together during data selection, regardless of whether they are in one or more tables. Application partitioning is unique to HP Test Data Management and contrasts with the more common table partitioning offered by the database management software, which only groups related rows from one table. |
| <b>business flow</b>            | A series of activities, such as extraction operations and scripts, that run in sequence. You build business flows in Designer.                                                                                                                                                                                                                 |
| <b>business flow status</b>     | The Web Console shows the last run of each business flow. The states are Complete/Error/Running.                                                                                                                                                                                                                                               |
| <b>cartridge</b>                | An instance of model- or schema-based eligibility criteria used to copy data from one location to another. Cartridges capture the application and business rules to ensure referential integrity of the data. For any one model in your project, you may have many cartridges that use it.                                                     |
| <b>chaining table</b>           | The lower level table in a many-to-one or a many-to-many relationship between higher level and lower level tables in the model hierarchy.                                                                                                                                                                                                      |
| <b>collection</b>               | The configuration of a directory location and file pattern to match a set of extracted XML files, thus allowing SQL access to the extracted data.                                                                                                                                                                                              |

|                                     |                                                                                                                                                                                                                                                                                                                                   |
|-------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>comma separated values (CSV)</b> | A database to file output format that stores the data as values separated by commas and a metadata file. Each line in the CSV file corresponds to a row in a table. Within a line, fields are separated by commas, each field belonging to one table column. CSV files provide a simple format that many applications can import. |
| <b>command</b>                      | Command files or JavaScript files launched by the Web Console on your behalf with status displays.                                                                                                                                                                                                                                |
| <b>condition</b>                    | In Designer, the way you branch your business flow to run or skip an activity based on some criteria.                                                                                                                                                                                                                             |
| <b>configuration parameter</b>      | A type of parameter that has its values set by an administrator (someone who has repository privileges from Console) through the administrator interface. Typically, this type of parameter represents values that should be changed very infrequently, perhaps only at deployment time.                                          |
| <b>console user</b>                 | The Web Console identifies individual users, who are distinct from database users. The properties for a Console user are User Name, Full Name, Password, Enabled, Description, Email, Phone, and Privileges.                                                                                                                      |
| <b>console user name</b>            | The login name associated with a Console user.                                                                                                                                                                                                                                                                                    |
| <b>constraint</b>                   | A column or a list of columns that enables you to identify rows in the database and relate them to one another.                                                                                                                                                                                                                   |
| <b>customization</b>                | A change that an administrator or DBA makes to a project provided by a third party, typically for a packaged application like Oracle PeopleSoft or Oracle E-Business Suite. As long as the customization is allowable by the project, the user can merge the customization into newer revisions of the third party project.       |
| <b>customization mode</b>           | A Designer mode that provides visual cues to indicate customizations in the model. In a project with locked files, customization mode is on by default, but you can toggle it on and off from the toolbar in the model editor.                                                                                                    |
| <b>data masking</b>                 | The process of replacing private or confidential data during movement with a specified mask. You can choose from pre-defined masks that are part of HP Test Data Management or create your own mask.                                                                                                                              |
| <b>data movement</b>                | The method used by HP Test Data Management to actually copy data.                                                                                                                                                                                                                                                                 |
| <b>database constraint</b>          | A constraint that exists in the database and can be discovered and referenced from Designer.                                                                                                                                                                                                                                      |
| <b>database to file</b>             | A movement in which data goes from an active database to a file (XML or CSV format).                                                                                                                                                                                                                                              |
| <b>Deployment Assistant</b>         | The user interface component used to deploy or generate business flows. You invoke Deployment Assistant from within Designer.                                                                                                                                                                                                     |

|                               |                                                                                                                                                                                                                                                                                                                |
|-------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>description</b>            | A technical description created by the developer for her own reference. These descriptions do not appear in the generated PDF file for the cartridge or business flow.                                                                                                                                         |
| <b>Designer</b>               | The user interface component used to develop, test, and deploy your extraction solution. Designer is a powerful graphical development environment for extraction solutions.                                                                                                                                    |
| <b>driving table</b>          | A driving object is a root of a model hierarchy. Its relationship to the child tables drives the selection of transactions.                                                                                                                                                                                    |
| <b>dynamic list of values</b> | A list of values for a parameter that obtains its members from a SELECT statement that returns identifiers and labels.                                                                                                                                                                                         |
| <b>dynamic parameter</b>      | A type of parameter that has its value set by a Groovy script that runs at deployment time to obtain a value. For example, this type of parameter can supply the type or version of a database or application, which can be obtained programmatically at deployment time.                                      |
| <b>embedded repository</b>    | A Java database, installed with HP Test Data Management, that can act as your repository database, where you store your HP Test Data Management metadata. Alternatively, your source database or another database can act as the repository database.                                                          |
| <b>environment</b>            | The source and (optional) target credentials against which you plan to run commands. You can define multiple environments within your installation to identify various source databases.                                                                                                                       |
| <b>error</b>                  | One of the ways in which you can interrupt a business flow. Error indicates that the business flow failed for some reason.                                                                                                                                                                                     |
| <b>exclusive rules</b>        | One of the ways in which HP Test Data Management determines whether to include or exclude rows from the extract operation. Exclusive rules require all rows in the constraint table to match for inclusion. Exclusive rules exclude the instance if the condition on any child is false, like STATUS='CLOSED'. |
| <b>exit</b>                   | One of the ways in which you can interrupt a business flow. You can exit successfully or with a warning.                                                                                                                                                                                                       |
| <b>export</b>                 | The way that you save an HP Test Data Management project to an exchange format (.hdp) from the File menu. See also <i>import</i> .                                                                                                                                                                             |
| <b>export data</b>            | The way that a user can send data to CSV format from Preview using the toolbar item.                                                                                                                                                                                                                           |
| <b>extract data store</b>     | The location where the data is to be copied. Can be an XML or CVS file.                                                                                                                                                                                                                                        |
| <b>generate documentation</b> | The process of collecting and grouping all annotations into a PDF file that also describes the business flow or cartridge structure.                                                                                                                                                                           |

|                              |                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>import</b>                | The way that you transfer projects from exchange format (.hdp) into the Project Navigator.                                                                                                                                                                                                                                                                                                                                                                           |
| <b>inclusive rules</b>       | One of the ways in which HP Test Data Management determines whether to include or exclude rows from the extract operation. Inclusive rules require only one row in the constraint table to match the rule and be included. Inclusive rules include the instance if the condition on any child is true, like <code>PRODUCT_RECALLED='Y'</code> .                                                                                                                      |
| <b>interrupt</b>             | The way to stop or pause a business flow (pause, error, exit with warning, exit successfully).                                                                                                                                                                                                                                                                                                                                                                       |
| <b>local cache</b>           | A capture of the metadata for your databases, schemas, and tables used when working offline in Designer.                                                                                                                                                                                                                                                                                                                                                             |
| <b>local deployment</b>      | The generation and deployment of your cartridge or business flow to an environment on your local, Designer client. Deployment files are generated locally and then deployed to the designated, local environment.                                                                                                                                                                                                                                                    |
| <b>lookup table</b>          | A table that contains helpful non-transactional information. For example, non-transactional information could be status definitions, or the name of the sales representative.                                                                                                                                                                                                                                                                                        |
| <b>model</b>                 | A model identifies the tables and table relationships representing a business entity or related business entities. A project can have multiple models. Each model contains a driving table and all of its child and descendent tables.                                                                                                                                                                                                                               |
| <b>model compatibility</b>   | Each model in your project can have one or more dynamic parameters associated with it to verify the compatibility with the target environment. If the compatibility parameter returns false, then the cartridge referencing the model will not deploy or run and throw an error. For example, the script could return false for Oracle 10.2 and true for Oracle 11.1 to indicate that a cartridge referencing the model can only deploy and run against Oracle 11.1. |
| <b>model-based cartridge</b> | A cartridge that moves data based upon a defined data model with relationships. This type of cartridge is typically used for ongoing extract operations.                                                                                                                                                                                                                                                                                                             |
| <b>OLTP database</b>         | The online transaction processing database that typically is your active or source database.                                                                                                                                                                                                                                                                                                                                                                         |
| <b>pause</b>                 | One of the ways in which you can interrupt a business flow. Pausing suspends the business flow while awaiting operator intervention.                                                                                                                                                                                                                                                                                                                                 |
| <b>query server</b>          | The component that provides SQL access to XML or CVS files.                                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>remote deployment</b>     | The generation and deployment of your cartridge or business flow to an environment on a system that is remote from your Designer client. Deployment files are generated locally and then deployed to the designated, remote environment.                                                                                                                                                                                                                             |

|                                    |                                                                                                                                                                                                                                                                        |
|------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>repository</b>                  | The location that holds business flow metadata, product configuration data, and data collected during runtime. The repository can be located on your active database, another logical database, or can be embedded database.                                           |
| <b>rule</b>                        | Qualifications added to the model in order to include or exclude data based on certain criteria. For example, you might add a rule to exclude from extracting any orders that are not yet closed.                                                                      |
| <b>runtime parameter</b>           | A type of parameter that has its values set by the operator executing the job in Console or on the command line. Typically, this type of parameter represents operational values that tend to change frequently and therefore need to be set each time the job is run. |
| <b>schema-based cartridge</b>      | A cartridge that moves data based upon the database schema rather than a defined data model with relationships. This type of cartridge is typically used for database retirement or the cleanup of orphan tables.                                                      |
| <b>selection</b>                   | The form of data selection to use (standard or advanced) for choosing data. When creating a cartridge or adding it to a business flow, you must specify the selection method.                                                                                          |
| <b>source</b>                      | The location (database) from which you are copying or moving data.                                                                                                                                                                                                     |
| <b>standard selection</b>          | A method of data selection that restricts itself to the rows identified by the model. Unlike advanced selection, it does not attempt to traverse related rows across multiple tables.                                                                                  |
| <b>table use</b>                   | A database table, view, or synonym that is referenced in Designer, for example, in the model. The same table can be used multiple times in a model. For example, a table could be appear as a transactional table and a lookup table in the same model.                |
| <b>target</b>                      | The location (XML) to which you are copying data.                                                                                                                                                                                                                      |
| <b>transactional data movement</b> | Transactional movement uses set-based data movement and is the default method of movement.                                                                                                                                                                             |
| <b>transactional table</b>         | A table that contains information about the business transaction. For example, a transactional table might contain detailed tax or payment information related to each business transaction.                                                                           |
| <b>unique identifiers (UIDs)</b>   | A 16 hexadecimal identifier calculated based on the content of a Designer file. This value is used to determine if the user has customized key pieces of a project.                                                                                                    |
| <b>virtual constraint</b>          | A constraint that you define in Designer that only exists within HP Test Data Management as opposed to a database constraint, which exists within the database.                                                                                                        |
| <b>Web Console</b>                 | A browser-based interface where you can create and manage your deployment environments, and deploy, run, administer, and monitor your business flows.                                                                                                                  |



# Index

## A

- accessing
  - copied data, 82
  - data files, 105
  - installing query server, 105
  - metadata, 136
  - Oracle queries, 134
  - starting query server, 106
- active
  - environments, 49
- adding
  - data source, 152
  - hints, 171
  - session variables, 171
- analytics
  - eligibility, 94
- audience, intended, 7

## B

- before you begin
  - related documentation, 14
- businessflow.install.configuration, 192
- business flows
  - before you run, 77
  - before you run on command line, 85
  - cancelling, 81
  - cancelling from command line, 89
  - configuring, 61
  - deploying, 56
  - importing, 58
  - parameters, 61
  - recovering, 81
  - redeploying, 58
  - removing, 60
  - running, 77
  - running from command line, 86
  - scheduling, 79

## C

- cancelling
  - business flows, 81
  - business flows from command line, 89
  - failed jobs, 80
  - failed jobs from command line, 87
- cartridges
  - configuring, 62
  - parameters, 62
- character encoding, 183
- client
  - JDBC, 113, 115
  - ODBC, 116
  - OLEDB, 117
- collections
  - connecting from SQL Server, 135
  - creating, 118
  - Oracle Heterogeneous Services, 129
  - querying from SQL Server, 135
  - SQL Server, 134
  - viewing from Excel, 124
  - viewing from OpenOffice.org Base, 127
- commands
  - ALTER SESSION, 175
  - monitoring, 94
  - SET, 175
- compression
  - GZIP, 165
  - XML, 165
- configuring
  - database to file, 61
  - ODBC on UNIX, 108, 109
  - parameters, 61
- connecting
  - to data source, 113
- connection-sources.xml, 103
- context values
  - about, 173
- conventions, document, 8

- copied data
  - accessing, 82
  - relocating, 82
- creating
  - collections, 118

## D

- data
  - accessing, 82
- databases
  - link, Oracle, 134
- database to file
  - configuring, 61
  - core parameters, 165
  - PDM parameters, 168
  - performance parameters, 166
  - validation parameters, 167
- data sources, 106
  - adding, 152
  - dropping, 152
  - ODBC on Unix, 153
  - relocating, 154
- data type mapping file, 52
  - editing, 54
  - validating, 55
- deleting
  - environments, 50
- deploying
  - business flows, 56
  - preventing, 99
  - properties file for scripted, 183
  - scripted, 183
- documentation
  - conventions, 8
  - HP web site, 8
  - related, 7, 8
  - updates, 9
- dropping
  - data source, 152

## E

- eligibility analytics
  - viewing, 94
- email
  - configuring email subscriptions, 75

- encryption keys
  - changing, 102
  - deployment properties, 192

- environment.id, 192

- environments
  - creating, 45
  - deleting, 50
  - enabling user access, 73
  - scripted creation, 187
  - setting active, 49
  - tutorial, 23

- Excel
  - query wizard, 125, 126
  - special characters, 125
  - viewing collections from, 124

- exclusion
  - analytics, 94

- extracted data
  - relocating from command line, 89

## G

- granting
  - privileges, 71
- GZIP compression, 165

## H

- Heterogeneous Services
  - agent process, 129
  - database link, 134
  - initialization file, 129
  - listener, 130
  - Oracle, 129
  - prior to Oracle 11, 64 bit OS, 131
  - tnsnames, 131
- history
  - jobs, 93
- HP
  - Subscriber's choice web site, 10

## I

- ij, 113
- importing
  - business flows, 58
- indexes
  - query server, 157

## installing

- new repository, 38
- ODBC driver, 108
- ODBC on UNIX, 108, 109
- OLEDDB driver, 108
- query server, 105
- repository, scripted, 184
- scripted, 183

Interactive JDBC client (ij), 113

Interactive SQL, 113, 116, 117

ISO 8859-1, 183

## J

### JDBC

- client, 113, 115
- connection information, 115
- OpenOffice.org Base, 127
- URL, 47, 49

### jobs

- failed, 80, 87
- monitoring, 91
- not responding, 80, 87
- recovery script, 88
- scheduling, 79
- suspended, 80, 87

## L

### licensing, HP

- end user license agreement, 2

linked server, 136

### locking

- lock\_repository script, 99
- repositories, 99

### log files

- log4j.properties, 96
- logging levels, 96
- oaclient.log, 163
- oaclientuninstall.log, 163
- oaerror.log, 163
- oaserveruninstall.log, 163
- obt.log, 96
- obt.log,query server, 163
- using, 95
- viewing, 95

## M

### mapping file, 52

- editing, 54
- validating, 55

### monitoring

- commands, 94
- detailed status, 92
- history, 93
- information, 91
- jobs, 91
- log files, 95
- run details, 92
- status overview, 91

### multiple nodes

- Web Console, 42

## N

### nodes

- adding Web Console, 42

## O

### oaclient.log

- query server, 163

### oaclientuninstall.log

- query server, 163

### oaerror.log

- query server, 163

### oaserver

- query server, 149

### oaserver.log

- query server, 163

### oaserveruninstall.log

- query server, 163

### obt.log

- for query server, 163
- main log file, 96

### ODBC

- client, 116
- database link, 134
- data source, 106
- driver for UNIX, 108, 109
- installing driver, 108
- new data source on Unix, 153
- OpenOffice.org Base, 127

### OLEDDB

- client, 117
- installing driver, 108

- OpenOffice.org Base
  - JDBC, 127
  - ODBC, 127
  - viewing collections from, 127

- Oracle
  - database link, 134
  - Heterogeneous Services, 129
  - RAC connection through JDBC, 47, 49
  - SQL trace, 181

## P

- parameters
  - cartridge, 62
  - configuration, database to file, 165
  - configuring, 61

- passwords
  - changing encryption keys, 102
  - changing for repositories, 102
  - changing in Web Console, 74
  - changing repository passwords, 102

- ports
  - starting Web Console on, 36

- prerequisites
  - product, 7

- privileges
  - understanding, 71

## Q

- queries
  - Excel, 124
  - OpenOffice.org Base, 127
  - Oracle, 134
  - wizard, 125, 126

- query server
  - connecting to data source, 113
  - creating collections, 118
  - indexes, 157
  - installing, 105
  - installing ODBC driver, 108
  - installing OLEDB driver, 108
  - multiple data sources, 151
  - options, 159
  - overview, 105
  - privileges, 155
  - roles, 155
  - starting, 106
  - uninstall, 149
  - users, 155
  - viewing CSV file, 138

## R

- recovering
  - business flows, 81
  - failed jobs, 80
  - failed jobs from command line, 87
  - script for failed jobs, 88

- redeploying
  - business flows, 58

- relocating
  - copied data, 82
  - data sources, 154
  - extracted data from command line, 89

- removing
  - business flows, 60

- repositories
  - changing passwords, 102
  - installing, 38
  - lock\_repository script, 99
  - locking, 99
  - scripted setup, 184
  - tutorial for installing, 18
  - unlock\_repository script, 101
  - unlocking, 99, 100

- running
  - before you begin, 77
  - before you begin on command line, 85
  - business flows, 77
  - business flows from command line, 86
  - scheduling, 79
  - status detail, 92

- runPwManager, 102, 103

## S

- scheduling
  - jobs, 79
- seed statements
  - about, 172
  - files, 172
- selection
  - analytics, 94
- session variables
  - about, 175
- software
  - version, 1
- source.dbadmin.password, 192
- special characters
  - Excel, 125
- SQL
  - hints, 171
  - trace for Oracle, 181
  - tuning, 171
  - tuning hints, 171
  - tuning properties, 171
- sql\_tuning.properties
  - default hints, 177
- SQL Server
  - connecting for collections, 135
- SSL
  - starting Web Console with, 37
- starting
  - Web Console, 35
  - Web Console on different port, 36
  - Web Console tutorial, 17
  - Web Console with SSL, 37
- status
  - commands, 94
  - detailed, 92
  - overview, 91
  - run details, 92
- stopping
  - Web Console, 35, 37
- Subscriber's choice, HP, 10
- subscription service
  - Subscriber's choice, 10
- summary table
  - XML, 137

- support
  - web site, 10

## T

- test data
  - file naming parameters, 169
  - overview, 13
- tutorials
  - configuring Web Console, 17

## U

- unlocking
  - repositories, 100
  - unlock\_repository script, 101
- users
  - adding, 72
  - changing passwords, 74
  - email subscriptions, 75
  - enabling access to environments, 73
  - modifying, 73
  - privileges, 71
  - tutorial on creating, 28
  - updating personal information, 74

## V

- viewing
  - collections from Oracle Heterogeneous Services, 129
  - collections from SQL Server, 134
  - CSV files, 138
  - limitations, 139
  - metadata, 136

## W

### Web Console

- adding nodes, 42
- adding users, 72
- changing passwords, 74
- creating environments, 45
- deploying business flows, 56
- email access, 75
- enabling environment access, 73
- importing business flows, 58
- installing repository, 38
- installing repository tutorial, 18
- modifying users, 73
- overview, 14
- starting, 17, 35
- starting on different port, 36
- starting with SSL, 37
- stopping, 35, 37
- tutorial for configuring, 17
- tutorial for environments, 23
- tutorial on creating users, 28
- updating personal information, 74
- user privileges, 71

### Web service, 182

### web sites

- HP documentation, 8
- HP Subscriber's choice, 10
- support, 10

## X

### XML

- compression, 165
- summary table, 137

### XML data script

- COPY\_BE\_TO\_BE, 90
- COPY\_BE\_TO\_DB, 90
- MOVE\_BE\_TO\_DB, 90



